

Oracle® Solaris Cluster Data Service for SAP MaxDB Guide

ORACLE®

Part No: E99012
July 2020

Part No: E99012

Copyright © 2000, 2020, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Référence: E99012

Copyright © 2000, 2020, Oracle et/ou ses affiliés. Tous droits réservés.

Ce logiciel et la documentation qui l'accompagne sont protégés par les lois sur la propriété intellectuelle. Ils sont concédés sous licence et soumis à des restrictions d'utilisation et de divulgation. Sauf stipulation expresse de votre contrat de licence ou de la loi, vous ne pouvez pas copier, reproduire, traduire, diffuser, modifier, accorder de licence, transmettre, distribuer, exposer, exécuter, publier ou afficher le logiciel, même partiellement, sous quelque forme et par quelque procédé que ce soit. Par ailleurs, il est interdit de procéder à toute ingénierie inverse du logiciel, de le désassembler ou de le décompiler, excepté à des fins d'interopérabilité avec des logiciels tiers ou tel que prescrit par la loi.

Les informations fournies dans ce document sont susceptibles de modification sans préavis. Par ailleurs, Oracle Corporation ne garantit pas qu'elles soient exemptes d'erreurs et vous invite, le cas échéant, à lui en faire part par écrit.

Si ce logiciel, ou la documentation qui l'accompagne, est livré sous licence au Gouvernement des Etats-Unis, ou à quiconque qui aurait souscrit la licence de ce logiciel pour le compte du Gouvernement des Etats-Unis, la notice suivante s'applique :

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

Ce logiciel ou matériel a été développé pour un usage général dans le cadre d'applications de gestion des informations. Ce logiciel ou matériel n'est pas conçu ni n'est destiné à être utilisé dans des applications à risque, notamment dans des applications pouvant causer un risque de dommages corporels. Si vous utilisez ce logiciel ou ce matériel dans le cadre d'applications dangereuses, il est de votre responsabilité de prendre toutes les mesures de secours, de sauvegarde, de redondance et autres mesures nécessaires à son utilisation dans des conditions optimales de sécurité. Oracle Corporation et ses affiliés déclinent toute responsabilité quant aux dommages causés par l'utilisation de ce logiciel ou matériel pour des applications dangereuses.

Oracle et Java sont des marques déposées d'Oracle Corporation et/ou de ses affiliés. Tout autre nom mentionné peut correspondre à des marques appartenant à d'autres propriétaires qu'Oracle.

Intel et Intel Xeon sont des marques ou des marques déposées d'Intel Corporation. Toutes les marques SPARC sont utilisées sous licence et sont des marques ou des marques déposées de SPARC International, Inc. AMD, Opteron, le logo AMD et le logo AMD Opteron sont des marques ou des marques déposées d'Advanced Micro Devices. UNIX est une marque déposée de The Open Group.

Ce logiciel ou matériel et la documentation qui l'accompagne peuvent fournir des informations ou des liens donnant accès à des contenus, des produits et des services émanant de tiers. Oracle Corporation et ses affiliés déclinent toute responsabilité ou garantie expresse quant aux contenus, produits ou services émanant de tiers, sauf mention contraire stipulée dans un contrat entre vous et Oracle. En aucun cas, Oracle Corporation et ses affiliés ne sauraient être tenus pour responsables des pertes subies, des coûts occasionnés ou des dommages causés par l'accès à des contenus, produits ou services tiers, ou à leur utilisation, sauf mention contraire stipulée dans un contrat entre vous et Oracle.

Accès aux services de support Oracle

Les clients Oracle qui ont souscrit un contrat de support ont accès au support électronique via My Oracle Support. Pour plus d'informations, visitez le site <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> ou le site <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> si vous êtes malentendant.

Contents

- Using This Documentation** 11

- 1 Installing and Configuring HA for SAP MaxDB** 13
 - HA for SAP MaxDB Overview 13
 - Overview of the Installation and Configuration Process for HA for SAP MaxDB 14
 - Planning the HA for SAP MaxDB Installation and Configuration 15
 - Configuration Requirements 15
 - Supported Configurations of This Data Service 17
 - Configuration Considerations 19
 - Configuration Planning Questions 20
 - Installing and Configuring SAP MaxDB 20
 - ▼ How to Install and Configure SAP MaxDB 21
 - ▼ How to Enable SAP MaxDB to Run in a Cluster 23
 - Verifying the SAP MaxDB Installation and Configuration 25
 - ▼ How to Verify SAP MaxDB Installation and Configuration on Each Node 25
 - Installing the HA for SAP MaxDB Package 26
 - ▼ How to Install the HA for SAP MaxDB Package 26
 - Configuring the HASStoragePlus Resource Type to Work With HA for SAP MaxDB 28
 - ▼ How to Register and Configure an HASStoragePlus Resource 28
 - Registering and Configuring HA for SAP MaxDB 30
 - Setting HA for SAP MaxDB Extension Properties 30
 - Administering SAP xserver as a User Other Than Root 31
 - ▼ How to Register and Configure an SAP xserver Resource 31
 - ▼ How to Register and Configure a SAP MaxDB Resource 34
 - Tuning the HA for SAP MaxDB Fault Monitors 37
 - Factors That Affect the Interval Between Fault Monitor Probes 38
 - Operations by the HA for SAP MaxDB Fault Monitors During a Probe 38

Faults Detected by the HA for SAP MaxDB Fault Monitors	39
Forcing the SAP MaxDB Database Instance to Be Restarted if the Parent Kernel Process Is Terminated	40
Verifying the HA for SAP MaxDB Installation and Configuration	41
▼ How to Verify the Operation of the SAP MaxDB Fault Monitor	41
▼ How to Verify the Operation of the SAP xserver Fault Monitor	43
A HA for SAP MaxDB Extension Properties	45
SUNW.sapdb Extension Properties	45
SUNW.sap_xserver Extension Properties	49
Index	53

Tables

TABLE 1	Protection of SAP MaxDB Components by Oracle Solaris Cluster Data Services	14
TABLE 2	Tasks for Installing and Configuring HA for SAP MaxDB	14
TABLE 3	Resource Types for HA for SAP MaxDB Fault Monitors	37

Examples

EXAMPLE 1	Two-Node Configuration	17
EXAMPLE 2	Four-Node Configuration With SAP NetWeaver	18
EXAMPLE 3	Four-Node Configuration With SAP NetWeaver and SAP liveCache	18
EXAMPLE 4	Information About a Database User Who Administers a SAP MaxDB Instance	22
EXAMPLE 5	Enabling SAP MaxDB to Run in a Cluster	24
EXAMPLE 6	Creating an HASStoragePlus Resource	29
EXAMPLE 7	Configuring a SUNW.sap_xserver Resource	33
EXAMPLE 8	Creating a SUNW.sapdb Resource	36

Using This Documentation

- **Overview** – Explains how to install and configure the Oracle Solaris Cluster HA for SAP MaxDB data service
- **Audience** – Technicians, system administrators, and authorized service providers
- **Required knowledge** – Advanced experience troubleshooting and replacing hardware

Product Documentation Library

Documentation and resources for this product and related products are available at http://www.oracle.com/pls/topic/lookup?ctx=E69294_01.

Feedback

Provide feedback about this documentation at <http://www.oracle.com/goto/docfeedback>.

Installing and Configuring HA for SAP MaxDB

This chapter explains how to install and configure the Oracle Solaris Cluster HA for SAP MaxDB (HA for SAP MaxDB) data service.

This chapter contains the following sections.

- “HA for SAP MaxDB Overview” on page 13
- “Overview of the Installation and Configuration Process for HA for SAP MaxDB” on page 14
- “Planning the HA for SAP MaxDB Installation and Configuration” on page 15
- “Installing and Configuring SAP MaxDB” on page 20
- “Verifying the SAP MaxDB Installation and Configuration” on page 25
- “Installing the HA for SAP MaxDB Package” on page 26
- “Configuring the HASoragePlus Resource Type to Work With HA for SAP MaxDB” on page 28
- “Registering and Configuring HA for SAP MaxDB” on page 30
- “Tuning the HA for SAP MaxDB Fault Monitors” on page 37
- “Verifying the HA for SAP MaxDB Installation and Configuration” on page 41

HA for SAP MaxDB Overview

To eliminate single points of failure in an SAP MaxDB system, HA for SAP MaxDB provides the following features:

- Fault monitoring and automatic failover for the SAP MaxDB application. You must configure **HA for SAP MaxDB** as a failover data service.
- Fault monitoring and automatic restart for SAP xserver. You must configure **SAP xserver** as a multiple-master data service.

For conceptual information about failover data services and multiple-master data services, see the [Concepts for Oracle Solaris Cluster 4.4](#).

Each component of SAP MaxDB has a data service that protects the component when the component is configured with Oracle Solaris Cluster. See the following table.

Note - The files that are associated with the `SUNW.sap_xserver` resource type are supplied with the Oracle Solaris Cluster HA for SAP liveCache data service. The Oracle Solaris Cluster HA for SAP liveCache data service is also installed when you install the HA for SAP MaxDB data service.

TABLE 1 Protection of SAP MaxDB Components by Oracle Solaris Cluster Data Services

SAP MaxDB Component	Data Service
SAP MaxDB	HA for SAP MaxDB
SAP xserver	The resource type is <code>SUNW.sapdb</code> . Oracle Solaris Cluster HA for SAP liveCache
NFS file system	The resource type is <code>SUNW.sap_xserver</code> . Oracle Solaris Cluster HA for NFS The resource type is <code>SUNW.nfs</code> . For more information about this data service, see Oracle Solaris Cluster Data Service for NFS Guide .

Overview of the Installation and Configuration Process for HA for SAP MaxDB

The following table summarizes the tasks for installing and configuring HA for SAP MaxDB and provides cross-references to detailed instructions for performing these tasks. Perform the tasks in the order that they are listed in the table.

TABLE 2 Tasks for Installing and Configuring HA for SAP MaxDB

Task	Cross-Reference
Plan the HA for SAP MaxDB installation and configuration.	Your SAP MaxDB documentation. Planning and Administering Data Services for Oracle Solaris Cluster 4.4 “Planning the HA for SAP MaxDB Installation and Configuration” on page 15
Install and configure SAP MaxDB.	“Installing and Configuring SAP MaxDB” on page 20

Task	Cross-Reference
Verify the SAP MaxDB installation and configuration.	“Verifying the SAP MaxDB Installation and Configuration” on page 25
Install the HA for SAP MaxDB packages.	“Installing the HA for SAP MaxDB Package” on page 26
Configure the HASToragePlus resource to work with HA for SAP MaxDB.	“Relationship Between Resource Groups and Device Groups” in <i>Planning and Administering Data Services for Oracle Solaris Cluster 4.4</i> “Relationship Between Resource Groups and Device Groups” in <i>Planning and Administering Data Services for Oracle Solaris Cluster 4.4</i> “Synchronizing the Startups Between Resource Groups and Device Groups Using HASToragePlus” in <i>Planning and Administering Data Services for Oracle Solaris Cluster 4.4</i> “Configuring the HASToragePlus Resource Type to Work With HA for SAP MaxDB” on page 28
Register and configure the HA for SAP MaxDB data service.	“Registering and Configuring HA for SAP MaxDB” on page 30
(Optional) Tune the HA for SAP MaxDB fault monitors.	“Tuning the HA for SAP MaxDB Fault Monitors” on page 37
Verify the HA for SAP MaxDB installation and configuration.	“Verifying the HA for SAP MaxDB Installation and Configuration” on page 41

Planning the HA for SAP MaxDB Installation and Configuration

This section contains the information that you need to plan your HA for SAP MaxDB installation and configuration.

Note - Before you begin, consult your SAP MaxDB documentation for configuration restrictions and requirements that are not imposed by Oracle Solaris Cluster software. For information about restrictions that the Oracle Solaris Cluster software imposes, see the Oracle Solaris Cluster documentation.

Configuration Requirements

The configuration requirements in this section apply only to HA for SAP MaxDB.



Caution - If your data service configuration does not conform to these requirements, the data service configuration might not be supported.

For requirements that apply to all data services, see “[Configuration Guidelines for Oracle Solaris Cluster Data Services](#)” in *Planning and Administering Data Services for Oracle Solaris Cluster 4.4*.

SAP MaxDB Software Version Requirements

For the current supported versions of SAP MaxDB with this Oracle Solaris Cluster release, see the [Oracle Solaris Cluster 4 Compatibility Guide \(http://www.oracle.com/technetwork/server-storage/solaris-cluster/overview/solariscluster4-compatibilityguide-1429037.pdf\)](http://www.oracle.com/technetwork/server-storage/solaris-cluster/overview/solariscluster4-compatibilityguide-1429037.pdf).

HA for SAP MaxDB Configuration Requirements

Configure HA for SAP MaxDB as a failover data service. You cannot configure HA for SAP MaxDB either as a scalable data service or as a multiple-master data service. For more information, see the following sections:

- “[How to Enable SAP MaxDB to Run in a Cluster](#)” on page 23
- “[How to Register and Configure a SAP MaxDB Resource](#)” on page 34

SAP xserver Configuration Requirements

To enable client applications to access HA for SAP MaxDB, you must use SAP xserver. Configure SAP xserver as a multiple-master data service. Do *not* configure SAP xserver as a failover data service.

Configure SAP xserver so that SAP xserver starts on all nodes to which the SAP MaxDB resource can fail over. To implement this configuration, ensure that the node list of the SAP xserver resource group contains all nodes that are in the node list of the SAP MaxDB resource group. For more information, see “[How to Register and Configure an SAP xserver Resource](#)” on page 31.

Supported Configurations of This Data Service

The HA for SAP MaxDB data service supports configurations that conform to the requirements in [“Configuration Requirements” on page 15](#).

If you plan to use SAP MaxDB with other highly available SAP MaxDB applications, you must also configure the Oracle Solaris Cluster data services for those applications. For more information, see the following table.

SAP MaxDB Application	Oracle Solaris Cluster Data Service	Associated Document
SAP liveCache	Oracle Solaris Cluster HA for SAP liveCache	Oracle Solaris Cluster Data Service for SAP liveCache Guide
SAP NetWeaver	Oracle Solaris Cluster HA for SAP NetWeaver	Oracle Solaris Cluster Data Service for SAP NetWeaver Guide

The examples that follow show these supported configurations of HA for SAP MaxDB:


- Two-node cluster configuration
- Four-node cluster configuration with SAP NetWeaver
- Four-node cluster configuration with SAP NetWeaver and SAP liveCache

Note - HA for SAP MaxDB might support additional configurations. However, you must contact your Oracle service provider for information about additional configurations.

EXAMPLE 1 Two-Node Configuration

This example shows a two-node configuration in which a client application accesses the SAP MaxDB resource through the SAP xserver resource. The characteristics of this configuration are as follows:


- The SAP MaxDB resource is configured as a failover data service.
- The SAP xserver resource is configured as a multiple-master data service.



EXAMPLE 2 Four-Node Configuration With SAP NetWeaver

This example shows a four-node configuration in which SAP MaxDB is used with SAP NetWeaver. This configuration uses multiple Advanced Planner & Optimizer (APO) application servers. The characteristics of this configuration are as follows:


- The SAP MaxDB APO Central Instance (CI) resource is configured as a failover data service.
- The SAP MaxDB resource is configured as a failover data service.
- The SAP xserver resource is configured as a multiple-master data service.
- APO application server (APP) resources are configured as multiple-master data services.



EXAMPLE 3 Four-Node Configuration With SAP NetWeaver and SAP liveCache

This example shows a four-node configuration in which SAP MaxDB is used with SAP NetWeaver and SAP liveCache. This configuration uses multiple APO application servers. The characteristics of this configuration are as follows:

- The SAP MaxDB APO CI resource is configured as a failover data service.
- The SAP MaxDB resource is configured as a failover data service.
- The SAP xserver resource is configured as a multiple-master data service.
- APP resources are configured as multiple-master data services.
- The SAP liveCache resource is configured as a failover data service.



Configuration Considerations

The configuration considerations in the subsections that follow affect the installation and configuration of HA for SAP MaxDB.

Device Group for the SAP MaxDB Application

Ensure that you create a device group for the SAP MaxDB application as follows:

- Install SAP MaxDB on its own global device group. For more information, see [“Installing and Configuring SAP MaxDB” on page 20](#). This separate global device group for SAP MaxDB ensures that the SAP MaxDB resource can depend on the HASToragePlus resource only for SAP MaxDB.
- Create an HASToragePlus resource for the global device group on which SAP MaxDB is installed. For more information, see [“Configuring the HASToragePlus Resource Type to Work With HA for SAP MaxDB” on page 28](#).
- Ensure that the resource for SAP MaxDB depends on the HASToragePlus resource for the global device group on which SAP MaxDB is installed. For more information, see [“Registering and Configuring HA for SAP MaxDB” on page 30](#).

Dependencies of the SAP MaxDB Application on SAP xserver

Configure SAP MaxDB so that SAP MaxDB starts only on a node where SAP xserver is running. To implement this configuration, configure resources and resource groups as follows:

- Ensure that the resource for SAP MaxDB depends on the resource for SAP xserver.
- Create on the SAP MaxDB resource group a strong positive affinity for the SAP xserver resource group.

For more information, see [“Registering and Configuring HA for SAP MaxDB” on page 30](#).

Administration of SAP xserver by a User Other Than Root

You might be required to administer SAP xserver as a user other than root. In this situation, you must create and define that user as follows:

- You must create that user on all cluster nodes that master SAP xserver.
- You must define that user when you register and configure HA for SAP MaxDB. For more information, see [“Registering and Configuring HA for SAP MaxDB” on page 30](#).

Configuration Planning Questions

Answer the questions in this section to plan the installation and configuration of HA for SAP MaxDB.

- Which resource group will you use for the SAP MaxDB application resource and for the logical hostname for the SAP MaxDB resource?
Use the answer to this question when you perform the procedure [“How to Enable SAP MaxDB to Run in a Cluster” on page 23](#).
- What is the logical hostname for the SAP MaxDB resource? Clients access the data service through this logical hostname.
Use the answer to this question when you perform the following procedures:
 - [“How to Install and Configure SAP MaxDB” on page 21](#)
 - [“How to Enable SAP MaxDB to Run in a Cluster” on page 23](#)
- Where will the system configuration files reside?
See [Planning and Administering Data Services for Oracle Solaris Cluster 4.4](#) for the advantages and disadvantages of using the local file system instead of the cluster file system.

Installing and Configuring SAP MaxDB

To enable HA for SAP MaxDB to make SAP MaxDB highly available, additional installation and configuration operations are required. These operations supplement the standard installation and standard configuration of SAP MaxDB.

During a standard installation, SAP MaxDB is installed with a physical host name. To enable SAP MaxDB to run in a cluster, you must modify SAP MaxDB to use a logical hostname.

For information about the standard installation and standard configuration of SAP MaxDB, see the following documentation:

- If you are using SAP MaxDB with SAP NetWeaver, see the SAP NetWeaver documentation for information about how to install and configure SAP NetWeaver with SAP MaxDB.
- If you are using SAP MaxDB independently of SAP NetWeaver, see the SAP MaxDB documentation.

▼ How to Install and Configure SAP MaxDB

1. **On one node of the cluster, install the SAP MaxDB software.**
Ensure that you install SAP MaxDB on its own global device group.
2. **Perform a standard configuration of SAP MaxDB.**
3. **Create the .XUSER.62 file in the home directory of the operating system user that administers the SAP MaxDB instance.**
 - a. **Create a plain text file that contains information about the database user that administers the SAP MaxDB database instance.**
For information about the content of this file, see the SAP MaxDB documentation. For the name of the server on which the database is running, specify the logical hostname for the SAP MaxDB resource that you specified in [“Configuration Planning Questions” on page 20](#).

For an example of the content of this file, see [Example 4, “Information About a Database User Who Administers a SAP MaxDB Instance,” on page 22](#).
 - b. **As the SAP MaxDB admin user, generate the .XUSER.62 file from the plain text file that you created in [Step 3a](#).**
Use the SAP MaxDB command `xuser` for this purpose.


```
# xuser -b user-info-file
```



```
-b user-info-file
```


Specifies the plain text file from which you are generating the .XUSER.62 file
4. **Copy the `/usr/spool/sql` directory and its contents from the node on which you installed SAP MaxDB to all nodes where resources for SAP MaxDB and SAP xserver will run.**

To ensure that the same owner owns the directory and its contents on all nodes, use the `tar` command and the `ssh` command.

```
# tar cfB - /usr/spool/sql | ssh destination "cd /;tar xfb -"
```

destination

Specifies the node to which you are copying the `/usr/spool/sql` directory and its contents

The following example shows a plain text file that contains information about a database user that administers an SAP MaxDB instance.

5. Distribute `/etc/opt/sdb` on all nodes to run SAP MaxDB.

Copy the `/etc/opt/sdb` directory and its contents from the node on which you installed SAP MaxDB to all nodes where resources for SAP MaxDB and SAP xserver will run.

To ensure that the same owner owns the directory and its contents on all nodes, use the `tar` command and the `ssh` command.

```
# tar cfB - /etc/opt/sdb | ssh destination "cd /;tar xfb -"
```

destination

Specifies the node to which you are copying the `/etc/opt/sdb` directory and its contents

Example 4 Information About a Database User Who Administers a SAP MaxDB Instance

```
DEFAULT
dbm
dbm
TST
srvr-1
  blank line
  blank line
-1
-1
  blank line
```

This example specifies the following information about a database user who administers an SAP MaxDB instance:

- The user key that is used to address this combination of XUSER data is named `DEFAULT`.
- The user name and password of the database user are `dbm`.
- The name of the SAP MaxDB instance is `TST`.
- The logical hostname for the SAP MaxDB resource is `srvr-1`.
- No structured query language (SQL) mode is specified.

- The default time-out value of the SAP MaxDB instance is used.
- The default isolation level of the SAP MaxDB instance is used.

For more information, see the SAP MaxDB documentation.

▼ How to Enable SAP MaxDB to Run in a Cluster

1. **Create a failover resource group to contain the SAP MaxDB application resources and the logical hostname for the SAP MaxDB resource.**

Use the resource group that you identified when you answered the questions in [“Configuration Planning Questions” on page 20](#).

```
# clresourcegroup create -n node-list sapdb-rg
```

```
sapdb-rg
```

Specifies the name of the resource group that you are creating.

2. **Ensure that all network resources that you intend to you use are added to your name service database.**

3. **Add a logical hostname resource to the failover resource group that you created in [Step 1](#).**

```
# clreslogicalhostname create -g sapdb-rg \  
-h sapdb-logical-hostname sapdb-logical-hostname
```

```
-g sapdb-rg
```

Specifies that the logical hostname's database resource is to be added to the failover resource group that you created in [Step 1](#).

```
-h
```

Specifies the hostname list. You must use this option either when more than one logical host needs to be associated with the new SAP MaxDB resource or when the IP alias logical host does not have the same name as the SAP MaxDB resource itself. SAP MaxDB is the resource for the *sapdb-logical-hostname* that you specified in [“Configuration Planning Questions” on page 20](#).

```
sapdb-logical-hostname
```

Specifies the logical hostname of the server on which the database is running. This hostname must be the logical hostname for the SAP MaxDB resource that you specified in [“Configuration Planning Questions” on page 20](#).

Note - If you require a fully qualified hostname, you must specify the fully qualified name with the `-h` option and you cannot use the fully qualified form in the resource name.

4. Enable the resource group that you created in [Step 1](#).

```
# clresourcegroup online -eM sapdb-rg
```

```
-eM
```

Enables the resource group `sapdb-rg` created in [Step 1](#) and moves it to the `MANAGED` state.

Example 5 Enabling SAP MaxDB to Run in a Cluster

This example shows the sequence of commands that are required to enable SAP MaxDB to run in a cluster. The commands are run on only one cluster node.

1. The following command creates a failover resource group to contain the SAP MaxDB application resources and the logical hostname for the SAP MaxDB resource. The resource group is named `sapdbrg`. The `sapdbrg` resource group can be brought online on all cluster nodes.

```
# clresourcegroup create sapdbrg
```

2. The following command adds a logical hostname resource to the `sapdbrg` resource group. The logical hostname of the server on which the database is running is `svr-1`. When the `sapdbrg` resource group is brought online, an attempt is made for each node to discover a network interface on the subnet that the hostname list identifies.

```
# clreslogicalhostname create -g sapdbrg -h svr-1 -d sapdbl
```

Note - If you require a fully qualified hostname, you must specify the fully qualified name with the `-h` option and you cannot use the fully qualified form in the resource name.

3. The following command moves the `sapdbrg` resource group to the `MANAGED` state, brings the resource group online, and monitors the resources in the resource group.

```
# clresourcegroup online -eM sapdbrg
```


Verifying the SAP MaxDB Installation and Configuration

Before you install the HA for SAP MaxDB packages, verify that the SAP MaxDB software is correctly installed and configured to run in a cluster. This verification does *not* verify that the SAP MaxDB application is highly available because the HA for SAP MaxDB data service is not yet installed.

▼ How to Verify SAP MaxDB Installation and Configuration on Each Node

Perform this procedure on each node that can master the SAP MaxDB resource group.

1. **Assume the root role on a node that can master the SAP MaxDB resource group.**
2. **Switch the SAP MaxDB resource group to the node that you logged in to in [Step 1](#).**

```
# clresourcegroup switch -n node sapdb-rg
```

```
-n node
```

Specifies the node to which the SAP MaxDB resource group is to be switched

```
sapdb-rg
```

Specifies that the SAP MaxDB resource group *sapdb-rg* is to be switched to another node

3. **Confirm that the SAP MaxDB database can be started and be stopped.**

- a. **Become the OS user that administers the SAP MaxDB database.**

```
# su - os-sapdb-adm-user
```

```
os-sapdb-adm-user
```

Specifies the UNIX user identity of the OS user that administers the SAP MaxDB database. This user's home directory contains the `.XUSER.62` file that was created during the installation and configuration of SAP MaxDB. For more information, see [“Installing and Configuring SAP MaxDB” on page 20](#). You specify this user when you set the `DB_User` extension property as explained in [“How to Register and Configure a SAP MaxDB Resource” on page 34](#).

- b. **Start the SAP xserver.**

```
$ x_server start
```

- c. **Manually start the SAP MaxDB database instance on the node that you logged in to in [Step 1](#).**

```
$ dbmcli -U sapdb-adm-key db_online
```

```
-U sapdb-adm-key
```

Specifies that the `dbmcli` command is run with the user key of the database user who administers the SAP MaxDB instance. This user key is created during the installation and configuration of SAP MaxDB. For more information, see [“Installing and Configuring SAP MaxDB” on page 20](#). You specify this user key when you set the `User_Key` extension property as explained in [“How to Register and Configure a SAP MaxDB Resource” on page 34](#).

- d. **Confirm that the SAP MaxDB database instance is started.**

- e. **Manually stop the SAP MaxDB database instance.**

```
$ dbmcli -U sapdb-adm-key db_offline
```

```
-U sapdb-adm-key
```

Specifies that the `dbmcli` command is run with the user key that you used for starting the database in [Step 3c](#)

- f. **Confirm that the SAP MaxDB database instance is stopped.**

Installing the HA for SAP MaxDB Package

If you did not install the HA for SAP MaxDB package during your initial Oracle Solaris Cluster installation, perform this procedure to install the package.

▼ How to Install the HA for SAP MaxDB Package

Perform this procedure on each cluster node where you want the HA for SAP MaxDB software to run.

1. **On the cluster node where you are installing the data service package, assume the root role.**
2. **Ensure that the data service package is available from the configured publisher and that the `solaris` and `ha-cluster` publishers are valid.**

```
# pkg list -a ha-cluster/data-service/sapdb
# pkg publisher
PUBLISHER                TYPE    STATUS  P  LOCATION
solaris                   origin  online  F  solaris-repository
ha-cluster                 origin  online  F  ha-cluster-repository
```

For information about setting the `solaris` publisher, see [“Adding, Modifying, or Removing Package Publishers”](#) in *Updating Systems and Adding Software in Oracle Solaris 11.4*.

Tip - Use the `-nv` options whenever you install or update to see what changes will be made, such as which versions of which packages will be installed or updated and whether a new BE will be created.

If you do not get any error messages when you use the `-nv` options, run the command again without the `-n` option to actually perform the installation or update. If you do get error messages, run the command again with more `-v` options (for example, `-nvv`) or more of the package FMRI pattern to get more information to help you diagnose and fix the problem. For troubleshooting information, see [Appendix A, “Troubleshooting Package Installation and Update,”](#) in *Updating Systems and Adding Software in Oracle Solaris 11.4*.

3. **Install the HA for SAP MaxDB software package.**

```
# pkg install ha-cluster/data-service/sapdb
```

4. **Verify that the package installed successfully.**

```
$ pkg info ha-cluster/data-service/sapdb
```

Installation is successful if output shows that State is Installed.

5. **Perform any necessary updates to the Oracle Solaris Cluster software.**

For instructions on updating your software, see [Updating Your Oracle Solaris Cluster 4.4 Environment](#).

Configuring the HASStoragePlus Resource Type to Work With HA for SAP MaxDB

For maximum availability of the SAP MaxDB database, resources that HA for SAP MaxDB requires must be available before the SAP MaxDB database instance is started. An example of such a resource is the file system where programs and libraries for the SAP MaxDB runtime environment reside. To ensure that these resources are available, configure the HASStoragePlus resource type to work with HA for SAP MaxDB.

For information about the relationship between resource groups and disk device groups, see [“Relationship Between Resource Groups and Device Groups” in *Planning and Administering Data Services for Oracle Solaris Cluster 4.4*](#).

Configuring the HASStoragePlus resource type to work with HA for SAP MaxDB involves registering and configuring an HASStoragePlus resource.

▼ How to Register and Configure an HASStoragePlus Resource

Perform this procedure on any one cluster node.

1. **Register the SUNW.HASStoragePlus resource type.**

```
# clresourcetype register SUNW.HASStoragePlus
```

2. **Create an HASStoragePlus resource for the global device group on which SAP MaxDB is installed.**

Create this resource in the SAP MaxDB resource group. This resource must perform an affinity switchover for all global devices that are defined for this resource.

```
# clresource create -d -g sapdb-rg \  
-t SUNW.HASStoragePlus -p FileSystemMountPoints=mountpoint-list \  
-p GlobalDevicePaths=sapdb-device-group \  
-p AffinityOn=TRUE hasp-resource
```

```
-d
```

Specifies that a new resource is to be created in a disabled state.

`-g sapdb-rg`

Specifies that the resource is to be added to the SAP MaxDB resource group.

`-t SUNW.HAStoragePlus`

Specifies that the resource is an instance of the SUNW.HAStoragePlus resource type.

`-p FileSystemMountPoints=mountpoint-list`

Specifies a list of valid mount points for the file system.

`-p GlobalDevicePaths=sapdb-device-group`

Specifies the name of the global device group on which the SAP MaxDB software is installed.

`-p AffinityOn=TRUE`

Specifies that this resource performs an affinity switchover for all global devices that are defined for this resource.

hasp-resource

Specifies that the resource that you are creating is named *hasp-resource*.

Example 6 Creating an HAStoragePlus Resource

```
# clresource create -g sapdbrg \  
-t SUNW.HAStoragePlus -p FileSystemMountPoints=/global/sapdbdata \  
-p GlobalDevicePaths=sapdbdg -p AffinityOn=TRUE hasprs
```

This example shows the creation of a SUNW.HAStoragePlus resource that has the following characteristics:

- The resource is named *hasprs*.
- The resource is a member of a resource group that is named *sapdbrg*. The creation of this resource group is shown in [Example 5, “Enabling SAP MaxDB to Run in a Cluster,” on page 24](#).
- The resource is an instance of the SUNW.HAStoragePlus resource type. The registration of this resource type is not shown in this example.
- The mount point for the file system is */global/sapdbdata*.
- The SAP MaxDB software is installed on a global device group that is named *sapdbdg*.
- The *hasprs* resource performs an affinity switchover for all global devices that are defined for this resource.

Next Steps Go to [“Registering and Configuring HA for SAP MaxDB” on page 30](#).

Registering and Configuring HA for SAP MaxDB

To enable HA for SAP MaxDB to make SAP MaxDB highly available, configure Oracle Solaris Cluster data services as follows:

- Configure SAP xserver as a multiple-master data service.
- Configure HA for SAP MaxDB as a failover data service.

Before you perform this procedure, ensure that the HA for SAP MaxDB data service packages are installed.



Caution - One SAP xserver serves multiple SAP MaxDB instances and, if SAP liveCache is used, multiple SAP liveCache instances in the cluster. Therefore, do *not* configure more than one SAP xserver resource on the same cluster. If more than one SAP xserver resource runs on the same cluster, conflicts between the SAP xserver resources occur. These conflicts cause all SAP xserver resources to become unavailable. If you attempt to start the SAP xserver a second time, the attempt fails. The error message `Address already in use` is also displayed.

Setting HA for SAP MaxDB Extension Properties

The sections that follow contain instructions for registering and configuring resources. These instructions explain how to set *only* extension properties that HA for SAP MaxDB requires you to set. For information about all HA for SAP MaxDB extension properties, see [Appendix A, “HA for SAP MaxDB Extension Properties”](#). You can update some extension properties dynamically. You can update other properties, however, only when you create or disable a resource. The Tunable entry indicates when you can update a property.

To set an extension property of a resource, include the following option to modify the resource:

`-p property=value`

`-p property`

Identifies the extension property that you are setting

`value`

Specifies the value to which you are setting the extension property

You can also use the procedures in [Chapter 2, “Administering Data Service Resources”](#) in [Planning and Administering Data Services for Oracle Solaris Cluster 4.4](#) to configure resources after the resources are created.

Administering SAP xserver as a User Other Than Root

You might be required to administer SAP xserver as a user other than root. In this situation, you must create and define that user as follows:

- You must create that user on all cluster nodes that master SAP xserver.
- You must define that user when you register and configure an SAP xserver resource. To define the user who administers SAP xserver, set the Xserver_User extension property when you create an SAP xserver resource. For more information about the Xserver_User extension property, see [“SUNW.sap_xserver Extension Properties” on page 49](#).

▼ How to Register and Configure an SAP xserver Resource

1. **Assume the root role on a cluster node.**
2. **Register the SUNW.sap_xserver resource type.**

```
# clresourcetype register SUNW.sap_xserver
```

3. **Create a scalable resource group for the SAP xserver resource.**

Configure SAP xserver so that SAP xserver starts on all nodes to which the SAP MaxDB resource can fail over. To implement this configuration, ensure that the node list of the SAP xserver resource group contains all nodes that are in the node list of the SAP MaxDB resource group. This resource group is created when the procedure [“How to Enable SAP MaxDB to Run in a Cluster” on page 23](#) is performed.

```
# clresourcegroup create \  
-p Maximum primaries=nodes-in-sapdb-rg \  
-p Desired primaries=nodes-in-sapdb-rg xserver-rg
```

```
-p Maximum primaries=nodes-in-sapdb-rg
```

Specifies the maximum number of nodes on which the SAP xserver resource can start. This number is equal to the number of nodes that are in the node list of the SAP MaxDB resource group. You must specify the same number as the value of the Desired_primaries property.

-p `Desired primaries=nodes-in-sapdb-rg`

Specifies the desired number of nodes on which the SAP xserver resource can start. This number is equal to the number of nodes that are in the node list of the SAP MaxDB resource group. You must specify the same number as the value of the `Maximum primaries` property.

xserver-rg

Specifies that the resource group that you are creating is named *xserver-rg*.

4. Add the `HASStoragePlus` resource to the SAP xserver resource group.

```
# clresource create -g xserver-rg \  
-t SUNW.HASStoragePlus \  
-p FileSystemMountPoints=mountpoints \  
-p AffinityOn=false xserver-storage-resource
```

-g *xserver-rg*

Specifies that the resource that you are creating is added to the resource group *xserver-rg*.

-t `SUNW.HASStoragePlus`

Specifies that the resource type of the resource you are creating is `SUNW.HASStoragePlus`.

-p `FileSystemMountPoints=mountpoint,...`

Specifies the mount points for the resource group you are creating.

-p `AffinityOn=false`

Indicates that the SAP xserver resource does not have to be colocated with the device group.

xserver-storage-resource

Specifies that the resource that you are creating is named *xserver-storage-resource*.

For more details on how to set up an `HASStoragePlus` resource, see [“Enabling Highly Available Local File Systems”](#) in *Planning and Administering Data Services for Oracle Solaris Cluster 4.4*.

5. Create an SAP xserver resource in the resource group that you created in [Step 3](#).

```
# clresource create -d -g xserver-rg \  
-t SUNW.sap_xserver \  
-p Resource_dependencies_offline_restart=storage-resource \  
-p Resource_dependencies=rest-of-the-tree
```


`-g xserver-rg`

Specifies that the resource is to be added to the resource group that you created in [Step 3](#)

`-t SUNW.sap_xserver`

Specifies that the resource is an instance of the `SUNW.sap_xserver` resource type

`-p Resource_dependencies_offline_restart=storage-resource`

Sets a resource dependency between `storage-resource` and the `HASStoragePlus` resource we created in [Step 4](#).

`storage-resource`

Specifies that the resource that you are creating is named `storage-resource`.

6. Enable the resource group that you created in [Step 3](#).

```
# clresourcegroup online -eM xserver-rg
```

`-eM`

Enables the resource group and moves it to the `MANAGED` state.

`xserver-rg`

Specifies the name of the resource group.

Example 7 Configuring a `SUNW.sap_xserver` Resource

This example shows the sequence of commands that are required to configure an SAP xserver resource. The commands are run on only one cluster node.

1. The following command creates a multiple-master resource group to contain an SAP xserver resource for a four-node cluster. The resource group is named `xsvrrg`. The `xsvrrg` resource group can be brought online on all cluster nodes.

```
# clresourcegroup create \  
-p Maximum primaries=4 \  
-p Desired primaries=4 xsvrrg
```

2. The following command adds the `HASStoragePlus` resource to the SAP xserver resource group. The `xserver-storage-resource` is called `xsstorrs` and the mount point, `mtp1`.

```
# clresource create -d -g xsvrrg \  
-t SUNW.HASStoragePlus \  
-p filesystemmountpoints=mtp1 \  
-p affinityon=false xsstorrs
```

3. The following command creates an SAP xserver resource that is named `xsvrrs` in the `xsvrrg` resource group. The SAP xserver resource is an instance of the `SUNW.sap_xserver` resource type. The registration of this resource type is not shown in this example.

```
# clresource create -d -g xsvrrg -t SUNW.sap_xserver \  
-p resource_dependencies_offline_restart=storage-resource \  
-p resource_dependencies=rest-of-the-tree
```

4. The following command moves the `xsvrrg` resource group to the `MANAGED` state and brings the resource group online.

```
# clresourcegroup online -eM xsvrrg
```

▼ How to Register and Configure a SAP MaxDB Resource

1. Register the `SUNW.sapdb` resource type.

```
# clresourcetype register SUNW.sapdb
```

2. Create an SAP MaxDB resource in the SAP MaxDB resource group.

Ensure that the SAP MaxDB resource depends on the following resources:

- The `HASStoragePlus` resource for the global device group on which SAP MaxDB is installed.
- The SAP xserver resource.

When you create this resource, specify the following information about the SAP MaxDB database instance. This information is created when SAP MaxDB is installed and configured as explained in [“Installing and Configuring SAP MaxDB” on page 20](#).

- The name of the SAP MaxDB database.
- The UNIX user identity of the OS user who administers the SAP MaxDB database instance.
- The user key of the database user who administers the SAP MaxDB database instance.

```
# clresource create -d -g sapdb-rg \  
-t SUNW.sapdb \  
-p DB_Name=db-name \  
-p DB_User=os-sapdb-adm-user \  
-p User_Key=sapdb-adm-key \  
-p Resource_dependencies_offline_restart=storage-resource \  
-p Resource_dependencies=rest-of-the-tree
```

- d
Specifies that the resource that you are creating is not immediately enabled.
- g *sapdb-rg*
Specifies that the resource is to be added to the SAP MaxDB resource group.
- t *SUNW.sapdb*
Specifies that the resource is an instance of the *SUNW.sapdb* resource type.
- p *DB_Name=db-name*
Specifies the name of the SAP MaxDB database instance in uppercase.
- p *DB_User=os-sapdb-adm-user*
Specifies the UNIX user identity of the OS user who administers the SAP MaxDB database. This user's home directory contains the *.XUSER.62* file that was created during the installation and configuration of SAP MaxDB. For more information, see [“Installing and Configuring SAP MaxDB” on page 20](#).
- p *User_Key=sapdb-adm-key*
Specifies the user key of the database user who administers the SAP MaxDB database instance. This user key is created during the installation and configuration of SAP MaxDB. For more information, see [“Installing and Configuring SAP MaxDB” on page 20](#).
- p *Resource_dependencies_offline_restart=storage-resource *
Specifies that the SAP MaxDB resource depends on the *HASStoragePlus* resource for the global device group on which SAP MaxDB is installed.
- sapdb-rs*
Specifies that the resource that you are creating is named *sapdb-rs*.

3. Ensure that the SAP MaxDB resource group is brought online only on a node where the SAP xserver resource group is online.

To meet this requirement, create on the SAP MaxDB resource group a strong positive affinity for the SAP xserver resource group.

```
# clresourcegroup set -p RG_affinities=++xserver-rg sapdb-rg
```

- p *RG_affinities=++xserver-rg*
Specifies that the SAP MaxDB resource group declares a strong positive affinity for the SAP xserver resource group.

sapdb-rg

Specifies that the SAP MaxDB resource group is to be modified.

4. Enable the SAP MaxDB resource group.

```
#clresourcegroup online -eM sapdb-rg
```

-eM

Enables the SAP MaxDB resource group and moves it to the MANAGED state.

sapdb-rg

Specifies the name of the SAP MaxDB resource group to be brought online.

5. (Optional) Consider configuring your cluster to prevent noncritical resource groups from being brought online on the same node as the SAP MaxDB resource group.

You might plan to run lower-priority services on a node to which the SAP MaxDB resource can fail over. In this situation, consider using resource group affinities to shut down the noncritical services when the SAP MaxDB resource fails over to the node.

To specify this behavior, declare on the resource group for each noncritical service a strong negative affinity for the SAP MaxDB resource group.

```
# clresourcegroup set -p RG_affinities---sapdb-rg noncritical-rg
```

-p

Sets the resource group property to the specified value.

noncritical-rg

Specifies the name of the noncritical resource group.

Example 8 Creating a SUNW.sapdb Resource

```
# clresource create -d -g sapdbrg -t SUNW.sapdb \  
-p DB_Name=TST -p DB_User=dbadmin \  
-p User_Key=DEFAULT -p Resource_dependencies_offline_restart=hasprsr,xsrvrss sapdbrs
```

This example shows the creation of a SUNW.sapdb resource that has the following characteristics:

- The resource is named sapdbrs.

- The resource is a member of a resource group that is named `sapdbrg`. The creation of this resource group is shown in [Example 5, “Enabling SAP MaxDB to Run in a Cluster,” on page 24](#).
- The resource is an instance of the `SUNW.sapdb` resource type. The registration of this resource type is not shown in this example.
- The SAP MaxDB database instance that is associated with this resource is named `TST`.
- The UNIX user identity of the OS user who administers the SAP MaxDB database is `dbadmin`.
- The user key of the database user who administers the SAP MaxDB database is `DEFAULT`.
- The SAP MaxDB resource depends on the following resources:
 - An `HASStoragePlus` resource that is named `hasprs`. The creation of the `hasprs` resource is shown in [Example 6, “Creating an HASStoragePlus Resource,” on page 29](#).
 - A `SUNW.sap_xserver` resource that is named `xsvrrs`. The creation of the `xsvrrs` resource is shown in [Example 7, “Configuring a SUNW.sap_xserver Resource,” on page 33](#).

Tuning the HA for SAP MaxDB Fault Monitors

Fault monitoring for the HA for SAP MaxDB data service is provided by the following fault monitors:

- The SAP MaxDB fault monitor
- The SAP xserver fault monitor

Each fault monitor is contained in a resource whose resource type is shown in the following table.

TABLE 3 Resource Types for HA for SAP MaxDB Fault Monitors

Fault Monitor	Resource Type
SAP MaxDB	<code>SUNW.sapdb</code>
SAP xserver	<code>SUNW.sap_xserver</code>

System properties and extension properties of these resources control the behavior of the fault monitors. The default values of these properties determine the preset behavior of the fault monitors. The preset behavior should be suitable for most Oracle Solaris Cluster installations. Therefore, you should tune the HA for SAP MaxDB fault monitors *only* if you need to modify this preset behavior.

Tuning the HA for SAP MaxDB fault monitors involves the following tasks:

- Setting the interval between fault monitor probes
- Setting the timeout for fault monitor probes
- Defining the criteria for persistent faults
- Specifying the failover behavior of a resource

For more information, see [“Tuning Fault Monitors for Oracle Solaris Cluster Data Services” in *Planning and Administering Data Services for Oracle Solaris Cluster 4.4*](#). Information about the HA for SAP MaxDB fault monitors that you need to perform these tasks is provided in the subsections that follow.

HA for SAP MaxDB also enables you to control how the fault monitor responds if the SAP MaxDB parent kernel process is not running. For more information, see [“Forcing the SAP MaxDB Database Instance to Be Restarted if the Parent Kernel Process Is Terminated” on page 40](#).

Tune the HA for SAP MaxDB fault monitors when you register and configure HA for SAP MaxDB. For more information, see [“Registering and Configuring HA for SAP MaxDB” on page 30](#).

Factors That Affect the Interval Between Fault Monitor Probes

To determine whether SAP xserver and the SAP MaxDB database instance are operating correctly, the HA for SAP MaxDB fault monitors probe these resources periodically. The optimum interval between fault monitor probes depends on the time that is required to respond to a fault in a resource. This time depends on how the complexity of the resource affects the time that is required for operations such as restarting the resource.

For example, SAP xserver is a much simpler resource and can be restarted much quicker than SAP MaxDB. Therefore, the optimum interval between fault monitor probes of SAP xserver is shorter than the optimum interval between probes of SAP MaxDB.

Operations by the HA for SAP MaxDB Fault Monitors During a Probe

The optimum timeout for fault monitor probes depends on the operations that a fault monitor performs to probe the resource.

Operations by the SAP MaxDB Fault Monitor During a Probe

During a probe, the SAP MaxDB fault monitor performs the following operations:

1. The SAP MaxDB fault monitor determines whether the SAP MaxDB database instance is online.
2. If the SAP MaxDB database instance is online, the SAP MaxDB fault monitor determines whether the parent kernel process of the SAP MaxDB database instance is running. You can control how the fault monitor responds if the parent kernel process is not running. For more information, see [“Forcing the SAP MaxDB Database Instance to Be Restarted if the Parent Kernel Process Is Terminated”](#) on page 40.
3. The SAP MaxDB fault monitor determines whether SAP xserver is available. This fault monitoring supplements the fault monitoring that the SAP xserver fault monitor provides.

Operations by the SAP xserver Fault Monitor During a Probe

During a probe, the SAP xserver fault monitor determines whether SAP xserver is available.

Faults Detected by the HA for SAP MaxDB Fault Monitors

Faults that each HA for SAP MaxDB fault monitor detects are described in the subsections that follow.

Faults Detected by the SAP MaxDB Fault Monitor

The SAP MaxDB fault monitor detects the following faults in SAP MaxDB:

- A status of the SAP MaxDB database instance that is not ONLINE, for example, OFFLINE or ADMIN
- Unexpected termination of the parent kernel process of the SAP MaxDB database instance

The SAP MaxDB fault monitor also detects the unavailability of SAP xserver. This fault monitoring supplements the fault monitoring that the SAP xserver fault monitor provides.

Note - If the SAP MaxDB fault monitor detects that SAP xserver is unavailable twice within the retry interval, the SAP MaxDB fault monitor restarts SAP MaxDB. By restarting SAP MaxDB, the fault monitor ensures that the SAP MaxDB database fails over to another node when SAP xserver is persistently unavailable.

Faults Detected by the SAP xserver Fault Monitor

The SAP xserver fault monitor detects following faults:

- **Unavailability of SAP xserver.** Unavailability of SAP xserver is also detected by the SAP MaxDB fault monitor.
- **Persistent system errors.** A persistent system error is a system error that occurs four times within the retry interval. If a persistent system error occurs, the fault monitor restarts SAP xserver.

Recovery Actions in Response to Detected Faults

To minimize the disruption that transient faults in a resource cause, a fault monitor restarts the resource in response to such faults. For persistent faults, more disruptive action than restarting the resource is required:

- For the SAP MaxDB resource, the fault monitor fails over the resource to another node. The SAP MaxDB resource is a failover resource.
- For the SAP xserver resource, the fault monitor takes the resource offline. The SAP xserver is a multiple-master resource.

Forcing the SAP MaxDB Database Instance to Be Restarted if the Parent Kernel Process Is Terminated

By default, unexpected termination of the parent kernel process does *not* cause the SAP MaxDB fault monitor to restart the SAP MaxDB database instance. The SAP MaxDB database instance can continue to function without the parent kernel process. Restarting the SAP MaxDB database instance in this situation might cause unnecessary unavailability of the SAP MaxDB database instance. Therefore, you should force the SAP MaxDB database instance to be restarted *only* if you require a feature that the parent kernel process provides. An example of such a feature is maintaining the integrity of the log history.

To force the SAP MaxDB database instance to be restarted if the parent kernel process is terminated, set the `Restart_if_Parent_Terminated` extension property of the `SUNW.sapdb` resource to `True`.

Verifying the HA for SAP MaxDB Installation and Configuration

After you install, register, and configure HA for SAP MaxDB, verify the HA for SAP MaxDB installation and configuration. Verifying the HA for SAP MaxDB installation and configuration determines if the HA for SAP MaxDB data service makes the SAP MaxDB application highly available.

Verifying the HA for SAP MaxDB installation involves verifying the operation of the following fault monitors:

- The SAP MaxDB fault monitor
- The SAP xserver fault monitor

▼ How to Verify the Operation of the SAP MaxDB Fault Monitor

Perform this procedure on each node where SAP MaxDB can run.

1. **Assume a root role to a node that can master the SAP MaxDB resource group.**
2. **Switch the SAP MaxDB resource group to the node that you logged in to in [Step 1](#).**

```
# clresourcegroup switch -n node sapdb-rg
```

node

Specifies the node to which the SAP MaxDB resource group is to be switched

sapdb-rg

Specifies the name of the SAP MaxDB resource group is to be switched to another node

3. **Abnormally terminate SAP MaxDB.**

- a. **Determine the process identities of all kernel processes for the SAP MaxDB database instance that you are running.**

```
# ps -ef | grep kernel | grep db-name
```

db-name

Specifies the name of the SAP MaxDB database instance in uppercase

- b. **Kill all kernel processes for the SAP MaxDB database instance that you are running.**

```
# kill -9 sapdb-kernel-pid
```

sapdb-kernel-pid

Specifies the process identities of the SAP MaxDB kernel processes that you determined in [Step 3a](#)

4. **Confirm that the HA for SAP MaxDB fault monitor performs the appropriate operation from the following list:**

- Restarting the SAP MaxDB resource
- Failing over the SAP MaxDB resource to another node

The expected behavior of the fault monitor depends on the failure history of the resource and the value of the `Failover_enabled` extension property. For more information, see the following sections:

- [“Tuning the HA for SAP MaxDB Fault Monitors” on page 37](#)
- [“SUNW.sapdb Extension Properties” on page 45](#)

5. **Terminate SAP MaxDB normally.**

- a. **Become the OS user who administers the SAP MaxDB database.**

```
# su - os-sapdb-adm-user
```

os-sapdb-adm-user

Specifies the UNIX user identity of the OS user who administers the SAP MaxDB database. This user's home directory contains the `.XUSER.62` file that was created during the installation and configuration of SAP MaxDB. For more information, see [“Installing and Configuring SAP MaxDB” on page 20](#). You specify this user when you set the `DB_User` extension property as explained in [“How to Register and Configure a SAP MaxDB Resource” on page 34](#).

b. Manually stop the SAP MaxDB database instance.

```
# dbmcli -U sapdb-adm-key db_offline
```

```
-U sapdb-adm-key
```

Specifies that the `dbmcli` command is run with the user key of the database user who administers the SAP MaxDB database. This user key is created during the installation and configuration of SAP MaxDB. For more information, see [“Installing and Configuring SAP MaxDB” on page 20](#). You specify this user key when you set the `User_Key` extension property as explained in [“How to Register and Configure a SAP MaxDB Resource” on page 34](#).

6. Confirm that the HA for SAP MaxDB fault monitor performs the appropriate operation from the following list:

- Restarting the SAP MaxDB resource
- Failing over the SAP MaxDB resource to another node

The expected behavior of the fault monitor depends on the failure history of the resource and the value of the `Failover_enabled` extension property. For more information, see the following sections:

- [“Tuning the HA for SAP MaxDB Fault Monitors” on page 37](#)
- [“SUNW.sapdb Extension Properties” on page 45](#)

▼ How to Verify the Operation of the SAP xserver Fault Monitor

Perform this procedure on each node that can master SAP xserver.

1. **Log in to a node that can master SAP xserver.**
2. **Abnormally terminate SAP xserver.**
 - a. **Determine the process identities of all SAP xserver processes.**

```
# ps -ef | grep vsrver
```

- b. **Kill all SAP xserver processes.**

```
# kill -9 xserver-pid
```

xserver-pid

Specifies the process identities of the SAP xserver processes that you determined in [Step 2a](#)

3. Confirm that the SAP xserver fault monitor restarts the SAP xserver resource.

4. Terminate SAP xserver normally.

a. Become the OS user who administers SAP xserver.

```
# su - os-sapxsrvr-adm-user
```

os-sapxsrvr-adm-user

Specifies the UNIX user identity of the OS user who administers SAP xserver. By default, this user is root. You can specify this user by setting the Xserver_User extension property. For more information, see [“SUNW.sap_xserver Extension Properties” on page 49](#).

b. Manually stop the SAP xserver.

```
# x_server stop
```

5. Confirm that the SAP xserver fault monitor restarts the SAP xserver resource.

HA for SAP MaxDB Extension Properties

Extension properties for HA for SAP MaxDB resource types are described in the following sections.

- [“SUNW.sapdb Extension Properties” on page 45](#)
- [“SUNW.sap_xserver Extension Properties” on page 49](#)

For details about system-defined properties, see the [r_properties\(7\)](#) man page and the [rg_properties\(7\)](#) man page.

SUNW.sapdb Extension Properties

The `SUNW.sapdb` resource type represents the SAP MaxDB application in a Oracle Solaris Cluster configuration. The extension properties of this resource type are as follows:

dbmcli_Start_Option

The option that is passed to the `dbmcli` command to start the SAP MaxDB database instance.

Data type	String
Default	<code>db_online</code>
Range	Not applicable
Tunable	When disabled

DB_Name

The name of the SAP MaxDB database instance in uppercase. This name is created when SAP MaxDB is installed and configured as explained in [“Installing and Configuring SAP MaxDB” on page 20](#).

Data type	String
Default	No default defined
Range	Not applicable
Tunable	When disabled

DB_User

The UNIX user identity of the operating system (OS) user who administers the SAP MaxDB database instance. This user's home directory contains the .XUSER.62 file that was created during the installation and configuration of SAP MaxDB. For more information, see [“Installing and Configuring SAP MaxDB” on page 20](#).

Data type	String
Default	No default defined
Range	Not applicable
Tunable	When disabled

Failover_enabled

Specifies whether the fault monitor fails over the SAP MaxDB resource if the number of attempts to restart exceeds `Retry_count` within the time that `Retry_interval` specifies. The possible values of this extension property are as follows:

- `True` – Specifies that the fault monitor fails over the SAP MaxDB resource
- `False` – Specifies that the fault monitor does *not* fail over the SAP MaxDB resource

Data type	Boolean
Default	True
Range	Not applicable
Tunable	Any time

Independent_Program_Path

The full path to the directory that contains the following programs and libraries for the SAP MaxDB application:

- Programs that are independent of the database software version

- Libraries for the client runtime environment

HA for SAP MaxDB determines the path to the `dbmcli` command from the value of this property. The `dbmcli` command resides in the `bin` subdirectory of the directory that this property specifies.

Data type	String
Default	<code>/sapdb/programs</code>
Range	Not applicable
Tunable	When disabled

Monitor_retry_count

The maximum number of restarts by the process monitor facility (PMF) that are allowed for the fault monitor.

Data type	Integer
Default	4
Range	No range defined
Tunable	Any time

Monitor_retry_interval

The period of time in minutes during which the PMF counts restarts of the fault monitor.

Data type	Integer
Default	2
Range	No range defined
Tunable	Any time

Pid_Dir_Path

The full path to the directory under which files that store the process identities of SAP MaxDB kernel processes are created. The process identities of SAP MaxDB kernel processes are stored in the following files:

- `pid-dir/ppid/db-name`

- *pid-dir/pid/db-name*

The replaceable items in these file paths are as follows:

- *pid-dir* is the directory that the `Pid_Dir_Path` extension property specifies
- *db-name* is the name of the SAP MaxDB database instance that the `DB_Name` extension property specifies

Data type	String
Default	<code>/var/spool/sql</code>
Range	Not applicable
Tunable	When disabled

Probe_timeout

The timeout value in seconds that the fault monitor uses to probe an SAP MaxDB database instance.

Data type	Integer
Default	90
Range	30–99,999
Tunable	Any time

Restart_if_Parent_Terminated

Determines whether the fault monitor restarts the SAP MaxDB database instance if the parent kernel process is terminated. The possible values of this extension property are as follows:

- `True` – Specifies that the fault monitor restarts the SAP MaxDB database instance if the parent kernel process is terminated
- `False` – Specifies that the fault monitor does *not* restart the SAP MaxDB database instance if the parent kernel process is terminated

Data type	Boolean
Default	<code>False</code>
Range	Not applicable
Tunable	Any time

User_Key

The user key of the database user who administers the SAP MaxDB database instance. This user key is created when SAP MaxDB is installed and configured as explained in [“Installing and Configuring SAP MaxDB” on page 20](#).

Data type	String
Default	No default defined
Range	Not applicable
Tunable	When disabled

SUNW.sap_xserver Extension Properties

The SUNW.sap_xserver resource type represents SAP xserver in a Oracle Solaris Cluster configuration. The extension properties of this resource type are as follows:

Confdir_List

The full path to the directory that contains the SAP MaxDB software and SAP MaxDB database instance.

Data type	String
Default	/sapdb
Range	Not applicable
Tunable	At creation

Independent_Program_Path

The full path to the directory that contains the following programs and libraries for SAP xserver:

- Programs that are independent of the database software version
- Libraries for the client runtime environment

HA for SAP MaxDB determines the path to the `x_server` command from the value of this property. The `x_server` command resides in the `bin` subdirectory of the directory that this property specifies.

Data type	String
Default	No default defined
Range	Not applicable
Tunable	When disabled
Introduced in release	3.1 4/04

Monitor_retry_count

The maximum number of restarts by the PMF that are allowed for the fault monitor.

Data type	Integer
Default	4
Range	No range defined
Tunable	Any time

Monitor_retry_interval

The period of time in minutes during which the PMF counts restarts of the fault monitor.

Data type	Integer
Default	2
Range	No range defined
Tunable	Any time

Probe_timeout

The timeout value in seconds for fault monitor probes.

Data type	Integer
Default	120
Range	No range defined
Tunable	Any time

Soft_Stop_Pct

The percentage of the Stop method timeout that is used to stop SAP xserver by using the SAP utility `x_server stop`. If this timeout is exceeded, the SIGKILL signal is used to stop all SAP xserver processes.

Data type	Integer
Default	50
Range	1–100
Tunable	When disabled

Xserver_User

The UNIX user identity of the OS user who administers SAP xserver.

Data type	String
Default	root
Range	Not applicable
Tunable	At creation

Index

A

- Address already in use error message, 30
- affinities
 - resource groups
 - creating, 35
 - planning, 19
- affinity switchover, 28

C

- caution notice
 - multiple SAP xserver resources, 30
- clusters
 - running SAP MaxDB in, 23
- Confdir_List extension property
 - SUNW.sap_xserver resource type, 49
- configuring
 - device groups
 - performing, 28
 - planning, 19
 - file systems
 - performing, 28, 28
 - planning, 19
 - HA for SAP MaxDB
 - overview, 14
 - performing, 30
 - planning, 15
 - HASStoragePlus resource
 - performing, 28
 - planning, 19
 - SAP MaxDB application, 20
- creating
 - HASStoragePlus resource, 28

- SAP MaxDB resource, 34
- SAP MaxDB resource group, 23
- SAP xserver resource, 32
- SAP xserver resource group, 31
- .XUSER.62 file, 21

D

- database instance *See* SAP MaxDB database instance
- database users
 - identity of OS user, 46
 - sample definition, 22
 - user key for, 49
- DB_Name extension property, 45
- DB_User extension property, 46
- dbmcli command
 - path to, 47
 - start option, 45
- dbmcli_Start_Option extension property, 45
- defining
 - SAP MaxDB instance user, 21
 - SAP xserver user
 - planning for nondefault, 20
 - specifying nondefault, 31
- dependencies
 - device groups
 - creating, 34
 - planning, 19, 19
 - SAP MaxDB resource
 - creating, 34
 - planning, 19, 19
- device groups
 - configuring

- performing, 28
- planning, 19
- installation of SAP MaxDB, 21
- SAP MaxDB application, 19

directories, 45

- See also* paths
- /usr/spool/sql, 21, 22

E

enabling

- SAP MaxDB resource group, 36
- SAP xserver resource group, 33

extension properties, 45, 45

- See also* properties
- See also* system properties
- SUNW.sap_xserver resource type, 49
- SUNW.sapdb resource type, 45

F

Failover_enabled extension property

- SUNW.sapdb resource type, 46

fault monitors

- faults detected by, 39
- probe interval, 38
- probe timeout, 38
- response to faults, 39
- SAP MaxDB
 - faults detected, 39
 - resource type for, 37
 - verifying operation of, 41
- SAP xserver
 - faults detected, 40
 - resource type for, 37
 - verifying operation of, 43
- tuning, 37

faults

- recovery actions, 40
- responses to, 39

file systems

- configuration

- performing, 28, 28
- planning, 19
- protection by data services, 14

files

- process identity, 47
- system configuration, 20

H

HA for SAP MaxDB

- configuration
 - performing, 30
 - planning, 15
 - with HASToragePlus resource, 28
- fault monitors, 37
- installing, 26
 - verifying installation, 41
- overview, 13
- SAP liveCache application, use with, 17
- SAP NetWeaver application, use with, 17
- service configuration, 16
- software package, installing, 26

HASToragePlus resource

- configuration
 - performing, 28
 - planning, 19
- dependency of SAP MaxDB resource on
 - creating, 34
 - planning, 19
- resource group for, 28
- SAP MaxDB device group, 19

I

Independent_Program_Path extension property

- SUNW.sap_xserver resource type, 49
- SUNW.sapdb resource type, 46

installing

- HA for SAP MaxDB, 26
 - overview, 14
 - verifying installation, 41
- SAP MaxDB application, 20

intervals

fault monitor probes, 38

K

kernel processes

identities, 47

termination of parent

extension property, 48

restarting SAP MaxDB after, 40

L

libraries

SAP MaxDB

SUNW.sap_xserver resource type, 49

SUNW.sapdb resource type, 46

SAP xserver, 49

locations *See* paths

log history

preserving, 40

logical hostnames

resource group for

creating, 23

enabling, 25

planning, 20

resources

creating, 23

planning, 20

M

maximum values

nodes for SAP xserver, 31

restarts

SUNW.sap_xserver resource type, 50

SUNW.sapdb resource type, 47

Monitor_retry_count extension property

SUNW.sap_xserver resource type, 50

SUNW.sapdb resource type, 47

Monitor_retry_interval extension property

SUNW.sap_xserver resource type, 50

SUNW.sapdb resource type, 47

N

names

SAP MaxDB database instance, 45

network addresses *See* logical hostnames

NFS file system

protection by data services, 14

nodes

for SAP xserver and SAP MaxDB, 16

O

operating system users

of SAP MaxDB database instance

defining, 21

extension property for, 46

sample definition, 22

of SAP xserver

defining, 20

extension property for, 51

Oracle Solaris Cluster HA for SAP liveCache

relation to SUNW.sap_xserver resource type, 14

Oracle Solaris Cluster software

publisher, 27, 27

overriding

default SAP xserver users, 31

P

package, 26

parent kernel processes

extension property, 48

restarting SAP MaxDB after termination of, 40

paths

dbmcli command, 47

process identity files, 47

SAP MaxDB programs and libraries

SUNW.sap_xserver resource type, 49

SUNW.sapdb resource type, 46

SAP xserver programs and libraries, 49

x_server command, 49

persistent faults

recovery actions, 40

Pid_Dir_Path extension property, 47

- Probe_timeout extension property
 - SUNW.sap_xserver resource type, 50
 - SUNW.sapdb resource type, 48
- processes
 - identities, 47
 - termination of parent
 - extension property, 48
 - restarting SAP MaxDB after, 40
- programs
 - SAP MaxDB
 - SUNW.sap_xserver resource type, 49
 - SUNW.sapdb resource type, 46
 - SAP xserver, 49
- protection
 - SAP MaxDB application, 14
- publisher
 - Oracle Solaris Cluster software, 27, 27

R

- recovery actions
 - after faults, 40
- registering
 - SUNW.HASStoragePlus resource type, 28
 - SUNW.sap_xserver resource type
 - during initial set up, 31
 - SUNW.sapdb resource type, 34
- resource groups
 - HASStoragePlus resource, 28
 - logical hostname
 - creating, 23
 - enabling, 25
 - logical hostnames
 - planning, 20
 - SAP MaxDB
 - creating, 23
 - enabling, 25
 - planning, 20
 - SAP xserver
 - creating, 31
 - enabling, 33
 - planning, 16
- resource types

- fault monitors, 37
- SUNW.HASStoragePlus, 28
 - See also* HASStoragePlus resource
 - registering, 28
- SUNW.nfs, 14
- SUNW.sap_xserver
 - extension properties, 49
 - initial registration, 31
 - instantiating, 32
 - protection by, 14
 - relation to Oracle Solaris Cluster HA for SAP liveCache, 14
- SUNW.sapdb
 - extension properties, 45
 - initial registration, 34
 - instantiating, 34
 - protection by, 14
- resources
 - logical hostname
 - creating, 23
 - planning, 20
 - SAP MaxDB
 - creating, 34
 - SAP xserver
 - creating, 32
- responses
 - to faults, 39
- Restart_if_Parent_Terminated extension property
 - SUNW.sapdb resource type, 48
 - tuning, 41
- restarts
 - interval between
 - SUNW.sap_xserver resource type, 50
 - SUNW.sapdb resource type, 47
 - maximum allowed
 - SUNW.sap_xserver resource type, 50
 - SUNW.sapdb resource type, 47

S

- SAP liveCache application
 - use with HA for SAP MaxDB, 17
- SAP MaxDB application

- configuring, 20
 - device group for, 19
 - fault monitor, 37
 - installing, 20
 - paths to programs and libraries
 - SUNW.sap_xserver resource type, 49
 - SUNW.sapdb resource type, 46
 - processes
 - paths to process identity files, 47
 - termination of parent, 40, 48
 - protection by data services, 14
 - resource group for
 - creating, 23
 - enabling, 25
 - planning, 20
 - running in cluster, 23
 - software versions, 16
 - termination of parent kernel process, 40
 - verifying installation and configuration, 25
- SAP MaxDB database instance
- database user, 49
 - name, 45
 - operating system user, 46
 - starting
 - dbmcli command options, 45
 - SAP MaxDB verification, 26
 - stopping, 26
- SAP MaxDB resource
- creating, 34
 - dependency on other resources
 - creating, 34
 - planning, 19
- SAP MaxDB resource group
- affinity for SAP xserver resource group
 - creating, 35
 - planning, 19
- SAP NetWeaver application
- use with HA for SAP MaxDB, 17
- SAP xserver
- administration by nondefault users
 - planning, 20
 - specifying, 31
 - caution notice, 30
 - fault monitor, 37
 - multiple instances of, 30
 - nodes for, 16
 - operating system user, 51
 - paths to programs and libraries, 49
 - protection by data services, 14
 - resource group for
 - creating, 31
 - enabling, 33
 - planning, 16
 - service configuration, 16
 - starting, 25
 - stopping
 - command for, 44
 - time allowed for, 51
- SAP xserver resource, 32
- dependency of SAP MaxDB resource on
 - creating, 34
 - planning, 19
- SAP xserver resource group
- affinity of SAP MaxDB resource group for
 - creating, 35
 - planning, 19
- SIGKILL signal, 51
- Soft_Stop_Pct extension property, 51
- software package, 26
- starting
- SAP MaxDB database instance
 - dbmcli command options, 45
 - SAP MaxDB verification, 26
 - SAP xserver, 25
- stopping
- SAP MaxDB database instance, 26
 - SAP xserver
 - command for, 44
 - time allowed for, 51
- SUNW.HAStoragePlus resource type, 28
- See also* HAStoragePlus resource
 - registering, 28
- SUNW.nfs resource type, 14
- SUNW.sap_xserver resource type
- extension properties, 49
 - instantiating, 32

- protection by, 14
- registering
 - during initial setup, 31
 - relation to Oracle Solaris Cluster HA for SAP liveCache, 14
- SUNW.sapdb resource type
 - extension properties, 45
 - instantiating, 34
 - protection by, 14
 - registering, 34
- system configuration files
 - location, 20
- system properties
 - effect on fault monitors, 37

T

- timeouts
 - fault monitor
 - guidelines for setting, 38
 - SUNW.sap_xserver resource type, 50
 - SUNW.sapdb resource type, 48
 - stop method, 51
- transient faults
 - recovery actions, 40
- tuning
 - fault monitors, 37

U

- User_Key extension property, 49
- users
 - of SAP MaxDB database instance
 - database, 49
 - operating system, 46
 - sample definition, 22
 - of SAP xserver, 51
 - planning for nondefault, 20
 - specifying nondefault, 31
- /usr/spool/sql directory, 21, 22

V

- verifying
 - SAP MaxDB application, 25
- version requirements
 - SAP MaxDB application, 16

X

- x_server command
 - path to, 49
- Xserver_User extension property
 - specifying, 31
 - SUNW.sap_xserver resource type, 51
- .XUSER.62 file
 - creating, 21
 - and DB_User extension property, 46
 - example, 22