

Common Core - Security Management System User Guide

## **Oracle FLEXCUBE Universal Banking**

Release 14.0.0.0.0

**Part No. E88855-01**

February 2018

Common Core - Security Management System User Guide  
Oracle Financial Services Software Limited

Oracle Park

Off Western Express Highway  
Goregaon (East)  
Mumbai, Maharashtra 400 063  
India

Worldwide Inquiries:

Phone: +91 22 6718 3000

Fax: +91 22 6718 3001

<https://www.oracle.com/industries/financial-services/index.html>

Copyright © 2007, 2018, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are “commercial computer software” pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

---

# Contents

|                                                              |            |
|--------------------------------------------------------------|------------|
| <b>1. Preface .....</b>                                      | <b>1-1</b> |
| 1.1 Introduction.....                                        | 1-1        |
| 1.2 Audience.....                                            | 1-1        |
| 1.3 Documentation Accessibility .....                        | 1-1        |
| 1.4 Organization .....                                       | 1-1        |
| 1.5 Abbreviations.....                                       | 1-2        |
| 1.6 Glossary of Icons.....                                   | 1-2        |
| 1.7 Related Documents .....                                  | 1-3        |
| <b>2. Security Management .....</b>                          | <b>2-1</b> |
| 2.1 Introduction.....                                        | 2-1        |
| 2.2 Bank Level Parameter Setup.....                          | 2-2        |
| 2.2.1 Invoking SMS Bank Parameters Maintenance Screen.....   | 2-2        |
| 2.2.2 Password Restriction Button .....                      | 2-7        |
| 2.3 Bank Restriction .....                                   | 2-8        |
| 2.4 User Details Modification in Bulk .....                  | 2-9        |
| 2.4.1 Invoking the User Credentials Change Screen .....      | 2-9        |
| 2.5 Common Branch Restrictions.....                          | 2-11       |
| 2.5.1 Invoking the Branch Restriction Screen .....           | 2-11       |
| 2.6 Function Maintenance .....                               | 2-12       |
| 2.6.1 Invoking Function Description Maintenance Screen ..... | 2-12       |
| 2.6.2 Defining the Menu .....                                | 2-16       |
| 2.7 Defining Password Restriction.....                       | 2-16       |
| 2.8 User Role Maintenance .....                              | 2-17       |
| 2.8.1 Invoking Role Maintenance Screen.....                  | 2-17       |
| 2.8.2 Defining Functions for a Role Profile .....            | 2-18       |
| 2.8.3 Process Stage Rights Button.....                       | 2-19       |
| 2.8.4 Branch Restriction Button.....                         | 2-20       |
| 2.8.5 Account Class Restriction Button .....                 | 2-20       |
| 2.8.6 Rights Button .....                                    | 2-21       |
| 2.8.7 Copying the Role Profile of an Existing Role.....      | 2-23       |
| 2.8.8 Closing a Role Profile .....                           | 2-23       |
| 2.8.9 Defining Roles for Oracle FLEXCUBE Branch Users.....   | 2-24       |
| 2.9 User Holidays Maintenance.....                           | 2-24       |
| 2.9.1 Invoking User Holiday Maintenance Screen.....          | 2-24       |
| 2.9.2 Viewing Holiday Summary Details.....                   | 2-25       |
| 2.10 User Creation .....                                     | 2-26       |
| 2.10.1 Restricted Passwords Button .....                     | 2-29       |
| 2.10.2 Copying the User Profile of an Existing User .....    | 2-30       |
| 2.10.3 Deleting a User Profile.....                          | 2-30       |
| 2.10.4 Closing a User Profile.....                           | 2-30       |
| 2.11 User Profile Entitlements.....                          | 2-30       |
| 2.11.1 Invoking User Maintenance Screen.....                 | 2-31       |
| 2.11.2 Additional Details tab.....                           | 2-36       |
| 2.11.3 Roles Button .....                                    | 2-37       |
| 2.11.4 Rights Button .....                                   | 2-38       |
| 2.11.5 Functions Button.....                                 | 2-40       |

|           |                                                            |            |
|-----------|------------------------------------------------------------|------------|
| 2.11.6    | Account Classes Button .....                               | 2-41       |
| 2.11.7    | Branches Button .....                                      | 2-42       |
| 2.11.8    | Products Button .....                                      | 2-44       |
| 2.11.9    | Disallowed Functions Button .....                          | 2-45       |
| 2.11.10   | Centralized Role Button.....                               | 2-45       |
| 2.11.11   | Dashboard Mapping Button.....                              | 2-46       |
| 2.12      | Department Details .....                                   | 2-48       |
| 2.12.1    | Specifying Department Details .....                        | 2-48       |
| 2.13      | Process Codes .....                                        | 2-48       |
| 2.13.1    | Maintaining Process Codes.....                             | 2-49       |
| 2.14      | Single Sign On (SSO) Enabled Environment .....             | 2-50       |
| 2.15      | Defining Entity Maintenance .....                          | 2-50       |
| <b>3.</b> | <b>Associated Functions .....</b>                          | <b>3-1</b> |
| 3.1       | Clearing a User ID .....                                   | 3-1        |
| 3.1.1     | Invoking the Clear User Screen.....                        | 3-1        |
| 3.2       | System Time Level .....                                    | 3-2        |
| 3.2.1     | Changing the System Time Level.....                        | 3-2        |
| 3.3       | Language Codes .....                                       | 3-3        |
| 3.3.1     | Defining Language Codes .....                              | 3-3        |
| 3.4       | Branch of Operation .....                                  | 3-4        |
| 3.4.1     | Changing the Branch of Operation .....                     | 3-4        |
| 3.5       | User Password .....                                        | 3-4        |
| 3.5.1     | Changing the User Password .....                           | 3-4        |
| 3.6       | SSO Parameters .....                                       | 3-5        |
| 3.6.1     | Maintaining SSO Parameters .....                           | 3-5        |
| 3.7       | Transaction Status Control .....                           | 3-6        |
| 3.7.1     | Maintaining Transaction Status Control.....                | 3-6        |
| 3.8       | Customized Hot Keys .....                                  | 3-7        |
| 3.8.1     | Configuring Customized Hot Keys.....                       | 3-7        |
| 3.9       | Viewing User Activities .....                              | 3-8        |
| 3.9.1     | Viewing User Activities .....                              | 3-8        |
| <b>4.</b> | <b>Error Codes and Messages .....</b>                      | <b>4-1</b> |
| 4.1       | Error Codes .....                                          | 4-2        |
| <b>5.</b> | <b>Reports .....</b>                                       | <b>5-1</b> |
| 5.1       | Batch Performance Statistics Report.....                   | 5-1        |
| 5.1.1     | Generating Batch Performance Statistics Report.....        | 5-1        |
| 5.1.2     | Contents of the Performance Statistics report.....         | 5-2        |
| 5.2       | Change Control Log Report.....                             | 5-3        |
| 5.2.1     | Generating Change Control Log Report.....                  | 5-3        |
| 5.2.2     | Contents of the Report .....                               | 5-4        |
| 5.3       | Disabled Users System Violation Log Report.....            | 5-5        |
| 5.3.1     | Generating Disabled Users System Violation Log Report..... | 5-5        |
| 5.3.2     | Contents of the Report .....                               | 5-6        |
| 5.4       | Event Log Report.....                                      | 5-6        |
| 5.4.1     | Generating Event Log Report.....                           | 5-7        |
| 5.4.2     | Contents of the Report .....                               | 5-7        |
| 5.5       | New User Created Report .....                              | 5-8        |
| 5.5.1     | Generating New User Created Report .....                   | 5-8        |
| 5.5.2     | Contents of the Report .....                               | 5-9        |

|           |                                                            |            |
|-----------|------------------------------------------------------------|------------|
| 5.6       | Role Profile Report .....                                  | 5-10       |
| 5.6.1     | Generating Role Profile Report .....                       | 5-10       |
| 5.6.2     | Contents of the Report .....                               | 5-10       |
| 5.7       | Security Maintenance Inactive User Report .....            | 5-11       |
| 5.7.1     | Generating Security Maintenance Inactive User Report ..... | 5-11       |
| 5.7.2     | Contents of the Report .....                               | 5-12       |
| 5.8       | User Change Control Log Report .....                       | 5-13       |
| 5.8.1     | Generating User Change Control Log Report .....            | 5-13       |
| 5.8.2     | Contents of the Report .....                               | 5-14       |
| 5.9       | User Log Details Log Report .....                          | 5-15       |
| 5.9.1     | Generating User Log Details Log Report .....               | 5-15       |
| 5.9.2     | Contents of the Report .....                               | 5-16       |
| 5.10      | User Role Summary Report .....                             | 5-17       |
| 5.10.1    | Generating Role Summary Report .....                       | 5-17       |
| 5.10.2    | Contents of the Report .....                               | 5-18       |
| 5.11      | User Status Log Report .....                               | 5-19       |
| 5.11.1    | Generating User Status Log Report .....                    | 5-19       |
| 5.11.2    | Contents of the Report .....                               | 5-20       |
| <b>6.</b> | <b>Function ID Glossary .....</b>                          | <b>6-1</b> |

---

# 1. Preface

## 1.1 Introduction

This Manual is designed to help you to quickly get familiar with the Security Management System (SMS) module of Oracle FLEXCUBE.

It provides an overview of the module and takes you through the various stages in setting- up and using the security features that Oracle FLEXCUBE offers.

Besides this User Manual, you can find answers to specific features and procedures in the Online Help, which can be invoked, by choosing Help Contents from the *Help* Menu of the software. You can further obtain information specific to a particular field by placing the cursor on the relevant field and striking <F1> on the keyboard.

## 1.2 Audience

This Manual is intended for the following User/User Roles:

| Role                             | Function                                                                                                                                  |
|----------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------|
| Oracle FLEXCUBE Implementers     | To set up the initial startup parameters in the individual client workstations.<br>To set up security management parameters for the Bank. |
| SMS Administrator for the Bank   | To set the SMS bank parameters.<br>To identify the Branch level SMS Administrators.                                                       |
| SMS Administrator for the Branch | To create User and Rsddole profiles for the branches of your bank. Will also grant access to the various functions to the Users.          |
| A Oracle FLEXCUBE user           | Any user of Oracle FLEXCUBE whose activities are traced by the SMS module.                                                                |

## 1.3 Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

## 1.4 Organization

This manual is organized into the following chapters:

| Chapter   | Description                                                                                                                           |
|-----------|---------------------------------------------------------------------------------------------------------------------------------------|
| Chapter 1 | <i>About this Manual</i> gives information on the intended audience. It also lists the various chapters covered in this User Manual.  |
| Chapter 2 | <i>Security Management</i> explains how to define and maintain the security of the banking system in terms of users access and roles. |

|                  |                                                                                                                                                                                                                                                                                     |
|------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Chapter 3</b> | <i>Associated Functions</i> discusses on the details pertaining to defining and maintaining additional security options such as clearing user profile, changing system time level, maintaining SSO parameters, error Messages, and viewing user activity, branch status, and so on. |
| <b>Chapter 4</b> | <i>Error Codes and Messages</i> lists all the error codes with the associated messages that you can encounter while working with this module.                                                                                                                                       |
| <b>Chapter 5</b> | <i>Reports</i> provides a list of reports that can be generated in this module.                                                                                                                                                                                                     |
| <b>Chapter 6</b> | <i>Function ID Glossary</i> has alphabetical listing of Function/Screen ID's used in the module with page references for quick navigation.                                                                                                                                          |

## 1.5 Abbreviations

| Abbreviation | Description                                          |
|--------------|------------------------------------------------------|
| FC           | Oracle FLEXCUBE                                      |
| AEOD         | Auto End of Day                                      |
| BOD          | Beginning of Day                                     |
| EOD          | End of Day                                           |
| EOTI         | End of Transaction Input                             |
| EOFI         | End of Financial Input                               |
| The System   | This term is always used to refer to Oracle FLEXCUBE |
| SI           | Standing Instructions                                |
| MM           | Money Market                                         |
| RM           | Relationship Manager                                 |

## 1.6 Glossary of Icons

This User Manual may refer to all or some of the following icons.

| Icons                                                                               | Function    |
|-------------------------------------------------------------------------------------|-------------|
|  | Exit        |
|  | Add row     |
|  | Delete row  |
|  | Option List |

## **1.7     Related Documents**

For further information on procedures discussed in the manual, refer to the Oracle FLEXCUBE manuals on:

- The Procedures User Manual
- The Security Management System User Manual

---

## 2. Security Management

### 2.1 Introduction

Controlled access to the system is a basic parameter that determines the robustness of the security in banking software. In Oracle FLEXCUBE, we have employed a multi-pronged approach to ensure that this parameter is in place.

#### **Only Authorized Users Access the System**

First, only authorized users can access the system with the help of a unique User ID and a password. Secondly, a user should have access rights to execute a function.

#### **User Profiles**

The user profile of a user contains the User ID, the password and the functions to which the user has access.

#### **Restricted Number of Unsuccessful Attempts**

You can define the maximum number of unsuccessful attempts after which a User ID should be disabled. When a User ID has been disabled, the Administrator should enable it. The password of a user can be made applicable only for a fixed period. This forces the user to change the password at regular intervals thus reducing security risks. Further, you can define passwords that could be commonly used by a user as Restrictive Passwords at the user, user role and bank level. A user cannot use any password that is listed as a Restrictive Password at any of these levels.

#### **Restricted Access to Branches**

You can indicate the branches from where a user can operate in the Restricted Access screen.

#### **All Activities Tracked**

Extensive log is kept of all the activities on the system. You can generate reports on the usage of the system anytime. These reports give details of unsuccessful attempts at accessing the system along with the nature of these attempts. It could be an invalid password attempt, the last login time of a user etc.

#### **Audit Trail**

Whenever a record is saved in the module, the ID of the user who saved the record is displayed in the 'Input By' field at the bottom of the screen. The date and time at which the record is saved is displayed in the Date/Time field.

A record that you have entered should be authorized by a user, bearing a different login ID, before the EOD is run. Once the record is authorized, the ID of the user who authorized the record will be displayed in the 'Authorized By' field. The date and time at which the record was authorized is displayed in the 'Date/Time' field positioned next to the 'Authorized By' field.

The number of modifications that have happened to the record is stored in the field 'Modification Number'. The Status of the record whether it is Open or Closed is also recorded in the 'Open' check box.

This chapter contains the following sections:

- [Section 2.2, "Bank Level Parameter Setup"](#)
- [Section 2.3, "Bank Restriction"](#)
- [Section 2.4, "User Details Modification in Bulk"](#)
- [Section 2.5, "Common Branch Restrictions"](#)

- [Section 2.6, "Function Maintenance"](#)
- [Section 2.7, "Defining Password Restriction"](#)
- [Section 2.8, "User Role Maintenance"](#)
- [Section 2.9, "User Holidays Maintenance"](#)
- [Section 2.10, "User Creation"](#)
- [Section 2.11, "User Profile Entitlements"](#)
- [Section 2.12, "Department Details"](#)
- [Section 2.13, "Process Codes"](#)
- [Section 2.14, "Single Sign On \(SSO\) Enabled Environment"](#)

## 2.2 Bank Level Parameter Setup

This section contains the following topics:

- [Section 2.2.1, "Invoking SMS Bank Parameters Maintenance Screen"](#)
- [Section 2.2.2, "Password Restriction Button"](#)

### 2.2.1 Invoking SMS Bank Parameters Maintenance Screen

Certain parameters related to security management should be defined at the bank level. These parameters will apply to all the users of the system. Examples of such parameters are the number of invalid login attempts after which a user-id should be disabled, the maximum and minimum length for a password, the number of previous passwords that should not be used, the interval at which the password should be changed by every user, and so on..

You can invoke the 'SMS Bank Parameters ' screen by typing 'SMDBANKP' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

**SMS Banks Parameters**

Enter Query

**Bank Level Parameters**

Site Code \* \_\_\_\_\_

Activation Key \_\_\_\_\_

**Password Length (Characters)**

Maximum \* 15

Minimum \* 8

**Invalid Logins**

Cumulative \_\_\_\_\_

Successive \_\_\_\_\_

**Parameters**

Password Repetitions \_\_\_\_\_

Force Password Change After \_\_\_\_\_

Intimate User (Before Password Expiry) \_\_\_\_\_

Archival Period (in days) \_\_\_\_\_

Minimum Days Between Password Changes \_\_\_\_\_

Dormancy Days \_\_\_\_\_

Maximum Consecutive Repetitive Characters \_\_\_\_\_

Minimum Number Of Numeric \* Characters In Password \_\_\_\_\_

Minimum Number Of Special \* Characters In Password \_\_\_\_\_

Minimum Number of LowerCase \* Characters in Password \_\_\_\_\_

Minimum Number of UpperCase \* Characters in Password \_\_\_\_\_

☐ Display Legal Notice

**Password Restrictions**

| Maker   | Date Time: | Mod No | Record Status        |
|---------|------------|--------|----------------------|
| Checker | Date Time: |        | Authorization Status |

[Exit](#)

---

**Note**

You can modify the Bank Parameters only when the Head Office branch is in the transaction input stage.

---

**Specifying Invalid Logins**

You can specify the allowable number of times an invalid login attempt is made by a user. Each user accesses the system through a unique User ID and password. While logging on to the system, if either the User ID or the Password is wrong, it amounts to an invalid login attempt.

You can stipulate the allowable number of cumulative invalid attempts made during the course of a day, as well as the allowable number of consecutive or successive invalid attempts made at a time. In either case, if the number of invalid attempts exceeds the stipulated number, the user ID is disabled.

By default, the allowable number of cumulative invalid attempts is six, and the allowable number of consecutive invalid attempts is three. You can change the default and specify the allowable number of attempts in each case. You can specify an allowable number for cumulative attempts between 6 and 99, and for consecutive (successive) attempts, between 3 and 5.

Once specified, you can change the allowable number of cumulative or consecutive login attempts, provided you do so only at a time when no users are logged in to the system.

When authentication of credentials is unsuccessful due to an incorrect user ID, then the user ID will not be logged in the audit logs. In case the user ID is correct and the password is wrong, the attempt is logged in the audit log and the successive and cumulative failure count is incremented. When the user ID and password are correct, this is logged into the audit logs.

**Specifying Parameter****Archival Period in Days**

You can specify the period (in calendar days) for which the audit trail details of system security related activities (such as usage of the system by a user, activities by the system administrator, and so on.) should be maintained. The system defaults to a value of 30, which you can change.

You can specify an archival period that is greater than or equal to 7 calendar days.

**Dormancy Days**

Oracle FLEXCUBE allows you to automatically disable the profile of all the users who have not logged into the system for a pre-defined period of time. A user ID is considered dormant if the difference between the last login date and the current date is equal to or greater than the number of 'Dormancy Days' that you specify in this screen. This is reckoned in calendar days i.e. inclusive of holidays.

All dormant users (whose home branch is same as the current branch) are disabled during the end of day run at the current branch.

**Password External**

The password external is enabled if the PASSWORD\_EXTERNAL is maintained as 'Y' in the property file. However, you cannot edit this check box.

If 'Password External' is enabled then you cannot modify the user and the password.

## **Specifying Warning Screen Text**

### **Warning Screen Text**

At your bank, you may require a warning message containing legal requirements and security policy to be displayed to all users before allowing them to login to Oracle FLEXCUBE.

You can specify the text (content) of such a message, in the Warning Screen Text field. This message will be displayed soon after a user launches the Oracle FLEXCUBE login screen. The user will be allowed to continue with the login process only after he clicks on the OK button on the message window.

You can modify the contents of the message only during the transaction input stage. The changes will come into effect during the next login by a user. The maximum size of the warning message is '1000' characters.

---

#### **Note**

You will be allowed to specify the contents of the warning message only if the 'Display Legal Notice' option is enabled.

---

## **Specifying Screen Saver Details**

You can lock the Oracle FLEXCUBE application screen if there is no activity for some time. You can log in back to the screen only if you specify the password of your user ID.

### **Screensaver Required**

Check this box if screensaver is required.

### **Screensaver Interval Modifiable at User level**

Check this box if you want to modify the screensaver interval at user level.

### **Screensaver Interval (in seconds)**

Specify the time in seconds, after which the screen should be locked.

If both 'Screensaver required' and 'Screensaver Interval Modifiable at User level' are checked in bank level, then it will be visible at user level. Otherwise it will be hidden.

The system will default the screensaver time out from that maintained in bank parameter screen. Administrator who creates user will be allowed to change the same during user creation time.

The screensaver interval maintained at user level should be always be less than or equal to that maintained at bank level.

If screensaver interval is not specified in user level, the system will take the interval from bank parameter maintenance.

The screensaver interval can be specified by the user only if 'Screensaver Modifiable at User Level' is checked in the bank parameter maintenance.

## **Specifying Parameters for User Passwords**

You can specify the following parameters that would govern user passwords:

### **Password Length (characters)**

You can indicate the range of length (in terms of number of characters) of a user password. The number of characters in a user password is not allowed to exceed the maximum length, or fall below the minimum length that you specify here.

The minimum length defaults to 8, and the maximum length to 15. You can change the defaults and specify the required range. If you do so, you can specify a minimum length between 8 and 11 characters, and a maximum length between 12 and 30 characters. The minimum length that you specify must not exceed the maximum length that you have specified.

### **Force Password Change after**

The password of a user can be made valid for a fixed period after which a password change should be forced. In the 'Force Password Change after' field, you can specify the number of calendar days for which the password should be valid. After the specified number of days has elapsed for the user's password, it is no longer valid and a password change is forced.

The number of calendar days defined here will be applicable for a password change of any nature - either through the 'Change Password' function initiated by the user or a forced change initiated by the system.

The system defaults to a value of 30, which can be changed. If you change it, the number of days you specify here should be between 15 and 180 days, inclusive.

### **Password Repetitions**

You can stipulate the number of previous passwords that cannot be set as the new current password, when a password change occurs.

The system defaults to a value of three (i.e., when a user changes the user password, the user's previous three passwords cannot be set as the new password). You can change the default, and if you do, you can specify a number between one and five, inclusive.

For example, while setting up the Bank Level Parameters, you have given a value of '2' in the Password Repetitions field. Suppose that a user of the system has the user ID and password for login.

If the user wants to change the password for the first time, he/she should invoke the Change Password screen. The user cannot choose his current password again, but has to enter a new password.

The user wants to change the password for the second time. As the last two passwords cannot be used (Password Repetitions = 2 in the Bank Level Parameters table), the user cannot enter either of the old password. He/she should enter a password which is different from the previous two password.

The number you specify here should be greater than or equal to 1 and less than or equal to 5.

### **Minimum Days between Password Changes**

You can specify the minimum number of calendar days that must elapse between two password changes. After a user has changed the user password, it cannot be changed again until the minimum number of days you specify here have elapsed.

By default, the minimum days between password changes is set to One. However, you can modify this.

---

**Note**

- The minimum days between password changes should not be a value more than the days defined in the field 'Force Password Change After'.
  - It is recommended not to set the minimum days between password changes to '0'
- 

**Intimate Users (before password expiry)**

The number of days for which a password is to be valid is defined in the 'Force Password Change' after field. You can also indicate the number of working days before password expiry that a warning is to be issued to the user. When the user logs into the system (the stipulated number of days before the expiry date of the password), a warning message will continue to be displayed till the password expires or till the user changes it.

By default, the value for this parameter is two (i.e., two days before password expiry). You can change the default if required. If you do, you can specify a number greater than zero and less than or equal to five.

For example, if the value specified in the Intimate User (Before Password Expiry) field is 2 and a user's password is due to expire on January 31. The warning message is displayed on January 29 and January 30 whenever the user logs in.

**Specifying Restrictions on User Passwords**

You are allowed to place restrictions on the number of alpha and numeric characters that can be specified for a user password.

**Maximum Consecutive Repetitive Characters**

You can define the maximum number of allowable repetitive characters occurring consecutively, in a user password. This specification is validated whenever a user changes the user password, and is applicable for a password change of any nature - either through the 'Change Password' function initiated by the user or a forced change initiated by the system.

For example, the value specified in the Maximum Consecutive Repetitive Characters field is 3 and a user decides to change his password to STUDDDD123. The System will not allow this password change as the Maximum Repetitive Characters value has exceeded in the recurrence of 'D' in the password.

**Minimum Number of Special Characters in Password**

You can define minimum number of special characters allowed in a user password. The system validates these specifications only when a user chooses to change the password.

If you do not specify the limits, the following default values will be used:

- Minimum No of Special Characters = 1

**Minimum Number of Numeric Characters in Password**

Likewise, you can also define the minimum number of numeric characters allowed in a user password. The system validates the password only when a user chooses to change his password.

If you do not specify the limits, the following default values will be used:

- Minimum No of Numeric Characters = 1

---

**Note**

You can specify any number between 0 and 11 in each of these fields. However, you must ensure that the sum total of the minimum number of special characters and the minimum number of numeric characters is less than or equal to the 'Maximum Password Length'.

---

**Minimum Number of Lower Case Characters in Password**

You can define the minimum number of lowercase characters allowed in a user password. The allowed lower case characters are from the US-ASCII character set only. The system validates these specifications only when a user chooses to change the password

If you do not specify the limits, the following default values will be used:

- Minimum No of Lower Case Characters = 1
- Maximum No of Numeric Characters = Maximum Password Length

**Minimum Number of Upper Case Characters in Password**

You can define the minimum number of upper case characters allowed in a user password. The allowed upper case characters are from the US-ASCII character set only. The system validates these specifications only when a user chooses to change the password.

If you do not specify the limits, the following default values will be used:

- Minimum No of Upper Case Characters = 1
- Maximum No of Numeric Characters = Maximum Password Length


## **2.2.2 Password Restriction Button**

You can define a list of passwords that cannot be used by any user of the system in the bank. This list, called the Restrictive Passwords list can be defined at three levels:

- At the bank level (applicable to all the users of the system)
- At the user role level (applicable for all the users assigned the same role)
- At the user level (applicable for the user)

The list of Restrictive Passwords should typically contain those passwords the users are most likely to use: the name of your bank, city, country, etc. For a user role, it could contain names, or terms, that are commonly used in the department. At the user level, it could contain the names of loved ones, and so on. By disallowing users from using such common passwords, you can reduce the risk of somebody other than the user knowing the password.

Click 'Password Restrictions' button to define restricted passwords at the bank level that should not be used by any user of the bank.



The screenshot shows a 'Password Restrictions' window. It features a search bar at the top with '1 Of 1' and a 'Go' button. Below the search bar is a table with one column labeled 'Password'. The table contains one row with a checkbox and the text 'Password'. At the bottom right of the window are 'Ok' and 'Exit' buttons.

To add a password to the 'Password' list, click add icon. To select a record in the list use the check box beside it.

After you listed the restrictive passwords in the 'Password' list, click 'Ok' button to save the password restrictions.

## 2.3 Bank Restriction

You can restrict administrators of branches from performing operations related to specific functions in branches other than their home branch. These are referred to as 'Branch Restrictions for Specific Applications'. You can also maintain a list of branches in which the administrator of a certain branch is allowed / restricted to perform specific operations. These other restrictions are referred to as 'Common Branch Restrictions'.

According to the restrictions you maintain, the administrator of a specific branch is allowed to perform specific operations in the administrator's home branch, as well as any branch found in the list of allowed branches.

According to your requirements, the implementers at your installation configure a list of the specific functions or applications for which you might wish to maintain such branch restrictions. You can maintain branch restrictions for each of these applications, as required.

To invoke the 'Bank Restrictions' screen, by typing 'SMDBNKRT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Bank Restriction

New Enter Query

Bank Code 000

1 Of 1 Go

| Restriction Type | Description |
|------------------|-------------|
|------------------|-------------|

Maker Date Time: Mod No Record Status

Checker Date Time: Authorization Status

Exit

## 2.4 User Details Modification in Bulk

This section contains the following topics:

- [Section 2.4.1, "Invoking the User Credentials Change Screen"](#)

### 2.4.1 Invoking the User Credentials Change Screen

You can change or reset user passwords in bulk if you have the system admin rights. After modification of the user list, click 'Save', The modified user list will be stored in a temporary table. The lists of users which are modified and mapped with a unique sequence number will not be available until the particular sequence number is authorized. When the particular sequence number is authorized those user details will be changed and updated.

You can invoke this screen by typing 'SMDCHPWD' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

In this screen, the following information is to be provided.

### Sequence Number

Click on 'New' icon to generate a new 'Sequence Number'.

### Process Date

Select a date by clicking on the calendar icon beside the field. This field is generally useful for querying purpose.

### Description

Provide a description of what modification is being done on selected user ids.

### User Id

Select the User Id to be changed from the option list provided.

### Name

Name of the user specific to the selected user id will be displayed in this field.

### Password

Password of the selected user id will be displayed here. This field will be editable only if the 'Auto Generation Required' option is not selected at the application level. If the 'Auto Generation Required' option is checked, the password will be auto generated by the application.

### Reset Password

Select this checkbox to reset the password in case of user ids where password needs to be auto generated.

If the external password is enabled in the bank parameters, then the Password and Reset Password will be disabled for editing.

## 2.5 Common Branch Restrictions

This section contains the following topics:

- [Section 2.5.1, "Invoking the Branch Restriction Screen"](#)

### 2.5.1 Invoking the Branch Restriction Screen

To recall, in the Branch Restrictions maintenance, you have identified those applications and operations, for which you intend to maintain branch restrictions. Having done this, you must proceed to create the appropriate common branch restrictions for each branch administrator. You can maintain these restrictions in the common 'Branch Restrictions' screen.

You can invoke this screen by typing 'SMDBRRST' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

This can be done only at the head office branch.

Branch Restrictions

New Enter Query

User Branch \*  
Description

Restriction Type \*  
Description

Branch Restrictions ☐ Allowed ☒ Disallowed

1 Of 1 Go

| Branch Code * | Branch Name |
|---------------|-------------|
|---------------|-------------|

Field

Maker Date Time: Mod No Record Status

Checker Date Time: Authorization Status

Exit

In this screen, you create common branch restrictions by specifying the information described below.

#### User Branch

You must first select the home branch of the administrator for which you are maintaining common branch restrictions, in the User Branch field.

#### Restriction Type

You must also indicate the specific application for which you wish to maintain common branch restrictions, for the administrator of the selected branch. You can only specify a restriction type that has been maintained in the SMS Branch Restriction Type maintenance.

#### Branch Restriction

You maintain common branch restrictions by creating a list of branches for each administrator, in which the administrator will either be allowed / disallowed access to perform operations related to the selected application (Restriction Type). You can maintain either an 'allowed' or a 'disallowed' restriction list.

The common branch restrictions you maintain are applicable for operations in the selected application (Restriction Type) in the home branch (User Branch) of the administrator and the list of allowed / disallowed branches.

For example, suppose that you have created the following common branch restrictions:

| Home Branch | Restriction Type | Allowed Branches   |
|-------------|------------------|--------------------|
| 000         | USRADMIN         | 000, 001, 002, 005 |
| 001         | USRADMIN         | 001, 006           |
| 002         | ICCFRULE         | 002, 005, 006      |
| 005         | EODOPERATN       | 002, 005, 006      |
| 006         | ICRATES          | 004, 005, 006      |

The administrator of branch 000 can perform user administration for the branches 000, 001, 002 and 005, but not for 006. Similarly, the administrator of branch 002 can create ICCF rules in branches 002, 005 and 006, but not in branches 000 and 001.

When the administrator of branch 000 attempts to create a new user in the User Profile screen, the branches available in the Home Branch field in the screen will be 000, 001, 002 and 005.

---

**Note**

- The administrator of the head office branch is allowed to perform all operations in any of the other branches
  - When a new branch is created, it must be manually added to the allowed / disallowed list, as required
  - For those applications (Restriction Types) that you have specified in the SMS Branch Restriction Types maintenance, you must create the appropriate common branch restrictions in the Common Branch Restrictions screen. If no restrictions have been created in the Common Branch Restrictions screen for a specific branch for an application chosen in the SMS Branch Restriction Types maintenance, operations pertaining to the application will not be allowed from that branch.
  - To allow the administrator of a certain branch to perform operations pertaining to a specific application for all branches, you can either maintain an allowed list with all branches selected or maintain a disallowed list with none of the branches selected.
- 

## 2.6 Function Maintenance

This section contains the following topics:

- [Section 2.6.1, "Invoking Function Description Maintenance Screen"](#)
- [Section 2.6.2, "Defining the Menu"](#)

### 2.6.1 Invoking Function Description Maintenance Screen

Any function that is a part of the system should be defined through the 'Function Description Maintenance' screen before it is available for execution. Mostly, our professionals carry out this activity. You can modify the description of the function that appears in the Application

Browser through this screen. You can invoke this screen by typing 'SMDFNDSC' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The following details are captured here:

### Function Id

Select the Function Id for which you want to give access rights, from the option list.

### Module List

Select the module to which the Function id has to be mapped. All Functions are mapped to specific modules.

### Name

Specify the executable to open the Function Id.

### Type

Select the type of Function Id here from the drop-down list. The options available are:

- Form
- Report
- Stored Procedure

### Menu Head

Select the menu head from the drop-down list. The options available are:

- Module
- Report

You can then specify the rights to the different actions for the functions by checking against the action. These actions can be:

- Static Maintenance Functions
  - New (Define a new record)
  - Copy (Copy details of an existing record)

- Delete (Delete an existing record)
- Close (Close an existing record)
- Unlock (to amend an existing record)
- Reopen (Reopen an existing record)
- Print (Print the details of selected records)
- Authorize (Authorize any maintenance activity on a record)
- Contracts and on-line transaction processing
  - Reverse (reverse an authorized contract)
  - Rollover (to manually roll over an existing contract into a new contract)
  - Confirm (to indicate the counterparty or broker confirmation of a contract)
  - Liquidate (to manually liquidate a contract)
  - Hold (to put a contract on hold)
  - View (to see the details of the contract)
- Reports
  - Generate (to generate reports)
  - View (view the reports)
  - Print (print the reports)

To delete the access rights given for a Function, select the Function ID and click delete icon.

### **Module Group ID**

Specify the group ID of the module. Alternatively, you can select the module group ID from the option list. The list displays all valid module group IDs maintained in the system.

### **User Function ID**

Specify a custom function id which can be used as an alias for the function id selected.

If you input this value in the field at the top right corner of the Application tool bar and click on the adjoining arrow button, system will check for the mapped function id and will launch that function id screen.

### **Execute Category**

You can either select 'Java' or 'PL/SQL' from the drop-down list.

If you select 'Java', the ODT screen processing logic is done through application layer. If you select 'PL/SQL', then the ODT screen processing logic is done through database layer.

### **Tanking Required**

Check this box to indicate that the maintenance records that are created or modified in the system, for the function Id specified here, need to be tanked till they get authorized.

The new or the modified records are written to the static tables only after authorization.

*For more details on tanking of maintenance records refer the Core Services user manual.*

### **Dual Authorization**

Check this box to enable dual authorization for records that are created or modified in the system, for the specified function id. If dual authorization is enabled then after creation or modification of a maintenance record, an intermediate verifier (First Authorizer) has to verify the record before the record can actually be authorized.

You cannot enable both 'Dual Authorization' and 'Auto Authorization' for a function id at the same time, as they are mutually exclusive.

**Remarks Required**

Check this box to enable capturing of maker remarks on the actions like save, close and reopen of records belonging to the selected function id.

If this box is checked then system pops up a 'Maker Remarks' window and forces the maker to save remarks while saving, closing or reopening a record, The checker/authorizer can view the maker remarks entered and also enter remarks for each modification while authorizing the record.

**Excel Export Required**

Check this box to enable data export for the selected function id.

If this box is checked, system allows you to export data from records belonging to the selected function id into an excel file.

**Multi Branch Access Required**

Check this box to configure dual access framework for the function ID.

---

**Note**

- If the function level check box is unchecked, the transactions will be posted in the current branch.
  - Dual access functionality is enabled only when the 'Multi Branch Access' check box is checked at 'User ID' and 'Function ID' levels.
- 

**Available**

Check this box to make the Function accessible in the Oracle FLEXCUBE menu. The definition of the menu would be as specified in the Column at the bottom of the 'Function Description Maintenance' screen. If this box is unchecked, then this screen will not be accessible from the menu even if it is selected for the Role that is assigned to the user.

**Automatic End Of Day aware**

Check this box to consider the Function for an AEOD run.

**Log Event**

Check this box to enable the event log for a particular Function ID, Oracle FLEXCUBE maintains an extensive log of the activities of every user. This can later be used for reporting on the user activities.

**Cust Access**

Check this box to make the Function available to Users who are classified as Customers.

**Auto authorization**

As configured for your installation according to your requirement, automatic authorization is applicable for a pre-shipped list of functions. For those functions, you can revoke the applicability of automatic authorization, if required.

It is not possible to indicate the applicability of automatic authorization for any other functions than those pre-shipped functions configured for your installation.

**Head Office Function**

Check this box to enable the Function to be handled only by the users of the Head Office. Users of the other branches would be only allowed to view the Function.

## 2.6.2 Defining the Menu

The Oracle FLEXCUBE menu can be defined in the Function Description section.

You can define menu appearance for a given Language. The Menu can only be drilled down up to two sub menu levels.

For example, for Language Code 'ENG' if the Main menu value is given as Security Management', Sub Menu1 as 'Maintenance' and Sub Menu2 as 'Function Description' for Function id SMDFNDSC then on the Oracle FLEXCUBE menu it would appear as follows:



## 2.7 Defining Password Restriction

System allows you to create a list of words that the users, having a certain Role are likely to use as Passwords and on which restrictions can be placed. The list of Restrictive Passwords should contain those passwords that the users are most likely to use: the name of your bank, city, country, and so on. For a user role, it could contain names, or terms, that are commonly used in the department. At the user level, it could contain the names of loved ones, etc. By disallowing users from using such common passwords, you can reduce the risk of somebody other than the user knowing the password.

You can invoke this screen by typing 'SSDROLD' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button. Any user, who is attached to the role, cannot use a password in this list.

You can define only the functions that are applicable for the role and the list of Restrictive Passwords for a role. All the other attributes of a user profile should be defined when the user profile is being created.

## 2.8 User Role Maintenance

This section contains the following topics:

- [Section 2.8.1, "Invoking Role Maintenance Screen"](#)
- [Section 2.8.2, "Defining Functions for a Role Profile"](#)
- [Section 2.8.3, "Process Stage Rights Button"](#)
- [Section 2.8.4, "Branch Restriction Button"](#)
- [Section 2.8.5, "Account Class Restriction Button"](#)
- [Section 2.8.6, "Rights Button"](#)
- [Section 2.8.7, "Copying the Role Profile of an Existing Role"](#)
- [Section 2.8.8, "Closing a Role Profile"](#)
- [Section 2.8.9, "Defining Roles for Oracle FLEXCUBE Branch Users"](#)

### 2.8.1 Invoking Role Maintenance Screen

It is likely that users working in the same department at the same level of hierarchy need to have similar user profiles. In such cases, you can define a Role Profile that includes access rights to the functions that are common to a group of users. A user can be linked to a Role Profile by which you give the user access rights to all the functions in the Role Profile.

The roles defined will be effective only after dual authorization.

Role profiles are defined in the 'Role Maintenance' screen. You can invoke this screen by typing 'SMDROLDF' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screen is as shown below:

Role Maintenance

New Enter Query

Role Id \*

Role Description

☐ Centralisation Role

Maintenance | Reports | Batch | Online | Process Stage Rights | Acc Class Restriction | Branch Restriction | Rights | Web Branch | Fields

Maker Date Time: Mod No Record Status

Checker Date Time: Authorization Status

Exit

You can specify the following details

#### **Role ID**

Specify the role profile.

#### **Role Description**

Specify the role description.

#### **Centralisation Role**

Check this box to centralise the role.

### **2.8.2 Defining Functions for a Role Profile**

After you have defined the basic attributes of a role profile (the Role Identification, Description) you should define the functions to which the role profile has access. Check centralization role to specify that the role is applicable for centralized users. The role is automatically associated with all branches accessible to you, if the multi branch operational parameter is enabled. The various functions in the system fall under different categories.

To assign a function to a role in the 'Role Maintenance' screen, you must click the function category button to which the function belongs. The function category buttons in the 'Role Maintenance' screen are as follows:

- **Maintenance** - Functions related to the maintenance of static tables
- **Reports** - Functions related to the generation of reports in the various modules
- **Batch** - Functions related to the automated operations (like automatic liquidation of contract, interest, and so on.)
- **On Line** - Functions related to contract processing
- **Process Stage Rights** - Functions related to workflow

- **Acc Class Restriction** – Functions related to restricting the role from using certain account classes
- **Branch Restriction** – Functions related to restricting the association of roles to certain branches.
- **Rights** – Functions related to giving necessary rights for perform various operations in respect of incoming and outgoing messages
- **Web Branch** – Functions related to the Teller Module for the role of branch users.
- **Branch Limit** – Function related to setting up Branch limits.
- **Fields** – Functions related to User Defined Fields.

The lower portion of the Role Description screen has buttons corresponding to each of the above function categories. Click on a button to view the corresponding screen.

### 2.8.3 Process Stage Rights Button

You can specify the function id to which the role profile is associated. Click 'Process Stage Rights' button in the 'Role Maintenance' screen. The 'Process Stage Rights' screen is opened.

| Role Function | Editable |
|---------------|----------|
|---------------|----------|

You can specify the following details:

#### **Role Function**

Specify the function id for which you need to provide access rights. Alternatively you can select the function id from the option list. The list displays all valid function ids maintained in the system for the selected category.

#### **Editable**

Check this box to provide editing access for the selected function id.

## 2.8.4 Branch Restriction Button

You can specify the branches to which the role profile is associated, and for which it is available. Click 'Branch Restriction' button in the 'Role Maintenance' screen. The 'Branch Restriction' screen is opened.

Role Maintenance  
Branch Restriction

Branch

1 Of 1

Go

| Branch * | Branch Name |
|----------|-------------|
|----------|-------------|

Branch Restriction ☐ Allowed ☒ Disallowed

Ok Exit

You can maintain a list of branches for which the role is either:

- Allowed
- Disallowed

Choose the 'Allowed' option to maintain an allowed list, and the 'Branch Restrictions' list will show the list of allowed branches. Choose the 'Disallowed' option, to maintain a disallowed list of branches.

If you maintain an 'Allowed' list, then the role profile will be available only for those branches that you specify in the Branch Restrictions list. Similarly, if you maintain a 'Disallowed' list, then the role profile will not be available only for those branches that you specify in the Branch Restrictions list.

After choosing either the 'Allowed' or 'Disallowed' option, click add icon to add a record under the 'Branch Restrictions' list. Into each added record field, select the required branch from the adjoining option list.

## 2.8.5 Account Class Restriction Button

You can restrict the role from using certain account classes that are maintained in Oracle FLEXCUBE. Click 'Acc Class Restriction' to specify the account class restrictions. The 'Account Class Restriction' screen is displayed.

The screen is as shown below:

The screenshot shows a 'Role Maintenance' window with a tab titled 'Acc Class Restriction'. Inside, there's a table with two columns: 'Account Class' and 'Description'. The table is currently empty. Below the table, there are two radio buttons: 'Allowed' and 'Disallowed', with 'Disallowed' being the selected option. At the bottom right of the window, there are 'Ok' and 'Exit' buttons. The window also has a search bar at the top with '1 Of 1' and a 'Go' button.

You can either allow or disallow association of the role with certain account classes. Subsequently, specify the account classes, which have to be restricted for the role.

After choosing the 'Allowed' or 'Disallowed' option, click add icon to add a record under the 'Account Class Restrictions' list. Into each added record's field, select the required account class from the adjoining option list.

*For more details about account class restriction, refer Account Class Restriction at User Role maintenance and User Profile maintenance levels of this user manual.*

## 2.8.6 **Rights Button**

For a role profile, you can specify the necessary rights to perform various operations in respect of incoming and outgoing messages, in the Messaging module of Oracle FLEXCUBE. You can grant specific permissions for operations on messages, as well as allot the messaging queues to which the role has access.

In the 'Role Maintenance' screen, click 'Rights' button to open the 'Rights' screen. Here you can grant the rights pertaining to the Messaging module, to the role.

The screen is as shown below:

Role Maintenance

Rights

Grant Rights

- ☐ Cancel
- ☐ Change Node
- ☐ Release
- ☐ Change Media
- ☐ Branch Move
- ☐ Hold
- ☐ Test Input
- ☐ Change Address
- ☐ Reinstall
- ☐ Change Priority
- ☐ Auth Cancel
- ☐ Auth Change Node
- ☐ Release
- ☐ Change Media
- ☐ Auth Branch Move
- ☐ Hold
- ☐ Auth Test Input
- ☐ Change Address

Limits

- ☐ Auth Reinstall
- ☐ Change Priority
- ☐ Install
- ☐ Test Check
- ☐ Link Contract
- ☐ Change Branch In
- ☐ Change Message
- ☐ Change Force Release Fund
- ☐ Suppress
- ☐ Delete
- ☐ Print
- ☐ FT Upload
- ☐ Move To Queue
- ☐ Change Address In
- ☐ Auth Change Message
- ☐ Auth Rights
- ☐ Change Force Cover Match

Queue Rights

1 Of 1

Go

Ok Exit

Check against the messaging operations for which you want to grant the permission.

### Granting rights pertaining to operations on messages

You can grant permissions for the following operations on outgoing messages:

- Generating a message
- Printing a message
- Placing a message on hold
- Releasing a message on hold
- Cancelling a message
- Inserting a testword
- Reinstating a message
- Changing the priority of a message
- Request information relating to Status of a message
- Request cancellation of a message
- Changing the media through which a message is transmitted
- Changing the address to which a message is to be sent
- Moving a message to another branch
- Changing the node from which a message should be generated
- Authorization of any of the operations listed above, in respect of outgoing messages

You can grant permissions for the following operations on incoming messages:

- Printing a message
- Authorizing a testword
- Routing a message to a queue
- Associating a message with a contract

- Uploading incoming messages
- Making changes (edit) incoming messages. You can also grant permissions for changing the branch and the address in incoming messages
- Authorizing changes made to incoming messages
- 'Force Release' payment message transactions with 'Funding Exception' status and insufficient funds
- Suppressing a message
- Deleting a message

Granting each of these permissions in the Rights screen enables the user having this role to perform the corresponding functions in the Incoming and Outgoing Message Browsers. The appropriate button in the Browser, in each case, is enabled for the users associated with the role.

For details regarding each of these operations in respect of both incoming and outgoing messages, consult the **Messaging System** user manual

Apart from these functions, you can also grant permission for the cover matching function for incoming payment message transactions.

For details regarding uploading incoming payment transaction messages and cover matching for incoming payment transactions, refer the 'Straight Through Processing' chapter in the Funds Transfer user manual.

### **Grant Queues**

You can grant the message queues to which the role has access, and in which users associated with the role can perform messaging operations according to the messaging rights you have assigned. The required queues can be selected and listed in the 'Queues' list under the 'Grant Queues' section.

## **2.8.7 Copying the Role Profile of an Existing Role**

Often, you may have to create a Role Profile that closely resembles an existing one. In such a case, you can copy the existing profile on to the new one.

Select 'Copy' from the Actions menu in the Application toolbar or click copy icon. A list of existing role profiles will be displayed. Click on the one you want to copy. All the details of the profile except the Role ID will be copied and displayed. Enter a unique Role ID. You can change any of the details of the profile before saving it.

## **2.8.8 Closing a Role Profile**

A Role Profile should be closed only if there are no users linked to it. Thus, before closing a role profile, you should modify each user profile attached to it and delete the link to the role.

Select 'Close' from the Actions menu in the Application toolbar to delete an existing role profile. If the role is linked to any user, a warning message will be displayed. This message will bring your attention to the fact that the user profile to which the role is linked will not be the same if the role profile is closed.

You will be prompted to confirm the closure. The Role Profile will be closed only if you confirm the Closure.

## 2.8.9 Defining Roles for Oracle FLEXCUBE Branch Users

You can define a role with functions typically performed by you from Oracle FLEXCUBE Branch system. You can maintain the role 'Teller' and select the branch function from the 'Web branch' button.

---

### Note

- In case you wish to give access of the host functions to the 'Teller', you can attach role like 'ALLROLES' or other role with host functions in addition to the 'Teller' role. You can do this at the User Profile level for the branch you are allowed.
  - The system generates notification on authorization of any modification, addition or deletion of role.
- 

## 2.9 User Holidays Maintenance

This section contains the following topics:

- [Section 2.9.1, "Invoking User Holiday Maintenance Screen"](#)
- [Section 2.9.2, "Viewing Holiday Summary Details"](#)

### 2.9.1 Invoking User Holiday Maintenance Screen

You can block a specific user login for a certain time frame by defining holiday slots for that user profile. You can define holiday slots through the 'User Holiday Maintenance' screen. You can invoke this screen by typing 'SMDUSHOL' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The 'User Holiday Maintenance' screen is shown below.

| Maker   | Date Time: | Mod No | Record Status        |
|---------|------------|--------|----------------------|
| Checker | Date Time: |        | Authorization Status |

Specify the following details:

### Branch Code

The branch code of the user selected in the 'User ID' field is displayed here.

### User ID

Specify the user ID of the user for whom you want to define the holiday period. The adjoining option list displays all the valid user profiles maintained in the system. You can select the appropriate one.

### Leave From

Select the start date for the holiday period from the adjoining calendar.

### Leave To

Select the end date for the holiday period from the adjoining calendar.

The user will not be allowed to log in within the specified holiday range.

### Remarks

Specify a brief description for the holiday.

You can maintain multiple holiday slots for a user but the system will not allow including a specific day in more than one slot.

## 2.9.2 Viewing Holiday Summary Details

You can view holiday periods maintained for any user profile in the 'Users Holiday' screen. You can also invoke this screen by typing 'SMSUSHOL' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screen is as shown below:

| Authorization Status | Record Status | User ID | Leave From | Leave To |
|----------------------|---------------|---------|------------|----------|
|----------------------|---------------|---------|------------|----------|

You can query for records based on the following criteria:

- Authorization Status
- Record Status
- Branch Code
- User ID
- Leave From
- Leave To

Click 'Search' button. Based on your preferences, the system identifies all records satisfying the criteria and displays the following details for every record:

- Authorization Status
- Record Status
- Branch Code
- User ID
- Leave From
- Leave To
- Maker ID
- Maker Date Stamp
- Checker ID
- Checker Date Stamp

## 2.10 User Creation

You can create an user through the 'User Creation' screen. You can invoke this screen by typing SSDUSRDF in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button. The 'User Creation' screen is shown below

The screenshot displays the 'User Creation' application window. At the top, there is a title bar 'User Creation' and a menu bar with 'New' and 'Enter Query'. The main area is divided into several sections:

- User Details:** Includes fields for 'User Identification \*', 'Name \*', 'LDAP DN', 'MFA ID', 'MFA Enabled' (with a dropdown set to 'Disabled'), and 'Home Entity \*'. A 'Validate' button is located next to the 'LDAP DN' field.
- User Password:** Includes fields for 'Password', 'Password Changed On', 'Email', 'Status Changed On', and 'Reference No'. Below these is a 'User Status \*' section with radio buttons for 'Enabled', 'Hold', 'Disabled', and 'Locked'.
- Invalid Logins:** Includes fields for 'No of Cumulative Logins', 'No of Successive Logins', and 'Last Signed On'.
- Screen Saver Details:** Includes a field for 'Screensaver Interval (in seconds)'.

At the bottom, there is a 'Restricted Password' section and a table with the following columns: 'Maker', 'Checker', 'Date Time:', 'Mod No', 'Record Status', and 'Authorization Status'. An 'Exit' button is located in the bottom right corner.

## User Identification

Specify the User Id with which a User logs into Oracle FLEXCUBE. This User Id is unique across all branches. The minimum length of UserId must be six and the maximum number can be 12 characters.

## Restrictions on User Profile Administration

A branch administrator can create, modify or delete user profiles only in the Head Office, Home branch of the administrator or in those branches that are allowed for the restriction type USRADMIN, in the Common Branch Restrictions.

When the administrator of a branch attempts to create a new user in the User Profile screen, the branches available in the Home Branch field in the screen are only those allowed branches maintained in the Common Branch Restrictions for restriction type 'USRADMIN'.

*For details about the Common Branch Restrictions, refer the section 'Creating Common Branch Restrictions' in this user manual.*

For example, suppose that you have created the following branch restrictions:

| Home Branch | Restriction Type | Allowed Branches   |
|-------------|------------------|--------------------|
| 000         | USRADMIN         | 000, 001, 002, 005 |
| 001         | USRADMIN         | 001, 006           |

The administrator of branch 000 can perform user administration for the branches 000, 001, 002 and 005, but not for 006.

When the administrator of branch 000 attempts to create a new user in the User Profile screen, the branches available in the Home Branch field in the screen will be 000, 001, 002 and 005.

## User Status

Select the status of the user from the options available. The options available are:

- Enabled
- Hold
- Disabled

For a user to be able to login to Oracle FLEXCUBE, his status should be set as '**Enabled**'. The field '**Status Changed on**' displays the date and time when the Status of the User was last changed.

## LDAP DN

The LDAP Details that have been maintained in the SSO screen have to be input here. Clicking on the 'Validate' button validates the LDAP details entered in the **Single Sign On**. The application will verify if only one user ID in FLEXCUBE UBS is mapped to the subject (DN) while authentication via SSO.



## **Multi-Factor Authentication**

### **MFA Enabled**

Select whether multi-factor authentication is enabled for the user ID or not from the drop-down list. The list displays the following values:

- Disabled - If you select this, multi factor authentication will be disabled for the user
- Enabled - If you select this, multi factor authentication will be enabled for the user. If MFA is enabled, then it is mandatory to specify the MFA ID
- Locked - The system updates the status to Locked in specific situation. For example, in case of cumulative invalid logins beyond the permissible attempts, the system may change the MFA status to 'Locked'. This limit is usually defined in the external system that validates the MFA credentials.

### **MFA ID**

Specify the multi-factor user ID assigned to the user. This field is enabled if you select 'Enabled' option in the MFA Enabled field.

For more information on multi factor authentication, refer to the section 'Multi-Factor Authentication Limits' in this User Manual.

## **User Password**

### **Password**

Specify the Users Password here. This is a Hidden Field. The Password set must not be a restricted word. It should also be governed by the parameters set in the SMS Bank Parameters table, like Maximum and Minimum length, Number of Alphabetic and Numeric characters etc.

---

#### **Note**

If the application level parameter which indicates the auto generation of the password is required or not is set to Y (Yes), then this field will be disabled and the system will create a random password in accordance with the parameters maintained at the level of the bank. The new password will be send to the respective user via mail.

---

### **Password Changed On**

The date when the password was last changed gets displayed here.

### **Email**

Specify a valid Email id at the time of user creation. All system generated passwords shall be communicated to the user via this mail id.

**Start Date**

Specify the date from which the User is valid. The Branch date gets defaulted if no other value is specified.

**End Date**

Specify the End Date upto which the User is valid. By default the user does not have an End Date associated, unless otherwise specified.

**Invalid Logins****Cumulative**

The number of Cumulative Invalid Login attempts allowed for a User before the User status gets Disabled is specified in the 'SMS Bank Parameters' screen. The actual attempts that a user makes when he logs into Oracle FLEXCUBE get displayed here.

**Successive**

The number of Successive Invalid Login attempts allowed for a User before the User status gets Disabled is specified in the 'SMS Bank Parameters' screen. The actual attempts that a user makes while he logs into Oracle FLEXCUBE get displayed here.

**Last Signed On**

This is a display field which shows the Date and Time of the Users last Login.


**Screen Saver Details****Screensaver Interval (in seconds)**

The system defaults the screen saver interval based on the screen saver details maintained in the bank parameters screen.

**2.10.1 Restricted Passwords Button**

You can maintain a list of passwords that the user is most likely to use. For example, a user may tend to use the names of persons, bank, department, etc. as a password, as these are easy to remember. This might be a security risk as it will be easy for another person to guess a password. To prevent this, you can maintain a list of passwords that the user should not use. This list of restrictive passwords will be checked before a password is accepted when the user is changing passwords. If the password entered by the user exists in the list, it will not be accepted.

To specify a list of passwords that the user is not allowed to use, click 'Restricted Passwords' button in the User Profile definition screen.



The user for whom you are defining the restrictive passwords cannot use restrictive passwords defined in the Bank Level Parameters screen and the Role Profile screen.

### 2.10.2 Copying the User Profile of an Existing User

Often, you may have to create a user profile that closely resembles an existing one. In such a case, you can copy the existing profile on to the new one.

Select 'Copy' from the Actions menu in the Application toolbar. A list of existing user profiles will be displayed. Click on the one you want to copy. All the details of the profile except the User ID and the password will be copied and displayed for the new user. Enter a unique User ID and give a password. You can change any of the details of the profile before saving it.

### 2.10.3 Deleting a User Profile

Enter the User ID. The details defined will be displayed. Select 'Delete' from the Actions menu in the Application toolbar to delete an existing user profile. Only users that have not been authorized can be deleted by the creator. You will be prompted to confirm the deletion. The user profile will be deleted only if you confirm the deletion.

### 2.10.4 Closing a User Profile

Users Ids that are no longer usable can be closed. For Closing, Enter the User ID. The details defined will be displayed. Select 'Close' from the Actions menu in the Application toolbar to close an existing user profile. The profile can be closed only if the User is currently not logged on to the system.

You will be prompted to confirm the Closure. The user profile will be closure only if you confirm the Closure.

## 2.11 User Profile Entitlements

This section consists of the following topics:

- [Section 2.11.1, "Invoking User Maintenance Screen"](#)
- [Section 2.11.3, "Roles Button"](#)

- [Section 2.11.4, "Rights Button"](#)
- [Section 2.11.5, "Functions Button"](#)
- [Section 2.11.6, "Account Classes Button"](#)
- [Section 2.11.7, "Branches Button"](#)
- [Section 2.11.8, "Products Button"](#)
- [Section 2.11.9, "Disallowed Functions Button"](#)
- [Section 2.11.9, "Disallowed Functions Button"](#)
- [Section 2.11.10, "Centralized Role Button"](#)
- [Section 2.11.11, "Dashboard Mapping Button"](#)

### 2.11.1 Invoking User Maintenance Screen

A User Profile defines the activities that a user can carry out on the system. It also contains the user ID, the name through which the user will access the system and the password. The user profiles will be effective only after dual authorization.

You can create User Profiles through the 'User Maintenance' screen. You can invoke this screen by typing SMDUSRDF in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button. The 'User Entitlements' screen is shown below.

The screenshot shows the 'User Maintenance' application window. At the top, there are tabs for 'New' and 'Enter Query'. Below this, there are two sub-tabs: 'User Details' (active) and 'Additional Details'. The 'User Details' section contains several input fields: 'User Identification \*', 'Name \*', 'Language \*', 'Home Branch \*', 'Time Level \*', 'Department Code', 'Department Description', 'Amount Format' (with a dropdown), 'Number Format Mask' (with radio buttons for 'XXX.XXX.XXX.XXX' and 'XX,XX,XX,XX,XXX'), 'Date Format' (with a dropdown), 'Supervisor Identification', and 'Supervisor Name'. To the right of these fields is a 'Classification' section with a list of options: 'Staff' (selected), 'Branch', 'Multi Branch Access', 'Other RM Customer Access Restricted', 'Show Dashboards', 'Alerts on Home', 'Front-End Debug Enabled' (checked), and 'External Alerts'. At the bottom of the window, there is a navigation bar with links: 'Roles', 'Rights', 'Functions', 'Account Classes', 'Branches', 'Products', 'Disallowed Functions', 'Fields', and 'Centralized Role'. Below this bar is a table with columns: 'Maker', 'Date Time:', 'Mod No', 'Record Status', 'Checker', 'Date Time:', 'Authorization Status', and an 'Exit' button.

Specify the following details:

#### User Identification

Specify the user identification. This ID identifies the user whose profile you are defining. In a user ID, you can use alphabets in upper or lower case, numbers 0 to 9 and \_ (underscore).

The number of characters in a User ID should be greater than or equal to six and less than 12.

#### Name

Specify the name of the user.

## **Classification**

### **Staff**

All internal users of the bank can be classified as Staff. You can include any of the functions available in the system in the user profile.

### **Branch**

This indicates a branch user. This is used to identify a branch user and branch specific user maintenance for Branch user.

### **Multi Branch Access Required**

Check this box if you need to configure dual access framework for the specified User ID.

### **Other RM Customer Access Restricted**

You can restrict the users' access to the transactions of the customers who are assigned to a different relationship manager. Check this box to restrict the user from viewing, creating, authorizing or amending the transactions of the customers who are not assigned to him/her. The customers not assigned to the RM include the customers assigned to other relationship managers as well as those who are not assigned to any relationship manager.

If you do not check this box, the user can view, create, authorize and amend the transactions of the customers assigned to other relationship managers.

This is applicable to the users created with their role as 'Relationship Manager'.

### **Show Dashboards**

Check this box if you want the system to display all the Dashboards assigned to your 'User Role, on the landing page.

### **Alerts on Home**

Check this box if you want the system to display the Alerts, relevant to you, on the landing page.

### **Front-End Debug Enabled**

Check this box to enable the debug window for a user.

### **Auto Authorization**

To indicate that a user is allowed to perform automatic authorization, you must enable the 'Auto Authorize' option in the User Maintenance screen.

If automatic authorization has been enabled for a function, branch and user profile, and such a user has rights for both input and authorize operations, any record maintained by such a user in the corresponding function (maintenance or online) screens will be automatically authorized when the Save operation is performed.

Consider the following example.

You have enabled automatic authorization for the following branches in the Branch Parameters:

| <b>Branch</b> | <b>Automatic Authorization Enabled</b> |
|---------------|----------------------------------------|
| 000           | Yes                                    |
| 001           | No                                     |
| 002           | Yes                                    |

In the Function Description maintenance, automatic authorization has been enabled for the following functions:

| Function                         | Automatic Authorization Enabled |
|----------------------------------|---------------------------------|
| Customer Information Maintenance | Yes                             |
| LD Contract Online               | Yes                             |
| Customer Account Maintenance     | Yes                             |
| FT Contract Online               | No                              |

You have maintained automatic authorization rights for specific users in the User Profile maintenance as shown below:

| User   | Automatic Authorization Enabled |
|--------|---------------------------------|
| Ronald | Yes                             |
| George | Yes                             |
| Smith  | No                              |

You have also maintained transaction access rights for the users as shown below:

| User   | Branch | Function                         | Input Access | Authorize Access |
|--------|--------|----------------------------------|--------------|------------------|
| Ronald | 000    | Customer Information Maintenance | Yes          | Yes              |
| Ronald | 001    | Customer Information Maintenance | Yes          | Yes              |
| Ronald | 000    | FT Contract Online               | Yes          | Yes              |
| Ronald | 000    | Customer Account Maintenance     | Yes          | No               |
| George | 001    | LD Contract Online               | Yes          | Yes              |
| George | 000    | Customer Account Maintenance     | Yes          | Yes              |
| Smith  | 000    | LD Contract Online               | Yes          | Yes              |
| Smith  | 000    | Customer Account Maintenance     | Yes          | Yes              |

According to your maintenance, automatic authorization would be performed as shown below:

| User   | Branch | Function                         | Automatic Authorization on Save? | Reason                                                                                                                                |
|--------|--------|----------------------------------|----------------------------------|---------------------------------------------------------------------------------------------------------------------------------------|
| Ronald | 000    | Customer Information Maintenance | Yes                              | Input and Authorize rights enabled for the user, as well as automatic authorization rights enabled for the user, branch and function. |

|        |     |                                  |     |                                                                                                                                                                                                                              |
|--------|-----|----------------------------------|-----|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Ronald | 001 | Customer Information Maintenance | No  | Automatic authorization not enabled for branch 001                                                                                                                                                                           |
| Ronald | 000 | FT Contract Online               | No  | Automatic authorization not enabled for the FT Contract Online function                                                                                                                                                      |
| Ronald | 000 | Customer Account Maintenance     | No  | Authorization access not enabled for the user                                                                                                                                                                                |
| George | 001 | LD Contract Online               | No  | Automatic authorization not enabled for branch 001                                                                                                                                                                           |
| George | 000 | Customer Account Maintenance     | Yes | Input and Authorize rights enabled for the user, as well as automatic authorization rights enabled for the user, branch and function. The user can also authorize any maintenance done by the user Ronald in this function.. |
| Smith  | 000 | LD Contract Online               | No  | Authorization access not enabled for the user                                                                                                                                                                                |

- For more details about automatic authorization, consult the *Common Procedures user manual*.

### Language

Select the Language in which the Users screen have to be defined, from the option list. The Language Codes maintained through the 'Language codes' screen will be available for selection.

### Home Branch

By default the Current Branch is displayed here. All users have to be attached to a branch.

### Time Level

Time level is defaulted to nine here. You can specify the time level you need to maintain at the User level, if needed. You can specify values between zero and nine.

Time level can be specified at two levels - at the Branch level and at the User level.

If you need to login, then the time level maintained at your User Profile should be greater than or equal to that maintained at the Branch level.

Time levels are maintained to prevent you from logging into the application when the system is processing EOC batch. Before EOC Operations, the time level of the system is increased, so that it is higher than that maintained at the User level. However, if you are not logged out when the Time level is raised to the one higher than yours, then you can continue to use the application.

You can modify time level at user profile level when branch is at Transaction Input stage.

---

**Note**

After modifying the time level value to the value you need to maintain, move the cursor to any other field and then click the save icon.

---

**Department Code**

Specify the department code. The adjoining option list displays a list of all the valid department codes maintain in the system. You can choose the appropriate one.

**Department Description**

The system displays the Department description.

**Number Format Mask**

Select the format of mask number either in Million or in /Lakh from the following options:

- XXX,XXX,XXX,XXX
- XX,XX,XX,XX,XXX

**Supervisor Identification**

Specify the ID of the supervisor of the user. The option list displays all valid supervisor identifications maintained in the system. Choose the appropriate one.

In case of relationship managers, you can also use this field to define the RM hierarchy. For defining RM hierarchy in this method, you need to select the RM user who is one level up in the hierarchical order as the supervisor.

If the user is the superior in the RM hierarchical order, you can specify his/her own user ID as supervisor ID. The supervisor ID option list also shows the user ID of the user being maintained. This means, you can define an RM user as his/her own supervisor.

---

**Note**

The RM hierarchy defined in this method is enabled only if the checkbox 'RM Hierarchy Setup Required' is not checked in 'Bank Parameters Maintenance' screen.

---

**Supervisor Name**

Based on the supervisor ID selected, the system displays the name of the supervisor.

**Start Date**

Specify the date from which the User is valid. The default date appears if date is not specified.

**End Date**

Specify the end date up to which the User is valid. By default, there is no end date unless specified.

**Number Format Mask**

Select the format of mask number either in Million or in /Lakh from the following options:

- XXX,XXX,XXX,XXX
- XX,XX,XX,XX,XXX

**Front-End Debug Enabled**

Check this box to enable the debug window for a user.

## 2.11.2 Additional Details tab

### **Customer Number**

For User Profiles of your choice, Oracle FLEXCUBE allows you to restrict the viewing and printing of Balances (in case of accounts) and financial details of contracts involving customers who also happen to be employees of your bank. In order to enable this option, while creating the User Profile of the employee you can link the customer number (CIF ID) of the employee with the User ID.

### **Tax Identifier**

Specify the tax identifier code of the customer to monitor Anti Money Laundering activities. A user with restricted access will not be able to view/print details of contracts involving the product in all Contract Functions and Contract Summary screens for the following modules:

- Corporate Teller
- Clearing
- Funds Transfer
- Payment and Collections
- The Contract Online and Cycle Due screen of SI
- Foreign Exchange (online and payment)
- The Contract Online, Value Dated Amendments and Payments Input screens of MM
- The Contract Online put, Value Dated Amendments, Payments Input and Loans

---

#### **Note**

The view restriction is not applicable to the transaction or contract screens in which the other staff accounts are involved.

---

The other functions to which the user will have restrictive rights is as follows:

- Ad-hoc loan statement generation
- Queries – Accounting Entries
- Customer Based Information Retrieval
- Limits Overrides showing account balances
- Message Browser
- Payments and Collections Message browser

---

#### **Note**

In the Payments and Collection module the restriction is applicable to product categories and not products.

---

If a balance exception has occurred, the balances are not displayed for the restricted user but will be replaced by \*\*.

---

#### **Note**

The restricted users will be able to:

- View/print financial information pertaining to contracts they have initiated or view/print balances pertaining to their own accounts

- Post transactions to the staff accounts or create contracts for staff members, even if the user is restricted to view/print balances / contract information pertaining to other colleagues.
  - In case of balance exception during transaction posting, the balance will not be displayed. The Exception Message will only state that the account will be 'overdrawn' on account of the transaction.
  - Post transactions and view transaction information until the contract is authorized. After authorization, such users cannot access the contract
- 

The only exception is that when the user has captured a contract, the user will be allowed to view the details till the contract gets authorized.

#### **MFI User**

Select the 'MFI User' check box to indicate that the user is a Microfinance (Account Officer) user. By default, the system leaves this check box deselected to indicate that all users would be normal users.

---

#### **Note**

An account officer can book loan accounts for customers who are linked to him/her.

---

For more details, refer to 'Linking Customers to Account Officers' in the Microfinance User Manual.

#### **F10 Access Required**

Select this check box to access 'Customer Signature and Image View' (SVDIMGVW) screen.

#### **F11 Access Required**

Select this check box to access 'Customer Account Balance View (STDCUBAL) screen.

#### **F12 Access Required**

Select this check box to access 'Customer Signature and Image View' (SVDIMGVW) screen.

### **2.11.3 Roles Button**

A Role is always associated to a User for a specific Branch. The values set at the Role level are directly inherited by the User for that branch, like Functions Ids, Account Class and Branch Restrictions, Input and Authorization Limits, and so on.

To attach the user profile you are defining to a role, you must use the 'Roles' screen. Click 'Roles' button and the 'Roles' screen will be displayed. The roles to be attached to the user profile can be listed under 'Roles' list.

The screenshot shows a web application window titled "Roles". Inside the window, there is a section labeled "User Role Mapping". Below this section is a table with the following columns: "Branch Code", "Role", and "Role Description". The "Branch Code" and "Role" columns have small dropdown arrows next to them. The "Role Description" column is currently empty. At the bottom right of the window, there are two buttons: "Ok" and "Exit".

Specify the following details:

#### **Branch Code**

Specify the branch code assigned to the user role. The option list displays all the valid branch codes maintained in the system. You can choose the appropriate one.

#### **Role**

Specify the role assigned to the user for the selected branch. The option list displays all valid roles maintained in the system. Choose the appropriate one.

---

#### **Note**

You can assign the role of Relationship Manager to a user by selecting 'RM-ROLE'.

---

#### **Role Description**

Based on the role selected, the system displays the role description.


Click add icon to add a record under the 'Roles' list. Specify the above details to attach more roles to the user.

To delete a role(s) that has been attached to a user profile, check the box beside it and click delete icon.

### **2.11.4 Rights Button**

A user should have the necessary rights to perform various operations in respect of incoming and outgoing messages, in the Messaging module of Oracle FLEXCUBE. You can grant specific permissions for operations on messages, as well as allot the messaging queues to which the user has access. In the User Maintenance screen, click 'Rights' button to grant these rights pertaining to the Messaging module, to the user.

The screen is as shown below:



Check against the messaging operations for which you want to grant the permission.

### **Granting rights pertaining to operations on messages**

You can grant permissions for the following operations on outgoing messages:

- Generating a message
- Printing a message
- Placing a message on hold
- Releasing a message on hold
- Canceling a message
- Inserting a test word
- Reinstating a message
- Changing the priority of a message
- Requesting status of a message
- Requesting cancellation of a message
- Changing the media through which a message is transmitted
- Changing the address to which a message is to be sent
- Moving a message to another branch
- Changing the node from which a message should be generated
- Authorization of any of the operations listed above, in respect of outgoing messages

You can grant permissions for the following operations on incoming messages:

- Printing a message
- Authorizing a test word
- Routing a message to a queue
- Associating a message with a contract
- Uploading incoming messages

- Making changes (edit) incoming messages. You can also grant permissions for changing the branch and the address in incoming messages
- Authorizing changes made to incoming
- 'Force Release' payment message transactions with 'Funding Exception' status and insufficient funds
- Suppressing a message
- Deleting a message

Granting each of these permissions in the Rights screen enables the user to perform the corresponding functions in the Incoming and Outgoing Message Browsers. The appropriate button in the Browser, in each case, is enabled for the user.

*For details regarding each of these operations in respect of both incoming and outgoing messages, consult the Messaging System user manual*

Apart from these functions, you can also grant permission for the cover matching function for incoming payment message transactions.

*For details regarding uploading incoming payment transaction messages and cover matching for incoming payment transactions, refer the Straight Through Processing chapter in the Funds Transfer user manual.*

### **Queues**

You can allot the message queues to which the user has access, and in which the user can perform messaging operations according to the messaging rights you have assigned. The required queues can be selected and listed in the 'Queues' list under the 'Grant Queues' section.

## **2.11.5 Functions Button**

In addition to attaching a user profile to a role, you can give rights to individual functions. For a user profile to which no role is attached, you can give access to specific functions. If you have:

- Attached one or more roles to a user profile
- You have given access to individual functions to a profile to which roles are attached


The rights for Function IDs that figure in both the role and user specific functions will be applied as explained in the following example.

### **Example**

The role profile FXDP1 has access to New, Copy, Delete, Close, Reopen, Unlock and Print for the Forward Rates table.

You attach the user profile of Tanya to the role FXDP1. While allotting rights to individual functions for Tanya, you give rights to New, Copy, Delete and Close for the Forward Rates table. The role has access rights to Reopen, Unlock and Print in addition to these. In such a case, the user profile of Tanya will have rights to only the functions to which rights are given at the user profile level (that is, New, Copy, Delete and Close) even if the role FXDP1 has rights to other functions.

To give access to functions for the user profile you are defining, click 'Functions' button in the 'User Profile Definition' screen. The 'Functions' screen will be displayed as shown below:



The various functions in the system fall under different categories.

To assign a function to a user profile in the User Functions screen, you must select the tab of the function category to which the function belongs. The function categories and their respective tab in the User Functions screen are as follows:

| Category (Tab) | Description                                                                                             |
|----------------|---------------------------------------------------------------------------------------------------------|
| Maintenance    | Functions relating to the maintenance of static tables.                                                 |
| On-line        | Functions relating to contract processing.                                                              |
| Batch          | Functions relating to the automated operations (like automatic liquidation of contract, interest, etc.) |
| Reports        | Functions relating to the generation of reports in the various modules.                                 |
| Process        | Functions relating to access rights for the tasks under a process                                       |

Click on the corresponding category tab to associate the required functions as described below:

To add a function, click add icon. At Function Identification, you should select the function for which you want to give rights. The adjoining option list displays a list of Function IDs belonging to the category along with their descriptions. From this list you can pick up the function for which you want to give access rights by double clicking on it when it is highlighted. You can then specify the rights to the different actions for the functions by checking against the action.

### 2.11.6 Account Classes Button

You can restrict the user from using certain account classes that are maintained in Oracle FLEXCUBE in two ways.

- You can map an user role which has an account class restriction at User Role level, for an allowed branch in the Roles button at User Profile level.

Restricted account classes can be viewed in 'Account Class' option list at User Role level and not at User Profile level.

- Select account classes from the 'Account Class' option list and then select an option from the following at User Profile level:
  - Allowed–Select to allow selected account classes and disallow unselected account classes.
  - Disallow–Select to disallow selected account classes and allow unselected account classes.

In both the cases, user can query customer accounts belonging to restricted account class. However, the system will not allow creation and modification of an account under restricted account class.

Click 'Account Classes' button to specify such account class restrictions.

The screenshot shows a software window titled 'User Entitlements' with a sub-tab 'Account Classes'. Inside the window, there are two radio buttons under the heading 'Account Class Restriction': 'Allowed' (which is selected) and 'Disallowed'. Below this, there is a section titled 'Account Classes' containing a search bar with the text '1 Of 1' and a 'Go' button. Underneath the search bar is a table with a single header 'Account Class'. At the bottom right of the window, there are two buttons: 'Ok' and 'Exit'.

You can either allow or disallow the user from using certain account classes. Subsequently, specify the account classes, which have to be allowed or restricted for the user depending on the option selected. The following options are provided:

- Allowed–Select to allow user to use specified account classes.
- Disallowed–Select to disallow user to use specified account classes.

### 2.11.7 **Branches Button**

To specify the branches from which the Staff and Branch users of the bank can operate, you must use the 'Branches' screen.

Click 'Branches' button in the User Maintenance screen and 'Branches' screen will be displayed as shown below.

The screenshot shows a web application window titled "User Entitlements" with a sub-header "Branches". Below the sub-header, there are two radio buttons for "Branch Restriction": "Allowed" (which is selected) and "Disallowed". Below this, there is a table titled "Branches". The table has two columns: "Branch" and "Branch Name". The table is currently empty. At the bottom right of the window, there are two buttons: "Ok" and "Exit".

You can maintain a list of branches to which the user is either:

- Allowed
- Disallowed

To maintain an allowed list of branches choose the Allowed option. Then the 'Branch Restrictions' list will show the list of allowed branches. To maintain a disallowed list of branches, choose the Disallowed option.

If you maintain an 'allowed' list, then the user profile will be available only for those branches that you specify in the Branch Restrictions list. Similarly, if you maintain a 'disallowed' list, then the user profile will not be available only for those branches that you specify in the Branch Restrictions list. Any branch that is 'Disallowed' will not appear to that user in his 'Change Branch' list.

After choosing either the 'Allowed' or 'Disallowed' option, click add icon to add a record under the 'Branch Restrictions' list. Into each added record's field, select the required branch by clicking the adjoining option list.

---

#### Note

- The branch in which the user profile is defined is known as the Home Branch. The branches the user can access are known as the Host Branches
  - You should create an ID called GUEST in each branch. When a user belonging to the Staff category changes the branch of operation, he can perform the functions defined for the GUEST ID in the Host Branch.
-

### 2.11.8 Products Button

You can restrict the user from using certain products maintained in FLEXCUBE. Such product restrictions for the user can be specified in the 'Products' screen. Click 'Products' button and the 'Products' screen will be displayed.

The screenshot shows a web application window titled 'User Entitlements' with a sub-header 'Products'. Below this is a table with two columns: 'Product Code' and 'Product Description'. The table is currently empty. Below the table, there is a section for 'Posting Restriction' with two radio buttons: 'Allowed' (which is selected) and 'Disallowed'. At the bottom right of the window, there are two buttons: 'Ok' and 'Exit'.

In this screen you can place the following restrictions on the User Profile:

- Posting Restriction
- Access Restriction

Users who have posting restrictions will not be able to process transactions involving restricted products. Users with access restrictions will not be allowed to view or print financial details of contracts involving restricted products.

To allow or disallow the user from posting into/accessing certain products by

- Select the option 'Allowed' if you want to allow the user to post entries into/access certain products
- Select the option 'Disallowed' to disallow the user from posting/accessing certain products

After choosing the 'Allowed' or 'Disallowed' option, click add icon to add a record under the 'Products' list. Into each added record's field select the required Product Code by clicking the adjoining option list.

---

#### Note

- If for a product the Access restriction has not been maintained but Posting is allowed the restricted user can post transactions for that product and can view the contract information until such time that the contract gets authorized.
  - For the PC module, you can apply restrictions on product categories.
-

### 2.11.9 Disallowed Functions Button

You can restrict certain functions from being performed by a user. You can specify such restrictions in the 'Disallowed Functions' screen. Click 'Disallowed Functions' button to invoke this screen.

The screenshot shows a web application window titled 'User Entitlements' with a subtitle 'Disallowed Functions'. The main content area is titled 'Function Disallow' and contains a table with one header row: a checkbox and a column labeled 'Function \*'. The table is currently empty. At the bottom right of the window are 'Ok' and 'Exit' buttons.

Click add icon to add a record under the 'Function' list. Into each added field, select the required function by clicking the adjoining option list.

### 2.11.10 Centralized Role Button

The centralization role can be linked to a user here. You can view centralized role maintained for the user profile in the 'Centralized Role' screen. Click 'Centralized Role' button to invoke this screen.

The screenshot shows a web application window titled 'User Entitlements' with a subtitle 'Centralized Role Mapping'. The main content area is titled 'Centralized Role Mapping' and contains a table with one header row: a checkbox, a column labeled 'Role \*', and a column labeled 'Role Description'. The table is currently empty. At the bottom right of the window are 'Ok' and 'Exit' buttons.

If the multi branch operational parameter is enabled and the centralization roles are defined, then the roles are automatically assigned to the branches based on the branch restricted details specified in the user maintenance screen. You can also include additional list of normal roles from the Roles sub screen.

---

**Note**

You cannot assign a centralized role to a subset of allowed branches of a user. You have to manually assign the normal role to each applicable branch.

---

### 2.11.11 Dashboard Mapping Button

If you checked the 'Show Dashboards' check box in the main page of the 'User Maintenance' screen, then you can map the specified 'User' to one or more Dashboards in the 'Dashboard Maintenance' sub-screen. Click 'Dashboard Mapping' button to invoke this screen.

User Entitlements

Dashboard Maintenance

User Identification

Name

1 Of 1

| Function Id | Description | Sequence Number | Clause Wizard | Where Clause | Show In Dash board |
|-------------|-------------|-----------------|---------------|--------------|--------------------|
|-------------|-------------|-----------------|---------------|--------------|--------------------|

Ok Exit

The system defaults the following from the main screen:

- User Identification
- Name

Click 'Populate' button, the system displays DFIs mapped to the specified 'User Role'. The system defaults the following details:

- Function ID – Function ID of the Dashboard assigned to the 'User'.
- Description – Description of the Dashboard

You can maintain the following details for the dash:

**Sequence Number**

Specify the sequence number, based on the 'User' preference.

## Clause Wizard

Click to invoke 'Dashboard Condition' sub-screen. You can maintain filter conditions for each DFI the 'User' is mapped to.



You can maintain filter conditions for a specific Dashboard:

### Column Name

Specify the column name for which you want to maintain filter conditions. The adjoining option list displays all valid columns available in the Dashboard. Choose the appropriate one.

### Condition

Select the filter condition you want to maintain. The following conditions are available:

- AND
- OR
- (
- )
- =
- >
- <

Click 'Add' to add the selected conditions to 'Where Clause'.

### Where Clause

Here, the system defaults the values specified in 'Dashboard Condition' screen.

### Show in Dashboard

Check this box if you want to display a specific Dashboard assigned to the 'User'.

---

#### Note

The system generates a notification on authorization of any modification, addition or deletion of user.

---

## 2.12 Department Details

This section contains the following topics:

- [Section 2.12.1, "Specifying Department Details"](#)

### 2.12.1 Specifying Department Details

Oracle FLEXCUBE allows you to maintain department details in the system. However, only privileged administrative users can edit the department details. You can capture department details in the 'Department Maintenance' screen. You can invoke this screen by typing 'SMDDPTMT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Department Maintenance

lew

Department Details

Department Code \* AAA

Department Short Name \* AAAA

Department Description \* AAAA

Maker 217413M Date Time: 2014-01-01 13:55:24 Mod No 1 Record Status Open

Checker 217413M Date Time: 2014-01-01 13:55:24 Authorization Authorized Status

Exit

### Department Details

Here you can specify the following:

#### **Department Code**

Specify the department code. You can enter a maximum of 3 alphanumeric characters.

#### **Department Short Name**

Specify the department short name. You can enter a maximum of 10 alphanumeric characters.

#### **Department Description**

Specify the department description. You can enter a maximum of 225 alphanumeric characters.

## 2.13 Process Codes

This section contains the following topics:

- [Section 2.13.1, "Maintaining Process Codes"](#)

### 2.13.1 Maintaining Process Codes

You can maintain the process codes using the 'Process Definition' screen. You can invoke this screen by typing 'SMDPRCDE' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The 'Process Definition' screen is shown below:

| Fields  |        |            |            |               |                   |
|---------|--------|------------|------------|---------------|-------------------|
| Maker   | SYSTEM | Date Time: | 1998-01-01 | Mod No        | 1                 |
| Checker | SYSTEM | Date Time: | 1998-01-01 | Record Status | Open              |
|         |        |            |            | Authorization | Authorized Status |

You can specify the following here:

#### Process Code

Specify a unique code for the process.


#### Description

Enter an appropriate description of the process.

After entering the details, click the 'Save' button.

## 2.14 Single Sign On (SSO) Enabled Environment

Provided you have opted for the SSO Enabled option at bank level, you can log in from an LDAP (Oracle Internet Directory) external system into Oracle FLEXCUBE through the screen shown below.



After successful authentication and authorization of the user is carried out by the LDAP (Oracle Internet Directory), a request is forwarded to gain access into Oracle FLEXCUBE. On clicking the 'Submit' button you can directly get into Oracle FLEXCUBE without specifying Oracle FLEXCUBE user id and password.

## 2.15 Defining Entity Maintenance

The 'Entity Maintenance' screen is used for maintaining or modifying the entities and Java Naming and Directory Interface (JNDI).

You can invoke this screen by typing 'SMDENTDT' in the field at the top right corner of the Application toolbar and clicking on the adjoining arrow button.

Entity Maintenance

Enter Query

Entity ID \*

Entity Description

JNDI Name

Maker

Checker

Date Time:

Date Time:

Mod No

Record Status

Authorization Status

Exit

---

## 3. Associated Functions

This chapter contains the following sections:

- [Section 3.1, "Clearing a User ID"](#)
- [Section 3.2, "System Time Level"](#)
- [Section 3.3, "Language Codes"](#)
- [Section 3.4, "Branch of Operation"](#)
- [Section 3.5, "User Password"](#)
- [Section 3.6, "SSO Parameters"](#)
- [Section 3.7, "Transaction Status Control"](#)
- [Section 3.8, "Customized Hot Keys"](#)
- [Section 3.9, "Viewing User Activities"](#)

### 3.1 Clearing a User ID

This section contains the following topics:

- [Section 3.1.1, "Invoking the Clear User Screen"](#)

#### 3.1.1 Invoking the Clear User Screen

When a User logs into the system, the system maintains a record of the user with the date and time of login. On a successful, normal log out this record gets deleted.

Occasionally, you may come across a situation when a user who is logged into the system is forced out. However, the ID of the user still continues to have a status of Currently Logged In. In such a situation, the user will not be allowed to log in to the system again.

Such User IDs can be cleared through the 'Clear User Profile' screen. You can invoke this screen by typing 'CLRU' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows the 'Clear User' application window. It features a title bar with the text 'Clear User' and standard window controls (minimize, maximize, close). The main area contains a form with two input fields: 'User Id' and 'Branch Code'. Below these fields is a blue 'Fetch' button. Underneath the form is a section titled 'Records' which contains a table. The table has three columns: 'Branch Code', 'User Id', and 'User Name'. The table is currently empty. At the bottom right of the window, there are two buttons: 'Clear' and 'Exit'.

You can search for the users based on the following parameters:

- User Id
- Branch Code

Once you have specified the parameters click 'Fetch' button. The system lists the following details of the users who have logged into the application:

- Branch Code
- User ID
- User Name

To force log out a user, check the box against the relevant user record and click 'Clear' button. The system will display a message to confirm the clear operation. To force log out all the users in a page, check the box against the header row, which will select all the users in the page. Further click the 'Clear' button. The selected users are logged off from the application.

Select the check boxes next to the User IDs which you want to clear and then click 'Clear' button.

## **3.2 System Time Level**

This section contains the following topics:

- [Section 3.2.1, "Changing the System Time Level"](#)

### **3.2.1 Changing the System Time Level**

The time level is allotted at two levels — at the system (branch) level and at the user level. For a user to be able to login, the time level for the user profile should be greater than or equal to that of the system. The time level can be between zero and nine.

You can change time level of the branch by using the 'Change Time Level' screen. You can invoke this screen by typing 'SMDCHNTL' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button. Click 'Users' button for a display of the details of users who are currently logged in.

This screen shows a list of all users who are currently logged in and their respective Time Levels. When the Time Level of the branch is changed the system validates and displays a message if the Time Level of any of the Users is lesser than that of the newly changed value. These users can continue to log onto and work on the system till they log off. When they try

to log in back the system validates and only allows such users access whose time levels are greater than that of the system.

## 3.3 Language Codes

This section contains the following topics:

- [Section 3.3.1, "Defining Language Codes"](#)

### 3.3.1 Defining Language Codes

Every language that is supported by the system is identified by a Language Code. In Oracle FLEXCUBE, this code is a three character alphanumeric code.

Invoke the 'Language Code Maintenance' screen by typing SMDLNGCE' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

For example, for English language, the code you could enter in Oracle FLEXCUBE could be ENG.

## 3.4 Branch of Operation

This section contains the following topics:

- [Section 3.4.1, "Changing the Branch of Operation"](#)

### 3.4.1 Changing the Branch of Operation

Through this function, you can change the branch of operation to a branch other than the one you are signed on to. The branches to which you can change into will be defined in your user profile. You can change your branch of operation only when a function that has been initiated by you in the current branch has been completed.

The screen is as shown below:

**List of Values Branch Code**

☐ Case Sensitive

Branch Code %      Branch Status %  
Branch Name %      Time Level %

**Search Results**

1 Of 1

| Branch Code | Branch Name             | Branch Status     | Time Level |
|-------------|-------------------------|-------------------|------------|
| 000         | FLEXCUBE UNIVERSAL BANK | TRANSACTION INPUT | 9          |

## 3.5 User Password

This section contains the following topics:

- [Section 3.5.1, "Changing the User Password"](#)

### 3.5.1 Changing the User Password

The Password of a User can be changed either when it expires or at the will of the user using the 'Change Password' screen.

**Change Password**

Enter Old Password   
Enter new password   
Confirm New Password

The following details are captured here:

**Enter Old password**

Specify the old password which has to be changed.

**Enter new password**

Specify the new password.

**Confirm new password**

Specify the new password.

Click 'Save' to save the new password. Click 'Cancel' to exit the screen.

## 3.6 SSO Parameters

This section contains the following topics:

- [Section 3.6.1, "Maintaining SSO Parameters"](#)

### 3.6.1 Maintaining SSO Parameters

LDAP is an external directory system which stores the details regarding user ids and password.

Once SSO has been enabled for your bank, the SSO parameters need to be maintained. This can be done using the 'Single Sign On Maintenance' screen. You can invoke this screen by typing 'SMDSOPRM' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

| Maker   | Date Time: | Mod No | Record Status        |
|---------|------------|--------|----------------------|
| Checker | Date Time: |        | Authorization Status |

Exit

The following details can be maintained in this screen:

**LDAP Host**

Indicate the machine or server name where LDAP (Oracle Internet Directory) is installed.

**LDAP Port**

Specify the network Port number where the LDAP (Oracle Internet Directory) listen to the Server.

**LDAP Admin id**

Specify the admin user id of the LDAP (Oracle Internet Directory).

**LDAP Password**

Specify the Password for the LDAP Admin User which is provided during installation.

**LDAP Base**

Specify the directory information tree (DIT) structure under which the data is to be stored, which is provided during installation. This is used while validating the user present in the LDAP (Oracle Internet Directory).

**Time Out Duration (Sec)**

You can stipulate the allowable idle time (in seconds) that a user can spend without performing any activity, after logging in to the system.

## 3.7 Transaction Status Control

This section contains the following topics:

- [Section 3.7.1, "Maintaining Transaction Status Control"](#)

### 3.7.1 Maintaining Transaction Status Control

The 'Transaction Status Control Maintenance' screen allows the user to define the various action buttons depending on the status of the contract. You can invoke this screen by typing 'SMSTXNST' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button. For each Transaction Status, the record status 'Authorized' or 'Unauthorized', could also affect the Action buttons.

Some of the statuses that a Contract could have are:

- Y-Irrevocable
- A-Authorized
- U-Unauthorized
- V-Reversed
- L-Liquidated
- S-Closed
- H-Hold
- K-Cancelled
- N-NON-CUMULATIVE
- T-TIME
- O-OUR

Transaction Status Control Maintenance

Enter Query

Transaction status Maintenance

| Transaction Status Maintenance | Authorization | New                                 | Copy                                | Delete                              | Closed                              | Unlock                              | Reopen                              | Print                               | Authorize                           | Reverse                             |
|--------------------------------|---------------|-------------------------------------|-------------------------------------|-------------------------------------|-------------------------------------|-------------------------------------|-------------------------------------|-------------------------------------|-------------------------------------|-------------------------------------|
| C                              | A             | <input checked="" type="checkbox"/> | <input checked="" type="checkbox"/> | <input type="checkbox"/>            | <input type="checkbox"/>            | <input checked="" type="checkbox"/> | <input checked="" type="checkbox"/> | <input checked="" type="checkbox"/> | <input type="checkbox"/>            | <input checked="" type="checkbox"/> |
| C                              | U             | <input checked="" type="checkbox"/> | <input type="checkbox"/>            | <input type="checkbox"/>            | <input type="checkbox"/>            | <input type="checkbox"/>            | <input type="checkbox"/>            | <input checked="" type="checkbox"/> | <input checked="" type="checkbox"/> | <input type="checkbox"/>            |
| O                              | A             | <input checked="" type="checkbox"/> | <input type="checkbox"/>            | <input type="checkbox"/>            | <input checked="" type="checkbox"/> | <input type="checkbox"/>            | <input type="checkbox"/>            | <input checked="" type="checkbox"/> | <input type="checkbox"/>            | <input type="checkbox"/>            |
| O                              | U             | <input checked="" type="checkbox"/> | <input type="checkbox"/>            | <input checked="" type="checkbox"/> | <input type="checkbox"/>            | <input checked="" type="checkbox"/> | <input type="checkbox"/>            | <input checked="" type="checkbox"/> | <input checked="" type="checkbox"/> | <input type="checkbox"/>            |
| A                              | A             | <input checked="" type="checkbox"/> | <input checked="" type="checkbox"/> | <input type="checkbox"/>            | <input checked="" type="checkbox"/> | <input checked="" type="checkbox"/> | <input type="checkbox"/>            | <input checked="" type="checkbox"/> | <input type="checkbox"/>            | <input checked="" type="checkbox"/> |
| A                              | U             | <input checked="" type="checkbox"/> | <input checked="" type="checkbox"/> | <input checked="" type="checkbox"/> | <input type="checkbox"/>            | <input checked="" type="checkbox"/> | <input type="checkbox"/>            | <input checked="" type="checkbox"/> | <input checked="" type="checkbox"/> | <input type="checkbox"/>            |
| C                              | A             | <input checked="" type="checkbox"/> | <input checked="" type="checkbox"/> | <input type="checkbox"/>            | <input type="checkbox"/>            | <input type="checkbox"/>            | <input checked="" type="checkbox"/> | <input checked="" type="checkbox"/> | <input type="checkbox"/>            | <input type="checkbox"/>            |

Cancel

Check the box against a transaction record to select the actions allowed for that transaction. Following are the actions that are allowed on a record:

- New
- Copy
- Delete
- Close
- Unlock
- Reopen
- Print
- Auth
- Reverse

## 3.8 Customized Hot Keys

This section contains the following topics:

- [Section 3.8.1, "Configuring Customized Hot Keys"](#)

### 3.8.1 Configuring Customized Hot Keys

Oracle FLEXCUBE allows you to configure Hot keys or Shortcut keys for function ids, using which you can launch the function id screens without typing the function ids. For this you need to map each function id to a hot key using the 'Hot Key Maintenance' screen. To invoke the 'Hot Keys Maintenance' screen click the option 'Hot Keys' under 'Options' menu. You invoke

this screen by typing 'SMDHOTKY' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Hot Keys Maintenance

User \*

Hot Key

Ctrl+1

Ctrl+2

Ctrl+3

Ctrl+4

Ctrl+5

Ctrl+6

Ctrl+7

Ctrl+8

Ctrl+9

Exit

The following details are captured in this screen:

#### **User Id**

The id of the user who has logged in is displayed here.

#### **Hot Key Details**

Here, you can map a function id against each hot key. You can select the function id to be mapped against the hot key from the adjoining option list.

## **3.9 Viewing User Activities**

This section contains the following topics:

- [Section 3.9.1, "Viewing User Activities"](#)

### **3.9.1 Viewing User Activities**

You can view a log of activities of Oracle FLEXCUBE users through the 'User Activity' screen. You can view user activities only through Oracle FLEXCUBE host system. This screen is not available for viewing in the branch installations. You can invoke this screen by typing 'SMSUSRAC' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screen is displayed as below:

The screenshot shows a web application window titled "User Activity". At the top, there are tabs for "Search", "Advanced Search", and "Reset". Below these are search filters: "User ID" and "Branch Code" with magnifying glass icons, and "Function Id" with a magnifying glass icon. Below the filters is a pagination bar showing "Records per page: 15", "1 Of 1", and a "Go" button. Below the pagination bar is a table with the following columns: "User ID", "IP Address", "Branch Code", "Function Id", "Sequence Number", "System Start Time", "System End Time", and "Exit". The table is currently empty. At the bottom right of the window is an "Exit" button.

You can query for records based on the following criteria:

- User ID
- Branch Code
- Function ID

Click 'Search' button. Based on your preferences, the system identifies all records satisfying the criteria and displays the following details for every record:

- User ID
- IP Address
- Branch Code
- Function ID
- Sequence No
- System Start Time
- System End Time
- Exit Flag

---

## 4. Error Codes and Messages

This chapter contains the following section:

- [Section 4.1, "Error Codes"](#)

## 4.1 Error Codes

| Error Code | Message                                                                                                |
|------------|--------------------------------------------------------------------------------------------------------|
| SM-00001   | Unauthorized installation. Contact Oracle Financial Services representative                            |
| SM-00002   | Licensed number of users exceeded. Try again after a while                                             |
| SM-00003   | Guest ids can sign on only via change branch function                                                  |
| SM-00004   | Invalid login                                                                                          |
| SM-00005   | User already logged in                                                                                 |
| SM-00006   | User status is disabled. Please contact your system administrator.                                     |
| SM-00007   | User status on hold. Contact your system administrator                                                 |
| SM-00008   | Your time level does not permit you to log in. Contact your branch system administrator                |
| SM-00009   | Please change password now!                                                                            |
| SM-00010   | Password file missing or corrupt                                                                       |
| SM-00011   | Contact your system administrator. Oracle built in problem                                             |
| SM-00012   | SMTBS_passwords table missing or entries not found                                                     |
| SM-00014   | Password due to expire on \$1                                                                          |
| SM-00015   | User profile expired. Contact branch system administrator                                              |
| SM-00016   | Your time level does not permit you to launch this function                                            |
| SM-00030   | This function is currently not available for execution                                                 |
| SM-00031   | This form \$1 is not available. Contact your branch system administrator                               |
| SM-00032   | The time level in the branch has changed. Your time level does not permit you to execute any functions |
| SM-00033   | The number of users currently executing functions in this module has exceeded the license limit.       |
| SM-00034   | This function is not available for customer access                                                     |
| SM-00035   | This function is not available for staff access                                                        |
| SM-00036   | Function ID is not correct. Enter function ID again                                                    |
| SM-00037   | Main menu and sub menu descriptions cannot be same                                                     |
| SM-00040   | Wrong password. Enter password again                                                                   |
| SM-00041   | The new and confirmed passwords do not match. Enter passwords again                                    |
| SM-00042   | The password entered is restricted. Try another password                                               |

| Error Code | Message                                                                               |
|------------|---------------------------------------------------------------------------------------|
| SM-00043   | The password entered has already been used. Try another password                      |
| SM-00044   | Length of password is less than \$1 characters                                        |
| SM-00045   | Length of password is more than \$1 characters                                        |
| SM-00046   | The password string contains special characters that are not allowed. Retype password |
| SM-00050   | Control clerks passwords do not match. Retype passwords again                         |
| SM-00060   | There are users currently logged in with a lesser time level. Do you want to change?  |
| SM-00070   | You are currently executing some functions. Exit from those functions and try again   |
| SM-00080   | User ID already exists.                                                               |
| SM-00081   | Negative amount not allowed                                                           |
| SM-00082   | Start cannot be before today                                                          |
| SM-00083   | End date cannot be before start date                                                  |
| SM-00084   | Start date cannot be null                                                             |
| SM-00085   | User profile saved                                                                    |
| SM-00086   | Could not save user profile                                                           |
| SM-00087   | User profile deleted                                                                  |
| SM-00088   | Could not delete user profile                                                         |
| SM-00089   | Mandatory or not null fields are missing                                              |
| SM-00090   | Role ID already exists                                                                |
| SM-00091   | Users attached to the role. Cannot delete                                             |
| SM-00092   | Role deleted                                                                          |
| SM-00093   | Invalid role ID                                                                       |
| SM-00094   | Currency code not defined                                                             |
| SM-00095   | Branch code not defined                                                               |
| SM-00096   | Customer no not defined                                                               |
| SM-00097   | Customer category not defined                                                         |
| SM-00098   | Role profile saved                                                                    |
| SM-00100   | Cannot delete the role. There are users attached to this role.                        |
| SM-00101   | Cannot delete function. There are users attached to this function.                    |

| Error Code | Message                                                                                |
|------------|----------------------------------------------------------------------------------------|
| SM-00102   | Cannot modify function. There are users attached to this function.                     |
| SM-00103   | Do you want to delete the user?                                                        |
| SM-00104   | Do you want to delete the role?                                                        |
| SM-00105   | Cannot delete role. Users attached to role.                                            |
| SM-00110   | Site code length cannot be less than 4 characters                                      |
| SM-00111   | Cumulative invalid logins - number should be greater than 5 and less than 100          |
| SM-00112   | Successive invalid logins - number should be greater than 2 and less than 6            |
| SM-00113   | Password prevent reuse value should be between 1 and 5                                 |
| SM-00114   | Minimum password length should be between 6 and 10                                     |
| SM-00115   | Maximum password length should be between 9 and 12                                     |
| SM-00116   | Graph not found. Contact your branch administrator                                     |
| SM-00117   | Password change after message - no of days should be greater than 15 and less than 180 |
| SM-00118   | Archival period should be greater than 0                                               |
| SM-00119   | Enter the role description                                                             |
| SM-00120   | Cannot delete/modify role of other branch                                              |
| SM-00121   | Idle time before sign off should be between 30 and 600                                 |
| SM-00122   | Password expiry message - between 0 and 5                                              |
| SM-00123   | Enter a valid module ID                                                                |
| SM-00125   | Min password length should be less than Max password length                            |
| SM-00126   | Override idle time should be greater than 10                                           |
| SM-00130   | User access to \$1 \$2 denied                                                          |
| SM-00131   | Duplicate values encountered                                                           |
| SM-00140   | Guest ID not defined in branch \$1                                                     |
| SM-00150   | Maximum value encountered                                                              |
| SM-00160   | Users attached to the language code. Cannot delete                                     |
| SM-00161   | Language code already exists. Try another one                                          |
| SM-00170   | Reserved word cannot be used                                                           |
| SM-00500   | Mandatory values missing or null                                                       |

| Error Code | Message                                                                                                 |
|------------|---------------------------------------------------------------------------------------------------------|
| SM-00501   | Activation key contains irrelevant characters. Wrong activation key                                     |
| SM-00502   | Installation with this key already done. Cannot duplicate                                               |
| SM-00503   | Installation not done. Contact BSA or Oracle Financial Services representative                          |
| SM-00510   | No branches defined for user                                                                            |
| SM-00520   | Could not delete function. Role attached                                                                |
| SM-00530   | Could not delete function. Users attached                                                               |
| SM-00171   | Max password Length can not be null                                                                     |
| SM-00172   | Min password Length can not be null                                                                     |
| SM-00173   | Min password alphabets length can not be greater than Max password alphabets length                     |
| SM-00174   | Min password alphabets length can not be greater than Max password length                               |
| SM-00175   | Min password alphabets length + Max password numeric length can not be greater than Max password Length |
| SM-00176   | Min password alphabets length + Min password numeric length can not be greater than Min password Length |
| SM-00177   | Min password numeric length can not be greater than Max password numeric length                         |
| SM-00178   | Min password numeric length can not be greater than Max password length                                 |
| SM-00179   | Min password numeric length + Max password alphabets length can not be greater than Max password Length |
| SM-00180   | Max password alphabets length can not be lesser than Min password alphabets length                      |
| SM-00181   | Max password alphabets length can not be greater than Max password length                               |
| SM-00183   | Max password numeric length can not be greater than Max password length                                 |
| SM-00184   | Max password numeric length can not be lesser than Min password numeric length                          |
| SM-00185   | Password can not contain more than \$1 consecutive characters                                           |
| SM-00186   | Password should contain atleast \$1 Numeric characters                                                  |
| SM-00187   | Password should contain atleast \$1 Alphabetic characters                                               |
| SM-00188   | Min password alphabetic length can not be lesser than Min password length                               |

| Error Code | Message                                                                    |
|------------|----------------------------------------------------------------------------|
| SM-00189   | Min password numeric length can not be Greater than Min password length    |
| SM-00200   | Maximum No of Consecutive Characters should be Greater than 0              |
| SM-00201   | The transaction amount exceeds the maximum input amount for the user       |
| SM-00202   | The User is Un-Authorized                                                  |
| SM-00203   | The Last Login date was - \$1                                              |
| SM-00204   | Failed to validate transaction limits for the User                         |
| SM-00205   | Limits Id already exists                                                   |
| SM-00206   | Dormancy Days Should be Greater than 0                                     |
| SM-00207   | Warning Screen Text can not be Null                                        |
| SM-00208   | Role Limits attached to the User are Unauthorized                          |
| SM-00209   | Restriction type cannot be null                                            |
| SM-00251   | Value for legal notice is needed.                                          |
| SM-00252   | Value for legal notice is not needed.                                      |
| SM-00300   | Values for user limits are not applicable for the chosen transaction limit |
| SM-00301   | Values for role limits are not applicable for the chosen transaction limit |
| SM-00500   | Mandatory values missing or null                                           |
| SM-00501   | Activation key contains irrelevant characters. Wrong activation key        |
| SM-00502   | Installation with this key already done. Cannot duplicate                  |
| SM-00503   | Installation not done. Contact BSA or i-flex representative                |
| SM-00510   | No branches defined for user                                               |
| SM-00520   | Could not delete function. Role attached                                   |
| SM-00530   | Could not delete function. Users attached                                  |
| SM-00540   | Could not delete function                                                  |
| SM-00550   | Function successfully saved                                                |
| SM-00560   | Function not implemented                                                   |
| SM-00610   | No functions defined for the user                                          |
| SM-00612   | You are not logged on                                                      |
| SM-00900   | Process completed                                                          |
| SM-00901   | Please select user ids to Enable                                           |

| Error Code | Message                                                                                              |
|------------|------------------------------------------------------------------------------------------------------|
| SM-00998   | Password should be alphanumeric                                                                      |
| SM-00999   | First and last letter cannot be numeric                                                              |
| SM-01000   | Invalid password. Bad sign on                                                                        |
| SM-01001   | Invalid name. Bad sign on                                                                            |
| SM-01002   | Successive invalid logins. Forced disable                                                            |
| SM-01003   | Cumulative invalid logins. Forced disable                                                            |
| SM-01004   | Password expired. Password changed                                                                   |
| SM-01005   | User initiated password change.                                                                      |
| SM-01006   | Forced password change                                                                               |
| SM-01007   | Status enabled                                                                                       |
| SM-01008   | Status put on hold                                                                                   |
| SM-01009   | No of licensed users for modules exceeded                                                            |
| SM-01010   | No of licensed users for bank exceeded                                                               |
| SM-01011   | Wrong activation key entered                                                                         |
| SM-01012   | Duplicate terminal ID encountered.                                                                   |
| SM-01013   | SMS user profile cleared                                                                             |
| SM-01014   | Restricted access program invoked by control clerks                                                  |
| SM-01015   | User profile definition form invoked                                                                 |
| SM-01016   | Role profile definition form invoked                                                                 |
| SM-01017   | SMS bank parameters definition form invoked                                                          |
| SM-01018   | Wrong control clerk password entered                                                                 |
| SM-01019   | Function id is not available for current module                                                      |
| SM-01099   | Your Current amount decimal separator is not \$1'. Please ask IT to change machine oracle settings.' |
| SM-01100   | Entries in SMS bank parameters missing                                                               |
| SM-01101   | Could not get today s date for the head office                                                       |
| SM-01102   | Bank code not maintained in branch table                                                             |
| SM-01103   | Local currency not maintained in bank table                                                          |
| SM-01104   | User already signed on                                                                               |
| SM-01105   | User \$1 in branch \$2 changed branch to branch \$3 as user \$4                                      |

| Error Code | Message                                              |
|------------|------------------------------------------------------|
| SM-01205   | Both Passwords expired. Change Password Now          |
| SM-01206   | Password1 expired. Change Password Now               |
| SM-01207   | Password2 expired. Change Password Now               |
| SM-0200    | Cannot restrict current password                     |
| SM-02000   | Internal error: exception raised in \$1              |
| SM-02001   | Enter from date                                      |
| SM-02002   | Enter to date                                        |
| SM-02003   | From date cannot be later than to date               |
| SM-02004   | Enter from time                                      |
| SM-02005   | Enter to time                                        |
| SM-02006   | From time cannot be later than to time               |
| SM-02007   | Select all users to use purge option                 |
| SM-02008   | Role ID should be entered                            |
| SM-02009   | User ID should be entered                            |
| SM-05000   | Installation successful                              |
| SM-06001   | User does not exist                                  |
| SM-06500   | Document Long Description is Mandatory               |
| SM-0999    | You do not have access to this function              |
| SM-09999   | Internal error: unhandled exception raised           |
| SM-10000   | Do you want to reset cumulative invalid logins to 0? |
| SM-10001   | Head office branch code is not valid                 |
| SM-10002   | Language code must be 3 characters                   |
| SM-10003   | Branch is closed                                     |
| SM-10004   | Number of invalid logins since last logout = \$1     |
| SM-10005   | This Function has been linked to a role              |
| SM-3001    | User does not have rights                            |
| SM-3002    | Incorrect User ID or password                        |
| SM-555555  | Sign off allowed only from home branch               |
| SM-555556  | Logout allowed only from home branch                 |

| Error Code | Message                                                                               |
|------------|---------------------------------------------------------------------------------------|
| SM-555557  | Triggers in the database are disabled. Please contact System Administrator.           |
| SM-666666  | Amount exceeds users authorization limit                                              |
| SM-666666  | Amount exceeds users authorization limit                                              |
| SM-700007  | Terminal ID should be Four Characters in Length                                       |
| SM-7001    | Invalid User Id or Password                                                           |
| SM-7002    | User does not have rights                                                             |
| SM-7003    | Invalid Login                                                                         |
| SM-7004    | User already logged in                                                                |
| SM-7005    | User Status is Disabled                                                               |
| SM-7006    | User Status on Hold                                                                   |
| SM-7007    | Your Time level does not permit you to Login                                          |
| SM-7008    | Please change Password now!                                                           |
| SM-7010    | Password file missing or corrupt                                                      |
| SM-7011    | Oracle built in problem                                                               |
| SM-7012    | Password due to expire on \$1                                                         |
| SM-7013    | User Profile expired                                                                  |
| SM-7014    | Wrong Password                                                                        |
| SM-7015    | Enter Password again                                                                  |
| SM-7016    | The New and Confirmed Passwords do not match                                          |
| SM-7017    | Enter Passwords again                                                                 |
| SM-7018    | The Password entered is Restricted. Try another Password                              |
| SM-7019    | The Password entered has already been used. Try another Password                      |
| SM-7020    | Length of Password is less than \$1 characters                                        |
| SM-7021    | Length of Password is more than \$1 characters                                        |
| SM-7022    | The Password string contains special characters that are not allowed. Retype Password |

| Error Code | Message                                                                                |
|------------|----------------------------------------------------------------------------------------|
| SM-7023    | Password cannot contain more than \$1 consecutive identical characters                 |
| SM-7024    | You cannot change Password today                                                       |
| SM-7025    | The password should be mix of alphabetic and numeric characters                        |
| SM-7026    | Control Clerks Passwords do not match. Retype Passwords again                          |
| SM-7027    | There are Users currently logged in with a lesser time level. Do you want to change?   |
| SM-7028    | User Id already exists.                                                                |
| SM-7029    | Cumulative Invalid Logins - Number should be greater than 5 and less than 100          |
| SM-7031    | Password prevent reuse value should be between 1 and 5 Minimum                         |
| SM-7032    | Password length should be between 6 and 10                                             |
| SM-7033    | Maximum Password Length should be between 9 and 12                                     |
| SM-7034    | Password expiry message - between 0 and 5                                              |
| SM-7035    | Password change after message - no of days should be greater than 15 and less than 180 |
| SM-7036    | User Access to \$1 \$2 denied                                                          |
| SM-7037    | Consecutive Password Characters should be greater than 1                               |
| SM-7038    | The User is un-authorized                                                              |
| SM-7039    | The Last Login date was - \$1                                                          |
| SM-7040    | Password Changed Successfully                                                          |
| SM-7041    | Invalid Password. Bad Sign On                                                          |
| SM-7042    | Invalid Name. Bad Sign On                                                              |
| SM-7043    | Successive Invalid Logins                                                              |
| SM-7044    | Forced Disable Cumulative Invalid Logins                                               |
| SM-7045    | Forced Disable Password expired.                                                       |
| SM-7046    | Password changed                                                                       |
| SM-7047    | User initiated Password change                                                         |

| Error Code | Message                                                                      |
|------------|------------------------------------------------------------------------------|
| SM-7048    | Forced password change                                                       |
| SM-7049    | Status Enabled                                                               |
| SM-7050    | Status put on                                                                |
| SM-7051    | Hold User already Signed on                                                  |
| SM-7052    | Do you want to reset Cumulative Invalid Logins to 0 ?                        |
| SM-7053    | Number of Invalid Logins Since Last Logout = \$1                             |
| SM-7054    | User Password Changed Successfully                                           |
| SM-7055    | Change password now !!                                                       |
| SM-7056    | Terminal Id not set                                                          |
| SM-7057    | Message Digest not matched                                                   |
| SM-7058    | User Not Logged In. Please login again                                       |
| SM-7059    | Fast Path Cannot Contain Special Characters                                  |
| SM-7060    | Currency sold and Currency bought can not be same.                           |
| SM-7070    | Branch date is ahead of host date, cannot proceed                            |
| SM-77777   | User does not have rights to authorize the override                          |
| SM-AUTH01  | The transaction amount exceeds the maximum authorization amount for the User |
| SM-BRN01   | Not a Valid user for Branch                                                  |
| SM-BRN02   | Password for Branch User cannot be null                                      |
| SM-BVALUE1 | \$1 Back value days cannot be null                                           |
| SM-C0050   | Invalid Branch Code                                                          |
| SM-C0051   | Function ID Already attached                                                 |
| SM-C0052   | Branch or Function id should not be null                                     |
| SM-CHBRLO  | Change Branch to Home Branch In-Order to Logoff.                             |
| SM-CHBRSO  | Change Branch to Home Branch In-Order to Signoff.                            |
| SM-CLBRN01 | Branch User Profile Updated at Host                                          |

| Error Code | Message                                                         |
|------------|-----------------------------------------------------------------|
| SM-CLS001  | Users attached to Role. Close?                                  |
| SM-CV001   | Sequence no cannot be null                                      |
| SM-CV002   | Sequence no is a numeric field                                  |
| SM-CV003   | Group ID cannot be null                                         |
| SM-CV004   | Module code cannot be null                                      |
| SM-CV005   | Source code cannot be null                                      |
| SM-CV006   | Template ID cannot be null                                      |
| SM-CV007   | Duplicate broker ID                                             |
| SM-CV008   | Liquidation code cannot be null                                 |
| SM-CV009   | Duplicate details in record not allowed                         |
| SM-CV010   | Basis amount to cannot be null                                  |
| SM-CV011   | Floor basis amount has to be less than basis amount to          |
| SM-CV012   | Rate cannot be null for percentage type                         |
| SM-CV013   | Min amount cannot be more than floor charge for percentage type |
| SM-CV014   | Max amount cannot be less than floor charge for percentage type |
| SM-CV015   | Flat amount cannot be null for flat amount type                 |
| SM-CV016   | Invalid rate, rate is too high                                  |
| SM-CV017   | Floor basis amount cannot be null                               |
| SM-CV018   | Floor charge cannot be null                                     |
| SM-CV019   | Basis amount to cannot be less than basis amount from           |
| SM-CV020   | Duplicate rule code                                             |
| SM-CV021   | Minimum amount must be less than maximum amount                 |
| SM-CV022   | Maximum amount must be more than minimum amount                 |
| SM-CV023   | Rule cannot be null                                             |
| SM-CV024   | Group already exists                                            |

| Error Code | Message                                                                         |
|------------|---------------------------------------------------------------------------------|
| SM-CV025   | The record is already closed                                                    |
| SM-CV026   | Intermediate table has to be entered                                            |
| SM-CV027   | Upload table has to be entered                                                  |
| SM-CV028   | Cube table has to be entered                                                    |
| SM-CV029   | Source field cannot be null                                                     |
| SM-CV030   | Destination field cannot be null                                                |
| SM-CV031   | Destination field already maintained                                            |
| SM-CV032   | Group ID already maintained                                                     |
| SM-CV033   | Template ID already maintained for this group                                   |
| SM-CV034   | Sequence no already maintained for this group                                   |
| SM-CV035   | Invalid column name                                                             |
| SM-DATE1   | Failed to convert date format                                                   |
| SM-DEMO01  | Oracle FLEXCUBE not properly installed, exiting!                                |
| SM-DEMO02  | Demo version will expire after \$1 day(s)                                       |
| SM-DEMO03  | Welcome to Oracle FLEXCUBE                                                      |
| SM-DEMO04  | Only one user is allowed to login in demo version of Oracle FLEX-CUBE, exiting! |
| SM-DEMO05  | Insufficient parameters to launch Oracle FLEXCUBE, exiting!                     |
| SM-DEMO06  | Oracle FLEXCUBE demo version does not allow this function                       |
| SM-DEMO07  | Demo version expired, please contact i-flex!!!                                  |
| SM-DEMO08  | Demo version allows only \$1 contracts.                                         |
| SM-DEMO09  | Demo version expires today                                                      |
| SM-DTCH01  | Users are running functions.                                                    |
| SM-DTCH02  | AEOD dates not maintained                                                       |
| SM-DTCH03  | Wrong branch status to run this form                                            |
| SM-EFIN01  | Users in transactions input                                                     |

| Error Code | Message                                                                                                                   |
|------------|---------------------------------------------------------------------------------------------------------------------------|
| SM-EXTUS   | Oracle FLEXCUBE has been launched from another application. Sign off disallowed. Please exit                              |
| SM-FND01   | Menu items not populated                                                                                                  |
| SM-PRD02   | Deletion not allowed as periods beyond \$1 exist for the financial cycle                                                  |
| SM-PRD03   | The period end date has to be the last day of a month                                                                     |
| SM-PWC01   | Password same as previously used password                                                                                 |
| SM-QRY-01  | The form is in the enter-query mode. Please click on the exit toolbar button or exit menu item to get to the normal mode. |
| SM-QRY01   | The form is in the enter-query mode. Please click on the exit toolbar button or exit menu item to get to the normal mode. |

## 5. Reports

The chapter contains the following sections:

- [Section 5.1, "Batch Performance Statistics Report"](#)
- [Section 5.2, "Change Control Log Report"](#)
- [Section 5.3, "Disabled Users System Violation Log Report"](#)
- [Section 5.4, "Event Log Report"](#)
- [Section 5.5, "New User Created Report"](#)
- [Section 5.6, "Role Profile Report"](#)
- [Section 5.7, "Security Maintenance Inactive User Report"](#)
- [Section 5.8, "User Change Control Log Report"](#)
- [Section 5.9, "User Log Details Log Report"](#)
- [Section 5.10, "User Role Summary Report"](#)
- [Section 5.11, "User Status Log Report"](#)

### 5.1 Batch Performance Statistics Report

This section contains the following topics:

- [Section 5.1.1, "Generating Batch Performance Statistics Report"](#)
- [Section 5.1.2, "Contents of the Performance Statistics report"](#)

#### 5.1.1 Generating Batch Performance Statistics Report

This report provides the maximum, minimum and average performance record of each batch operation across all the branches in Oracle FLEXCUBE. It also has the option of generating report within a given date and time range. You can generate this report using the 'Batch Performance Statistics Report' screen. To invoke this screen, type 'SMRBASTA' in the field at top right corner of the Application tool bar and click the adjoining arrow button.

The screenshot shows a window titled "Batch Performance Statistics". It contains several input fields and buttons for generating a report. Under the "Report" section, there are text boxes for "Batch" and "Branch", each with a magnifying glass icon. Under the "Period" section, there are "Start Date" and "End Date" fields, both with a date picker icon. Below these, there are dropdown menus for "Report Format" (set to "PDF") and "Report Output" (set to "View"). On the right side, there are dropdowns for "Printer At" (set to "Client") and "Printer". At the bottom right, there are "Ok" and "Exit" buttons.

Specify the following details:

## **Report**

You can indicate the following details for report generation:

### **Batch**

Specify the batch for which the report has to be generated. The adjoining option list displays the list of all batches available in the system. You can select the appropriate one. However, you can leave this field blank if you have mentioned the branch. This will imply that the report needs to be generated for the given branch across all batches.

### **Branch**

Specify the branch for which the report has to be generated. The adjoining option list displays the list of all branches available in the system. You can select the appropriate one. However, you can also leave this field blank if you have mentioned the batch. This will imply that the report needs to be generated for the given batch across all branches.

### **Period**

Select the period within which the data for report generation should be fetched.

### **Start Date.**

Indicate the date from which records should be considered for report generation, using the adjoining calendar.

### **End Date**

Indicate the date until which records should be considered for report generation, using the adjoining calendar.

## **5.1.2 Contents of the Performance Statistics report**

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

### **Header**

The Header carries the title of the report, information on the branch code, the ID of the user who generated the report, the date and time at which it was generated, the branch date, the modules covered in the report.

### **Body of the report**

The following details are displayed in the report.

| <b>Term</b>  | <b>Description</b>                                                                               |
|--------------|--------------------------------------------------------------------------------------------------|
| EOC Stage    | This indicates the End of Cycle stage.                                                           |
| Branch Code  | This indicates the code of the branch.                                                           |
| Start Time   | This indicates the start time from which the records have been considered for report generation. |
| End Time     | This indicates the end time until which the records have been considered for report generation.  |
| Maximum Time | This indicates the maximum time taken for the batch operation.                                   |

|              |                                                             |
|--------------|-------------------------------------------------------------|
| Minimum Time | This indicates the minimum time taken for batch operation.  |
| Average Time | This indicatess the average time taken for batch operation. |

## 5.2 Change Control Log Report

This section contains the following topics:

- [Section 5.2.1, "Generating Change Control Log Report"](#)
- [Section 5.2.2, "Contents of the Report"](#)

### 5.2.1 Generating Change Control Log Report

The Change Control Log report provides change control log details. You can invoke the screen by typing the 'SMRCONTL' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.

You can specify the following parameters:

#### Branch Options

You can generate the report based on the following branch criteria. The following options are available for section:

- All
- Single

#### Branch Code

Specify a valid branch code for which you want to generate the report from the adjoining option list, if you have selected 'Single'.

#### User Options

You can generate the report based on the following User criteria. The following options are available for section:

- All

- Single

#### **User**

Specify a valid User ID for which you want to generate the report from the adjoining option list, if you have selected 'Single'.

#### **Module Options**

You can generate the report based on the following Module criteria. The following options are available for section:

- All
- Single

#### **Module Code**

Specify a valid module code for which you want to generate the report from the adjoining option list, if you have selected 'Single'.

#### **Main**

You can specify the following parameters:

#### **Date**

Specify a valid date for which you want to generate the report from the adjoining calendar.

### **5.2.2 Contents of the Report**

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

#### **Header**

The following details are displayed in the header section:

| Field Name  | Field Description                                         |
|-------------|-----------------------------------------------------------|
| Branch      | Indicates Branch Code and Branch Name                     |
| Branch Date | Indicates Current Date of the Branch                      |
| User ID     | Indicates User ID                                         |
| Date & Time | Indicates the Date and Time when the report was generated |
| Module      | Indicates module for which report is generated.           |

#### **Body of the Report**

The following details are displayed as body of the generated report:

| Field Name        | Field Description           |
|-------------------|-----------------------------|
| Branch            | Indicates Branch Code       |
| User ID           | Indicates User ID           |
| Module            | Indicates Module            |
| Function Modified | Indicates Function Modified |

|                       |                                     |
|-----------------------|-------------------------------------|
| Modification Number   | Indicates Modification Number       |
| Field Name            | Indicates Field Name                |
| Status                | Indicates Status                    |
| Old Value             | Indicates Amount                    |
| New Value             | Indicates Currency code             |
| Maker Date Checker ID | Indicates Maker Date and Checker ID |

## 5.3 **Disabled Users System Violation Log Report**

This section contains the following topics:

- [Section 5.3.1, "Generating Disabled Users System Violation Log Report"](#)
- [Section 5.3.2, "Contents of the Report"](#)

### 5.3.1 **Generating Disabled Users System Violation Log Report**

You can invoke the screen by typing the code 'SSRUSRDS' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.

You can specify the following parameters:

#### **User Options**

You can generate the report based on the following User criteria. The following options are available for section:

- All

- Single

#### **User**

Specify a valid User ID for which you want to generate the report from the adjoining option list, if you have selected 'Single'.

### **5.3.2 Contents of the Report**

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

#### **Header**

The following details are displayed in the header section:

| Field Name  | Field Description                                         |
|-------------|-----------------------------------------------------------|
| Branch      | Indicates Branch Code and Branch Name                     |
| Branch Date | Indicates Current Date of the Branch                      |
| User ID     | Indicates User ID                                         |
| Date & Time | Indicates the Date and Time when the report was generated |
| Page        | Indicates the number of pages                             |
| Module      | Indicates module for which report is generated.           |

#### **Body of the Report**

The following details are displayed as body of the generated report:

| Field Name      | Field Description             |
|-----------------|-------------------------------|
| User ID         | Indicates User ID             |
| Terminal ID     | Indicates Terminal ID         |
| Start Date Time | Indicates start date and time |
| Balloon Help    | Indicates balloon help        |
| Message         | Displays the message          |

## **5.4 Event Log Report**

This section contains the following topics:

- [Section 5.4.1, "Generating Event Log Report"](#)
- [Section 5.4.2, "Contents of the Report"](#)

### 5.4.1 Generating Event Log Report

The Event Log report provides event log details. You can invoke the screen by typing the code 'SMREVNLO' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.

Event Log

Input User

☒ All  
☐ Single

User

Start Date

Report Format

Report Output

Printer At

Printer

Ok Cancel

You can specify the following parameters:

#### Input User

You can generate the report based on the following User criteria. The following options are available for section:

- All
- Single

#### User

Specify a valid User ID for which you want to generate the report from the adjoining option list, if you have selected 'Single'.

#### Start Date

Specify start date of the event for which you want to generate the report from the adjoining calendar.

### 5.4.2 Contents of the Report

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

#### Header

The following details are displayed in the header section:

| Field Name  | Field Description                     |
|-------------|---------------------------------------|
| Branch      | Indicates Branch Code and Branch Name |
| Branch Date | Indicates Current Date of the Branch  |

|             |                                                           |
|-------------|-----------------------------------------------------------|
| User ID     | Indicates User ID                                         |
| Date & Time | Indicates the Date and Time when the report was generated |
| Module      | Indicates module for which report is generated.           |

### Body of the Report

The following details are displayed as body of the generated report:

| Field Name         | Field Description                     |
|--------------------|---------------------------------------|
| Start Date         | Indicates the start date of the event |
| End Date           | Indicates the end date of the event   |
| Application        | Indicates application details         |
| Current Branch     | Indicates current branch code         |
| Transaction Branch | Indicates transaction branch code     |
| User ID            | Indicates User ID                     |

## 5.5 New User Created Report

This section contains the following topics:

- [Section 5.5.1, "Generating New User Created Report"](#)
- [Section 5.5.2, "Contents of the Report"](#)

### 5.5.1 Generating New User Created Report

The New User Created report provides details of the new users created. You can invoke the screen by typing the code 'SMRWNWUSR' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.

You can specify the following parameters:

## **Branch Options**

You can generate the report based on the following branch criteria. The following options are available for section:

- All
- Single

### **Branch Code**

Specify a valid branch code for which you want to generate the report from the adjoining option list, if you have selected 'Single'.

## **User Creation**

You can specify the following parameter:

### **From Date**

Specify date from when you want to generate the report from the adjoining calendar.

### **To Date**

Specify date till when you want to generate the report from the adjoining calendar

## **5.5.2 Contents of the Report**

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

### **Header**

The following details are displayed in the header section:

| Field Name  | Field Description                                         |
|-------------|-----------------------------------------------------------|
| Branch      | Indicates Branch Code and Branch Name                     |
| Branch Date | Indicates Current Date of the Branch                      |
| User ID     | Indicates User ID                                         |
| Date & Time | Indicates the Date and Time when the report was generated |
| Module      | Indicates module for which report is generated.           |

### **Body of the Report**

The following details are displayed as body of the generated report:

| Field Name  | Field Description                                |
|-------------|--------------------------------------------------|
| Start Date  | Indicates the start date of the event            |
| User ID     | Indicates user ID                                |
| Creator     | Indicates creator's ID                           |
| Authorizer  | Indicates authorizer's ID code                   |
| Home Branch | Indicates home branch code                       |
| Role ID     | Indicates role ID to which the user ID is mapped |

## 5.6 Role Profile Report

This section contains the following topics:

- [Section 5.6.1, "Generating Role Profile Report"](#)
- [Section 5.6.2, "Contents of the Report"](#)

### 5.6.1 Generating Role Profile Report

The Role Profile report provides details of the role profiles. You can invoke the screen by typing the code 'SMRROLPR' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.

Role Profile

Role Profile

☐ All  
☒ Single

Role

From Date:

To Date:

Report Format:

Report Output:

Printer At:

Printer:

Ok Cancel

You can specify the following parameters:

#### Role Profile

You can generate the report based on the following role criteria. The following options are available for section:

- All
- Single

#### **Role**

Specify a valid Role ID for which you want to generate the report from the adjoining option list, if you have selected 'Single'.

### 5.6.2 Contents of the Report

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

#### **Header**

The following details are displayed in the header section:

| Field Name | Field Description                     |
|------------|---------------------------------------|
| Branch     | Indicates Branch Code and Branch Name |

|             |                                                           |
|-------------|-----------------------------------------------------------|
| Branch Date | Indicates Current Date of the Branch                      |
| User ID     | Indicates User ID                                         |
| Date & Time | Indicates the Date and Time when the report was generated |
| Module      | Indicates module for which report is generated.           |

### **Body of the Report**

The following details are displayed as body of the generated report:

| <b>Field Name</b>    | <b>Field Description</b>                       |
|----------------------|------------------------------------------------|
| Role                 | Indicates Role ID                              |
| Function             | Indicates Function name                        |
| Function Description | Indicates Function description                 |
| Branch Allowed       | Indicates branches allowed for the role        |
| Acc Class Allowed    | Indicates account classes allowed for the role |
| Limit Currency       | Indicates limit currency for the role          |
| Input Limit          | Indicates input limit for the role             |
| Authorizer Limit     | Indicates authorization limit for the role     |

## **5.7 Security Maintenance Inactive User Report**

This section contains the following topics:

- [Section 5.7.1, "Generating Security Maintenance Inactive User Report"](#)
- [Section 5.7.2, "Contents of the Report"](#)

### **5.7.1 Generating Security Maintenance Inactive User Report**

You can invoke the screen by typing the code 'SSRPINST' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.

You can specify the following parameters:

### **User Options**

You can generate the report based on the following User criteria. The following options are available for section:

- All
- Single

### **User**

Specify a valid User ID for which you want to generate the report from the adjoining option list, if you have selected 'Single'.

## **5.7.2 Contents of the Report**

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

### **Header**

The following details are displayed in the header section:

| Field Name  | Field Description                     |
|-------------|---------------------------------------|
| Branch      | Indicates Branch Code and Branch Name |
| Branch Date | Indicates Current Date of the Branch  |
| User ID     | Indicates User ID                     |

|             |                                                           |
|-------------|-----------------------------------------------------------|
| Date & Time | Indicates the Date and Time when the report was generated |
| Page        | Indicates number of pages                                 |
| Module      | Indicates module for which report is generated.           |

### **Body of the Report**

The following details are displayed as body of the generated report:

| Field Name     | Field Description        |
|----------------|--------------------------|
| User ID        | Indicates User ID        |
| Last Signed on | Indicates Last Signed on |
| Inactivity     | Indicates inactivity     |
| User Status    | Indicates user status    |

## **5.8 User Change Control Log Report**

This section contains the following topics:

- [Section 5.8.1, "Generating User Change Control Log Report"](#)
- [Section 5.8.2, "Contents of the Report"](#)

### **5.8.1 Generating User Change Control Log Report**

You can invoke the screen by typing the code 'SSRCONTL' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.

### User Options

You can generate the report based on the following User criteria. The following options are available for section:

- All
- Single

### User

Specify a valid User ID for which you want to generate the report from the adjoining option list, if you have selected 'Single'.

### Main

You can specify the following parameters:

#### Date

Specify a valid date for which you want to generate the report from the adjoining calendar.

## 5.8.2 Contents of the Report

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

### Header

The following details are displayed in the header section:

| Field Name  | Field Description                     |
|-------------|---------------------------------------|
| Branch      | Indicates Branch Code and Branch Name |
| Branch Date | Indicates Current Date of the Branch  |

|             |                                                           |
|-------------|-----------------------------------------------------------|
| User ID     | Indicates User ID                                         |
| Date & Time | Indicates the Date and Time when the report was generated |
| Module      | Indicates module for which report is generated.           |

### **Body of the Report**

The following details are displayed as body of the generated report:

| Field Name            | Field Description                   |
|-----------------------|-------------------------------------|
| Branch                | Indicates Branch Code               |
| User ID               | Indicates User ID                   |
| Module                | Indicates Module                    |
| Function Modified     | Indicates Function Modified         |
| Modification Number   | Indicates Modification Number       |
| Field Name            | Indicates Field Name                |
| Status                | Indicates Status                    |
| Old Value             | Indicates Amount                    |
| New Value             | Indicates Currency code             |
| Maker Date Checker ID | Indicates Maker Date and Checker ID |

## **5.9 User Log Details Log Report**

You can specify the following parameters

- [Section 5.9.1, "Generating User Log Details Log Report"](#)
- [Section 5.9.2, "Contents of the Report"](#)

### **5.9.1 Generating User Log Details Log Report**

You can invoke the screen by typing the code 'SSRUSLOG' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.

### User Options

You can generate the report based on the following User criteria. The following options are available for section:

- All
- Single

### User

Specify a valid User ID for which you want to generate the report from the adjoining option list, if you have selected 'Single'.

## 5.9.2 Contents of the Report

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

### Header

The following details are displayed in the header section:

| Field Name  | Field Description                                         |
|-------------|-----------------------------------------------------------|
| Branch      | Indicates Branch Code and Branch Name                     |
| Branch Date | Indicates Current Date of the Branch                      |
| User ID     | Indicates User ID                                         |
| Date & Time | Indicates the Date and Time when the report was generated |
| Page        | Indicates the page number                                 |
| Module      | Indicates module for which report is generated.           |

## Body of the Report

The following details are displayed as body of the generated report:

| Field Name                  | Field Description                         |
|-----------------------------|-------------------------------------------|
| User ID                     | Indicates the User ID                     |
| User Name                   | Indicates the User Name                   |
| Status                      | Indicates the status enabled or disabled  |
| Number of Cumulative Logins | Indicates the number of cumulative logins |
| Number of Successive Logins | Indicates the number of successive logins |
| Last Signed On              | Indicates last signed on                  |
| Inactive                    | Indicates inactive in days                |

## 5.10 User Role Summary Report

This section contains the following topics:

- [Section 5.10.1, "Generating Role Summary Report"](#)
- [Section 5.10.2, "Contents of the Report"](#)

### 5.10.1 Generating Role Summary Report

The User Role Summary report provides user role summary details. You can invoke the screen by typing the code 'SMRSUMRY' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.

User Role Summary

Role Option

Branch Option

Role Level

Branch Code

Report Format

Report Output

Printer At

Printer

Ok Exit

You can specify the following parameters:

## **Status Report**

You can specify the following parameters

### **User Status**

You can generate the report based on the following user status criteria. The following options are available for section:

- Enabled
- Disabled

### **Role Options**

You can generate the report based on the following role criteria. The following options are available for section:

- All
- Single

### **Role Level**

Specify a valid role level for which you want to generate the report from the adjoining option list, if you have selected 'Single'.

### **Branch Options**

You can generate the report based on the following branch criteria. The following options are available for section:

- All
- Single

### **Branch Code**

Specify a valid branch code for which you want to generate the report from the adjoining option list, if you have selected 'Single'.

## **5.10.2 Contents of the Report**

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

### **Header**

The following details are displayed in the header section:

| Field Name  | Field Description                                         |
|-------------|-----------------------------------------------------------|
| Branch      | Indicates Branch Code and Branch Name                     |
| Branch Date | Indicates Current Date of the Branch                      |
| User ID     | Indicates User ID                                         |
| Date & Time | Indicates the Date and Time when the report was generated |
| Module      | Indicates module for which report is generated.           |

## Body of the Report

The following details are displayed as body of the generated report:

| Field Name  | Field Description                        |
|-------------|------------------------------------------|
| Branch      | Indicates Branch Code                    |
| Branch Name | Indicates Branch name                    |
| Role ID     | Indicates Role ID                        |
| User ID     | Indicates User ID                        |
| Status      | Indicates Status                         |
| No of Users | This indicates the total number of users |

## 5.11 User Status Log Report

This section contains the following topics:

- [Section 5.11.1, "Generating User Status Log Report"](#)
- [Section 5.11.2, "Contents of the Report"](#)

### 5.11.1 Generating User Status Log Report

. You can invoke the screen by typing the code 'SSRUSSTS' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.

User Status Log

User Options

All (selected) Single

User Id 412701A01

Main

Report Format PDF

Report Output View

Printer At Client

Printer

Ok Exit

### User Options

You can generate the report based on the following User criteria. The following options are available for section:

- All
- Single

**User**

Specify a valid User ID for which you want to generate the report from the adjoining option list, if you have selected 'Single'.

**5.11.2 Contents of the Report**

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

**Header**

The following details are displayed in the header section:

| Field Name  | Field Description                                         |
|-------------|-----------------------------------------------------------|
| Branch      | Indicates Branch Code and Branch Name                     |
| Branch Date | Indicates Current Date of the Branch                      |
| User ID     | Indicates User ID                                         |
| Date & Time | Indicates the Date and Time when the report was generated |
| Module      | Indicates module for which report is generated.           |

**Body of the Report**

The following details are displayed as body of the generated report:

| Field Name | Field Description   |
|------------|---------------------|
| User ID    | Indicates User ID   |
| User Name  | Indicates User Name |
| Status     | Indicates Status    |

---

## 6. Function ID Glossary

### C

CLRU .....3-1

### S

SMDBANKP .....2-2

SMDBNKRT .....2-8

SMDBRRES .....2-11

SMDCHNTL .....3-2

SMDCHPWD .....2-10

SMDDPTMT .....2-48

SMDENTDT .....2-50

SMDFNDS .....2-13

SMDHOTKY .....3-8

SMDLNGCE .....3-3

SMDPRCDE .....2-49

SMDROLD .....2-16, 2-17

SMDSOPRM .....3-5

SMDUSHOL .....2-24

SMDUSRDF .....2-26, 2-31

SMRBASTA .....5-1

SMRCONTL .....5-3

SMREVNLO .....5-7

SMRWNUSR .....5-8

SMRROLPR .....5-10, 5-11

SMRSUMRY .....5-17

SMSMFALM .....2-50

SMSTXNST .....3-6

SMSUSHOL .....2-25

SMSUSRAC .....3-8

SSDROLD .....2-16

SSDUSRDF .....2-26

SSRCONTL .....5-13, 5-15

SSRPINST .....5-11

SSRUSLOG .....5-15

SSRUSRDS .....5-5

STDCUBAL .....2-37

SVDIMGVW .....2-37