

Oracle® Communications
Diameter Signaling Router
DSR Cloud Installation Guide
Release 8.3
E93227-01

September 2018

ORACLE®

Oracle Communications Diameter Signaling Router Cloud Installation Guide, Release 8.3

Copyright © 2018 Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.



CAUTION: MOS (<https://support.oracle.com>) is your initial point of contact for all product support and training needs. A representative at Customer Access Support (CAS) can assist you with MOS registration.

Call the CAS main number at 1-800-223-1711 (toll-free in the US), or call the Oracle Support hotline for your local country from the list at <http://www.oracle.com/us/support/contact/index.html>.

See more information on My Oracle Support (MOS) in Appendix K.

Table of Contents

1. Introduction	7
1.1 References	7
1.2 Acronyms.....	8
1.3 Terminology.....	9
1.4 How to Use This Document.....	10
2. Installation Overview	11
2.1 Required Materials	11
2.2 Installation Overview	11
2.2.1 Installation Strategy	11
2.2.2 SNMP Configuration.....	13
2.2.3 Installation Procedures.....	14
2.3 Optional Features	17
3. Software Installation Procedure.....	17
3.1 Create DSR Guests (VMware)	18
3.2 Create DSR Guests (KVM/OpenStack).....	20
3.3 Create DSR Guests (OVM-S/OVM-M)	28
3.4 Configure Virtual Machines	32
4. Software Installation Using HEAT Templates (OpenStack).....	40
4.1 Prepare OpenStack Template and Environment files	40
4.2 Create OpenStack Parameters files.....	41
4.3 Deploy HEAT Templates	49
5. Application Configuration	52
5.1 Configure Signaling Devices (Optional)	112
5.2 Configure Signaling Network Routes	114
5.3 Configure DSCP (Optional)	117
5.4 Configure IP Front End (Optional).....	121
5.5 Configure the Desired MTU value	126
5.6 SNMP Configuration (Optional).....	127
5.7 Create iDIH Virtual Machines - VMware (Optional).....	129
5.8 Create iDIH Virtual Machines - KVM/OpenStack (Optional).....	131
5.9 Create iDIH Virtual Machines - OVM-S/OVM-M (Optional).....	135
5.10 Configure iDIH Virtual Machines (Optional)	144
5.11 Post iDIH Installation Configuration (Optional).....	148
6. Post-Install Activities	165
Appendix A. Sample Network Element and Hardware Profiles.....	177
Appendix B. List of Frequently Used Time Zones	178

Appendix C. Common KVM/OpenStack Tasks	180
Appendix C.1 Create a Network Port	180
Appendix C.2 Create and Boot OpenStack Instance	181
Appendix C.3 Configure Networking for OpenStack Instance	182
Appendix D. Common OVM Manager Tasks (CLI)	182
Appendix D.1 Set Up the Server	182
Appendix D.2 Server Pool	189
Appendix E. Scale a Signaling Node	189
Appendix F. Firewall Ports.....	190
Appendix G. Application VIP Failover Options (OpenStack)	190
Appendix G.1 Application VIP Failover Options	190
Appendix G.2 Allowed Address Pairs.....	192
Appendix G.3 OpenStack Configuration Requirements	192
Appendix G.4 After a VM Instance has been Booted: Allowed Address Pairs	193
Appendix G.5 Before a VM Instance has been Booted: Allowed Address Pairs	193
Appendix G.6 Disable Port Security	194
Appendix G.7 After a VM Instance has been Booted: Port Security	195
Appendix G.8 Before a VM Instance has been Booted: Port Security	195
Appendix G.9 Managing Application Virtual IP Addresses within VM Instances	196
Appendix H. Sample Net Rules File	197
Appendix I. Performance Tuning Recommended	197
Appendix I.1 KVM/OpenStack	197
Appendix I.2 VMware	198
Appendix J. Example Files	199
Appendix J.1 Example Template File	199
Appendix J.2 Example Parameter File	200
Appendix K. My Oracle Support (MOS)	203

List of Tables

Table 1. Acronyms	8
Table 2. Terminology	9
Table 3. Installation Overview Without Using HEAT Templates.....	14
Table 4. Installation Procedures Using HEAT Templates.....	16
Table 5. Post-DSR Installation Configuration Step	17
Table 6. List of Selected Time Zone Values	178

List of Figures

Figure 1. Example of a Procedure Steps Used in This Document	11
Figure 2. DSR Single Site Installation Procedure Map Without Using HEAT Templates	12
Figure 3. DSR Installation Procedure Map Using HEAT Templates	13
Figure 4. Example Network Element XML File	178
Figure 5. Neutron High-Level Data Model	191

List of Procedures

Procedure 1. (VMware) Import DSR OVA	18
Procedure 2. (VMware only) Configure NOAM Guests Role Based On Resource Profile and Configure Network	18
Procedure 3. (VMware only) Configure Remaining DSR Guests Based on Resource Profile and Configure Network	19
Procedure 4. Import DSR OVA (KVM/OpenStack Only)	20
Procedure 5. (KVM/OpenStack Only) Configure NOAM Guests Role Based on Resource Profile	22
Procedure 6. (KVM/OpenStack Only) Configure Remaining DSR Guests Based on Resource Profile and Configure Network	25
Procedure 7. (OVM-S/OVM-M). Import DSR OVA and prepare for VM creation	28
Procedure 8. (OVM-S/OVM-M). Configure each DSR VM	32
Procedure 9. Prepare OpenStack Templates and Environment Files for NOAM/Signaling Stacks	40
Procedure 10. Create OpenStack Parameter File for NOAM	41
Procedure 11. Create OpenStack Parameter File for Signaling	43
Procedure 12. Deploy HEAT Templates	49
Procedure 13. Configure the First NOAM NE and Server	52
Procedure 14. Configure the NOAM Server Group	58
Procedure 15. Configure the Second NOAM Server	61
Procedure 16. Complete Configuring the NOAM Server Group	64
Procedure 17. Configure the DR NOAM NE and Server (Optional)	67
Procedure 18. Configure the DR NOAM Server Group (Optional)	72
Procedure 19. Configure the Second DR NOAM Server (Optional)	74
Procedure 20. Complete Configuring the DR NOAM Server Group (Optional)	77
Procedure 21. Configure the SOAM NE	80
Procedure 22. Configure the SOAM Servers	82
Procedure 23. Configure the SOAM Server Group	86
Procedure 24. Activate PCA/DCA (PCA/DCA Only)	90
Procedure 25. Configure the MP Virtual Machines	91
Procedure 26. Configure the MP Virtual Machines (Optional)	100
Procedure 27. Configure Places and Assign MP Servers to Places (PCA and DCA Only)	105
Procedure 28. Configure the MP Server Group(s) and Profiles	107
Procedure 29. Configure the Signaling Devices (Optional)	112
Procedure 30. Configure the Signaling Network Routes	114
Procedure 31. Configure DSCP Values for Outgoing Traffic (Optional)	117
Procedure 32. IP Front End (IPFE) Configuration	121
Procedure 33. Configure SNMP Trap Receiver(s) (Optional)	127

Procedure 34. (VMware only) Create iDIH Oracle, Mediation, and Application VMs (Optional)	129
Procedure 35. (KVM/OpenStack Only) Create iDIH Oracle, Mediation, and Application VMs (Optional)	131
Procedure 36. (OVM-S/OVM-M). Import Three IDIH OVAs and Create and Configure a VM for Each...	135
Procedure 37. Configure iDIH VM Networks (Optional)	144
Procedure 38. Run Post Installation Scripts on iDIH VMs (Optional)	148
Procedure 39. Configure DSR Reference Data Synchronization for iDIH (Optional)	150
Procedure 40. iDIH Configuration: Configuring the SSO Domain (Optional)	153
Procedure 41. Integrate iDIH into DSR (Optional)	160
Procedure 42. iDIH Configuration: Configure the Mail Server (Optional)	161
Procedure 43. iDIH Configuration: Configure SNMP Management Server (Optional)	163
Procedure 44. iDIH Configuration: Change Network Interface (Optional)	164
Procedure 45. Configure ComAgent Connections.....	165
Procedure 46. Complete PCA Configuration (Optional)	171
Procedure 47. Backups and Disaster Prevention	171
Procedure 48. (KVM/OpenStack Only) Configure Port Security.....	175
Procedure 49. Enable/Disable DTLS (SCTP Diameter Connections Only).....	176
Procedure 50. Shared Secret Encryption Key Revocation (RADIUS Only)	177
Procedure 51. DSR Performance Tuning	177
Procedure 52. Create a Network Port.....	180
Procedure 53. Create and Boot OpenStack Instance.....	181
Procedure 54. Configure Networking for OpenStack Instance	182
Procedure 55. Set Up the Server	182
Procedure 56. Scale a Signaling Node	189

1. Introduction

This document installs the Diameter Signaling Router (DSR) 8.3 and compatible IDIH applications on a supported Cloud platform

This document assumes platform-related configuration has already been done.

The audience for this document includes Oracle customers as well as these groups: Software System, Product Verification, Documentation, and Customer Service including Software Operations and First Office Application.

1.1 References

- [1] Communication Agent Configuration Guide
- [2] DSR PCA Activation Guide
- [3] DSR Meta Administration Feature Activation Procedure
- [4] DSR Full Address Based Resolution (FABR) Feature Activation Procedure
- [5] DSR Range Based Address Resolution (RBAR) Feature Activation
- [6] SDS SW Installation and Configuration Guide
- [7] Operations, Administration, and Maintenance (OAM) User's Guide
- [8] Communication Agent User's Guide
- [9] Diameter User's Guide
- [10] Mediation User's Guide
- [11] Range Based Address Resolution (RBAR) User's Guide
- [12] Full Address Based Resolution (FABR) User's Guide
- [13] IP Front End (IPFE) User's Guide
- [14] DSR Alarms and KPIs Reference
- [15] Measurements Reference
- [16] Diameter Common User's Guide
- [17] DSR Security Guide
- [18] DSR IPv6 Migration Guide
- [19] DSR DTLS Feature Activation Procedure
- [20] DSR RADIUS Shared Secret Encryption Key Revocation MOP MO008572
- [21] DCA Framework and Application Activation and Deactivation Guide
- [22] Oracle VM Concepts Guide, Release 3.4
- [23] Networking v2.0 API documentation
- [24] DSR Cloud Benchmarking Guide

1.2 Acronyms

An alphabetized list of acronyms used in the document.

Table 1. Acronyms

Acronym	Definition
CD	Compact Disk
DA-MP	Diameter Agent Message Processor
DSCP	Differentiated Services Code Point
DSR	Diameter Signaling Router
ESXi	Elastic Sky X Integrated
FABR	Full Address Based Resolution
iDIH	Integrated Diameter Intelligence Hub
IPFE	IP Front End
KVM	Kernel-based Virtual Machine
MP	Message Processor
NAPD	Network Architecture Planning Diagram
NE	Network Element
NOAM	Network Operation Administration and Maintenance
OS	Operating System (for example, TPD)
OVA	Open Virtualization Archive
OVM-M	Oracle VM Manager
OVM-S	Oracle VM Server
PDRA	Policy Diameter Routing Agent
PCA	Policy and Charging Application
RBAR	Range Based Address Resolution
SAN	Storage Area Network
SFTP	Secure File Transfer Protocol
SNMP	Simple Network Management Protocol
SOAM	Software Operation Administration and Maintenance
SSO	Single Sign On
TPD	Tekelec Platform Distribution
TSA	Target Set Address
VIP	Virtual IP
VM	Virtual Machine
vSTP	Virtual Signaling Transfer Point

1.3 Terminology

Multiple server types may be involved with the procedures in this manual. Therefore, most steps in the written procedures begin with the name or type of server to which the step applies.

Table 2. Terminology

Term	Definition
Site	<p>Applicable for various applications, a site is type of place. A place is configured object that allows servers to be associated with a physical location.</p> <p>A site place allows servers to be associated with a physical site. For example, sites may be configured for Atlanta, Charlotte, and Chicago. Every server is associated with exactly one site when the server is configured.</p> <p>For the Policy and Charging DRA application, when configuring a site, only put DA-MPs and SBR MP servers in the site. Do not add NOAM, SOAM, or IPFE MPs to a site.</p>
Place Association	<p>Applicable for various applications, a Place Association is a configured object that allows places to be grouped together. A place can be a member of more than one place association.</p> <p>The Policy and Charging DRA application defines two place association types: policy binding region and Policy and Charging mated sites.</p>
Policy and Charging SBR Server Group Redundancy	<p>The Policy and Charging application uses SBR server groups to store the application data. The SBR server groups support both two and three site redundancy. The server group function name is Policy and Charging SBR.</p>
Server Group Primary Site	<p>A server group primary site is a term used to represent the principle location within a SOAM or SBR server group. SOAM and SBR server groups are intended to span several sites (places). For the Policy and Charging DRA application, these sites (places) are all configured within a single Policy and Charging Mated Sites place association.</p> <p>For the Diameter custom application, these sites (places) are configured in Applications Region place association.</p> <p>The primary site may be in a different site (place) for each configured SOAM or SBR server group.</p> <p>A primary site is described as the location in which the active and standby servers reside; however, there cannot be any preferred spare servers within this location. All SOAM and SBR server groups have a primary site.</p>
Server Group Secondary Site	<p>A server group secondary site is a term used to represent location in addition to the Primary Site within a SOAM or SBR Server Group. SOAM and SBR server groups are intended to span several sites (places). For the Policy and Charging DRA application, these sites (places) are all configured within a single Policy and Charging Mated Sites place association.</p> <p>For the Diameter custom application, these sites (places) are configured in Applications Region place association.</p> <p>The secondary site may be in a different sites (places) for each configured SOAM or SBR server group.</p> <p>A secondary site is described as the location in which only preferred spare servers reside. The active and standby servers cannot reside within this location. If two site redundancy is wanted, a secondary site is required for all SOAM and SBR server groups.</p>

Term	Definition
Session Binding Repository Server Group Redundancy	The DCA application may use SBR server groups to store application session data. The SBR server groups support both two and three site redundancy. The server group function name is Session and Binding Repository .
Two Site Redundancy	<p>Two site redundancy is a data durability configuration in which Policy and Charging data is unaffected by the loss of one site in a Policy and Charging Mated Sites Place Association containing two sites.</p> <p>Two site redundancy is a feature provided by server group configuration. This feature provides geographic redundancy. Some server groups can be configured with servers located in two geographically separate sites (locations). This feature ensures there is always a functioning active server in a server group even if all the servers in a single site fail.</p>

1.4 How to Use This Document


Although this document is primarily to be used as an initial installation guide, its secondary purpose is as a reference for disaster recovery procedures. When executing this document for either purpose, there are a few points to help ensure you understand this document's intent. These points are:

1. Before beginning a procedure, completely read the instructional text (it will appear immediately after the Section heading for each procedure) and all associated procedural **WARNINGS** or **NOTES**.
2. Before execution of a **STEP** within a procedure, completely read the left and right columns including any **STEP** specific **WARNINGS** or **NOTES**.

If a procedural **STEP** fails to execute successfully, STOP and contact Oracle's Customer Service for assistance before attempting to continue. See Appendix K for information on contacting Oracle Customer Support.

Figure 1 shows an example of a procedural step used in this document.

- Any sub-steps within a step are referred to as step X.Y. The example in Figure 1 shows steps 1 through 3, and step 3.1.
- GUI menu items, action links, and buttons to be clicked on are in bold Arial font.
- GUI fields and values to take note of during a step are in bold Arial font.
- Where it is necessary to explicitly identify the server on which a particular step is to be taken, the server name is given in the title box for the step (for example, "ServerX" in step 2 Figure 1).



Title	Directive/Result Step	Description
<input type="checkbox"/> 1. Change directory	Change to the backout directory. <div style="border: 1px solid #ccc; padding: 5px; display: inline-block;"> <code>\$ cd /var/TKLC/backout</code> </div>	The Title column describes the operations to perform during that step. Each command the user enters, and any response output, is formatted in 10-point Courier font.

2.	ServerX: Connect to the console of the server	Establish a connection to the server using cu on the terminal server/console. <code>\$ cu -l /dev/ttyS7</code>
3.	Verify Network Element data	View the Network Elements configuration data; verify the data; save and print report. 3. Select Configuration > Network Elements to view Network Elements Configuration screen.

Figure 1. Example of a Procedure Steps Used in This Document

2. Installation Overview

This section provides a brief overview of the recommended methods for installing the source release software that is installed and running on a Cloud to the target release software.

2.1 Required Materials

1. One target release DSR OVA Media
2. Three (3) iDIH OVA (Optional iDIH)
 - a. iDIH Application OVA
 - b. iDIH Oracle OVA
 - c. iDIH Mediation OVA

2.2 Installation Overview

This section describes the overall strategy to employ for a single or multi-site DSR and iDIH installation. It also lists the procedures required for installation with estimated times. Section 2.2.1 discusses the overall installation strategy and includes an installation flowchart to determine exactly which procedures should be run for an installation. Section 2.2.3 lists the steps required to install a DSR system. The later sections expand on the information from the matrix and provide a general timeline for the installation. Additionally, basic firewall port information is included in Appendix F Firewall Ports. It should also be noted that some procedures are cloud platform dependent and not all procedures are performed on all cloud platforms.

2.2.1 Installation Strategy

A successful installation of DSR requires careful planning and assessment of all configuration materials and installation variables.

1. An overall installation requirement is decided upon. The following data are collected:
 - The total number of sites
 - The number of virtual machines at each site and their role(s)
 - What time zone should be used across the entire collection of DSR sites?
 - Will SNMP traps be viewed at the NOAM or will an external NMS be used? (Or both?)
2. A site survey (NAPD) is conducted with the customer to determine exact networking and site details.

Note: XMI and IMI addresses are difficult to change once configured. It is **very important these addresses are well planned and not expected to change after a site is installed.**

DSR currently supports the following installation strategies:

- DSR installation without using HEAT templates

[Figure 2] illustrates the overall process that each DSR installation involves. In summary, this involves creation of guests and configures each guest role based on Resource Profile and Configure Network.

- DSR installation using HEAT templates (OpenStack only)

[Figure 3] illustrates the overall process that each DSR installation involves using the Heat Templates. In summary, this involves creation of parameter files, environment files, template files, DSR Topology Configuration xml and deploys DSR using open stack CLI commands.




Figure 2. DSR Single Site Installation Procedure Map Without Using HEAT Templates




Figure 3. DSR Installation Procedure Map Using HEAT Templates

2.2.2 SNMP Configuration

The network-wide plan for SNMP configuration should be decided upon before DSR installation proceeds. This section provides some recommendations for these decisions.

SNMP traps can originate from DSR Application Servers (NOAM, SOAM, MPs of all types) in a DSR installation.

DSR application servers can be configured to:

1. Send all their SNMP traps to the NOAM by merging from their local SOAM. All traps terminate at the NOAM and are viewable from the NOAM GUI (entire network) and the SOAM GUI (site specific). Traps are displayed on the GUI both as alarms and logged in trap history. **This is the default configuration option and no changes are required for this to take effect.**
2. Send all their SNMP traps to an external Network Management Station (NMS). The traps are seen at the SOAM and/or NOAM as alarms **AND** they are viewable at the configured NMS(s) as traps.

Application server SNMP configuration is done from the NOAM GUI near the end of DSR installation. See the procedure list for details.

2.2.3 Installation Procedures

The following table illustrates the progression of the installation process by procedure with estimated times. The estimated times and the phases that must be completed may vary due to differences in typing ability and system configuration. The phases outlined are to be executed in the order they are listed.

- If installation strategy is **Install DSR without using HEAT templates**, then follow Table 3.
- If installation strategy is **Install DSR using HEAT templates**, then follow Table 4.

Table 3. Installation Overview Without Using HEAT Templates

Procedure	Phase	Elapsed Time (Minutes)	
		This Step	Cum.
Procedure 1 or Procedure 2 or Procedure 7	Import DSR OVA	5	5
Procedure 2 or Procedure 5	Configure DSR NOAM Guest Role Based on Resource Profile	10	15
Procedure 3 or Procedure 6	Configure DSR Remaining Guests Role Based on Resource Profile	40	55
Procedure 13	Configure the First NOAM NE and Server	25	80
Procedure 14	Configure the NOAM Server Group	15	95
Procedure 15	Configure the Second NOAM Server	15	110
Procedure 16	Complete Configuring the NOAM Server Group	10	120
Procedure 17	Configure the DR NOAM NE and Server (Optional)	25	145
Procedure 18	Configure the DR NOAM Server Group (Optional)	15	160
Procedure 19	Configure the Second DR NOAM Server (Optional)	15	175
Procedure 20	Complete Configuring the DR NOAM Server Group (Optional)	10	185
Procedure 21	Configure the SOAM NE	15	200
Procedure 22	Configure the SOAM Servers	10	210
Procedure 23	Configure the SOAM Server Group	10	220
Procedure 24	Activate PCA/DCA (PCA/DCA Only)	10	230
Procedure 25	Configure the MP Virtual Machines	5	235
Procedure 26	Configure the MP Virtual Machines (Optional)	10	245
Procedure 27	Configure Places and Assign MP Servers to Places (PCA and DCA Only)	10	255
Procedure 28	Configure the MP Server Group(s) and Profiles	5	260
Procedure 29	Configure the Signaling Devices (Optional)	10	270
Procedure 30	Configure the Signaling Network Routes	20	290
Procedure 31	Configure DSCP Values for Outgoing Traffic (Optional)	5	295
Procedure 32	IP Front End (IPFE) Configuration	45	340

Procedure	Phase	Elapsed Time (Minutes)	
		This Step	Cum.
Procedure 33	Configure SNMP Trap Receiver(s) (Optional)	15	355
Procedure 34	(VMware only) Create iDIH Oracle, Mediation, and Application VMs (Optional)	10	365
Procedure 35	(KVM/OpenStack Only) Create iDIH Oracle, Mediation, and Application VMs (Optional)	10	375
Procedure 36	(OVM-S/OVM-M). Import Three IDIH OVAs and Create and Configure a VM for Each	10	385
Procedure 37	Configure iDIH VM Networks (Optional)	10	395
Procedure 38	Run Post Installation Scripts on iDIH VMs (Optional)	25	420
Procedure 39	Configure DSR Reference Data Synchronization for iDIH (Optional)	30	450
Procedure 40	iDIH Configuration: Configuring the SSO Domain (Optional)	10	460
Procedure 41	Integrate iDIH into DSR (Optional)	10	470
Procedure 42	iDIH Configuration: Configure the Mail Server (Optional)	10	480
Procedure 43	iDIH Configuration: Configure SNMP Management Server (Optional)	20	500
Procedure 44	iDIH Configuration: Change Network Interface (Optional)	30	530
Procedure 45	Configure ComAgent Connections	15	545
Procedure 46	Complete PCA Configuration (Optional)	5	550
Procedure 47	Backups and Disaster Prevention	15	565
Procedure 48	(KVM/OpenStack Only) Configure Port Security	10	575
Procedure 49	Enable/Disable DTLS (SCTP Diameter Connections Only)	10	585
Procedure 50	Shared Secret Encryption Key Revocation (RADIUS Only)	10	595
Procedure 51	DSR Performance Tuning	10	600

Note: Refer section 3 Software Installation Procedure for detailed procedures.

Table 4. Installation Procedures Using HEAT Templates

Procedure	Phase	Elapsed Time (Minutes)	
		This Step	Cum.
Procedure 4	Import DSR OVA	5	5
Procedure 10	Create OpenStack Parameter File for NOAM	10	15
Procedure 11	Create OpenStack Parameter File for Signaling	15	30
Procedure 12	Deploy HEAT Templates	15	45
Procedure 13	Configure the First NOAM NE and Server	10	55
Procedure 14	Configure the NOAM Server Group	25	80
Procedure 15	Configure the Second NOAM Server	15	95
Procedure 16	Complete Configuring the NOAM Server Group	15	110
Procedure 21	Configure the SOAM NE	10	120
Procedure 22	Configure the SOAM Servers	15	135
Procedure 23	Configure the SOAM Server Group	10	145
Procedure 24	Activate PCA/DCA (PCA/DCA Only)	10	155
Procedure 25	Configure the MP Virtual Machines	5	160
Procedure 27	Configure Places and Assign MP Servers to Places (PCA and DCA Only)	10	170
Procedure 28	Configure the MP Server Group(s) and Profiles	5	175
Procedure 29	Configure the Signaling Devices (Optional)	10	185
Procedure 30	Configure the Signaling Network Routes	20	205
Procedure 31	Configure DSCP Values for Outgoing Traffic (Optional)	5	210
Procedure 32	IP Front End (IPFE) Configuration	15	225
Procedure 33	Configure SNMP Trap Receiver(s) (Optional)	15	240
Procedure 45	Configure ComAgent Connections	20	260
Procedure 47	Backups and Disaster Prevention	15	275
Procedure 48	(KVM/OpenStack Only) Configure Port Security	30	305
Procedure 49	Enable/Disable DTLS (SCTP Diameter Connections Only)	15	320
Procedure 50	Shared Secret Encryption Key Revocation (RADIUS Only)	10	330
Procedure 51	DSR Performance Tuning	10	340

Note: Refer section 4 Software Installation Using HEAT Templates (OpenStack) for detailed procedures.

2.3 Optional Features

When DSR installation is complete, further configuration and/or installation steps are needed for optional features that may be present in this deployment. Please refer to Table 5 for the post-DSR installation configuration documentation needed for their components.

Table 5. Post-DSR Installation Configuration Step

Feature	Document
Diameter Mediation	DSR Meta Administration Feature Activation Procedure
Full Address Based Resolution (FABR)	DSR FABR Feature Activation Procedure
Range Based Address Resolution (RBAR)	DSR RBAR Feature Activation Procedure
SCEF Feature Activation	DSR SCEF Feature Activation Guide
Policy and Charging Application (PCA)	PCA Activation Procedure
Host Intrusion Detection System (HIDS)	DSR Security Guide, Section 3.2
Diameter Custom Applications (DCA)	DCA Framework and Application Activation and Deactivation Procedures

3. Software Installation Procedure

As mentioned earlier, the host configuration and virtual networks should be done before executing the procedures in this document. It is assumed that at this point the user has access to:

- Consoles of all guests and hosts at all sites
- ssh access to the guests at all sites
- GUI access to hosts at all sites
- A configuration station with a web browser, ssh client, and scp client
- VM Manager Privileges to add OVA's to catalog (VMware only)
- KVM/OpenStack admin and tenant privileges
- OVM-S/OVM-M credentials and privileges, OVM-M cli tool must be installed and is accessible

SUDO

As a non-root user (**admusr**), many commands (when run as admusr) now require the use of **sudo**.

VIP/TSA (OpenStack Only)

OpenStack release Kilo or later is required to configure VIP and target set addresses. Kilo release 2015.1.2 or later is preferred.

IPv6

IPv6 configuration of XMI and IMI networks has been introduced in DSR 7.1. Standard IPv6 formats for IPv6 and prefix can be used in all IP configuration screens, which enable the DSR to be run in an IPv6 only environment. When using IPv6 for XMI and management, you must place the IPv6 address in brackets (highlighted in red below), example as followed:

`https://[<IPv6 address>]`

If a dual-stack (IPv4 and IPv6) network is required, configure the topology with IPv4 first, and then **migrate** to IPv6. Reference [18] DSR IPv6 Migration Guide for instructions on how to accomplish this migration.

3.1 Create DSR Guests (VMware)

Procedure 1. (VMware) Import DSR OVA

STEP #	Procedure	Description
<p>This procedure adds the DSR OVA to the VMware catalog or repository.</p> <p>Check off (✓) each step as it is completed. Steps with shaded boxes require user input.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>		
1. <input type="checkbox"/>	Add DSR OVA image	<ol style="list-style-type: none"> 1. Launch the VMware client of your choice. 2. Add the DSR OVA image to the VMware catalog or repository. Follow the instructions provided by the Cloud solutions manufacturer.

Procedure 2. (VMware only) Configure NOAM Guests Role Based On Resource Profile and Configure Network

STEP #	Procedure	Description
<p>This procedure configures networking on VMs.</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, My Oracle Support (MOS) and ask for assistance.</p>		
1. <input type="checkbox"/>	Create the NOAM1 VM from the OVA image	<ol style="list-style-type: none"> 1. Browse the library or repository that you placed the OVA image. 2. Deploy the OVA Image using vSphere Client or vSphere Web Client. 3. Name the NOAM1 VM and select the data store.
2. <input type="checkbox"/>	Configure resources for the NOAM1 VM	Configure the NOAM1 per the resource profiles defined in [24] DSR Cloud Benchmarking Guide for the DSR NOAM using the vSphere Client or vSphere Web Client .
3. <input type="checkbox"/>	Power on NOAM1	Use the vSphere Client or vSphere Web Client to power on the NOAM1 VM.

STEP #	Procedure	Description
4. <input type="checkbox"/>	Configure NOAM1	<ol style="list-style-type: none"> Access the NOAM1 VM console via the vSphere Client or vSphere Web Client. Login as the admusr user. Set the <ethX> device: Note: Where ethX is the interface associated with the XMI network. <code>\$ sudo netAdm add --device=<ethX> --address=<IP Address in External management Network> --netmask=<Netmask> --onboot=yes --bootproto=none</code> Add the default route for ethX: <code>\$ sudo netAdm add --route=default --gateway=<gateway address for the External management network> --device=<ethX></code> Ping the XMI gateway for network verification. <code>\$ ping -c3 <Gateway of External Management Network></code>
5. <input type="checkbox"/>	Configure NOAM2	Repeat steps 1 through 4 for the NOAM2 VM.

Procedure 3. (VMware only) Configure Remaining DSR Guests Based on Resource Profile and Configure Network

STEP #	Procedure	Description
This procedure adds network addresses for all VMs.		
Note: This procedure provides an example for creating an SOAM. Follow the same steps to create other guests with their respective VM names and profiles.		
Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.		
If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.		
1. <input type="checkbox"/>	Create the SOAM1 VM from the OVA image	<ol style="list-style-type: none"> Browse the library or repository that you placed the OVA image. Deploy the OVA image using vSphere Client or vSphere Web Client. Name the SOAM1 VM and select the data store.
2. <input type="checkbox"/>	Configure resources for the SOAM1 VM	Configure the SOAM1 VM per the resource profiles defined in [24] DSR Cloud Benchmarking Guide for the DSR SO using the vSphere Client or vSphere Web Client . Interfaces must be added per the OCDSR Network to Device Assignments defined in [24] DSR Cloud Benchmarking Guide.
3. <input type="checkbox"/>	Power on SOAM1 VM	<ol style="list-style-type: none"> Power on the DSR SOAM1 VM with the vSphere Client or vSphere Web Client. Monitor the vApps screen's Virtual Machines tab until the DSR VM reports Powered On in the Status column.

STEP #	Procedure	Description
4. <input type="checkbox"/>	Configure XMI interface	<ol style="list-style-type: none"> Access the VM console via the vSphere Client or vSphere Web Client. Login as the admusr user. Set the ethX device: Note: Where ethX is the interface associated with the XMI network. <code>\$ sudo netAdm add --device=<ethX> --address=<IP Address in External Management Network> --netmask=<Netmask> --onboot=yes --bootproto=none</code> Add the default route for ethX: <code>\$ sudo netAdm add --route=default --gateway=<gateway address for the External management network> --device=<ethX></code>
5. <input type="checkbox"/>	Verify network connectivity	<ol style="list-style-type: none"> Access the SOAM1 VM console using the vSphere Client or vSphere Web Client. Login as the admusr user. Ping the NOAM1. <code>\$ ping -c3 <IP Address in External Management Network></code>
6. <input type="checkbox"/>	Procedure overview	Repeat steps 1 through 5 for the following VMs. Use unique labels for the VM names: MP(s) IPFE(s) SOAM(s) Session SBRs, Binding SBR (Optional Components) DR NOAMs (Optional Components)

3.2 Create DSR Guests (KVM/OpenStack)

Procedure 4. Import DSR OVA (KVM/OpenStack Only)

STEP #	Procedure	Description
This procedure adds the DSR image to the glance image catalog. Check off (✓) each step as it is completed. Steps with shaded boxes require user input. If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.		

STEP #	Procedure	Description
1. <input type="checkbox"/>	Preparation	<ol style="list-style-type: none"> 1. Create instance flavors. If not yet done, use the resource profiles defined in [24] DSR Cloud Benchmarking Guide values to create flavors for each type of VM. Flavors can be created with the Horizon GUI in the Admin section, or with the nova flavor-create command line tool. Make the flavor names as informative as possible. As flavors describe resource sizing, a common convention is to use a name like "0406060" where the first two figures (04) represent the number of virtual CPUs, the next two figures (06) might represent the RAM allocation in GB and the final three figures (060) might represent the disk space in GB. 2. If using an Intel 10 Gigabit Ethernet ixgbe driver on the host nodes, please note that the default LRO (Large Receive Offload) option must be disabled on the host command line. Please see the Intel release notes for more details. This action can be performed with the following command. <code>\$ sudo ethtool -K <ETH_DEV> lro off</code> 3. If using IPFE Target Set Addresses (TSA): <ol style="list-style-type: none"> a. Read and understand the Disable Port Security procedure in Appendix G.6, including the warning note. b. Enable the Neutron port security extension. <p>Note: This step is NOT applicable for HEAT deployment.</p>

STEP #	Procedure	Description
2. □	Add DSR OVA image	<ol style="list-style-type: none"> 1. Copy the OVA file to the OpenStack control node. <code>\$ scp DSR-x.x.x.x.x.ova admusr@node:~</code> 2. Log into the OpenStack control node. <code>\$ ssh admusr@node</code> 3. In an empty directory, unpack the OVA file using tar. <code>\$ tar xvf DSR-x.x.x.x.x.ova</code> 4. One of the unpacked files has a .vmdk suffix. This is the VM image file that must be imported. <code>DSR-x.x.x.x-disk1.vmdk</code> 5. Source the OpenStack admin user credentials. <code>\$. keystonec_admin</code> 6. Select an informative name for the new image. <code>dsr-8.2.x.x.x-original</code> 7. Import the image using the glance utility from the command line. <code>\$ glance image-create --name dsr-8.2.x.x.x-original --visibility public --protected false --progress --container-format bare --disk-format vmdk --file DSR-x.x.x.x-disk1.vmdk</code> <p>This process takes about 5 minutes depending on the underlying infrastructure.</p> 8. (Optional – Steps 8 and 9 are not needed if VMDK is used.) Convert VMDK to QCOW2 format. <p>Use the qemu-img tool to create a qcows2 image file using this command. <code>qemu-img convert -f vmdk -O qcows2 <VMDK filename> <QCOW2 filename></code></p> <p>For example: <code>qemu-img convert -f vmdk -O qcows2 DSR-82_12_0.vmdk DSR-82_12_0.qcows2</code></p> <p>Install the qemu-img tool (if not already installed) using this yum command. <code>sudo yum install qemu-img</code></p> 9. Import the converted qcows2 image using the “glance” utility from the command line. <code>\$ glance image-create --name dsr-8.2.x.x.x-original --is-public True --is-protected False --progress --container-format bare --disk-format qcows2 --file DSR-x.x.x.x-disk1.qcows2</code> <p>This process take about 5 minutes depending on the underlying infrastructure.</p>

Procedure 5. (KVM/OpenStack Only) Configure NOAM Guests Role Based on Resource Profile

STEP #	Procedure	Description
--------	-----------	-------------

STEP #	Procedure	Description
<p>This procedure configures networking on VMs.</p>		
<p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p>		
<p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>		
1. <input type="checkbox"/>	Name the new VM instance	<ol style="list-style-type: none"> 1. Create an informative name for the new instance: NOAM1. 2. Examine the OCDSR Network to Device Assignments defined in [24] DSR Cloud Benchmarking Guide.
2. <input type="checkbox"/>	Create and boot the NOAM VM instance from the glance image	<ol style="list-style-type: none"> 1. Get the following configuration values. <ol style="list-style-type: none"> The image ID. \$ glance image-list The flavor ID. \$ nova flavor-list The network ID(s) \$ neutron net-list An informative name for the instance. NOAM1 NOAM2 2. Create and boot the VM instance. The instance must be owned by the DSR tenant user, not the admin user. Source the credentials of the DSR tenant user and issue the following command. Use one --nic argument for each IP/interface. Number of IP/interfaces for each VM type must conform with the OCDSR Network to Device Assignments defined in [24] DSR Cloud Benchmarking Guide. Note: IPv6 addresses should use the v6-fixed-ip argument instead of v4-fixed-ip. \$ nova boot --image <image ID> --flavor <flavor id> --nic net-id=<first network id>,v4-fixed-ip=<first ip address> --nic net-id=<second network id>,v4-fixed-ip=<second ip address> <instance name> 3. View the newly created instance using the nova tool. \$ nova list --all-tenants <p>The VM takes approximately 5 minutes to boot and may be accessed through both network interfaces and the Horizon console tool.</p>

STEP #	Procedure	Description
3. <input type="checkbox"/>	Configure NOAM VIP (Optional)	<p>Note: Refer to For information about Firewall Ports, Refer to DSR 8.3 IP flow document, E99037-01.</p> <p>Application VIP Failover Options (OpenStack) in 0 for more information on VIP.</p> <p>If an NOAM VIP is needed, execute the following commands:</p> <ol style="list-style-type: none"> 1. Find the port ID associated with the NOAM instance XMI interface. <pre>\$ neutron port-list</pre> <ol style="list-style-type: none"> 2. Add the VIP IP address to the address pairs list of the NOAM instance XMI interface port. <pre>\$ neutron port-update <Port ID> --allowed_address_pairs list=true type=dict ip_address=<VIP address to be added></pre>
4. <input type="checkbox"/>	Check if interface is configured	<p>If DHCP is enabled on the Neutron subnet, VM configures the VNIC with the IP address provided in step 2. To verify, ping the XMI IP address provided with the nova boot command from step 2:</p> <pre>\$ ping <XMI-IP-Provided-During-Nova-Boot></pre> <p>If the ping is successful, ignore step 5. to configure the interface manually.</p>
5. <input type="checkbox"/>	Manually configure interface, if not already done (Optional)	<p>Note: If the instance is already configured with an interface and has successfully pinged (step 4.), then ignore this step to configure the interface manually.</p> <ol style="list-style-type: none"> 1. Log into the Horizon GUI as the DSR tenant user. 2. Go to the Compute/Instances section. 3. Click the Name field of the newly created instance. 4. Select the Console tab. 5. Login as the admusr user. 6. Configure the network interfaces, conforming with the OCDSR Network to Device Assignments defined in [24] DSR Cloud Benchmarking Guide. <pre>\$ sudo netAdm add --onboot=yes --device=eth0 --address=<xmi ip> --netmask=<xmi net mask></pre> <pre>\$ sudo netAdm add --route=default --device=eth0 --gateway=<xmi gateway ip></pre> <p>Verify network connectivity by pinging Gateway of XMI network.</p> <pre>\$ ping -c3 <XMI Gateway></pre> <p>Under some circumstances, it may be necessary to configure as many as 6 or more interfaces.</p> <ol style="list-style-type: none"> 7. Reboot the NOAM VM. It takes approximately 5 minutes for the VM to complete rebooting. <pre>\$ sudo init 6</pre> <p>The new VM should now be accessible via both network and Horizon consoles.</p>
6. <input type="checkbox"/>	Configure NOAM2	Repeat steps 1 through 5 for NOAM2.

Procedure 6. (KVM/OpenStack Only) Configure Remaining DSR Guests Based on Resource Profile and Configure Network


STEP #	Procedure	Description
<p>This procedure adds network addresses for all VMs.</p> <p>Note: This procedure provides an example for creating an SOAM. Follow the same steps to create other guests with their respective VM names and profiles.</p>		
<p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>		
1. □	Name the new VM instance	<ol style="list-style-type: none"> 1. Create an informative name for the new instance: SOAM1. 2. Examine the OCDSR Network to Device Assignments defined in [24] DSR Cloud Benchmarking Guide.
2. □	Create and boot the SOAM VM instance from the glance image	<ol style="list-style-type: none"> 1. Get the following configuration values. <ol style="list-style-type: none"> g. The image ID. \$ glance image-list h. The flavor ID. \$ nova flavor-list i. The network ID(s) \$ neutron net-list j. An informative name for the instance. SOAM1 SOAM2 2. Create and boot the VM instance. The instance must be owned by the DSR tenant user, not the admin user. Source the credentials of the DSR tenant user and issue the following command. Use one --nic argument for each IP/interface. Number of IP/interfaces for each VM type must conform with the OCDSR Network to Device Assignments defined in [24] DSR Cloud Benchmarking Guide. Note: IPv6 addresses should use the v6-fixed-ip argument instead of v4-fixed-ip. \$ nova boot --image <image ID> --flavor <flavor id> --nic net-id=<first network id>,v4-fixed-ip=<first ip address> --nic net-id=<second network id>,v4-fixed-ip=<second ip address> <instance name> 3. View the newly created instance using the nova tool. \$ nova list --all-tenants <p>The VM takes approximately 5 minutes to boot and may be accessed through both network interfaces and the Horizon console tool.</p>

STEP #	Procedure	Description
3. <input type="checkbox"/>	Configure SOAM VIP (Optional)	<p>Note: Refer to Allowed Address Pairs in Appendix G.2 for more information on VIP.</p> <p>If an SOAM VIP is needed, execute the following commands:</p> <ol style="list-style-type: none"> 1. Find the port ID associated with the SOAM instance XMI interface. <code>\$ neutron port-list</code> 2. Add the VIP IP address to the address pairs list of the SOAM instance XMI interface port. <code>\$ neutron port-update <Port ID> --allowed_address_pairs list=true type=dict ip_address=<VIP address to be added></code>
4. <input type="checkbox"/>	Check if interface is configured	<p>If DHCP is enabled on Neutron subnet, VM configures the VNIC with the IP address provided in step 2 above.</p> <p>To verify, ping the XMI IP address provided with nova boot... command (step 2): <code>\$ ping <XMI-IP-Provided-During-Nova-Boot></code></p> <p>If the ping is successful, ignore step 5 to configure the interface manually.</p>
5. <input type="checkbox"/>	Manually configure interface, if not already done (Optional)	<p>Note: If the instance is already configured with an interface and successfully pinging (step 4), then ignore this step to configure the interface manually.</p> <ol style="list-style-type: none"> 1. Log into the Horizon GUI as the DSR tenant user. 2. Go to the Compute/Instances section. 3. Click the Name field of the newly created instance. 4. Select the Console tab. 5. Login as the admusr user. 6. Configure the network interfaces, conforming with the OCDSR Network to Device Assignments defined in [24] DSR Cloud Benchmarking Guide. <ul style="list-style-type: none"> <code>\$ sudo netAdm add --onboot=yes --device=eth0 --address=<xmi ip> --netmask=<xmi net mask></code> <code>\$ sudo netAdm add --route=default --device=eth0 --gateway=<xmi gateway ip></code> Verify network connectivity by pinging Gateway of XMI network. <code>\$ ping -c3 <XMI Gateway></code> Under some circumstances, it may be necessary to configure as many as 6 or more interfaces. 7. Reboot the SOAM VM. It takes approximately 5 minutes for the VM to complete rebooting. <code>\$ sudo init 6</code> <p>The new VM should now be accessible via both network and Horizon consoles.</p>

STEP #	Procedure	Description
6. <input type="checkbox"/>	Verify network connectivity	<ol style="list-style-type: none"> 1. Access the SOAM1 VM console using the openstack. 2. Login as the admusr user. 3. Ping the NOAM1. <pre>\$ ping -c3 <IP Address in External Management Network></pre>
7. <input type="checkbox"/>	Procedure overview	<p>Repeat steps 1 through 6 for the following VMs. Use unique labels for the VM names. Assign addresses to all desired network interfaces:</p> <p>MP(s) IPFE(s) MP vSTP (For vSTP configuration) (Optional Components) SOAM(s) Session SBRs, Binding SBR (Optional Components) DR NOAMs (Optional Components)</p>

3.3 Create DSR Guests (OVM-S/OVM-M)

Procedure 7. (OVM-S/OVM-M). Import DSR OVA and prepare for VM creation

STEP #	Procedure	Description
This procedure imports the DSR image. This procedure requires values for these variables:		
<ul style="list-style-type: none"> • <OVM-M IP> = IP address to access a sh prompt on the OVM server • <URL to OVA> = link to a source for downloading the product image (.ova) • <MyRepository name> = name of the repository in the OVM to hold the product image (.ova) 		
Execution of this procedure discovers and uses the values of these variables:		
<ul style="list-style-type: none"> • <Virtual Appliance OVA ID> • <OVA VM name_vm_vm> • <OVM network id for (each subnet)> • <OVM network name for (each subnet)> 		
Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.		
If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.		
1.	Preparation: Access command line of OVM	<p>Refer to Common OVM Manager Tasks (CLI) in Appendix D for setting up the platform.</p> <ol style="list-style-type: none"> 1. Get the site-specific values for these variables (overwrite example). <code><OVM-M IP> = 100.64.62.221</code> 2. Use the respective value for <OVM-M IP> into the command. <code>ssh -l admin <OVM-M IP> -p 10000</code> <p>Example: <code>ssl -l admin 100.64.62.221 -p 10000</code></p> <p>Alternatively, use a terminal emulation tool like putty.</p> 

STEP #	Procedure	Description
2. □	OVM-M CLI: Import the VirtualAppliance/OVA	<ol style="list-style-type: none"> Get the site-specific values for these variables (overwrite example). <code><URL to OVA> = http://10.240.155.70/iso/DSR/8.2/ova/DSR-8.2.0.0.0_82.4.0.ova</code> <code><MyRepository name> = XLab Utility Repo01</code> Use the respective values for <code><MyRepository name></code> and <code><URL to OVA></code> into the command. <code>OVM> importVirtualAppliance Repository name='<MyRepository name>' url="<URL to OVA>"</code> Example: <code>OVM> importVirtualAppliance Repository name='XLab Utility Repo01'</code> <code>url=http://10.240.155.70/iso/DSR/8.2/ova/DSR-8.2.0.0.0_82.4.0.ova</code> Execute the command and validate success. Examine the screen results to find site-specific text for variables in these locations: Command: <code>importVirtualAppliance Repository name='XLab Utility Repo01'</code> <code>url=http://10.240.155.70/iso/DSR/8.2/ova/DSR-8.2.0.0.0_82.4.0.ova</code> Status: Success Time: 2017-04-18 15:23:31,044 EDT JobId: 1492543363365 Data: <code>id: 1128a1c6ce name: DSR-8.2.0.0.0_82.4.0.ova</code> Use the respective values for values for these variables (overwrite example). <code><Virtual Appliance OVA ID> = 1128a1c6ce</code>

STEP #	Procedure	Description
3. □	OVM-M CLI: Get the virtual appliance ID	<p>The virtual appliance OVA ID is used in later steps.</p> <ol style="list-style-type: none"> Get the site-specific text for these variables (overwrite example). <code><Virtual Appliance OVA ID> = 1128a1c6ce</code> Use the respective values for <code><Virtual Appliance OVA ID></code> into the command. <code>OVM> show VirtualAppliance id=<Virtual Appliance OVA id></code> Example: <code>OVM> show VirtualAppliance id=1128a1c6ce</code> Execute the command and validate success. Examine the screen results to find site-specific text for variables in these locations: Command: <code>show VirtualAppliance id=1128a1c6ce</code> Status: Success Time: 2017-04-18 15:23:53,534 EDT Data: <code>Origin = http://10.240.155.70/iso/DSR/8.2/ova/DSR-8.2.0.0.0_82.4.0.ova</code> <code>Repository = 0004fb0000030000da5738315337bfc7 [XLab Utility Repo01]</code> <code>Virtual Appliance Vm 1 = 11145510c0_vm_vm [vm]</code> <code>Virtual Appliance VirtualDisk 1 = 11145510c0_disk_disk1 [disk1]</code> <code>Id = 11145510c0 [DSR-8.2.0.0.0_82.4.0.ova]</code> <code>Name = DSR-8.2.0.0.0_82.4.0.ova</code> <code>Description = Import URL: http://10.240.155.70/iso/DSR/8.2/ova/DSR-8.2.0.0.0_82.4.0.ova</code> <code>Locked = false</code> Use the respective values for these variables (overwrite example). <code><OVA VM name_vm_vm> = 11145510c0_vm_vm</code>

STEP #	Procedure	Description																								
4. □	OVM-M CLI: Determine the OVM network IDs (established during the platform installation)	<p>OVM> list Network</p> <ol style="list-style-type: none"> 1. Execute the command and validate success. 2. Examine the screen results to find the find site-specific OVM values for each subnet: <ul style="list-style-type: none"> • <OVM network ID> • <OVM network name> 3. Note the entire screen results. Refer to this data in later steps. <p>Command: list network</p> <p>Status: Success</p> <p>Time: 2017-04-19 18:51:42,494 EDT</p> <p>Data:</p> <pre> id:10486554b5 name:XSI-7 (10.196.237.0/25) id:10f4d5744c name:XMI-11 (10.75.159.0/25) id:10775cf4e5 name:IDIH Internal id:102e89a481 name:IMI Shared (169.254.9.0/24) id:c0a80500 name:192.168.5.0 id:10d8de6d9a name:XSI-6 (10.196.236.128/25) id:10806a91fb name:XSI-8 (10.296.237.128/25) id:10a7289add name:Control DHCP id:1053a604f0 name:XSI-5 (10.196.236.0/25) id:10345112c9 name:XMI-10 (10.75.158.128/25) </pre> <ol style="list-style-type: none"> 4. Use the respective values for network ID variables (change the examples in this table according to the values). <table border="1" data-bbox="486 1290 1455 1539"> <thead> <tr> <th></th> <th>OAM (XMI)</th> <th>Local (IMI)</th> <th>Signaling A (XSI1)</th> <th>Signaling B (XSI2)</th> <th>Signaling C (XSI3-16)</th> <th>Replication (SBR Rep)</th> <th>DIH Internal</th> </tr> </thead> <tbody> <tr> <td><OVM network name></td> <td>XMI-10</td> <td>IMI Shared</td> <td>XSI-5</td> <td>XSI-6</td> <td>XSI-7</td> <td>DIH Internal</td> <td>XMI-10</td> </tr> <tr> <td><OVM network ID></td> <td>10345112c9</td> <td>102e89a481</td> <td>1053a604f0</td> <td>10d8de6d9a</td> <td></td> <td>10486554b5</td> <td>10775cf4e5</td> </tr> </tbody> </table>		OAM (XMI)	Local (IMI)	Signaling A (XSI1)	Signaling B (XSI2)	Signaling C (XSI3-16)	Replication (SBR Rep)	DIH Internal	<OVM network name>	XMI-10	IMI Shared	XSI-5	XSI-6	XSI-7	DIH Internal	XMI-10	<OVM network ID>	10345112c9	102e89a481	1053a604f0	10d8de6d9a		10486554b5	10775cf4e5
	OAM (XMI)	Local (IMI)	Signaling A (XSI1)	Signaling B (XSI2)	Signaling C (XSI3-16)	Replication (SBR Rep)	DIH Internal																			
<OVM network name>	XMI-10	IMI Shared	XSI-5	XSI-6	XSI-7	DIH Internal	XMI-10																			
<OVM network ID>	10345112c9	102e89a481	1053a604f0	10d8de6d9a		10486554b5	10775cf4e5																			

3.4 Configure Virtual Machines

Procedure 8. (OVM-S/OVM-M). Configure each DSR VM

STEP #	Procedure	Description
This procedure creates virtual machines. Repeat this procedure for each DSR VM guest that needs to be created. This procedure requires values for these variables:		
<ul style="list-style-type: none"> • <OVA VM name_vm_vm> • <ServerPool name> • <VM name> • <OVM network ID for XMI> • <OVM network ID for IMI> • <OVM network ID for XSI#> where # is a numeric from 1-16, for the signaling networks • <OVM network ID for Replication XSI#> • <URL for OVM GUI> • <VM IP in XMI> from the NAPD • <Gateway for XMI> from the NAPD • <NetMask for XMI> from the NAPD 		
Execution of this procedure discovers and uses the values of these variables:		
<ul style="list-style-type: none"> • <VM ID> • <vCPUs Production> • <VNIC 1 ID> • <interface name> defined in [24] DSR Cloud Benchmarking Guide 		
Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.		
If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.		
1.	<p><input type="checkbox"/> OVM-M CLI: Create a VM for each guest from the VM in the OVA virtual appliance</p>	<ol style="list-style-type: none"> 1. Get the site-specific text for these variables (overwrite example). <code><OVA VM name_vm_vm> = 11145510c0_vm_vm</code> 2. Use the respective values for <OVA VM name> into the command. <code>OVM> createVmFromVirtualApplianceVm VirtualApplianceVm name=<OVA VM name></code> Example: <code>OVM> createVmFromVirtualApplianceVm VirtualApplianceVm name=11145510c0_vm_vm</code> 3. Execute the command and validate success. 4. Examine the screen results to find site-specific text for variables in these locations: <code>Command: createVmFromVirtualApplianceVm VirtualApplianceVm name=11145510c0_vm_vm</code> <code>Status: Success</code>

STEP #	Procedure	Description
		<p>Time: 2017-04-18 16:02:09,141 EDT JobId: 1492545641976 Data: id: 0004fb00000600004a0e02bdf9fc1bcd name:DSR-8.2.0.0.0_82.4.0.0.ova_vm 5. Use the respective values for these variables (overwrite example). <VM ID> = 0004fb00000600004a0e02bdf9fc1bcd</p>
2. □	OVM-M CLI: Add the VM to the server pool	<p>1. Get the site-specific text for these variables (overwrite example). <VM ID> = 0004fb00000600004a0e02bdf9fc1bcd <ServerPool name> = XLab Pool 01 2. Use the respective values for <VM ID> and <ServerPool name> into the command. OVM> add Vm id=<VM id> to ServerPool name=<ServerPool name> Example: OVM> add Vm id=0004fb00000600004a0e02bdf9fc1bcd to ServerPool name="XLab Pool 01" 3. Execute the command and validate success. Command: add Vm id=0004fb0000060000beb93da703830d3c to ServerPool name="XLab Pool 01" Status: Success Time: 2017-04-19 21:05:10,950 EDT JobId: 1492650310802 Note: Refer to the Server Pool section in Appendix D.2 for more information.</p>

STEP #	Procedure	Description												
3. <input type="checkbox"/>	OVM-M CLI: Edit VM to apply required profile/resources	<ol style="list-style-type: none"> Get the site-specific text for these variables (overwrite example). <pre><VM ID> = 0004fb000060004a0e02bdf9fc1bcd <VM name> = na-noam-na-2a <vCPUs Production> = 4</pre> Refer to [24] DSR Cloud Benchmarking Guide for recommended resource. <table border="1" data-bbox="535 473 1449 650"> <thead> <tr> <th data-bbox="535 473 682 587">VM Name</th><th data-bbox="682 473 829 587">vCPUs Lab</th><th data-bbox="829 473 975 587">RAM (GB) Lab</th><th data-bbox="975 473 1122 587">vCPUs Production</th><th data-bbox="1122 473 1269 587">RAM (GB) Production</th><th data-bbox="1269 473 1449 587">Storage (GB) Lab and Production</th></tr> </thead> <tbody> <tr> <td data-bbox="535 587 682 650">Type of guest host</td><td data-bbox="682 587 829 650">#</td><td data-bbox="829 587 975 650">#</td><td data-bbox="975 587 1122 650">#</td><td data-bbox="1122 587 1269 650">#</td><td data-bbox="1269 587 1449 650">#</td></tr> </tbody> </table> Use the respective values for <VM ID>, <VM name>, and <vCPUs Production> into the command. <pre>OVM> edit Vm id=<VM id> name=<VM name> memory=6144 memoryLimit=6144 cpuCountLimit=<vCPUs Production> cpuCount=<vCPUs Production> domainType=XEN_HVM description="<VM name>"</pre> Example: <pre>OVM> edit Vm id=0004fb000060004a0e02bdf9fc1bcd name=na-noam-na-2a memory=6144 memoryLimit=6144 cpuCountLimit=4 cpuCount=4 domainType=XEN_HVM description="na-noam-na-2a"</pre> Execute the command and validate success. <pre>Command: edit Vm id=0004fb000060004a0e02bdf9fc1bcd name=na-noam-na-2a memory=6144 memoryLimit=6144 cpuCountLimit=4 cpuCount=4 domainType=XEN_HVM description="na-noam-na-2a" Status: Success Time: 2017-04-18 17:55:25,645 EDT JobId: 1492552525477</pre> <p>Now, the VM has a name and resources.</p>	VM Name	vCPUs Lab	RAM (GB) Lab	vCPUs Production	RAM (GB) Production	Storage (GB) Lab and Production	Type of guest host	#	#	#	#	#
VM Name	vCPUs Lab	RAM (GB) Lab	vCPUs Production	RAM (GB) Production	Storage (GB) Lab and Production									
Type of guest host	#	#	#	#	#									
4. <input type="checkbox"/>	OVM-M CLI: Determine VNIC ID	<ol style="list-style-type: none"> Get the site-specific text for these variables (overwrite example). <pre><VM name> = na-noam-na-2a</pre> Use the respective value for <VM name> into the command. <pre>OVM> show Vm name=<VM name></pre> Example: <pre>OVM> show Vm name=na-noam-na-2a</pre> Execute the command and validate success. Examine the screen results to find site-specific text for variables in these locations: <pre>Status = Stopped Memory (MB) = 6144</pre> 												

STEP #	Procedure	Description
		<pre> Max. Memory (MB) = 6144 Processors = 4 Max. Processors = 4 Priority = 50 Processor Cap = 100 High Availability = No Operating System = Oracle Linux 6 Mouse Type = PS2 Mouse Domain Type = Xen HVM Keymap = en-us Start Policy = Use Pool Policy Origin = http://10.240.155.70/iso/DSR/8.2/ova/DSR-8.2.0.0.0_82.4.0.ova Disk Limit = 4 Huge Pages Enabled = No Config File Absolute Path = 192.168.5.5:/storage/ovm01/repository/VirtualMachines/00 04fb00000600004a0e02bdf9fc1bcd/vm.cfg Config File Mounted Path = /OVS.Repositories/0004fb0000030000da5738315337bfc7/Virtu alMachines/0004fb00000600004a0e02bdf9fc1bcd/vm.cfg Server Pool = 0004fb00000200009148c8926d307f05 [XLab Pool 01] Repository = 0004fb0000030000da5738315337bfc7 [XLab Utility Repo01] Vnic 1 = 0004fb0000070000091e1ab5ae291d8a [Template Vnic] VmDiskMapping 1 = 0004fb0000130000a1996c6074d40563 [Mapping for disk Id (79def426328a4127b5bf9f7ae53d3f48.img)] VmDiskMapping 2 = 0004fb00001300002db3d4b67a143ab5 [Mapping for disk Id (EMPTY_CDROM)] Restart Action On Crash = Restart Id = 0004fb00000600004a0e02bdf9fc1bcd [na-noam-na-2a] Name = na-noam-na-2a Description = na-noam-na-2a Locked = false DeprecatedAttrs = [Huge Pages Enabled (Deprecated for PV guest)] 5. Use the respective values for these variables (overwrite example). </pre>

STEP #	Procedure	Description																
		<Vnic 1 ID> = 0004fb0000070000091e1ab5ae291d8a																
5. <input type="checkbox"/>	Determine network interfaces for the type of guest host	<p>Refer to [24] DSR Cloud Benchmarking Guide to learn which network interfaces need to be configured for each guest type. The table looks like this:</p> <table border="1" data-bbox="491 382 1432 536"> <thead> <tr> <th></th><th>OAM (XMI)</th><th>Local (IMI)</th><th>Sig A (XSI1)</th><th>Sig B (XSI2)</th><th>Sig C (XSI3-16)</th><th>Rep (SBR)</th><th>DIH Internal</th></tr> </thead> <tbody> <tr> <td>Type of guest host</td><td>eth#</td><td>eth#</td><td>eth#</td><td>eth#</td><td>eth#</td><td>eth#</td><td>eth#</td></tr> </tbody> </table> <p>Note: The VNICs need to be created in the correct order so the interfaces are associated with the correct network.</p>		OAM (XMI)	Local (IMI)	Sig A (XSI1)	Sig B (XSI2)	Sig C (XSI3-16)	Rep (SBR)	DIH Internal	Type of guest host	eth#						
	OAM (XMI)	Local (IMI)	Sig A (XSI1)	Sig B (XSI2)	Sig C (XSI3-16)	Rep (SBR)	DIH Internal											
Type of guest host	eth#	eth#	eth#	eth#	eth#	eth#	eth#											
6. <input type="checkbox"/>	OVM-M CLI: Attach XMI VNIC (if required by guest host type)	<p>Add (attach) VNIC ID of the XMI network to VM:</p> <ol style="list-style-type: none"> 1. Get the site-specific text for these variables (overwrite example) <a href"=""><VNIC 1 ID> = 0004fb0000070000091e1ab5ae291d8a <a href"=""><OVM network ID for XMI> = 10345112c9 2. Use the respective values for <VNIC 1 ID> and <OVM network ID for XMI> into the command <a href"="">OVM> add Vnic ID=<Vnic 1 ID> to Network name=<OVM network ID for XMI> Example: <a href"="">OVM> add Vnic ID=0004fb0000070000091e1ab5ae291d8a to Network name=10345112c9 3. Execute the command and validate success. Command: <a href"="">add Vnic id=0004fb0000070000091e1ab5ae291d8a to Network name=10345112c9 Status: Success Time: <a href"="">2017-04-19 19:08:59,496 EDT JobId: <a href"="">1492643339327 																

STEP #	Procedure	Description
7. <input type="checkbox"/>	OVM-M CLI: Create and attach IMI VNIC (if required by guest host type)	<p>Create VNIC ID on the IMI network and attach to VM:</p> <ol style="list-style-type: none"> Get the site-specific text for these variables (overwrite example). <code><VM name> = na-noam-na-2a</code> <code><OVM network ID for IMI> = 102e89a481</code> Use the respective values for <code><OVM network ID for IMI></code> and <code><VM name></code> into the command. <code>OVM> create Vnic network=<OVM network ID for IMI> name=<VM name>-IMI on Vm name=<VM name></code> Example: <code>OVM> create Vnic network=102e89a481 name=na-noam-na-2a-IMI on Vm name=na-noam-na-2a</code> Execute the command and validate success. Command: <code>create Vnic network=102e89a481 name=na-noam-na-2a-IMI on Vm name=na-noam-na-2a</code> Status: Success Time: 2017-04-19 21:21:57,363 EDT JobID: 1492651317194 Data: <code>id:0004fb00000700004f16dc3bfe0750a7 name:na-noam-na-2a-IMI</code>
8. <input type="checkbox"/>	OVM-M CLI: Create and attach XSI VNIC(s) (if required by guest host type) Note: Repeat this step if the VM will have multiple signaling networks, specifying the number of the network	<p>Create VNIC ID on the XSI network(s) and attach to VM:</p> <ol style="list-style-type: none"> Get the site-specific text for these variables (overwrite example). <code><VM name> = hostname</code> <code><OVM network ID for XSI#> = 1053a604f0</code> <code><#> = the number of the XSI network [1-16]</code> Use the respective values for <code><OVM network ID for XSI#></code> and <code><VM name></code> into the command. <code>OVM> create Vnic network=<OVM network id for XSI#> name=<VM name>-XSI<#> on Vm name=<VM name></code> Example: <code>OVM> create Vnic network=1053a604f0 name=hostname-XSI1 on Vm name=hostname</code> Execute the command and validate success.

STEP #	Procedure	Description
9. <input type="checkbox"/>	OVM-M CLI: Create and attach replication VNIC (if required by guest host type)	<p>Create VNIC ID on the Replication network and attach to VM:</p> <ol style="list-style-type: none"> 1. Get the site-specific text for these variables (overwrite example). <code><VM name> = hostname</code> <code><OVM network ID for Replication XSI#> = 10486554b5</code> <code><OVM network name for Replication XSI#> = XSI7</code> <code><#> = the number of the XSI Replication network [1-16]</code> 2. Use the respective values for <code><OVM network ID for Replication XSI#></code>, <code><OVM network name for Replication XSI#></code>, and <code><VM name></code> into the command. <code>OVM> create Vnic network=<OVM network id for Replication XSI#> name=<VM name>-<OVM network name for Replication XSI#> on Vm name=<VM name></code> Example: <code>OVM> create Vnic network=10486554b5 name= hostname-XSI7 on Vm name=hostname</code> 3. Execute the command and validate success.
10. <input type="checkbox"/>	OVM-M CLI: Start VM	<ol style="list-style-type: none"> 1. Get the site-specific text for these variables (overwrite example). <code><VM name> = na-noam-na-2a</code> 2. Use the respective values for <code><VM name></code> into the command. <code>OVM> start Vm name=<VM name></code> Example: <code>OVM> start Vm name=na-noam-na-2a</code> 3. Execute the command and validate success. Command: <code>start Vm name=na-noam-na-2a</code> Status: Success Time: 2017-04-19 19:29:35,376 EDT JobId: 1492644568558

STEP #	Procedure	Description
11. <input checked="" type="checkbox"/>	OVM-M GUI: Configure the XMI network interface for this VM	<ol style="list-style-type: none"> 1. Get the site-specific text for these variables (overwrite example). <ul style="list-style-type: none"> <URL for OVM GUI> = https://100.64.62.221:7002/ovm/console/faces/resource/resourceView.jspx <interface name> = from the table in [24] DSR Cloud Benchmarking Guide <VM IP in XMI> = from the NAPD <Gateway for XMI> = from the NAPD <NetMask for XMI> = from the NAPD 2. Access the CLI of the console for the VM: 3. Log into the OVM-M GUI by typing the <URL for OVM GUI> into a browser. <ol style="list-style-type: none"> k. Navigate to the Servers and VMs tab. l. Expand and select the <ServerPool name>. m. From the Perspective list, select Virtual Machines. n. Select the <VM name> from the rows listed, and click the Launch Console icon. o. In the Console window, log into the VM as the admusr. 4. Use the respective values for <interface name>, <VM IP in XMI>, <Gateway for XMI>, and <NetMask for XMI> into the commands <p>XMI:</p> <pre>\$ sudo netAdm set --onboot=yes --device=<interface name> --address=<VM IP in XMI> --netmask=<NetMask for XMI> \$ sudo netAdm add --route=default --device=<interface name> -gateway=<Gateway for XMI></pre> <p>Example:</p> <pre>\$ sudo netAdm set --onboot=yes --device=eth0 -- address=10.75.158.189 --netmask=255.255.255.128</pre> <p>Example:</p> <pre>\$ sudo netAdm add --route=default --device=eth0 -- gateway=10.75.158.129</pre> <ol style="list-style-type: none"> 5. Execute the command and validate success 6. Verify network connectivity by pinging Gateway of network <pre>\$ ping -c3 <Gateway for XMI></pre> 7. Reboot the VM. It takes approximately 5 minutes for the VM to complete rebooting. <pre>\$ sudo init 6</pre> <p>The new VM should now be accessible via both network and console.</p>

4. Software Installation Using HEAT Templates (OpenStack)

4.1 Prepare OpenStack Template and Environment files

Procedure 9. Prepare OpenStack Templates and Environment Files for NOAM/Signaling Stacks

STEP #	Procedure	Description
This procedure gathers required templates and environment files to provide while deploying NOAM/signaling stacks.		
Prerequisite: All the respective infrastructures has to be up and running.		
Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.		
If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.		
1. <input type="checkbox"/>	Login to Oracle document repository - OTN	Log into the Oracle Document Repository at http://docs.oracle.com/en/industries/communications/diameter-signaling-router/index.html
2. <input type="checkbox"/>	Select the DSR Release	Select the respective release folder. For example, Release 8.2.x.
3. <input type="checkbox"/>	Download HEAT templates	Download the HEAT Templates zip file under Cloud Installation and Upgrade section.
4. <input type="checkbox"/>	Unzip the HEAT templates to a folder	<ol style="list-style-type: none"> 1. Create a new folder with any name for storing the HEAT templates under the home directory. Example : /home/heat_templates 2. Store the downloaded HEAT templates zip file in the folder. Example : /home/heat_templates/exampleHeat.zip 3. Unzip the downloaded heat templates. unzip /home/heat_templates/exampleHeat.zip

5. <input type="checkbox"/>	Determine the template and environment files	<p>Below are possible deployment use cases of DSR. The HEAT templates contain files for all scenarios. Determine the appropriate template and environment files with respect to your requirement.</p> <p>Note: Currently, SS7 MPs are not supported. Refer to Appendix J.2 Example Parameter File.</p> <table border="1"> <thead> <tr> <th>Deployment Use Case</th><th>Template Files</th><th>Environment Files</th></tr> </thead> <tbody> <tr> <td>Dynamic IP - With VIP</td><td>NOAM Template dsrNetworkOam_provider.yaml Signaling Template dsrSignalingNode_provider.yaml</td><td>dsrResources_provider.yaml</td></tr> <tr> <td>Dynamic IP - Without VIP</td><td>NOAM Template dsrNetworkOamNoVip_provider.yaml Signaling Template dsrSignalingNodeNoVip_provider.yaml</td><td>dsrResourcesNoVip_provider.yaml</td></tr> <tr> <td>Fixed IP - With VIP</td><td>NOAM Template dsrNetworkOam_fixedIps.yaml Signaling Template dsrSignalingNode_fixedIps.yaml</td><td>dsrResources_fixedIps.yaml</td></tr> <tr> <td>Fixed IP - Without VIP</td><td>NOAM Template Yet to be created Signaling Template Yet to be created.</td><td>Yet to be created</td></tr> <tr> <td>Dynamic IP - With IDIH nodes</td><td>NOAM Template dsrNetworkOam_provider.yaml Signaling Template dsrSignalingNode_dih_provider.yaml</td><td>idihResources_provider.yaml</td></tr> <tr> <td>Fixed IP - With IDIH nodes</td><td>NOAM Template dsrNetworkOam_fixedIps.yaml Signaling Template dsrSignalingNode_dih_fixedIps.yaml</td><td>dsrResources_dih_fixedIps.yaml</td></tr> </tbody> </table>	Deployment Use Case	Template Files	Environment Files	Dynamic IP - With VIP	NOAM Template dsrNetworkOam_provider.yaml Signaling Template dsrSignalingNode_provider.yaml	dsrResources_provider.yaml	Dynamic IP - Without VIP	NOAM Template dsrNetworkOamNoVip_provider.yaml Signaling Template dsrSignalingNodeNoVip_provider.yaml	dsrResourcesNoVip_provider.yaml	Fixed IP - With VIP	NOAM Template dsrNetworkOam_fixedIps.yaml Signaling Template dsrSignalingNode_fixedIps.yaml	dsrResources_fixedIps.yaml	Fixed IP - Without VIP	NOAM Template Yet to be created Signaling Template Yet to be created.	Yet to be created	Dynamic IP - With IDIH nodes	NOAM Template dsrNetworkOam_provider.yaml Signaling Template dsrSignalingNode_dih_provider.yaml	idihResources_provider.yaml	Fixed IP - With IDIH nodes	NOAM Template dsrNetworkOam_fixedIps.yaml Signaling Template dsrSignalingNode_dih_fixedIps.yaml	dsrResources_dih_fixedIps.yaml
Deployment Use Case	Template Files	Environment Files																					
Dynamic IP - With VIP	NOAM Template dsrNetworkOam_provider.yaml Signaling Template dsrSignalingNode_provider.yaml	dsrResources_provider.yaml																					
Dynamic IP - Without VIP	NOAM Template dsrNetworkOamNoVip_provider.yaml Signaling Template dsrSignalingNodeNoVip_provider.yaml	dsrResourcesNoVip_provider.yaml																					
Fixed IP - With VIP	NOAM Template dsrNetworkOam_fixedIps.yaml Signaling Template dsrSignalingNode_fixedIps.yaml	dsrResources_fixedIps.yaml																					
Fixed IP - Without VIP	NOAM Template Yet to be created Signaling Template Yet to be created.	Yet to be created																					
Dynamic IP - With IDIH nodes	NOAM Template dsrNetworkOam_provider.yaml Signaling Template dsrSignalingNode_dih_provider.yaml	idihResources_provider.yaml																					
Fixed IP - With IDIH nodes	NOAM Template dsrNetworkOam_fixedIps.yaml Signaling Template dsrSignalingNode_dih_fixedIps.yaml	dsrResources_dih_fixedIps.yaml																					

4.2 Create OpenStack Parameters files

Procedure 10. Create OpenStack Parameter File for NOAM

STEP #	Procedure	Description
		<p>This procedure instructs how to manually create input parameters file to be provided while deploying NOAM stacks.</p> <p>Prerequisite: All the respective infrastructures has to be up and running</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>

STEP #	Procedure	Description												
1. □	Login to OpenStack server CLI	Log into the OpenStack server through command line.												
2. □	Create the parameter file	<ol style="list-style-type: none"> 1. Go to the folder created in Procedure 9, step 4. for storing the templates. 2. Create an empty NOAM parameter file in this folder following this naming convention to identify the purpose of the file. <code><DSR Name>_<Site Name>_NetworkOam_Params.yaml</code> For example: <code>dsrCloudInit_Site00_NetworkOam_Params.yaml</code> 												
3. □	Sample file	<p>Refer to Appendix J.1 Example Template File for a sample file with values.</p> <p>Note: It is important to keep the example file ready since this helps you understand the use of each key value pair described in the next step while creating the parameter file.</p>												
4. □	Populate the parameters file	<p>Refer to Appendix J.1 Example Template File to create the parameter file in YAML format.</p> <p>Note: Follow these guidelines while working with the YAML files.</p> <ul style="list-style-type: none"> • The file must end with .yaml extension. • YAML must be case-sensitive and indentation-sensitive. • YAML does not support the use of tabs. Instead of tabs, it uses spaces. • This file is in YAML format and it contains key:value pairs. • The first key should be parameters: and then the remaining required key/value pairs for the topology. <p>This table lists all required key:value pairs.</p> <table border="1"> <thead> <tr> <th>Key Name</th> <th>Type</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>numPrimaryNoams</td> <td>number</td> <td> <p>The number of NOAMs that receive and load DSR topology information.</p> <p>Note: In DSR 8.2, use 1 as valid value.</p> <p>This NOAM represents active NOAM.</p> </td></tr> <tr> <td>numNoams</td> <td>number</td> <td> <p>The number of NOAMs in the DSR topology other than primary NOAM.</p> <p>Note: In DSR 8.2, use 1 as valid value.</p> <p>This NOAM represents standby NOAM.</p> </td></tr> <tr> <td>noamImage</td> <td>string</td> <td> <p>The VM image for the NOAM.</p> <p>Note: This image is used for both active and standby NOAMs.</p> </td></tr> </tbody> </table>	Key Name	Type	Description	numPrimaryNoams	number	<p>The number of NOAMs that receive and load DSR topology information.</p> <p>Note: In DSR 8.2, use 1 as valid value.</p> <p>This NOAM represents active NOAM.</p>	numNoams	number	<p>The number of NOAMs in the DSR topology other than primary NOAM.</p> <p>Note: In DSR 8.2, use 1 as valid value.</p> <p>This NOAM represents standby NOAM.</p>	noamImage	string	<p>The VM image for the NOAM.</p> <p>Note: This image is used for both active and standby NOAMs.</p>
Key Name	Type	Description												
numPrimaryNoams	number	<p>The number of NOAMs that receive and load DSR topology information.</p> <p>Note: In DSR 8.2, use 1 as valid value.</p> <p>This NOAM represents active NOAM.</p>												
numNoams	number	<p>The number of NOAMs in the DSR topology other than primary NOAM.</p> <p>Note: In DSR 8.2, use 1 as valid value.</p> <p>This NOAM represents standby NOAM.</p>												
noamImage	string	<p>The VM image for the NOAM.</p> <p>Note: This image is used for both active and standby NOAMs.</p>												

STEP #	Procedure	Description			
		noamFlavor	string	The flavor that defines the VM size for the NOAM. Note: This flavor is used for both active and standby NOAMs.	
		primaryNoamVmNames	comma_delimited_list	List of Primary NOAM VM names Note: Number of VMnames must be equal to the numPrimaryNoams value.	
		noamVmNames	comma_delimited_list	List of NOAM VM names other than primary NOAM VMs. Note: Number of VMnames must be equal to the numNoams value.	
		noamAZ	string	The availability zone into which NOAM servers should be placed. Note: In DSR 8.2, all NOAM servers are placed in the same availability zone.	
		noamSG	string	The server group where NOAMs at this site belong.	
		xmiPublicNetwork	string	External management interface.	
		imiPrivateNetwork	string	Internal management interface.	
		imiPrivateSubnet	string	Name of the IMI network.	
		imiPrivateSubnetCidr	string	The address range for the subnet.	
		ntpServer	string	IP of the NTP server.	
Note: The below 3 keys are ONLY applicable for fixed IP scenario.					
primaryNoamXmilps		comma_delimited_list	Previously reserved IP for the primary NOAM to talk to external devices.		
noamXmilps		comma_delimited_list	Previously reserved IP for non-primary NOAMs to talk to external devices.		
noamVip		string	VIP for NOAMs.		

Procedure 11. Create OpenStack Parameter File for Signaling

STEP #	Procedure	Description
--------	-----------	-------------

This procedure manually creates the input parameters file to provide while deploying signaling stacks.

Prerequisite: All the respective infrastructures has to be up and running.

Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.

If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.

1. <input type="checkbox"/>	Log into the OpenStack server CLI	Log into the OpenStack CLI.																								
2. <input type="checkbox"/>	Create the parameter file	<ol style="list-style-type: none"> 1. Go to the folder created in Procedure 9, step 4. for storing the templates. 2. Create an empty signaling parameter file in this folder following this naming convention to identify the purpose of the file. <p><DSR Name>_<Site Name>_SignalingNode_Params.yaml</p> <p>For example:</p> <p>dsrCloudInit_Site00_SignalingNode_Params.yaml</p>																								
3. <input type="checkbox"/>	Sample file	<p>Refer to Appendix J.1 Example Template File for a sample file with values.</p> <p>Note: It is important to keep the example file ready since this helps you understand the use of each key value pair described in the next step while creating the parameter file.</p>																								
4. <input type="checkbox"/>	Populate the parameters file	<p>Refer to Appendix J.1 Example Template File to create the parameter file in YAML format.</p> <p>Note: Follow these guidelines while working with the YAML files.</p> <ul style="list-style-type: none"> • The file must end with .yaml extension. • YAML must be case-sensitive and indentation-sensitive. • YAML does not support the use of tabs. Instead of tabs, it uses spaces. • This file is in YAML format and it contains key:value pairs. • The first key should be parameters: and then the remaining required key/value pairs for the topology. <p>This table lists all required key:value pairs.</p> <table border="1"> <thead> <tr> <th>Key Name</th><th>Type</th><th>Description</th></tr> </thead> <tbody> <tr> <td>numSoams</td><td>number</td><td>The number of SOAMs at this signaling node.</td></tr> <tr> <td>soamImage</td><td>string</td><td>The VM image for an SOAM.</td></tr> <tr> <td>soamFlavor</td><td>string</td><td>The flavor that defines the VM size for an SOAM.</td></tr> <tr> <td>soamVmNames</td><td>comma_delimited_list</td><td>List of SOAM VM names.</td></tr> <tr> <td>soamAZ</td><td>string</td><td>The availability zone into which SOAM servers should be placed</td></tr> <tr> <td>soamSG</td><td>string</td><td>Note: In DSR 8.2, all SOAM servers are placed in the same availability zone</td></tr> <tr> <td></td><td></td><td>Server group for the SOAM VMs.</td></tr> </tbody> </table>	Key Name	Type	Description	numSoams	number	The number of SOAMs at this signaling node.	soamImage	string	The VM image for an SOAM.	soamFlavor	string	The flavor that defines the VM size for an SOAM.	soamVmNames	comma_delimited_list	List of SOAM VM names.	soamAZ	string	The availability zone into which SOAM servers should be placed	soamSG	string	Note: In DSR 8.2, all SOAM servers are placed in the same availability zone			Server group for the SOAM VMs.
Key Name	Type	Description																								
numSoams	number	The number of SOAMs at this signaling node.																								
soamImage	string	The VM image for an SOAM.																								
soamFlavor	string	The flavor that defines the VM size for an SOAM.																								
soamVmNames	comma_delimited_list	List of SOAM VM names.																								
soamAZ	string	The availability zone into which SOAM servers should be placed																								
soamSG	string	Note: In DSR 8.2, all SOAM servers are placed in the same availability zone																								
		Server group for the SOAM VMs.																								

numDas	number	The number of DAs at this signaling node.
dalImage	string	The VM image for a DA.
daFlavor	string	The flavor that defines the VM size for a DA.
daVmNames	comma_delimited_list	List of DA VM names.
daAZ	string	The availability zone into which DA servers should be placed. Note: In DSR 8.2, all DA-MP servers are placed in the same availability zone.
daSG	string	Server group for the DA VMs.
daProfileName	string	The MP profile to be applied to all DAs. Possible values are: VM_Relay, VM_Database, VM_6K_Mps, VM_8K_Mps, VM_10K_Mps, VM_12K_Mps, VM_14K_Mps, VM_16K_Mps, VM_18K_Mps, VM_21K_Mps, VM_24K_Mps, VM_27K_Mps, VM_30K_Mps
numIpFes	number	The number of IPFEs at this signaling node.
ipfImage	string	The VM image for an IPFE.
ipfeFlavor	string	The flavor that defines the VM size for an IPFE.
ipfeVmNames	comma_delimited_list	List of IPFE VM names.
ipfeAZ	string	The availability zone into which IPFE servers should be placed. Note: In DSR 8.2, all IPFE servers are placed in the same availability zone.
ipfeSGs	comma_delimited_list	Server group for each IPFE VM.
numStps	number	The number of STPs at this signaling node.
stpImage	string	The VM image for an STP.
stpFlavor	string	The flavor that defines the VM size for an STP.
stpVmNames	comma_delimited_list	List of STP VM names.

stpAZ	string	The availability zone into which STP servers should be placed. Note: In DSR 8.2, all STP servers are placed in the same availability zone.
stpSG	string	Server group for the STP VMs.
xmiPublicNetwork	string	External management interface.
imiPrivateNetwork	string	Internal management interface.
imiPrivateSubnet	string	Name of the IMI network.
imiPrivateSubnetCidr	string	The address range for the subnet.
xsiPublicNetwork	string	External signaling interface.
primaryNoamVmName	string	Name of NOAM VM that the config XML was loaded onto Note: NOT used in 8.2. In DSR 8.2, user should NOT provide any value to this key.
noamXmilps	comma_delimited_list	The XMI IPs for all NOAM servers, excluding VIPs. Note: NOT used in 8.2. In DSR 8.2, user should NOT provide any value to this key.
ntpServer	string	IP of the NTP server.
Note: The below keys are ONLY applicable for fixed IP scenario, with or without IDIH nodes		
soamXmilps	comma_delimited_list	Previously reserved IP for non-primary SOAMs to talk to external devices.
soamVip	string	VIP for SOAMs.
daXmilps	comma_delimited_list	Previously reserved IP for DA MP to talk to external devices.
daXsilps	comma_delimited_list	Previously reserved IP for DA MP to talk to signaling devices.
ipfeXmilps	comma_delimited_list	Previously reserved IP for IPFE to talk to external devices.
ipfeXsilps	comma_delimited_list	Previously reserved IP for IPFE to talk to signaling devices.
stpXmilps	comma_delimited_list	Previously reserved IP for STP to talk to external devices.

stpXsilps	comma_delimited_list	Previously reserved IP for STP to talk to signaling devices.
ipfeXsiPublicIp	string	Reserved single IP address on signaling network to which remote diameter hosts route packets for load balancing over set of message processors.
stpSctpPorts	comma_delimited_list	<p>The SCTP ports to be associated with STP.</p> <p>Note: If there is no STP in topology then provide empty list, for example, for example, []</p> <p>Note: Open these ports beforehand on which STP connections are going to be created while doing configuration.</p>
These two parameters are applicable for TCP/SCTP to use with the Diameter connection.		
<p>Note: Open these ports beforehand on which Diameter connections are going to be created while doing Diameter configuration.</p>		
diameterTcpPorts	comma_delimited_list	The TCP ports to be associated with. If this parameter is not provided, then default ports are assigned.
diameterSctpPorts	comma_delimited_list	The SCTP ports to be associated with. If this parameter is not provided, then default ports are assigned.
The below keys are applicable only for scenarios which include IDIH nodes.		
idihAppImage	string	The VM image for the IDIH Application VM
idihAppFlavor	string	The flavor that defines the size for the IDIH Application VM
idihAppVmName	string	The IDIH Mediation VM name.
idihMedImage	string	The flavor that defines the size for the IDIH Mediation VM
idihMedVmName	string	The IDIH Mediation VM name
idihDbImage	string	The VM image for the IDIH Database VM
idihDbFlavor	string	The flavor that defines the size for the IDIH Database VM
idihDbVmName	string	The IDIH Database VM name



idihAZ	string	The availability zone into which IDIH VMs should be placed
idihIntPrivateNetwork	string	Name of the internal tenant network (that will be created) for communication between IDIH VMs
idihIntPrivateSubnet	string	Name of the subnet (that will be created) on the IDIH internal tenant network (idihIntPrivateNetwork)
<p>Note: At least one is mandatory (either TCP/SCTP parameter). Refer to this table to determine the valid combinations for SCTP/TCP port configurations.</p>		
diameterTcpPorts	diameterSctpPorts	Is Valid?
[]	[]	NO
[""]	[""]	NO
["<port(s)>"]	[]	YES
[]	["<port(s)>"]	YES
["<port(s)>"]	["<port(s)>"]	YES
<p>Note: Repeat steps 2 and 3 of this procedure for each additional site.</p>		

4.3 Deploy HEAT Templates

Procedure 12. Deploy HEAT Templates

STEP #	Procedure	Description
This procedure instructs how to deploy HEAT templates to create NOAM and Signaling stacks.		
Prerequisite: All the respective infrastructures has to be up and running. The required input files are all available.		
Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.		
If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.		
1. <input type="checkbox"/>	Login to OpenStack server CLI	Log into the OpenStack CLI.
2. <input type="checkbox"/>	Prepare the input files required for the deployment	<p>To create NOAM and signaling stacks, provide these input files as parameters while deploying the HEAT templates.</p> <p>Template Files</p> <p>With respect to the deployment scenario decided in Procedure 9, step 2. the template files for NOAM and signaling stacks have been already determined.</p> <p>Environment Files</p> <p>With respect to the deployment scenario decided in Procedure 9, step 2. the environment files for NOAM and signaling stacks have been already determined.</p> <p>Parameter Files</p> <p>The parameter file for NOAM has already been created in Procedure 10. The parameter file for signaling has already been created in Procedure 11.</p>
3. <input type="checkbox"/>	Deploy NOAM stack	<p>Execute the OpenStack command to create NOAM stack using the three input files. Make sure the template and environment files are selected with respect to NOAM stack as per in Procedure 9, step 2.</p> <pre>openstack stack create -e <EnvironmentFileForNOAM.yaml> -e <ParameterFileForNOAM.yaml> -t <TemplateFileForNOAM> <NOAMStackName></pre> <p>Example for VIP scenario:</p> <pre>\$ openstack stack create -e dsrResources_provider.yaml -e SinglesiteProvider_Site00_NetworkOam_Params.yaml -t dsrNetworkOam_provider.yaml SinglesiteProvider_Site00_NetworkOam</pre>


STEP #	Procedure	Description														
4. □	Deploy signaling stack	<p>Execute the OpenStack command to create signaling stack using the three input files. Make sure the template and environment files are selected with respect to signaling stack as per in Procedure 9, step 2.</p> <pre>openstack stack create -e <EnvironmentFileForSignaling.yaml> -e <ParameterFileForSignaling.yaml> -t <TemplateFileForSignaling> <SignalingStackName></pre> <p>Example for VIP scenario:</p> <pre>\$ openstack stack create -e dsrResources_provider.yaml -e SinglesiteProvider_Site00_SignalingNode_Params.yaml -t dsrSignalingNode_provider.yaml SinglesiteProvider_Site00_Signaling</pre>														
5. □	Verify the stack creation status	<ol style="list-style-type: none"> 1. Execute this command to see the stack creation status. <pre>\$ openstack stack show <stackname></pre> <table border="1"> <thead> <tr> <th>ID</th> <th>Name</th> <th>Status</th> <th>Created</th> </tr> </thead> <tbody> <tr> <td>(uuid)</td> <td>teststack</td> <td>CREATE_IN_PROGRESS</td> <td>(timestamp)</td> </tr> </tbody> </table> <p>It takes about 2 minutes to complete the creation.</p> 2. Execute the command again to verify the status. <pre>\$ openstack stack show <stackname></pre> <table border="1"> <thead> <tr> <th>ID</th> <th>Stack Name</th> <th>Stack Status</th> </tr> </thead> <tbody> <tr> <td>950ed51a-cca7-478a-81e4-3d61562c045d</td> <td>teststack</td> <td>CREATE_COMPLETE</td> </tr> </tbody> </table> 	ID	Name	Status	Created	(uuid)	teststack	CREATE_IN_PROGRESS	(timestamp)	ID	Stack Name	Stack Status	950ed51a-cca7-478a-81e4-3d61562c045d	teststack	CREATE_COMPLETE
ID	Name	Status	Created													
(uuid)	teststack	CREATE_IN_PROGRESS	(timestamp)													
ID	Stack Name	Stack Status														
950ed51a-cca7-478a-81e4-3d61562c045d	teststack	CREATE_COMPLETE														



STEP #	Procedure	Description
<p>6. <input type="checkbox"/> Retrieve required IPs from created stacks</p>	<p>1. Log into the OpenStack GUI with valid credentials.</p>  <p>2. Navigate to Project > Orchestration and click Stacks.</p>  <p>3. Select the stack you created (<stackname>) and click Overview to see the IP details of the stack.</p>  <p>Note:</p> <ul style="list-style-type: none"> • All NOAM IP information displays in the NOAM stack (<NOAMStackName>). • All signaling IP information displays in the signaling stack (<SignalingStackName>). <p>4. Retrieve the IP details for DSR configuration.</p>	


5. Application Configuration

Procedure 13. Configure the First NOAM NE and Server



STEP #	Procedure	Description
This procedure configures the first NOAM VM.		
Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.		
If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.		
1.	Resolve the Hostname: Get the HTTPD running	Change Hostname from the default value using sudo: 1. Edit /etc/hosts file Note: Remove any occurrence of “.” and the “.<availability zone>” name, such as “.novalocal” from the hostname that might have got appended. a) Append the hostname to the IPv4 line as, “127.0.0.1 localhost localhost4 NOAM1” b) Append the hostname to the IPv6 line as, “::1 localhost localhost6 NOAM1” 2. Edit /etc/syconfig/network. a) Change the “HOSTNAME=XXXX” line to the new hostname. “HOSTNAME=NOAM1” b) Set the hostname on the command line: \$ sudo hostname NOAM1 3. Reboot the VM \$ sudo init 6

STEP #	Procedure	Description
2. <input type="checkbox"/>	NOAM GUI: Login	<p>Establish a GUI session as the guiadmin user on the NOAM server by using the XMI IP address.</p>  <p>Mon Jul 11 13:59:37 2016 EDT</p> <p>Log In Enter your username and password to log in</p> <p>Username: <input type="text"/></p> <p>Password: <input type="password"/></p> <p><input type="checkbox"/> Change password</p> <p>Log In</p> <p>Welcome to the Oracle System Login.</p> <p>This application is designed to work with most modern HTML5 compliant browsers and uses both JavaScript and cookies. Please refer to the Oracle Software Web Browser Support Policy for details.</p> <p>Unauthorized access is prohibited.</p> <hr/> <p><i>Oracle and Java are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.</i></p> <p>Copyright © 2010, 2016, Oracle and/or its affiliates. All rights reserved.</p>

STEP #	Procedure	Description
3. <input type="checkbox"/>	NOAM GUI: Create the NOAM network element using the XML file	<ol style="list-style-type: none"> 1. Navigate to Configuration > Networking > Networks.  2. Click Browse and type the pathname of the NOAM network XML file.  3. Click Upload File to upload the XML file. See the examples in Appendix A Sample Network Element and Hardware Profiles and configure the NOAM network element.  4. Once the data has been uploaded, you should see a tabs display with the name of your network element. Click on this tab which describes the individual networks that are now configured. 

STEP #	Procedure	Description																																																
4. <input type="checkbox"/>	NOAM GUI: Map services to networks	<p>1. Navigate to Configuration > Networking > Services.</p> <p>2. Click Edit and set the services as shown in the table below:</p> <table border="1" data-bbox="486 354 1388 720"> <thead> <tr> <th data-bbox="486 354 763 397">Name</th><th data-bbox="763 354 1106 397">Intra-NE Network</th><th data-bbox="1106 354 1388 397">Inter-NE Network</th></tr> </thead> <tbody> <tr> <td data-bbox="486 397 763 439">OAM</td><td data-bbox="763 397 1106 439"><IMI Network></td><td data-bbox="1106 397 1388 439"><XMI Network></td></tr> <tr> <td data-bbox="486 439 763 481">Replication</td><td data-bbox="763 439 1106 481"><IMI Network></td><td data-bbox="1106 439 1388 481"><XMI Network></td></tr> <tr> <td data-bbox="486 481 763 523">Signaling</td><td data-bbox="763 481 1106 523">Unspecified</td><td data-bbox="1106 481 1388 523">Unspecified</td></tr> <tr> <td data-bbox="486 523 763 566">HA_Secondary</td><td data-bbox="763 523 1106 566">Unspecified</td><td data-bbox="1106 523 1388 566">Unspecified</td></tr> <tr> <td data-bbox="486 566 763 608">HA_MP_Secondary</td><td data-bbox="763 566 1106 608">Unspecified</td><td data-bbox="1106 566 1388 608">Unspecified</td></tr> <tr> <td data-bbox="486 608 763 650">Replication_MP</td><td data-bbox="763 608 1106 650"><IMI Network></td><td data-bbox="1106 608 1388 650">Unspecified</td></tr> <tr> <td data-bbox="486 650 763 692">ComAgent</td><td data-bbox="763 650 1106 692"><IMI Network></td><td data-bbox="1106 650 1388 692">Unspecified</td></tr> </tbody> </table> <p>For example, if your IMI network is named IMI and your XMI network is named XMI, then your services configuration should look like the following:</p> <table border="1" data-bbox="486 804 910 1431"> <thead> <tr> <th data-bbox="486 804 649 825">Name</th><th data-bbox="649 804 780 825">Intra-NE Network</th><th data-bbox="780 804 910 825">Inter-NE Network</th></tr> </thead> <tbody> <tr> <td data-bbox="486 825 649 889">OAM</td><td data-bbox="649 825 780 889">INTERNALIMI</td><td data-bbox="780 825 910 889">INTERNALXMI</td></tr> <tr> <td data-bbox="486 889 649 952">Replication</td><td data-bbox="649 889 780 952">INTERNALIMI</td><td data-bbox="780 889 910 952">INTERNALXMI</td></tr> <tr> <td data-bbox="486 952 649 1015">Signaling</td><td data-bbox="649 952 780 1015">Unspecified</td><td data-bbox="780 952 910 1015">Unspecified</td></tr> <tr> <td data-bbox="486 1015 649 1079">HA_Secondary</td><td data-bbox="649 1015 780 1079">Unspecified</td><td data-bbox="780 1015 910 1079">Unspecified</td></tr> <tr> <td data-bbox="486 1079 649 1142">HA_MP_Secondary</td><td data-bbox="649 1079 780 1142">Unspecified</td><td data-bbox="780 1079 910 1142">Unspecified</td></tr> <tr> <td data-bbox="486 1142 649 1205">Replication_MP</td><td data-bbox="649 1142 780 1205">INTERNALIMI</td><td data-bbox="780 1142 910 1205">Unspecified</td></tr> <tr> <td data-bbox="486 1205 649 1269">ComAgent</td><td data-bbox="649 1205 780 1269">INTERNALIMI</td><td data-bbox="780 1205 910 1269">Unspecified</td></tr> </tbody> </table> <p>3. Click OK to apply the Service-to-Network selections. Dismiss any possible popup notifications.</p>	Name	Intra-NE Network	Inter-NE Network	OAM	<IMI Network>	<XMI Network>	Replication	<IMI Network>	<XMI Network>	Signaling	Unspecified	Unspecified	HA_Secondary	Unspecified	Unspecified	HA_MP_Secondary	Unspecified	Unspecified	Replication_MP	<IMI Network>	Unspecified	ComAgent	<IMI Network>	Unspecified	Name	Intra-NE Network	Inter-NE Network	OAM	INTERNALIMI	INTERNALXMI	Replication	INTERNALIMI	INTERNALXMI	Signaling	Unspecified	Unspecified	HA_Secondary	Unspecified	Unspecified	HA_MP_Secondary	Unspecified	Unspecified	Replication_MP	INTERNALIMI	Unspecified	ComAgent	INTERNALIMI	Unspecified
Name	Intra-NE Network	Inter-NE Network																																																
OAM	<IMI Network>	<XMI Network>																																																
Replication	<IMI Network>	<XMI Network>																																																
Signaling	Unspecified	Unspecified																																																
HA_Secondary	Unspecified	Unspecified																																																
HA_MP_Secondary	Unspecified	Unspecified																																																
Replication_MP	<IMI Network>	Unspecified																																																
ComAgent	<IMI Network>	Unspecified																																																
Name	Intra-NE Network	Inter-NE Network																																																
OAM	INTERNALIMI	INTERNALXMI																																																
Replication	INTERNALIMI	INTERNALXMI																																																
Signaling	Unspecified	Unspecified																																																
HA_Secondary	Unspecified	Unspecified																																																
HA_MP_Secondary	Unspecified	Unspecified																																																
Replication_MP	INTERNALIMI	Unspecified																																																
ComAgent	INTERNALIMI	Unspecified																																																
5. <input type="checkbox"/>	NOAM GUI: Insert the 1st NOAM VM	<p>1. Navigate to Configuration > Servers.</p> <p> Main Menu <ul style="list-style-type: none"> Administration Configuration <ul style="list-style-type: none"> Networking <ul style="list-style-type: none"> Servers Server Groups Resource Domains </p> <p>2. Click Insert to insert the new NOAM server into servers table (the first or</p>																																																


STEP #	Procedure	Description																																
		<p>server).</p> <p>Attribute Value</p> <table border="1"> <tr> <td>Hostname *</td> <td><input type="text"/></td> </tr> <tr> <td>Role *</td> <td>- Select Role - <input type="button" value="▼"/></td> </tr> <tr> <td>System ID</td> <td><input type="text"/></td> </tr> <tr> <td>Hardware Profile</td> <td>DSR Guest <input type="button" value="▼"/></td> </tr> <tr> <td>Network Element Name *</td> <td>- Unassigned - <input type="button" value="▼"/></td> </tr> <tr> <td>Location</td> <td><input type="text"/></td> </tr> </table> <p>3. Fill in the fields as follows:</p> <p>Hostname: <Hostname> Role: NETWORK_OAM&P System ID: <Site System ID> Hardware Profile: DSR_Guest Network Element Name: [Select NE from drop-down list] The network interface fields are now available with selection choices based on the chosen hardware profile and network element.</p> <table border="1"> <thead> <tr> <th colspan="3">OAM Interfaces [At least one interface is required.]:</th> </tr> <tr> <th>Network</th> <th>IP Address</th> <th>Interface</th> </tr> </thead> <tbody> <tr> <td>INTERNAL_XMI (10.196.227.0/24)</td> <td>10.196.227.21</td> <td>eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (6)</td> </tr> <tr> <td>INTERNAL_IMI (169.254.1.0/24)</td> <td>169.254.1.21</td> <td>eth1 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (3)</td> </tr> </tbody> </table> <p>Ok Apply Cancel</p> <p>4. Fill in the server IP addresses for the XMI network. Select ethX for the interface. Leave the VLAN checkbox unchecked.</p> <p>5. Fill in the server IP addresses for the IMI network. Select ethX for the interface. Leave the VLAN checkbox unchecked.</p> <p>6. Add the following NTP servers:</p> <table border="1"> <thead> <tr> <th>NTP Server</th> <th>Preferred?</th> </tr> </thead> <tbody> <tr> <td>Valid NTP Server</td> <td>Yes</td> </tr> <tr> <td>Valid NTP Server</td> <td>No</td> </tr> <tr> <td>Valid NTP Server</td> <td>No</td> </tr> </tbody> </table> <p>7. Click OK when you have completed entering all the server data.</p> <p>Note: Properly configure the NTP on the controller node to reference lower</p>	Hostname *	<input type="text"/>	Role *	- Select Role - <input type="button" value="▼"/>	System ID	<input type="text"/>	Hardware Profile	DSR Guest <input type="button" value="▼"/>	Network Element Name *	- Unassigned - <input type="button" value="▼"/>	Location	<input type="text"/>	OAM Interfaces [At least one interface is required.]:			Network	IP Address	Interface	INTERNAL_XMI (10.196.227.0/24)	10.196.227.21	eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (6)	INTERNAL_IMI (169.254.1.0/24)	169.254.1.21	eth1 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (3)	NTP Server	Preferred?	Valid NTP Server	Yes	Valid NTP Server	No	Valid NTP Server	No
Hostname *	<input type="text"/>																																	
Role *	- Select Role - <input type="button" value="▼"/>																																	
System ID	<input type="text"/>																																	
Hardware Profile	DSR Guest <input type="button" value="▼"/>																																	
Network Element Name *	- Unassigned - <input type="button" value="▼"/>																																	
Location	<input type="text"/>																																	
OAM Interfaces [At least one interface is required.]:																																		
Network	IP Address	Interface																																
INTERNAL_XMI (10.196.227.0/24)	10.196.227.21	eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (6)																																
INTERNAL_IMI (169.254.1.0/24)	169.254.1.21	eth1 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (3)																																
NTP Server	Preferred?																																	
Valid NTP Server	Yes																																	
Valid NTP Server	No																																	
Valid NTP Server	No																																	



STEP #	Procedure	Description
		stratum NTP servers.
6. <input type="checkbox"/>	NOAM GUI: Export the initial configuration	<ol style="list-style-type: none"> 1. Navigate to Configuration > Servers.  2. From the GUI screen, select the NOAM server and click Export to generate the initial configuration data for that server. Go to the Info tab to confirm the file has been created. 
7. <input type="checkbox"/>	NOAM Server: Copy configuration file to 1 st NOAM server	<ol style="list-style-type: none"> 1. Obtain a terminal window to the 1st NOAM server, logging in as the admusr user. 2. Copy the configuration file created in the previous step from the /var/TKLC/db/filemgmt directory on the 1st NOAM to the /var/tmp directory. The configuration file has a filename like TKLCConfigData.<hostname>.sh. The following is an example: <pre>\$ sudo cp /var/TKLC/db/filemgmt/TKLCConfigData.<hostname>.sh /var/tmp/TKLCConfigData.sh</pre>
8. <input type="checkbox"/>	First NOAM Server: Wait for configuration to complete	<p>The automatic configuration daemon looks for the file named TKLCConfigData.sh in the /var/tmp directory, implements the configuration in the file, and prompts the user to reboot the server.</p> <p>If you are on the console, wait to be prompted to reboot the server, but DO NOT reboot the server, it is rebooted later in this procedure.</p> <p>Verify the script completed successfully by checking the following file.</p> <pre>\$ sudo cat /var/TKLC/appw/logs/Process/install.log</pre> <p>Note: Ignore the warning about removing the USB key since no USB key is present. No response occurs until the reboot prompt is issued.</p>



STEP #	Procedure	Description
9. <input type="checkbox"/>	First NOAM Server: Set the time zone (Optional) and reboot the server	<p>To change the system time zone, from the command line prompt, execute set_ini_tz.pl. The following command example uses the America/New_York time zone.</p> <p>Replace, as appropriate, with the time zone you have selected for this installation. For a full list of valid time zones, see Appendix B List of Frequently Used Time Zones.</p> <pre>\$ sudo /usr/TKLC/appworks/bin/set_ini_tz.pl "America/New_York" >/dev/null 2>&1</pre> <pre>\$ date</pre> <pre>\$ sudo init 6</pre> <p>Wait for server to reboot.</p>
10. <input type="checkbox"/>	First NOAM Server: Verify server health	<ol style="list-style-type: none"> 1. Log into the NOAM1 as the admusr user. 2. Execute the following command as admusr on the 1st NOAM server and make sure no errors are returned: <pre>\$ sudo syscheck</pre> <pre>Running modules in class hardware</pre> <pre>OK</pre> <pre>Running modules in class disk</pre> <pre>OK</pre> <pre>Running modules in class net</pre> <pre>OK</pre> <pre>Running modules in class system</pre> <pre>OK</pre> <pre>Running modules in class proc</pre> <pre>OK</pre> <pre>LOG LOCATION: /var/TKLC/log/syscheck/fail_log</pre>

Procedure 14. Configure the NOAM Server Group

STEP #	Procedure	Description
<p>This procedure configures the NOAM server group.</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>		
1. <input type="checkbox"/>	NOAM GUI: Login	<p>Establish a GUI session on the first NOAM server by using the XMI IP address of the first NOAM server. Open the web browser and type http://<NO1_XMI_Address> as the URL.</p> <p>Login as the guiadmin user. If prompted by a security warning, click Continue to this Website to proceed.</p>



STEP #	Procedure	Description																		
2. <input type="checkbox"/>	NOAM GUI: Enter NOAM server group data	<p>1. Navigate to Configuration > Server Groups.</p>  <p>2. Click Insert and fill in the following fields:</p> <p>Server Group Name: [Enter Server Group Name] Level: A Parent: None Function: DSR (Active/Standby Pair) WAN Replication Connection Count: Use Default Value</p> <p>Adding new server group</p> <table border="1" data-bbox="494 967 1277 1600"> <thead> <tr> <th data-bbox="494 967 861 1020">Field</th> <th data-bbox="861 967 1171 1020">Value</th> <th data-bbox="1171 967 1277 1020">Desc</th> </tr> </thead> <tbody> <tr> <td data-bbox="494 1020 861 1157">Server Group Name *</td> <td data-bbox="861 1020 1171 1157">ZombieNOAM</td> <td data-bbox="1171 1020 1277 1157">Unique require</td> </tr> <tr> <td data-bbox="494 1157 861 1262">Level *</td> <td data-bbox="861 1157 1171 1262">A</td> <td data-bbox="1171 1157 1277 1262">Select</td> </tr> <tr> <td data-bbox="494 1262 861 1368">Parent *</td> <td data-bbox="861 1262 1171 1368">NONE</td> <td data-bbox="1171 1262 1277 1368">Select</td> </tr> <tr> <td data-bbox="494 1368 861 1474">Function *</td> <td data-bbox="861 1368 1171 1474">DSR (active/standby pair)</td> <td data-bbox="1171 1368 1277 1474">Select</td> </tr> <tr> <td data-bbox="494 1474 861 1600">WAN Replication Connection Count</td> <td data-bbox="861 1474 1171 1600">1</td> <td data-bbox="1171 1474 1277 1600">Specify</td> </tr> </tbody> </table> <p>3. Click OK when all fields are filled in.</p>	Field	Value	Desc	Server Group Name *	ZombieNOAM	Unique require	Level *	A	Select	Parent *	NONE	Select	Function *	DSR (active/standby pair)	Select	WAN Replication Connection Count	1	Specify
Field	Value	Desc																		
Server Group Name *	ZombieNOAM	Unique require																		
Level *	A	Select																		
Parent *	NONE	Select																		
Function *	DSR (active/standby pair)	Select																		
WAN Replication Connection Count	1	Specify																		


STEP #	Procedure	Description
3. <input type="checkbox"/>	NOAM GUI: Edit the NOAM Server Group	<p>1. Navigate to Configuration > Server Groups.</p>  <p>2. Select the new server group and click Edit.</p>  <p>Select the network element that represents the NOAM.</p>  <p>3. In the portion of the screen that lists the servers for the server group, find the NOAM server being configured. Mark the Include in SG checkbox.</p> <p>4. Leave the other box unchecked.</p> <p>5. Click OK.</p>
4. <input type="checkbox"/>	NOAM Server: Verify NOAM VM role	<p>1. From console window of the first NOAM VM, execute the <code>ha.mystate</code> command to verify the DbReplication and VIP items under the resourceId column has a value of Active under the role column.</p> <p>You may have to wait a few minutes for it to be in that state.</p> <p>For Example:</p>  <pre>[admusr@NO1 ~]\$ ha.mystate resourceId role node DC subResources lastUpdate ----- ----- DbReplication Act/Act A1348.092 * 0 0527:050750.672 Act/Act A1348.092 * 0 0527:050750.673 VIP Act/Act A1348.092 * 0 0527:050750.672 Act/Act A1348.092 * 0 0527:050750.673 CLOUDPROCESSESRES Act/OOS A1348.092 * 0 0527:050750.672 CAPM_HELP_Proc Act/OOS A1348.092 * 0 0527:050750.625 DSROAM_Proc Act/OOS A1348.092 * 0 0527:050755.725 CAPM_PSFS_Proc Act/Act A1348.092 * 0 0527:050800.737 [admusr@NO1 ~]\$</pre>

STEP #	Procedure	Description																								
5. <input type="checkbox"/>	NOAM GUI: Restart 1 st NOAM VM	<p>1. From the NOAM GUI, navigate to Status & Manage > Server.</p>  <p>2. Select the first NOAM server. Click Restart.</p>  <p>3. Click OK on the confirmation screen and wait for restart to complete.</p> 																								
6. <input type="checkbox"/>	NOAM Server: Set sysmetric thresholds for VMs. Note: These commands disable the message rate threshold alarms	<p>From console window of the first NOAM VM, execute the iset commands as admusr:</p> <pre>\$ sudo iset -feventNumber='-1' SysMetricThreshold where "metricId='RoutingMsgRate' and function='DIAM'" \$ sudo iset -feventNumber='-1' SysMetricThreshold where "metricId='RxRbarMsgRate' and function='RBAR'" \$ sudo iset -feventNumber='-1' SysMetricThreshold where "metricId='RxFabrMsgRate' and function='FABR'"</pre> <p>Verify, if the correct value was configured.</p> <p>For example:</p> <pre>\$ sudo iqt SysMetricThreshold grep RxFabrIngressMsgRate</pre> <table border="1"> <tr><td>RxFabrMsgRate</td><td>FABR</td><td>*C</td><td>RunningAvg</td><td>-1</td><td>38000</td><td>36000</td><td>3000</td></tr> <tr><td>RxFabrMsgRate</td><td>FABR</td><td>**</td><td>RunningAvg</td><td>-1</td><td>32000</td><td>28000</td><td>3000</td></tr> <tr><td>RxFabrMsgRate</td><td>FABR</td><td>-*</td><td>RunningAvg</td><td>-1</td><td>2400</td><td>20000</td><td>3000</td></tr> </table>	RxFabrMsgRate	FABR	*C	RunningAvg	-1	38000	36000	3000	RxFabrMsgRate	FABR	**	RunningAvg	-1	32000	28000	3000	RxFabrMsgRate	FABR	-*	RunningAvg	-1	2400	20000	3000
RxFabrMsgRate	FABR	*C	RunningAvg	-1	38000	36000	3000																			
RxFabrMsgRate	FABR	**	RunningAvg	-1	32000	28000	3000																			
RxFabrMsgRate	FABR	-*	RunningAvg	-1	2400	20000	3000																			

Procedure 15. Configure the Second NOAM Server

STEP #	Procedure	Description
--------	-----------	-------------



STEP #	Procedure	Description										
<p>This procedure configures the second NOAM server.</p>												
<p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p>												
<p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>												
1. <input type="checkbox"/>	NOAM GUI: Login	<ol style="list-style-type: none"> 1. If not already done, establish a GUI session on the first NOAM server by using the XMI IP address of the first NOAM server. Open the web browser and type http://<NO1_XMI_IP_Address> as the URL. 2. Login as the guiadmin user. 										
2. <input type="checkbox"/>	NOAM GUI: Insert the 2nd NOAM VM	<ol style="list-style-type: none"> 1. Navigate to Configuration > Servers.  2. Click Insert to insert the new NOAM server into servers table (the first or server).  3. Fill in the fields as follows: <table> <tr> <td>Hostname:</td> <td><Hostname></td> </tr> <tr> <td>Role:</td> <td>NETWORK_OAM&P</td> </tr> <tr> <td>System ID:</td> <td><Site System ID></td> </tr> <tr> <td>Hardware Profile:</td> <td>DSR Guest</td> </tr> <tr> <td>Network Element Name:</td> <td>[Choose NE list]</td> </tr> </table> <p>The network interface fields are now available with selection choices based on the chosen hardware profile and network element.</p> 	Hostname:	<Hostname>	Role:	NETWORK_OAM&P	System ID:	<Site System ID>	Hardware Profile:	DSR Guest	Network Element Name:	[Choose NE list]
Hostname:	<Hostname>											
Role:	NETWORK_OAM&P											
System ID:	<Site System ID>											
Hardware Profile:	DSR Guest											
Network Element Name:	[Choose NE list]											


STEP #	Procedure	Description																	
		<p>OAM Interfaces [At least one interface is required.]:</p> <table border="1" data-bbox="507 291 1388 487"> <thead> <tr> <th data-bbox="507 297 670 318">Network</th><th data-bbox="670 297 1095 318">IP Address</th><th data-bbox="1095 297 1388 318">Interface</th></tr> </thead> <tbody> <tr> <td data-bbox="507 340 670 361">INTERNALXMI (10.196.227.0/24)</td><td data-bbox="670 340 1095 361">10.196.227.21</td><td data-bbox="1095 340 1388 361">eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (6)</td></tr> <tr> <td data-bbox="507 382 670 403">INTERNALIMI (169.254.1.0/24)</td><td data-bbox="670 382 1095 403">169.254.1.21</td><td data-bbox="1095 382 1388 403">eth1 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (3)</td></tr> </tbody> </table> <p data-bbox="507 445 736 487">Ok Apply Cancel</p> <ol style="list-style-type: none"> <li data-bbox="502 508 1383 566">4. Fill in the server IP addresses for the XMI network. Select ethX for the interface. Leave the VLAN checkbox unmarked. <li data-bbox="502 587 1383 644">5. Fill in the server IP addresses for the IMI network. Select ethX for the interface. Leave the VLAN checkbox unmarked. <li data-bbox="502 665 915 686">6. Add the following NTP servers: <table border="1" data-bbox="507 699 1388 895"> <thead> <tr> <th data-bbox="507 699 931 720">NTP Server</th><th data-bbox="931 699 1388 720">Preferred?</th></tr> </thead> <tbody> <tr> <td data-bbox="507 741 931 762">Valid NTP Server</td><td data-bbox="931 741 1388 762">Yes</td></tr> <tr> <td data-bbox="507 783 931 804">Valid NTP Server</td><td data-bbox="931 783 1388 804">No</td></tr> <tr> <td data-bbox="507 825 931 846">Valid NTP Server</td><td data-bbox="931 825 1388 846">No</td></tr> </tbody> </table> <ol style="list-style-type: none"> <li data-bbox="502 895 1307 916">7. Click OK when you have completed entering all the server data. <p>Note: Properly configure the NTP on the controller node to reference lower stratum NTP servers.</p>	Network	IP Address	Interface	INTERNALXMI (10.196.227.0/24)	10.196.227.21	eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (6)	INTERNALIMI (169.254.1.0/24)	169.254.1.21	eth1 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (3)	NTP Server	Preferred?	Valid NTP Server	Yes	Valid NTP Server	No	Valid NTP Server	No
Network	IP Address	Interface																	
INTERNALXMI (10.196.227.0/24)	10.196.227.21	eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (6)																	
INTERNALIMI (169.254.1.0/24)	169.254.1.21	eth1 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (3)																	
NTP Server	Preferred?																		
Valid NTP Server	Yes																		
Valid NTP Server	No																		
Valid NTP Server	No																		
3. <input type="checkbox"/>	NOAM GUI: Export the initial configuration	<ol style="list-style-type: none"> <li data-bbox="502 1022 997 1043">1. Navigate to Configuration > Servers.  <ol style="list-style-type: none"> <li data-bbox="502 1079 801 1353">2. From the GUI screen, select server just configured and click Export to generate the initial configuration data for that server. Go to the Info tab to confirm the file has been created. <p data-bbox="507 1459 915 1501">Insert Edit Delete Export Report</p>																	
4. <input type="checkbox"/>	First NOAM Server: Copy configuration file to 2 nd NOAM server	<ol style="list-style-type: none"> <li data-bbox="502 1543 1302 1564">1. Obtain a terminal session to the 1st NOAM as the admusr user. <li data-bbox="502 1586 1339 1643">2. Login as the admusr user to the NO1 shell and issue the following commands: <pre data-bbox="540 1664 1351 1755"> \$ sudo scp /var/TKLC/db/filemgmt/TKLCConfigData.<hostname>.sh admusr@<ipaddr>:/var/tmp/TKLCConfigData.sh </pre> <p>Note: ipaddr is the IP address of NOAM2 assigned to its ethX interface associated with the xmi network.</p>																	




STEP #	Procedure	Description
5. <input type="checkbox"/>	Second NOAM Server: Wait for configuration to complete	<ol style="list-style-type: none"> 1. Obtain a terminal session to the 2nd NOAM as the admusr user. The automatic configuration daemon looks for the file named TKLCConfigData.sh in the /var/tmp directory, implements the configuration in the file, and prompts the user to reboot the server. 2. If you are on the console, wait to be prompted to reboot the server, but DO NOT reboot the server, it is rebooted later in this procedure. 3. Verify script completed successfully by checking the following file. <code>\$ sudo cat /var/TKLC/appw/logs/Process/install.log</code> Note: Ignore the warning about removing the USB key since no USB key is present.
6. <input type="checkbox"/>	Second NOAM Server: Reboot the server	<p>Obtain a terminal session to the 2nd NOAM as the admusr user.</p> <code>\$ sudo init 6</code> <p>Wait for server to reboot.</p>
7. <input type="checkbox"/>	Second NOAM Server: Verify server health	<ol style="list-style-type: none"> 1. Log into the NOAM2 as admusr and wait. 2. Execute the following command as super-user on the 2nd NO server and make sure no errors are returned: <pre>\$ sudo syscheck Running modules in class hardware... OK Running modules in class disk... OK Running modules in class net... OK Running modules in class system... OK Running modules in class proc... OK LOG LOCATION: /var/TKLC/log/syscheck/fail_log</pre>

Procedure 16. Complete Configuring the NOAM Server Group

STEP #	Procedure	Description
		<p>This procedure finishes configuring the NOAM Server Group.</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>

STEP #	Procedure	Description
1. <input type="checkbox"/>	NOAM GUI: Edit the NOAM Server Group Data	<ol style="list-style-type: none"> From the GUI session on the first NOAM server, navigate to Configuration > Server Groups.  Select the NOAM server group and click Edit.  Add the second NOAM server to the server group by marking the Include in SG checkbox for the second NOAM server. Click Apply.  Click Add to add a NOAM VIP. Type the VIP Address and click OK. 




STEP #	Procedure	Description
2. <input type="checkbox"/>	Establish GUI session on the NOAM VIP	<p>Establish a GUI session on the NOAM by using the NOAM VIP address. Login as the guiadmin user.</p>  <p>Oracle System Login</p> <p>Mon Jul 11 13:59:37 2016 EDT</p> <p>Log In Enter your username and password to log in</p> <p>Username: <input type="text"/></p> <p>Password: <input type="password"/></p> <p><input type="checkbox"/> Change password</p> <p>Log In</p> <p>Welcome to the Oracle System Login.</p> <p>This application is designed to work with most modern HTML5 compliant browsers and uses both JavaScript and cookies. Please refer to the Oracle Software Web Browser Support Policy for details.</p> <p>Unauthorized access is prohibited.</p> <p><small>Oracle and Java are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.</small></p> <p><small>Copyright © 2010, 2016, Oracle and/or its affiliates. All rights reserved.</small></p>
3. <input type="checkbox"/>	Wait for remote database alarm to clear	Wait for the alarm ID 10200 Remote Database re-initialization in progress to be cleared before proceeding (Alarms & Events > View Active).

STEP #	Procedure	Description
4. <input type="checkbox"/>	NOAM GUI: Restart 2 nd NOAM VM	<ol style="list-style-type: none"> 1. Navigate to Status & Manage > Server and select the second NOAM server.  2. Click Restart.  3. Click OK on the confirmation screen.  <p>Wait approximately 3-5 minutes before proceeding to allow the system to stabilize indicated by having the Appl State as Enabled.</p>
5. <input type="checkbox"/>	SDS can now be installed (Optional)	If this deployment contains SDS, SDS can now be installed. Refer to document referenced in [6] SDS SW Installation and Configuration Guide.


Procedure 17. Configure the DR NOAM NE and Server (Optional)

STEP #	Procedure	Description
		<p>This procedure configures the first DR NOAM VM.</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>

STEP #	Procedure	Description
1. <input type="checkbox"/>	Primary NOAM VIP GUI: Login	<p>Establish a GUI session on the primary NOAM server by using the XMI VIP IP address.</p>

STEP #	Procedure	Description
2. <input type="checkbox"/>	Primary NOAM VIP GUI: Create the DR NOAM network element using the XML file	<ol style="list-style-type: none"> 1. Navigate to Configuration > Networking > Networks.  2. Click Browse and type the pathname to the NOAM network XML file.  3. Click Upload File to upload the XML file.  <p>See the examples in Appendix A Sample Network Element and Hardware Profiles and configure the NOAM network element.</p> 4. Once the data has been uploaded, you should see a tabs appear with the name of your network element. Click on this tab, which describes the individual networks that are now configured: 
3. <input type="checkbox"/>	Primary NOAM VIP GUI: Insert the 1st DR NOAM VM	<ol style="list-style-type: none"> 1. Navigate to Configuration > Servers.  2. Click Insert to insert the new NOAM server into servers table (the first or server).

STEP #	Procedure	Description																																			
		<p>Attribute Value</p> <table border="1" data-bbox="507 276 1367 819"> <tr> <td data-bbox="507 276 780 382">Hostname *</td> <td data-bbox="780 276 1367 382"></td> </tr> <tr> <td data-bbox="507 382 780 487">Role *</td> <td data-bbox="780 382 1367 487"> - Select Role - <input type="button" value="▼"/> </td> </tr> <tr> <td data-bbox="507 487 780 593">System ID</td> <td data-bbox="780 487 1367 593"></td> </tr> <tr> <td data-bbox="507 593 780 656">Hardware Profile</td> <td data-bbox="780 593 1367 656"> DSR Guest <input type="button" value="▼"/> </td> </tr> <tr> <td data-bbox="507 656 780 762">Network Element Name *</td> <td data-bbox="780 656 1367 762"> - Unassigned - <input type="button" value="▼"/> </td> </tr> <tr> <td data-bbox="507 762 780 819">Location</td> <td data-bbox="780 762 1367 819"></td> </tr> </table> <p>3. Fill in the fields as follows:</p> <p>Hostname: <Hostname> Role: NETWORK OAM&P System ID: <Site System ID> Hardware Profile: DSR Guest Network Element Name: [Select NE from list]</p> <p>The network interface fields are now available with selection choices based on the chosen hardware profile and network element</p> <table border="1" data-bbox="507 1142 1388 1353"> <tr> <td colspan="3" data-bbox="507 1142 1388 1174">OAM Interfaces [At least one interface is required.]:</td> </tr> <tr> <td data-bbox="507 1174 780 1205">Network</td> <td data-bbox="780 1174 1106 1205">IP Address</td> <td data-bbox="1106 1174 1388 1205">Interface</td> </tr> <tr> <td data-bbox="507 1205 780 1248">INTERNALXMI (10.196.227.0/24)</td> <td data-bbox="780 1205 1106 1248">10.196.227.21</td> <td data-bbox="1106 1205 1388 1248"> eth0 <input type="button" value="▼"/> <input type="checkbox" value="VLAN (6)"/> </td> </tr> <tr> <td data-bbox="507 1248 780 1290">INTERNALIMI (169.254.1.0/24)</td> <td data-bbox="780 1248 1106 1290">169.254.1.21</td> <td data-bbox="1106 1248 1388 1290"> eth1 <input type="button" value="▼"/> <input type="checkbox" value="VLAN (3)"/> </td> </tr> <tr> <td data-bbox="507 1332 567 1353">Ok</td> <td data-bbox="584 1332 644 1353">Apply</td> <td data-bbox="644 1332 747 1353">Cancel</td> </tr> </table> <p>4. Fill in the server IP addresses for the XMI network. Select ethX for the interface. Leave the VLAN checkbox unchecked.</p> <p>5. Fill in the server IP addresses for the IMI network. Select ethX for the interface. Leave the VLAN checkbox unchecked.</p> <p>6. Add the following NTP servers:</p> <table border="1" data-bbox="518 1586 1323 1776"> <tr> <th data-bbox="518 1586 943 1628">NTP Server</th> <th data-bbox="943 1586 1323 1628">Preferred?</th> </tr> <tr> <td data-bbox="518 1628 943 1670">Valid NTP Server</td> <td data-bbox="943 1628 1323 1670">Yes</td> </tr> <tr> <td data-bbox="518 1670 943 1712">Valid NTP Server</td> <td data-bbox="943 1670 1323 1712">No</td> </tr> <tr> <td data-bbox="518 1712 943 1776">Valid NTP Server</td> <td data-bbox="943 1712 1323 1776">No</td> </tr> </table> <p>7. Click OK when you have completed entering all the server data.</p> <p>Note: Properly configure the NTP on the controller node to reference lower</p>	Hostname *		Role *	- Select Role - <input type="button" value="▼"/>	System ID		Hardware Profile	DSR Guest <input type="button" value="▼"/>	Network Element Name *	- Unassigned - <input type="button" value="▼"/>	Location		OAM Interfaces [At least one interface is required.]:			Network	IP Address	Interface	INTERNALXMI (10.196.227.0/24)	10.196.227.21	eth0 <input type="button" value="▼"/> <input type="checkbox" value="VLAN (6)"/>	INTERNALIMI (169.254.1.0/24)	169.254.1.21	eth1 <input type="button" value="▼"/> <input type="checkbox" value="VLAN (3)"/>	Ok	Apply	Cancel	NTP Server	Preferred?	Valid NTP Server	Yes	Valid NTP Server	No	Valid NTP Server	No
Hostname *																																					
Role *	- Select Role - <input type="button" value="▼"/>																																				
System ID																																					
Hardware Profile	DSR Guest <input type="button" value="▼"/>																																				
Network Element Name *	- Unassigned - <input type="button" value="▼"/>																																				
Location																																					
OAM Interfaces [At least one interface is required.]:																																					
Network	IP Address	Interface																																			
INTERNALXMI (10.196.227.0/24)	10.196.227.21	eth0 <input type="button" value="▼"/> <input type="checkbox" value="VLAN (6)"/>																																			
INTERNALIMI (169.254.1.0/24)	169.254.1.21	eth1 <input type="button" value="▼"/> <input type="checkbox" value="VLAN (3)"/>																																			
Ok	Apply	Cancel																																			
NTP Server	Preferred?																																				
Valid NTP Server	Yes																																				
Valid NTP Server	No																																				
Valid NTP Server	No																																				


STEP #	Procedure	Description
		stratum NTP servers.
4. <input type="checkbox"/>	Primary NOAM VIP GUI: Export the initial configuration	<p>1. Navigate to Configuration > Servers.</p>  <p>2. From the GUI screen, select the NOAM server and click Export to generate the initial configuration data for that server. Go to the Info tab to confirm the file has been created.</p> <p>Buttons: Insert, Edit, Delete, Export, Report</p>
5. <input type="checkbox"/>	Primary NOAM Server: Copy configuration file from the 1 st Primary NOAM server to the 1 st NOAM at the DR-NOAM server	<p>1. Obtain a terminal window to the Primary NOAM server, logging in as the admusr user.</p> <p>2. Copy the configuration file created in the previous step from the /var/TKLC/db/filemgmt directory on the 1st NOAM at the DR-NOAM server in the /var/tmp directory. The configuration file has a filename like TKLCConfigData.<hostname>.sh. The following is an example:</p> <pre>\$ sudo cp /var/TKLC/db/filemgmt/TKLCConfigData.<hostname>.sh /var/tmp/TKLCConfigData.sh</pre>
6. <input type="checkbox"/>	First DR NOAM Server: Wait for configuration to complete	<p>The automatic configuration daemon looks for the file named TKLCConfigData.sh in the /var/tmp directory, implements the configuration in the file, and prompts the user to reboot the server.</p> <p>If you are on the console, wait to be prompted to reboot the server, but DO NOT reboot the server, it is rebooted later in this procedure.</p> <p>Verify the script completed successfully by checking the following file.</p> <pre>\$ sudo cat /var/TKLC/appw/logs/Process/install.log</pre> <p>Note: Ignore the warning about removing the USB key since no USB key is present. No response occurs until the reboot prompt is issued.</p>
7. <input type="checkbox"/>	First DR NOAM Server: Reboot the server	<p>Obtain a terminal window to the 1st DR NOAM server, logging in as the admusr user.</p> <pre>\$ sudo init 6</pre> <p>Wait for server to reboot.</p>






STEP #	Procedure	Description
8. <input type="checkbox"/>	First DR NOAM Server: Verify server health	<ol style="list-style-type: none"> 1. Obtain a terminal window to the 1st DR NOAM server, logging in as the admusr user. 2. Execute the following command as admusr and make sure that no errors are returned: <pre>\$ sudo syscheck Running modules in class hardware... OK Running modules in class disk... OK Running modules in class net... OK Running modules in class system... OK Running modules in class proc... OK LOG LOCATION: /var/TKLC/log/syscheck/fail_log</pre>

Procedure 18. Configure the DR NOAM Server Group (Optional)

STEP #	Procedure	Description
		<p>This procedure configures the DR NOAM server group.</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>



1. <input type="checkbox"/>	Primary NOAM VIP GUI: Login	<ol style="list-style-type: none"> 1. Establish a GUI session on the primary NOAM server by using the XMI IP address of the first NOAM server. Open the web browser and type http://<NO1_XMI_IP_Address> as the URL. 2. Login as the guiadmin user. If prompted by a security warning, click Continue to this Website to proceed.
--------------------------------	------------------------------------	--


STEP #	Procedure	Description																					
2. <input type="checkbox"/>	Primary NOAM VIP GUI: Enter DR NOAM server group data	<p>1. Using the GUI session on the primary NOAM server, navigate to Configuration > Server Groups.</p>  <p>2. Click Insert and fill in the following fields:</p> <p>Server Group Name: [Enter Server Group Name] Level: A Parent: None Function: DSR (Active/Standby Pair) WAN Replication Connection Count: Use Default Value</p> <p>Adding new server group</p> <table border="1" data-bbox="505 971 1077 1436"> <thead> <tr> <th data-bbox="505 971 783 1013">Field</th> <th data-bbox="783 971 995 1013">Value</th> <th data-bbox="995 971 1077 1013">Desc</th> </tr> </thead> <tbody> <tr> <td data-bbox="505 1013 783 1098">Server Group Name *</td> <td data-bbox="783 1013 995 1098">ZombieNOAM</td> <td data-bbox="995 1013 1077 1098">Uniqu</td> </tr> <tr> <td data-bbox="505 1098 783 1182">Level *</td> <td data-bbox="783 1098 995 1182">A</td> <td data-bbox="995 1098 1077 1182">Select</td> </tr> <tr> <td data-bbox="505 1182 783 1246">Parent *</td> <td data-bbox="783 1182 995 1246">NONE</td> <td data-bbox="995 1182 1077 1246">Select</td> </tr> <tr> <td data-bbox="505 1246 783 1330">Function *</td> <td data-bbox="783 1246 995 1330">DSR (active/standby pair)</td> <td data-bbox="995 1246 1077 1330">Select</td> </tr> <tr> <td data-bbox="505 1330 783 1415">WAN Replication Connection Count</td> <td data-bbox="783 1330 995 1415">1</td> <td data-bbox="995 1330 1077 1415">Specify</td> </tr> <tr> <td data-bbox="505 1415 783 1436"></td> <td data-bbox="783 1415 995 1436">Ok</td> <td data-bbox="995 1415 1077 1436">Apply</td> </tr> </tbody> </table> <p>3. Click OK when all fields are filled in.</p>	Field	Value	Desc	Server Group Name *	ZombieNOAM	Uniqu	Level *	A	Select	Parent *	NONE	Select	Function *	DSR (active/standby pair)	Select	WAN Replication Connection Count	1	Specify		Ok	Apply
Field	Value	Desc																					
Server Group Name *	ZombieNOAM	Uniqu																					
Level *	A	Select																					
Parent *	NONE	Select																					
Function *	DSR (active/standby pair)	Select																					
WAN Replication Connection Count	1	Specify																					
	Ok	Apply																					

STEP #	Procedure	Description						
3.	<input type="checkbox"/> Primary NOAM VIP GUI: Edit the DR NOAM server group	<p>1. Navigate to Configuration > Server Groups.</p>  <p>2. Select the new server group and click Edit.</p>  <p>3. Select the network element that represents the DR NOAM.</p> <table border="1" data-bbox="518 804 1400 931"> <thead> <tr> <th data-bbox="518 804 829 846">Server</th> <th data-bbox="829 804 1171 846">SG Inclusion</th> <th data-bbox="1171 804 1400 846">Preferred HA Role</th> </tr> </thead> <tbody> <tr> <td data-bbox="518 889 829 931">DSRDRNO1</td> <td data-bbox="829 889 1171 931"> <input checked="" type="checkbox"/> Include in SG </td> <td data-bbox="1171 889 1400 931"> <input type="checkbox"/> Prefer server as spare </td> </tr> </tbody> </table> <p>4. In the portion of the screen that lists the servers for the server group, find the NOAM server being configured. Mark the Include in SG checkbox.</p> <p>5. Leave other boxes unchecked.</p> <p>6. Click OK.</p>	Server	SG Inclusion	Preferred HA Role	DSRDRNO1	<input checked="" type="checkbox"/> Include in SG	<input type="checkbox"/> Prefer server as spare
Server	SG Inclusion	Preferred HA Role						
DSRDRNO1	<input checked="" type="checkbox"/> Include in SG	<input type="checkbox"/> Prefer server as spare						
4.	<input type="checkbox"/> Primary NOAM VIP GUI: Restart 1 st DR NOAM VM	<p>1. From the NOAM GUI, navigate to Status & Manage > Server.</p>  <p>2. Select the first NOAM server. Click Restart.</p>  <p>3. Click OK on the confirmation screen and wait for restart to complete.</p> 						

Procedure 19. Configure the Second DR NOAM Server (Optional)

STEP #	Procedure	Description



STEP #	Procedure	Description										
<p>This procedure configures the second DR NOAM server.</p>												
<p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p>												
<p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>												
1. <input type="checkbox"/>	Primary NOAM VIP GUI: Login	<ol style="list-style-type: none"> 1. If not already done, establish a GUI session on the first NOAM server by using the XMI IP address of the first NOAM server. Open the web browser and type http://<NOAM1_XMI_IP_Address> as the URL. 2. Login as the guiadmin user. 										
2. <input type="checkbox"/>	Primary NOAM VIP GUI: Insert the 2nd DR NOAM VM	<ol style="list-style-type: none"> 1. Navigate to Main Menu > Configuration > Servers.  2. Click Insert to insert the new NOAM server into servers table (the first or second server).  <p>3. Fill in the fields as follows:</p> <table> <tbody> <tr> <td>Hostname:</td> <td><Hostname></td> </tr> <tr> <td>Role:</td> <td>NETWORK_OAM&P</td> </tr> <tr> <td>System ID:</td> <td><Site System ID></td> </tr> <tr> <td>Hardware Profile:</td> <td>DSR_Guest</td> </tr> <tr> <td>Network Element Name:</td> <td>[Choose NE from list]</td> </tr> </tbody> </table> <p>The network interface fields are now available with selection choices based on the chosen hardware profile and network element.</p> 	Hostname:	<Hostname>	Role:	NETWORK_OAM&P	System ID:	<Site System ID>	Hardware Profile:	DSR_Guest	Network Element Name:	[Choose NE from list]
Hostname:	<Hostname>											
Role:	NETWORK_OAM&P											
System ID:	<Site System ID>											
Hardware Profile:	DSR_Guest											
Network Element Name:	[Choose NE from list]											


STEP #	Procedure	Description																	
		<p>OAM Interfaces [At least one interface is required.]:</p> <table border="1" data-bbox="507 291 1388 487"> <thead> <tr> <th data-bbox="507 297 736 325">Network</th><th data-bbox="736 297 1095 325">IP Address</th><th data-bbox="1095 297 1388 325">Interface</th></tr> </thead> <tbody> <tr> <td data-bbox="507 340 736 367">INTERNALXMI (10.196.227.0/24)</td><td data-bbox="736 340 1095 367">10.196.227.21</td><td data-bbox="1095 340 1388 367">eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (6)</td></tr> <tr> <td data-bbox="507 382 736 409">INTERNALIMI (169.254.1.0/24)</td><td data-bbox="736 382 1095 409">169.254.1.21</td><td data-bbox="1095 382 1388 409">eth1 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (3)</td></tr> </tbody> </table> <p data-bbox="507 445 736 473">Ok Apply Cancel</p> <ol style="list-style-type: none"> <li data-bbox="502 502 1383 566">4. Fill in the server IP addresses for the XMI network. Select ethX for the interface. Leave the VLAN checkbox unmarked. <li data-bbox="502 580 1383 644">5. Fill in the server IP addresses for the IMI network. Select ethX for the interface. Leave the VLAN checkbox unmarked. <li data-bbox="502 658 915 686">6. Add the following NTP servers: <table border="1" data-bbox="518 699 1393 895"> <thead> <tr> <th data-bbox="518 699 943 726">NTP Server</th><th data-bbox="943 699 1393 726">Preferred?</th></tr> </thead> <tbody> <tr> <td data-bbox="518 741 943 768">Valid NTP Server</td><td data-bbox="943 741 1393 768">Yes</td></tr> <tr> <td data-bbox="518 783 943 811">Valid NTP Server</td><td data-bbox="943 783 1393 811">No</td></tr> <tr> <td data-bbox="518 825 943 853">Valid NTP Server</td><td data-bbox="943 825 1393 853">No</td></tr> </tbody> </table> <ol style="list-style-type: none"> <li data-bbox="502 910 1307 937">7. Click OK when you have completed entering all the server data. <p>Note: Properly configure the NTP on the controller node to reference lower stratum NTP servers.</p>	Network	IP Address	Interface	INTERNALXMI (10.196.227.0/24)	10.196.227.21	eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (6)	INTERNALIMI (169.254.1.0/24)	169.254.1.21	eth1 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (3)	NTP Server	Preferred?	Valid NTP Server	Yes	Valid NTP Server	No	Valid NTP Server	No
Network	IP Address	Interface																	
INTERNALXMI (10.196.227.0/24)	10.196.227.21	eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (6)																	
INTERNALIMI (169.254.1.0/24)	169.254.1.21	eth1 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (3)																	
NTP Server	Preferred?																		
Valid NTP Server	Yes																		
Valid NTP Server	No																		
Valid NTP Server	No																		
3. <input type="checkbox"/>	Primary NOAM VIP GUI: Export the initial configuration	<ol style="list-style-type: none"> <li data-bbox="502 1036 997 1064">1. Navigate to Configuration > Servers.  <ol style="list-style-type: none"> <li data-bbox="502 1094 997 1438">2. From the GUI screen, select the server just configured and click Export to generate the initial configuration data for that server. <p data-bbox="507 1459 915 1507">Insert Edit Delete Export Report</p> <ol style="list-style-type: none"> <li data-bbox="502 1522 1188 1550">3. Go to the Info tab to confirm the file has been created. 																	
4. <input type="checkbox"/>	Primary NOAM: Copy configuration file to 2 nd DR NOAM server	<ol style="list-style-type: none"> <li data-bbox="502 1564 1356 1592">1. Obtain a terminal session to the primary NOAM as the admusr user. <li data-bbox="502 1607 1372 1670">2. Login as the admusr user to the NOAM1 shell and issue the following commands: <pre data-bbox="540 1691 1351 1790"> \$ sudo scp /var/TKLC/db/filemgmt/TKLCConfigData.<hostname>.sh admusr@<ipaddr>:/var/tmp/TKLCConfigData.sh </pre> <p>Note: ipaddr is the IP address of DR NOAM assigned to its ethx interface associated with the XMI network.</p>																	



STEP #	Procedure	Description
5. <input type="checkbox"/>	Second DR NOAM Server: Wait for configuration to complete	<ol style="list-style-type: none"> 1. Obtain a terminal session to the 2nd DR NOAM as the admusr user. The automatic configuration daemon looks for the file named TKLCConfigData.sh in the /var/tmp directory, implements the configuration in the file, and prompts the user to reboot the server. 2. If you are on the console, wait to be prompted to reboot the server, but DO NOT reboot the server, it is rebooted later in this procedure. 3. Verify script completed successfully by checking the following file. <code>\$ sudo cat /var/TKLC/appw/logs/Process/install.log</code> Note: Ignore the warning about removing the USB key since no USB key is present.
6. <input type="checkbox"/>	Second DR NOAM Server: Reboot the server	<p>Obtain a terminal session to the 2nd DR NOAM as the admusr user.</p> <code>\$ sudo init 6</code> <p>Wait for server to reboot.</p>
7. <input type="checkbox"/>	Second DR NO Server: Verify server health	<ol style="list-style-type: none"> 1. Obtain a terminal session to the 2nd DR NOAM as the admusr user. 2. Execute the following command as super-user and make sure no errors are returned: <code>\$ sudo syscheck</code> <code>Running modules in class hardware...</code> <code>OK</code> <code>Running modules in class disk...</code> <code>OK</code> <code>Running modules in class net...</code> <code>OK</code> <code>Running modules in class system...</code> <code>OK</code> <code>Running modules in class proc...</code> <code>OK</code> <code>LOG LOCATION: /var/TKLC/log/syscheck/fail_log</code>

Procedure 20. Complete Configuring the DR NOAM Server Group (Optional)

STEP #	Procedure	Description
		<p>This procedure finishes configuring the DR NOAM Server Group.</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>


STEP #	Procedure	Description									
1. <input type="checkbox"/>	PRIMARY NOAM VIP GUI: Edit the DR NOAM server group data	<p>1. From the GUI session on the primary NOAM server, navigate to Configuration > Server Groups.</p>  <p>2. Select the NOAM server group and click Edit.</p>  <p>3. Add the second NOAM server to the server group by marking the Include in SG checkbox for the second NOAM server. Click Apply.</p> <table border="1" data-bbox="514 855 1395 1003"> <thead> <tr> <th data-bbox="514 855 840 897">Server</th> <th data-bbox="840 855 1166 897">SG Inclusion</th> <th data-bbox="1166 855 1395 897">Preferred HA Role</th> </tr> </thead> <tbody> <tr> <td data-bbox="514 897 840 939">DSRDRN01</td> <td data-bbox="840 897 1166 939"><input checked="" type="checkbox"/> Include in SG</td> <td data-bbox="1166 897 1395 939"><input type="checkbox"/> Prefer server as spare</td> </tr> <tr> <td data-bbox="514 939 840 982">DSRDRN02</td> <td data-bbox="840 939 1166 982"><input checked="" type="checkbox"/> Include in SG</td> <td data-bbox="1166 939 1395 982"><input type="checkbox"/> Prefer server as spare</td> </tr> </tbody> </table> <p>4. Click Add to add an NOAM VIP. Type the VIP Address and click OK.</p> 	Server	SG Inclusion	Preferred HA Role	DSRDRN01	<input checked="" type="checkbox"/> Include in SG	<input type="checkbox"/> Prefer server as spare	DSRDRN02	<input checked="" type="checkbox"/> Include in SG	<input type="checkbox"/> Prefer server as spare
Server	SG Inclusion	Preferred HA Role									
DSRDRN01	<input checked="" type="checkbox"/> Include in SG	<input type="checkbox"/> Prefer server as spare									
DSRDRN02	<input checked="" type="checkbox"/> Include in SG	<input type="checkbox"/> Prefer server as spare									


STEP #	Procedure	Description
2. <input type="checkbox"/>	Primary NOAM VIP GUI: Establish GUI Session on the NOAM VIP	<p>Establish a GUI session on the primary NOAM by using the NOAM VIP address. Login as the guiadmin user.</p>  <p>Welcome to the Oracle System Login.</p> <p>This application is designed to work with most modern HTML5 compliant browsers and uses both JavaScript and cookies. Please refer to the Oracle Software Web Browser Support Policy for details.</p> <p>Unauthorized access is prohibited.</p> <p><small>Oracle and Java are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.</small></p> <p><small>Copyright © 2010, 2016, Oracle and/or its affiliates. All rights reserved.</small></p>
3. <input type="checkbox"/>	Primary NOAM VIP GUI: Wait for Remote Database Alarm to Clear	<p>Wait for the alarm ID 10200 Remote Database re-initialization in progress to be cleared before proceeding (Alarms & Events > View Active).</p> 

STEP #	Procedure	Description						
4. <input type="checkbox"/>	Primary NOAM VIP GUI: Restart 2 nd DR NOAM VM	<ol style="list-style-type: none"> 1. Navigate to Status & Manage > Server and select the second DR NOAM server.  2. Click Restart.  3. Answer OK on the confirmation screen.  <p>Wait approximately 3-5 minutes before proceeding to allow the system to stabilize indicated by having the Appl State as Enabled.</p>						
5. <input type="checkbox"/>	Primary NOAM: Modify DSR OAM process	Establish an SSH session to the primary NOAM, login as the admusr user. Execute the following commands: <ol style="list-style-type: none"> 1. Retrieve the cluster ID of the DR-NOAM: <code>\$ sudo iqt -NodeID TopologyMapping where "NodeID='<DR_NOAM_Host_Name>'"</code> <table border="1" data-bbox="543 1273 1245 1358"> <tr> <th>Server_ID</th> <th>NodeID</th> <th>ClusterID</th> </tr> <tr> <td>1</td> <td>Oahu-DSR-DR-NOAM-2</td> <td>A1055</td> </tr> </table> 2. Execute the following command to start the DSR OAM process on the DR-NOAM. <code>\$ echo "<clusterID> DSROAM_Proc Yes" iload -ha -xun -fcluster -fresource -foptional HaClusterResourceCfg</code> 	Server_ID	NodeID	ClusterID	1	Oahu-DSR-DR-NOAM-2	A1055
Server_ID	NodeID	ClusterID						
1	Oahu-DSR-DR-NOAM-2	A1055						

Procedure 21. Configure the SOAM NE




STEP #	Procedure	Description
		This procedure configures the SOAM network element. Check off (\) each step as it is completed. Boxes have been provided for this purpose under each step number. If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.

STEP #	Procedure	Description
1. <input type="checkbox"/>	Primary NOAM VIP GUI: Establish GUI session on the NOAM VIP	<p>If needed, establish a GUI session on the NOAM by using the NOAM VIP address. Login as the guiadmin user.</p>  <p>Mon Jul 11 13:59:37 2016 EDT</p> <p>Log In Enter your username and password to log in</p> <p>Username: <input type="text"/></p> <p>Password: <input type="password"/></p> <p><input type="checkbox"/> Change password</p> <p>Log In</p> <p>Welcome to the Oracle System Login.</p> <p>This application is designed to work with most modern HTML5 compliant browsers and uses both JavaScript and cookies. Please refer to the Oracle Software Web Browser Support Policy for details.</p> <p>Unauthorized access is prohibited.</p> <hr/> <p><i>Oracle and Java are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.</i></p> <p>Copyright © 2010, 2016, Oracle and/or its affiliates. All rights reserved.</p>



STEP #	Procedure	Description
2. <input type="checkbox"/>	Primary NOAM VIP GUI: Create the SOAM network element using an XML file	<p>Make sure to have an SOAM network element XML file available on the PC running the web browser. The SOAM network element XML file is similar to what was created and used in Procedure 13, but defines the SOAM network element.</p> <p>Refer to Appendix A Sample Network Element and Hardware Profiles for a sample network element xml file</p> <p>1. Navigate to Configuration > Networking > Networks.</p>  <p>2. Click Browse and type the path and name of the SOAM network XML file.</p> <p>To create a new Network Element, upload a valid configuration file:</p> <p><input type="button" value="Browse..."/> zombieSOAM.xml <input type="button" value="Upload File"/></p> <p>Copyright © 2010, 2016, Oracle and/or its affiliates. All rights reserved.</p> <p>3. Click Upload to upload the XML file and configure the SOAM network element.</p> 

Procedure 22. Configure the SOAM Servers

STEP #	Procedure	Description
		<p>This procedure configures the SOAM servers.</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>

STEP #	Procedure	Description
1. <input type="checkbox"/>	Primary NOAM VIP GUI: Establish GUI session on the NOAM VIP	<p>If needed, establish a GUI session on the NOAM by using the NOAM VIP address. Login as the guiadmin user.</p>  <p>Welcome to the Oracle System Login.</p> <p>This application is designed to work with most modern HTML5 compliant browsers and uses both JavaScript and cookies. Please refer to the Oracle Software Web Browser Support Policy for details.</p> <p>Unauthorized access is prohibited.</p> <p>Oracle and Java are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.</p> <p>Copyright © 2010, 2018, Oracle and/or its affiliates. All rights reserved.</p>
2. <input type="checkbox"/>	Primary NOAM VIP GUI: Insert the 1 st SOAM server	<ol style="list-style-type: none"> 1. Navigate to Configuration > Server.  <ol style="list-style-type: none"> 2. Click Insert to insert the new SOAM server into servers table. 


STEP #	Procedure	Description																																		
		<p>3. Fill in the fields as follows:</p> <p>Hostname: <SO1-Hostname> Role: SYSTEM OAM System ID: <Site System ID> Hardware Profile: DSR Guest Network Element Name: [Choose NE from list]</p> <table border="1" data-bbox="535 502 1367 1015"> <thead> <tr> <th data-bbox="535 502 780 555">Attribute</th><th data-bbox="780 502 1367 555">Value</th></tr> </thead> <tbody> <tr> <td data-bbox="535 555 780 618">Hostname *</td><td data-bbox="780 555 1367 618"></td></tr> <tr> <td data-bbox="535 618 780 682">Role *</td><td data-bbox="780 618 1367 682">- Select Role -</td></tr> <tr> <td data-bbox="535 682 780 745">System ID</td><td data-bbox="780 682 1367 745"></td></tr> <tr> <td data-bbox="535 745 780 808">Hardware Profile</td><td data-bbox="780 745 1367 808">DSR Guest</td></tr> <tr> <td data-bbox="535 808 780 872">Network Element Name *</td><td data-bbox="780 808 1367 872">- Unassigned -</td></tr> <tr> <td data-bbox="535 872 780 1015">Location</td><td data-bbox="780 872 1367 1015"></td></tr> </tbody> </table> <p>The network interface fields are now available with selection choices based on the chosen hardware profile and network element.</p> <table border="1" data-bbox="491 1100 1405 1353"> <thead> <tr> <th colspan="3" data-bbox="491 1100 1405 1132">OAM Interfaces [At least one interface is required.]:</th></tr> <tr> <th data-bbox="491 1132 682 1163">Network</th><th data-bbox="682 1132 1106 1163">IP Address</th><th data-bbox="1106 1132 1405 1163">Interface</th></tr> </thead> <tbody> <tr> <td data-bbox="491 1163 682 1205">INTERNALXMI (10.196.227.0/24)</td><td data-bbox="682 1163 1106 1205">10.196.227.23</td><td data-bbox="1106 1163 1405 1205">eth0 <input checked="" type="checkbox"/> VLAN (6)</td></tr> <tr> <td data-bbox="491 1205 682 1248">INTERNALIMI (169.254.1.0/24)</td><td data-bbox="682 1205 1106 1248">169.254.1.23</td><td data-bbox="1106 1205 1405 1248">eth1 <input checked="" type="checkbox"/> VLAN (3)</td></tr> </tbody> </table> <p data-bbox="491 1326 719 1353">Ok Apply Cancel</p> <p>4. Fill in the server IP addresses for the XMI network. Select ethX for the interface. Leave the VLAN checkbox unmarked.</p> <p>5. Fill in the server IP addresses for the IMI network. Select ethX for the interface. Leave the VLAN checkbox unmarked.</p> <p>6. Add the following NTP servers:</p> <table border="1" data-bbox="502 1586 1383 1776"> <thead> <tr> <th data-bbox="502 1586 931 1638">NTP Server</th><th data-bbox="931 1586 1383 1638">Preferred?</th></tr> </thead> <tbody> <tr> <td data-bbox="502 1638 931 1681">Valid NTP Server</td><td data-bbox="931 1638 1383 1681">Yes</td></tr> <tr> <td data-bbox="502 1681 931 1723">Valid NTP Server</td><td data-bbox="931 1681 1383 1723">No</td></tr> <tr> <td data-bbox="502 1723 931 1776">Valid NTP Server</td><td data-bbox="931 1723 1383 1776">No</td></tr> </tbody> </table> <p>7. Click OK when you have completed entering the server data.</p> <p>Note Properly configure the NTP on the controller node to reference lower</p>	Attribute	Value	Hostname *		Role *	- Select Role -	System ID		Hardware Profile	DSR Guest	Network Element Name *	- Unassigned -	Location		OAM Interfaces [At least one interface is required.]:			Network	IP Address	Interface	INTERNALXMI (10.196.227.0/24)	10.196.227.23	eth0 <input checked="" type="checkbox"/> VLAN (6)	INTERNALIMI (169.254.1.0/24)	169.254.1.23	eth1 <input checked="" type="checkbox"/> VLAN (3)	NTP Server	Preferred?	Valid NTP Server	Yes	Valid NTP Server	No	Valid NTP Server	No
Attribute	Value																																			
Hostname *																																				
Role *	- Select Role -																																			
System ID																																				
Hardware Profile	DSR Guest																																			
Network Element Name *	- Unassigned -																																			
Location																																				
OAM Interfaces [At least one interface is required.]:																																				
Network	IP Address	Interface																																		
INTERNALXMI (10.196.227.0/24)	10.196.227.23	eth0 <input checked="" type="checkbox"/> VLAN (6)																																		
INTERNALIMI (169.254.1.0/24)	169.254.1.23	eth1 <input checked="" type="checkbox"/> VLAN (3)																																		
NTP Server	Preferred?																																			
Valid NTP Server	Yes																																			
Valid NTP Server	No																																			
Valid NTP Server	No																																			




STEP #	Procedure	Description
		stratum NTP servers.
3. <input type="checkbox"/>	Primary NOAM VIP GUI: Export the initial configuration	<ol style="list-style-type: none"> 1. Navigate to Configuration > Server.  2. From the GUI screen, select the desired server and click Export to generate the initial configuration data for that server.  3. Go to the Info tab to confirm the file has been created.
4. <input type="checkbox"/>	Primary NOAM: Copy configuration file to the 1 st SOAM server	Login as the admusr user to the NOAM1 shell and issue the commands: <code>\$ sudo scp /var/TKLC/db/filemgmt/TKLCConfigData.<hostname>.sh admusr@<ipaddr>:/var/tmp/TKLCConfigData.sh</code>
5. <input type="checkbox"/>	First SOAM Server: Wait for configuration to complete	<ol style="list-style-type: none"> 1. Obtain a terminal session on the 1st SOAM as the admusr user. The automatic configuration daemon looks for the file named TKLCConfigData.sh in the /var/tmp directory, implements the configuration in the file, and prompts the user to reboot the server. 2. If you are on the console wait to be prompted to reboot the server, but DO NOT reboot the server, it is rebooted later in this procedure. 3. Verify script completed successfully by checking the following file. <code>\$ sudo cat /var/TKLC/appw/logs/Process/install.log</code> <p>Note: Ignore the warning about removing the USB key since no USB key is present.</p>



STEP #	Procedure	Description
6. <input type="checkbox"/>	First SOAM Server: Reboot the server	<p>Obtain a terminal session to the 1st SOAM as the admusr user.</p> <pre>\$ sudo init 6</pre> <p>Wait for server to reboot.</p>
7. <input type="checkbox"/>	First SOAM Server: Verify Server Health	<ol style="list-style-type: none"> After the system reboots, login again as the admusr user. Execute the following command and make sure that no errors are returned: <pre># sudo syscheck</pre> <pre>Running modules in class hardware...</pre> <pre>OK</pre> <pre>Running modules in class disk...</pre> <pre>OK</pre> <pre>Running modules in class net...</pre> <pre>OK</pre> <pre>Running modules in class system...</pre> <pre>OK</pre> <pre>Running modules in class proc...</pre> <pre>OK</pre> <pre>LOG LOCATION: /var/TKLC/log/syscheck/fail_log</pre>
8. <input type="checkbox"/>	Insert and Configure the 2 nd SOAM server, repeat steps 1 through 7 for 2 nd SOAM	<ol style="list-style-type: none"> Repeat this procedure to insert and configure the 2nd SOAM server. Enter the network data for the 2nd SOAM server, transfer the TKLCConfigData file to the 2nd SOAM server, and reboot the 2nd SOAM server when asked at a terminal window. Wait approximately 5 minutes for the 2nd SOAM server to reboot. <p>Note: For DSR mated sites, repeat this step for additional/spare SOAM server for mated site.</p>


Procedure 23. Configure the SOAM Server Group

STEP #	Procedure	Description
--------	-----------	-------------

STEP #	Procedure	Description														
This procedure configures the SOAM server group.																
Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.																
If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.																
1. <input type="checkbox"/>	Primary NOAM VIP GUI: Enter SOAM server group data	<ol style="list-style-type: none"> From the GUI session on the NOAM VIP address, navigate to Configuration > Server Groups.  Click Insert and add the SOAM server group name along with the values for the following fields: <table border="1" data-bbox="489 908 881 971"> <tr> <td>Insert</td> <td>Edit</td> <td>Delete</td> <td>Report</td> </tr> </table> <table> <tr> <td>Name:</td> <td>[Enter Server Group Name]</td> </tr> <tr> <td>Level:</td> <td>B</td> </tr> <tr> <td>Parent:</td> <td>[Select the NOAM Server Group]</td> </tr> <tr> <td>Function:</td> <td>DSR (Active/Standby Pair)</td> </tr> <tr> <td>WAN Replication Connection Count:</td> <td>Use Default Value</td> </tr> </table> Click OK when all fields are filled. <p>Note: For DSR mated sites, repeat this step for additional SOAM server groups where the preferred SOAM spares may be entered before the active/standby SOAMs.</p>	Insert	Edit	Delete	Report	Name:	[Enter Server Group Name]	Level:	B	Parent:	[Select the NOAM Server Group]	Function:	DSR (Active/Standby Pair)	WAN Replication Connection Count:	Use Default Value
Insert	Edit	Delete	Report													
Name:	[Enter Server Group Name]															
Level:	B															
Parent:	[Select the NOAM Server Group]															
Function:	DSR (Active/Standby Pair)															
WAN Replication Connection Count:	Use Default Value															

STEP #	Procedure	Description									
2. <input type="checkbox"/>	Primary NOAM VIP GUI: Edit the SOAM server group and add VIP	<p>1. Navigate to Configuration > Server Groups.</p>  <p>2. Select the new SOAM server group and click Edit.</p> <table border="1" data-bbox="497 686 1439 834"> <thead> <tr> <th data-bbox="497 686 832 728">Server</th><th data-bbox="832 686 1191 728">SG Inclusion</th><th data-bbox="1191 686 1439 728">Preferred HA Role</th></tr> </thead> <tbody> <tr> <td data-bbox="497 728 832 770">SO1</td><td data-bbox="832 728 1191 770"><input checked="" type="checkbox"/> Include in SG</td><td data-bbox="1191 728 1439 770"><input type="checkbox"/> Prefer server as spare</td></tr> <tr> <td data-bbox="497 770 832 834">SO2</td><td data-bbox="832 770 1191 834"><input checked="" type="checkbox"/> Include in SG</td><td data-bbox="1191 770 1439 834"><input type="checkbox"/> Prefer server as spare</td></tr> </tbody> </table> <p>3. Add both SOAM servers to the server group primary site by marking the Include in SG checkbox.</p> <p>4. Click Apply.</p>	Server	SG Inclusion	Preferred HA Role	SO1	<input checked="" type="checkbox"/> Include in SG	<input type="checkbox"/> Prefer server as spare	SO2	<input checked="" type="checkbox"/> Include in SG	<input type="checkbox"/> Prefer server as spare
Server	SG Inclusion	Preferred HA Role									
SO1	<input checked="" type="checkbox"/> Include in SG	<input type="checkbox"/> Prefer server as spare									
SO2	<input checked="" type="checkbox"/> Include in SG	<input type="checkbox"/> Prefer server as spare									
3. <input type="checkbox"/>	Primary NOAM VIP GUI: Add the SOAM VIP	<p>1. Navigate to Configuration > Server Groups.</p>  <p>2. Select the new SOAM server group and click Edit.</p> <p>3. Click Add to add a SOAM VIP. Type the VIP Address and click OK.</p> 									

STEP #	Procedure	Description									
4. <input type="checkbox"/>	Primary NOAM VIP GUI: Edit the SOAM server group and add preferred spares for site redundancy (Optional)	<p>If the two-site redundancy feature is wanted for the SOAM server group, add an SOAM server located in its server group secondary site by marking the Include in SG and Preferred Spare checkboxes.</p> <table border="1" data-bbox="479 365 1442 502"> <thead> <tr> <th data-bbox="479 365 806 418">Server</th><th data-bbox="806 365 1132 418">SG Inclusion</th><th data-bbox="1132 365 1442 418">Preferred HA Role</th></tr> </thead> <tbody> <tr> <td data-bbox="479 418 806 470">SO1</td><td data-bbox="806 418 1132 470"><input checked="" type="checkbox"/> Include in SG</td><td data-bbox="1132 418 1442 470"><input type="checkbox"/> Prefer server as spare</td></tr> <tr> <td data-bbox="479 470 806 502">SO2</td><td data-bbox="806 470 1132 502"><input checked="" type="checkbox"/> Include in SG</td><td data-bbox="1132 470 1442 502"><input checked="" type="checkbox"/> Prefer server as spare</td></tr> </tbody> </table> <p>For more information about server group secondary site or site redundancy, see the Terminology section.</p>	Server	SG Inclusion	Preferred HA Role	SO1	<input checked="" type="checkbox"/> Include in SG	<input type="checkbox"/> Prefer server as spare	SO2	<input checked="" type="checkbox"/> Include in SG	<input checked="" type="checkbox"/> Prefer server as spare
Server	SG Inclusion	Preferred HA Role									
SO1	<input checked="" type="checkbox"/> Include in SG	<input type="checkbox"/> Prefer server as spare									
SO2	<input checked="" type="checkbox"/> Include in SG	<input checked="" type="checkbox"/> Prefer server as spare									
5. <input type="checkbox"/>	Primary NOAM VIP GUI: Edit the SOAM server group and add additional SOAM VIPs (Optional)	<ol style="list-style-type: none"> 1. Click Add to add SOAM VIPs. 2. Type the VIP Address and click OK. <p>Note: Additional SOAM VIPs only apply to SOAM server groups with preferred spare SOAMs.</p> 									
6. <input type="checkbox"/>	Primary NOAM VIP GUI: Wait for replication	<p>After replication, the server status should be active (Status & Manage > HA).</p>  <p>Note: This may take up to 5 minutes while the servers figure out master/slave relationship.</p> <p>Look for the alarm ID 10200 Remote Database re-initialization in progress to be cleared before proceeding (Alarms > View Active).</p>									

STEP #	Procedure	Description
7. <input type="checkbox"/>	Primary NOAM VIP GUI: Restart 1 st SOAM server	<ol style="list-style-type: none"> From the NOAM GUI, navigate to Status & Manage > Server and select the 1st SOAM server.  <ol style="list-style-type: none"> Click Restart. Click OK on the confirmation screen. <p>10.75.153.171 says</p> <p>Are you sure you wish to restart application software on the following server(s)? DsrSite00NOAM00</p> <p>OK Cancel</p> <p>Wait for restart to complete. Wait for the Appl State to change to Enabled, and all other columns to Norm.</p>
8. <input type="checkbox"/>	Primary NOAM VIP GUI: Restart 2 nd SOAM server	Repeat step 7 for the second SOAM.
9. <input type="checkbox"/>	Primary NOAM VIP GUI: Restart all preferred spare SOAM servers (Optional)	<ol style="list-style-type: none"> If additional preferred spare servers are configured for secondary sites, navigate to Status & Manage > Server and select all Preferred Spare SOAM servers. Click Restart. Click OK to the confirmation popup. Wait for the Appl State to change to Enabled and all other columns to change to Norm.



Procedure 24. Activate PCA/DCA (PCA/DCA Only)


STEP #	Procedure	Description
	This procedure activates PCA/DCA. Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number. If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.	



STEP #	Procedure	Description
1. <input type="checkbox"/>	(PCA Only) activate PCA feature	<p>If you are installing PCA, execute the applicable procedures (Added SOAM site activation or complete system activation) of the DSR PCA Activation Guide [2] to activate PCA.</p> <p>Note: If not all SOAM sites are ready at this point, then you should repeat activation for each new SOAM site that comes online.</p> <p>Note: Ignore steps to restart DA-MPs and SBRs that have yet to be configured.</p>
2. <input type="checkbox"/>	(DCA Only) activate DCA feature	<p>If you are installing PCA, execute [21] DCA Framework and Application Activation and Deactivation Guide to activate the DCA framework and feature.</p> <p>Note: If not all SOAM sites are ready at this point, then you should repeat activation for each new SOAM site that comes online.</p> <p>Note: Ignore steps to restart DA-MPs and SBRs that have yet to be configured.</p>



Procedure 25. Configure the MP Virtual Machines

STEP #	Procedure	Description
This procedure configures MP VMs (IPFE, SBR, DA-MP, and vSTP).		
<p>Note: If you are adding MPs to expand an existing DSR, which was upgraded from 7.x to 8.x, skip this procedure and execute Procedure 26.</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>		
1. <input type="checkbox"/>	Primary NOAM VIP GUI: Establish GUI Session on the NOAM VIP	<ol style="list-style-type: none"> 1. If needed, establish a GUI session on the NOAM by using the NOAM VIP address. 2. Login as the guiadmin user.


STEP #	Procedure	Description
2. <input type="checkbox"/>	Primary NOAM VIP GUI: Navigate to the signaling network configuration screen	<ol style="list-style-type: none"> 1. Navigate to Configuration > Networking > Networks.  2. Navigate to the SO Network Element tab under which the MPs are to be configured.  3. Click Insert in the lower left corner. 
3. <input type="checkbox"/>	Primary NOAM VIP GUI: Add signaling networks	<p>The following screen displays:</p>  <ol style="list-style-type: none"> 1. Type the Network Name, Network Type, VLAN ID, Network Address, Netmask, and Router IP that matches the signaling network. Note: Even if the network does not use VLAN tagging, you should type the correct VLAN ID here as indicated by the NAPD. <ol style="list-style-type: none"> a. Select Signaling for Network Type. b. Select No for Default Network. c. Select Yes for Routable. 2. Click OK if you are finished adding signaling networks -OR- Click Apply to save this signaling network and repeat this step to enter additional signaling networks.

STEP #	Procedure	Description
4. <input type="checkbox"/>	Primary NOAM VIP GUI: (PCA/DCA only) Navigate to signaling network configuration screen	<p>Note: Execute this step only if you are defining a separate, dedicated network for SBR Replication.</p> <ol style="list-style-type: none"> 1. Navigate to Configuration > Networking > Networks.  2. Click Insert in the lower left corner. 
5. <input type="checkbox"/>	Primary NOAM VIP GUI: (PCA only) Define SBR DB replication network	<p>Note: Execute this step only if you are defining a separate, dedicated network for SBR replication.</p>  <ol style="list-style-type: none"> 1. Type the Network Name, Network Type, VLAN ID, Network Address, Netmask, and Router IP that matches the SBR DB replication network. <p>Note: Even if the network does not use VLAN tagging, you should type the correct VLAN ID here as indicated by the NAPD.</p> <ol style="list-style-type: none"> a. Select No for Default Network. b. Select Yes for Routable. 2. Click OK if you are finished adding signaling networks. -OR- Click Apply to save this signaling network and repeat this step to enter additional signaling networks.
6. <input type="checkbox"/>	Primary NOAM VIP GUI: (PCA)	<p>Note: Execute this step only if you are defining a separate, dedicated network for SBR replication.</p>


STEP #	Procedure	Description												
	only) Perform additional service to networks mapping	<p>1. Navigate to Configuration > Networking > Services.</p>  <p>2. Click Edit.</p>  <p>3. Set the services using one of the following scenarios:</p> <ul style="list-style-type: none"> If the dual-path HA configuration is required: For HA_MP_Secondary, Oracle recommends the inter-NE network is set as the XMI network and intra-NE network is set as the IMI network. If the primary interface (Replication_MP) SBR DB Replication Network interface goes down, use the secondary network for sharing HA status to reduce the likelihood of a split brain. This leads to DSR mate isolation from the active SBR and results in traffic loss until SBR DB Replication Network is down. <table border="1" data-bbox="496 1148 1400 1360"> <thead> <tr> <th data-bbox="496 1148 768 1227">Name</th><th data-bbox="768 1148 980 1227">Intra-NE Network</th><th data-bbox="980 1148 1400 1227">Inter-NE Network</th></tr> </thead> <tbody> <tr> <td data-bbox="496 1227 768 1269">HA_MP_Secondary</td><td data-bbox="768 1227 980 1269"><IMI Network></td><td data-bbox="980 1227 1400 1269"><XMI Network></td></tr> <tr> <td data-bbox="496 1269 768 1311">Replication_MP</td><td data-bbox="768 1269 980 1311"><IMI Network></td><td data-bbox="980 1269 1400 1311"><SBR DB Replication Network></td></tr> <tr> <td data-bbox="496 1311 768 1360">ComAgent</td><td data-bbox="768 1311 980 1360"><IMI Network></td><td data-bbox="980 1311 1400 1360"><SBR DB Replication Network></td></tr> </tbody> </table>  <ul style="list-style-type: none"> If the dual-path HA configuration is NOT required: The intra-NE network is set as the IMI network and inter-NE network is set as the PCA replication network (configured in step 5. This may lead to a split database scenario in case the SBR DB Replication Network interface goes down. Due to this, an active SBR server in each site is in effect. 	Name	Intra-NE Network	Inter-NE Network	HA_MP_Secondary	<IMI Network>	<XMI Network>	Replication_MP	<IMI Network>	<SBR DB Replication Network>	ComAgent	<IMI Network>	<SBR DB Replication Network>
Name	Intra-NE Network	Inter-NE Network												
HA_MP_Secondary	<IMI Network>	<XMI Network>												
Replication_MP	<IMI Network>	<SBR DB Replication Network>												
ComAgent	<IMI Network>	<SBR DB Replication Network>												

STEP #	Procedure	Description																					
		<table border="1" data-bbox="494 255 1400 473"> <thead> <tr> <th data-bbox="494 255 763 325">Name</th><th data-bbox="763 255 997 325">Intra-NE Network</th><th data-bbox="997 255 1400 325">Inter-NE Network</th></tr> </thead> <tbody> <tr> <td data-bbox="494 325 763 371">HA_MP_Secondary</td><td data-bbox="763 325 997 371"><IMI Network></td><td data-bbox="997 325 1400 371"><SBR DB Replication Network></td></tr> <tr> <td data-bbox="494 371 763 418">Replication_MP</td><td data-bbox="763 371 997 418"><IMI Network></td><td data-bbox="997 371 1400 418"><SBR DB Replication Network></td></tr> <tr> <td data-bbox="494 418 763 473">ComAgent</td><td data-bbox="763 418 997 473"><IMI Network></td><td data-bbox="997 418 1400 473"><SBR DB Replication Network></td></tr> </tbody> </table> <table border="1" data-bbox="494 473 1237 889"> <tbody> <tr> <td data-bbox="494 473 763 593">HA_MP_Secondary</td><td data-bbox="763 473 997 593">INTERNALIMI</td><td data-bbox="997 473 1237 593">Replication</td></tr> <tr> <td data-bbox="494 593 763 734">Replication_MP</td><td data-bbox="763 593 997 734">INTERNALIMI</td><td data-bbox="997 593 1237 734">Replication</td></tr> <tr> <td data-bbox="494 734 763 889">ComAgent</td><td data-bbox="763 734 997 889">INTERNALIMI</td><td data-bbox="997 734 1237 889">Replication</td></tr> </tbody> </table> <p data-bbox="494 899 1171 931">4. Click OK to apply the Service-to-Network selections.</p>	Name	Intra-NE Network	Inter-NE Network	HA_MP_Secondary	<IMI Network>	<SBR DB Replication Network>	Replication_MP	<IMI Network>	<SBR DB Replication Network>	ComAgent	<IMI Network>	<SBR DB Replication Network>	HA_MP_Secondary	INTERNALIMI	Replication	Replication_MP	INTERNALIMI	Replication	ComAgent	INTERNALIMI	Replication
Name	Intra-NE Network	Inter-NE Network																					
HA_MP_Secondary	<IMI Network>	<SBR DB Replication Network>																					
Replication_MP	<IMI Network>	<SBR DB Replication Network>																					
ComAgent	<IMI Network>	<SBR DB Replication Network>																					
HA_MP_Secondary	INTERNALIMI	Replication																					
Replication_MP	INTERNALIMI	Replication																					
ComAgent	INTERNALIMI	Replication																					
7. <input type="checkbox"/>	Primary NOAM VIP GUI: Insert the MP or IPFE server – Part 1	<p data-bbox="494 963 997 994">1. Navigate to Configuration > Servers.</p>  <p data-bbox="494 1300 1318 1332">2. Click Insert to add the new MP or IPFE server into servers table.</p>  <p data-bbox="494 1427 861 1459">3. Fill in the following values:</p>																					

STEP #	Procedure	Description																																	
		<table border="1"> <thead> <tr> <th>Attribute</th> <th>Value</th> </tr> </thead> <tbody> <tr> <td>Hostname *</td> <td><input type="text"/></td> </tr> <tr> <td>Role *</td> <td>- Select Role - <input type="button" value="▼"/></td> </tr> <tr> <td>System ID</td> <td><input type="text"/></td> </tr> <tr> <td>Hardware Profile</td> <td>DSR Guest <input type="button" value="▼"/></td> </tr> <tr> <td>Network Element Name *</td> <td>- Unassigned - <input type="button" value="▼"/></td> </tr> <tr> <td>Location</td> <td><input type="text"/></td> </tr> </tbody> </table> <p>4. Fill in the fields as follows:</p> <p>Hostname: <Hostname> Role: MP System ID: <Site System ID> Hardware Profile: DSR Guest Network Element Name: [Choose NE from list]</p> <table border="1"> <thead> <tr> <th colspan="3">OAM Interfaces [At least one interface is required.]:</th> </tr> <tr> <th>Network</th> <th>IP Address</th> <th>Interface</th> </tr> </thead> <tbody> <tr> <td>INTERNALXMI (10.196.227.0/24)</td> <td><input type="text" value="10.196.227."/></td> <td>eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (6)</td> </tr> <tr> <td>INTERNALIMI (169.254.1.0/24)</td> <td><input type="text" value="169.254.1."/></td> <td>eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (3)</td> </tr> <tr> <td>XSI-1 (10.196.228.0/25)</td> <td><input type="text" value="10.196.228."/></td> <td>eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN(26)</td> </tr> <tr> <td>XSI-2 (10.196.128.0/25)</td> <td><input type="text" value="10.196.228."/></td> <td>eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN(27)</td> </tr> </tbody> </table> <p>5. For the XMI network, type the MP's XMI IP address. Select the correct interface. 6. Leave the VLAN checkbox unmarked. 7. For the IMI network, type the MP's IMI IP address. Select the correct</p>	Attribute	Value	Hostname *	<input type="text"/>	Role *	- Select Role - <input type="button" value="▼"/>	System ID	<input type="text"/>	Hardware Profile	DSR Guest <input type="button" value="▼"/>	Network Element Name *	- Unassigned - <input type="button" value="▼"/>	Location	<input type="text"/>	OAM Interfaces [At least one interface is required.]:			Network	IP Address	Interface	INTERNALXMI (10.196.227.0/24)	<input type="text" value="10.196.227."/>	eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (6)	INTERNALIMI (169.254.1.0/24)	<input type="text" value="169.254.1."/>	eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (3)	XSI-1 (10.196.228.0/25)	<input type="text" value="10.196.228."/>	eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN(26)	XSI-2 (10.196.128.0/25)	<input type="text" value="10.196.228."/>	eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN(27)	
Attribute	Value																																		
Hostname *	<input type="text"/>																																		
Role *	- Select Role - <input type="button" value="▼"/>																																		
System ID	<input type="text"/>																																		
Hardware Profile	DSR Guest <input type="button" value="▼"/>																																		
Network Element Name *	- Unassigned - <input type="button" value="▼"/>																																		
Location	<input type="text"/>																																		
OAM Interfaces [At least one interface is required.]:																																			
Network	IP Address	Interface																																	
INTERNALXMI (10.196.227.0/24)	<input type="text" value="10.196.227."/>	eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (6)																																	
INTERNALIMI (169.254.1.0/24)	<input type="text" value="169.254.1."/>	eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (3)																																	
XSI-1 (10.196.228.0/25)	<input type="text" value="10.196.228."/>	eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN(26)																																	
XSI-2 (10.196.128.0/25)	<input type="text" value="10.196.228."/>	eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN(27)																																	

STEP #	Procedure	Description								
		<p>interface.</p> <ol style="list-style-type: none"> a. Leave the VLAN checkbox unmarked. b. For the Replication network, type the MP's XSI2 IP address. This is the IP address should be used from the name defined in step 5 above. This name would be the same name that is referred to as SBR DB Replication Network in step 6). Select the correct interface. Leave the VLAN checkbox unmarked. <ol style="list-style-type: none"> 8. For the XSI1 network, type the MP's XSI1 IP address. Select the correct interface. <ol style="list-style-type: none"> a. Leave the VLAN checkbox unmarked. 9. For the XSI2 network, type the MP's XSI2 IP address. Select the correct interface. <ol style="list-style-type: none"> a. Leave the VLAN checkbox unmarked. <p>Note: If more XSI networks are configured, follow the same method of entry as XSI1 and XSI2. All interfaces need to be added sequentially for any server.</p> <ol style="list-style-type: none"> 10. Add the following NTP servers: <table border="1" data-bbox="518 925 1400 1108"> <thead> <tr> <th data-bbox="518 925 959 975">NTP Server</th><th data-bbox="959 925 1400 975">Preferred?</th></tr> </thead> <tbody> <tr> <td data-bbox="518 975 959 1026">Valid NTP server</td><td data-bbox="959 975 1400 1026">Yes</td></tr> <tr> <td data-bbox="518 1026 959 1077">Valid NTP server</td><td data-bbox="959 1026 1400 1077">No</td></tr> <tr> <td data-bbox="518 1077 959 1108">Valid NTP server</td><td data-bbox="959 1077 1400 1108">No</td></tr> </tbody> </table> <ol style="list-style-type: none"> 11. Click OK when all fields are filled in to finish MP server insertion. <p>Note: Properly configure the NTP on the controller node to reference lower stratum NTP servers.</p>	NTP Server	Preferred?	Valid NTP server	Yes	Valid NTP server	No	Valid NTP server	No
NTP Server	Preferred?									
Valid NTP server	Yes									
Valid NTP server	No									
Valid NTP server	No									
8. <input type="checkbox"/>	Primary NOAM VIP GUI: Export the initial configuration	<ol style="list-style-type: none"> 1. Navigate to Configuration > Networking > Servers. <ul style="list-style-type: none">  Main Menu  Administration  Configuration <ul style="list-style-type: none">  Networking  Servers  Server Groups  Resource Domains  Places  Place Associations 2. From the GUI screen, select the server that was just configured and click Export to generate the initial configuration data for that server.  3. Go to the Info tab to confirm the file has been created. 								
9. <input type="checkbox"/>	MP Server: Log into the MP	Obtain a terminal window connection on the MP or IPFE server.								


STEP #	Procedure	Description
10. <input type="checkbox"/>	Primary NOAM VIP GUI: Copy configuration file to MP or IPFE server	<p>From the active NOAM console, login as the admusr user.</p> <pre>\$ sudo scp /var/TKLC/db/filemgmt/TKLCConfigData.<hostname>.sh admusr@<ipaddr>:/var/tmp/TKLCConfigData.sh</pre> <p>Note: ipaddr is the XMI IP address of the MP or IPFE.</p>
11. <input type="checkbox"/>	MP Server: Wait for configuration to complete	<ol style="list-style-type: none"> 1. Obtain a terminal session on the MP or IPFE as the admusr user. The automatic configuration daemon looks for the file named TKLCConfigData.sh in the /var/tmp directory, implements the configuration in the file, and prompts the user to reboot the server. 2. If you are on the console, wait to be prompted to reboot the server, but DO NOT reboot the server, it is rebooted later in this procedure. 3. Verify script completed successfully by checking the following file. <pre>\$ sudo cat /var/TKLC/appw/logs/Process/install.log</pre> <p>Note: Ignore the warning about removing the USB key since no USB key is present.</p>
12. <input type="checkbox"/>	MP Server: Reboot the server	<p>Obtain a terminal session on the MP or IPFE as the admusr user.</p> <pre>\$ sudo init 6</pre> <p>Wait for server to reboot.</p>
13. <input type="checkbox"/>	MP Server: Verify server health	<ol style="list-style-type: none"> 1. After the reboot, login as the admusr user. 2. Execute the following command as super-user on the server and make sure that no errors are returned: <pre>\$ sudo syscheck</pre> <pre>Running modules in class hardware...</pre> <pre>OK</pre> <pre>Running modules in class disk...</pre> <pre>OK</pre> <pre>Running modules in class net...</pre> <pre>OK</pre> <pre>Running modules in class system...</pre> <pre>OK</pre> <pre>Running modules in class proc...</pre> <pre>OK</pre> <pre>LOG LOCATION: /var/TKLC/log/syscheck/fail_log</pre>
14. <input type="checkbox"/>	MP Server: Delete Auto-Configured Default Route on	<p>Note: THIS STEP IS OPTIONAL AND SHOULD ONLY BE EXECUTED IF YOU PLAN TO CONFIGURE A DEFAULT ROUTE ON YOUR MP THAT USES A SIGNALING (XSI) NETWORK INSTEAD OF THE XMI NETWORK. Not executing this step means a default route is not configurable on this MP and you have to create separate network</p>


STEP #	Procedure	Description
	MP and Replace it with a Network Route using the XMI Network (Optional)	<p>routes for each signaling network destination.</p> <ol style="list-style-type: none"> 1. Log into the MP as the admusr user. (Alternatively, you can log into the VM's console.) 2. Determine <XMI_Gateway_IP> from your SO site network element information. 3. Gather the following items: <NO_XMI_Network_Address> <NO_XMI_Network_Netmask> Note: You can either consult the XML files you imported earlier, or go to the NO GUI and view these values from the Configuration > Networking > Networks menu. 4. Create network routes to the NO's XMI (OAM) network: <ol style="list-style-type: none"> a. Navigate to NOAM VIP GUI Configuration > Networking > Routes. b. Select the Specific MP. c. Click Insert. d. Enter details. e. Click OK. <p>Insert Route on DAMP</p>  <p>5. (Optional) [MP console] If sending SNMP traps from individual servers, create host routes to customer SNMP trap destinations on the XMI network:</p> <pre>\$ sudo /usr/TKLC/plat/bin/netAdm add --route=host --address=<Customer_NMS_IP> --gateway=<MP_XMI_Gateway_IP_Address> --device=<MP_XMI_Interface></pre> <p>6. Route to <MP_XMI_Interface> added.</p>

STEP #	Procedure	Description
		<p>7. Repeat for any existing customer NMS stations.</p> <p>8. Delete the existing default route:</p> <pre>\$ sudo /usr/TKLC/plat/bin/netAdm delete -- route=default --gateway=<MP_XMI_Gateway_IP> -- device=<MP_XMI_Interface></pre> <p>Route to <MP_XMI_Interface> removed.</p> <p>9. [MP Console] Ping active NO XMI IP address to verify connectivity:</p> <pre>\$ ping <ACTIVE_NO_XMI_IP_Address> PING 10.240.108.6 (10.240.108.6) 56(84) bytes of data. 64 bytes from 10.240.108.6: icmp_seq=1 ttl=64 time=0.342 ms 64 bytes from 10.240.108.6: icmp_seq=2 ttl=64 time=0.247 ms</pre> <p>10. (Optional) [MP Console] Ping Customer NMS Station(s):</p> <pre>\$ ping <Customer_NMS_IP> PING 172.4.116.8 (172.4.118.8) 56(84) bytes of data. 64 bytes from 172.4.116.8: icmp_seq=1 ttl=64 time=0.342 ms 64 bytes from 172.4.116.8: icmp_seq=2 ttl=64 time=0.247 ms</pre> <p>11. If you do not get a response, then verify your network configuration. If you continue to get failures then halt the installation and contact Oracle customer support.</p>
15. <input type="checkbox"/>	Repeat for remaining MPs and IPFEs	Repeat steps 7 through 14 for all remaining MP (SBR, DA-MP, IPFE and vSTP) servers.


Procedure 26. Configure the MP Virtual Machines (Optional)

STEP #	Procedure	Description
		<p>This procedure configures MP VMs (IPFE, SBR, DA-MP, and vSTP).</p> <p>Note: This procedure is ONLY required if additional MPs are required to be added to expand an existing DSR, which was upgraded from 7.x to 8.x.</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>

STEP #	Procedure	Description														
1. <input type="checkbox"/>	Primary NOAM VIP GUI: Establish GUI Session on the NOAM VIP	Establish a GUI session on the NOAM by using the NOAM VIP address. Login as the guiadmin user.														
2. <input type="checkbox"/>	Primary NOAM VIP GUI: Insert the MP or IPFE server – Part 1	<p>1. Navigate to Configuration > Servers.</p>  <p>2. Click Insert to add the new MP or IPFE server into servers table.</p>  <p>3. Fill in the following values:</p> <table border="1" data-bbox="514 1045 1395 1890"> <thead> <tr> <th data-bbox="514 1045 873 1108">Attribute</th> <th data-bbox="873 1045 1395 1108">Value</th> </tr> </thead> <tbody> <tr> <td data-bbox="514 1108 873 1214">Hostname *</td> <td data-bbox="873 1108 1395 1214"><input type="text"/></td> </tr> <tr> <td data-bbox="514 1214 873 1362">Role *</td> <td data-bbox="873 1214 1395 1362"><input type="button" value="- Select Role -"/></td> </tr> <tr> <td data-bbox="514 1362 873 1467">System ID</td> <td data-bbox="873 1362 1395 1467"><input type="text"/></td> </tr> <tr> <td data-bbox="514 1467 873 1615">Hardware Profile</td> <td data-bbox="873 1467 1395 1615"><input type="button" value="DSR Guest"/></td> </tr> <tr> <td data-bbox="514 1615 873 1763">Network Element Name *</td> <td data-bbox="873 1615 1395 1763"><input type="button" value="- Unassigned -"/></td> </tr> <tr> <td data-bbox="514 1763 873 1890">Location</td> <td data-bbox="873 1763 1395 1890"><input type="text"/></td> </tr> </tbody> </table>	Attribute	Value	Hostname *	<input type="text"/>	Role *	<input type="button" value="- Select Role -"/>	System ID	<input type="text"/>	Hardware Profile	<input type="button" value="DSR Guest"/>	Network Element Name *	<input type="button" value="- Unassigned -"/>	Location	<input type="text"/>
Attribute	Value															
Hostname *	<input type="text"/>															
Role *	<input type="button" value="- Select Role -"/>															
System ID	<input type="text"/>															
Hardware Profile	<input type="button" value="DSR Guest"/>															
Network Element Name *	<input type="button" value="- Unassigned -"/>															
Location	<input type="text"/>															

STEP #	Procedure	Description																	
		<p>4. Fill in the fields as follows:</p> <p>Hostname: <Hostname> Role: MP System ID: <Site System ID> Hardware Profile: DSR Guest Network Element Name: [Choose NE from list]</p> <p>OAM Interfaces [At least one interface is required.]:</p> <table border="1" data-bbox="502 523 1400 713"> <thead> <tr> <th data-bbox="502 544 584 566">Network</th><th data-bbox="796 544 878 566">IP Address</th><th data-bbox="1220 544 1286 566">Interface</th></tr> </thead> <tbody> <tr> <td data-bbox="502 587 731 608">INTERNALXMI (10.196.227.0/24)</td><td data-bbox="796 587 1122 608">10.196.227.</td><td data-bbox="1220 587 1400 608">eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (6)</td></tr> <tr> <td data-bbox="502 671 731 692">INTERNALIMI (169.254.1.0/24)</td><td data-bbox="796 671 1122 692">169.254.1.</td><td data-bbox="1220 671 1400 692">eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (3)</td></tr> </tbody> </table> <p>5. For the XMI network, type the MP's XMI IP address. Select the correct interface. Leave the VLAN checkbox unmarked.</p> <p>6. For the IMI network, type the MP's IMI IP address. Select the correct interface. Leave the VLAN checkbox unmarked.</p> <p>7. Add the following NTP servers:</p> <table border="1" data-bbox="518 1009 1400 1199"> <thead> <tr> <th data-bbox="518 1009 959 1051">NTP Server</th><th data-bbox="959 1009 1400 1051">Preferred?</th></tr> </thead> <tbody> <tr> <td data-bbox="518 1072 959 1115">Valid NTP server</td><td data-bbox="959 1072 1400 1115">Yes</td></tr> <tr> <td data-bbox="518 1136 959 1178">Valid NTP server</td><td data-bbox="959 1136 1400 1178">No</td></tr> <tr> <td data-bbox="518 1199 959 1241">Valid NTP server</td><td data-bbox="959 1199 1400 1241">No</td></tr> </tbody> </table> <p>8. Click OK when all fields are filled in to finish MP server insertion.</p> <p>Note: Properly configure the NTP on the controller node to reference lower stratum NTP servers.</p>	Network	IP Address	Interface	INTERNALXMI (10.196.227.0/24)	10.196.227.	eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (6)	INTERNALIMI (169.254.1.0/24)	169.254.1.	eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (3)	NTP Server	Preferred?	Valid NTP server	Yes	Valid NTP server	No	Valid NTP server	No
Network	IP Address	Interface																	
INTERNALXMI (10.196.227.0/24)	10.196.227.	eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (6)																	
INTERNALIMI (169.254.1.0/24)	169.254.1.	eth0 <input type="button" value="▼"/> <input type="checkbox"/> VLAN (3)																	
NTP Server	Preferred?																		
Valid NTP server	Yes																		
Valid NTP server	No																		
Valid NTP server	No																		
3. <input type="checkbox"/>	Primary NOAM VIP GUI: Export the initial configuration	<p>1. Navigate to Configuration > Networking > Servers.</p>  <p>2. From the GUI screen, select the server that was just configured and click Export to generate the initial configuration data for that server.</p> <p>Insert Edit Delete Export Report</p> <p>3. Go to the Info tab to confirm the file has been created.</p>																	



STEP #	Procedure	Description
4. <input type="checkbox"/>	MP Server: Log into the MP	Obtain a terminal window connection on the MP or IPFE server.
5. <input type="checkbox"/>	Primary NOAM VIP Server: Copy configuration file to MP or IPFE server	<p>From the active NOAM console, login as the admusr user.</p> <pre>\$ sudo scp /var/TKLC/db/filemgmt/TKLCConfigData.<hostname>.sh admusr@<ipaddr>:/var/tmp/TKLCConfigData.sh</pre> <p>Note: ipaddr is the XMI IP address of the MP or IPFE.</p>
6. <input type="checkbox"/>	MP Server: Wait for configuration to complete	<ol style="list-style-type: none"> 1. Obtain a terminal session on the MP or IPFE as the admusr user. The automatic configuration daemon looks for the file named TKLCConfigData.sh in the /var/tmp directory, implements the configuration in the file, and prompts the user to reboot the server. 2. If you are on the console, wait to be prompted to reboot the server, but DO NOT reboot the server, it is rebooted later in this procedure. 3. Verify script completed successfully by checking the following file. <pre>\$ sudo cat /var/TKLC/appw/logs/Process/install.log</pre> <p>Note: Ignore the warning about removing the USB key since no USB key is present.</p>
7. <input type="checkbox"/>	MP Server: Reboot the server	<p>Obtain a terminal session on the MP or IPFE as the admusr user.</p> <pre>\$ sudo init 6</pre> <p>Wait for server to reboot.</p>
8. <input type="checkbox"/>	MP Server: Verify server health	<ol style="list-style-type: none"> 1. After the reboot, login as the admusr user. 2. Execute the following command as super-user on the server and make sure that no errors are returned: <pre>\$ sudo syscheck</pre> <pre>Running modules in class hardware...</pre> <pre>OK</pre> <pre>Running modules in class disk...</pre> <pre>OK</pre> <pre>Running modules in class net...</pre> <pre>OK</pre> <pre>Running modules in class system...</pre> <pre>OK</pre> <pre>Running modules in class proc...</pre> <pre>OK</pre> <pre>LOG LOCATION: /var/TKLC/log/syscheck/fail_log</pre>
9.	MP Server:	Note: THIS STEP IS OPTIONAL AND SHOULD ONLY BE EXECUTED IF


STEP #	Procedure	Description
<input type="checkbox"/>	<p>Delete Auto-Configured Default Route on MP and Replace it with a Network Route using the XMI Network (Optional)</p>	<p>YOU PLAN TO CONFIGURE A DEFAULT ROUTE ON YOUR MP THAT USES A SIGNALING (XSI) NETWORK INSTEAD OF THE XMI NETWORK. Not executing this step means a default route is not configurable on this MP and you have to create separate network routes for each signaling network destination.</p> <ol style="list-style-type: none"> 1. Log into the MP as the admusr user. (Alternatively, you can log into the VM's console.) 2. Determine <XMI_Gateway_IP> from your SO site network element information. 3. Gather the following items: <NO_XMI_Network_Address> <NO_XMI_Network_Netmask> <p>Note: You can either consult the XML files you imported earlier, or go to the NO GUI and view these values from the Configuration > Networking > Networks menu.</p> 4. Create network routes to the NO's XMI (OAM) network: <ol style="list-style-type: none"> a. Navigate to NOAM VIP GUI Configuration > Networking > Routes. b. Select the Specific MP. c. Click Insert. d. Enter details. e. Click OK. <p>Insert Route on DAMP</p>  <p>5. (Optional) [MP console] If sending SNMP traps from individual servers, create host routes to customer SNMP trap destinations on the XMI network:</p> <pre>\$ sudo /usr/TKLC/plat/bin/netAdm add --route=host --address=<Customer_NMS_IP></pre>

STEP #	Procedure	Description
		<pre>--gateway=<MP_XMI_Gateway_IP_Address> --device=<MP_XMI_Interface> 6. Route to <MP_XMI_Interface> added. 7. Repeat for any existing customer NMS stations. 8. Delete the existing default route: \$ sudo /usr/TKLC/plat/bin/netAdm delete -- route=default --gateway=<MP_XMI_Gateway_IP> -- device=<MP_XMI_Interface> Route to <MP_XMI_Interface> removed. 9. [MP Console] Ping active NO XMI IP address to verify connectivity: \$ ping <ACTIVE_NO_XMI_IP_Address> PING 10.240.108.6 (10.240.108.6) 56(84) bytes of data. 64 bytes from 10.240.108.6: icmp_seq=1 ttl=64 time=0.342 ms 64 bytes from 10.240.108.6: icmp_seq=2 ttl=64 time=0.247 ms 10. (Optional) [MP Console] Ping Customer NMS Station(s): \$ ping <Customer_NMS_IP> PING 172.4.116.8 (172.4.118.8) 56(84) bytes of data. 64 bytes from 172.4.116.8: icmp_seq=1 ttl=64 time=0.342 ms 64 bytes from 172.4.116.8: icmp_seq=2 ttl=64 time=0.247 ms 11. If you do not get a response, then verify your network configuration. If you continue to get failures then halt the installation and contact Oracle customer support.</pre>
10. <input type="checkbox"/>	Repeat for remaining MPs and IPFEs	Repeat steps 2 through 9 for all remaining newly created MPs.

Procedure 27. Configure Places and Assign MP Servers to Places (PCA and DCA Only)


STEP #	Procedure	Description
		<p>This procedure adds places in the PCA, and DCA networks.</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>

STEP #	Procedure	Description															
1. <input type="checkbox"/> (PCA Only) Primary NOAM VIP GUI: Configure Places		<ol style="list-style-type: none"> Establish a GUI session on the NOAM by using the XMI VIP address. Login as the guiadmin user. Navigate to Configuration > Networking > Places.  Click Insert.  Fill in the fields as follows: <p>Inserting a new Place</p> <table border="1"> <thead> <tr> <th colspan="3">Place</th> </tr> <tr> <th>Field</th> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>Place Name *</td> <td>ZombiePlace</td> <td>Unique identifier used to label a Place. [Def: and space.] [A value is required.]</td> </tr> <tr> <td>Parent *</td> <td>NONE</td> <td>The Parent of this Place [A value is required.]</td> </tr> <tr> <td>Place Type *</td> <td>Site</td> <td>The Type of this Place [A value is required.]</td> </tr> </tbody> </table> <p>Place Name: <Site Name> Parent: NONE Place Type: Site</p> Repeat this step for each of the PCA/DCA Places (Sites) in the network. See the Terminology section for more information on Sites & Places. 	Place			Field	Value	Description	Place Name *	ZombiePlace	Unique identifier used to label a Place. [Def: and space.] [A value is required.]	Parent *	NONE	The Parent of this Place [A value is required.]	Place Type *	Site	The Type of this Place [A value is required.]
Place																	
Field	Value	Description															
Place Name *	ZombiePlace	Unique identifier used to label a Place. [Def: and space.] [A value is required.]															
Parent *	NONE	The Parent of this Place [A value is required.]															
Place Type *	Site	The Type of this Place [A value is required.]															


STEP #	Procedure	Description
2. <input type="checkbox"/>	NOAM VIP GUI: Assign MP server to places	<p>1. Select the place configured in step 1 and click Edit.</p>  <p>2. Mark all the checkboxes for PCA/DCA DA-MP and SBR servers that are assigned to this place.</p> <p>3. Repeat this step for all other DA-MP or SBR servers you wish to assign to places.</p> <p>Note: All DA-MPs and SBR servers must be added to the Site Place that corresponds to the physical location of the server.</p> <p>See the Terminology section for more information on Sites & Places.</p>



Procedure 28. Configure the MP Server Group(s) and Profiles


STEP #	Procedure	Description
		<p>This procedure configures MP server groups.</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>
1. <input type="checkbox"/>	Primary NOAM VIP GUI: Enter MP Server Group Data Applicable to all C level servers (DAMP, IPFE, VSTP,)	<p>1. From the GUI session on the NOAM VIP address, navigate to Configuration > Server Groups.</p>

STEP #	Procedure	Description																		
	SBRs)	<p>  <pre> - Main Menu + Administration - Configuration + Networking + Servers + Server Groups + Resource Domains + Places + Place Associations </pre> </p> <p>2. Click Insert and fill out the following fields:</p> <p>Server Group Name: [Server Group Name]</p> <p>Level: C</p> <p>Parent: [SOAM Server Group That is Parent To this MP]</p> <p>Function: Select the Proper Function for this MP Server Group:</p> <table border="1" data-bbox="514 819 1416 1311"> <thead> <tr> <th data-bbox="514 819 742 903">Server Group Function</th> <th data-bbox="742 819 1036 903">MPs Will Run</th> <th data-bbox="1036 819 1416 903">Redundancy Model</th> </tr> </thead> <tbody> <tr> <td data-bbox="514 903 742 977">DSR (multi-active cluster)</td> <td data-bbox="742 903 1036 977">Diameter Relay and Application Services</td> <td data-bbox="1036 903 1416 977">Multiple MPs Active per SG</td> </tr> <tr> <td data-bbox="514 977 742 1056">DSR (active-standby pair)</td> <td data-bbox="742 977 1036 1056">Diameter Relay and Application Services</td> <td data-bbox="1036 977 1416 1056">1 Active MP and 1 Standby MP/Per SG</td> </tr> <tr> <td data-bbox="514 1056 742 1098">IP Front End</td> <td data-bbox="742 1056 1036 1098">IPFE application</td> <td data-bbox="1036 1056 1416 1098">1 Active MP Per SG</td> </tr> <tr> <td data-bbox="514 1098 742 1267">SBR</td> <td data-bbox="742 1098 1036 1267">Policy and Charging Session/or Policy Binding Function/Universal SBR</td> <td data-bbox="1036 1098 1416 1267">1 Active MP, 1 Standby MP, 2 Optional Spare Per SG</td> </tr> <tr> <td data-bbox="514 1267 742 1311">STP</td> <td data-bbox="742 1267 1036 1311">vSTP</td> <td data-bbox="1036 1267 1416 1311">Multiple vSTP MP per SG</td> </tr> </tbody> </table> <p>For vSTP:</p> <p>If configuring only vSTP application, ignore all other IPFE configuration. Currently, there is no specific MP profile for vSTP MP.</p> <p>Notes:</p> <ul style="list-style-type: none"> IPFE interaction with vSTP MP is NOT supported. There is no support of TSA/Auto selection for vSTP MPs. vSTP MP can co-exist with DA-MP under a SOAM but different server group. <p>For PCA application:</p> <ul style="list-style-type: none"> Online Charging function(only) <p>At least one MP Server Group with the SBR function must be configured.</p> <p>At least one MP Server Group with the DSR (multi-active cluster) function must be configured.</p> <ul style="list-style-type: none"> Policy DRA function 	Server Group Function	MPs Will Run	Redundancy Model	DSR (multi-active cluster)	Diameter Relay and Application Services	Multiple MPs Active per SG	DSR (active-standby pair)	Diameter Relay and Application Services	1 Active MP and 1 Standby MP/Per SG	IP Front End	IPFE application	1 Active MP Per SG	SBR	Policy and Charging Session/or Policy Binding Function/Universal SBR	1 Active MP, 1 Standby MP, 2 Optional Spare Per SG	STP	vSTP	Multiple vSTP MP per SG
Server Group Function	MPs Will Run	Redundancy Model																		
DSR (multi-active cluster)	Diameter Relay and Application Services	Multiple MPs Active per SG																		
DSR (active-standby pair)	Diameter Relay and Application Services	1 Active MP and 1 Standby MP/Per SG																		
IP Front End	IPFE application	1 Active MP Per SG																		
SBR	Policy and Charging Session/or Policy Binding Function/Universal SBR	1 Active MP, 1 Standby MP, 2 Optional Spare Per SG																		
STP	vSTP	Multiple vSTP MP per SG																		

STEP #	Procedure	Description									
		<p>At least two MP Server Groups with the SBR function must be configured. One stores session data and one stores binding data.</p> <p>At least one MP Server Group with the DSR (multi-active cluster) function must be configured.</p> <p>WAN Replication Connection Count:</p> <p>For non-Policy and Charging SBR Server Groups: Default Value</p> <p>For Policy and Charging Server Groups: 8</p> <p>For the PCA application, the following types of MP Server Groups must be configured:</p> <ul style="list-style-type: none"> DA-MP (Function: DSR (multi-active cluster)) SBR (Function: SBR) IPFE (Function: IP Front End) <p>3. Click OK when all fields are filled in.</p>									
2. <input type="checkbox"/>	<p>Primary NOAM VIP GUI: Repeat for additional server groups</p>	<p>Repeat step 1 for any remaining MP and IPFE server groups you wish to create. For instance, when installing an IPFE, you need to create an IP front end server group for each IPFE server.</p>									
3. <input type="checkbox"/>	<p>Primary NOAM VIP GUI: Edit the MP server groups to include MPs</p>	<ol style="list-style-type: none"> 1. Navigate to Configuration > Server Groups, select a server group that you just created, and click Edit. 2. Select the network element representing the MP server group you wish to edit. 3. Mark the Include in SG checkbox for every MP server you wish to include in this server group. Leave other checkboxes blank. <table border="1" data-bbox="496 1227 1405 1368"> <thead> <tr> <th data-bbox="496 1227 845 1262">Server</th> <th data-bbox="845 1227 1171 1262">SG Inclusion</th> <th data-bbox="1171 1227 1405 1262">Preferred HA Role</th> </tr> </thead> <tbody> <tr> <td data-bbox="496 1273 845 1305">DAMP1</td> <td data-bbox="845 1273 1171 1305"><input checked="" type="checkbox"/> Include in SG</td> <td data-bbox="1171 1273 1405 1305"><input type="checkbox"/> Prefer server as spare</td> </tr> <tr> <td data-bbox="496 1315 845 1347">DAMP2</td> <td data-bbox="845 1315 1171 1347"><input checked="" type="checkbox"/> Include in SG</td> <td data-bbox="1171 1315 1405 1347"><input type="checkbox"/> Prefer server as spare</td> </tr> </tbody> </table> <p>Note: Each IPFE, and vSTP-MP server should be in its own server group.</p> <ol style="list-style-type: none"> 4. Click OK. 	Server	SG Inclusion	Preferred HA Role	DAMP1	<input checked="" type="checkbox"/> Include in SG	<input type="checkbox"/> Prefer server as spare	DAMP2	<input checked="" type="checkbox"/> Include in SG	<input type="checkbox"/> Prefer server as spare
Server	SG Inclusion	Preferred HA Role									
DAMP1	<input checked="" type="checkbox"/> Include in SG	<input type="checkbox"/> Prefer server as spare									
DAMP2	<input checked="" type="checkbox"/> Include in SG	<input type="checkbox"/> Prefer server as spare									

STEP #	Procedure	Description						
4. <input type="checkbox"/>	(PCA only) Primary NOAM VIP GUI: Edit the MP server group and add preferred spares for site redundancy (Optional)	<p>If two-site redundancy for the Policy and Charging SBR Server Group is wanted, add a MP server that is physically located in a separate site (location) to the server group by marking the Include in SG checkbox and also mark the Preferred Spare checkbox.</p> <table border="1" data-bbox="496 397 1410 487"> <thead> <tr> <th data-bbox="496 397 845 447">Server</th><th data-bbox="845 397 1171 447">SG Inclusion</th><th data-bbox="1171 397 1410 447">Preferred HA Role</th></tr> </thead> <tbody> <tr> <td data-bbox="496 447 845 487">SBR1</td><td data-bbox="845 447 1171 487"><input checked="" type="checkbox"/> Include in SG</td><td data-bbox="1171 447 1410 487"><input checked="" type="checkbox"/> Prefer server as spare</td></tr> </tbody> </table> <p>If three-site redundancy for the SBR MP server group is wanted, add two SBR MP servers that are both physically located in separate sites (location) to the server group by marking the Include in SG and Preferred Spare checkboxes for both servers.</p> <p>Note: The preferred spare servers should be different sites from the original server. There should be servers from three separate sites (locations).</p> <p>Note: There must first be non-preferred spare present in the server group before adding the preferred spare.</p> <p>For more information about site redundancy for Policy and Charging SBR Server Groups, see the Terminology section.</p> <p>Click OK to save.</p>	Server	SG Inclusion	Preferred HA Role	SBR1	<input checked="" type="checkbox"/> Include in SG	<input checked="" type="checkbox"/> Prefer server as spare
Server	SG Inclusion	Preferred HA Role						
SBR1	<input checked="" type="checkbox"/> Include in SG	<input checked="" type="checkbox"/> Prefer server as spare						
5. <input type="checkbox"/>	Primary NOAM VIP GUI: Repeat For additional server groups	Repeat steps 1 through 4 for any remaining MP and IPFE server groups you need to create.						
6. <input type="checkbox"/>	Primary NOAM VIP GUI: Wait for replication to complete on all MPs	<p>Wait for the alarm 10200: Remote Database re-initialization in progress to be cleared (Alarms & Events > Active Alarms).</p>  <p>This should happen shortly after you have verified the Norm DB status in the previous step.</p>						


STEP #	Procedure	Description
7. <input type="checkbox"/>	SOAM VIP GUI: Assign profiles to DA-MPs from SOAM GUI	<ol style="list-style-type: none"> 1. Log into the GUI of the active SOAM server as the guiadmin user. 2. From the SO GUI, navigate to Diameter Common > MPs > Profiles Assignments.  3. For each MP, select the proper profile assignment based on the MP's type and the function it serves:  4. When finished, click Assign.

STEP #	Procedure	Description
8.	<input type="checkbox"/> Primary NOAM VIP GUI: Restart MP VM	<ol style="list-style-type: none"> From the NOAM GUI, navigate to Status & Manage > Server.  <pre> Status & Manage +-- Network Elements +-- Server +-- HA +-- Database +-- KPIs +-- Processes </pre> For each MP server: <ol style="list-style-type: none"> Select the MP server. Click Restart. Click OK on the confirmation screen. Wait for the message that tells you that the restart was successful. <p>Policy and Charging DRA/DCA Installations: You may continue to see alarms related to ComAgent until you complete PCA/DCA installation.</p>

5.1 Configure Signaling Devices (Optional)

Procedure 29. Configure the Signaling Devices (Optional)

STEP #	Procedure	Description
		<p>This procedure configures signaling network interfaces to the newly added MP servers.</p> <p>Note: This procedure is ONLY required if additional MPs need to be added to expand an existing DSR, which was upgraded from 7.x to 8.x.</p> <p>Prerequisite: Execute Procedure 26.</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>



STEP #	Procedure	Description
1. <input type="checkbox"/>	Newly created MP Server console: Manually configure signaling interface	<ol style="list-style-type: none"> SSH into the newly added MP <pre>\$ ssh admusr@<XMI_Interface_of_Newly_Created_MP></pre> Configure the signaling network interfaces, conforming the OCDSR Network to Device Assignments defined in [24] DSR Cloud Benchmarking Guide. <pre>\$ sudo netAdm add --onboot=yes --bootproto=none --device=eth2 --address=<xsi1 ip> --netmask=<xsi1 net mask></pre> <pre>\$ sudo netAdm add --onboot=yes --bootproto=none --device=eth3 --address=<xsi2 ip> --netmask=<xsi2 net mask></pre> <p>Repeat the above netAdm commands to configure the required number of the Signaling network interfaces.</p> Reboot the VM. It takes approximately 5 minutes for the VM to complete rebooting. <pre>\$ sudo init 6</pre>
2. <input type="checkbox"/>	Primary NOAM VIP GUI: Take ownership of the Signaling interfaces and make it Deployed	<ol style="list-style-type: none"> Navigate to Configuration > Networking > Devices.  You should see several tabs each representing a server in the system. Click on the tab representing the newly created MP.  Select all newly configured Signaling Ethernet devices that have Discovered as their Configuration Status.  <p>Click Take Ownership.</p> <p>Take Ownership button: Converts a discovered device to a configured one.</p> <p>After a brief moment, the selected devices display a Configuration Status of Deployed.</p>

STEP #	Procedure	Description
3. <input type="checkbox"/>	Repeat for remaining MPs and IPFEs	Repeat steps 1 and 2 for all remaining newly created MPs.


5.2 Configure Signaling Network Routes

Procedure 30. Configure the Signaling Network Routes

STEP #	Procedure	Description
		<p>This procedure configures signaling network routes on MP-type servers (DA-MP, IPFE, SBR, etc.). Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>
1. <input type="checkbox"/>	Establish GUI session on the NOAM VIP	<p>Establish a GUI session on the NOAM by using the NOAM VIP address. Login as the guiadmin user.</p>  <p>The screenshot shows the Oracle System Login page. At the top is the Oracle logo. Below it is the title "Oracle System Login" and the date "Mon Jul 11 13:59:37 2016 EDT". The main area is a "Log In" form with fields for "Username" and "Password", a "Change password" checkbox, and a "Log In" button. Below the form is a welcome message: "Welcome to the Oracle System Login." A note below it states: "This application is designed to work with most modern HTML5 compliant browsers and uses both JavaScript and cookies. Please refer to the Oracle Software Web Browser Support Policy for details." At the bottom, there is a copyright notice: "Copyright © 2010, 2016, Oracle and/or its affiliates. All rights reserved." and a trademark notice: "Oracle and Java are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners."</p>

STEP #	Procedure	Description
2. <input type="checkbox"/>	NOAM VIP: Navigate to routes configuration screen	<ol style="list-style-type: none"> 1. Navigate to Configuration > Networking > Network > Routes.  2. Select the first MP Server you see listed on the first row of tabs as shown, and click the Entire Server Group link. Initially, no routes should display. 
3. <input type="checkbox"/>	NOAM VIP: Add route	Click Insert at the bottom of the screen to add additional routes. 
4. <input type="checkbox"/>	Primary NOAM VIP GUI: Add default route for MPs going through signaling network gateway (Optional)	<p>***OPTIONAL — Only execute this step if you performed Procedure 25, step 14. , that you have deleted default XMI route and plan to replace it with default XSI routes.</p> <p>To delete the existing default route:</p> <ol style="list-style-type: none"> 1. Log into the PRIMARY NOAM VIP GUI. 2. Navigate to Configuration > Networking > Networks. 3. Select the specific SO tab. 4. Select the XMI network and click Unlock. Click OK. 5. Navigate to Configuration > Networking > Routes. 6. Select the Specific MP XMI route and click Delete. 7. Click OK. 8. Repeat the above steps for all required MPs to delete the XMI routes. 9. Navigate to Configuration > Networking > Networks. 10. Select the respective SOAM tab. 11. Select the XMI network and click Lock. 12. Click OK. <p>If your MP servers no longer have a default route, then you can insert a default route here, which uses one of the signaling network gateways.</p>


Step #	Procedure	Description																		
		<p>Insert Route on DAMP1</p> <table border="1" data-bbox="502 318 1400 952"> <thead> <tr> <th data-bbox="502 318 633 361">Field</th><th data-bbox="633 318 943 361">Value</th><th data-bbox="943 318 1400 361">Description</th></tr> </thead> <tbody> <tr> <td data-bbox="502 361 633 487">Route Type *</td><td data-bbox="633 361 943 487"> <input type="radio"/> Net <input checked="" type="radio"/> Default <input type="radio"/> Host </td><td data-bbox="943 361 1400 487">Select a route type. [Default = N/A. Options = Net, Default, Host]</td></tr> <tr> <td data-bbox="502 487 633 614">Device *</td><td data-bbox="633 487 943 614"> <input type="text" value="eth3"/> <input type="button" value="▼"/> </td><td data-bbox="943 487 1400 614">Select the network device name through which traffic is to be sent. [A value is required.]</td></tr> <tr> <td data-bbox="502 614 633 741">Destination</td><td data-bbox="633 614 943 741"> <input type="text"/> </td><td data-bbox="943 614 1400 741">The destination network address. [Default = N/A. Format = IP address]</td></tr> <tr> <td data-bbox="502 741 633 868">Netmask</td><td data-bbox="633 741 943 868"> <input type="text"/> </td><td data-bbox="943 741 1400 868">A valid netmask for the network route destination IP address.</td></tr> <tr> <td data-bbox="502 868 633 952">Gateway IP *</td><td data-bbox="633 868 943 952"> <input type="text"/> </td><td data-bbox="943 868 1400 952">The IP address of the gateway for this route. [Default = N/A. Format = IP address]</td></tr> </tbody> </table> <p data-bbox="518 963 812 994"> <input type="button" value="Ok"/> <input type="button" value="Apply"/> <input type="button" value="Cancel"/> </p> <p data-bbox="543 1009 829 1041">Route Type: Default</p> <p data-bbox="543 1047 1416 1110">Device: Select the signaling device directly attached to the network where the XSI default gateway resides.</p> <p data-bbox="543 1117 1354 1180">Gateway IP: The XSI gateway you wish to use for default signaling network access.</p> <p data-bbox="494 1186 665 1218">13. Click OK.</p>	Field	Value	Description	Route Type *	<input type="radio"/> Net <input checked="" type="radio"/> Default <input type="radio"/> Host	Select a route type. [Default = N/A. Options = Net, Default, Host]	Device *	<input type="text" value="eth3"/> <input type="button" value="▼"/>	Select the network device name through which traffic is to be sent. [A value is required.]	Destination	<input type="text"/>	The destination network address. [Default = N/A. Format = IP address]	Netmask	<input type="text"/>	A valid netmask for the network route destination IP address.	Gateway IP *	<input type="text"/>	The IP address of the gateway for this route. [Default = N/A. Format = IP address]
Field	Value	Description																		
Route Type *	<input type="radio"/> Net <input checked="" type="radio"/> Default <input type="radio"/> Host	Select a route type. [Default = N/A. Options = Net, Default, Host]																		
Device *	<input type="text" value="eth3"/> <input type="button" value="▼"/>	Select the network device name through which traffic is to be sent. [A value is required.]																		
Destination	<input type="text"/>	The destination network address. [Default = N/A. Format = IP address]																		
Netmask	<input type="text"/>	A valid netmask for the network route destination IP address.																		
Gateway IP *	<input type="text"/>	The IP address of the gateway for this route. [Default = N/A. Format = IP address]																		


STEP #	Procedure	Description
5. <input type="checkbox"/>	Primary NOAM VIP GUI: Add network routes for Diameter peers	<p>1. Use this step to add IP4 and/or IPv6 routes to Diameter peer destination networks. The goal for this step is to ensure Diameter traffic uses the gateway(s) on the signaling networks.</p> <p>Insert Route on BuenosAires-DAMP1</p>  <p>Route Type: Net</p> <p>Device: Select the appropriate signaling interface that is used to connect to that network</p> <p>Destination: Type the Network ID of network to which the peer node is connected to</p> <p>Netmask: Type the corresponding Netmask</p> <p>Gateway IP: Type the IP of the customer gateway.</p> <p>2. If you have more routes to enter, click Apply to save the current route entry. Repeat this step to enter more routes.</p> <p>3. If you have finished entering routes, click OK to save the latest route and leave this screen.</p>
6. <input type="checkbox"/>	Repeat steps 2-5 for all other MP server groups	The routes entered in this procedure should now be configured on all MPs in the server group for the first MP you selected. If you have additional MP server groups, repeat from step 2 but this time, select an MP from the next MP server group. Continue until you have covered all MP server groups.


5.3 Configure DSCP (Optional)

Procedure 31. Configure DSCP Values for Outgoing Traffic (Optional)

STEP #	Procedure	Description
		<p>This procedure configures the DSCP values for outgoing packets on servers. DSCP values can be applied to an outbound interface as a whole, or to all outbound traffic using a specific TCP or SCTP source port. This step is optional and should only be executed if has been decided that your network uses packet DSCP markings for Quality-of-Service purposes.</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>


STEP #	Procedure	Description
1. <input type="checkbox"/>	Primary NOAM VIP GUI: Establish GUI session on the NOAM VIP	<p>Establish a GUI session on the NOAM by using the NOAM VIP address. Login as the guiadmin user.</p>  <p>Establish a GUI session on the NOAM by using the NOAM VIP address. Login as the guiadmin user.</p> <p>ORACLE®</p> <p>Oracle System Login</p> <p>Mon Jul 11 13:59:37 2016 EDT</p> <p>Log In Enter your username and password to log in</p> <p>Username: <input type="text"/></p> <p>Password: <input type="password"/></p> <p><input type="checkbox"/> Change password</p> <p>Log In</p> <p>Welcome to the Oracle System Login.</p> <p>This application is designed to work with most modern HTML5 compliant browsers and uses both JavaScript and cookies. Please refer to the Oracle Software Web Browser Support Policy for details.</p> <p>Unauthorized access is prohibited.</p> <p><small>Oracle and Java are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.</small></p> <p><small>Copyright © 2010, 2016, Oracle and/or its affiliates. All rights reserved.</small></p>


STEP #	Procedure	Description
2. <input type="checkbox"/>	Primary NOAM VIP GUI: Option 1: Configure interface DSCP	<p>Note: The values displayed in the screenshots are for demonstration purposes only. The exact DSCP values for your site will vary.</p> <ol style="list-style-type: none"> 1. Navigate to Configuration > Networking>DSCP > Interface DSCP.  2. Select the server to configure from the list of servers on the 2nd line. You can view all servers with Entire Network selected; or limit yourself to a particular server group by clicking on the server group name's tab.  3. Click Insert.  4. Select the network Interface from the list, and type the DSCP value to apply to packets leaving this interface.  5. Click OK if there are no more interfaces on this server to configure, or Apply to finish this interface and continue with more interfaces by selecting them from the list and typing their DSCP values.



STEP #	Procedure	Description
3. <input type="checkbox"/>	Primary NOAM VIP GUI: Option 2: Configure port DSCP	<p>Note: The values displayed in the screenshots are for demonstration purposes only. The exact DSCP values for your site will vary.</p> <ol style="list-style-type: none"> 1. Navigate to Configuration > Networking > DSCP > Port DSCP.  2. Select the server to configure from the list of servers on the 2nd line. You can view all servers with Entire Network selected; or limit yourself to a particular server group by clicking on the server group name's tab. 3. Click Insert. <p>Main Menu: Configuration > DSCP > Port DSCP</p>  <p>4. Type the source Port and DSCP value, and select the transport Protocol.</p> <p>Main Menu: Configuration > DSCP > Port DSCI</p>  <p>Insert DSCP by Port on ZombieNOAM2</p>  <p>5. Click OK if there are no more port DSCPs on this server to configure, or Apply to finish this port entry and continue entering more port DSCP mappings.</p>
4. <input type="checkbox"/>	Repeat for additional servers	Repeat steps 2-3 for all remaining servers.


5.4 Configure IP Front End (Optional)


Procedure 32. IP Front End (IPFE) Configuration

STEP #	Procedure	Description
<p>This procedure configures IP Front End (IPFE) and optimizes performance.</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>		
<p>1. <input type="checkbox"/> SOAM VIP: Login</p> <p>Log into the SOAM VIP GUI as the guiadmin user.</p> 		
1.	SOAM VIP: Login	<p>Log into the SOAM VIP GUI as the guiadmin user.</p> 

STEP #	Procedure	Description																		
2. <input type="checkbox"/>	SOAM VIP: Configuration of replication IPFE association data	<ol style="list-style-type: none"> 1. Navigate to IPFE > Configuration > Options.  2. Type the IP address of the 1st IPFE in the IPFE-A1 IP Address field and the IP address of the 2nd IPFE in the IPFE-A2 IP Address field. 3. If applicable, type the address of the 3rd and 4th IPFE servers in IPFE-B1 IP Address and IPFE-B2 IP Address fields. <table border="1" data-bbox="497 644 1428 876"> <thead> <tr> <th data-bbox="497 644 595 665">Variable</th> <th data-bbox="595 644 1003 665">Value</th> <th data-bbox="1003 644 1428 665">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="497 665 595 686">Inter-IPFE Synchronization</td> <td data-bbox="595 665 1003 686"></td> <td data-bbox="1003 665 1428 686"></td> </tr> <tr> <td data-bbox="497 686 595 749">IPFE-A1 IP Address</td> <td data-bbox="595 686 1003 749">169.254.1.26 - IPFE1</td> <td data-bbox="1003 686 1428 749">IPv4 or IPv6 address of IPFE-A1. This selection is disabled when a Target Set has IPFE-A1 selected as Active.</td> </tr> <tr> <td data-bbox="497 749 595 813">IPFE-A2 IP Address</td> <td data-bbox="595 749 1003 813">169.254.1.27 - IPFE2</td> <td data-bbox="1003 749 1428 813">IPv4 or IPv6 address of IPFE-A2. This selection is disabled when a Target Set has IPFE-A2 selected as Active.</td> </tr> <tr> <td data-bbox="497 813 595 876">IPFE-B1 IP Address</td> <td data-bbox="595 813 1003 876"><unset></td> <td data-bbox="1003 813 1428 876">IPv4 or IPv6 address of IPFE-B1. This selection is disabled when a Target Set has IPFE-B1 selected as Active.</td> </tr> <tr> <td data-bbox="497 876 595 939">IPFE-B2 IP Address</td> <td data-bbox="595 876 1003 939"><unset></td> <td data-bbox="1003 876 1428 939">IPv4 or IPv6 address of IPFE-B2. This selection is disabled when a Target Set has IPFE-B2 selected as Active.</td> </tr> </tbody> </table> <p>Note: It is recommended the address reside on the IMI (Internal Management Interface) network.</p> <p>Note: IPFE-A1 and IPFE-A2 must have connectivity between each other using these addresses. The same applies with IPFE-B1 and IPFE-B2.</p>	Variable	Value	Description	Inter-IPFE Synchronization			IPFE-A1 IP Address	169.254.1.26 - IPFE1	IPv4 or IPv6 address of IPFE-A1. This selection is disabled when a Target Set has IPFE-A1 selected as Active.	IPFE-A2 IP Address	169.254.1.27 - IPFE2	IPv4 or IPv6 address of IPFE-A2. This selection is disabled when a Target Set has IPFE-A2 selected as Active.	IPFE-B1 IP Address	<unset>	IPv4 or IPv6 address of IPFE-B1. This selection is disabled when a Target Set has IPFE-B1 selected as Active.	IPFE-B2 IP Address	<unset>	IPv4 or IPv6 address of IPFE-B2. This selection is disabled when a Target Set has IPFE-B2 selected as Active.
Variable	Value	Description																		
Inter-IPFE Synchronization																				
IPFE-A1 IP Address	169.254.1.26 - IPFE1	IPv4 or IPv6 address of IPFE-A1. This selection is disabled when a Target Set has IPFE-A1 selected as Active.																		
IPFE-A2 IP Address	169.254.1.27 - IPFE2	IPv4 or IPv6 address of IPFE-A2. This selection is disabled when a Target Set has IPFE-A2 selected as Active.																		
IPFE-B1 IP Address	<unset>	IPv4 or IPv6 address of IPFE-B1. This selection is disabled when a Target Set has IPFE-B1 selected as Active.																		
IPFE-B2 IP Address	<unset>	IPv4 or IPv6 address of IPFE-B2. This selection is disabled when a Target Set has IPFE-B2 selected as Active.																		

STEP #	Procedure	Description						
3. <input type="checkbox"/>	SOAM VIP: Configuration of IPFE target sets (Part 1)	<ol style="list-style-type: none"> 1. Log into the SOAM VIP GUI as the guiadmin user. 2. Navigate to IPFE > Configuration > Target Sets.  <ol style="list-style-type: none"> 3. Click either Insert IPv4 or Insert IPv6 depending on the IP version of the target set you plan to use. <p>This screen displays the following configurable settings:</p> <p>Protocols: Protocols the target set supports.</p> <table border="1"> <tr> <td data-bbox="514 686 660 792">Protocols</td> <td data-bbox="660 686 1052 792"> <input type="radio"/> TCP only <input type="radio"/> SCTP only <input checked="" type="radio"/> Both TCP and SCTP </td> </tr> </table> <p>Delete Age: Specifies when the IPFE should remove its association data for a connection. Any packets presenting a source IP address/port combination that had been previously stored as association state but have been idle longer than the Delete Age configuration is treated as a new connection and does not automatically go to the same application server.</p> <table border="1"> <tr> <td data-bbox="514 1045 660 1108">Delete Age *</td> <td data-bbox="660 1045 1003 1108">600</td> </tr> </table> <p>Load Balance Algorithm: Hash or Least Load options.</p> <table border="1"> <tr> <td data-bbox="514 1214 660 1277">Load Balance Algorithm</td> <td data-bbox="660 1214 1003 1277"> <input type="radio"/> Hash <input checked="" type="radio"/> Least Load </td> </tr> </table> <p>Note: For the IPFE to provide Least Load distribution, navigate to IPFE > Configuration > Options, Monitoring Protocol must be set to Heartbeat so the application servers can provide the load information the IPFE uses to select the least-loaded server for connections.</p>  <p>Note: The Least Load option is the default setting, and is the recommended option with exception of unique backward compatibility scenarios.</p>	Protocols	<input type="radio"/> TCP only <input type="radio"/> SCTP only <input checked="" type="radio"/> Both TCP and SCTP	Delete Age *	600	Load Balance Algorithm	<input type="radio"/> Hash <input checked="" type="radio"/> Least Load
Protocols	<input type="radio"/> TCP only <input type="radio"/> SCTP only <input checked="" type="radio"/> Both TCP and SCTP							
Delete Age *	600							
Load Balance Algorithm	<input type="radio"/> Hash <input checked="" type="radio"/> Least Load							
4. <input type="checkbox"/>	SOAM VIP: Configuration of IPFE target sets (Part 2)	<ol style="list-style-type: none"> 1. Navigate to IPFE > Configuration > Target Sets. 						

STEP #	Procedure	Description										
		 <p>(Optional): If you have selected the Least Load algorithm, then you may configure the following fields to adjust the algorithm's behavior:</p> <p>MPS Factor: Messages per Second (MPS) is one component of the least load algorithm. This field allows you to set it from 0 (not used in load calculations) to 100 (the only component used for load calculations). It is recommended that IPFE connections have Reserved Ingress MPS set to something other than the default, which is 0. To configure Reserved Ingress MPS, navigate to Main Menu > Diameter > Configuration > Configuration Sets > Capacity Configuration. If you choose not to use Reserved Ingress MPS, set MPS Factor to 0, and Connection Count Factor, described below, to 100.</p> <p>Connection Count Factor: This is the other component of the least load algorithm. This field allows you to set it from 0 (not used in load calculations) to 100 (the only component used for load calculations). Increase this setting if connection storms (the arrival of many connections at a very rapid rate) are a concern.</p> <p>MPS Factor * <input type="text" value="50"/></p> <p>Connection Count Factor * <input type="text" value="50"/></p> <p>Allowed Deviation: Percentage within which two application server's load calculation results are considered to be equal. If very short, intense connection bursts are expected to occur, increase the value to smooth out the distribution.</p> <p>Allowed Deviation * <input type="text" value="5"/></p> <p>Primary Public IP Address: IP address for the target set.</p> <p>Public IP Address</p> <table border="1"> <tr> <td>Address *</td> <td><input type="text"/></td> </tr> </table> <p>Active IPFE</p> <table border="1"> <tr> <td>IPFE A1</td> <td>-----</td> <td>IPFE A2</td> <td><input checked="" type="radio"/></td> </tr> <tr> <td>IPFE B1</td> <td>-----</td> <td>IPFE B2</td> <td><input type="radio"/></td> </tr> </table> <p>Note: This address must reside on the XSI (External Signaling Interface) network because it is used by the application clients to reach the application servers. This address MUST NOT be a real interface</p>	Address *	<input type="text"/>	IPFE A1	-----	IPFE A2	<input checked="" type="radio"/>	IPFE B1	-----	IPFE B2	<input type="radio"/>
Address *	<input type="text"/>											
IPFE A1	-----	IPFE A2	<input checked="" type="radio"/>									
IPFE B1	-----	IPFE B2	<input type="radio"/>									

STEP #	Procedure	Description
		<p>address (that is, must not be associated with a network interface card).</p> <p>Active IPFE: IPFE to handle the traffic for the target set address.</p> <p>Secondary Public IP Address: If this target set supports either multi-homed SCTP or Both TCP and SCTP, provide a Secondary IP Address.</p>  <p>Note: A secondary address is required to support SCTP multi-homing. A secondary address can support TCP, but the TCP connections are not multi-homed.</p> <p>Note: If SCTP multi-homing is to be supported, select the mate IPFE of the Active IPFE for the Active IPFE for secondary address to ensure SCTP failover functions as designed.</p> <p>Target Set IP List: Select an IP address, a secondary IP address if supporting SCTP multi-homing, a description, and a weight for the application server.</p>  <p>Note: The IP address must be on the XSI network since they must be on the same network as the target set address. This address must also match the IP version of the target set address (IPv4 or IPv6). If the Secondary Public IP Address is configured, it must reside on the same application server as the first IP address.</p> <p>Note: If all application servers have an equal weight (for example, 100, which is the default), they have an equal chance of being selected. Application servers with larger weights have a greater chance of being selected.</p> <ol style="list-style-type: none"> 2. Click Add to add more application servers (up to 16). 3. Click Apply. <p style="text-align: center;">Ok Apply Cancel</p>

STEP #	Procedure	Description
5. <input type="checkbox"/>	SOAM VIP: Repeat for additional configuration of IPFE target sets	Repeat for steps 3 and 4 for each target set (up to 16). At least one target set must be configured.

5.5 Configure the Desired MTU value

By default DSR defines MTU size of all its management and/or signaling networks as 1500 bytes. If the configured virtual network(s) on cloud is VXLAN based and MTU size defined/negotiated on it is 1500 bytes, then we need to accommodate VXLAN header (size 65 bytes) within these 1500 bytes.


STEP #	Procedure	Description
<p>This procedure configures the desired MTU value. Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number. If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>		
<p>1. <input type="checkbox"/></p> <p>Verify the MTU on DSR system</p> <p>Verify the MTU on DSR system, by executing: <code>iqt -pE NetworkDeviceOption</code></p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <code>DeviceOption_ID=0 Keyword=MTU Device_ID=0 Value=1500 DeviceOption_ID=1 Keyword=bootProto Device_ID=0 Value=none DeviceOption_ID=2 Keyword=onboot Device_ID=0 Value=yes DeviceOption_ID=3 Keyword=MTU Device_ID=1 Value=1500 DeviceOption_ID=4 Keyword=bootProto Device_ID=1 Value=none DeviceOption_ID=5 Keyword=onboot Device_ID=1 Value=yes DeviceOption_ID=6 Keyword=MTU Device_ID=2 Value=1500 DeviceOption_ID=7 Keyword=bootProto Device_ID=2 Value=none DeviceOption_ID=8 Keyword=onboot Device_ID=2 Value=yes DeviceOption_ID=9 Keyword=MTU Device_ID=3 Value=1500 DeviceOption_ID=10 Keyword=bootProto Device_ID=3 Value=none DeviceOption_ID=11 Keyword=onboot Device_ID=3 Value=yes DeviceOption_ID=12 Keyword=MTU Device_ID=4 Value=1500 DeviceOption_ID=13 Keyword=bootProto Device_ID=4 Value=none DeviceOption_ID=14 Keyword=onboot Device_ID=4 Value=yes</code> </div> <p>Sample output:</p>		
<p>2. <input type="checkbox"/></p> <p>Change the MTU value on DSR system (Optional)</p> <p>If the MTU value is 1500 bytes, change it to 1435 bytes, by executing: <code>iset -fValue=1435 NetworkDeviceOption where Keyword='MTU'" ===== changed 256 records =====</code></p> <p>Wait for few minutes.</p>		


3.	Verify the MTU value	<p>Verify the MTU value on DSR system by executing: <code>ip addr</code></p> <p>Sample output:</p> <pre>1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00 inet 127.0.0.1/8 scope host lo inet6 ::1/128 scope host valid_lft forever preferred_lft forever 2: control: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1450 qdisc pfifo_fast state UP qlen 1000 link/ether 02:79:b5:f7:65:0e brd ff:ff:ff:ff:ff:ff inet 192.168.1.32/24 brd 192.168.1.255 scope global control inet6 fe80::79:b5ff:fe7:650e/64 scope link valid_lft forever preferred_lft forever 3: xmi: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1435 qdisc pfifo_fast state UP qlen 1000 link/ether 02:90:04:c6:3b:e1 brd ff:ff:ff:ff:ff:ff inet 10.75.198.37/25 brd 10.75.198.127 scope global xmi inet 10.75.198.4/25 scope global secondary xmi inet6 2606:b400:605:b821:90:4ff:fec6:3be1/64 scope global dynamic valid_lft 2591870sec preferred_lft 604670sec inet6 fe80::90:4ff:fec6:3be1/64 scope link valid_lft forever preferred_lft forever 4: imi: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1435 qdisc pfifo_fast state UP qlen 1000 link/ether 02:3b:48:96:3c:61 brd ff:ff:ff:ff:ff:ff inet 192.168.100.32/24 brd 192.168.100.255 scope global imi inet6 fe80::3b:48ff:fe96:3c61/64 scope link valid_lft forever preferred_lft forever</pre> <p>Verify on all nodes: <code>iqt -pE NetworkDeviceOption</code></p> <p>Sample output:</p> <pre>DeviceOption_ID=0 Keyword=MTU Device_ID=0 Value=1435 DeviceOption_ID=1 Keyword=bootProto Device_ID=0 Value=none DeviceOption_ID=2 Keyword=onboot Device_ID=0 Value=yes DeviceOption_ID=3 Keyword=MTU Device_ID=1 Value=1435 DeviceOption_ID=4 Keyword=bootProto Device_ID=1 Value=none DeviceOption_ID=5 Keyword=onboot Device_ID=1 Value=yes DeviceOption_ID=6 Keyword=MTU Device_ID=2 Value=1435 DeviceOption_ID=7 Keyword=bootProto Device_ID=2 Value=none DeviceOption_ID=8 Keyword=onboot Device_ID=2 Value=yes DeviceOption_ID=9 Keyword=MTU Device_ID=3 Value=1435 DeviceOption_ID=10 Keyword=bootProto Device_ID=3 Value=none DeviceOption_ID=11 Keyword=onboot Device_ID=3 Value=yes DeviceOption_ID=12 Keyword=MTU Device_ID=4 Value=1435 DeviceOption_ID=13 Keyword=bootProto Device_ID=4 Value=none DeviceOption_ID=14 Keyword=onboot Device_ID=4 Value=yes</pre>
----	----------------------	---

5.6 SNMP Configuration (Optional)

Procedure 33. Configure SNMP Trap Receiver(s) (Optional)

STEP #	Procedure	Description
		<p>This procedure configures forwarding of SNMP.</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step</p>

STEP #	Procedure	Description				
		<p>number. If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>				
4. <input type="checkbox"/>	NOAM VIP: Configure system-wide SNMP trap receiver(s)	<p>1. Using a web browser, log into the NOAM VIP as the guiadmin user. Navigate to Administration > SNMP.</p>  <p>2. Click Insert.</p> <p>3. Type the IP address or Hostname of the Network Management Station (NMS) to forward traps to. This IP should be reachable from the NOAM's XMI network.</p> <p>4. Continue to add secondary manager IPs in the corresponding fields, if needed.</p> <p>Manager 1 <input type="text"/></p> <p>Traps Enabled checkboxes can be marked on a per manager basis.</p> <p>Traps Enabled <input type="checkbox"/> Manager 1 <input type="checkbox"/> Manager 2 <input type="checkbox"/> Manager 3 <input type="checkbox"/> Manager 4 <input type="checkbox"/> Manager 5</p> <p>Type the SNMP Community Name.</p> <table border="1"> <tr> <td data-bbox="514 1383 938 1425">SNMPv2c Read-Only Community Name</td> <td data-bbox="938 1383 1346 1425">*****</td> </tr> <tr> <td data-bbox="514 1488 938 1531">SNMPv2c Read-Write Community Name</td> <td data-bbox="938 1488 1346 1531"></td> </tr> </table> <p>5. Leave all other fields with their default values.</p> <p>6. Click OK.</p>	SNMPv2c Read-Only Community Name	*****	SNMPv2c Read-Write Community Name	
SNMPv2c Read-Only Community Name	*****					
SNMPv2c Read-Write Community Name						
5. <input type="checkbox"/>	NOAM VIP: Enable traps from individual servers (Optional)	<p>Note: By default, SNMP traps from MPs are aggregated and displayed at the active NOAM. If instead, you want every server to send its own traps directly to the NMS, then execute this procedure.</p> <p>This procedure requires all servers, including MPs, have an XMI interface on which the customer SNMP Target server (NMS) is reachable.</p> <p>1. Using a web browser, log into the NOAM VIP as the guiadmin user.</p>				

STEP #	Procedure	Description
		<p>1. Navigate to Administration > SNMP.</p>  <p>2. Make sure the Enabled checkbox is marked, if not, mark it as shown below:</p>  <p>3. Click Apply and verify the data is committed.</p>

5.7 Create iDIH Virtual Machines - VMware (Optional)

Procedure 34. (VMware only) Create iDIH Oracle, Mediation, and Application VMs (Optional)



STEP #	Procedure	Description
		<p>This procedure creates the iDIH Oracle, Mediation, and Application guest.</p> <p>Needed material: iDIH Oracle OVA, iDIH Mediation OVA, and iDIH Application OVA.</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>
1.	<input type="checkbox"/> Add the iDIH Oracle OVA to VMware	<ol style="list-style-type: none"> 1. Launch the VMware client of your choice. 2. Add the iDIH Oracle OVA image to the VMware catalog or repository. Follow the instructions provided by the Cloud solutions manufacturer.
2.	<input type="checkbox"/> Create the Oracle VM from the OVA image	<ol style="list-style-type: none"> 1. Browse the library or repository that you placed the iDIH Oracle OVA image. 2. Deploy the OVA Image using vSphere Client or the vSphere Web Client. 3. Name the iDIH Oracle VM and select the data store.
3.	<input type="checkbox"/> Configure resources for the iDIH Oracle VM	<ol style="list-style-type: none"> 1. Configure the iDIH Oracle VM per the resource profiles defined in [24] DSR Cloud Benchmarking Guide using the vSphere client or the vSphere web client. 2. Record the Ethernet addresses associated with each interface and the virtual network with which it is associated. <p>Note: Make sure the order of the interface creation is XMI, INT, and then IMI, if there is any. Only the Mediation VM requires the IMI interface.</p>

STEP #	Procedure	Description
4. <input type="checkbox"/>	iDIH Oracle VM Only: Create a raw storage block device (external device)	<p>Note: This step is ONLY required for iDIH Oracle VM.</p> <p>Create an extra disk for the Oracle VM. Add the second disk using the vSphere client or the vSphere web client.</p>
5. <input type="checkbox"/>	Power on the iDIH Oracle VM	Use the vSphere client or vSphere web client to power on the iDIH Oracle VM .
6. <input type="checkbox"/>	iDIH Oracle VM Only: Verify the extra/second disk exists	<p>Note: This step is ONLY required for iDIH Oracle VM.</p> <p>Check if the raw storage block device (external disk) added in step 3 exists by executing any of these commands:</p> <pre>\$ ls /dev/[sv]db \$ fdisk -l \$ df -h</pre> <p>Note: Please DO NOT mount or format the added raw block device. Oracle ASM (Automatic Storage Management) automatically manages it. If you see it has been mounted, unmount it and make sure to completely remove the entry in the /etc/fstab.</p>
7. <input type="checkbox"/>	Repeat	<p>Repeat steps 1 through 6 for the following VMs. Use unique labels for the VM names:</p> <ul style="list-style-type: none"> iDIH Application iDIH Mediation

5.8 Create iDIH Virtual Machines - KVM/OpenStack (Optional)

Procedure 35. (KVM/OpenStack Only) Create iDIH Oracle, Mediation, and Application VMs (Optional)

STEP #	Procedure	Description
<p>This procedure creates the iDIH Oracle, Mediation, and Application guest.</p> <p>Needed material: iDIH Oracle OVA, iDIH Mediation OVA, and iDIH Application OVA</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>		
<p>1. <input type="checkbox"/> Add the iDIH Oracle OVA to KVM/Open Stack</p> <p>1. Copy the OVA file to the OpenStack control node.</p> <pre>\$ scp oracle-8.2.x.x.x.ova admusr@node:~</pre> <p>2. Log into the OpenStack control node.</p> <pre>\$ ssh admusr@node</pre> <p>3. In an empty directory, unpack the OVA file using tar.</p> <pre>\$ tar xvf oracle-8.2.x.x.x.ova</pre> <p>4. One of the unpacked files has a .vmdk suffix. This is the VM image file that must be imported.</p> <p>oracle-8.2.x.x.x-disk1.vmdk</p> <p>Note: The OVA format only supports files with a max size of 8GB, so a vmdk file larger than that is split. You should be able to concatenate the files together to merge them back into one file:</p> <pre>\$ cat ORA-80_x_x.vmdk.000000000 ORA-80_x_x.vmdk.000000001 > ORA-80_x_x.vmdk</pre> <p>5. Source the OpenStack admin user credentials.</p> <pre>\$. keystonerc_admin</pre> <p>6. Select an informative name for the new image.</p> <p>ORA-8.2_x_x</p> <p>7. Import the image using the glance utility from the command line.</p> <pre>\$ glance image-create --name oracle-8.2.x.x.x-original --visibility public --protected false --progress --container-format bare --disk-format vmdk --file oracle-8.2.x.x.x-disk1.vmdk</pre> <p>This process takes about 5 minutes depending on the underlying infrastructure.</p> <p>8. (Optional – Steps 8 and 9 are not needed if VMDK is used.) Convert VMDK to QCOW2 format.</p> <p>Use the qemu-img tool to create a qcows2 image file using this command.</p> <pre>qemu-img convert -f vmdk -O qcows2 <VMDK filename> <QCOW2 filename></pre> <p>For example:</p> <pre>qemu-img convert -f vmdk -O qcows2 DSR-82_12_0.vmdk DSR-</pre>		

STEP #	Procedure	Description																																																																						
		<p>82_12_0.qcow2</p> <p>Install the qemu-img tool (if not already installed) using this yum command. <code>sudo yum install qemu-img</code></p> <p>9. Import the converted qcow2 image using the glance utility from the command line.</p> <pre>\$ glance image-create --name dsr-x.x.x-original --is-public True --is-protected False --progress --container-format bare --disk-format qcow2 --file DSR-x.x.x-disk1.qcow2</pre> <p>This process take about 5 minutes depending on the underlying infrastructure.</p>																																																																						
2. <input type="checkbox"/>	Create flavors for iDIH	<p>Examine the storage recommendations in the resource profiles defined in [24] DSR Cloud Benchmarking Guide. A block storage must be created and attached for the Oracle VM. For example, create an idih.db for the Oracle database with a 100GB ephemeral disk.</p>  <table border="1"> <thead> <tr> <th>Flavor Name</th> <th>VCPUs</th> <th>RAM</th> <th>Root Disk</th> <th>Ephemeral Disk</th> <th>Swap Disk</th> <th>ID</th> <th>Public</th> <th>Metadata</th> <th>Actions</th> </tr> </thead> <tbody> <tr> <td>dsr.so.no</td> <td>4</td> <td>6GB</td> <td>60GB</td> <td>0GB</td> <td>0MB</td> <td>48c0c717-2b78-401c-b24e-4455e26159ac</td> <td>Yes</td> <td>No</td> <td>Edit Flavor</td> </tr> <tr> <td>idih</td> <td>4</td> <td>8GB</td> <td>64GB</td> <td>0GB</td> <td>0MB</td> <td>50eb1952-d9bc-418a-ab2d-66e923d460d1</td> <td>Yes</td> <td>No</td> <td>Edit Flavor</td> </tr> <tr> <td>idih.db</td> <td>4</td> <td>8GB</td> <td>120GB</td> <td>100GB</td> <td>0MB</td> <td>4936397c-827a-499d-aad4-4784e0bd4e0</td> <td>Yes</td> <td>No</td> <td>Edit Flavor</td> </tr> <tr> <td>sds</td> <td>4</td> <td>12GB</td> <td>125GB</td> <td>0GB</td> <td>0MB</td> <td>537c4225-d902-43f1-b6fb4163a67bc1ec</td> <td>Yes</td> <td>No</td> <td>Edit Flavor</td> </tr> <tr> <td>dsr.ipfe</td> <td>4</td> <td>16GB</td> <td>60GB</td> <td>0GB</td> <td>0MB</td> <td>793a6712-2659-4dad-894d-0ad46a7a8a2</td> <td>Yes</td> <td>No</td> <td>Edit Flavor</td> </tr> <tr> <td>dsr.mp</td> <td>8</td> <td>16GB</td> <td>60GB</td> <td>0GB</td> <td>0MB</td> <td>3a6f6973-293c-498f-bef9-a6810dffa6cb</td> <td>Yes</td> <td>No</td> <td>Edit Flavor</td> </tr> </tbody> </table>	Flavor Name	VCPUs	RAM	Root Disk	Ephemeral Disk	Swap Disk	ID	Public	Metadata	Actions	dsr.so.no	4	6GB	60GB	0GB	0MB	48c0c717-2b78-401c-b24e-4455e26159ac	Yes	No	Edit Flavor	idih	4	8GB	64GB	0GB	0MB	50eb1952-d9bc-418a-ab2d-66e923d460d1	Yes	No	Edit Flavor	idih.db	4	8GB	120GB	100GB	0MB	4936397c-827a-499d-aad4-4784e0bd4e0	Yes	No	Edit Flavor	sds	4	12GB	125GB	0GB	0MB	537c4225-d902-43f1-b6fb4163a67bc1ec	Yes	No	Edit Flavor	dsr.ipfe	4	16GB	60GB	0GB	0MB	793a6712-2659-4dad-894d-0ad46a7a8a2	Yes	No	Edit Flavor	dsr.mp	8	16GB	60GB	0GB	0MB	3a6f6973-293c-498f-bef9-a6810dffa6cb	Yes	No	Edit Flavor
Flavor Name	VCPUs	RAM	Root Disk	Ephemeral Disk	Swap Disk	ID	Public	Metadata	Actions																																																															
dsr.so.no	4	6GB	60GB	0GB	0MB	48c0c717-2b78-401c-b24e-4455e26159ac	Yes	No	Edit Flavor																																																															
idih	4	8GB	64GB	0GB	0MB	50eb1952-d9bc-418a-ab2d-66e923d460d1	Yes	No	Edit Flavor																																																															
idih.db	4	8GB	120GB	100GB	0MB	4936397c-827a-499d-aad4-4784e0bd4e0	Yes	No	Edit Flavor																																																															
sds	4	12GB	125GB	0GB	0MB	537c4225-d902-43f1-b6fb4163a67bc1ec	Yes	No	Edit Flavor																																																															
dsr.ipfe	4	16GB	60GB	0GB	0MB	793a6712-2659-4dad-894d-0ad46a7a8a2	Yes	No	Edit Flavor																																																															
dsr.mp	8	16GB	60GB	0GB	0MB	3a6f6973-293c-498f-bef9-a6810dffa6cb	Yes	No	Edit Flavor																																																															
3. <input type="checkbox"/>	Create network interfaces	<p>Examine the network interface recommendations defined in [24] DSR Cloud Benchmarking Guide. Network ports must be created for each recommended interface. For example:</p>  <table border="1"> <thead> <tr> <th>Project</th> <th>Network Name</th> <th>Subnets Associated</th> <th>DHCP Agents</th> <th>Shared</th> <th>Status</th> <th>Admin State</th> <th>Actions</th> </tr> </thead> <tbody> <tr> <td>admin</td> <td>img_network</td> <td>img_subnet 192.168.99.0/24</td> <td>1</td> <td>No</td> <td>Active</td> <td>UP</td> <td>Edit Network</td> </tr> <tr> <td>admin</td> <td>int_network</td> <td>int_subnet 10.254.254.0/27</td> <td>1</td> <td>No</td> <td>Active</td> <td>UP</td> <td>Edit Network</td> </tr> <tr> <td>admin</td> <td>private_network</td> <td>private_subnet 192.168.100.0/24</td> <td>1</td> <td>No</td> <td>Active</td> <td>UP</td> <td>Edit Network</td> </tr> <tr> <td>admin</td> <td>xsi1_network</td> <td>xsi1_subnet 192.168.101.0/24</td> <td>1</td> <td>No</td> <td>Active</td> <td>UP</td> <td>Edit Network</td> </tr> <tr> <td>admin</td> <td>xsi2_network</td> <td>xsi2_subnet 192.168.102.0/24</td> <td>1</td> <td>No</td> <td>Active</td> <td>UP</td> <td>Edit Network</td> </tr> <tr> <td>admin</td> <td>external_network</td> <td>public_subnet 10.250.65.0/24</td> <td>1</td> <td>Yes</td> <td>Active</td> <td>UP</td> <td>Edit Network</td> </tr> </tbody> </table>	Project	Network Name	Subnets Associated	DHCP Agents	Shared	Status	Admin State	Actions	admin	img_network	img_subnet 192.168.99.0/24	1	No	Active	UP	Edit Network	admin	int_network	int_subnet 10.254.254.0/27	1	No	Active	UP	Edit Network	admin	private_network	private_subnet 192.168.100.0/24	1	No	Active	UP	Edit Network	admin	xsi1_network	xsi1_subnet 192.168.101.0/24	1	No	Active	UP	Edit Network	admin	xsi2_network	xsi2_subnet 192.168.102.0/24	1	No	Active	UP	Edit Network	admin	external_network	public_subnet 10.250.65.0/24	1	Yes	Active	UP	Edit Network														
Project	Network Name	Subnets Associated	DHCP Agents	Shared	Status	Admin State	Actions																																																																	
admin	img_network	img_subnet 192.168.99.0/24	1	No	Active	UP	Edit Network																																																																	
admin	int_network	int_subnet 10.254.254.0/27	1	No	Active	UP	Edit Network																																																																	
admin	private_network	private_subnet 192.168.100.0/24	1	No	Active	UP	Edit Network																																																																	
admin	xsi1_network	xsi1_subnet 192.168.101.0/24	1	No	Active	UP	Edit Network																																																																	
admin	xsi2_network	xsi2_subnet 192.168.102.0/24	1	No	Active	UP	Edit Network																																																																	
admin	external_network	public_subnet 10.250.65.0/24	1	Yes	Active	UP	Edit Network																																																																	
4. <input type="checkbox"/>	Create and boot the iDIH VM instance	<p>1. Get the following configuration values.</p> <p>The image ID.</p> <pre>\$ glance image-list</pre>																																																																						

STEP #	Procedure	Description
	from the glance image	<p>The flavor ID.</p> <pre>\$ nova flavor-list</pre> <p>The network ID(s)</p> <pre>\$ neutron net-list</pre> <p>An informative name for the instance.</p> <p>iDIH-Oracle iDIH-Mediation iDIH-Application</p> <p>2. Create and boot the VM instance.</p> <p>The instance must be owned by the DSR tenant user, not the admin user. Source the credentials of the DSR tenant user and issue the following command. Use one --nic argument for each IP/interface. Number of IP/interfaces for each VM type must conform with the interface-to-network mappings defined in [24] DSR Cloud Benchmarking Guide.</p> <p>Note: IPv6 addresses should use the v6-fixed-ip argument instead of v4-fixed-ip.</p> <p>For Oracle VM Only</p> <p>Create the ephemeral storage for only the Oracle VM.</p> <pre>\$ nova boot --image <image ID> --flavor <flavor id or name> --nic net-id=<xmi network id>,v4-fixed-ip=<xmi ip address> --nic net-id=<int network id>,v4-fixed-ip=<int ip address> --ephemeral size=100 --config-drive true <instance name></pre> <p>For example:</p> <pre>\$ nova boot --image 7e881048-190c-4b66-b26e-dc5b9dc3c07f --flavor idih.db --nic net-id=e96cb10a-9514-4702-b0c5-64fc99eb3fdd,v4-fixed-ip=10.250.65.161 --nic net-id=674b8461-ffed-4818-8dea-7544f9c06e5f,v4-fixed-ip=10.254.254.2 --ephemeral size=100 -config-drive true iDIH-Oracle</pre> <p>For Application VM Only</p> <pre>\$ nova boot --image <image ID> --flavor <flavor id or name> --nic net-id=<xmi network id>,v4-fixed-ip=<xmi ip address> --nic net-id=<int network id>,v4-fixed-ip=<int ip address> --config-drive true <instance name></pre> <p>For example:</p> <pre>\$ nova boot --image 7e881048-190c-4b66-b26e-dc5b9dc3c07f --flavor idih.db --nic net-id=e96cb10a-9514-4702-b0c5-64fc99eb3fdd,v4-fixed-ip=10.250.65.161 --nic net-id=674b8461-ffed-4818-8dea-7544f9c06e5f,v4-fixed-ip=10.254.254.4 -config-drive true iDIH-App</pre> <p>For Mediation VM Only</p> <p>For Mediation, add the IMI interface as the IMI interface.</p> <pre>\$ nova boot --image <image ID> --flavor <flavor id or</pre>

STEP #	Procedure	Description
		<pre data-bbox="535 261 1429 375">name> --nic net-id=<xmi network id>,v4-fixed-ip=<xmi ip address> --nic net-id=<int network id>,v4-fixed-ip=<int ip address> --nic net-id=<imi network id>,v4-fixed-ip=<imi ip address> -config-drive true <instance name></pre> <p data-bbox="535 392 698 424">For example:</p> <pre data-bbox="535 441 1405 642">\$ nova boot --image f548c2cd-1ddd-4c56-b619-b49a69af8801 --flavor idih --nic net-id=e96cb10a-9514-4702-b0c5-64fc99eb3fdd,v4-fixed-ip=10.250.65.162 --nic net-id=674b8461-ffed-4818-8dea-7544f9c06e5f,v4-fixed-ip=10.254.254.3 --nic net-id=3d9b9da8-96ad-4f29-9f82-98b00ea30446,v4-fixed-ip=192.168.99.3 -config-drive true iDIH-Mediation</pre> <p data-bbox="486 658 1165 690">3. View the newly created instance using the nova tool.</p> <pre data-bbox="535 707 959 734">\$ nova list --all-tenants</pre> <p data-bbox="486 751 1413 815">The VM takes approximately 5 minutes to boot and may be accessed through both network interfaces and the Horizon console tool.</p>
5. <input type="checkbox"/>	Verify configured interface	<p data-bbox="486 840 1429 925">If DHCP is enabled on the Neutron subnet, VM configures the VNIC with the IP address provided in step 4. To verify, ping the XMI IP address provided with the nova boot... command from step 4:</p> <pre data-bbox="486 941 1152 969">\$ ping <XMI-IP-Provided-During-Nova-Boot></pre> <p data-bbox="486 986 1413 1017">If successfully pinging, ignore the step 6 to manually configuring the interface.</p>


STEP #	Procedure	Description
6. <input type="checkbox"/>	Manually configure interface, if not already done (Optional)	<p>Note: If the instance is already configured with an interface and has successfully pinged (step 5), then ignore this step to configure the interface manually.</p> <ol style="list-style-type: none"> 1. Log into the Horizon GUI as the DSR tenant user. 2. Go to the Compute/Instances section. 3. Click the Name field of the newly created instance. 4. Select the Console tab. 5. Login as the admusr user. 6. Configure the network interfaces, conforming with the interface-to-network mappings defined in [24] DSR Cloud Benchmarking Guide. <pre>\$ sudo netAdm add --onboot=yes --device=eth0 --address=<xmi ip> --netmask=<xmi net mask> \$ sudo netAdm add --onboot=yes --device=eth1 --address=<int ip> --netmask=<int net mask> \$ sudo netAdm add --route=default --device=eth0 --gateway=<xmi gateway ip></pre> An additional interface eth2 needs to be configured ONLY for Mediation VM. To configure the eth2: <pre>\$ sudo netAdm add --onboot=yes --device=eth2 --address=<imi ip> --netmask=<imi net mask></pre> 7. Reboot the VM. It takes approximately 5 minutes for the VM to complete rebooting. <pre>\$ sudo init 6</pre> <p>The new VM should now be accessible using both network and Horizon consoles.</p>
7. <input type="checkbox"/>	Repeat	Repeat steps 1 through 4 for the following VMs. Use unique labels for the VM names: iDIH-Application iDIH-Mediation

5.9 Create iDIH Virtual Machines - OVM-S/OVM-M (Optional)

Procedure 36. (OVM-S/OVM-M). Import Three IDIH OVAs and Create and Configure a VM for Each

STEP #	Procedure	Description
--------	-----------	-------------

STEP #	Procedure	Description
		<p>This procedure imports the IDIH image and creates/configures a VM. Repeat this procedure three times for:</p> <ul style="list-style-type: none"> • IDIH-Oracle (db) • IDIH-Application (app) • IDIH-Mediation (med) <p>Replace XXX in variable names with the different suffix – when repeating.</p> <p>This procedure requires values for these variables:</p> <ul style="list-style-type: none"> • <OVM-M IP> = IP address to access a sh prompt on the OVM server • <URL to IDIH-XXX OVA>= link(s) to a source for each IDIH product image (.ova) • <MyRepository name> = name of the repository in the OVM to hold the product images (.ova) • <ServerPool name> • <VM name> • <OVM network ID for XMI> • <OVM network ID for IDIH Internal> • <OVM network ID for IMI> <p>Execution of this procedure will discover and use the values of these variables:</p> <ul style="list-style-type: none"> • <Virtual Appliance IDIH-XXX OVA ID> • <IDIH-XXX-OVA VM name_vm_vm> • <VM id> • <vCPUs Production> • <Vnic 1 id> • <size in GB> • <VirtualDiskId> • <VirtualDiskName> • <Slot#> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>

STEP #	Procedure	Description
1. <input type="checkbox"/>	Preparation: Access command line of OVM	<p>Refer to Common OVM Manager Tasks (CLI) for setting up the platform.</p> <p>1. Use the respective value for <OVM-M IP> into the command.</p> <pre>ssh -l admin <OVM-M IP> -p 10000</pre> <p>Example: <code>ssh -l admin 100.64.62.221 -p 10000</code></p> <p>Alternate: use a terminal emulation tool like putty.</p> 

STEP #	Procedure	Description
2. □	OVM-M CLI: Import the VirtualAppliance/OVA for IDIH-XXX	<ol style="list-style-type: none"> 1. Use the respective values for <MyRepository name> and <URL to IDIH-XXX OVA> into the command. <pre>OVM>importVirtualAppliance Repository name='<MyRepository name>' url=<URL to IDIH-XXX OVA></pre> Example: <pre>OVM> importVirtualAppliance Repository name='XLab Utility Repo01' url=http://10.240.155.70/iso/IDIH/8.2/ova/oracle- 8.2.0.0.0_82.4.0.ova</pre> 2. Execute the command and validate success. 3. Examine the screen results to find site-specific text for variables in these locations: <pre>Command: importVirtualAppliance Repository name='XLab Utility Repo01' url=http://10.240.155.70/iso/DSR/8.2/ova/DSR- 8.2.0.0.0_82.4.0.ova</pre> <p>Status: Success</p> <p>Time: 2017-04-18 15:23:31,044 EDT</p> <p>JobId: 1492543363365</p> <p>Data:</p> <pre>ID: 1128a1c6ce name: DSR-8.2.0.0.0_82.4.0.ova</pre> 4. Use the respective values for values for these variables (overwrite example). <pre><Virtual Appliance IDIH-XXX OVA ID> = 1128a1c6ce</pre>

STEP #	Procedure	Description
3. □	OVM-M CLI: Get the virtual appliance name. It is used in <IDIH-XXX OVA VM name> in later steps	<ol style="list-style-type: none"> 1. Use the respective values for <Virtual Appliance IDIH-XXX OVA ID> in the command. <code>OVM> show VirtualAppliance id=<Virtual Appliance IDIH-XXX OVA id></code> Example: <code>OVM> show VirtualAppliance id=1128a1c6ce</code> 2. Execute the command and validate success. 3. Examine the screen results to find site-specific text for variables in these locations: Command: <code>show VirtualAppliance id=1128a1c6ce</code> Status: Success Time: 2017-04-18 15:23:53,534 EDT Data: <code>Origin = http://10.240.155.70/iso/DSR/8.2/ova/DSR-8.2.0.0.0_82.4.0.ova</code> <code>Repository = 0004fb0000030000da5738315337bfc7 [XLab Utility Repo01]</code> <code>Virtual Appliance Vm 1 = 11145510c0_vm_vm [vm]</code> <code>Virtual Appliance VirtualDisk 1 = 11145510c0_disk_disk1 [disk1]</code> <code>Id = 11145510c0 [DSR-8.2.0.0.0_82.4.0.ova]</code> <code>Name = DSR-8.2.0.0.0_82.4.0.ova</code> <code>Description = Import URL:</code> <code>http://10.240.155.70/iso/DSR/8.2/ova/DSR-8.2.0.0.0_82.4.0.ova</code> <code>Locked = false</code> 4. Use the respective values for these variables (overwrite example). <code><IDIH-XXX-OVA VM name_vm_vm> = 11145510c0_vm_vm</code>

STEP #	Procedure	Description
4. <input type="checkbox"/>	OVM-M CLI: Create a VM for IDIH-XXX OVA VM	<p>Create a virtual machine from the virtual machine in the OVA virtual appliance.</p> <ol style="list-style-type: none"> 1. Use the respective value for <IDIH-db-OVA VM name_vm_vm> into the command. <pre>OVM> createVmFromVirtualApplianceVm VirtualApplianceVm name=<IDIH-XXX-OVA VM name_vm_vm></pre> <p>Example:</p> <pre>OVM> createVmFromVirtualApplianceVm VirtualApplianceVm name=11145510c0_vm_vm</pre> 2. Execute the command and validate success. 3. Examine the screen results to find site-specific text for variables in these locations: <p>Command: <code>createVmFromVirtualApplianceVm</code> <code>VirtualApplianceVm name=11145510c0_vm_vm</code></p> <p>Status: Success</p> <p>Time: 2017-04-18 16:02:09,141 EDT</p> <p>JobId: 1492545641976</p> <p>Data:</p> <pre>id: 0004fb00000600004a0e02bdf9fc1bcd name: oracle- 8.2.0.0.0_82.4.0.ova</pre> <ol style="list-style-type: none"> 4. Use the respective values for these variables (overwrite example). <code><VM id> = 0004fb00000600004a0e02bdf9fc1bcd</code>
5. <input type="checkbox"/>	OVM-M CLI: Add the VM to the server pool	<ol style="list-style-type: none"> 1. Use the respective values for <VM ID> and <ServerPool name> into the command. <pre>OVM> add Vm id=<VM id> to ServerPool name="<ServerPool name>"</pre> <p>Example:</p> <pre>OVM> add Vm id=0004fb00000600004a0e02bdf9fc1bcd to ServerPool name="XLab Pool 01"</pre> 2. Execute the command and validate success. <p>Note: Refer Server Pool section in Appendix D.2 for further information on Server Pool.</p>

STEP #	Procedure	Description																
6. <input type="checkbox"/>	OVM-M CLI: Edit VM to apply required profile/resources	<ol style="list-style-type: none"> Refer to [24] DSR Cloud Benchmarking Guide for recommended resource. <table border="1" data-bbox="494 302 1432 487"> <thead> <tr> <th data-bbox="494 302 649 439">VM Name</th><th data-bbox="649 302 788 439">vCPUs Lab</th><th data-bbox="788 302 926 439">RAM (GB) Lab</th><th data-bbox="926 302 1065 439">vCPUs Production</th><th data-bbox="1065 302 1204 439">RAM (GB) Production</th><th data-bbox="1204 302 1432 439">Storage (GB) Lab and Production</th></tr> </thead> <tbody> <tr> <td data-bbox="494 439 649 487">Type of guest host</td><td data-bbox="649 439 788 487">#</td><td data-bbox="788 439 926 487">#</td><td data-bbox="926 439 1065 487">#</td><td data-bbox="1065 439 1204 487">#</td><td data-bbox="1204 439 1432 487">#</td></tr> </tbody> </table> <ol style="list-style-type: none"> Use the respective values for <VM ID>, <VM name>, and <vCPUs Production> into the command. <code>OVM> edit Vm id=<VM id> name=<VM name> memory=6144 memoryLimit=6144 cpuCountLimit=<vCPUs Production> cpuCount=<vCPUs Production> domainType=XEN_HVM description="<VM name>"</code> Example: <code>OVM> edit Vm id=0004fb00000600004a0e02bdf9fc1bcd name=na_idih-db memory=6144 memoryLimit=6144 cpuCountLimit=4 cpuCount=4 domainType=XEN_HVM description="na_idih-db"</code> Execute the command and validate success. Now, the VM has a name and resources. 	VM Name	vCPUs Lab	RAM (GB) Lab	vCPUs Production	RAM (GB) Production	Storage (GB) Lab and Production	Type of guest host	#	#	#	#	#				
VM Name	vCPUs Lab	RAM (GB) Lab	vCPUs Production	RAM (GB) Production	Storage (GB) Lab and Production													
Type of guest host	#	#	#	#	#													
7. <input type="checkbox"/>	OVM-M CLI: Determine VNIC ID	<ol style="list-style-type: none"> Use the respective value for <VM name> in the command. <code>OVM> show Vm name=<VM name></code> Example: <code>OVM> show Vm name= na_idih-db</code> Execute the command and validate success. Examine the screen results to find site-specific text for variables in these locations: <code>Vnic 1 = 0004fb0000070000091e1ab5ae291d8a</code> Use the respective values for these variables (overwrite example). <code><Vnic 1 ID> = 0004fb0000070000091e1ab5ae291d8a</code> 																
8. <input type="checkbox"/>	Determine network interfaces for the type of guest host	Refer to [24] DSR Cloud Benchmarking Guide to learn which network interfaces need to be configured for each guest type. The table looks like this: <table border="1" data-bbox="494 1484 1432 1664"> <thead> <tr> <th></th><th data-bbox="649 1484 788 1622">OAM (XMI)</th><th data-bbox="788 1484 926 1622">Loca I (IMI)</th><th data-bbox="926 1484 1065 1622">Sig A (XSI1)</th><th data-bbox="1065 1484 1204 1622">Sig B (XSI2)</th><th data-bbox="1204 1484 1432 1622">Sig C (XSI3-16)</th><th data-bbox="1432 1484 1473 1622">Rep (SBR)</th><th data-bbox="1473 1484 1514 1622">DIH Interna I</th></tr> </thead> <tbody> <tr> <td data-bbox="494 1622 649 1664">Type of guest host</td><td data-bbox="649 1622 788 1664">eth#</td><td data-bbox="788 1622 926 1664">eth#</td><td data-bbox="926 1622 1065 1664">eth#</td><td data-bbox="1065 1622 1204 1664">eth#</td><td data-bbox="1204 1622 1432 1664">eth#</td><td data-bbox="1432 1622 1473 1664">eth#</td><td data-bbox="1473 1622 1514 1664">eth#</td></tr> </tbody> </table> <p>Note: The VNICs need to be created in the correct order so the interfaces are associated with the correct network.</p>		OAM (XMI)	Loca I (IMI)	Sig A (XSI1)	Sig B (XSI2)	Sig C (XSI3-16)	Rep (SBR)	DIH Interna I	Type of guest host	eth#						
	OAM (XMI)	Loca I (IMI)	Sig A (XSI1)	Sig B (XSI2)	Sig C (XSI3-16)	Rep (SBR)	DIH Interna I											
Type of guest host	eth#	eth#	eth#	eth#	eth#	eth#	eth#											

STEP #	Procedure	Description
9. <input type="checkbox"/>	OVM-M CLI: Add (attach) XMI VNIC ID of the XMI network to VM (if required by guest host type)	<p>1. Use the respective values for <Vnic 1 ID> and <OVM network ID for XMI> into the command</p> <pre>OVM> add Vnic ID=<Vnic 1 ID> to Network name=<OVM network ID for XMI></pre> <p>Example:</p> <pre>OVM> add Vnic ID=0004fb0000070000091elab5ae291d8a to Network name=10345112c9</pre> <p>2. Execute the command and validate success.</p>
10. <input type="checkbox"/>	OVM-M CLI: Create and attach IDIH Internal VNIC to VM (if required by guest host type)	<p>1. Use the respective values for <OVM network ID for IDIH Internal> and <VM name> into the command</p> <pre>OVM> create Vnic network=<OVM network id for IDIH Internal> name=<VM name>-int on Vm name=<VM name></pre> <p>Example:</p> <pre>OVM> create Vnic network=DIH Internal name=na_idih-db-int on Vm name=na_idih-db</pre> <p>2. Execute the command and validate success</p>
11. <input type="checkbox"/>	OVM-M CLI: Create and attach IMI VNIC ID to VM (if required by guest host type)	<p>1. Use the respective values for <OVM network ID for IMI> and <VM name> into the command.</p> <pre>OVM> create Vnic network=<OVM network ID for IMI> name=<VM name>-IMI on VM name=<VM name></pre> <p>Example:</p> <pre>OVM> create Vnic network=102e89a481 name= na_idih-db-IMI on Vm name= na_idih-db</pre> <p>2. Execute the command and validate success.</p>

STEP #	Procedure	Description
12. <input type="checkbox"/>	[iDIH Oracle VM Only] OVM-M CLI: Create a raw storage block device (external device)	<p>Create an extra virtual disk (only required on IDIH-Oracle (db) if the system is using OVM).</p> <ol style="list-style-type: none"> Decide on a name for the virtual disk: <VirtualDiskName> Refer the resource profiles defined in [24] DSR Cloud Benchmarking Guide to learn the required GB of Storage for the IDIH type: <size in GB> Use the respective value for <MyRepository Name> into the command. <pre>OVM> create VirtualDisk name='<VirtualDiskName>' size=<size in GB> sparse=<Yes/No> shareable=<Yes/No> on Repository name='<MyRepository Name>'</pre> <p>Example:</p> <pre>OVM> create VirtualDisk name=idih-db_disk1 size=100 sparse=No shareable=No on Repository name='XLab Utility Repo01'</pre> <ol style="list-style-type: none"> Examine the screen results to find site-specific text for variables in these locations: <pre>Command: create VirtualDisk name=idih-db_disk size=100 sparse=No shareable=No on Repository name='XLab Utility Repo01'</pre> <pre>Status: Success</pre> <pre>Time: 2017-04-24 15:29:12,502 EDT</pre> <pre>JobId: 1493061481113</pre> <pre>Data:</pre> <pre>id:0004fb00001200001bae7adbe6b20e19.img name:idih-db_disk</pre> <ol style="list-style-type: none"> Use the respective values for these variables (overwrite example). <pre><VirtualDiskId> = 0004fb00001200001bae7adbe6b20e19.img</pre> <pre><VirtualDiskName> = idih-db_disk</pre>

STEP #	Procedure	Description
13. <input type="checkbox"/>	[iDIH Oracle VM Only] OVM-M CLI: Map the created virtual disk to a slot on the VM	<ol style="list-style-type: none"> Decide on a slot for the virtual disk: <Slot#> Use the respective values for <Slot#> & <VirtualDiskId> & <VirtualDiskName> & <VM name> into the command. <code>OVM> create VmDiskMapping slot=<Slot#> virtualDisk=<VirtualDiskId> name="<VirtualDiskName>" on Vm name=<VM name></code> Example: <code>OVM> create VmDiskMapping slot=2 virtualDisk=0004fb00001200001bae7adbe6b20e19.img name='idih-db_disk' on Vm name=na_idih-db</code> Execute the command and validate success. <code>Command: create VmDiskMapping slot=2 virtualDisk=0004fb00001200001bae7adbe6b20e19.img name='idih-db_disk' on Vm name=na_idih-db</code> Status: Success Time: 2017-04-24 15:32:50,875 EDT JobId: 1493062370724 Data: <code>id:0004fb000013000057ab9b00e6d47add name:idih-db_disk</code>
14. <input type="checkbox"/>	OVM-M CLI: Start VM	<ol style="list-style-type: none"> Use the respective value for <VM name> into the command <code>OVM> start Vm name=<VM name></code> Example: <code>OVM> start Vm name= na_idih-db</code> Execute the command and validate success
15. <input type="checkbox"/>	Repeat	Repeat steps 2 through 14 for the following VMs. Use Unique labels for the VM names: iDIH-Application iDIH-Mediation

5.10 Configure iDIH Virtual Machines (Optional)

Procedure 37. Configure iDIH VM Networks (Optional)

STEP #	Procedure	Description
This procedure configures the iDIH guest VM external management networks.		
Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.		
If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.		
1. <input type="checkbox"/>	Log into the Oracle VM console	<ol style="list-style-type: none"> Access the iDIH Oracle VM console. Login as the admusr user.

STEP #	Procedure	Description
2. <input type="checkbox"/> (Oracle VM only) Verify the extra/second disk exists		<p>Note: This step is required ONLY for the Oracle VM.</p> <p>Check if the raw storage block device (external disk) exists by executing any of below commands (similar to the screenshot):</p> <pre>\$ ls /dev/[sv]db</pre> <p>Note: The command [sv] db means, <code>sdb</code> and <code>vdb</code>, depending on the hardware.</p> <p>Example using, <code>\$ ls /dev/sdb</code></p> <pre>Disk /dev/sdb: 107.4 GB, 107374182400 bytes 255 heads, 63 sectors/track, 13054 cylinders Units = cylinders of 16065 * 512 = 8225280 bytes Sector size (logical/physical): 512 bytes / 512 bytes I/O size (minimum/optimal): 512 bytes / 512 bytes Disk identifier: 0x00000000</pre> <p><code>\$ sudo fdisk -l</code></p> <pre>Disk /dev/vda: 75.2 GB, 75161927680 bytes 16 heads, 63 sectors/track, 145635 cylinders Units = cylinders of 1008 * 512 = 516096 bytes Sector size (logical/physical): 512 bytes / 512 bytes I/O size (minimum/optimal): 512 bytes / 512 bytes Disk identifier: 0x000af813 Device Boot Start End Blocks Id System /dev/vdal * 3 1043 524288 83 Linux /dev/vda2 1043 145636 72875008 8e Linux LVM Disk /dev/mapper/vgroot-plat_root: 1073 MB, 1073741824 bytes 255 heads, 63 sectors/track, 130 cylinders Units = cylinders of 16065 * 512 = 8225280 bytes Sector size (logical/physical): 512 bytes / 512 bytes I/O size (minimum/optimal): 512 bytes / 512 bytes Disk identifier: 0x00000000</pre> <p><code>\$ df -h</code></p> <pre>[admusr@DsrSite00NOAM00 ~]\$ df -h Filesystem Size Used Avail Use% Mounted on /dev/mapper/vgroot-plat_root 976M 289M 637M 32% / tmpfs 2.9G 0 2.9G 0% /dev/shm /dev/vdal 488M 38M 426M 9% /boot /dev/mapper/vgroot-plat_tmp 976M 1.6M 924M 1% /tmp /dev/mapper/vgroot-plat_usr 4.8G 3.0G 1.6G 66% /usr /dev/mapper/vgroot-plat_var 976M 427M 499M 47% /var /dev/mapper/vgroot-plat_var_tklc 3.9G 189M 3.5G 6% /var/TKLC /dev/mapper/vgroot-apw_tmp 8.3G 20M 7.8G 1% /tmp/appworks_temp /dev/mapper/vgroot-netbackup_lv 4.8G 10M 4.6G 1% /usr/openv /dev/mapper/vgroot-logs_process 3.3G 11M 3.2G 1% /var/TKLC/appw/logs/Process /dev/mapper/vgroot-logs_security 488M 396K 462M 1% /var/TKLC/appw/logs/Security /dev/mapper/vgroot-filemgmt 14G 42M 14G 1% /var/TKLC/db/filemgmt /dev/mapper/vgroot-run_db 8.3G 230M 7.6G 3% /var/TKLC/rundb</pre>

STEP #	Procedure	Description
		<p>If the extra disk does not exist, revisit the procedures for respective hypervisors. (Procedure 34 for KVM, and Procedure 35 for OVM-M).</p> <p>Note: Please DO NOT mount or format the added raw block device. Oracle ASM (Automatic Storage Management) automatically manages it. To verify it, execute the following command:</p> <pre>\$ df</pre> <p>If you see it has been mounted, unmount it and completely remove the entry in the /etc/fstab.</p> <p>For example:</p> <ol style="list-style-type: none"> 1. If any external drive (such as, /dev/vdb) is mounted, then unmount the external drive by executing the following command on oracle server: <code>umount /dev/vdb</code> 2. Edit the /etc/fstab file on oracle server and if any entry for /dev/vdb is present in the file, then remove the entry and save the file.
3. <input type="checkbox"/>	Delete the eth0 interface	<pre>\$ sudo netAdm delete --device=eth0</pre> <p>Note: Note down the MAC address before the eth0 is deleted. This helps in identifying the MAC address of eth0 in case the persistence net rules file is not generated.</p>
4. <input type="checkbox"/>	Trigger net rules file creation	<p>Run the udevadm command to recreate net rules file.</p> <pre>\$ sudo udevadm trigger --subsystem-match=net</pre> <p>Note: If this command does not create the net rules file, create it manually. Refer to Sample Net Rules File.</p>
5. <input type="checkbox"/>	Modify the ethernet interface names in the net rules file	<ol style="list-style-type: none"> 1. Update the net rules file to replace the default interfaces names ethX with XMI and INT interfaces names. Replace eth0 with xmi; and eth1 with int interface. Also, respective MAC addresses should be updated for each interface in lower case. MAC addresses can be determined using <code>ifconfig -a</code> command from the console. <p>Note: The Mediation VM requires the user to rename a third interface: eth2 as imi interface.</p> 2. Refer to Sample Net Rules File for a sample net rules file. <pre>\$ sudo vi /etc/udev/rules.d/70-persistent-net.rules</pre> <div data-bbox="496 1459 1263 1755" style="background-color: black; color: green; padding: 10px;"> <pre># PCI device 0x15ad:0x07b0 (vmxnet3) SUBSYSTEM=="net", ACTION=="add", DRIVERS=="?*", ATTR(address)=="00:50:56:b9:2d:b1", ATTR(type)=="1", KERNEL=="eth*", NAME="eth1" # PCI device 0x15ad:0x07b0 (vmxnet3) SUBSYSTEM=="net", ACTION=="add", DRIVERS=="?*", ATTR(address)=="00:50:56:b9:ea:b2", ATTR(type)=="1", KERNEL=="eth*", NAME="eth0" # PCI device 0x15ad:0x07b0 (vmxnet3) SUBSYSTEM=="net", ACTION=="add", DRIVERS=="?*", ATTR(address)=="00:50:56:b9:2d:b2", ATTR(type)=="1", KERNEL=="eth*", NAME="int" # PCI device 0x15ad:0x07b0 (vmxnet3) SUBSYSTEM=="net", ACTION=="add", DRIVERS=="?*", ATTR(address)=="00:50:56:b9:ea:b1", ATTR(type)=="1", KERNEL=="eth*", NAME="imi"</pre> </div> <ol style="list-style-type: none"> 3. Reboot the VM. <pre>\$ sudo init 6</pre>

STEP #	Procedure	Description
6. <input type="checkbox"/>	As admusr on the Oracle VM configure the networks with netAdm	<ol style="list-style-type: none"> 1. Log into the iDIH Oracle VM console as the admusr user. 2. The XMI network should already exist, but it can be created with the following command. <code>\$ sudo netAdm add --device=xmi --address=<IP Address in External Management Network> --netmask=<Netmask> --onboot=yes</code> 3. Configure the int network IP address and netmask. <code>\$ sudo netAdm add --device=int --address=10.254.254.2 --netmask=255.255.255.224</code> <p>Note: It is advisable to use the following IP as internal IP addresses defined for: Oracle VM internal IP = 10.254.254.2; the Mediation VM internal IP = 10.254.254.3; and the application internal IP address = 10.254.254.4. The netmasks for all is 255.255.255.224.</p> 4. Mediation Only. If this is a Mediation VM, configure the Mediation internal management network. <code>\$ sudo netAdm add --device=imi --address=<IP Address in Internal Management Network> --netmask=<Netmask></code> 5. Configure the default gateway. <code>\$ sudo netAdm add --route=default --gateway=<gateway address for the External Management Network> --device=xmi</code> <p>The VM network configuration has been completed. You should be able to ssh into the server through XMI interface.</p>
7. <input type="checkbox"/>	As admusr on the Oracle VM configure NTP and the Oracle VM hostname	<ol style="list-style-type: none"> 1. On the Oracle VM console, launch the platform configuration menu. <code>\$ sudo su - platcfg</code> 2. From the platform configuration menu configure ntpserver1 with the IP address supplied for NTP. <p>Navigate to Network Configuration > NTP > Edit > ntpserver1. Click Yes when asked to restart NTP.</p> <p>Note: Properly configure the NTP on the controller node to reference lower stratum NTP servers.</p> 3. Exit the network configuration menu. 4. Configure the Oracle VM hostname. <p>Navigate to Server Configuration > Hostname > Edit.</p> <p>Note:</p> <ul style="list-style-type: none"> • Typically, we select hostname and identify the host as iDIH application, iDIH Mediation, and iDIH Oracle. • Remove any occurrence of “.” and the “.<availability zone>” name, such as “.novalocal” from the hostname that might have got appended. 5. Exit the platform configuration menu.

STEP #	Procedure	Description
8. <input type="checkbox"/>	Repeat	<p>Repeat Steps 1 through 7 for the following VMs. Use unique labels for the VM names:</p> <ul style="list-style-type: none"> iDIH Mediation iDIH Application <p>Note: Logout and Login to each VM to update the environment variable before executing the next procedure (Procedure 38: Post Installation Scripts on iDIH VMs).</p>

5.11 Post iDIH Installation Configuration (Optional)

Procedure 38. Run Post Installation Scripts on iDIH VMs (Optional)

STEP #	Procedure	Description
<p>This procedure runs post installation scripts on the iDIH VMs.</p> <p>Prerequisite: Procedure 3 has been completed.</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>		
1. <input type="checkbox"/>	Log into the iDIH Oracle VM Console	<ol style="list-style-type: none"> Access the iDIH Oracle VM console. Login as the admusr user.
2. <input type="checkbox"/>	Run the iDIH Oracle post installation script	<ol style="list-style-type: none"> Wait for the software upgrades to complete on all iDIH VMs. <p>Note: Verify the /etc/hosts file before, and after the execution of the script configureOracle.sh, having internal IP address for all the three guests.</p> <ol style="list-style-type: none"> As admusr on the iDIH Oracle VM console, run the Oracle post installation script. <pre>\$ sudo /opt/xIH/oracle/configureOracle.sh</pre> <p>Note: The Oracle post installation script runs for 5 to 15 minutes depending on the Oracle version and patch level. Wait for it to complete before the next step is executed. Once the script execution is over, it will come out without any message.</p> <p>Note: To verify the install status, check the /var/TKLC/xIH/log/oracle/post_image_install.log file for any errors. The error stating: Cannot use backup/restore functions while using dispatcher can safely be ignored.</p>
3. <input type="checkbox"/>	Log into the iDIH Mediation VM Console as admusr	<ol style="list-style-type: none"> Access the iDIH Mediation VM console. Login as the admusr user.

STEP #	Procedure	Description
4. <input type="checkbox"/>	Run the iDIH Mediation VM post installation script	<p>The Oracle post installation script must come to completion before the Mediation post installation script is run.</p> <ol style="list-style-type: none"> As the admusr user on the iDIH Mediation VM console, run the Mediation post installation script. <pre>\$ sudo /opt/xIH/mediation/install.sh</pre> <p>Note: The Mediation post installation script runs for 2 to 10 minutes. Wait for it to complete before the next step is executed. To verify the install status, check the <code>/var/TKLC/xIH/log/mediation/post_image_install.log</code> file for any errors.</p> <p>Note: It is assumed network configuration and functionality is correct before installation. If you encounter an issue of the mediation post installation script <code>/opt/xIH/mediation/install.sh</code> hanging at the beginning as shown below, but you are still able to ssh to Oracle VM using internal IP, make sure the internal interface (int) MTU has the correct setting - 1500 MTU. If yes, MTU size adjustment may be needed. For verification, connect to oracle using sqlplus using the following commands:</p> <ol style="list-style-type: none"> Log into the Mediation server as admusr. Execute the command sudo su - tekelec. Execute the command sqlplus /@NSP. <ol style="list-style-type: none"> As tekelec on the iDIH Mediation VM console, run the following commands: <pre>\$ sudo su - tekelec \$ iset -fnodeName='hostname' -fhostName='hostname' NodeInfo where 1=1</pre> <p>Note: Replace hostname with the actual hostname of Mediation VM.</p>
5. <input type="checkbox"/>	Log into the iDIH application VM console as admusr	<ol style="list-style-type: none"> Access the iDIH Application VM console. Login as the admusr user.
6. <input type="checkbox"/>	Run the iDIH Application post installation script	<p>The Mediation post installation script must come to completion before the Application post installation script is run.</p> <p>As the admusr user on the iDIH Application VM console, run the Application post installation script.</p> <pre>\$ sudo /opt/xIH/apps/install.sh</pre> <p>Note:</p> <ul style="list-style-type: none"> The application post installation script runs for 2 to 10 minutes. Wait for it to complete before executing the next step. Verify the <code>/etc/hosts</code> file before, and after the execution of the script <code>configureOracle.sh</code>, having internal IP address for all the three guests.

STEP #	Procedure	Description
7. <input type="checkbox"/>	Run the iDIH health check script on each of the iDIH VMs	<p>Once all of the iDIH VMs have restarted. Run the health check scripts on each iDIH VM.</p> <ol style="list-style-type: none"> As the admusr user on the iDIH Oracle VM console, run the health check script and verify the results. Ignore the NTP message stating the tvoe-host is not integrated. <code>\$ sudo /usr/TKLC/xIH/plat/bin/analyze_server.sh -i</code> As admusr on the iDIH Application VM console, run the health check script and verify the results. Ignore the NTP message stating tvoe-host is not integrated. <code>\$ sudo /usr/TKLC/xIH/plat/bin/analyze_server.sh -i</code> As admusr on the iDIH Mediation VM console, run the health check script and verify results. Ignore the NTP message stating tvoe-host is not integrated. <code>\$ sudo /usr/TKLC/xIH/plat/bin/analyze_server.sh -i</code> <p>Note: Ignore NTP message stating the tvoe-host is not integrated.</p>

Procedure 39. Configure DSR Reference Data Synchronization for iDIH (Optional)

STEP #	Procedure	Description
This procedure configures DSR reference data synchronization for iDIH.		
Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.		
If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.		
1. <input type="checkbox"/>	iDIH Application Server: Login	<ol style="list-style-type: none"> Establish an SSH session to the iDIH Application Server. Login as the admusr user. Issue the following command to login as a tekelec user. <code>\$ sudo su - tekelec</code>
2. <input type="checkbox"/>	iDIH Application Server: Execute configuration script	<ol style="list-style-type: none"> Execute the following script using SOAM VIP address: <code>Apps/trda-config.sh</code> <p>Note: The SO IP address to be used here is the internal xmi address of the SO and not the floating-ip or external address (if used any).</p> <p>Example output:</p> <pre>corsair-app:[user/TKLC/xIH apps/trda-config.sh] dos2unix: converting file /usr/TKLC/xIH/bea/user_projects/domains/tekelec/nsp/trace- refdata-ad Please enter DSR oam server IP address: 10.240.39.175 SQL*Plus: Release 12.1.0.2.0 Production on Thu Oct 1 15:04:40 2015 Copyright (c) 1982, 2014, Oracle. All rights reserved.</pre>


STEP #	Procedure	Description
		<pre>Last Successful login time: Thu Oct 01 2015 13:27:57 - 04:00 Connected to: Oracle Database 12c Enterprise Edition Release 12.1.0.2.0 - 64bit Production With the Partitioning, Automatic Storage Management, OLAP, Advanced Analytics and Real Application Testing options SQL> SQL> 2 3 4 5 1 row merged. SQL> Commit complete. SQL> Disconnected from Oracle Database 12c Enterprise Edition Release 12.1.0.2.0 - 64bit Produ With the Partitioning, Automatic Storage Management, OLAP, Advanced Analytics and Real Application Testing options Buildfile: /usr/TKLC/xIH/apps/trace-refdata-adapter/build.xml app.disable: common.weblogic.stop: [echo] [echo] [echo] ===== [echo] application: xihtra [echo] date: 2015-10-01 15:04:41 [echo] ===== [echo] === stop application EAR [echo] date: 2015-10-01 15:04:41 [java] weblogic.Deployer invoked with options: - adminurl t3://appserver:7001 - userconfigprojects/domains/tekelec/keyfile.secure -name xIH Trace Reference Data Adapter -stop [java] <Oct 1, 2015 3:05:08 PM EDT> <Info> <J2EE Deployment SPI> <BEA-260121> <Initiating [java] Task 24 initiated: [Deployer:149026]stop application xIH Trace Reference Data Adap [java] Task 24 completed: [Deployer:149026]stop application xIH Trace Reference Data Adap [java] Target state: stop completed on Server nsp</pre>


STEP #	Procedure	Description
		<pre> [java] BUILD SUCCESSFUL Total time: 29 seconds Buildfile: /usr/TKLC/xIH/apps/trace-refdata- adapter/build.xml app.enable: common.weblogic.start: [echo] [echo] [echo] ===== [echo] application: xihtra [echo] date: 2015-10-01 15:05:10 [echo] ===== [echo] === start application EAR [echo] date: 2015-10-01 15:05:10 [java] weblogic.Deployer invoked with options: - adminurl t3://appserver:7001 - userconfigprojects/domains/tekelec/keyfile.secure -name xIH Trace Reference Data Adapter -start [java] <Oct 1, 2015 3:05:56 PM EDT> <Info> <J2EE Deployment SPI> <BEA-260121> <Initiating [java] Task 25 initiated: [Deployer:149026]start application xIH Trace Reference Data Ada [java] Task 25 completed: [Deployer:149026]start application xIH Trace Reference Data Ada [java] Target state: start completed on Server nsp [java] BUILD SUCCESSFUL Total time: 1 minute 17 seconds 2. When asked to Please enter DSR OAM server IP address, type the VIP of the DSR SOAM (or active DSR SOAM if VIP is not available) and click Enter. Note: If the address typed is unreachable, the script exits with error Unable to connect to <ip-address>!</pre>
3. <input type="checkbox"/>	iDIH Application Server: Monitor completion	<ol style="list-style-type: none"> 1. Monitor the log file located at: <code>/var/TKLC/xIH/log/apps/weblogic/apps/application.log</code> 2. Examine the log file for entries containing text Trace Reference Data Adapter.



STEP #	Procedure	Description
4. <input type="checkbox"/>	iDIH Application Server (Optional): Switch iDIH from one DSR to another DSR in a different network	<p>Note: This is an optional step which is needed to switch an iDIH from one DSR to another DSR in a different network</p> <ol style="list-style-type: none"> 1. Establish an SSH session to the iDIH Application Server. 2. Login as the tekelec user 3. Execute these commands: <ol style="list-style-type: none"> a. cd /usr/TKLC/xIH/apps/trace-refdata-adapter b. ant clean.data c. cd /usr/TKLC/xIH/apps/xihoam d. ant imp.init (flush comagent connection data) e. cd /usr/TKLC/xIH/apps/trace-refdata-adapter f. ant app.enable (Sync MOs from SOAM) g. cd /usr/TKLC/xIH/apps h. ./trda-config.sh <DSR SOAM VIP in different network>



Procedure 40. iDIH Configuration: Configuring the SSO Domain (Optional)



STEP #	Procedure	Description
		<p>This procedure configures the SSO domain for iDIH.</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>





STEP #	Procedure	Description
1. <input type="checkbox"/>	NOAM VIP GUI: Login	<ol style="list-style-type: none">1. Establish a GUI session on the NOAM server by using the VIP IP address of the NOAM server. Open the web browser and type https://<Primary_NOAM_VIP_IP_Address> as the URL.2. Login as the admusr user. 

STEP #	Procedure	Description
2. <input type="checkbox"/>	NOAM VIP GUI: Configure DNS	<ol style="list-style-type: none"> 1. Navigate to Administration > Remote Servers > DNS Configuration.  2. Select the NOAM tab. 3. Configure values for the following fields: Domain Name Name Server Search Domain 1 4. If values have already been configured, click Cancel; otherwise configure the values and click OK.

STEP #	Procedure	Description
3. <input type="checkbox"/>	NOAM VIP GUI: Establish SSO local zone	<p>1. Navigate to Access Control > Certification Management.</p>  <p>2. Click Establish SSO Zone.</p>  <p>3. Type a value for Zone Name.</p>  <p>4. Click OK.</p> <p>Information for the new certificate type of SSO local displays.</p> <p>5. Click Report.</p>  <p>6. The Certificate Report displays. Select and copy the encoded certificate text to the clipboard for future access.</p> <p>Example of Certificate Report:</p> <pre data-bbox="502 1305 1432 1862"> -----BEGIN CERTIFICATE----- MIICKzCCAdWgAwIBAgIJJA0VfSLNc3CeJMA0GCSqGSIb3DQEBCwUAMHExCzAJBgNV BAYTA1VTMQswCQYDVQQIDAJOQzEQMA4GA1UEBwwHUmFsZWlnaDEPMA0GA1UECgwG T3JhY2x1MQswCQYDVQQLDAJQVjEQMA4GA1UEAwwHTGliZXJ0eTETMBEGCSqGSIb3 DQEJARYEdGVzdDAeFw0xNTA1MDQxNDIzNTRaFw0xNjA1MDMxNDIzNTRaMHExCzAJ BgNVBAYTA1VTMQswCQYDVQQIDAJOQzEQMA4GA1UEBwwHUmFsZWlnaDEPMA0GA1UE CgwGT3JhY2x1MQswCQYDVQQLDAJQVjEQMA4GA1UEAwwHTGliZXJ0eTETMBEGCSqG SIb3DQEJARYEdGVzdDBcMA0GCSqGSIb3DQEBAQUAA0sAMEgCQQCZ/MpkhlvMP/iJ s5xD02MwxJm3jYim43H8gR9pfBTMNP6L9kluJYi+2T0hngJFQLpIn6SK6pXnuAGY f/vDWfqPAgMBAAGjUDBOMB0GA1UdDgQWBBS6IzIOLP1gizQ6+BERr8Fo2XyDVDAf BgNVHSMEGDAwgsB6IzIOLP1gizQ6+BERr8Fo2XyDVDAfBgNVHRMEBTADAQH/MA0G CSqGSIb3DQEBCwUAA0EAowIqBMEQyvfvt38r/yfgIx3w5dN8SBwHjHC5TpJrHV6U zFlg5dfzoLz7ditjGOhWJ919VRw39LQ81KFp7SMXwA== -----END CERTIFICATE----- </pre>

STEP #	Procedure	Description
4. <input type="checkbox"/>	iDIH Application Server GUI: Login	<p>1. Establish a GUI session on the iDIH application server, using the xmi IP address: <a href="https://<app server IP>">https://<app server IP></p> <p>2. Login as the idihadmin user.</p> 
5. <input type="checkbox"/>	iDIH Application Server GUI: Launch the OAM portal	<p>Navigate to the OAM portal icon to start the OAM web application.</p> 



STEP #	Procedure	Description
6. <input type="checkbox"/>	iDIH Application Server GUI: Configure the SSO domain	<p>1. Navigate to System > Single Sign On.</p>  <p>Select the SSO Parameters tab.</p>  <p>2. Click the Edit Value icon.</p>  <p>3. Type a value for the Domain Name.</p> <p>Note: This should be the same domain name assigned in the DSR NOAM DNS Configuration (step 2).</p> <p>4. Click the Save icon.</p>  <p>5. Click the Refresh icon to display data saved for the remote zone.</p> 

STEP #	Procedure	Description
7. <input type="checkbox"/>	iDIH Application Server GUI: Configure the SSO Remote Zone	<p>1. Navigate to System > Single Sign On.</p>  <p>2. Select the SSO Zones tab.</p>  <p>3. Click the Add icon.</p>  <p>4. Type a value for field Remote Name.</p>  <p>5. For field X.509 Certificate, paste the encoded certificate text from the clipboard that was previously copied from the DSR NOAM.</p>  <p>6. Click the Save icon.</p>  <p>7. Click the Refresh icon to display the data saved for remote zone.</p> 

Procedure 41. Integrate iDIH into DSR (Optional)

S T E P #	<p>This procedure configures the iDIH connections to DSR.</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>												
1. <input type="checkbox"/>	<p>Configure the iDIH ComAgent connection on the NOAM</p> <p>1. Navigate to Communication Agent > Configuration > Remote Servers.</p>  <p>2. Click Insert.</p>  <p>3. Add the iDIH Mediation server.</p> <p>4. For the Remote Server IP Address field, type the IMI IP address of the iDIH Mediation server.</p> <p>5. For the IP Address Preference field, select the IP protocol preference (if IPv6 and IPv4 are configured).</p> <table border="1" style="width: 100%; border-collapse: collapse;"> <thead> <tr> <th style="text-align: left; padding: 2px;">Field</th> <th style="text-align: left; padding: 2px;">Value</th> </tr> </thead> <tbody> <tr> <td style="padding: 2px;">Remote Server Name *</td> <td style="padding: 2px;"><input type="text"/></td> </tr> <tr> <td style="padding: 2px;">Remote Server IPv4 IP Address</td> <td style="padding: 2px;"><input type="text"/></td> </tr> <tr> <td style="padding: 2px;">Remote Server IPv6 IP Address</td> <td style="padding: 2px;"><input type="text"/></td> </tr> <tr> <td style="padding: 2px;">Remote Server Mode *</td> <td style="padding: 2px;"><input type="button" value="-- Select --"/></td> </tr> <tr> <td style="padding: 2px;">IP Address Preference</td> <td style="padding: 2px;"><input type="button" value="ComAgent Network Preference"/></td> </tr> </tbody> </table> <p>6. Set the Remote Server Mode to Server.</p>	Field	Value	Remote Server Name *	<input type="text"/>	Remote Server IPv4 IP Address	<input type="text"/>	Remote Server IPv6 IP Address	<input type="text"/>	Remote Server Mode *	<input type="button" value="-- Select --"/>	IP Address Preference	<input type="button" value="ComAgent Network Preference"/>
Field	Value												
Remote Server Name *	<input type="text"/>												
Remote Server IPv4 IP Address	<input type="text"/>												
Remote Server IPv6 IP Address	<input type="text"/>												
Remote Server Mode *	<input type="button" value="-- Select --"/>												
IP Address Preference	<input type="button" value="ComAgent Network Preference"/>												



Procedure 41. Integrate iDIH into DSR (Optional)

2. <input type="checkbox"/> Configure the Troubleshooting with iDIH on the SOAM	<ol style="list-style-type: none"> 1. Navigate to Diameter > Troubleshooting with iDIH > Configuration > Options.  2. Type the fully qualified iDIH host name (or IP address) in the iDIH Visualization Address field:  3. Click Apply.
---	---



Procedure 42. iDIH Configuration: Configure the Mail Server (Optional)

S T E P #	<p>This procedure configures the SMTP mail server.</p> <p>Note: This procedure is optional; however, this option is required for security (password initialization set to AUTOMATIC) and forwarding (forwarding by mail filter defined), and is available only on the Application server.</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>
1. <input type="checkbox"/> iDIH Application Server: Login	<ol style="list-style-type: none"> 1. Establish an SSH session to the iDIH Application server. 2. Login as the admusr user.

Procedure 42. iDIH Configuration: Configure the Mail Server (Optional)

2. <input type="checkbox"/> iDIH Application Server: Configure the authenticated mail server	<ol style="list-style-type: none"> From the platcfg menu, type the following command: <code>\$ sudo su - platcfg</code> Select Application Server Configuration.  Select SMTP Configuration.  Select Edit. Enter the following parameters: <ul style="list-style-type: none"> • Mail Server IP Address • User • Password • Email Address (From) • Mail smtp timeout • Mail smtp connectiontimeout • SNMP over SSL used? Select OK. Select Exit to exit the platcfg menu.
---	---

Procedure 43. iDIH Configuration: Configure SNMP Management Server (Optional)



S T E P #	<p>This procedure configures the SNMP management server.</p> <p>Note: This procedure is optional; however, this option is required for forwarding (forwarding by SNMP filter defined), and is available only on the Application server.</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>
1. <input type="checkbox"/> iDIH Application Server: Login	<ol style="list-style-type: none"> 1. Establish an SSH session to the iDIH Application server. 2. Login as the admusr user.
2. <input type="checkbox"/> iDIH Application Server: Configure the authenticated mail server	<ol style="list-style-type: none"> 1. From the platcfg menu, type the following command: <code>\$ sudo su - platcfg</code> 2. Select Application Server Configuration.  3. Select SNMP Agent Configuration.  4. Select Edit. 5. Enter the IP Address of the SNMP management server. <p>Note: The SNMP agent configuration is updated and the SNMP management server automatically restarts.</p> <ol style="list-style-type: none"> 6. Select OK. 7. Select Exit to exit the platcfg menu.

Procedure 44. iDIH Configuration: Change Network Interface (Optional)




		<p>This procedure changes the default network interface.</p> <p>Note: Initially, the default network interface used to transport TTRs from DSR to DIH uses the internal IMI network; however, this can be changed, if required. It should be noted that changing this interface could degrade performance of TTR transmission.</p> <p>Note: A script is provided to manage the settings so the operator does not need to know the details required to apply the settings. There are two settings interface.name and interface.enabled.</p> <p>When interface.enabled=True, then communications over the interface.name =value, where value is the name of the network interface as defined on the platform, is the only specified interface used for communications.</p> <p>When interface.enabled=False then communications over the named interface is not enforced, that is, all interfaces configured on the platform are allowed to be used for communications.</p> <p>For example, if it is required to use the XMI interface for communication instead of the default internal IMI interface, then the operator would supply XMI when asked for the interface name and True when asked if interface filtering should be applied.</p> <p>S T E P # Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>
1. <input type="checkbox"/>	iDIH Mediation Server: Login	<ol style="list-style-type: none"> Establish an SSH session to the iDIH Mediation server. Login as the admusr user. Type the following command to login in as the Tekelec user. <code>\$ sudo su - tekelec</code>
2. <input type="checkbox"/>	iDIH Mediation Server: Execute the change interface script	<ol style="list-style-type: none"> To execute the change interface script, type the following command: <code>\$ chgIntf.sh</code> Answer the questions during the script as follows. This script is used to change the interface name (default = imi) used for mediation communications and whether to enable network interface filtering or not. Please answer the following questions or enter CTRL-C to exit out of the script. <code>Current setting are: interface.name=imi interface.enabled=True</code> <code>Enter new network interface name, return to keep current [imi]: xmi</code> <code>Do you want to enable network interface filtering [True False], return to keep current [True]:</code> <code>Updating configuration properties file with 'interface.name=xmi' and 'interface.enabled=True', and restarting mediation configuration bundle...</code>

6. Post-Install Activities



Procedure 45. Configure ComAgent Connections

S T E P #	<p>This procedure configures ComAgent connections on DSR for use in the FABR application.</p> <p>Prerequisite: FABR application is activated.</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>
1. <input type="checkbox"/>	<p>SDS NOAM VIP GUI: Login</p> <p>1. Establish a GUI session on the SDS NOAM server by using the VIP IP address of the NOAM server. Open the web browser and type https://<Primary_SDS_NOAM_VIP_IP_Address> as the URL.</p> <p>2. Login as the admusr user.</p> 
2. <input type="checkbox"/>	<p>SDS NOAM VIP GUI: Configure remote server IP address</p> <p>1. Navigate to Communication Agent > Configuration > Remote Servers.</p>  <p>2. Click Insert.</p> 




Procedure 45. Configure ComAgent Connections

3. <input type="checkbox"/> SDS NOAM VIP GUI: Configure remote server IP address	<ol style="list-style-type: none"> Type Remote Server Name for the DSR MP server.  Type the Remote Server IMI IP address.   <p>Note: This should be the IMI IP address of the DAMP server.</p> Select Client for the Remote Server Mode from the list.  Select IP Address Preference (ComAgent Network Preference, IPv4, or IPv6) from the list.  Select the Local Server Group from the available SDS DP server groups and click 'Add' to assign. 
--	---

Procedure 45. Configure ComAgent Connections

		 <p>6. Click Apply.</p>
4. <input type="checkbox"/>	SDS NOAM VIP GUI: Repeat	Repeat steps 2-3 for each remote MP in the same SOAM NE.
5. <input type="checkbox"/>	DSR NOAM VIP GUI: Login	<ol style="list-style-type: none"> 1. Establish a GUI session on the DSR NOAM server by using the VIP IP address of the NOAM server. Open the web browser and type https://<Primary_DSR_NOAM_VIP_IP_Address> as the URL 2. Login as the guiadmin user. 





Procedure 45. Configure ComAgent Connections

6. <input type="checkbox"/>	DSR NOAM VIP GUI: Configure remote server IP address	<ol style="list-style-type: none"> 1. Navigate to Communication Agent > Configuration > Remote Servers.  2. Click Insert. 
7. <input type="checkbox"/>	DSR NOAM VIP GUI: Configure remote server IP address	<ol style="list-style-type: none"> 1. Type Remote Server Name for the DSR MP server.  2. Type the Remote Server IMI IP address.  <p>Note: This should be the IMI IP address of the DP server.</p> 3. Select Server for the Remote Server Mode from the list.  4. Select IP Address Preference (ComAgent Network Preference, IPv4, or IPv6) from the list.  5. Select the Local Server Group from the available DSR MP server groups and click 'Add' to assign.

Procedure 45. Configure ComAgent Connections

		<p>Available Local Server Groups</p> <p>Assigned Local Server Groups *</p> <p>Available Local Server Groups</p> <p>Assigned Local Server Groups</p> <p>Assigned Local Server Groups *</p> <p>Available Local Server Groups</p> <p>Assigned Local Server Groups</p> <p>6. Click Apply.</p> <p>Ok Apply Cancel</p>
8.	<input type="checkbox"/> DSR NOAM VIP GUI: Repeat	Repeat steps 6-7 for each remote DP in the same SOAM NE.
9.	<input type="checkbox"/> DSR NOAM VIP GUI: Configure connection groups	Navigate to Communication Agent > Configuration > Connection Groups . <ul style="list-style-type: none"> - Communication Agent <ul style="list-style-type: none"> - Configuration <ul style="list-style-type: none"> - Remote Servers - Connection Groups - Routed Services

Procedure 45. Configure ComAgent Connections

<input type="checkbox"/> 10.	DSR NOAM VIP GUI: Edit connection groups	<ol style="list-style-type: none"> 1. Select the DPSvcGroup connection group.  <ol style="list-style-type: none"> 2. Click Edit. 3. Select the DP Servers from the Available Servers in Network Element list and click >> to assign. <p>Editing existing Connection Groups</p>  <p>Editing existing Connection Groups</p>  <ol style="list-style-type: none"> 4. Click OK. 
<input type="checkbox"/> 11.	DSR NOAM VIP GUI: Verify servers in group	Verify the correct number of servers are in the connection group. 

Procedure 46. Complete PCA Configuration (Optional)

S	This procedure completes PCA configuration.	
T	Prerequisite: PCA application is activated.	
E	Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.	
P		
#	If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.	
1. <input type="checkbox"/>	Complete PCA configuration	Refer to Section PCA Configuration of [2] DSR PCA Activation Guide for the steps required to complete PCA configuration.




Procedure 47. Backups and Disaster Prevention

S	This procedure provides instruction on backups and disaster prevention.	
T	Prerequisite: DSR and optional sub-systems are installed configured.	
E	Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.	
P		
#	If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.	
1. <input type="checkbox"/>	Backup from VIM	<p>The preferred method of backing up cloud system VM instances is by snapshutting. Once the DSR and optional sub-systems are installed and configured, but before adding traffic, use the appropriate cloud tool such as the VMware Manager or the OpenStack Horizon GUI, to take snapshots of critical VM instances. It is particularly important to snapshot the control instances, such as the NOAM and SOAM.</p> <p>Note: To be on the safer side, follow the below steps also to back up the NOAM and SOAM database</p>
2. <input type="checkbox"/>	Identify Backup Server	<p>Identify an external server to be used as a backup server for the following steps. The server should not be co-located with any of the following items:</p> <ul style="list-style-type: none"> • Cloud Infrastructure Manager Server/Controller • DSR NOAM • DSR SOAM



Procedure 47. Backups and Disaster Prevention

3. <input type="checkbox"/> NOAM/SOAM	VIP: Login	<ol style="list-style-type: none">Establish a GUI session on the NOAM or SOAM server by using the VIP IP address of the NOAM or SOAM server.Open the web browser and enter a URL of: <a href="http://<Primary_NOAM_SOAM_VIP_IP_Address>">http://<Primary_NOAM_SOAM_VIP_IP_Address>Login as the guiadmin user:
---	-------------------	--

Procedure 47. Backups and Disaster Prevention

4. <input type="checkbox"/> NOAM/SOAM VIP: Backup configuration data for the system	<ol style="list-style-type: none"> 1. Navigate to Main Menu > Status & Manage > Database.  2. Select the active NOAM server and click Backup.  3. Make sure the Configuration checkbox is marked.  4. Enter a filename for the backup and click OK.
--	--

Procedure 47. Backups and Disaster Prevention

<p>5. <input type="checkbox"/> NOAM/SOAM</p> <p>VIP: Verify the backup file existence.</p>	<p>1. Navigate to Main Menu > Status & Manage > Files.</p>  <p>Main Menu: Status & Manage > Files</p> <table border="1"> <thead> <tr> <th>File Name</th> <th>Size</th> <th>Type</th> <th>Timestamp</th> </tr> </thead> <tbody> <tr> <td>TKLCCConfigData.Martinique-NO1.sh</td> <td>5.1 KB</td> <td>sh</td> <td>2016-10-03 04:30:11 EDT</td> </tr> <tr> <td>TKLCCConfigData.Martinique-SO1.sh</td> <td>4 KB</td> <td>sh</td> <td>2016-10-03 01:47:08 EDT</td> </tr> <tr> <td>TKLCCConfigData.SS7-MP.sh</td> <td>6.3 KB</td> <td>sh</td> <td>2016-10-05 04:51:20 EDT</td> </tr> <tr> <td>ugwrap.log</td> <td>1.3 KB</td> <td>log</td> <td>2016-10-03 01:09:41 EDT</td> </tr> <tr> <td>upgrade.log</td> <td>209.5 KB</td> <td>log</td> <td>2016-10-03 01:19:23 EDT</td> </tr> </tbody> </table> <p>2. Select the active NOAM or SOAM tab.</p> <p>3. The files on this server display. Verify the existence of the backup file.</p>	File Name	Size	Type	Timestamp	TKLCCConfigData.Martinique-NO1.sh	5.1 KB	sh	2016-10-03 04:30:11 EDT	TKLCCConfigData.Martinique-SO1.sh	4 KB	sh	2016-10-03 01:47:08 EDT	TKLCCConfigData.SS7-MP.sh	6.3 KB	sh	2016-10-05 04:51:20 EDT	ugwrap.log	1.3 KB	log	2016-10-03 01:09:41 EDT	upgrade.log	209.5 KB	log	2016-10-03 01:19:23 EDT
File Name	Size	Type	Timestamp																						
TKLCCConfigData.Martinique-NO1.sh	5.1 KB	sh	2016-10-03 04:30:11 EDT																						
TKLCCConfigData.Martinique-SO1.sh	4 KB	sh	2016-10-03 01:47:08 EDT																						
TKLCCConfigData.SS7-MP.sh	6.3 KB	sh	2016-10-05 04:51:20 EDT																						
ugwrap.log	1.3 KB	log	2016-10-03 01:09:41 EDT																						
upgrade.log	209.5 KB	log	2016-10-03 01:19:23 EDT																						
<p>6. <input type="checkbox"/> NOAM/SOAM</p> <p>VIP: Download the file to a local machine.</p>	<p>1. From the previous step, select the backup file.</p> <p>2. Click Download.</p> <p>Delete View Upload Download Deploy ISO Validate ISO</p> <p>1.1 GB used (5.93%) of 18.4 GB available System utilization: 1.1 GB (5.99%) of 18.4 GB available.</p> <p>3. Click OK.</p> 																								
<p>7. <input type="checkbox"/> Upload the image to secure location</p>	<p>Transfer the backed up image to a secure location identified in step 2 where the server backup files are fetched in case of system disaster recovery.</p>																								
<p>8. <input type="checkbox"/> Backup active SOAM</p>	<p>Repeat Steps 4 through 7 to back up the active SOAM.</p>																								

Procedure 48. (KVM/OpenStack Only) Configure Port Security

S T E P #	<p>This procedure configures port security on TSA.</p> <p>Prerequisite: Perform Enable the Neutron port security extension first. We require this extension to disable the Neutron anti-spoofing filter rules for a given port. Refer to Disable Port Security in Appendix G.6 where this is discussed.</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>	
1. <input type="checkbox"/> IPFE with TSA only. Remove allowable address pair security on IPFE XSI network and DAMP XSI interfaces on IPFE and MP instances	<p>If stacks are deployed using HEAT template, follow this step.</p> <ol style="list-style-type: none"> 1. Determine the TSA IP address used in Procedure 32, step 2. 2. Determine the corresponding XSI interface IP address assigned to that TSA used in Procedure 32, step 2. 3. Determine the XSI IP address of IPFE used in Procedure 32, step 2. 4. Log into the OpenStack control node as the admusr user. 5. Source the tenant user credentials. 6. Determine the port ID of the XSI interface IP address. <pre>\$ neutron port-list -F id -F fixed_ips grep <XSI network></pre> <p>Note: <port ID> is the value in first column of the output to this command.</p> <ol style="list-style-type: none"> 7. Remove allowed_address_pairs: <pre>\$ neutron port-update <Port ID> --no-allowed-address-pairs</pre> <p>Note: Execute neutron port-show command to verify allowed_address_pairs attribute is empty.</p>	
2. <input type="checkbox"/> IPFE with TSA only. Remove port security on TSA XSI network interfaces on IPFE and MP instances	<p>If using IPFE with Target Set Addresses (TSA).</p> <ol style="list-style-type: none"> 1. Determine the TSA IP address as used in section 5.4, Procedure 32. 2. Determine the corresponding XSI interface IP address as used in section 5.4, Procedure 32. 3. Log into the OpenStack control node as the admusr user. 4. Source the tenant user credentials. 5. Determine security groups associated with the IPFE instance. <pre>\$ nova list-secgroup <VM instance ID></pre> <p>Note: <VM instance ID> can be queried from the output of nova list command in the ID column for the given VM.</p> <ol style="list-style-type: none"> 6. Save the ID and names of the listed security groups for later use. 7. Remove all listed security groups. <pre>\$ nova remove-secgroup <VM instance ID> <Security group ID></pre> <p>Note: Use the <VM instance ID> and <Security group ID> as noted down in the step-6 above.</p>	

Procedure 48. (KVM/OpenStack Only) Configure Port Security

	<p>Alternatively, use the following syntax:</p> <pre>\$ nova remove-secgroup <VM instance name> <Security group name></pre> <p>8. Determine the port ID of the XSI interface IP address from step 2 above.</p> <pre>\$ neutron port-list -F id -F fixed_ips grep <instance IP on TSA/XSI network></pre> <p>Note: <port ID> is the value in first column of the output to this command.</p> <p>9. Disable port security for the port found in step 7.</p> <pre>\$ neutron port-update <Port ID> --port-security-enabled=false</pre> <p>10. Re-enable port security for all the interfaces not on the TSA/XSI port used in step 9, including XMI, IMI, and others.</p> <p>11. Determine the port IDs of the instance IP addresses not associated with the TSA/XSI network.</p> <pre>\$ neutron port-list -F id -F fixed_ips grep <instance IP not on TSA/XSI network></pre> <p>12. For each of the non TSA/XSI instance ports perform the following command for each of the security groups from step 6.</p> <pre>\$ neutron port-update <Port ID> --security-group <Security group ID></pre> <p>Note: Use the <Security Group ID> as noted down in the step-6 above.</p>
--	---

Procedure 49. Enable/Disable DTLS (SCTP Diameter Connections Only)

S	This procedure prepares clients before configuring SCTP Diameter connections.	
T	Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.	
E		
P		
#	If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.	
1.	<input type="checkbox"/> Enable/Disable DTLS (SCTP Diameter connections only)	<p>Oracle's SCTP Datagram Transport Layer Security (DTLS) has SCTP AUTH extensions by default. SCTP AUTH extensions are required for SCTP DTLS. However, there are known impacts with SCTP AUTH extensions as covered by the CVEs referenced below. It is highly recommended that customers prepare clients before the DSR connections are established after installation. This ensures the DSR to client SCTP connection establishes with SCTP AUTH extensions enabled. See RFC 6083. If customers DO NOT prepare clients to accommodate the DTLS changes, then the SCTP connections to client devices WILL NOT establish after the DSR is installed.</p> <ul style="list-style-type: none"> • https://access.redhat.com/security/cve/CVE-2015-1421 • https://access.redhat.com/security/cve/CVE-2014-5077 <p>Execute procedures in [19] DSR DTLS Feature Activation Procedure to disable/enable the DTLS feature.</p>

Procedure 50. Shared Secret Encryption Key Revocation (RADIUS Only)

S T E P #	<p>This procedure changes the shared secret encryption key on DSR RADIUS setup.</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>	
1. <input type="checkbox"/>	Revoke RADIUS shared secret encryption key	<p>Refer to RADIUS Shared Secret Key revocation MOP to change the encryption key on the DSR installed setup. Refer to [20] DSR RADIUS Shared Secret Encryption Key Revocation MOP MO008572.</p> <p>Note: It is highly recommended to change the key after installation due to security reasons.</p>

Procedure 51. DSR Performance Tuning

S T E P #	<p>This procedure changes tuning parameters for the system to achieve better performance.</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>	
1. <input type="checkbox"/>	Performance tuning (Optional)	Refer Appendix I Performance Tuning Recommended for performance tuning on DSR.

Appendix A. Sample Network Element and Hardware Profiles

To enter all the network information for a network element into an AppWorks-based system, a specially formatted XML file needs to be filled out with the required network information. The network information is needed to configure both the NOAM and any SOAM network elements.

It is expected that the maintainer/creator of this file has networking knowledge of this product and the customer site at which it is being installed. The following is an example of a network element XML file.

The SOAM network element XML file needs to have same network names for the networks as the NOAM network element XML file has. It is easy to accidentally create different network names for NOAM and SOAM network elements, and then the mapping of services to networks are not possible.

```

<?xml version="1.0"?>
<networkelement>
  <name>NE</name>
  <networks>
    <network>
      <name>XMI</name>
      <vlanId>3</vlanId>
      <ip>10.2.0.0</ip>
      <mask>255.255.255.0</mask>
      <gateway>10.2.0.1</gateway>
      <isDefault>true</isDefault>
    </network>
  </networks>
</networkelement>

```

```

<network>
  <name>IMI</name>
  <vlanId>4</vlanId>
  <ip>10.3.0.0</ip>
  <mask>255.255.255.0</mask>
  <nonRoutable>true</nonRoutable>
</network>
</networks>
</networkelement>

```

Figure 4. Example Network Element XML File

Note: The Network Element Name should be unique when creating multiple Network Elements.

Appendix B. List of Frequently Used Time Zones

This table lists several valid time zone strings that can be used for the time zone setting in a CSV file, or as the time zone parameter when manually setting a DSR time zone.

Table 6. List of Selected Time Zone Values

Time Zone Value	Description	Universal Time Code (UTC) Offset
UTC	Universal Time Coordinated	UTC-00
America/New_York	Eastern Time	UTC-05
America/Chicago	Central Time	UTC-06
America/Denver	Mountain Time	UTC-07
America/Phoenix	Mountain Standard Time — Arizona	UTC-07
America/Los_Angeles	Pacific Time	UTC-08
America/Anchorage	Alaska Time	UTC-09
Pacific/Honolulu	Hawaii	UTC-10
Africa/Johannesburg		UTC+02
America/Mexico_City	Central Time — most locations	UTC-06
Africa/Monrovia		UTC+00
Asia/Tokyo		UTC+09
America/Jamaica		UTC-05
Europe/Rome		UTC+01
Asia/Hong_Kong		UTC+08
Pacific/Guam		UTC+10
Europe/Athens		UTC+02
Europe/London		UTC+00
Europe/Paris		UTC+01

Time Zone Value	Description	Universal Time Code (UTC) Offset
Europe/Madrid	mainland	UTC+01
Africa/Cairo		UTC+02
Europe/Copenhagen		UTC+01
Europe/Berlin		UTC+01
Europe/Prague		UTC+01
America/Vancouver	Pacific Time — west British Columbia	UTC-08
America/Edmonton	Mountain Time — Alberta, east British Columbia & west Saskatchewan	UTC-07
America/Toronto	Eastern Time — Ontario — most locations	UTC-05
America/Montreal	Eastern Time — Quebec — most locations	UTC-05
America/Sao Paulo	South & Southeast Brazil	UTC-03
Europe/Brussels		UTC+01
Australia/Perth	Western Australia — most locations	UTC+08
Australia/Sydney	New South Wales — most locations	UTC+10
Asia/Seoul		UTC+09
Africa/Lagos		UTC+01
Europe/Warsaw		UTC+01
America/Puerto Rico		UTC-04
Europe/Moscow	Moscow+00 — west Russia	UTC+04
Asia/Manila		UTC+08
Atlantic/Reykjavik		UTC+00
Asia/Jerusalem		UTC+02

Appendix C. Common KVM/OpenStack Tasks

Appendix C.1 Create a Network Port

Procedure 52. Create a Network Port

1. <input type="checkbox"/>	Create the network ports for the NO network interfaces	<ol style="list-style-type: none"> 1. Each network interface on an instance must have an associated network port. An instance usually has at least eth0 and eth1 for a public and private network respectively. Some configurations require 6 or more interfaces and corresponding network ports. 2. Determine the IP address for the interface. For eth0, the IP might be 10.x.x.157. For eth1, the IP might be 192.168.x.157 3. Identify the neutron network ID associated with each IP/interface using the neutron command line tool. <code>\$ neutron net-list</code> 4. Identify the neutron subnet ID associated with each IP/interface using the neutron command line tool. <code>\$ neutron subnet-list</code> 5. Create the network port using the neutron command line tool, being sure to choose an informative name. Note the use of the subnet ID and the network ID (final argument). Port names are usually a combination of instance name and network name. NO1-xmi SO2-im1 MP5-xsi2 The ports must be owned by the DSR tenant user, not the admin user. Either source the credentials of the DSR tenant user or use the DSR tenant user ID as the value for the --tenant-id argument. <code>\$. keystonec_dsr_user</code> <code>\$ keystone user-list</code> <code>\$ neutron port-create --name=NO1-xmi --tenant-id <tenant id> --fixed-ip subnet_id=<subnet id>,ip_address=10.x.x.157 <network id></code> <code>\$ neutron port-create --name=NO1-im1 --tenant-id <tenant id> --fixed-ip subnet_id=<subnet id>,ip_address=192.168.x.157 <network id></code> View your newly created ports using the neutron tool. <code>\$ neutron port-list</code>
--------------------------------	--	---

Appendix C.2 Create and Boot OpenStack Instance

Procedure 53. Create and Boot OpenStack Instance

<p>1. <input type="checkbox"/> Create a VM instance from a glance image</p>	<p>1. Get the following configuration values.</p> <p>The image ID.</p> <pre>\$ glance image-list</pre> <p>The flavor ID.</p> <pre>\$ nova flavor-list</pre> <p>The network ID(s)</p> <pre>\$ neutron net-list</pre> <p>An informative name for the instance.</p> <p>NO1 SO2 MP5</p> <p>2. Create and boot the VM instance.</p> <p>The instance must be owned by the DSR tenant user, not the admin user. Source the credentials of the DSR tenant user and issue the following command. Number of IP/interfaces for each VM type must conform with the OCDSR Network to Device Assignments defined in [24] DSR Cloud Benchmarking Guide.</p> <p>Note: IPv6 addresses should use the v6-fixed-ip argument instead of v4-fixed-ip.</p> <pre>\$ nova boot --image <image ID> --flavor <flavor id> --nic net-id=<first network id>,v4-fixed-ip=<first ip address> --nic net-id=<second network id>,v4-fixed-ip=<second ip address> InstanceName</pre> <p>View the newly created instance using the nova tool.</p> <pre>\$ nova list --all-tenants</pre> <p>The VM takes approximately 5 minutes to boot. At this point, the VM has no configured network interfaces and can only be accessed by the Horizon console tool.</p>
---	--

Appendix C.3 Configure Networking for OpenStack Instance

Procedure 54. Configure Networking for OpenStack Instance

1. <input type="checkbox"/>	Verify/Configure the network interface	<ol style="list-style-type: none"> Check if the interface is configured automatically. If DHCP is enabled on Neutron subnet, VM configures the VNIC with the IP address. To verify, ping the XMI IP address provided with the nova boot command: <pre>\$ ping <XMI-IP-Provided-During-Nova-Boot></pre> If the ping is successful, ignore the next part to configure the interface manually. Manually configure the interface, if not already done (optional). <ol style="list-style-type: none"> Log into the Horizon GUI as the DSR tenant user. Go to the Compute/Instances section. Click on the Name field of the newly created instance. Select the Console tab. Login as the admusr user. Configure the network interfaces, conforming with the interface-to-network mappings defined in [24] DSR Cloud Benchmarking Guide. <pre>\$ sudo netAdm add --onboot=yes --device=eth0 --address=<xmi ip> --netmask=<xmi net mask></pre> <pre>\$ sudo netAdm add --route=default --device=eth0 --gateway=<xmi gateway ip></pre> Under some circumstances, it may be necessary to configure as many as 6 or more interfaces. Reboot the VM. It takes approximately 5 minutes for the VM to complete rebooting. <pre>\$ sudo init 6</pre> The new VM should now be accessible using both network and Horizon console.
--------------------------------	--	---

Appendix D. Common OVM Manager Tasks (CLI)

Appendix D.1 Set Up the Server

Note: This section sets up the server using the command line interface of OVM Manager. All configurations/setup **can also be done** from the GUI/dashboard of OVM Manager.

Procedure 55. Set Up the Server

1. <input type="checkbox"/>	Log into the OVM-M command line interface	<pre>ssh -l admin <OVM-M IP> -p 1000</pre> Example: <pre>[root@manager01 ~]# ssh -l admin 10.240.16.138 -p 10000</pre> <code>admin@10.240.16.138's password:</code>
--------------------------------	---	---

Procedure 55. Set Up the Server

2. <input type="checkbox"/>	OVM-M CLI: Discover Oracle VM server	<pre>discoverServer ipAddress=value password=value takeOwnership= { Yes No }</pre> <p>Example:</p> <pre>OVM>discoverServer ipAddress=10.240.16.139 password=password takeOwnership=Yes</pre>
3. <input type="checkbox"/>	OVM-M CLI: Create an ethernet-based network with the VM role	<pre>create Network [roles= { MANAGEMENT LIVE_MIGRATE CLUSTER_HEARTBEAT VIRTUAL_MACHINE STORAGE }] name=value [description=value] [on Server instance]</pre> <p>Example:</p> <pre>OVM>create Network name=XMI roles=VIRTUAL_MACHINE</pre>
4. <input type="checkbox"/>	OVM-M CLI: Add a port from each Oracle VM server to the network	<p>Note: Skip this step and proceed to step 5 for bonded interfaces.</p> <ol style="list-style-type: none"> Find the ID of an Ethernet port. <pre>OVM> show Server name=MyServer1 ... Ethernet Port 1 = 0004fb00002000007711332ff75857ee [eth0 on MyServer3.virtlab.info] Ethernet Port 2 = 0004fb0000200000d2e7d2d352a6654e [eth1 on MyServer3.virtlab.info] Ethernet Port 3 = 0004fb0000200000c12192a08f2236e4 [eth2 on MyServer3.virtlab.info]</pre> Add a port from each Oracle VM Server to the network. <pre>OVM>add Port instance to { BondPort Network } instance</pre> <p>Example:</p> <pre>OVM>add Port id=0004fb0000200000d2e7d2d352a6654e to Network name=MyVMNetwork</pre>

Procedure 55. Set Up the Server

5.	OVM-M CLI: <input type="checkbox"/> Create Bondport (For Bonded Interfaces)	<ol style="list-style-type: none"> Find the ID of an Ethernet port. <pre>OVM>list Port Status: Success Time: 2016-08-22 04:43:02,565 EDT Data: id:0004fb000020000045b4e8dc0b3acc6 name:usb0 on vms01.test.com id:0004fb00002000005fde208ce6392c0a name:eth4 on vms01.test.com id:0004fb0000200000b1dceeb39006d839 name:eth5 on vms01.test.com id:0004fb000020000027e3a02bc28dd153 name:eth2 on vms01.test.com id:0004fb0000200000fce443e0d30cd3d5 name:eth3 on vms01.test.com id:0004fb0000200000a908e402fc542312 name:eth0 on vms01.test.com id:0004fb0000200000247b03c2a4a090ec name:eth1 on vms01.test.com</pre> Create Bondport on required interfaces. <pre>OVM>create BondPort ethernetPorts="0004fb0000200000b1dceeb39006d839,0004fb0 000200000fce443e0d30cd3d5" mode=ACTIVE_PASSIVE mtu=1500 name=bond1 on Server name=compute01.test.com Command: create BondPort ethernetPorts="0004fb0000200000b1dceeb39006d839,0004fb0 000200000fce443e0d30cd3d5" mode=ACTIVE_PASSIVE mtu=1500 name=bond1 on Server name=compute01.test.com Status: Success</pre>
6.	OVM-M CLI: <input type="checkbox"/> Add VLAN Interface to network (for VLAN tagged networks)	<ol style="list-style-type: none"> Find the ID of an Ethernet port. <pre>OVM>list BondPort Command: list BondPort Status: Success Time: 2016-08-22 04:38:22,327 EDT Data: id:0004fb00002000005a45a0761813d512 name:bond1 id:0004fb0000200000645cf865736cea8 name:bond0 on compute01.test.com</pre> Create VLAN interface. <pre>OVM>create VlanInterface vlanId=43 name=bond1.43 on BondPort id=0004fb00002000005a45a0761813d512</pre>

Procedure 55. Set Up the Server

	<p>Command: create VlanInterface vlanId=43 name=bond1.43 on BondPort id=0004fb00002000005a45a0761813d512</p> <p>Status: Success</p> <p>3. Add remaining VLAN interfaces to the same bond accordingly, like:</p> <p>OVM>create VlanInterface vlanId=44 name=bond1.44 on BondPort id=0004fb00002000005a45a0761813d512</p> <p>OVM>create VlanInterface vlanId=30 name=bond1.30 on BondPort id=0004fb00002000005a45a0761813d512</p> <p>OVM>create VlanInterface vlanId=31 name=bond1.31 on BondPort id=0004fb00002000005a45a0761813d512</p> <p>4. Add VLAN interfaces to network.</p> <p>OVM>add VlanInterface name=bond1.43 to Network name=XMI</p> <p>Command: add VlanInterface name=bond1.43 to Network name=XMI</p> <p>Status: Success</p> <p>Time: 2016-08-22 05:14:29,321 EDT</p> <p>JobId: 1471857258238</p> <p>OVM>add VlanInterface name=bond1.44 to Network name=IMI</p> <p>Command: add VlanInterface name=bond1.44 to Network name=IMI</p> <p>Status: Success</p> <p>Time: 2016-08-22 05:15:24,216 EDT</p> <p>JobId: 1471857321329</p> <p>OVM>add VlanInterface name=bond1.30 to Network name=XSI1</p> <p>Command: add VlanInterface name=bond1.30 to Network name=XSI1</p> <p>Status: Success</p> <p>Time: 2016-08-22 05:15:39,190 EDT</p> <p>JobId: 1471857337005</p> <p>OVM>add VlanInterface name=bond1.31 to Network name=XSI2</p> <p>Command: add VlanInterface name=bond1.31 to Network name=XSI2</p> <p>Status: Success</p> <p>Time: 2016-08-22 05:15:52,576 EDT</p> <p>JobId: 1471857349684</p>
--	--

Procedure 55. Set Up the Server

7. <input type="checkbox"/>	OVM-M CLI: Create unclustered server pool	<p>Note: To create clustered server pool, ignore this step and proceed to next.</p> <pre>OVM>create ServerPool clusterEnable=No name=MyServerPool description='Unclustered server pool'</pre>
8. <input type="checkbox"/>	OVM-M CLI: Create clustered server pool (Optional)	<p>Note: Skip this step if an unclustered server pool is already created. This step is only if required to create a clustered server pool.</p> <ol style="list-style-type: none"> To create a clustered server pool you must provide a file system or physical disk to use for the server pool file system. To find a file system or physical disk, use the list command: <pre>OVM>list FileSystem id:66a61958-e61a-44fe-b0e0-9dd64abef7e3 name:nfs on 10.172.76.125:/mnt/vol1/poolfs03 id:0004fb0000050000b85745f78b0c4b61 name:fs on 350014ee2568cc0cf id:4ebb1575-e611-4662-87b9-a84b40ce3db7 name:nfs on 10.172.76.125:/mnt/vol1/poolfs04 id:858d98c5-3d8b-460e-9160-3415cbdda738 name:nfs on 10.172.76.125:/mnt/vol1/poolfs01 id:0dea4818-20e6-4d3a-958b-b12cf91588b5 name:nfs on 10.172.76.125:/mnt/vol1/poolfs02 id:35b4f1c6-182b-4ea5-9746-51393f3b515c name:nfs on 10.172.76.125:/mnt/vol2/repo03 id:aeb6143d-0a96-4845-9690-740bbf1e225e name:nfs on 10.172.76.125:/mnt/vol1/repo01 id:05e8536f-8d9c-4d7c-bbb2-29b3ffafe011 name:nfs on 10.172.76.125:/mnt/vol2/repo02 id:0004fb00000500006a46a8dbd2461939 name:MyServerPool_cluster_heartbeat id:0004fb00000500000809e28f4fab56b1 name:fs on 350014ee20137ee44 OVM>list PhysicalDisk id:0004fb000018000019b86ccf3f473a9e name:FreeBSD (9) id:0004fb0000180000c4609a67d55b5803 name:FreeBSD (3) id:0004fb00001800002179de6afe5f0cf3 name:SATA_WDC_WD5001ABYS_-_WD-WCAS86288968 id:0004fb0000180000a0b43f9684fc78ac name:FreeBSD (2) id:0004fb0000180000732be086afb26911 name:FreeBSD (7) id:0004fb000018000067ce80973e18374e name:FreeBSD (8) id:0004fb000018000035ce16ee4d58dc4d name:FreeBSD (1) id:0004fb00001800006855117242d9a537 name:FreeBSD (6) id:0004fb0000180000a9c7a87ba52ce5ec name:FreeBSD (5) id:0004fb0000180000ebabef9838188d78 name:SATA_WDC_WD5001ABYS_-_WD-WCAS86571931</pre>

Procedure 55. Set Up the Server

		<pre> id:0004fb00001800008f6ea92426f2cfb8 name:SATA_WDC_WD5001ABYS-_WD-WCAS86257005 id:0004fb00001800008ccb1925cdbbd181 name:SATA_WDC_WD5001ABYS-_WD-WCAS86578538 id:0004fb0000180000e034b4662665161c name:FreeBSD (4) </pre> <p>2. Before you create a clustered server pool you must refresh the file system or physical disk to be used for the server pool file system. To refresh a file system:</p> <pre> OVM>refresh { AccessGroup Assembly FileServer FileSystem PhysicalDisk Repository Server StorageArray VirtualAppliance } instance </pre> <p>For example, to refresh a physical disk:</p> <pre> OVM>refresh PhysicalDisk id=0004fb000018000035ce16ee4d58dc4d </pre> <p>3. Refresh a file system:</p> <pre> OVM>refresh FileSystem name="nfs on 10.172.76.125://mnt//vol1//repo01" OVM>create ServerPool clusterEnable=Yes filesystem="nfs on 10.172.76.125://mnt//vol1//poolfs01" name=MyServerPool description='Clustered server pool' </pre>
9. <input type="checkbox"/>	OVM-M CLI: Add Oracle VM servers to the server pool	<pre> OVM>add Server name=MyServer to ServerPool name=MyServerPool </pre>
10. <input type="checkbox"/>	OVM-M CLI: Create storage repository	<p>1. Find the physical disk (LUN) to use for creating the storage repository.</p> <pre> OVM>list FileServer </pre> <p>Command: list FileServer</p> <p>Status: Success</p> <p>Time: 2016-08-19 02:11:39,779 EDT</p> <p>Data:</p> <pre> id:0004fb00000900000445dac29e88bc38 name:Local FS vms03.test.com id:0004fb000009000045715cad6f165ecf name:Local FS vms01.test.com id:0004fb0000090000df4cd9c3170092e4 name:Local FS vms02.test.com id:0004fb000009000064b96ed88a9a0185 name:Local FS vms04.test.com </pre> <p>2. Find a local file system on an Oracle VM server that has access to the LUN.</p> <pre> OVM>list FileServer </pre> <p>Command: list FileServer</p> <p>Status: Success</p>

Procedure 55. Set Up the Server

	<pre> Time: 2016-08-19 02:11:39,779 EDT Data: id:0004fb00000900000445dac29e88bc38 name:Local FS vms03.test.com id:0004fb000009000045715cad6f165ecf name:Local FS vms01.test.com id:0004fb0000090000df4cd9c3170092e4 name:Local FS vms02.test.com id:0004fb000009000064b96ed88a9a0185 name:Local FS vms04.test.com </pre> <p>3. Create file system.</p> <pre> OVM>create FileSystem name=VmsFs01 physicalDisk="OVM_SYS_REPO_PART_3600605b00a2a024000163e 490ac3f392" on FileServer name="Local FS vms01.test.com" Command: create FileSystem name=VmsFs01 physicalDisk="OVM_SYS_REPO_PART_3600605b00a2a024000163e 490ac3f392" on FileServer name="Local FS vms01.test.com" Status: Success </pre> <p>Time: 2016-08-19 02:22:46,581 EDT</p> <p>JobId: 1471587738752</p> <p>Data:</p> <pre> id:0004fb00000500006779d42da60c0be6 name:VmsFs01 </pre> <p>4. Create repository.</p> <pre> OVM>create Repository name=Vms01Repo on FileSystem name=VmsFs01 Command: create Repository name=Vms01Repo on FileSystem name=VmsFs01 Status: Success </pre> <p>Time: 2016-08-19 02:24:04,092 EDT</p> <p>JobId: 1471587843432</p> <p>Data:</p> <pre> id:0004fb00000300003c8f771791114d53 name:Vms01Repo </pre> <p>5. Add server pool to repository.</p> <pre> OVM> add ServerPool name=TestPool001 to Repository name=Vms01Repo Refresh the storage repository using the syntax: </pre> <pre> OVM> refresh Repository name=MyRepository </pre>
--	---

Appendix D.2 Server Pool

A server pool is a required entity in Oracle VM, even if it contains a single Oracle VM Server. In practice, several Oracle VM servers form a server pool, and an Oracle VM environment may contain one or several server pools. Server pools are typically clustered, although an unclustered server pool is also possible. Server pools have shared access to storage repositories and exchange and store vital cluster information in the server pool file system. Refer [22] Oracle VM Concepts Guide for more information.

Appendix E. Scale a Signaling Node

Execute this procedure only if an additional signaling node(s) needs to be deployed to an existing DSR deployment.

Procedure 56. Scale a Signaling Node

S T E P #	<p>Note: This procedure is ONLY required if additional Signaling Node(s) needs to be deployed to an existing DSR deployment.</p> <p>Prerequisite: DSR topology is already deployed and configured as per section 4 Software Installation Using HEAT Templates (OpenStack).</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>	
1. <input type="checkbox"/>	<p>Create new signaling stack</p>	<ol style="list-style-type: none"> 1. Prepare OpenStack templates and environment files for signaling stacks by following instructions in Procedure 9 for signaling stacks. 2. Create OpenStack parameter file for signaling stacks by following instructions in Procedure 11. <p>Note: Change the number of signaling node(s) as per the requirement.</p> <ol style="list-style-type: none"> 3. Deploy the stacks by following instructions in Procedure 12. <p>Note: New stack is created as part of this procedure.</p>
2. <input type="checkbox"/>	<p>Configure new site in the existing topology</p>	<ol style="list-style-type: none"> 1. Create a new network element by following Procedure 21 to define the network for new site being configured. 2. Configure the SOAM servers by following Procedure 22 to create the SOAM servers. 3. Configure the SOAM server group by following Procedure 23 to create SOAM server group. 4. Configure the MP virtual machines by following Procedure 24. 5. Configure the MP server group(s) and profiles by following Procedure 28. 6. Configure the signaling network routes by following Procedure 30. 7. If deployed stack contains IPFE servers, then configure the IPFE by following Procedure 32.
3. <input type="checkbox"/>	<p>Repeat</p>	<p>Repeat this procedure if more signaling nodes are required.</p>

Appendix F. Firewall Ports

Flow Description	Purpose	Protocol/Port	IP Protocol Version
NTP flow for time sync	XMI network	UDP:123	IPv4 , IPv6
hostname resolution (dns)	XMI, IMI Network	UDP/TCP: 53	IPv4, IPv6
LightWeight Directory Access Protocol (LDAP)	XMI Network	UDP/TCP: 389	IPv4, IPv6
SSH	XMI Network	TCP: 22	IPv4, IPv6
GUI	XMI Network	TCP: 80, TCP:443	IPv4, IPv6

For information about Firewall Ports, Refer to DSR 8.3 IP flow document, E99037-01.

Appendix G. Application VIP Failover Options (OpenStack)

Appendix G.1 Application VIP Failover Options

Within an OpenStack cloud environment, there are several options for allowing applications to manage their own virtual IP (VIP) addresses as is traditionally done in telecommunications applications. This document describes two of those options:

- Allowed address pairs
- Disable port security

Each of these options is covered in the major sub-sections that follow. The last major sub-section discusses how to utilize application managed virtual IP addresses within an OpenStack VM instance.

Both of these options effectively work around the default OpenStack Networking (Neutron) service anti-spoofing rules that ensure that a VM instance cannot send packets out a network interface with a source IP address different from the IP address Neutron has associated with the interface. In the Neutron data model, the logical notion of networks, sub-networks and network interfaces are realized as networks, subnets, and ports as shown in Figure 5:




Figure 5. Neutron High-Level Data Model

Note how a port in the Neutron data model maps to at most one VM instance where internal to the VM instance, the port is represented as an available network device such as eth0. VM instances can have multiple network interfaces in which case there are multiple Neutron ports associated with the VM instance, each with different MAC and IP addresses.

Each Neutron port by default has one MAC Address and one IPv4 or IPv6 address associated with it. The IP address associated with a port can be assigned in two ways:

- Automatically by Neutron when creating a port to fulfill an OpenStack Compute (Nova) service request to associate a network interface with a VM instance to be instantiated

OR

- Manually by a cloud administrator when creating or updating a Neutron port

The anti-spoofing rules are enforced at the Neutron port level by ensuring that the source IP address of outgoing packets matches the IP address Neutron has associated with the corresponding port assigned to the VM instance. By default if the source IP address in the outgoing packet does not match the IP address associated with the corresponding Neutron port then the packet is dropped.

These anti-spoofing rules clearly create a complication for the use of application managed virtual IP addresses since Neutron is not going to know about the VIPs being applied by the application to VM instance network interfaces without some interaction between the application (or a higher level management element) and Neutron. Which is why the two options in this document either fully disable the port security measures within Neutron, including the anti-spoofing rules, or expand the set of allowable source IP addresses to include the VIPs that may be used by the application running within a VM instance.

Note that for both of the options described in the following sub-sections, there is a particular Neutron service extension or feature that must be enabled for the option to work. For one option (allowed address pairs) the required Neutron extension is enabled in most default deployments whereas for the other option (allow port security to be disabled) it is not.

Within this document when describing how to use either of these two options, there are example command line operations that interact with the OpenStack Neutron service using its command line utility, simply

named neutron. However, be aware that all of the operations performed using the neutron command line utility can also be performed through the Neutron REST APIs, see the [Networking v2.0 API documentation](#) for more information.

Appendix G.2 Allowed Address Pairs

This section describes an option that extends the set of source IP addresses that can be used in packets being sent out a VM instance's network interface (which maps to a Neutron port). This option utilizes a Neutron capability, called the allowed-address-pairs extension, which allows an entity (cloud administrator, management element, etc.) to define additional IP addresses to be associated with a Neutron port. In this way, if an application within the VM instance sends an outgoing packet with one of those additional IP addresses, then Neutron anti-spoofing rules enforcement logic does not drop those packets. The Neutron allowed-address-pairs extension is available starting with the OpenStack Havana release.

The three sub-sections that follow describe the OpenStack configuration requirements for this option, how to use this option after a VM instance has already booted, and how to utilize this option before a VM instance has booted.

Appendix G.3 OpenStack Configuration Requirements

The Neutron allowed-address-pairs extension needs to be enabled for this option to work. For most OpenStack cloud deployments this extension should be enabled by default but to check, run the following command (after sourcing the appropriate user credentials file):

```
# neutron ext-list
+-----+-----+
| alias | name
+-----+-----+
| security-group | security-group
| l3_agent_scheduler | L3 Agent Scheduler
| net-mtu | Network MTU
| ext-gw-mode | Neutron L3 Configurable external gateway mode
| binding | Port Binding
| provider | Provider Network
| agent | agent
| quotas | Quota management support
| subnet_allocation | Subnet Allocation
| dhcp_agent_scheduler | DHCP Agent Scheduler
| l3-ha | HA Router extension
| multi-provider | Multi Provider Network
| external-net | Neutron external network
| router | Neutron L3 Router
| allowed-address-pairs | Allowed Address Pairs
| extraroute | Neutron Extra Route
| extra_dhcp_opt | Neutron Extra DHCP opts
| dvr | Distributed Virtual Router
+-----+-----+
```

The allowed-address-pairs extension should appear in the list of extensions as shown in the bold line above.

Appendix G.4 After a VM Instance has been Booted: Allowed Address Pairs

If a VM instance has already been booted, that is, instantiated, and you need to associate one or more additional IP addresses with the Neutron port assigned to the VM instance then you need to execute a command of the following form:

```
# neutron port-update <Port ID> --allowed_address_pairs list=true type=dict ip_address=<VIP address to be added>
```

Where the bolded items have the following meaning:

- <Port ID>
Identifies the ID of the port within Neutron which can be determined by listing the ports, `neutron port-list`, or if the port is named then the port ID can be obtained directly in the above command with a sequence like `$(neutron port-show -f value -F id <Port Name>)` to replace the <Port ID> placeholder.
- <VIP address to be added>
Identifies the IP address, a virtual IP address in this case, that should additionally be associated with the port where this can be a single IP address, for example, 10.133.97.135/32, or a range of IP addresses as indicated by a value such as 10.133.97.128/30.

So for example if you wanted to indicate to Neutron that the allowed addresses for a port should include the range of addresses between 10.133.97.136 to 10.133.97.139 and the port had an ID of 8a440d3f-4e5c-4ba2-9e5e-7fc942111277 then you would type the following command:

```
# neutron port-update 8a440d3f-4e5c-4ba2-9e5e-7fc942111277 --allowed_address_pairs list=true type=dict ip_address=10.133.97.136/30
```

Appendix G.5 Before a VM Instance has been Booted: Allowed Address Pairs

If you want to associate additional allowed IP addresses with a port before it is associated with a VM instance then you need to first create the port and then associate one or more ports with a VM instance when it is booted. The command to create a new port with defined allowed address pairs is of the following form:

```
# neutron port-create --name <Port Name> --fixed-ip subnet-id=$(neutron subnet-show -f value -F id <Subnet name>),ip_address=<Target IP address> $(neutron net-show -f value -F id <Network name>) --allowed_address_pairs list=true type=dict ip_address=<VIP address to be added>
```

Where the bolded items have the following meaning:

- <Port Name>
This is effectively a string alias for the port that is useful when trying to locate the ID for the port but the **--name <Port Name>** portion of the command is completely optional.
- <Subnet name>
The name of the subnet to which the port should be added.
- <Target IP address>
The unique IP address to be associated with the port.
- <Network Name>
The name of the network with which the port should be associated.
- <VIP address to be added>
This parameter value has the same meaning as described in the previous section.

So for example if you wanted to indicate to Neutron that a new port should have an IP address of 10.133.97.133 on the **ext-subnet** subnet with a single allowed address pair, 10.133.97.134, then you would type a command similar to the following:

```
# neutron port-create --name foo --fixed-ip subnet-id=$(neutron subnet-show -f value -F id ext-subnet),ip_address=10.133.97.133 $(neutron net-show -f value -F id ext-net) --allowed_address_pairs list=true type=dict ip_address=10.133.97.134/32
```

Once the port or ports with the additional allowed addresses have been created, when you boot the VM instance use a nova boot command similar to the following:

```
# nova boot --flavor m1.xlarge --image testVMimage --nic port-id=$(neutron port-show -f value -F id <Port Name>) testvm3
```

where the flavor, image, and VM instance name values need to be replaced by values appropriate for your VM. If the port to be associated with the VM instance is not named, then you need to obtain the port's ID using the neutron port-list command and replace the `$(neutron port-show -f value -F id <Port Name>)` sequence in the above command with the port's ID value.

Appendix G.6 Disable Port Security

This section describes an option that rather than extending the set of source IP addresses that are associated with a Neutron port, as is done with the allowed-address-pairs extension, to disable the Neutron anti-spoofing filter rules for a given port. This option allows all IP packets originating from the VM instance to be propagated no matter whether the source IP address in the packet matches the IP address associated with the Neutron port or not. This option relies upon the Neutron port security extension that is available starting with the OpenStack Kilo release.

The three sub-sections that follow describe the OpenStack configuration requirements for this option, how to use this option after a VM instance has already booted, and how to use this option before a VM instance has booted.

OpenStack Configuration Requirements

The Neutron port security extension needs to be enabled for this method to work. For the procedure to enable the port security extension see the [ML2 Port Security Extension Wiki page](#).

Note: Enabling the port security extension when there are already existing networks within the OpenStack cloud causes all network related requests into Neutron to fail due to a [known bug in Neutron](#). There is a fix identified for this bug that is part of the Liberty release and is scheduled to be backported to the Kilo 2015.1.2 release. In the meantime, **this option is only non-disruptive when working with a new cloud deployment where the cloud administrator can enable this feature before any networks and VM instances that use those networks are created.** The port security extension can be enabled in an already deployed OpenStack cloud, but all existing networks, subnets, ports, etc., need to be deleted before enabling the port security extension. This typically means all VM instances also need to be deleted as well, but a knowledgeable cloud administrator **may** be able to do the following to limit the disruption of enabling the port security extension:

- Record the current IP address assignments for all VM instances,
- Remove the network interfaces from any existing VM instances,
- Delete the Neutron resources,
- Enable the port security extension,
- Re-create the previously defined Neutron resources (networks, subnets, ports, etc.), and then
- Re-add the appropriate network interfaces to the VMs.

Depending on the number of VM instances running in the cloud, this procedure may or may not be practical.

Appendix G.7 After a VM Instance has been Booted: Port Security

If you need to disable port security for a port after it has already been associated with a VM instance, then you need to execute one or both of the following commands to use the port security option. First, if the VM instance with which the existing port is associated has any associated security groups ([run nova list-secgroup <VM instance name>](#) to check), then you first need to run a command of the following form for each of the security group(s) associated with the VM instance:

```
# nova remove-secgroup <VM instance name> <Security group name>
```

where the bolded item has the following meaning:

- <VM instance name>
Identifies the name of the VM instance for which the identified security group name should be deleted.
- <Security group name>
Identifies the name of the security group that should be removed from the VM instance.

So for example if you wanted to remove the default security group from a VM instance named 'testvm4' then you would type a command similar to the following:

```
# nova remove-secgroup testvm4 default
```

Once any security groups associated with VM instance to which the Neutron port is assigned have been removed, then the Neutron port(s) associated with the target VM instance need to be updated to disable port security on those ports. The command to disable port security for a specific Neutron port is of the form:

```
# neutron port-update <Port ID> -- port-security-enabled=false
```

where the bolded item has the following meaning:

- <Port ID>
Identifies the ID of the port within Neutron which can be determined by listing the ports, [neutron port-list](#), or if the port is named then the port ID can be obtained directly in the above command with a sequence such as [\\$\(neutron port-show -f value -F id <Port Name>\)](#).

So for example if you wanted to indicate to Neutron that port security should be disabled for a port with an ID of 6d48b5f2-d185-4768-b5a4-c0d1d8075e41 then you would type the following command:

```
# neutron port-update 6d48b5f2-d185-4768-b5a4-c0d1d8075e41 --port-security-enabled=false
```

If the port-update command succeeds, within the VM instance with which the 6d48b5f2-d185-4768-b5a4-c0d1d8075e41 port is associated, application managed VIPs can now be added to the network interface within the VM instance associated with the port and network traffic using that VIP address should now propagate.

Appendix G.8 Before a VM Instance has been Booted: Port Security

If you want to disable port security for a port before it is associated with a VM instance, then you need to first create the port at which time you can specify that port security should be disabled. The command to create a new port with port security disabled is of the following form:

```
# neutron port-create --name <Port Name> --port-security-enabled=false --fixed-ip subnet-id=$(neutron subnet-show -f value -F id <Subnet
```

```
name> , ip_address=<Target IP address> $(neutron net-show -f value -F id
<Network name>)
```

where the bolded items have the following meaning:

- <Port Name>

This is effectively a string alias for the port that is useful when trying to locate the ID for the port but the **--name <Port Name>** portion of the command is completely optional.

- <Subnet name>

The name of the subnet to which the port should be added.

- <Target IP address>

The unique IP address to be associated with the port.

- <Network Name>

The name of the network with which the port should be associated.

So for example if you wanted to indicate to Neutron that a new port should have port security disabled and an IP address of 10.133.97.133 on the **ext-subnet** subnet then you would type a command similar to the following:

```
# neutron port-create --name foo --port-security-enabled=false --fixed-ip
subnet-id=$(neutron subnet-show -f value -F id ext-
subnet),ip_address=10.133.97.133 $(neutron net-show -f value -F id ext-net)
```

Once the port or ports with port security disabled have been created, when you boot the VM instance, you need to execute a command similar to the following:

```
# nova boot --flavor m1.xlarge --image testVMimage --nic port-id=$(neutron
port-show -f value -F id <Port Name>) testvm3
```

where the flavor, image, and VM instance name values need to be replaced by values appropriate for your VM. If the port to be associated with the VM instance is not named, then you need to obtain the port's ID using the neutron port-list command and replace the **\$(neutron port-show -f value -F id <Port Name>)** sequence in the above command with the port's ID value.

Appendix G.9 Managing Application Virtual IP Addresses within VM Instances

Once either of the previously described options is in place to enable applications to manage their own virtual IP addresses, there should be no modifications required to how the application already manages its VIPs in a non-virtualized configuration. There are many ways that an application can add or remove virtual IP addresses but as a reference point, here are some example command line operations to add a virtual IP address of 10.133.97.136 to the eth0 network interface within a VM and then send four gratuitous ARP packets to refresh the ARP caches of any neighboring nodes:

```
# ip address add 10.133.97.136/23 broadcast 10.133.97.255 dev eth0 scope
global
# arping -c 4 -U -I eth0 10.133.97.136
```

As the creation of virtual IP addresses typically coincides with when an application is assigned an active role, the above operations would be performed both when an application instance first receives an initial active HA role or when an application instance transitions from a standby HA role to the active HA role.

Appendix H. Sample Net Rules File

Udev uses rules files that determine how it identifies devices and creates device names. The udev daemon (udevd) reads the rules files at system startup and stores the rules in memory. If the kernel discovers a new device or an existing device goes offline, the kernel sends an event action (uevent) notification to udevd, which matches the in-memory rules against the device attributes in /sys to identify the device. As part of device event handling, rules can specify additional programs that should run to configure a device. Rules file, which have the file extension .rules, is located in the following directory: /etc/udev/rules.d/*.rules

Sample File:

```
# eth0 interface with MAC address "fa:16:3e:cc:12:d6" will be assigned "xmi"
SUBSYSTEM=="net", ACTION=="add", DRIVERS=="?*", 
ATTR{address}=="fa:16:3e:cc:12:d6", ATTR{dev_id}=="0x0", ATTR{type}=="1",
KERNEL=="eth*", NAME="xmi"

# eth1 interface with MAC address "fa:16:3e:1a:8d:8a" will be assigned "int"
SUBSYSTEM=="net", ACTION=="add", DRIVERS=="?*", 
ATTR{address}=="fa:16:3e:1a:8d:8a", ATTR{dev_id}=="0x0", ATTR{type}=="1",
KERNEL=="eth*", NAME="int"
```

Note: If you need a 3rd interface add respective entry also. The iDIH Mediation VM needs an imi interface too.

```
# eth1 interface with MAC address "fa:16:3e:1a:8d:8a" will be assigned "int"
SUBSYSTEM=="net", ACTION=="add", DRIVERS=="?*", ATTR{address}=="fa:16:3e:8a:1a:12", ATTR{dev_id}=="0x0", ATTR{type}=="1", KERNEL=="eth*", NAME="imi":
```

Notes:

1. MAC address of each interfaces can be determined using the following command issued from the console: `ifconfig -a`
2. Update MAC address for each interface. The MAC addresses must be entered in all lower case.
3. Update the interface names as in the above example

Appendix I. Performance Tuning Recommended

Appendix I.1 KVM/OpenStack

For the DSR system to achieve 50K MPS or more through IPFE, a few tuning parameters need to be changed.

txqueuelen

Tuned on the compute hosts.

Purpose: default value of 500 is too small. Our recommendation is to set to 30000. Increases the network throughput of a VM.

How/What to change:

On each compute host, do the following as root.

```
# cat > /etc/udev/rules.d/60-tap.rules << EOF
KERNEL=="tap*", RUN+="/sbin/ip link set %k txqueuelen 30000"
EOF
```

Reload and apply to the running system

```
# udevadm control --reload-rules
# udevadm trigger --attr-match=subsystem=net
```

Ring buffer increase on the physical ethernet interfaces

Tuned on the compute hosts.

Purpose: Improves the overall network throughput of the host.

How/What to change: This varies depending on the Host OS. The following steps are applicable to centos/fedora/rhel.

Add the following line into the network script of the interface you want to change. For example: To change the ring buffer on the eth2 interface. Edit /etc/sysconfig/network-scripts/ifcfg-eth2 to add the `ETHTOOL_OPTS=` line as shown.

```
DEVICE=eth2
TYPE=Ethernet
ETHTOOL_OPTS="--set-ring eth2 rx 4096 tx 4096"
```

Restart the network using "service network restart" as root. Check the setting using `ethtool -g eth2`.

Multiqueue [on IPFE]

To be enabled on the openstack flavor and glance image for IPFE instance.

Purpose: Improves the network throughput of a VM.

How/What to change:

You need to update the flavor and the image to enable multiqueue. All guests using that image will be created with multiqueue.

```
# openstack flavor set m1.large --property hw:vif_multiqueue_enabled=true
# glance image-update b5592ed4-8f41-48a9-9f0c-e0e46cb3dd6c --property
hw_vif_multiqueue_enabled=true
```

On the Guest set the number of queues to number of vcpus.

```
ethtool -L <eth interface> combined <number of vcpus>
```

Appendix I.2 VMware

txqueuelen

Tuned on the ESXi hosts.

Purpose: Default value of 500 is too small. The recommendation is to set to 10000 which increases the network throughput of a VM. ESXi defaults the value to 500 and permits a max value of 10000

How/What to change:

Log into the cli console of the ESX host and execute the below esxcli command:

```
#esxcli system settings advanced set -i=10000 -o=/Net/MaxNetifTxQueueLen
```

Ring buffer increase on the physical Ethernet interfaces

Tuned on the ESXi hosts.

Purpose: Improves the overall network throughput of the host. On an ESXi host Rx buffer defaults to 512 and Tx buffer defaults to 1024 and the max value for both is 4096

How/What to change:

Log into the cli console of the ESX host and execute the below esxcli commands:

```
#esxcfg-nics -l      (lists all the physical NICs attached to the host)
#ethtool -g <interface name>  (shows the current ring buffer size)
#ethtool -G <interface name> rx 4096  (increases the rx buffer size to
4096)
#ethtool -G <interface name> tx 4096  (increases the tx buffer size to
4096)
```

Multiqueue

Already enabled on ESXi for vmxnet3 adapters.

Purpose: Improves the network throughput of a VM.

Advanced NUMA settings

Tuned on ESXi hosts.

Purpose: Prevents the ESXi scheduler to move VMs around from one NUMA node to another.

How/What to change:

Log into the cli console of the ESX host and execute the below esxcli commands:

```
#esxcli system settings advanced set -i=0 -o=/Numa/SwapLoadEnable
#esxcli system settings advanced set -i=0 -o=/Numa/SwapLocalityEnable
```

Appendix J. Example Files**Appendix J.1 Example Template File**

Basic guidelines to follow while working with YAML files:

- The file must be ended with .yaml extension.
- YAML must be case-sensitive and indentation-sensitive.
- YAML does not support the use of tabs. Instead of tabs, it uses spaces.

YAML is a human-friendly data serialization standard for all programming languages.

The values of the **key:value** can be broadly classified into the following types:

Type	Description	Examples
string	A literal string.	“String param”
number	An integer or float.	“2”; “0.2”
comma_delimited_list	An array of literal strings that are separated by commas. The total number of strings should be one more than the total number of commas.	["one", "two"]; “one, two”; Note: “one, two” returns [“one”, “two”]
json	A JSON-formatted map or list.	{"key": “value”}
boolean	Boolean type value, which can be equal “t”, “true”, “on”, “y”, “yes”, or “1” for true value and “f”, “false”, “off”, “n”, “no”, or “0” for false value.	“on”, “n”

Appendix J.2 Example Parameter File

The parameter file defines the topology details. This includes all VM details such as the number of VMs, flavors, network names, etc. It is a list of key/value pairs. By referring to the **parameters** definition section in the template file, the initialization of the parameters has to be done in this section.

File Naming Convention

It is not mandatory to have a specific name for the file; but just to provide a self-explanatory name for the file, it is recommended to follow this convention:

<DSR Name>_<Site Name>_<NetworkOam/SignallingNode>_Params.yaml

For example:

- dsrCloudInit_Site00_NetworkOam_Params.yaml
- dsrCloudInit_Site00_SignalingNode_Params.yaml

Sample File

Network OAM params file

parameters:

```
numPrimaryNoams: 1
numNoams: 1
noamImage: DSR-60147
noamFlavor: dsr.noam
primaryNoamVmNames: ["DsrSite00NOAM00"]
noamVmNames: ["DsrSite00NOAM01"]
noamAZ: nova
xmiPublicNetwork: ext-net
imiPrivateNetwork: imi
imiPrivateSubnet: imi-sub
imiPrivateSubnetCidr: 192.168.221.0/24
ntpServer: 10.250.32.10
noamSG: Site00_NOAM_SG
```

Signaling params file

parameters:

```
numSoams: 2
numDas: 1
numlpfes: 1
numStps: 0
soamImage: DSR-60147
soamFlavor: dsr.soam
soamVmNames: ["DsrSite00SOAM00", "DsrSite00SOAM01"]
dalimage: DSR-60147
```

```
daFlavor: dsr.da
daVmNames: ["DsrSite00DAMP00", "DsrSite00DAMP01"]
daProfileName: "VM_30K_Mps"
ipfelImage: DSR-60147
ipfeFlavor: dsr.ipfe
ipfeVmNames: ["DsrSite00IPFE00", "DsrSite00IPFE01"]
stplImage: none
stpFlavor: none
stpVmNames: none
xmiPublicNetwork: ext-net
imiPrivateNetwork: imi
imiPrivateSubnet: imi-sub
imiPrivateSubnetCidr: 192.167.2.0/24
xsiPublicNetwork: ext-net
ntpServer: 10.250.32.10
soamAZ: nova
daAZ: nova
ipfeAZ: nova
stpAZ: nova
soamSG: Site00_SOAM_SG
daSG: Site00_DAMP_SG
ipfeSGs: ["Site00_IPFE_SG0", "Site00_IPFE_SG1"]
stpSG: Site00_STP_SG
primaryNoamVmName: DsrSite00NOAM00
noamXmilps: ["10.75.191.170"]
diameterTcpPorts: [3868]
diameterSctpPorts: []
stpSctpPorts:[]
```

Network OAM params file (Fixed IP)

parameters:

```
numPrimaryNoams: 1
numNoams: 1
noamlImage: DSR-8.2.0.0.0_82.5.1.vmdk
noamFlavor: dsr.noam
primaryNoamVmNames: ["DsrSite00NOAM00"]
noamVmNames: ["DsrSite00NOAM01"]
noamAZ: nova
primaryNoamXmilps: ["10.196.12.83"]
noamXmilps: ["10.196.12.84"]
noamVip: 10.196.12.85
xmiPublicNetwork: ext-net3
imiPrivateNetwork: imi
imiPrivateSubnet: imi-sub
imiPrivateSubnetCidr: 192.168.221.0/24
ntpServer: 10.75.185.194
noamSG: Site00_NOAM_SG
```

Signaling params file (Fixed IP)

parameters:

```
numSoams: 2
numDas: 2
numlpfes: 1
numStps: 0
soamlImage: DSR-8.2.0.0.0_82.5.1.vmdk
soamFlavor: dsr.soam
soamVmNames: ["DsrSite00SOAM00", "DsrSite00SOAM01"]
soamXmilps: ["10.196.12.83", "10.196.12.84"]
soamVip: 10.196.12.86
daProfileName: "VM_30K_Mps"
dalImage: DSR-8.2.0.0.0_82.5.1.vmdk
daFlavor: dsr.da
daVmNames: ["DsrSite00DAMP00", "DsrSite00DAMP01"]
daMpXmilps: ["10.196.12.25", "10.196.12.26"]
daMpXsilps: ["10.196.52.73", "10.196.52.74"]
ipfelImage: DSR-8.2.0.0.0_82.5.1.vmdk
```

```

ipfeFlavor: dsr.ipfe
ipfeVmNames: ["DsrSite00IPFE00", "DsrSite00IPFE01"]
ipfeXmilps: ["10.196.12.85"]
ipfeXsilps: ["10.196.52.75"]
ipfeXsiPublicIp: 10.196.52.80
stplImage: DSR-8.2.0.0.0_82.5.1.vmdk
stpFlavor: dsr.vstp
stpVmNames: ["DsrSite00STP00", "DsrSite00STP01"]
stpXmilps: ["10.196.12.29", "10.196.12.30"]
stpXsilps: ["10.196.52.77", "10.196.52.78"]
xmiPublicNetwork: ext-net3
imiPrivateNetwork: imi
imiPrivateSubnet: imi-sub
imiPrivateSubnetCidr: 192.167.2.0/24
xsiPublicNetwork: ext-net2
ntpServer: 10.250.32.10
soamAZ: nova
daAZ: nova
ipfeAZ: nova
stpAZ: nova
soamSG: Site00_SOAM_SG
daSG: Site00_DAMP_SG
ipfeSGs: ["Site00_IPFE_SG0", "Site00_IPFE_SG1"]
stpSG: Site00_STP_SG
diameterTcpPorts: [3868]
diameterSctpPorts: []
stpSctpPorts: []

```

Appendix K. My Oracle Support (MOS)

MOS (<https://support.oracle.com>) is your initial point of contact for all product support and training needs. A representative at Customer Access Support (CAS) can assist you with MOS registration.

Call the CAS main number at **1-800-223-1711** (toll-free in the US), or call the Oracle Support hotline for your local country from the list at <http://www.oracle.com/us/support/contact/index.html>. When calling, make the selections in the sequence shown below on the Support telephone menu:

1. Select **2** for New Service Request.
2. Select **3** for Hardware, Networking and Solaris Operating System Support.
3. Select one of the following options:

For technical issues such as creating a new Service Request (SR), select 1.

For non-technical issues such as registration or assistance with MOS, select 2.

You are connected to a live agent who can assist you with MOS registration and opening a support ticket. MOS is available 24 hours a day, 7 days a week, 365 days a year.

Emergency Response

In the event of a critical service situation, emergency response is offered by the CAS main number at 1-800-223-1711 (toll-free in the US), or by calling the Oracle Support hotline for your local country from the list at <http://www.oracle.com/us/support/contact/index.html>. The emergency response provides immediate coverage, automatic escalation, and other features to ensure that the critical situation is resolved as rapidly as possible.

A critical situation is defined as a problem with the installed equipment that severely affects service, traffic, or maintenance capabilities, and requires immediate corrective action. Critical situations affect service and/or system operation resulting in one or several of these situations:

- A total system failure that results in loss of all transaction processing capability
- Significant reduction in system capacity or traffic handling capability
- Loss of the system's ability to perform automatic system reconfiguration
- Inability to restart a processor or the system
- Corruption of system databases that requires service affecting corrective actions
- Loss of access for maintenance or recovery operations
- Loss of the system ability to provide any required critical or major trouble notification

Any other problem severely affecting service, capacity/traffic, billing, and maintenance capabilities may be defined as critical by prior discussion and agreement with Oracle.

Locate Product Documentation on the Oracle Help Center

Oracle Communications customer documentation is available on the web at the Oracle Help Center (OHC) site, <http://docs.oracle.com>. You do not have to register to access these documents. Viewing these files requires Adobe Acrobat Reader, which can be downloaded at <http://www.adobe.com>.

1. Access the **Oracle Help Center** site at <http://docs.oracle.com>.
2. Click Industries.
3. Under the **Oracle Communications** subheading, click the **Oracle Communications documentation** link. The Communications Documentation page appears. Most products covered by these documentation sets display under the headings **Network Session Delivery and Control Infrastructure** or **Platforms**.
4. Click on your Product and then the Release Number. A list of the entire documentation set for the selected product and release displays. To download a file to your location, right-click the PDF link, select **Save target as** (or similar command based on your browser), and save to a local folder.