

Oracle® Communications

Diameter Signaling Router Equipment Identity Register (EIR)

User's Guide

Release 8.3

E93573

September 2018

E93573

Copyright © 2018, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

1	Introduction	
	Revision History	1-1
	Overview	1-1
	Scope and Audience	1-1
	Manual Organization	1-1
	Documentation Admonishments	1-2
	Locate Product Documentation on the Oracle Help Center Site	1-2
	Customer Training	1-3
	My Oracle Support	1-3
	Emergency Response.....	1-3
2	Feature Description	
	Equipment Identity Register Overview	2-1
	EIR Call Flows	2-2
	SS7/Sigtran EIR Call Flow	2-2
	Diameter EIR Call Flow	2-5
	EIR List Determination	2-6
	EIR Protocol	2-7
	Check_IMEI Message Handling.....	2-7
	EIR List Log File Serviceability	2-8
3	EIR Functionality	
	Global Response.....	3-1
	IMSI Screening	3-3
	Equipment Identity Database	3-4
	EIR Logging	3-5
	EIR Interface	3-6
4	EIR Configuration	
	EIR Configuration Procedure.....	4-1
5	EIR Alarms and Measurements.....	5-1

List of Figures

2-1	vSTP EIR Call Flow.....	2-3
2-2	Diameter EIR Call Flow.....	2-6
3-1	Sample Log File.....	3-6
4-1	EIR Subscriber Screen.....	4-2

List of Tables

1-1	Revision History.....	1-1
1-2	Admonishments.....	1-2
2-1	Example of Individual IMEIs.....	2-3
2-2	Logic for IMEIs in Multiple Lists.....	2-4
3-1	Attribute/Parameter Mapping.....	3-1
3-2	IMSI Range.....	3-3
3-3	UDR Attributes.....	3-5

Introduction

This chapter provides a brief description of the Equipment Identity Register (EIR) feature for Oracle Communications Diameter Signaling Router (DSR). The chapter also includes the scope, audience, and organization of the manual; how to find related publications; and how to contact Oracle for assistance.

Revision History

Table 1-1 *Revision History*

Date	Description
September 2018	New Document

Overview

This manual describes the EIR feature for DSR. EIR is used to reduce the number of Global System for Mobile (GSM) handset thefts by providing a mechanism to assist network operators in preventing stolen or disallowed handsets from accessing the network. This control is accomplished by comparing the International Mobile Equipment Identity (IMEI) that is provided during handset registration to a set of three lists provided by the network operator:

- Black - Mobile Stations (MS) on the Blacklist are denied access to the network
- White - MS's on the Whitelist are allowed access to the network
- Gray - MS's on the Graylist are allowed on the network, but may be tracked

Additionally, the operator can perform IMSI (International Mobile Subscriber Identity) based screening. The operator can allow the black listed IMEI based on the IMSI by provisioning the IMSI along with IMEI.

EIR is an optional feature on DSR and can be enabled and disabled administratively.

Scope and Audience

This manual is intended for anyone responsible for installing, maintaining, and using the EIR feature on Oracle Communications DSR. Users of this manual and the others in the DSR family of documents must have a working knowledge of telecommunications and network installations.

Manual Organization

This manual is organized into the following chapters:

- [Introduction](#) contains general information about the EIR documentation, the organization of this manual, and how to get technical assistance.
- [Feature Description](#) provides a functional description of the EIR feature, including network perspectives, assumptions and limitations, a database overview, and EIR user interface.
- [#unique_12](#) describes EIR functionality.
- [EIR Functionality](#) provides procedures for configuring the EIR feature for use in DSR.
- [EIR Alarms and Measurements](#) describes EIR-related events and alarms; commands to use for maintenance; and status and alarm reporting for DSR.

Documentation Admonishments

Admonishments are icons and text throughout this manual that alert the reader to assure personal safety, to minimize possible service interruptions, and to warn of the potential for equipment damage.

Table 1-2 Admonishments

Icon	Description
 DANGER	Danger: (This icon and text indicate the possibility of personal injury.)
 WARNING	Warning: (This icon and text indicate the possibility of equipment damage.)
 CAUTION	Caution: (This icon and text indicate the possibility of service interruption.)

Locate Product Documentation on the Oracle Help Center Site

Oracle Communications customer documentation is available on the web at the Oracle Help Center site, <http://docs.oracle.com>. You do not have to register to access these documents. Viewing these files requires Adobe Acrobat Reader, which can be downloaded at <http://www.adobe.com>.

1. Access the Oracle Help Center site at <http://docs.oracle.com>.
2. Click **Industries**.
3. Under the Oracle Communications subheading, click **Oracle Communications documentation** link.

The Communications Documentation page displays. Most products covered by these documentation sets display under the headings Network Session Delivery and Control Infrastructure and Platforms.

4. Click on your product and then the release number.

A list of the documentation set for the selected product and release displays.

5. To download a file to your location, right-click the **PDF** link, select **Save target as** (or similar command based on your browser), and save to a local folder.

Customer Training

Oracle University offers training for service providers and enterprises. Visit our web site to view, and register for, Oracle Communications training at <http://education.oracle.com/communication>.

To obtain contact phone numbers for countries or regions, visit the Oracle University Education web site at www.oracle.com/education/contacts.

My Oracle Support

My Oracle Support (<https://support.oracle.com>) is your initial point of contact for all product support and training needs. A representative at Customer Access Support can assist you with My Oracle Support registration.

Call the Customer Access Support main number at 1-800-223-1711 (toll-free in the US), or call the Oracle Support hotline for your local country from the list at <http://www.oracle.com/us/support/contact/index.html>. When calling, make the selections in the sequence shown below on the Support telephone menu:

1. Select **2** for New Service Request.
2. Select **3** for Hardware, Networking and Solaris Operating System Support.
3. Select one of the following options:
 - For Technical issues such as creating a new Service Request (SR), select **1**.
 - For Non-technical issues such as registration or assistance with My Oracle Support, select **2**.

You are connected to a live agent who can assist you with My Oracle Support registration and opening a support ticket.

My Oracle Support is available 24 hours a day, 7 days a week, 365 days a year.

Emergency Response

In the event of a critical service situation, emergency response is offered by the Customer Access Support (CAS) main number at 1-800-223-1711 (toll-free in the US), or by calling the Oracle Support hotline for your local country from the list at <http://www.oracle.com/us/support/contact/index.html>. The emergency response provides immediate coverage, automatic escalation, and other features to ensure that the critical situation is resolved as rapidly as possible.

A critical situation is defined as a problem with the installed equipment that severely affects service, traffic, or maintenance capabilities, and requires immediate corrective action. Critical situations affect service and/or system operation resulting in one or several of these situations:

- A total system failure that results in loss of all transaction processing capability

- Significant reduction in system capacity or traffic handling capability
- Loss of the system's ability to perform automatic system reconfiguration
- Inability to restart a processor or the system
- Corruption of system databases that requires service affecting corrective actions
- Loss of access for maintenance or recovery operations
- Loss of the system ability to provide any required critical or major trouble notification

Any other problem severely affecting service, capacity/traffic, billing, and maintenance capabilities may be defined as critical by prior discussion and agreement with Oracle.

Feature Description

This chapter provides a functional description of the EIR feature, including network perspectives, assumptions and limitations, and a database overview. EIR is implemented on both vSTP and diameter networks.

Equipment Identity Register Overview

A handset theft problem exists in GSM networks in many countries. A person obtains a legitimate subscription to a network, and then obtains a legitimate IMSI, MSISDN, and SIM card. The person initially buys an inexpensive handset and then steals a better handset from another subscriber. After the handset is stolen, the thief replaces the SIM card with a legitimate SIM card. Because the SIM card and subscriber information contained on the SIM card (IMSI, MSISDN) are legitimate, the phone will operate and the network operator cannot determine that the subscriber is using a stolen handset. In addition to individual handset theft, organized groups stealing entire shipments of mobile handsets from warehouses and sell these handsets on the Black Market.

The Equipment Identity Register (EIR) is a network entity used in GSM networks that stores lists of International Mobile Equipment Identity (IMEI) numbers, which correspond to physical handsets (not subscribers). The IMEI is used to identify the actual handset and is not dependent upon the International Mobile Subscriber Identity (IMSI), Mobile Station ISDN Number (MSISDN), or the Subscriber Identity Module (SIM). The IMSI, MSISDN, and SIM are all subscriber-specific and move with the subscriber when purchasing a new handset. The IMEI is handset-specific.

The EIR feature can be used to reduce the number of GSM handset thefts by providing a mechanism that allows network operators to prevent stolen or disallowed handsets from accessing the network. This control is accomplished by comparing the IMEI that is provided during handset registration to the following set of lists provided by the network operator:

- Black - Mobile Stations (MS) on the Blacklist are denied access to the network
- Gray - MSs on the Graylist are allowed on the network, but may be tracked
- White - MSs on the Whitelist are allowed access to the network

The Oracle Communications User Data Repository (UDR) stores the Whitelist, Graylist, and Blacklist of IMEI numbers. When a subscriber roams to a new MSC or VLR location, the handset attempts registration with the MSC or VLR. Before the MSC registers the subscriber with the VLR, it may send a query to DSR for EIR status of the handset. DSR returns a response indicating whether the IMEI is allowed, disallowed, or not valid. If the IMEI is allowed, the MSC completes registration; otherwise, registration is rejected.

EIR may also contain associations between individual IMEIs and IMSIs. This can provide a further level of screening by directly associating a particular IMEI with a particular IMSI. This association is used in the following way:

- If an IMEI is found on a Blacklist, an additional check of the IMSI could then be made.
- If the IMSI from the handset matches the IMSI provisioned with the IMEI, this would override the Blacklist condition and allow registration to continue. This could be used to protect against mistaken Blacklist entries in the database, or to prevent unauthorized "handset sharing."

The IMSI Range Logic Support feature includes an IMSI range check logic before an IMEI lookup in the database. This feature helps to allow a specific set of subscribers on basis of IMSI.

EIR Call Flows

A call can follow and SS7/Sigtran or Diameter call flow.

SS7/Sigtran EIR Call Flow

When a handset roams into a new MSC/VLR area, it attempts a registration procedure with the VLR. In a network without the EIR function, this procedure results in the VLR sending a location update message to the HLR providing the HLR with the current MSC location of the Mobile Station (MS)/handset. When the EIR function is deployed in a network, this registration procedure is interrupted to validate the IMEI of the MS/handset attempting to register before completing the registration procedure and updating the HLR.

In the network with EIR, the MSC/VLR sends a MAP_CHECK_IMEI message to DSR requesting EIR processing before sending a location update to HLR. This message contains, at a minimum, the IMEI of the MS attempting registration. It may also contain the IMSI of the subscriber whose SIM card is currently being used in the MS/handset. Upon receipt of this message, EIR searches the White, Gray, and Black Lists for a match on the IMEI. EIR then returns a response to the MSC. Depending upon the result of the search, the response contains either the equipment status of the MS/handset (whether the IMEI for the MS/handset is allowed or not based on its status in the White, Gray, or Black Lists), or a user error (invalid or unknown IMEI). The MSC then either continues the registration procedure (if the IMEI is allowed) or rejects it (if the IMEI is disallowed, invalid, or unknown).


If the IMSI is also included in the message, EIR attempts to match this IMSI to one provisioned with the IMEI before sending a response to the MSC. A match on IMSI overrides any Blacklist condition found based on the IMEI match alone and causes a response of MS allowed.

[#unique_21/unique_21_Connect_42_FIG_061D41F4AC2D4BC7A9C81DB64F799476](#) illustrates the steps for the vSTP EIR call flow process.

1. MSC sends a CheckIMEI request to vSTP-MP over SS7 links.
2. vSTP-MP queries the UDR NOAM for IMEI/IMSI DB. The query is sent to all UDR NOAMs in primary and secondary sites in a round-robin manner. vSTP-MP uses the ComAgent StackEvent request to query the UDR database.
3. UDR NOAM looks up the IMEI/IMSI database and sends a response to the vSTP-MP. The response to vSTP-MP is then sent as a ComAgent StackEvent response.

4. EIR on vSTP-MP receives the response from UDR; applies the business logic on the received ComAgent StackEvent response; creates a SS7 CheckIMEI response message; and encodes it to send to MSC.

Figure 2-1 vSTP EIR Call Flow



The UDR information contains the list of IMEIs and an indication to the list where they are located. UDR contains two types of IMEIs: Individual IMEIs ([#unique_21/unique_21_Connect_42_TABLE_4BE7F1C183E246C892DD5100A075339A](#)) and ranges of IMEIs ([#unique_21/unique_21_Connect_42_TABLE_2EB45F8E383F4D3384EB5AFAF2B0F4DE](#)). The Individual IMEIs are searched first. The IMEI entries in this list may also contain an association to an IMSI. If no individual IMEI match is found, IMEI ranges are searched.

EIR can support up to 100 million subscriber entries, including both individual IMEI and a range of IMEIs.

Table 2-1 Example of Individual IMEIs

IMEI	IMSI (optional)	White List	Gray List	Black List
12345678901234	495867256894125	No	No	Yes
234567890123456		No	Yes	No
49876523576823		No	Yes	Yes
68495868392048	495867565874236	Yes	Yes	No
29385572695759		Yes	Yes	Yes

As shown in [#unique_21/unique_21_Connect_42_TABLE_4BE7F1C183E246C892DD5100A075339A](#), it is possible for a given IMEI to be on more than one list (on the Whitelist, and also on the Gray and/or Black List). The logic illustrated by [#unique_21/unique_21_Connect_42_TABLE_2EB45F8E383F4D3384EB5AFAF2B0F4DE](#) is used to determine which answer to return in the CHECK_IMEI response, determined by which list or lists the IMEI is on. [#unique_21/unique_21_Connect_42_TABLE_2EB45F8E383F4D3384EB5AFAF2B0F4DE](#) also shows

three possible EIR response types. The EIR response type is a system-wide EIR option that is configured by the user. The combination of the setting of the EIR response type, the list or lists in which the IMEI is located, and the optional IMSI check determines the response returned to the querying MSC.

Table 2-2 Logic for IMEIs in Multiple Lists

Presence in List			EIR Response Type		
White	Gray	Black	Type 1	Type 2	Type 3
X			in White List	in White List	in White List
X	X		in Gray List	in Gray List	in Gray List
X	X	X	in Black List	in Black List	in Black List
X		X	in Black List	in Black list	in Black List
	X		in Gray List	in Gray List	Unknown
	X	X	in Black List	in Black List	Unknown
		X	in Black List	in Black List	Unknown
			in White List	Unknown	Unknown

Example Scenarios

Example One

1. A CHECK_IMEI is received with IMEI = 49876523576823, no IMSI in message.
2. An individual IMEI match is found ([#unique_21/unique_21_Connect_42_TABLE_4BE7F1C183E246C892DD5100A075339A](#), entry 3) indicating the IMEI is on the Gray and Black Lists.

The EIR Response Type is set to Type 3 and an IMSI is not present.

3. [#unique_21/unique_21_Connect_42_TABLE_2EB45F8E383F4D3384EB5AFAF2B0F4DE](#) indicates the required response is Unknown.
4. EIR formulates a CHECK_IMEI error response with Error = 7 Unknown Equipment

Example Two

Example 2 is the same as Example 1, except that the setting of the EIR Response Type is re-provisioned by the operator to Type 2.

1. A CHECK_IMEI is received with IMEI = 49876523576823, no IMSI in message.
2. An individual IMEI match is found ([#unique_21/unique_21_Connect_42_TABLE_4BE7F1C183E246C892DD5100A075339A](#), entry 3), indicating the IMEI is on the Gray and Black Lists.

The EIR Response Type is set to Type 2, and an IMSI is not present.

3. [#unique_21/unique_21_Connect_42_TABLE_2EB45F8E383F4D3384EB5AFAF2B0F4DE](#) indicates the required response is Blacklisted.
4. EIR formulates a CHECK_IMEI response with Equipment Status = 1 Blacklist.

Example Three

1. A CHECK_IMEI is received with IMEI = 12345678901234, and IMSI = 495867256894125.
2. An individual IMEI match is found ([#unique_21/unique_21_Connect_42_TABLE_4BE7F1C183E246C892DD5100A075339A](#), entry 1) indicating the IMEI is on the Blacklist.
3. The EIR Response Type is set to Type 1.
4. [#unique_21/unique_21_Connect_42_TABLE_2EB45F8E383F4D3384EB5AFAF2B0F4DE](#) indicates that the normally required response would be Blacklisted; however, because an IMSI is present in the message, and the IMEI is on the Blacklist, the IMSI is compared to the IMSI entry in the database for this IMEI.
5. In this case, the IMSI in the RTDB matches the IMSI in the query, thus the Blacklist condition is cancelled.
6. EIR formulates a CHECK_IMEI response with Equipment Status = 0 Whitelist.

Example Four

1. A CHECK_IMEI is received with IMEI = 12345678901234, and IMSI = 495867256894126.
2. An individual IMEI match is found ([#unique_21/unique_21_Connect_42_TABLE_4BE7F1C183E246C892DD5100A075339A](#) entry 1), indicating the IMEI is on the Blacklist.
3. The EIR Response Type is set to Type 1.
4. [#unique_21/unique_21_Connect_42_TABLE_2EB45F8E383F4D3384EB5AFAF2B0F4DE](#) indicates that the normally required response would be Blacklisted, however; because an IMSI is present in the message, and the IMEI is on the Blacklist, the IMSI is compared to the IMSI entry in the RTDB for this IMEI.
5. In this case, the IMSI in the RTDB does not match the IMSI in the query, the Blacklist condition is maintained.
6. EIR formulates a CHECK_IMEI response with Equipment Status = 1 Blacklist.


Diameter EIR Call Flow

Figure 2-2 illustrates the steps of the diameter EIR call flow process.

1. MME/SGSN sends the ECR message to DAMP over S13/S13' interface links.
2. DAMP queries the UDR active and standby NOAMs in a round-robin manner for IMEI data. DAMP uses the ComAgent StackEvent request for querying the UDR DB.
3. UDR NOAM looks up the IMEI DB and sends a response to the DAMP. The response to DAMP is sent as a ComAgent StackEvent response.

4. EIR on DAMP receives the response from UDR; applies the business logic on received ComAgent StackEvent response; creates an ECA message; and encodes it to send to MME.

Figure 2-2 Diameter EIR Call Flow



EIR List Determination

The EIR list determination algorithm is the same for both SS7/Sigtran and Diameter.

Whitelist Processing

Indicates the IMEI is valid and registration should be allowed for this MS/UE (User equipment).

If the EIR Global Response configuration option is set (with the `eirgrsp` parameter) to a value other than `off`, the IMEI is treated as being on the list indicated by the EIR Global Response option, regardless of the actual status of the IMEI. No list logic processing is performed on the IMEI.

If the EIR Global Response option is set to `off`, the individual IMEIs are searched first.

If no match is found, the range IMEIs are searched next. If the IMEI is found only on the Whitelist after either search, the list logic processing is complete, and the Whitelist status of the IMEI is sent to the MSC.

Blacklist Processing

Indicates the IMEI is invalid and registration should not be allowed for this MS/UE (User equipment).

If the IMEI is found on the Blacklist after either search, list logic processing continues based on the EIR response type, set by the `eirrspstype` parameter of the `chg-gsmopts` command. If the EIR response type is type 3, and the IMEI is not also found on the Whitelist, the status of the IMEI is unknown.

If the IMEI is also found on the Whitelist, or if the EIR response type is either type 1 or 2, the value of the IMSI Check option, set with the `eirimschk` parameter of the `chg-gsmopts` command, is checked. If the IMSI check option is `on`, and the IMSI is present in the message, the RTDB is searched for the IMSI. If there is a match for the IMSI, the status of the IMEI is determined to be "White with Override." If there is no

match for the IMSI, the status of the IMEI is determined to be "Black with IMSI Match Failed." If the value of the IMSI Check option is `off`, the status of the IMEI is determined to be "on the Blacklist".

Graylist Processing

Indicates the IMEI is questionable. Registration should be allowed, but the MS/UE should be tracked.

If the IMEI is found on the Graylist after either search, list logic processing continues based on the EIR response type. If the EIR response type is type 3, and the IMEI is not also found on the White List, the status of the IMEI is unknown.

If the IMEI is also found on the Whitelist, or if the EIR response type is either type 1 or 2, the status of the IMEI is determined to be on the Graylist.

EIR Protocol

Messages for Local Subsystems

The message arrives at the EIR subsystem as Rt-on-SSN or Rt-on-GT. If the message arrives as Rt-on-SSN, it must contain either the DSR true point code or the EIR capability point code in the DPC field of the message, and the DSR EIR subsystem number in the Called Party Subsystem field of the message. If the EIR query has DSR capability point code for the DPC, then DSR processes the message, but it is not able to divert this message in the event of subsystem failure.

If a message arrives at the EIR subsystem as Rt-on-GT, it should also contain a service selector that translates to the EIR subsystem. These messages also contain one of the DSR capability point codes in the DPC field. DSR also processes the message if it has the DSR true point code for the DPC, but it is not able to divert these messages in the event of subsystem failure.

SCCP Management to Support EIR

vSTP does not support a mated subsystem, hence, in case of SSN failure or a routing failure, messages are not routed to the mated node.

vSTP-MP can receive messages from a network with a CdPA routing indicator of route-on-gt and DPC is TPC in these situations:

- If a message has the subsystem (SSN) present and the SSN value is from EIR, then the message is sent for EIR processing.
- If message does not have the SSN or the SSN is not from EIR, then the SCCP layer performs normal GTT routing.

Note: The SSN status management and network management messages, for example, SSP and UPU, do not support EIR; however, if the remote node sends an SST message, then SCCP handles the message.

Check_IMEI Message Handling

When the CHECK_IMEI message is received by the protocol, the IMSI (if active) and SVN are parsed from the MSU. Because different vendors place the IMSI information in different locations within the message, the decoder searches for the IMSI in multiple locations.

Once the required data is parsed, a lookup is performed in the RTDB to determine the response type for the IMEI/IMSI combination.

The appropriate response message is sent to the originating MSC.

Encoding Errors

When a response is generated, it is sent based on the CgPA information in the incoming message. However, some conditions may prevent DSR from generating the response. Most of the errors involve GTT on the CgPA; if the incoming data is Rt-on-SSN, the number of potential errors is much smaller.

Whenever an encoding error is detected, the response message is discarded.

Data Collection

See [EIR Alarms and Measurements](#) for a description of the measurements collected for the EIR feature.

EIR List Log File Serviceability

When the file system reaches 80% of its total capacity, a minor alarm is raised. A major alarm is raised at 90%. All of the files in this partition are managed from **Debug > Manage Logs & Backups**.

EIR log entries are delivered to and stored on the MPS using a best effort approach.

Logs are retained in these conditions:

- One million records can be logged in 24 hours
- An hourly synchronization takes place from the MP to the active SOAM
- The active SOAM synchronizes the log with the standby SOAM for backup
- The log is retained for 5 days on the SOAM

EIR Functionality

This chapter identifies requirements for EIR.

Global Response

The Equipment Identity Register (EIR) provides an EirOptions table to configure the global response type (eirGlobalResp). If this option is set to on, then a checkIMEI response is sent to the MSC. By default, the eirGlobalResp option within EIR is set to off. If you leave it off, this order determines the equipment status.

1. IMSI range screening.
2. IMEI and IMEI range screening.
3. SV screening where the last two digits of IMEI are used for the software version.
4. IMSI exact match.

The attribute or parameter follows these rules for its name:

- Common parameters for SS7 and Diameter have an "eir" prefix.
- Diameter-specific parameters have a "diameter" prefix.
- Specific parameters have an "ss7" prefix.

The EIR attributes/parameter included in EIR are listed in [Table 3-1](#).

Table 3-1 Attribute/Parameter Mapping

Attribute/Parameter Name	Description	Default Value	Valid Values or Range
ss7DefMapVer	Map version to decode message	V3	V1, V2, V3
eirDefMcc	E212 default mobile country code.	None	XXX (X = 0-9, A-F,a-f)
eirDefMnc	E212 default mobile network code.	None	XX or XXX (X = 0-9, A-F,a-f)

Table 3-1 (Cont.) Attribute/Parameter Mapping

Attribute/Parameter Name	Description	Default Value	Valid Values or Range
eirDefImsiResp	EIR default IMSI response. Note: When IMSI lookup is successful, this parameter defines the IMSI override lookup response.	Whitelist	Whitelist, Blacklist, Graylist, Unknown
eirGlobalResp	EIR Global Response status.	Off	Off, Whitelist, Blacklist, Graylist, Unknown
eirDefResp	EIR default response status (used when UDR connectivity is down) Note: If this parameter is set to on, then the IMSI response is used; otherwise, equipment status is set based on the IMEI lookup.	Whitelist	Whitelist, Blacklist, Graylist, Unknown
eirImsiChk	EIR IMSI Check status. This parameter is not valid for IMEI ranges.	false	true, false
eirRespType	EIR Response Type.	Type1	Type1, Type2, Type3
eirImsiScrn	EIR IMSI range screening. Search IMSI in IMSI range table.	true	true, false
diameterCongErr	Value in the 'result code' AVP of the response send, at the time of Congestion.	3004	3004, 5006

Table 3-1 (Cont.) Attribute/Parameter Mapping

Attribute/Parameter Name	Description	Default Value	Valid Values or Range
diameterVendorId	S13 local Vendor ID. All the outgoing messages that require Vendor ID in VENDOR_SPECIFIC_APPLICATION_ID will use this configured value. Currently only 10415 is supported.	10415	10415
diameterProductName	Product Name. It contains the vendor-assigned name for the product. All the outgoing messages that require Product name AVP will use this configured value.	DSR	DSR

IMSI Screening

The IMSI range table contains the options for screening the IMSI. The IMSI range table is used to search for matching IMSI before checking the IMEI in the UDR database.

Table 3-2 IMSI Range

Field	Description	Range	Comments
startAddr	Start of IMSI digits	15 digits	The IMSI prefix begins with 0 and must be 15 digits to be accepted. This field is the key field.
endAddr	End of IMSI digits	15 digits	The IMSI prefix begins with 0 and must be 15 digits to be accepted.
equipmentStatus	Equipment status	White list, Black list, Gray list, Unknown	

The IMSI range supports POST, DELETE, and PUT operations to create, delete, and update the IMSI range. To manage IMSI screening, follow these rules:

- If IMSI is present in the configured IMSI ranges, send the corresponding configured equipment status in Check_IMEI response or ECA message.
- If IMSI is not present in the configured ranges, proceed further and send the IMEI lookup query to UDR and get the configured IMEI data.
- A maximum of 1000 entries is allowed in the EirImsiRange table.

- Assume IMSI is in international format.
- All 15 digits are used for lookup.
- If the length of the IMSI in the message is less than 15, then 0s are added to the beginning of the IMSI number to make 15 digits.

Create IMSI Range

To create the IMSI range, follow this procedure.

1. Create a file with this content.

```
$ cat imsiaddr.txt
{
  "startAddr": "070200000000000",
  "equipmentStatus": "Blacklist",
  "endAddr": "070200000000000"
}
```

Note: If IMSI is less than 15 digits, add zero(s) until it becomes 15 digits.

2. Use that file to provision the IMSI range using any REST-based client.

Equipment Identity Database

The database schema used in UDR includes:

- Bulk upload of data for provisioning is supported.
- IMEI is validated to 15 digits when provisioning. Once IMEI can consist of up to 10 IMSI.
- The database supports a 1000 IMSI range to support white listing special subscribers.
- It is also possible to provision the Software Version (SV) against the IMEI.
- The SV is two digits, if it is not provisioned. The default value of 99 is stored against the IMEI.

Note: BCD and HEX values in the IMEI and SV are not supported.

- UDR is able to respond with an error `INVALID_KEY_VALUE` when IMEI is provisioned with any value other than numeric digits.
- UDR is able to respond with an error `INVALID_KEY_VALUE` over the provisioning interface when it detects that IMEI being provisioned is not correct in length.
- UDR allows provisioning of the type of Black listing against the IMEI (within the main subscriber profile) and SV as shown in [Table 3-3](#).

Table 3-3 UDR Attributes

Attribute	White List	Gray List	Black List	SV
Allowed Values	TRUE/FALSE	TRUE/FALSE	TRUE/FALSE	00 to 99 Decimal only
Default Values	TRUE	FALSE	FALSE	99

EIR Logging

Logs are written in each STP MP's and DAMP's file management area located at /var/TKLC/db/filemgmt/Eir_logs/. The file name is comprised of "File creation date and time"- "File close date and time"- "MP host name". A sample EIR log file name would be EIR_28052018.070425-28052018.120427_so1mp1__logs.

The log file consists of CSV entries for each MAP_CHECK_IMEI/ECR received that resulted in a match with an IMEI entry that is considered either gray or black-listed or unknown. Each new line contains the information about the caller and handset; and a Timestamp, Reason, and Status. If IMSI is not present or EIR is not able to decode the IMSI in the message, then the IMSI is left blank in the EIR log. The last 2 million entries received from DSR are included and this log feature is the same fro both SS7/ Sigtran and Diameter. Each entry follows these rules:

- EIR logs an entry when:
 - Equipment status is found to be blacklisted or graylisted
 - Equipment status is blacklisted, but allowed due to IMSI override
 - In error scenario, like the UDR connection is not available and the configured default response in error (EIR options table) is black or gray.
- A configurable flag is provided in EirOptions table in case logging is needed for the whitelisted devices. Default value of the flag will be `off`.

Diameter Log File

The Diameter log file contains this information:

- Date and time of the message
- The IMEI digits from the ECR message
- MEI SV, if available
- The IMSI digits from the ECR message (if present)
- Origin-host of ECR message
- Device Status - Whether the IMEI was Whitelisted, Graylisted, or Blacklisted
- Reason - Blacklisted, but allowed due to IMSI override or IMEI Range Match

The MP copies the log file to the SOAM every hour to /var/TKLC/db/filemgmt/export/Eir_Log/Deir.

SS7/Sigtran Log File

The SS7/Sigtran log file contains this information:

- SS7/Sigtran
- The IMEI digits from the CHECK_IMEI message
- IMEI SV, if available
- The IMSI digits from the CHECK_IMEI message (if present)
- SCCP CgPA Digits from the source of query
- Device Status - Whether the IMEI was Whitelisted, Graylisted, or Blacklisted
- Reason - Blacklisted, but allowed due to IMSI override or IMEI Range Match

The MP copies the log file to the SOAM every hour to /var/TKLC/db/filegmt/export/Eir_Log/Vstp.

For example, if an MP server receives entry ID 1234 on July 15, 2003, at exactly 4:36 PM from a Service Module card provisioned at address 192.168.120.1 indicating that Blacklisted subscriber 9195551212 using handset 12345678901234 was detected, this entry is created:

```
20030715163600,192.168.61.1,1234,9195551212,12345678901234,0
```

Figure 3-1 Sample Log File

```
EIR_28052018.070425-28052018.120427_ravieir-so1mp1_logs.csv - Notepad
File Edit Format View Help
Timestamp,Imei,ImeiSV,Imsi,CgpaDigits,Reason,Status
28:05:2018 07:04:25,3333333333323,,9116660090003,,IMEI Range Match,whitelist
28:05:2018 07:04:26,3333333333323,,9116660090003,,IMEI Range Match,whitelist
28:05:2018 07:11:28,3333333333323,,9116660090001,,IMEI Range Match,Blacklist
28:05:2018 07:11:29,3333333333323,,9116660090001,,IMEI Range Match,Blacklist
28:05:2018 07:16:25,3333333333323,,9116660090001,,IMSI Override,whitelist
28:05:2018 07:16:26,3333333333323,,9116660090001,,IMSI Override,whitelist
```

EIR Interface

EIR supports both SS7 and Diameter interfaces through the MAP_CHECK_IMEI request and response messages on the SS7 interface; and the Equipment Check Request and Answer messages on the S13 and S13' Diameter interfaces. For more details on the supported interfaces, refer to 3GPP Specification document.

EIR Configuration

This chapter provides procedures to configure the connection required for EIR to access the database on UDR NOAM using Application administration.

EIR Configuration Procedure

Use this procedure to set up EIR.


1. From an active UDR NOAM, add DAMP to UDR.
 - a. Log into UDR as the admin and navigate to **Communication Agent > Configuration > Remote Servers** and click **Insert**.
 - b. Specify the DAMP server XSI IP address as a client.
 - c. Select the UDR server group from Available Local Server Groups that needs to communicate with the DAMP.
 - d. Navigate to **Communication Agent > Maintenance > Connection Status** and verify the connections are set to **InService**.
 - e. Verify the **Routed Services Status** is set to Normal by navigating to **Communication Agent > Maintenance > Routed Services Status** and then:
 - For Diameter, verify the **DRADbSvc** status is Normal.
 - For SS7, verify the **STPDbSvc** status is Normal.
2. From an active UDR NOAM, add vSTP MP to UDR.
 - a. Log into UDR as the admin and navigate to **Communication Agent > Configuration > Remote Servers** and click **Insert**.
 - b. Specify the vSTP MP server XSI IP address as a client.
 - c. Select the UDR server group from Available Local Server Groups that needs to communicate with the vSTP MP.
 - d. Navigate to **Communication Agent > Maintenance > Connection Status** and verify the connections are set to **InService**.
 - e. Verify the **Routed Services Status** is set to Normal by navigating to **Communication Agent > Maintenance > Routed Services Status** and then:
 - For Diameter, verify the **DRADbSvc** status is Normal.
 - For SS7, verify the **STPDbSvc** status is Normal.
3. From an active DSR NOAM, add UDR to DSR NOAM.

- a. Navigate to **Communication Agent > Configuration > Remote Servers** and click **Insert**.
 - b. Specify the UDR NO server XSI IP address as a server.
 - c. Select the DAMP server group in **Local SG** that needs to communication with UDR.
 - d. Add the standby server to the DR NOAM.
 - e. Set the Connection Groups by navigating to **Communication Agent > Configuration > Remote Servers** and then:
 - For Diameter, click **Edit**.
 - For SS7, select the **STPSvcGroup** and click **Edit**.
 - f. Add all available UDR NO servers.
4. From an active UDR SOAM, ensure ComAgent connection are InService.
 - a. Navigate to **Communication Agent > Maintenance > Connection Status**.
 - b. Make sure the ComAgent connection is set to **InService**.
 5. From an active NOAM, add subscribers in UDR.
 - a. Add the required fields for the EIR subscriber profile according to .

List	Field name	Type	Value Range	Default Value
White List	WL	INT	0-1	1
Gray List	GL	INT	0-1	0
Black List	BL	INT	0-1	0
Software Version	SV	INT	0-1	99

The EIR profile fields should look similar to [Figure 4-1](#).

Figure 4-1 EIR Subscriber Screen



- b. Navigate to **UDR > Configuration > Provisioning Options** and mark the **Allow SOAP Connections** and **Allow REST Connections** checkboxes.

- c. Click **Apply**.
 - d. Navigate to **UDR > Configuration > Provisioning Connections** and type the provisioning client's IP address for the White list.
6. From an active SOAM, add entries to the EirlmsiRange table.
Refer to [IMSI Screening](#).
7. From an active SOAM, set the EIR admin state to Enabled.
Navigate to **Diameter > Maintenance > Application**, click **Enable**.
For SS7, execute the `applicationAdmin Eir Enabled` command.
`applicationAdmin Eir Enabled`
8. For Diameter only, from an active SOAM, add S13 application ID in DSR.
Navigate to **Diameter > Configuration > Application IDs**, click **Insert** and add the S13 interface application ID.
9. For Diameter only, from an active SOAM, add an application route table in DSR for EIR.
Navigate to **Diameter > Configuration > Application Route Tables** and insert the new ART or add a rule in an existing ART.

EIR Alarms and Measurements

Alarms and Events

New alarms and events have been added to the Alarms and KPIs reference guide. See the EIR sections.

Measurements

New measurements have been added to the Measurements reference guide. See the EIR section.
