

Oracle® Communications

Upgrade Procedure

Diameter Signal Routing User Data Repository Software Upgrade Procedure for Release 8.4

F12364-01

April 2019

ORACLE®

CAUTION:

Before recovering any system, access My Oracle Support
(<https://support.oracle.com>) and review any Alerts that relate to this procedure.

My Oracle Support (<https://support.oracle.com>) is your initial point of contact for all product support and training needs. A representative at Customer Access Support (CAS) can assist you with My Oracle Support registration.

Call the CAS main number at 1-800-223-1711 (toll-free in the US), or call the Oracle Support hotline for your local country from the list at <http://www.oracle.com/us/support/contact/index.html>.

See more information on My Oracle Support in the Appendix J.

Copyright © 2014, 2017, 2018, 2019 Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

TABLE OF CONTENTS

CHAPTER 1. INTRODUCTION.....	8
1.1 Purpose and Scope	8
1.1.1 What is Not Covered by this Document.....	8
1.2 References.....	8
1.3 Acronyms	9
1.4 Terminology.....	10
1.5 How to use this Document.....	11
1.5.1 Performing Procedures	12
1.6 Recommendations.....	13
1.6.1 Frequency of Health Checks.....	13
1.6.2 Logging of Upgrade Activities	13
CHAPTER 2. GENERAL DESCRIPTION	14
2.1 Supported Upgrade Paths	14
2.2 Firmware Updates	14
2.3 PM&C (Management Server) Upgrades	15
2.4 TVOE Upgrade	15
2.5 Traffic Management during Upgrade	16
2.6 Provisioning during Upgrade	16
2.7 Configurations	16
2.7.1 Low Capacity Configurations (Fully Virtualized with TVOE).....	16
2.7.2 Cloud Configurations.....	17
2.8 Sequence of Upgrade.....	17
CHAPTER 3. UPGRADE PLANNING AND PRE-UPGRADE PROCEDURES	18
3.1 Required Materials	18
3.1.1 Application ISO Image File/Media.....	18
3.1.2 Logins, Passwords and Site Information.....	18
3.2 Maintenance Window for PM&C and TVOE Upgrades	20
3.3 Pre-Upgrade Procedures.....	20
3.3.1 Hardware Upgrade Preparation	20
3.3.2 Review Release Notes	20
3.3.3 Required Materials Check.....	21
3.3.4 Perform Health Check (Upgrade Preparation).....	21
3.3.5 ISO Administration	21
3.3.6 Upgrade TVOE Hosts at a Site (before application upgrade MW)	27

Oracle Communications User Data Repository Software Upgrade Procedure	
3.4 Order of Application Upgrade	28
3.5 Upgrade Execution Overview for Normal Capacity C-Class Configuration.....	29
3.5.1 Primary NOAMP/DR NOAMP Execution Overview	29
3.6 Upgrade Execution Overview for Low Capacity Configurations	29
3.6.1 Primary NOAMP/DR NOAMP Execution Overview	29
3.7 Upgrade Acceptance Overview	30
CHAPTER 4. PRIMARY NOAMP/DR NOAMP UPGRADE EXECUTION	31
4.1 Perform Health Check (Pre Upgrade).....	31
4.2 Primary NOAMP/DR NOAMP Upgrade	32
4.2.1 Remove Additional GUI Sessions.....	32
4.2.2 Full Database Backup (All Servers)	34
4.2.3 Major Upgrade DR NOAMP NE	37
4.2.4 Incremental Upgrade DR NOAMP NE	39
4.2.5 Major Upgrade Primary NOAMP NE.....	41
4.2.6 Incremental Upgrade Primary NOAMP NE.....	44
4.3 Perform Health Check (Post Primary NOAMP/DR NOAMP Upgrade)	45
CHAPTER 5. SINGLE SERVER UPGRADE.....	46
5.1 Upgrading a Single Server.....	46
CHAPTER 6. UPGRADE ACCEPTANCE.....	49
6.1 Accept Upgrade.....	49
CHAPTER 7. TVOE PERFORMANCE TUNING	52
CHAPTER 8. RECOVERY PROCEDURES	54
8.1 Order of Backout	54
8.2 Backout Setup	54
8.3 Backout of DR NOAMP NE	55
8.4 Backout of Primary NOAMP NE	57

APPENDIX A. ACCESSING THE OAM SERVER GUI (NOAMP).....	60
APPENDIX B. HEALTH CHECK PROCEDURES	62
APPENDIX C. UPGRADE OF A SERVER	69
APPENDIX D. BACKOUT OF A SERVER	77
APPENDIX E. VERIFYING SERVERS ARE SYNCRONIZED	84
APPENDIX F. DETERMINE IF TVOE UPGRADE IS REQUIRED	85
APPENDIX G. UPGRADE TVOE PLATFORM	86
APPENDIX H. CHANGE RESOURCES ALLOCATED TO VM GUESTS.....	88
APPENDIX I. CONFIGURING SERVICES FOR DUAL PATH HA.....	91
APPENDIX J. MY ORACLE SUPPORT	94
APPENDIX K. LOCATE PRODUCT DOCUMENTATION ON THE ORACLE HELP CENTER SITE	95

List of Figures

Figure 1: Supported Upgrade Paths.....	14
Figure 4: Low Capacity Single-Site Configuration	16

List of Tables

Table 1: Acronyms.....	9
Table 2: Terminology	10
Table 3: Sample Procedure	12
Table 4: Sequence of upgrade	17
Table 5: Pre-Upgrade Overview	20
Table 6: DR NOAMP Upgrade Procedures for Normal Capacity C-Class Configurations	29
Table 7: Primary NOAMP Upgrade Procedures for Normal Capacity C-Class Configurations.....	29
Table 8: DR NOAMP Upgrade Procedures for Low Capacity Configurations.....	29
Table 9: Primary NOAMP Upgrade Procedures for Low Capacity Configurations.....	30
Table 10: Upgrade Acceptance overview	30

List of Procedures

Procedure 2: Required Materials Check	21
Procedure 3: Perform Health Check (Upgrade Preparation).....	21
Procedure 4: ISO Administration for Upgrades	21
Procedure 5: Upgrade TVOE Hosts at a Site (before application upgrade MW)	28
Procedure 6: Health Check (Pre Upgrade).....	31
Procedure 7: Remove Additional GUI Sessions	32
Procedure 8: Full Database Backup	34
Procedure 9: Major Upgrade DR NOAMP NE	37
Procedure 10: Incremental Upgrade DR NOAMP NE.....	39
Procedure 11: Major Upgrade Primary NOAMP NE	41
Procedure 12: Incremental Upgrade Primary NOAMP NE	44
Procedure 13: Health Check (Post Primary NOAMP/DR NOAMP Upgrade).....	45
Procedure 14: Upgrade Single Server	46
Procedure 15: Accept Upgrade.....	49
Procedure 16: TVOE Performance Tuning	52
Procedure 17: Backout of DR NOAMP NE.....	55
Procedure 18: Backout of Primary NOAMP NE.....	57
Procedure 19: Accessing the OAM Server GUI (NOAMP)	60
Procedure 20: Health Check Procedures	62
Procedure 21: Initiate Upgrade Server	69
Procedure 22: Backout of a Server	77
Procedure 23: Verifying servers are Syncronized	84
Procedure 24: Determine if TVOE Upgrade is Required.....	85
Procedure 25: Upgeade TVOE Platform.....	86
Procedure 26: Change VCPU Cores and RAM Allocated To NOAMP Guests	88
Procedure 27: Configuring Services for Dual Path HA	91

Chapter 1. Introduction

1.1 Purpose and Scope

This document describes the methods utilized and the procedures performed for a major upgrade from Oracle Communications User Data Repository 12.1/12.2 to Oracle Communications User Data Repository 12.5.1 release. The audience for this document includes Oracle customers as well as the following internal groups: Software Development, Quality Assurance, Product Verification, Information Development, and Consulting Services including NPX. This document provides step-by-step instructions to perform any Release 12.5.1 or later software upgrade. The Oracle Communications User Data Repository software includes all Oracle Tekelec Platform Distribution (TPD) software. Any TPD upgrade necessary is included automatically as part of the software upgrade. Performing this procedure assumes that the Oracle Communications User Data Repository software load (ISO file, CD-ROM, or other form of media) has been delivered or downloaded to the premises. This includes delivery of the software load to the local workstation being used to perform this upgrade.

1.1.1 What is Not Covered by this Document

- Distribution of Oracle Communications User Data Repository 12.5.1 software loads. Visit the Oracle Software Delivery Cloud here: <https://edelivery.oracle.com/osdc/faces/Home.jspx>
- Distribution of Oracle Communications User Data Repository software that goes with Oracle Communications DSR product is not covered.
- Initial installation of Oracle Communications User Data Repository 12.5.1 software. Refer [1].
- PM&C upgrade. Refer to [3].
- Firmware upgrade. Use the upgrade procedures and release notes documents contained in the Firmware Upgrade Packs to assess whether a firmware upgrade is necessary. Refer to [3].

1.2 References

Oracle documentation is available on the web at the Oracle Help Center (OHC) site, <http://docs.oracle.com>. You do not have to register to access these documents. Viewing these files requires Adobe Acrobat Reader, which can be downloaded at www.adobe.com.

1. Log into the Oracle Technology Network site at <http://docs.oracle.com>.
2. Select **Find a product**
3. Enter **User Data Repository**

The CGBU Documentation page opens.

4. Select **User Data Repository** followed by version
5. Select **platform/Tekelec** for Platform and TVOE documents

- [1] Oracle Communications User Data Repository 12.5.1 Installation and Configuration Guide, E83421-01, latest revision
- [2] TVOE 3.4 Software Upgrade Document, E80324, latest revision
- [3] Oracle Communications PM&C 6.4 Incremental Upgrade Procedure, E82636-01, latest revision.
- [4] Oracle Communications User Data Repository Cloud Installation and Configuration Guide, E83397-01, latest revision

1.3 Acronyms

Table 1: Acronyms

Acronym	Meaning
CGBU	Communications Global Business unit
CD-ROM	Compact Disc Read-only Media
CSV	Comma-separated Values
DB	Database
DR	Disaster Recovery
FOA	First Office Application
GA	General Availability
GPS	Global Product Solutions
GUI	Graphical User Interface
HA	High Availability
IMI	Internal Management Interface
IP	Internet Protocol
IPM	Initial Product Manufacture
ISO	ISO 9660 file system (when used in the context of this document)
LA	Limited Availability
MOP	Method of Procedure
MW	Maintenance Window
NE	Network Element
NO	Network OAMP
NOAMP	Network OAMP
OA	HP Onboard Administrator
OAM	Operations, Administration and Maintenance
OAMP	Operations, Administration, Maintenance and Provisioning
PM&C	Platform Management and Configuration
RMS	Rack Mount Server
SPR	Subscriber Profile Repository
TPD	Tekelec Platform Distribution
TVOE	Tekelec Virtualized Operating Environment
UDR	User Data Repository
UI	User Interface

Acronym	Meaning
VIP	Virtual IP
VM	Virtual Machine
VPN	Virtual Private Network
XMI	External Management Interface
XSI	External Signaling Interface

1.4 Terminology

This section describes terminology as it is used in this document.

Table 2: Terminology

Term	Meaning
Upgrade	The process of converting an application from its current release on a system to a new release.
Major Upgrade	An upgrade from a current release to a new major release. An example of a major upgrade is: release 12.2 to 12.5, or release 12.4 to release 12.5
Incremental Upgrade	An upgrade from a current build to a new build in the same major release. An example of an incremental upgrade is: release 12.5.x to 12.5.y.
Release	Release is any particular distribution of software that is different from any other distribution.
Single Server Upgrade	The process of converting an Oracle Communications User Data Repository server from its current release on a single server to a new release.
Blade (or Managed Blade) Upgrade	Single server upgrade performed on a blade. This upgrade requires the use of the PM&C GUI.
Standalone Server Upgrade	Single server upgrade performed on a standalone server. This upgrade requires the use of the platcfg UI.
Software Only Upgrade	An upgrade that does not require a database schema change, only the software is changed.
DB Conversion Upgrade	An upgrade that requires a database schema change that is performed during an upgrade that is necessitated by new feature content or bug fixes.
Backout	The process of converting a single Oracle Communications User Data Repository server to a prior version. This could be performed due to failure in single server upgrade or the upgrade cannot be accepted. Backout is a user initiated process.
Downgrade/Backout	The process of converting an Oracle Communications User Data Repository server from its current release to a prior release. This could be performed due to a misbehaving system. After the upgrade is accepted, servers cannot be backed out to previous release.
Rollback	Automatic recovery procedure that puts a server into its pre-upgrade status. This procedure occurs automatically during upgrade if there is a failure.
Source Release	Software release to upgrade from.
Target Release	Software release to upgrade to.
Oracle RMS	Oracle Server X5-2 or Netra X5-2

Term	Meaning
Primary NOAM Network Element	The network element that contains the active and standby NOAM servers in an Oracle Communications User Data Repository. If the NOAMs are deployed on a rack-mount server (and often not co-located with any other site), that RMS is considered the primary NOAM network element. If the NOAMs are virtualized on a C-class blade that is part of one of the sites, then the primary NOAM network element and the signaling network element hosting the NOAMs are one and the same.
DR NOAM Network Element	Disaster Recovery NOAMs that are ready to take over as the primary Site if a disaster should occur.
Site	Physical location where one or more network elements reside.
Health Check	Procedure used to determine the health and status of the network. This includes statuses displayed from the GUI. This can be observed Pre-Server Upgrade, In-Progress Server Upgrade, and Post-Server Upgrade.
Upgrade Ready	<p>State that allows for graceful upgrade of a server without degradation of service. It is a state that a server is required to be in before it can be upgraded. The state is defined by the following attributes:</p> <p>Server is Forced Standby</p> <p>Server is Application Disabled (signaling servers do not process any traffic)</p>
UI	User interface. platcfg UI refers specifically to the Platform Configuration Utility User Interface, which is a text-based user interface.
Management Server	Server deployed with HP c-class or RMS used to host PM&C application, to configure Cisco 4948 switches and to serve other configuration purposes.
PM&C Application	PM&C is an application that provides platform-level management functionality for HPC/RMS system, such as the capability to manage and provision platform components of the system so it can host applications.
Software Centric	The business practice of delivering an Oracle software product, while relying on the customer to procure the requisite hardware components. Oracle provides the hardware specifications, but does not provide the hardware, and is not responsible for hardware installation, configuration, or maintenance.
Enablement	The business practice of providing support services (hardware, software, documentation, and so on) that enable a 3rd party entity to install, configuration, and maintain Oracle products for Oracle customers.
NO	Network OAM for Oracle Communications User Data Repository.

1.5 How to use this Document

When using this document, there are a few key points which help to understand the intent of the author. These points are as follows;

1. Before beginning a procedure, completely read the instructional text (immediately after the section heading for each procedure) and all associated procedural warnings or notes.
2. Before performing a step in a procedure, completely read the left and right columns including any step specific warnings or notes.
3. If a procedural step fails to run successfully or fails to receive the required output, stop and contact the CAS main number at 1-800-223-1711 (toll-free in the US), or call the Oracle Support hotline for

your local country from the list at <http://www.oracle.com/us/support/contact/index.html> for assistance before attempting to continue.

1.5.1 Performing Procedures

Familiarize yourself with the structure and conventions used in these procedures before performing them. Table 1 and the details below provide an example of how procedural steps might be displayed in this document.

Column 1: Step

- Column 1 in Table 1 contains the step number and also a checkbox if the step requires an action.
- Sub-steps in a Step X are referred to as Step X.Y. (See example: Step 1 has sub-steps Steps 1.1 to 1.2).
- Mark checkboxes in as steps are performed to keep track of the progress during the procedure.

Column 2: Procedure

- Column 2 in Table 1 contains a heading which indicates the server/IP being accessed as well as text instructions and/or notes. This column may also describe the operations to be performed or observed during the step.

Column 3: Result

- Column 3 in Table 1 generally displays the results of performing the instructions in column 2.
- The Result column can also display any of the following:
 - Inputs (commands or responses) required.
 - Outputs which are displayed on the terminal.
 - Illustrations or graphic figures related to the step instruction.
 - Screen captures from the product GUI related to the step instruction.

Table 3: Sample Procedure

Step	Procedure	Result
1. <input type="checkbox"/>	Active NOAMP VIP: 1. Access the command prompt. 2. Log into the server as the admusr user.	Login as: admusr Using keyboard-interactive authentication. Password: <password> NOTE: The password does not show on the screen as the characters are entered.
2. <input type="checkbox"/>	Active NOAMP VIP: Output displays as the server returns to a command prompt.	*** TRUNCATED OUTPUT *** <pre> VPATH=/opt/TKLCcomcol/runcm6.3:/opt/TKLCcomcol/cm6.3 PRODPATH= RELEASE=6.3 RUNID=00 VPATH=/var/TKLC/rundb:/usr/TKLC/appworks:/usr/TKLC/udr:/usr/TKLC/awpcommon:/usr/TKLC/comagent-gui:/usr/TKLC/comagent:/usr/TKLC/dpi:/usr/TKLC/capm/prod/plugins PRODPATH=/opt/comcol/prod RUNID=00 [admusr@908070109-NO-A ~]\$</pre>

Step	Procedure	Result
3. <input type="checkbox"/>	Active NOAMP VIP: Verify that the correct date and time are displayed in GMT (+/- 4 min.)	<pre>date -u Thu Apr 24 17:13:17 UTC 2014 [admusr@908070109-NO-A filemgmt]\$</pre>
THIS PROCEDURE HAS BEEN COMPLETED		

1.6 Recommendations

This section provides recommendations to consider when preparing to perform the procedures in this document.

1.6.1 Frequency of Health Checks

You can run the Perform Health Check or View Logs steps freely or repeat as many times as necessary in between procedures during the upgrade process. It is not recommended to do this in between steps in a procedure, unless there is a failure to troubleshoot.

1.6.2 Logging of Upgrade Activities

It is a best practice to use a terminal session with logging enabled to capture command activities and output during the upgrade procedures. These can be used for analysis in the event of issues encountered during the activity. These logs are saved off line at the completion of the activity.

Note that GUI activities are logged in a security log, but it is also recommended to use a screen capture tool to collect a sequence of screen shots before, during, and after the upgrade. This can also be useful for later analysis.

Chapter 2. General Description

This document defines the step-by-step actions performed for a software upgrade of an in-service Oracle Communications User Data Repository from the source release to the target release. A major upgrade advances the Oracle Communications User Data Repository software from 12.2.x source release, or 12.4.x source release to 12.5.x target release. An incremental upgrade advances the software from 12.5.a-b.b.b to 12.5.b-c.c.c.

2.1 Supported Upgrade Paths

Figure 1 shows the supported Oracle Communications User Data Repository upgrade paths.




Figure 1: Supported Upgrade Paths

NOTE: Initial installation is not in the scope of this upgrade document. See [1] for initial installation requirements.

2.2 Firmware Updates

Firmware upgrades are not in the scope of this document, but may be required before upgrading Oracle Communications User Data Repository. It is assumed that these are done when needed by the hardware, and there is typically not a dependency between firmware version and the 12.5.1 release. Use the Upgrade Procedures and Release Notes documents contained in the Firmware Upgrade Packs to assess whether a firmware upgrade is necessary. Perform firmware upgrade procedures if required by [3].

2.3 PM&C (Management Server) Upgrades

Each site may have a PM&C (Management server) that provides support for maintenance activities at the site. There is a separate procedure for PM&C upgrade, including TVOE. PM&C must be upgraded before the other servers at the site are upgraded on partially virtualized configurations. Refer to [3].

2.4 TVOE Upgrade

TVOE (Virtual Operating Environment) is an operating system for a server, which hosts multiple virtual servers on the same hardware. It is typically used to make more efficient use of a Hardware server (Rack Mount or Blade), while maintaining application independence, for Oracle Communications User Data Repository applications that do not require the full resources of a modern Hardware server.

In Oracle Communications User Data Repository architecture, TVOE hosts are used to host several functions, including:

- PM&C
- Oracle Communications User Data Repository NOAMP, applications

TVOE host servers (that is, servers running TVOE and one or more Oracle Communications User Data Repository applications) must be upgraded before upgrading the guest applications, to assure compatibility. However, TVOE is backward compatible with older application revs, so the TVOE host and the applications do not have to be upgraded in the same Maintenance window.

The TVOE server hosting PM&C, and the PM&C application, must be upgraded before other TVOE host upgrades, since PM&C is used to perform the TVOE upgrades.

There are three supported strategies for TVOE upgrade (Options A, B and C):

- Option A: Upgrade TVOE environments as a separate activity that is planned and performed days or weeks before the application upgrades (perhaps site-at-a-time)
- Options to Upgrade TVOE and application at the same maintenance window:
 - Option B: Upgrade TVOE and application, followed by another TVOE and application. Example: for standby NOAMP Upgrade:
 - i. Stop the application
 - ii. Upgrade TVOE
 - iii. Upgrade the application
 - iv. Start the application
 - v. Repeat for the active NOAMP.
 - Option C: Upgrade multiple TVOE hosts at a site, and then start upgrading the applications (same Maintenance Window)

Note that TVOE upgrades require a brief shutdown of the guest applications on the server. Note also that the TVOE virtual hosts may be hosting NOAMP applications.

The procedure for upgrading TVOE environments before the application upgrades (Option A) is documented in 3.3.6.

2.5 Traffic Management during Upgrade

Upgrade of NOAM servers is not expected to affect traffic-handling servers.

2.6 Provisioning during Upgrade

For Oracle Communications User Data Repository 12.5.1, provisioning (live traffic) continues while the upgrade is being performed. While the standby NOAMP is being upgraded, the active NOAMP receives provisioning requests. After the upgrade is complete, replication is turned on to the standby NOAMP to sync the most recent requests from the active NOAMP. Then the standby NOAMP becomes active to start receiving provisioning requests, while the previous active NOAMP is being upgraded.

2.7 Configurations

2.7.1 Low Capacity Configurations (Fully Virtualized with TVOE)


This includes all Oracle Communications User Data Repository software running on a TVOE virtualization environment in each server, resulting in a fully-virtualized, fully-redundant HA configuration. This can be deployed either as a single site or as a geo-redundant deployment, with 2 servers at each site. (Each blade/server hosts 1 NOAMP or 2 NOAMP instance).

DL380 RMS server supports 2 disk configurations: 12 x146GB 15K RPM drives and 6x600GB 10K RPM drives (Low Speed Drive Configuration)

Hardware IDs Supported:

- ProLiantBL460Gen8, ProLiantBL460Gen8+ or ProLiantBL460Gen9
- ProLiantDL380Gen8, ProLiantDL380Gen8+ or ProLiantDL380Gen9
- ORACLESERVERX5-2

Figure 2: Low Capacity Single-Site Configuration



2.7.2 Cloud Configurations

This includes all Oracle Communications User Data Repository software running in a cloud environment. This can be deployed either as a single site or as a geo-redundant deployment, with 1 or two 2 servers filling each role at each site. See reference [4] for full details.

Non HA				
Min number of VMs	Max number of VMs	Min number of VMs	Max number of VMs	HA config
1	2	2	2	Active-Standby
1	2	2	2	Active-Standby
1	1	2	4	Active-Active

2.8 Sequence of Upgrade

Oracle Communications User Data Repository supports fully virtualized configurations, partially virtualized configurations, and cloud configurations. In fully virtualized configurations PM&C, NOAMPs functions are hosted over TVOE on one server. In cloud configurations, TVOE and PM&C upgrade operations do not apply. The upgrade procedures vary slightly between these configurations.

Table 4: Sequence of upgrade

Fully Virtualized configurations	Partially Virtualized configurations	Cloud configurations
Required Materials Check	Required Materials Check	Required Materials Check
Update firmware if required. Use the Upgrade Procedures and Release Notes documents contained in the Firmware Upgrade Packs to assess whether a firmware upgrade is necessary.	Update firmware if required. Refer to Use the Upgrade Procedures and Release Notes documents contained in the Firmware Upgrade Packs to assess whether a firmware upgrade is necessary.	N/A
Upgrade TVOE if required. Refer to [2]	Upgrade PM&C if required. Refer to [3].	N/A
Upgrade PM&C, if required refer [3]	Upgrade TVOE, if required Refer [2].	N/A
Upgrade Oracle Communications User Data Repository application	Upgrade Oracle Communications User Data Repository application	Upgrade Oracle Communications User Data Repository application

Chapter 3. Upgrade Planning and pre-upgrade procedures

This section contains all information necessary to prepare for and perform an upgrade. The materials required to perform an upgrade are described and the pre-upgrade procedures that are run to ensure the system is ready for upgrade. Then, the actual procedures for each supported upgrade path are given.

There are overview tables throughout this section that help you plan the upgrade and estimate how long it takes to perform various actions. The stated time durations for each step or group of steps are estimates only. Do not use the overview tables to perform any actions on your system. Only the procedures are used when performing upgrade actions, beginning with Procedure 2: Required Materials Check.

3.1 Required Materials

The following materials and information are needed to perform an upgrade:

- Target-release application ISO image file, or target-release application media.
- GUI access to the Oracle Communications User Data Repository Network OAMP VIP with Administrator privileges.
- User logins, passwords, IP addresses and other administration information. See Section 3.1.2.
- SSH/SFTP access to the Oracle Communications User Data Repository Network OAMP XMI VIP as the admusr user.

NOTE: All logins into the Oracle Communications User Data Repository NO servers are made via the External Management (XMI) VIP unless otherwise stated.

- VPN access to the network is required if that is the only method to log into the OAM servers.
- Direct access to the blades/RMS iLO IP addresses (whichever applicable) from the workstations directly connected to the servers is required.
- Direct access to server IMI IP addresses from the local workstation is preferable in the case of a backout.

NOTE: If direct access to the IMI IP addresses cannot be made available, then target server access can be made via a tandem connection through the active primary NO (that is, An SSH connection is made to the active primary NO XMI first, then from the active primary NO, a 2nd SSH connection can be made to the target IMI IP address of the server).

3.1.1 Application ISO Image File/Media

You must obtain a copy of the target release ISO image file. This file is necessary to perform the upgrade. The Oracle Communications User Data Repository ISO image file is in the format:

UDR-12.5.1.0.0_17.7.0-x86_64.iso

NOTE: Actual number values may vary between releases.

When performing this upgrade procedure, it is assumed that the Oracle Communications User Data Repository ISO image file has been delivered to the premises. The ISO image file must reside on the local workstation used to perform the upgrade, and anybody performing the upgrade must have access to the ISO image file. If you are at a remote location, it is assumed the ISO file is available to you before starting the upgrade procedure.

3.1.2 Logins, Passwords and Site Information

Obtain all the information requested in the following table. This ensures that the necessary administration information is available before an upgrade starts. Consider the confidential nature of the information recorded in this

Oracle Communications User Data Repository Software Upgrade Procedure
table. While all of the information in the table is required to complete the upgrade, there may be security policies in place that require secure disposal after the upgrade completes.

	Description	Recorded Value
Credentials	GUI Admin Username ¹	
	GUI Admin Password	
	Admusr Password ²	
	Root Password ³	
	Blades iLO Admin Username	
	Blades iLO Admin Password	
	PM&C GUI Admin Username	
	PM&C GUI Admin Password	
	PM&C root Password	
	PM&C pmacftpusr password	
	OA GUI Username	
	OA GUI Password	
VPN Access Details	Customer VPN information (if needed)	
NO	Primary NOAMP	
	DR NOAMP	
	XMI VIP address ⁴	
	NO 1 XMI IP Address	
	NO 2 XMI IP Address	
PM&C	PM&C Management IP Address (Site 1)	
PM&C	PM&C Management IP Address(Site 2)	
Software	Source Release Number	
	Target Release Number	
	ISO Image (.iso) file name	

¹ The user must have administrator privileges. This means the user belongs to the admin group in Group Administration.

² This is the password for the admusr login on the servers. This is not the same login as the GUI Administrator. The admusr password is required if recovery procedures are needed. If the admusr password is not the same on all other servers, then all root passwords for the servers must also be recorded; use additional space at the bottom of this table.

³ This is the password for the root login on the servers. This is not the same login as the GUI Administrator. The root password is required if recovery procedures are needed. If the root password is not the same on all other servers, then all root passwords for the servers must also be recorded; use additional space at the bottom of this table.

⁴ All logins into the NO servers are made via the External Management VIP unless otherwise stated.

3.2 Maintenance Window for PM&C and TVOE Upgrades

This document includes steps to upgrade PM&C and TVOE as an integrated activity with the upgrades of the Oracle Communications User Data Repository application. However, it is an option to perform these PM&C and TVOE upgrades as separately planned activities.

- PM&C Upgrade procedure is provided in reference [3].
- TVOE host environment upgrade procedures are included in architecture-specific sections this document.

Both PM&C and TVOE upgrades are backwards compatible to prior releases on Oracle Communications User Data Repository. It may be done a site-at-a-time.

3.3 Pre-Upgrade Procedures

The pre-upgrade procedures in Table 5 do not have an affect on the live system.

Table 5: Pre-Upgrade Overview

Procedure Number	Procedure Title	Elapsed Time (Hours:Minutes)	
		This Step	Cumulative
1	Required Materials Check	00:15	00:15
2	ISO Administration	*	*
Appendix B	Health Check Procedures (depends on number of servers)	0:10-1:15	00:25-01:30

***NOTE:** ISO transfers to the target systems cannot be estimated because times vary significantly depending on the number of systems and the speed of the network.

The ISO transfers to the target systems must be performed before the scheduled maintenance window. Schedule the required maintenance windows accordingly.

3.3.1 Hardware Upgrade Preparation

Hardware preparation is not necessary when upgrading to release 12.5.1.

3.3.2 Review Release Notes

Before starting the upgrade, review the release notes for the Oracle Communications User Data Repository 12.5.1 release to understand the functional differences and possible traffic impacts of the upgrade.

It is important to check Oracle Communications UDR-PCRF compatibility before performing a major upgrade since all versions are not compatible. Release notes for this and all release are available at <https://docs.oracle.com>.

3.3.3 Required Materials Check

This procedure verifies that all required materials needed to perform an upgrade have been collected and recorded.

This procedure verifies that all required materials are present.

Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.

Procedure 1: Required Materials Check

Step	Procedure	Result
1. <input type="checkbox"/>	Verify all required materials are present.	Materials are listed in Section 3.1. Verify all required materials are present.
2. <input type="checkbox"/>	Verify all administration data needed during upgrade.	Double-check that all information in Section 3.1.2 is filled-in and accurate.
3. <input type="checkbox"/>	Contact Oracle CGBU Customer Care Center	Contact the My Oracle Support and inform them of plans to upgrade this system. See Appendix J for these instructions.

3.3.4 Perform Health Check (Upgrade Preparation)

Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.

Procedure 2: Perform Health Check (Upgrade Preparation)

Step	Procedure
1. <input type="checkbox"/>	<p>This procedure is part of software upgrade preparation and is used to determine the health and status of the Oracle Communications User Data Repository network and servers. This may be performed multiple times but must also be performed at least once in 24 to 36 hours before the start of the upgrade procedures.</p> <ul style="list-style-type: none"> • Perform Health Check procedures as specified in Appendix B.



3.3.5 ISO Administration



Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.



Procedure 3: ISO Administration for Upgrades

Step	Procedure	Result
1. <input type="checkbox"/>	Using the VIP address, access the primary NOAMP GUI.	Access the primary NOAMP GUI as specified in Appendix A .

Step	Procedure	Result																																												
2. <input type="checkbox"/> Active NOAMP VIP: Upload ISO file to the active NOAMP server	<p>1. Navigate to Main Menu → Status & Manage → Files</p> <p>2. Using the cursor, select the active NOAMP server from the list tabs.</p> <p>3. Click Upload.</p>	<p>Main Menu: Status & Manage -> Files</p> <p>Filter* Tasks</p> <table border="1"> <thead> <tr> <th data-bbox="535 312 616 333">OCUDR-A</th> <th data-bbox="633 312 714 333">OCUDR-B</th> <th data-bbox="731 312 812 333">DR-OCUDR-A</th> <th data-bbox="829 312 910 333">DR-OCUDR-B</th> </tr> </thead> <tbody> <tr> <td data-bbox="535 354 616 375">File Name</td> <td data-bbox="633 354 649 375"></td> <td data-bbox="731 354 747 375">Size</td> <td data-bbox="763 354 780 375">Type</td> <td data-bbox="796 354 878 375">Timestamp</td> </tr> <tr> <td data-bbox="535 397 747 418">TKLCCConfigData.DR-OCUDR-A.sh</td> <td data-bbox="633 397 665 418">6.6 KB</td> <td data-bbox="731 397 747 418">sh</td> <td data-bbox="763 397 845 418">2018-05-09 01:08:40 EDT</td> <td data-bbox="861 397 878 418"></td> </tr> <tr> <td data-bbox="535 439 747 460">TKLCCConfigData.DR-OCUDR-B.sh</td> <td data-bbox="633 439 665 460">6.6 KB</td> <td data-bbox="731 439 747 460">sh</td> <td data-bbox="763 439 845 460">2018-05-09 01:08:40 EDT</td> <td data-bbox="861 439 878 460"></td> </tr> <tr> <td data-bbox="535 481 747 502">TKLCCConfigData.OCUDR-A.sh</td> <td data-bbox="633 481 665 502">5.8 KB</td> <td data-bbox="731 481 747 502">sh</td> <td data-bbox="763 481 845 502">2018-05-09 00:53:59 EDT</td> <td data-bbox="861 481 878 502"></td> </tr> <tr> <td data-bbox="535 523 747 544">TKLCCConfigData.OCUDR-B.sh</td> <td data-bbox="633 523 665 544">6.5 KB</td> <td data-bbox="731 523 747 544">sh</td> <td data-bbox="763 523 845 544">2018-05-09 01:08:40 EDT</td> <td data-bbox="861 523 878 544"></td> </tr> <tr> <td data-bbox="535 566 616 587">udrInitConfig.sh</td> <td data-bbox="633 566 698 587">43.5 KB</td> <td data-bbox="731 566 747 587">sh</td> <td data-bbox="763 566 845 587">2018-01-24 11:13:33 EST</td> <td data-bbox="861 566 878 587"></td> </tr> <tr> <td data-bbox="535 608 616 629">ugwrap.log</td> <td data-bbox="633 608 665 629">1.3 KB</td> <td data-bbox="731 608 747 629">log</td> <td data-bbox="763 608 845 629">2018-01-24 12:13:10 EST</td> <td data-bbox="861 608 878 629"></td> </tr> <tr> <td data-bbox="535 650 616 671">upgrade.log</td> <td data-bbox="633 650 698 671">980.3 KB</td> <td data-bbox="731 650 747 671">log</td> <td data-bbox="763 650 845 671">2018-01-24 12:15:36 EST</td> <td data-bbox="861 650 878 671"></td> </tr> </tbody> </table> <p>Delete View Upload Download Deploy ISO Validate ISO</p>	OCUDR-A	OCUDR-B	DR-OCUDR-A	DR-OCUDR-B	File Name		Size	Type	Timestamp	TKLCCConfigData.DR-OCUDR-A.sh	6.6 KB	sh	2018-05-09 01:08:40 EDT		TKLCCConfigData.DR-OCUDR-B.sh	6.6 KB	sh	2018-05-09 01:08:40 EDT		TKLCCConfigData.OCUDR-A.sh	5.8 KB	sh	2018-05-09 00:53:59 EDT		TKLCCConfigData.OCUDR-B.sh	6.5 KB	sh	2018-05-09 01:08:40 EDT		udrInitConfig.sh	43.5 KB	sh	2018-01-24 11:13:33 EST		ugwrap.log	1.3 KB	log	2018-01-24 12:13:10 EST		upgrade.log	980.3 KB	log	2018-01-24 12:15:36 EST	
OCUDR-A	OCUDR-B	DR-OCUDR-A	DR-OCUDR-B																																											
File Name		Size	Type	Timestamp																																										
TKLCCConfigData.DR-OCUDR-A.sh	6.6 KB	sh	2018-05-09 01:08:40 EDT																																											
TKLCCConfigData.DR-OCUDR-B.sh	6.6 KB	sh	2018-05-09 01:08:40 EDT																																											
TKLCCConfigData.OCUDR-A.sh	5.8 KB	sh	2018-05-09 00:53:59 EDT																																											
TKLCCConfigData.OCUDR-B.sh	6.5 KB	sh	2018-05-09 01:08:40 EDT																																											
udrInitConfig.sh	43.5 KB	sh	2018-01-24 11:13:33 EST																																											
ugwrap.log	1.3 KB	log	2018-01-24 12:13:10 EST																																											
upgrade.log	980.3 KB	log	2018-01-24 12:15:36 EST																																											

Step	Procedure	Result
3. <input type="checkbox"/> Active NOAMP VIP: 1. Click Browse . 2. Select the Drive and directory location of the ISO file for the target release. Select the ISO file and click Open . 3. Click Upload .	<p>NOTES:</p> <ul style="list-style-type: none"> It is recommended to access the ISO file for the target release from a local hard drive partition as opposed to a network or flash drive location. Depending on network conditions, this upload may take an extended period of time (> 60 secs.). Alternatively, the ISO file can be manually transferred to the <code>/var/TKLC/db/filemgmt</code> directory of the active NOAMP server using SFTP. The ISO in the file management directory must have global read permission or the GUI ISO transfer fails, with a security log indicating the lack of read permission. If you upload the file using the GUI, the ISO has global read permission. If you have transferred the ISO to the NO without global read permission, you can log in as admusr and use <code>chmod 644</code> to give it read permission. When scp files use <code>scp -p</code> command.   	

Step	Procedure	Result																																				
4. <input type="checkbox"/>	<p>Active NOAMP VIP: Click the Timestamp link located on the top right of the right panel. A reverse-sorted list of files showing the newest files at the top displays. The ISO file uploaded in Step 3 of this procedure is at the top most position in the File Name column.</p>	<p>Main Menu: Status & Manage -> Files</p>  <table border="1"> <thead> <tr> <th data-bbox="514 348 660 369">File Name</th> <th data-bbox="660 348 693 369">Size</th> <th data-bbox="693 348 726 369">Type</th> <th data-bbox="726 348 758 369">Timestamp</th> </tr> </thead> <tbody> <tr> <td data-bbox="514 390 660 411">TKLCConfigData.DR-OCUDR-A.sh</td> <td data-bbox="660 390 693 411">6.6 KB</td> <td data-bbox="693 390 726 411">sh</td> <td data-bbox="726 390 758 411">2018-05-09 01:08:40 EDT</td> </tr> <tr> <td data-bbox="514 432 660 454">TKLCConfigData.DR-OCUDR-B.sh</td> <td data-bbox="660 432 693 454">6.6 KB</td> <td data-bbox="693 432 726 454">sh</td> <td data-bbox="726 432 758 454">2018-05-09 01:08:40 EDT</td> </tr> <tr> <td data-bbox="514 475 660 496">TKLCConfigData.OCUDR-A.sh</td> <td data-bbox="660 475 693 496">5.8 KB</td> <td data-bbox="693 475 726 496">sh</td> <td data-bbox="726 475 758 496">2018-05-09 00:53:59 EDT</td> </tr> <tr> <td data-bbox="514 517 660 538">TKLCConfigData.OCUDR-B.sh</td> <td data-bbox="660 517 693 538">6.5 KB</td> <td data-bbox="693 517 726 538">sh</td> <td data-bbox="726 517 758 538">2018-05-09 01:08:40 EDT</td> </tr> <tr> <td data-bbox="514 559 660 580">UDR-12.4.0.0.0_16.15.0-x86_64.iso</td> <td data-bbox="660 559 693 580">1 GB</td> <td data-bbox="693 559 726 580">iso</td> <td data-bbox="726 559 758 580">2018-03-28 10:33:53 EDT</td> </tr> <tr> <td data-bbox="514 601 660 623">udrInitConfig.sh</td> <td data-bbox="660 601 693 623">43.5 KB</td> <td data-bbox="693 601 726 623">sh</td> <td data-bbox="726 601 758 623">2018-01-24 11:13:33 EST</td> </tr> <tr> <td data-bbox="514 644 660 665">ugrwrap.log</td> <td data-bbox="660 644 693 665">1.3 KB</td> <td data-bbox="693 644 726 665">log</td> <td data-bbox="726 644 758 665">2018-01-24 12:13:10 EST</td> </tr> <tr> <td data-bbox="514 686 660 707">upgrade.log</td> <td data-bbox="660 686 693 707">980.3 KB</td> <td data-bbox="693 686 726 707">log</td> <td data-bbox="726 686 758 707">2018-01-24 12:15:36 EST</td> </tr> </tbody> </table>	File Name	Size	Type	Timestamp	TKLCConfigData.DR-OCUDR-A.sh	6.6 KB	sh	2018-05-09 01:08:40 EDT	TKLCConfigData.DR-OCUDR-B.sh	6.6 KB	sh	2018-05-09 01:08:40 EDT	TKLCConfigData.OCUDR-A.sh	5.8 KB	sh	2018-05-09 00:53:59 EDT	TKLCConfigData.OCUDR-B.sh	6.5 KB	sh	2018-05-09 01:08:40 EDT	UDR-12.4.0.0.0_16.15.0-x86_64.iso	1 GB	iso	2018-03-28 10:33:53 EDT	udrInitConfig.sh	43.5 KB	sh	2018-01-24 11:13:33 EST	ugrwrap.log	1.3 KB	log	2018-01-24 12:13:10 EST	upgrade.log	980.3 KB	log	2018-01-24 12:15:36 EST
File Name	Size	Type	Timestamp																																			
TKLCConfigData.DR-OCUDR-A.sh	6.6 KB	sh	2018-05-09 01:08:40 EDT																																			
TKLCConfigData.DR-OCUDR-B.sh	6.6 KB	sh	2018-05-09 01:08:40 EDT																																			
TKLCConfigData.OCUDR-A.sh	5.8 KB	sh	2018-05-09 00:53:59 EDT																																			
TKLCConfigData.OCUDR-B.sh	6.5 KB	sh	2018-05-09 01:08:40 EDT																																			
UDR-12.4.0.0.0_16.15.0-x86_64.iso	1 GB	iso	2018-03-28 10:33:53 EDT																																			
udrInitConfig.sh	43.5 KB	sh	2018-01-24 11:13:33 EST																																			
ugrwrap.log	1.3 KB	log	2018-01-24 12:13:10 EST																																			
upgrade.log	980.3 KB	log	2018-01-24 12:15:36 EST																																			
5. <input type="checkbox"/>	<p>Active NOAMP VIP: UNDEPLOY all unneeded ISO images.</p>	<p>1. Select Status & Manage -> Files from the left-side menu; the Files screen displays.</p> <p>Main Menu: Status & Manage -> Files</p>  <table border="1"> <thead> <tr> <th data-bbox="514 1129 660 1151">File Name</th> <th data-bbox="660 1129 693 1151">Size</th> <th data-bbox="693 1129 726 1151">Type</th> <th data-bbox="726 1129 758 1151">Timestamp</th> </tr> </thead> <tbody> <tr> <td data-bbox="514 1172 660 1193">TKLCConfigData.DR-OCUDR-A.sh</td> <td data-bbox="660 1172 693 1193">6.6 KB</td> <td data-bbox="693 1172 726 1193">sh</td> <td data-bbox="726 1172 758 1193">2018-05-09 01:08:40 EDT</td> </tr> <tr> <td data-bbox="514 1214 660 1235">TKLCConfigData.DR-OCUDR-B.sh</td> <td data-bbox="660 1214 693 1235">6.6 KB</td> <td data-bbox="693 1214 726 1235">sh</td> <td data-bbox="726 1214 758 1235">2018-05-09 01:08:40 EDT</td> </tr> <tr> <td data-bbox="514 1256 660 1277">TKLCConfigData.OCUDR-A.sh</td> <td data-bbox="660 1256 693 1277">5.8 KB</td> <td data-bbox="693 1256 726 1277">sh</td> <td data-bbox="726 1256 758 1277">2018-05-09 00:53:59 EDT</td> </tr> <tr> <td data-bbox="514 1298 660 1320">TKLCConfigData.OCUDR-B.sh</td> <td data-bbox="660 1298 693 1320">6.5 KB</td> <td data-bbox="693 1298 726 1320">sh</td> <td data-bbox="726 1298 758 1320">2018-05-09 01:08:40 EDT</td> </tr> <tr> <td data-bbox="514 1341 660 1362">UDR-12.4.0.0.0_16.15.0-x86_64.iso</td> <td data-bbox="660 1341 693 1362">1 GB</td> <td data-bbox="693 1341 726 1362">iso</td> <td data-bbox="726 1341 758 1362">2018-03-28 10:33:53 EDT</td> </tr> <tr> <td data-bbox="514 1383 660 1404">udrInitConfig.sh</td> <td data-bbox="660 1383 693 1404">43.5 KB</td> <td data-bbox="693 1383 726 1404">sh</td> <td data-bbox="726 1383 758 1404">2018-01-24 11:13:33 EST</td> </tr> <tr> <td data-bbox="514 1425 660 1446">ugrwrap.log</td> <td data-bbox="660 1425 693 1446">1.3 KB</td> <td data-bbox="693 1425 726 1446">log</td> <td data-bbox="726 1425 758 1446">2018-01-24 12:13:10 EST</td> </tr> <tr> <td data-bbox="514 1467 660 1488">upgrade.log</td> <td data-bbox="660 1467 693 1488">980.3 KB</td> <td data-bbox="693 1467 726 1488">log</td> <td data-bbox="726 1467 758 1488">2018-01-24 12:15:36 EST</td> </tr> </tbody> </table> <p>2. Select the ISOs to be undeployed and click Undeploy ISO at the bottom of the table.</p> <p>3. Click OK to confirm the ISO undeployment.</p> <p>4. Verify that the ISO undeployment is successful.</p> <p>NOTE: The Tasks menu message box at the top of the Files page displays the status of the undeployment for each server. In addition, an ISO Deployment report can be viewed by selecting the ISO and clicking View ISO Deployment Report.</p>	File Name	Size	Type	Timestamp	TKLCConfigData.DR-OCUDR-A.sh	6.6 KB	sh	2018-05-09 01:08:40 EDT	TKLCConfigData.DR-OCUDR-B.sh	6.6 KB	sh	2018-05-09 01:08:40 EDT	TKLCConfigData.OCUDR-A.sh	5.8 KB	sh	2018-05-09 00:53:59 EDT	TKLCConfigData.OCUDR-B.sh	6.5 KB	sh	2018-05-09 01:08:40 EDT	UDR-12.4.0.0.0_16.15.0-x86_64.iso	1 GB	iso	2018-03-28 10:33:53 EDT	udrInitConfig.sh	43.5 KB	sh	2018-01-24 11:13:33 EST	ugrwrap.log	1.3 KB	log	2018-01-24 12:13:10 EST	upgrade.log	980.3 KB	log	2018-01-24 12:15:36 EST
File Name	Size	Type	Timestamp																																			
TKLCConfigData.DR-OCUDR-A.sh	6.6 KB	sh	2018-05-09 01:08:40 EDT																																			
TKLCConfigData.DR-OCUDR-B.sh	6.6 KB	sh	2018-05-09 01:08:40 EDT																																			
TKLCConfigData.OCUDR-A.sh	5.8 KB	sh	2018-05-09 00:53:59 EDT																																			
TKLCConfigData.OCUDR-B.sh	6.5 KB	sh	2018-05-09 01:08:40 EDT																																			
UDR-12.4.0.0.0_16.15.0-x86_64.iso	1 GB	iso	2018-03-28 10:33:53 EDT																																			
udrInitConfig.sh	43.5 KB	sh	2018-01-24 11:13:33 EST																																			
ugrwrap.log	1.3 KB	log	2018-01-24 12:13:10 EST																																			
upgrade.log	980.3 KB	log	2018-01-24 12:15:36 EST																																			

Step	Procedure	Result
6. <input type="checkbox"/>	<p>Active NOAMP VIP (GUI): Transfer ISO to all remaining servers via the GUI session.</p> <p>Select the <ISO filename> and then click Deploy ISO.</p> <p>Click OK.</p>	
7. <input type="checkbox"/>	<p>Active NOAMP VIP (GUI): This moves the ISO file to the isos directory and starts the secure copy of the ISO to each server in the system. A status window opens as well.</p>	

Step	Procedure	Result																																				
8. <input type="checkbox"/>	<p>Active NOAMP VIP (GUI): To view the status of the deployed ISO, select the file <code>isos/<ISO filename></code> and then click View ISO Deployment Report or click the Tasks dropdown.</p> <p>NOTE: This button displays when a deployed ISO is selected. All other times, it is the View button.</p> <p>To view the <code>isos</code> directory on each server that is deployed, select the server tabs near the top of the menu.</p> <p>As an optional check (after the ISO is deployed), can click Validate ISO to ensure it is valid.</p>	<p>Main Menu: Status & Manage -> Files</p> <thead> <tr> <th>File Name</th> <th>Size</th> <th>Type</th> <th>Timestamp</th> </tr> </thead> <tbody> <tr> <td>isos/UDR-12.4.0.0.0_16.15.0-x86_64.iso</td> <td>1 GB</td> <td>iso</td> <td>2018-03-28 10:33:53 EDT</td> </tr> <tr> <td>TKLCConfigData.DR-OCUDR-A.sh</td> <td>6.6 KB</td> <td>sh</td> <td>2018-05-09 01:08:40 EDT</td> </tr> <tr> <td>TKLCConfigData.DR-OCUDR-B.sh</td> <td>6.6 KB</td> <td>sh</td> <td>2018-05-09 01:08:40 EDT</td> </tr> <tr> <td>TKLCConfigData.OCUDR-A.sh</td> <td>5.8 KB</td> <td>sh</td> <td>2018-05-09 00:53:59 EDT</td> </tr> <tr> <td>TKLCConfigData.OCUDR-B.sh</td> <td>6.5 KB</td> <td>sh</td> <td>2018-05-09 01:08:40 EDT</td> </tr> <tr> <td>udrInitConfig.sh</td> <td>43.5 KB</td> <td>sh</td> <td>2018-01-24 11:13:33 EST</td> </tr> <tr> <td>ugwrap.log</td> <td>1.3 KB</td> <td>log</td> <td>2018-01-24 12:13:10 EST</td> </tr> <tr> <td>upgrade.log</td> <td>980.3 KB</td> <td>log</td> <td>2018-01-24 12:15:36 EST</td> </tr> </tbody>	File Name	Size	Type	Timestamp	isos/UDR-12.4.0.0.0_16.15.0-x86_64.iso	1 GB	iso	2018-03-28 10:33:53 EDT	TKLCConfigData.DR-OCUDR-A.sh	6.6 KB	sh	2018-05-09 01:08:40 EDT	TKLCConfigData.DR-OCUDR-B.sh	6.6 KB	sh	2018-05-09 01:08:40 EDT	TKLCConfigData.OCUDR-A.sh	5.8 KB	sh	2018-05-09 00:53:59 EDT	TKLCConfigData.OCUDR-B.sh	6.5 KB	sh	2018-05-09 01:08:40 EDT	udrInitConfig.sh	43.5 KB	sh	2018-01-24 11:13:33 EST	ugwrap.log	1.3 KB	log	2018-01-24 12:13:10 EST	upgrade.log	980.3 KB	log	2018-01-24 12:15:36 EST
File Name	Size	Type	Timestamp																																			
isos/UDR-12.4.0.0.0_16.15.0-x86_64.iso	1 GB	iso	2018-03-28 10:33:53 EDT																																			
TKLCConfigData.DR-OCUDR-A.sh	6.6 KB	sh	2018-05-09 01:08:40 EDT																																			
TKLCConfigData.DR-OCUDR-B.sh	6.6 KB	sh	2018-05-09 01:08:40 EDT																																			
TKLCConfigData.OCUDR-A.sh	5.8 KB	sh	2018-05-09 00:53:59 EDT																																			
TKLCConfigData.OCUDR-B.sh	6.5 KB	sh	2018-05-09 01:08:40 EDT																																			
udrInitConfig.sh	43.5 KB	sh	2018-01-24 11:13:33 EST																																			
ugwrap.log	1.3 KB	log	2018-01-24 12:13:10 EST																																			
upgrade.log	980.3 KB	log	2018-01-24 12:15:36 EST																																			

| 9. | **Active NOAMP terminal** Log on to the active NOAMP terminal using the credentials provided | Use your SSH client to connect to the server (For example: ssh or putty): ``` ssh<server address> login as: admusr password: <enter password> ``` |
| 10. | **Active NOAMP terminal:** Mount the ISO image that is used for upgrade | ``` $ sudo mount -o loop /var/TKLC/db/filemgmt/isos/UDR-12.5.1.0.0_17.7.0-x86_64.iso /mnt/upgrade ``` |

Step	Procedure	Result
11. <input type="checkbox"/>	Active NOAMP terminal: Extract and copy the script to /var/tmp	Copy the file to /var/tmp for execution. <pre>\$ cp /mnt/upgrade/upgrade/bin/changeLinksToFiles.php /var/tmp</pre>
12. <input type="checkbox"/>	Active NOAMP terminal: Unmount the ISO image	<pre>\$ sudo umount /mnt/upgrade</pre>
13. <input type="checkbox"/>	Active NOAMP terminal: Verify that the script copied is executable	<pre>\$ chmod +x /var/tmp/changeLinksToFiles.php</pre>
14. <input type="checkbox"/>	Active NOAMP terminal: Run the script	<pre>\$ /var/tmp/changeLinksToFiles.php</pre>
THIS PROCEDURE HAS BEEN COMPLETED		

3.3.6 Upgrade TVOE Hosts at a Site (before application upgrade MW)

This procedure applies if the TVOE hosts at a site (primary or DR) are upgraded before the start of the Oracle Communications User Data Repository 12.5.1 Upgrade of the NOs and other servers. Performing the TVOE upgrade before reduces the time required for Oracle Communications User Data Repository application upgrade procedures.

Precondition: *The PM&C application at each site (and the TVOE host running the PM&C Virtual server, must be upgraded before performing TVOE host OS Upgrade for servers that are managed by this PM&C.*

Impact: *TVOE host upgrades require that the Oracle Communications User Data Repository applications running on the host be shut down for up to 30 minutes during the upgrade.*

Procedure	This Step	Cum.	Procedure Title	Impact
Appendix B	0:01-0:05	0:01-0:05	Perform Health Check (Upgrade Preparation)	
Refer to [2]	30 min per TVOE host (see note)	0:01- 3:05	Upgrade TVOE Hosts at a Site (before application upgrade MW)	Oracle Communications User Data Repository servers running as virtual guests on the TVOE host is stopped and unable to perform their Oracle Communications User Data Repository role while the TVOE host is being upgraded.
Appendix B	0:01-0:05	0:02- 3:10	Verify health of site	

NOTE: Depending on the risk tolerance, it is possible to perform multiple TVOE upgrades in parallel.

Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.

Procedure 4: Upgrade TVOE Hosts at a Site (before application upgrade MW)

Step	Procedure	Result
1. <input type="checkbox"/>	Record site	Record Site to be upgraded _____
2. <input type="checkbox"/>	Select Order of TVOE server upgrades	<p>Record the TVOE hosts to be upgraded, in order: (It is best to upgrade standby servers before active servers, to minimize failovers. Otherwise, any order is OK.)</p> <hr/> <hr/> <hr/> <hr/> <hr/> <hr/> <p>NOTE: The site PM&C Software Inventory form typically lists the TVOE hosts at a site, and their versions.</p>
3. <input type="checkbox"/>	Upgrade the TVOE hosting the standby servers	<p>Upgrade the TVOE host of a standby server: Perform Appendix G, Upgrade TVOE Platform</p>
4. <input type="checkbox"/>	Upgrade the TVOE hosting the active servers	<p>Upgrade TVOE of the active server Perform Appendix G, Upgrade TVOE Platform</p> <p>NOTE: This causes a failover of the Oracle Communications User Data Repository on the TVOE.</p>
5. <input type="checkbox"/>	Repeat for TVOE hosts at a Site	Repeat steps 3 and 4 for multiple TVOE hosts at a site, as time permits.

3.4 Order of Application Upgrade

The following list displays the order to upgrade the servers (primary and DR sites):

4. Site 2 NOAMPs (DR spares)
5. Primary standby NOAMP
6. Primary active NOAMP

3.5 Upgrade Execution Overview for Normal Capacity C-Class Configuration

3.5.1 Primary NOAMP/DR NOAMP Execution Overview

The times in Table 6 and Table 7 are the estimated times for upgrading 2 NOAMPs and 2 DR NOAMPs. The DR NOAMPs are upgraded first, followed by the primary NOAMPs.

Table 6: DR NOAMP Upgrade Procedures for Normal Capacity C-Class Configurations

Procedure Number	Procedure Title	Elapsed Time (Hours:Minutes)	
		This Step	Cumulative
4	Remove Additional GUI Sessions	00:05	00:05
5	Full Database Backup	00:30	00:35
6 or 7	Major Upgrade DR NOAMP NE or Incremental Upgrade DR NOAMP NE	03:30	04:05

Table 7: Primary NOAMP Upgrade Procedures for Normal Capacity C-Class Configurations

Procedure Number	Procedure Title	Elapsed Time (Hours:Minutes)	
		This Step	Cumulative
8 or 9	Major Upgrade Primary NOAMP NE or <i>Incremental Upgrade Primary NOAMP NE</i>	03:30	03:30

***NOTE:** Times estimates are based on a large Database.

3.6 Upgrade Execution Overview for Low Capacity Configurations

3.6.1 Primary NOAMP/DR NOAMP Execution Overview

The times in Table 8 and Table 9 are the estimated times for upgrading 2 NOAMPs and 2 DR NOAMPs. The primary NOAMPs are upgraded first, followed by the DR NOAMPs.

Table 8: DR NOAMP Upgrade Procedures for Low Capacity Configurations

Procedure Number	Procedure Title	Elapsed Time (Hours:Minutes)	
		This Step	Cumulative
4	Remove Additional GUI Sessions	00:05	00:05
5	Full Database Backup	00:30	00:35
6 or 7	Major Upgrade DR NOAMP NE or Incremental Upgrade DR NOAMP NE	01:00	01:35

Table 9: Primary NOAMP Upgrade Procedures for Low Capacity Configurations

Procedure Number	Procedure Title	Elapsed Time (Hours:Minutes)	
		This Step	Cumulative
8 or 9	Major Upgrade Primary NOAMP NE or Incremental Upgrade Primary NOAMP NE	01:00	01:00

*NOTE: Times estimates are based on a small Database.

3.7 Upgrade Acceptance Overview

Table 10: Upgrade Acceptance overview

Procedure Number	Procedure Title	Elapsed Time (Hours:Minutes)	
		This Step	Cumulative
15	<i>Accept Upgrade</i>	00:20	00:20

Chapter 4. Primary NOAMP/DR NOAMP Upgrade Execution

Open A Service Ticket at My Oracle Support (Appendix J) and inform them of your plans to upgrade this system before performing this upgrade.

Before upgrade, perform the system Health Check Appendix B.

This check ensures that the system to be upgraded is in an upgrade-ready state. Performing the system health check determines which alarms are present in the system and if upgrade can proceed with alarms.

***** **WARNING** *****

If there are servers in the system, which are not in the Normal state, put these servers into the Normal or the Application Disabled state before the upgrade process is started.

The sequence of upgrade is designed so that servers providing support services to other servers are upgraded first.

***** **WARNING** *****

Read the following notes on this procedure:

Procedure completion times listed in this document are estimates. Times may vary due to differences in database size, user experience, and user preparation.

Where possible, command response outputs are shown as accurately as possible. Exceptions are as follows:

- Session banner information such as time and date.
- System-specific configuration information such as hardware locations, IP addresses and hostnames.
- ANY information marked with XXXX or YYYY. Where appropriate, instructions are provided to determine what output is expected in place of XXXX or YYYY
- Aesthetic differences unrelated to functionality such as browser attributes: window size, colors, toolbars, and button layouts.

After completing each step and at each point where data is recorded from the screen, the technician performing the upgrade must mark the provided checkbox.

For procedures which are performed multiple times, a mark can be made below the checkbox (in the same column) for each additional iteration of the step.

Retention of captured data is required for future support references.

4.1 Perform Health Check (Pre Upgrade)

Procedure 5: Health Check (Pre Upgrade)

1. <input type="checkbox"/>	This procedure is part of software upgrade preparation and is used to determine the health and status of the Oracle Communications User Data Repository network and servers. This may be performed multiple times but must also be performed at least once 24 to 36 hours before the start of a maintenance window. Perform Health Check procedures as specified in Appendix B .
-----------------------------	--

4.2 Primary NOAMP/DR NOAMP Upgrade



This procedures detail how to perform upgrades for primary NOAMP and DR NOAMP servers.


4.2.1 Remove Additional GUI Sessions

Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.

Procedure 6: Remove Additional GUI Sessions

Step	Procedure	Result												
1. <input type="checkbox"/>	Using the VIP address, access the primary NOAMP GUI.	Access the primary NOAMP GUI as specified in Appendix A .												
2. <input type="checkbox"/>	Active NOAMP VIP: Navigate to Main Menu → Administration → Access Control → Sessions	<p>Main Menu: Administration -> Access Control -> Sessions</p> <table border="1"> <tr> <td>Sess ID</td> <td>Expiration Time</td> <td>Login Time</td> <td>User</td> <td>Group</td> <td>Remote IP</td> </tr> <tr> <td>19</td> <td>Wed Mar 01 17:32:38 2017 EST</td> <td>Wed Mar 01 14:25:14 2017 EST</td> <td>guiadmin</td> <td>admin</td> <td>10.75.10.242</td> </tr> </table>	Sess ID	Expiration Time	Login Time	User	Group	Remote IP	19	Wed Mar 01 17:32:38 2017 EST	Wed Mar 01 14:25:14 2017 EST	guiadmin	admin	10.75.10.242
Sess ID	Expiration Time	Login Time	User	Group	Remote IP									
19	Wed Mar 01 17:32:38 2017 EST	Wed Mar 01 14:25:14 2017 EST	guiadmin	admin	10.75.10.242									
3. <input type="checkbox"/>	Active NOAMP VIP: In the right panel, the list of active GUI sessions connected to the active NOAMP server displays.	<p>Main Menu: Administration -> Access Control -> Sessions</p> <table border="1"> <tr> <td>Sess ID</td> <td>Expiration Time</td> <td>Login Time</td> <td>User</td> <td>Group</td> <td>Remote IP</td> </tr> <tr> <td>19</td> <td>Wed Mar 01 17:32:38 2017 EST</td> <td>Wed Mar 01 14:25:14 2017 EST</td> <td>guiadmin</td> <td>admin</td> <td>10.75.10.242</td> </tr> </table>	Sess ID	Expiration Time	Login Time	User	Group	Remote IP	19	Wed Mar 01 17:32:38 2017 EST	Wed Mar 01 14:25:14 2017 EST	guiadmin	admin	10.75.10.242
Sess ID	Expiration Time	Login Time	User	Group	Remote IP									
19	Wed Mar 01 17:32:38 2017 EST	Wed Mar 01 14:25:14 2017 EST	guiadmin	admin	10.75.10.242									


Step	Procedure	Result
4. <input type="checkbox"/>	<p>Active NOAMP VIP:</p> <p>The User ID and Remote IP address of each session are displayed as seen on the right.</p> <p>Every attempt is made to contact users not engaged in this Upgrade activity and request that they discontinue GUI access until the upgrade activity has completed.</p>	
5. <input type="checkbox"/>	<p>Active NOAMP VIP:</p> <p>If unable to identify or contact the session owners, sessions not related to the upgrade activity may be selected and deleted as follows:</p> <ol style="list-style-type: none"> 1. Select the session for deletion with the cursor. 2. In the bottom left of the right panel, click Delete. 3. Click OK. 	 <p>NOTE: The Session screen prevents you from deleting the session users are connected to. If attempting to do so by accident, a message may be received in the Banner area stating Logout to delete your own session (id=xx).</p>



Step	Procedure	Result
6. <input type="checkbox"/>	Active NOAMP VIP: A confirmation message displays in the Info tab indicating the session ID which was deleted.	
7. <input type="checkbox"/>	Active NOAMP VIP: Delete any additional GUI sessions as needed.	Repeat Steps 5 and 6 of this Procedure for each additional GUI session to be deleted.
THIS PROCEDURE HAS BEEN COMPLETED		




4.2.2 Full Database Backup (All Servers)

This procedure is part of software upgrade preparation and is used to conduct a full backup of the COMCOL run environment on every server. This backup is used in the event of a backout or rollback of the software release.

Procedure 7: Full Database Backup

Step	Procedure	Result
1. <input type="checkbox"/>	Using the VIP address, access the primary NOAMP GUI as specified in Appendix A .	
2. <input type="checkbox"/>	Active NOAMP VIP: Navigate to Main Menu → Status & Manage → Database	
3. <input type="checkbox"/>	Active NOAMP VIP: Record the names of all servers.	Using the information provided in Section 3.1.2 (<i>Logins, Passwords and Site Information</i>) record the names of all servers to the Servers Worksheet in Appendix C.2 (print or photocopy additional pages if necessary to accommodate your number of Network Elements). NOTE: The full backup on every server can be done from the NOAMP GUI.

Step	Procedure	Result																																																									
4. <input type="checkbox"/>	<p>Active NOAMP VIP: Navigate to Main Menu → Administration → Software Management → Upgrade Backup the COMCOL run environment</p>	<p>Main Menu: Administration -> Software Management -> Upgrade</p>  <table border="1"> <thead> <tr> <th>Hostname</th> <th>Upgrade State</th> <th>OAM HA Role</th> <th>Server Role</th> <th>Function</th> <th>Application Version</th> <th>Start Time</th> <th>Finish Time</th> </tr> <tr> <th>Server Status</th> <th>Appl HA Role</th> <th colspan="3">Network Element</th> <th>Upgrade ISO</th> <th colspan="2">Status Message</th> </tr> </thead> <tbody> <tr> <td>OCUDR-A</td> <td>Backup Needed</td> <td>Active</td> <td>Network OAM&P</td> <td>OAM&P</td> <td>12.4.0.0-0-16.14.0</td> <td></td> <td></td> </tr> <tr> <td></td> <td>Err</td> <td>N/A</td> <td colspan="3">Site1_NE_NO</td> <td></td> <td></td> </tr> <tr> <td>OCUDR-B</td> <td>Backup Needed</td> <td>Standby</td> <td>Network OAM&P</td> <td>OAM&P</td> <td>12.4.0.0-0-16.14.0</td> <td></td> <td></td> </tr> <tr> <td></td> <td>Err</td> <td>N/A</td> <td colspan="3">Site1_NE_NO</td> <td></td> <td></td> </tr> </tbody> </table>	Hostname	Upgrade State	OAM HA Role	Server Role	Function	Application Version	Start Time	Finish Time	Server Status	Appl HA Role	Network Element			Upgrade ISO	Status Message		OCUDR-A	Backup Needed	Active	Network OAM&P	OAM&P	12.4.0.0-0-16.14.0				Err	N/A	Site1_NE_NO					OCUDR-B	Backup Needed	Standby	Network OAM&P	OAM&P	12.4.0.0-0-16.14.0				Err	N/A	Site1_NE_NO													
Hostname	Upgrade State	OAM HA Role	Server Role	Function	Application Version	Start Time	Finish Time																																																				
Server Status	Appl HA Role	Network Element			Upgrade ISO	Status Message																																																					
OCUDR-A	Backup Needed	Active	Network OAM&P	OAM&P	12.4.0.0-0-16.14.0																																																						
	Err	N/A	Site1_NE_NO																																																								
OCUDR-B	Backup Needed	Standby	Network OAM&P	OAM&P	12.4.0.0-0-16.14.0																																																						
	Err	N/A	Site1_NE_NO																																																								
5. <input type="checkbox"/>	<p>Active NOAMP VIP: Click Backup All at left bottom of the screen; the full backups begin. After clicking backup, an additional screen opens. Default is to exclude the database parts. If the database parts are included, then the backup takes longer and produce larger backup files in /var/TKLC/db/file_mgmt. They are not required for a full backup. Click OK to begin the backup.</p>	<p>Main Menu: Administration -> Software Management -> Upgrade</p>  <table border="1"> <thead> <tr> <th>Hostname</th> <th>Upgrade State</th> <th>OAM HA Role</th> <th>Server Role</th> <th>Function</th> <th>Application Version</th> <th>Start Time</th> <th>Finish Time</th> </tr> <tr> <th>Server Status</th> <th>Appl HA Role</th> <th colspan="3">Network Element</th> <th>Upgrade ISO</th> <th colspan="2">Status Message</th> </tr> </thead> <tbody> <tr> <td>OCUDR-A</td> <td>Backup Needed</td> <td>Active</td> <td>Network OAM&P</td> <td>OAM&P</td> <td>12.4.0.0-0-16.14.0</td> <td></td> <td></td> </tr> <tr> <td></td> <td>Err</td> <td>N/A</td> <td colspan="3">Site1_NE_NO</td> <td></td> <td></td> </tr> <tr> <td>OCUDR-B</td> <td>Backup Needed</td> <td>Standby</td> <td>Network OAM&P</td> <td>OAM&P</td> <td>12.4.0.0-0-16.14.0</td> <td></td> <td></td> </tr> <tr> <td></td> <td>Err</td> <td>N/A</td> <td colspan="3">Site1_NE_NO</td> <td></td> <td></td> </tr> </tbody> </table> <p>Backup Backup All Checkup Checkup All Upgrade Server Accept Report Report All</p> <table border="1"> <thead> <tr> <th>Network element</th> <th>Action</th> <th>Server(s) in the proper state for backup</th> </tr> </thead> <tbody> <tr> <td>Site1_NE_NO</td> <td><input checked="" type="checkbox"/> Back up</td> <td>OCUDR-A OCUDR-B</td> </tr> <tr> <td>Site2_NE_DR_NO</td> <td><input checked="" type="checkbox"/> Back up</td> <td>DR-OCUDR-A DR-OCUDR-B</td> </tr> </tbody> </table> <p>Full backup options</p> <p>Database parts exclusion <input checked="" type="radio"/> Exclude <input type="radio"/> Do not exclude</p> <p>Select "Exclude" to perform a full backup of the COMCOL run environment, excluding the /db/filemgmt. Select "Do not exclude" to perform a full backup of the COMCOL run environment without /db/filemgmt.</p> <p>Ok Cancel</p>	Hostname	Upgrade State	OAM HA Role	Server Role	Function	Application Version	Start Time	Finish Time	Server Status	Appl HA Role	Network Element			Upgrade ISO	Status Message		OCUDR-A	Backup Needed	Active	Network OAM&P	OAM&P	12.4.0.0-0-16.14.0				Err	N/A	Site1_NE_NO					OCUDR-B	Backup Needed	Standby	Network OAM&P	OAM&P	12.4.0.0-0-16.14.0				Err	N/A	Site1_NE_NO					Network element	Action	Server(s) in the proper state for backup	Site1_NE_NO	<input checked="" type="checkbox"/> Back up	OCUDR-A OCUDR-B	Site2_NE_DR_NO	<input checked="" type="checkbox"/> Back up	DR-OCUDR-A DR-OCUDR-B
Hostname	Upgrade State	OAM HA Role	Server Role	Function	Application Version	Start Time	Finish Time																																																				
Server Status	Appl HA Role	Network Element			Upgrade ISO	Status Message																																																					
OCUDR-A	Backup Needed	Active	Network OAM&P	OAM&P	12.4.0.0-0-16.14.0																																																						
	Err	N/A	Site1_NE_NO																																																								
OCUDR-B	Backup Needed	Standby	Network OAM&P	OAM&P	12.4.0.0-0-16.14.0																																																						
	Err	N/A	Site1_NE_NO																																																								
Network element	Action	Server(s) in the proper state for backup																																																									
Site1_NE_NO	<input checked="" type="checkbox"/> Back up	OCUDR-A OCUDR-B																																																									
Site2_NE_DR_NO	<input checked="" type="checkbox"/> Back up	DR-OCUDR-A DR-OCUDR-B																																																									

Step	Procedure	Result
6. <input type="checkbox"/>	<p>Active NOAMP VIP: The Server Status indicates Backup in Progress</p> <p>The progress of the full backups can be viewed in the Tasks box, as well as from the Status & Manage->Tasks->Active Tasks screen.</p> <p>As each full backup completes, its task updates to indicate its success or failure.</p> <p>When all full backup tasks finish successfully, this procedure is complete.</p>	  
7. <input type="checkbox"/>	<p>Active NOAMP VIP: Navigate to Main Menu → Administration → Software Management → Upgrade</p> <p>Click Tasks dropdown.</p>	 <p>When complete, Progress should display 100%.</p>
8. <input type="checkbox"/>	Mark the backup of the server as complete.	Reference the Servers Worksheet in Appendix C.2 and check off the server which just completed backup.
THIS PROCEDURE HAS BEEN COMPLETED		



4.2.3 Major Upgrade DR NOAMP NE

This procedure details how to perform major upgrades for DR NOAMP server to various possible upgrade paths.

NOTE: Ensure you are on latest patch before upgrading from Release 12.2 to 12.5.1.

Procedure 8: Major Upgrade DR NOAMP NE

Step	Procedure	Result
1. <input type="checkbox"/>	Using the VIP address, access the primary NOAMP GUI.	Access the primary NOAMP GUI as specified in Appendix A .
2. <input type="checkbox"/>	Active NOAMP VIP: Navigate to Main Menu → Status & Manage → Database	<p>Main Menu: Status & Manage -> Database</p>
3. <input type="checkbox"/>	Record the name of the DR NOAMP Network Element in the space provided to the right.	Using the information provided in Section 3.1.2 (<i>Logins, Passwords and Site Information</i>) record the name of the DRNOAMP Network Element in the space provided below: DR NOAMP Network Element: _____

Step	Procedure	Result
4. <input type="checkbox"/>	Active NOAMP VIP: From the Network Element filter list, select the NE name for the DR NOAMP.	
5. <input type="checkbox"/>	Active NOAMP VIP: Click Go .	
6. <input type="checkbox"/>	Active NOAMP VIP: The list of servers associated with DR NOAMP Network Element displays.	 <p>Identify each server and its associated Role and HA Role.</p>
7. <input type="checkbox"/>	Active NOAMP VIP: Record the server names appropriately in the space provided to the right.	Identify the DR NOAMP server names and record them in the space provided below: Spare NOAMP Server: _____ Spare NOAMP Server: _____



Step	Procedure	Result
NOTE: For Step 8 of this Procedure, select one spare DR NOAMP.		
*** Verify the Databases are in sync using Appendix E before upgrading each spare server.		
8. <input type="checkbox"/>	Active NOAMP VIP: Upgrade server for the first spare DR NOAMP server.	Upgrade server for the first spare DR NOAMP server(identified in Step 7 of this Procedure) as specified in Appendix C.1 Upgrade Server
9. <input type="checkbox"/>	Active NOAMP VIP: Upgrade server for the second spare DR NOAMP server.	Upgrade server for the second spare DR NOAMP server(identified in Step 7 of this Procedure) as specified in Appendix C.1 Upgrade Server
THIS PROCEDURE HAS BEEN COMPLETED		

4.2.4 Incremental Upgrade DR NOAMP NE

Procedure 9: Incremental Upgrade DR NOAMP NE

Step	Procedure	Result																																																							
1. <input type="checkbox"/>	Using the VIP address, access the primary NOAMP GUI as specified in Appendix A .																																																								
2. <input type="checkbox"/>	Active NOAMP VIP: Navigate to Main Menu → Status & Manage → Database	<p>Main Menu: Status & Manage → Database</p> <thead> <tr> <th>Network Element</th> <th>Server</th> <th>Role</th> <th>OAM Max HA Role</th> <th>Application Max HA Role</th> <th>Status</th> <th>DB Level</th> <th>OAM Repl Status</th> <th>SIG Repl Status</th> <th>Repl Status</th> <th>Repl Audit Status</th> </tr> </thead> <tbody> <tr> <td>Site2_NE_DR_NO</td> <td>DR-OCUDR-B</td> <td>Network OAM&P</td> <td>Spare</td> <td>N/A</td> <td>Normal</td> <td>0</td> <td>Normal</td> <td>NotApplicable</td> <td>Allowed</td> <td>NotApplicable</td> </tr> <tr> <td>Site1_NE_NO</td> <td>OCUDR-A</td> <td>Network OAM&P</td> <td>Active</td> <td>N/A</td> <td>Normal</td> <td>0</td> <td>Normal</td> <td>NotApplicable</td> <td>Allowed</td> <td>NotApplicable</td> </tr> <tr> <td>Site1_NE_NO</td> <td>OCUDR-B</td> <td>Network OAM&P</td> <td>Standby</td> <td>N/A</td> <td>Normal</td> <td>0</td> <td>Normal</td> <td>NotApplicable</td> <td>Allowed</td> <td>NotApplicable</td> </tr> <tr> <td>Site2_NE_DR_NO</td> <td>DR-OCUDR-A</td> <td>Network OAM&P</td> <td>Spare</td> <td>N/A</td> <td>Normal</td> <td>0</td> <td>Normal</td> <td>NotApplicable</td> <td>Allowed</td> <td>NotApplicable</td> </tr> </tbody>	Network Element	Server	Role	OAM Max HA Role	Application Max HA Role	Status	DB Level	OAM Repl Status	SIG Repl Status	Repl Status	Repl Audit Status	Site2_NE_DR_NO	DR-OCUDR-B	Network OAM&P	Spare	N/A	Normal	0	Normal	NotApplicable	Allowed	NotApplicable	Site1_NE_NO	OCUDR-A	Network OAM&P	Active	N/A	Normal	0	Normal	NotApplicable	Allowed	NotApplicable	Site1_NE_NO	OCUDR-B	Network OAM&P	Standby	N/A	Normal	0	Normal	NotApplicable	Allowed	NotApplicable	Site2_NE_DR_NO	DR-OCUDR-A	Network OAM&P	Spare	N/A	Normal	0	Normal	NotApplicable	Allowed	NotApplicable
Network Element	Server	Role	OAM Max HA Role	Application Max HA Role	Status	DB Level	OAM Repl Status	SIG Repl Status	Repl Status	Repl Audit Status																																															
Site2_NE_DR_NO	DR-OCUDR-B	Network OAM&P	Spare	N/A	Normal	0	Normal	NotApplicable	Allowed	NotApplicable																																															
Site1_NE_NO	OCUDR-A	Network OAM&P	Active	N/A	Normal	0	Normal	NotApplicable	Allowed	NotApplicable																																															
Site1_NE_NO	OCUDR-B	Network OAM&P	Standby	N/A	Normal	0	Normal	NotApplicable	Allowed	NotApplicable																																															
Site2_NE_DR_NO	DR-OCUDR-A	Network OAM&P	Spare	N/A	Normal	0	Normal	NotApplicable	Allowed	NotApplicable																																															

| 3. | Record the name of the DR NOAMP Network Element in the space provided to the right. | Using the information provided in Section 3.1.2 (*Logins, Passwords and Site Information*) record the name of the DRNOAMP Network Element in the space provided below: DR NOAMP Network Element: _____ |

Step	Procedure	Result
4. <input type="checkbox"/>	Active NOAMP VIP: From the Network Element filter list, select the NE name for the DR NOAMP.	
5. <input type="checkbox"/>	Active NOAMP VIP: Click Go .	
6. <input type="checkbox"/>	Active NOAMP VIP: The list of servers associated with DR NOAMP Network Element displays.	 <p>Identify each server and its associated Role and HA Role.</p>
7. <input type="checkbox"/>	Active NOAMP VIP: Record the server names appropriately in the space provided to the right.	Identify the DR NOAMP server names and record them in the space provided below: Spare NOAMP Server: _____ Spare NOAMP Server: _____
NOTE: For Step 8 of this Procedure, select one spare DR NOAMP. *** Verify the Databases are in sync using Appendix E before upgrading each spare server.		

Step	Procedure	Result
8. <input type="checkbox"/>	Active NOAMP VIP: Upgrade server for the first spare DR NOAMP server.	Upgrade server for the first spare DR NOAMP server (identified in Step 7 of this Procedure) as specified in Appendix C.1 Upgrade Server
9. <input type="checkbox"/>	Active NOAMP VIP: Upgrade server for the second spare DR NOAMP server.	Upgrade server for the second spare DR NOAMP server (identified in Step 7 of this Procedure) as specified in Appendix C.1 Upgrade Server
THIS PROCEDURE HAS BEEN COMPLETED		



4.2.5 Major Upgrade Primary NOAMP NE

This procedure details how to perform major upgrades for primary NOAMP server to various possible upgrade paths.

NOTE: Ensure you are on latest patch before upgrading from Release 12.4 to 12.5.

Procedure 10: Major Upgrade Primary NOAMP NE

Step	Procedure	Result																																																							
1. <input type="checkbox"/>	Using the VIP address, access the primary NOAMP GUI as specified in Appendix A .																																																								
2. <input type="checkbox"/>	Active NOAMP VIP: Navigate to Main Menu → Status & Manage → Database	<p>Main Menu: Status & Manage -> Database</p> <table border="1"> <thead> <tr> <th>Network Element</th> <th>Server</th> <th>Role</th> <th>OAM Max HA Role</th> <th>Application Max HA Role</th> <th>Status</th> <th>DB Level</th> <th>OAM Repl Status</th> <th>S10 Repl Status</th> <th>Repl Status</th> <th>Repl Audit Status</th> </tr> </thead> <tbody> <tr> <td>Site2_NE_DR_NO</td> <td>DR-OCUDR-B</td> <td>Network OAM&P</td> <td>Spare</td> <td>N/A</td> <td>Normal</td> <td>0</td> <td>Normal</td> <td>NotApplicable</td> <td>Allowed</td> <td>NotApplicable</td> </tr> <tr> <td>Site1_NE_NO</td> <td>OCUDR-A</td> <td>Network OAM&P</td> <td>Active</td> <td>N/A</td> <td>Normal</td> <td>0</td> <td>Normal</td> <td>NotApplicable</td> <td>Allowed</td> <td>NotApplicable</td> </tr> <tr> <td>Site1_NE_NO</td> <td>OCUDR-B</td> <td>Network OAM&P</td> <td>Standby</td> <td>N/A</td> <td>Normal</td> <td>0</td> <td>Normal</td> <td>NotApplicable</td> <td>Allowed</td> <td>NotApplicable</td> </tr> <tr> <td>Site2_NE_DR_NO</td> <td>DR-OCUDR-A</td> <td>Network OAM&P</td> <td>Spare</td> <td>N/A</td> <td>Normal</td> <td>0</td> <td>Normal</td> <td>NotApplicable</td> <td>Allowed</td> <td>NotApplicable</td> </tr> </tbody> </table>	Network Element	Server	Role	OAM Max HA Role	Application Max HA Role	Status	DB Level	OAM Repl Status	S10 Repl Status	Repl Status	Repl Audit Status	Site2_NE_DR_NO	DR-OCUDR-B	Network OAM&P	Spare	N/A	Normal	0	Normal	NotApplicable	Allowed	NotApplicable	Site1_NE_NO	OCUDR-A	Network OAM&P	Active	N/A	Normal	0	Normal	NotApplicable	Allowed	NotApplicable	Site1_NE_NO	OCUDR-B	Network OAM&P	Standby	N/A	Normal	0	Normal	NotApplicable	Allowed	NotApplicable	Site2_NE_DR_NO	DR-OCUDR-A	Network OAM&P	Spare	N/A	Normal	0	Normal	NotApplicable	Allowed	NotApplicable
Network Element	Server	Role	OAM Max HA Role	Application Max HA Role	Status	DB Level	OAM Repl Status	S10 Repl Status	Repl Status	Repl Audit Status																																															
Site2_NE_DR_NO	DR-OCUDR-B	Network OAM&P	Spare	N/A	Normal	0	Normal	NotApplicable	Allowed	NotApplicable																																															
Site1_NE_NO	OCUDR-A	Network OAM&P	Active	N/A	Normal	0	Normal	NotApplicable	Allowed	NotApplicable																																															
Site1_NE_NO	OCUDR-B	Network OAM&P	Standby	N/A	Normal	0	Normal	NotApplicable	Allowed	NotApplicable																																															
Site2_NE_DR_NO	DR-OCUDR-A	Network OAM&P	Spare	N/A	Normal	0	Normal	NotApplicable	Allowed	NotApplicable																																															
3. <input type="checkbox"/>	Record the name of the primary NOAMP Network Element in the space provided to the right.	Using the information provided in Section 3.1.2 (<i>Logins, Passwords and Site Information</i>) record the name of the primary NOAMP Network Element in the space provided below: Primary NOAMP Network Element: _____																																																							



Step	Procedure	Result
4. <input type="checkbox"/>	Active NOAMP VIP: From the Network Element filter list, select the Network Element name for the primary NOAMP.	
5. <input type="checkbox"/>	Active NOAMP VIP: Click Go located on the right end of the filter bar.	
6. <input type="checkbox"/>	Active NOAMP VIP: The list of servers associated with the primary NOAMP Network Element displays. Identify each server and the associated Role and HA Role.	
7. <input type="checkbox"/>	Active NOAMP VIP: Record the server names appropriately in the space provided to the right.	Identify the primary NOAMP server names and record them in the space provided below: Standby NOAMP: _____ Active NOAMP: _____
NOTE: Steps 8 through 10 must be performed on an active NOAMP if upgrade is being done from 12.1.0.0.0-13.8.0 to 12.5		



Step	Procedure	Result
8. <input type="checkbox"/>	Active NOAMP Server: Access the command prompt and login into the active NOAMP server as admusr user	<pre>login as: admusr root@10.250.xx.yy's password:<admusr_password> Last login: Mon Jul 30 10:33:19 2012 from 10.250.80.199 [root@pc9040833-no-a ~]#</pre>
9. <input type="checkbox"/>	Active NOAMP Server: Switch to root user.	<pre>[admusr@ pc9040833-no-a ~]\$ su - password: <root_password></pre>
10. <input type="checkbox"/>	Active NOAMP Server: NOTE: Subscription Flags are set to a random value before upgrade, you must manually reset the flags.	Run the <code>iset</code> command using the console for the active NOAMP. <pre># iset -fflags=0 Subscription where "1=1"</pre>
11. <input type="checkbox"/>	Active NOAMP Server: Performing workarounds for known bugs	Refer to the Oracle Communications UDR 12.5 Release Notes document for known customer bugs, evaluate for applicability and perform the workarounds as documented.
NOTE: Step 12 is for the STANDBY NOAMP ONLY.		
12. <input type="checkbox"/>	Active NOAMP VIP: Upgrade server for the standby NOAMP server.	Upgrade server for the standby NOAMP server (identified in Step 7 of this Procedure) as specified in Appendix C.1 Upgrade Server
		!! WARNING !! STEP 12 MUST BE COMPLETED BEFORE CONTINUING ON TO STEP 13. *** Verify the Databases are in sync using Appendix E before upgrading the active server
13. <input type="checkbox"/>	Active NOAMP VIP: Upgrade server for the active NOAMP server.	Upgrade server for the active NOAMP server (identified in Step 7 of this Procedure) as specified in Appendix C.1 Upgrade Server.

Step	Procedure	Result
THIS PROCEDURE HAS BEEN COMPLETED		

4.2.6 Incremental Upgrade Primary NOAMP NE

Procedure 11: Incremental Upgrade Primary NOAMP NE

Step	Procedure	Result
1. <input type="checkbox"/>	Using the VIP address, access the primary NOAMP GUI as specified in Appendix A .	
2. <input type="checkbox"/>	Active NOAMP VIP: Navigate to Main Menu → Status & Manage → Database	
3. <input type="checkbox"/>	Record the name of the primary NOAMP Network Element in the space provided to the right. Using the information provided in Section 3.1.2 (Logins, Passwords and Site Information) record the name of the primary NOAMP Network Element in the space provided below: Primary NOAMP Network Element: _____	
4. <input type="checkbox"/>	Active NOAMP VIP: From the Network Element filter list, select the Network Element name for the primary NOAMP.	

Step	Procedure	Result
5. <input type="checkbox"/>	Active NOAMP VIP: Click Go located on the right end of the filter bar.	
6. <input type="checkbox"/>	Active NOAMP VIP: The list of servers associated with the primary NOAMP Network Element displays. Identify each server and its associated Role and HA Role.	
7. <input type="checkbox"/>	Active NOAMP VIP: Record the server names appropriately in the space provided to the right.	Identify the primary NOAMP server names and record them in the space provided below: Standby NOAMP: _____ Active NOAMP: _____
NOTE: Step 8 is for the STANDBY NOAMP ONLY.		
8. <input type="checkbox"/>	Active NOAMP VIP: Upgrade server for the standby NOAMP server(identified in Step 7 of this Procedure) as specified in Appendix C.1 Upgrade Server	
		!! WARNING !! STEP 8 MUST BE COMPLETED BEFORE CONTINUING ON TO STEP 9. *** Verify the Databases are in sync using Appendix E before upgrading the active server
9. <input type="checkbox"/>	Active NOAMP VIP: Upgrade server for the active NOAMP server (identified in Step 7 of this Procedure) as specified in Appendix C.1 Upgrade Server.	
THIS PROCEDURE HAS BEEN COMPLETED		

4.3 Perform Health Check (Post Primary NOAMP/DR NOAMP Upgrade)

Procedure 12: Health Check (Post Primary NOAMP/DR NOAMP Upgrade)

1. <input type="checkbox"/>	This procedure is part of software upgrade preparation and is used to determine the health and status of the Oracle Communications User Data Repository network and servers. Perform Health Check procedures as specified in Appendix B .
-----------------------------	---


Chapter 5. Single server upgrade






A 1-RMS server configuration is used for lab setup and virtualization demonstration only. This configuration does not support HA and is not intended for production network. This one server lab RMS supports the ability to perform and upgrade which allows all configuration data and database records to be carried forward to the next release.

5.1 Upgrading a Single Server

This procedure is for upgrading a one server Lab RMS only.

Procedure 13: Upgrade Single Server

Step	Procedure	Result
1. <input type="checkbox"/>	Identify NOAMP IP Address	Identify IP Address of the single NOAMP server to be upgraded.
2. <input type="checkbox"/>	Server IMI IP (SSH): SSH to server and login as root user	Use your SSH client to connect to the server (ex. ssh, putty): <code>ssh<server address></code> <code>login as: admusr</code> <code>password: <enter password></code> <code>Switch to root su -</code> <code>password: <enter password></code>
3. <input type="checkbox"/>	Open the platcfg tool	<code>su - platcfg</code>
4. <input type="checkbox"/> <input checked="" type="checkbox"/>	Exit /var/TKLC/db/filemgmt directory on server to be upgraded	Verify that there is not a user in the <code>/var/TKLC/db/filemgmt</code> directory
5. <input type="checkbox"/>	Select Maintenance and press Enter	

Step	Procedure	Result
6. <input type="checkbox"/>	Select Upgrade and press Enter	
7. <input type="checkbox"/>	<p>Validate the Media by selecting Validate Media and pressing Enter</p> <p>Select the proper iso for the upgrade</p>	 
8. <input type="checkbox"/>	Select Early Upgrade Checks and press Enter .	
9. <input type="checkbox"/>	<p>Start the upgrade by selecting Initiate Upgrade and pressing Enter.</p> <p>Wait for Upgrade to complete anywhere from 15 minutes to 1.5 hrs.</p>	

Step	Procedure	Result
10. <input type="checkbox"/>	Accept the upgrade	Accept upgrade as specified in Procedure 15:Accept Upgrade.
THIS PROCEDURE HAS BEEN COMPLETED		

Chapter 6. Upgrade Acceptance

The upgrade must be accepted or rejected before any subsequent upgrades are performed.

The Alarm 32532 (Server Upgrade Pending Accept/Reject) displays for each server until one of these two actions (accept or reject) is performed.

An upgrade is only accepted after it is determined to be successful because the accept action is final. This frees up file storage but prevents a backout from the previous upgrade.



6.1 Accept Upgrade


NOTE: After the upgrade is accepted for a server, that server is not allowed to backout to previous release from which the upgrade was done

This procedure details how to accept a successful upgrade of Oracle Communications User Data Repository system.

Procedure 14: Accept Upgrade

Step	Procedure	Result																																																							
1. <input type="checkbox"/>	Using the VIP IP, access the primary NOAMP GUI as specified in Appendix A.																																																								
2. <input type="checkbox"/>	Active NOAMP VIP: Navigate to Main Menu → Administration → Software Management → Upgrade	<p>Main Menu: Administration -> Software Management -> Upgrade</p> <p>Filter* Tasks*</p> <table border="1"> <thead> <tr> <th>NO_SG</th> <th>SO_SG</th> <th>Hostname</th> <th>Upgrade State</th> <th>OAM HA Role</th> <th>Server Role</th> <th>Function</th> <th>Application Version</th> <th>Start Time</th> <th>Finish Time</th> <th>Status Message</th> </tr> </thead> <tbody> <tr> <td></td> <td></td> <td>BL908050101-no-a</td> <td>Accept or Reject</td> <td>Active</td> <td>Network OAM&P</td> <td>OAM&P</td> <td>12.4.0.0.0-16.14.0</td> <td>2018-02-13 04:40:45 EST</td> <td>2018-02-13 04:55:05 EST</td> <td>Success: Server upgrade is complete</td> </tr> <tr> <td></td> <td></td> <td>BL908050103-no-b</td> <td>Accept or Reject</td> <td>Standby</td> <td>Network OAM&P</td> <td>OAM&P</td> <td>12.4.0.0.0-16.14.0</td> <td>2018-02-13 05:04:10 EST</td> <td>2018-02-13 05:21:02 EST</td> <td>Success: Server upgrade is complete</td> </tr> <tr> <td></td> <td></td> <td></td> <td>Err</td> <td>N/A</td> <td></td> <td></td> <td>UDR-12.4.0.0.0_16.14.0-x86_64.iso</td> <td></td> <td></td> <td></td> </tr> <tr> <td></td> <td></td> <td></td> <td>Err</td> <td>N/A</td> <td></td> <td></td> <td>UDR-12.4.0.0.0_16.14.0-x86_64.iso</td> <td></td> <td></td> <td></td> </tr> </tbody> </table>	NO_SG	SO_SG	Hostname	Upgrade State	OAM HA Role	Server Role	Function	Application Version	Start Time	Finish Time	Status Message			BL908050101-no-a	Accept or Reject	Active	Network OAM&P	OAM&P	12.4.0.0.0-16.14.0	2018-02-13 04:40:45 EST	2018-02-13 04:55:05 EST	Success: Server upgrade is complete			BL908050103-no-b	Accept or Reject	Standby	Network OAM&P	OAM&P	12.4.0.0.0-16.14.0	2018-02-13 05:04:10 EST	2018-02-13 05:21:02 EST	Success: Server upgrade is complete				Err	N/A			UDR-12.4.0.0.0_16.14.0-x86_64.iso							Err	N/A			UDR-12.4.0.0.0_16.14.0-x86_64.iso			
NO_SG	SO_SG	Hostname	Upgrade State	OAM HA Role	Server Role	Function	Application Version	Start Time	Finish Time	Status Message																																															
		BL908050101-no-a	Accept or Reject	Active	Network OAM&P	OAM&P	12.4.0.0.0-16.14.0	2018-02-13 04:40:45 EST	2018-02-13 04:55:05 EST	Success: Server upgrade is complete																																															
		BL908050103-no-b	Accept or Reject	Standby	Network OAM&P	OAM&P	12.4.0.0.0-16.14.0	2018-02-13 05:04:10 EST	2018-02-13 05:21:02 EST	Success: Server upgrade is complete																																															
			Err	N/A			UDR-12.4.0.0.0_16.14.0-x86_64.iso																																																		
			Err	N/A			UDR-12.4.0.0.0_16.14.0-x86_64.iso																																																		

Step	Procedure	Result
3. <input type="checkbox"/>	Active NOAMP VIP (GUI): Accept upgrade for selected servers	<p>Accept upgrade of selected servers</p> <p>1. Select the server. 2. Click the Accept</p> <p>Main Menu: Administration > Software Management > Upgrade</p>  <p>A confirmation dialog warns that after the upgrade is accepted, the servers cannot be reverted back to their previous image states.</p> <p>3. Click OK</p> <p>The Upgrade Administration screen displays.</p> <p>An informational message indicates the servers where the upgrade was accepted.</p>
4. <input type="checkbox"/>	Active NOAMP VIP: Accept upgrade of the rest of the system	<p>Accept Upgrade on all remaining servers in the Oracle Communications User Data Repository system:</p> <p>Repeat all sub-steps of step 3 of this procedure on remaining servers until the upgrade of all servers in the Oracle Communications User Data Repository system has been accepted.</p> <p>NOTE: As the upgrade is accepted on each server the corresponding Alarm ID 32532 (Server Upgrade Pending Accept/Reject) is removed.</p>
5. <input type="checkbox"/>	Active NOAMP VIP: Verify accept	<p>Check that alarms are removed:</p> <p>Navigate to Alarms & Events → View Active</p> <p>Main Menu: Alarms & Events -> View Active</p>  <p>Verify that Alarm ID 32532 (Server Upgrade Pending Accept/Reject) is not displayed under active alarms on Oracle Communications User Data Repository system</p>
6. <input type="checkbox"/>	Active NOAMP VIP:	Verify server status is Backup Needed.

Step	Procedure	Result
	<p>Main Menu → Administration → Software Management → Upgrade</p>	<p>Main Menu: Administration -> Software Management -> Upgrade</p> 
7. <input type="checkbox"/>	<p>Active NOAMP VIP: Configure services</p>	<p>Run the procedure specified in Appendix I: Configuring Services for Dual Path HA.</p>
THIS PROCEDURE HAS BEEN COMPLETED		

Chapter 7. TVOE Performance tuning

This script is necessary because it can be modified by the build. By making this script part of the upgrade, it is ensuring that new changes and tuning are applied after the upgrade is complete.

NOTE: This procedure does not apply to Oracle Communications User Data Repository Cloud based systems.

Procedure 15: TVOE Performance Tuning

Step	Procedure	Result
1. <input type="checkbox"/>	NOAMP: Transfer file to TVOE host	<p>Login to NOAMP and transfer file to TVOE HOST</p> <pre># scp /var/TKLC/db/filemgmt/udrInitConfig.sh \ admusr@<tvoe_host_name>:/var/tmp admusr@<tvoe_host_name>'s password:<admusr_password></pre> <p>If an error message such as <code>scp: /var/tmp/udrInitConfig.sh: Permission denied</code> displays, delete the old file from TVOE or copy the old file with a new name such as <code>udrInitConfig_1.sh</code> and attempt the transfer again.</p>
2. <input type="checkbox"/>	Login to TVOE host: 1.SSH to server. 2.Log into the server as the admusr user.	<pre># ssh admusr@<tvoe_host_name> admusr@<tvoe_host_name>'s password:<admusr_password></pre>
3. <input type="checkbox"/>	TVOE host: Switch to root user.	<pre>[admusr@hostname1326744539 ~]\$ su - password: <root_password></pre>
4. <input type="checkbox"/>	TVOE host: Change directory.	<pre># cd /var/tmp</pre>
5. <input type="checkbox"/>	TVOE host: Update script permissions.	<pre># chmod 555 udrInitConfig.sh</pre>
6. <input type="checkbox"/>	TVOE host: Run configuration script as root	<pre># ./udrInitConfig.sh</pre> <p>Verify that failures are not reported. A trace to display the settings for all VM Guests on this server are listed in the output.</p> <p>If a failure occurs, save the log file <code>/var/TKLC/log/udrVMCfg/udrInitConfig.log</code> and contact My Oracle Support (Appendix J) for assistance.</p>

Step	Procedure	Result
7. <input type="checkbox"/>	TVOE host: Reboot the server.	<pre># init 6</pre> <p>NOTE: Rebooting the TVOE host brings down the Oracle Communications User Data Repository servers running there. Be advised that this operation can affect traffic processing and HA status of related Oracle Communications User Data Repository servers in the network.</p>
THIS PROCEDURE HAS BEEN COMPLETED		

Chapter 8. Recovery Procedures

Upgrade procedure recovery issues are directed to the My Oracle Support (Appendix J). Persons performing the upgrade are familiar with these documents.

Recovery procedures are covered under the Disaster Recovery Guide. Perform this procedure only if there is a problem and it is required to revert back to the pre-upgrade version of the software.



!! WARNING !! Do not attempt to perform these backout procedures without first contacting the My Oracle Support. Refer to Appendix J.



!! WARNING !! Backout procedures cause traffic loss.

NOTES: These recovery procedures are provided for the backout of an upgrade only. (that is, for the backout from a failed target release to the previously installed release).
Backout of an initial installation is not supported.

8.1 Order of Backout

The following list displays the order to backout the servers (primary and DR sites):

1. DR NOAMPs (spares)
2. Primary standby NOAMP
3. Primary active NOAMP
4. TVOE and/or PM&C (if necessary, if upgraded as part of this procedure)

8.2 Backout Setup

Identify IP addresses of all servers that need to be backed out.

1. Select **Administration** → **Software Management** → **Upgrade**
2. Based on the Application Version column, identify all the hostnames that need to be backed out.
3. Select **Configuration** → **Servers**
4. Identify the IMI IP addresses of all the hostnames identified in step 2. These addresses are required to access the server when performing the backout.

The reason to perform a backout has a direct impact on any additional backout preparation that must be done. The backout procedure causes traffic loss.

NOTE: Verify that the two backup archive files created using the procedure in 4.2.2 Full Database Backup (All Network Elements, All Servers) are present on every server that is to be backed-out.

These archive files are located in the `/var/TKLC/db/filemgmt` directory and have different filenames than other database backup files.



The filenames have the format:

- `Backup.<application>.<server>.FullDBParts.<role>.<date_time>.UPG.tar.bz2`
- `Backup.<application>.<server>.FullRunEnv.<role>.<date_time>.UPG.tar.bz2`

8.3 Backout of DR NOAMP NE

Procedure 16: Backout of DR NOAMP NE

Step	Procedure	Result																																			
1. <input type="checkbox"/>	Using the VIP address, access the primary NOAMP GUI.	Access the primary NOAMP GUI as specified in Appendix A.																																			
2. <input type="checkbox"/>	Active NOAMP VIP: Navigate to Main Menu → Status & Manage → Network Elements	<p>Main Menu: Status & Manage -> Network Elements</p> <p>Filter* ▾</p> <table border="1"> <thead> <tr> <th>Network Element Name</th> <th>Customer Router Monitoring</th> </tr> </thead> <tbody> <tr> <td>Site1_NE_NO</td> <td>Disabled</td> </tr> <tr> <td>Site2_NE_DR_NO</td> <td>Disabled</td> </tr> </tbody> </table>	Network Element Name	Customer Router Monitoring	Site1_NE_NO	Disabled	Site2_NE_DR_NO	Disabled																													
Network Element Name	Customer Router Monitoring																																				
Site1_NE_NO	Disabled																																				
Site2_NE_DR_NO	Disabled																																				
3. <input type="checkbox"/>	Record the name of the DR NOAMP NE to be backed out in the space provided to the right.	Record the name of the DR NOAMP NE to be backed out. DR NOAMP NE: _____																																			
4. <input type="checkbox"/>	Active NOAMP VIP: Navigate to Main Menu → Status & Manage → Server	<p>Main Menu: Status & Manage -> Server</p> <p>Filter* ▾</p> <table border="1"> <thead> <tr> <th>Server Hostname</th> <th>Network Element</th> <th>Appl State</th> <th>Aim</th> <th>DB</th> <th>Reporting Status</th> <th>Proc</th> </tr> </thead> <tbody> <tr> <td>DR-OCUDR-A</td> <td>Site2_NE_DR_NO</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>DR-OCUDR-B</td> <td>Site2_NE_DR_NO</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>OCUDR-A</td> <td>Site1_NE_NO</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>OCUDR-B</td> <td>Site1_NE_NO</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> </tbody> </table>	Server Hostname	Network Element	Appl State	Aim	DB	Reporting Status	Proc	DR-OCUDR-A	Site2_NE_DR_NO	Enabled	Err	Norm	Norm	Norm	DR-OCUDR-B	Site2_NE_DR_NO	Enabled	Err	Norm	Norm	Norm	OCUDR-A	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm	OCUDR-B	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm
Server Hostname	Network Element	Appl State	Aim	DB	Reporting Status	Proc																															
DR-OCUDR-A	Site2_NE_DR_NO	Enabled	Err	Norm	Norm	Norm																															
DR-OCUDR-B	Site2_NE_DR_NO	Enabled	Err	Norm	Norm	Norm																															
OCUDR-A	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm																															
OCUDR-B	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm																															

Step	Procedure	Result
5. <input type="checkbox"/>	Active NOAMP VIP: 3. From the Status & Manage → Server filter list, select the name for the DR NOAMP NE. 4. Click Go .	
6. <input type="checkbox"/>	Active NOAMP VIP: The list of servers associated with the DR NOAMP NE displays. Identify each server hostname and its associated Reporting Status and Appl State.	
7. <input type="checkbox"/>	Using the list of servers associated with the DR NOAMP NE in Step 6, record the server names associated with the DR NOAMP NE.	Identify the DR NOAMP server names and record them in the space provided below: Standby DR NOAMP: _____ Active DR NOAMP: _____
8. <input type="checkbox"/>	Active NOAMP VIP: Perform Appendix D for the first spare-DR NOAMP server	Backout the target release for the spare DR NOAMP server as specified in Appendix D (Backout of a Server).

Step	Procedure	Result
9. <input type="checkbox"/>	Active NOAMP VIP: Perform Appendix D for the second spare—DR NOAMP server.	Backout the target release for the spare DR NOAMP Server as specified in Appendix D (Backout of a Server).
10. <input type="checkbox"/>	Active NOAMP VIP: Perform Health Check at this time only if all servers are backed out. Otherwise, proceed with the next backout	Perform Health Check procedures (Post Backout) as specified in Appendix B , if Backout procedures have been completed for all required servers.
THIS PROCEDURE HAS BEEN COMPLETED		

8.4 Backout of Primary NOAMP NE

Procedure 17: Backout of Primary NOAMP NE

Step	Procedure	Result								
1. <input type="checkbox"/>	Using the VIP address, access the primary NOAMP GUI.	Access the primary NOAMP GUI as specified in Appendix A.								
2. <input type="checkbox"/>	Active NOAMP VIP: Navigate to Main Menu → Status & Manage → Network Elements	<p>Main Menu: Status & Manage -> Network Elements</p> <table border="1"> <thead> <tr> <th colspan="2">Filter*</th> </tr> <tr> <th>Network Element Name</th> <th>Customer Router Monitoring</th> </tr> </thead> <tbody> <tr> <td>Site1_NE_NO</td> <td>Disabled</td> </tr> <tr> <td>Site2_NE_DR_NO</td> <td>Disabled</td> </tr> </tbody> </table>	Filter*		Network Element Name	Customer Router Monitoring	Site1_NE_NO	Disabled	Site2_NE_DR_NO	Disabled
Filter*										
Network Element Name	Customer Router Monitoring									
Site1_NE_NO	Disabled									
Site2_NE_DR_NO	Disabled									
3. <input type="checkbox"/>	Record the name of the NOAMP NE to be downgraded (backed out) in the space provided to the right.	Record the name of the primary NOAMP NE which is backed out. Primary NOAMP NE: _____								


Step	Procedure	Result																																			
4. <input type="checkbox"/>	Active NOAMP VIP: Navigate to Main Menu → Status & Manage → Server	<p>Main Menu: Status & Manage -> Server</p> <p>Filter* ▾</p> <table border="1"> <thead> <tr> <th>Server Hostname</th> <th>Network Element</th> <th>Appl State</th> <th>Alm</th> <th>DB</th> <th>Reporting Status</th> <th>Proc</th> </tr> </thead> <tbody> <tr> <td>DR-OCUDR-A</td> <td>Site2_NE_DR_NO</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>DR-OCUDR-B</td> <td>Site2_NE_DR_NO</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>OCUDR-A</td> <td>Site1_NE_NO</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>OCUDR-B</td> <td>Site1_NE_NO</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> </tbody> </table>	Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc	DR-OCUDR-A	Site2_NE_DR_NO	Enabled	Err	Norm	Norm	Norm	DR-OCUDR-B	Site2_NE_DR_NO	Enabled	Err	Norm	Norm	Norm	OCUDR-A	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm	OCUDR-B	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm
Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc																															
DR-OCUDR-A	Site2_NE_DR_NO	Enabled	Err	Norm	Norm	Norm																															
DR-OCUDR-B	Site2_NE_DR_NO	Enabled	Err	Norm	Norm	Norm																															
OCUDR-A	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm																															
OCUDR-B	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm																															
5. <input type="checkbox"/>	Active NOAMP VIP: 1. From the Status & Manage/ Server filter list, select the name for the primary NOAMP NE. 2. Click Go	<p>Filter</p> <p>Scope:</p> <p>Site1_NE_NO ▾ Server Group ▾ Reset</p> <p>Display Filter:</p> <p>None ▾ = ▾ Reset</p> <p>Go</p>																																			
6. <input type="checkbox"/>	Active NOAMP VIP: A list of servers associated with the primary NOAMP NE displays. Identify each server hostname and its associated Reporting Status and Appl State.	<p>Main Menu: Status & Manage -> Server (Filtered)</p> <p>Filter* ▾</p> <table border="1"> <thead> <tr> <th>Server Hostname</th> <th>Network Element</th> <th>Appl State</th> <th>Alm</th> <th>DB</th> <th>Reporting Status</th> <th>Proc</th> </tr> </thead> <tbody> <tr> <td>OCUDR-A</td> <td>Site1_NE_NO</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>OCUDR-B</td> <td>Site1_NE_NO</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> </tbody> </table>	Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc	OCUDR-A	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm	OCUDR-B	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm														
Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc																															
OCUDR-A	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm																															
OCUDR-B	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm																															
7. <input type="checkbox"/>	Using the list of servers associated with the primary NOAMP NE record the server names associated with the primary NOAMP NE.	Identify the primary NOAMP server names and record them in the space provided below: Standby Primary NOAMP: _____ Active Primary NOAMP: _____																																			

Step	Procedure	Result
8. <input type="checkbox"/>	Active NOAMP VIP: Perform Appendix D for the standby primary NOAMP server	Backout the target release for the standby primary NOAMP server as specified in Appendix D (Backout of a Server).
9. <input type="checkbox"/>	Active NOAMP VIP: Perform Appendix D for the active primary NOAMP server.	Backout the target release for the active primary NOAMP server as specified in Appendix D (Backout of a Server).
10. <input type="checkbox"/>	Active NOAMP VIP: Perform Health Check at this time only if all servers are backed out.	Perform Health Check procedures (Post Backout) as specified in Appendix B , if Backout procedures have been completed for all required servers.
11. <input type="checkbox"/>	Perform backout procedures for TVOE and/or PM&C if necessary	<ul style="list-style-type: none"> • Refer to the recovery procedures in TVOE 3.4 Upgrade document [2] if a TVOE backout is required. • Refer to the recovery procedures in PM&C Incremental Upgrade Procedure [3] if a PM&C backout is required.
THIS PROCEDURE HAS BEEN COMPLETED		

Appendix A. Accessing the OAM Server GUI (NOAMP)

Procedure 18: Accessing the OAM Server GUI (NOAMP)

Step	Procedure	Result
1. <input type="checkbox"/>	<p>Active OAM VIP:</p> <ol style="list-style-type: none"> 1. Launch Internet Explorer or other and connect to the XMI Virtual IP address (VIP) assigned to active OAM site 2. If a certificate error is received, click Proceed anyway. 	 <p>There's a problem with this website's security certificate</p> <p>This might mean that someone's trying to fool you or steal any info you send to the server. You should close this site immediately.</p> <p><input type="checkbox"/> Go to my homepage instead</p> <p> Continue to this webpage (not recommended)</p>
2. <input type="checkbox"/>	<p>Active OAM VIP: The login screen displays.</p> <p>Login to the GUI using the default user and password.</p>	

Step	Procedure	Result
3. <input type="checkbox"/>	<p>Active OAM VIP: The Main Menu displays.</p> <p>Verify that the message across the top of the right panel indicates that the browser is using the VIP connected to the active OAM server.</p>	 <p>Main Menu: [Main]</p> <p>This is the user-defined message. It can be modified using the 'General Options' menu.</p> <p>Login Name: [REDACTED] Last Login Time: [REDACTED] Last Login IP: [REDACTED] Recent Failed: [REDACTED]</p> <p>NOTE: The message may show connection to either a ACTIVE NETWORK OAMP or a SYSTEM OAM depending on the selected NE.</p>

THIS PROCEDURE HAS BEEN COMPLETED


Appendix B. Health Check Procedures



This procedure is part of software upgrade preparation and is used to determine the health and status of the Oracle Communications User Data Repository network and servers.



Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.



Procedure 19: Health Check Procedures

Step	Procedure	Result																																			
1. <input type="checkbox"/>	Using the VIP address, access the primary NOAMP GUI.	Access the primary NOAMP GUI as specified in Appendix A.																																			
2. <input type="checkbox"/>	Active NOAMP VIP: Navigate to Main Menu → Status & Manage → Server	<p>Main Menu: Status & Manage -> Server</p> <p>Filter* ▾</p> <table border="1"> <thead> <tr> <th>Server Hostname</th> <th>Network Element</th> <th>Appl State</th> <th>Alm</th> <th>DB</th> <th>Reporting Status</th> <th>Proc</th> </tr> </thead> <tbody> <tr> <td>DR-OCUDR-A</td> <td>Site2_NE_DR_NO</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>DR-OCUDR-B</td> <td>Site2_NE_DR_NO</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>OCUDR-A</td> <td>Site1_NE_NO</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>OCUDR-B</td> <td>Site1_NE_NO</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> </tbody> </table> <p>Verify that all server statuses show Norm.</p>	Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc	DR-OCUDR-A	Site2_NE_DR_NO	Enabled	Err	Norm	Norm	Norm	DR-OCUDR-B	Site2_NE_DR_NO	Enabled	Err	Norm	Norm	Norm	OCUDR-A	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm	OCUDR-B	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm
Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc																															
DR-OCUDR-A	Site2_NE_DR_NO	Enabled	Err	Norm	Norm	Norm																															
DR-OCUDR-B	Site2_NE_DR_NO	Enabled	Err	Norm	Norm	Norm																															
OCUDR-A	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm																															
OCUDR-B	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm																															
3. <input type="checkbox"/>	Active NOAMP VIP: If any other server statuses are present, they are listed in a colored box. NOTE: Other server states include Err, Warn, Man, Unk and Disabled.	<p>Main Menu: Status & Manage -> Server</p> <p>Filter* ▾</p> <table border="1"> <thead> <tr> <th>Server Hostname</th> <th>Network Element</th> <th>Appl State</th> <th>Alm</th> <th>DB</th> <th>Reporting Status</th> <th>Proc</th> </tr> </thead> <tbody> <tr> <td>DR-OCUDR-A</td> <td>Site2_NE_DR_NO</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>DR-OCUDR-B</td> <td>Site2_NE_DR_NO</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>OCUDR-A</td> <td>Site1_NE_NO</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>OCUDR-B</td> <td>Site1_NE_NO</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> </tbody> </table> <p>If server state is any value besides NORM, follow Appendix J to contact My Oracle Support.</p>	Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc	DR-OCUDR-A	Site2_NE_DR_NO	Enabled	Err	Norm	Norm	Norm	DR-OCUDR-B	Site2_NE_DR_NO	Enabled	Err	Norm	Norm	Norm	OCUDR-A	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm	OCUDR-B	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm
Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc																															
DR-OCUDR-A	Site2_NE_DR_NO	Enabled	Err	Norm	Norm	Norm																															
DR-OCUDR-B	Site2_NE_DR_NO	Enabled	Err	Norm	Norm	Norm																															
OCUDR-A	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm																															
OCUDR-B	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm																															

Step	Procedure	Result																																																																												
4. <input type="checkbox"/>	Active NOAMP VIP: Navigate to Main Menu → Alarm & Events → View Active	<p>Main Menu: Alarms & Events -> View Active</p> <p>Thu Apr 24 14:35:33 2014</p> <p>Filter ▾ Warning ▾ Tasks ▾</p> <table border="1"> <thead> <tr> <th>Seq #</th> <th>Event ID</th> <th>Timestamp</th> <th>Severity</th> <th>Product</th> <th>Process</th> <th>NE</th> <th>Server</th> <th>Type</th> <th>Instance</th> </tr> <tr> <th colspan="10">Alarm Text</th> <th>Additional Info</th> </tr> </thead> <tbody> <tr> <td>15674</td> <td>31270</td> <td>2014-04-24 14:34:58.215 EDT</td> <td>MINOR</td> <td>Platform</td> <td>ProcWatch</td> <td>UDR_NO_BL</td> <td>908070109-NO-A</td> <td>SW</td> <td></td> <td>GN_WARNING: Program tracing is enabled [ProcWatchMain.cxx:131] [12179:ProcW... More...</td> </tr> <tr> <td>1950</td> <td></td> <td>Logging Output</td> <td></td> <td></td> <td></td> <td></td> <td></td> <td></td> <td></td> <td></td> </tr> <tr> <td>15673</td> <td>31113</td> <td>2014-04-24 14:34:29.134 EDT</td> <td>MINOR</td> <td>Platform</td> <td>inetrep</td> <td>UDR_NO_BL</td> <td>908070110-NO-B</td> <td>REPL</td> <td></td> <td>GN_INHIBITWRN local DB replication state is inhibited ^A [5371:RepChannel... More...</td> </tr> <tr> <td>15528</td> <td>13027</td> <td>2014-04-24 14:34:26.707 EDT</td> <td>MINOR</td> <td>Platform</td> <td>inetrep</td> <td>UDR_NO_BL</td> <td>908070109-NO-A</td> <td>REPL</td> <td></td> <td>GN_INHIBITWRN local DB replication state is inhibited ^A [4759:RepChannel... More...</td> </tr> <tr> <td></td> <td></td> <td></td> <td>MAJOR</td> <td>Provisioning</td> <td>xsas</td> <td>UDR_NO_BL</td> <td>908070109-NO-A</td> <td>PROV</td> <td></td> <td>No remote provisioning clients are connected. GN_INFOWRN for information only [SoapListener.C:775] ^A No remote provisi... More...</td> </tr> </tbody> </table>	Seq #	Event ID	Timestamp	Severity	Product	Process	NE	Server	Type	Instance	Alarm Text										Additional Info	15674	31270	2014-04-24 14:34:58.215 EDT	MINOR	Platform	ProcWatch	UDR_NO_BL	908070109-NO-A	SW		GN_WARNING: Program tracing is enabled [ProcWatchMain.cxx:131] [12179:ProcW... More...	1950		Logging Output									15673	31113	2014-04-24 14:34:29.134 EDT	MINOR	Platform	inetrep	UDR_NO_BL	908070110-NO-B	REPL		GN_INHIBITWRN local DB replication state is inhibited ^A [5371:RepChannel... More...	15528	13027	2014-04-24 14:34:26.707 EDT	MINOR	Platform	inetrep	UDR_NO_BL	908070109-NO-A	REPL		GN_INHIBITWRN local DB replication state is inhibited ^A [4759:RepChannel... More...				MAJOR	Provisioning	xsas	UDR_NO_BL	908070109-NO-A	PROV		No remote provisioning clients are connected. GN_INFOWRN for information only [SoapListener.C:775] ^A No remote provisi... More...
Seq #	Event ID	Timestamp	Severity	Product	Process	NE	Server	Type	Instance																																																																					
Alarm Text										Additional Info																																																																				
15674	31270	2014-04-24 14:34:58.215 EDT	MINOR	Platform	ProcWatch	UDR_NO_BL	908070109-NO-A	SW		GN_WARNING: Program tracing is enabled [ProcWatchMain.cxx:131] [12179:ProcW... More...																																																																				
1950		Logging Output																																																																												
15673	31113	2014-04-24 14:34:29.134 EDT	MINOR	Platform	inetrep	UDR_NO_BL	908070110-NO-B	REPL		GN_INHIBITWRN local DB replication state is inhibited ^A [5371:RepChannel... More...																																																																				
15528	13027	2014-04-24 14:34:26.707 EDT	MINOR	Platform	inetrep	UDR_NO_BL	908070109-NO-A	REPL		GN_INHIBITWRN local DB replication state is inhibited ^A [4759:RepChannel... More...																																																																				
			MAJOR	Provisioning	xsas	UDR_NO_BL	908070109-NO-A	PROV		No remote provisioning clients are connected. GN_INFOWRN for information only [SoapListener.C:775] ^A No remote provisi... More...																																																																				
5. <input type="checkbox"/>	Active NOAMP VIP: Click Export .	 <p>NOTE: This step cannot be performed if global provisioning is disabled. The Export button is grayed out in that scenario.</p>																																																																												
6. <input type="checkbox"/>	Active NOAMP VIP: Click Ok at the bottom of the screen. Default values are fine.	<p>Main Menu: Alarms & Events -> View Active [Export]</p> <p>Wed Mar 01 16:05:38 2014</p> <table border="1"> <thead> <tr> <th>Attribute</th> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>Export Frequency</td> <td> <input checked="" type="radio"/> Once <input type="radio"/> Fifteen Minutes <input type="radio"/> Hourly <input type="radio"/> Daily <input type="radio"/> Weekly </td> <td>Select how often the data will be written to the export directory. Selecting "Once" will perform the operation immediately. Note that the Fifteen Minute, Hourly, Daily and Weekly scheduling options are only available when provisioning is enabled. [Default: Once.]</td> </tr> <tr> <td>Task Name *</td> <td>APDE Alarm Export</td> <td>Periodic export task name. [Required. The length should not exceed 40 characters. Valid characters are alphanumeric, minus sign, and spaces between words. The first character must be an alpha character. The last character must be an alpha character or a number.] [A value is required.]</td> </tr> <tr> <td>Description</td> <td></td> <td>Periodic export task description. [Optional. The length should not exceed 255 characters. Valid characters are alphanumeric, minus sign, underscore, and spaces between words. The first character must be an alpha character. The last character must be an alpha character or a number.]</td> </tr> <tr> <td>Filename Prefix</td> <td></td> <td>Export filename prefix. Characters to prepend the generated export filename. [Optional. The length should not exceed 8 characters. Valid characters are alphanumeric.]</td> </tr> <tr> <td>Minute</td> <td>0</td> <td>Select the minute of each hour when the data will be written to the export directory. Only if Export Frequency is hourly or fifteen minutes. If Export Frequency is fifteen minutes, transfers occur four times per hour, and this field displays the minute of the first transfer. [Default = 0. Range = 0 to 59.]</td> </tr> <tr> <td>Time of Day</td> <td>12:00 AM</td> <td>Select the time of day when the data will be written to the export directory. Only if Export Frequency is daily or weekly. Select from 15-minute increments, or fill in a specific value. [Default = 12:00 AM. Range = HH:MM with AM/PM.]</td> </tr> <tr> <td>Day of Week</td> <td> <input checked="" type="radio"/> Sunday <input type="radio"/> Monday <input type="radio"/> Tuesday <input type="radio"/> Wednesday <input type="radio"/> Thursday <input type="radio"/> Friday </td> <td>Select the day of week when the data will be written to the export directory. Only if Export Frequency is weekly. [Default: Sunday.]</td> </tr> </tbody> </table>	Attribute	Value	Description	Export Frequency	<input checked="" type="radio"/> Once <input type="radio"/> Fifteen Minutes <input type="radio"/> Hourly <input type="radio"/> Daily <input type="radio"/> Weekly	Select how often the data will be written to the export directory. Selecting "Once" will perform the operation immediately. Note that the Fifteen Minute, Hourly, Daily and Weekly scheduling options are only available when provisioning is enabled. [Default: Once.]	Task Name *	APDE Alarm Export	Periodic export task name. [Required. The length should not exceed 40 characters. Valid characters are alphanumeric, minus sign, and spaces between words. The first character must be an alpha character. The last character must be an alpha character or a number.] [A value is required.]	Description		Periodic export task description. [Optional. The length should not exceed 255 characters. Valid characters are alphanumeric, minus sign, underscore, and spaces between words. The first character must be an alpha character. The last character must be an alpha character or a number.]	Filename Prefix		Export filename prefix. Characters to prepend the generated export filename. [Optional. The length should not exceed 8 characters. Valid characters are alphanumeric.]	Minute	0	Select the minute of each hour when the data will be written to the export directory. Only if Export Frequency is hourly or fifteen minutes. If Export Frequency is fifteen minutes, transfers occur four times per hour, and this field displays the minute of the first transfer. [Default = 0. Range = 0 to 59.]	Time of Day	12:00 AM	Select the time of day when the data will be written to the export directory. Only if Export Frequency is daily or weekly. Select from 15-minute increments, or fill in a specific value. [Default = 12:00 AM. Range = HH:MM with AM/PM.]	Day of Week	<input checked="" type="radio"/> Sunday <input type="radio"/> Monday <input type="radio"/> Tuesday <input type="radio"/> Wednesday <input type="radio"/> Thursday <input type="radio"/> Friday	Select the day of week when the data will be written to the export directory. Only if Export Frequency is weekly. [Default: Sunday.]																																																				
Attribute	Value	Description																																																																												
Export Frequency	<input checked="" type="radio"/> Once <input type="radio"/> Fifteen Minutes <input type="radio"/> Hourly <input type="radio"/> Daily <input type="radio"/> Weekly	Select how often the data will be written to the export directory. Selecting "Once" will perform the operation immediately. Note that the Fifteen Minute, Hourly, Daily and Weekly scheduling options are only available when provisioning is enabled. [Default: Once.]																																																																												
Task Name *	APDE Alarm Export	Periodic export task name. [Required. The length should not exceed 40 characters. Valid characters are alphanumeric, minus sign, and spaces between words. The first character must be an alpha character. The last character must be an alpha character or a number.] [A value is required.]																																																																												
Description		Periodic export task description. [Optional. The length should not exceed 255 characters. Valid characters are alphanumeric, minus sign, underscore, and spaces between words. The first character must be an alpha character. The last character must be an alpha character or a number.]																																																																												
Filename Prefix		Export filename prefix. Characters to prepend the generated export filename. [Optional. The length should not exceed 8 characters. Valid characters are alphanumeric.]																																																																												
Minute	0	Select the minute of each hour when the data will be written to the export directory. Only if Export Frequency is hourly or fifteen minutes. If Export Frequency is fifteen minutes, transfers occur four times per hour, and this field displays the minute of the first transfer. [Default = 0. Range = 0 to 59.]																																																																												
Time of Day	12:00 AM	Select the time of day when the data will be written to the export directory. Only if Export Frequency is daily or weekly. Select from 15-minute increments, or fill in a specific value. [Default = 12:00 AM. Range = HH:MM with AM/PM.]																																																																												
Day of Week	<input checked="" type="radio"/> Sunday <input type="radio"/> Monday <input type="radio"/> Tuesday <input type="radio"/> Wednesday <input type="radio"/> Thursday <input type="radio"/> Friday	Select the day of week when the data will be written to the export directory. Only if Export Frequency is weekly. [Default: Sunday.]																																																																												

Step	Procedure	Result																												
7. <input type="checkbox"/>	<p>Active NOAMP</p> <p>VIP: Click Tasks.</p> <p>The name of the exported Alarms CSV file displays in the banner at the top of the right panel.</p>	 <p>Main Menu: Alarms & Events -> View Active</p> <p>Tasks</p> <table border="1"> <thead> <tr> <th>NO_grp</th> <th>ID</th> <th>Hostname</th> <th>Name</th> <th>Task State</th> <th>Details</th> <th>Progress</th> </tr> </thead> <tbody> <tr> <td>Seq #</td> <td>9</td> <td>NO-B</td> <td>APDE Alarm Export</td> <td>completed</td> <td>Alarms_20170301-160625-EST 9.csv.gz</td> <td>100%</td> </tr> <tr> <td></td> <td>56872</td> <td></td> <td></td> <td></td> <td></td> <td></td> </tr> <tr> <td></td> <td>1458</td> <td></td> <td></td> <td></td> <td></td> <td></td> </tr> </tbody> </table> <p>Server Core File Detected</p> <p>GN_WARNING/WRN Platform detected an error condition [cmplatalarm.cxx] More...</p>	NO_grp	ID	Hostname	Name	Task State	Details	Progress	Seq #	9	NO-B	APDE Alarm Export	completed	Alarms_20170301-160625-EST 9.csv.gz	100%		56872							1458					
NO_grp	ID	Hostname	Name	Task State	Details	Progress																								
Seq #	9	NO-B	APDE Alarm Export	completed	Alarms_20170301-160625-EST 9.csv.gz	100%																								
	56872																													
	1458																													
8. <input type="checkbox"/>	<p>Active NOAMP</p> <p>VIP: Record the filename of Alarms CSV file generated in the space provided to the right.</p>	<p>Example: Alarms<yyyymmdd>_<hhmmss>.csv</p> <p>Alarms _____ - _____.csv</p>																												
9. <input type="checkbox"/>	<p>Active NOAMP</p> <p>VIP: Click Report.</p>	 <p>Report</p>																												

Step	Procedure	Result						
10. <input type="checkbox"/>	Active NOAMP VIP: Active Alarms & Events Report is generated and displayed in the right panel.	<p>Main Menu: Alarms & Events -> View Active [Report]</p>  <pre> TIMESTAMP: 2018-05-15 06:46:56.350 EDT NETWORK_ELEMENT: Site1_NE_NO SERVER: OCUDR-A SEQ_NUM: 32758 EVENT_NUMBER: 13075 SEVERITY: CRITICAL PRODUCT: Provisioning PROCESS: udrprov TYPE: PROV INSTANCE: NAME: Provisioning Interfaces Disabled DESC: Provisioning Interfaces Disabled. ERR_INFO: GN_NOTENAB/WRN SOAP and REST interfaces are disabled ^^ [30479:ProvController.C:164] NSECS: 1638939351337559701 ID: 0 TIMESTAMP: 2018-05-15 06:29:14.812 EDT NETWORK_ELEMENT: Site1_NE_NO SERVER: OCUDR-A SEQ_NUM: 32743 EVENT_NUMBER: 32532 SEVERITY: MINOR PRODUCT: TPD PROCESS: cmplatalarm TYPE: PLAT INSTANCE: NAME: Server Upgrade Pending Accept/Reject DESC: Server Upgrade Pending Accept/Reject ERR_INFO: </pre>						
11. <input type="checkbox"/>	Active NOAMP VIP: 1. Click Save . 2. Click Save and save to a directory.							
12. <input type="checkbox"/>	Active NOAMP VIP: Navigate to Main Menu → Configuration → Network Elements	<p>Main Menu: Status & Manage -> Network Elements</p>  <table border="1"> <thead> <tr> <th data-bbox="535 1353 1106 1396">Network Element Name</th><th data-bbox="1106 1353 1547 1396">Customer Router Monitoring</th></tr> </thead> <tbody> <tr> <td data-bbox="535 1396 1106 1501">Site1_NE_NO</td><td data-bbox="1106 1396 1547 1501">Disabled</td></tr> <tr> <td data-bbox="535 1501 1106 1712">Site2_NE_DR_NO</td><td data-bbox="1106 1501 1547 1712">Disabled</td></tr> </tbody> </table>	Network Element Name	Customer Router Monitoring	Site1_NE_NO	Disabled	Site2_NE_DR_NO	Disabled
Network Element Name	Customer Router Monitoring							
Site1_NE_NO	Disabled							
Site2_NE_DR_NO	Disabled							

Step	Procedure	Result
13. <input type="checkbox"/>	Active NOAMP VIP: Navigate to Main Menu → Configuration → Server Groups	
14. <input type="checkbox"/>	Active NOAMP VIP: Click Report .	
15. <input type="checkbox"/>	Active NOAMP VIP: A Server Group Report is generated and displayed in the right panel.	
16. <input type="checkbox"/>	Active NOAMP VIP: 1. Click Save 2. Click Save .	

Step	Procedure	Result																																								
17. <input type="checkbox"/>	Provide the saved files to the Customer Care Center for Health Check Analysis.	If executing this procedure as a pre or post upgrade health check (HC1/HC2/HC3), provide the following saved files to the Customer Care Center for proper Health Check Analysis: <ul style="list-style-type: none"> • Active Alarms & Events Report [Appendix B, Step 11] • Network Elements Report [Appendix B, Step 1] • Server Group Report [Appendix B, Step 16] 																																								
18. <input type="checkbox"/>	Active NOAMP VIP: Navigate to Main Menu → Status & Manage → HA	<p>Main Menu: Status & Manage -> HA</p> <p>Filter* ▾</p> <table border="1"> <thead> <tr> <th>Hostname</th> <th>OAM HA Role</th> <th>Application HA Role</th> <th>Max Allowed HA Role</th> <th>Mate Hostname List</th> <th>Network Element</th> <th>Server Role</th> <th>Active VIPs</th> </tr> </thead> <tbody> <tr> <td>OCUDR-A</td> <td>Active</td> <td>N/A</td> <td>Active</td> <td>OCUDR-B</td> <td>Site1_NE_NO</td> <td>Network OAM&P</td> <td>10.10.1.6</td> </tr> <tr> <td>OCUDR-B</td> <td>Standby</td> <td>N/A</td> <td>Active</td> <td>OCUDR-A</td> <td>Site1_NE_NO</td> <td>Network OAM&P</td> <td></td> </tr> <tr> <td>DR-OCUDR-A</td> <td>Spare</td> <td>N/A</td> <td>Active</td> <td>DR-OCUDR-B</td> <td>Site2_NE_DR_NO</td> <td>Network OAM&P</td> <td>10.10.1.39</td> </tr> <tr> <td>DR-OCUDR-B</td> <td>Spare</td> <td>N/A</td> <td>Active</td> <td>DR-OCUDR-A</td> <td>Site2_NE_DR_NO</td> <td>Network OAM&P</td> <td></td> </tr> </tbody> </table>	Hostname	OAM HA Role	Application HA Role	Max Allowed HA Role	Mate Hostname List	Network Element	Server Role	Active VIPs	OCUDR-A	Active	N/A	Active	OCUDR-B	Site1_NE_NO	Network OAM&P	10.10.1.6	OCUDR-B	Standby	N/A	Active	OCUDR-A	Site1_NE_NO	Network OAM&P		DR-OCUDR-A	Spare	N/A	Active	DR-OCUDR-B	Site2_NE_DR_NO	Network OAM&P	10.10.1.39	DR-OCUDR-B	Spare	N/A	Active	DR-OCUDR-A	Site2_NE_DR_NO	Network OAM&P	
Hostname	OAM HA Role	Application HA Role	Max Allowed HA Role	Mate Hostname List	Network Element	Server Role	Active VIPs																																			
OCUDR-A	Active	N/A	Active	OCUDR-B	Site1_NE_NO	Network OAM&P	10.10.1.6																																			
OCUDR-B	Standby	N/A	Active	OCUDR-A	Site1_NE_NO	Network OAM&P																																				
DR-OCUDR-A	Spare	N/A	Active	DR-OCUDR-B	Site2_NE_DR_NO	Network OAM&P	10.10.1.39																																			
DR-OCUDR-B	Spare	N/A	Active	DR-OCUDR-A	Site2_NE_DR_NO	Network OAM&P																																				
19. <input type="checkbox"/>	Active NOAMP VIP: Verify that the HA Status for all servers shows either Active or Standby.	<p>Main Menu: Status & Manage -> HA</p> <p>Filter* ▾</p> <table border="1"> <thead> <tr> <th>Hostname</th> <th>OAM HA Role</th> <th>Application HA Role</th> <th>Max Allowed HA Role</th> <th>Mate Hostname List</th> <th>Network Element</th> <th>Server Role</th> <th>Active VIPs</th> </tr> </thead> <tbody> <tr> <td>OCUDR-A</td> <td>Active</td> <td>N/A</td> <td>Active</td> <td>OCUDR-B</td> <td>Site1_NE_NO</td> <td>Network OAM&P</td> <td>10.10.1.6</td> </tr> <tr> <td>OCUDR-B</td> <td>Standby</td> <td>N/A</td> <td>Active</td> <td>OCUDR-A</td> <td>Site1_NE_NO</td> <td>Network OAM&P</td> <td></td> </tr> <tr> <td>DR-OCUDR-A</td> <td>Spare</td> <td>N/A</td> <td>Active</td> <td>DR-OCUDR-B</td> <td>Site2_NE_DR_NO</td> <td>Network OAM&P</td> <td>10.10.1.39</td> </tr> <tr> <td>DR-OCUDR-B</td> <td>Spare</td> <td>N/A</td> <td>Active</td> <td>DR-OCUDR-A</td> <td>Site2_NE_DR_NO</td> <td>Network OAM&P</td> <td></td> </tr> </tbody> </table>	Hostname	OAM HA Role	Application HA Role	Max Allowed HA Role	Mate Hostname List	Network Element	Server Role	Active VIPs	OCUDR-A	Active	N/A	Active	OCUDR-B	Site1_NE_NO	Network OAM&P	10.10.1.6	OCUDR-B	Standby	N/A	Active	OCUDR-A	Site1_NE_NO	Network OAM&P		DR-OCUDR-A	Spare	N/A	Active	DR-OCUDR-B	Site2_NE_DR_NO	Network OAM&P	10.10.1.39	DR-OCUDR-B	Spare	N/A	Active	DR-OCUDR-A	Site2_NE_DR_NO	Network OAM&P	
Hostname	OAM HA Role	Application HA Role	Max Allowed HA Role	Mate Hostname List	Network Element	Server Role	Active VIPs																																			
OCUDR-A	Active	N/A	Active	OCUDR-B	Site1_NE_NO	Network OAM&P	10.10.1.6																																			
OCUDR-B	Standby	N/A	Active	OCUDR-A	Site1_NE_NO	Network OAM&P																																				
DR-OCUDR-A	Spare	N/A	Active	DR-OCUDR-B	Site2_NE_DR_NO	Network OAM&P	10.10.1.39																																			
DR-OCUDR-B	Spare	N/A	Active	DR-OCUDR-A	Site2_NE_DR_NO	Network OAM&P																																				
20. <input type="checkbox"/>	Active NOAMP VIP: Repeat Step 19 of this procedure until the last page of the [Main Menu: Status & Manage → HA] screen is reached.	Verify the HA Status for each page of the [Main Menu: Status & Manage → HA] screen, and click Next .																																								
Steps 21 to 23 are for pre-upgrade only																																										
21. <input type="checkbox"/>	Check if a new firmware release is required for the system.	<ol style="list-style-type: none"> 1. Contact the Oracle CGBU Customer Care Center by referring to Appendix J of this document to determine the minimum supported firmware release required for the target Oracle Communications User Data Repository release. Target Firmware Rev: _____ Example: FW rev 2.2.9 2. Consult My Oracle Support (Appendix J) to determine if a firmware upgrade is required. If an upgrade is required, acquire the firmware release package and follow procedures suggested by My Oracle Support. 3. Plan for firmware upgrade maintenance windows, if needed, since this activity is typically performed before the Oracle Communications User Data Repository upgrade. 																																								



Step	Procedure	Result
22. <input type="checkbox"/>	Check the existing PM&C version and identify if PM&C upgrade is required, before starting with upgrade(applies to servers that are running PM&C)	Determine the PM&C version installed by logging into PM&C GUI. For incremental upgrades, follow reference [3].
23. <input type="checkbox"/>	Check the TVOE host server software version	<p>1. Find the target Oracle Communications User Data Repository release. 2. Contact the My Oracle Support by referring to (Appendix J) of this document to determine the minimum supported TVOE OS version required for the target release.</p> <p>Required TVOE Release: _____</p> <p>Example: 872-2525-101-3.4.0_82.22.0-TVOE-x86_64.iso</p> <p>3. Follow Appendix F for the procedure to check the current TVOE HOST OS version, for all TVOE hosts.</p> <p><i>IMPORTANT: If TVOE hosts are not on the correct release, refer to Section 3.3.5 to plan for TVOE host upgrades.</i></p>
STEP 24 IS POST-UPGRADE ONLY		
24. <input type="checkbox"/>	Active NOAMP VIP: Determine if any errors were reported.	Use an SSH client to connect to the recently upgraded servers (for example: ssh or putty): <pre>ssh<server IMI IP address> login as: admusr password: <enter password> Switch to root su - password: <enter password> # verifyUpgrade</pre> Examine the output of the command to determine if any errors were reported. Contact the Oracle CGBU Customer Care Center if errors occur.
THIS PROCEDURE HAS BEEN COMPLETED		



Appendix C. Upgrade of a Server



C.1 UPGRADE SERVER





Procedure 20: Initiate Upgrade Server




Step	Procedure	Result																																																
1. <input type="checkbox"/>	Using the VIP address, access the primary NOAMP GUI.	<p>Access the primary NOAMP GUI as specified in Appendix A.</p> <p>NOTE: Ensure that there are no users in the <code>/var/TKLC/db/filemgmt</code> directory on server to be upgraded</p>																																																
2. <input type="checkbox"/>	<p>Active NOAMP VIP:</p> <ol style="list-style-type: none"> 1. Navigate to Main Menu → Administration → Software Management → Upgrade 2. Select server group tab for servers to be upgraded. 3. Verify that the Upgrade State shows Ready for the servers to be upgraded. 4. Verify the Application Version value for servers is the source software release version 	<p>Main Menu: Administration -> Software Management -> Upgrade</p> <table border="1"> <thead> <tr> <th>Hostname</th> <th>Upgrade State</th> <th>OAM HA Role</th> <th>Server Role</th> <th>Function</th> <th>Application Version</th> <th>Start Time</th> <th>Finish Time</th> </tr> <tr> <th></th> <th>Server Status</th> <th>Appl HA Role</th> <th colspan="2">Network Element</th> <th>Upgrade ISO</th> <th colspan="2">Status Message</th> </tr> </thead> <tbody> <tr> <td>OCUDR-A</td> <td>Ready</td> <td>Active</td> <td>Network OAM&P</td> <td>OAM&P</td> <td>12.4.0.0-16.14.0</td> <td></td> <td></td> </tr> <tr> <td>OCUDR-B</td> <td>Err</td> <td>N/A</td> <td>Site1_NE_NO</td> <td></td> <td></td> <td></td> <td></td> </tr> <tr> <td>OCUDR-B</td> <td>Ready</td> <td>Standby</td> <td>Network OAM&P</td> <td>OAM&P</td> <td>12.4.0.0-16.14.0</td> <td></td> <td></td> </tr> <tr> <td></td> <td>Err</td> <td>N/A</td> <td>Site1_NE_NO</td> <td></td> <td></td> <td></td> <td></td> </tr> </tbody> </table>	Hostname	Upgrade State	OAM HA Role	Server Role	Function	Application Version	Start Time	Finish Time		Server Status	Appl HA Role	Network Element		Upgrade ISO	Status Message		OCUDR-A	Ready	Active	Network OAM&P	OAM&P	12.4.0.0-16.14.0			OCUDR-B	Err	N/A	Site1_NE_NO					OCUDR-B	Ready	Standby	Network OAM&P	OAM&P	12.4.0.0-16.14.0				Err	N/A	Site1_NE_NO				
Hostname	Upgrade State	OAM HA Role	Server Role	Function	Application Version	Start Time	Finish Time																																											
	Server Status	Appl HA Role	Network Element		Upgrade ISO	Status Message																																												
OCUDR-A	Ready	Active	Network OAM&P	OAM&P	12.4.0.0-16.14.0																																													
OCUDR-B	Err	N/A	Site1_NE_NO																																															
OCUDR-B	Ready	Standby	Network OAM&P	OAM&P	12.4.0.0-16.14.0																																													
	Err	N/A	Site1_NE_NO																																															



Step	Procedure	Result
3. <input type="checkbox"/>	<p>Active NOAMP</p> <p>VIP:</p> <ol style="list-style-type: none"> 1. Select the server (for one server at a time) or select no servers (for group-based auto upgrade) 2. Ensure the Upgrade Server or Auto Upgrade button is enabled. 3. Click Auto Upgrade or Upgrade Server <p>NOTE: Auto Upgrade does not update the active NOAMP server.</p>	<p>Single Server</p> <p>Main Menu: Administration -> Software Management -> Upgrade</p>  <p>Group Based</p> <p>Main Menu: Administration -> Software Management -> Upgrade [Initiate]</p> 

Step	Procedure	Result
4. <input type="checkbox"/>	<p>Active NOAMP VIP:</p> <p>1. The Upgrade[Initiate] screen displays</p> <p>2. Select the ISO to use in the server upgrade</p> <p>If Auto Upgrade option was selected for group-based upgrade:</p> <ul style="list-style-type: none"> • NO/SO: Bulk upgrades servers in groups according to the availability setting. • MP: Serial upgrades servers one at a time starting with standby server <p>NOTE: For MPs, you can select the required percent availability. (recommended to have at least 50% available)</p> <p>3. Click Ok to start the upgrade</p>	<p>Upgrade Server:</p> <p>Main Menu: Administration -> Software Management -> Upgrade [Initiate]</p>  <p>Auto Upgrade:</p> <p>Main Menu: Administration -> Software Management -> Upgrade [Initiate]</p>  <p>NOTE: During the upgrade you might see the following expected alarms. Not all servers have all alarms:</p> <ul style="list-style-type: none"> 31101 (DB Replication to a slave DB has failed) 31106 (DB Merging to a parent Merge Node has failed) 31107 (DB Merging from a child source Node has failed) 31114 (DB Replication of configuration data via ...) 13071 (No northbound Provisioning Connections) 10073 (Server Group Max Allowed HA Role Warning) 10075 (Application processes have been manually stopped) 32515 (Server HA Failover Inhibited) 31283 (HA Highly available server failed to receive) 31226 (The High Availability Status is degraded)

Step	Procedure	Result
5. <input type="checkbox"/>	<p>Active NOAMP</p> <p>VIP: ** For active NOAMP only: After Step 4 completes, the session automatically terminates and you are logged out of the GUI.</p> <p>The Log In screen displays as the standby NOAMP server goes through HA switchover and becomes the active server.</p> <p>Login to the GUI using the default user and password.</p>	 <p>Log In Enter your username and password to log in Session timed out at 2:13:27 pm. Username: <input type="text"/> Password: <input type="password"/> <input type="checkbox"/> Change password <input type="button" value="Log In"/></p>
6. <input type="checkbox"/>	<p>Active NOAM VIP: ** For active NOAMP only</p> <p>The Main Menu displays.</p> <p>Verify that the message across the top of the right panel indicates that the browser is using the VIP connected to the active NOAMP server.</p>	 <p>Main Menu: [Main]</p> <p>Main Menu</p> <ul style="list-style-type: none"> Administration General Options Access Control Software Management <ul style="list-style-type: none"> Versions Upgrade Remote Servers Configuration Alarms & Events Security Log Status & Manage Measurements Communication Agent <p>This is the user-defined welcome message. It can be modified using the 'General Options' item under the 'Administration' menu.</p> <p>Login Name: guadmin Last Login Time: 2017-01-24 09:47:46</p>

Step	Procedure	Result																														
7. <input type="checkbox"/>	<p>Active NOAMP VIP: View in-progress status</p> <p>1. Select Main Menu → Administration → Software Management → Upgrade</p> <p>2. Observe the Upgrade State of the servers of interest throughout the upgrade.</p> <p>Status Message contains additional upgrade details which allow upgrades in progress to be monitored. The following screen shots are examples of what to expect during upgrade.</p> <p>The Progress can be viewed on the Task list</p> <p>3. Wait for each upgrade to report Success before proceeding to the next step.</p>	<p>Main Menu: Administration -> Software Management -> Upgrade</p>  <p>Main Menu: Administration -> Software Management -> Upgrade</p>  <p>Main Menu: Administration -> Software Management -> Upgrade</p>  <p>Main Menu: Administration -> Software Management -> Upgrade</p>  <p>Tasks</p> <table border="1"> <thead> <tr> <th>ID</th> <th>Hostname</th> <th>Name</th> <th>Task State</th> <th>Details</th> <th>Progress</th> </tr> </thead> <tbody> <tr> <td>3</td> <td>OCUDR-A</td> <td>OCUDR-B Server Upgrade</td> <td>running</td> <td>Upgrade is in progress</td> <td>28%</td> </tr> <tr> <td>2</td> <td>OCUDR-A</td> <td>DR-OCUDR-A Server Upgrade</td> <td>completed</td> <td>Server upgrade execution complete.</td> <td>100%</td> </tr> <tr> <td>1</td> <td>OCUDR-A</td> <td>DR-OCUDR-B Server Upgrade</td> <td>completed</td> <td>Server upgrade execution complete.</td> <td>100%</td> </tr> <tr> <td>75</td> <td>DR-OCUDR-A</td> <td>Pre-upgrade full backup</td> <td>completed</td> <td>Full backup on DR-OCUDR-A</td> <td>100%</td> </tr> </tbody> </table>	ID	Hostname	Name	Task State	Details	Progress	3	OCUDR-A	OCUDR-B Server Upgrade	running	Upgrade is in progress	28%	2	OCUDR-A	DR-OCUDR-A Server Upgrade	completed	Server upgrade execution complete.	100%	1	OCUDR-A	DR-OCUDR-B Server Upgrade	completed	Server upgrade execution complete.	100%	75	DR-OCUDR-A	Pre-upgrade full backup	completed	Full backup on DR-OCUDR-A	100%
ID	Hostname	Name	Task State	Details	Progress																											
3	OCUDR-A	OCUDR-B Server Upgrade	running	Upgrade is in progress	28%																											
2	OCUDR-A	DR-OCUDR-A Server Upgrade	completed	Server upgrade execution complete.	100%																											
1	OCUDR-A	DR-OCUDR-B Server Upgrade	completed	Server upgrade execution complete.	100%																											
75	DR-OCUDR-A	Pre-upgrade full backup	completed	Full backup on DR-OCUDR-A	100%																											

Step	Procedure	Result
8. <input type="checkbox"/>	<p>Active NOAMP VIP:</p> <ol style="list-style-type: none"> 1. Select the appropriate tab (NO_SG, MP_SG or SO_SG) and select the row containing the hostname of the server that was upgraded. 2. Verify that the Status Message shows Success and Upgrade State is Accept or Reject 	<p>Main Menu: Administration > Software Management > Upgrade</p>  <p>NOTE: If the upgrade status indicates that the server could not restart the application to complete the upgrade and alarm 10134 (Server Upgrade Failed) displays; ensure that replication is up. Use <code>irepstat</code> command on active server and verify status is Active:</p> <ul style="list-style-type: none"> • The Status changes to Success • Alarm 10134 to clear <p>Main Menu: Administration > Software Management > Upgrade</p> 
9. <input type="checkbox"/>	<ol style="list-style-type: none"> 1. If upgrade status still indicates that server could not restart the application to complete the upgrade, restart the server by clicking the Restart. 2. Verify that the Status Message shows Success and Upgrade State is Accept or Reject 	<p>Restart server that is being upgraded from Main Menu → Status & Manage → Server</p> <p>Main Menu: Status & Manage -> Server</p>  <div data-bbox="775 1267 1305 1351" style="border: 1px solid #ccc; padding: 5px; text-align: center;"> <input type="button" value="Stop"/> <input type="button" value="Restart"/> <input type="button" value="Reboot"/> <input type="button" value="NTP Sync"/> <input type="button" value="Report"/> </div>

Step	Procedure	Result																																																		
10. <input type="checkbox"/>	<p>Active NOAMP VIP: Navigate to Main Menu → Status & Manage → HA [Edit]</p>	<p>NOTE: Only perform the following step if Upgrade State is DEGRADED.</p> <p>Change Max Allowed HA Role for server (server that was upgraded) to Active</p>  <p>Modifying HA attributes</p> <table border="1"> <thead> <tr> <th>Hostname</th> <th>Max Allowed HA Role</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>OCUDR-A</td> <td>Active</td> <td>The maximum desired HA Role for OCUDR-A</td> </tr> <tr> <td>OCUDR-B</td> <td>Active</td> <td>The maximum desired HA Role for OCUDR-B</td> </tr> <tr> <td>DR-OCUDR-A</td> <td>Active</td> <td>The maximum desired HA Role for DR-OCUDR-A</td> </tr> <tr> <td>DR-OCUDR-B</td> <td>Active</td> <td>The maximum desired HA Role for DR-OCUDR-B</td> </tr> </tbody> </table> <p>Restart server from Main Menu->Status & Manage -> Server screen</p>  <table border="1"> <thead> <tr> <th>Server Hostname</th> <th>Network Element</th> <th>Appl State</th> <th>Alm</th> <th>DB</th> <th>Reporting Status</th> <th>Proc</th> </tr> </thead> <tbody> <tr> <td>DR-OCUDR-A</td> <td>Site2_NE_DR_NO</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>DR-OCUDR-B</td> <td>Site2_NE_DR_NO</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr style="outline: 2px solid blue;"> <td>OCUDR-A</td> <td>Site1_NE_NO</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>OCUDR-B</td> <td>Site1_NE_NO</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> </tbody> </table> <p style="text-align: center;"> <input type="button" value="Stop"/> <input type="button" value="Restart"/> <input type="button" value="Reboot"/> <input type="button" value="NTP Sync"/> <input type="button" value="Report"/> </p>	Hostname	Max Allowed HA Role	Description	OCUDR-A	Active	The maximum desired HA Role for OCUDR-A	OCUDR-B	Active	The maximum desired HA Role for OCUDR-B	DR-OCUDR-A	Active	The maximum desired HA Role for DR-OCUDR-A	DR-OCUDR-B	Active	The maximum desired HA Role for DR-OCUDR-B	Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc	DR-OCUDR-A	Site2_NE_DR_NO	Enabled	Err	Norm	Norm	Norm	DR-OCUDR-B	Site2_NE_DR_NO	Enabled	Err	Norm	Norm	Norm	OCUDR-A	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm	OCUDR-B	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm
Hostname	Max Allowed HA Role	Description																																																		
OCUDR-A	Active	The maximum desired HA Role for OCUDR-A																																																		
OCUDR-B	Active	The maximum desired HA Role for OCUDR-B																																																		
DR-OCUDR-A	Active	The maximum desired HA Role for DR-OCUDR-A																																																		
DR-OCUDR-B	Active	The maximum desired HA Role for DR-OCUDR-B																																																		
Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc																																														
DR-OCUDR-A	Site2_NE_DR_NO	Enabled	Err	Norm	Norm	Norm																																														
DR-OCUDR-B	Site2_NE_DR_NO	Enabled	Err	Norm	Norm	Norm																																														
OCUDR-A	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm																																														
OCUDR-B	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm																																														

Step	Procedure	Result
11. <input type="checkbox"/>	Active NOAMP VIP: View post-upgrade status	<p>View post-upgrade status of the servers. The following alarms may be present.</p> <p>Active NO server has the following expected alarm:</p> <p> Alarm ID is 13071 (No Northbound Provisioning Connections)</p> <p>You may also see the alarm:</p> <p> Alarm ID is 32532 (Server Upgrade Pending Accept/Reject)</p> <p>You may also see this alarm due to DRNO servers Max Allowed HA Role being set to standby in Procedure 7.</p> <p> Alarm ID is 10073 (Server Group Max Allowed HA Role Warning)</p>
12. <input type="checkbox"/>	Active NOAMP VIP: Clear browser cache	<p>JavaScript libraries, images and other objects are often modified in the upgrade. Browsers can cause GUI problems by holding on to the old objects in the built-in cache. To prevent these problems always clear the browser cache before logging in to an NO or SO which has been upgraded:</p> <p>Simultaneously hold down Ctrl-Shift-Delete.</p> <p>Select the appropriate type of objects and delete from the cache. For Internet Explorer the relevant object type is Temporary Internet Files. Other browsers may label these objects differently.</p>

THIS PROCEDURE HAS BEEN COMPLETED

C.2 SERVER WORKSHEET

Select the worksheet that matches the site configuration.

RMS Site Configuration (Low Capacity):



ACTIVE SITE	DR SITE
<input type="checkbox"/> Active NOAMP: _____	<input type="checkbox"/> Active DR NOAMP: _____
<input type="checkbox"/> Standby NOAMP: _____	<input type="checkbox"/> Standby DR NOAMP: _____

C-Class Site Configuration (Normal Configuration):




ACTIVE SITE	DR SITE
<input type="checkbox"/> Active Primary NOAMP: _____	<input type="checkbox"/> Active DR NOAMP: _____
<input type="checkbox"/> Standby Primary NOAMP: _____	<input type="checkbox"/> Standby DR NOAMP: _____


Appendix D. Backout of a Server

Procedure 21: Backout of a Server


Step	Procedure	Result																																																
1. <input type="checkbox"/>	Using the VIP address, access the primary NOAMP GUI.	Access the primary NOAMP GUI as specified in Appendix A.																																																
2. <input type="checkbox"/>	Active NOAMP VIP: Navigate to Main Menu → Administration → Software Management → Upgrade	 <p>Main Menu: Administration -> Software Management -> Upgrade</p> <table border="1"> <thead> <tr> <th>Hostname</th> <th>Upgrade State</th> <th>OAM HA Role</th> <th>Server Role</th> <th>Function</th> <th>Application Version</th> <th>Start Time</th> <th>Finish Time</th> </tr> <tr> <th>Server Status</th> <th>Appl HA Role</th> <th>Network Element</th> <th colspan="4">Upgrade ISO</th> <th>Status Message</th> </tr> </thead> <tbody> <tr> <td>OCUDR-A</td> <td>Accept or Reject</td> <td>Active</td> <td>Network OAM&P</td> <td>OAM&P</td> <td>12.4.0.0.0-16.15.0</td> <td>2018-05-15 06:20:58 EDT</td> <td>2018-05-15 06:32:09 EDT</td> </tr> <tr> <td></td> <td>Err</td> <td>N/A</td> <td>Site1_NE_NO</td> <td></td> <td>UDR-12.4.0.0.0_16.15.0-x86_64.iso</td> <td></td> <td>Success: Server upgrade is complete</td> </tr> <tr> <td>OCUDR-B</td> <td>Accept or Reject</td> <td>Standby</td> <td>Network OAM&P</td> <td>OAM&P</td> <td>12.4.0.0.0-16.15.0</td> <td>2018-05-15 05:57:49 EDT</td> <td>2018-05-15 06:17:01 EDT</td> </tr> <tr> <td></td> <td>Err</td> <td>N/A</td> <td>Site1_NE_NO</td> <td></td> <td>UDR-12.4.0.0.0_16.15.0-x86_64.iso</td> <td></td> <td>Success: Server upgrade is complete</td> </tr> </tbody> </table>	Hostname	Upgrade State	OAM HA Role	Server Role	Function	Application Version	Start Time	Finish Time	Server Status	Appl HA Role	Network Element	Upgrade ISO				Status Message	OCUDR-A	Accept or Reject	Active	Network OAM&P	OAM&P	12.4.0.0.0-16.15.0	2018-05-15 06:20:58 EDT	2018-05-15 06:32:09 EDT		Err	N/A	Site1_NE_NO		UDR-12.4.0.0.0_16.15.0-x86_64.iso		Success: Server upgrade is complete	OCUDR-B	Accept or Reject	Standby	Network OAM&P	OAM&P	12.4.0.0.0-16.15.0	2018-05-15 05:57:49 EDT	2018-05-15 06:17:01 EDT		Err	N/A	Site1_NE_NO		UDR-12.4.0.0.0_16.15.0-x86_64.iso		Success: Server upgrade is complete
Hostname	Upgrade State	OAM HA Role	Server Role	Function	Application Version	Start Time	Finish Time																																											
Server Status	Appl HA Role	Network Element	Upgrade ISO				Status Message																																											
OCUDR-A	Accept or Reject	Active	Network OAM&P	OAM&P	12.4.0.0.0-16.15.0	2018-05-15 06:20:58 EDT	2018-05-15 06:32:09 EDT																																											
	Err	N/A	Site1_NE_NO		UDR-12.4.0.0.0_16.15.0-x86_64.iso		Success: Server upgrade is complete																																											
OCUDR-B	Accept or Reject	Standby	Network OAM&P	OAM&P	12.4.0.0.0-16.15.0	2018-05-15 05:57:49 EDT	2018-05-15 06:17:01 EDT																																											
	Err	N/A	Site1_NE_NO		UDR-12.4.0.0.0_16.15.0-x86_64.iso		Success: Server upgrade is complete																																											
3. <input type="checkbox"/>	Active NOAMP VIP: 1. Select the tab containing the server to be downgraded. 2. Scroll to the row containing the hostname of the server to be backed-out. 3. Verify that the Upgrade State shows Accept or Reject.	 <p>Main Menu: Administration -> Software Management -> Upgrade</p> <table border="1"> <thead> <tr> <th>Hostname</th> <th>Upgrade State</th> <th>OAM HA Role</th> <th>Server Role</th> <th>Function</th> <th>Application Version</th> <th>Start Time</th> <th>Finish Time</th> </tr> <tr> <th>Server Status</th> <th>Appl HA Role</th> <th>Network Element</th> <th colspan="4">Upgrade ISO</th> <th>Status Message</th> </tr> </thead> <tbody> <tr> <td>OCUDR-A</td> <td>Accept or Reject</td> <td>Active</td> <td>Network OAM&P</td> <td>OAM&P</td> <td>12.4.0.0.0-16.15.0</td> <td>2018-05-15 06:20:58 EDT</td> <td>2018-05-15 06:32:09 EDT</td> </tr> <tr> <td></td> <td>Err</td> <td>N/A</td> <td>Site1_NE_NO</td> <td></td> <td>UDR-12.4.0.0.0_16.15.0-x86_64.iso</td> <td></td> <td>Success: Server upgrade is complete</td> </tr> <tr> <td>OCUDR-B</td> <td>Accept or Reject</td> <td>Standby</td> <td>Network OAM&P</td> <td>OAM&P</td> <td>12.4.0.0.0-16.15.0</td> <td>2018-05-15 05:57:49 EDT</td> <td>2018-05-15 06:17:01 EDT</td> </tr> <tr> <td></td> <td>Err</td> <td>N/A</td> <td>Site1_NE_NO</td> <td></td> <td>UDR-12.4.0.0.0_16.15.0-x86_64.iso</td> <td></td> <td>Success: Server upgrade is complete</td> </tr> </tbody> </table>	Hostname	Upgrade State	OAM HA Role	Server Role	Function	Application Version	Start Time	Finish Time	Server Status	Appl HA Role	Network Element	Upgrade ISO				Status Message	OCUDR-A	Accept or Reject	Active	Network OAM&P	OAM&P	12.4.0.0.0-16.15.0	2018-05-15 06:20:58 EDT	2018-05-15 06:32:09 EDT		Err	N/A	Site1_NE_NO		UDR-12.4.0.0.0_16.15.0-x86_64.iso		Success: Server upgrade is complete	OCUDR-B	Accept or Reject	Standby	Network OAM&P	OAM&P	12.4.0.0.0-16.15.0	2018-05-15 05:57:49 EDT	2018-05-15 06:17:01 EDT		Err	N/A	Site1_NE_NO		UDR-12.4.0.0.0_16.15.0-x86_64.iso		Success: Server upgrade is complete
Hostname	Upgrade State	OAM HA Role	Server Role	Function	Application Version	Start Time	Finish Time																																											
Server Status	Appl HA Role	Network Element	Upgrade ISO				Status Message																																											
OCUDR-A	Accept or Reject	Active	Network OAM&P	OAM&P	12.4.0.0.0-16.15.0	2018-05-15 06:20:58 EDT	2018-05-15 06:32:09 EDT																																											
	Err	N/A	Site1_NE_NO		UDR-12.4.0.0.0_16.15.0-x86_64.iso		Success: Server upgrade is complete																																											
OCUDR-B	Accept or Reject	Standby	Network OAM&P	OAM&P	12.4.0.0.0-16.15.0	2018-05-15 05:57:49 EDT	2018-05-15 06:17:01 EDT																																											
	Err	N/A	Site1_NE_NO		UDR-12.4.0.0.0_16.15.0-x86_64.iso		Success: Server upgrade is complete																																											


Step	Procedure	Result															
4. <input type="checkbox"/>	<p>Active NOAMP VIP: Make the server ready for downgrade.</p> <p>1. Navigate to Main Menu → Status & Manage → HA 2. Click Edit 3. Select the server to be downgraded and select a Max Allowed Role value of Standby or spare for DR servers. 4. Click OK</p> <p>NOTE: For active NOAMP only, you are logged out after this step because of the HA switchover. You must log back in to continue.</p> <p>The active server is standby</p>	<p>Main Menu: Status & Manage -> HA [Edit]</p> <p>Modifying HA attributes</p> <table border="1"> <thead> <tr> <th data-bbox="584 466 747 500">Hostname</th> <th data-bbox="747 466 1008 500">Max Allowed HA Role</th> <th data-bbox="1008 466 1530 500">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="584 551 747 585">OCUDR-A</td> <td data-bbox="747 551 1008 585">Active</td> <td data-bbox="1008 551 1530 585">The maximum desired HA Role for OCUDR-A</td> </tr> <tr> <td data-bbox="584 673 747 707">OCUDR-B</td> <td data-bbox="747 673 1008 707">Standby</td> <td data-bbox="1008 673 1530 707">The maximum desired HA Role for OCUDR-B</td> </tr> <tr> <td data-bbox="584 796 747 830">DR-OCUDR-A</td> <td data-bbox="747 796 1008 830">Active</td> <td data-bbox="1008 796 1530 830">The maximum desired HA Role for DR-OCUDR-A</td> </tr> <tr> <td data-bbox="584 918 747 952">DR-OCUDR-B</td> <td data-bbox="747 918 1008 952">Active</td> <td data-bbox="1008 918 1530 952">The maximum desired HA Role for DR-OCUDR-B</td> </tr> </tbody> </table> <p>Ok Cancel</p>	Hostname	Max Allowed HA Role	Description	OCUDR-A	Active	The maximum desired HA Role for OCUDR-A	OCUDR-B	Standby	The maximum desired HA Role for OCUDR-B	DR-OCUDR-A	Active	The maximum desired HA Role for DR-OCUDR-A	DR-OCUDR-B	Active	The maximum desired HA Role for DR-OCUDR-B
Hostname	Max Allowed HA Role	Description															
OCUDR-A	Active	The maximum desired HA Role for OCUDR-A															
OCUDR-B	Standby	The maximum desired HA Role for OCUDR-B															
DR-OCUDR-A	Active	The maximum desired HA Role for DR-OCUDR-A															
DR-OCUDR-B	Active	The maximum desired HA Role for DR-OCUDR-B															

Step	Procedure	Result
5. <input type="checkbox"/>	<p>Active NOAMP VIP: Navigate to Main Menu → Status & Manage → Server</p> <p>1. Select the server to be downgraded and click STOP 2. Click OK to confirm the operation, then ensure the Appl State updates to Disabled.</p>	 <div data-bbox="768 445 1323 566" style="border: 1px solid black; padding: 5px; text-align: center;"> <input type="button" value="Stop"/> <input type="button" value="Restart"/> <input type="button" value="Reboot"/> <input type="button" value="NTP Sync"/> <input type="button" value="Report"/> </div> <div data-bbox="736 572 1356 861" style="border: 1px solid black; padding: 10px; text-align: center;"> <p>Are you sure you wish to stop application software on the following server(s)? OCUDR-B</p> <div style="display: flex; justify-content: space-around; width: 100%;"> <input type="button" value="OK"/> <input type="button" value="Cancel"/> </div> </div> 
6. <input type="checkbox"/>	<p>Active NOAMP VIP: Navigate to Main Menu → Administration → Software Management → Upgrade</p>	

Step	Procedure	Result
7. <input type="checkbox"/>	Active NOAMP VIP: <ol style="list-style-type: none"> 1. Select the tab containing the server to be downgraded. 2. Scroll to the row containing the hostname of the server to be backed-out. 3. Verify that the Upgrade State shows Backout Ready. (It may take a few moments to change status) 	
8. <input type="checkbox"/>	Server XMI IP (SSH): SSH to server	Use your SSH client to connect to the server (ex. ssh, putty): <pre>ssh<server address></pre>
9. <input type="checkbox"/>	Server XMI IP (SSH): Login as admusr user	Login as admusr: <pre>login as: admusr Password: <enter password> Switch to root su - password: <enter password></pre>
10. <input type="checkbox"/>	Server XMI IP (SSH): Perform the backout	1. Find out the state of the server which is going to be backed out. Server is in Standby or Spare. Run the following command to find the HA state: <pre># ha.mystate</pre> <p>NOTE: If the state of the server is Active, then perform these steps to move to standby.</p> 2. Go to MAIN MENU: STATUS & MANAGE → HA 3. Click Edit 4. Switch Max Allowed HA role to standby 5. Perform the backout using the reject script: <pre># screen # /var/TKLC/backout/reject</pre> <p>NOTE: If backout asks if you would like to continue backout, answer y.</p>
11. <input type="checkbox"/>	Server XMI IP (SSH): Backout proceeds	Informational messages come across the terminal screen as the backout proceeds. After backout is complete, the server automatically reboots.


Step	Procedure	Result
12. <input type="checkbox"/>	Server XMI IP (SSH): SSH to server and login as root user	Use your SSH client to connect to the server (ex. ssh, putty): <pre>ssh<server address> login as: admusr password: <enter password> Switch to root su - password: <enter password></pre>
13. <input type="checkbox"/>	Server XMI IP (SSH):	Perform the backout_restore utility to restore the full database run environment: <pre>#/usr/TKLC/appworks/sbin/backout_restore</pre> NOTE: If asked if you would like to proceed, answer y. If the restore was successful, the following message is displayed: Success: Full restore of COMCOL run env has completed. Return to the backout procedure document for further instruction.
14. <input type="checkbox"/>		Enter the following command to reboot the server. If logged in as admusr, it is necessary to use sudo. <pre># init 6</pre> This step takes several minutes and terminates the SSH session.
15. <input type="checkbox"/>	Server XMI IP (SSH): SSH to backed-out server and login as root user	Use your SSH client to connect to the server (ex. ssh, putty): <pre>ssh<server address> login as: admusr password: <enter password> Switch to root su - password: <enter password></pre>
16. <input type="checkbox"/>	Server XMI IP (SSH): Verify services restart	If this is an NOAMP server, verify httpd service is running. Run the command: <pre># service httpd status</pre> Verify expected output displays httpd is running (the process IDs are variable so the list of numbers can be ignored): <pre>httpd<process IDs are listed here> is running...</pre> If httpd is still not running after approximately 3 minutes, then services have failed to restart. Exit from the command line of backed-out server. <pre># exit</pre>
17. <input type="checkbox"/>	Using the VIP address, access the primary NOAMP GUI.	Access the primary NOAMP GUI as specified in Appendix A.

Step	Procedure	Result															
18. <input type="checkbox"/>	Active NOAMP VIP: Verify server states. Navigate to Main Menu → Administration → Software Management → Upgrade	<p>Main Menu: Administration -> Software Management -> Upgrade</p>  <ul style="list-style-type: none"> • If the state is Ready, you are finished with this procedure. • If the state is Not Ready, continue to next step. 															
19. <input type="checkbox"/>	Active NOAMP VIP: 1. Correct Upgrade State on downgraded server 2. Navigate to Main Menu Status & Manage → HA[Edit] 3. Select the downgraded server. 4. Select a Max Allowed HA Role value of Active 5. Click Ok. 6. Verify the Max Allowed HA Role is set to the specified value for the server.	<p>Due to backout being initiated from the command line instead of through the GUI, you must modify the downgraded server so that its Upgrade State moves to Ready.</p> <p>Main Menu: Status & Manage -> HA [Edit]</p> <p>Modifying HA attributes</p> <table border="1"> <thead> <tr> <th data-bbox="556 1009 687 1051">Hostname</th> <th data-bbox="687 1009 997 1051">Max Allowed HA Role</th> <th data-bbox="997 1009 1563 1051">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="556 1100 687 1142">OCUDR-A</td> <td data-bbox="687 1100 997 1142">Active</td> <td data-bbox="997 1100 1563 1142">The maximum desired HA Role for OCUDR-A</td> </tr> <tr> <td data-bbox="556 1212 687 1254">OCUDR-B</td> <td data-bbox="687 1212 997 1254">Active</td> <td data-bbox="997 1212 1563 1254">The maximum desired HA Role for OCUDR-B</td> </tr> <tr> <td data-bbox="556 1324 687 1366">DR-OCUDR-A</td> <td data-bbox="687 1324 997 1366">Active</td> <td data-bbox="997 1324 1563 1366">The maximum desired HA Role for DR-OCUDR-A</td> </tr> <tr> <td data-bbox="556 1436 687 1478">DR-OCUDR-B</td> <td data-bbox="687 1436 997 1478">Active</td> <td data-bbox="997 1436 1563 1478">The maximum desired HA Role for DR-OCUDR-B</td> </tr> </tbody> </table>	Hostname	Max Allowed HA Role	Description	OCUDR-A	Active	The maximum desired HA Role for OCUDR-A	OCUDR-B	Active	The maximum desired HA Role for OCUDR-B	DR-OCUDR-A	Active	The maximum desired HA Role for DR-OCUDR-A	DR-OCUDR-B	Active	The maximum desired HA Role for DR-OCUDR-B
Hostname	Max Allowed HA Role	Description															
OCUDR-A	Active	The maximum desired HA Role for OCUDR-A															
OCUDR-B	Active	The maximum desired HA Role for OCUDR-B															
DR-OCUDR-A	Active	The maximum desired HA Role for DR-OCUDR-A															
DR-OCUDR-B	Active	The maximum desired HA Role for DR-OCUDR-B															

Step	Procedure	Result																															
20. <input type="checkbox"/>	<p>Active NOAMP VIP: Navigate to Main Menu Administration→ Software Management→ Upgrade; Select the tab of the server group containing the server to be downgraded. Verify its Upgrade State is Ready. (It might take a couple minutes for the grid to update.)</p>	<p>Main Menu: Administration -> Software Management -> Upgrade</p>  <table border="1"> <thead> <tr> <th rowspan="2">Hostname</th> <th>Upgrade State</th> <th>OAM HA Role</th> <th>Server Role</th> <th>Function</th> <th>Application Version</th> <th>Start Time</th> <th>Finish Time</th> </tr> <tr> <th>Server Status</th> <th>Appl HA Role</th> <th colspan="2">Network Element</th> <th>Upgrade ISO</th> <th colspan="2">Status Message</th> </tr> </thead> <tbody> <tr> <td>OCUDR-A</td> <td>Ready</td> <td>Active</td> <td>Network OAM&P</td> <td>OAM&P</td> <td>12.4.0.0-16.14.0</td> <td></td> <td></td> </tr> <tr> <td>OCUDR-B</td> <td>Ready</td> <td>Standby</td> <td>Network OAM&P</td> <td>OAM&P</td> <td>12.4.0.0-16.14.0</td> <td></td> <td></td> </tr> </tbody> </table>	Hostname	Upgrade State	OAM HA Role	Server Role	Function	Application Version	Start Time	Finish Time	Server Status	Appl HA Role	Network Element		Upgrade ISO	Status Message		OCUDR-A	Ready	Active	Network OAM&P	OAM&P	12.4.0.0-16.14.0			OCUDR-B	Ready	Standby	Network OAM&P	OAM&P	12.4.0.0-16.14.0		
Hostname	Upgrade State	OAM HA Role		Server Role	Function	Application Version	Start Time	Finish Time																									
	Server Status	Appl HA Role	Network Element		Upgrade ISO	Status Message																											
OCUDR-A	Ready	Active	Network OAM&P	OAM&P	12.4.0.0-16.14.0																												
OCUDR-B	Ready	Standby	Network OAM&P	OAM&P	12.4.0.0-16.14.0																												
21. <input type="checkbox"/>	Verify application version	Verify the Application Version value for this server has been downgraded to the original release version.																															
THIS PROCEDURE HAS BEEN COMPLETED																																	

Appendix E. Verifying servers are Syncronized

Procedure 22: Verifying servers are Syncronized

Step	Procedure	Result																																																							
1. <input type="checkbox"/>	<p>Active NOAMP VIP: Confirm servers are in sync before upgrading the next server</p> <p>1. Navigate to Main Menu → Status & Manage → Database 2. Repl Status is Allowed 3. The DB Levels is the same or close in numbers.</p>	<p>Main Menu: Status & Manage -> Database</p>  <table border="1"> <thead> <tr> <th>Network Element</th><th>Server</th><th>Role</th><th>OAM Max HA Role</th><th>Application Max HA Role</th><th>Status</th><th>DB Level</th><th>OAM Repl Status</th><th>SIG Repl Status</th><th>Repl Status</th><th>Repl Audit Status</th></tr> </thead> <tbody> <tr> <td>Site2_NE_DR_NO</td><td>DR-OCUDR-B</td><td>Network OAM&P</td><td>Spare</td><td>N/A</td><td>Normal</td><td>0</td><td>Normal</td><td>NotApplicable</td><td>Allowed</td><td>NotApplicable</td></tr> <tr> <td>Site1_NE_NO</td><td>OCUDR-A</td><td>Network OAM&P</td><td>Active</td><td>N/A</td><td>Normal</td><td>0</td><td>Normal</td><td>NotApplicable</td><td>Allowed</td><td>NotApplicable</td></tr> <tr> <td>Site1_NE_NO</td><td>OCUDR-B</td><td>Network OAM&P</td><td>Standby</td><td>N/A</td><td>Normal</td><td>0</td><td>Normal</td><td>NotApplicable</td><td>Allowed</td><td>NotApplicable</td></tr> <tr> <td>Site2_NE_DR_NO</td><td>DR-OCUDR-A</td><td>Network OAM&P</td><td>Spare</td><td>N/A</td><td>Normal</td><td>0</td><td>Normal</td><td>NotApplicable</td><td>Allowed</td><td>NotApplicable</td></tr> </tbody> </table>	Network Element	Server	Role	OAM Max HA Role	Application Max HA Role	Status	DB Level	OAM Repl Status	SIG Repl Status	Repl Status	Repl Audit Status	Site2_NE_DR_NO	DR-OCUDR-B	Network OAM&P	Spare	N/A	Normal	0	Normal	NotApplicable	Allowed	NotApplicable	Site1_NE_NO	OCUDR-A	Network OAM&P	Active	N/A	Normal	0	Normal	NotApplicable	Allowed	NotApplicable	Site1_NE_NO	OCUDR-B	Network OAM&P	Standby	N/A	Normal	0	Normal	NotApplicable	Allowed	NotApplicable	Site2_NE_DR_NO	DR-OCUDR-A	Network OAM&P	Spare	N/A	Normal	0	Normal	NotApplicable	Allowed	NotApplicable
Network Element	Server	Role	OAM Max HA Role	Application Max HA Role	Status	DB Level	OAM Repl Status	SIG Repl Status	Repl Status	Repl Audit Status																																															
Site2_NE_DR_NO	DR-OCUDR-B	Network OAM&P	Spare	N/A	Normal	0	Normal	NotApplicable	Allowed	NotApplicable																																															
Site1_NE_NO	OCUDR-A	Network OAM&P	Active	N/A	Normal	0	Normal	NotApplicable	Allowed	NotApplicable																																															
Site1_NE_NO	OCUDR-B	Network OAM&P	Standby	N/A	Normal	0	Normal	NotApplicable	Allowed	NotApplicable																																															
Site2_NE_DR_NO	DR-OCUDR-A	Network OAM&P	Spare	N/A	Normal	0	Normal	NotApplicable	Allowed	NotApplicable																																															

Appendix F. Determine if TVOE Upgrade is Required

When upgrading a server that exists as a virtual guest on a TVOE host, it is first necessary to determine whether the TVOE host (that is, bare-metal) server must first be upgraded to a newer release of TVOE.

NOAM servers are often implemented as TVOE guests in C-class deployments, so the TVOE upgrade check is necessary. MPs are deployed as guests on the same TVOE host as the OAM servers, and so by the time the MP servers are being upgraded, TVOE has been upgraded and there is no need to do so again.

NOTE: This procedure does not apply to Oracle Communications User Data Repository Cloud based systems.

This procedure checks if TVOE upgrade is required.

Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.

Procedure 23: Determine if TVOE Upgrade is Required

Step	Procedure	Result
1. <input type="checkbox"/>	Determine the version of TVOE running on the server that hosts the virtual guest being upgraded.	<p>1. Log into the host server where TVOE is installed.</p> <p>2. Run the following command to get the current TVOE installed version:</p> <pre>[root@udrTVOEblade2 ~]# appRev Install Time: Tue Aug 7 08:17:52 2012 Product Name: TVOE Product Release: 2.0.0_80.16.0 Part Number ISO: 872-2290-104 Part Number USB: 872-2290-104 Base Distro Product: TPD Base Distro Release: 6.0.0_80.16.0 Base Distro ISO: TPD.install-6.0.0_80.16.0-CentOS7.4 -x86_64.iso OS: CentOS 6.2</pre>
2. <input type="checkbox"/>	Check the TVOE release version required for target release	Contact My Oracle Support referring Appendix J of this document to determine the appropriate release version.
3. <input type="checkbox"/>	If the release in Step 1 is less than what is required in Step 2 then upgrade of TVOE is required	The procedure to upgrade TVOE on the host server is in Appendix G.

Appendix G. Upgrade TVOE Platform

This appendix provides the procedure for upgrading TVOE on a host server that supports one or more Oracle Communications User Data Repository virtual guests.

If upgrading an Oracle Communications User Data Repository server that is deployed as a virtual guest on a bare-metal server running the TVOE host software, then TVOE itself may have to be upgraded first. Refer to Appendix F to determine if a TVOE upgrade is required.

NOTES:


- If you are upgrading a server that is not virtualized by TVOE, then this Appendix does not apply.
- This procedure does not apply to Oracle Communications User Data Repository Cloud based systems.

This procedure verifies that all required materials are present.

Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.

Procedure 24: Upgeade TVOE Platform

Step	Procedure	Result
1. <input type="checkbox"/>	Disable all the applications running on current TVOE.	<p>1. Access the primary NOAMP GUI as specified in Appendix A</p> <p>2. Navigate to Status & Manage → Server</p> <p>The Server Status screen is displayed</p> <p>3. Identify the SO or MP (virtual) servers that are running on the TVOE environment to be upgraded, and select these</p> <p>4. Click Stop.</p> <p>5. Confirm the operation by clicking OK</p> <p>6. Verify that the Appl State for all the selected servers changed to Disabled</p>
2. <input type="checkbox"/>	Find out the guests running on TVOE host.	<p>List the guests running on the TVOE host by using following command:</p> <pre># ssh admusr@<TVOE IP> login as: admusr password: <enter password> Switch to root su - password: <enter password> # virsh list --all</pre> <p>NOTE: The output of the <code>virsh list</code> command lists all the guests running on current TVOE host.</p>
3. <input type="checkbox"/>	Shutdown each guest running on TVOE host.	<p>Run the following command for each guest identified in Step 2:</p> <pre># virsh shutdown <guestname></pre> <p>NOTES</p> <ul style="list-style-type: none"> • Alternatively, you can use the Manage software inventory screen on PM&C to shutdown the guests. • Server is not listed on the Status & Manage screen after being shutdown from the TVOE host.

Step	Procedure	Result
4. <input type="checkbox"/>	Upgrade TVOE	<p>Periodically run the following command until the command displays no entries. This means that all VMs have been shut down:</p> <pre data-bbox="584 270 747 297"># virsh list</pre> <p>After all VMs are down, upgrade TVOE using PM&C Aided TVOE Upgrade Procedure from <i>TVOE 3.4 Software Upgrade Document</i>, E80324, latest revision.</p> <p>NOTE: If active NO is hosted on the TVOE which is being upgraded, then VIP may be lost until TVOE is successfully upgraded.</p>
5. <input type="checkbox"/>	After completed	<p>After the TVOE upgrade is completed on the host server, the applications may not be started automatically.</p> <p>Proceed with the next step to restore service.</p>
6. <input type="checkbox"/>	Verify Enable Virtual Guest Watchdog is set for VM	<p>From the PM&C VM Management form, verify that Enable Virtual Watchdog is selected.</p> 
7. <input type="checkbox"/>	Enable all the applications disabled in step1	<ol style="list-style-type: none"> 1. Enable all applications running on current TVOE: 2. Log into the NOAM VIP GUI 3. Navigate to Status & Manage → Server. The Server Status screen is displayed 4. Select all the applications (NOs/SOs) running on current TVOE, excluding the server which is in upgrade Ready state. The Upgrade State can be verified from the Administration → Upgrade screen. 5. Click Restart. 6. Confirm the operation by clicking OK. 7. Verify that the Appl State for all the selected servers is Enabled.

Appendix H. Change Resources Allocated To VM Guests

H.1 CHANGE VCPU CORES AND RAM ALLOCATED TO NOAMP GUESTS

This Appendix provides the procedure for changing VCPU cores and RAM allocated to NOAMP virtual guests.

This needs PM&C GUI screen.

This procedure has to be followed only if it is being done for either of the following cases:

1. upgrade is being done from G8 profile to G9 profile;
2. upgrade is being done from Oracle Communications User Data Repository 10.2.x Oracle RMS low capacity setup;

NOTE: If you are upgrading to a G8 profile then this appendix does not apply.





NOTE: This procedure does not apply to Oracle Communications User Data Repository Cloud based systems.

This procedure verifies that all required materials are present.

Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.

Procedure 25: Change VCPU Cores and RAM Allocated To NOAMP Guests

Step	Procedure	Result
1. <input type="checkbox"/>	Login to PM&C GUI screen.	<p>Oracle System Login Mon Oct 19 05:33:36 2015 EDT</p> <div style="border: 1px solid #ccc; padding: 10px; width: fit-content; margin: auto;"> <p style="text-align: center;">Log In Enter your username and password to log in</p> <p style="text-align: center;">Session timed out at 5:33:36 am.</p> <div style="display: flex; justify-content: space-between;"> <div style="width: 45%;"> <p>Username: <input type="text" value="pmacadmin"/></p> <p>Password: <input type="password" value="*****"/></p> <p><input type="checkbox"/> Change password</p> </div> <div style="width: 45%;"> <p style="text-align: center;">Log In</p> </div> </div> <p style="text-align: center; font-size: small;">Unauthorized access is prohibited. This Oracle system requires the use of Microsoft Internet Explorer 8.0, 9.0, or 10.0 with support for JavaScript and cookies.</p> </div>

Step	Procedure	Result
2. <input type="checkbox"/>	Navigate to Main Menu->VM Management	
3. <input type="checkbox"/>	Select the TVOE that contains NO server from VM Entities list	
4. <input type="checkbox"/>	Change Current Power State to Shutdown	
5. <input type="checkbox"/>	Click Edit.	

Step	Procedure	Result
6. <input type="checkbox"/>	For Gen9 upgrade only: Change Num vCPUs to 28	<p>Edit VM Guest Name: UDRPV01-S2-NO-LC-B Host: fe80::8edc:d4ff:feae:ad4 Current Power State: Shut Down</p> <p>VM Info Software Network Media</p> <p>Num vCPUs: 28 Memory (MBs): 131,072</p> <p>* Do not oversubscribe the TVOE host's memory.</p> <p>VM UUID: af6edd74-53cc-44ff-8712-d4a955661cbf</p>
7. <input type="checkbox"/>	For Oracle RMS upgrade only: Change Num vCPUs to 36 and Memory (MBs) to 196608	<p>Edit VM Guest Name: NO-A Host: fe80::4405:d3ff:fee6:56d3 Current Power State: Shut Down</p> <p>VM Info Software Network Media</p> <p>Num vCPUs: 36 Memory (MBs): 196,608</p> <p>* Do not oversubscribe the TVOE host's memory.</p> <p>VM UUID: fe38720b-5cf5-4041-acd2-a01569fe1533</p> <p>Enable Virtual Watchdog: <input checked="" type="checkbox"/></p> <p>If an error displays in the GUI and it inhibits allocating 36 vCPU cores to NOAMP, ensure that the PM&C has been upgraded to version 6.0.1.0.1-60.22.0 or higher.</p>
8. <input type="checkbox"/>	Click Save .	<p>Save Cancel</p>
9. <input type="checkbox"/>	Change Current Power State to On	<p>Current Power State: Shut Down</p> <p>On Change</p> <p>NOTE: Power-up procedure takes a while.</p>
10. <input type="checkbox"/>	When the Power is on, the current power state should show running.	<p>View VM Guest Name: UDRPV01-S1-MP-1 Host: Enc: 11902 Bay: 5F Current Power State: Running</p> <p>VM Info Software Network Media</p>
THIS PROCEDURE HAS BEEN COMPLETED		

Appendix I. Configuring Services for Dual Path HA


This Appendix provides the procedure for updating Oracle Communications User Data Repository Services for the Dual Path HA feature. This applies to all configurations that make use of a Secondary/DR Site.

This procedure verifies that all required materials are present.

Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.

Procedure 26: Configuring Services for Dual Path HA

Step	Procedure	Result																								
1. <input type="checkbox"/>	Using the VIP address, access the primary NOAMP GUI.	Access the primary NOAMP GUI as specified in Appendix A.																								
2. <input type="checkbox"/>	Active NOAMP VIP: Navigate to Main Menu → Configuration → Networking → Services	<p>Main Menu: Configuration > Networking > Services</p> <table border="1"> <thead> <tr> <th>Name</th> <th>Intra-NE Network</th> <th>Inter-NE Network</th> </tr> </thead> <tbody> <tr> <td>OAM</td> <td>IMI</td> <td>XMI</td> </tr> <tr> <td>Replication</td> <td>IMI</td> <td>XMI</td> </tr> <tr> <td>Signaling</td> <td>XSH1</td> <td>XSH1</td> </tr> <tr> <td>HA_Secondary</td> <td>IMI</td> <td>XSH1</td> </tr> <tr> <td>HA_MP_Secondary</td> <td>IMI</td> <td>XMI</td> </tr> <tr> <td>Replication_MP</td> <td>IMI</td> <td>XMI</td> </tr> <tr> <td>ComAgent</td> <td>IMI</td> <td>XSH1</td> </tr> </tbody> </table>	Name	Intra-NE Network	Inter-NE Network	OAM	IMI	XMI	Replication	IMI	XMI	Signaling	XSH1	XSH1	HA_Secondary	IMI	XSH1	HA_MP_Secondary	IMI	XMI	Replication_MP	IMI	XMI	ComAgent	IMI	XSH1
Name	Intra-NE Network	Inter-NE Network																								
OAM	IMI	XMI																								
Replication	IMI	XMI																								
Signaling	XSH1	XSH1																								
HA_Secondary	IMI	XSH1																								
HA_MP_Secondary	IMI	XMI																								
Replication_MP	IMI	XMI																								
ComAgent	IMI	XSH1																								

Step	Procedure	Result
3. <input type="checkbox"/>	<p>Active NOAMP VIP: Change Service value.</p> <p>1. Change Inter-NE HA_Secondary to XSI1. 2. Click Apply. 3. Click OK.</p>	 <div data-bbox="685 1140 1330 1362"> <p>You must restart all Servers to apply any services changes, ComAgent</p> <p>OK Cancel</p> </div> <p>NOAMP and MP servers need to be restarted.</p>
4. <input type="checkbox"/>	<p>Active NOAMP VIP: The Services configuration screen opens.</p>	

Step	Procedure	Result																																			
5. <input type="checkbox"/>	Reboot all NOAMP servers	<p>Reboot all NOAMP servers either by using:</p> <ul style="list-style-type: none"> The active NOAMP GUI Status & Manage → Server screen and click Reboot: <div data-bbox="556 291 1462 686"> <p>Main Menu: Status & Manage -> Server</p> <p>Filter* ▾</p> <table border="1"> <thead> <tr> <th>Server Hostname</th> <th>Network Element</th> <th>Appl State</th> <th>Alm</th> <th>DB</th> <th>Reporting Status</th> <th>Proc</th> </tr> </thead> <tbody> <tr> <td>DR-OCUDR-A</td> <td>Site2_NE_DR_NO</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>DR-OCUDR-B</td> <td>Site2_NE_DR_NO</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>OCUDR-A</td> <td>Site1_NE_NO</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>OCUDR-B</td> <td>Site1_NE_NO</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> </tbody> </table> <div data-bbox="736 580 1274 686"> <p>Stop Restart Reboot NTP Sync Report</p> </div> <ul style="list-style-type: none"> The terminal of each server with the reboot command: <pre>\$ sudo reboot</pre> <p>NOTE: This is performed on all NOAMPs.</p> </div>	Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc	DR-OCUDR-A	Site2_NE_DR_NO	Enabled	Err	Norm	Norm	Norm	DR-OCUDR-B	Site2_NE_DR_NO	Enabled	Err	Norm	Norm	Norm	OCUDR-A	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm	OCUDR-B	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm
Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc																															
DR-OCUDR-A	Site2_NE_DR_NO	Enabled	Err	Norm	Norm	Norm																															
DR-OCUDR-B	Site2_NE_DR_NO	Enabled	Err	Norm	Norm	Norm																															
OCUDR-A	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm																															
OCUDR-B	Site1_NE_NO	Enabled	Err	Norm	Norm	Norm																															

THIS PROCEDURE HAS BEEN COMPLETED

Appendix J. My Oracle Support

My Oracle Support (<https://support.oracle.com>) is your initial point of contact for all product support and training needs. A representative at Customer Access Support (CAS) can assist you with My Oracle Support registration.

Call the CAS main number at 1-800-223-1711 (toll-free in the US), or call the Oracle Support hotline for your local country from the list at <http://www.oracle.com/us/support/contact/index.html>. When calling, make these selections on the Support telephone menu:

1. Select **2** for New Service Request
2. Select **3** for Hardware, Networking and Solaris Operating System Support
3. Select one of the following options:
 - o For Technical issues such as creating a Service Request (SR), Select **1**
 - o For Non-technical issues such as registration or assistance with My Oracle Support, Select **2**

You are connected to a live agent who can assist you with My Oracle Support registration and opening a support ticket.

My Oracle Support is available 24 hours a day, 7 days a week, 365 days a year.

Appendix K. Locate Product Documentation on the Oracle Help Center SITE

Oracle Communications customer documentation is available on the web at the Oracle Help Center (OHC) site, <http://docs.oracle.com>. You do not have to register to access these documents. Viewing these files requires Adobe Acrobat Reader, which can be downloaded at <http://www.adobe.com>.

1. Log into the Oracle Technology Network site at <http://docs.oracle.com>.
2. Select the **Find a product**
3. Enter **User Data Repository**

Takes you to CGBU Documentation.
A list of the documentation set for the selected product and release displays.
4. Select **User Data Repository** followed by version
5. To download a file to your location, right-click the **PDF**, select **Save target as** (or similar command based on your browser), and save to a local folder.