

Oracle GL Adapter IBM WebSphere MQ Installation  
Oracle FLEXCUBE Universal Banking  
Release 14.4.0.0.0  
[May] [2020]



---

# Table of Contents

|           |   |             |
|-----------|---|-------------|
| <b>1.</b> | <b>CONFIGURING IBM WEBSPHERE MQ.....</b>                                  | <b>1-1</b>  |
| 1.1       | PREREQUISITE .....  | 1-1         |
| 1.2       | CREATING QUEUE MANAGER.....   | 1-1         |
| 1.2.1     | Using WebSphere MQ Explorer.....  | 1-1         |
| 1.3       | CREATING QUEUES IN THAT QUEUE MANAGER .....                               | 1-6         |
| 1.3.1     | Using WebSphere MQ Explorer .....   | 1-6         |
| 1.4       | BINDING THE QUEUE WITH THE JNDI PROVIDER.....                             | 1-11        |
| 1.4.1     | Binding of the Queues Managers and Queues.....                            | 1-11        |
| <b>2.</b> | <b>CREATING AND MAPPING JMS RESOURCES IN WEBSPHERE APPLICATION SERVER</b> | <b>2-1</b>  |
| 2.1       | CREATION OF WEBSPHERE MQ QUEUE CONNECTION FACTORIES.....                  | 2-1         |
| 2.2       | CREATION OF WEBSPHERE MQ QUEUE DESTINATIONS .....                         | 2-10        |
| 2.3       | CREATION OF MESSAGE LISTENER PORTS .....                                  | 2-4         |
| <b>3.</b> | <b>APPENDIX .....</b>   | <b>3-13</b> |
| 3.1       | ORACLE GL ADAPTER INSTALLATION DOCUMENTS .....                            | 3-13        |

---

# 1. Configuring IBM WebSphere MQ


## 1.1 Prerequisite

- ✓ Make sure that WebSphere MQ 6.0 (with JMS Bindings) is installed. If it is not installed then please contact WebSphere MQ Administrator for getting it installed on your machine.
- ✓ X-Windows for using WebSphere MQ Explorer on UNIX machines.


## 1.2 Creating Queue Manager

### 1.2.1 Using WebSphere MQ Explorer

1. Go to Start→Programs→IBM WebSphere MQ→ WebSphere MQ Explorer.



2. Right-click on the queue manager's icon, from the popup menu select New, and select Queue Manager.



3. Give the name of the Queue Manager

✓ Click on the check box specifying Make this the default Queue Manager

✓ Click on Finish

**Create Queue Manager**

**Queue Manager**  
Enter basic values (Step 1)

**Queue manager name:** QM\_cvrhp1455

☒ Make this the default queue manager

Default transmission queue:

Dead letter queue:

Max handle limit: 256

Trigger interval: 999999999

Max uncommitted messages: 10000

< Back   Next >   **Finish**   Cancel

4. Following screen shall be displayed

[Note: Make sure that the Queue Manager is started and Running]

The screenshot displays the IBM WebSphere MQ Explorer interface. On the left, the 'Navigator' pane shows a tree structure with 'Queue Managers' expanded, and 'QM\_cvrhp1455' selected. The main 'Content' pane shows the 'Queue Manager QM\_cvrhp1455' details. It includes three sections: 'Connection QuickView', 'Status QuickView', and 'Properties QuickView', each with a table of attributes and their values. The 'Connection QuickView' table shows 'Connection status' as 'Connected' and 'Connection type' as 'Local'. The 'Status QuickView' table shows 'Queue manager status' as 'Running'. The 'Properties QuickView' table shows 'Queue manager name' as 'QM\_cvrhp1455' and 'Platform' as 'Windows'.

| Connection QuickView:    |           |
|--------------------------|-----------|
| Connection status        | Connected |
| Connection type          | Local     |
| Connection name          |           |
| Channel name             |           |
| Channel definition table |           |
| Refresh interval         | 15        |
| Autoreconnect            | Yes       |
| Last updated: 17:25:15   |           |


| Status QuickView:        |         |
|--------------------------|---------|
| Queue manager status     | Running |
| Command server status    |         |
| Channel initiator status |         |
| Connection count         |         |
| Last updated: 17:20:14   |         |

| Properties QuickView:      |              |
|----------------------------|--------------|
| Queue manager name         | QM_cvrhp1455 |
| Description                |              |
| Platform                   | Windows      |
| Command level              | 600          |
| Default transmission queue |              |
| Startup                    | Automatic    |

## 1.3 Creating Queues in that Queue manager

### 1.3.1 Using WebSphere MQ Explorer

1. Open the queue manager in the explorer which was created as in section 1.2
  - ✓ Right-click on the queues icon.
  - ✓ From the popup menu select New, and then select Local Queue as shown bellow.



2. Following screen will be displayed. Type the Name of the Queue and then Click on Next.

New Local Queue

Create a Local Queue

Enter the details of the object you wish to create

Name:

NOTIFY\_DEST\_QUEUE

Create it with the attributes like:

SYSTEM.DEFAULT.LOCAL.QUEUE

Select...

< Back Next > Finish Cancel

3. Following screen will be displayed.

- ✓ In General Properties Tab for Persistence Attribute, select **Persistent** from drop down list.

**New Local Queue**

**Change properties**  
Change the properties of the new Local Queue

**General**

Queue name: NOTIFY\_DEST\_QUEUE

Queue type: Local

Description:

Put messages: Allowed

Get messages: Allowed

Default priority: 0

Persistence: Persistent

Scope: Queue manager

Usage: Normal

< Back Next > Finish Cancel

4. Click on Extended on the Left Hand side. Following screen will be displayed.

- ✓ For **Max queue depth**, enter **999999999**.
- ✓ For **Max message length**, enter **104857600**.
- ✓ Click on Finish.

The screenshot shows a window titled "New Local Queue" with a subtitle "Change properties". Below the subtitle is the instruction "Change the properties of the new Local Queue". On the left is a tree view with the following items: General, Extended (highlighted with a red box), Cluster, Triggering, Events, Storage, and Statistics. The main area is titled "Extended" and contains the following settings:

- Max queue depth: 999999999 (boxed with a red rectangle)
- Max message length: 104857600 (boxed with a red rectangle)
- Shareability: Shareable
- Default input open option: Input shared
- Message delivery sequence: Priority
- Retention interval: 999999999
- Definition type: Predefined
- Distribution lists: Not Supported

At the bottom right are four buttons: "< Back", "Next >", "Finish" (boxed with a red rectangle), and "Cancel".

5. Following screen will be displayed.

- ✓ Make sure that the Queue is displayed in Contents Window.



## 1.4 **Binding the Queue with the JNDI provider**

IBM provides a tool called JmsAdmin tool for binding (JNDI) the queue managers and queues with the JNDI providers. Right now the most popular JNDI provider is file system JNDI provider. This document lists steps for JNDI binding of the queue managers and queues with the file system JNDI provider.

JmsAdmin tool can be found under,

<WEBPSHERE\_MQ\_HOME>\java\bin (On Windows as well as on UNIX)

where,

WEBPSHERE\_MQ\_HOME is the directory where IBM WebSphere MQ is installed.

### 1.4.1 **Binding of the Queues Managers and Queues**

1. Make sure that you have also installed WebSphere MQ client on the server. This can be confirmed by the presence of folder <WEBPSHERE \_HOME>\java\bin.
2. Make sure that all the jar files inside the folder <WEBPSHERE \_HOME>\java\lib is listed in the classpath.
3. Go to the folder <WEBPSHERE \_HOME>\java\bin
4. Open file JMSAdmin.config
5. Now modify the parameter "INITIAL\_CONTEXT\_FACTORY". This parameter should be equal to the value com.sun.jndi.fscontext.RefFSContextFactory. This parameter indicates context factory of the Messaging Server and same property is supposed to be maintained in the properties file.

e.g.:

INITIAL\_CONTEXT\_FACTORY=com.sun.jndi.fscontext.RefFSContextFactory

For Commenting any line use the symbol #

e.g.:

#INITIAL\_CONTEXT\_FACTORY=com.sun.jndi.fscontext.RefFSContextFactory is the commented line.

6. Now modify the parameter called "PROVIDER\_URL" in this file to the required value.

e.g.: PROVIDER\_URL=file:/C:/jmsobj (Windows)

PROVIDER\_URL=file:/home/KERNEL/jmsobj (UNIX)

This parameter indicates a directory on the local disc where the JMS binding file is to be created. Same property is supposed to be maintained in the KERNEL properties file. This should be an existing directory on the machine.

7. After saving the changes open a new command prompt
8. Go to <WEBPSHERE \_HOME>\java\bin
9. Type "jmsadmin" on the prompt and press enter

e.g. C:\IBM\WebSphereMQ\java\bin>jmsadmin (windows)

\$ jmsadmin (UNIX)

10. This should clear the command window and give a prompt like

**InitCtx>**

Here the bindings for the Queue manager and the queues will be created.

11. For creating bindings for the connection to the Queue manager type the following command on the command window.

```
define qcf(<JNDI_MAPPING_OF_QUEUE_MANAGER>) qmgr(<QUEUE_MANAGER_NAME>)  
host(<IP_ADD_OF_MQ_SERVER_MACHINE>) port (<PORT_OF_QUEUE_MANAGER>)  
tran (CLIENT)
```

e.g. InitCtx>define qcf (ADOGL\_MDBQCF) qmgr(QM\_cvrhp1453) host (10.80.4.102) port(1414) tran(CLIENT)

**[Note: This command has to be given in a single line.]**

This defines the JNDI mapping (ADOGL\_MDBQCF) for the queue manager (QM\_cvrhp1455) running on machine (10.70.4.56) and port (1414)

This JNDI mapping (ADOGL\_MDBQCF) should be the same as that maintained in the properties file (ADOGL\_MDB\_Prop.properties) parameter (ADOGL\_MDB\_JMS\_QCF) value.

e.g. ADOGL\_MDB\_JMS\_QCF= ADOGL\_MDBQCF

12. For creating bindings for the queues type the following command on the command window.

**DEFINE Q(<QUEUE\_NAME>) QUEUE(<QUEUE\_NAME>) QMGR(<QUEUE\_MANAGER\_NAME>)**

e.g.: InitCtx> DEFINE Q(NOTIFY\_DEST\_QUEUE) QUEUE(NOTIFY\_DEST\_QUEUE) QMGR(QM\_cvrhp1455)

This will bind the queue called "NOTIFY\_DEST\_QUEUE" by the binding name "NOTIFY\_DEST\_QUEUE" to the queue manager "QM\_cvrhp1455". Normally the binding name and the queue name should be the same as shown in this example.

---


## 2. Creating and Mapping JMS Resources in WebSphere Application Server

### 2.1 Creation of WebSphere MQ Queue Connection Factories

1. On the Left Hand Side of the WebSphere Application Server Admin Console, click on **Resources** and Expand the **JMS Providers**.
2. Now click on **WebSphere MQ** option.
3. Following screen will be displayed. Select the **Node** Option and then press **Apply**.
4. Now Click on **WebSphere MQ Queue connection factories** listed under Additional Properties



5. Following screen will be displayed. Click on **New**.



6. Following screen will be displayed.

✓ Configure the details as mentioned below:

|                        |  |
|------------------------|--|
| <b>Name:</b>           | ADOGL_MDBQCF (Name of the QCF as specified)          |
| <b>JNDI Name:</b>      | ADOGL_MDBQCF (Name of the QCF as specified)          |
| <b>Queue Manager:</b>  | Name of the Queue Manager that we create in IBM MQ.  |
| <b>Host:</b>           | IP Address of the Machine where IBM MQ is installed. |
| <b>Port:</b>           | 1414. (CONFIGURABLE AS PER REQUIREMENT)              |
| <b>Transport Type:</b> | CLIENT.  |

**[Note: The rest all fields are optional and can be ignored. Some of the fields will have values which will be defaulted automatically. ]**

WebSphere MQ messaging provider

WebSphere MQ messaging provider

Messages

Additional Properties for this object will not be available to edit until its general properties are applied by clicking on either Apply or OK.

WebSphere MQ messaging provider > WebSphere MQ queue connection factories > New

A queue connection factory is used to create connections to the associated JMS provider of JMS queue destinations, for point-to-point messaging. Use WebSphere MQ queue connection factory administrative objects to manage queue connection factories for the WebSphere MQ JMS provider.

Configuration

General Properties

\* Scope  
cells:cvrhp1455Node01Cell:nodes:cvrhp1455Node01

\* Name  
ADOGL\_MDBQCF

\* JNDI name  
ADOGL\_MDBQCF

Description  
Queue Connection Factory for Oracle GL Adapter

Category

Component-managed authentication alias  
(none)

Container-managed authentication alias  
(none)

Mapping-configuration alias  
(none)

The additional properties will not be available until the general properties for this item are saved.

Additional Properties

Custom properties

Connection pool

Session pools

Related Items

J2EE Connector Architecture (J2C) authentication data entries

Queue manager  
QM\_cvrhp1455

Host  
10.80.4.138

Port  
1414

Channel

Transport type  
CLIENT

Model queue definition

Client ID

CCSID

☒ Enable message retention

☒ XA enabled

☒ Enable return methods during shutdown

Local server address

Polling interval  
5000 milliseconds

Rescan interval  
5000 milliseconds

SSL cipher suite

SSL CRL

SSL peer name

Temporary queue prefix

7. Make sure following two are selected,

- ✓ **XA Enabled**
- ✓ **Enable MQ connection pooling**

Then click on **Apply**

The screenshot shows a configuration window with the following fields and options:


- Client ID:
- CCSID:
- ☒ Enable message retention
- ☒ XA enabled
- ☒ Enable return methods during shutdown
- Local server address:
- Polling interval:  milliseconds
- Rescan interval:  milliseconds
- SSL cipher suite:
- SSL CRL:
- SSL peer name:
- Temporary queue prefix:
- ☒ Enable MQ connection pooling
- Buttons:


8. Following screen will be displayed. Click on **Save**.

WebSphere MQ messaging provider

**WebSphere MQ messaging provider** ?

☐ Messages

 Changes have been made to your local configuration. Click **Save** to apply changes to the master configuration.

 The server may need to be restarted for these changes to take effect.

**WebSphere MQ messaging provider** > **WebSphere MQ queue connection factories** > **ADOGL\_MDBQCF**

A queue connection factory is used to create connections to the associated JMS provider of JMS queue destinations, for point-to-point messaging. Use WebSphere MQ queue connection factory administrative objects to manage queue connection factories for the WebSphere MQ JMS provider.

Configuration

**General Properties**

\* Scope  
cells:cvrhp1455Node01Cell:nodes:cvrhp1455Node01

\* Name  
ADOGL\_MDBQCF

\* JNDI name  
ADOGL\_MDBQCF

Description  
Queue Connection Factory for Oracle GL Adapter

Category

Component-managed authentication alias  
(none)

Container-managed authentication alias  
(none)

Mapping-configuration alias  
(none)


**Additional Properties**

- [Custom properties](#)
- [Connection pool](#)
- [Session pools](#)

**Related Items**

- [J2EE Connector Architecture \(J2C\) authentication data entries](#)

9. Following screen will be displayed. Click on **Save**.



10. Following screen will be displayed.

- ✓ It should show the Queue Connection Factory that has been created in the above steps as shown bellow.





**WebSphere MQ messaging provider** ?

[WebSphere MQ messaging provider](#) > **WebSphere MQ queue connection factories**

A queue connection factory is used to create connections to the associated JMS provider of JMS queue destinations, for point-to-point messaging. Use WebSphere MQ queue connection factory administrative objects to manage queue connection factories for the WebSphere MQ JMS provider.

⊕ Preferences

New Delete

| Select                   | Name ↕                       | JNDI name ↕  | Description ↕                                  | Category ↕ |
|--------------------------|------------------------------|--------------|--|------------|
| <input type="checkbox"/> | <a href="#">ADOGL_MDBQCF</a> | ADOGL_MDBQCF | Queue Connection Factory for Oracle GL Adapter |            |

Total 1

## 2.2 Creation of WebSphere MQ Queue Destinations

1. On the Left Hand Side of the WebSphere Application Server Admin Console, click on **Resources** and Expand the **JMS Providers**.
2. Now click on **WebSphere MQ** option.
3. Following screen will be displayed. Select the **Node** Option and then press **Apply**.
4. Now Click on **WebSphere MQ Queue destinations** listed under Additional Properties

WebSphere MQ messaging provider

**WebSphere MQ messaging provider**

A JMS provider enables asynchronous messaging based on the Java Message Service (JMS). It provides J2EE connection factories to create connections for specific JMS queue or topic destinations. WebSphere MQ JMS provider administrative objects are used to manage JMS resources for WebSphere MQ as the JMS provider.

Configuration

☐ Scope: Cell=**CVRDD0722Node01Cell**, Node=**CVRDD0722Node01**

☐ Cell : CVRDD0722Node01Cell Scope specifies the level at which the resource definition is visible. For detailed information on what scope is and how it works, [see the scope settings help](#)

☒ **Node : CVRDD0722Node01**

☐ Server : server1

**Apply**

**General Properties**

Scope  
cells:CVRDD0722Node01Cell:nodes:CVRDD0722Node01

Name  
WebSphere MQ JMS Provider

Description  
WebSphere MQ Messaging Provider

Class path  
\${MQJMS\_LIB\_ROOT}

Native library path  
\${MQJMS\_LIB\_ROOT}

**Additional Properties**

- [WebSphere MQ connection factories](#)
- [WebSphere MQ queue connection factories](#)
- [WebSphere MQ queue destinations](#)**
- [WebSphere MQ topic connection factories](#)
- [WebSphere MQ topic destinations](#)

**Back**

- Following screen will be displayed. Click on **New**.

WebSphere MQ messaging provider

**WebSphere MQ messaging provider** > **WebSphere MQ queue destinations**

Queue destinations provided for point-to-point messaging by the WebSphere MQ JMS provider. Use WebSphere MQ queue destination administrative objects to manage queue destinations for the WebSphere MQ JMS provider.

⊕ Preferences

**New** Delete

⊞ ⊞ ⊞ ⊞

| Select  | Name ▾ | JNDI name ▾ | Description ▾ | Category ▾ |
|---------|--------|-------------|---------------|------------|
| None    |        |             |               |            |
| Total 0 |        |             |               |            |

- Following screen will be displayed. Configure with the details as mentioned below and click on **Apply**.

|                            |   |
|----------------------------|---|
| <b>Name:</b>               | NOTIFY_DEST_QUEUE (Name of the queue as specified)              |
| <b>JNDI Name:</b>          | NOTIFY_DEST_QUEUE (Name of the queue as specified)              |
| <b>Base Queue Name:</b>    | NOTIFY_DEST_QUEUE (Name of the queue as specified)              |
| <b>Queue Manager Host:</b> | IP Address of the Machine where the IBM MQ server is installed. |
| <b>Port:</b>               | 1414. MQ Port (CONFIGURABLE AS PER REQUIREMENT)                 |

*[Note: The Rest of the fields are optional and some are de-faulted automatically and hence can be ignored.]*

WebSphere MQ messaging provider ?

☐ Messages
 

Additional Properties for this object will not be available to edit until its general properties are applied by clicking on either Apply or OK.

[WebSphere MQ messaging provider](#) > [WebSphere MQ queue destinations](#) > New

Queue destinations provided for point-to-point messaging by the WebSphere MQ JMS provider. Use WebSphere MQ queue destination administrative objects to manage queue destinations for the WebSphere MQ JMS provider.

Configuration

General Properties

\* Scope

cells:cvrhp1455Node01Cell:nodes:cvrhp1455Node01

\* Name

NOTIFY\_DEST\_QUEUE

\* JNDI name

NOTIFY\_DEST\_QUEUE

Description

Incoming Queue for ADOGL\_MDB

Category

Persistence

APPLICATION DEFINED

Priority

APPLICATION DEFINED

Specified priority

0

Expiry

APPLICATION DEFINED

The additional properties will not be available until the general properties for this item are saved.

Additional Properties

Custom properties

MQ Config

2-12

ORACLE

Specified expiry  
0 milliseconds

\* Base queue name  
NOTIFY\_DEST\_QUEUE  
Base queue manager name  
QM\_cvrhp1455

CCSID

☐ Use native encoding

Integer encoding  
Normal

Decimal encoding  
Normal

Floating point encoding  
IEEENormal

Target client  
JMS

#### WebSphere MQ Queue Connection Properties

Queue manager host  
10.80.4.138  
Queue manager port  
1414

Server connection channel name

User ID

Password

Apply OK Reset Cancel

7. Following screen will be displayed. Click on **Save**.

WebSphere MQ messaging provider

WebSphere MQ messaging provider

Messages

⚠

Changes have been made to your local configuration. Click **Save** to apply changes to the master configuration.

ℹ

The server may need to be restarted for these changes to take effect.

[WebSphere MQ messaging provider](#) > [WebSphere MQ queue destinations](#) > NOTIFY\_DEST\_QUEUE

Queue destinations provided for point-to-point messaging by the WebSphere MQ JMS provider. Use WebSphere MQ queue destination administrative objects to manage queue destinations for the WebSphere MQ JMS provider.

Configuration

General Properties

\* Scope

cells:cvrhp1455Node01Cell:nodes:cvrhp1455Node01

\* Name

NOTIFY\_DEST\_QUEUE

\* JNDI name

NOTIFY\_DEST\_QUEUE

Description

Incoming Queue for ADOGL\_MDB

Category

Persistence

APPLICATION DEFINED

Priority

APPLICATION DEFINED

Specified priority

0

Expiry

Additional Properties

Custom properties

MQ Config

2-1

ORACLE

8. Following screen will be displayed. Click on **Save**.

WebSphere MQ messaging provider

**WebSphere MQ messaging provider** ? -

[WebSphere MQ messaging provider](#) > [WebSphere MQ queue destinations](#) > NOTIFY\_DEST\_QUEUE > **Save**

Save your workspace changes to the master configuration

Click Save to update the master repository with your changes. Click Discard to discard your changes and begin work again using the master repository configuration. Click Cancel to continue working with your changes.

⊕ Total changed documents: 1

Save

Discard

Cancel

9. Following screen will be displayed. Click on **Save**.

- ✓ It should show the Queue that has been created in the above steps as shown bellow.

WebSphere MQ messaging provider

**WebSphere MQ messaging provider** ?

[WebSphere MQ messaging provider](#) > **WebSphere MQ queue destinations**

Queue destinations provided for point-to-point messaging by the WebSphere MQ JMS provider. Use WebSphere MQ queue destination administrative objects to manage queue destinations for the WebSphere MQ JMS provider.

⊕ Preferences

New Delete


⊞ ⊞ ⊞ ⊞

| Select                   | Name ↕                            | JNDI name ↕       | Description ↕                | Category ↕ |
|--------------------------|-----------------------------------|-------------------|------------------------------|------------|
| <input type="checkbox"/> | <a href="#">NOTIFY_DEST_QUEUE</a> | NOTIFY_DEST_QUEUE | Incoming Queue for ADOGL_MDB |            |

Total 1

## 2.3 Creation of Message Listener Ports

1. On the Left Hand Side Click on Servers and then click on Application Servers.
2. Now Click on **Server1** on Right Hand Side.



The screenshot displays the Oracle WebLogic Server console. On the left, the 'Servers' node is expanded, showing 'Application servers' and 'Web servers'. The 'Application servers' node is selected. The main panel shows the 'Application servers' page, which includes a description of an application server and a table of servers.

**Application servers**

An application server is a server which provides services required to run enterprise applications.

**Preferences**

| Select                   | Name    | Node            | Version |
|--------------------------|---------|-----------------|---------|
| <input type="checkbox"/> | server1 | CVRDD0722Node01 | 6.0.2.0 |

Total 1

3. Following screen will be displayed.

- ✓ Expand **Messaging** under **Communications** and then click on **Message Listener Service**.

**Application servers** > **server1**

An application server is a server which provides services required to run enterprise applications.

**Runtime** | **Configuration**

**General Properties**

Name:

☐ Run in development mode

☒ Parallel start

**Server-specific Application Settings**

Classloader policy:

Class loading mode:

**Container Settings**

- Web Container Settings
- EJB Container Settings
- Container Services
- Business Process Services

**Server messaging**

- Messaging engines
- Messaging engine inbound transports
- WebSphere MQ link inbound transports
- SIB service

**Server Infrastructure**

- Java and Process Management
- Administration

**Communications**

- Ports
- Messaging
  - Message Listener Service

**Performance**

4. Following screen will be displayed. Click on **Listener Ports**.



5. Following screen will be displayed. Click on **New**.



6. Following screen will be displayed. Configure the **Listener Port** with the following details and then click on **Apply**.

|                                      |   |
|--------------------------------------|---|
| <b>Name:</b>                         | OGL_MDB_LISTENER (Name of the Listener can be anything. But remember to give the same name while deploying corresponding MDB)   |
| <b>Initial State:</b>                | Started.  |
| <b>Description:</b>                  | JMSListener Description   |
| <b>Connection Factory JNDI Name:</b> | ADOGL_MDBQCF(The same name that was created under step 5 for WebSphere MQ queue connection factory. Here specify the name of the Queue Connection Factory of the queue on which Listener has to attached) |
| <b>Destination Name:</b>             | NOTIFY_DEST_QUEUE(The same name that was created under step 8 for Wbsphere MQ queue destinations. Here specify the name of the Queue on which Listener has to attached)                                   |

*[Note: The rest all values will be de-faulted automatically.]*

**Application servers** ?

[Application servers](#) > [server1](#) > [Message Listener Service](#) > [Listener Ports](#) > **New**

Listener ports for Message Driven Beans to listen upon for messages. Each port specifies the JMS Connection Factory and JMS Destination that an MDB, deployed against that port, will listen upon.

**Runtime** Configuration

**General Properties**

\* Name  
OGL\_MDB\_LISTENER

\* Initial State  
Started

Description

\* Connection factory JNDI name  
ADOGL\_MDBQCF

\* Destination JNDI name  
NOTIFY\_DEST\_QUEUE

Maximum sessions  
1

Maximum retries  
0

Maximum messages  
1

Apply

OK

Reset

Cancel

7. Following screen will be displayed. Click on **Save**.

#### Application servers

Application servers

Messages

⚠

Changes have been made to your local configuration. Click **Save** to apply changes to the master configuration.

ℹ

The server may need to be restarted for these changes to take effect.

Application servers > server1 > Message Listener Service > Listener Ports > OGL\_MDB\_LISTENER

Listener ports for Message Driven Beans to listen upon for messages. Each port specifies the JMS Connection Factory and JMS Destination that an MDB, deployed against that port, will listen upon.

Runtime

Configuration

General Properties

\* Name

OGL\_MDB\_LISTENER

\* Initial State

Started

Description

\* Connection factory JNDI name

ADOGL\_MDBQCF

\* Destination JNDI name

NOTIFY\_DEST\_QUEUE

Maximum sessions

1

Maximum retries

0

Maximum messages

1

Apply


OK

Reset

Cancel

8. Following screen will be displayed. Click on **Save**.

Application servers




9. Following screen will be displayed.

- ✓ It should show the Listener Port that has been created in the above steps as shown bellow.

Application servers

Clos



10. Restart the Application server then follow steps 1,2,3,4 specified under this section. The Listener Port will be shown as started (as displayed in the following screen).

Application servers Close

---

Application servers

> server1





> Message Listener Service



> Listener Ports

Listener ports for Message Driven Beans to listen upon for messages. Each port specifies the JMS Connection Factory and JMS Destination that an MDB, deployed against that port, will listen upon.

⊞ Preferences

New Delete Start Stop



| Select                   | Name ▾                           | Description ▾ | Connection factory JNDI name ▾ | Destination JNDI name ▾ | Status  |
|--------------------------|----------------------------------|---------------|--------------------------------|-------------------------|---|
| <input type="checkbox"/> | <a href="#">OGL MDB LISTENER</a> |               | ADOGL_MDBQCF                   | NOTIFY_DEST_QUEUE       |        |

Total 1

---

## 3. Appendix

### 3.1 Oracle GL Adapter Installation Documents

Please refer [ADOGL\\_Installation\\_FCUBSV.UM7.2.0.0.0.0.doc](#).



Oracle GL Adapter IBM WebSphere MQ Installation  
[May] [2020]  
Version 14.4.0.0.0

Oracle Financial Services Software Limited  
Oracle Park  
Off Western Express Highway  
Goregaon (East)  
Mumbai, Maharashtra 400 063  
India

Worldwide Inquiries:  
Phone: +91 22 6718 3000  
Fax: +91 22 6718 3001  
[www.oracle.com/financialservices/](http://www.oracle.com/financialservices/)

Copyright © [2007], [2020], Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

**U.S. GOVERNMENT END USERS:** Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.