

Standalone Scheduler Property File Creation  
Oracle FLEXCUBE Investor Servicing  
Release 14.7.2.0.0  
[May] [2023]



---

## Table of Contents

<b>1.</b>	<b>CREATING PROPERTY FILE FOR STANDALONE SCHEDULER .....</b>	<b>1-1</b>
1.1	INTRODUCTION .....	1-1
1.2	CREATING PROPERTY FILE .....	1-1
1.2.1	<i>Setting Common Properties .....</i>	<i>1-4</i>
1.2.2	<i>Configuring Scheduler .....</i>	<i>1-5</i>
1.2.3	<i>Setting EMS Properties .....</i>	<i>1-11</i>
1.2.4	<i>Saving Property File .....</i>	<i>1-15</i>

# 1. Creating Property File for Standalone Scheduler


## 1.1 Introduction

This chapter explains the steps to create property file for Standalone Scheduler.

## 1.2 Creating Property File

To create the property file for Oracle FLEXCUBE, follow the steps given below:

1. Launch Oracle FLEXCUBE Universal Installer.
2. Click 'Next' and the following screen is displayed.



3. Select 'Scheduler'.

- Click 'Next' and the following screen is displayed.

The screenshot shows a window titled "Oracle FLEXCUBE Investor Servicing" with the Oracle logo in the top right corner. The main content area has a header "Welcome To Oracle FLEXCUBE" and a sub-header "Choose Oracle FLEXCUBE Component for installation." Below this is a list box containing three options: "Property File", "Build Application", and "Deploy Application". The "Property File" option is selected and highlighted. Below the list box are three dropdown menus: "File Seperator Style" with "Linux" selected, "Application Server" with "Weblogic" selected, and "DataBase Server" with "Oracle" selected. At the bottom of the window is a grey bar containing four buttons: "Log", "Back", "Next", and "Exit".

Select 'Property File'.

- Specify the following details:

#### **Operating System**

Specify the operating system in which you are creating the property file. Select the appropriate one from the adjoining drop-down list.

#### **Application Server**

Specify the application server in which you are creating the property file. Select the appropriate one from the adjoining drop-down list.

6. Once you have specified the details, click 'Next' to continue and following screen is displayed:

The screenshot shows the 'Property File Creation' screen in the Oracle FLEXCUBE Investor Servicing application. The header bar is red with 'Oracle FLEXCUBE Investor Servicing' on the left and the 'ORACLE' logo on the right. The main content area has a title 'Property File Creation' and a subtitle 'Specify the Property File path.' Below this is a label 'Centralized Property File' followed by a text input field and a folder icon. A large gray box contains the instruction: 'For Modifying the Existing Property file specify the path else leave the path unchanged for loading the default property file.' At the bottom, there is a 'Log' button on the left and 'Back', 'Next', and 'Exit' buttons on the right.

7. Specify the following details:


The property file needs to be built before the EAR file. If you are creating a new property file, leave the field blank. If you wish to modify an existing property file, you can manually specify the location of the property file.

When you click 'Next', the following screen is displayed.

The screenshot shows the 'Property File Creation' screen after clicking 'Next'. The header bar is red with 'Oracle FLEXCUBE Investor Servicing' on the left and the 'ORACLE' logo on the right. The main content area has a title 'Property File Creation' and a subtitle 'Current screen provides an option for modifying Security Key for encryption.' Below this is a label 'Security Key for Encryption Logic' followed by a text input field containing 'oraclefinancials'. There is a checked checkbox labeled 'Platform Security Available'. Below that is a label 'SMS Security Key' followed by a text input field containing 'oraclefinancials'. A large gray box contains the instruction: 'Security Key is used for Encryption Logic.' At the bottom, there is a 'Log' button on the left and 'Back', 'Next', and 'Exit' buttons on the right.

## Platform Security

If Platform Security is not enabled, the Installer will pop-up a window.



If Platform Security is checked for weblogic the symmetric key is not stored in the property file for security reasons. If Platform Security is unchecked the symmetric key is available in the property file and a warning message is displayed to the user.

## SMS Security Key


Specify the security key for the Encryption, here in this case it is 'oraclefinancials'.

Click 'Next' and the following screen is displayed:

### 1.2.1 Setting Common Properties

This section describes the process of setting common properties of Standalone Installer.

1. The installer displays the 'Common Properties' screen.



2. Specify the following details:

### Debug Logs Required

If you require debug option, select 'Yes' from the drop-down list. If you do not require debug option, select 'No'.

**Work Area**

Specify the work area.

For example: D:\BrnDbgs\

**Signature Path**

Specify the location at which the signature images are placed.

**Excel Path**

Specify the location at which the excel files are generated.

**Data Source**

Specify the JNDI location. The standard format is 'jdbc/fcjdevDS'.

**Request Time Out**

Specify the database request timeout value in milli seconds. This is the maximum number of seconds the database waits for a query to return the result.

**Connection Time Out**

Specify the database connection timeout value in seconds. This is the maximum number of seconds the application waits for a connection to the database to open.

**Session Time Out**

Enter the session time out value in seconds. This is the maximum number of seconds during which the application gets active without any user intervention. If there is no user intervention continuously for the duration specified here, the user session gets expire.

**LOV Fetch Required**

If you check this box, the option lists in Oracle FLEXCUBE displays the matching values based on the first characters that you enter in a field. If you specify the first three characters of a value to be entered in an option list and tab out, the system displays the complete list of values that are matching the first three characters.

If you do not check this, option lists does not show the matching values based on the first few characters. You need to specify the complete value against the field.

**Max Image size**

Specify the maximum image size in bytes.

Click 'Next' and the following screen is displayed:

## **1.2.2 Configuring Scheduler**

This section describes the method to configure scheduler data source.

1. System displays the following screen:

**Oracle FLEXCUBE Investor Servicing** **ORACLE**

**Property File Creation**  
Current screen provides an option for Scheduler configuration.

Scheduler Datasource:

Scheduler Log Rotation Interval:

Provide the Scheduler Datasource Name in the field Scheduler Datasource.

Provide the Scheduler Log Rotation Value To move old Scheduler Log to another file at specific time intervals .

2. Specify the following details:

#### **Scheduler Datasource**

Specify the scheduler datasource which Oracle FLEXCUBE will access.

#### **Scheduler Log Rotation Interval**

Specify the scheduler log rotation interval.

#### **Scheduler Log Rotation Interval**

Select the interval between each rotation of scheduler log.

3. Click 'Next' and the following screen is displayed:

**Oracle FLEXCUBE Investor Servicing** **ORACLE**

**Property File Creation**  
Current screen provides an option for configuring Scheduler Destination Queue.

Notify Destination:

Queue Name:

Queue Connection Factory:  ☐ Secure

Notify Queue Location:

4. Specify the following details:



## Notify Destination

Specify the notify destination. Select one of the following options:

- QUEUE
- TOPIC

## Queue Name

Set 'NOTIFY\_DEST\_QUEUE' as the destination queue name.

## Queue Connection Factory

Set 'NotifyDestQCF' as the queue connection factory.

## Secure

Check this box to indicate that it is a secured queue connection factory. If you check this box, you will be prompted to specify the caller ID and caller password as shown in the following screen.

The screenshot shows a window titled "Oracle FLEXCUBE Investor Servicing" with the Oracle logo in the top right corner. The main area is titled "Property File Creation" and contains the text: "Current screen provides an option for configuring Scheduler Destination Queue." Below this, there are several input fields and a checkbox:

- Notify Destination:** A dropdown menu with "QUEUE" selected.
- Queue Name:** A text box containing "NOTIFY\_DEST\_QUEUE".
- Queue Connection Factory:** A text box containing "NotifyDestQCF".
- Secure:** A checked checkbox.
- Caller ID:** An empty text box.
- Caller Password:** An empty text box.
- Notify Queue Location:** A dropdown menu with "Internal" selected.


At the bottom of the window, there are four buttons: "Log", "Back", "Next", and "Exit".

## Caller ID

Specify the caller ID for the secured queue connection factory.

## Caller Password

Specify the password for the caller ID to access the secured queue connection factory.

 If the queue connection factory is not secured, i.e., if you have not checked the box 'Secure', the installer will not display the fields 'Caller ID' and 'Caller Password'. You need not provide these details in that case.

## Notify Queue Location

Specify the notify queue location. Select one of the following options:

- Internal
- External



For Oracle WebLogic application server, the notify queue location should be selected as 'Internal'. If you choose 'Internal' as the 'Notify Queue Location', the screen provided in the following step does not get displayed. You will be navigated to next step where you can specify the notified deferred queue name and connection factory.

Click 'Next' to proceed with scheduler configuration.



If you choose 'Internal' as the 'Notify Queue Location', you will be directly navigated to the following screen. In that case, the installer will not show the screen explained in the previous step.

The screenshot shows a software installation window titled 'Oracle FLEXCUBE Investor Servicing' with the Oracle logo in the top right corner. The main heading is 'Property File Creation'. Below it, a message states: 'Current screen provides an option for Scheduler configuration.' There are two input fields: 'Notify Deferred Queue Name' with the text 'DEFFERED\_DEST\_QUEUE' and 'Deferred Queue Connection Factory' with the text 'DeferredDestQCF'. To the right of the second field is a checkbox labeled 'Secure' which is currently unchecked. At the bottom of the window, there are four buttons: 'Log', 'Back', 'Next', and 'Exit'.

5. Specify the following details:

**Notify Deferred Queue Name**

Set 'DEFFERED\_DEST\_QUEUE' as the notified deferred queue name.

**Deferred Queue Connection Factory**

Set 'DeferredDestQCF' as the deferred queue connection factory.

## Secure

Check this box to indicate that it is a secured deferred queue connection factory. If you check this box, you will be prompted to enter the caller ID and caller password as shown in the following screen.

The screenshot shows a web application window titled "Oracle FLEXCUBE Investor Servicing" with the Oracle logo in the top right corner. The main heading is "Property File Creation". Below it, a message states: "Current screen provides an option for Scheduler configuration." The form contains the following fields and controls:

- Notify Deferred Queue Name:** A text box containing the value "DEFERRED\_DEST\_QUEUE".
- Deferred Queue Connection Factory:** A text box containing the value "DeferredDestQCF". To its right is a checked checkbox labeled "Secure".
- Caller ID:** An empty text box.
- Caller Password:** An empty text box.

At the bottom of the form, there are four buttons: "Log", "Back", "Next", and "Exit".

6. Specify the caller ID and caller password for the secured deferred queue connection factory.
7. Click 'Next' and the following screen is displayed:

The screenshot shows a web application window titled "Oracle FLEXCUBE Investor Servicing" with the Oracle logo in the top right corner. The main heading is "Property File Creation". Below it, a message states: "Current screen provides an option for Scheduler Notify Internal Queue configuration." The form contains the following fields and controls:

- Notify Queue Name:** A text box containing the value "NOTIFY\_QUEUE".
- Dead Letter Queue Name:** A text box containing the value "NOTIFY\_QUEUE\_DLQ".
- Notify Queue Connection Factory:** A text box containing the value "NOTIFY\_MDB\_QCF". To its right is an unchecked checkbox labeled "Secure".

At the bottom of the form, there are four buttons: "Log", "Back", "Next", and "Exit".

8. Specify the following details:

**Notify Queue Name**

Set 'NOTIFY\_QUEUE' as the notify queue name.

**Dead Letter Queue Name**

Set 'NOTIFY\_QUEUE\_DLQ' as the dead letter queue name.

**Notify Queue Connection Factory**

Set 'NOTIFY\_MDB\_QCF' as the notify queue connection factory.

**Secure**

Check this box to indicate that it is a secured queue connection factory. If you check this box, you will be prompted to enter the caller ID and caller password as shown in the following screen.

Oracle FLEXCUBE Investor Servicing

ORACLE

Property File Creation

Current screen provides an option for Scheduler Notify Internal Queue configuration.

Notify Queue Name: NOTIFY\_QUEUE

Dead Letter Queue Name: NOTIFY\_QUEUE\_DLQ

Notify Queue Connection Factory: NOTIFY\_MDB\_QCF ☒ Secure

Caller ID: [Empty Field]

Caller Password: [Empty Field]

Log Back Next Exit

9. Specify the caller ID and caller password for the secured notify queue connection factory.

10. Click 'Next' and the following screen is displayed:

### 1.2.3 Setting EMS Properties

**Oracle FLEXCUBE Investor Servicing** **ORACLE**

**Property File Creation**  
Current screen provides an option for Scheduler EMS Queue configuring.

No.	Name	Value
1	Incoming Dead Letter Queue Name	EMS_QUEUE_DLQ
2	Incoming backup Queue Name	EMS_QUEUE_BACK
3	Incoming Queue Connection Factory	EmsQcf
4	Secure Incoming Queue Connection	<input type="checkbox"/>
5	Incoming Queue Caller Id	
6	Incoming Queue Caller Password	
7	Outgoing Dead Letter Queue Name	EMS_QUEUE_DLQ
8	Outgoing Queue Connection Factory	EmsQcf
9	Secure Outging Queue Connection	<input type="checkbox"/>

**Oracle FLEXCUBE Investor Servicing** **ORACLE**

**Property File Creation**  
Current screen provides an option for Scheduler EMS Queue configuring.

No.	Name	Value
10	Outgoing Queue Caller Id	
11	Outgoing Queue Caller Password	
12	Outgoing Queue Provider Url	t3://10.10.10.10:1010
13	Queue Principal	*****
14	Queue Credential	*****
15	Incoming Queue Name	EMS_INQUEUE
16	Outgoing Queue Name	EMS_OUTQUEUE
17	SFMS Incoming Queue	SFMS_INQUEUE
18	RTGS Incoming Queue	RTGS_INQUEUE

Specify the following details:

#### Incoming Dead Letter Queue Name

Set 'EMS\_QUEUE\_DLQ' as the incoming dead letter queue name.

#### Incoming Backup Queue Name

Specify the name of the incoming backup queue for which EMS is configured.

Set 'EMS\_QUEUE\_BACK' as the incoming backup queue name.

### **Incoming Queue Connection Factory**

Specify the name of the incoming connection factory to which EMS listens. You need to create this connection factory at the application server.

For details on connection factory creation, follow the steps described for creation of notify connection factories.

Set 'EmsQcf' as the incoming queue connection factory.

### **Secure Incoming Queue Connection**

Check this box to indicate that it is a secured queue connection.

### **Incoming Queue Caller ID**

Specify the caller ID for the secured queue connection.

### **Incoming Queue Caller Password**

Specify the caller password for the secured queue connection.

### **Outgoing Dead Letter Queue Name**

Set 'EMS\_QUEUE\_DLQ' as outgoing dead letter queue name.

### **Outgoing Queue Connection Factory**

Specify the name of the outgoing connection factory to which EMS listens. You need to create this connection factory at the application server.

For details on connection factory creation, follow the steps described for creation of notify connection factories.

### **Set 'EmsQcf' as the outgoing queue connection factory. Secure Outgoing Queue Connection**

Check this box to indicate that it is a secured outgoing queue connection.

### **Outgoing Queue Caller ID**

Specify the caller ID for the secured queue connection.

### **Outgoing Queue Caller Password**

Specify the caller Password for the secured queue connection.

### **Outgoing Queue Provider URL**

In case EMS OUT MDB is to be configured to queue, you need to specify the URL for outgoing provider based on the application server. By default, the Installer displays the outgoing queue provider URL for Oracle WebLogic.

This value is application server dependent.

The details of Outgoing Queue Provider URL to be used for different application servers are given below:

Application Server	EMS Out Initial Context Factory
Oracle WebLogic	t3://<ip_adress>:port E.g.: t3://10.10.10.10:1010 Here, 10.10.10.10 represents the local host and 1010 to the target server default port (AdminServer/ManagedServer).

#### **Queue Principal**

If EMS OUT MDB has to be configured to queue, you need to specify the EMS out queue principal. This is the user name for the application server in which the queue is configured.

#### **Queue Credential**

If EMS OUT MDB has to be configured to queue, you need to specify the EMS out queue credential. This is the password for the above user name created for application server in which the queue configured.

#### **Incoming Queue Name**

Specify the name of the incoming queue for which EMS is configured. By default, this is set as 'EMS\_QUEUE\_DLQ'. Outgoing Queue Name

Specify the name of the outgoing queue for which EMS is configured. By default, this is set as 'EMS\_QUEUE\_DLQ'. SFMS Incoming Queue

Specify the name of the SFMS Incoming Queue. By default, this is set as 'SFMS\_INQUEUE'.

#### **RTGS Incoming Queue**

Specify the name of the RTGS incoming Queue. By default, this is set as 'RTGS\_INQUEUE'.

Once you have specified the above details, click 'Next' and system displays the next screen.

No.	Name	Value
1	File TransferMode FTPS	FTPS
2	Server	10.10.10.10
3	User id	OFSS
4	Password	.....
5	File Type	.txt
6	Swift Format	1
7	Swift Message Delimiter	<input checked="" type="checkbox"/>
8	Swift Message Terminator	<input checked="" type="checkbox"/>
9	MEDIA	SWIFT

11. Specify the following details:

#### **File Transfer Mode FTPS**

Specify the mode of transferring files to EMS. Select one of the following:

- FTPS
- SFTP
- HTTP

#### **Server**

Specify the server IP address for the selected file transfer mode.

#### **User ID**

Specify the user ID to access the server of the file transfer mode.

#### **Password**

Specify the password to for the above user ID.

#### **File Type**

Specify the type of file that is transferred. By default, the Installer sets it as '.txt'.

#### **SWIFT Message Delimiter**

Specify the character which is used as the message delimiter.

#### **SWIFT Message Terminator**

Specify the character which is used as the message terminator.



12. Once you have specified the above details, click 'Next'. and the following screen is displayed:

No.	Name	Value
1	Signature Block	<input checked="" type="checkbox"/>
2	Keystore File Name	/keystore
3	Keystore Alias name	.....
4	Keystore Password	.....

Log Back Next Exit

13. Specify the following details:

**Signature Block**

Check this box to enable signature block.

**Keystore File Name**

Specify the keystore file name.

**Keystore Alias Name**

Specify the keystore alias name.

**Keystore Password**


Specify the keystore password.

14. Once you have specified the above details, click 'Next' and system displays the next screen.


#### 1.2.4 Saving Property File

After completing all the required settings explained above, you need to save the property file.


1. Save the property file.



2. You can view the status of property file creation in the above screen. Once the file is saved, the installer displays the following message:



3. If you do not use the 'Save' or 'Save As' buttons, the installer will save the properties file in 'C:\Users\<username>' folder. In that case, you will see the message below.



This completes the properties file creation.



Scheduler Property File Creation  
[May] [2023]  
Version 14.7.2.0.0

Oracle Financial Services Software Limited  
Oracle Park  
Off Western Express Highway  
Goregaon (East)  
Mumbai, Maharashtra 400 063  
India

Worldwide Inquiries:  
Phone: +91 22 6718 3000  
Fax: +91 22 6718 3001  
[www.oracle.com/financialservices/](http://www.oracle.com/financialservices/)

Copyright © [2007], [2023], Oracle and/or its affiliates.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

**U.S. GOVERNMENT END USERS:** Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software" or "commercial computer software documentation" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.