Oracle® Communications User Data Repository

Cloud Disaster Recovery Guide

Release 15.0.0.0.0

F87585-01

October 2023



Oracle Communications User Data Repository Cloud Disaster Recovery Guide, Release 15.0.0.0.0 F87585-01

Copyright © 2016, 2017, 2018, 2022, 2023 Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

CAUTION: Open an Service Request on MOS and confer with Oracle before executing Disaster Recovery Procedure

Before recovering any system, please access My Oracle Support (MOS) (https://support.oracle.com) and review any MOS Alerts that relate to this procedure.

My Oracle Support (MOS) (https://support.oracle.com) is your initial point of contact for all product support and training needs. A representative at Customer Access Support (CAS) can assist you with MOS registration.

Call the CAS main number at 1-800-223-1711 (toll-free in the US), or call the Oracle Support hotline for your local country from the list at http://www.oracle.com/us/support/contact/index.html.

See more information on MOS in the Appendix section.

.

TABLE OF CONTENTS

1	INTRODUCTION	5
	1.1 Purpose and Scope	5
	1.2 References	5
	1.3 Acronyms	6
	1.4 Terminology	7
	1.5 How to Use this Document	7
2	GENERAL DESCRIPTION	8
	2.1 Complete Site Outage (All Servers)	8
	2.2 Partial outage with one NOAMP server intact and both SOAMs failed	8
	2.3 Partial outage with both NOAMP servers failed and one SOAM server intact	8
	2.4 Partial outage with NOAMP and one SOAM server intact	9
	2.5 Partial outage with Corrupt Database	9
3	PROCEDURE OVERVIEW	10
	3.1 Required Materials	10
	3.2 Disaster Recovery Strategy	11
	3.3 Procedure Preparation	12
4	DISASTER RECOVERY PROCEDURE	14
	4.1 Recovering and Restoring System Configuration	15
	4.1.1 Recovery Scenario 1 (Complete Site Outage)	15
	4.1.2 Recovery Scenario 2 (Partial Server Outage with one NOAMP server intact and both SOAMs failed)	40
	4.1.3 Recovery Scenario 3 (Partial Server Outage with all NOAMP servers failed and one SOAM server intact)	62
	4.1.4 Recovery Scenario 4 (Partial Server Outage with one NOAMP server and one SOAM server intact)	
	4.1.5 Recovery Scenario 5 (Database Recovery)	93
5	RESOLVING USER CREDENTIAL ISSUES AFTER DATABASE RESTORE	98
	5.1 Keeping a Restored User (Resetting User Password)	98
	5.2 Removing a Restored User	. 100
	5.3 Restoring a Modified User	. 101
	5.4 Restoring an Archive that does not contain a Current User	. 102
	Appendix A. Oracle Communications User Data Repository Database Backup	. 106
	Appendix B. Inhibit A and B Level Replication on C-Level Servers	. 110

Oracle Communications User Data Repository Cloud Disaster Recovery Guide

Appendix C.	Un-Inhibit A and B Level Replication on C-Level Servers	112
Appendix D.	My Oracle Support (MOS)	114
Appendix E.	Locate Product Documentation on the Oracle Help Center Site	115
List of Figur Figure 1. Determin	es ning Recovery Scenario	11
List of Table	S	
Table 1. Terminol	logy	7
Table 2: Recovery	Scenarios	12

1 INTRODUCTION

1.1 Purpose and Scope

This document describes disaster recovery procedures used during disaster scenarios of the cloud based Oracle Communications User Data Repository 15.0.0.0.0 product.

This document is a guide to describe procedures used to execute disaster recovery for Oracle Communications User Data Repository Cloud deployments. This includes recovery of partial or a complete loss of one or more Oracle Communications User Data Repository virtual servers (Primary or DR). The audience for this document includes Oracle customers as well as the following internal groups: Software Development, Quality Assurance, Product Verification, Information Development, and Consulting Services including NPx.. This document provides step-by-step instructions to execute disaster recovery for Oracle Communications User Data Repository 15.0.0.0.0 Executing this procedure also involves referring to and executing procedures in existing support documents found in the reference section.

This document is intended for execution by Customer Service team on the fielded Oracle Communications User Data Repository 15.0.0.0.0 systems.

1.2 References

- [1] Oracle Communications User Data Repository 12.11 Disaster Recovery Guide, F56665-01, latest revision
- [2] Oracle Communications User Data Repository 15.0 Cloud Installation and Configuration Guide, F87587-0, latest revision

1.3 Acronyms

Acronym	Meaning
BIOS	Basic Input Output System
CD	Compact Disk
DR	Disaster Recovery
FRU	Field Replaceable Unit
IMI	Internal Management Interface
ISL	Inter-Switch-Link
NE	Network Element
MP Host Server	Server that contains one SOAM and two MPs
NOAMP	Network Operations, Administration, Maintenance & Provisioning
ISO	Constains software images
OVA	Open Virtualization Archive
MOS	My Oracle Support
NAPD	Network Architecture Planning Diagram
SOAM	Systems Operations, Administration & Maintenance
TAC	Technical Assistance Centers
TPD	Tekelec Platform Distribution (Linux OS)
UDR	User Data Repository
VIP	Virtual IP
VM	Virtual Machine
XMI	External Management Interface

1.4 Terminology

Table 1. Terminology

Base hardware	Base hardware includes all hardware components (bare metal) and electrical wiring to allow a server to power on.
Base software	Base software includes installing the server's operating system: Tekelec Platform Distribution (TPD).
Failed server	A failed server in disaster recovery context refers to a server that has suffered partial or complete software and/or hardware failure to the extent that it cannot restart or be returned to normal operation and requires intrusive activities to re-install the software and/or hardware.
Enablement	The business practice of providing support services (hardware, software, documentation, etc) that enable a 3 rd party entity to install, configuration, and maintain Oracle products for Oracle customers.
Software Centric	The business practice of delivering an Oracle software product, while relying upon the customer to procure the requisite hardware components. Oracle provides the hardware specifications, but does not provide the hardware, and is not responsible for hardware installation, configuration, or maintenance.

1.5 How to Use this Document

When executing this document, understanding the following helps to ensure that the user understands the manual's intent:

- Before beginning a procedure, completely read the instructional text (it appears immediately after the Section heading for each procedure) and all associated procedural WARNINGS or NOTES.
- Before execution of a STEP within a procedure, completely read the left and right columns including any STEP specific WARNINGS and/or NOTES.

If a procedural STEP fails to execute successfully, please STOP and contact My Oracle Support (MOS).

2 GENERAL DESCRIPTION

Disaster recovery procedures falls into five basic categories. It is primarily dependent on the state of the NOAMP servers and SOAM servers:

Recovery of the entire site from a total outage	 All NOAMP servers failed All SOAM servers failed 1 or more MP servers failed
Recovery of one or more servers with at least one NOAMP server intact	 1 or more NOAMP servers intact 1 or more SOAM or MP servers failed
Recovery of the NOAMP pair with one or more SOAM servers intact	 All NOAMP servers failed 1 or more SOAM servers intact
Recovery of one or more server with at least one NOAMP and one SOAM server intact.	 1 or more NOAMP servers intact 1 or more SOAM servers intact 1 SOAM or 1 or more MP servers failed
Recovery of one or more servers with corrupt database	 Case 1: No Replication Channel Case 2: Replication Channel Available

2.1 Complete Site Outage (All Servers)

This is the worst case scenario where all the servers in the site have suffered complete software failure. The servers are recovered using OVA images then restoring database backups to the active NOAMP and SOAM servers. Note: NOAMP servers which were originally installed by ISO instead of OVA will be recovered using ISO.

Database backups will be taken from customer offsite backup storage locations (assuming these were performed and stored offsite prior to the outage). If no backup files are available, the only option is to rebuild the entire network from scratch. The network data must be reconstructed from whatever sources are available, including entering all data manually.

2.2 Partial outage with one NOAMP server intact and both SOAMs failed

This case assumes that at least one NOAMP servers intact. All SOAM servers have failed and are recovered using OVA images. Database is restored on the SOAM server and replication will recover the database of the remaining servers.

2.3 Partial outage with both NOAMP servers failed and one SOAM server intact

Database is restored on the NOAMP and replication will recover the database of the remaining servers.

2.4 Partial outage with NOAMP and one SOAM server intact

The simplest case of disaster recovery is with at least one NOAMP and at least one SOAM servers intact. All servers are recovered using base recovery of software. Database replication from the active NOAMP and SOAM servers will recover the database to all servers.

2.5 Partial outage with Corrupt Database

Case 1: Database is corrupted, <u>replication channel is inhibited</u> (either manually or because of comcol upgrade barrier) and database backup is available.

Case 2: Database is corrupted but replication channel is available.

3 PROCEDURE OVERVIEW

This section lists the materials required to perform disaster recovery procedures and a general overview (disaster recovery strategy) of the procedure executed.

3.1 Required Materials

The following items are needed for disaster recovery:

- 1. A hardcopy of this document (E71445-01) and hardcopies of all documents in the reference list
- 2. Hardcopy of all NAPD performed at the initial installation and network configuration of this customer's site. If the NAPD cannot be found, escalate this issue within My Oracle Support (MOS) until the NAPD documents can be located.
- 3. Oracle Communications User Data Repository recent backup files: electronic backup file (preferred) or hardcopy of all Oracle Communications User Data Repository configuration and provisioning data.
- 4. Latest Network Element report: Electronic file or hardcopy of Network Element report.
- 5. The network element XML file used for the VMs initial configuration.

The software media referenced here may be acquired online from the Oracle e-Delivery service at edelivery.oracle.com

This document and others referenced here can be acquired online from the Oracle Document Repository at the followin URL:

http://docs.oracle.com/en/industries/communications/user-data-repository/index.html


Note: For all Disaster Recovery scenarios, we assume that the NOAMP Database backup and the SOAM database backup were performed around the same time, and that no synchronization issues exist among them.

3.2 Disaster Recovery Strategy

Disaster recovery procedure execution is performed as part of a disaster recovery strategy with the basic steps listed below:

- 1. Evaluate failure conditions in the network and determine that normal operations cannot continue without disaster recovery procedures. This means the failure conditions in the network match one of the failure scenarios described in section 2.
- 2. Read and review the content in this document.
- 3. Gather required materials in section 3.1 Required Materials
- 4. From the failure conditions, determine the Recovery Scenario and procedure to follow (using Figure 1. Determining Recovery Scenario.
- 5. Execute appropriate recovery procedures (listed in section 4).

Figure 1. Determining Recovery Scenario



3.3 **Procedure Preparation**

Disaster recovery procedure execution is dependent on the failure conditions in the network. The severity of the failure determines the recovery scenario for the network. Use Table 2: Recovery Scenarios below to evaluate the correct recovery scenario and follow the procedure(s) listed to restore operations.

Note: A failed server in disaster recovery context refers to a server that has suffered partial or complete software failure to the extent that it cannot restart or be returned to normal operation and requires intrusive activities to re-deploy base software.

Table 2: Recovery Scenarios

Recovery Scenario	Failure Condition	Section
1	 All NOAMP servers failed. All SOAM servers failed. MP servers may or may not be failed. 	Section Recovery Scenario 1 (Complete Site Outage)
2	 At least 1 NOAMP server is intact and available. All SOAM servers failed. MP servers may or may not be failed. 	Section Recovery Scenario 2 (Partial Server Outage with one NOAMP server intact and both SOAMs failed)
3	 All NOAMP servers failed. At least 1 SOAM server is intact and available. MP servers may or may not be failed. 	Section Recovery Scenario 3 (Partial Server Outage with all NOAMP servers failed and one SOAM server intact)
4	 At least 1 NOAMP server is intact and available. At least 1 SOAM is intact and available. 1 or more MP servers have failed. 	Section Recovery Scenario 4 (Partial Server Outage with one NOAMP server and one SOAM server intact)
5	 Server is intact Database gets corrupted on the server 	Section Recovery Scenario 5 (Database Recovery)
5: Case 1	 Server is intact Database gets corrupted on the server 	Section Recovery Scenario 5: Case 1

Oracle Communications User Data Repository Cloud Disaster Recovery Guide

	Replication is inhibited (either manually or because of comcol upgrade barrier)	
5: Case 2	 Server is intact Database gets corrupted on the server Replication is occurring to the server with corrupted database 	Section Recovery Scenario 5: Case 2

4 DISASTER RECOVERY PROCEDURE

Call the CAS main number at **1-800-223-1711** (toll-free in the United States), or call the Oracle Support hotline for your local country from the list at http://www.oracle.com/us/support/contact/index.html prior to executing this procedure to ensure that the proper recovery planning is performed.

Before disaster recovery, users must properly evaluate the outage scenario. This check ensures that the correct procedures are executed for the recovery.

**** WARNING *****

**** WARNING *****

Note: Disaster recovery is an exercise that requires collaboration of multiple groups and is expected to be coordinated by the TAC prime. Based on TAC's assessment of Disaster, it may be necessary to deviate from the documented process.

4.1 Recovering and Restoring System Configuration

Disaster recovery requires configuring the system as it was before the disaster and restoration of operational information. There are 7 distinct procedures to choose from depending on the type of recovery needed. Only one of these should be followed (not all).

4.1.1 Recovery Scenario 1 (Complete Site Outage)

For a complete server outage, NOAMP servers are recovered using recovery procedures for software and then executing a database restore to the active NOAMP server. All other servers are recovered using recovery procedures for software.

Database replication from the active NOAMP server will recover the database on these servers. The major activities are summarized in the list below. Use this list to understand the recovery procedure summary. Do not use this list to execute the procedure. The actual detailed steps are in . The major activities are summarized as follows:

Recover Base software for all VMs:

- Recover the Virtual Machines hosting the NOAMPs and SOAMs
- Recover the **Active NOAMP** server by recovering the NOAMPs base software
- Recover the NOAMP database
- Reconfigure the application

Recover the Standby NOAMP server by recovering base software, for a Non-HA deployment this can be skipped.

• Reconfigure the Oracle Communications User Data Repository Application

Recover all SOAM and MP servers by recovering software, In a Non-HA deployment the Standby SOAM servers can be skipped.

- Recover the SOAM database
- Reconfigure the Oracle Communications User Data Repository Application
- Reconfigure the signaling interface and routes on the MPs, the Oracle Communications User Data Repository software will automatically reconfigure the signaling interface from the recovered database.

Restart process and re-enable provisioning replication

Note: Any other applications DR recovery actions (PCRF, etc) may occur in parallel. These actions can/should be worked simultaneously; doing so would allow faster recovery of the complete solution.


Procedure 1: Recovery Scenario 1 -- Complete Server Outage

S T	This procedure performs recovery if both NOAMP servers are failed and all SOAM servers are failed. This procedure also caters the C-Level Sever failure	
E P	Check off $()$ each step as it is completed. Boxes have been provided for this purpose under each step number.	
#	If this procedure fai	ls, contact My Oracle Support (MOS), and ask for assistance.
1.	Gather Required Materials	Gather the documents and required materials listed in Section Required Materials
2.	Recover the Failed Software	Execute the following procedures from reference Oracle Communications User Data Repository 15.0 Cloud Installation and Configuration Guide, latest revision [2]:
		Procedure 2: Deploy Oracle Communications User Data Repository Virtual Machines
4.	Obtain Latest Database Backup and Network	Obtain the most recent database backup file from external backup sources (ex. file servers) or tape backup sources.
	Configuration Data.	From required materials list in Section 3.1 Required Materials ; use site survey documents and Network Element report (if available), to determine network configuration data.
5.	Execute UDR Installation Procedure for the First	Configure the First NOAMP server by executing procedures from reference Oracle Communications User Data Repository 15.0 Cloud Installation and Configuration Guide, latest revision [2]:
	NOAMP	Procedure 3 "Configure NOAMP-A Server (1st NOAMP Only)"
		Note: If Topology or nodeId alarms are persistent after the database restore, refer to the steps below.


Procedure 1: Recovery Scenario 1 -- Complete Server Outage


6.	Active NOAMP: Login	Login to the NOAMP GUI as the <i>guiadmin</i> user:
		ORACLE"
		Oracle System Login Fri Mar 20 12:29:52 2015 EDT
		Log In Enter your username and password to log in Username: quiadmin
		Password: Change password Log In
		Welcome to the Oracle System Login.
		Unauthorized access is prohibited. This Oracle system requires the use of Microsoft Internet Explorer 8.0, 9.0, or 10.0 with support for JavaScript and cookies. Oracle and Java are registered trademarks of Oracle Corporation and/or its affiliates.
		Other names may be trademarks of their respective owners

Procedure 1: Recovery Scenario 1 -- Complete Server Outage



Procedure 1: Recovery Scenario 1 -- Complete Server Outage






If the verification is successful, Click BACK button and continue to next step in this procedure.

This is an expected text in Topology Compatibility.

Procedure 1: Recovery Scenario 1 -- Complete Server Outage



Procedure 1: Recovery Scenario 1 -- Complete Server Outage

11.	Active NOAMP: Login	Establish a GUI session on the NOAMP server by using the VIP IP address of the NOAMP server. Open the web browser and enter a URL of: http:// <primary_noamp_vip_ip_address></primary_noamp_vip_ip_address>
		Login as the guiadmin user: Oracle System Login Fri Mar 20 12:29:52 2015 EDT Log in Enter your username and password to log in Username: guiadmin Password:
12.	Active NOAMP: Monitor and Confirm database restoral	Wait for 5-10 minutes for the System to stabilize with the new topology: Monitor the Info tab for "Success". This will indicate that the backup is complete and the system is stabilized.
		Following alarms must be ignored for NOAMP and MP Servers until all the Servers are configured:
		Alarms with Type Column as "REPL", "COLL", "HA" (with mate NOAMP), "DB" (about Provisioning Manually Disabled)
		Note: Do not pay attention to alarms until all the servers in the system are completely restored.
		Note: The Configuration and Maintenance information will be in the same state it was backed up during initial backup.
13.	Active NOAMP: Login	Login to the recovered Active NOAMP via SSH terminal as <i>admusr</i> user.


Procedure 1: Recovery Scenario 1 -- Complete Server Outage

14.	Active NOAMP: Restore /etc/hosts/ File of the Active NOAMP	Execute the following command:
	NOAMP	\$ sudo AppWorks AppWorks updateServerAliases <noamp host="" name=""></noamp>
15.	Active NOAMP: Recover Standby NOAMP	Configure the second NOAMP server by executing procedures from reference <i>Oracle Communications User Data Repository 15.0 Cloud Installation and Configuration Guide, latest revision</i> [2]:
	(HA Deployments Only)	Procedure 4 "Create Configuration for Remaining Servers", Step 22.
	• *	Procedure 10 "Apply Configuration for Remaining Servers" for second NOAMP.
		Note: If Topology or nodeId alarms are persistent after the database restore, refer to the steps below.
16.	Active NOAMP:	Navigate to Main Menu → Status & Manage → Server,
	Restart UDR application on Recovered NOAMP	Status & Manage Network Elements Server HA Database KPIs Processes Tasks
		Select the recovered standby NOAMP server and click on Restart .
		Stop Restart Reboot NTP Sync Report


Procedure 1: Recovery Scenario 1 -- Complete Server Outage

17.	Active NOAMP: Set HA on Standby NOAMP	Navigate to Status & Manage → HA Status & Manage Network Elements Server Notabase KPIs Processes Files Click on Edit at the bottom of the screen Select the standby NOAMP server, set it to Active Press OK
18.	Active NOAMP: Stop Replication to the C-Level Servers of this Site.	Inhibit Replication to the working C Level (MP) Servers which belong to the same site as of the failed SOAM servers, as the recovery of Active SOAM will cause the database wipeout in the C level servers because of the replication Execute Appendix B: Inhibit A and B Level Replication on C-Level Servers
19.	Active NOAMP: Recover SOAM Server	Recover the SOAM server by executing procedures from reference Oracle Communications User Data Repository 15.0 Cloud Installation and Configuration Guide, latest revision [2]:
		Procedure 4 "Create Configuration for Remaining Servers", Step 22.
		Procedure 10 "Apply Configuration for Remaining Servers" for SOAM

Procedure 1: Recovery Scenario 1 -- Complete Server Outage



Procedure 1: Recovery Scenario 1 -- Complete Server Outage



Procedure 1: Recovery Scenario 1 -- Complete Server Outage

22.	Recovered SOAM: Login	Establish a GUI session on the recovered SOAM server. Open the web browser and enter a URL of:					
		http:// <recovered_soam_ip_address></recovered_soam_ip_address>					
		Login as the <i>guiadmin</i> user:					
		Chaulthorized access is prohibited. This Oracle system Login Unauthorized access is prohibited. This Oracle system Login. Oracle and Java are registered trademarks of Oracle Corporation and for its affiliates. Other names any be trademarks of the corporation and the staffiliates.					
		were removered to access A or their respective vinites.					

23. Recovered SOAM: Verify the Archive Contents and Database Compatibility

Navigate to Main Menu \rightarrow Status & Manage \rightarrow Database

Select the **Active SOAM** server and click on the **Compare**.

Enable Provisioning Report Inhibit Replication Backup... Compare... Restore... Man Audit Suspend Auto Audit

The following screen is displayed; click the button for the restored database file that was uploaded as a part of **Step 13** of this procedure.

Database Compare

Select archive to compare on server: blade02

Classification prior blade02. Configuration NETWORK_OAMP 20100928_021502.AUTO tar
Classification prior blade02. Configuration NETWORK_OAMP 20100939_021501.AUTO tar
Classification prior blade02. Configuration NETWORK_OAMP 20100930_021501.AUTO tar
Classification prior blade02. Configuration NETWORK_OAMP 20100930_021501.AUTO tar
Classification prior blade02. Configuration NETWORK_OAMP 20100903_021502.AUTO tar
Classification prior blade02. Configuration NETWORK_OAMP 20100903_021502.AUTO tar
Classification prior blade02. Configuration NETWORK_OAMP 20100903_021502.AUTO tar
Classification prior blade02. Configuration NETWORK_OAMP 20100904_021502.AUTO tar
Classification prior blade02. Configuration prior blade02. Configuration prior blade02.

Classification prior blade02. Configuration prior blade02.

Classification prior blade02. Configuration prior blade02.

Classification prior blade02.

Classification prior

Verify that the output window matches the screen below.

Note: You will get a database mismatch regarding the NodeIDs of the VMs. That is expected. If that is the only mismatch, proceed, otherwise stop and contact My Oracle Support (MOS).



Note: Archive Contents and Database Compatibilities must be the following:

Archive Contents: Configuration data

Database Compatibility: The databases are compatible.

Note: The following is expected Output for Topology Compatibility Check since we are restoring from existing backed up data base to database with just one SOAM:


Topology Compatibility

THE TOPOLOGY SHOULD BE COMPATIBLE MINUS THE NODEID.

Note: We are trying to restore a backed up database onto an empty SOAM database. This is an expected text in Topology Compatibility.

If the verification is successful, Click **BACK** button and continue to **next step** in this procedure.

Procedure 1: Recovery Scenario 1 -- Complete Server Outage




Procedure 1: Recovery Scenario 1 -- Complete Server Outage

25.	Recovered SOAM: Monitor and Confirm database restoral	Wait for 5-10 minutes for the System to stabilize with the new topology: Monitor the Info tab for "Success". This will indicate that the backup is complete and the system is stabilized. Note: Do not pay attention to alarms until all the servers in the system are completely restored. Note: The Configuration and Maintenance information will be in the same state it was backed up during initial backup.
26.	Active NOAMP: Login	Establish a GUI session on the NOAMP server by using the VIP IP address of the NOAMP server. Open the web browser and enter a URL of: http:// <primary_noamp_vip_ip_address> Login as the guiadmin user: Cracle System Login Fri Mar 20 12:29:52 2015 EDT Log In Enter your username and password to log in Username: guidmin Password: Change password Change password Unaufhorized access a prohibited. That Cracle System requires the use of Microsoft internet Explorer 8 0. 9. 0. 0 or 10 0 with support for Java-Script and cookies. Cracle and laws are registered trademarks of Orace Corporation anafor its affiliates. Other names may be trademarks of their respective owners.</primary_noamp_vip_ip_address>

Procedure 1: Recovery Scenario 1 -- Complete Server Outage


27.	Active NOAMP: Recover remaining SOAM (HA Deployments Only)	NOTE: For Non-HA sites SKIP this step. Recover second SOAM server by executing procedures from reference Oracle Communications User Data Repository 15.0 Cloud Installation and Configuration Guide, latest revision [2]:					
		Procedure 4 "Create Configuration for Remaining Servers", Step 22.					
		Procedure 10 "Apply Configuration for Remaining Servers" for remaining SOAM.					
NOTE: Wait for server to reboot before continuing.							
28.	Active NOAMP: Restart UDR application on remaining SOAM (HA Deployments Only)	NOTE: For Non-HA sites SKIP this step. Navigate to Main Menu → Status & Manage → Server, Status & Manage Network Elements Server HA Database KPIs Processes Tasks Files Select the recovered server and click on Restart. Stop Restart Reboot NTP Sync Report					

Procedure 1: Recovery Scenario 1 -- Complete Server Outage





Procedure 1: Recovery Scenario 1 -- Complete Server Outage


31.	Active NOAMP: Restart UDR application for Recovered MP	Navigate to Main Menu → Status & Manage → Server, Status & Manage Network Elements Server NHA Notabase NFIs Files Select the recovered server and click on Restart. Stop Restart Reboot NTP Sync Report
32.	Active NOAMP: Set HA on all MP Servers	Navigate to Status & Manage → HA Status & Manage Network Elements Server Database KPIs Processes Tasks Files Click on Edit at the bottom of the screen For each server whose Max Allowed HA Role is set to Standby, set it to Active Press OK
33.	Active NOAMP: Perform key exchange between the active-NOAMP and recovered servers.	Establish an SSH session to the Active NOAMP, login as <i>admusr</i> . Execute the following command to perform a keyexchange from the active NOAMP to each recovered server: \$ keyexchange admusr@ <recovered hostname="" server=""></recovered>



35.	Active NOAMP:	Login to the Active NOAMP via SSH terminal as <i>admusr</i> user.										
	Verify Replication Between Servers	Execute the following command:										
		\$ sudo irepstat -m										
		Output like below shall be generated:										
		Policy 0 ActStb [DbReplication]										·
		RDU06-MP1 Stby										
		BC From	RDU06-S01 A	ctive	0 (0.50 ^	0.17%	cpu 4	2B/s	A=non	е	
		CC From	RDU06-MP2 A	ctive	0 (0.10 ^	0.17	0.88%	cpu 32	2B/s .	A=non	.e
		RDU06-MP2	Active									
		BC From A=none	RDU06-SO1 A	ctive	0 (0.50 ^	0.10%	cpu 3	3B/s			
		CC To	RDU06-MP1 A	ctive	0 (0.10	0.08%	cpu 2	0B/s	A=non	е	
			Active									
		AB To 21B/s	RDU06-SO1 A	ctive	0 (0.50 1	%R 0.	03%cp1	u			
		RDU06-SO1	Active									
			RDU06-NO1 A			0.50 ^	0.04%	cpu 2	4B/s			
			RDU06-MP1 A			0.50 1		_				
		BC To	RDU06-MP2 A	ctive	0 (0.50 1	%R 0.	07%cp1	u 21B,	/s		
36.	Active NOAMP: Verify the Database states		nin Menu → S tatus & Man; Network El Server HA Database	age	Ianag	er → I)atab:	ase				
Verify that the "OAM Max HA Role" is either "Active" or "Standby" for N SOAM and "Application Max HA Role" for MPs is "Active", and that the st "Normal" as shown below:									for NO	OAMI	P and	
		Network Element	Server	Role	OAM Max HA Role	Application Max HA Role	Status	DB Level	OAM Repl Status	SIG Repl Status	Repl Status	Repl Audit Status
		NO_10303 SO_10303	NO2 PSBR	Network OAM&P	Active Active	OOS Active	Normal Normal	0	Normal Normal	NotApplicab Normal	Allowed	AutoInProg AutoInProg
		SO_10303	MP2	MP	Active	Active	Normal	0	Normal	Normal	Allowed	AutoInProg
		SO_10303 NO_10303	S01 N01	System OAM Network OAM&P	Standby Standby	00S	Normal Normal	0	Normal Normal	NotApplicab NotApplicab		AutoInProg
		SO_10303	IPFE	MP Network OAM&P	Active	008	Normal	0	Normal	NotApplicab Normal	Allowed	AutoInProg AutoInProg
		SO_10303	SO2	System OAM	Active	008	Normal	0	Normal	NotApplicab	Allowed	AutoInProg







43.	Active SOAM: Enable SPR Features	Navigate to Main Menu → Diameter → Maintenance → Applications Maintenance Route Lists Route Groups Peer Nodes Connections Egress Throttle Groups Applications DA-MPs Select the feature application. Click the Enable button. Enable Disable Pause updates	
44.	Active SOAM: Examine All Alarms	Navigate to Main Menu → Alarms & Events → View Active Alarms & Events View Active View History View Trap Log Examine all active alarms and refer to the on-line help on how to address them. If needed contact My Oracle Support (MOS).	
45.	Active NOAMP: Examine All Alarms	Login to the NOAMP VIP if not already logged in. Navigate to Main Menu → Alarms & Events → View Active Alarms & Events View Active View History View Trap Log Examine all active alarms and refer to the on-line help on how to address them. If needed contact My Oracle Support (MOS).	
46.	Restore GUI Usernames and Passwords	If applicable, Execute steps in Section 5 to recover the user and group information restored.	
47.	Backup and Archive All the Databases from the Recovered System	Execute Appendix A Oracle Communications User Data Repository Database Backup to back up the Configuration databases.	
	THIS PROCEDURE HAS BEEN COMPLETED		

4.1.2 Recovery Scenario 2 (Partial Server Outage with one NOAMP server intact and both SOAMs failed)

For a partial server outage with an NOAMP server intact and available; SOAM servers are recovered using recovery procedures for software and then executing a database restore to the active SOAM server using a database backup file obtained from the SOAM servers. All other servers are recovered using recovery procedures for software. Database replication from the active NOAMP server will recover the database on these servers. The major activities are summarized in the list below. Use this list to understand the recovery procedure summary. Do not use this list to execute the procedure. The actual procedures' detailed steps are in **Procedure 2**. The major activities are summarized as follows:

Recover Standby NOAMP server (if needed) by recovering software and the database.

• Recover the software.

Recover Active SOAM server by recovering software.

- Recover the software.
- Recover the Database.

Recover any failed **SOAM and MP** servers by recovering software.

- Recover the software.
- The database has already been restored at the active SOAM server and does not require restoration at the SO and MP servers.

Release 15.0.0.0.0 40 October 2023

Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

S T	This procedure performs recovery if at least 1 NOAMP server is available but all SOAM servers in a site have failed. This includes any SOAM server that is in another location.		
E	Check off (√) each st	Check off $(\sqrt{)}$ each step as it is completed. Boxes have been provided for this purpose under each step number.	
P	If this procedure fails	s, contact My Oracle Support (MOS), and ask for assistance.	
#			
1.	Gather Required Materials	Gather the documents and required materials listed in Section Required Materials	
2.	Active NOAMP: Login	Establish a GUI session on the NOAMP server by using the VIP IP address of the NOAMP server. Open the web browser and enter a URL of:	
		http:// <primary_noamp_vip_ip_address></primary_noamp_vip_ip_address>	
		Login as the <i>guiadmin</i> user:	
		Log In Enter your username and password to log in Username: guiadmin Password: Change password Log In Wecome to the Oracle System Logn. Unauthorized access is prohibited. This Oracle system requires the use of Microsoft Internet Explorer 8.0, 9.0, or 10.0 with support for JavaScript and cookies. Oracle and Java are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.	

Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

3.	Active NOAMP: Set Failed Servers to Standby	Navigate to Main Menu → Status & Manage → HA Status & Manage Network Elements Server HA Database KPIs Processes Select Edit Set the Max Allowed HA Role drop down box to Standby for the failed servers. Select Ok Ok Cancel
4.	Create VMs Recover the Failed Software	Execute the following procedures from reference Oracle Communications User Data Repository 15.0 Cloud Installation and Configuration Guide, latest revision [2]: Procedure 2: Deploy Oracle Communications User Data Repository Virtual Machines on VMware
5.	Repeat for Remaining Failed Servers	If necessary, repeat step 5 for all remaining failed servers.
6.	Active NOAMP: Login	Establish a GUI session on the NOAMP server by using the VIP IP address of the NOAMP server. Open the web browser and enter a URL of: http:// <primary_noamp_vip_ip_address> Login as the <i>guiadmin</i> user: Oracle System Login Fit Nut 20 12:29:52 2015 EOT Log in Enter your username and password to log in Username: guadrum Password: Vivocare to the Oracle System be use of the requester part crosses. Oracle de Alla se reproduct advances of port corporate advances of port corporate access of Corporate advances of the requester across.</primary_noamp_vip_ip_address>


Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

7.	Active NOAMP: Recover Standby NOAMP	Configure the standby NOAMP server by executing procedures from reference Oracle Communications User Data Repository 15.0 Cloud Installation and Configuration Guide, latest revision [2]:
		Procedure 4 "Create Configuration for Remaining Servers", Step 22.
		Procedure 10 "Apply Configuration for Remaining Servers" for NOAMP.
		Note: If Topology or nodeId alarms are persistent after the database restore, refer to the steps below.
8.	Active NOAMP: Restart UDR application on Recovered NOAMP	Navigate to Main Menu → Status & Manage → Server, Status & Manage Network Elements Server HA Database KPIs Processes Tasks Files
		Select the recovered standby NOAMP server and click on Restart . Stop Restart Reboot NTP Sync Report
9.	Active NOAMP: Set HA on Recovered NOAMP	Navigate to Status & Manage Status & Manage Network Elements Server HA Database KPIs Processes Tasks Files
		Click on Edit at the bottom of the screen Select the standby NOAMP server, set it to Active
		Press OK


Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

10.	Active NOAMP: Stop Replication to the MP Servers of this Site.	Inhibit Replication to the working C Level Servers which belong to the same site as the failed SOAM servers, as the recovery of Active SOAM will cause the database wipeout in the C level servers because of the replication Execute Appendix B Inhibit A and B Level Replication on C-Level Servers
11.	Active NOAMP: Recover SOAM Server	Recovery the SOAM server by executing procedures from reference Oracle Communications User Data Repository 15.0 Cloud Installation and Configuration Guide, latest revision [2]: Procedure 4 "Create Configuration for Remaining Servers", Step 22. Procedure 10 "Apply Configuration for Remaining Servers" for SOAM
12.	Active NOAMP: Restart UDR application on Recovered SOAM	Navigate to Main Menu → Status & Manage → Server Status & Manage Network Elements Server HA Database KPIs Processes Tasks Files Select the recovered SOAM server and click on Restart. Stop Restart Reboot NTP Sync Report

Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact




Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact




Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

15.	Recovered SOAM: Login	Establish a GUI session on the recovered SOAM server. Open the web browser and enter a URL of:
		http:// <recovered_soam_ip_address></recovered_soam_ip_address>
		Login as the <i>guiadmin</i> user:
		ORACLE"
		Oracle System Login Fri Mar 20 12:29:52 2015 EDT
		Log in Enter your username and password to log in Username: guadnin Password: Change password
		Log in Wecome to the Cracie System Login.
		Unauthorized access is prohibbed. This Chacks system requires the use of Microsoft Internet Explorer 6.0, 9.0, or 10.0 with support for JavaScript and cookers.
		Oracle and Jase are registered tradvanate of Onice Corporation and/or its affiliates. Other names may be trademants of their respective owners.



Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact



Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

18.	Recovered SOAM: Monitor	Wait for 5-10 minutes for the System to stabilize with the new topology:
	and Confirm database restoral	Monitor the Info tab for "Success". This will indicate that the backup is complete and the system is stabilized.
		Note: Do not pay attention to alarms until all the servers in the system are completely restored.
		Note: The Configuration and Maintenance information will be in the same state it was backed up during initial backup.
19.	Active NOAMP:	NOTE: For Non-HA sites SKIP this step
	Recover remaining SOAM Server	Configure the remaining SOAM server by executing procedures from reference Oracle Communications User Data Repository 15.0 Cloud Installation and Configuration
	(HA Deployments Only)	Guide, latest revision [2]:
		Procedure 4 "Create Configuration for Remaining Servers", Step 22.
		Procedure 10 "Apply Configuration for Remaining Servers" for second SOAM.
		NOTE: Wait for server to reboot before continuing.
20.	Active NOAMP:	Navigate to Main Menu → Status & Manage → Server
	Restart UDR application on	Status & Manage Network Elements
	Recovered SOAM	Server Server
	(HA Deployments Only)	o HA o Database
		KPIs Processes
		Tasks Files
		The second section is a second section in the second section in the second section is a second section in the second section in the second section is a second section in the second section in the second section is a second section in the second section in the second section is a second section in the second section in the second section is a second section in the second section in the second section is a second section in the second section in the second section is a second section in the second section in the second section is a second section in the second section in the second section is a second section in the second section in the second section is a second section in the second section in the second section is a second section in the second section in the second section is a second section in the second section in the second section is a second section in the second section in the second section is a second section in the second section in the second section is a second section in the second section in the second section is a second section in the second section in the second section is a second section in the second section in the second section is a second section in the second section in the second section is a section in the second section in the section is a section in the section in the section in the section is a section in the section in the section in the section is a section in the section in
		Select the recovered SOAM server and click on Restart .
		Stop Restart Reboot NTP Sync Report


Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

21.	Active NOAMP: Set HA on SOAM Servers (HA Deployments Only)	NOTE: For Non-HA sites SKIP this step Navigate to Status & Manage → HA Status & Manage Network Elements Server Database KPIS Processes Tasks Files Click on Edit at the bottom of the screen For each SOAM server whose Max Allowed HA Role is set to Standby, set it to Active Press OK
22.	Recovered Servers: Login	Establish an SSH to the recovered server's XMI address:


Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

23.	23. Recovered Servers: Sync NTP	1) Perform the following to retrieve the remote NTP server:
		\$ sudo ntpq -np
		Example output:
		[admusr@NOAMP-2 ~]\$ ntpq -np
		remote refid st t when poll reach delay offset jitter
		*10.240.9.186 10.250.33.2 3 u 356 1024 377 1.409 0.113 2.434
		2) Stop ntpd service:
		\$ sudo service ntpd stop
		3) Sync the date to the ntp remote server:
		\$ sudo ntpdate <ntp remote="" server=""></ntp>
		Note: The remote server below will be that of the one gathered in sub step 1.
		4) Start the ntp service:
		\$ sudo service ntpd start

Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact




Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact



Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

27.	Active NOAMP: Set HA on all MP Servers	Navigate to Status & Manage Status & Manage Network Elements Server HA Database KPIs Processes Tasks Files Click on Edit at the bottom of the screen For each server whose Max Allowed HA Role is set to Standby, set it to Active Press OK
28.	Active NOAMP: Perform key exchange between the active-NOAMP and recovered servers.	Establish an SSH session to the Active NOAMP, login as admusr. Execute the following command to perform a keyexchange from the active NOAMP to each recovered server: \$ keyexchange admusr@ <recovered hostname="" server=""> Note: If an export server is configured, perform this step.</recovered>


Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact




Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

30.	Active NOAMP:	Login to the Active NOAMP via SSH terminal as <i>admusr</i> user.
	Verify Replication Between Servers.	Execute the following command:
		\$ sudo irepstat -m
		Output like below shall be generated:
		Policy 0 ActStb [DbReplication]
		RDU06-MP1 Stby
		BC From RDU06-S01 Active 0 0.50 ^0.17%cpu 42B/s A=none
		CC From RDU06-MP2 Active 0 0.10 ^0.17 0.88%cpu 32B/s A=none
		RDU06-MP2 Active
		BC From RDU06-S01 Active 0 0.50 ^0.10%cpu 33B/s A=none
		CC To RDU06-MP1 Active 0 0.10 0.08%cpu 20B/s A=none
		RDU06-NO1 Active
		AB To RDU06-S01 Active 0 0.50 1%R 0.03%cpu 21B/s
		RDU06-S01 Active
		AB From RDU06-N01 Active 0 0.50 ^0.04%cpu 24B/s
		BC To RDU06-MP1 Active 0 0.50 1%R 0.04%cpu 21B/s
		BC To RDU06-MP2 Active 0 0.50 1%R 0.07%cpu 21B/s


Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact



Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact



Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact



Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

37.	Active SOAM: Enable SPR Features	Navigate to Main Menu → Diameter → Maintenance → Applications
	reatures	Maintenance Route Lists Route Groups Peer Nodes Connections Egress Throttle Groups Applications DA-MPs
		Select the feature application Click the Enable button. Enable Disable Pause updates
38.	Active SOAM: Examine All Alarms	Navigate to Main Menu → Alarms & Events → View Active Alarms & Events View Active View History View Trap Log
		Examine all active alarms and refer to the on-line help on how to address them. If needed contact My Oracle Support (MOS).
39.	Active NOAMP: Examine All Alarms	Login to the NOAMP VIP if not already logged in.
	Alainis	Navigate to Main Menu → Alarms & Events → View Active Alarms & Events View Active View History View Trap Log
		Examine all active alarms and refer to the on-line help on how to address them.
40.	Backup and Archive All the Databases from the Recovered System	If needed contact My Oracle Support (MOS). Execute Appendix A Oracle Communications User Data Repository Database Backup to back up the Configuration database.
		THIS PROCEDURE HAS BEEN COMPLETED

4.1.3 Recovery Scenario 3 (Partial Server Outage with all NOAMP servers failed and one SOAM server intact)

For a partial server outage with an SOAM server intact and available; NOAMP servers are recovered using recovery procedures for software and then executing a database restore to the active NOAMP server using a NOAMP database backup file obtained from external backup sources such as customer servers. All other servers are recovered using recovery procedures for software. Database replication from the active NOAMP/active SOAM server will recover the database on these servers. The major activities are summarized in the list below. Use this list to understand the recovery procedure summary. Do not use this list to execute the procedure. The actual procedures' detailed steps are in **Procedure 3**. The major activities are summarized as follows:

Recover Active NOAMP server by recovering software and the database.

- Recover the software.
- Recover the database

Recover Standby NOAMP servers by recovering software.

• Recover the software.


Recover any failed **SOAM and MP servers** by recovering software.

- Recover the software.
- Database is already intact at one SOAM server and does not require restoration at the other SOAM and MP servers.


Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact


S T	This procedure perf	forms recovery if ALL NOAMP servers are failed but 1 or more SOAM servers are intact.	
E P #	Check off ($$) each step as it is completed. Boxes have been provided for this purpose under each step number.		
	" If this procedure fails, contact My Oracle Support (MOS), and ask for assistance.		
1.	Gather Required Materials	Gather the documents and required materials listed in Section Required Materials	
2.	Recover the Failed Software	Execute the following procedures from reference Oracle Communications User Data Repository 15.0 Cloud Installation and Configuration Guide, latest revision [2]:	
		Procedure 2: Deploy Oracle Communications User Data Repository Virtual Machines on VMware	
3.	Obtain Latest Database Backup and Network	Obtain the most recent database backup file from external backup sources (ex. file servers) or tape backup sources.	
	Configuration Data.	From required materials list in Section Required Materials ; use site survey documents and Network Element report (if available), to determine network configuration data.	
4.	Execute UDR Installation Procedure for the First	Configure the First NOAMP server by executing procedures from reference Oracle Communications User Data Repository 15.0 Cloud Installation and Configuration Guide, latest revision [2]:	
	NOAMP	Procedure 3 "Configure NOAMP-A Server (1st NOAMP Only)" for first NOAMP.	
		Note: If Topology or nodeld alarms are persistent after the database restore, refer to the steps below.	
5.	Active NOAMP: Login	Login to the NOAMP GUI as the guiadmin user: Oracle System Login Enter your username and password to log in Username: guidnin Password: """" Password: """" Wetcome to the Cracle System Login Username: One Course System Login Unauthorized access is prohibited. The Oncie System Ingers the use of Micropol Internet Epitorer 8.0, 9.0, or 10 one temporar to antiform and coolines. Oracle and Just are registered radiomates of Onese Copposation motify at affiliates. Oracle and Just are registered radiomates of their respection context.	

Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact



Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact






Release 15.0.0.0.0 October 2023 66

procedure.

If the verification is successful, Click BACK button and continue to next step in this

Procedure 3: Recovery Scenario 3 - Partial Outage One SOAM Intact



Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact

10.	Active NOAMP: Login	Establish a GUI session on the NOAMP server by using the VIP IP address of the NOAMP server. Open the web browser and enter a URL of: http:// <primary_noamp_vip_ip_address> Login as the <i>guiadmin</i> user: Oracle System Login In Mar 20 12:79:52 2015 EDT Log In Enter your username and password to log in Username: guidnin Password: Log In Username: Guidnin Password: Change password Log In Unashvired access to published. This Orace system has be used it forced till stemed Dipover 6 0, 0, 0, or 10 this suggest of saverlage has be used to forced oracle. Oracle and alless are applied refraemed a college. Oracle and alless are applied refraemed and oracle and annuals. Other reserve ring de its demands of one respective ouvers.</primary_noamp_vip_ip_address>
11.	Active NOAMP: Monitor and Confirm database restoral	Wait for 5-10 minutes for the System to stabilize with the new topology: Monitor the Info tab for "Success". This will indicate that the backup is complete and the system is stabilized. Following alarms must be ignored for NOAMP and MP Servers until all the Servers are configured: Alarms with Type Column as "REPL", "COLL", "HA" (with mate NOAMP), "DB" (about Provisioning Manually Disabled) Note: Do not pay attention to alarms until all the servers in the system are completely restored. Note: The Configuration and Maintenance information will be in the same state it was backed up during initial backup.
12.	Active NOAMP: Login	Login to the recovered Active NOAMP via SSH terminal as <i>admusr</i> user.

Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact

13.	Active NOAMP: Restore /etc/hosts/	Execute the following command:
	File of the Active NOAMP	\$ sudo AppWorks AppWorks_AppWorks updateServerAliases <noamp host="" name=""></noamp>
14.	Active NOAMP: Re-enable Provisioning	Navigate to Main Menu → Status & Manage → Database Enable Provisioning Report Inhibit/Allow Replication Backup Com
		Click on the Enable Provisioning . A pop-up window will appear to confirm as shown below, press OK .
		Enable provisioning. Are you sure?
		OK Cancel
15.	Active NOAMP: Recover Standby NOAMP	Configure the second NOAMP server by executing procedures from reference Oracle Communications User Data Repository 15.0 Cloud Installation and Configuration Guide, latest revision [2]:
	(HA Deployments	Procedure 4 "Create Configuration for Remaining Servers", Step 2.
	Only)	Procedure 10 "Apply Configuration for Remaining Servers" for second NOAMP.
		Note: If Topology or nodeId alarms are persistent after the database restore, refer to the steps below.
16.	Active NOAMP: Recover remaining failed SOAM Servers	Repeat Step 7 for any SOAM server that needs to be recovered.

Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact

17.	Active NOAMP: Set HA on all C- Level Servers	Navigate to Status & Manage Status & Manage Network Elements Server Database KPIs Processes Tasks Files Click on Edit at the bottom of the screen For each server whose Max Allowed HA Role is set to Standby, set it to Active Press OK
18.	Recovered Servers: Login	Establish an SSH to the recovered server's XMI address:


Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact

19. Recovered Servers: Syr		1) Perform the following to retrieve the remote NTP server:
		\$ sudo ntpq -np
		Example output:
		[admusr@NOAMP-2 ~]\$ ntpq -np remote refid st t when poll reach delay offset jitter
		*10.240.9.186 10.250.33.2 3 u 356 1024 377 1.409 0.113 2.434
		2) Stop ntpd service:
		\$ sudo service ntpd stop
		3) Sync the date to the ntp remote server:
		\$ sudo ntpdate <ntp remote="" server=""></ntp>
		Note: The remote server below will be that of the one gathered in sub step 1.
		4) Start the ntp service:
		\$ sudo service ntpd start

Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact

20.	Active NOAMP: Restart UDR application on recovered servers	Navigate to Main Menu → Status & Manage → Server, Status & Manage Network Elements Server HA Database KPIs Processes Tasks Files Select each recovered server and click on Restart.
		Stop Restart Reboot NTP Sync Report
21.	Active NOAMP: Perform key exchange between the active- NOAMP and recovered servers.	Establish an SSH session to the Active NOAMP, login as <i>admusr</i> . Execute the following command to perform a keyexchange from the active NOAMP to each recovered server:
		\$ keyexchange admusr@ <recovered hostname="" server=""></recovered>
		Note: If an export server is configured, perform this step.


Procedure 3: Recovery Scenario 3 - Partial Outage One SOAM Intact




Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact

23.	Active NOAMP:	Login to the Active NOAMP via SSH terminal as admusr user.
	Verify Replication Between Servers.	Execute the following command:
		\$ sudo irepstat -m
		Output like below shall be generated:
		Policy 0 ActStb [DbReplication]
		RDU06-MP1 Stby
		BC From RDU06-S01 Active 0 0.50 ^0.17%cpu 42B/s A=none
		CC From RDU06-MP2 Active 0 0.10 ^0.17 0.88%cpu 32B/s A=none
		RDU06-MP2 Active
		BC From RDU06-S01 Active 0 0.50 ^0.10%cpu 33B/s A=none
		CC To RDU06-MP1 Active 0 0.10 0.08%cpu 20B/s A=none
		RDU06-NO1 Active
		AB To RDU06-S01 Active 0 0.50 1%R 0.03%cpu 21B/s
		RDU06-S01 Active
		AB From RDU06-NO1 Active 0 0.50 ^0.04%cpu 24B/s
		BC To RDU06-MP1 Active 0 0.50 1%R 0.04%cpu 21B/s
		BC To RDU06-MP2 Active 0 0.50 1%R 0.07%cpu 21B/s


Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact



Procedure 3: Recovery Scenario 3 - Partial Outage One SOAM Intact



Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact



Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact

30.	Active SOAM: Enable Optional Features	Navigate to Main Menu → Diameter → Maintenance → Applications Maintenance Route Lists Route Groups Peer Nodes Connections Egress Throttle Groups Applications DA-MPs Select the SPR feature application. Click the Enable button.
31.	Active SOAM: Examine All Alarms	Navigate to Main Menu → Alarms & Events → View Active Alarms & Events View Active View History View Trap Log Examine all active alarms and refer to the on-line help on how to address them. If needed contact My Oracle Support (MOS).
32.	Active NOAMP: Examine All Alarms	Login to the NOAMP VIP if not already logged in. Navigate to Main Menu → Alarms & Events → View Active Alarms & Events View Active View History View Trap Log Examine all active alarms and refer to the on-line help on how to address them. If needed contact My Oracle Support (MOS).
33.	Restore GUI Usernames and Passwords	If applicable, Execute steps in Section 5 to recover the user and group information restored.

Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact

34.	Backup and Archive All the Databases from the Recovered System	Execute Appendix A Oracle Communications User Data Repository Database Backup to back up the Configuration databases.
THIS PROCEDURE HAS BEEN COMPLETED		

4.1.4 Recovery Scenario 4 (Partial Server Outage with one NOAMP server and one SOAM server intact)

For a partial outage with an NOAMP server and an SOAM server intact and available, only base recovery of software is needed. The intact NO and SOAM servers are capable of restoring the database via replication to all servers. The major activities are summarized in the list below. Use this list to understand the recovery procedure summary. Do not use this list to execute the procedure. The actual procedures' detailed steps are in Procedure 4. The major activities are summarized as follows:

Recover Standby NOAMP server by recovering software.

• Recover the software.

The database is intact at the active NOAMP server and does not require restoration at the standby NOAMP server.

- Recover any failed SO and MP servers by recovering software.
- Recover the software.

The database in intact at the active NOAMP server and does not require restoration at the SO and MP servers.

• Re-apply signaling networks configuration if the failed VM is an MP.

Procedure 4: Recovery Scenario 4 – Partial Outage One NOAMP & One SOAM Intact

S T	This procedure performs recovery if at least 1 NOAMP server is intact and available and 1 SOAM server is intact and available.		
E P	Check off $(\sqrt{)}$ each step as it is completed. Boxes have been provided for this purpose under each step number.		
#	If this procedure fai	ls, contact My Oracle Support (MOS), and ask for assistance.	
1.	Gather Required Materials	Gather the documents and required materials listed in Section 3.1 Required Materials	
2.	Active NOAMP: Login	Establish a GUI session on the NOAMP server by using the VIP IP address of the NOAMP server. Open the web browser and enter a URL of:	
		http:// <primary_noamp_vip_ip_address></primary_noamp_vip_ip_address>	
		Login as the guiadmin user: Oracle System Login Fri Mar 20 12:29:52 2015 EDT Log In Enter your username and password to log in Username: guiadmin Password: Change password Log In Welcome to the Oracle System Login. Unauthorized access is prohibited: This Oracle system requires the use of Microsoft Internet Explorer 8.0, 9.0, or 100 with support for JavaScraft and cooless. Oracle and Java aire registered trademarks of oracle Corporation andor its affiliates. Other names may be indemarks of their respective owners.	
3.	Active NOAMP: Set Failed Servers to Standby	Navigate to Main Menu → Status & Manage → HA Status & Manage Network Elements Server Database KPIs Processes Select Edit Set the Max Allowed HA Role drop down box to Standby for the failed servers. Select Ok Ok Cancel	

Procedure 4: Recovery Scenario 4 – Partial Outage One NOAMP & One SOAM Intact

4.	Recover the Failed Software	Execute the following procedures from reference Oracle Communications User Data Repository 15.0 Cloud Installation and Configuration Guide, latest revision [2]: Procedure 2: Deploy Oracle Communications User Data Repository Virtual Machines on VMware	
5.	Repeat for Remaining Failed Servers	If necessary, repeat 4 for all remaining failed servers.	
6.	Active NOAMP: Login	Establish a GUI session on the NOAMP server by using the VIP IP address of the NOAMP server. Open the web browser and enter a URL of:	
		http:// <primary_noamp_vip_ip_address></primary_noamp_vip_ip_address>	
		Login as the <i>guiadmin</i> user:	
		ORACLE"	
		Oracle System Login Fri Mar 20 12:29:52 2015 EDT	
		Log In Enter your username and password to log in Username: guiadmin Password: •••••• Change password Log In	
		Welcome to the Oracle System Login. Unauthorized access is prohibited. This Oracle system requires the use of Microsoft Internet Explorer 8.0, 9.0, or 10.0 with support for JavaScript and cookies.	
		Oracle and Java are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.	
7.	Active NOAMP: Recover Standby NOAMP if needed	Configure the second NOAMP server by executing procedures from reference Oracle Communications User Data Repository 15.0 Cloud Installation and Configuration Guide, latest revision [2]:	
		Procedure 4 "Create Configuration for Remaining Servers", Step 2.	
		Procedure 10 "Apply Configuration for Remaining Servers"	
		Note: If Topology or nodeId alarms are persistent after the database restore, refer to the steps below.	


Procedure 4: Recovery Scenario 4 – Partial Outage One NOAMP & One SOAM Intact

8.	Active NOAMP: Recover the Failed SOAM Servers if needed	Repeat Step 7 for any SOAM server that needs to be recovered.
9.	Active NOAMP: Set HA on Recovered Servers	Navigate to Status & Manage → HA Status & Manage Network Elements Server HA Database KPIs Processes Tasks Files Click on Edit at the bottom of the screen For each server whose Max Allowed HA Role is set to Standby, set it to Active Press OK
10.	Recovered Servers: Login	Establish an SSH to the recovered server's XMI address:

Procedure 4: Recovery Scenario 4 – Partial Outage One NOAMP & One SOAM Intact

Recovered Servers: Sync	1) Perform the following to retrieve the remote NTP server:
NTP	\$ sudo ntpq -np
	Example output:
	[admusr@NOAMP-2 ~]\$ ntpq -np remote refid st t when poll reach delay offset jitter
	*10.240.9.186 10.250.33.2 3 u 356 1024 377 1.409 0.113 2.434
	2) Stop ntpd service:
	\$ sudo service ntpd stop
	3) Sync the date to the ntp remote server:
	\$ sudo ntpdate <ntp remote="" server=""></ntp>
	Note: The remote server below will be that of the one gathered in sub step 1.
	4) Start the ntp service:
	\$ sudo service ntpd start


Procedure 4: Recovery Scenario 4 – Partial Outage One NOAMP & One SOAM Intact



Procedure 4: Recovery Scenario 4 – Partial Outage One NOAMP & One SOAM Intact

15.	Active NOAMP: Set HA on all MP servers	Navigate to Status & Manage Status & Manage Network Elements Server HA Database KPIs Processes Tasks Files Click on Edit at the bottom of the screen For each server whose Max Allowed HA Role is set to Standby, set it to Active Press OK
16.	Active NOAMP: Login	Login to the recovered Active NOAMP via SSH terminal as <i>admusr</i> user.
17.	Active NOAMP: Perform key exchange between the active- NOAMP and recovered servers.	Establish an SSH session to the Active NOAMP, login as admusr. Execute the following command to perform a keyexchange from the active NOAMP to each recovered server: \$ keyexchange admusr@ <recovered hostname="" server=""></recovered>
18.	Active NOAMP: Establish SSH	Establish an SSH session to the active NOAMP, login as <i>admusr</i> .


Procedure 4: Recovery Scenario 4 – Partial Outage One NOAMP & One SOAM Intact




Procedure 4: Recovery Scenario 4 – Partial Outage One NOAMP & One SOAM Intact

20. □	Active NOAMP: Verify Replication	Login to the Active NOAMP via SSI Execute the following command:	I tern	ninal as <i>admusr</i> user.
	Between Servers.			
		\$ sudo irepstat -m		
		Output like below shall be generate	d:	
		Policy 0 ActStb [DbReplicat	ion]	
		RDU06-MP1 Stby		
		BC From RDU06-S01 Active A=none	0	0.50 ^0.17%cpu 42B/s
			0	0.10 ^0.17 0.88%cpu 32B/s A=none
		RDU06-MP2 Active		0.50.40.400
				0.50 ^0.10%cpu 33B/s A=none
		RDU06-NO1 Active	U	0.10 0.08%cpu 20B/s A=none
		AB To RDU06-S01 Active	0	0.50 1%R 0.03%cpu 21B/s
		RDU06-S01 Active	ŭ	0.00 101 0.0000pa 115, 0
		AB From RDU06-NO1 Active	0	0.50 ^0.04%cpu 24B/s
		BC To RDU06-MP1 Active	0	0.50 1%R 0.04%cpu 21B/s
		BC To RDU06-MP2 Active 21B/s	0	0.50 1%R 0.07%cpu


Procedure 4: Recovery Scenario 4 – Partial Outage One NOAMP & One SOAM Intact



Procedure 4: Recovery Scenario 4 – Partial Outage One NOAMP & One SOAM Intact



Procedure 4: Recovery Scenario 4 – Partial Outage One NOAMP & One SOAM Intact



Procedure 4: Recovery Scenario 4 – Partial Outage One NOAMP & One SOAM Intact

27.	Active SOAM: Enable Optional Features	Navigate to Main Menu → Diameter → Maintenance → Applications Maintenance Route Lists Route Groups Peer Nodes Connections Egress Throttle Groups Applications DA-MPs Select the SPR feature applications. Click the Enable button. Pause updates
28.	Active SOAM: Examine All Alarms	Navigate to Main Menu → Alarms & Events → View Active Alarms & Events View Active View History View Trap Log Examine all active alarms and refer to the on-line help on how to address them. If needed contact My Oracle Support (MOS).
29.	Active NOAMP: Examine All Alarms	Login to the NOAMP VIP if not already logged in. Navigate to Main Menu → Alarms & Events → View Active Alarms & Events View Active View History View Trap Log Examine all active alarms and refer to the on-line help on how to address them. If needed contact My Oracle Support (MOS).

Procedure 4: Recovery Scenario 4 – Partial Outage One NOAMP & One SOAM Intact

30.	Restart oampAgent if Needed	Note: If alarm "10012: The responder for a monitored table failed to respond to a table change" is raised, the oampAgent needs to be restarted.	
		Establish an SSH session to each server that has the alarm.	
		Login as admusr	
		Execute the following commands:	
		\$ sudo pm.set off oampAgent	
		\$ sudo pm.set on oampAgent	
31.	Backup and Archive All the	Execute Appendix A Oracle Communications User Data Repository Database Backup to back up the Configuration databases.	
	Databases from	Backup to back up the Configuration databases.	
	the Recovered System		
	THIS PROCEDURE HAS BEEN COMPLETED		

4.1.5 Recovery Scenario 5 (Database Recovery)

The following sections deal with recovering from database corruption, whether a backup is present or not.

4.1.5.1 Recovery Scenario 5: Case 1

For a partial outage with

- Server having a corrupted database
- Replication channel from parent is inhibited because of upgrade activity or
- Server is in a different release then that of its Active parent because of upgrade activity.
- Verify that the Server Runtime backup files, performed at the start of the upgrade, are present in /var/TKLC/db/filemgmt area in the following format
 - $\circ \quad Backup. UDR. HPC02-NO2. FullDBParts. NETWORK_OAMP. 20140524_223507. UPG. tar. bz 20140524_223507. UPG. bz 20140524_223507. UPG. bz 20140524_223507. UPG. bz 20140524_223507. UPG. bz 20140524_22507. UPG. bz 20140524_22507. UPG. bz 20140524_22$
 - o Backup.UDR.HPC02-NO2.FullRunEnv.NETWORK_OAMP.20140524_223507.UPG.tar.bz2

Note: During recovery, the corrupted Database will get replaced by the sever Runtime backup. Any configuration done after taking the backup will not be visible post recovery.

Procedure 5: Recovery Scenario 5 (Case 1) – Database Recovery Backup Present

S T E P #	This procedure performs recovery if database is corrupted in the system Check off ($$) each step as it is completed. Boxes have been provided for this purpose under each step number. If this procedure fails, contact My Oracle Support (MOS) , and ask for assistance.	
1.	Active NOAMP: Set Failed Servers to Standby	Navigate to Main Menu → Status & Manage → HA Status & Manage Network Elements Server HA Database KPIS Processes Select Edit Set the Max Allowed HA Role drop down box to Standby for the failed servers. Select Ok Ok Cancel
2.	Server with DB Corruption: Login	Establish an SSH session to the server in question. Login as <i>admusr</i> user.
3.	Server with DB Corruption: Change runlevel to 3	Execute the following command to bring the system to runlevel 3. \$ sudo init 3

Procedure 5: Recovery Scenario 5 (Case 1) – Database Recovery Backup Present

4.	Server with DB Corruption: Recover System	Execute the following command and follow the instructions appearing the console prompt \$ sudo /usr/TKLC/appworks/sbin/backout_restore
5.	Server with DB Corruption: Change runlevel to 4	Execute the following command to bring the system back to runlevel 4. \$ sudo init 4
6.	Server with DB Corruption: Verify the server	Execute the following command to verify if the processes are up and running \$ sudo pm.getprocs
7.	Active NOAMP: Set Failed Servers to Active	Navigate to Status & Manage → HA Status & Manage Network Elements Server Database Files Click on Edit at the bottom of the screen For each failed server whose Max Allowed HA Role is set to Standby, set it to Active Press OK
8.	Backup and Archive All the Databases from the Recovered System	Execute Appendix A Oracle Communications User Data Repository Database Backup to back up the Configuration databases:
	l	THIS PROCEDURE HAS BEEN COMPLETED

4.1.5.2 Recovery Scenario 5: Case 2

For a partial outage with

- Server having a corrupted database
- Replication channel is available or
- Server has the same release as that of its Active parent

Procedure 6: Recovery Scenario 5 (Case 2) – Database Recovery Backup Not Present

S T	This procedure perforeplicated	orms recovery if database got corrupted in the system and system is in the state to get								
E P	Check off $()$ each step as it is completed. Boxes have been provided for this purpose under each step number.									
#	If this procedure fail	If this procedure fails, contact My Oracle Support (MOS), and ask for assistance.								
1.	Active NOAMP: Set Failed Servers to Standby	Navigate to Main Menu → Status & Manage → HA Status & Manage Network Elements Server HA Database KPIs Processes Select Edit Set the Max Allowed HA Role drop down box to Standby for the failed servers. Select Ok Ok Cancel								
2.	Server with DB Corruption: Login	Establish an SSH session to the server in question. Login as <i>admusr</i> user.								
3.	Server with DB Corruption: Take Server out of Service	Execute the following command to take the server out of service. \$ sudo bash -1 \$ sudo prod.clobber								
4.	Server with DB Corruption: Take Server to DbUp State and Start the Application	Execute the following commands to take the server to Dbup and start the Oracle Communications User Data Repository application: \$ sudo bash -1 \$ sudo prod.start								

Procedure 6: Recovery Scenario 5 (Case 2) – Database Recovery Backup Not Present

5.	Server with DB Corruption:	Execute the following commands to verify the processes are up and running:										
	Verify the Server State	\$ sudo pm.getprocs										
		Execute the following command to verify if replication channels are up and running:										
		\$ sudo irepstat										
		Execute the following command to verify if merging channels are up and running:										
		\$ sudo inetmstat										
6.	Active NOAMP: Restart UDR application	Navigate to Main Menu → Status & Manage → Server Status & Manage Network Elements Server HA Database Files Files Select each recovered server and click on Restart. Stop Restart Reboot NTP Sync Report										

Procedure 6: Recovery Scenario 5 (Case 2) – Database Recovery Backup Not Present

7.	Active NOAMP: Set Failed Servers to Active	Navigate to Status & Manage Status & Manage Network Elements Server Database KPIs Processes Tasks Files Click on Edit at the bottom of the screen For each failed server whose Max Allowed HA Role is set to Standby, set it to Active Press OK
8.	Backup and Archive All the Databases from the Recovered System	Execute Appendix A Oracle Communications User Data Repository Database Backup to back up the Configuration databases:
		THIS PROCEDURE HAS BEEN COMPLETED

5 RESOLVING USER CREDENTIAL ISSUES AFTER DATABASE RESTORE

User incompatibilities may introduce security holes or prevent access to the network by administrators. User incompatibilities are not dangerous to the database, however. Review each user difference carefully to ensure that the restoration will not impact security or accessibility.


5.1 Keeping a Restored User (Resetting User Password)

User accounts kept across a restore operation should have their passwords reset. This procedure guides you through that process.

Procedure 7: Keep Restored User (Resetting User Password)

S T	Perform this proce	dure to keep users that will be restored by system restoration.
E P #	number.	step as it is completed. Boxes have been provided for this purpose under each step
	If this procedure fa	tils, contact My Oracle Support (MOS), and ask for assistance.
1.	Before Restoration: Notify Affected Users (Before Restoration)	Contact each user that is affected <u>before the restoration</u> and notify them that you will reset their password during this maintenance operation.
2.	After Restoration: Login to the	Establish a GUI session on the NOAMP server by using the VIP IP address of the NOAMP server. Open the web browser and enter a URL of:
	Active NOAMP	http:// <primary_noamp_vip_ip_address></primary_noamp_vip_ip_address>
	(Before Restoration)	Login as the <i>guiadmin</i> user:
		ORACLE"
		Oracle System Login Fri Mer 20 12:29:52 2015 EDT
		Log in Enter your username and password to log in Username: guiadmin Password: ••••••• Change password Log in
		Welcome to the Oracle System Login.
		Unauthorized access is prohibited. This Oracle system requires the use of Microsoft Internet Explorer 8.0, 9.0, or 10.0 with support for JavaScript and cookies.
		Cracie and Java are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

Procedure 7: Keep Restored User (Resetting User Password)




5.2 Removing a Restored User

Procedure 8: Remove the Restored User

S T	Perform this proce	edure to remove users that will be restored by system restoration						
E P	Check off $()$ each number.	h step as it is completed. Boxes have been provided for this purpose under each step						
#	If this procedure f	ails, contact My Oracle Support (MOS), and ask for assistance.						
1.	After Restoration: Login to the	Establish a GUI session on the NOAMP server by using the VIP IP address of the NOAMP server. Open the web browser and enter a URL of:						
	Active NOAMP	http:// <primary_noamp_vip_ip_address></primary_noamp_vip_ip_address>						
		Login as the <i>guiadmin</i> user:						
		ORACLE"						
		Oracle System Login Fri Mar 20 12:29:52 2015 EDT						
		Log In Enter your username and password to log in Username: guiadmin Password: •••••• Change password Log In						
		Welcome to the Oracle System Login. Unauthorized access is prohibited. This Oracle system requires the use of Microsoft Internet Explorer 8.0, 9.0, or 10.0 with support for JavaScript and cookies.						
		Oracle and Java are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.						

Procedure 8: Remove the Restored User



5.3 Restoring a Modified User

These users have had a password change prior to creation of the backup and archive file. The will be reverted by system restoration of that file.

- The password for user 'testuser' differs between the selected backup file and the current database.

Before Restoration:

Verify that you have access to a user with administrator permissions that is not affected.

Contact each user that is affected and notify them that you will reset their password during this maintenance operation.

After Restoration:

Log in and reset the passwords for all users in this category. See the steps in Section 5.1 (Keeping a Restored User) for resetting passwords for a user.

5.4 Restoring an Archive that does not contain a Current User


These users have been created after the backup operation. The will be deleted by system restoration of that file.

If the user is no longer desired, do not perform any additional steps. The user is permanently removed.


Procedure 9: Restoring an Archive that does not Contain a Current User

S T E P #	Check off $(\sqrt{)}$ each s number.	ure to remove users that will be restored by system restoration step as it is completed. Boxes have been provided for this purpose under each step ls, contact My Oracle Support (MOS), and ask for assistance. Contact each user that is affected before the restoration and notify them that you will
	Restoration: Notify Affected Users (Before Restoration)	reset their password during this maintenance operation.
2.	Before Restoration: Login to the Active NOAMP (Before Restoration)	Establish a GUI session on the NOAMP server by using the VIP IP address of the NOAMP server. Open the web browser and enter a URL of: http:// <primary_noamp_vip_ip_address> Login as the guiadmin user: Cracle System Login Enter your username and password to log in Username: guiadmin Password Change password Change password Unauthoritied access is prohibited. This Oracle System requires the use of thicrosoft internet Explorer 8.0. 9.0, or 10 with support for Javascript and cooker. Oracle and Java are registered transferance of Oracle Cooperation andor its affiliates. Other names may be trademarks of their respective counters.</primary_noamp_vip_ip_address>


Procedure 9: Restoring an Archive that does not Contain a Current User



Procedure 9: Restoring an Archive that does not Contain a Current User



Procedure 9: Restoring an Archive that does not Contain a Current User




Appendix A. Oracle Communications User Data Repository Database Backup

Procedure 12: Restoring an Archive that does not Contain a Current User

S T E	The intent of this procedure is to back up the provision and configuration information from an NOAMP or SOAM server after the disaster recovery is complete									
P	Check off $()$ each step as it is completed. Boxes have been provided for this purpose under each step number.									
#	If this procedure fai	ls, contact My Oracle Support (MOS), and ask for assistance.								
1.	Active NOAMP/SOAM: Login	Establish a GUI session on the Active NOAMP or SOAM server by using the								
		Open the web browser and enter a URL of:								
		http:// <primary_noamp soam_vip_ip_address=""></primary_noamp>								
		Login as the <i>guiadmin</i> user:								
		Oracle System Login Fri Mar 20 12:29:52 2015 EDT								
		Log In Enter your username and password to log in Username: guiadmin Password: •••••• Change password Log In Welcome to the Oracle System Login. Unauthorized access is prohibited. This Oracle system requires the use of Microsoft Internet Explorer 8.0, 9.0, or 10.0 with support for JavaScript and cookies. Oracle and Java are registered trademarks of Oracle Corporation and/or its affiliates.								
		Other names may be trademarks of their respective owners.								


Procedure 12: Restoring an Archive that does not Contain a Current User



Procedure 12: Restoring an Archive that does not Contain a Current User




Procedure 12: Restoring an Archive that does not Contain a Current User



Appendix B. Inhibit A and B Level Replication on C-Level Servers

Procedure 13: Inhibit A and B Level Replication on C-Level Servers



Procedure 13: Inhibit A and B Level Replication on C-Level Servers

3	Active NOAMP: Verify Replication has been Inhibited. After executing above steps to inhibit replication on MP(s), no alarms on GUI would be raised informing that replication on MP is disabled.										
	analyzing l lected site										
	Perform the following command:										
		\$ sudo i	.qt NodeI	nfo							
	Expected output:										
		nodeId	nodeName	hostName	e nodeCapability	inhibitRepPlans	siteId	excludeTables			
		A1386.099	A1386.099 NO1 NO1 Active NO_HPC03								
		B1754.109	SO1	SO1	Active		SO_HPC03				
		C2254.131	MP2	MP2	Active	AB	SO_HPC03				
		C2254.233	MP1	MP1	Active	A B	SO_HPC03				
	1	THIS PE	ROCEDURI	E HAS B	EEN COMP	PLETED					

Release 15.0.0.0.0 111 October 2023

Appendix C. Un-Inhibit A and B Level Replication on C-Level Servers

Procedure 14: Un-Inhibit A and B Level Replication on C-Level Servers

S	The intent of this pr	ocedure	is to Un-i	nhil	bit A ar	nd B leve	el repli	cation or	n all C L	evel servers of	his site
E P #	Check off $(\sqrt{)}$ each snumber.	step as it	t is comple	ted	. Boxes	s have be	een pro	ovided for	r this pu	rpose under eac	h step
"	If this procedure fai	ls, conta	ct My Or	acl	e Supp	ort (MO	OS) , an	d ask for	assistar	ice.	
1.	Active NOAMP: Login	Login	to the Act	ive	NOAM	IP serve	r via S	SH as <i>au</i>	<i>lmusr</i> us	ser.	
2.	Active NOAMP:	Execu	te the follo	wii	ng com	mand:					
	Un-Inhibit replication on all C level Servers	Note: and go	deId liliset -f: deName= NE name oing to Con	of infig	C*' nibitl nibitl i''; o the site guration hot belovered th	and seppladone can be form \rightarrow Services for the site of the site	siteI ans=' found c ver G	d=' <ne '="" by="" e.g<="" log="" node="" out="" roups="" scretails.="" th=""><th>gging intreen.</th><th>to the Active No</th><th>DAMP GUI o the site</th></ne>	gging intreen.	to the Active No	DAMP GUI o the site
			Server Group Name	Loud	Darset	Function	Servers				3
			MPSG	C	SOSG	DSR (multi- active cluster)	NE SO_HPC03 SO_HPC03	Senier SeverIIP1 SeverIIP2	HA Role Pref	WPs	
			NOSG	A	NONE	DSR (active/standb) pair)	NE NO_HPC03 NO_HPC03	Serveri Serveri/01 Serveri/02	HA Role Pref	VIPs 10.240.10.166	
						p.m.)				10.240.10.166	
			SOSG	В	NOSG	DSR (adheistandb pair)	NE SOLERON SO_HPO03	Senier SenierS01 SenierS02	HA Role Pref	WPs 10.240.10.186 10.240.10.186	

Procedure 14: Un-Inhibit A and B Level Replication on C-Level Servers

3.	Active NOAMP: Verify Replication has been Inhibited.	be raised in Verification	of forming of replicibit Rep Pl B shall be the following of the following	that replication un- ans field set as 'A	eation on linhibition for all the B':	MP is disable on MPs can	on MP(s), no alarms on GUI d. be done by analyzing NodeI for the selected site e.g. Site			
		nodeId	nodeName	hostName r	nodeCapability	inhibitRepPlans	siteId excludeTables			
		A1386.099	A1386.099 NO1 NO1 Active NO_HPC03							
		B1754.109	B1754.109 SO1 SO1 Active SO_HPC03							
		C2254.131	MP2	MP2	Active		SO_HPC03			
		C2254.233	MP1	MP1	Active		SO_HPC03			

Appendix D. My Oracle Support (MOS)

MOS (https://support.oracle.com) is your initial point of contact for all product support and training needs. A representative at Customer Access Support (CAS) can assist you with MOS registration.

Call the CAS main number at **1-800-223-1711** (toll-free in the US), or call the Oracle Support hotline for your local country from the list at http://www.oracle.com/us/support/contact/index.html. When calling, make the selections in the sequence shown below on the Support telephone menu:

Select 2 for New Service Request

Select 3 for Hardware, Networking and Solaris Operating System Support Select one of the following options:

- For Technical issues such as creating a new Service Request (SR), Select 1
- For Non-technical issues such as registration or assistance with MOS, Select 2

You will be connected to a live agent who can assist you with MOS registration and opening a support ticket.

MOS is available 24 hours a day, 7 days a week, 365 days a year.

Appendix E. Locate Product Documentation on the Oracle Help Center Site

Oracle Communications customer documentation is available on the web at the Oracle Help Center (OHC) site, http://docs.oracle.com. You do not have to register to access these documents. Viewing these files requires Adobe Acrobat Reader, which can be downloaded at http://www.adobe.com.

- 1. Access the Oracle Help Center site at http://docs.oracle.com
- 2. Click Industries.
- 3. Under the Oracle Communications subheading, click the **Oracle Communications documentation** link. The Communications Documentation page appears. Most products covered by these documentation sets will appear under the headings "Network Session Delivery and Control Infrastructure" or "Platforms."
- 4. Click on your Product and then the Release Number.

 A list of the entire documentation set for the selected product and release appears.
- 5. To download a file to your location, right-click the **PDF** link, select **Save target as** (or similar command based on your browser), and save to a local folder.