Oracle® AI Database Database Net Services Reference





Oracle Al Database Database Net Services Reference, 26ai

G44161-01

Copyright © 2002, 2025, Oracle and/or its affiliates.

Primary Author: Spurthi SV

Contributing Authors: Doug Williams, Prakash Jashnani

Contributors: Alan Williams, Abhishek Dadhich, Anisha Chauhan, Anita Patel, Ashish Trivedi, Bhaskar Gharu, Bhaskar Mathur, Ching Tai, Christopher Jones, David Lin, Deepak Yadav, Feroz Khan, Gulshan Kumar, Hector Pujol, Jean Zeng, Kant Patel, Kevin Neel, Krishna Itikarlapalli, Kunal Waghmare, Mark Dilman, Michael McMahon, Misaki Miyashita, Manjunatha Kuruba, Mohammad Raihan Afzal, Murali Purayathu, Norman Woo, Peter Knaggs, Rajbir Chahal, Robert Achacoso, Santanu Datta, Saravanakumar Ramasubramanian, Sarma Namuduri, Scot McKinley, Seshan Parameswaran, Sharad Chandran R, Sherry LaMonica, Srinivas Pamu, Steve Ding, Sudarshan Soma, Sudeep Reguna, Sweta Mogra, Thanigai Nallathambi, Vikram Kumar, Yi Ouyang

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, MySQL, and NetSuite are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

Preface

Audi	ence		
Documentation Accessibility			
Dive	Diversity and Inclusion		
Conv	ention/	ns	
LIST	ener	r Control Utility	
1.1		ener Control Utility Overview	1
1.2		and SHOW Listener Control Utility Commands	2
1.3		erstanding Distributed Operations	2
1.4		erstanding Oracle Net Listener Security	3
1.5		ener Control Utility Commands	3
	L.5.1	EXIT	5
		HELP	5
		QUIT	6
		RELOAD	7
	L.5.5	_	8
	L.5.6	SERVICES	8
1	L.5.7		10
1	L.5.8	SET CURRENT_LISTENER	11
1	L.5.9	SET DISPLAYMODE	11
1	L.5.10	SET INBOUND_CONNECT_TIMEOUT	12
	L.5.11	-	13
1	L.5.12	_	13
1	L.5.13	_	14
1	L.5.14	SET SAVE_CONFIG_ON_STOP	15
1	L.5.15	SET TRC_DIRECTORY	16
1	L.5.16	SET TRC_FILE	16
1	L.5.17	SET TRC_LEVEL	17
1	L.5.18		18
1	L.5.19	SHOW STATS	19
	L.5.20		22
1	L.5.21	START	23

1.5.2	2 STATUS	25
1.5.2	3 STOP	26
1.5.2	4 TRACE	27
1.5.2	5 VERSION	28
Oracle	Connection Manager Control Utility	
2.1 Co	nnection Manager Control Utility Command Modes and Syntax	1
2.2 Ora	acle Connection Manager Control Utility Overview	2
2.3 Ora	acle Connection Manager Control Utility Commands	3
2.3.1		5
2.3.2		6
	CLOSE NON_ADMIN_ENDPOINTS	8
2.3.4		8
2.3.5	HELP	9
2.3.6	QUIT	10
2.3.7	RELOAD	10
2.3.8		11
2.3.9	SET	12
2.3.1		13
2.3.1	_	13
2.3.1	2 SET EVENT	14
2.3.1	3 SET IDLE_TIMEOUT	15
2.3.1	4 SET INBOUND_CONNECT_TIMEOUT	16
2.3.1	_	17
2.3.1	6 SET LOG_LEVEL	18
2.3.1	7 SET OUTBOUND_CONNECT_TIMEOUT	19
2.3.1	8 SET SESSION_TIMEOUT	19
2.3.1	9 SET TRACE_DIRECTORY	20
2.3.2	0 SET TRACE_LEVEL	21
2.3.2	1 SHOW	22
2.3.2	2 SHOW ALL	22
2.3.2	3 SHOW CONNECTIONS	24
2.3.2	4 SHOW DEFAULTS	27
2.3.2	5 SHOW EVENTS	28
2.3.2	6 SHOW GATEWAYS	28
2.3.2	7 SHOW PARAMETERS	29
2.3.2	8 SHOW RULES	30
2.3.2	9 SHOW SERVICES	32
2.3.3	0 SHOW STATS	33
2.3.3	1 SHOW STATUS	36
2.3.3	2 SHOW VERSION	37

	2.3.33 2.3.34	SHUTDOWN STARTUP	37 38
	2.3.35	SUSPEND GATEWAY	41
2	Syntay I	Rules for Configuration Files	
3			1
		view of Configuration File Syntax ax Rules for Configuration Files	1 2
	-	vork Character Set for Keywords	2
		nitted Listener and Net Service Name Character Set	3
4	Protoco	l Address Configuration	
	4.1 Proto	ocol Addresses	1
	4.1.1	ADDRESS	1
	4.1.2	ADDRESS_LIST	2
	4.2 Proto	ocol Parameters	2
	4.3 Reco	ommended Port Numbers	4
	4.4 Port	Number Limitations	4
5	Parame	ters for sqlnet.ora Files	
	5.1 Over	view of Profile Configuration Files	1
	5.2 Profil	le Parameters in sqlnet.ora Files	2
	5.2.1	ACCEPT_MD5_CERTS	11
	5.2.2	ACCEPT_SHA1_CERTS	11
	5.2.3	ALLOWED_WEAK_CERT_ALGORITHMS	12
	5.2.4	AZURE_DB_APP_ID_URI	13
	5.2.5	BEQUEATH_DETACH	14
	5.2.6	CLIENT_CERTIFICATE	15
	5.2.7	CLIENT_ID	16
	5.2.8	EXADIRECT_FLOW_CONTROL	18
	5.2.9	EXADIRECT_RECVPOLL	19
	5.2.10	DEFAULT_SDU_SIZE	19
	5.2.11	DISABLE_INTERRUPT	20
	5.2.12	DISABLE_OOB	20
	5.2.13	DISABLE_OOB_AUTO	21
	5.2.14	IPC.KEYPATH	21
	5.2.15	KERBEROS5_PRINCIPAL	22
	5.2.16	MAX_CONDUITS	23
	5.2.17	NAMES.DEFAULT_DOMAIN	24
	5.2.18	NAMES.DIRECTORY_PATH	24

5.2.19	NAMES.LDAP_AUTHENTICATE_BIND	25
5.2.20	NAMES.LDAP_AUTHENTICATE_BIND_METHOD	25
5.2.21	NAMES.LDAP_CONN_TIMEOUT	26
5.2.22	NAMES.LDAP_PERSISTENT_SESSION	26
5.2.23	NAMES.NIS.META_MAP	27
5.2.24	OCI_COMPARTMENT	27
5.2.25	OCI_CONFIG_FILE	29
5.2.26	OCI_DATABASE	31
5.2.27	OCI_IAM_URL	32
5.2.28	OCI_PROFILE	34
5.2.29	OCI_TENANCY	35
5.2.30	PASSWORD_AUTH	37
5.2.31	RECV_BUF_SIZE	41
5.2.32	REDIRECT_URI	41
5.2.33	SDP.PF_INET_SDP	43
5.2.34	SEC_USER_AUDIT_ACTION_BANNER	43
5.2.35	SEC_USER_UNAUTHORIZED_ACCESS_BANNER	44
5.2.36	SEND_BUF_SIZE	44
5.2.37	SEPS_WALLET_LOCATION	45
5.2.38	SQLNET.ALLOW_WEAK_CRYPTO	46
5.2.39	SQLNET.ALLOW_WEAK_CRYPTO_CLIENTS	47
5.2.40	SQLNET.ALLOWED_LOGON_VERSION_CLIENT	48
5.2.41	SQLNET.ALLOWED_LOGON_VERSION_SERVER	50
5.2.42	SQLNET.AUTHENTICATION_SERVICES	54
5.2.43	SQLNET.BREAK_RESET_TIMEOUT	56
5.2.44	SQLNET.CLIENT_REGISTRATION	56
5.2.45	SQLNET.CLOUD_USER	57
5.2.46	SQLNET.COMPRESSION	58
5.2.47	SQLNET.COMPRESSION_ACCELERATION	59
5.2.48	SQLNET.COMPRESSION_LEVELS	59
5.2.49	SQLNET.COMPRESSION_THRESHOLD	60
5.2.50	SQLNET.CRYPTO_CHECKSUM_CLIENT	60
5.2.51	SQLNET.CRYPTO_CHECKSUM_SERVER	61
5.2.52	SQLNET.CRYPTO_CHECKSUM_TYPES_CLIENT	61
5.2.53	SQLNET.CRYPTO_CHECKSUM_TYPES_SERVER	62
5.2.54	SQLNET.DBFW_PUBLIC_KEY	63
5.2.55	SQLNET.DOWN_HOSTS_TIMEOUT	63
5.2.56	SQLNET.ENCRYPTION_CLIENT	64
5.2.57	SQLNET.ENCRYPTION_SERVER	64
5.2.58	SQLNET.ENCRYPTION_TYPES_CLIENT	65
5.2.59	SQLNET.ENCRYPTION_TYPES_SERVER	66
5.2.60	SQLNET.EXPIRE_TIME	67

5.2.61	SQLNET.IGNORE_ANO_ENCRYPTION_FOR_TCPS	68
5.2.62	SQLNET.INBOUND_CONNECT_TIMEOUT	68
5.2.63	SQLNET.FALLBACK_AUTHENTICATION	69
5.2.64	SQLNET.KERBEROS5_CC_NAME	69
5.2.65	SQLNET.KERBEROS5_CLOCKSKEW	71
5.2.66	SQLNET.KERBEROS5_CONF	71
5.2.67	SQLNET.KERBEROS5_CONF_LOCATION	72
5.2.68	SQLNET.KERBEROS5_KEYTAB	73
5.2.69	SQLNET.KERBEROS5_REALMS	73
5.2.70	SQLNET.OUTBOUND_CONNECT_TIMEOUT	74
5.2.71	SQLNET.RADIUS_ALLOW_WEAK_CLIENTS	75
5.2.72	SQLNET.RADIUS_ALLOW_WEAK_PROTOCOL	76
5.2.73	SQLNET.RADIUS_ALTERNATE	77
5.2.74	SQLNET.RADIUS_ALTERNATE_PORT	78
5.2.75	SQLNET.RADIUS_ALTERNATE_RETRIES	79
5.2.76	SQLNET.RADIUS_ALTERNATE_TIMEOUT	79
5.2.77	SQLNET.RADIUS_ALTERNATE_TLS_HOST	79
5.2.78	SQLNET.RADIUS_ALTERNATE_TLS_PORT	80
5.2.79	SQLNET.RADIUS_AUTHENTICATION	81
5.2.80	SQLNET.RADIUS_AUTHENTICATION_INTERFACE	82
5.2.81	SQLNET.RADIUS_AUTHENTICATION_PORT	82
5.2.82	SQLNET.RADIUS_AUTHENTICATION_RETRIES	83
5.2.83	SQLNET.RADIUS_AUTHENTICATION_TIMEOUT	83
5.2.84	SQLNET.RADIUS_AUTHENTICATION_TLS_HOST	84
5.2.85	SQLNET.RADIUS_AUTHENTICATION_TLS_PORT	84
5.2.86	SQLNET.RADIUS_CHALLENGE_KEYWORD	85
5.2.87	SQLNET.RADIUS_CHALLENGE_RESPONSE	85
5.2.88	SQLNET.RADIUS_CLASSPATH	86
5.2.89	SQLNET.RADIUS_SECRET	86
5.2.90	SQLNET.RADIUS_SEND_ACCOUNTING	87
5.2.91	SQLNET.RADIUS_TRANSPORT_PROTOCOL	87
5.2.92	SQLNET.RECV_TIMEOUT	88
5.2.93	SQLNET.SEND_TIMEOUT	89
5.2.94	SQLNET.URI	90
5.2.95	SQLNET.USE_HTTPS_PROXY	90
5.2.96	SQLNET.WALLET_OVERRIDE	91
5.2.97	SSL_ALLOW_WEAK_DN_MATCH	92
5.2.98	SSL_CERTIFICATE_ALIAS	93
5.2.99	SSL_CERTIFICATE_THUMBPRINT	94
5.2.100	SSL_CERT_REVOCATION	96
5.2.101	SSL_CRL_FILE	97
5.2.102	SSL_CRL_PATH	97

5	5.2.103	SSL_CIPHER_SUITES	98
5	5.2.104	SSL_CLIENT_AUTHENTICATION	100
5	5.2.105	SSL_DISABLE_WEAK_EC_CURVES	101
5	5.2.106	SSL_ENABLE_WEAK_CIPHERS	102
5	5.2.107	SSL_EXTENDED_KEY_USAGE	103
5	5.2.108	SSL_SERVER_DN_MATCH	104
5	5.2.109	SSL_VERSION	105
5	5.2.110	TCP.ALLOWED_PROXIES	107
5	5.2.111	TCP.CONNECT_TIMEOUT	108
5	5.2.112	TCP.EXCLUDED_NODES	109
5	5.2.113	TCP.INVITED_NODES	109
5	5.2.114	TCP.NODELAY	110
5	5.2.115	TCP.QUEUESIZE	110
5	5.2.116	TCP.VALIDNODE_CHECKING	110
5	5.2.117	TENANT_ID	111
5	5.2.118	TNSPING.TRACE_DIRECTORY	113
5	5.2.119	TNSPING.TRACE_LEVEL	113
5	5.2.120	TOKEN_AUTH	114
5	5.2.121	TOKEN_LOCATION	132
5	5.2.122	TLS_KEY_EXCHANGE_GROUPS	135
5	5.2.123	USE_CMAN	137
5	5.2.124	USE_DEDICATED_SERVER	138
5	5.2.125	USE_SNI	139
5	5.2.126	WALLET_LOCATION	139
5.3	ADR D	piagnostic Parameters in sqlnet.ora	142
5	5.3.1 A	About ADR Diagnostic Parameters	143
5	5.3.2 A	ADR_BASE	143
5	5.3.3	DIAG_ADR_ENABLED	144
5	5.3.4 E	ENABLE_CONCISE_LOGS	144
5	5.3.5 L	LOG_SUPPRESSED_COUNT	145
5	5.3.6 L	LOG_SUPPRESSED_TIME	146
5	5.3.7	FRACE_LEVEL_CLIENT	147
5	5.3.8	FRACE_LEVEL_SERVER	148
5	5.3.9	FRACE_TIMESTAMP_CLIENT	148
5	5.3.10	TRACE_TIMESTAMP_SERVER	149
5.4	Non-A	DR Diagnostic Parameters in sqlnet.ora Files	149
5	5.4.1 L	LOG_DIRECTORY_CLIENT	150
5	5.4.2 L	LOG_DIRECTORY_SERVER	151
5	5.4.3 L	LOG_FILE_CLIENT	151
5	5.4.4 L	LOG_FILE_SERVER	152
5	5.4.5	FRACE_DIRECTORY_CLIENT	152
5	5.4.6	TRACE DIRECTORY SERVER	152

	5.4.7	TRACE_FILE_CLIENT	153
	5.4.8	TRACE_FILE_SERVER	153
	5.4.9	TRACE_FILEAGE_CLIENT	154
	5.4.10	TRACE_FILEAGE_SERVER	154
	5.4.11	TRACE_FILELEN_CLIENT	155
	5.4.12	TRACE_FILELEN_SERVER	155
	5.4.13	TRACE_FILENO_CLIENT	155
	5.4.14	TRACE_FILENO_SERVER	156
	5.4.15	TRACE_UNIQUE_CLIENT	157
ŝ	Local N	aming Parameters in the tnsnames.ora File	
	6.1 Over	rview of Local Naming Parameters	2
	6.2 Gen	eral Syntax of tnsnames.ora	3
	6.3 Usin	g Multiple Descriptions in tnsnames.ora Files	3
	6.4 Multi	iple Address Lists in tnsnames.ora Files	3
	6.5 Con	nect-Time Failover and Client Load Balancing with Oracle Connection Managers	4
	6.6 Con	nect Descriptor Descriptions	6
	6.6.1	DESCRIPTION_LIST	6
	6.6.2	DESCRIPTION	6
	6.7 Proto	ocol Addresses	7
	6.7.1	ADDRESS	7
	6.7.2	HTTPS_PROXY	7
	6.7.3	HTTPS_PROXY_PORT	8
	6.7.4	ADDRESS_LIST	9
	6.8 Option	onal Parameters for Description	9
	6.8.1	ENABLE	10
	6.8.2	EXPIRE_TIME	10
	6.8.3	FAILOVER	11
	6.8.4	LOAD_BALANCE	12
	6.8.5	RECV_BUF_SIZE	13
	6.8.6	SDU	14
	6.8.7	SEND_BUF_SIZE	14
	6.8.8	SOURCE_ROUTE	15
	6.8.9	TYPE_OF_SERVICE	16
	6.8.10	USE_SNI	17
	6.9 Con	nection Data Section	17
	6.9.1	CONNECT_DATA	19
	6.9.2	COLOCATION_TAG	19
	6.9.3	CONNECTION_ID_PREFIX	20
	6.9.4	FAILOVER_MODE	20
	6.9.5	GLOBAL_NAME	21

6.9.6	HS	22
6.9.7	INSTANCE_NAME	22
6.9.8	POOL_BOUNDARY	23
6.9.9	POOL_CONNECTION_CLASS	25
6.9.10	POOL_NAME	26
6.9.11	POOL_PURITY	27
6.9.12	RDB_DATABASE	27
6.9.13	SHARDING_KEY	28
6.9.14	SHARDING_KEY_ID	30
6.9.15	SUPER_SHARDING_KEY	31
6.9.16	SERVER	33
6.9.17	SERVICE_NAME	33
6.9.18	TUNNEL_SERVICE_NAME	34
6.10 Sec	urity Section	34
6.10.1	AUTHENTICATION_SERVICE	36
6.10.2	AZURE_DB_APP_ID_URI	38
6.10.3	CLIENT_CERTIFICATE	40
6.10.4	CLIENT_ID	42
6.10.5	IGNORE_ANO_ENCRYPTION_FOR_TCPS	44
6.10.6	KERBEROS5_CC_NAME	44
6.10.7	KERBEROS5_PRINCIPAL	45
6.10.8	OCI_COMPARTMENT	47
6.10.9	OCI_CONFIG_FILE	49
6.10.10	OCI_DATABASE	50
6.10.11	OCI_IAM_URL	52
6.10.12	OCI_PROFILE	54
6.10.13	B OCI_TENANCY	55
6.10.14	PASSWORD_AUTH	56
6.10.15	REDIRECT_URI	60
6.10.16	S SECURITY	61
6.10.17	SEPS_WALLET_LOCATION	62
6.10.18	S SSL_CERTIFICATE_ALIAS	63
6.10.19	SSL_CERTIFICATE_THUMBPRINT	64
6.10.20	SSL_CLIENT_AUTHENTICATION	65
6.10.21	. SSL_DISABLE_WEAK_EC_CURVES	66
6.10.22	SSL_SERVER_CERT_DN	68
6.10.23	S SSL_SERVER_DN_MATCH	69
6.10.24	SSL_VERSION	71
6.10.25	5 TENANT_ID	72
6.10.26	TOKEN_AUTH	74
6.10.27	TOKEN_LOCATION	92
6.10.28	TLS KEY EXCHANGE GROUPS	95

6.10.29	WALLET_LOCATION	97
6.11 Time	eout Parameters	99
6.11.1	CONNECT_TIMEOUT	99
6.11.2	RETRY_COUNT	100
6.11.3	RETRY_DELAY	101
6.11.4	TRANSPORT_CONNECT_TIMEOUT	102
6.11.5	RECV_TIMEOUT	102
6.12 Con	npression Parameters	103
6.12.1	COMPRESSION	104
6.12.2	COMPRESSION_LEVELS	104
Centraliz	zed Configuration Provider Naming Parameters	
	view of Centralized Configuration Provider Naming Parameters	1
	ved Parameter Names and Values in Connect Descriptors	2
7.2.1	Naming-Restricted Parameter Names	2
7.2.2	Naming-Restricted Parameter Values	4
	entication Parameters for Azure App Configuration Store	5
7.3.1	AUTHENTICATION	5
	AZURE_CLIENT_ID	7
	AZURE_TENANT_ID	8
	AZURE_CLIENT_SECRET	9
	AZURE_CLIENT_CERTIFICATE_PATH	9
7.3.6	AZURE_MANAGED_IDENTITY_CLIENT_ID	10
7.3.7	HTTPS_PROXY	11
7.3.8	HTTPS_PROXY_PORT	11
7.3.9	TIMEOUT	12
7.4 Author	entication Parameters for OCI Object Storage	12
7.4.1	AUTHENTICATION	13
7.4.2	OCI_PROFILE	14
7.4.3	OCI_PROFILE_PATH	15
7.4.4	OCI_TENANCY	16
7.4.5	OCI_USER	16
7.4.6	OCI_KEY_FILE	17
7.4.7	OCI_FINGERPRINT	18
7.4.8	HTTPS_PROXY	18
7.4.9	HTTPS_PROXY_PORT	19
7.4.10	TIMEOUT	19
Oracle N	Net Listener Parameters in the listener.ora File	
8.1 Over	view of Oracle Net Listener Configuration File	1

8.2	Proto	ocol Address Parameters	2
	8.2.1	ADDRESS	3
	8.2.2	DESCRIPTION	3
	8.2.3	Firewall	4
	8.2.4	IP	4
	8.2.5	QUEUESIZE	4
	8.2.6	RECV_BUF_SIZE	5
	8.2.7	SEND_BUF_SIZE	6
8.3	Conr	nection Rate Limiter Parameters	7
	8.3.1	CONNECTION_RATE_listener_name	7
	8.3.2	RATE_LIMIT	7
8.4	Cont	rol Parameters	8
	8.4.1	ADMIN_RESTRICTIONS_listener_name	10
	8.4.2	ALLOW_MULTIPLE_REDIRECTS_listener_name	11
	8.4.3	CRS_NOTIFICATION_listener_name	11
	8.4.4	DEDICATED_THROUGH_BROKER_LISTENER	12
	8.4.5	DEFAULT_SERVICE_listener_name	12
	8.4.6	ENABLE_EXADIRECT_listener_name	13
	8.4.7	INBOUND_CONNECT_TIMEOUT_listener_name	13
	8.4.8	LOCAL_REGISTRATION_ADDRESS_listener_name	14
	8.4.9	MAX_ALL_CONNECTIONS_listener_name	14
	8.4.10	MAX_REG_CONNECTIONS_listener_name	15
	8.4.11	REGISTRATION_EXCLUDED_NODES_listener_name	15
	8.4.12	REGISTRATION_INVITED_NODES_listener_name	15
	8.4.13	REMOTE_REGISTRATION_ADDRESS_listener_name	16
	8.4.14	SAVE_CONFIG_ON_STOP_listener_name	17
	8.4.15	SERVICE_RATE_listener_name	17
	8.4.16	SSL_CIPHER_SUITES	18
	8.4.17	SSL_CLIENT_AUTHENTICATION	19
	8.4.18	SSL_DISABLE_WEAK_EC_CURVES	20
	8.4.19	SSL_VERSION	22
	8.4.20	SUBSCRIBE_FOR_NODE_DOWN_EVENT_listener_name	23
	8.4.21	TLS_KEY_EXCHANGE_GROUPS	24
	8.4.22	USE_SID_AS_SERVICE_listener_name	26
	8.4.23	USE_SNI_listener_name	26
	8.4.24	VALID_NODE_CHECKING_REGISTRATION_listener_name	27
	8.4.25	WALLET_LOCATION	28
8.5	ADR	Diagnostic Parameters for Oracle Net Listener	29
	8.5.1	ADR_BASE_listener_name	30
	8.5.2	DIAG_ADR_ENABLED_listener_name	31
	8.5.3	LOG_FILE_NUM_listener_name	31
	854	LOG FILE SIZE listener name	32

8.5.5	LOGGING_listener_name	32
8.5.6	TRACE_LEVEL_listener_name	32
8.5.7	TRACE_TIMESTAMP_listener_name	33
8.6 Non-	-ADR Diagnostic Parameters for Oracle Net Listener	33
8.6.1	LOG_DIRECTORY_listener_name	34
8.6.2	LOG_FILE_listener_name	34
8.6.3	TRACE_DIRECTORY_listener_name	34
8.6.4	TRACE_FILE_listener_name	35
8.6.5	TRACE_FILEAGE_listener_name	35
8.6.6	TRACE_FILELEN_listener_name	35
8.6.7	TRACE_FILENO_listener_name	36
8.7 Class	s of Secure Transports Parameters	36
8.7.1	SECURE_REGISTER_listener_name	37
8.7.2	Using COST Parameters in Combination	37
8.7.3	DYNAMIC_REGISTRATION_listener_name	38
8.7.4	SECURE_PROTOCOL_listener_name	38
8.7.5	SECURE_CONTROL_listener_name	39
	rview of Oracle Connection Manager Configuration File	1
	cle Connection Manager Parameters	3
9.2.1	ADDRESS	6
9.2.2	ADMIN_GROUP	7
9.2.3	ASO_AUTHENTICATION_FILTER	8
9.2.4	BANDWIDTH	8
9.2.5	CLIENT_DN_RULE_MATCH	9
9.2.6	COMPRESSION	9
	COMPRESSION_LEVELS	10
9.2.8	COMPRESSION_THRESHOLD	10
9.2.9	CONNECTION_STATISTICS	10
9.2.10	-	11
9.2.11		11
9.2.12	_	12
9.2.13 9.2.14	_	13
		14
9.2.15 9.2.16	_	15
9.2.16		15 15
9.2.17		16
9.2.10		17
9.2.19		18
5.2.20		10

	9.2.21	LOG_FILE_SIZE	18
	9.2.22	LOG_SUPPRESS_NODES	19
	9.2.23	MAX_ALL_CONNECTIONS	19
	9.2.24	MAX_CMCTL_SESSIONS	20
	9.2.25	MAX_BANDWIDTH_GROUP	20
	9.2.26	MAX_CONNECTIONS	21
	9.2.27	MAX_GATEWAY_PROCESSES	21
	9.2.28	MAX_REG_CONNECTIONS	22
	9.2.29	MIN_GATEWAY_PROCESSES	22
	9.2.30	NEXT_HOP	22
	9.2.31	OUTBOUND_CONNECT_TIMEOUT	23
	9.2.32	REGISTRATION_EXCLUDED_NODES	24
	9.2.33	REGISTRATION_INVITED_NODES	24
	9.2.34	REST_ADDRESS	25
	9.2.35	RULE	25
	9.2.36	SDU	27
	9.2.37	SERVICE_RATE	27
	9.2.38	SESSION_TIMEOUT	28
	9.2.39	SSL_CIPHER_SUITES	28
	9.2.40	SSL_CLIENT_AUTHENTICATION	30
	9.2.41	SSL_VERSION	31
	9.2.42	TRACE_FILE	33
	9.2.43	USE_SERVICE_AS_TNSNAMES_ALIAS	33
	9.2.44	USE_SID_AS_SERVICE	34
	9.2.45	USE_SNI	34
	9.2.46	VALID_NODE_CHECKING_REGISTRATION	35
	9.2.47	WALLET_LOCATION	36
9.3	Orac	le Connection Manager in Traffic Director Mode Parameters	38
	9.3.1	SERVICE_AFFINITY	38
	9.3.2	TDM	39
	9.3.3	TDM_BIND_THREAD	39
	9.3.4	TDM_DATATYPE_CHECK	40
	9.3.5	TDM_PERPDB_PRCP_CONNFACTOR	40
	9.3.6	TDM_PRCP_MAX_CALL_WAIT_TIME	42
	9.3.7	TDM_PRCP_MAX_TXN_CALL_WAIT_TIME	42
	9.3.8	TDM_SHARED_THREADS_MAX	43
	9.3.9	TDM_SHARED_THREADS_MIN	43
		TDM_STATS_FREQUENCY	43
_	9.3.11		44
9.4		Diagnostic Parameters for Oracle Connection Manager	44
	9.4.1	ADR_BASE	45
	942	DIAG ADR ENABLED	45

	9.4.3	LOG_LEVEL	46		
	9.4.4	TRACE_LEVEL	46		
	9.4.5	TRACE_TIMESTAMP	47		
	9.5 Non	n-ADR Diagnostic Parameters for Oracle Connection Manager	47		
	9.5.1	LOG_DIRECTORY	47		
	9.5.2	TRACE_DIRECTORY	48		
	9.5.3	TRACE_FILELEN	48		
	9.5.4	TRACE_FILENO	49		
	9.6 Ora	cle Connection Manager Tunneling Parameters	49		
	9.6.1	TUNNELING	50		
	9.6.2	TUNNEL_CAPACITY	50		
	9.6.3	MAX_TUNNELS	51		
	9.6.4	TUNNEL_PROBE_INTERVAL	51		
	9.6.5	NON_TUNNEL_GATEWAYS	51		
	9.6.6	TUNNEL_ADDRESS	52		
	9.6.7	GATEWAY_PROCESSES	52		
10	Directory Usage Parameters in the Idap.ora File				
	10.1 Ov	verview of Directory Server Usage File	1		
	10.2 Dir	rectory Usage Parameters	1		
	10.2.1	DEFAULT_ADMIN_CONTEXT	2		
	10.2.2	2 DIRECTORY_SERVER_TYPE	2		
	10.2.3	B DIRECTORY_SERVERS	2		
11	LDAP Parameters in the Connect Identifier				
	11.1 Ab	out Using LDAP Parameters in the Connect Identifier	1		
	11.2 All	owed Parameters in the Connect Identifier	1		
	11.2.1	Protocol-Specific Parameters	2		
	11.2.2	2 AUTHENTICATE_BIND	2		
	11.2.3	B AUTHENTICATE_BIND_METHOD	3		
	11.2.4	DIRECTORY_SERVER_TYPE	4		
	11.2.5	WALLET_LOCATION	4		
Α	Upgrad	Upgrade Considerations for Oracle Net Services			
	A.1 And	onymous Access to Oracle Internet Directory	A-1		
В	LDAP Schema for Oracle Net Services				
	B.1 Stru	uctural Object Classes	B-1		

B.2 Attributes B-2

Configuring OpenLDAP Server to Use Oracle Net Naming Directory



Preface

Review this publication to obtain a complete listing and description of control utility commands and configuration file parameters that you can use to manage Oracle Net Services components.

- Audience
- Documentation Accessibility
- Diversity and Inclusion
- Conventions

Audience

Oracle Database Net Services Reference is intended for network administrators who are responsible for configuring and administering network components.

To use this document, you should be familiar with the networking concepts and configuration tasks described in *Oracle Database Net Services Administrator's Guide*.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

Access to Oracle Support

Oracle customer access to and use of Oracle support services will be pursuant to the terms and conditions specified in their Oracle order for the applicable services.

Diversity and Inclusion

Oracle is fully committed to diversity and inclusion. Oracle respects and values having a diverse workforce that increases thought leadership and innovation. As part of our initiative to build a more inclusive culture that positively impacts our employees, customers, and partners, we are working to remove insensitive terms from our products and documentation. We are also mindful of the necessity to maintain compatibility with our customers' existing technologies and the need to ensure continuity of service as Oracle's offerings and industry standards evolve. Because of these technical constraints, our effort to remove insensitive terms is ongoing and will take time and external cooperation.

Conventions

The following text conventions are used in this document:



Convention	Meaning	
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.	
italic	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.	
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.	

Listener Control Utility

This chapter describes the Listener Control Utility commands and syntax. The terms **SQL*Net** and **Net Services** are used interchangeably throughout Oracle documentation.

Listener Control Utility Overview

To perform basic management functions on one or more listeners, you can use the Listener Control utility commands. You can also use these commands to view and change parameter settings.

SET and SHOW Listener Control Utility Commands

The \mathtt{SET} and \mathtt{SHOW} commands enable you to alter and view listener configuration parameters.

Understanding Distributed Operations

Listener Control utility can perform operations on local or remote listeners.

Understanding Oracle Net Listener Security

Authentication for listener administration depends on whether you access the listener locally or remotely.

<u>Listener Control Utility Commands</u>

Use Listener Control Utility commands to manage and configure your listeners.

1.1 Listener Control Utility Overview

To perform basic management functions on one or more listeners, you can use the Listener Control utility commands. You can also use these commands to view and change parameter settings.

The Listener Control utility enables you to administer listeners. The syntax of Listener Control utility commands is as follows:

```
lsnrctl command listener_name
```

In the preceding command, <code>listener_name</code> is the name of the listener that you want to administer. If you do not specify a specific listener in the command string, then the command is directed to the default listener name, <code>LISTENER</code>.

You can also issue Listener Control utility commands at the LSNRCTL> program prompt. To obtain the prompt, enter lsnrctl with no arguments at the operating system command line. When you run lsnrctl, the program is started. You can then enter the commands from the program prompt. The basic syntax of issuing commands from LSNRCTL> program prompt is:

```
lsnrctl
LSNRCTL> command listener_name
```

You can combine commands in a standard text file and then run them as a sequence of commands. To run in batch mode, use this format:

```
lsnrctl @file_name
```



To identify comments in the batch script, you can use either REM or #. All other lines are considered commands. Commands that require confirmation do not require confirmation during batch processing.

For most commands, Listener Control utility establishes an Oracle Net connection with the listener that transmits the command. To initiate an Oracle Net connection to the listener, Listener Control utility must obtain the protocol addresses for the named listener or a listener named LISTENER. This is done by resolving the listener name with one of the following:

- listener.ora file in the directory specified by the TNS_ADMIN environment variable.
- listener.ora file in the ORACLE_HOME/network/admin directory.
- Naming method; for example, a tnsnames.ora file.

If none of the preceding mechanisms resolve the listener name, then Listener Control utility uses the default listener name LISTENER, resolves the host name IP address, and uses port 1521.

The Listener Control utility supports the following types of commands:

- Operational commands, such as START, and STOP.
- Modifier commands, such as SET TRC LEVEL.
- Informational commands, such as STATUS, and SHOW LOG FILE.

1.2 SET and SHOW Listener Control Utility Commands

The SET and SHOW commands enable you to alter and view listener configuration parameters.

Use the SET command to alter parameter values for a specified listener. You set the name of the listener to administer using the SET CURRENT_LISTENER command. Parameter values remain in effect until the listener is shut down. If you want these settings to persist, then use the SAVE_CONFIG command to save changes to the listener.ora file.

You can use the SHOW command to display the current value of a configuration setting.

1.3 Understanding Distributed Operations

Listener Control utility can perform operations on local or remote listeners.

This example explains how to configure listeners for remote administration.

Set Up a Computer to Remotely Administer a Listener

Ensure that the Listener Control utility (lsnrctl) executable is installed in the ORACLE_HOME/bin directory. You can resolve the name of the listener that you want to administer either through a listener.ora file, or by a naming method.

When you administer a listener remotely, you can issue all of the commands except START. However, Listener Control utility only starts the listener on the same computer from which the utility runs.

When issuing commands, specify the listener name as an argument. If you omit the listener name in the command, then the listener name set with the command SET CURRENT_LISTENER is used. If you do not set the listener name with that command, then the command is directed to the default listener name, LISTENER.



Example 1-1 Issuing Commands Using the Listener Control Utility

LSNRCTL> SERVICES lsnr

1.4 Understanding Oracle Net Listener Security

Authentication for listener administration depends on whether you access the listener locally or remotely.

Local listener administration security is administered using local operating system authentication. Local authentication restricts listener administration to the user account that started the listener or to the super user. By default, remote listener administration is disabled.

Oracle recommends that you perform listener administration in the default mode and that you access the system remotely using a remote login. When you administer the listener remotely, use either Oracle Enterprise Manager Cloud Control or Secure Shell (SSH) to access the remote host.

1.5 Listener Control Utility Commands

Use Listener Control Utility commands to manage and configure your listeners.

EXIT

Use the Listener Control utility command EXIT to exit from the Listener Control utility and return to the operating system prompt.

HELP

Use the Listener Control utility command HELP to list the Listener Control utility commands and to obtain syntax help for particular Listener Control utility commands.

QUIT

Use the Listener Control utility command QUIT to exit from the Listener Control utility and return to the operating system prompt.

RELOAD

Use the Listener Control utility command RELOAD to reload the listener.ora file so that you can add or change statically configured services without stopping the listener.

SAVE CONFIG

Use the Listener Control utility command SAVE_CONFIG to save the current configuration state of the listener to the listener.ora file.

SERVICES

Use the Listener Control utility command SERVICES to return details about database services, instances, and service handlers to which listeners forward client connection requests.

SET

Use the Listener Control utility command SET to alter listener parameter values.

• SET CURRENT LISTENER

Use the Listener Control utility command SET CURRENT_LISTENER to set the name of the listener to administer.

SET DISPLAYMODE

Use the Listener Control utility command SET DISPLAYMODE to change the format and detail level for the SERVICES and STATUS commands.



SET INBOUND CONNECT TIMEOUT

Use the Listener Control utility command SET INBOUND_CONNECT_TIMEOUT to specify the duration in which clients must complete connection requests to listeners after establishing network connections.

SET LOG DIRECTORY

Use the Listener Control utility command SET LOG_DIRECTORY to set the destination directory to which the listener log file is written.

SET LOG FILE

Use the Listener Control utility command SET LOG_FILE to set the listener log file name.

SET LOG STATUS

Use the Listener Control utility command SET LOG STATUS to turn listener logging on or off.

SET SAVE CONFIG ON STOP

Use the Listener Control utility command SET SAVE_CONFIG_ON_STOP to specify whether listener parameter value changes that you make with the SET command are saved to the listener.ora file when you stop the listener with the STOP command.

• <u>SET TRC DIRECTORY</u>

Use the Listener Control utility command SET TRC_DIRECTORY to set the destination directory into which Oracle writes listener trace files.

SET TRC FILE

Use the Listener Control utility command \mathtt{SET} $\mathtt{TRC_FILE}$ to set the names of listener trace files.

SET TRC LEVEL

Use the Listener Control utility command \mathtt{SET} $\mathtt{TRC_LEVEL}$ to set a specific listener tracing level.

SHOW

Use the Listener Control utility command SHOW to list current listener parameter values.

SHOW STATS

Use the Listener Control utility \mathtt{SHOW} STATS command with the -REG option to display statistics about database service registration commands.

SPAWN

Use the Listener Control utility command SPAWN to start a program that is stored on the computer on which the listener is running and that is listed with an alias in the listener.ora file.

START

Use the Listener Control utility command START to start a named listener.

STATUS

Use the Listener Control utility command STATUS to show listener status information.

STOP

Use the Listener Control utility command STOP to stop the named listener.

TRACE

Use the Listener Control utility command TRACE to set listener tracing.

VERSION

Use the Listener Control utility command VERSION to show the current version of Listener Control utility.



1.5.1 EXIT

Use the Listener Control utility command EXIT to exit from the Listener Control utility and return to the operating system prompt.

Purpose

To exit from the Listener Control utility and return to the operating system prompt.

Prerequisites

None

Syntax

From the Listener Control utility:

LSNRCTL> EXIT

Arguments

None

Usage Notes

This command is identical to the QUIT command.

Example

LSNRCTL> EXIT

1.5.2 HELP

Use the Listener Control utility command HELP to list the Listener Control utility commands and to obtain syntax help for particular Listener Control utility commands.

Purpose

To provide a list of the Listener Control utility commands or to provide syntax help for a particular Listener Control utility command.

Prerequisites

None

Syntax

From the operating system:

lsnrctl HELP command

From the Listener Control utility:

LSNRCTL> HELP command



Arguments

command: The Listener Control utility command. Commands are shown in the following example output.

When you enter a command as an argument to \mathtt{HELP} , the Listener Control utility displays information about how to use the command. When you enter \mathtt{HELP} without an argument, the Listener Control utility lists all the commands.

Example

```
LSNRCTL> HELP
The following operations are available
An asterisk (*) denotes a modifier or extended command:
exit
quit
reload
services
set*
show*
spawn
start
status
stop
trace
version
```

1.5.3 QUIT

Use the Listener Control utility command QUIT to exit from the Listener Control utility and return to the operating system prompt.

Purpose

To exit from the Listener Control utility and return to the operating system prompt.

Prerequisites

None

Syntax

From the Listener Control utility:

LSNRCTL> QUIT

Arguments

None

Usage Notes

This command is identical to the EXIT command.



Example

LSNRCTL> QUIT

1.5.4 RELOAD

Use the Listener Control utility command RELOAD to reload the listener.ora file so that you can add or change statically configured services without stopping the listener.

Purpose

To reload the listener.ora file. This command enables you to add or change statically configured services without actually stopping the listener.

When you run this command, the database services, instances, service handlers, and listening endpoints previously registered dynamically with the listener are unregistered, and subsequently registered again.

To obtain a lightweight reload without dropping registration, use the option <code>-with_ha</code>. Using this option ensures that registered services remain available to clients during reload.

Prerequisites

None

Syntax

From the operating system:

```
lsnrctl RELOAD [-with_ha] listener_name
```

From the Listener Control utility:

```
LSNRCTL> RELOAD [-with_ha] listener_name
```

Arguments

listener_name: The listener name, if the default name of LISTENER is not used.

-with_ha: command option used with RELOAD that indicates that the reload of listener.ora is completed without dropping existing registrations.

Example

```
LSNRCTL> RELOAD

Connecting to (DESCRIPTION=(ADDRESS=(PROTOCOL=TCP)(HOST=sales-server)
(PORT=1521)))

The command completed successfully
```



1.5.5 SAVE_CONFIG

Use the Listener Control utility command SAVE_CONFIG to save the current configuration state of the listener to the listener.ora file.

Purpose

To save the current configuration state of the listener, including trace level, trace file, trace directory, and logging to the listener.ora file. Any changes are stored in listener.ora, preserving formatting, comments, and case as much as possible. Before modification of the listener.ora file, a backup of the file, called listener.bak, is created.

Syntax

From the operating system:

```
lsnrctl SAVE_CONFIG listener_name
```

From the Listener Control utility:

```
LSNRCTL> SAVE_CONFIG listener_name
```

Arguments

listener name: The listener name, if the default name of LISTENER is not used.

Usage Notes

This command enables you to save all run-time configuration changes to the listener.ora file.

Example

```
LSNRCTL> SAVE_CONFIG listener

Connecting to (DESCRIPTION=(ADDRESS=(PROTOCOL=TCP)(HOST=sales-server)
(PORT=1521)))

Saved LISTENER configuration parameters.

Listener Parameter File /oracle/network/admin/listener.ora
Old Parameter File /oracle/network/admin/listener.bak
The command completed successfully
```

1.5.6 SERVICES

Use the Listener Control utility command SERVICES to return details about database services, instances, and service handlers to which listeners forward client connection requests.

Purpose

To obtain detailed information about the database services, instances, and service handlers (dispatchers and dedicated servers) to which the listener forwards client connection requests.

Prerequisites

None



Syntax

Arguments

From the operating system:

```
lsnrctl SERVICES listener_name
```

From the Listener Control utility:

```
LSNRCTL> SERVICES listener_name
```

listener_name: The listener name, if the default name of LISTENER is not used.

Usage Notes

The SET DISPLAYMODE command changes the format and the detail level of the output.



Oracle Al Database Net Services Administrator's Guide for a complete description of SERVICES output

Example

This example shows SERVICES output in the default display mode. The output shows the following:

- An instance named sales belonging to two services, sales1.us.example.com and sales2.us.example.com, with a total of three service handlers.
- Service sales1.us.example.com is handled by one dispatcher only.
- Service sales2.us.example.com is handled by one dispatcher and one dedicated server, as specified in the following.

```
LSNRCTL> SERVICES
Connecting to (DESCRIPTION=(ADDRESS=(PROTOCOL=ipc)(KEY=net)))
Services Summary...
Service "sales1.us.example.com" has 1 instance(s).
  Instance "sales", status READY, has 1 handler(s) for this service...
    Handler(s):
      "D000" established:0 refused:0 current:0 max:10000 state:ready
         DISPATCHER <machine: sales-server, pid: 5696>
         (ADDRESS=(PROTOCOL=tcp)(HOST=sales-server)(PORT=53411))
Service "sales2.us.example.com" has 1 instance(s).
  Instance "sales", status READY, has 2 handler(s) for this service...
    Handler(s):
      "DEDICATED" established:0 refused:0 state:ready
         LOCAL SERVER
      "D001" established:0 refused:0 current:0 max:10000 state:ready
         DISPATCHER <machine: sales-server, pid: 5698>
```



(ADDRESS=(PROTOCOL=tcp)(HOST=sales-server)(PORT=52618))
The command completed successfully

1.5.7 SET

Use the Listener Control utility command SET to alter listener parameter values.

Purpose

To alter the parameter values for the listener. Parameter value changes remain in effect until the listener is shut down. To make changes permanent, use the SAVE_CONFIG command to save changes to the listener.ora file.

Prerequisites

None

Syntax

From the operating system:

lsnrctl SET parameter

From the Listener Control utility:

LSNRCTL> SET parameter

Arguments

parameter: A SET parameter to modify its configuration setting. Parameters are shown in the example output.

When you enter SET without an argument, the Listener Control utility lists all of the parameters.

Usage Notes

If you are using the SET commands to alter the configuration of a listener other than the default LISTENER listener, then use the SET CURRENT_LISTENER command to set the name of the listener to administer.

Example

LSNRCTL> SET
The following operations are available with set.
An asterisk (*) denotes a modifier or extended command.
current_listener
displaymode
inbound_connect_timeout
log_file
log_directory
log_status
rawmode
save_config_on_stop
trc_file



trc_directory
trc level

1.5.8 SET CURRENT_LISTENER

Use the Listener Control utility command SET CURRENT_LISTENER to set the name of the listener to administer.

Purpose

To set the name of the listener that you want to administer. After you set the listener name with this command, you can issue subsequent commands that normally require <code>listener_name</code> without specifying the listener.

Syntax

From the Listener Control utility:

LSNRCTL> SET CURRENT_LISTENER listener_name

Arguments

listener_name: The listener name, if you are not using the default name LISTENER.

Usage Notes

When you specify a listener name using SET CURRENT_LISTENER, the Listener Control utility commands act on the listener name that you specify with this command. You do not have to continue to specify the name of the listener.

Example

LSNRCTL> SET CURRENT_LISTENER lsnr Current Listener is lsnr

1.5.9 SET DISPLAYMODE

Use the Listener Control utility command SET DISPLAYMODE to change the format and detail level for the SERVICES and STATUS commands.

Purpose

To change the format and level of detail for the SERVICES and STATUS commands.

Syntax

From the Listener Control utility:

LSNRCTL> SET DISPLAYMODE {compat | normal | verbose | raw}

Arguments

Specify one of the following modes:

compat: Output that is compatible with earlier releases of the listener.



normal: Output that is formatted and descriptive. Oracle recommends this mode.

verbose: All data received from the listener in a formatted and descriptive output.

raw: All data received from the listener without any formatting. This argument should be used only if recommended by Oracle Support Services.

Example

LSNRCTL> SET DISPLAYMODE normal Service display mode is NORMAL

1.5.10 SET INBOUND_CONNECT_TIMEOUT

Use the Listener Control utility command SET INBOUND_CONNECT_TIMEOUT to specify the duration in which clients must complete connection requests to listeners after establishing network connections.

Purpose

To specify the time, in seconds, for the client to complete its connect request to the listener after establishing the network connection.

If the listener does not receive the client request in the time specified, then it terminates the connection. In addition, the listener logs the IP address of the client and an ORA-12525: TNS: listener has not received client's request in time allowed error message to the listener.log file.



(i) See Also

Oracle AI Database Net Services Administrator's Guide for additional information about specifying the time out for client connections

Syntax

From the Listener Control utility:

LSNRCTL> SET INBOUND_CONNECT_TIMEOUT time

Arguments

time: The duration of time in seconds. Default setting is 60 seconds.

Example

LSNRCTL> SET INBOUND_CONNECT_TIMEOUT 2 Connecting to (ADDRESS=(PROTOCOL=TCP)(HOST=sales-server)(PORT=1521)) LISTENER parameter "inbound_connect_timeout" set to 2 The command completed successfully.



1.5.11 SET LOG_DIRECTORY

Use the Listener Control utility command SET LOG_DIRECTORY to set the destination directory to which the listener log file is written.

Purpose

To set the destination directory to which the listener log file is written. By default, the log file is written to the ORACLE_HOME/network/log directory.



(i) Note

This command works only if Automatic Diagnostic Repository (ADR) is disabled. The default is for ADR to be enabled and to use the log directory ORACLE_HOME/log/ diag/product_type.

Prerequisites

None

Syntax

From the operating system:

lsnrctl SET LOG_DIRECTORY directory

From the Listener Control utility:

LSNRCTL> SET LOG_DIRECTORY directory

Arguments

directory: The directory path of the listener log file.

Example

LSNRCTL> SET LOG_DIRECTORY /usr/oracle/admin Connecting to (ADDRESS=(PROTOCOL=TCP)(HOST=sales-server)(PORT=1521)) LISTENER parameter "log_directory" set to /usr/oracle/admin The command completed successfully

1.5.12 SET LOG_FILE

Use the Listener Control utility command SET LOG_FILE to set the listener log file name.

Purpose

To set the name for the listener log file. By default, the log file name is listener.log.





(i) Note

This command works only if Automatic Diagnostic Repository (ADR) is disabled. The default is for ADR to be enabled and to use the log directory <code>ORACLE_HOME/log/</code> diag/product_type.

Prerequisites

None

Syntax

From the operating system:

```
lsnrctl SET LOG_FILE file_name
```

From the Listener Control utility:

```
LSNRCTL> SET LOG_FILE file_name
```

Arguments

file_name: The file name of the listener log.

Example

```
LSNRCTL> SET LOG_FILE list.log
Connecting to (ADDRESS=(PROTOCOL=TCP)(HOST=sales-server)(PORT=1521))
LISTENER parameter "log_file" set to list.log
The command completed successfully
```

1.5.13 SET LOG_STATUS

Use the Listener Control utility command SET LOG STATUS to turn listener logging on or off.

Purpose

To turn listener logging on or off.

Prerequisites

None

Syntax

From the operating system:

```
lsnrctl SET LOG_STATUS {on | off}
```

From the Listener Control utility:

LSNRCTL> SET LOG_STATUS {on | off}



Arguments

on: To turn logging on.
off: To turn logging off.

Example

```
LSNRCTL> SET LOG_STATUS on
Connecting to (ADDRESS=(PROTOCOL=TCP)(HOST=sales-server)(PORT=1521))
LISTENER parameter "log_status" set to ON
The command completed successfully
```

1.5.14 SET SAVE_CONFIG_ON_STOP

Use the Listener Control utility command SET SAVE_CONFIG_ON_STOP to specify whether listener parameter value changes that you make with the SET command are saved to the listener.ora file when you stop the listener with the STOP command.

Purpose

To specify whether changes made to parameter values for the listener by the SET command are saved to the listener.ora file when the listener is stopped with the STOP command.

When you save changes, the Listener Control utility tries to preserve formatting, comments, and letter case. Before the command modifies the listener.ora file, it creates a backup of the file called listener.bak.

To have all parameters saved immediately, use the SAVE CONFIG command.

Syntax

From the operating system:

```
lsnrctl SET SAVE_CONFIG_ON_STOP {on | off}
```

From the Listener Control utility:

```
LSNRCTL> SET SAVE_CONFIG_ON_STOP {on | off}
```

Arguments

on: To save configuration to listener.ora.

off: To not save configuration to listener.ora.

Example

```
LSNRCTL> SET SAVE_CONFIG_ON_STOP on
LISTENER parameter "save_config_on_stop" set to ON
The command completed successfully
```



1.5.15 SET TRC_DIRECTORY

Use the Listener Control utility command SET TRC_DIRECTORY to set the destination directory into which Oracle writes listener trace files.

Purpose

To set the destination directory where the listener trace files are written. By default, the trace file are written to the ORACLE HOME/network/trace directory.



(i) Note

This command works only if Automatic Diagnostic Repository (ADR) is disabled. The default is for ADR to be enabled and to use the log directory ORACLE_HOME/log/ diag/product_type.

Prerequisites

None

Syntax

From the operating system:

lsnrctl SET TRC_DIRECTORY directory

From the Listener Control utility:

LSNRCTL> SET TRC_DIRECTORY directory

Arguments

directory: The directory path of the listener trace files.

Example

LSNRCTL> SET TRC_DIRECTORY /usr/oracle/admin Connecting to (ADDRESS=(PROTOCOL=TCP)(HOST=sales-server)(PORT=1521)) LISTENER parameter "trc_directory" set to /usr/oracle/admin The command completed successfully

1.5.16 SET TRC_FILE

Use the Listener Control utility command SET TRC_FILE to set the names of listener trace files.

Purpose

To set the name of the listener trace file. By default, the trace file name is listener.trc.





(i) Note

This command works only if Automatic Diagnostic Repository (ADR) is disabled. The default is for ADR to be enabled and to use the log directory <code>ORACLE_HOME/log/</code> diag/product_type.

Prerequisites

None

Syntax

From the operating system:

```
lsnrctl SET TRC_FILE file_name
```

From the Listener Control utility:

```
LSNRCTL> SET TRC_FILE file_name
```

Arguments

file_name: The file name of the listener trace.

Example

```
LSNRCTL> SET TRC_FILE list.trc
Connecting to (ADDRESS=(PROTOCOL=TCP)(HOST=sales-server)(PORT=1521))
LISTENER parameter "trc_file" set to list.trc
The command completed successfully
```

1.5.17 SET TRC_LEVEL

Use the Listener Control utility command SET TRC LEVEL to set a specific listener tracing level.

Purpose

To set a specific level of tracing for listeners.

Prerequisites

None

Syntax

From the operating system:

```
lsnrctl SET TRC_LEVEL level
```

From the Listener Control utility:

LSNRCTL> SET TRC_LEVEL level



Arguments

level: One of the following trace levels:

- off for no trace output
- user for user trace information
- admin for administration trace information
- support for Oracle Support Services trace information

Usage Notes

This command has the same functionality as the TRACE command.

Example

```
LSNRCTL> SET TRC_LEVEL admin
Connecting to (ADDRESS=(PROTOCOL=TCP)(HOST=sales-server)(PORT=1521))
LISTENER parameter "trc_level" set to admin
The command completed successfully
```

1.5.18 SHOW

Use the Listener Control utility command SHOW to list current listener parameter values.

Purpose

To view the current parameter values for the listener.

All of the SET parameters have equivalent SHOW parameters.

Prerequisites

None

Syntax

From the operating system:

lsnrctl SHOW parameter

From the Listener Control utility:

LSNRCTL> SHOW parameter

Arguments

parameter: A parameter whose settings you want to review. Parameters are shown in the example output.

When you enter SHOW without an argument, the Listener Control utility lists all the parameters.



Example

LSNRCTL> SHOW

The following properties are available with SHOW:

An asterisk (*) denotes a modifier or extended command:

current_listener

displaymode
inbound_connect_timeout

log_file

log_directory

log_status

rawmode

save_config_on_stop

trc_file

trc_directory

trc level

1.5.19 SHOW STATS

Use the Listener Control utility SHOW STATS command with the -REG option to display statistics about database service registration commands.

Purpose

To display statistics about the number of registration commands that the database listener receives while handling client connection requests.

Using these statistics, you can monitor service registration or service update operations, such as REGISTER, UPDATE, RE-REGISTER, and UN-REGISTER. This also helps you evaluate the traffic and overhead of these operations at Oracle Database.

Prerequisites

The listener must be running.

Syntax

From the operating system:

lsnrctl SHOW STATS -REG

From the Listener Control (LSNRCTL) utility:

LSNRCTL> SHOW STATS -REG

Usage Notes

- In addition to LSNRCTL, you can run this command from the Oracle Connection Manager Control (CMCTL) utility.
- If you enter SHOW STATS -REG without any argument, then the output displays a global-level data for all instances, registered services, handlers allocated to each service, listening endpoints, and access control lists (ACLs).
- Recent count is a periodic count of all commands received by the listener from the last reset, that is, from the time you cleared the Recent section using -clear. If you have not



used -clear till now, then this field displays a cumulative count (total number of commands collected since the listener started).

For a detailed description about other sections of the output, see *Oracle AI Database Net Services Administrator's Guide*.

Arguments and Examples

Argument and Description	Example								
To display a recent and cumulative count of all registration commands at a global level:	LSNRCTL:lsnr1> show stats -reg								
-reg	Global Level:								
			Recent						
j	Recent Duration: 5 days 17 hr. 15 min. 25 sec								
			Service						
	Registration	2	2	2	4	0			
	Updates Re-Register	3	0	0	12	0			
	Re-Register	0	3	0	0	0			
	Un-Register	0	0	0	0	0			
	Cumulative								
	Registration	3	3		6	0			
	Updates	4	0	0	12	0			
	Re-Register	0	3	0	0	0			
	Un-Register		0	0	0	0			
	The command co	omplete	ed succe	ssful	ly				
To display a recent and cumulative count of all registration commands for the specified instance	LSNRCTL:lsnr1> show stats -reg -inst sales1								
name:	Instance Name: sales1								
-inst instance_name			Recent						
	Recent Duration: 5 days 15 hr. 17 min. 18 sec								
	Command Ins	stance	Service	ENDP	Handler	TNF			
				0	4	0			
	Registration	2	2	2	- 1				
	Registration Updates	2 3	2 0	0	12	0			
	Registration Updates Re-Register	2 3 0	2 0 0	0	12	0			
	Registration Updates Re-Register Un-Register	2 3 0 0	2 0 0 0	0 0 0	12 0 0	0 0 0			
	Registration Updates Re-Register Un-Register	2 3 0 0	2 0 0 0 Cumulat		12 0 0	0 0 0			
	Registration Updates Re-Register Un-Register Registration		Cumulat	ive		0 0 0			
	Registration		Cumulat	ive					
			Cumulat 2 3	2 0 3		0			
	Registration Updates			2 0 3	4 12 0	0			



Argument and Description	Example					
To display a recent and cumulative count of registration commands for all instances:	LSNRCTL:lsnr1	> show	v stats -	-reg	-all_ins	t
-all_inst	Instance Name	: sale	es1			
			Recent			
	Recent Durati	on: 5	days 15	hr.	3 min. 2	sec
				ENDP	Handler	INF
	Registration				2	0
	Updates		0			0
	Re-Register Un-Register		0	0	0 0	0
	UII-REGISTEI	U	Cumulat	-		U
	Registration	1		1		0
	Updates		0	2	5	
	Re-Register			0		0
	Un-Register	0	0	0	0	0
	Instance Name	: sale				
	Recent Durati	on: 2	Recent	nr 2	min 2	sec
					Handler	
	Registration					0
	Updates					0
	Re-Register				0	0
	Un-Register	0	0		0	0
			Cumulat			
	Registration		1	1	3	0
	Updates				5	
	Re-Register	0		0	0 0	0
	Un-Register	0	0	0	U	U
	The command o	omplet	ced succe	essfu	lly	
To display a recent and cumulative count of all registration commands for the specified service name:						les.us.example.com
	Service Name:			-		
-serv service_name	Recent Durati	Flag	_	odnes	s Delt	
	Recent Cumulative	2		0	0	
	The command completed successfully					
	THE COMMINATION C	Ompici	ca sacci	LBBIU	 y	
To display a recent and cumulative count of registration commands for all database services:	LSNRCTL:lsnr1			-reg	-all_ser	V
-all_serv	Service Name:			mnle	COM	
				-	5 min. 2	5 sec
	Receill Dulati					
	Recent Duraci	Flag	gs Goo	odnes	2 2010	
	Recent Duraci		•	oanes 2	0	
		Flag	•			
	Recent CumulativeService Name:	Flag 1 2 emplo	oyee.us.e	2 0 examp	0 0	
	Recent Cumulative	Flag 1 2 emplo on: 8	 oyee.us.e days 2 l	2 0 examp	0 0 le.com min. 25	
	Recent CumulativeService Name: Recent Durati	Flagent Flagen	 oyee.us.e days 2 l	2 0 examp nr. 5 odnes	0 0 le.com min. 25 s Delt	
	Recent CumulativeService Name:	Flag 1 2 emplo on: 8	 oyee.us.e days 2 l	2 0 examp	0 0 le.com min. 25	



Argument and Description	Example							
To reset the Recent section to 0 after fetching the values:	LSNRCTL:lsnr1> show stats -reg -clear							
-clear	Global Level:							
This gives you a fresh set of data in the Recent section. You can use -clear with all the SHOW STATS arguments.	Recent Recent Duration: 0 days 0 hr. 0 min. 4 sec Command Instance Service ENDP Handler INF							
	Registration	0	0	0	0	0		
	Updates	0	0	0	0	0		
	Re-Register	0	0	0	0	0		
	Un-Register	0	0	0	0	0		
	Cumulative							
	Registration	3	3	3	6	0		
	Updates	4	0	0	13	0		
	Re-Register	1	0	0	0	0		
	Un-Register	0	1	0	0	0		
	The command co	omplet	ed suc	cessful	ly			

Related Topics

Oracle Al Database Net Services Administrator's Guide

1.5.20 SPAWN

Use the Listener Control utility command SPAWN to start a program that is stored on the computer on which the listener is running and that is listed with an alias in the listener.ora file.

Purpose

To start a program stored on the computer on which the listener is running and that is listed with an alias in the listener.ora file.

Prerequisites

None

Syntax

From the operating system:

```
lsnrctl SPAWN listener_name alias (arguments='arg1,arg2,...')
```

From the Listener Control utility:

```
LSNRCTL> SPAWN listener_name alias (arguments='arg1,arg2,...')
```

Arguments

listener_name: The listener name, if the default name of LISTENER is not used.



alias: The alias of the program to be spawned is specified by a listener.ora file entry that is similar to the following:

```
alias = (PROGRAM=(NAME=)(ARGS=)(ENVS=))
```

For example:

```
nstest = (PROGRAM=(NAME=nstest)(ARGS=test1)(ENVS='ORACLE_HOME=/usr/oracle'))
```

Example

The nstest program, shown in the preceding section, can then be spawned using the following command:

lsnrctl SPAWN listener name nstest

1.5.21 START

Use the Listener Control utility command START to start a named listener.

Purpose

To start the named listener.

Prerequisites

The listener must not be running.

Syntax

From the operating system:

```
lsnrctl START listener_name
```

From the Listener Control utility:

LSNRCTL> START listener_name



(i) Note

On Microsoft Windows, if the database was installed with the Oracle Home User, then the utility can prompt for a password. The password is the operating system password for the Oracle Home User. The prompt is displayed only if the listener service does not exist and if it needs to be created as part of starting the listener.

Arguments

listener name: The listener name if the default name of LISTENER is not used.



Usage Notes

To start a listener that you configured in the listener.ora file whose name does not contain the string LISTENER.

For example, if the listener name is tcp_lsnr, enter:

```
lsnrctl START tcp lsnr
```

From the Listener Control utility:

```
LSNRCTL> START tcp_lsnr
```

Example

```
LSNRCTL> START
Starting /private/sales_group/sales/bin/tnslsnr: please wait...
TNSLSNR for Linux: Version 23.4.0.0.0
System parameter file is $ORACLE_HOME/network/admin/listener.ora
Log messages written to $ORACLE_BASE/diag/tnslsnr/node_name/listener/alert/
log.xml
Listening on: (DESCRIPTION=(ADDRESS=(PROTOCOL=tcp)(HOST=sales-server)
(PORT=1521)))
Connecting to (DESCRIPTION=(ADDRESS=(PROTOCOL=TCP)(HOST=sales-server)
(PORT=1521)))
STATUS of the LISTENER
-----
Alias
                         LISTENER
Version
                        TNSLSNR for Linux: Version 23.4.0.0.0
                        21-MAR-2024 21:50:49
Start Date
Uptime
                         0 days 0 hr. 0 min. 0 sec
Trace Level
                         off
Security
                         ON: Local OS Authetication
SNMP
                         OFF
Listener Parameter File $ORACLE_HOME/network/admin/listener.ora
Listener Log File
                        $ORACLE_BASE/diag/tnslsnr/node_name/listener/alert/
log.xml
Listening Endpoints Summary...
  (DESCRIPTION=(ADDRESS=(PROTOCOL=tcp)(HOST=sales-server)(PORT=1521)))
The listener supports no services
The command completed successfully
```

(i) See Also

Oracle AI Database Administrator's Reference for Microsoft Windows for information about the Oracle Home User



1.5.22 STATUS

Use the Listener Control utility command STATUS to show listener status information.

Purpose

To display basic status information about a listener, including a summary of listener configuration settings, listening protocol addresses, and a summary of services that are registered with the listener.



Note

You can also obtain the status of the listener through the Oracle Enterprise Manager Cloud Control console.

Prerequisites

None

Syntax

From the operating system:

lsnrctl STATUS listener_name

From the Listener Control utility:

LSNRCTL> STATUS listener_name

Arguments

listener_name: The listener name, if the default name of LISTENER is not used.

Usage Notes

The SET DISPLAYMODE command changes the format and the level of output detail.



(i) See Also

Oracle Al Database Net Services Administrator's Guide for a complete description of STATUS output

Example

The following example shows STATUS output in the default display mode. The output contains:

- Listener configuration settings
- Listening endpoints summary



Services summary, which is an abbreviated version of the SERVICES command output

```
LSNRCTL> STATUS
Connecting to (DESCRIPTION=(ADDRESS=(PROTOCOL=ipc)(KEY=net)))
STATUS of the LISTENER
Alias
                         LISTENER
Version
                         TNSLSNR for Linux: Version 23.4.0.0.0 -
Production
                         12-MAR-2024 12:02:00
Start Date
Uptime
                         0 days 0 hr. 5 min. 29 sec
                         support
Trace Level
Security
                         OFF
SNMP
                         OFF
Listener Parameter File /oracle/network/admin/listener.ora
Listener Log File
                       /oracle/network/log/listener.log
Listener Trace File
                         /oracle/network/trace/listener.trc
Listening Endpoints Summary...
  (DESCRIPTION=(ADDRESS=(PROTOCOL=ipc)(KEY=net)))
  (DESCRIPTION=(ADDRESS=(PROTOCOL=tcp)(HOST=sales-server)(PORT=1521)))
  (DESCRIPTION=(ADDRESS=(PROTOCOL=tcps)(HOST=sales-server)(PORT=2484)))
Services Summary...
Service "sales1.us.example.com" has 1 instance(s).
  Instance "sales", status READY, has 1 handler(s) for this service...
Service "sales2.us.example.com" has 1 instance(s).
  Instance "sales", status READY, has 2 handler(s) for this service...
The command completed successfully
```

1.5.23 STOP

Use the Listener Control utility command STOP to stop the named listener.

Purpose

To stop the named listener.

Prerequisites

The named listener must be running.

Syntax

From the operating system:

```
lsnrctl STOP listener_name
```

From the Listener Control utility:

LSNRCTL> STOP listener_name



Arguments

listener_name: The listener name, if the default name of LISTENER is not used.

Example

```
LSNRCTL> STOP
Connecting to (ADDRESS=(PROTOCOL=TCP)(HOST=sales-server)(PORT=1521))
The command completed successfully
```

1.5.24 TRACE

Use the Listener Control utility command TRACE to set listener tracing.

Purpose

To set tracing for the listener.

Syntax

From the operating system:

```
lsnrctl trace level listener_name
```

From the Listener Control utility:

```
LSNRCTL> trace level listener_name
```

Arguments

leve1: One of the following trace levels:

- off for no trace output
- user for user trace information
- admin for administration trace information
- support for Oracle Support Services trace information

listener_name: Specify the listener name, if the default name of LISTENER is not used.

Usage Notes

This command has the same functionality as the SET TRC_LEVEL command.

Example

```
LSNRCTL> TRACE ADMIN lsnr
Connecting to (ADDRESS=(PROTOCOL=TCP)(HOST=sales-server)(PORT=1521))
Opened trace file: /oracle/network/trace/listener.trc
The command completed successfully
```



1.5.25 VERSION

Use the Listener Control utility command VERSION to show the current version of Listener Control utility.

Purpose

To display the current version of Listener Control utility.

Prerequisites

None

Syntax

From the operating system:

```
lsnrctl VERSION listener_name
```

From the Listener Control utility:

```
LSNRCTL> VERSION listener_name
```

Arguments

listener_name: The listener name, if the default name of LISTENER is not used.

Example

```
LSNRCTL> version listener

Connecting to ADDRESS=(PROTOCOL=TCP)(HOST=sales-server)(PORT=1521))

TNSLSNR for Linux: Version 23.4.0.0.0

TNS for Linux: Version 23.4.0.0.0

Oracle Bequeath NT Protocol Adapter for Linux: Version 23.4.0.0.0

Unix Domain Socket IPC NT Protocol Adaptor for Linux: Version

23.4.0.0.0

TCP/IP NT Protocol Adapter for Linux: Version 23.4.0.0.0

The command completed successfully
```

Oracle Connection Manager Control Utility

This chapter describes Oracle Connection Manager Control Utility commands and syntax .

- Connection Manager Control Utility Command Modes and Syntax
 Oracle Connection Manager Control utility (CMCTL) enables you to start up, configure, and alter how client connection requests are managed.
- Oracle Connection Manager Control Utility Overview
- Oracle Connection Manager Control Utility Commands
 Use Oracle Connection Manager Control utility commands to manage and configure
 Oracle Connection Manager instances.

2.1 Connection Manager Control Utility Command Modes and Syntax

Oracle Connection Manager Control utility (CMCTL) enables you to start up, configure, and alter how client connection requests are managed.

The syntax of the Oracle Connection Manager Control utility is:

cmctl command [argument]

Oracle Connection Manager Control utility supports the following command types:

- Initialization and termination commands such as STARTUP and SHUTDOWN
- Alter commands such as SET LOG LEVEL and SET EVENT
- Display commands, such as SHOW STATUS and SHOW RULES
- Gateway commands such as SHOW GATEWAYS and RESUME GATEWAYS



Note

Use SET commands to dynamically alter configuration parameters that control how the listener receives client connections. Changes only remain in effect until Oracle Connection Manager shuts down. You cannot save changes to the cman.ora file.

Use the Oracle Connection Manager Control utility in command mode or batch mode.

- Using command mode:
 - From the Oracle Connection Manager Control utility:

Enter cmctl at the command line to obtain the program prompt and run the command:

cmctl
CMCTL> command

From the operating system:

Enter the command from the operating system command prompt:

```
cmctl [command] [argument1 . . . argumentN] [-c instance_name]
```

You can append an Oracle Connection Manager instance name as an argument to all commands that you run in this manner. If you do not include an Oracle Connection Manager instance name, then the default instance name is assumed. The default name is cman hostname.

Using batch mode:

You can combine commands in a standard text file and run them as a sequence of commands. To run commands in batch mode, use the following syntax:

cmctl @input_file

(i) See Also

Oracle Al Database Net Services Administrator's Guide for more information about Oracle Connection Manager architecture

2.2 Oracle Connection Manager Control Utility Overview

Oracle Connection Manager Control utility (CMCTL) enables you to administer Oracle Connection Manager. Use Oracle Connection Manager Control utility commands to administer one or more Oracle Connection Manager instances. Additionally, you can view and change parameter settings.



2.3 Oracle Connection Manager Control Utility Commands

Use Oracle Connection Manager Control utility commands to manage and configure Oracle Connection Manager instances.

ADMINISTER

Use the Oracle Connection Manager Control Utility command ADMINISTER to select Oracle Connection Manager instances to administer.

CLOSE CONNECTIONS

Use the Oracle Connection Manager Control Utility command CLOSE CONNECTIONS to terminate connections.

CLOSE NON ADMIN ENDPOINTS

Use the Oracle Connection Manager Control Utility command ${\tt CLOSE}$ ${\tt NON_ADMIN_ENDPOINTS}$ to close all non-admin listening endpoints.

EXIT

Use the Oracle Connection Manager Control Utility command EXIT to exit from Oracle Connection Manager utility.

HELP

Use the Oracle Connection Manager Control Utility \mathtt{HELP} command to display all of the Oracle Connection Manager Control utility commands or to show the syntax of a particular command.

QUIT

Use the Oracle Connection Manager Control Utility command QUIT to exit Oracle Connection Manager Control utility.

RELOAD

Use the Oracle Connection Manager Control utility RELOAD command to make the utility dynamically reread parameters and rules.

RESUME GATEWAYS

Use the Oracle Connection Manager Control Utility command RESUME GATEWAYS to resume suspended gateway processes.

SET

Use the Oracle Connection Manager Control Utility SET command to list the parameters that you can modify using this command.

SET ASO AUTHENTICATION FILTER

Use the Oracle Connection Manager Control Utility command \mathtt{SET} $\mathtt{ASO_AUTHENTICATION_FILTER}$ to indicate whether clients must use Oracle Database security authentication.

SET CONNECTION STATISTICS

Use the Oracle Connection Manager Control Utility SET CONNECTION_STATISTICS command to specify whether gateway processes collect connection statistics.

SET EVENT

Use the Oracle Connection Manager Control Utility SET EVENT command to log information for a particular event.

SET IDLE TIMEOUT

Use the Oracle Connection Manager Control Utility SET IDLE_TIMEOUT command to specify the amount of time that clients can be idle without transmitting data.



SET INBOUND CONNECT TIMEOUT

Use the Oracle Connection Manager Control Utility SET INBOUND_CONNECT_TIMEOUT command to specify the maximum amount of time that Oracle Connection Manager listeners wait for client connection requests before timing out.

SET LOG DIRECTORY

Use the Oracle Connection Manager Control Utility SET LOG_DIRECTORY command to designate where Oracle Connection Manager log files are written.

SET LOG LEVEL

Use the Oracle Connection Manager Control Utility SET LOG_LEVEL command to set Oracle Connection Manager log levels.

SET OUTBOUND CONNECT TIMEOUT

Use the Oracle Connection Manager Control Utility SET OUTBOUND_CONNECT_TIMEOUT command to specify the time limit that Oracle Connection Manager instances wait for server connections before timing out.

SET SESSION TIMEOUT

Use the Oracle Connection Manager Control utility \mathtt{SET} $\mathtt{SESSION_TIMEOUT}$ command to specify the maximum duration of Oracle Connection Manager sessions.

SET TRACE DIRECTORY

Use the Oracle Connection Manager Control utility SET TRACE_DIRECTORY command to designate where Oracle Connection Manager instance trace files are written.

SET TRACE LEVEL

Use the Oracle Connection Manager Control utility \mathtt{SET} TRACE_LEVEL command to set Oracle Connection Manager instance trace levels.

SHOW

Use the Oracle Connection Manager Control utility SHOW command to display the parameters that you can use as arguments for this command.

SHOW ALL

Use the Oracle Connection Manager Control utility SHOW ALL command to combine and display SHOW PARAMETERS and SHOW RULES command output.

SHOW CONNECTIONS

Use the Oracle Connection Manager Control utility SHOW CONNECTIONS command to display connection information.

SHOW DEFAULTS

Use the Oracle Connection Manager Control utility SHOW DEFAULTS command to display default parameter settings.

SHOW EVENTS

Use the Oracle Connection Manager Control utility ${\tt SHOW}$ EVENTS command to display events that are currently operating.

SHOW GATEWAYS

Use the Oracle Connection Manager Control utility SHOW GATEWAYS command to display the statuses of gateway processes.

SHOW PARAMETERS

Use the Oracle Connection Manager Control utility SHOW PARAMETERS command to display the parameter settings for an instance.

• SHOW RULES

Use the Oracle Connection Manager Control Utility ${\tt SHOW}$ RULES command to display an instance access control list.



SHOW SERVICES

Use the Oracle Connection Manager Control utility SHOW SERVICES command to display Oracle Connection Manager instance information.

SHOW STATS

Use the Oracle Connection Manager Control utility SHOW STATS command with the -REG option to display statistics about database service registration commands.

SHOW STATUS

Use the Oracle Connection Manager Control utility SHOW STATUS command to display Oracle Connection Manager instance information.

SHOW VERSION

Use the Oracle Connection Manager Control utility SHOW VERSION command

SHUTDOWN

Use the Oracle Connection Manager Control utility SHUTDOWN command to shut down gateway processes or an entire Oracle Connection Manager instance.

STARTUP

Use the Oracle Connection Manager Control utility STARTUP command to start Oracle Connection Manager.

SUSPEND GATEWAY

Use the Oracle Connection Manager Control utility SUSPEND GATEWAY command to specify the gateway processes than cannot accept new client connections.

2.3.1 ADMINISTER

Use the Oracle Connection Manager Control Utility command ADMINISTER to select Oracle Connection Manager instances to administer.

Purpose

To select an Oracle Connection Manager instance.

Prerequisites

None

Syntax

From the Oracle Connection Manager Control utility:

CMCTL> ADMINISTER [-c] instance name

Arguments

instance_name: The Oracle Connection Manager instance name that you want to administer. Instances are defined in the cman.ora file.

Usage Notes

You can run the ADMINISTER command only within the utility. You cannot issue this command from the operating system.

ADMINISTER enables you to choose Oracle Connection Manager instances to administer. To start the Oracle Connection Manager instance, run the STARTUP command.

When you omit the instance name from the command, the instance that is administered defaults to the local instance.



Use the -c option to administer an instance that is not the local instance.

Example

```
CMCTL> ADMINISTER cman_indl040ad Current instance cman_indl040ad is already started Connections refer to (address=(protocol=TCP)(host=indl040ad)(port=1560)). The command completed successfully
```

2.3.2 CLOSE CONNECTIONS

Use the Oracle Connection Manager Control Utility command CLOSE CONNECTIONS to terminate connections.

Purpose

To terminate connections, using specific qualifiers to select the connections to close.

Prerequisites

Oracle Connection Manager must be running.

Syntax

From the operating system:

```
cmctl CLOSE CONNECTIONS [in state] [gt time] [from source] [to destination]
[for service] [using gateway_process_id] [connect_identifier_list]
[-c cman_name]
```

From the Oracle Connection Manager Control utility:

```
CMCTL> CLOSE CONNECTIONS [in state] [gt time] [from source] [to destination] [for service] [using gateway_process_id] [connect_identifier_list
```

Arguments

state: One of the following values to specify the connection state:

- idle: Connections that are inactive in the established state.
- connecting: Connections that are in the process of connecting.
- established: Connections that are connected and are transferring data.
- terminating: Connections that are disconnecting.

If you do not specify a state, then CLOSE CONNECTIONS defaults to all possible states. If the time qualifier is included under these conditions, then the time specified is the amount of time that has elapsed since a client initiated a connection.

time: The time format. Use the following format to specify connections that have a duration greater than the time indicated:

```
gt[hh:mm:]ss
```

source: The source address. Use one of the following formats to specify the source address:



- from IP
- from hostname
- from subnet

destination: The destination address. Use one of the following formats to specify the destination address:

- to IP
- to hostname
- to subnet

service: The service name. Use the service_name parameter to specify the service, such as sales.us.example.com.

gateway_process_id: The gateway process identifier is a number. Use this number to specify connections that are proxied by the gateway process indicated. To determine the gateway process identifier, use the Oracle Connection Manager control utility show gateways command.

connect_identifier_list: The connection identifiers. Use a space between multiple connection identifiers in a list.

Usage Notes

Because the CLOSE CONNECTIONS command terminates connections, it might generate error messages on both the client and the server sides.

The IDLE state qualifier always requires a time qualifier.

Issuing CLOSE CONNECTIONS without an argument closes all connections.

Examples

The following example shuts down connections in any state. The elapsed time of the connection must be greater than 1 hour and 30 minutes. The connection source is the specified subnet, and the destination is the specified host name.

```
CMCTL> CLOSE CONNECTIONS gt 1:30:00 from 192.0.2.32/24 to host1
```

The following example shuts down those connections proxied by gateway process 0 that have been in the idle state more than 30 minutes:

```
CMCTL> CLOSE idle CONNECTIONS gt 30:00 using 0
```

The following example shuts down connections that are connected to the service sales.us.example.com:

CMCTL> CLOSE established CONNECTIONS for sales.us.example.com

REST API for CLOSE CONNECTIONS Command

```
POST /close/connections
JSON Payload
{
"in" : [ "idle" | "connecting" | "established" | "terminating"]
"gt" : "[hh:mm:]ss",
   "from" : ["source ip " | "hostname " | "subnet"],
   "to" : ["destination ip" | "hostname" | "subnet"],
   "for" : "service name",
   "using" : "gateway process identifier",
```



```
"connect_id_list" : [id1, id2, .. ]
}
```

2.3.3 CLOSE NON_ADMIN_ENDPOINTS

Use the Oracle Connection Manager Control Utility command CLOSE NON_ADMIN_ENDPOINTS to close all non-admin listening endpoints.

Purpose

To shut down all non-admin listening addresses.

Prerequisites

Oracle Connection Manager must be running.

Syntax

From the operating system:

```
cmctl close non_admin_endpoints [-c instance_name]
```

From Oracle Connection Manager Control utility:

```
CMCTL> CLOSE NON ADMIN ENDPOINTS
```

Usage Notes

You can tag Oracle Connection Manager addresses as admin endpoints by specifying the ADDRESS networking parameter. Thus, when you run the CLOSE NON_ADMIN_ENDPOINTS command, Oracle Connection Manager Control utility continues to run admin commands using tagged listening endpoints. The closed endpoints can be used by other process or another instance of Oracle Connection Manager.

Example

```
CMCTL> CLOSE NON_ADMIN_ENDPOINTS
The command completed successfully.
```

Related Topics

ADDRESS

The ADDRESS networking parameter specifies the protocol address of Oracle Connection Manager.

2.3.4 EXIT

Use the Oracle Connection Manager Control Utility command EXIT to exit from Oracle Connection Manager utility.

Purpose

To exit from Oracle Connection Manager Control utility.



Prerequisites

None

Syntax

From the operating system:

```
cmctl EXIT [-c instance_name]
```

From Oracle Connection Manager Control utility:

CMCTL> EXIT

Usage Notes

This command is identical to the QUIT command.

Example 2-1 Example

CMCTL> EXIT

2.3.5 HFI P

Use the Oracle Connection Manager Control Utility HELP command to display all of the Oracle Connection Manager Control utility commands or to show the syntax of a particular command.

Purpose

To provide a list of all commands for Oracle Connection Manager Control utility or to provide help with the syntax of a particular command.

Prerequisites

None

Syntax

From the operating system:

```
cmctl HELP [command] [-c instance_name]
```

From the Oracle Connection Manager Control utility:

CMCTL> HELP [command]

From the operating system:

cmctl HELP [command] [-c instance_name]

From the Oracle Connection Manager Control utility:

CMCTL> HELP [command]

Arguments

command: Specify a HELP command. Commands are shown in the following sample output.

When you enter a command as an argument to HELP, Oracle Connection Manager Control utility displays information about how to use the command. When you enter HELP without an argument, Oracle Connection Manager Control utility displays a list of all the commands.



Example

CMCTL> HELP

The following operations are available

An asterisk (*) denotes a modifier or extended command:

administer close* exit
resume* save_passwd set*
shutdown sleep startup
show_version quit reload show* suspend*

2.3.6 QUIT

Use the Oracle Connection Manager Control Utility command QUIT to exit Oracle Connection Manager Control utility.

Purpose

To exit Oracle Connection Manager Control utility and return to the operating system prompt.

Prerequisites

None

Syntax

CMCTL> QUIT

From the Oracle Connection Manager Control utility:

cmctl QUIT

From the operating system:

Usage Notes

This command is identical to the EXIT command.

Example

CMCTL> QUIT

2.3.7 RELOAD

Use the Oracle Connection Manager Control utility RELOAD command to make the utility dynamically reread parameters and rules.

Purpose

To dynamically reread parameters and rules.

Prerequisites

Oracle Connection Manager must be running.

Syntax

From the operating system:



```
cmctl RELOAD [-with_ha] [-c instance_name]
```

From the Oracle Connection Manager Control utility:

CMCTL> RELOAD [-with ha]

Arguments

-with_ha: It is used to reload cman.ora without dropping registrations

Usage Notes

Configuration information that you modify using the RELOAD command applies only to new connections. Existing connections are unaffected. The SET RELOAD command restores configurations set in cman.ora, and overrides the SET command.

The RELOAD command reregisters gateways with the Oracle Connection Manager listener during which some new connections might be refused until the registration completes.

You can use the <code>-with_ha</code> option with <code>RELOAD</code> to not drop registrations, thus providing high service availability during reload.

Example

CMCTL> RELOAD
The command completed successfully

REST API for RELOAD Command

POST /reload

2.3.8 RESUME GATEWAYS

Use the Oracle Connection Manager Control Utility command RESUME GATEWAYS to resume suspended gateway processes.

Purpose

To resume gateway processes that have been suspended.

Prerequisites

Oracle Connection Manager must be running.

Syntax

From the operating system:

```
cmctl RESUME GATEWAYS [gateway_process_id] [cman_name]
```

From the Oracle Connection Manager Control utility:

CMCTL> RESUME GATEWAYS [gateway_process_id]

Arguments

gateway_process_id: One or more gateway processes to reopen. Separate multiple gateway processes using a space between the process identifiers.



Usage Notes

Running the RESUME GATEWAYS command without an argument reopens all closed gateway processes.

Example

```
CMCTL> RESUME GATEWAYS 1
The command completed successfully
```

REST API for RESUME GATEWAYS Command

```
POST /resume/gateways
JSON Payload
    {
        "gateway_id_list" : [id1, id2, ...]
}
```

2.3.9 SET

Use the Oracle Connection Manager Control Utility SET command to list the parameters that you can modify using this command.

Purpose

To display a list of parameters that can be modified using this command.

Prerequisites

None

Syntax

From the operating system:

```
cmctl SET
```

From the Oracle Connection Manager Control utility:

```
CMCTL> SET
```

Example

```
CMCTL> SET
The following operations are available after set
An asterisk (*) denotes a modifier or extended command:

aso_authentication_filter outbound_connect_timeout
connection_statistics session_timeout
event trace_directory
idle_timeout trace_level
inbound_connect_timeout
log_directory
log level
```



2.3.10 SET ASO_AUTHENTICATION_FILTER

Use the Oracle Connection Manager Control Utility command SET ASO_AUTHENTICATION_FILTER to indicate whether clients must use Oracle Database security authentication.

Purpose

To indicate whether the client must use Oracle Database security to authenticate.

Prerequisites

Oracle Connection Manager must be running.

Syntax

From the operating system:

```
cmctl SET ASO_AUTHENTICATION_FILTER {on | off}[-c instance_name]
```

From the Oracle Connection Manager Control utility:

```
CMCTL> SET ASO_AUTHENTICATION_FILTER {on | off}
```

Arguments

on: To reject connections that are not using Secure Network Service (SNS) to perform client authentication. SNS is part of Oracle Database security.

off: To specify that no authentication is required for client connections. This is the default.

Example

```
CMCTL> set aso_authentication_filter ON CMAN_user.us.example.com parameter aso_authentication_filter set to ON The command completed successfully
```

REST API for SET ASO_AUTHENTICATION_FILTER Command

```
POST /set/authlevel
JSON Payload
{
    "authlevel": "true" | "false"
}
```

2.3.11 SET CONNECTION_STATISTICS

Use the Oracle Connection Manager Control Utility SET CONNECTION_STATISTICS command to specify whether gateway processes collect connection statistics.

Purpose

To specify whether gateway processes collect connection statistics.



Prerequisites

To specify whether gateway processes collect connection statistics.

Syntax

From the operating system:

```
cmctl SET CONNECTION_STATISTICS {yes | no}[-c instance_name]
```

From the Oracle Connection Manager Control utility:

```
CMCTL> SET CONNECTION_STATISTICS {yes | no}
```

Arguments

yes: To have gateway processes collect connection statistics.

no: To not have gateway processes collect connection statistics. This is the default.

Usage Notes

If you set connection_statistics to yes, then you can obtain statistics by running the show connections command.

Example

```
CMCTL> set connection_statistics ON CMAN_user.us.example.com parameter connection_statistics set to ON The command completed successfully
```

REST API for SET CONNECTION_STATISTICS Command

```
POST /set/connstats/
JSON Payload
{
"connection_statistics" : "yes" | "no"
}
```

2.3.12 SET EVENT

Use the Oracle Connection Manager Control Utility \mathtt{SET} EVENT command to log information for a particular event.

Purpose

To log information for a particular event.

Syntax

From the operating system:

```
cmctl SET EVENT event_group [-c instance_name]
```

From the Oracle Connection Manager Control utility:

```
CMCTL> SET EVENT event_group {on | off}
```



Arguments

event_group: Specify one of the following event groups:

- init_and_term: Initialization and termination event group.
- memory_ops: Memory operations event group.
- conn_hdlg: Connection handling event group.
- proc_mgmt: Process management event group.
- reg_and_load: Registration and load update event group.
- wake_up: Events related to Connection Manager Administration (CMADMIN) wakeup queue event group.
- timer: Gateway timeouts event group.
- cmd proc: Command processing event group.
- relay: Events associated with connection control blocks event group.

on: To enable an event group.

off: To disable an event group.

Usage Notes

The SET EVENT command accepts only one argument at a time. To log multiple events, run the command for each event separately.

Example

```
CMCTL> set event memory_ops off cman11 event memory_ops set to OFF. The command completed successfully.
```

2.3.13 SET IDLE_TIMEOUT

Use the Oracle Connection Manager Control Utility SET IDLE_TIMEOUT command to specify the amount of time that clients can be idle without transmitting data.

Purpose

To specify the amount of time a client can be idle without transmitting data.

Prerequisites

Oracle Connection Manager must be running.

Syntax

From the operating system:

```
cmctl SET IDLE_TIMEOUT [time] [-c instance_name]
```

From the Oracle Connection Manager Control utility:

```
CMCTL> SET IDLE_TIMEOUT [time]
```



Arguments

time: Specify the idle timeout in seconds. The default is 0 (zero), which disables this feature.

Example

```
CMCTL> SET IDLE_TIMEOUT 30
CMAN_user.us.example.com parameter idle_timeout set to 30
The command completed successfully
```

REST API for SET IDLE_TIMEOUT Command

```
POST /set/maxidletime
JSON Payload
{
"idle_timeout" : "time"
}
```

2.3.14 SET INBOUND_CONNECT_TIMEOUT

Use the Oracle Connection Manager Control Utility SET INBOUND_CONNECT_TIMEOUT command to specify the maximum amount of time that Oracle Connection Manager listeners wait for client connection requests before timing out.

Purpose

To specify the maximum amount of time the Oracle Connection Manager listener waits for a valid connection request from the client before timing out.

Prerequisites

Oracle Connection Manager must be running.

Syntax

From the operating system:

```
cmctl SET INBOUND_CONNECT_TIMEOUT [time] [-c instance_name]
```

From Oracle Connection Manager Control:

```
CMCTL> SET INBOUND_CONNECT_TIMEOUT [time]
```

Arguments

time: The inbound connect timeout in seconds. The default is 0 (zero), which disables this feature.

Example

```
CMCTL> SET INBOUND_CONNECT_TIMEOUT 30
CMAN_user.us.example.com parameter inbound_connect_timeout set to 30
The command completed successfully
```



REST API for SET INBOUND CONNECT TIMEOUT Command

```
POST /set/maxcntdtime
JSON Payload
"inbound_connect_timeout" : "time"
```

2.3.15 SET LOG_DIRECTORY

Use the Oracle Connection Manager Control Utility SET LOG_DIRECTORY command to designate where Oracle Connection Manager log files are written.



(i) Note

This command works only if you have not enabled Automatic Diagnostic Repository (ADR). The default is for ADR to be enabled and use the log directory <code>ORACLE_HOME/</code> log.

Purpose

To designate where the log files for Oracle Connection Manager are written.

Prerequisites

Oracle Connection Manager must be running.

Syntax

From the operating system:

```
cmctl SET LOG_DIRECTORY [directory_path] [-c instance_name]
```

From the Oracle Connection Manager Control utility:

```
CMCTL> SET LOG_DIRECTORY [directory_path]
```

Arguments

directory_path: The location of the log directory. The default path is as follows:

Linux and UNIX:

```
ORACLE_HOME/network/log directory
```

Microsoft Windows:

```
ORACLE_HOME\network\log directory
```

Usage Notes

Use the Show parameters command to determine the location of the log files.



Example

```
CMCTL>
SET LOG_DIRECTORY /disk1/user_cman_test/oracle/network/admin
CMAN_user.us.example.com parameter log_directory set to
/disk1/user_cman_test/oracle/network/admin
```

The command completed successfully

2.3.16 SET LOG_LEVEL

Use the Oracle Connection Manager Control Utility \mathtt{SET} $\mathtt{LOG_LEVEL}$ command to set Oracle Connection Manager log levels.

Purpose

To set the log level for Oracle Connection Manager.

Prerequisites

Oracle Connection Manager must be running.

Syntax

From the operating system:

```
cmctl SET LOG_LEVEL [level] [-c instance_name]
CMCTL> SET LOG_LEVEL [level]
```

From Oracle Connection Manager Control utility:

Arguments

- off: No logging.
- user: User log information.
- admin: Administrative log information.
- support: Oracle Support Services log information. This is the default.

level: Specify one of the following log levels:

Usage Notes

Specify off to capture the minimum amount of log information. Specify support to capture the maximum amount.

Example

```
CMCTL> SET LOG_LEVEL SUPPORT
CMAN_user.us.example.com parameter log_level set to SUPPORT
The command completed successfully
```

REST API for SET LOG LEVEL Command

POST /set/loglevel JSON Payload



```
{
"log_level" : "level"
}
```

2.3.17 SET OUTBOUND_CONNECT_TIMEOUT

Use the Oracle Connection Manager Control Utility SET OUTBOUND_CONNECT_TIMEOUT command to specify the time limit that Oracle Connection Manager instances wait for server connections before timing out.

Purpose

To specify the maximum amount of time the Oracle Connection Manager instance waits for a valid connection with the server before timing out.

Prerequisites

Oracle Connection Manager must be running.

Syntax

From the operating system:

```
cmctl SET OUTBOUND_CONNECT_TIMEOUT [time] [-c instance_name]
```

From the From the Oracle Connection Manager Control utility:

```
CMCTL> SET OUTBOUND_CONNECT_TIMEOUT [time]
```

Arguments

time: The outbound connect timeout in seconds. The default is 0.

Example

```
CMCTL> SET OUTBOUND_CONNECT_TIMEOUT 30
CMAN_user.us.example.com parameter outbound_connect_timeout set to 30
The command completed successfully
```

REST API for SET OUTBOUND_CONNECT_TIMEOUT Command

```
POST /set/octo
JSON Payload
{
"outbound_connect_timeout" : "time"
}
```

2.3.18 SET SESSION_TIMEOUT

Use the Oracle Connection Manager Control utility SET SESSION_TIMEOUT command to specify the maximum duration of Oracle Connection Manager sessions.

Purpose

To specify the maximum amount of time for a session of Oracle Connection Manager.



Prerequisites

Oracle Connection Manager must be running.

Syntax

From the operating system:

```
cmctl SET SESSION_TIMEOUT [time] [-c instance_name]
```

From the Oracle Connection Manager Control utility:

```
CMCTL> SET SESSION_TIMEOUT [time]
```

Arguments

time: The session timeout in seconds. The default is 0 (zero), which disables this feature.

Example

```
CMCTL> SET SESSION_TIMEOUT 60
CMAN_user.us.example.com parameter session_timeout set to 60
The command completed successfully
```

REST API for SET SESSION TIMEOUT Command

```
POST /set/mct
JSON Payload
"session timeout" : "time"
```

2.3.19 SET TRACE DIRECTORY

Use the Oracle Connection Manager Control utility SET TRACE DIRECTORY command to designate where Oracle Connection Manager instance trace files are written.



(i) Note

This command works only if you have not enabled Automatic Diagnostic Repository (ADR). The default is for ADR to be enabled.

Purpose

To designate where the trace files for Oracle Connection Manager instances are written.

Prerequisites

Oracle Connection Manager must be running.

Syntax

From the operating system:

```
cmctl SET TRACE_DIRECTORY [directory_path] [-c instance_name]
```



From the Oracle Connection Manager Control utility:

CMCTL> SET TRACE_DIRECTORY [directory_path]

Arguments

directory_path: The location of the trace directory. The default path is <code>ORACLE_HOME/network/trace</code>.

Usage Notes

Use the Show parameters command to determine the trace file locations.

Example

CMCTL> SET TRACE_DIRECTORY /disk1/mpurayat_newtest/oracle/network/trace cman1 parameter trace_directory set to /disk1/mpurayat_newtest/oracle/network/trace

The command completed successfully

2.3.20 SET TRACE LEVEL

Use the Oracle Connection Manager Control utility SET TRACE_LEVEL command to set Oracle Connection Manager instance trace levels.

Purpose

To set the trace level for an Oracle Connection Manager instance.

Prerequisites

Oracle Connection Manager must be running.

Syntax

From the operating system:

```
cmctl SET TRACE_LEVEL [level] [-c instance_name]
```

From the Oracle Connection Manager Control utility:

```
CMCTL> SET TRACE_LEVEL [level]
```

Arguments

level: Specify one of the following log levels:

- off: No tracing. This is the default.
- user: User trace information.
- admin: Administrative trace information.
- support: Oracle Support Services trace information.

Usage Notes

Specify off to capture the minimum amount of trace information. Specify support to capture the maximum amount.

Use the Show parameters command to determine the current trace level.



Example

```
CMCTL> SET TRACE_LEVEL USER
CMAN_user.us.example.com parameter trace_level set to USER
The command completed successfully
```

REST API for SET TRACE_LEVEL Command

```
POST /set/tracelevel
JSON Payload
{
"trace_level" : "level"
}
```

2.3.21 SHOW

Use the Oracle Connection Manager Control utility SHOW command to display the parameters that you can use as arguments for this command.

Purpose

To display a list of parameters that you can use as arguments for the SHOW command. Entering one of these parameters with the command displays the parameter value or values.

Prerequisites

None

Syntax

From the operating system:

```
cmctl SHOW [-c instance_name]
```

From the Oracle Connection Manager Control utility:

```
CMCTL> SHOW
```

Example

```
CMCTL> SHOW

The following operations are available after show

An asterisk (*) denotes a modifier or extended command:

all gateways status

connections parameters version

defaults rules

events services
```

2.3.22 SHOW ALL

Use the Oracle Connection Manager Control utility Show all command to combine and display Show parameters and Show rules command output.

Purpose

To combine and display output from the SHOW PARAMETERS and SHOW RULES commands.



Prerequisites

Oracle Connection Manager must be running.

Syntax

From the operating system:

```
cmctl SHOW ALL [-c instance_name]
```

From the Oracle Connection Manager Control utility:

```
CMCTL> SHOW ALL
```

Example

```
CMCTL> SHOW ALL
listener_address
(address=(protocol=tcp)(host=users.us.example.com)(port=1630))
aso_authentication_filter
                           OFF
connection_statistics
                            OFF
event_group
                           OFF
log_directory
                        /disk1/user_cman_test/oracle/network/log/
log_level
                        SUPPORT
                           256
max_connections
idle_timeout
                             0
                             0
inbound_connect_timeout |
session_timeout
                             0
outbound_connect_timeout
                             0
                           16
max_gateway_processes
min_gateway_processes
                             2
                             4
max_cmctl_sessions
                       /disk1/user_cman_test/oracle/network/trace/
trace_directory
trace_level
                           OFF
trace_timestamp
                            OFF
trace_filelen
                              0
trace_fileno
(rule_list=
(rule=
 (src=*)
 (dst=*)
 (srv=*)
  (act=accept)
The command completed successfully
```

REST API for SHOW ALL Command

GET /show/all



2.3.23 SHOW CONNECTIONS

Use the Oracle Connection Manager Control utility SHOW CONNECTIONS command to display connection information.

Purpose

To display information about specific connections or all connections.

Prerequisites

Oracle Connection Manager must be running.

Syntax

From the operating system:

```
cmctl SHOW CONNECTIONS [information] [in state] [qt time] [from source]
[to destination] [for service] [using gateway process id]
[connect identifier list] [-c instance name]
```

From the Oracle Connection Manager Control utility:

```
CMCTL> SHOW CONNECTIONS [information][in state] [gt time] [from source]
[to destination] [for service] [using gateway_process_id]
[connect_identifier_list]
```

Arguments

information: Specify one of the following values to display information about connections. Information categories include connection identifier, source, destination, service, current state, total idle time, and total elapsed time.

- count: The total number of connections that meet the criteria specified by the other qualifiers. This is the default.
- detail: All information about connections specified by the other qualifiers.

state: Specify one of the following values to specify the connection state:

- idle: Connections that are inactive in the established state.
- connecting: Connections that are in the process of connecting.
- established: Connections that are connected and are transferring data.
- terminating: Connections that are disconnecting.

If you do not specify a state, then SHOW CONNECTIONS defaults to all possible states. If the time qualifier is included under these conditions, then the time specified is the amount of time that has elapsed since a client initiated a connection.



(i) Note

This argument is not supported with Oracle Connection Manager in Traffic Director mode.

time: Use the following format to specify connections greater than the time indicated:



qt[hh:mm:]ss



Note

This argument is not supported with Oracle Connection Manager in Traffic Director mode.

source: Specify one of the following formats to specify the source address:

- from IP
- from hostname
- from subnet

destination: Specify one of the following formats to specify the destination address:

- to IP
- to hostname
- to subnet

service: Use the *service_name* format to request a service:

gateway process id: Use the following format to specify connections that are proxied by the gateway process indicated:

using gateway_process_id

connect_identifier_list: Separate multiple connection identifiers using a space.

Usage Notes

Connections are sorted by gateway process identifier and connection identifier, in ascending order.

Issuing Show Connections without an argument displays all connections.

Examples

The following command displays a detailed description of connections in any state. The elapsed time of the connection must be greater than 1 hour and 30 minutes. The connection source is the specified subnet, and the destination is the specified host name.

```
CMCTL> SHOW CONNECTIONS gt 1:30:00 from 192.0.2.32/24 to host1
```

The following command displays the number of connections proxied by Oracle Connection Manager using the gateway process identifier 0 that have been in the idle state more than 30 minutes:

CMCTL> SHOW idle CONNECTIONS count gt 30:00 using 0

The following command displays a detailed description of connections that are connected to the service sales.us.example.com:

CMCTL> SHOW established CONNECTIONS detail for sales.us.example.com



REST API for SHOW CONNECTIONS Command

```
POST /show/connections
JSON Payload
{
"count" : "[yes | no]",
"in": "[ idle | connecting | established | terminated]",
"gt" : " time elapsed since client connection, [hh:mm:]ss format",
"from" : "[ IP | hostname | subnet]",
"to" : "[ IP | hostname | subnet]",
"for" : "service name",
"using" : " gateway process id",
"connect_ids" : [id1, id2]
}
```

An example to show the established connection details for sales.us.example.com using the json schema is:

```
{
"count": "no",
"state" : "established",
"for" : "sales.us.example.com"
}
```

Additional Statistics Shown in Traffic Director Mode

Each connection to Oracle Connection Manager in Traffic Director mode displays these additional statistics:

- Source Host Name: Host name of the client connection.
- Source Process Id: Process Id of the connected client.
- Source Program Name: The name of the connected client program.
- Destination Hostname: Host name of the database server to which the client is connected through Oracle Connection Manager.
- State: State of the inbound connection with one of the following values
 - THREAD WAIT: Connection is waiting for a worker thread, not seen in dedicated threads mode
 - ACTIVE: Connection is transferring data, occupying the thread
 - IDLE: Connection is established but inactive, can still occupy the thread if tdm_bind_thread=true in cman.ora
- Idle time: Cumulative time in us the connection is in IDLE state.
- Thread Wait time: Cumulative time in \$\mu\$s the connection is in THREAD WAIT state. It is always 0 in dedicated threads mode.
- Active time: Cumulative time in us the connection is in ACTIVE state.
- PRCP State: State of the inbound connection with respect to the Proxy Resident Connection Pool (PRCP) and can be one of the following values
 - WAIT: Connection is waiting for a session from the PRCP



- CHECKED-OUT: Connection is holding an outbound session from PRCP but not making any OCI calls
- ACTIVE: Connection is holding an outbound session from PRCP and busy with OCI calls
- CHECKED-IN: Connection released the CHECKED-OUT session back to the PRCP
- NO STATE: Clients to a service without a configured PRCP configured have this state
- PRCP Wait time, PRCP Checked-out time, and PRCP Active time: Cumulative time in the connection is in PRCP WAIT, CHECKED-OUT, and ACTIVE states. All these three states are zero in case of non-PRCP service.
- Total Session Gets: Total count of PRCP session get requests from this connection. It is always 1 if PRCP is not configured.
- Session Get Hits: Number of times a session is found existing in the PRCP out of all the requests. It is always 0 if PRCP is not configured.

2.3.24 SHOW DEFAULTS

Use the Oracle Connection Manager Control utility SHOW DEFAULTS command to display default parameter settings.

Purpose

To display default parameter settings.

Prerequisites

Oracle Connection Manager must be running.

Syntax

From the operating system:

```
cmctl SHOW DEFAULTS [-c instance_name]
```

From the Oracle Connection Manager Control utility:

CMCTL> SHOW DEFAULTS

Example

```
CMCTL> SHOW DEFAULTS
listener_address
(address=(protocol=tcp)(host=users.us.example.com)(port=1521))
aso_authentication_filter |
                              OFF
connection_statistics
                              OFF
event_group
log_directory
                          /disk1/user_cman_test/oracle/network/log/
log_level
                          SUPPORT
                              256
max_connections
                                0
idle_timeout
                                0
inbound_connect_timeout
session_timeout
                                0
outbound_connect_timeout
                                0
max_gateway_processes
                               16
min_gateway_processes
                                2
max_cmctl_sessions
trace_directory
                            /disk1/user_cman_test/oracle/network/trace/
trace level
                              OFF
trace_timestamp
                              OFF
```



trace	0			
trace	e_filenc			0
The o	command	completed	succe	essfully

REST API for SHOW DEFAULTS Command

GET /show/defaults

2.3.25 SHOW EVENTS

Use the Oracle Connection Manager Control utility SHOW EVENTS command to display events that are currently operating.

Purpose

To display the events that are in operation.

Prerequisites

Oracle Connection Manager must be running.

Syntax

From the operating system:

```
cmctl SHOW EVENTS [-c instance_name]
```

From the Oracle Connection Manager Control utility:

CMCTL> SHOW EVENTS

Example

CMCTL> SHOW EVENTS
Event Groups:
memory_ops
The command completed successfully

2.3.26 SHOW GATEWAYS

Use the Oracle Connection Manager Control utility SHOW GATEWAYS command to display the statuses of gateway processes.

Purpose

To display the current status of a specific gateway process or processes. Statistics displayed include number of active connections, number of peak active connections, total number of connections handled, and number of connections refused.

Prerequisites

Oracle Connection Manager must be running.

Syntax

From the operating system:

cmctl SHOW GATEWAYS [gateway] [-c instance_name]



From the Oracle Connection Manager Control utility:

```
CMCTL> SHOW GATEWAYS [gateway]
```

Arguments

gateway: The identifier of the gateway or gateways whose status to display.

Issuing SHOW GATEWAYS without an argument displays the status of all gateway processes.

Usage Notes

To display multiple gateways, use a space to separate the identifiers when entering the command.

Example

```
CMCTL> SHOW GATEWAYS 1

Gateway ID 1

Gateway state READY

Number of active connections 0

Peak active connections 0

Total connections 0

Total connections refused 0

The command completed successfully
```

REST API for SHOW GATEWAYS Command

```
POST /show/gateways
JSON Payload
{
  "gateway_ids" : [id1, id2.. ]
}
```

2.3.27 SHOW PARAMETERS

Use the Oracle Connection Manager Control utility SHOW PARAMETERS command to display the parameter settings for an instance.

Purpose

To display current parameter settings for an instance.

Prerequisites

Oracle Connection Manager must be running.

Syntax

From the operating system:

```
cmctl SHOW PARAMETERS [-c instance_name]
```

From the Oracle Connection Manager Control utility:

CMCTL> SHOW PARAMETERS



Usage Notes

Several configuration parameters can be dynamically modified using the SET command. Therefore, the information that SHOW PARAMETERS displays might be different from what appears in the cman.ora file.

Example

```
CMCTL> SHOW PARAMETERS
listener_address
(address=(protocol=tcp)(host=users.us.example.com)(port=1630))
aso_authentication_filter | ON
connection_statistics |
event_group | (memory_ops)
log_directory | /disk1/user_cman_test/oracle/network/log/
log_level | GUDDODT
                         SUPPORT
max_connections
idle_timeout
                              0
inbound_connect_timeout
                              0
                              Ω
session_timeout
outbound_connect_timeout
                             Λ
                            16
max_gateway_processes
                             2
min_gateway_processes
                              4
max_cmctl_sessions
trace_directory
                       /disk1/user_cman_test/oracle/network/trace/
trace_level
                         SUPPORT
                            OFF
trace_timestamp
trace_filelen
                              0
trace_fileno
                              0
The command completed successfully
```

REST API for SHOW PARAMETERS Command

GET /show/parameters

2.3.28 SHOW RULES

Use the Oracle Connection Manager Control Utility ${\tt SHOW}$ RULES command to display an instance access control list.

Purpose

To display the access control list currently used by the instance.

Prerequisites

Oracle Connection Manager must be running.

Syntax

From the operating system:

```
cmctl SHOW RULES [-c instance_name]
```

From the Oracle Connection Manager Control utility:

CMCTL> SHOW RULES



```
cmctl SHOW RULES [-c instance_name]
```

From the Oracle Connection Manager Control utility:

CMCTL> SHOW RULES

Usage Notes

You can update the rules list by issuing the RELOAD command.

Example

```
CMCTL> SHOW RULES
Number of filtering rules currently in effect: 5
(rule_list=
  (rule=
    (src=usunnae12)
    (dst=usunnae13)
    (srv=*)
    (act=accept)
    (action_list=(mit=120)(mct=1800)(conn_stats=on)(aut=off))
  (rule=
    (src=usunnae12)
    (dst=usunnae14)
    (srv=service2)
    (act=accept)
  (rule=
    (src=*)
    (dst=usunnae15)
    (srv=*)
    (act=accept)
    (action_list=(mit=120)(mct=3000)(moct=200)(aut=on))
  (rule=
    (src=*)
    (dst=usunnae16)
    (srv=*)
    (act=reject)
    (action_list=(moct=20)(aut=on))
  (rule=
    (src=users.us.example.com)
    (dst=users.us.example.com)
    (srv=cmon)
    (act=accept)
    (action_list=(mit=100)(mct=1130)(moct=200)(aut=on))
```

REST API for SHOW RULES Command

GET /show/rules



2.3.29 SHOW SERVICES

Use the Oracle Connection Manager Control utility SHOW SERVICES command to display Oracle Connection Manager instance information.

Purpose

To display comprehensive information about Oracle Connection Manager instances. The information displayed includes the number of handlers for the gateway and CMADMIN processes, listening ports of handlers, and the number of connections, both refused and current.

Prerequisites

Oracle Connection Manager must be running.

Syntax

From the operating system:

```
cmctl SHOW SERVICES [-c instance_name]
```

From the Oracle Connection Manager Control utility:

CMCTL> SHOW SERVICES

Example

```
CMCTL> SHOW SERVICES
Services Summary...
Proxy service "cmgw" has 1 instance(s).
  Instance "cman", status READY, has 2 handler(s) for this service...
   Handler(s):
      "cmgw001" established:0 refused:0 current:0 max:256 state:ready
         <machine: user-sun, pid: 29190>
         (ADDRESS=(PROTOCOL=tcp)(HOST=user-sun)(PORT=33175))
      "cmgw000" established:0 refused:0 current:0 max:256 state:ready
         <machine: user-sun, pid: 29188>
         (ADDRESS=(PROTOCOL=tcp)(HOST=user-sun)(PORT=33174))
Service "cmon" has 1 instance(s).
  Instance "cman", status READY, has 1 handler(s) for this service...
    Handler(s):
      "cmon" established:0 refused:0 current:0 max:4 state:ready
         <machine: user-sun, pid: 29184>
         (ADDRESS=(PROTOCOL=tcp)(HOST=users)(PORT=33168))
The command completed successfully
```

REST API for SHOW SERVICES Command

GET /show/services



2.3.30 SHOW STATS

Use the Oracle Connection Manager Control utility SHOW STATS command with the -REG option to display statistics about database service registration commands.

Purpose

To display statistics about the number of registration commands that the Oracle Connection Manager (CMAN) listener receives while handling client connection requests.

Using these statistics, you can monitor service registration or service update operations, such as REGISTER, UPDATE, RE-REGISTER, and UN-REGISTER. This also helps you evaluate the traffic and overhead of these operations at CMAN.

Prerequisites

CMAN must be running.

Syntax

From the operating system:

cmctl SHOW STATS -REG

From the Oracle Connection Manager Control (CMCTL) utility:

CMCTL> SHOW STATS -REG

Usage Notes

- In addition to CMCTL, you can run this command from the Listener Control (LSNRCTL) utility.
- If you enter SHOW STATS -REG without any argument, then the output displays a global-level data for all instances, registered services, handlers allocated to each service, listening endpoints, and access control lists (ACLs).
- Recent count is a periodic count of all commands received by the listener from the last reset, that is, from the time you cleared the Recent section using -clear. If you have not used -clear till now, then this field displays a cumulative count (total number of commands collected since the CMAN instance started).

For a detailed description about other sections of the output, see *Oracle AI Database Net Services Administrator's Guide*.



Arguments and Examples

Argument and Description	Example						
To display a recent and cumulative count of all registration commands at a global level:	CMCTL:cman1> s		_				
-req	Global Level:						
3	Recent						
	Recent Duratio	n · 5		r 15	min 2F	5 000	
			Service				
	Registration Updates Re-Register	2	Δ	۸	10	0	
	Opuaces	2	2	0	12	0 0	
	Re-Register	0	0	0	0	0	
	Un-Register	U	Cumulat			0	
	Danishustian	2				0	
	Registration	3	3	3	1.0	0	
	Updates						
	Re-Register					0	
	Un-Register		0	-	0	0	
	The command co	mplet	ed succes	stull	У		
To display a recent and cumulative count of all registration commands for the specified instance name:	CMCTL:cman1> s			-ins	t sales1	L	
-inst instance_name			Recent				
	Recent Duratio	n: 5 o	davs 15 h	r. 17	min. 18	3 sec	
	Command Instance Service ENDP Handler INF						
	Registration					0	
	Updates					0	
	Re-Register						
	Un-Register					0	
		-	Cumulati		•	•	
	Registration	2			4	0	
	Registration Updates	3	3	0	12	0	
	Re-Register	0	0	3	0	0	
	Un-Register		0	0	0	0	
	The command co					•	
	TITE COMMUNICITY CC	which	ca bucces	DIUII	1		



Argument and Description	Example					
To display a recent and cumulative count of registration commands for all instances:						
-all_inst	Instance Name					
	Tibediec Name	bal	Recen	t		
	Recent Durati	on: 5	days	15 hr.	3 min. 2	sec
					Handler	
	Registration	1	1	1	2	0
	Updates	21	0	0	5	0
	Re-Register		0	0		0
	Un-Register	0	0	0	0	0
	Danistustian	1		ative	4	0
	Registration	1 25	1 0	1 2	4 5	0
	Updates Re-Register		3	0		0
	Un-Register		0	0	0	0
				-	-	•
	Instance Name	: sale	es2			
			Recen	t		
	Recent Durati					
					Handler	
	Registration			1	2	0
	Updates			0		0
	Re-Register		1	0	0	0
	Un-Register	0	0	0 ative	0	0
	Registration	1	1	acive 1	3	0
	Updates	10	0	2	5	0
	Re-Register	0	3	0	0	0
	Un-Register	0	0	0	0	0
	The command o	comple	ed su	ccessfu	lly	
To display a recent and cumulative count of all registration commands for the specified service name:	CMCTL:cman1>			-reg -s	erv sale	s.us.example.com
	Service Name: sales.us.example.com					
-serv service_name	Recent Durati		_			
			•	Goodnes		a
	Recent Cumulative	0		0	0	
	The command of		-ad en			
	THE COMMAND C	.ompic	.ca sa	CCCBBIU	y	
To display a recent and cumulative count of registration commands for all database services:	CMCTL:cman1>	show :	stats	-reg -a	ll_serv	
-all_serv	Service Name:	sale	s.us.e	xample.	com	
	Recent Duration: 5 days 15 hr. 5 min.					5 sec
		Flag		Goodnes		
	Recent	1		2	0	
	Cumulative	2		0	0	
	Service Name: Recent Durati	on: 8	oyee.u days gs	2 hr. 5 Goodnes	min. 25 s Delt	
	Recent	1		0	0	
	Cumulative	1	,	0	0	
	The command o	omple	ed su	ccessiu	тту	



Argument and Description	Example					
To reset the Recent section to 0 after fetching the values:	CMCTL:cman1> s	show :	stats -	reg -cl	ear	
-clear	Global Level:					
This gives you a fresh set of data in the Recent section. You can use -clear with all the SHOW STATS arguments.	Recent Duration Command Instruction Registration Updates Re-Register Un-Register	on: 0	e Servi 0 0		min. 4 : Handle: 0 0 0 0	
	Cumulative					
	Registration	3	3	3	6	0
	Updates	4	0	0	13	0
	Re-Register	1	0	0	0	0
	Un-Register	0	1	0	0	0
	The command co	omple	ted suc	cessful	ly	

Related Topics

Oracle Al Database Net Services Administrator's Guide

2.3.31 SHOW STATUS

Use the Oracle Connection Manager Control utility SHOW STATUS command to display Oracle Connection Manager instance information.

Purpose

To display basic information about the instance, including version, start time, and current statistics.

Prerequisites

Oracle Connection Manager must be running.

Syntax

From the operating system:

cmctl SHOW STATUS

From the Oracle Connection Manager Control utility:

CMCTL> SHOW STATUS

Example



Trace Level OFF
Instance Config file /diskl/user_cman_test/oracle/network/admin/cman.ora
Instance Log directory /diskl/user_cman_test/oracle/network/log/
Instance Trace directory /diskl/user_cman_test/oracle/network/trace/
The command completed successfully

REST API for SHOW STATUS Command

GET /show/status

2.3.32 SHOW VERSION

Use the Oracle Connection Manager Control utility SHOW VERSION command

Purpose

To display the current version and name of the Oracle Connection Manager Control utility.

Prerequisites

None

Syntax

From the operating system:

cmctl SHOW VERSION [-c instance_name]

From the Oracle Connection Manager Control utility:

CMCTL> SHOW VERSION

Examples

CMCTL> SHOW VERSION
CMAN for Linux: Version 23.4.0.0.0
The command completed successfully

REST API for SHOW VERSION Command

GET /show/version

2.3.33 SHUTDOWN

Use the Oracle Connection Manager Control utility SHUTDOWN command to shut down gateway processes or an entire Oracle Connection Manager instance.

Purpose

To shut down specific gateway processes or the entire Oracle Connection Manager instance.

Prerequisites

Oracle Connection Manager must be running.



Syntax

From the operating system:

cmctl SHUTDOWN [gateways gateway] [normal | abort] [timeout value] [notify] [c instance_name]

From the Oracle Connection Manager Control utility:

CMCTL> SHUTDOWN [gateways gateway] {normal | abort} [timeout value] [notify]

Arguments

gateways: To shut down a specific gateway. To specify more than one gateway, separate gateways using a space.

normal: To reject new connections and terminate after existing connections close. This is the default.

abort: To shut down Oracle Connection Manager immediately, and close all open connections.

timeout value: To specify the amount of time in seconds that Oracle Connection Manager must wait before shutting down.

notify: To notify the client that Oracle Connection Manager is shutting down.

Usage Notes

Running the SHUTDOWN command without an argument shuts down all of the gateways.

Examples

CMCTL> SHUTDOWN GATEWAYS 0
CMCTL> SHUTDOWN ABORT
CMCTL> SHUTDOWN NOTIFY

2.3.34 STARTUP

Use the Oracle Connection Manager Control utility STARTUP command to start Oracle Connection Manager.

Purpose

To start Oracle Connection Manager.

Prerequisites

Another Oracle Connection Manager instance configured with the same protocol address must not be running.

Syntax

From the operating system:

cmctl STARTUP [-c instance_name]



From the Oracle Connection Manager Control utility:

CMCTL> STARTUP

Usage Notes

 Before running this command, you must use the ADMINISTER command to select an instance to start.

Issuing this command starts all instance components, which are the listener, CMADMIN, and the gateway processes. The command fails if any one of these components is already running.

 The use of password access to Oracle Connection Manager parameters is desupported in Oracle AI Database 26ai.

Oracle provides an enhanced connection method, Local Operating System Authentication" (LOSA), which permits only the user who started CMAN to perform admin operations. This method is consistent with other operating system authentication methods used with Oracle Database. If you are currently using password access to CMAN, then Oracle recommends that you remove the CMAN password, and instead rely on LOSA.

Example

```
CMCTL> STARTUP
Starting Oracle Connection Manager instance cman_1. Please wait...
CMAN for Linux: Version 23.4.0.0.0
Status of the Instance
_____
Instance name
                      cman 1
Version
                       CMAN for Linux: Version 23.4.0.0.0
Start date
                      22-Feb-2024 01:16:55
                       0 days 0 hr. 0 min. 9 sec
Uptime
Num of gateways started 8
Average Load level 0
                      SUPPORT
Log Level
                       OFF
Trace Level
Instance Config file $ORACLE_HOME/network/admin/cman.ora
Instance Log directory $ORACLE BASE/diag/netcman/node_name/cman_1/alert
Instance Trace directory $ORACLE_BASE/diag/netcman/node_name/cman_1/trace
The command completed successfully
```

STARTUP - MIGRATE

Use the STARTUP -MIGRATE parameter to start Oracle Connection Manager (CMAN) in migration mode. Youcan start a new instance of CMAN in migration mode, and migrate connected sessions from the already running instance of Oracle CMAN.

Prerequisites

A CMAN instance with the same configuration as the new instance must be running in a different <code>ORACLE_HOME</code> on the same host where the new CMAN is being started.

Syntax

From the operating system:

```
cmctl STARTUP -MIGRATE [-c instance_name]
```



Usage Notes

This command starts new instance components, such as, the listener, CMADMIN, and the gateway processes.

The new listener inherits the listening endpoints and the listen queue from the old listener. It also accepts new connection requests.

The old gateway processes migrate the connected sessions to new gateways. This migration happens without the client or the server intervention.

The old listener exits after processing the pending connections. The old instance, CMADMIN, and the gateway processes will exit as soon as migration is complete or after 7 minutes timeout.

Use instance_name_old as the instance name to monitor the old instance.

Example

```
CMCTL STARTUP -MIGRATE -C cman_1
CMCTL for Linux: Version 23.4.0.0.0
Copyright (c) 1996, 2024, Oracle. All rights reserved.
Current instance cman_1_ is already started
Connecting to (DESCRIPTION=(address=(protocol=tcp)(host=localhost)
(port=2556)))
CMAN Session Migration Stats
No of Gateways
Total Connections
TCP Connections
TCPS Connections(Migratable)
Starting CMAN Session Migration....
-----
Old CMADMIN address alias parameter cman_1_old set to
(configuration=(ADDRESS=(PROTOCOL=ipc)(KEY="#124470.1")
(KEYPATH=/var/tmp/.oracle_754500)))
Starting Oracle Connection Manager instance cman 1. Please wait...
CMAN for Linux: Version 23.4.0.0.0 - Development
Status of the Instance
_____
Instance name cman_1
                       CMAN for Linux: Version 23.4.0.0.0
Version
Start date
                       27-FEB-2024 05:31:03
                       0 days 0 hr. 0 min. 9 sec
Uptime
Num of gateways started 1
Average Load level 0
                      SUPPORT
Log Level
Trace Level
                       SUPPORT
Instance Config file /network/admin/cman.ora
Instance Log directory $ORACLE BASE/diag/netcman/node name/cman 1/alert
Instance Trace directory $ORACLE_BASE/diag/netcman/node_name/cman_1/trace
The command completed successfully.
Now session migration will be initiated by gateways separately....
```



2.3.35 SUSPEND GATEWAY

Use the Oracle Connection Manager Control utility SUSPEND GATEWAY command to specify the gateway processes than cannot accept new client connections.

Purpose

To specify which gateway processes will no longer accept new client connections.

Prerequisites

Oracle Connection Manager must be running.

Syntax

From the operating system:

```
cmctl SUSPEND GATEWAY [gateway_process_id] [-c instance_name]
```

From the Oracle Connection Manager Control utility:

```
CMCTL> SUSPEND GATEWAY [gateway_process_id]
```

Arguments

gateway_process_id: The gateway process that will no longer accept new connections. Specify multiple gateway processes by entering a space between entries.

Issuing Suspend Gateway without an argument suspends all gateway processes.

Usage Notes

Use the RESUME GATEWAYS command to enable gateway processes to accept new connections.

Example

```
CMCTL> SUSPEND GATEWAY 1
The command completed successfully
```

REST API for SUSPEND GATEWAY Command

```
POST /suspend
{
    "gateway" : "gateway id"
}
```

Syntax Rules for Configuration Files

Learn the syntax rules for configuring Oracle Net Services parameters, keywords, addresses, and naming methods.

- Overview of Configuration File Syntax
 Create Oracle Net Services configuration files using syntax rules and standard conventions.
- Syntax Rules for Configuration Files
 Follow the structure, hierarchy, and character requirements for configuration files.
- <u>Network Character Set for Keywords</u>
 Use the permitted character set for keyword values and network character sets.
- Permitted Listener and Net Service Name Character Set
 Create listener names and net service names for clients that comply with Oracle Net Services character set requirements.

3.1 Overview of Configuration File Syntax

Create Oracle Net Services configuration files using syntax rules and standard conventions.

The Oracle Net Services configuration files contain parameters that include keyword-value pairs. Keyword-value pairs are surrounded by parentheses:

```
parameter=(keyword=value)
```

Some keywords have other keyword-value pairs as their values:

```
(keyword=
     (keyword1=value1)
     (keyword2=value2))
```

For example, the address portion of the local naming configuration file (tnsnames.ora) can include lines such as:

```
(ADDRESS=
    (PROTOCOL=tcp)
    (HOST=sales-server)
    (PORT=1521))
```

Set up your configuration files using indentation to show what keyword is the parent or owner of other keyword-value pairs. If you do not indent your files this way, then you must still indent a wrapped line by at least one space, or it will be misread as a new parameter. The following syntax is acceptable:

```
(ADDRESS=(PROTOCOL=tcp)
  (HOST=sales-server)(PORT=1521))
```



The following syntax is not acceptable:

```
(ADDRESS=(PROTOCOL=tcp)
(HOST=sales-server)(PORT=1521))
```

3.2 Syntax Rules for Configuration Files

Follow the structure, hierarchy, and character requirements for configuration files.

The following rules apply to the configuration file syntax:

- Any keyword in a configuration file that begins a parameter that also includes one or more keyword-value pairs must be in the far-left column of a line. If you indent the keyword by one or more spaces, then Oracle interprets the indented keyword as a continuation of the previous line.
- All characters must be part of the network character set.
- Keywords are not case-sensitive. However, values can be case-sensitive depending on your operating system and protocol.
- In keyword-value pairs, spaces around the equal sign (=) are optional.
- There is a hierarchy of keywords that requires that some keywords are always followed by others. At any level in the hierarchy, keywords can be listed in any order. For example, the following entries are equally valid:

```
(ADDRESS=
  (PROTOCOL=TCP)
  (HOST=sales-server)
  (PORT=1521))

(ADDRESS=
  (PROTOCOL=tcp)
  (PORT=1521)
  (HOST=sales-server))
```

- Keywords cannot contain spaces.
- Values must not contain spaces, unless the values with spaces are enclosed within double guotation marks (") or single quotation marks (').
- If the keyword-value pair consists of a single word, or a concatenation of words on either side of the equal sign, then no parentheses are needed.
- The maximum length of a connect descriptor is 4KB.
- You can include comments by using the number sign (#) at the beginning of a line.
 Anything following the number sign to the end of the line is considered a comment.

3.3 Network Character Set for Keywords

Use the permitted character set for keyword values and network character sets.



The network character set for keyword values consists of the following characters. Connect descriptors must be made up of single-byte characters.

```
A-Z, a-Z
0-9
( ) < > / \
, . : ; ' "=- _
$ + * # & ! % ? @
```

Within this character set, the following symbols are reserved:

```
( ) = \ " ' #
```

Reserved symbols are used as delimiters, not as part of a keyword or a value, unless the keyword or value has quotation marks. If you have a value that contains reserved symbols, then use either single or double quotation marks to enclose the value. To include quotation marks within a value that is surrounded by quotation marks, use different quotation marks. The backslash (\) is used as an escape character.

You can use the following characters within a connect descriptor, but not in a keyword or value:

- Space
- Tab
- Carriage return
- Newline

3.4 Permitted Listener and Net Service Name Character Set

Create listener names and net service names for clients that comply with Oracle Net Services character set requirements.

Listener names and net service names are limited to the following character set:

```
[a...z] [A...Z] [0...9] _
```

The first character in the listener name or net service name must be an alphanumeric character. In general, names up to 64 characters are acceptable. In addition, a database service name must match the global database name that is defined by the database administrator, which consists of a database name and the database domain. Both net service names and global database names are not case-sensitive.

Protocol Address Configuration

Learn how to configure connections for Oracle Database instances and clients.

A network object is identified by a protocol address. When a connection is made, the client and the receiver of the request (a listener or Oracle Connection Manager) are configured with identical protocol addresses. The client uses this address to send the connection request to a particular network object location. The recipient "listens" for requests on this address, and grants connections based on its address information matching the client's information.

Protocol Addresses

The protocol address comprises ADDRESS and ADDRESS_LIST elements.

Protocol Parameters

The listener and Oracle Connection Manager are identified by protocol addresses.

Recommended Port Numbers

Oracle recommends that you use the default port numbers for client and Oracle Connection Manager connections.

Port Number Limitations

Use this procedure to configure listeners to use a system port number in the 1 to 1024 range.

4.1 Protocol Addresses

The protocol address comprises ADDRESS and ADDRESS LIST elements.

• ADDRESS

The ADDRESS networking parameter specifies the protocol address under the ADDRESS_LIST or DESCRIPTION parameter.

ADDRESS LIST

The ADDRESS_LIST networking parameter specifies the number of protocol addresses sharing common characteristics.

4.1.1 ADDRESS

The ADDRESS networking parameter specifies the protocol address under the ADDRESS_LIST or DESCRIPTION parameter.

Purpose

To define a protocol address.

Usage Notes

Put this parameter under an ADDRESS_LIST or DESCRIPTION parameter. A DESCRIPTION is used in a tnsnames.ora or a listener.ora file.



Example

```
(ADDRESS=
  (PROTOCOL=tcp)
  (HOST=sales-server)
  (PORT=1521))
```

Related Topics

- Protocol Parameters
 - The listener and Oracle Connection Manager are identified by protocol addresses.
- Oracle Al Database Global Data Services Concepts and Administration Guide

4.1.2 ADDRESS_LIST

The ADDRESS_LIST networking parameter specifies the number of protocol addresses sharing common characteristics.

Purpose

To define a list of protocol addresses that share common characteristics.

Usage Notes

This parameter is not mandatory when specifying multiple addresses.

Example

```
(ADDRESS_LIST=
  (LOAD_BALANCE=on)
  (ADDRESS=
     (PROTOCOL=tcp)
     (HOST=sales-server)
     (PORT=1521))
  (ADDRESS=
     (PROTOCOL=tcp)
     (HOST=hr-server)
     (PORT=1521)))
```

4.2 Protocol Parameters

The listener and Oracle Connection Manager are identified by protocol addresses.

The following table lists the parameters that Oracle protocol support uses:

Table 4-1 Protocol-Specific Parameters

B		Post factors
Protocol	Parameter	Description
IPC	PROTOCOL	Specify ipc as the value.



Table 4-1 (Cont.) Protocol-Specific Parameters

Protocol	Parameter	Description
IPC	KEYPATH	On UNIX variants, the IPC protocol uses the UNIX domain socket and this socket creates an internal file for client/server communication. The parameter <code>keypath</code> specifies the location where this file is created. If you use <code>keypath</code> , then use the same value of a version greater than 18 on the client and listener sides.
IPC	KEY	Specify a unique name for the service. Oracle recommends using the service name or the Oracle system identifier (SID) of the service. Example:
		(PROTOCOL=ipc)(KEY=sales)
Named Pipes	PROTOCOL	Specify nmp as the value.
Named Pipes	SERVER	Specify the Oracle server name.
Named Pipes	PIPE	Specify the pipe name used to connect to the database server. This is the same PIPE keyword specified on the server with Named Pipes. This name can be any name. Example:
		(PROTOCOL=nmp)(SERVER=sales)(PIPE=dbpipe0)
SDP	PROTOCOL	Specify sdp as the value.
SDP	HOST	Specify the host name or IP address of the computer.
SDP	PORT	Specify the listening port number. Example:
		(PROTOCOL=sdp)(HOST=sales-server)(PORT=1521) (PROTOCOL=sdp)(HOST=192.0.2.204)(PORT=1521)
TCP/IP	PROTOCOL	Specify top as the value.
TCP/IP	HOST	Specify the host name or IP address of the computer.
TCP/IP	PORT	Specify the listening port number. Example:
		(PROTOCOL=tcp)(HOST=sales-server)(PORT=1521) (PROTOCOL=tcp)(HOST=192.0.2.204)(PORT=1521)
TCP/IP with TLS	PROTOCOL	Specify tcps as the value.
TCP/IP with TLS	HOST	Specify the host name or IP address of the computer.
TCP/IP with TLS	PORT	Specify the listening port number. Example:
		(PROTOCOL=tcps)(HOST=sales-server)(PORT=2484) (PROTOCOL=tcps)(HOST=192.0.2.204)(PORT=2484)
Exadirect	PROTOCOL	Specify exadirect as the value.
Exadirect	HOST	Specify the IP address of the InfiBand interface.



Table 4-1 (Cont.) Protocol-Specific Parameters

Protocol	Parameter	Description
Exadirect	PORT	Specify the listening port number. Example:
		(PROTOCOL=exadirect)(HOST=sales-server)(PORT=2484) (PROTOCOL=tcps)(HOST=192.0.2.204)(PORT=1522)
Websocket	PROTOCOL	Specify \ensuremath{ws} as the value; use this protocol only as a web server back-end database server.
Websocket	HOST	Specify the host name or IP address of the computer.
Websocket	PORT	Specify the listening port number.
		Example:
		(protocol=ws)(host=sales-server)(port=1524)
Secure Websocket	PROTOCOL	Specify ws as the value; use this protocol on the client side to connect to a web server with websocket protocol support. Configure the web server to make a websocket connection to the database listener. Configure the wallet in sqlnet.ora.
		Use SQLNET.URI for mapping on web server.
Secure Websocket	HOST	Specify the host name or IP address of the web server with websocket support.
Secure Websocket	PORT	Specify the listening port number.
		Example:
		(protocol=wss)(host=sales-server)(port=1524)

4.3 Recommended Port Numbers

Oracle recommends that you use the default port numbers for client and Oracle Connection Manager connections.

Table 4-2 Recommended Port Numbers

Port	Description
1521	Default listening port for client connections to the listener.
	This port number can change to the officially registered port number of 2483 for TCP/IP, and 2484 for TCP/IP with TLS.
1521	Default and officially registered listening port for client connections to Oracle Connection Manager.
1830	Default and officially registered listening port for administrative commands to Oracle Connection Manager.

4.4 Port Number Limitations

Use this procedure to configure listeners to use a system port number in the 1 to 1024 range.

Oracle accepts port numbers from 1 to 65535. However, port numbers below 1024 are typically reserved. Only privileged processes can listen for TCP connections on ports below 1024.

To configure a listener to listen on a port number lower than 1024, complete the following procedure:



(i) Note

This procedure is a guideline. Your operating system can require a different procedure.

- 1. Use Oracle Net Configuration Assistant or Oracle Net Manager to configure the listener with protocol addresses and other configuration parameters.
- 2. Log in as the root user on the machine that has the listener.
- 3. Set file ownership and access permissions for the listener executable (tnslsnr) and the dependent shared libraries, so that these files can be modified only by the root user.
- **4.** Starting with the root directory, ensure that the permissions of the individual directories in the path names to these files share the same ownership and access permissions.
- 5. Start the listener as the root user.
- 6. Enter the following command at the prompt:

```
tnslsnr listener name -user user -group group
```

In the preceding command, the following options are used:

Table 4-3 tnslsnr Utility Options

Options	Description
listener_name	Specify the name of the listener to configure. If omitted, then the default name LISTENER is used.
user	Specify the user whose privileges you want the listener to use when super user (root) privileges are not needed. After performing the privileged operations, the listener gives up root privileges irreversibly.
group	Specify the group whose privileges you want the listener to use when super user (root) group privileges are not needed. After performing the privileged operations, the listener gives up root group privileges irreversibly.

During this step, the listener changes from root to the user and group privileges that you specify. All operations are done with the specified user and group privileges, except for the issuing of the system calls that are needed to listen on configured endpoints. The listener reverts to the root user to listen on reserved addresses, such as TCP port numbers that are lower than 1024.

After the listener starts listening on all of its endpoints that you configured in the <code>listener.ora</code> file, it permanently switches to the specified user and group. At that point, the listener gives up the <code>root</code> privilege that it initially had. The <code>-user</code> and <code>-group</code> command line arguments only accept user and group identifiers specified in numeric form.

For example, to run a listener called mylsnr with root privileges, and to have it use privileges of the Oracle user with the user identifier (UID) of 37555, and with OSDBA group dba membership, with a group identifier (GID) of 16, enter the following command at the prompt:

tnslsnr mylsnr -user 37555 -group 16

After the listener starts, you can administer it with Listener Control utility.



△ Caution

- Oracle recommends that the user under whose privileges the listener process runs is the oracle user, or a similarly privileged user with whose privileges the listener process normally runs on the operating system.
- Do not leave the listener process running as the root user. Running processes as the super user is a security risk.

Parameters for sqlnet.ora Files

This chapter describes the sqlnet.ora file parameters.

- Overview of Profile Configuration Files
 Learn about profile configuration files.
- Profile Parameters in sqlnet.ora Files

These are the sqlnet.ora profile configuration parameters that you use to administer database clients and servers.

- ADR Diagnostic Parameters in sqlnet.ora
 Diagnostic data for critical errors is stored in the sqlnet.ora Automatic Diagnostic Repository (ADR).
- Non-ADR Diagnostic Parameters in sqlnet.ora Files
 Learn about sqlnet.ora parameters that you use when you disable ADR.

5.1 Overview of Profile Configuration Files

Learn about profile configuration files.

The sqlnet.ora file is the Net Services profile configuration file. The sqlnet.ora file resides on clients and databases. You store and implement profiles using this file. You can also configure the database with access control parameters in the sqlnet.ora file. These parameters specify whether clients are allowed or denied access to a database based on the parameter settings.

The sqlnet.ora file enables you to:

- Specify the client domain to append to unqualified names
- Prioritize naming methods
- Enable logging and tracing features
- Route connections through specific processes
- Configure parameters for external naming
- Configure Oracle Advanced Security
- Use protocol-specific parameters to restrict access to the database

Oracle Net searches for the sqlnet.ora file in the following locations and in the following order:

- In the directory specified in the TNS ADMIN environment variable, if it is set.
- In the ORACLE_BASE_HOME/network/admin directory.
- In the ORACLE HOME/network/admin directory.



(i) Note

- The settings in the sqlnet.ora file apply to all pluggable databases (PDBs) in multitenant container database environments.
- Oracle Net Services supports the IFILE parameter in the sqlnet.ora file, with up
 to three levels of nesting. The parameter is added manually to the file. The
 following is an example of the syntax:

```
IFILE=/tmp/listener_em.ora
IFILE=/tmp/listener_cust1.ora
IFILE=/tmp/listener_cust2.ora
```

Refer to Oracle Database Reference for additional information.

- With Oracle Instant Client, the sqlnet.ora file is located in the subdirectory of the Oracle Instant Client software. For example, in the /opt/oracle/ instantclient_release_number/network/admin directory.
- In the read-only Oracle home mode, the sqlnet.ora file default location is ORACLE BASE HOME/network/admin.
- In the read-only Oracle home mode, the parameters are stored in the ORACLE_BASE_HOME location by default.

5.2 Profile Parameters in sqlnet.ora Files

These are the sqlnet.ora profile configuration parameters that you use to administer database clients and servers.

Note

Starting with Oracle AI Database 26ai, the parameter ENCRYPTION_WALLET_LOCATION is desupported.

To store and retrieve the TDE wallet, use the WALLET_ROOT structure (introduced with Oracle Database 18c).

The WALLET_ROOT parameter is described in *Oracle AI Database Transparent Data Encryption Guide*.

ACCEPT_MD5_CERTS

The sqlnet.ora profile parameter ACCEPT_MD5_CERTS accepts MD5 signed certificates.

ACCEPT SHA1 CERTS

Use the sqlnet.ora profile parameter ACCEPT_SHA1_CERTS to determine whether SQL Net accepts SHA1 signed certificates.

ALLOWED WEAK CERT ALGORITHMS

Use the sqlnet.ora parameter ALLOWED_WEAK_CERT_ALGORITHMS to allow the use of deprecated certification algorithms as an exception.



AZURE DB APP ID URI

Use the AZURE_DB_APP_ID_URI parameter to specify the application ID URI of the Oracle Database instance, registered with Microsoft Entra ID (previously called Microsoft Azure Active Directory).

BEQUEATH DETACH

Use the sqlnet.ora parameter to enable and disable handling signals on Linux and UNIX systems.

CLIENT CERTIFICATE

Use the CLIENT_CERTIFICATE parameter to specify the file system path to a client certificate that authenticates your database client application.

CLIENT ID

Use the CLIENT_ID parameter to specify the ID of the database client Microsoft Entra ID app registration.

EXADIRECT FLOW CONTROL

The sqlnet.ora profile parameter EXADIRECT_FLOW_CONTROL enables or disables Exadirect flow control.

EXADIRECT RECVPOLL

Use the sqlnet.ora parameter <code>EXADIRECT_RECVPOLL</code> to specify the amount of time that a receiver polls for incoming data.

DEFAULT SDU SIZE

Use the sqlnet.ora profile parameter to specify the session data unit size (SDU) for connections.

DISABLE INTERRUPT

Use the sqlnet.ora profile parameter DISABLE_INTERRUPT to disable Oracle Net handling of a SIGINIT signal in client applications.

DISABLE OOB

Use the sqlnet.ora profile parameter DISABLE_OOB to enable or disable Oracle Net to send or receive out-of-band break messages using urgent data from the underlying protocol.

DISABLE OOB AUTO

Use the sqlnet.ora profile parameter DISABLE_OOB_AUTO to disable server path checks for out-of-band break messages at the time of the connection.

IPC.KEYPATH

Use the sqlnet.ora profile parameter IPC.KEYPATH to specify the destination directory where the internal file is created for UNIX domain sockets.

KERBEROS5 PRINCIPAL

Use the $\tt KERBEROS5_PRINCIPAL$ parameter to set the Kerberos principal name associated with the Kerberos credentials cache (CC) file.

MAX CONDUITS

Use the sqlnet.ora parameter MAX_CONDUITS to specify the maximum number of conduits between the listener and the broker or dispatcher for handing off client connections.

NAMES.DEFAULT DOMAIN

Use the sqlnet.ora profile parameter NAMES.DEFAULT_DOMAIN to set the name of the domain in which clients most often look up names resolution requests.

• NAMES.DIRECTORY PATH

Use the sqlnet parameter NAMES.DIRECTORY_PATH to specify the order of the naming methods for client name resolution lookups.



NAMES.LDAP AUTHENTICATE BIND

Use the sqlnet parameter NAMES.LDAP_AUTHENTICATE_BIND to specify whether the LDAP naming adapter should authenticate using a specified wallet when it connects to the LDAP directory to resolve connect string names.

NAMES.LDAP AUTHENTICATE BIND METHOD

Use the sqlnet parameter NAMES.LDAP_AUTHENTICATE_BIND_METHOD to specify an authentication method for the client LDAP naming adapter.

NAMES.LDAP CONN TIMEOUT

Use the sqlnet parameter NAMES.LDAP_CONN_TIMEOUT to specify the number of seconds that indicates that a non-blocking connect timeout to the LDAP server occurred.

NAMES.LDAP PERSISTENT SESSION

Use the sqlnet parameter NAMES.LDAP_PERSISTENT_SESSION to specify whether the LDAP naming adapter should leave the session with the LDAP server open after name lookups are complete.

NAMES.NIS.META MAP

Use the sqlnet parameter NAMES.NIS.META_MAP to specify the map file to use to map Network Information Service (NIS) attributes to an NIS mapname.

OCI COMPARTMENT

Use the OCI_COMPARTMENT parameter to specify Oracle Cloud Identifier (OCID) of the compartment that holds database instances for client connections.

OCI CONFIG FILE

Use the OCI_CONFIG_FILE parameter to specify the directory location where the Oracle Cloud Infrastructure (OCI) configuration file is stored.

OCI DATABASE

Use the $\texttt{OCI_DATABASE}$ parameter to specify Oracle Cloud Identifier (OCID) of the database that you want to access for the client connection.

OCI IAM URL

Use the OCI_IAM_URL parameter to specify an endpoint URL that the database client must connect with to get the database token for authenticating Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) users on OCI Database as a Service (DBaaS).

OCI PROFILE

Use the OCI_PROFILE parameter to specify the profile name for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) users.

OCI TENANCY

Use the OCI_TENANCY parameter to specify Oracle Cloud Identifier (OCID) of the user's tenancy.

PASSWORD_AUTH

RECV BUF SIZE

Use the sqlnet parameter RECV_BUF_SIZE to specify buffer space limit for session receive operations.

REDIRECT URI

Use the REDIRECT_URI parameter to specify the redirect URI, registered for your Microsoft Entra ID client application.

SDP.PF_INET_SDP

Use the sqlnet parameter SDP.PF_INET_SDP to specify the protocol family or address family constant for the SDP protocol on your system.



SEC USER AUDIT ACTION BANNER

Use the sqlnet parameter SEC_USER_AUDIT_ACTION_BANNER to specify a text file that contains the banner contents that warn users about user action auditing.

SEC USER UNAUTHORIZED ACCESS BANNER

Use the sqlnet parameter SEC_USER_UNAUTHORIZED_ACCESS_BANNER to specify the file that contains the banner contents that warn users about unauthorized database access.

SEND BUF SIZE

Use the sqlnet parameter $SEND_BUF_SIZE$ to specify the buffer space limit for session send operations.

SEPS WALLET LOCATION

Use the SEPS_WALLET_LOCATION parameter to specify the wallet location for secure external password store (SEPS) and to enable the use of specified wallet for authentication.

SQLNET.ALLOW WEAK CRYPTO

Use the sqlnet.ora compatibility parameter $SQLNET.ALLOW_WEAK_CRYPTO$ to configure your client-side network connection by reviewing the specified encryption and crypto-checksum algorithms.

• SQLNET.ALLOW WEAK CRYPTO CLIENTS

Use the sqlnet.ora compatibility parameter $SQLNET.ALLOW_WEAK_CRYPTO_CLIENTS$ to configure your server-side network connection by reviewing the specified encryption and crypto-checksum algorithms.

SOLNET.ALLOWED LOGON VERSION CLIENT

Use the sqlnet parameter $SQLNET.ALLOWED_LOGON_VERSION_CLIENT$ to define minimum authentication protocols that servers acting as clients to other servers can use for connecting to Oracle Database instances.

SQLNET.ALLOWED LOGON VERSION SERVER

Use the sqlnet.ora parameter $SQLNET.ALLOWED_LOGON_VERSION_SERVER$ to set the minimum authentication protocol that is permitted when connecting to Oracle Database instances.

SOLNET.AUTHENTICATION SERVICES

Use the sqlnet.ora parameter $SQLNET.AUTHENTICATION_SERVICES$ to enable one or more authentication services.

SQLNET.BREAK RESET TIMEOUT

Use the sqlnet.ora parameter SQLNET.BREAK_RESET_TIMEOUT to specify the duration of time that a database client or server should wait for the completion of break/reset operation.

SOLNET.CLIENT REGISTRATION

Use the sqlnet.ora parameter $SQLNET.CLIENT_REGISTRATION$ to set a unique identifier for the client computer.

SQLNET.CLOUD USER

Use the sqlnet.ora parameter SQLNET.CLOUD_USER to specify a user name for web server HTTP basic authentication.

SQLNET.COMPRESSION

Use the ${\tt sqlnet.ora}$ parameter ${\tt SQLNET.COMPRESSION}$ to enable or disable data compression.

SQLNET.COMPRESSION ACCELERATION

Use the sqlnet.ora parameter $SQLNET.COMPRESSION_ACCELERATION$ to specify the use of hardware accelerated version of compression using this parameter if it is available for that platform.



SOLNET.COMPRESSION LEVELS

Use the sqlnet.ora parameter SQLNET.COMPRESSION_LEVELS to specify the compression level.

SQLNET.COMPRESSION THRESHOLD

Use the sqlnet.ora parameter SQLNET.COMPRESSION_THRESHOLD to specify the minimum data size for which compression is needed.

SOLNET.CRYPTO CHECKSUM CLIENT

Use the sqlnet.ora parameter SQLNET.CRYPTO_CHECKSUM_CLIENT to specify the desired data integrity behavior when this client or server acting as a client connects to a server.

SQLNET.CRYPTO CHECKSUM SERVER

Use the sqlnet.ora parameter SQLNET.CRYPTO_CHECKSUM_SERVER to specify the data integrity behavior when a client or another server acting as a client connects to this server.

SQLNET.CRYPTO CHECKSUM TYPES CLIENT

Use the sqlnet.ora parameter SQLNET.CRYPTO_CHECKSUM_TYPES_CLIENT to specify a list of data integrity algorithms that this client or server acting as a client uses.

SQLNET.CRYPTO CHECKSUM TYPES SERVER

Use the sqlnet.ora parameter $SQLNET.CRYPTO_CHECKSUM_TYPES_SERVER$ to specify the data integrity algorithms that this server or client to another server uses, in order of intended use.

SOLNET.DBFW PUBLIC KEY

Use the sqlnet.ora parameter $SQLNET.DBFW_PUBLIC_KEY$ to provide Oracle Database Firewall public keys to the Advanced Security Option (ASO) by specifying the file that stores the public keys.

SOLNET.DOWN HOSTS TIMEOUT

Use the sqlnet.ora parameter $SQLNET.DOWN_HOSTS_TIMEOUT$ to specify the amount of time in seconds that server hosts down state information remains in the client cache.

SOLNET.ENCRYPTION CLIENT

Use the sqlnet.ora parameter $SQLNET.ENCRYPTION_CLIENT$ to set the encryption behavior when this client or server acting as a client connects to a server.

SQLNET.ENCRYPTION SERVER

The sqlnet.ora parameter SQLNET.ENCRYPTION_SERVER specifies the encryption behavior when a client or a server acting as a client connects to this server.

SOLNET.ENCRYPTION TYPES CLIENT

Use the sqlnet.ora parameter $SQLNET.ENCRYPTION_TYPES_CLIENT$ to specify the encryption algorithms this client or the server acting as a client uses.

• <u>SQLNET.ENCRYPTION_TYPES_SERVER</u>

Use the sqlnet.ora parameter $SQLNET.ENCRYPTION_TYPES_SERVER$ to specify the encryption algorithms this server uses in the order of the intended use.

SOLNET.EXPIRE TIME

Use the sqlnet.ora parameter SQLNET.EXPIRE_TIME to specify how often, in minutes, to verify that client and server connections are alive.

SQLNET.IGNORE AND ENCRYPTION FOR TCPS

Use the sqlnet.ora parameter $SQLNET.IGNORE_ANO_ENCRYPTION_FOR_TCPS$ to ignore the value that is set for the parameter $SQLNET.ENCRYPTION_SERVER$ for TCPS connections. This disables ANO encryption on the TCPS listener.

• SQLNET.INBOUND_CONNECT_TIMEOUT

Use the sqlnet.ora parameter $SQLNET.INBOUND_CONNECT_TIMEOUT$ to specify the amount of time that clients have to connect with the database and authenticate.



SOLNET.FALLBACK AUTHENTICATION

Use the sqlnet.ora parameter SQLNET.FALLBACK_AUTHENTICATION to specify whether to attempt password-based authentication if Kerberos authentication fails.

SQLNET.KERBEROS5 CC NAME

Use the sqlnet.ora parameter SQLNET.KERBEROS5_CC_NAME to specify the complete path name to the Kerberos credentials cache (CC) file.

SOLNET.KERBEROS5 CLOCKSKEW

Use the sqlnet.ora parameter SQLNET.KERBEROS5_CLOCKSKEW to specify how much time elapses before a Kerberos credential is considered out-of-date.

SOLNET.KERBEROS5 CONF

Use the sqlnet.ora parameter $SQLNET.KERBEROS5_CONF$ to specify the path name to the Kerberos configuration file that contains the realm for the default Key Distribution Center (KDC) and that maps realms to KDC hosts.

SQLNET.KERBEROS5 CONF LOCATION

Use the sqlnet.ora parameter SQLNET.KERBEROS5_CONF_LOCATION to specify the directory for the Kerberos configuration file. The SQLNET.KERBEROS5_CONF_LOCATION parameter also specifies that the file is created by the system and not by the client.

SQLNET.KERBEROS5 KEYTAB

Use the sqlnet.ora parameter SQLNET.KERBEROS5_KEYTAB to specify the path name to the Kerberos principal or, secret, key mapping file that extracts keys and decrypts incoming authentication information.

SQLNET.KERBEROS5 REALMS

Use the sqlnet.ora parameter SQLNET.KERBEROS5_REALMS to specify the complete path name to the Kerberos realm translation file that maps a host name or domain name to a realm.

SQLNET.OUTBOUND CONNECT TIMEOUT

Use the sqlnet.ora parameter SQLNET.OUTBOUND_CONNECT_TIMEOUT to specify the amount of time, in milliseconds, seconds, or minutes, in which clients must establish Oracle Net connections to database instances.

SQLNET.RADIUS ALLOW WEAK CLIENTS

Use the client-side sqlnet.ora parameter $SQLNET.RADIUS_ALLOW_WEAK_CLIENTS$ to control the transport protocol that the Oracle Database client must use for communicating with the Oracle Database server.

SQLNET.RADIUS ALLOW WEAK PROTOCOL

Use the server-side sqlnet.ora parameter $SQLNET.RADIUS_ALLOW_WEAK_PROTOCOL$ to allow weak Oracle Database clients to use RADIUS authentication.

SQLNET.RADIUS ALTERNATE

Use the sqlnet.ora parameter SQLNET.RADIUS_ALTERNATE to specify an alternate RADIUS server to be used when the primary server is unavailable.

SOLNET.RADIUS ALTERNATE PORT

Use the sqlnet.ora parameter $SQLNET.RADIUS_ALTERNATE_PORT$ to specify the listening port of an alternate RADIUS server.

SQLNET.RADIUS ALTERNATE RETRIES

Use the sqlnet.ora parameter SQLNET.RADIUS_ALTERNATE_RETRIES to specify the number of times that the database resends messages to alternate RADIUS servers.

SOLNET.RADIUS ALTERNATE TIMEOUT

Use the sqlnet.ora parameter $SQLNET.RADIUS_ALTERNATE_TIMEOUT$ to set the time for an alternate RADIUS server to wait for a response.



SOLNET.RADIUS ALTERNATE TLS HOST

Use the sqlnet.ora parameter SQLNET.RADIUS_ALTERNATE_TLS_HOST to specify the host name of an alternate RADIUS server to be used when the primary server is unavailable.

SQLNET.RADIUS ALTERNATE TLS PORT

Use the sqlnet.ora parameter $SQLNET.RADIUS_ALTERNATE_TLS_PORT$ to specify the listening port of an alternate RADIUS server.

SOLNET.RADIUS AUTHENTICATION

Use the sqlnet.ora parameter SQLNET.RADIUS_AUTHENTICATION to specify the location of a primary RADIUS server.

• SOLNET.RADIUS AUTHENTICATION INTERFACE

Use the sqlnet.ora parameter SQLNET.RADIUS_AUTHENTICATION_INTERFACE to specify the class that contains the user interface for interacting with users.

SQLNET.RADIUS AUTHENTICATION PORT

Use the sqlnet.ora parameter SQLNET.RADIUS_AUTHENTICATION_PORT to specify the listening port of a primary RADIUS server.

SQLNET.RADIUS AUTHENTICATION RETRIES

Use the sqlnet.ora parameter SQLNET.RADIUS_AUTHENTICATION_RETRIES to specify the number of times the database should resend messages to a primary RADIUS server.

SOLNET.RADIUS AUTHENTICATION TIMEOUT

Use the sqlnet.ora parameter $SQLNET.RADIUS_AUTHENTICATION_TIMEOUT$ to specify the amount of time that the database should wait for a response from a primary RADIUS server.

SQLNET.RADIUS AUTHENTICATION TLS HOST

Use the sqlnet.ora parameter $SQLNET.RADIUS_AUTHENTICATION_TLS_HOST$ to specify the host name of a primary RADIUS server.

SQLNET.RADIUS AUTHENTICATION TLS PORT

Use the sqlnet.ora parameter SQLNET.RADIUS_AUTHENTICATION_TLS_PORT to specify the listening port of a primary RADIUS server.

SQLNET.RADIUS CHALLENGE KEYWORD

Use the sqlnet.ora parameter SQLNET.RADIUS_CHALLENGE_KEYWORD to set the keyword for requesting a challenge from the RADIUS server.

SQLNET.RADIUS CHALLENGE RESPONSE

Use the sqlnet.ora parameter $SQLNET.RADIUS_CHALLENGE_RESPONSE$ to enable or disable challenge responses.

SQLNET.RADIUS CLASSPATH

Use the sqlnet.ora parameter SQLNET.RADIUS_CLASSPATH to set the path for Java classes and JDK Java libraries.

SQLNET.RADIUS SECRET

Use the sqlnet.ora parameter $SQLNET.RADIUS_SECRET$ to specify the location of a RADIUS secret key.

SQLNET.RADIUS SEND ACCOUNTING

Use the sqlnet.ora parameter $SQLNET.RADIUS_SEND_ACCOUNTING$ to enable and disable accounting.

SQLNET.RADIUS TRANSPORT PROTOCOL

Use the server-side sqlnet.ora parameter $SQLNET.RADIUS_TRANSPORT_PROTOCOL$ to control the transport protocol that the Oracle Database server must use for communicating with the RADIUS server.



SOLNET.RECV TIMEOUT

Use the sqlnet.ora parameter $SQLNET.RECV_TIMEOUT$ to specify the duration of time that a database client or server should wait for data from a peer after establishing a connection.

SQLNET.SEND TIMEOUT

Use the sqlnet.ora parameter SQLNET.SEND_TIMEOUT to specify the duration of time in which a database must complete send operations to clients after establishing connections.

SOLNET.URI

Use the sqlnet.ora parameter SQLNET.URI to specify a database client URI mapping on a web server.

SOLNET.USE HTTPS PROXY

Use the sqlnet.ora parameter SQLNET.USE_HTTPS_PROXY to enable forward HTTP proxy tunneling for client connections.

SQLNET.WALLET OVERRIDE

Use the sqlnet.ora parameter SQLNET.WALLET_OVERRIDE to determine whether a client should override strong authentication credentials with the password credential from the stored wallet.

• SSL ALLOW WEAK DN MATCH

Use the sqlnet.ora parameter $SSL_ALLOW_WEAK_DN_MATCH$ to allow the earlier weaker distinguished name (DN) matching behavior during server-side certificate validation.

SSL CERTIFICATE ALIAS

Use the sqlnet.ora or thinnames.ora parameter SSL_CERTIFICATE_ALIAS to specify the certificate alias to use in Transport Layer Security (TLS) connections.

SSL CERTIFICATE THUMBPRINT

Use the sqlnet.ora or this names.ora parameter SSL_CERTIFICATE_THUMBPRINT to specify the certificate thumbprint to use in Transport Layer Security (TLS) connections.

SSL CERT REVOCATION

Use the sqlnet.ora parameter $SSL_CERT_REVOCATION$ to configure revocation checks for certificates.

SSL CRL FILE

Use the sqlnet.ora parameter SSL_CRL_FILE to specify the name of the file in which you assemble the certificate revocation list (CRL) for client authentication.

SSL CRL PATH

Use the sqlnet.ora parameter SSL_CRL_PATH to specify the destination directory of the certificate revocation list (CRL) for client authentication.

SSL_CIPHER_SUITES

Use the SSL_CIPHER_SUITES parameter to control the combination of authentication, encryption, and data integrity algorithms used by Transport Layer Security (TLS).

SSL CLIENT AUTHENTICATION

Use the SSL_CLIENT_AUTHENTICATION parameter to specify whether the database client is authenticated using Transport Layer Security (TLS).

SSL DISABLE WEAK EC CURVES

Use the SSL_DISABLE_WEAK_EC_CURVES parameter to disable the use of weak Elliptic Curve Cryptography (ECC) curves.

• SSL ENABLE WEAK CIPHERS

Use the sqlnet.ora parameter $SSL_ENABLE_WEAK_CIPHERS$ to enable the use of weak Transport Layer Security (TLS) cipher suites.



SSL EXTENDED KEY USAGE

Use the sqlnet.ora parameter $SSL_EXTENDED_KEY_USAGE$ to specify the purpose certificate keys.

SSL SERVER DN MATCH

Use the SSL_SERVER_DN_MATCH parameter to enforce server-side certificate validation through distinguished name (DN) matching.

SSL VERSION

Use the SSL_VERSION parameter to define valid Transport Layer Security (TLS) versions to be used for connections.

TCP.ALLOWED PROXIES

Use the sqlnet.ora parameter TCP.ALLOWED_PROXIES to specify a list of the Oracle Connection Manager (CMAN) addresses that can forward client IP address to the database server.

TCP.CONNECT TIMEOUT

Use the sqlnet.ora parameter TCP.CONNECT_TIMEOUT to specify the amount of time in which a client must establish TCP connections to database servers.

TCP.EXCLUDED NODES

Use the sqlnet.ora parameter TCP.EXCLUDED_NODES to specify which clients are denied access to the database.

TCP.INVITED NODES

Use the sqlnet.ora parameter TCP. INVITED_NODES to specify which clients are allowed access to the database.

TCP.NODELAY

Use the sqlnet.ora parameter TCP.NODELAY to preempt delays in buffer flushing within the TCP/IP protocol stack.

TCP.OUEUESIZE

Use the sqlnet.ora parameter TCP.QUEUESIZE to configure the maximum length of queues for pending connections on TCP listening sockets.

TCP.VALIDNODE CHECKING

Use the sqlnet.ora parameter TCP.VALIDNODE_CHECKING to enable and disable valid node checking for incoming connections.

TENANT ID

Use the TENANT_ID parameter to specify the ID of your Microsoft Entra ID tenant.

TNSPING.TRACE_DIRECTORY

Use the sqlnet.ora parameter <code>TNSPING.TRACE_DIRECTORY</code> to specify the destination directory for the <code>TNSPING</code> utility trace file, <code>tnsping.trc</code>.

TNSPING.TRACE LEVEL

Use the sqlnet.ora parameter TNSPING.TRACE_LEVEL to enable or disable TNSPING utility tracing at a specified level.

TOKEN AUTH

Use the TOKEN_AUTH parameter to configure token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) or Microsoft Azure users of Microsoft Entra ID (previously called Microsoft Azure Active Directory).

TOKEN LOCATION

Use the TOKEN_LOCATION parameter to specify the directory location where token file is stored for token-based authentication.



TLS KEY EXCHANGE GROUPS

Use the TLS_KEY_EXCHANGE_GROUPS parameter to enable or disable post-quantum cryptographic (PQC) ML-KEM algorithms and classical ECDHE groups for TLS connections.

USE CMAN

Use the sqlnet.ora parameter USE_CMAN to specify client routing to Oracle Connection Manager.

USE DEDICATED SERVER

Use the sqlnet.ora parameter USE_DEDICATED_SERVER to append (SERVER=dedicated) to the CONNECT_DATA section of the connect descriptor that the client uses.

USE SNI

Use the sqlnet.ora parameter USE_SNI to enable setting Server Name Indication (SNI) value using CONNECT_DATA parameters.

WALLET LOCATION

Use the WALLET_LOCATION parameter to specify the location of Oracle wallets.

5.2.1 ACCEPT MD5 CERTS

The sqlnet.ora profile parameter ACCEPT_MD5_CERTS accepts MD5 signed certificates.

Purpose

To enable sqlnet to accept MD5 signed certificates. In addition to sqlnet.ora, you must also set this parameter in listener.ora.

Default

FALSE

Values

- TRUE to accept MD5 signed certificates
- FALSE to not accept MD5 signed certficates

5.2.2 ACCEPT_SHA1_CERTS

Use the sqlnet.ora profile parameter ACCEPT_SHA1_CERTS to determine whether SQL Net accepts SHA1 signed certificates.

Purpose

To determine whether sqlnet accepts SHA1 signed certificates. In addition to setting this parameter in sqlnet.ora, you must also set this parameter in listener.ora.

The use of SHA-1 with DBMS_CRYPTO, SQLNET.CRYPTO_CHECKSUM_TYPES_CLIENT and SQLNET.CRYPTO_CHECKSUM_TYPES_SERVER is deprecated.

Using SHA-1 (Secure Hash Algorithm 1) with the parameters

SQLNET.CRYPTO_CHECKSUM_TYPES_CLIENT and SQLNET.CRYPTO_CHECKSUM_TYPES_SERVER is deprecated in this release, and can be desupported in a future release. Using SHA-1 ciphers with DBMS_CRYPTO is also deprecated (HASH_SH1, HMAC_SH1). Instead of using SHA1, Oracle recommends that you start using a stronger SHA-2 cipher in place of the SHA-1 cipher.



Default

TRUE

Values

- TRUE to accept SHA1 signed certificates
- FALSE to not accept SHA1 signed certificates

5.2.3 ALLOWED WEAK CERT ALGORITHMS

Use the sqlnet.ora parameter ALLOWED_WEAK_CERT_ALGORITHMS to allow the use of deprecated certification algorithms as an exception.

Purpose

To allow the use of earlier weaker algorithms for backward compatibility. This is useful for environments that still require the use of certificates associated with deprecated algorithms, such as MD5 or SHA1 signed certificates.

Usage Notes

Starting in Oracle AI Database 26ai, the ALLOW_MD5_CERTS and ALLOW_SHA1_CERTS sqlnet.ora parameters are deprecated.

Instead of these parameters, use the ALLOWED_WEAK_CERT_ALGORITHMS sqlnet.ora parameter, which is new with Oracle AI Database 26ai.

If ALLOWED_WEAK_CERT_ALGORITHMS is set, then Oracle Database ignores ALLOW_MD5_CERTS and ALLOW_SHA1_CERTS. If ALLOWED_WEAK_CERT_ALGORITHMS is not set, then Oracle Database checks and uses the ALLOW_MD5_CERTS and ALLOW_SHA1_CERTS settings.

Values

MD5 | SHA1

Oracle Database allows you to use only those weak algorithms that you set here:

- When set to MD5, it allows MD5 but disables SHA1.
- When set to SHA1, it allows SHA1 but disables MD5.
- When set to MD5, SHA1, it allows both MD5 and SHA1.

Ensure that you enclose the values in parenthesis. If you want to specify both MD5 and SHA1, then separate the values with a comma.

Default

SHA1

Examples

ALLOWED_WEAK_CERT_ALGORITHMS=(SHA1)

ALLOWED_WEAK_CERT_ALGORITHMS=(MD5,SHA1)



Related Topics

Oracle AI Database Security Guide

5.2.4 AZURE DB APP ID URI

Use the AZURE_DB_APP_ID_URI parameter to specify the application ID URI of the Oracle Database instance, registered with Microsoft Entra ID (previously called Microsoft Azure Active Directory).

Purpose

To specify the application ID URI that uniquely identifies your database instance in Entra ID.

This URI value is used to compose the authorization scope (permission) of your database token request during token-based authentication:

```
$Scope = "database_app_id_uri/scope"
```

For example:

```
$Scope = "https://application.example.com/123ab4cd-1a2b-1234-a12b-
aa00123b2cd3/session:scope:connect"
```

Here, the app ID URI https://application.example.com/123ab4cd-1a2b-1234-a12b-aa00123b2cd3 is part of the scope.

Usage Notes

This parameter is mandatory. You must set it along with the <code>TOKEN_AUTH</code> parameter for the <code>AZURE_INTERACTIVE</code>, <code>AZURE_SERVICE_PRINCIPAL</code>, <code>AZURE_MANAGED_IDENTITY</code>, and <code>AZURE_DEVICE_CODE</code> authentication flows.

For the JDBC-thin clients, you can specify this parameter in the connect string, Easy Connect syntax, tnsnames.ora file, or properties. For the thick clients (OCI and Instant Client) and ODP.NET core and managed database clients, you can specify this parameter in the connect string, sqlnet.ora file, Easy Connect syntax, or tnsnames.ora file. The parameter value specified in the connect string takes precedence.

Default

None

Value

You can get the application ID URI value by logging in to the Azure portal. This is listed as the Application ID URI value on the App registrations - Overview page.

Note that this is the value that you specified while registering your Oracle Database instance with the Entra ID tenancy, as shown in *Oracle AI Database Security Guide*.

Examples

In the tnsnames.ora file:

```
net_service_name=
    (DESCRIPTION =
```



```
(ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr)(PORT=1521))
       (SECURITY=
          (SSL SERVER DN MATCH=TRUE)
          (SSL SERVER CERT DN="C=US,O=example,CN=OracleContext")
          (TOKEN_AUTH=AZURE_INTERACTIVE)
          (AZURE DB APP ID URI=https://application.example.com/
123ab4cd-1a2b-1234-a12b-aa00123b2cd3))
       (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))
In the sqlnet.ora file:
SSL_SERVER_DN_MATCH=TRUE
TOKEN AUTH=AZURE INTERACTIVE
AZURE_DB_APP_ID_URI=https://application.example.com/123ab4cd-1a2b-1234-a12b-
aa00123b2cd3
In the Easy Connect string:
tcps:sales-svr:1521/sales.us.example.com?
TOKEN_AUTH=AZURE_INTERACTIVE&AZURE_DB_APP_ID_URI=https://
```

application.example.com/123ab4cd-1a2b-1234-a12b-aa00123b2cd3

In these examples, the CLIENT_ID, TENANT_ID, and REDIRECT_URI parameters are not specified. CLIENT_ID and TENANT_ID are required parameters when using the thick clients (OCI and Instant Client). These parameters are optional for the JDBC-thin and ODP.NET core and managed database clients, which can automatically get these values from the Azure SDK configuration.

Related Topics

- Oracle Database Security Guide
- TOKEN AUTH

Use the TOKEN AUTH parameter to configure token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) or Microsoft Azure users of Microsoft Entra ID (previously called Microsoft Azure Active Directory).

5.2.5 BEQUEATH_DETACH

Use the sqlnet.ora parameter to enable and disable handling signals on Linux and UNIX systems.

Purpose

To enable or disable signal handling on Linux and UNIX systems

Default

no

Values

- yes to turn signal handling off
- no to leave signal handling on



Example

BEQUEATH_DETACH=yes

5.2.6 CLIENT_CERTIFICATE

Use the CLIENT_CERTIFICATE parameter to specify the file system path to a client certificate that authenticates your database client application.

Purpose

File system path to a client certificate that authenticates your database client application in Microsoft Entra ID. A client certificate is the digital certificate of an Azure cloud resource, and the client uses this certificate as a credential to prove its identity when requesting an Entra ID access token. This is used for the AZURE SERVICE PRINCIPAL token-based authentication flow.



(i) Note

Only the JDBC-thin clients and ODP.NET core and managed database clients (and not the thick clients, such as OCI and Instant Client) support certificate-based authentication.

Usage Notes

The Entra ID client uses a client ID and a client secret to retrieve the Entra ID OAuth2 database access token. If a client secret is not configured, then the client driver automatically reads the file system path of a client certificate from the AZURE_CLIENT_CERTIFICATE_PATH environment variable in the Azure SDK configuration. If the application client is public, then it uses only a client ID.

For more information about using certificates with service principals, review Microsoft documentation.

- This parameter is optional. You can set it if you have not configured the SDKs.
 - Note that this parameter is ignored if the client driver is configured with a client secret.
- You can specify this parameter along with the TOKEN AUTH=AZURE SERVICE PRINCIPAL setting in the connect string, Easy Connect syntax, or this names or a file. The parameter value specified in the connect string takes precedence.
- The supported formats for a certificate file are:
 - .pem (Privacy Enhanced Mail)
 - .pfx (Personal Information Exchange)

This format is password-protected. If the file is in a .pfx format, then you must also set the corresponding AZURE_CLIENT_CERTIFICATE_PASSWORD parameter.

You cannot store the certificate in an Oracle Wallet or Azure Key Vault.

Because this certificate is a credential for accessing the database, you must protect it on your file system.

Default

None



Value

Full path (including a file name) to the Azure certificate file

Examples

```
In the tnsnames.ora file:
```

In the Easy Connect string:

```
tcps:sales-svr:1521/sales.us.example.com?
TOKEN_AUTH=AZURE_SERVICE_PRINCIPAL&AZURE_DB_APP_ID_URI=https://
application.example.com/123ab4cd-1a2b-1234-a12b-
aa00123b2cd3&CLIENT_CERTIFICATE=ORACLE_HOME/.azure/certificates/my-app.pem
```

In these examples, the CLIENT_ID and TENANT_ID parameters are not specified. These parameters are optional for the JDBC-thin and ODP.NET core and managed database clients, which can automatically get these values from the Azure SDK configuration.

Related Topics

- Oracle Database Security Guide
- TOKEN AUTH

Use the TOKEN_AUTH parameter to configure token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) or Microsoft Azure users of Microsoft Entra ID (previously called Microsoft Azure Active Directory).

5.2.7 CLIENT ID

Use the CLIENT_ID parameter to specify the ID of the database client Microsoft Entra ID app registration.

Purpose

To specify the client ID assigned to your database client during Entra ID app registration. Note that this is not the client ID for the database server. This application is your database client that requests to get an access token for the user during Azure token-based authentication.



Usage Notes

You use this parameter along with the TOKEN_AUTH parameter for the AZURE_INTERACTIVE, AZURE_SERVICE_PRINCIPAL, AZURE_MANAGED_IDENTITY, and AZURE_DEVICE_CODE authentication flows, as follows:

The AZURE_MANAGED_IDENTITY authentication flow is applicable to client-side or server-side
applications hosted on Azure environments, such as Azure App Service or Azure virtual
machine.

When using the JDBC-thin clients and ODP.NET core and managed database clients, the client driver uses a system-assigned managed identity. A system-assigned managed identity is an implicit identity assigned by Entra ID to your application, and is configured in the Azure SDK by default. Optionally, you can set this parameter to explicitly assign the client ID of a user-assigned managed identity to your application.

When using the thick clients (OCI and Instant Client), which do not use the Azure SDKs, you must set this parameter to assign a user-assigned managed identity to your application.

 For other authentication flows, when using the JDBC-thin clients and ODP.NET core and managed database clients, the client driver searches for the client ID in the Azure SDK configuration. In this case, this parameter is optional.

When using the OCI and Instant Clients, you must set this parameter (along with other required parameters, such as <code>TENANT_ID</code>). Otherwise, an error message appears prompting you to configure the required parameters.

Note that this parameter is mandatory for the OCI and Instant Clients. It is optional only when using the JDBC-thin clients and ODP.NET core and managed database clients.

For the JDBC-thin clients, you can specify this parameter in the connect string, Easy Connect syntax, tnsnames.ora file, or properties. For the thick clients (OCI and Instant Client) and ODP.NET core and managed database clients, you can specify this parameter in the connect string, sqlnet.ora file, Easy Connect syntax, or tnsnames.ora file. The parameter value specified in the connect string takes precedence.

Default

None

Value

You can get the client ID value by logging in to the Azure portal. This is listed as the Application (client) ID value on the App registrations - Overview page.

Examples

In the tnsnames.ora file:



```
(CLIENT_ID=123ab4cd-1a2b-1234-a12b-aa00123b2cd3)
(CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))
)
```

In the sqlnet.ora file:

```
SSL_SERVER_DN_MATCH=TRUE

TOKEN_AUTH=AZURE_INTERACTIVE

AZURE_DB_APP_ID_URI=https://application.example.com/123ab4cd-1a2b-1234-a12b-aa00123b2cd3

CLIENT_ID=123ab4cd-1a2b-1234-a12b-aa00123b2cd3
```

In the Easy Connect string:

```
tcps:sales-svr:1521/sales.us.example.com?
TOKEN_AUTH=AZURE_INTERACTIVE&AZURE_DB_APP_ID_URI=https://
application.example.com/123ab4cd-1a2b-1234-a12b-
aa00123b2cd3&CLIENT ID=123ab4cd-1a2b-1234-a12b-aa00123b2cd3
```

In these examples, the <code>TENANT_ID</code> and <code>REDIRECT_URI</code> parameters are not specified. <code>TENANT_ID</code> is required when using the thick clients (OCI and Instant Client). This parameter is optional for the JDBC-thin and ODP.NET core and managed database clients, which can automatically get this value from the Azure SDK configuration.

Related Topics

- Oracle Database Security Guide
- TOKEN AUTH

Use the TOKEN_AUTH parameter to configure token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) or Microsoft Azure users of Microsoft Entra ID (previously called Microsoft Azure Active Directory).

5.2.8 EXADIRECT_FLOW_CONTROL

The sqlnet.ora profile parameter EXADIRECT_FLOW_CONTROL enables or disables Exadirect flow control.

Purpose

To enable or disable Exadirect flow control.

Usage Notes

Set to on, the parameter enables Oracle Net to broadcast the available receive window to the sender. The sender limits the sends based on the receiver broadcast window.

Default

off

Example

EXADIRECT_FLOW_CONTROL=on



5.2.9 EXADIRECT_RECVPOLL

Use the sqlnet.ora parameter EXADIRECT_RECVPOLL to specify the amount of time that a receiver polls for incoming data.

Purpose

To specify the amount of time that a receiver polls for incoming data.

Usage Notes

You can set the parameter to a fixed value or set the parameter to AUTO to automatically tune the polling value.

Default

0

Example

```
EXADIRECT_RECVPOLL = 10
EXADIRECT_RECVPOLL = AUTO
```

5.2.10 DEFAULT_SDU_SIZE

Use the sqlnet.ora profile parameter to specify the session data unit size (SDU) for connections.

Purpose

To specify the SDU size, in bytes, for connections.

Usage Notes

Oracle recommends setting this parameter in both the client-side and server-side sqlnet.ora files to ensure that the same SDU size is used throughout a connection. When the configured values of client and database server do not match for a session, the lower of the two values is used.

You can override this parameter for a particular client connection by specifying the SDU parameter in the connect descriptor for a client.

Default

For clients: 8192 bytes (8 KB)

For servers: 65536 bytes (64KB)

Value

512 to 2097152 bytes

Example 5-1 Example

DEFAULT_SDU_SIZE=4096



5.2.11 DISABLE_INTERRUPT

Use the sqlnet.ora profile parameter DISABLE_INTERRUPT to disable Oracle Net handling of a SIGINIT signal in client applications.

Purpose

To disable Oracle Net handling of a SIGINIT signal in client applications.

Usage Notes

Oracle Net installs a signal handler to catch a SIGINT signal. By default, the action on receipt of a SIGINIT signal is to cancel the current operation. If you set this parameter to TRUE, then you can override the default behavior and ignore Oracle Net handling of SIGINT signals.

For details on installing and uninstalling your own signal handlers in addition to Oracle Net, see *Oracle AI Database Administrator's Reference for Linux and UNIX-Based Operating Systems*.

Default

FALSE

Example

DISABLE_INTERRUPT=TRUE

5.2.12 DISABLE OOB

Use the sqlnet.ora profile parameter DISABLE_OOB to enable or disable Oracle Net to send or receive out-of-band break messages using urgent data from the underlying protocol.

Purpose

To enable or disable Oracle Net to send or receive out-of-band break messages using urgent data provided by the underlying protocol.

Usage Notes

Set to off, the parameter enables Oracle Net to send and receive break messages. Set to on, the parameter disables the ability to send and receive break messages. Once enabled, this feature applies to all protocols that the client uses.

Default

off

Example 5-2 Example

DISABLE_OOB=on



5.2.13 DISABLE_OOB_AUTO

Use the sqlnet.ora profile parameter DISABLE_OOB_AUTO to disable server path checks for out-of-band break messages at the time of the connection.

Purpose

To disable sqlnet.ora from checking for out-of-band (OOB) break messages in the server path at connection time.

Usage Notes

By default, the client determines if the server path supports out-of-band break messages at the time of establishing the connection. If <code>DISABLE_OOB_AUTO</code> is set to <code>TRUE</code>, then the client does not perform this check at connection time.

Default

FALSE

Example 5-3 Example

DISABLE_OOB_AUTO = TRUE

5.2.14 IPC.KEYPATH

Use the sqlnet.ora profile parameter IPC.KEYPATH to specify the destination directory where the internal file is created for UNIX domain sockets.

Purpose

To specify the destination directory where the internal file is created for UNIX domain sockets.

Usage Notes

This parameter applies only to Oracle Net usage of UNIX domain sockets and does not apply to other uses of UNIX domain sockets in Oracle Database, such as in Oracle Clusterware. If you use the IPC.KEYPATH parameter, then you should use the same value for IPC_KEYPATH on both the client and the listener on Oracle Database versions that are greater than Oracle Database 18c.

Default

The directory path is either /var/tmp/.oracle for Oracle Linux, Oracle Solaris or /tmp/.oracle for other UNIX variants.

Example

ipc.keypath=/home/oracleuser.



5.2.15 KERBEROS5_PRINCIPAL

Use the KERBEROS5_PRINCIPAL parameter to set the Kerberos principal name associated with the Kerberos credentials cache (CC) file.

Purpose

When you configure Kerberos authentication for an Oracle Database client, you can specify multiple Kerberos principals with a single Oracle Database client.

This is an optional parameter. When specified, it is used to verify if the principal name in the credential cache (specified using KERBEROS5_CCC_NAME) matches the parameter value.

Usage Notes

Use this parameter in the SECURITY section of the tnsnames.ora file, or set it in the sqlnet.ora file. Alternatively, you can set KERBEROS5_PRINCIPAL in the connect string along with the KERBEROS5_CC_NAME parameter to connect as a different Kerberos principal.

The parameter value specified in the connect string takes precedence over the value specified in the sqlnet.ora or tnsnames.ora file.

Each Kerberos principal must have a valid credential cache. Oracle Database checks KERBEROS5_PRINCIPAL against the value that is retrieved from the credential cache. If the two values do not match, then the user is not authenticated.

Examples

 For a user krbuser1, who is externally authenticated using the Kerberos principal krbprincl@example.com and the credential cache for this principal is located at /tmp/ krbuser1/krb.cc, the connect descriptor in the tnsnames.ora file is:

In the sqlnet.ora file:

```
SQLNET.KERBEROS5_CC_NAME=/tmp/krbuser1/krb.cc
KERBEROS5 PRINCIPAL=krbprinc1@example.com
```

 For a user krbuser2, who is externally authenticated using the Kerberos principal krbprinc2@example.com and the credential cache for this principal is located at /tmp/ krbuser2/krb.cc, the connect descriptor in the tnsnames.ora file is:



(SECURITY=
 (KERBEROS5_CC_NAME=/tmp/krbuser2/krb.cc)
 (KERBEROS5_PRINCIPAL=krbprinc2@example.com)))

In sqlnet.ora file:

SQLNET.KERBEROS5_CC_NAME=/tmp/krbuser2/krb.cc KERBEROS5_PRINCIPAL=krbprinc2@example.com

Note

The connection fails if the principal in the /tmp/krbuser1/krb.cc file does not contain the krbprincl@example.com value.

Related Topics

SQLNET.KERBEROS5 CC NAME

Use the sqlnet.ora parameter $SQLNET.KERBEROS5_CC_NAME$ to specify the complete path name to the Kerberos credentials cache (CC) file.

KERBEROS5 CC NAME

Use the tnsnames.ora parameter KERBEROS5_CC_NAME to specify the complete path name to the Kerberos credentials cache (CC) file.

Oracle AI Database Security Guide

5.2.16 MAX_CONDUITS

Use the sqlnet.ora parameter MAX_CONDUITS to specify the maximum number of conduits between the listener and the broker or dispatcher for handing off client connections.

Purpose

To set the maximum number of conduits created between the listener and the broker or dispatcher processes over which client connections are handed off.

Usage Notes

Setting a higher value enables multiple connections to be handed off in parallel, which is particularly useful during a logon storm when there is a spike in incoming connections.

Default

50

Example

MAX_CONDUITS=80



5.2.17 NAMES.DEFAULT_DOMAIN

Use the sqlnet.ora profile parameter NAMES.DEFAULT_DOMAIN to set the name of the domain in which clients most often look up names resolution requests.

Purpose

To set the domain from which the client most often looks up names resolution requests.

Usage Notes

When you set NAMES.DEFAULT_DOMAIN, the default domain name is automatically appended to any unqualified net service name or service name.

For example, if you set the default domain to www.example.com, then Oracle searches the connect string CONNECT scott@sales as www.example.com. If the connect string includes the domain extension, such as CONNECT scott@sales.www.example.com, then the domain is not appended to the string.

Default

None

Example

NAMES.DEFAULT_DOMAIN=example.com

5.2.18 NAMES.DIRECTORY_PATH

Use the sqlnet parameter NAMES.DIRECTORY_PATH to specify the order of the naming methods for client name resolution lookups.

Purpose

To specify the order of the naming methods for client name resolution lookups.

Default

NAMES.DIRECTORY_PATH=(tnsnames, ezconnect, ldap)

Values

The following table shows the NAMES.DIRECTORY_PATH values for the naming methods.

Naming Method Value	Description
tnsnames (local naming method)	Set to resolve a network service name through the tnsnames.ora file on the client.
ldap (directory naming method)	Set to resolve a database service name, net service name, or network service alias through a directory server.
ezconnect or hostname (Easy Connect naming method)	Select to enable clients to use a TCP/IP connect identifier that consists of a host name and optional port and service name.
nis (external naming method)	Set to resolve service information through an existing Network Information Service (NIS).



Example

NAMES.DIRECTORY_PATH=(tnsnames)

5.2.19 NAMES.LDAP_AUTHENTICATE_BIND

Use the sqlnet parameter NAMES.LDAP_AUTHENTICATE_BIND to specify whether the LDAP naming adapter should authenticate using a specified wallet when it connects to the LDAP directory to resolve connect string names.

Purpose

To specify whether the LDAP naming adapter should attempt to authenticate using a specified wallet when it connects to the LDAP directory to resolve the service name in the connect string.

Usage Notes

When set to FALSE, the LDAP connection is established using an anonymous bind.

When set to TRUE, the LDAP connection is authenticated using an Oracle wallet. You must specify the wallet location using the WALLET LOCATION parameter.

The parameter WALLET_LOCATION is deprecated for use with Oracle Al Database 26ai for the Oracle Database server. It is not deprecated for use with the Oracle Database client or listener.

For Oracle Database server, Oracle recommends that you use the WALLET_ROOT system parameter instead of using WALLET_LOCATION.

Values

TRUE | FALSE

Default

FALSE

Example

NAMES.LDAP_AUTHENTICATE_BIND=TRUE

5.2.20 NAMES.LDAP AUTHENTICATE BIND METHOD

Use the sqlnet parameter NAMES.LDAP_AUTHENTICATE_BIND_METHOD to specify an authentication method for the client LDAP naming adapter.

Purpose

To specify the authentication method that the client LDAP naming adapter should use while connecting to the LDAP directory to resolve connect string names.

Usage Notes

The simple authentication method over LDAPS (LDAP over TLS connection) is supported.

You store the directory entry DN and password in an Oracle wallet. When the client connects to the LDAP server, it is authenticated using the credentials stored in this wallet. The wallet trust store must contain root certificates issued by the certificate authority of the LDAP server.



The LDAP naming adapter uses the <code>oracle.ldap.client.dn</code> and <code>oracle.ldap.client.password</code> entries from the wallet for authenticating to the LDAP server. If these entries are not present, then the client attempts an anonymous authentication using TLS or LDAPS.

Values

- LDAPS_SIMPLE_AUTH
- NONE

Default

NONE

Example

NAMES.LDAP_AUTHENTICATE_BIND_METHOD=LDAPS_SIMPLE_AUTH

Related Topics

Oracle Al Database Net Services Administrator's Guide

5.2.21 NAMES.LDAP_CONN_TIMEOUT

Use the sqlnet parameter NAMES.LDAP_CONN_TIMEOUT to specify the number of seconds that indicates that a non-blocking connect timeout to the LDAP server occurred.

Purpose

The parameter value -1 is for infinite timeout.

Default

15 seconds

Values

Values are in seconds. The range is -1 to the number of seconds that is acceptable for your environment. There is no upper limit.

To specify the number of seconds for a non-blocking connect timeout to the LDAP server.

Usage Notes

Example

names.ldap_conn_timeout = -1

5.2.22 NAMES.LDAP_PERSISTENT_SESSION

Use the sqlnet parameter NAMES.LDAP_PERSISTENT_SESSION to specify whether the LDAP naming adapter should leave the session with the LDAP server open after name lookups are complete.

Purpose

To specify whether the LDAP naming adapter should leave the session with the LDAP server open after a name lookup is complete.



Usage Notes

The parameter value is Boolean.

If you set the parameter to TRUE, then the connection to the LDAP server is left open after the name lookup is complete. The connection remains open for the duration of the process. If the connection is lost, then it is re-established as needed.

If you set the parameter to FALSE, then the LDAP connection is terminated as soon as the name lookup completes. Every subsequent look-up opens the connection, performs the look-up, and closes the connection. This option prevents LDAP from having a large number of clients connected to it at any one time.

Default

false

Example

NAMES.LDAP_PERSISTENT_SESSION=true

5.2.23 NAMES.NIS.META_MAP

Use the sqlnet parameter NAMES.NIS.META_MAP to specify the map file to use to map Network Information Service (NIS) attributes to an NIS mapname.

Purpose

To specify the map file to be used to map Network Information Service (NIS) attributes to an NIS mapname.

Default

sqlnet.maps

Example

NAMES.NIS.META_MAP=sqlnet.maps

5.2.24 OCI_COMPARTMENT

Use the OCI_COMPARTMENT parameter to specify Oracle Cloud Identifier (OCID) of the compartment that holds database instances for client connections.

Purpose

To define the scope of your database token request. This value instructs the database client to initiate a token request to databases within the specified compartment only. You use this parameter while configuring token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) users on OCI Database as a Service (DBaaS).

Usage Notes

The <code>OCI_COMPARTMENT</code> parameter is optional if you have not specified the <code>OCI_DATABASE</code> parameter. If you choose to set <code>OCI_DATABASE</code>, then you must also set <code>OCI_COMPARTMENT</code> to limit your token request to the specified database within that compartment.



If you do not set both the OCI_COMPARTMENT and OCI_DATABASE parameters, then the entire tenancy is the scope of your token request.

You can use this parameter along with the PASSWORD_AUTH and TOKEN_AUTH authentication settings:

- With the PASSWORD_AUTH configuration, the database client can only request an IAM database token using the IAM user name and IAM database password.
- With the TOKEN_AUTH configuration, the database client can request an IAM database token using the API-key, delegation token, security token, resource principal, or instance principal credentials. You can also enable the database client to directly retrieve the dbtoken with IAM Single-Sign On (SSO) credentials by using the OCI_INTERACTIVE, OCI_API_KEY, OCI_INSTANCE_PRINCIPAL, OCI_DELEGATION_TOKEN, and OCI RESOURCE PRINCIPAL authentication flows.

Use this parameter under the SECURITY section of the tnsnames.ora file, sqlnet.ora file, Easy Connect syntax, or directly as part of the command-line connect string. The parameter value specified in the connect string takes precedence over the other specified values.

Default

None

Value

OCID for the IAM compartment to allow access for the database token. You can get the OCID value for your compartment from the Compartments information page in the OCI console.

The compartment OCID uses this syntax:

```
OCI_COMPARTMENT=compartment_OCID
```

For details on the syntax options, see Oracle Cloud IDs (OCIDs).

Examples

```
In the thshames ora file:
```

```
net_service_name=
  (DESCRIPTION=
     (ADDRESS=(PROTOCOL=tcps)(HOST=salesserver1)(PORT=1522))
     (SECURITY=
        (SSL_SERVER_DN_MATCH=TRUE)
        (SSL SERVER CERT DN="C=US,O=example,CN=OracleContext")
        (PASSWORD_AUTH=OCI_TOKEN)
        (OCI_IAM_URL=https://auth.us-region-1.example.com/v1/actions/
generateScopedAccessBearerToken)
        (OCI_TENANCY=ocid1.tenancy..12345)
        (OCI_COMPARTMENT=ocid1.compartment..12345)
        (OCI_DATABASE=ocid1.autonomousdatabase.oc1.12345))
     (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))
In the sqlnet.ora file:
SSL_SERVER_DN_MATCH=TRUE
PASSWORD_AUTH=OCI_TOKEN
OCI_IAM_URL=https://auth.us-region-1.example.com/v1/actions/
```



generateScopedAccessBearerToken
OCI_TENANCY=ocid1.tenancy..12345
OCI_COMPARTMENT=ocid1.compartment..12345
OCI_DATABASE=ocid1.autonomousdatabase.oc1.12345

In the Easy Connect syntax:

tcps:sales-svr:1521/sales.us.example.com?
TOKEN_AUTH=OCI_INTERACTIVE&OCI_COMPARTMENT=ocid1.compartment..12345&OCI_DATABA
SE=ocid1.autonomousdatabase.oc1.12345

Related Topics

- Oracle Al Database Security Guide
- PASSWORD AUTH
- TOKEN AUTH

Use the TOKEN_AUTH parameter to configure token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) or Microsoft Azure users of Microsoft Entra ID (previously called Microsoft Azure Active Directory).

• OCI_DATABASE

Use the $OCI_DATABASE$ parameter to specify Oracle Cloud Identifier (OCID) of the database that you want to access for the client connection.

5.2.25 OCI_CONFIG_FILE

Use the <code>OCI_CONFIG_FILE</code> parameter to specify the directory location where the Oracle Cloud Infrastructure (OCI) configuration file is stored.

Purpose

To specify the directory location of the OCI configuration file. This file stores the client connection information for OCI Identity and Access Management (IAM) users as part of their profile. The SDK, CLI, and other OCI tools use this file to access the IAM user credentials during IAM token-based authentication.

Usage Notes

This is an optional parameter. If you do not set this parameter, then the database client gets the user's profile from the default configuration file located at C:/user-profile/.oci/config. You can use this parameter to override the default configuration file location. In this case, the database client searches for the profile in the location specified by OCI_CONFIG_FILE.

You can use this parameter along with the TOKEN_AUTH parameter for the OCI_API_KEY and OCI_INTERACTIVE authentication flows:

- When using the OCI_INTERACTIVE authentication flow, if this parameter is not set and the configuration file is also not present in the default location, then Oracle Database prompts the user for a region ID, presenting a list of region IDs from which the user can choose.
- When using the OCI_API_KEY authentication flow, if this parameter is not set and the default configuration file is also not present, then an ORA-50109 error message is returned. In this case, you must set this parameter to include the configuration file location.

For JDBC-thin clients, you can specify this parameter in the Easy Connect syntax or tnsnames.ora connect string. For ODP.NET Core classes and ODP.NET Managed Driver



classes, you can specify this parameter in the sqlnet.ora file, Easy Connect syntax, or this this connect string. The parameter value specified in the connect string takes precedence.

Default

None

Value

Full path (including a file name) to the OCI configuration file

Examples

```
In the thshames ora file:
net service name=
    (DESCRIPTION =
       (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr)(PORT=1521))
       (SECURITY=
          (SSL_SERVER_DN_MATCH=TRUE)
          (SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleContext")
          (TOKEN AUTH=OCI INTERACTIVE)
          (OCI_CONFIG_FILE=/home/dbuser1/config))
       (CONNECT DATA=(SERVICE NAME=sales.us.example.com))
In the sqlnet.ora file:
SSL SERVER DN MATCH=TRUE
TOKEN AUTH=OCI INTERACTIVE
OCI CONFIG FILE=/home/dbuser1/config
In the Easy Connect string:
tcps:sales-svr:1521/sales.us.example.com?
TOKEN_AUTH=OCI_INTERACTIVE&OCI_CONFIG_FILE=/home/dbuser1/config
```

In these examples, the optional OCI_PROFILE parameter is not specified. Thus, the client automatically gets the DEFAULT profile from the specified configuration file directory.

Related Topics

- Oracle Database Security Guide
- TOKEN AUTH

Use the TOKEN_AUTH parameter to configure token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) or Microsoft Azure users of Microsoft Entra ID (previously called Microsoft Azure Active Directory).

OCI PROFILE

Use the OCI_PROFILE parameter to specify the profile name for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) users.



5.2.26 OCI_DATABASE

Use the OCI_DATABASE parameter to specify Oracle Cloud Identifier (OCID) of the database that you want to access for the client connection.

Purpose

To define the scope of your database token request. The database OCID value instructs the database client to initiate a token request to the specified database within your compartment. You use this parameter while configuring token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) users on OCI Database as a Service (DBaaS).

Usage Notes

This is an optional parameter. You can set this parameter to limit the access to only a particular database. If you set <code>OCI_DATABASE</code>, then you must also provide specific compartment identifier using the <code>OCI_COMPARTMENT</code> parameter.

You can use this parameter along with the PASSWORD_AUTH and TOKEN_AUTH authentication settings:

- With the PASSWORD_AUTH configuration, the database client can only request an IAM database token using the IAM user name and IAM database password.
- With the TOKEN_AUTH configuration, the database client can request an IAM database token using the API-key, delegation token, security token, resource principal, or instance principal credentials. You can also enable the database client to directly retrieve the dbtoken with IAM Single-Sign On (SSO) credentials by using the OCI_INTERACTIVE, OCI_API_KEY, OCI_INSTANCE_PRINCIPAL, OCI_DELEGATION_TOKEN, and OCI_RESOURCE_PRINCIPAL authentication flows.

Specify this parameter under the SECURITY section of the tnsnames.ora file, sqlnet.ora file, Easy Connect syntax, or directly as part of the command-line connect string. The parameter value specified in the connect string takes precedence.

Default

None

Value

OCID of the database that you want to access for the client connection. You can get the OCID value for your database from the Database details page in the OCI console.

The database OCID uses this syntax:

```
OCI_DATABASE=database_OCID
```

For details on the syntax options, see Oracle Cloud IDs (OCIDs).

Examples



```
(SECURITY=
        (SSL SERVER DN MATCH=TRUE)
        (SSL SERVER CERT DN="C=US,O=example,CN=OracleContext")
        (PASSWORD AUTH=OCI TOKEN)
        (OCI_IAM_URL=https://auth.us-region-1.example.com/v1/actions/
generateScopedAccessBearerToken)
        (OCI TENANCY=ocid1.tenancy..12345)
        (OCI_COMPARTMENT=ocid1.compartment..12345)
        (OCI DATABASE=ocid1.autonomousdatabase.oc1.12345))
     (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))
In the sqlnet.ora file:
SSL_SERVER_DN_MATCH=TRUE
PASSWORD_AUTH=OCI_TOKEN
OCI_IAM_URL=https://auth.us-region-1.example.com/v1/actions/
generateScopedAccessBearerToken
OCI_TENANCY=ocid1.tenancy..12345
OCI COMPARTMENT=ocid1.compartment..12345
OCI DATABASE=ocid1.autonomousdatabase.oc1.12345
In the Easy Connect syntax:
```

```
tcps:sales-svr:1521/sales.us.example.com?
TOKEN_AUTH=OCI_INTERACTIVE&OCI_COMPARTMENT=ocid1.compartment..12345&OCI_DATABA
SE=ocid1.autonomousdatabase.oc1.12345
```

Related Topics

- Oracle AI Database Security Guide
- PASSWORD AUTH
- TOKEN AUTH

Use the TOKEN_AUTH parameter to configure token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) or Microsoft Azure users of Microsoft Entra ID (previously called Microsoft Azure Active Directory).

OCI COMPARTMENT

Use the OCI_COMPARTMENT parameter to specify Oracle Cloud Identifier (OCID) of the compartment that holds database instances for client connections.

5.2.27 OCI IAM URL

Use the OCI_IAM_URL parameter to specify an endpoint URL that the database client must connect with to get the database token for authenticating Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) users on OCI Database as a Service (DBaaS).

Purpose

To specify the IAM URL for your REST API requests. The database client connects to this URL to retrieve the database token from IAM.



Usage Notes

You set the OCI_IAM_URL parameter along with the PASSWORD_AUTH and OCI_TENANCY parameters while configuring IAM token-based authentication (using the IAM user name and IAM database password to retrieve the database token). These parameters are mandatory.

With this configuration, the database client can only request an IAM database token using the IAM user name and IAM database password. The client cannot request an IAM database token for an API-key, delegation token, security token, resource principal, service principal, or instance principal.

You can also set the optional OCI_COMPARTMENT and OCI_DATABASE parameters to specify the scope of your token request.

Use this parameter under the SECURITY section of the tnsnames.ora file, sqlnet.ora file, or directly as part of the command-line connect string. The parameter value specified in the connect string takes precedence over the other specified values.

Default

None

Value

OCI IAM endpoint URL that the database client must connect with to get the database token. This URL is specific to your region and uses this syntax:

<authentication_regional_endpoint>/v1/actions/generateScopedAccessBearerToken

You can derive this value by replacing *<authentication_regional_endpoint>* with the API endpoint URL for your region. To obtain the appropriate API endpoint URL, see <u>Identity and Access Management Data Plane API</u>.

For example, if you want to use the URL as https://auth.us-region-1.example.com, then your OCI_IAM_URL value is:

```
https://auth.us-region-1.example.com/v1/actions/generateScopedAccessBearerToken
```

Examples

In the tnsnames.ora file:



In the sqlnet.ora file:

SSL_SERVER_DN_MATCH=TRUE

PASSWORD_AUTH=OCI_TOKEN

OCI_IAM_URL=https://auth.us-region-1.example.com/v1/actions/
generateScopedAccessBearerToken

OCI_TENANCY=ocid1.tenancy..12345

In these examples, the optional OCI_COMPARTMENT and OCI_DATABASE parameters are not specified and thus the entire tenancy is set as the scope of the token request.

Related Topics

- Oracle Al Database Security Guide
- PASSWORD AUTH

5.2.28 OCI_PROFILE

Use the OCI_PROFILE parameter to specify the profile name for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) users.

Purpose

To specify the profile name for IAM users. This profile is the client connection information stored in the OCI configuration file, and is used during IAM token-based authentication.

Usage Notes

- This is an optional parameter. A profile named DEFAULT is already set in the configuration
 file. The database client gets the DEFAULT profile from the OCI configuration file (from either
 the default C:/user-profile/.oci/config directory location or the location specified by
 OCI_CONFIG_FILE).
- You can specify this parameter to override the DEFAULT profile set in the configuration file and assign a new profile name for the IAM user.
 - When this parameter is not set and the profile is also not present in the configuration file, then an error message appears indicating that token-based authentication has failed due to the profile not existing.
- You can use this parameter along with the TOKEN_AUTH parameter for the OCI_API_KEY and OCI_INTERACTIVE authentication flows.

For JDBC-thin clients, you can specify this parameter in the Easy Connect syntax or tnsnames.ora connect string. For ODP.NET Core classes and ODP.NET Managed Driver classes, you can specify this parameter in the sqlnet.ora file, Easy Connect syntax, or tnsnames.ora connect string. The parameter value specified in the connect string takes precedence.

Values

- DEFAULT: This means that no value is explicitly defined for a given profile, and the profile is inherited from the default profile set in the configuration file.
- profile_name: Specify a new configuration profile name (for example, ADMIN_USER) to override the DEFAULT profile set in the configuration file.



Default

DEFAULT

Examples

```
In the tnsnames.ora file:
net_service_name=
    (DESCRIPTION =
       (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr)(PORT=1521))
       (SECURITY=
          (SSL_SERVER_DN_MATCH=TRUE)
          (SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleContext")
          (TOKEN_AUTH=OCI_INTERACTIVE)
          (OCI_CONFIG_FILE=/home/dbuser1/config))
          (OCI_PROFILE=ADMIN_USER))
       (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))
In the sqlnet.ora file:
SSL_SERVER_DN_MATCH=TRUE
TOKEN_AUTH=OCI_INTERACTIVE
OCI_CONFIG_FILE=/home/dbuser1/config
OCI_PROFILE=ADMIN_USER
In the Easy Connect string:
tcps:sales-svr:1521/sales.us.example.com?
TOKEN_AUTH=OCI_INTERACTIVE&OCI_CONFIG_FILE=/home/dbuser1/
config&OCI PROFILE=ADMIN USER
```

Related Topics

- Oracle Database Security Guide
- TOKEN AUTH

Use the TOKEN_AUTH parameter to configure token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) or Microsoft Azure users of Microsoft Entra ID (previously called Microsoft Azure Active Directory).

OCI CONFIG FILE

Use the OCI_CONFIG_FILE parameter to specify the directory location where the Oracle Cloud Infrastructure (OCI) configuration file is stored.

5.2.29 OCI_TENANCY

Use the OCI_TENANCY parameter to specify Oracle Cloud Identifier (OCID) of the user's tenancy.

Purpose

To specify OCID of the user's tenancy (root compartment).



Usage Notes

You set this parameter along with the mandatory PASSWORD_AUTH and OCI_IAM_URL parameters while configuring token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) users on OCI Database as a Service (DBaaS).

With this configuration, the database client can only request an IAM database token using the IAM user name and IAM database password. The client cannot request an IAM database token for an API-key, delegation token, security token, resource principal, service principal, or instance principal.

You can also set the optional <code>OCI_COMPARTMENT</code> and <code>OCI_DATABASE</code> parameters to specify the scope of your token request. If you do not set the <code>OCI_COMPARTMENT</code> and <code>OCI_DATABASE</code> parameter values, then the entire tenancy is the scope of your token request.

Use this parameter under the SECURITY section of the tnsnames.ora file, sqlnet.ora file, or directly as part of the command-line connect string. The parameter value specified in the connect string takes precedence over the other specified values.

Default

None

Value

OCID of the user's tenancy. You can get the OCID value for your tenancy from the Tenancy information page in the OCI console.

The tenancy OCID uses this syntax:

```
OCI_TENANCY=tenancy_OCID
```

For details on the syntax options, see Oracle Cloud IDs (OCIDs).

Examples

In the tnsnames.ora file:



generateScopedAccessBearerToken
OCI TENANCY=ocid1.tenancy..12345

In these examples, the optional OCI_COMPARTMENT and OCI_DATABASE parameters are not specified and thus the entire tenancy is set as the scope of the token request.

Related Topics

- Oracle Al Database Security Guide
- PASSWORD AUTH

5.2.30 PASSWORD_AUTH

Use the PASSWORD_AUTH parameter to configure an authentication method for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) users on OCI Database as a Service (DBaaS). With this setting, client connections use the IAM user name and IAM database password for logging in users to the database.

Purpose

To configure either IAM database password verifier authentication or IAM token-based authentication, using the IAM user name and IAM database password for the access.

For password verifier authentication, the database server retrieves an IAM database password verifier from IAM. For token-based authentication, the database client requests a database token (db-token) from IAM.

Usage Notes

- Use this parameter under the SECURITY section of the tnsnames.ora file, sqlnet.ora file, or directly as part of the command-line connect string. The parameter value specified in the connect string takes precedence over the other specified values.
- This setting instructs the database client to either use the existing password login process
 with the database server (password verifier authentication) or to get a token with the IAM
 user name and IAM database password (token-based authentication). This IAM database
 password is different from the OCI console password. An IAM user can set this password
 from the OCI console.

See <u>Create an OCI IAM password to use for Autonomous Databases User Authentication</u> and Authorization.

By default, this parameter is set to PASSWORD_VERIFIER. The
 PASSWORD_AUTH=PASSWORD_VERIFIER setting configures IAM database password verifier
 authentication. The database server retrieves an IAM database password verifier (an
 encrypted hash of password) from IAM to authenticate users.

When an IAM user logs in with the IAM user name and IAM database password using <code>@connect_identifier</code>, the <code>PASSWORD_AUTH=PASSWORD_VERIFIER</code> setting along with <code>@connect_identifier</code> instructs the database client to follow the existing user name and password login process with the database server.

You can use the PASSWORD_AUTH parameter to override the tnsnames.ora or sqlnet.ora setting by specifying a different value in the connect string.

• To configure IAM token-based authentication with the IAM user name and IAM database password, set PASSWORD_AUTH=OCI_TOKEN. The database client requests a database token (db-token) from IAM for the user to access the database.



This db-token obtained by the client is a bearer token with an expiration time and scope, and does not come with a private key. These tokens are transmitted over secure channels. You must use only the TCP/IP with Transport Layer Security (TLS) protocol, otherwise an error message appears indicating that non-TLS connections are disallowed.

When an IAM user logs in with the IAM user name and IAM database password using / @connect identifier, the PASSWORD AUTH=OCI TOKEN setting along with / @connect identifier instructs the database client to get the token directly from an OCI IAM endpoint using a REST API request. If the IAM user is mapped to a database schema (exclusively or shared), then the login is completed.

For the database client to retrieve the token from IAM, you must set additional parameters so that the database client can find the IAM endpoint along with additional meta-data. The additional parameters are OCI_IAM_URL and OCI_TENANCY along with the optional OCI COMPARTMENT and OCI DATABASE. These values enable the database client to make appropriate calls to the specified endpoint.

The OCI IAM URL parameter specifies the API endpoint URL that the database client must connect with. The OCI TENANCY parameter specifies the OCID (Oracle Cloud Identifier) of the user's tenancy. The optional OCI_COMPARTMENT and OCI_DATABASE parameters limit the scope of your request.

This authentication method is more secure than using a password verifier because a password verifier is considered sensitive. Also, only the database client can retrieve the database token. Applications or tools cannot pass these types of tokens through the database client API.

(i) Note

You can also use other IAM user credentials (such as API-key, security token, resource principal, service principal, instance principal, or delegation token) to get the db-token. This db-token is a proof-of-possession (PoP) token. In this case, you use a different parameter setting (TOKEN_AUTH=OCI_TOKEN).

Unlike the IAM database password that can only be used by the database client to retrieve the token, these credentials require an application or tool to retrieve the token. See TOKEN AUTH.

Default

PASSWORD_VERIFIER



Values and Examples

Value **Example**

For IAM database password verifier authentication: In the tnsnames.ora file:

PASSWORD_AUTH=PASSWORD_VERIFIER

Note: Use of IAM user name and IAM database password with the IAM database password verifier is the default configuration, and you do not need to set any additional parameters for the client.

However, if PASSWORD_AUTH is set to OCI_TOKEN in the client-side sqlnet.ora file, then the client tries to connect with OCI IAM to retrieve a database token using the IAM user name and IAM database password. In this case, you can override this setting for a particular connection using PASSWORD_AUTH=PASSWORD_VERIFIER.

net_service_name= (DESCRIPTION = (ADDRESS=(PROTOCOL=tcps) (HOST=sales-svr)(PORT=1521)) (SECURITY= (SSL_SERVER_DN_MATCH=TRUE) (SSL_SERVER_CERT_DN="C=US,O=example,C N=OracleContext") (PASSWORD_AUTH=PASSWORD_VERIFIER)) (CONNECT_DATA=(SERVICE_NAME=sales.us. example.com)) In the sqlnet.ora file:

PASSWORD_AUTH=PASSWORD_VERIFIER



Value

For IAM token-based authentication with the IAM user name and IAM database password:

PASSWORD AUTH=OCI TOKEN

Note: You must configure the TCPS protocol (PROTOCOL=tcps) and set the SSL_SERVER_DN_MATCH parameter to TRUE for token-based authentication.

Example

In the tnsnames.ora file:

```
net service name=
  (DESCRIPTION=
     (ADDRESS=(PROTOCOL=tcps)
(HOST=salesserver1)(PORT=1522))
     (SECURITY=
        (SSL_SERVER_DN_MATCH=TRUE)
(SSL_SERVER_CERT_DN="C=US,O=example,C
N=OracleContext")
        (PASSWORD_AUTH=OCI_TOKEN)
        (OCI_IAM_URL=https://auth.us-
region-1.example.com/v1/actions/
generateScopedAccessBearerToken)
(OCI_TENANCY=ocid1.tenancy..12345))
(CONNECT_DATA=(SERVICE_NAME=sales.us.
example.com))
  )
```

In the sqlnet.ora file:

SSL_SERVER_DN_MATCH=TRUE
PASSWORD_AUTH=OCI_TOKEN
OCI_IAM_URL=https://auth.usregion-1.example.com/v1/actions/
generateScopedAccessBearerToken
OCI_TENANCY=ocid1.tenancy..12345

In these examples, the optional OCI_COMPARTMENT and OCI_DATABASE parameters are not specified and thus the entire tenancy is set as the scope of the token request.

Related Topics

- Oracle AI Database Security Guide
- OCI IAM URL

Use the OCI_IAM_URL parameter to specify an endpoint URL that the database client must connect with to get the database token for authenticating Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) users on OCI Database as a Service (DBaaS).

OCI TENANCY

Use the OCI_TENANCY parameter to specify Oracle Cloud Identifier (OCID) of the user's tenancy.

OCI COMPARTMENT

Use the OCI_COMPARTMENT parameter to specify Oracle Cloud Identifier (OCID) of the compartment that holds database instances for client connections.



OCI DATABASE

Use the OCI_DATABASE parameter to specify Oracle Cloud Identifier (OCID) of the database that you want to access for the client connection.

5.2.31 RECV_BUF_SIZE

Use the sqlnet parameter RECV_BUF_SIZE to specify buffer space limit for session receive operations.

Purpose

To specify the buffer space limit for receive operations of sessions.

Usage Notes

You can override this parameter for a particular client connection by specifying the <u>RECV_BUF_SIZE</u> parameter in the connect descriptor for a client.

This parameter is supported by the TCP/IP, TCP/IP with TLS, and SDP protocols.



Additional protocols might support this parameter on certain operating systems. Refer to the operating system-specific documentation for additional information about additional protocols that support this parameter.

Default

The default value for this parameter is operating system specific. The default for Linux 2.6 operating system is 87380 bytes.

Example

RECV_BUF_SIZE=11784

Related Topics

Oracle Al Database Net Services Administrator's Guide

5.2.32 REDIRECT_URI

Use the REDIRECT_URI parameter to specify the redirect URI, registered for your Microsoft Entra ID client application.

Purpose

To specify the redirect URI (or reply URL), registered for your Entra ID client application. This is used for the AZURE_INTERACTIVE token-based authentication flow. This URL obtains the authorization code from the Entra authentication endpoint and determines which port to use to receive the authorization code.

Usage Notes

This is an optional parameter. If you do not specify this parameter, then it uses the default value of http://localhost, which is the most common redirect URL.



Specify this parameter only if necessary for your use case. The authorization server redirects the user to your specified address only if you have registered the redirect URI for the client application in the Azure portal, as shown in *Oracle AI Database Security Guide*.

You can specify this parameter along with the <code>TOKEN_AUTH=AZURE_INTERACTIVE</code> setting in the connect string, Easy Connect syntax, or <code>tnsnames.ora</code> file. The parameter value specified in the connect string takes precedence.

Default

The default redirect URI for all clients is:

```
http://localhost
```

Value

You can get a redirect URI value by logging in to the Azure portal. All URI values are listed as Redirect URIs on the App registrations - Authentication page of your Entra ID service.

Note that this is the value that you specified while registering your database client application with Entra ID.

Examples

In the thshames ora file:

```
net_service_name=
    (DESCRIPTION =
          (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr)(PORT=1521))
          (SECURITY=
                (SSL_SERVER_DN_MATCH=TRUE)
                (SSL_SERVER_CERT_DN="C=US,0=example,CN=OracleContext")
                (TOKEN_AUTH=AZURE_INTERACTIVE)
                (AZURE_DB_APP_ID_URI=https://application.example.com/
123ab4cd-1a2b-1234-a12b-aa00123b2cd3)
                (REDIRECT_URI=http://localhost:1575))
                (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))
                )
```

In the Easy Connect string:

```
tcps:sales-svr:1521/sales.us.example.com?
TOKEN_AUTH=AZURE_INTERACTIVE&AZURE_DB_APP_ID_URI=https://
application.example.com/123ab4cd-1a2b-1234-a12b-
aa00123b2cd3&REDIRECT_URI=http://localhost:1575
```

In these examples, the CLIENT_ID and TENANT_ID parameters are not specified. CLIENT_ID and TENANT_ID are required parameters when using the thick clients (OCI and Instant Client). These parameters are optional for the JDBC-thin and ODP.NET core and managed database clients, which can automatically get these values from the Azure SDK configuration.

Related Topics

Oracle Database Security Guide



TOKEN AUTH

Use the TOKEN_AUTH parameter to configure token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) or Microsoft Azure users of Microsoft Entra ID (previously called Microsoft Azure Active Directory).

5.2.33 SDP.PF INET SDP

Use the sqlnet parameter SDP.PF_INET_SDP to specify the protocol family or address family constant for the SDP protocol on your system.

Purpose

To specify the protocol family or address family constant for the SDP protocol on your system.

Default

27

Values

Any positive integer

Example

SDP.PF_INET_SDP=30

5.2.34 SEC_USER_AUDIT_ACTION_BANNER

Use the sqlnet parameter SEC_USER_AUDIT_ACTION_BANNER to specify a text file that contains the banner contents that warn users about user action auditing.

Purpose

To specify a text file containing the banner contents that warn users about possible user action auditing.

Usage Notes

You must specify the complete path of the text file in the sqlnet.ora file on the server. Oracle Call Interface (OCI) applications can use OCI features to retrieve this banner and display it to users.

Default

None

Values

Name of the file for which the database owner has read permissions.

Example

SEC_USER_AUDIT_ACTION_BANNER=/opt/oracle/admin/data/auditwarning.txt



5.2.35 SEC_USER_UNAUTHORIZED_ACCESS_BANNER

Use the sqlnet parameter SEC_USER_UNAUTHORIZED_ACCESS_BANNER to specify the file that contains the banner contents that warn users about unauthorized database access.

Purpose

To specify the name of a text file containing the banner contents that warn users about unauthorized access to the database.

Usage Notes

You must specify the complete path of the text file in the sqlnet.ora file on the server. OCI applications can use OCI features to retrieve this banner and display it to users.

Default

None

Values

Name of the banner file for which the database owner has read permissions.

Example

SEC_USER_UNAUTHORIZED_ACCESS_BANNER=/opt/oracle/admin/data/unauthwarning.txt

5.2.36 SEND BUF SIZE

Use the sqlnet parameter SEND BUF SIZE to specify the buffer space limit for session send operations.

Purpose

To specify the buffer space limit for send operations of sessions.

Usage Notes

You can override this parameter for a particular client connection by specifying the SEND BUF SIZE parameter in the connect descriptor for a client.

This parameter is supported by the TCP/IP, TCP/IP with TLS, and SDP protocols.



(i) Note

Additional protocols might support this parameter on certain operating systems. Refer to the operating system-specific documentation for additional information about additional protocols that support this parameter.

Default

The default value for this parameter is operating system specific. The default for Linux 2.6 operating systems is 16 KB.



Example

SEND_BUF_SIZE=11784

Related Topics

Oracle AI Database Net Services Administrator's Guide

5.2.37 SEPS_WALLET_LOCATION

Use the SEPS_WALLET_LOCATION parameter to specify the wallet location for secure external password store (SEPS) and to enable the use of specified wallet for authentication.

Purpose

To specify the directory path of the client-side oracle wallet and to configure the client to use secure external password store for authentication purposes. Setting this parameter causes all CONNECT /@db_connect_string statements to use the information in the SEPS wallet at the specified location to authenticate to databases.

Usage Notes

You can set SEPS_WALLET_LOCATION in the sqlnet.ora file to specify a common wallet location for all connections. You can also set it in the connect string or tnsnames.ora file to specify a different wallet location for a particular connection.

Use of SEPS_WALLET_LOCATION in the connect string or thsnames.ora overrides the sqlnet.ora SEPS_WALLET_LOCATION setting for the specific tnsnames.ora service.

To disable authentication using SEPS, you must unset SEPS_WALLET_LOCATION parameter. You must also unset SQLNET.WALLET_OVERRIDE or set it to FALSE in sqlnet.ora file.



(i) Note

If the SEPS WALLET LOCATION parameter is set, the SQLNET. WALLET OVERRIDE parameter is ignored.

Default

None

Examples

If you created the wallet in \$ORACLE_HOME/network/admin and your Oracle home is set to/ private/ora db, then you need to enter the following into your client sqlnet.ora file.

```
SEPS WALLET LOCATION=/private/ora db/network/admin
```

You can also set this parameter under the SECURITY section of the tnsnames.ora or directly as part of the command-line connect string. The parameter value specified in the connect string take precedence over the other specified values.

```
net_service_name=
  (DESCRIPTION=
    (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr)(PORT=1521))
```



```
(CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))
  (SECURITY=(SEPS_WALLET_LOCATION=/private/ora_db/network/admin)))
```

Related Topics

Oracle AI Database Security Guide

5.2.38 SQLNET.ALLOW_WEAK_CRYPTO

Use the sqlnet.ora compatibility parameter $SQLNET.ALLOW_WEAK_CRYPTO$ to configure your client-side network connection by reviewing the specified encryption and crypto-checksum algorithms.

Purpose

To configure your client-side network connection by reviewing the encryption and cryptochecksum algorithms enabled on the client and server. This ensures that the connection does not encounter compatibility issues and your configuration uses supported strong algorithms.

Usage Notes

• The DES, DES40, 3DES112, 3DES168, RC4_40, RC4_56, RC4_128, RC4_256, and MD5 algorithms are deprecated in this release.

As a result of this deprecation, Oracle recommends that you review your network encryption and integrity configuration to check if you have specified any of the deprecated weak algorithms.

To transition your Oracle Database environment to use stronger algorithms, download and install the patch described in My Oracle Support note <u>2118136.2</u>.

- If you set this parameter to TRUE, then you can specify deprecated algorithms for backward compatibility. This configuration allows patched clients to connect to unpatched servers, and thus such a connection is less secure.
- If you set this parameter to FALSE, then you can specify only supported algorithms so that
 clients and servers can communicate in a fully patched environment. The server enforces
 key fold-in for all Kerberos and JDBC thin clients. This configuration strengthens the
 connection between clients and servers by using strong native network encryption and
 integrity capabilities.

Using this setting, if native network encryption or checksumming is enabled and a patched server or client attempts to communicate with an unpatched old client or server, then the connection fails with an error message.

Values

- TRITE
- FALSE

Default Value

TRUE

Recommended Value

FALSE





(i) Note

Before setting this parameter to FALSE, you must remove all deprecated algorithms listed in the server and client sqlnet.ora files.

Example

SQLNET.ALLOW_WEAK_CRYPTO = FALSE

Related Topics

- Oracle AI Database Security Guide
- SOLNET.ENCRYPTION TYPES CLIENT Use the sqlnet.ora parameter SQLNET.ENCRYPTION_TYPES_CLIENT to specify the encryption algorithms this client or the server acting as a client uses.
- SQLNET.CRYPTO CHECKSUM TYPES CLIENT Use the sqlnet.ora parameter SQLNET.CRYPTO CHECKSUM TYPES CLIENT to specify a list of data integrity algorithms that this client or server acting as a client uses.

5.2.39 SQLNET.ALLOW WEAK CRYPTO CLIENTS

Use the sqlnet.ora compatibility parameter SQLNET.ALLOW WEAK CRYPTO CLIENTS to configure your server-side network connection by reviewing the specified encryption and cryptochecksum algorithms.

Purpose

To configure your server-side network connection by reviewing the encryption and cryptochecksum algorithms enabled on the client and server. This ensures that the connection does not encounter compatibility issues and your configuration uses supported strong algorithms.

Usage Notes

The DES, DES40, 3DES112, 3DES168, RC4 40, RC4 56, RC4 128, RC4 256, and MD5 algorithms are deprecated in this release.

As a result of this deprecation, Oracle recommends that you review your network encryption and integrity configuration to check if you have specified any of the deprecated weak algorithms.

To transition your Oracle Database environment to use stronger algorithms, download and install the patch described in My Oracle Support note 2118136.2.

- If you set this parameter to TRUE, then you can specify deprecated algorithms for backward compatibility. This configuration allows patched servers to connect to unpatched clients, and thus such a connection is less secure.
- If you set this parameter to FALSE, then you can specify only supported algorithms so that clients and servers can communicate in a fully patched environment. The server enforces key fold-in for all Kerberos and JDBC thin clients. This configuration strengthens the connection between clients and servers by using strong native network encryption and integrity capabilities.



Using this setting, if native network encryption or checksumming is enabled and a patched server or client attempts to communicate with an unpatched old client or server, then the connection fails with an error message.

Values

- TRUE
- FALSE

Default Value

TRUE

Recommended Value

FALSE



Note

Before setting this parameter to FALSE, you must remove all deprecated algorithms listed in the server and client sqlnet.ora files.

Example

SQLNET.ALLOW WEAK CRYPTO CLIENTS = FALSE

Related Topics

- Oracle AI Database Security Guide
- SOLNET.ENCRYPTION TYPES SERVER Use the sqlnet.ora parameter SQLNET.ENCRYPTION TYPES SERVER to specify the encryption algorithms this server uses in the order of the intended use.
- SQLNET.CRYPTO CHECKSUM TYPES SERVER Use the sqlnet.ora parameter SQLNET.CRYPTO_CHECKSUM_TYPES_SERVER to specify the data integrity algorithms that this server or client to another server uses, in order of intended use.

5.2.40 SQLNET.ALLOWED LOGON VERSION CLIENT

Use the sqlnet parameter SQLNET.ALLOWED_LOGON_VERSION_CLIENT to define minimum authentication protocols that servers acting as clients to other servers can use for connecting to Oracle Database instances.

Purpose

To set the minimum authentication protocol allowed for clients when a server is acting as a client, such as connecting over a database link, when connecting to Oracle Database instances.

Usage Notes

The term VERSION in the parameter name refers to the version of the authentication protocol, not the version of the Oracle Database release.



If the version does not meet or exceed the value defined by this parameter, then authentication fails with an ORA-28040: The database does not accept your client's authentication protocol; login denied error.

The database password verifier for Oracle Database 10g, 10g is no longer supported or available on Oracle AI Database 26ai. Refer to the database upgrade guide preinstallation chapters for information about how to identify the Oracle Database 10G database password verifiers, and how to update the database user to use the latest and most secure database password verifier cryptography.

Values

12a for Oracle Database 12c Release 1 (12.1.0.2) or later (strongest protection)



(i) Note

Using this setting, the clients can only authenticate using a de-optimized password version. For example, the 12C password version.

12 for the critical patch updates CPUOct2012 and later Oracle Database 11g authentication protocols (default setting)



(i) Note

Using this setting, the clients can only authenticate using a verifier that uses salt. For example, the 11g or 12c password versions.

Default

12

Example

If an Oracle AI Database 26ai database hosts a database link to an Oracle Database 19q database, then set the SQLNET.ALLOWED LOGON VERSION CLIENT parameter as follows for the database link connection to proceed:

SQLNET.ALLOWED_LOGON_VERSION_CLIENT=12

In this case, you cannot configure the more secure SQLNET.ALLOWED LOGON VERSION CLIENT setting of 12a on the 26ai server hosting the database link because the account on the Oracle Database 19g database might not have its password changed and thus might only have the 11G verifier.

Related Topics

- Oracle Al Database Reference
- Oracle Al Database Security Guide
- Oracle Al Database Upgrade Guide



5.2.41 SQLNET.ALLOWED_LOGON_VERSION_SERVER

Use the sqlnet.ora parameter $SQLNET.ALLOWED_LOGON_VERSION_SERVER$ to set the minimum authentication protocol that is permitted when connecting to Oracle Database instances.

Purpose

To set the minimum authentication protocol for connecting to Oracle Database instances.

Usage Notes

Authentication Protocol Versions:

The term VERSION in the parameter name refers to the version of the authentication protocol, not the Oracle Database release.

A value that appears higher up in <u>Table 5-1</u> is less compatible (in terms of the protocol that clients must understand in order to authenticate) but simultaneously more secure than a value that appears lower down. The server is also more restrictive in terms of the password version that must exist to authenticate any specific account. Whether a client can authenticate to a specific account depends on both the server's setting of its SQLNET.ALLOWED_LOGON_VERSION_SERVER parameter, as well as on the password versions that exist for the specified account. You can see the list of password versions in file DBA_USERS.PASSWORD_VERSIONS.

If the client does not have the ability listed in the "Ability Required of the Client" column that corresponds to the row that matches the value of the

SQLNET.ALLOWED_LOGON_VERSION_SERVER parameter in <u>Table 5-1</u>, then authentication fails with an ORA-28040: The database does not accept your client's authentication protocol; login denied or an ORA-03134: Connections to this server version are no longer supported error.

A setting of 12 (the default) enables only the 11G and 12C password versions. A setting of 12a enables only the 12C password version.

Note the following implications of setting the value to 12 or 12a:

- Releases of OCI clients earlier than Oracle Database 10g cannot authenticate to the Oracle database using password-based authentication.
- If an older client (such as Oracle Database 10g, which has the critical patch update CPUOct2012 and thus has the O5L_NP capability) attempts to authenticate to a more recent server and the server that it is authenticating to does not have the necessary 11G password version (which is required to authenticate to such an older client), then the client will receive an ORA-03134: Connections to this server version are no longer supported error message.

To enable older Oracle Database 10*g* clients to authenticate when the server is using the default SQLNET.ALLOWED_LOGON_VERSION_SERVER=12 setting, ensure that the PASSWORD_VERSIONS value (found in DBA_USERS) for the account contains the value 11G (meaning that an SHA-1 verifier has been provisioned for the account). You may need to reset the password of the account if 11G does not appear in the list of password versions of the account. Resetting the password of the account automatically causes the server to provision the necessary 11G password version for the authentication of older clients (which have the 05L NP capability).

 To take advantage of the 12C password version introduced in Oracle Database release 12.2, user passwords should be expired to encourage users to change their passwords and cause the new 12C password version to be generated for their account.



By default, new passwords are treated in a case-sensitive fashion. When an account password is changed, the earlier 10g case-insensitive password version and the 11g password version are both automatically removed, and the new 12C password version is generated.

JDBC Thin Client Support:

In Oracle Database release 12.1.0.2 and later, if you set the sqlnet.ora parameter SQLNET.ALLOWED LOGON VERSION SERVER to 12a and you create a new account or change the password of an existing account, then only the new 12C password version is generated. The 12C password version is based on a SHA-2 (Secure Hash Algorithm) SHA-512 salted cryptographic hash deoptimized using the PBKDF2 (Password-Based Key Derivation Function 2) algorithm. When the database server is running with ALLOWED LOGON VERSION SERVER set to 12a, it is running in exclusive mode. In this mode, to log in using a JDBC client, the JRE version must be at least version 8. The JDBC client enables its 07L MR capability flag only when it is running with at least version 8 of the JRE.

(i) Note

Check the PASSWORD_VERSIONS column of the DBA_USERS catalog view in Oracle Database Reference to see the list of password versions for any given account.

If you set the sqlnet.ora parameter SQLNET.ALLOWED LOGON VERSION SERVER to 12, then the server runs in exclusive mode and only the 11g and 12g password versions (the SHA-1 and PBKDF2 SHA-2 based hashes of the password, respectively) are generated and allowed to be used. In such cases, fully-patched JDBC clients having the CPUOct2012 patch can connect because these JDBC clients provide the 05L_NP client ability.

Older JDBC clients that do not have the CPUOct2012 containing the fix for the stealth password cracking vulnerability CVE-2012-3132, do not provide the O5L NP client ability. Therefore, ensure that all of the JDBC clients are patched properly.

Desupport of Oracle Database 10G Password Verifier

The database password verifier for Oracle Database 10g, 10g is no longer supported or available on Oracle AI Database 26ai. Refer to the database upgrade guide preinstallation chapters for information about how to identify the Oracle Database 10G database password verifiers, and how to update the database user to use the latest and most secure database password verifier cryptography.

Be aware that the older client capabilities are not sufficient to authenticate with more modern servers because these servers use the default configuration of ALLOWED LOGON VERSION SERVER=12 and do not support the 10g verifier. You should upgrade all clients to Oracle Database release 12c so that the 12c password version can be used exclusively to authenticate. By default, Oracle Database release 11.2.0.3 and later clients have the O5L NP ability, which enables the 11g password version to be used exclusively. If you have an earlier Oracle Database client, then you must install the CPUOct2012 patch.

Client Capabilities:

The client must support certain abilities of the authentication protocol before the server will authenticate. If the client does not support a specified authentication ability, then the server rejects the connection with an ORA-28040 "The database does not accept your client's authentication protocol; login denied. " error message.



The following is the list of all client abilities. Some clients do not have all the listed abilities. Clients that are more recent have all of the capabilities of the older clients, but older clients tend to have fewer abilities than more recent clients. An ability that appears at the top in this list is more recent and secure than an ability that appears lower toward the bottom:

- O8L_LI: The ability to support long identifiers (user names up to 128 bytes).
- O7L_MR: The ability to perform the Oracle Database 10g authentication protocol using the 12C password version. For JDBC clients, only those running on at least JRE version 8 offer the O7L_MR capability.
- O5L_NP: The ability to perform Oracle Database 10g authentication protocols using the 11g password version, and generating a session key encrypted for critical patch update CPUOct2012.
- 05L (desupported with Oracle Al Database 26ai): The ability to perform the Oracle Database 10g authentication protocol using the 10g password version.
- 04L (desupported with Oracle AI Database 26ai): The ability to perform the Oracle9i database authentication protocol using the 10g password version.
- 03L (desupported with Oracle AI Database 26ai): The ability to perform the Oracle8i database authentication protocol using the 10g password version.

Using the Gradual Database Password Rollover Feature

When the gradual database password rollover feature is enabled for an account, the LOGON_INFO clause in the audit record enables you to see whether the user has logged in with the old password or whether an application has not yet been updated to log in using the new password.

For example:

```
(TYPE=(DATABASE));
(CLIENT ADDRESS=((PROTOCOL=ipc)(HOST=0.0.0)));
(LOGON_INFO=((VERIFIER=11G-OLD)
(CLIENT CAPABILITIES=05L NP,07L MR,08L LI)));
```

Allowed Parameter Settings:

The following table describes the allowed settings of the SQLNET.ALLOWED_LOGON_VERSION_SERVER parameter, its effect on the generated password versions when an account is created or a password is changed, the ability flag required of the client to authenticate while the server has this setting, and whether the setting is considered to be an exclusive mode.

Table 5-1 SQLNET.ALLOWED_LOGON_VERSION_SERVER Settings

Value of the ALLOWED_LOG ON_VERSION_S ERVER Parameter	Generated Password Version	Ability Required of the Client	Meaning for Clients	Server Runs in Exclusive Mode
12a	12C	O7L_MR	Only Oracle Database 12c release 1 (12.1.0.2 or later) clients can connect to the server.	Yes because it excludes the use of 11G password version.



Table 5-1 (Cont.) SQLNET.ALLOWED_LOGON_VERSION_SERVER Settings

Value of the ALLOWED_LOG ON_VERSION_S ERVER Parameter	Generated Password Version	Ability Required of the Client	Meaning for Clients	Server Runs in Exclusive Mode
12	11G, 12C	O5L_NP	Oracle Database 11 g release 2 (11.2.0.3 or later) clients can connect to the server. Older clients need the critical patch update CPUOct2012 or later, to gain the 05L_NP ability. Only older clients that have applied critical patch update CPUOct2012 or Update CPUOct2012 or	Yes because it excludes the use of the 10G password version.
			later can connect to the server.	

Values

- 12a for Oracle Database 12c release 12.1.0.2 or later authentication protocols (strongest protection)
- 12 for Oracle Database 12c release 12.1 authentication protocols (default and recommended value)

Note

- Starting with Oracle Database 12c Release 2 (12.2), the default value is 12.
- For earlier releases, the value 12 can be used after the critical patch updates CPUOct2012 and later are applied.

Default

12

Example

SQLNET.ALLOWED_LOGON_VERSION_SERVER=12

Related Topics

- Ensuring Against Password Security Threats by Using the 12C Password Version
- Managing Gradual Database Password Rollover for Applications
- Oracle Al Database Upgrade Guide



5.2.42 SQLNET.AUTHENTICATION_SERVICES

Use the sqlnet.ora parameter SQLNET.AUTHENTICATION_SERVICES to enable one or more authentication services.

Purpose

To enable one or more authentication services. If you have installed authentication, then Oracle recommends that you set <code>SQLNET.AUTHENTICATION_SERVICES</code> to either <code>NONE</code> or to one of the listed authentication methods.

Usage Notes

You can set this parameter in the sqlnet.ora file.

You can also set this value in the tnsnames.ora file or directly as part of the connect string. The SQLNET.AUTHENTICATION_SERVICES parameter is equivalent to the tnsnames.ora parameter AUTHENTICATION_SERVICE. The parameter value specified in the connect string takes precedence.

- When you set SQLNET.AUTHENTICATION_SERVICES to ALL, the server attempts to authenticate using each of the following methods.
 - Authentication based on a service external to the database, such as a service on the network layer, Kerberos, or RADIUS.
 - Authentication based on the operating system user's membership in an administrative operating system group. Group names are platform-specific. This authentication applies to administrative connections only.
 - 3. Authentication performed by the database.
 - 4. Authentication based on credentials stored in a directory server.

The server falls back to the authentication methods that appear further down on the list if attempts to use the authentication methods appearing higher on the list were unsuccessful.

- When using local database password authentication (no external authentication), set SQLNET.AUTHENTICATION_SERVICES=(NONE) for better client performance.
- Operating system authentication enables access to the database using any user name and any password when an administrative connection is attempted to the CDB root, such as using the AS SYSDBA clause when connecting using SQL*Plus.

An example of a connection to the CDB root is as follows.

sqlplus ignored_username/ignored_password AS SYSDBA

When the operating-system user who issued the preceding command is already a member of the appropriate administrative operating system group, then the connection is successful. This is because Oracle checks the group membership first, and thus the user name and password are ignored by the server.

Values

Authentication methods that are available with Oracle Net Services are:

- NONE for no authentication methods, including Microsoft Windows native operating system authentication. When you set SQLNET.AUTHENTICATION_SERVICES to NONE, then the user can use a valid user name and password to access the database.
- ALL for all authentication methods.



- BEQ for native operating system authentication for operating systems other than Microsoft Windows.
- KERBEROS5 for Kerberos authentication.
- RADIUS for Remote Authentication Dial-In User Service (RADIUS) authentication.
- TCPS for TLS authentication.
- NTS for Microsoft Windows native operating system authentication. In this case, the user must authenticate to the database (CDB root) with OS credentials using Windows native authentication. No external password is needed. NTS checks the group membership for an OS user. For example, if an OS user is a member of the ORA DBA group, then the user can log in to the database as SYSDBA.



(i) Note

With the SQLNET.AUTHENTICATION_SERVICES value NTS, if you try to connect through SQL*Plus using NTS authentication and specify an external password (for example, SQL*Plus SYSTEM/password), then the connection fails with an ORA-12638, 00000, "Failed to retrieve credentials for adapter_name. error message. For regular user name and password based authentication, set the value to NONE.

Default

TCPS



(i) Note

When installing Oracle Database with Database Configuration Assistant (DBCA), you can set this parameter to NTS in the sqlnet.ora file.

Examples

When specifying multiple authentication services, you must enclose the values within parentheses as follows:

SQLNET.AUTHENTICATION_SERVICES=(BEQ, KERBEROS5)

If you want to specify only a single authentication service, then parentheses are not required:

SQLNET.AUTHENTICATION SERVICES=KERBEROS5

Related Topics

- Configuring Authentication
- Setting the SQLNET.AUTHENTICATION SERVICES Parameter in sqlnet.ora
- **AUTHENTICATION SERVICE**

Use the tnsnames.ora parameter AUTHENTICATION_SERVICE to enable an authentication service.



5.2.43 SQLNET.BREAK_RESET_TIMEOUT

Use the sqlnet.ora parameter SQLNET.BREAK_RESET_TIMEOUT to specify the duration of time that a database client or server should wait for the completion of break/reset operation.

Purpose

To specify the time for a database client or server to wait for the break/reset operation to complete. If the break/reset operation does not complete in the specified time interval, then the connection is closed.

You can specify the time in hours, minutes, seconds, or milliseconds by using the hr, min, sec, or ms keyword respectively. If you do not specify a unit of measurement, then the default unit is sec.

Usage Notes

Setting this parameter ensures that the peer is not left waiting indefinitely for the completion of break/reset operation. If a peer does not receive response data within the specified BREAK_RESET_TIMEOUT interval, the connection will be closed. If you set the timeout interval, then set the value initially to a low value and adjust the value according to the system and network capacity.

Default

None

Minimum Value

1 ms

Allowed Range

Any number greater than the minimum value of 1 ms up to 4294967295 ms

Example

SQLNET.BREAK_RESET_TIMEOUT=10 ms

Related Topics

Oracle AI Database Net Services Administrator's Guide

5.2.44 SQLNET.CLIENT_REGISTRATION

Use the ${\tt sqlnet.ora}$ parameter ${\tt SQLNET.CLIENT_REGISTRATION}$ to set a unique identifier for the client computer.

Purpose

To set a unique identifier for the client computer.

Usage Notes

This identifier is passed to the listener with any connection request and is included in the audit trail. The identifier can be any alphanumeric string up to 128 characters long.



Default

None

Example

SQLNET.CLIENT_REGISTRATION=1432

5.2.45 SQLNET.CLOUD_USER

Use the sqlnet.ora parameter SQLNET.CLOUD_USER to specify a user name for web server HTTP basic authentication.

Purpose

To specify a user name for web server HTTP basic authentication.

Usage Notes

When you use a secure websocket protocol, the client uses this user as the user name for authentication. The password for this user should be stored in a wallet using mkstore commands.

Perform the following configuration steps to use HTTP basic authentication with secure websockets:

1. Create a wallet using the orapki utility.

```
orapki wallet create -wallet wallet_directory
Example
orapki wallet create -wallet /app/wallet
```

2. Add a web server public certificate.

```
orapki wallet -wallet wallet_directory -trusted_cert -cert web_server_public_certificate_in_pem_format 
Example
```

```
orapki wallet -wallet /app/wallet -trusted_cert -cert server_cert.txt
```

3. Add the web server user name to sqlnet.ora. This user name is only used for authenticating the web server. This is not a database user name. After web server authentication, the web server connects to the back-end database server and database authentication is completed.

Example

```
sqlnet.cloud_user = dbuser1
```

4. Add a web server user password to the wallet.

```
\label{location} \verb| -createEntry username password | \\ \textbf{Example} \\
```

```
mkstore -wrl /app/wallet -createEntry dbuser1 Secretdb#
```

5. Make the wallet automatically log in and protect this wallet directory using operating system file permissions or any other means. Do this so that only the database client can have read access to it. Refer to the operating system utilities for information about changing the file permissions.

```
orapki wallet create -wallet wallet_directory -auto_login
```



Example

orapki wallet create -wallet /app/wallet -auto_login



(i) Note

Oracle has introduced a new auto-login wallet version (7) with Oracle AI Database 26ai. Version 6 of the Oracle local auto-login wallet is deprecated.

You can update your local auto-login wallet by modifying it with orapki.

6. Update the sqlnet.ora file with the wallet entry.

Example

wallet location=(SOURCE=(METHOD=file)(METHOD DATA=(DIRECTORY=/app/wallet)))

(i) Note

- The parameter WALLET_LOCATION is deprecated for use with Oracle AI Database 26ai for the Oracle Database server. It is not deprecated for use with the Oracle Database client or listener.
 - For Oracle Database server, Oracle recommends that you use the WALLET_ROOT system parameter instead of using WALLET LOCATION.
- The mkstore wallet management command line tool is deprecated with Oracle Al Database 26ai, and can be removed in a future release.

To manage wallets, Oracle recommends that you use the orapki command line tool.

Default

None

Related Topics

Oracle AI Database Security Guide

5.2.46 SQLNET.COMPRESSION

Use the sqlnet.ora parameter SQLNET.COMPRESSION to enable or disable data compression.

Purpose

To enable or disable data compression. If both the server and client have this parameter set to ON, then compression is used for the connection.



Note

The SQLNET. COMPRESSION parameter applies to all database connections, except for Oracle Data Guard streaming redo and SecureFiles LOBs (Large Objects).



Default

off

Values

- on to enable data compression.
- off to disable data compression.

Example

SQLNET.COMPRESSION=on

5.2.47 SQLNET.COMPRESSION_ACCELERATION

Use the sqlnet.ora parameter SQLNET.COMPRESSION_ACCELERATION to specify the use of hardware accelerated version of compression using this parameter if it is available for that platform.

Purpose

To specify the use of hardware accelerated version of compression using this parameter if it is available for that platform.

Usage Notes

You can set this parameter in the Oracle Connection Manager alias description.

Default

on

Values

- on
- off
- 0
- 1

Example 5-4 Example

compression_acceleration = on

5.2.48 SQLNET.COMPRESSION_LEVELS

Use the sqlnet.ora parameter SQLNET.COMPRESSION LEVELS to specify the compression level.

Purpose

To specify the compression level.

Usage Notes

The compression levels are used at the time of negotiation to verify which levels are used at both ends, and to select one level.



For Database Resident Connection Pooling (DRCP), only the compression level low is supported.

Default

low

Values

- low to use low CPU usage and low compression ratio
- high to use high CPU usage and high compression ratio

Example

SQLNET.COMPRESSION_LEVELS=(high)

5.2.49 SQLNET.COMPRESSION_THRESHOLD

Use the sqlnet.ora parameter SQLNET.COMPRESSION_THRESHOLD to specify the minimum data size for which compression is needed.

Purpose

To specify the minimum data size, in bytes, for which compression is needed.

Usage Notes

Compression is not to be performed if the size of the data you are sending is less than this value

Default

1024 bytes

Example

 ${\tt SQLNET.COMPRESSION_THRESHOLD=1024}$

5.2.50 SQLNET.CRYPTO_CHECKSUM_CLIENT

Use the sqlnet.ora parameter $SQLNET.CRYPTO_CHECKSUM_CLIENT$ to specify the desired data integrity behavior when this client or server acting as a client connects to a server.

Purpose

To specify the checksum behavior for the client. The behavior partially depends on the SQLNET.CRYPTO_CHECKSUM_SERVER setting at the other end of the connection.

Default

accepted

Values

- accepted to enable the security service if required or requested by the other side
- rejected to disable the security service, even if required by the other side
- requested to enable the security service if the other side allows it



 required to enable the security service and disallow the connection if the other side is not enabled for the security service

Example

SQLNET.CRYPTO_CHECKSUM_CLIENT=accepted

5.2.51 SQLNET.CRYPTO_CHECKSUM_SERVER

Use the sqlnet.ora parameter SQLNET.CRYPTO_CHECKSUM_SERVER to specify the data integrity behavior when a client or another server acting as a client connects to this server.

Purpose

To specify the checksum behavior for the database. The behavior partially depends on the SQLNET.CRYPTO_CHECKSUM_CLIENT setting at the other end of the connection.

Default

accepted

Values

- accepted to enable the security service if required or requested by the other side
- rejected to disable the security service, even if required by the other side
- requested to enable the security service if the other side allows it
- required to enable the security service and disallow the connection if the other side is not enabled for the security service

Example

SQLNET.CRYPTO_CHECKSUM_SERVER=accepted

5.2.52 SQLNET.CRYPTO_CHECKSUM_TYPES_CLIENT

Use the sqlnet.ora parameter SQLNET.CRYPTO_CHECKSUM_TYPES_CLIENT to specify a list of data integrity algorithms that this client or server acting as a client uses.

Purpose

To specify a list of crypto-checksum algorithms for the client to use.

This list is used to negotiate a mutually acceptable algorithm with the other end of the connection. If an algorithm that is not installed on this side is specified, the connection terminates with the ORA-12650: No common encryption or data integrity algorithm error error message.

Default

All available algorithms

Values

MD5 for the RSA Data Security MD5 algorithm



The MD5 algorithm is deprecated in this release. To transition your Oracle Database environment to use stronger algorithms, download and install the patch described in My Oracle Support note 2118136.2.

SHA1 for the Secure Hash Algorithm

The use of SHA-1 with DBMS_CRYPTO, SQLNET.CRYPTO_CHECKSUM_TYPES_CLIENT and SQLNET.CRYPTO_CHECKSUM_TYPES_SERVER is deprecated.

Using SHA-1 (Secure Hash Algorithm 1) with the parameters SQLNET.CRYPTO_CHECKSUM_TYPES_CLIENT and SQLNET.CRYPTO_CHECKSUM_TYPES_SERVER is deprecated in this release, and can be desupported in a future release. Using SHA-1 ciphers with DBMS_CRYPTO is also deprecated (HASH_SH1, HMAC_SH1). Instead of using SHA1, Oracle recommends that you start using a stronger SHA-2 cipher in place of the SHA-1 cipher.

- SHA256 for SHA-2 uses 256 bits with the hashing algorithm
- SHA384 for SHA-2 uses 384 bits with the hashing algorithm
- SHA512 for SHA-2 uses 512 bits with the hashing algorithm

Example

SQLNET.CRYPTO_CHECKSUM_TYPES_CLIENT=(SHA256, MD5)

5.2.53 SQLNET.CRYPTO CHECKSUM TYPES SERVER

Use the sqlnet.ora parameter SQLNET.CRYPTO_CHECKSUM_TYPES_SERVER to specify the data integrity algorithms that this server or client to another server uses, in order of intended use.

Purpose

To specify a list of crypto-checksum algorithms for the database to use.

This list is used to negotiate a mutually acceptable algorithm with the other end of the connection. Each algorithm is checked against the list of available client algorithm types until a match is found. If an algorithm is specified that is not installed on this side, the connection terminates with the ORA-12650: No common encryption or data integrity algorithm error error message.

Default

All available algorithms

Values

MD5 for the RSA Data Security's MD5 algorithm

The MD5 algorithm is deprecated in this release. To transition your Oracle Database environment to use stronger algorithms, download and install the patch described in My Oracle Support note 2118136.2.

SHA1 for the Secure Hash algorithm

The use of SHA-1 with DBMS_CRYPTO, SQLNET.CRYPTO_CHECKSUM_TYPES_CLIENT and SQLNET.CRYPTO_CHECKSUM_TYPES_SERVER is deprecated.

Using SHA-1 (Secure Hash Algorithm 1) with the parameters SQLNET.CRYPTO_CHECKSUM_TYPES_CLIENT and SQLNET.CRYPTO_CHECKSUM_TYPES_SERVER is deprecated in this release, and can be desupported in a future release. Using SHA-1 ciphers with DBMS_CRYPTO is also deprecated (HASH_SH1, HMAC_SH1). Instead of using SHA1,



Oracle recommends that you start using a stronger SHA-2 cipher in place of the SHA-1 cipher.

- SHA256 for SHA-2 uses 256 bits with the hashing algorithm
- SHA384 for SHA-2 uses 384 bits with the hashing algorithm
- SHA512 for SHA-2 uses 512 bits with the hashing algorithm

Example

SQLNET.CRYPTO_CHECKSUM_TYPES_SERVER=(SHA256, MD5)

5.2.54 SQLNET.DBFW_PUBLIC_KEY

Use the sqlnet.ora parameter SQLNET.DBFW_PUBLIC_KEY to provide Oracle Database Firewall public keys to the Advanced Security Option (ASO) by specifying the file that stores the public keys.

Purpose

To provide Oracle Database Firewall public keys to Advanced Security Option (ASO) by specifying the name of the file that stores the Oracle Database Firewall public keys.

Default

None

Values

Full path name of the operating system file that has the public keys

Example

SQLNET.DBFW_PUBLIC_KEY="/path to file/dbfw public key file.txt"



"SQLNET.ENCRYPTION_TYPES_SERVER"

5.2.55 SQLNET.DOWN_HOSTS_TIMEOUT

Use the sqlnet.ora parameter SQLNET.DOWN_HOSTS_TIMEOUT to specify the amount of time in seconds that server hosts down state information remains in the client cache.

Purpose

To specify the amount of time in seconds that information about the down state of server hosts is kept in the client process cache.

Usage Notes

Clients discover the down state of server hosts when attempting connections. When a connection attempt fails, the information about the down state of the server host is added to the client process cache. Subsequent connection attempts by the same client process move the addresses of the down hosts to the end of the address list, thereby reducing the priority of down



hosts. When the duration of time that is specified by the SQLNET.DOWN_HOSTS_TIMEOUT parameter has elapsed, the host is purged from the process cache and its priority in the address list is restored.

Default

600 seconds (10 minutes)

Values

Any positive integer

Example

SOLNET.DOWN HOSTS TIMEOUT=60

5.2.56 SQLNET.ENCRYPTION CLIENT

Use the sqlnet.ora parameter SQLNET.ENCRYPTION_CLIENT to set the encryption behavior when this client or server acting as a client connects to a server.

Purpose

To enable encryption for clients. Setting the tnsnames.ora parameter IGNORE_ANO_ENCRYPTION_FOR_TCPS to TRUE disables SQLNET.ENCRYPTION_CLIENT.

The behavior of the client partially depends on the value set for SQLNET.ENCRYPTION_SERVER at the other end of the connection.

Default

accepted

Values

- accepted to enable the security service if required or requested by the other side
- rejected to disable the security service, even if required by the other side
- requested to enable the security service if the other side allows it
- required to enable the security service and disallow the connection if the other side is not enabled for the security service

Example

SQLNET.ENCRYPTION_CLIENT=accepted

5.2.57 SQLNET.ENCRYPTION SERVER

The sqlnet.ora parameter SQLNET.ENCRYPTION_SERVER specifies the encryption behavior when a client or a server acting as a client connects to this server.

Purpose

To enable encryption for the database. Setting SQLNET.IGNORE_ANO_ENCRYPTION_FOR_TCPS to FALSE disables SQLNET.ENCRYPTION_SERVER.

The behavior of the server partially depends on the SQLNET.ENCRYPTION_CLIENT setting at the other end of the connection.



Default

accepted

Values

- accepted to enable the security service if required or requested by the other side
- rejected to disable the security service, even if required by the other side
- requested to enable the security service if the other side allows it
- required to enable the security service and disallow the connection if the other side is not enabled for the security service

Example

SQLNET.ENCRYPTION_SERVER=accepted

5.2.58 SQLNET.ENCRYPTION_TYPES_CLIENT

Use the sqlnet.ora parameter SQLNET.ENCRYPTION_TYPES_CLIENT to specify the encryption algorithms this client or the server acting as a client uses.

Purpose

This list is used to negotiate a mutually acceptable algorithm with the other end of the connection. If an algorithm that is not installed is specified on this side, the connection terminates with the ORA-12650: No common encryption or data integrity algorithm error message.

Usage Notes

Starting with Oracle Database 21c, older encryption and hashing algorithms are deprecated.

The deprecated algorithms for DBMS_CRYPTO and native network encryption include MD4, MD5, DES, 3DES, and RC4-related algorithms as well as 3DES for Transparent Data Encryption (TDE). Removing older, less secure cryptography algorithms prevents accidental use of these algorithms. To meet your security requirements, Oracle recommends that you use more modern cryptography algorithms, such as the Advanced Encryption Standard (AES).

As a consequence of this deprecation, Oracle recommends that you review your network encryption configuration to see if you have specified use of any of the deprecated algorithms. If any are found, then switch to using a more modern cipher, such as AES. Also, if you are currently using 3DES encryption for your TDE deployment, then you should plan to migrate to a more modern algorithm such as AES. For more information, refer to *Oracle Database Security Guide*

To transition your Oracle Database environment to use stronger algorithms, download and install the patch described in My Oracle Support note <u>2118136.2</u>.

Default

All available algorithms

Values

Approved algorithms:

AES128 for AES (128-bit key size)



- AES192 for AES (192-bit key size)
- AES256 for AES (256-bit key size)

Deprecated algorithms:

- 3DES112 for triple DES with a two-key (112-bit) option
- 3DES168 for triple DES with a three-key (168-bit) option
- DES for standard DES (56-bit key size)
- DES40 for DES (40-bit key size)
- RC4_40 for RSA RC4 (40-bit key size)
- RC4_56 for RSA RC4 (56-bit key size)
- RC4_128 for RSA RC4 (128-bit key size)
- RC4_256 for RSA RC4 (256-bit key size)

Example

SQLNET.ENCRYPTION_TYPES_CLIENT=(AES256)

5.2.59 SQLNET.ENCRYPTION TYPES SERVER

Use the sqlnet.ora parameter $SQLNET.ENCRYPTION_TYPES_SERVER$ to specify the encryption algorithms this server uses in the order of the intended use.

Purpose

This list is used to negotiate a mutually acceptable algorithm with the client end of the connection. Each algorithm is checked against the list of available client algorithm types until a match is found. If an algorithm that is not installed is specified on this side, the connection terminates with an ORA-12650: No common encryption or data integrity algorithm error message.

Default

All available algorithms

Values

Approved algorithms:

- AES128 for AES (128-bit key size)
- AES192 for AES (192-bit key size)
- AES256 for AES (256-bit key size)

Deprecated algorithms:

- 3DES112 for triple DES with a two-key (112-bit) option
- 3DES168 for triple DES with a three-key (168-bit) option
- DES for standard DES (56-bit key size)
- DES40 for DES40 (40-bit key size)
- RC4_40 for RSA RC4 (40-bit key size)
- RC4_56 for RSA RC4 (56-bit key size)



- RC4_128 for RSA RC4 (128-bit key size)
- RC4_256 for RSA RC4 (256-bit key size)

Starting with Oracle Database 21c, older encryption and hashing algorithms are deprecated.

The deprecated algorithms for DBMS_CRYPTO and native network encryption include MD4, MD5, DES, 3DES, and RC4-related algorithms as well as 3DES for Transparent Data Encryption (TDE). Removing older, less secure cryptography algorithms prevents accidental use of these algorithms. To meet your security requirements, Oracle recommends that you use more modern cryptography algorithms, such as the Advanced Encryption Standard (AES).

As a consequence of this deprecation, Oracle recommends that you review your network encryption configuration to see if you have specified use of any of the deprecated algorithms. If any are found, then switch to using a more modern cipher, such as AES. Also, if you are currently using 3DES encryption for your TDE deployment, then you should plan to migrate to a more modern algorithm such as AES. For more information, refer to *Oracle Database Security Guide*

To transition your Oracle Database environment to use stronger algorithms, download and install the patch described in My Oracle Support note <u>2118136.2</u>.

Example

SQLNET.ENCRYPTION_TYPES_SERVER=(AES256, AES192, ...)

5.2.60 SQLNET.EXPIRE_TIME

Use the sqlnet.ora parameter SQLNET.EXPIRE_TIME to specify how often, in minutes, to verify that client and server connections are alive.

Purpose

To specify time intervals, in minutes, for how often to verify that client and server connections are alive.

Usage Notes

Setting a value greater than 0 ensures that connections are not left open indefinitely due to an unusual client termination. If your environment supports TCP keepalive tuning, then Oracle Net Services automatically uses the enhanced detection model and tunes the TCP keepalive parameters.

If the verification check identifies a terminated connection or a connection that is no longer usable, then the check returns an error, causing the server process to exit.

The sqlnet.ora parameter SQLNET.EXPIRE_TIME is primarily intended for the database server, which typically handles multiple connections simultaneously.

You can also use this parameter for database clients to verify if the server connection is alive.

Limitations on using the terminated connection detection feature are:

- You cannot use it on bequeathed connections.
- Though very small, a probe packet generates additional traffic that may degrade your network performance.
- Depending on your operating system, the server may need to perform additional processing to distinguish the connection probing event from other events. This can also result in degraded network performance.



Default

0

Minimum Value

0

Recommended Value

10

Example

SQLNET.EXPIRE_TIME=10

5.2.61 SQLNET.IGNORE ANO ENCRYPTION FOR TCPS

Use the sqlnet.ora parameter SQLNET.IGNORE_ANO_ENCRYPTION_FOR_TCPS to ignore the value that is set for the parameter SQLNET.ENCRYPTION_SERVER for TCPS connections. This disables ANO encryption on the TCPS listener.

Purpose

Use SQLNET.IGNORE_ANO_ENCRYPTION_FOR_TCPS on your server to ignore the value that is set for SQLNET.ENCRYPTION_SERVER for TCPS connections. Doing this disables ANO encryption on the TCPS listener.

Default

FALSE

Example 5-5 Example

SQLNET.IGNORE_ANO_ENCRYPTION_FOR_TCPS=TRUE

5.2.62 SQLNET.INBOUND CONNECT TIMEOUT

Use the sqlnet.ora parameter SQLNET.INBOUND_CONNECT_TIMEOUT to specify the amount of time that clients have to connect with the database and authenticate.

Purpose

Use the parameter $SQLNET.INBOUND_CONNECT_TIMEOUT$ to specify the time limit in ms, sec, or min, within which a client must connect with the database and provide authentication information.

Usage Notes

If the client fails to connect and complete the authentication within the specified timeframe, then the database terminates the connection. In addition, the database logs the IP address of the client and writes an ORA-12170 error message to the database alert log file.

The client receives either an ORA-12547: TNS:lost contact or an ORA-12637: Packet receive failed error message.

The default value of SQLNET.INBOUND_CONNECT_TIMEOUT is appropriate for typical scenarios. However, if you need to set a different value, then Oracle recommends setting this parameter



in combination with the INBOUND_CONNECT_TIMEOUT_listener_name parameter in the listener.ora file. When specifying the values for these parameters, note the following recommendations:

- Set both parameters to a low value initially.
- Set the value of the INBOUND_CONNECT_TIMEOUT_listener_name parameter to a lower value than the value that you have set for the SQLNET. INBOUND_CONNECT_TIMEOUT parameter.

It accepts different timeouts with or without space between the value and the unit. If you do not set a unit of measurement for SQLNET. INBOUND CONNECT TIMEOUT, then the default unit is sec. For example, you can set INBOUND_CONNECT_TIMEOUT_listener_name to 2 seconds and set the SQLNET. INBOUND CONNECT TIMEOUT parameter to 3 seconds. If clients are unable to complete the connections within the specified time due to system or network delays that are normal for the particular environment, then increase the value for SOLNET. INBOUND CONNECT TIMEOUT as needed.

Default

60 seconds

Example

SQLNET.INBOUND_CONNECT_TIMEOUT=3ms

5.2.63 SQLNET.FALLBACK AUTHENTICATION

Use the sqlnet.ora parameter SQLNET.FALLBACK_AUTHENTICATION to specify whether to attempt password-based authentication if Kerberos authentication fails.

Purpose

To specify whether to attempt to use password-based authentication if Kerberos authentication fails. This is relevant for direct connections as well as database link connections.

Default

FALSE

Example

SQLNET.FALLBACK_AUTHENTICATION=TRUE



(i) See Also

Oracle Database Security Guide

5.2.64 SQLNET.KERBEROS5 CC NAME

Use the sqlnet.ora parameter SQLNET.KERBEROS5_CC_NAME to specify the complete path name to the Kerberos credentials cache (CC) file.

Purpose

To specify the complete path name to the Kerberos CC file.



Usage Notes

You can set this parameter in the sqlnet.ora file.

You can also set this value in the <code>tnsnames.ora</code> file or directly as part of the connect string. The <code>SQLNET.KERBEROS5_CC_NAME</code> parameter is equivalent to the <code>tnsnames.ora</code> parameter <code>KERBEROS5_CC_NAME</code>. The parameter value specified in the connect string takes precedence.

 This parameter supports multiple principals for the storage of credentials that are returned by KDC in an encrypted format.

You can use the <code>okinit</code>, <code>oklist</code>, and <code>okdstry</code> utilities to configure encrypted cache files for all Kerberos principals. These utilities work with encrypted cache files only if you specify the cache path using <code>SQLNET.KERBEROS5 CC NAME</code>.

SQLNET.KERBEROS5_CC_NAME is mandatory for all additional Kerberos users and principals.
 Optionally, you can set the KERBEROS5_PRINCIPAL parameter to specify the Kerberos principal name associated with the credential cache (specified through SQLNET.KERBEROS5_CC_NAME). You can set KERBEROS5_PRINCIPAL in the connect string, sqlnet.ora file, or this names.ora file.

Oracle Database checks KERBEROS5_PRINCIPAL against the value that is retrieved from the credential cache. If the two values do not match, then the user is not authenticated.

Values and Examples

You can use the following formats to specify a value for SQLNET.KERBEROS5_CC_NAME:

- If the Oracle database is using a directory cache:
 - SQLNET.KERBEROS5_CC_NAME=complete_path_to_cc_file

For example:

```
SQLNET.KERBEROS5_CC_NAME=/tmp/kcache
SQLNET.KERBEROS5_CC_NAME=D:\tmp\kcache
```

SQLNET.KERBEROS5_CC_NAME=FILE:complete_path_to_cc_ file

For example:

```
SQLNET.KERBEROS5_CC_NAME=FILE:/tmp/kcache
```

- If the Oracle database is using the native Windows cache:
 - SOLNET.KERBEROS5 CC NAME=OSMSFT://
 - SQLNET.KERBEROS5 CC NAME=MSLSA:

The OSMSFT and MSLSA options specify that the file is on Microsoft Windows and is running Microsoft Kerberos Key Distribution Center (KDC).

Default

The default value is operating system-dependent, as follows:

- On Linux and UNIX operating systems: /tmp/krb5cc_userid
- On Microsoft Windows operating systems: c:\tmp\krbcache



Related Topics

KERBEROS5 PRINCIPAL

Use the KERBEROS5_PRINCIPAL parameter to set the Kerberos principal name associated with the Kerberos credentials cache (CC) file.

KERBEROS5 CC NAME

Use the tnsnames.ora parameter KERBEROS5_CC_NAME to specify the complete path name to the Kerberos credentials cache (CC) file.

Oracle AI Database Security Guide

5.2.65 SQLNET.KERBEROS5_CLOCKSKEW

Use the sqlnet.ora parameter SQLNET.KERBEROS5_CLOCKSKEW to specify how much time elapses before a Kerberos credential is considered out-of-date.

Purpose

To specify how many seconds elapse before a Kerberos credential is considered out-of-date.

Default

300

Example

SQLNET.KERBEROS5_CLOCKSKEW=1200



Oracle Database Security Guide

5.2.66 SQLNET.KERBEROS5_CONF

Use the sqlnet.ora parameter SQLNET.KERBEROS5_CONF to specify the path name to the Kerberos configuration file that contains the realm for the default Key Distribution Center (KDC) and that maps realms to KDC hosts.

Purpose

To specify the complete path name to the Kerberos configuration file that contains the realm for the default Key Distribution Center (KDC) and that also maps realms to KDC hosts.

Usage Notes

KDC maintains a list of user principals and is contacted through the kinit program for the user's initial ticket.

If you configure the SQLNET.KERBEROS5_CONF parameter, then the Kerberos 5 configuration file krb.conf is fetched from the directory path specified in the parameter. Alternately, you can skip configuring the SQLNET.KERBEROS5_CONF altogether and still ensure the discovery of your configuration file by placing the krb.conf file in one of the default search locations so as to allow for an automatic discovery by Kerberos authentication service.





If you choose to place the Kerberos configuration file in one of the default search paths, then it is optional to set the parameter value as AUTO_DISCOVER, as placing the krb.conf file in one of the default locations enables automatic discovery without having to set the AUTO DISCOVER parameter.

Default

On Linux and UNIX operating systems, krb.conf is automatically searched in the below file paths in the specified order:

- \$ORACLE BASE/network/admin/krb.conf
- \$ORACLE_BASE_HOME/network/admin/krb.conf
- \$ORACLE_HOME/network/admin/krb.conf
- /etc/krb.conf

c:\krb5\krb.conf on Microsoft Windows operating systems

Values

- Directory path to krb.conf file
- AUTO DISCOVER

Example

SQLNET.KERBEROS5_CONF=/krb5/krb.conf



(i) See Also

Oracle Database Security Guide

5.2.67 SQLNET.KERBEROS5_CONF_LOCATION

Use the sqlnet.ora parameter SQLNET.KERBEROS5_CONF_LOCATION to specify the directory for the Kerberos configuration file. The SQLNET. KERBEROS5 CONF LOCATION parameter also specifies that the file is created by the system and not by the client.

Purpose

To specify the directory for the Kerberos configuration file. The parameter also specifies that the file is created by the system, and not by the client.

Usage Notes

The configuration file uses DNS look-up to obtain the realm for the default KDC, and it maps realms to the KDC hosts. This option is supported for all operating systems that support this feature.



Default

/krb5 on Linux and UNIX operating systems

c:\krb5 on Microsoft Windows operating systems

Example

SQLNET.KERBEROS5_CONF_LOCATION=/krb5

5.2.68 SQLNET.KERBEROS5_KEYTAB

Use the sqlnet.ora parameter SQLNET.KERBEROS5_KEYTAB to specify the path name to the Kerberos principal or, secret, key mapping file that extracts keys and decrypts incoming authentication information.

Purpose

To specify the complete path name to the Kerberos principal or, secret, key mapping file that extracts keys and decrypts incoming authentication information.

Default

/etc/v5srvtab on Linux and UNIX operating systems

c:\krb5\v5srvtab on Microsoft Windows operating systems

Example

SQLNET.KERBEROS5_KEYTAB=/etc/v5srvtab



(i) See Also

Oracle Database Security Guide

5.2.69 SQLNET.KERBEROS5_REALMS

Use the sqlnet.ora parameter SQLNET.KERBEROS5_REALMS to specify the complete path name to the Kerberos realm translation file that maps a host name or domain name to a realm.

Purpose

To specify the complete path name to the Kerberos realm translation file that maps a host name or domain name to a realm.

Default

/krb5/krb.realms on Linux and UNIX operating systems

c:\krb5\krb.realms on Microsoft Windows operating systems

Example

SQLNET.KERBEROS5_REALMS=/krb5/krb.realms





(i) See Also

Oracle Database Security Guide

5.2.70 SQLNET.OUTBOUND_CONNECT_TIMEOUT

Use the sqlnet.ora parameter SQLNET.OUTBOUND_CONNECT_TIMEOUT to specify the amount of time, in milliseconds, seconds, or minutes, in which clients must establish Oracle Net connections to database instances.

Purpose

To specify the time in ms, sec, or min for clients to establish an Oracle Net connection to the database instance.

Usage Notes

If an Oracle Net connection is not established in the time specified, then the connection attempt is terminated. The client receives the following error:

```
ORA-12170: Cannot connect. Outbound connect timeout of time interval for
host_port or key. (CONNECTION_ID=ID_string).
```

The outbound connect timeout interval is a superset of the TCP connect timeout interval that specifies a limit on the time needed to establish a TCP connection. Additionally, the outbound connect timeout interval includes the time taken to be connected to an Oracle instance that is providing the service. It accepts different timeouts with or without space between the value and the unit.

Without this parameter, a client connection request to the database server may be blocked for the default TCP connect timeout duration (60 seconds) when the database server host system is unreachable. In this case, no unit is mentioned and the default unit is sec.

The outbound connect timeout interval is only applicable for TCP, TCP with TLS, and IPC transport connections.

This parameter is overridden by the CONNECT TIMEOUT parameter in the address description.

Default

None

Example

SOLNET.OUTBOUND CONNECT TIMEOUT=10 ms

Related Topics

CONNECT TIMEOUT

Use the tnsnames.ora parameter CONNECT_TIMEOUT to specify the amount of time, in milliseconds, seconds, or minutes, in which clients must establish Oracle Net connections to database instances.



5.2.71 SQLNET.RADIUS_ALLOW_WEAK_CLIENTS

Use the client-side sqlnet.ora parameter SQLNET.RADIUS_ALLOW_WEAK_CLIENTS to control the transport protocol that the Oracle Database client must use for communicating with the Oracle Database server.

Purpose

To control the transport protocol that the Oracle Database client must use for communication between the database client and database server, if the database client wants to use RADIUS authentication.

The default value is FALSE so that database clients can connect to the database server (to use RADIUS authentication) only if the connecting protocol used is TCPS.

Usage Notes

 Starting with Oracle Al Database 26ai, the older RADIUS API that is based on Request for Comments (RFC) 2138 is deprecated.

Oracle AI Database 26ai introduces an updated RADIUS API based on RFC 6613 and RFC 6614. Oracle recommends that you start planning on migrating to use the new RADIUS API as soon as possible. The new API is enabled by default. These parameters associated with the older RADIUS API are also deprecated: SQLNET.RADIUS_ALTERNATE, SQLNET.RADIUS_ALTERNATE_PORT, SQLNET.RADIUS_AUTHENTICATION, and SQLNET.RADIUS_AUTHENTICATION_PORT. Refer to the Radius API documentation for information on changing the default to use the older RADIUS API.

The updated RADIUS API uses TCPS as the protocol for secure communication.

 Starting with Oracle AI Database 26ai, users authenticating to the database using the legacy RADIUS API no longer are granted administrative privileges.

In previous releases, users authenticating with RADIUS API could be granted administrative privileges such as SYSDBA or SYSBACKUP. In Oracle AI Database 26ai, Oracle introduces a new RADIUS API that uses the latest standards. To grant administrative privileges to users, ensure the database connection to the database uses the new RADIUS API, and that you are using the Oracle AI Database 26ai client to connect to the Oracle AI Database 26ai server.

Values

- TRUE: To allow database clients to connect using a weak protocol, such as User Datagram Protocol (UDP).
- FALSE: To allow database clients to connect using only a strong protocol, such as TCPS.

Default

FALSE

Example

SOLNET.RADIUS ALLOW WEAK CLIENTS=FALSE

Related Topics

Oracle AI Database Security Guide



5.2.72 SQLNET.RADIUS_ALLOW_WEAK_PROTOCOL

Use the server-side sqlnet.ora parameter SQLNET.RADIUS_ALLOW_WEAK_PROTOCOL to allow weak Oracle Database clients to use RADIUS authentication.

Purpose

To allow weak Oracle Database clients, which use non-TCPS protocol for connecting to the Oracle Database server, to use RADIUS authentication.

The default value is FALSE so that only strong clients (using TCPS for connecting to the database server) can use RADIUS authentication.

Usage Notes

Starting with Oracle AI Database 26ai, the older RADIUS API that is based on Request for Comments (RFC) 2138 is deprecated.

Oracle AI Database 26ai introduces an updated RADIUS API based on RFC 6613 and RFC 6614. Oracle recommends that you start planning on migrating to use the new RADIUS API as soon as possible. The new API is enabled by default. These parameters associated with the older RADIUS API are also deprecated: SQLNET.RADIUS_ALTERNATE, SQLNET.RADIUS_ALTERNATE_PORT, SQLNET.RADIUS_AUTHENTICATION, and SQLNET.RADIUS_AUTHENTICATION_PORT. Refer to the Radius API documentation for information on changing the default to use the older RADIUS API.

The updated RADIUS API uses TCPS as the protocol for secure communication.

 Starting with Oracle AI Database 26ai, users authenticating to the database using the legacy RADIUS API no longer are granted administrative privileges.

In previous releases, users authenticating with RADIUS API could be granted administrative privileges such as SYSDBA or SYSBACKUP. In Oracle AI Database 26ai, Oracle introduces a new RADIUS API that uses the latest standards. To grant administrative privileges to users, ensure the database connection to the database uses the new RADIUS API, and that you are using the Oracle AI Database 26ai client to connect to the Oracle AI Database 26ai server.

Values

- TRUE: To allow weak database clients to use RADIUS authentication
- FALSE: To allow only strong database clients (and block weak clients) to use RADIUS authentication

Default

FALSE

Example

SQLNET.RADIUS_ALLOW_WEAK_PROTOCOL=FALSE

Related Topics

Oracle Al Database Security Guide



5.2.73 SQLNET.RADIUS_ALTERNATE

Use the sqlnet.ora parameter SQLNET.RADIUS_ALTERNATE to specify an alternate RADIUS server to be used when the primary server is unavailable.

Purpose

To specify the location of an alternate RADIUS server to be used for fault tolerance when the primary server is unavailable. The value can be either the IP address or host name of the server.

Usage Notes

Starting with Oracle AI Database 26ai, the older RADIUS API that is based on Request for Comments (RFC) 2138 is deprecated.

Oracle AI Database 26ai introduces an updated RADIUS API based on RFC 6613 and RFC 6614. Oracle recommends that you start planning on migrating to use the new RADIUS API as soon as possible. The new API is enabled by default. These parameters associated with the older RADIUS API are also deprecated: SQLNET.RADIUS ALTERNATE,

SQLNET.RADIUS_ALTERNATE_PORT, SQLNET.RADIUS_AUTHENTICATION, and SQLNET.RADIUS_AUTHENTICATION_PORT. Refer to the Radius API documentation for information on changing the default to use the older RADIUS API.

If your database server supports the updated RADIUS standards, then use the SQLNET.RADIUS_ALTERNATE_TLS_HOST parameter instead of the deprecated SQLNET.RADIUS ALTERNATE parameter.

If you need to enable pre-release 23ai clients to connect RADIUS users using the older RADIUS standards (which are blocked by default), then you must set one or both of the SQLNET.RADIUS ALLOW WEAK CLIENTS and SQLNET.RADIUS ALLOW WEAK PROTOCOL parameters.

Syntax

 ${\tt SQLNET.RADIUS_ALTERNATE=(\ hostname_or_IP_address_of_alternate_RADIUS_server)}$

Default

None

Example

SQLNET.RADIUS_ALTERNATE=(radius-server2)

Related Topics

- Oracle Al Database Security Guide
- SQLNET.RADIUS_ALTERNATE_TLS_HOST

 Use the sqlnet.ora parameter SQLNET.RADIUS_ALTERNATE_TLS_HOST to specify the host name of an alternate RADIUS server to be used when the primary server is unavailable.
- SQLNET.RADIUS_ALLOW_WEAK_CLIENTS
 Use the client-side sqlnet.ora parameter SQLNET.RADIUS_ALLOW_WEAK_CLIENTS to control the transport protocol that the Oracle Database client must use for communicating with the Oracle Database server.



SOLNET.RADIUS ALLOW WEAK PROTOCOL

Use the server-side sqlnet.ora parameter SQLNET.RADIUS_ALLOW_WEAK_PROTOCOL to allow weak Oracle Database clients to use RADIUS authentication.

5.2.74 SQLNET.RADIUS_ALTERNATE_PORT

Use the sqlnet.ora parameter SQLNET.RADIUS_ALTERNATE_PORT to specify the listening port of an alternate RADIUS server.

Purpose

To specify the listening port of an alternate RADIUS server.

Usage Notes

Starting with Oracle AI Database 26ai, the older RADIUS API that is based on Request for Comments (RFC) 2138 is deprecated.

Oracle AI Database 26ai introduces an updated RADIUS API based on RFC 6613 and RFC 6614. Oracle recommends that you start planning on migrating to use the new RADIUS API as soon as possible. The new API is enabled by default. These parameters associated with the older RADIUS API are also deprecated: SQLNET.RADIUS_ALTERNATE,

SQLNET.RADIUS_ALTERNATE_PORT, SQLNET.RADIUS_AUTHENTICATION, and SQLNET.RADIUS_AUTHENTICATION_PORT. Refer to the Radius API documentation for information on changing the default to use the older RADIUS API.

If your database server supports the updated RADIUS standards, then use the SQLNET.RADIUS_ALTERNATE_TLS_PORT parameter instead of the deprecated SQLNET.RADIUS_ALTERNATE_PORT parameter.

If you need to enable pre-release 23ai clients to connect RADIUS users using the older RADIUS standards (which are blocked by default), then you must set one or both of the SQLNET.RADIUS_ALLOW_WEAK_CLIENTS and SQLNET.RADIUS_ALLOW_WEAK_PROTOCOL parameters.

Syntax

SQLNET.RADIUS_ALTERNATE_PORT=(listening_port_of_alternate_RADIUS_server)

Default

1812

Example

SQLNET.RADIUS_ALTERNATE_PORT=(1667)

Related Topics

- Oracle AI Database Security Guide
- SQLNET.RADIUS ALTERNATE TLS_PORT

 Use the sqlnet.ora parameter SQLNET.RADIUS_ALTERNATE_TLS_PORT to specify the listening port of an alternate RADIUS server.
- SQLNET.RADIUS ALLOW WEAK CLIENTS

Use the client-side sqlnet.ora parameter SQLNET.RADIUS_ALLOW_WEAK_CLIENTS to control the transport protocol that the Oracle Database client must use for communicating with the Oracle Database server.



SQLNET.RADIUS ALLOW WEAK_PROTOCOL

Use the server-side sqlnet.ora parameter SQLNET.RADIUS_ALLOW_WEAK_PROTOCOL to allow weak Oracle Database clients to use RADIUS authentication.

5.2.75 SQLNET.RADIUS_ALTERNATE_RETRIES

Use the sqlnet.ora parameter SQLNET.RADIUS_ALTERNATE_RETRIES to specify the number of times that the database resends messages to alternate RADIUS servers.

Purpose

To specify the number of times that the database server should resend messages to an alternate RADIUS server.

Default

3

Example

SQLNET.RADIUS_ALTERNATE_RETRIES=4

5.2.76 SQLNET.RADIUS_ALTERNATE_TIMEOUT

Use the sqlnet.ora parameter $SQLNET.RADIUS_ALTERNATE_TIMEOUT$ to set the time for an alternate RADIUS server to wait for a response.

Purpose

To set the time, in seconds, for an alternate RADIUS server to wait for a response.

Syntax

SQLNET.RADIUS ALTERNATE TIMEOUT=time in seconds

Default

5

Example

SQLNET.RADIUS_ALTERNATE_TIMEOUT=5

Related Topics

Oracle AI Database Security Guide

5.2.77 SQLNET.RADIUS_ALTERNATE_TLS_HOST

Use the sqlnet.ora parameter SQLNET.RADIUS_ALTERNATE_TLS_HOST to specify the host name of an alternate RADIUS server to be used when the primary server is unavailable.

Purpose

To specify the host name of an alternate RADIUS server, which is used for fault tolerance when the primary server is unavailable.



Usage Notes

Use this parameter only if your RADIUS server implements RADIUS with TLS over TCP.

Syntax

 ${\tt SQLNET.RADIUS_ALTERNATE_TLS_HOST=(\it TLS_hostname_of_alternate_RADIUS_server)}$

Default

None

Example

SQLNET.RADIUS_ALTERNATE_TLS_HOST=(radius-server2)

Related Topics

Oracle AI Database Security Guide

5.2.78 SQLNET.RADIUS_ALTERNATE_TLS_PORT

Use the sqlnet.ora parameter $SQLNET.RADIUS_ALTERNATE_TLS_PORT$ to specify the listening port of an alternate RADIUS server.

Purpose

To specify the listening port of an alternate RADIUS server. The default port is 2083. If the alternate server uses a different port, then specify that value.

Usage Notes

Use this parameter only if your RADIUS server implements RADIUS with TLS over TCP.

Syntax

SQLNET.RADIUS_ALTERNATE_TLS_PORT=(listening_TLS_port_of_alternate_RADIUS_server)

Default

2083

Example

SQLNET.RADIUS_ALTERNATE_TLS_PORT=(5530)

Related Topics

Oracle Al Database Security Guide



5.2.79 SQLNET.RADIUS_AUTHENTICATION

Use the sqlnet.ora parameter $SQLNET.RADIUS_AUTHENTICATION$ to specify the location of a primary RADIUS server.

Purpose

To specify the location of a primary RADIUS server. The value can be either the IP address or host name of the server.

Usage Notes

Starting with Oracle AI Database 26ai, the older RADIUS API that is based on Request for Comments (RFC) 2138 is deprecated.

Oracle AI Database 26ai introduces an updated RADIUS API based on RFC 6613 and RFC 6614. Oracle recommends that you start planning on migrating to use the new RADIUS API as soon as possible. The new API is enabled by default. These parameters associated with the older RADIUS API are also deprecated: SQLNET.RADIUS ALTERNATE,

SQLNET.RADIUS_ALTERNATE_PORT, SQLNET.RADIUS_AUTHENTICATION, and SQLNET.RADIUS_AUTHENTICATION_PORT. Refer to the Radius API documentation for information on changing the default to use the older RADIUS API.

If your database server supports the updated RADIUS standards, then use the SQLNET.RADIUS_AUTHENTICATION_TLS_HOST parameter instead of the deprecated SQLNET.RADIUS AUTHENTICATION parameter.

If you need to enable pre-release 23ai clients to connect RADIUS users using the older RADIUS standards (which are blocked by default), then you must set one or both of the SQLNET.RADIUS ALLOW WEAK CLIENTS and SQLNET.RADIUS ALLOW WEAK PROTOCOL parameters.

Syntax

SQLNET.RADIUS_AUTHENTICATION=(hostname_or_IP_address_of_primary_RADIUS_server)

Default

Local host

Example

SQLNET.RADIUS_AUTHENETICATION=(radius-server1)

Related Topics

- Oracle Al Database Security Guide
- SQLNET.RADIUS AUTHENTICATION TLS HOST
 Use the sglnet.ora parameter SOLNET.RADIUS AUTHENTICATION
 - Use the sqlnet.ora parameter SQLNET.RADIUS_AUTHENTICATION_TLS_HOST to specify the host name of a primary RADIUS server.
- SQLNET.RADIUS_ALLOW_WEAK_CLIENTS

Use the client-side sqlnet.ora parameter SQLNET.RADIUS_ALLOW_WEAK_CLIENTS to control the transport protocol that the Oracle Database client must use for communicating with the Oracle Database server.



SOLNET.RADIUS ALLOW WEAK PROTOCOL

Use the server-side sqlnet.ora parameter SQLNET.RADIUS_ALLOW_WEAK_PROTOCOL to allow weak Oracle Database clients to use RADIUS authentication.

5.2.80 SQLNET.RADIUS_AUTHENTICATION_INTERFACE

Use the sqlnet.ora parameter SQLNET.RADIUS_AUTHENTICATION_INTERFACE to specify the class that contains the user interface for interacting with users.

Purpose

To specify the class containing the user interface that is used to interact with the user.

Default

DefaultRadiusInterface

Example

SQLNET.RADIUS_AUTHENTICATION_INTERFACE=DefaultRadiusInterface

5.2.81 SQLNET.RADIUS_AUTHENTICATION_PORT

Use the sqlnet.ora parameter $SQLNET.RADIUS_AUTHENTICATION_PORT$ to specify the listening port of a primary RADIUS server.

Purpose

To specify the listening port of a primary RADIUS server.

Usage Notes

Starting with Oracle AI Database 26ai, the older RADIUS API that is based on Request for Comments (RFC) 2138 is deprecated.

Oracle AI Database 26ai introduces an updated RADIUS API based on RFC 6613 and RFC 6614. Oracle recommends that you start planning on migrating to use the new RADIUS API as soon as possible. The new API is enabled by default. These parameters associated with the older RADIUS API are also deprecated: SQLNET.RADIUS_ALTERNATE,

SQLNET.RADIUS_ALTERNATE_PORT, SQLNET.RADIUS_AUTHENTICATION, and SQLNET.RADIUS_AUTHENTICATION_PORT. Refer to the Radius API documentation for information on changing the default to use the older RADIUS API.

If your database server supports the updated RADIUS standards, then use the SQLNET.RADIUS_AUTHENTICATION_TLS_PORT parameter instead of the deprecated SQLNET.RADIUS_AUTHENTICATION_PORT parameter.

If you need to enable pre-release 23ai clients to connect RADIUS users using the older RADIUS standards (which are blocked by default), then you must set one or both of the SQLNET.RADIUS_ALLOW_WEAK_CLIENTS and SQLNET.RADIUS_ALLOW_WEAK_PROTOCOL parameters.

Syntax

SQLNET.RADIUS_AUTHENTICATION_PORT=(listening_port_of_primary_RADIUS_server)



Default

1645

Example

SQLNET.RADIUS_AUTHENTICATION_PORT=(1667)

Related Topics

- Oracle AI Database Security Guide
- SQLNET.RADIUS AUTHENTICATION TLS PORT

Use the sqlnet.ora parameter SQLNET.RADIUS_AUTHENTICATION_TLS_PORT to specify the listening port of a primary RADIUS server.

SQLNET.RADIUS ALLOW WEAK CLIENTS

Use the client-side sqlnet.ora parameter $SQLNET.RADIUS_ALLOW_WEAK_CLIENTS$ to control the transport protocol that the Oracle Database client must use for communicating with the Oracle Database server.

SQLNET.RADIUS ALLOW WEAK PROTOCOL

Use the server-side sqlnet.ora parameter SQLNET.RADIUS_ALLOW_WEAK_PROTOCOL to allow weak Oracle Database clients to use RADIUS authentication.

5.2.82 SQLNET.RADIUS_AUTHENTICATION_RETRIES

Use the sqlnet.ora parameter $SQLNET.RADIUS_AUTHENTICATION_RETRIES$ to specify the number of times the database should resend messages to a primary RADIUS server.

Purpose

To specify the number of times the database should resend messages to a primary RADIUS server.

Default

3

Example

SQLNET.RADIUS_AUTHENTICATION_RETRIES=4

5.2.83 SQLNET.RADIUS_AUTHENTICATION_TIMEOUT

Use the sqlnet.ora parameter $SQLNET.RADIUS_AUTHENTICATION_TIMEOUT$ to specify the amount of time that the database should wait for a response from a primary RADIUS server.

Purpose

To specify the amount of time, in seconds, that the database should wait for a response from a primary RADIUS server.

Default

5



Example

SQLNET.RADIUS_AUTHENTICATION_TIMEOUT=10

5.2.84 SQLNET.RADIUS_AUTHENTICATION_TLS_HOST

Use the sqlnet.ora parameter $SQLNET.RADIUS_AUTHENTICATION_TLS_HOST$ to specify the host name of a primary RADIUS server.

Purpose

To specify the host name of a primary RADIUS server. This value is mandatory. If you do not set this parameter, then authentication fails.

Usage Notes

Use this parameter only if your RADIUS server implements RADIUS with TLS over TCP.

Syntax

SQLNET.RADIUS_AUTHENTICATION_TLS_HOST=(TLS_hostname_of_primary_RADIUS_server)

Default

None

Example

SQLNET.RADIUS_AUTHENTICATION_TLS_HOST=(radius-server1)

Related Topics

Oracle AI Database Security Guide

5.2.85 SQLNET.RADIUS_AUTHENTICATION_TLS_PORT

Use the sqlnet.ora parameter SQLNET.RADIUS_AUTHENTICATION_TLS_PORT to specify the listening port of a primary RADIUS server.

Purpose

To specify the listening port of a primary RADIUS server. The default port is 2083. If the server uses a different port, then specify that value.

Usage Notes

Use this parameter only if your RADIUS server implements RADIUS with TLS over TCP.

Syntax

SQLNET.RADIUS_AUTHENTICATION_TLS_PORT=(listening_TLS_port_of_primary_RADIUS_server)



Default

2083

Example

SQLNET.RADIUS_AUTHENTICATION_TLS_PORT=(5530)

Related Topics

Oracle AI Database Security Guide

5.2.86 SQLNET.RADIUS_CHALLENGE_KEYWORD

Use the sqlnet.ora parameter SQLNET.RADIUS_CHALLENGE_KEYWORD to set the keyword for requesting a challenge from the RADIUS server.

Purpose

To set the keyword for requesting a challenge from the RADIUS server. By setting the challenge keyword, you let the user avoid using a password on the client to verify identity.

Syntax

SQLNET.RADIUS_CHALLENGE_KEYWORD=keyword

Default

challenge

Example

SQLNET.RADIUS_CHALLENGE_KEYWORD=challenge

Related Topics

Oracle AI Database Security Guide

5.2.87 SQLNET.RADIUS_CHALLENGE_RESPONSE

Use the sqlnet.ora parameter $SQLNET.RADIUS_CHALLENGE_RESPONSE$ to enable or disable challenge responses.

Purpose

To turn the challenge responses on or off.

Default

off

Values

on | off



Example

SQLNET.RADIUS_CHALLENGE_RESPONSE=on

5.2.88 SQLNET.RADIUS_CLASSPATH

Use the sqlnet.ora parameter SQLNET.RADIUS_CLASSPATH to set the path for Java classes and JDK Java libraries.

Purpose

To set the path for Java classes for a graphical interface, and to set the path to JDK Java libraries.

If you use the challenge-response authentication mode, then RADIUS displays a Java-based graphical interface. This interface first requests a password and then additional information, for example, a dynamic password that the user obtains from a token card.

Syntax

SQLNET.RADIUS_CLASSPATH=path_to_GUI_Java_classes

Default

\$ORACLE_HOME/jlib/netradius.jar:\$ORACLE_HOME/JRE/lib/sparc/native_threads

Example

SQLNET.RADIUS_CLASSPATH=/jre1.1

Related Topics

Oracle AI Database Security Guide

5.2.89 SQLNET.RADIUS_SECRET

Use the sqlnet.ora parameter SQLNET.RADIUS_SECRET to specify the location of a RADIUS secret key.

Purpose

To specify the location of a RADIUS secret key.

Usage Notes

For RADIUS with TLS over TCP, the default value is radsec. This value is used if you do not set this parameter in the sqlnet.ora file.

There is no default value for RADIUS with UDP. You must configure this parameter with a directory path to the file containing secret key. For example:

ORACLE_HOME/network/security/radius.key



Example

SQLNET.RADIUS_SECRET=oracle/bin/admin/radiuskey

Related Topics

Oracle AI Database Security Guide

5.2.90 SQLNET.RADIUS_SEND_ACCOUNTING

Use the ${\tt sqlnet.ora}$ parameter ${\tt SQLNET.RADIUS_SEND_ACCOUNTING}$ to enable and disable accounting.

Purpose

To turn accounting ON and OFF. When you enable accounting, packets are sent to the active RADIUS server at the listening port number's value plus one.

Default

OFF

Values

ON | OFF

Example

SQLNET.RADIUS_SEND_ACCOUNTING=ON

Related Topics

Oracle AI Database Security Guide

5.2.91 SQLNET.RADIUS_TRANSPORT_PROTOCOL

Use the server-side sqlnet.ora parameter $SQLNET.RADIUS_TRANSPORT_PROTOCOL$ to control the transport protocol that the Oracle Database server must use for communicating with the RADIUS server.

Purpose

To specify mutual Transport Layer Security (mTLS), Transport Layer Security (TLS), or User Datagram Protocol (UDP) as the protocol for communication between the Oracle Database server (acting as the RADIUS client) and the RADIUS server.

Usage Notes

 Starting with Oracle AI Database 26ai, the older RADIUS API that is based on Request for Comments (RFC) 2138 is deprecated.

Oracle AI Database 26ai introduces an updated RADIUS API based on RFC 6613 and RFC 6614. Oracle recommends that you start planning on migrating to use the new RADIUS API as soon as possible. The new API is enabled by default. These parameters associated with the older RADIUS API are also deprecated: SQLNET.RADIUS_ALTERNATE, SQLNET.RADIUS_ALTERNATE_PORT, SQLNET.RADIUS_AUTHENTICATION, and



SQLNET.RADIUS_AUTHENTICATION_PORT. Refer to the Radius API documentation for information on changing the default to use the older RADIUS API.

 Both the mTLS and TLS protocols implement the latest RADIUS API standards and enforce stronger security.

When set to MTLS, a mutual or two-way TLS connection is established between the Oracle Database server and RADIUS server. You must configure an Oracle wallet on the database server to use mTLS. Ensure that the wallet stores RADIUS client user certificates and trusted CA certificates of both the RADIUS client and RADIUS server.

When set to TLS, a one-way TLS connection is established between the Oracle Database server and RADIUS server. For walletless TLS connections (which do not use a client wallet), the RADIUS client automatically picks up common root certificates from the system default certificate store to verify the RADIUS server certificates. Use this value if your RADIUS server supports TLS (RADIUS over TCP) or TCPS (RADIUS with TLS over TCP).

- If you must use RADIUS with UDP for backward compatibility, then set this parameter to UDP. However, note that RADIUS with UDP uses the older RADIUS API standards and is considered insecure.
- If you omit this parameter value, then the default protocol, mTLS, is used.

Values

MTLS | TLS | UDP

Default

MTLS

Example

SQLNET.RADIUS_TRANSPORT_PROTOCOL=MTLS

Related Topics

- Oracle AI Database Security Guide
- Oracle Al Database Net Services Administrator's Guide

5.2.92 SQLNET.RECV TIMEOUT

Use the sqlnet.ora parameter $SQLNET.RECV_TIMEOUT$ to specify the duration of time that a database client or server should wait for data from a peer after establishing a connection.

Purpose

To specify the time for a database client or server to wait for data from the peer after establishing a connection. The peer must send data within the time interval that you specify.

You can specify the time in hours, minutes, seconds, or milliseconds by using the hr, min, sec, or ms keyword respectively. If you do not specify a unit of measurement, then the default unit is sec.

Usage Notes

Setting this parameter for clients ensures that receive operations are not left in a wait state indefinitely or for a long period due to an unusual termination of the server process or server busy state. If a client does not receive response data in the time specified, then the client logs



ORA-12535: TNS:operation timed out and ORA-12609: TNS: Receive timeout occurred messages to the sqlnet.log file. If you set the value, then set the value initially to a low value and adjust the value according to the system and network capacity. If necessary, use this parameter with the SQLNET.SEND_TIMEOUT parameter.

You can also set this parameter on the server-side to specify the time, in ms, sec, or min, for a server to wait for client data after a connection is established. If a client does not send data in time specified, then the database server logs ORA-12535: TNS:operation timed out and ORA-12609: TNS: Receive timeout occurred messages to the sqlnet.log file. Without this parameter, the database server might continue to wait for data from clients that may be down or are experiencing problems. The server usually blocks input from the client and gets these timeouts frequently if you set it to a low value.

Default

None

Minimum Value

1 ms

Allowed Range

Any number greater than the minimum value of 1 ms up to 4294967295 ms.

Example

SQLNET.RECV_TIMEOUT=10 ms

Related Topics

Oracle Al Database Net Services Administrator's Guide

5.2.93 SQLNET.SEND TIMEOUT

Use the sqlnet.ora parameter SQLNET.SEND_TIMEOUT to specify the duration of time in which a database must complete send operations to clients after establishing connections.

Purpose

To specify the time for a database to complete send operations to clients after establishing connections.

You can specify the time in hours, minutes, seconds, or milliseconds by using the hr, min, sec, or ms keyword respectively. If you do not specify a unit of measurement, then the default unit is sec.

Usage Notes

Setting this parameter is recommended for environments in which clients shut down occasionally or unusually.

If the database server cannot complete a send operation in the time specified, then it logs ORA-12608: TNS: Send timeout occurred messages to the sqlnet.log file. Without this parameter, the database server might continue to send responses to clients that are unable to receive data due to a downed computer or a busy state.

You can also set this parameter on the client-side to specify the duration of time in ms, sec, or min, in which client must complete send operations to the database server after connections



are established. It accepts different timeouts with or without space between the value and the unit. If you do not specify a unit of measure, then the default unit is sec. Without this parameter, the client might continue to send requests to a database server that is saturated with requests. If you choose to set the value, then set the value initially to a low value and adjust the value according to system and network capacity.

If necessary, then use this parameter with the SQLNET.RECV_TIMEOUT parameter.

Default

None

Minimum Value

1 ms

Allowed Range

Any number greater than the minimum value of 1 ms up to 4294967295 ms.

Example

SQLNET.SEND_TIMEOUT=3 ms

Related Topics

Oracle Al Database Net Services Administrator's Guide

5.2.94 SQLNET.URI

Use the sqlnet.ora parameter SQLNET.URI to specify a database client URI mapping on a web server.

Purpose

To specify a database client URI mapping on a web server.

Usage Notes

Use this parameter to customize a URI for mapping the database websocket requests that come into a web server to the back-end database server. Secure websocket handshaking requests are sent with this URI.

Default

/sqlnet

Example 5-6 Example

sqlnet.uri="/my_uri_prefix/database/"

5.2.95 SQLNET.USE_HTTPS_PROXY

Use the sqlnet.ora parameter $SQLNET.USE_HTTPS_PROXY$ to enable forward HTTP proxy tunneling for client connections.

Purpose

To enable forward HTTP proxy tunneling for client connections.



Usage Notes

If set to on, then clients can tunnel secure connections over forward HTTP proxy using the HTTP CONNECT method. This helps access the public cloud database service because it eliminates the requirement to open an outbound port on a client-side firewall.

This parameter is applicable with Oracle Connection Manager on the server side.

Default

on

Example

SQLNET.USE HTTPS PROXY=on

5.2.96 SQLNET.WALLET_OVERRIDE

Use the sqlnet.ora parameter SQLNET.WALLET_OVERRIDE to determine whether a client should override strong authentication credentials with the password credential from the stored wallet.

Purpose

To determine whether a client should override strong authentication credentials with the password credential from the stored wallet to log in to a database.



(i) Note

This is a client-side parameter. The SQLNET.WALLET OVERRIDE=TRUE setting on the database server may break external procedures.

Usage Notes

- When you use wallets for authentication, the database credentials for user name and password are securely stored in an Oracle wallet. The auto-login feature of the wallet is enabled so that the database does not need a password to open the wallet. From the wallet, the database gets the credentials to access the database for the user.
 - Oracle has introduced a new auto-login wallet version (7) with Oracle AI Database 26ai. Version 6 of the Oracle local auto-login wallet is deprecated.
 - You can update your local auto-login wallet by modifying it with orapki.
- Wallet use can simplify large-scale deployments that rely on password credentials for connecting to databases. When this feature is configured, application code, batch jobs, and scripts do not need embedded user names and passwords. Risk is reduced because such passwords are no longer exposed, and password management policies are enforced without changing application code whenever user names or passwords change.
 - Users connect using the connect /@database_name command instead of specifying a user name and password explicitly. This simplifies the maintenance of the scripts and secures the password management for the applications.
- Middle-tier applications create an Oracle Applications wallet during installation to store an application's identity. The password may be randomly generated rather than hardcoded. When an Oracle application accesses the database, it sets appropriate values for SQLNET.AUTHENTICATION SERVICES and WALLET LOCATION. The new wallet-based



password authentication code uses the password credential in the Oracle Applications wallet to log in to the database.

The parameter WALLET_LOCATION is deprecated for use with Oracle AI Database 26ai for the Oracle Database server. It is not deprecated for use with the Oracle Database client or listener.

For Oracle Database server, Oracle recommends that you use the WALLET_ROOT system parameter instead of using WALLET_LOCATION.

Values

true | false

Example

SQLNET.WALLET_OVERRIDE=true

Related Topics

- My Oracle Support Note 340559.1
- Oracle AI Database Security Guide

5.2.97 SSL_ALLOW_WEAK_DN_MATCH

Use the sqlnet.ora parameter $SSL_ALLOW_WEAK_DN_MATCH$ to allow the earlier weaker distinguished name (DN) matching behavior during server-side certificate validation.

Purpose

The SSL_SERVER_DN_MATCH parameter controls the DN matching behavior. DN matching adds another client-side check on both the listener and server certificates to ensure that the certificates are the correct ones that the client expects.

Starting with Oracle AI Database 26ai, the DN matching behavior is enhanced for better security. You can use the SSL_ALLOW_WEAK_DN_MATCH parameter to revert to the earlier DN matching behavior, that is, checking only the server certificate and allowing a service name check for partial DN matching.

Usage Notes

This parameter, introduced with Oracle AI Database 26ai, provides you with a longer period of time to adjust to the new DN matching behavior of SSL_SERVER_DN_MATCH.

The SSL_ALLOW_WEAK_DN_MATCH parameter, though new to Oracle AI Database 26ai, is deprecated and will be removed in a future release. Oracle recommends that you get new certificates or change your DN matching strategy.

Values

TRUE | ON | YES | 1:

Allows SSL_SERVER_DN_MATCH to revert to its earlier (pre-Oracle Al Database release 26ai) DN matching behavior. DN matching only checks the server certificate (but not the listener certificate), and allows to check the service name for partial DN matching.

FALSE | OFF | NO | 0:



Enforces SSL_SERVER_DN_MATCH to use the enhanced DN matching behavior. DN matching checks both the listener and server certificates, and does not allow a service name check for partial DN matching.

Default

FALSE

Example

SSL_ALLOW_WEAK_DN_MATCH=FALSE

Related Topics

SSL SERVER DN MATCH

Use the SSL_SERVER_DN_MATCH parameter to enforce server-side certificate validation through distinguished name (DN) matching.

SSL SERVER CERT DN

Use the SSL_SERVER_CERT_DN parameter to specify the distinguished name (DN) of the database server.

Oracle AI Database Security Guide

5.2.98 SSL_CERTIFICATE_ALIAS

Use the sqlnet.ora or this names.ora parameter SSL_CERTIFICATE_ALIAS to specify the certificate alias to use in Transport Layer Security (TLS) connections.

Purpose

To specify the alias that you provided when storing the client or server certificate in an Oracle Database wallet.

When encrypting TLS connections, both the database client and database server need to provide a signed certificate. You can store this certificate in an Oracle Database wallet or Microsoft Certificate Store (MCS). If there is more than one certificate that can be used, the user or application settings can specify the particular certificate to connect with. This choice can be made manually by the user via graphical user interface (GUI) or automatically by the application using a thumbprint or alias name. A thumbprint or alias name can uniquely identify the certificate.

This parameter instructs the client or server to automatically select a particular certificate using the specified alias name. Thus, the user does not need to manually select the correct client certificate from the list available in a wallet.

Usage Notes

Use this parameter in the tnsnames.ora file, sqlnet.ora file, or directly as part of the command-line connect string. The parameter values specified in the connect string take precedence over the other specified values.

orapki helps you manage certificates and wallets for Oracle Database. To get the alias name value, run the following command:

orapki wallet display -wallet <wallet directory> -pwd <wallet password> -complete



Value

Certificate alias name

Default

None

Examples

In the tnsnames.ora file:

```
net_service_name=
   (DESCRIPTION=
        (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr)(PORT=1521))
        (SECURITY=(SSL_CERTIFICATE_ALIAS=my_cert))
)
```

In the Easy Connect string:

```
tcps://salesserver:1521/sales.us.example.com?SSL_CERTIFICATE_ALIAS=my_cert
```

• In the sqlnet.ora file:

```
SSL CERTIFICATE ALIAS=my cert
```

Related Topics

Oracle Al Database Security Guide

5.2.99 SSL_CERTIFICATE_THUMBPRINT

Use the sqlnet.ora or thinnames.ora parameter SSL_CERTIFICATE_THUMBPRINT to specify the certificate thumbprint to use in Transport Layer Security (TLS) connections.

Purpose

To specify the thumbprint signature for an X509 certificate. These thumbprints are automatically generated for certificates.

When encrypting TLS connections, both the database client and database server need to provide a signed certificate. You can store this certificate in an Oracle Database wallet or Microsoft Certificate Store (MCS). If there is more than one certificate that can be used, the user or application settings can specify the particular certificate to connect with. This choice can be made manually by the user via graphical user interface (GUI) or automatically by the application using a thumbprint or alias name. A thumbprint or alias name can uniquely identify the certificate.

This parameter instructs the client or server to automatically select a particular certificate using the specified thumbprint. Thus, the user does not need to manually select the correct certificate from the list available in a certificate store.

Usage Notes

Use this parameter in the tnsnames.ora file, sqlnet.ora file, or directly as part of the command-line connect string. The parameter values specified in the connect string take precedence over the other specified values.



You can specify both the SHA-1 and SHA-256 thumbprint information for the client certificate.

orapki helps you manage certificates and wallets for Oracle Database. To get the thumbprint value, run the following command:

```
orapki wallet display -wallet <wallet directory> -pwd <wallet password> -complete
```

Value

SHA-1 or SHA-256 thumbprint of the client certificate, in the <Algorithm>:<Hash> format For example:

```
SHA1:1B:11:01:5A:B1:2C:20:B2:12:34:3E:04:7B:83:47:DE:70:2E:4E:11

SHA256:B3:8A:5B:1A:03:63:83:92:2B:5D:E1:53:61:EE:03:94:0A:56:B4:56:41:7E:41:24:41:9B:88:EB:C6:1E:11:23

or

SHA1:1B11015AB12C20B212343E047B8347DE702E4E11

SHA256:B38A5B1A036383922B5DE15361EE03940A56B456417E4124419B88EBC61E1123
```

Default

None

Examples

• In the tnsnames.ora file:



In the Easy Connect string:

tcps://salesserver:1521/sales.us.example.com? SSL CERTIFICATE THUMBPRINT=SHA1:1B11015AB12C20B212343E047B8347DE702E4E11

In the sqlnet.ora file:

SSL CERTIFICATE THUMBPRINT=SHA256:B38A5B1A036383922B5DE15361EE03940A56B4564 17E4124419B88EBC61E1123

Related Topics

Oracle Al Database Security Guide

5.2.100 SSL_CERT_REVOCATION

Use the sqlnet.ora parameter SSL CERT REVOCATION to configure revocation checks for certificates.

Purpose

To configure a revocation check for a certificate.



Oracle Database Security Guide

Default

none

Values

none disables certificate revocation status checking. This is the default value.



(i) Note

Oracle recommends that you do not set the SSL_CERT_REVOCATION parameter to none because this removes a critical component in certificate-based authentication. Without certificate revocation status checking, you cannot protect against stolen certificates that are used for authentication. Set the none value only in cases where mitigating controls safeguard the use of certificates for authentication, such as network access control lists or Oracle Database Vault policies that limit the database connection to trusted clients.

- requested to perform certificate revocation if a Certificate Revocation List (CRL) is available. Reject an TLS connection if the certificate is revoked. If no appropriate CRL is found to determine the revocation status of the certificate and the certificate is not revoked, then accept the TLS connection.
- required to perform certificate revocation when a certificate is available. If a certificate is revoked and no appropriate CRL is found, then reject the TLS connection. If no appropriate CRL is found to ascertain the revocation status of the certificate and the certificate is not revoked, then accept the TLS connection.



Example

SSL_CERT_REVOCATION=required

5.2.101 SSL_CRL_FILE

Use the sqlnet.ora parameter SSL_CRL_FILE to specify the name of the file in which you assemble the certificate revocation list (CRL) for client authentication.

Purpose

To specify the name of the file where you can assemble the CRL for client authentication.

Usage Notes

This file contains the PEM-encoded CRL files, in order of preference. You can use this file alternatively or in addition to the SSL_CRL_PATH parameter. This parameter is only valid if SSL_CERT_REVOCATION is set to either requested or required.

Syntax

SSL_CRL_FILE=certificate_revocation_list_filename

Default

None

Example

SSL_CRL_FILE=crl.txt

Related Topics

SSL CERT REVOCATION

Use the ${\tt sqlnet.ora}$ parameter ${\tt SSL_CERT_REVOCATION}$ to configure revocation checks for certificates.

SSL CRL PATH

Use the sqlnet.ora parameter SSL_CRL_PATH to specify the destination directory of the certificate revocation list (CRL) for client authentication.

Oracle Al Database Security Guide

5.2.102 SSL_CRL_PATH

Use the sqlnet.ora parameter SSL_CRL_PATH to specify the destination directory of the certificate revocation list (CRL) for client authentication.

Purpose

To specify the directory path where CRLs are stored.

Usage Notes

This parameter is only valid if you set SSL CERT REVOCATION to either requested or required.

Both DER-encoded (binary format) and PEM-encoded (BASE64) CRLs are supported.



If you want to store CRLs in a local file system directory, then you must use the <code>orapki</code> utility to rename CRLs in your file system so the system can locate them.

Syntax

SSL_CRL_PATH=certificate_revocation_list_path

Default

None

Example

SSL_CRL_PATH=/home/user1/crldir

Related Topics

SSL CERT REVOCATION

Use the sqlnet.ora parameter SSL_CERT_REVOCATION to configure revocation checks for certificates.

SSL CRL FILE

Use the sqlnet.ora parameter SSL_CRL_FILE to specify the name of the file in which you assemble the certificate revocation list (CRL) for client authentication.

Oracle AI Database Security Guide

5.2.103 SSL_CIPHER_SUITES

Use the SSL_CIPHER_SUITES parameter to control the combination of authentication, encryption, and data integrity algorithms used by Transport Layer Security (TLS).

Purpose

To control the combination of authentication, encryption, and data integrity algorithms used by TLS. By default, the strongest protocol and cipher are negotiated between the database client and server. Setting this parameter will override the default behavior. You must use this parameter only if you have internal security controls that dictate the usage of certain protocol versions.

Usage Notes

Starting with Oracle AI Database 26ai, the use of Transport Layer Security protocol versions 1.0 and 1.1 are desupported.

In most cases, this change will not have any impact, because the database client and server will negotiate the use of the most secure protocol and cipher algorithm. However, if TLS 1.0 or 1.1 has been specified, then you must either remove it to allow the database server and client to pick the most secure protocol, or you must specify either TLS 1.2, or TLS 1.3, or both, for the protocol. Oracle recommends using the latest, most secure protocol. That protocol is TLS 1.3, which is introduced with Oracle AI Database 26ai.

Enclose the SSL_CIPHER_SUITES parameter value in parentheses. Otherwise, the cipher suite setting does not parse correctly.

Default

None



Values

Approved ciphers compatible with TLS 1.3:

- TLS_AES_256_GCM_SHA384
- TLS_CHACHA20_POLY1305_SHA256 (non-FIPS only)
- TLS_AES_128_CCM_SHA256
- TLS_AES_128_GCM_SHA256

Approved ciphers compatible with TLS 1.2:

- TLS_ECDHE_RSA_WITH_AES_256_GCM_SHA384
- TLS_ECDHE_RSA_WITH_AES_128_GCM_SHA256
- TLS_ECDHE_ECDSA_WITH_AES_256_GCM_SHA384
- TLS_ECDHE_ECDSA_WITH_AES_128_GCM_SHA256
- TLS_DHE_RSA_WITH_AES_256_GCM_SHA384
- TLS_DHE_RSA_WITH_AES_128_GCM_SHA256

Deprecated ciphers compatible with TLS 1.2:

- TLS_ECDHE_RSA_WITH_AES_256_CBC_SHA384
- TLS_ECDHE_RSA_WITH_AES_256_CBC_SHA
- TLS_ECDHE_RSA_WITH_AES_128_CBC_SHA256
- TLS_ECDHE_RSA_WITH_AES_128_CBC_SHA
- TLS_ECDHE_ECDSA_WITH_AES_256_CBC_SHA384
- TLS_ECDHE_ECDSA_WITH_AES_256_CBC_SHA
- TLS_ECDHE_ECDSA_WITH_AES_128_CBC_SHA256
- TLS_ECDHE_ECDSA_WITH_AES_128_CBC_SHA
- TLS_RSA_WITH_AES_256_GCM_SHA384
- TLS_RSA_WITH_AES_256_CBC_SHA256
- TLS_RSA_WITH_AES_256_CBC_SHA
- TLS_RSA_WITH_AES_128_GCM_SHA256
- TLS_RSA_WITH_AES_128_CBC_SHA256
- TLS_RSA_WITH_AES_128_CBC_SHA
- TLS_DHE_RSA_WITH_AES_256_CBC_SHA256
- TLS_DHE_RSA_WITH_AES_128_CBC_SHA256
- TLS_DHE_RSA_WITH_AES_256_CBC_SHA



Examples

SSL_CIPHER_SUITES=(TLS_ECDHE_ECDSA_WITH_AES_128_GCM_SHA256)

SSL_CIPHER_SUITES=(TLS_AES_256_GCM_SHA384, TLS_ECDHE_ECDSA_WITH_AES_128_GCM_SHA256)

Related Topics

- Set the TLS Cipher Suites on the Server
- Set the TLS Cipher Suites on the Client

5.2.104 SSL_CLIENT_AUTHENTICATION

Use the SSL_CLIENT_AUTHENTICATION parameter to specify whether the database client is authenticated using Transport Layer Security (TLS).

Purpose

To enable client authentication in a TLS connection. The connection can be one-way or two-way (mutual TLS or mTLS).

Usage Notes

When set to TRUE, a two-way TLS connection is initiated. Both the client and server (including the listener) authenticate each other. For example, if you set this parameter to TRUE in the server configuration (server-side sqlnet.ora), then the server attempts to authenticate the client. If you set it to TRUE in the listener configuration (listener.ora), then the listener attempts to authenticate the client.

When set to FALSE, only the client authenticates the server and listener as a one-way TLS connection. For example, if you set this parameter to FALSE in the server configuration, then the server does not authenticate the client. If you set it to FALSE in the listener configuration, then the listener does not authenticate the client.

When set to OPTIONAL, the server behaves as follows:

- If the client sends a certificate, then the connection is completed as a two-way TLS connection after authenticating the client.
- If the client does not send a certificate, then the connection is completed as a one-way TLS connection.

Ensure that this parameter setting is consistent for the server or listener (on one side) and the client (on the other). Otherwise, the connection may fail. For example, if you enable client authentication in the server or listener configuration, then you must enable it in the client configuration.

Default

TRUE

Values

- TRUE | ON | YES | 1: To enable mTLS
- FALSE | OFF | NO | 0: To enable one-way TLS



OPTIONAL: To enable both TLS and mTLS

Example

SSL CLIENT AUTHENTICATION=FALSE

Related Topics

Oracle AI Database Security Guide

5.2.105 SSL DISABLE WEAK EC CURVES

Use the SSL_DISABLE_WEAK_EC_CURVES parameter to disable the use of weak Elliptic Curve Cryptography (ECC) curves.

Purpose

To disable the use of weak ECC curves with key length less than 256 bits. You can set this parameter in the database server (sqlnet.ora), client (sqlnet.ora or tnsnames.ora connect string), or the listener (listener.ora).

Usage Notes

The Oracle Net Services parameter SSL DISABLE WEAK EC CURVES is deprecated in Oracle Al Database 26ai.

Elliptic Curve Cryptography (ECC) features in Oracle Net Services, such as those used for secure external password stores, have some curves disabled by default. Oracle and other major vendors disable weak elliptic curves by default to protect systems from known cryptographic vulnerabilities, and to enforce modern security standards. These older, weaker curves can be susceptible to a variety of attacks and may present security risks if used. Because Oracle no longer has ECC curves with key length less than 256 bit enabled, this parameter no longer serves a purpose, and will be removed in a future release. Oracle strongly recommends that you review your configurations to ensure that you follow security best practices.



(i) Note

SSL_DISABLE_WEAK_EC_CURVES is deprecated in favor of TLS_KEY_EXCHANGE_GROUPS parameter starting with Oracle AI Database 26ai.

By default, this parameter is set to FALSE to enable the use of all ECC curves. If you want to enable the use of only Oracle approved curves with ECC curve key size of 256 bits or higher, then set this parameter to TRUE.

When set to TRUE, you can use only the following ECC curves:

- secp256r1
- secp384r1
- secp521r1
- x25519



Values

- TRUE | ON | YES | 1: To enable only the Oracle approved ECC curves with minimum ECC curve key length of 256 bits
- FALSE | OFF | NO | 0: To enable all ECC curves

Default

FALSE

Examples

• In the tnsnames.ora file:

```
net_service_name=
  (DESCRIPTION=
       (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr)(PORT=1521))
       (SECURITY=(SSL_DISABLE_WEAK_EC_CURVES=TRUE))
)
```

In the sqlnet.ora file or the listener.ora file:

```
SSL_DISABLE_WEAK_EC_CURVES=TRUE
```

Related Topics

TLS KEY EXCHANGE GROUPS

Use the ${\tt TLS_KEY_EXCHANGE_GROUPS}$ parameter to enable or disable post-quantum cryptographic (PQC) ML-KEM algorithms and classical ECDHE groups for TLS connections.

5.2.106 SSL ENABLE WEAK CIPHERS

Use the sqlnet.ora parameter $SSL_ENABLE_WEAK_CIPHERS$ to enable the use of weak Transport Layer Security (TLS) cipher suites.

Purpose

To enable the use of weak TLS ciphers for backward compatibility. You can set this parameter on both the database server and client.

Usage Notes

By default, this parameter is set to FALSE to block the use of weak ciphers. This simplifies the passing of compliance audits and improves the overall security of your database. If you want to enable the use of weak ciphers, then set this parameter to TRUE.

When set to FALSE, you can use only the following strong ciphers:

- TLS_AES_128_CCM_SHA256
- TLS_AES_128_GCM_SHA256
- TLS_AES_256_GCM_SHA384
- TLS_CHACHA20_POLY1305_SHA256
- TLS_DHE_RSA_WITH_AES_128_GCM_SHA256



- TLS_DHE_RSA_WITH_AES_256_GCM_SHA384
- TLS_ECDHE_ECDSA_WITH_AES_128_GCM_SHA256
- TLS_ECDHE_ECDSA_WITH_AES_256_GCM_SHA384
- TLS_ECDHE_RSA_WITH_AES_128_GCM_SHA256
- TLS_ECDHE_RSA_WITH_AES_256_GCM_SHA384

With the SSL_ENABLE_WEAK_CIPHERS=FALSE setting, if you try to use a weak cipher, then the following error messages appear:

- On the database server: ORA-28860: Fatal SSL error
- On the database client: ORA-29039: There are no matching cipher suites

Values

- TRUE | ON | YES | 1: To enable weak ciphers
- FALSE | OFF | NO | 0: To disable weak ciphers

Default

FALSE

Example

SSL_ENABLE_WEAK_CIPHERS=FALSE

Related Topics

SSL CIPHER SUITES

Use the SSL_CIPHER_SUITES parameter to control the combination of authentication, encryption, and data integrity algorithms used by Transport Layer Security (TLS).

Oracle Al Database Security Guide

5.2.107 SSL_EXTENDED_KEY_USAGE

Use the sqlnet.ora parameter $SSL_EXTENDED_KEY_USAGE$ to specify the purpose certificate keys.

Purpose

To specify the purpose of the key in a certificate.

Usage Notes

When you specify this parameter, Oracle uses the certificate with the matching extended key.

Values

client authentication

Example

SSL_EXTENDED_KEY_USAGE="client authentication"



5.2.108 SSL_SERVER_DN_MATCH

Use the SSL_SERVER_DN_MATCH parameter to enforce server-side certificate validation through distinguished name (DN) matching.

Purpose

To enforce server-side certificate validation through DN matching.

The purpose of adding this DN matching parameter for the client is to further improve security on a Transport Layer Security (TLS) connection. A TLS connection relies on the client to verify if the database server certificate is valid and signed by a trusted root certificate. The listener and server certificate DN matching adds another client-side check on the listener and server certificates to ensure that the certificates are the correct ones that the client expects.

Usage Notes

- If you set this parameter to TRUE, then in addition to verifying the server's certificate chain, the client enforces another check against the listener and server through DN matching.
- You can configure either partial DN matching or full DN matching.

Through partial DN matching, the client checks the HOST parameter (in the client sqlnet.ora file or connect string) against a host name in the certificate DN or certificate Subject Alternative Name (SAN) field. The client checks HOST against both the listener and server certificates in this order:

1. The client first compares HOST with a host name in the listener certificate's DN. For example, CN part of DN:

```
"c=us,o=examplecorporation,cn=sales.us.example.com"
```

2. If no match is found in the listener certificate's DN, then the client compares HOST with a host name in the listener certificate's SAN field. For example:

```
"DNS:sales.us.example.com"
```

If no match is found in the listener certificate's SAN field, then the client does not try connecting to the server and the connection fails.

- 3. If the listener certificate check succeeds, then the client performs similar checks on the server certificate. That is, the client first compares HOST with a host name in the server certificate's DN.
- 4. If no match is found in the server certificate's DN, then the client compares HOST with a host name in the server certificate's SAN field.

Through full DN matching, the client checks the complete DN in SSL_SERVER_CERT_DN against the certificate DN of both the listener and server certificates. To enforce a full DN match, specify the complete DN using the SSL_SERVER_CERT_DN parameter in the tnsnames.ora file or connect string.

Oracle recommends that you use the same certificate for both the listener and server.

If you use different certificates with different DNs for the listener and server, then full DN matching fails. In this case, you need to get new certificates with the same DN (for full DN matching) or you need to change your DN matching strategy. If you have configured partial



DN matching, then it may also fail if HOST is not found in the certificate DN or SAN fields of both the listener and server certificates.

 Prior to Oracle AI Database 26ai, partial DN matching checked against host name and SAN only in the server certificate. If a match was not found, then along with the host name and SAN, it also checked the SERVICE_NAME parameter. Similarly, full DN matching checked against the complete DN only in the server certificate.

If you want to revert to the earlier weaker DN matching behavior (that is, checking only the server certificate and allowing a service name check for partial DN matching), then set SSL_ALLOW_WEAK_DN_MATCH=TRUE. However, note that the SSL_ALLOW_WEAK_DN_MATCH parameter is deprecated and will be removed in a future release. Oracle recommends that you get new certificates or change your DN matching strategy.

Default

NO

Values

• YES | ON | TRUE | 1:

To enforce partial or full DN matching. If the DN matches the host name or SAN in both the listener and server certificates, then the connection succeeds. If the DN does not match the host name or SAN in the server or listener certificate, then the connection fails.

NO | OFF | FALSE | 0:

To not enforce DN matching. If the DN does not match the host name or SAN in the sever or listener certificate, then the connection is successful, but an error is logged to the sqlnet.log file.

Example

SSL_SERVER_DN_MATCH=YES

Related Topics

SSL SERVER CERT DN

Use the $SSL_SERVER_CERT_DN$ parameter to specify the distinguished name (DN) of the database server.

SSL ALLOW WEAK DN MATCH

Use the sqlnet.ora parameter SSL_ALLOW_WEAK_DN_MATCH to allow the earlier weaker distinguished name (DN) matching behavior during server-side certificate validation.

Oracle AI Database Security Guide

5.2.109 SSL_VERSION

Use the SSL_VERSION parameter to define valid Transport Layer Security (TLS) versions to be used for connections.

Purpose

To define the version of TLS that must run on the systems with which the database server communicates. By default, the database server and client negotiate the strongest security protocol. Oracle does not recommend modifying this parameter, unless your security requirements mandate the usage of certain protocol versions.



Usage Notes

- Clients, listeners, and database servers must use compatible versions. Modify this
 parameter only when necessary to enforce the use of the more secure TLS protocol and
 not allow clients that only work with the older TLS protocols. The current default uses TLS
 1.3, which is the version required for multiple security compliance requirements. If you
 need to specify TLS 1.2, then also include TLS 1.3 to allow more secure connections.
- In addition to sqlnet.ora, listener.ora, and cman.ora, you can specify this parameter under the SECURITY section of the the section of the connect string. The parameter value specified in the connect string takes precedence over the other specified values.
- Starting with Oracle AI Database 26ai, the use of Transport Layer Security protocol versions 1.0 and 1.1 are desupported.
 - In most cases, this change will not have any impact, because the database client and server will negotiate the use of the most secure protocol and cipher algorithm. However, if TLS 1.0 or 1.1 has been specified, then you must either remove it to allow the database server and client to pick the most secure protocol, or you must specify either TLS 1.2, or TLS 1.3, or both, for the protocol. Oracle recommends using the latest, most secure protocol. That protocol is TLS 1.3, which is introduced with Oracle AI Database 26ai.
- Starting with Oracle AI Database 26ai, the Secure Socket Layer v3 protocol (SSLv3) is no longer supported for database server-client connections, and the sqlnet.ora parameter ADD SSLV3 TO DEFAULT has been removed.
 - SSLv3 is a much less secure protocol to secure the database server-to-client connection. Instead of using SSLv3, allow the database server and client to negotiate the most secure protocol that is common between the server and the client. Oracle AI Database 26ai provides TLS 1.2 and TLS 1.3 protocols for certificate-based network encryption.
- If you set SSL_VERSION to undetermined, then the most secure TLS protocol version is used. You can also use the SSL_VERSION=undetermined setting in the connect string for a specific connection to override the SSL_VERSION value configured in the sqlnet.ora, listener.ora, or cman.ora file.
- If you do not set SSL_VERSION to any value, then all the supported TLS protocol versions
 are tried starting with the most secure version. This is typically the most common
 configuration, ensuring that the strongest protocol is chosen during TLS negotiation.

Values

undetermined | TLSv1.2 | TLSv1.3

Default

undetermined

Syntax and Examples

To specify a single protocol version:

SSL VERSION=TLS protocol version

For example:

SSL_VERSION=TLSv1.3



To specify multiple protocol versions, use a comma-separated string of values, enclosed in parenthesis:

```
SSL VERSION=(TLS protocol version1,TLS protocol version2)
```

For example:

```
SSL_VERSION=(TLSv1.2,TLSv1.3)
```

(i) Note

Do not enclose protocol versions in parenthesis while specifying this parameter in the tnsnames.ora file or as part of the connect string, otherwise the setting will not parse correctly. For example:

```
net_service_name=
  (DESCRIPTION=
     (ADDRESS=(PROTOCOL=tcps)(HOST=salesserver)(PORT=1522))
     (SECURITY=(SSL VERSION=TLSv1.2,TLSv1.3))
```

Related Topics

- Set the Required TLS Version on the Server
- Set the Required TLS Version on the Client

5.2.110 TCP.ALLOWED_PROXIES

Use the sqlnet.ora parameter TCP.ALLOWED_PROXIES to specify a list of the Oracle Connection Manager (CMAN) addresses that can forward client IP address to the database server.

Purpose

To specify a list of the CMAN addresses (IP addresses or host names) that can forward client IP address to the database server.

Usage Notes

Use this parameter in the server-side sqlnet.ora file to list the allowed CMAN instances.

In addition to the TCP.ALLOWED PROXIES parameter, you must set the ENABLE IP FORWARDING parameter in the cman.ora file to enable client address forwarding. CMAN will forward client address only if ENABLE_IP_FORWARDING is set to ON.

You can use the SYS_CONTEXT ('USERENV', 'IP_ADDRESS') function to query the forwarded client address details.

Default

None



Value

A comma-separated list of IP addresses or host names from which you want to allow client address forwarding.

Example

TCP.ALLOWED_PROXIES=(10.1.1.1/24,cmanhost1.example.com)

Related Topics

ENABLE IP FORWARDING

Use the cman.ora parameter ENABLE_IP_FORWARDING to forward client IP address to the database server.

Oracle AI Database SQL Language Reference

5.2.111 TCP.CONNECT_TIMEOUT

Use the sqlnet.ora parameter TCP.CONNECT_TIMEOUT to specify the amount of time in which a client must establish TCP connections to database servers.

Purpose

To specify the time in ms, sec, or min, for a client to establish a TCP connection (PROTOCOL=tcp in the TNS connect address) to the database server.

Usage Notes

If a TCP connection to the database is not established in the specified amount of time, then the connection attempt ends. The client receives the following error:

ORA-12170: Cannot connect. TCP connect timeout of time_interval for host_port or key. (CONNECTION_ID=ID_string).

The timeout applies to each IP address that resolves to a host name. It accepts different timeouts with or without space between the value and the unit. For example, if a host name resolves to an IPv6 and an IPv4 address, and if the host is not reachable through the network, then the connection request times out twice because there are two IP addresses. In this example, the default timeout setting of 60 causes a timeout in 120 seconds. If you do not specify a unit of measure, then the default unit is sec.

Default

60

Example

TCP.CONNECT_TIMEOUT=10 ms



5.2.112 TCP.EXCLUDED_NODES

Use the sqlnet.ora parameter TCP.EXCLUDED_NODES to specify which clients are denied access to the database.

Purpose

To specify which clients are denied access to the database.

Usage Notes

This parameter is only valid when you set the **TCP.VALIDNODE_CHECKING** parameter to yes.

You can use wildcards in this parameter for IPv4 addresses and CIDR notation for IPv4 and IPv6 addresses.

Syntax

```
\verb|TCP.EXCLUDED_NODES=(hostname \mid ip\_address, hostname \mid ip\_address, \ldots)|
```

Example

```
TCP.EXCLUDED_NODES=(finance.us.example.com, mktg.us.example.com, 192.0.2.25, 172.30.*, 2001:DB8:200C:417A/32)
```

5.2.113 TCP.INVITED_NODES

Use the sqlnet.ora parameter TCP.INVITED_NODES to specify which clients are allowed access to the database.

Purpose

To specify which clients are allowed access to the database. This list takes precedence over the TCP.EXCLUDED NODES parameter if both lists are present.

Syntax

```
TCP.INVITED_NODES=(hostname | ip_address, hostname | ip_address, ...)
```

Usage Notes

- This parameter is only valid when you set the <u>TCP.VALIDNODE_CHECKING</u> parameter to yes.
- This parameter accepts wildcards for IPv4 addresses and CIDR notation for IPv4 and IPv6 addresses.

Example

```
TCP.INVITED_NODES=(sales.us.example.com, hr.us.example.com, 192.0.*, 2001:DB8:200C:433B/32)
```



5.2.114 TCP.NODELAY

Use the sqlnet.ora parameter TCP.NODELAY to preempt delays in buffer flushing within the TCP/IP protocol stack.

Purpose

To preempt delays in buffer flushing within the TCP/IP protocol stack.

Default

ves

Values

yes | no

Example

TCP.NODELAY=yes

5.2.115 TCP.QUEUESIZE

Use the sqlnet.ora parameter TCP.QUEUESIZE to configure the maximum length of queues for pending connections on TCP listening sockets.

Purpose

To configure the maximum length of the queue for pending connections on a TCP listening socket.

Default

System-defined maximum value. The defined maximum value for Linux is 128.

Values

Any integer value up to the system-defined maximum.

Examples

TCP.QUEUESIZE=100

5.2.116 TCP.VALIDNODE_CHECKING

Use the ${\tt sqlnet.ora}$ parameter TCP.VALIDNODE_CHECKING to enable and disable valid node checking for incoming connections.

Purpose

To enable and disable valid node checking for incoming connections.

Usage Notes

If you set this parameter to yes, then incoming connections are allowed only if the connections originate from a node that conforms to a list that you specified in the <u>TCP.INVITED_NODES</u> or <u>TCP.EXCLUDED_NODES</u> parameters.



The TCP.INVITED_NODES and TCP.EXCLUDED_NODES parameters are valid only when you set the TCP.VALIDNODE CHECKING parameter to yes.

You must set this parameter and the dependent parameters, TCP.INVITED_NODES and TCP.EXCLUDED_NODES, in the sqlnet.ora file of the listener. This is important in Oracle RAC environments where listeners run from the Oracle Grid Infrastructure home. Setting the parameter in the database home does not have an effect in Oracle RAC environments. In such environments, you must include the address of all Single Client Access Name (SCANs), Virtual IPs (VIPs), local IP in the TCP.INVITED NODES list.

In VLAN environments, the sqlnet.ora file present in the Oracle Grid Infrastructure homes should include all of the addresses of all of the VLANs. The VLANs perform the network segregation, whereas the values that are set for INVITED_NODES enables or restricts access to databases within the VLANs.

If multiple databases within the same VLAN require different INVITED_NODE lists, then you must configure separate listeners.

Default

no

Values

yes | no

Example

TCP.VALIDNODE_CHECKING=yes

5.2.117 TENANT_ID

Use the TENANT_ID parameter to specify the ID of your Microsoft Entra ID tenant.

Purpose

To specify the ID of the Entra ID tenant in which your Entra ID application is registered. This is the Azure tenancy ID that uniquely identifies your database instance in Entra ID.

Usage Notes

- You use this parameter along with the TOKEN_AUTH parameter for the AZURE_INTERACTIVE,
 AZURE_SERVICE_PRINCIPAL, AZURE_MANAGED_IDENTITY, and AZURE_DEVICE_CODE token based authentication flows.
- This parameter is mandatory for the thick clients (OCI and Instant Client). It is optional
 when using the JDBC-thin clients and ODP.NET core and managed database clients.
 - When using the JDBC-thin clients and ODP.NET core and managed database clients, if you have configured the Azure SDKs, then the client driver automatically searches for the tenant ID in the SDK configuration. If you have not configured the SDKs, then you must set this parameter.
 - When using the OCI and Instant Clients (which do not use the Azure SDKs), you must set this parameter (along with other required parameters, such as CLIENT_ID). Otherwise, an error message appears prompting you to configure the required parameters.
- For the JDBC-thin clients, you can specify this parameter in the connect string, Easy Connect syntax, tnsnames.ora file, or properties. For the thick clients (OCI and Instant Client) and ODP.NET core and managed database clients, you can specify this parameter



in the connect string, sqlnet.ora file, Easy Connect syntax, or tnsnames.ora file. The parameter value specified in the connect string takes precedence.

Default

None

Value

You can get the tenant ID value by logging in to the Azure portal. This is listed as Tenant ID on the Tenant Properties page.

Examples

```
In the tnsnames.ora file:
net_service_name=
    (DESCRIPTION =
       (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr)(PORT=1521))
       (SECURITY=
          (SSL_SERVER_DN_MATCH=TRUE)
          (SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleContext")
          (TOKEN_AUTH=AZURE_INTERACTIVE)
          (AZURE_DB_APP_ID_URI=https://application.example.com/
123ab4cd-1a2b-1234-a12b-aa00123b2cd3)
          (TENANT_ID=1a123ab1-a1b1-1a2b-a1b2-a12bcdab0123)
          (REDIRECT_URI=http://localhost:1575))
       (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))
In the sqlnet.ora file:
SSL_SERVER_DN_MATCH=TRUE
TOKEN_AUTH=AZURE_INTERACTIVE
AZURE_DB_APP_ID_URI=https://application.example.com/123ab4cd-1a2b-1234-a12b-
aa00123b2cd3
TENANT_ID=1a123ab1-a1b1-1a2b-a1b2-a12bcdab0123
REDIRECT_URI=http://localhost:1575
In the Easy Connect string:
tcps:sales-svr:1521/sales.us.example.com?
TOKEN_AUTH=AZURE_INTERACTIVE&AZURE_DB_APP_ID_URI=https://
application.example.com/123ab4cd-1a2b-1234-a12b-
aa00123b2cd3&TENANT_ID=1a123ab1-a1b1-1a2b-a1b2-
a12bcdab0123&REDIRECT_URI=http://localhost:1575
```

In these examples, the CLIENT_ID parameter is not specified. CLIENT_ID is required when using the thick clients (OCI and Instant Client). This parameter is optional for the JDBC-thin and ODP.NET core and managed database clients, which can automatically get this value from the Azure SDK configuration.

Related Topics

Oracle Database Security Guide



TOKEN AUTH

Use the TOKEN_AUTH parameter to configure token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) or Microsoft Azure users of Microsoft Entra ID (previously called Microsoft Azure Active Directory).

5.2.118 TNSPING.TRACE_DIRECTORY

Use the sqlnet.ora parameter TNSPING.TRACE_DIRECTORY to specify the destination directory for the TNSPING utility trace file, tnsping.trc.

Purpose

To specify the destination directory for the TNSPING utility trace file, tnsping.trc.

Default

The ORACLE_HOME/network/trace directory.

Example

TNSPING.TRACE DIRECTORY=/oracle/traces

5.2.119 TNSPING.TRACE_LEVEL

Use the sqlnet.ora parameter TNSPING.TRACE_LEVEL to enable or disable TNSPING utility tracing at a specified level.

Purpose

To enable or diable TNSPING utility tracing at a specified level.

Default

off

Values

- off for no trace output
- user for user trace information
- admin for administration trace information
- support for Oracle Support Services trace information

Example

TNSPING.TRACE_LEVEL=admin



5.2.120 TOKEN_AUTH

Use the TOKEN_AUTH parameter to configure token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) or Microsoft Azure users of Microsoft Entra ID (previously called Microsoft Azure Active Directory).

Purpose

Token-based access enforces strong authentication, which enables a more secure access to the database. IAM users can connect to OCI Database as a Service (DBaaS) databases, and Azure users can connect to Oracle Databases (cloud or on-premises).

With this setting, when a / (slash) login is used, the Oracle Database client either looks for a token file or directly gets the token using single-sign on (SSO) credentials.

Use this parameter under the SECURITY section of the tnsnames.ora file, sqlnet.ora file, or directly as part of the command-line connect string. The parameter value specified in the connect string takes precedence over the other specified values.

Usage Notes for IAM

OCI IAM token:

An OCI IAM token (db-token), which is obtained from IAM using Oracle Cloud Infrastructure (OCI) Command Line Interface (CLI) or programmatically from the OCI Software Development Kit (SDK), is a proof-of-possession (PoP) token with an expiration time and scope.

You can use one of the IAM user credentials, such as API-key, security token, resource principal, instance principal, or delegation token to retrieve the db-token and private key from IAM.

These tokens are transmitted over secure channels. You must use only the TCP/IP with Transport Layer Security (TLS) protocol, otherwise an error message appears indicating that non-TLS connections are disallowed.

Required setting for token-based authentication:

You must configure the TCPS protocol (PROTOCOL=tcps) and set the SSL_SERVER_DN_MATCH parameter to TRUE for token-based authentication.

Use a file location to send the token to Oracle Database:

When an IAM user logs in using <code>/@connect_identifier</code> (and <code>TOKEN_AUTH</code> is set to <code>OCI_TOKEN</code>), the <code>TOKEN_AUTH=OCI_TOKEN</code> setting along with <code>/@connect_identifier</code> instructs the database client to get the <code>db-token</code> and private key from either the default directory or the location specified by <code>TOKEN_LOCATION</code>.

Use the client API to send the token to Oracle Database:

If your client application is updated to retrieve tokens from IAM, then you can override the <code>TOKEN_AUTH=OCI_TOKEN</code> setting. The client application gets the <code>db-token</code> and private key from IAM and sends as attributes to the database client using the client API. In this case, you do not need to specify the <code>TOKEN_AUTH</code> and <code>TOKEN_LOCATION</code> parameters.

General IAM token-based authentication process:

 An IAM user or application in OCI first requests the db-token from IAM by using APIkey, security token, resource principal, service principal, instance principal, or delegation token (delegation token is available only in the Cloud Shell).



To use a security token, you need to generate it by completing the browser authentication process and then request the db-token using that security token. If the IAM policy that authorizes you to be issued the db-token exists, then the db-token is returned.

You request the db-token using OCI CLI (or OCI SDK for applications). For example, run the following OCI CLI command to request the db-token by using an API-key (apikey):

\$ oci iam db-token get --profile scott

The profile option specifies the profile for which you want to access the IAM user credentials and retrieve the db-token.

For more information on using OCI CLI, see the get command details in <u>Oracle Cloud</u> <u>Infrastructure CLI Command Reference</u>.

- 2. OCI CLI references the config file (that stores your IAM user credentials as part of the profile) and makes a call to IAM to get the db-token. The db-token and private key files are written at the default or specified token location.
- 3. You can specify the TOKEN_LOCATION parameter to override the default directory where the db-token and private key files are stored.

The database client gets the db-token and private key from the default token location or the location specified by TOKEN_LOCATION, signs the db-token with the private key and sends it to the database server. The database server verifies the db-token and gets the group membership information for the user. If the IAM user is mapped to a database schema (exclusively or shared), then the login is completed.

Use an Oracle Database client to directly send the token to Oracle Database:

This feature is available in environments that use the JDBC-thin clients and ODP.NET core and managed database clients. For the JDBC-thin clients, you can set this in the tnsnames.ora or Easy Connect connect string. For the ODP.NET core and managed database clients, you can set this in the sqlnet.ora, tnsnames.ora, or Easy Connect connect string. The parameter value specified in the connect string takes precedence.

To configure this feature for the JDBC-thin clients, see *Oracle Database JDBC Developer's Guide* and for the ODP.NET clients, see *Oracle Data Provider for .NET Developer's Guide*.

The following authentication flows enable the database client to directly retrieve the db-token with IAM SSO credentials:

OCI Interactive:

TOKEN_AUTH=OCI_INTERACTIVE specifies the OCI Interactive flow. This authenticates the token request interactively using a web browser, and is useful for client-side web applications or desktop applications.

The database client gets a default profile (named DEFAULT) from the OCI configuration file, which is stored either in the default directory or at the location specified by the OCI_CONFIG_FILE parameter. After validating the user's region against a list of valid regions, the client launches an authentication request to the user in a web browser, prompting to log in using the IAM user name and password along with any additional factors required by IAM.

Optionally, you can override the DEFAULT profile set in the configuration file by specifying the OCI PROFILE parameter.

OCI API Key:



TOKEN_AUTH=OCI_API_KEY specifies the OCI API Key flow. This authenticates the token request with IAM using an IAM-recognized API-key.

The database client reads the file system location of the API-key from the user's DEFAULT profile in the OCI configuration file, from either the default configuration file directory or the location specified by OCI_CONFIG_FILE.

Optionally, you can override the user's DEFAULT profile set in the configuration file by specifying the OCI_PROFILE parameter.

OCI Instance Principal:

TOKEN_AUTH=OCI_INSTANCE_PRINCIPAL specifies the OCI Instance Principal flow. This authenticates the token request with IAM as an OCI instance principal for applications running on OCI compute instances.

OCI Delegation Token:

TOKEN_AUTH=OCI_DELEGATION_TOKEN specifies the OCI Delegation Token flow. This authenticates the token request with IAM using a delegation token for applications running in an OCI Cloud Shell.

OCI Resource Principal:

TOKEN_AUTH=OCI_RESOURCE_PRINCIPAL specifies the OCI Resource Principal flow. This authenticates the token request with IAM as an OCI resource principal for applications running in a container (as an OCI function).

– Default:

TOKEN_AUTH=OCI_DEFAULT specifies the Default flow. With this setting, the client driver reads the predefined environment variables from the SDK configuration, evaluates each authentication flow in a sequence, and then assigns the most appropriate flow based on the environment where the application is running.

Sequence in which the driver evaluates each authentication flow with OCI_DEFAULT:

- 1. OCI API Key: The driver first checks if a configuration file is present at the location specified by the OCI_CONFIG_FILE parameter or at the default location (\$HOME/.oci/config). The driver then checks if the file contains a profile matching the name configured by the OCI_PROFILE parameter or the default name (DEFAULT). Finally, the driver checks if the profile is configured with an entry named key_file. If all of these checks succeed, then authentication with an API key is used. If any of these checks fail, then the driver proceeds to the next step.
- 2. OCI Delegation Token: The driver first checks if the OCI_CONFIG_FILE environment variable is set. The driver then checks if a file is present at the location configured by the OCI_CONFIG_FILE environment variable. The driver then checks if the file contains a profile named DEFAULT. Finally, the driver checks if the profile is configured with an entry named delegation_token_file. If all of these checks succeed, then authentication with a delegation token is used. If any of these checks fail, then the driver proceeds to the next step.
- 3. OCI Resource Principal: The driver first checks if the OCI_RESOURCE_PRINCIPAL_VERSION environment variable is set. The driver then checks if the variable is set to version 2.2 or 1.1. If the variable is set to 2.2, the driver then checks if the OCI_RESOURCE_PRINCIPAL_PRIVATE_PEM, OCI_RESOURCE_PRINCIPAL_RPST, and OCI_RESOURCE_PRINCIPAL_REGION environment variables are also set. Otherwise, if the variable is set to 1.1, then the driver checks if the OCI_RESOURCE_PRINCIPAL_RPT_ENDPOINT environment variable is also set. If the required variables for a version are set, then authentication as a



resource principal is used. If any variable is not set, then the driver proceeds to the next step.

- 4. OCI Instance Principal: The driver requests a certificate from the instance metadata service. The base URL of the service is http:// 169.254.169.254/opc/v2/. However, a fallback URL of http:// 169.254.169.254/opc/v1/ is used if the v2 service request fails. If a request to the v2 or v1 service succeeds, then authentication as an instance principal is used. If the request fails, then the driver proceeds to the next step.
- The driver reports an error indicating that authentication is not possible using any of the authentication flows.

You also need to specify the OCI_DATABASE and OCI_COMPARTMENT parameters for all these authentication flows, if the OCI database token policy limits you to access only a particular database or databases within a compartment.

(i) Note

You can also use another IAM credential, IAM database password, to request the dbtoken from IAM. This db-token is a bearer token and does not come with a private key. You can configure the database client to request this token using your IAM user name and IAM database password. An application cannot pass this type of db-token to the client. In this case, you use a different parameter setting (PASSWORD_AUTH=OCI_TOKEN).

Unlike the API-key, security token, resource principal, service principal, instance principal, and delegation token that require an application or tool to get a token, the IAM database password can only be used by the database client to retrieve the token. See PASSWORD AUTH.

Default Setting for IAM

None



Table 5-2 Values and Examples for IAM

Value	Example
TOKEN_AUTH=OCI_TOKEN	In the tnsnames.ora file:
	not govern as nome.
	<pre>net_service_name= (DESCRIPTION =</pre>
	(ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr)
	(PORT=1521))
	(SECURITY=
	(SSL_SERVER_DN_MATCH=TRUE)
	(SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleCont ext")
	(TOKEN_AUTH=OCI_TOKEN))
	(CONNECT_DATA=(SERVICE_NAME=sales.us.example.com)
	,
	In the sqlnet.ora file:
	SSL_SERVER_DN_MATCH=TRUE
	TOKEN_AUTH=OCI_TOKEN
	In these examples, the optional TOKEN_LOCATION parameter is not
	specified. Thus, the client automatically gets the db-token and private key from the default token location.



Table 5-2 (Cont.) Values and Examples for IAM

Value	Example
TOKEN_AUTH=OCI_INTERACTIVE	In the tnsnames.ora file:
	<pre>net_service_name= (DESCRIPTION =</pre>
	<pre>(SSL_SERVER_DN_MATCH=TRUE) (SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleCont ext") (TOKEN_AUTH=OCI_INTERACTIVE))</pre>
	<pre>(CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))</pre>
	In the sqlnet.ora file:
	SSL_SERVER_DN_MATCH=TRUE TOKEN_AUTH=OCI_INTERACTIVE
	In these examples, the optional OCI_CONFIG and OCI_PROFILE parameters are not specified. Thus, the client automatically gets the DEFAULT profile from the default configuration file directory.



Table 5-2 (Cont.) Values and Examples for IAM

Value	Example
TOKEN_AUTH=OCI_API_KEY	In the tnsnames.ora file:
	<pre>net_service_name= (DESCRIPTION = (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr) (PORT=1521)) (SECURITY= (SSL_SERVER_DN_MATCH=TRUE)</pre>
	(SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleCont ext")
	(TOKEN_AUTH=OCI_API_KEY))
	<pre>(CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))</pre>
	In the sqlnet.ora file:
	SSL_SERVER_DN_MATCH=TRUE TOKEN_AUTH=OCI_API_KEY
	In these examples, the optional OCI_CONFIG and OCI_PROFILE parameters are not specified. Thus, the client automatically gets the API-key value from the DEFAULT profile stored in the default configuration file directory.
TOKEN_AUTH=OCI_INSTANCE_PRI NCIPAL	In the tnsnames.ora file:
	<pre>net_service_name= (DESCRIPTION = (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr) (PORT=1521)) (SECURITY= (SSL_SERVER_DN_MATCH=TRUE)</pre>
	(SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleCont ext")
	(TOKEN_AUTH=OCI_INSTANCE_PRINCIPAL))
	<pre>(CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))</pre>
	In the sqlnet.ora file:
	SSL_SERVER_DN_MATCH=TRUE TOKEN_AUTH=OCI_INSTANCE_PRINCIPAL



Table 5-2 (Cont.) Values and Examples for IAM

```
Value
                             Example
TOKEN_AUTH=OCI_DELEGATION_T In the tnsnames.ora file:
                             net_service_name=
                                  (DESCRIPTION =
                                     (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr)
                             (PORT=1521))
                                     (SECURITY=
                                        (SSL_SERVER_DN_MATCH=TRUE)
                             (SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleCont
                             ext")
                                        (TOKEN_AUTH=OCI_DELEGATION_TOKEN))
                             (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com)
                             In the sqlnet.ora file:
                             SSL_SERVER_DN_MATCH=TRUE
                             TOKEN_AUTH=OCI_DELEGATION_TOKEN
TOKEN_AUTH=OCI_RESOURCE_PRI In the tnsnames.ora file:
NCIPAL
                             net service name=
                                  (DESCRIPTION =
                                     (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr)
                             (PORT=1521))
                                     (SECURITY=
                                        (SSL_SERVER_DN_MATCH=TRUE)
                             (SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleCont
                             ext")
                                        (TOKEN_AUTH=OCI_RESOURCE_PRINCIPAL))
                             (CONNECT DATA=(SERVICE NAME=sales.us.example.com)
                             In the sqlnet.ora file:
                             SSL SERVER DN MATCH=TRUE
                             TOKEN_AUTH=OCI_RESOURCE_PRINCIPAL
```

Usage Notes for Entra ID

Entra ID access token:



An Entra ID OAuth2 access token is a bearer token with an expiration time and scope. This token follows the OAuth2.0 standard with Entra ID extensions. You can request these tokens from tools and scripts run on Linux, Microsoft PowerShell, or other environments. You can also request these tokens programmatically using the Microsoft SDKs.

These tokens are transmitted over secure channels. You must use only the TCP/IP with Transport Layer Security (TLS) protocol, otherwise an error message appears indicating that non-TLS connections are disallowed.

Required setting for token-based authentication:

You must configure the TCPS protocol (PROTOCOL=tcps) and set the SSL_SERVER_DN_MATCH parameter to TRUE for token-based authentication.

Use a file location to send the token to Oracle Database:

When an Azure user logs in using <code>/@connect_identifier</code> (and <code>TOKEN_AUTH</code> is set to <code>OAUTH</code>), the <code>TOKEN_AUTH = OAUTH</code> setting instructs the database client to get the access token from the directory location specified by <code>TOKEN_LOCATION</code> if the token file is named <code>token</code>. If the token file name is different from <code>token</code>, then you must use the file name along with the directory location while specifying the <code>TOKEN_LOCATION</code> parameter.

The TOKEN_LOCATION parameter is mandatory for Azure token-based authentication. The database client gets the token from this location and sends it to the database server.

Use the client API to send the token to Oracle Database:

If your client application is updated to retrieve tokens from Entra ID, then you can override the TOKEN_AUTH=OAUTH setting. Entra ID directly passes the db-token as an attribute to the database client using the client API. When the client receives this request, the client sends it to the database server.

In this case, you do no need to specify the TOKEN_AUTH and TOKEN_LOCATION parameters.

General Azure token-based authentication process:

1. An Azure user or application first requests the access token from Entra ID using one of the supported authentication flows (resource owner password credentials, authorization code, on-behalf-of (OBO) flow, or client credentials).

An Azure user can connect using any supported utility to retrieve the token and store it in a local file directory.

You can request the token from tools and scripts run on Linux, Microsoft PowerShell, or other environments. You can also request programmatically using the Microsoft SDKs.

For detailed examples on how to retrieve an Entra ID OAuth2 access token, see *Oracle AI Database Security Guide*.

2. The database client then sends the token to the database server. The database server verifies the token (using the Entra ID public key) and extracts various claims from the token, including user name, app roles, and audience. If the Entra ID principal is mapped to a database schema (exclusively or shared), then the login is completed.

Use an Oracle Database client to directly send the token to Oracle Database:

This feature is available in environments that use the JDBC-thin clients, thick clients (Oracle Call Interface (OCI) and Oracle Database Instant Client, JDBC-thick, ODP.NET unmanaged, or Python-thick), ODP.NET Core classes, or ODP.NET Managed Driver classes.

For the thick clients, only the interactive flow is supported (TOKEN_AUTH=AZURE_INTERACTIVE).



For the JDBC-thin clients, you can set this in the tnsnames.ora or Easy Connect connect string. For the thick clients and ODP.NET core and managed database clients, you can set this in the tnsnames.ora, connect string, or sqlnet.ora file (except for REDIRECT_URI and CLIENT_CERTIFICATE). The parameter value specified in the connect string takes precedence.

To configure this feature for the JDBC clients, see *Oracle Database JDBC Developer's Guide*. For the ODP.NET clients, see *Oracle Data Provider for .NET Developer's Guide*. For the OCI and Instant Clients, see *Oracle Call Interface Developer's Guide*.

The following authentication flows enable the database client to directly retrieve an access token with Azure SSO credentials:

Azure OAuth2 Interactive:

TOKEN_AUTH=AZURE_INTERACTIVE specifies the Azure OAuth2 Interactive flow. This authenticates the token request interactively using a web browser, and is useful for client-side web applications or desktop applications.

When an Azure user logs in using /@connect_identifier (and TOKEN_AUTH is set to AZURE_INTERACTIVE), the TOKEN_AUTH=AZURE_INTERACTIVE setting along with / @connect_identifier instructs the database client driver to directly get an access token from Entra ID. This is for human users who are logging in to tools (such as SQLcl) and can also open a browser window in their environment for authentication.

If the user has not already logged in, then the database client launches an authentication request to the user (either in a dialog box if the user is using a web application or as a prompt if the user is working in a command line shell), prompting to log in using the Azure user name and password. After logging in to the Azure account, the user is redirected back to the client application (to its registered redirect URI).

Optionally, you can set the REDIRECT_URI parameter if you want to override the default redirect URI value (http://localhost).

You must set the AZURE_DB_APP_ID_URI parameter to compose the authorization scope of your token request.

The <code>CLIENT_ID</code> and <code>TENANT_ID</code> parameters are optional for the JDBC-thin and ODP.NET core and managed database clients, which can automatically get these values from the Azure SDK configuration. <code>CLIENT_ID</code> and <code>TENANT_ID</code> are required parameters for the OCI and Instant Clients.

Azure Service Principal:

TOKEN_AUTH=AZURE_SERVICE_PRINCIPAL specifies the Azure Service Principal flow. This authenticates the token request as a service principal by using either a client secret or a client certificate, and is useful for server-side applications (for example, microservices or back-end apps).

You must set the $\verb"azure_db_app_id_uri"$ parameter to compose the authorization scope of your token request.

The CLIENT_ID, TENANT_ID, and CLIENT_CERTIFICATE parameters are optional for the JDBC-thin and ODP.NET core and managed database clients, which can automatically get these values from the Azure SDK configuration. CLIENT_ID and TENANT_ID are required parameters for the OCI and Instant Clients.

Azure Managed Identity:

TOKEN_AUTH=AZURE_MANAGED_IDENTITY specifies the Azure Managed Identity flow. This authenticates the token request with Entra ID as an Azure managed identity, and is useful for client-side or server-side applications hosted on Azure environments (for example, Azure App Service or Azure virtual machine).



You must set the AZURE DB APP ID URI parameter to compose the authorization scope of your token request.

You can set the CLIENT ID parameter to configure a user-assigned managed identity for authenticating the token request. This parameter is optional for the JDBC-thin and ODP.NET core and managed database clients, which can automatically get this value from the Azure SDK configuration. CLIENT ID is required for the OCI and Instant Clients.

Azure Device Code:

TOKEN AUTH-AZURE DEVICE CODE specifies the Azure Device Code flow. This authenticates the token request interactively, and is for human users or client-side applications running on platforms with limited or no browser support (for example, command line environments such as SQLcl).

The database client displays a device code and an Entra ID login URL through the standard output of the tool, and prompts the user to enter the device code, Azure user name, and Azure password on any browser-supporting device (for example, cellphone or laptop). After completing the login in a web browser, the Azure SDK returns an access token to the client. The client sends the access token to the database to authorize the database user session.

You must set the AZURE_DB_APP_ID_URI parameter to compose the authorization scope of your token request.

The CLIENT ID and TENANT ID parameters are optional for the JDBC-thin and ODP.NET core and managed database clients, which can automatically get these values from the Azure SDK configuration. CLIENT ID and TENANT ID are required parameters for the OCI and Instant Clients.

(i) Note

You must explicitly enable the Azure OAuth2 Interactive and Azure Device Code flows for your Entra ID app in the Azure portal. To do so, on the App registrations - Authentication page, under Advanced Settings, set Allow public client flows to Yes.

Default:

TOKEN AUTH-AZURE DEFAULT specifies the Default flow. With this setting, the client driver reads the predefined environment variables from the SDK configuration, evaluates each authentication flow in a sequence, and then assigns the most appropriate flow based on the environment where the application is running.

Sequence in which the driver evaluates each authentication flow with AZURE_DEFAULT:

- 1. Azure Service Principal with Client Secret Credentials: The driver checks if client ID and client secret are configured as parameters to the driver or as SDK environment variables. If both are configured, then the driver authenticates as a service principal using a client secret. Otherwise, the driver proceeds to the next step.
- 2. Azure Service Principal with Client Certificate Credentials: The driver checks if client ID and client certificate are configured as parameters to the driver or SDK environment variables. If both are configured, then the driver authenticates as a service principal using a client certificate. Otherwise, the driver proceeds to the next step.



- 3. Azure Username Credentials: The driver checks if client ID, username, and password are configured as parameters to the driver or SDK environment variables. If all are configured, then the driver authenticates as a service principal using the username and password. Otherwise, the driver proceeds to the next step.
- 4. Azure Managed Identity: The driver checks if the MSI_ENDPOINT or IDENTITY_ENDPOINT environment variable is set. If either is set, then the driver authenticates as a managed identity using the configured endpoint. If neither is set, then the driver checks if the AZURE_TENANT_ID and AZURE_FEDERATED_TOKEN_FILE environment variables are set. If both are set, then the driver authenticates as a managed identity using the configured token file. If both are not set, then the driver requests an access token from the Azure Instance Metadata Service (IMDS) endpoint. If the request succeeds, then the driver authenticates as a managed identity. Otherwise, the driver proceeds to the next step.
- 5. Visual Studio Credentials: For ODP.NET Core classes and ODP.NET Managed Driver classes, the driver additionally evaluates the Azure user through Visual Studio Credentials authentication flow. The driver checks if the TENANT_ID parameter or the AZURE_TENANT_ID environment variable is set and if the Azure user is logged in to Visual Studio. If both the checks succeed, then authentication with the Visual Studio credentials is used. Otherwise, the driver proceeds to the next step.
- The driver reports an error indicating that authentication is not possible using any of the authentication flows.

Default Setting for Entra ID

None



Table 5-3 Values and Examples for Entra ID

Value	Example
TOKEN_AUTH=OAUTH	 If the token file is named token, TOKEN_AUTH=OAUTH, and TOKEN_LOCATION="token_file_directory":
	In the tnsnames.ora file:
	<pre>net_service_name= (DESCRIPTION=</pre>
	(ADDRESS=(PROTOCOL=tcps) (HOST=salesserver1)(PORT=1522))
	(SECURITY= (SSL_SERVER_DN_MATCH=TRUE)
	(SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleContext")
	(TOKEN_AUTH=OAUTH)
	(TOKEN_LOCATION="/home/dbuser1/access-token"))
	<pre>(CONNECT_DATA=(SERVICE_NAME=sales.us.example.c om)))</pre>
	In the sqlnet.ora file:
	SSL_SERVER_DN_MATCH=TRUE TOKEN AUTH=OAUTH
	TOKEN_LOCATION="/home/dbuser1/access-token"
	In these examples, the token file name is token. Thus, only the directory path (/home/dbuser1/access-token) is specified. The client automatically looks for the token file in the specified path and gets the access token.
	 If the token file name is different from token,
	TOKEN_AUTH=OAUTH, and TOKEN_LOCATION="token_file_directory/
	token_filename": In the thsnames.ora file:
	net_service_name= (DESCRIPTION=
	(ADDRESS=(PROTOCOL=tcps)
	(HOST=salesserver1)(PORT=1522))
	(SECURITY=
	(SSL_SERVER_DN_MATCH=TRUE)
	(SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleContext")
	(TOKEN_AUTH=OAUTH)
	(TOKEN_LOCATION="/home/dbuser1/



Table 5-3 (Cont.) Values and Examples for Entra ID

Value	Ennels	
Value	Example	
	<pre>access-token/mytoken"))</pre>	
	<pre>(CONNECT_DATA=(SERVICE_NAME=sales.us.example.c om)))</pre>	
	In the sqlnet.ora file:	
	SSL_SERVER_DN_MATCH=TRUE TOKEN_AUTH=OAUTH TOKEN_LOCATION="/home/dbuser1/access-token/ mytoken"	
	In these examples, the token file name is mytoken. Thus, both the file name and directory path (/home/dbuser1/access-token) are specified. The client gets the access token from the mytoken file in the specified path.	



Table 5-3 (Cont.) Values and Examples for Entra ID

```
Value
                               Example
                              In the tnsnames.ora file:
TOKEN_AUTH=AZURE_INTERACTIV
                               net_service_name=
                                   (DESCRIPTION =
                                       (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr)
                               (PORT=1521))
                                       (SECURITY=
                                          (SSL_SERVER_DN_MATCH=TRUE)
                               (SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleCont
                               ext")
                                          (TOKEN_AUTH=AZURE_INTERACTIVE)
                                          (AZURE_DB_APP_ID_URI=https://
                               application.example.com/123ab4cd-1a2b-1234-a12b-
                               aa00123b2cd3)
                                          (REDIRECT_URI=http://localhost:1575))
                               (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com)
                               In the sqlnet.ora file:
                               SSL SERVER DN MATCH=TRUE
                               TOKEN_AUTH=AZURE_INTERACTIVE
                               AZURE_DB_APP_ID_URI=https://
                               application.example.com/123ab4cd-1a2b-1234-a12b-
                               aa00123b2cd3
                               REDIRECT_URI=http://localhost:1575
                               In these examples, the CLIENT_ID and TENANT_ID parameters
                               are not specified. These parameters are optional for the JDBC-thin
                               and ODP.NET core and managed database clients, which can
                               automatically get these values from the Azure SDK configuration.
                               The thick clients (OCI and Instant Client) must specify these
                               parameters.
```



Table 5-3 (Cont.) Values and Examples for Entra ID

Value **Example** TOKEN_AUTH=AZURE_SERVICE_PR In the tnsnames.ora file: INCIPAL net_service_name= (DESCRIPTION = (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr) (PORT=1521)) (SECURITY= (SSL_SERVER_DN_MATCH=TRUE) (SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleCont ext") (TOKEN_AUTH=AZURE_SERVICE_PRINCIPAL) (AZURE_DB_APP_ID_URI=https:// application.example.com/123ab4cd-1a2b-1234-a12baa00123b2cd3)) (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com)) In the sqlnet.ora file: SSL_SERVER_DN_MATCH=TRUE TOKEN AUTH=AZURE SERVICE PRINCIPAL AZURE_DB_APP_ID_URI=https:// application.example.com/123ab4cd-1a2b-1234-a12baa00123b2cd3 In these examples, the CLIENT_ID, TENANT_ID, and CLIENT CERTIFICATE parameters are not specified. CLIENT ID and TENANT_ID are optional for the JDBC-thin and ODP.NET core and managed database clients, which can automatically get these values from the Azure SDK configuration. The thick clients (OCI and Instant Client) must specify these parameters.



Table 5-3 (Cont.) Values and Examples for Entra ID

Value **Example** TOKEN_AUTH=AZURE_MANAGED_ID In the tnsnames.ora file: net_service_name= (DESCRIPTION = (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr) (PORT=1521)) (SECURITY= (SSL_SERVER_DN_MATCH=TRUE) (SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleCont ext") (TOKEN_AUTH=AZURE_MANAGED_IDENTITY) (AZURE_DB_APP_ID_URI=https:// application.example.com/123ab4cd-1a2b-1234-a12baa00123b2cd3)) (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com)) In the sqlnet.ora file: SSL_SERVER_DN_MATCH=TRUE TOKEN AUTH=AZURE MANAGED IDENTITY AZURE_DB_APP_ID_URI=https:// application.example.com/123ab4cd-1a2b-1234-a12baa00123b2cd3 In these examples, the CLIENT_ID parameter is not specified. This parameter is optional for the JDBC-thin and ODP.NET core and managed database clients, which can automatically get this value from the Azure SDK configuration. The thick clients (OCI and Instant Client) must specify this parameter.



Table 5-3 (Cont.) Values and Examples for Entra ID

Value	Example	
TOKEN_AUTH=AZURE_DEVICE_COD E	In the tnsnames.ora file:	
	<pre>net_service_name= (DESCRIPTION = (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr) (PORT=1521)) (SECURITY= (SSL_SERVER_DN_MATCH=TRUE)</pre>	
	<pre>(SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleCont ext")</pre>	
	In the sqlnet.ora file:	
	SSL_SERVER_DN_MATCH=TRUE TOKEN_AUTH=AZURE_DEVICE_CODE AZURE_DB_APP_ID_URI=https:// application.example.com/123ab4cd-1a2b-1234-a12b-aa00123b2cd3	
	In these examples, the CLIENT_ID and TENANT_ID parameters are not specified. These parameters are optional for the JDBC-thin and ODP.NET core and managed database clients, which can automatically get these values from the Azure SDK configuration. The thick clients (OCI and Instant Client) must specify these parameters.	

Related Topics

- Authenticating and Authorizing IAM Users for Oracle DBaaS Databases
- Authenticating and Authorizing Microsoft Azure Users for Oracle Databases
- TOKEN LOCATION

Use the TOKEN_LOCATION parameter to specify the directory location where token file is stored for token-based authentication.

OCI CONFIG FILE

Use the <code>OCI_CONFIG_FILE</code> parameter to specify the directory location where the Oracle Cloud Infrastructure (OCI) configuration file is stored.

OCI PROFILE

Use the OCI_PROFILE parameter to specify the profile name for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) users.



OCI DATABASE

Use the OCI_DATABASE parameter to specify Oracle Cloud Identifier (OCID) of the database that you want to access for the client connection.

OCI COMPARTMENT

Use the OCI_COMPARTMENT parameter to specify Oracle Cloud Identifier (OCID) of the compartment that holds database instances for client connections.

AZURE DB APP ID URI

Use the AZURE_DB_APP_ID_URI parameter to specify the application ID URI of the Oracle Database instance, registered with Microsoft Entra ID (previously called Microsoft Azure Active Directory).

REDIRECT URI

Use the REDIRECT_URI parameter to specify the redirect URI, registered for your Microsoft Entra ID client application.

• CLIENT ID

Use the CLIENT_ID parameter to specify the ID of the database client Microsoft Entra ID app registration.

TENANT ID

Use the TENANT_ID parameter to specify the ID of your Microsoft Entra ID tenant.

CLIENT CERTIFICATE

Use the CLIENT_CERTIFICATE parameter to specify the file system path to a client certificate that authenticates your database client application.

5.2.121 TOKEN_LOCATION

Use the TOKEN_LOCATION parameter to specify the directory location where token file is stored for token-based authentication.

Purpose

To specify the token file directory location. You use this parameter while configuring token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) or Microsoft Azure users of Microsoft Entra ID. The database client gets the token from this location and sends it to the database server. For Entra ID, you can also specify the token file name along with the directory location.

Use this parameter along with the TOKEN_AUTH parameter in the tnsnames.ora file, sqlnet.ora file, or directly as part of the command-line connect string. The parameter values specified in the connect string take precedence over the other specified values.

Usage Notes for IAM

The TOKEN_LOCATION parameter is optional for IAM token-based authentication. You can use this parameter along with the TOKEN_AUTH parameter to override the default directory where the db-token and private key are stored. This location is used by the database client to retrieve the db-token and private key.

When an IAM user initiates a connection using <code>/@connect_identifier</code> (and <code>TOKEN_AUTH</code> is set to <code>OCI_TOKEN</code>), the database client retrieves the <code>db-token</code> and private key from either the default directory or the location specified by <code>TOKEN_LOCATION</code>. The client then signs the <code>db-token</code> using the private key and sends the <code>db-token</code> to the database server.

Default Setting for IAM

On Linux:



/home/username/.oci/db-token

On Windows:

The database client searches for the default directory in this order:

If the USERPROFILE environment variable is set, then the client searches in the USERPROFILE directory (for example, C:\Users\username).

If USERPROFILE is not set, then the client searches in HOMEDRIVE directory (for example, C:) with HOMEPATH (for example, \Users\username).

For example, the default token location directory on Windows is:

C:\Users\username\.oci\db-token

Values and Examples for IAM

Value	Example
TOKEN_LOCATION="token_file_directory"	In the tnsnames.ora file:
	<pre>net_service_name= (DESCRIPTION =</pre>
	(SECURITY=
	(SSL_SERVER_DN_MATCH=TRUE)
	<pre>(SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleContext")</pre>
	<pre>(CONNECT_DATA=(SERVICE_NAME=sales.us.example.com)))</pre>
	In the sqlnet.ora file:
	SSL_SERVER_DN_MATCH=TRUE TOKEN_AUTH=OCI_TOKEN TOKEN_LOCATION="/home/oracle/.oci/db-token"

Usage Notes for Entra ID

The TOKEN_LOCATION parameter is mandatory for Azure token-based authentication. You must use this parameter along with the TOKEN_AUTH parameter to specify the directory location where the Entra ID OAuth2 access token is stored. This location is used by the database client to get the access token.

If your token file is named token, then specify only the directory path. If the token file name is different from token, then you must use the file name along with the directory path.

When an Azure user initiates a connection using <code>/@connect_identifier</code>, the database client retrieves the access token from the location specified by <code>TOKEN_LOCATION</code> and sends the token to the database server.



Default Setting for Entra ID

None

Values and Examples for Entra ID

Value	Example
If the token file is named token:	In the tnsnames.ora file:
TOKEN_LOCATION="token_file_directory"	
	net_service_name=
	(DESCRIPTION=
	(ADDRESS=(PROTOCOL=tcps)(HOST=salesserver1)
	(PORT=1522))
	(SECURITY=
	(SSL_SERVER_DN_MATCH=TRUE)
	(SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleContext")
	(TOKEN_AUTH=OAUTH)(TOKEN_LOCATION="/home/
	dbuser1/access-token"))
	(CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))
)
	In the sqlnet.ora file:
	COL CEDVED DN MARCH EDVE
	SSL_SERVER_DN_MATCH=TRUE TOKEN AUTH=OAUTH
	TOKEN_AOTH-OAOTH TOKEN_LOCATION="/home/dbuser1/access-token"
	In these examples, the token file name is token. Thus, only the directory path (/home/dbuser1/access-token) is specified. The client automatically looks for the token file in the specified path and gets the access token.



Value	Example
If the token file name is different from token:	In the tnsnames.ora file:
TOKEN_LOCATION="token_file_directory/	
token_filename"	net_service_name=
	(DESCRIPTION=
	(ADDRESS=(PROTOCOL=tcps)(HOST=salesserver1)
	(PORT=1522))
	(SECURITY=
	(SSL_SERVER_DN_MATCH=ON)
	(SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleContext") (TOKEN_AUTH=OAUTH)
	(TOKEN_LOCATION="/home/dbuser1/access-token/
	<pre>mytoken"))</pre>
	<pre>(CONNECT_DATA=(SERVICE_NAME=sales.us.example.com)))</pre>
	In the sqlnet.ora file:
	SSL_SERVER_DN_MATCH=TRUE
	TOKEN AUTH=OAUTH
	TOKEN_LOCATION="/home/dbuser1/access-token/mytoken"
	In these examples, the token file name is mytoken. Thus, both the file name and directory path (/home/dbuser1/access-token) are specified. The client gets the access token from the mytoken file in the specified path.

Related Topics

- Authenticating and Authorizing IAM Users for Oracle DBaaS Databases
- Authenticating and Authorizing Microsoft Azure Users for Oracle Databases
- TOKEN AUTH

Use the TOKEN_AUTH parameter to configure token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) or Microsoft Azure users of Microsoft Entra ID (previously called Microsoft Azure Active Directory).

5.2.122 TLS_KEY_EXCHANGE_GROUPS

Use the TLS_KEY_EXCHANGE_GROUPS parameter to enable or disable post-quantum cryptographic (PQC) ML-KEM algorithms and classical ECDHE groups for TLS connections.

Purpose

To enable selection of classical or quantum-safe key exchange algorithms for TLS connections. You can set this parameter in the database server (sqlnet.ora), client (sqlnet.ora or tnsnames.ora connect string), or the listener (listener.ora).

Usage Notes

This parameter takes a combination of following values as a comma-separated list:



- ec: If the TLS_KEY_EXCHANGE_GROUPS value contains ec, the Oracle approved ECDHE groups secp256r1, secp384r1, secp521r1, and x25519 are enabled. This is similar to setting the deprecated parameter SSL_DISABLE_WEAK_EC_CURVES to TRUE.
- weak: If the parameter value contains weak, then all ECDHE groups are enabled including
 the weak groups that are disabled when the deprecated parameter
 SSL_DISABLE_WEAK_EC_CURVES is set to TRUE, as well as the Oracle approved ECDHE
 groups. Oracle does not recommend setting the value to weak.

① Note

Some groups from the Oracle approved ECDHE list may be moved to the weak groups list in the future, and such changes would be transparent.

• ml-kem: If the TLS_KEY_EXCHANGE_GROUPS value contains ml-kem, ML-KEM TLS groups are enabled.

(i) Note

- ML-KEM refers to the Module-Lattice-based Key Encapsulation Mechanism
 that allows secure exchange of cryptographic keys over insecure channels. It
 is a cryptographic protocol designed for quantum-safe key exchange and is
 part of the NIST Post-Quantum Cryptography (PQC) standardization process.
- ML-KEM is only valid with TLSv1.3, it does not apply to TLSv1.2.

ML-KEM negotiation can happen if both client and server support ML-KEM which is to say both client and server are DB26ai and:

- The server has TLS_KEY_EXCHANGE_GROUPS set to ml-kem and the client has the value set to ml-kem, ec or not have TLS_KEY_EXCHANGE_GROUPS set at all. In this case, the client uses ECDHE to send the key share in its initial handshake message. The server's list does not contain any key shares supported by the client. It finds the common group, which is ml-kem in this case, from the client's list and its own list and sends a retry request with its key share using ML-KEM. The client resends the key share, and the handshake proceeds with ml-kem as the negotiated group.
- The client sets TLS_KEY_EXCHANGE_GROUPS to ml-kem explicitly and the server has the value set to ec,ml-kem or ml-kem or not have TLS_KEY_EXCHANGE_GROUPS set at all. In this case, the client uses ml-kem to send the key share in its initial handshake message. The server supports this group and the handshake proceeds with ml-kem as the negotiated group.

Values

A comma-separated list of one or more of the values below:

- ec: To enable the Oracle approved ECDHE groups
- weak: To enable both the weak and Oracle approved ECDHE groups
- ml-kem: To enable the ML-KEM TLS groups

The following table shows the results of TLS negotiations based on TLS_KEY_EXCHANGE_GROUPS values from both the client and server.



Server-Side Value	Client-Side Value	Result
Not set	Not set	ECDHE
ec,ml-kem	ec,ml-kem	ECDHE
ec,ml-kem	ml-kem	ML-KEM
ml-kem	ec,ml-kem	ML-KEM
ml-kem	ml-kem	ML-KEM
ес	ec	ECDHE

ECDHE is given higher preference compared to ML-KEM. If TLS_KEY_EXCHANGE_GROUPS contains both ml-kem and ec, then ECDHE groups are given higher preference. The order in which the values are specified in TLS_KEY_EXCHANGE_GROUPS parameter does not matter.

Default

ec, weak, and ml-kem are enabled by default, in that order.

Examples

• In the tnsnames.ora file:

```
net_service_name=
  (DESCRIPTION=
        (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr)(PORT=1521))
        (SECURITY=(TLS_KEY_EXCHANGE_GROUPS=ml-kem,ec))
)
```

• In the sqlnet.ora file or the listener.ora file:

```
TLS_KEY_EXCHANGE_GROUPS=ml-kem,ec
```

Related Topics

SSL DISABLE WEAK EC CURVES

Use the SSL_DISABLE_WEAK_EC_CURVES parameter to disable the use of weak Elliptic Curve Cryptography (ECC) curves.

Oracle AI Database Security Guide

5.2.123 USE CMAN

Use the sqlnet.ora parameter USE_CMAN to specify client routing to Oracle Connection Manager.

Purpose

To specify client routing to Oracle Connection Manager.

Usage Notes

When set to true, the parameter routes the client to a protocol address for Oracle Connection Manager.



When set to false, the client picks one of the address lists at random and fails over to the other address list if the chosen ADDRESS_LIST fails. With USE_CMAN=true, the client always uses the first address list.

If no Oracle Connection Manager addresses are available, then connections are routed through any available listener address.

Default

false

Values

true | false

Example

USE_CMAN=true

5.2.124 USE_DEDICATED_SERVER

Use the sqlnet.ora parameter USE_DEDICATED_SERVER to append (SERVER=dedicated) to the CONNECT_DATA section of the connect descriptor that the client uses.

Purpose

To append (SERVER=dedicated) to the CONNECT_DATA section of the connect descriptor used by the client.

Usage Notes

The value for this parameter overrides the current value of the <u>SERVER</u> parameter in the tnsnames, or a file.

When set to on, the parameter <code>USE_DEDICATED_SERVER</code> automatically appends (<code>SERVER=dedicated</code>) to the connect data for a connect descriptor. This enables connections from this client use a dedicated server process, even if shared server is configured.

Default

off

Values

- on to append (SERVER=dedicated)
- off to send requests to existing server processes

Example

USE_DEDICATED_SERVER=on

Related Topics

Oracle Al Database Net Services Administrator's Guide



5.2.125 USE_SNI

Use the sqlnet.ora parameter USE_SNI to enable setting Server Name Indication (SNI) value using CONNECT_DATA parameters.

Purpose

To enable or disable setting of SNI value using CONNECT_DATA parameters for TLS connections.

Usage Notes

When USE_SNI is set and CONNECT_DATA in the connect string has any of the supported parameters for SNI, then those parameters are used to set the SNI value. This SNI value is then used by the listener to select the appropriate service handler for servicing the request without having to do a TLS handshake with the client. The supported CONNECT_DATA parameters for setting SNI include SERVICE_NAME, INSTANCE_NAME, SERVER and COLOCATION TAG.

When USE_SNI is set and CONNECT_DATA doesn't include any of the supported parameters listed above, then SNI value will not be set and the listener will perform the usual TLS handshake with the client to fetch the connect request.

Values

- ON | TRUE | YES to set SNI value using CONNECT DATA
- OFF | FALSE | NO to not set SNI value using CONNECT_DATA

Default Value

OFF

Example

USE_SNI=ON



Support for SNI is available in all versions starting 23.7, but not in earlier versions.

Related Topics

Oracle Al Database Net Services Administrator's Guide

5.2.126 WALLET_LOCATION

Use the WALLET_LOCATION parameter to specify the location of Oracle wallets.

Purpose

To specify the directory path where you want to create and store an Oracle wallet. Wallets securely contain certificates, secrets, private keys, and trust points used by Oracle Database.



Usage Notes

Deprecation of the server-side setting:

The parameter WALLET_LOCATION is deprecated for use with Oracle AI Database 26ai for the Oracle Database server. It is not deprecated for use with the Oracle Database client or listener.

For Oracle Database server, Oracle recommends that you use the WALLET_ROOT system parameter instead of using WALLET LOCATION.

Where to set this parameter:

You can set WALLET_LOCATION in the sqlnet.ora file to specify a common wallet location for all connections. You can also set it in the connect string or the the specify a different wallet location for a particular connection.

Use of WALLET_LOCATION in the connect string or thinnames.ora overrides the sqlnet.ora WALLET_LOCATION setting for the specific thinnames.ora service. The thinnames.ora WALLET_LOCATION setting enables a client to initiate multiple TLS sessions using different TLS certificates in the same client process.

Setting to use the system default certificate store instead of a client-side wallet:

The Linux and Windows database clients can use the system default certificate store to validate the Oracle Database server certificate, instead of creating a local wallet with root certificate. The default certificate store is located in /etc/pki/tls/cert.pem on Linux and Microsoft Certificate Store (MCS) on Windows.

If you set WALLET_LOCATION=SYSTEM in the connect string (in tnsnames.ora or directly to the command line), then the database client uses the default certificate store to validate the server certificate. In this case, the server certificate needs to be signed by a trusted root certificate that is already installed in the default certificate store.

For example:

```
net_service_name=
    (DESCRIPTION =
          (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr)(PORT=1234))
          (SECURITY=(WALLET_LOCATION=SYSTEM))
          (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))
          )
```

- Order in which the database client searches for a client wallet:
 - 1. The database client first tries to use a wallet from the WALLET_LOCATION directory specified in the connect string.
 - 2. If no wallet is present, then the client searches for the WALLET_LOCATION parameter value in the sqlnet.ora file.
 - 3. If no wallet is present, then the client searches for a wallet in the \$TNS_ADMIN environment variable directory.
 - 4. If no wallet is present, then the client searches in the default wallet location, that is, /etc/ORACLE/WALLETS/username on Linux and C:\Users\username\\ORACLE\WALLETS on Windows.
 - 5. If no wallet is present, then the client uses the wallet from the system default certificate store.



You can specify WALLET_LOCATION as SYSTEM in the connect string to ignore all the wallet configurations and use the system default certificate store instead.

Setting for walletless TLS connections:

The WALLET_LOCATION parameter is optional for TLS connections that do not use a client wallet. If you do not include WALLET_LOCATION in the connect string, tnsnames.ora, or sqlnet.ora, then the driver automatically picks up common root certificates from the system default certificate store (if the system is Windows or Linux).

However, you may need to perform additional steps in the following cases:

- If WALLET_LOCATION is set in sqlnet.ora for all connections, then you can override this setting for a specific connection that does not need a client wallet (using WALLET_LOCATION=SYSTEM in the connect string).
- If a wallet is present in the \$TNS_ADMIN environment variable directory, then the
 database client uses the \$TNS_ADMIN path as the default wallet location. In this case,
 you can either override the WALLET_LOCATION setting (using WALLET_LOCATION=SYSTEM
 in the connect string) or remove that wallet.
- Storage of wallet files:

The password-protected wallet is stored in an ewallet.p12 file. The auto-login and local auto-login wallets are stored in a cwallet.sso file.

For example, if an Oracle wallet is stored in the Microsoft Windows registry and the wallet's key (KEY) is SALESAPP, then the storage location of the password-protected wallet is HKEY_CURRENT_USER\SOFTWARE\ORACLE\WALLETS\SALESAPP\EWALLET.P12. The storage location of the auto-login and local auto-login wallets is HKEY_CURRENT_USER\SOFTWARE\ORACLE\WALLETS\SALESAPP\CWALLET.SSO.

Additional Parameters

Use SOURCE to specify the type of storage and storage location for wallets, as follows:

- METHOD: Type of storage
- METHOD_DATA: Storage location:
 - DIRECTORY: Location of wallet on the file system
 - KEY: Wallet type and location in the Microsoft Windows registry

Syntax and Examples

The syntax depends on the wallet as follows:

Wallet on the file system:

```
WALLET_LOCATION=
  (SOURCE=
     (METHOD=file)
     (METHOD_DATA=
           (DIRECTORY=directory)))
```

For example:

Microsoft certificate store:



```
WALLET_LOCATION=
  (SOURCE=
        (METHOD=mcs))
```

The key-value pair for MCS omits the METHOD_DATA parameter because MCS does not use wallets. Instead, Oracle PKI (public key infrastructure) applications obtain certificates, trust points and private keys directly from a user's profile.

Wallet in the Microsoft Windows registry:

Default

None

Related Topics

Oracle AI Database Security Guide

5.3 ADR Diagnostic Parameters in sqlnet.ora

Diagnostic data for critical errors is stored in the sqlnet.ora Automatic Diagnostic Repository (ADR).

About ADR Diagnostic Parameters

You can use Automatic Diagnostic Repository (ADR) diagnostic parameters when ADR is enabled, which is the default. Oracle ignores non-ADR parameters in the sqlnet.ora file when you enable ADR.

ADR BASE

Use the sqlnet.ora parameter ADR_BASE to specify the base location of the ADR files.

DIAG ADR ENABLED

Use the sqlnet.ora parameter DIAG_ADR_ENABLED to enable and disable ADR tracing.

ENABLE CONCISE LOGS

Use the sqlnet.ora parameter ENABLE_CONCISE_LOGS to enable or disable the logging in a concise format.

LOG SUPPRESSED COUNT

Use the sqlnet.ora parameter LOG_SUPPRESSED_COUNT to control the suppression of a log message based on the number of occurrences.

LOG SUPPRESSED TIME

Use the ${\tt sqlnet.ora}$ parameter ${\tt LOG_SUPPRESSED_TIME}$ to control the suppression of a log message based on the time interval.



TRACE LEVEL CLIENT

Use the sqlnet.ora parameter TRACE_LEVEL_CLIENT to enable and disable client tracing at a specific level.

• TRACE LEVEL SERVER

Use the sqlnet.ora parameter TRACE_LEVEL_SERVER to enable and disable server tracing at a specific level.

TRACE TIMESTAMP CLIENT

Use the sqlnet.ora parameter TRACE_TIMESTAMP_CLIENT to add time stamps to trace events in client trace files.

TRACE TIMESTAMP SERVER

Use the sqlnet.ora parameter TRACE_TIMESTAMP_CLIENT to add time stamps to trace events in database trace files.

5.3.1 About ADR Diagnostic Parameters

You can use Automatic Diagnostic Repository (ADR) diagnostic parameters when ADR is enabled, which is the default. Oracle ignores non-ADR parameters in the sqlnet.ora file when you enable ADR.

Since Oracle Database 11g, Oracle Database includes an advanced fault diagnostic infrastructure to prevent, detect, diagnose, and resolve problems. The problems might be critical errors such as those that are caused by database code bugs, metadata corruption, or customer data corruption.

When critical errors occur, they are assigned incident numbers. Diagnostic data for the errors, such as traces and dumps, are captured and tagged with the incident number. The data is then stored in ADR, which is a file-based repository outside the database.

The following sqlnet.ora parameters are used when you enable ADR (when DIAG_ADR_ENABLED is set to on):

5.3.2 ADR BASE

Use the sqlnet.ora parameter ADR BASE to specify the base location of the ADR files.

Purpose

To specify the base directory in which Oracle stores tracing and logging incidents when ADR is enabled.

Usage Notes

This parameter is applicable only to clients. On the server side, the ADR base location is defined by the <code>DIAGNOSTIC_DEST</code> initialization parameter in the <code>init.ora</code> file. See <code>DIAGNOSTIC</code> <code>DEST</code> in *Oracle Database Reference*.

Default

ORACLE_BASE or ORACLE_HOME/log (if ORACLE_BASE is not defined)

Values

Any valid directory path to a directory with write permission.



Example

ADR_BASE=/oracle/network/trace

5.3.3 DIAG_ADR_ENABLED

Use the sqlnet.ora parameter DIAG_ADR_ENABLED to enable and disable ADR tracing.

Purpose

To specify whether ADR tracing is enabled.

Usage Notes

If you set the DIAG_ADR_ENABLED parameter to OFF, then non-ADR file tracing is used.

Default

on

Values

on | off

Example 5-7 Example

DIAG_ADR_ENABLED=on

5.3.4 ENABLE_CONCISE_LOGS

Use the sqlnet.ora parameter ENABLE_CONCISE_LOGS to enable or disable the logging in a concise format.

Purpose

To control how you want to view error stack messages in Oracle Network logs (sqlnet.log files), either in a concise or long format.

Usage Notes

When set to TRUE, the logs are printed in a concise format. A concise format displays all the relevant information of a failure in a single line. This setting reduces the size of the log files and makes them easier to read.

When set to FALSE, the logs are printed in a longer, detailed format. A long format displays the messages in multiple lines, with additional details such as Version information.

Values

TRUE | FALSE

Default

TRUE



Example

ENABLE_CONCISE_LOGS=TRUE

Related Topics

Oracle AI Database Net Services Administrator's Guide

5.3.5 LOG SUPPRESSED COUNT

Use the sqlnet.ora parameter LOG_SUPPRESSED_COUNT to control the suppression of a log message based on the number of occurrences.

Purpose

To suppress an Oracle Network log message based on the specified number of occurrences on the database server.

You can suppress repeated or duplicate records so that they no longer appear in any log. This can save some disk space and allow ease of navigation through large amounts of data.



Note

You can set this parameter only on the database server side.

Usage Notes

- Both the sqlnet.ora parameters LOG_SUPPRESSED_COUNT and LOG_SUPPRESSED_TIME specify log suppression. These parameters are enabled by default, but you can override the default values.
 - LOG_SUPPRESSED_COUNT suppresses a duplicate message based on the number of occurrences. The default occurrence count is set to 50.
 - LOG SUPPRESSED TIME suppresses a duplicate message based on the time interval. The default time interval is set to 10 seconds.

Logging is suppressed when either of the conditions (occurrence count or time interval) is fulfilled.

Duplicate messages are initially printed until the number of occurrences exceeds the internal default threshold of repetition. This means that log suppression starts only after this threshold is hit until LOG SUPPRESSED COUNT times or LOG SUPPRESSED TIME seconds are exhausted.

For example, suppose LOG SUPPRESSED COUNT is set to 20 and LOG SUPPRESSED TIME is set to 4 seconds. When the message repeats 21 times in 3 seconds, logging is suppressed for that message based on the specified occurrence count of 20 times.

At each threshold (for example, after every 5 repetitions), a status message is logged, indicating the occurrence count and time after which logging will be suppressed:

Logging of network errors for PID: number will be turned off until log repeats LOG_SUPPRESSED_COUNT times or LOG_SUPPRESSED_TIME seconds are exhausted.



Value

Number of times (starting from the first occurrence) after which you want logging to be suppressed

Allowed Range

Any number greater than the minimum value of 1 up to 4294967295

Default

50

Example

LOG SUPPRESSED COUNT=100

Related Topics

LOG SUPPRESSED TIME

Use the sqlnet.ora parameter LOG_SUPPRESSED_TIME to control the suppression of a log message based on the time interval.

Oracle Al Database Net Services Administrator's Guide

5.3.6 LOG SUPPRESSED TIME

Use the sqlnet.ora parameter LOG SUPPRESSED TIME to control the suppression of a log message based on the time interval.

Purpose

To suppress an Oracle Network log message based on the specified time interval.

You can suppress repeated or duplicate records so that they no longer appear in any log. This can save some disk space and allow ease of navigation through large amounts of data.



(i) Note

You can set this parameter only on the database server side.

Usage Notes

- Both the sqlnet.ora parameters LOG_SUPPRESSED_COUNT and LOG_SUPPRESSED_TIME specify log suppression. These parameters are enabled by default, but you can override the default values.
 - LOG SUPPRESSED COUNT suppresses a duplicate message based on the number of occurrences. The default occurrence count is set to 50.
 - LOG_SUPPRESSED_TIME suppresses a duplicate message based on the time interval. The default time interval is set to 10 seconds.

Logging is suppressed when either of the conditions (occurrence count or time interval) is fulfilled.



Duplicate messages are initially printed until the number of occurrences exceeds the
internal default threshold of repetition. This means that log suppression starts only after
this threshold is hit until LOG_SUPPRESSED_COUNT times or LOG_SUPPRESSED_TIME seconds
are exhausted.

For example, suppose LOG_SUPPRESSED_COUNT is set to 20 and LOG_SUPPRESSED_TIME is set to 4 seconds. When the message repeats 15 times in 5 seconds, logging is suppressed for that message based on the specified time interval of 4 seconds.

At each threshold (for example, after every 5 repetitions), a status message is logged, indicating the occurrence count and time after which logging will be suppressed:

Logging of network errors for PID: number will be turned off until log repeats LOG_SUPPRESSED_COUNT times or LOG_SUPPRESSED_TIME seconds are exhausted.

Value

Time interval in seconds (starting from the first occurrence) after which you want logging to be suppressed

Allowed Range

Any number greater than the minimum value of 1 up to 4294967295

Default

10

Example

LOG_SUPPRESSED_TIME=20

Related Topics

LOG SUPPRESSED COUNT

Use the sqlnet.ora parameter $log_SUPPRESSED_COUNT$ to control the suppression of a log message based on the number of occurrences.

Oracle Al Database Net Services Administrator's Guide

5.3.7 TRACE_LEVEL_CLIENT

Use the sqlnet.ora parameter TRACE_LEVEL_CLIENT to enable and disable client tracing at a specific level.

Purpose

To enable client tracing at a specified level or to disable it.

Usage Notes

This parameter is also applicable when non-ADR tracing is used.

Default

off or 0

Values

off or 0 for no trace output



- user or 4 for user trace information
- admin or 10 for administration trace information
- support or 16 for Oracle Support Services trace information

Example

TRACE_LEVEL_CLIENT=user

5.3.8 TRACE_LEVEL_SERVER

Use the sqlnet.ora parameter TRACE_LEVEL_SERVER to enable and disable server tracing at a specific level.

Purpose

To turn server tracing on at a specified level or to turn it off.

Usage Notes

This parameter is also applicable when non-ADR tracing is used.

Default

off or 0

Values

- off or 0 for no trace output
- user or 4 for user trace information
- admin or 10 for administration trace information
- support or 16 for Oracle Support Services trace information

Example

TRACE_LEVEL_SERVER=admin

5.3.9 TRACE_TIMESTAMP_CLIENT

Use the sqlnet.ora parameter TRACE_TIMESTAMP_CLIENT to add time stamps to trace events in client trace files.

Purpose

To add a time stamp in the form of dd-mmm-yyyy hh:mm:ss:mil to every trace event in the client trace file, which has a default name of sqlnet.trc.

Usage Notes

This parameter is also applicable when non-ADR tracing is used.

Default

on



Values

on **or** true | off **or** false

Example

TRACE_TIMESTAMP_CLIENT=true

5.3.10 TRACE_TIMESTAMP_SERVER

Use the sqlnet.ora parameter TRACE_TIMESTAMP_CLIENT to add time stamps to trace events in database trace files.

Purpose

To add a time stamp in the form of dd-mmm-yyyy hh:mm:ss:mil to every trace event in the database server trace file, which has a default name of svr_pid.trc.

Usage Notes

This parameter is also applicable when non-ADR tracing is used.

Default

on

Values

on **or** true | off **or** false

Example

TRACE_TIMESTAMP_SERVER=true

5.4 Non-ADR Diagnostic Parameters in sqlnet.ora Files

Learn about sqlnet.ora parameters that you use when you disable ADR.

This section lists the sqlnet.ora parameters that are used when you disable ADR.



The default value of <code>DIAG_ADR_ENABLED</code> is on. Therefore, the <code>DIAG_ADR_ENABLED</code> parameter must explicitly be set to off to use non-ADR tracing.

LOG DIRECTORY CLIENT

Use the sqlnet.ora non-ADR diagnostic parameter $log_DIRECTORY_CLIENT$ to specify the destination directory for client log files.

LOG DIRECTORY SERVER

Use the non-ADR diagnostic sqlnet.ora parameter LOG_DIRECTORY_SERVER to specify the destination directory for database log files.



LOG FILE CLIENT

Use the non-ADR diagnostic sqlnet.ora parameter LOG_FILE_CLIENT to specify the name of log files for clients.

• LOG FILE SERVER

Use the non-ADR diagnostic sqlnet.ora parameter LOG_FILE_SERVER to specify log file names for the database.

TRACE DIRECTORY CLIENT

Use the non-ADR diagnostic sqlnet.ora parameter TRACE_DIRECTORY_CLIENT to specify the destination directory for client trace files.

TRACE DIRECTORY SERVER

Use the non-ADR diagnostic sqlnet.ora parameter TRACE_DIRECTORY_SERVER to specify the destination directory for database trace files.

• TRACE FILE CLIENT

Use the non-ADR diagnostic sqlnet.ora parameter TRACE_FILE_CLIENT to specify the names of client trace files.

TRACE FILE SERVER

Use the non-ADR diagnostic sqlnet.ora parameter TRACE_FILE_SERVER to specify the destination directory for database trace output.

TRACE FILEAGE CLIENT

Use the non-ADR diagnostic sqlnet.ora parameter TRACE_FILEAGE_CLIENT to specify the maximum age of client trace files in minutes.

TRACE FILEAGE SERVER

Use the non-ADR diagnostic sqlnet.ora parameter TRACE_FILEAGE_SERVER to specify the maximum age of database trace files in minutes.

TRACE FILELEN CLIENT

Use the non-ADR diagnostic sqlnet.ora parameter TRACE_FILELEN_CLIENT to specify the size of client trace files in kilobytes.

TRACE FILELEN SERVER

Use the non-ADR diagnostic sqlnet.ora parameter TRACE_FILELEN_SERVER to specify the size of database trace files in kilobytes.

TRACE FILENO CLIENT

Use the non-ADR diagnostic sqlnet.ora parameter TRACE_FILENO_CLIENT to specify the number of trace files for client tracing.

• TRACE FILENO SERVER

Use the non-ADR diagnostic sqlnet.ora parameter TRACE_FILENO_SERVER to specify the number of trace files for database tracing.

TRACE UNIQUE CLIENT

Use the non-ADR diagnostic sqlnet.ora parameter TRACE_UNIQUE_CLIENT to specify whether Oracle creates a unique trace file for each client trace session.

5.4.1 LOG_DIRECTORY_CLIENT

Use the sqlnet.ora non-ADR diagnostic parameter LOG_DIRECTORY_CLIENT to specify the destination directory for client log files.

Purpose

To specify the destination directory for the client log file. By default, the log file is created in the current working directory.



Usage Notes

Use this parameter when ADR is not enabled.

Values

Any valid directory path.

Example

LOG_DIRECTORY_CLIENT=/oracle/network/log

5.4.2 LOG_DIRECTORY_SERVER

Use the non-ADR diagnostic sqlnet.ora parameter LOG_DIRECTORY_SERVER to specify the destination directory for database log files.

Purpose

To specify the destination directory for database log files.

Usage Notes

Use this parameter when ADR is not enabled.

Default

ORACLE_HOME/network/trace

Values

Any valid directory path to a directory with write permission.

Example

LOG_DIRECTORY_SERVER=/oracle/network/trace

5.4.3 LOG_FILE_CLIENT

Use the non-ADR diagnostic sqlnet.ora parameter LOG_FILE_CLIENT to specify the name of log files for clients.

Purpose

To specify the name of the log file for the client.

Usage Notes

Use this parameter when ADR is not enabled.

Default

ORACLE_HOME/network/log/sqlnet.log

Values

The default value cannot be changed.



5.4.4 LOG_FILE_SERVER

Use the non-ADR diagnostic sqlnet.ora parameter LOG_FILE_SERVER to specify log file names for the database.

Purpose

To specify the name of the log file for the database.

Usage Notes

Use this parameter when ADR is not enabled.

Default

sqlnet.log

Values

Example

LOG_FILE_SERVER=svr.log

5.4.5 TRACE_DIRECTORY_CLIENT

Use the non-ADR diagnostic sqlnet.ora parameter TRACE_DIRECTORY_CLIENT to specify the destination directory for client trace files.

Purpose

To specify the destination directory for the client trace file. By default, the trace file is created in the current working directory.

Usage Notes

Use this parameter when ADR is not enabled.

Values

Any valid directory path to a directory with write permission.

Example

TRACE_DIRECTORY_CLIENT=/oracle/traces

5.4.6 TRACE_DIRECTORY_SERVER

Use the non-ADR diagnostic sqlnet.ora parameter TRACE_DIRECTORY_SERVER to specify the destination directory for database trace files.

Purpose

To specify the destination directory for the database server trace file. Use this parameter when ADR is not enabled.



Default

ORACLE_HOME/network/trace

Values

Any valid directory path to a directory with write permission.

Example

TRACE_DIRECTORY_SERVER=/oracle/traces

5.4.7 TRACE_FILE_CLIENT

Use the non-ADR diagnostic sqlnet.ora parameter TRACE_FILE_CLIENT to specify the names of client trace files.

Purpose

To specify the name of a client trace file.

Usage Notes

Use this parameter when ADR is not enabled.

Default

ORACLE_HOME/network/trace/cli.trc

Values

Any valid file name.

Example

 ${\tt TRACE_FILE_CLIENT=clientsqlnet.trc}$

5.4.8 TRACE_FILE_SERVER

Use the non-ADR diagnostic sqlnet.ora parameter TRACE_FILE_SERVER to specify the destination directory for database trace output.

Purpose

To specify the destination directory for the database server trace output.

Usage Notes

Use this parameter when ADR is not enabled.

Default

ORACLE_HOME/network/trace/svr_pid.trc

Values

Any valid file name. The process identifier (pid) is appended to the name automatically.



Example

TRACE_FILE_SERVER=svrsqlnet.trc

5.4.9 TRACE_FILEAGE_CLIENT

Use the non-ADR diagnostic sqlnet.ora parameter TRACE_FILEAGE_CLIENT to specify the maximum age of client trace files in minutes.

Purpose

To specify the maximum age of client trace files in minutes.

Usage Notes

When the age limit is reached, the trace information is written to the next file. The number of files is specified with the <u>TRACE_FILENO_CLIENT</u> parameter. Use this parameter when ADR is not enabled.

Default

Unlimited

This is the same as setting the parameter to 0.

Example 5-8 Example

TRACE_FILEAGE_CLIENT=60

5.4.10 TRACE FILEAGE SERVER

Use the non-ADR diagnostic sqlnet.ora parameter TRACE_FILEAGE_SERVER to specify the maximum age of database trace files in minutes.

Purpose

To specify the maximum age of database server trace files in minutes.

Usage Notes

When the age limit is reached, the trace information is written to the next file. The number of files is specified with the <u>TRACE_FILENO_SERVER</u> parameter. Use this parameter when ADR is not enabled.

Default

Unlimited

This is the same as setting the parameter too.

Example 5-9 Example

TRACE_FILEAGE_SERVER=60



5.4.11 TRACE_FILELEN_CLIENT

Use the non-ADR diagnostic sqlnet.ora parameter TRACE_FILELEN_CLIENT to specify the size of client trace files in kilobytes.

Purpose

When the file grows to the specified size, Oracle writes the trace information to the next file. The number of files is specified with the TRACE_FILENO_CLIENT parameter. Use this parameter when ADR is not enabled.

To specify the size of the client trace files in kilobytes (KB).

Usage Notes

Example

TRACE_FILELEN_CLIENT=100

5.4.12 TRACE_FILELEN_SERVER

Use the non-ADR diagnostic sqlnet.ora parameter TRACE_FILELEN_SERVER to specify the size of database trace files in kilobytes.

Purpose

To specify the size of the database server trace files in kilobytes (KB).

Usage Notes

When the file grows to the specified size, Oracle writes the trace information to the next file. The number of files is specified with the <u>TRACE_FILENO_SERVER</u> parameter. Use this parameter when ADR is not enabled.

Example

TRACE_FILELEN_SERVER=100

5.4.13 TRACE FILENO CLIENT

Use the non-ADR diagnostic sqlnet.ora parameter TRACE_FILENO_CLIENT to specify the number of trace files for client tracing.

Purpose

To specify the number of trace files for client tracing.

Usage Notes

When this parameter is set with the <u>TRACE_FILELEN_CLIENT</u> parameter, trace files are used in a cyclical fashion. The first file is filled first, then the second file, and so on. When the last file has been filled, then the first file is re-used, and so on.

When this parameter is set with the <u>TRACE_FILEAGE_CLIENT</u> parameter, trace files are cycled based on their age. The first file is used until the age limit is reached, then the second file is used, and so on. When the last file's age limit is reached, the first file is re-used.



When you set this parameter with both the TRACE_FILELEN_CLIENT and TRACE_FILEAGE_CLIENT parameters, trace files are replaced when either the size limit or the age limit is reached.

The trace file names are distinguished from one another by their sequence numbers. For example, if the default trace file of sqlnet.trc is used, and this parameter is set to 3, then the trace files would be named sqlnet1.trc, sqlnet2.trc and sqlnet3.trc.

In addition, trace events in the trace files are preceded by the sequence number of the file. Use this parameter when ADR is not enabled.

Default

None

Example

TRACE_FILENO_CLIENT=3

5.4.14 TRACE_FILENO_SERVER

Use the non-ADR diagnostic sqlnet.ora parameter TRACE_FILENO_SERVER to specify the number of trace files for database tracing.

Purpose

To specify the number of trace files for database server tracing.

Usage Notes

When you set this parameter with the <u>TRACE_FILELEN_SERVER</u> parameter, trace files are used in a cyclical fashion. The first file is filled first, then the second file, and so on. When the last file has been filled, then the first file is re-used.

When you set this parameter with the <u>TRACE_FILEAGE_SERVER</u> parameter, trace files are cycled based on the age of the trace file. The first file is used until the age limit is reached, then the second file is used, and so on. When the last file's age limit is reached, the first file is reused.

When this parameter is set with both the TRACE_FILELEN_SERVER and TRACE_FILEAGE_SERVER parameters, trace files are cycled when either the size limit or the age limit is reached.

The trace file names are distinguished from one another by their sequence numbers. For example, if the default trace file of svr_pid.trc is used, and this parameter is set to 3, then the trace files would be named svr1_pid.trc, svr2_pid.trc and svr3_pid.trc.

In addition, trace events in the trace files are preceded by the sequence number of the file. Use this parameter when ADR is not enabled.

Default

None

Example

TRACE_FILENO_SERVER=3



5.4.15 TRACE_UNIQUE_CLIENT

Use the non-ADR diagnostic sqlnet.ora parameter TRACE_UNIQUE_CLIENT to specify whether Oracle creates a unique trace file for each client trace session.

Purpose

To specify whether a unique trace file is created for each client trace session.

Usage Notes

When you set the value to on, a process identifier is appended to the name of each trace file, enabling several files to coexist. For example, trace files named sqlnetpid.trc are created if default trace file name sqlnet.trc is used. When you set the value to off, data from a new client trace session overwrites the existing file. Use this parameter when ADR is not enabled.

Default

on

Values

on or off

Example

TRACE_UNIQUE_CLIENT=on

Local Naming Parameters in the tnsnames.ora File

Learn about the Oracle Net service names local naming parameters that you specify in the tnsnames.ora configuration file.

Overview of Local Naming Parameters

The tnsnames.ora file is a configuration file that contains network service names that are mapped to connect descriptors for the Local Naming method.

General Syntax of tnsnames.ora

In this example, you can see the general tnsnames.ora file syntax.

Using Multiple Descriptions in tnsnames.ora Files

In this example, you can see two connect descriptors with multiple addresses.

Multiple Address Lists in tnsnames.ora Files

The tnsnames.ora file supports connect descriptors with multiple lists of addresses, each with its own characteristics. Learn how to configure multiple address lists in tnsnames.ora files.

Connect-Time Failover and Client Load Balancing with Oracle Connection Managers

When tnsnames.ora connect descriptors have at least two protocol addresses for Oracle Connection Manager, you can also include parameters for connect-time failover and load balancing in the file.

Connect Descriptor Descriptions

Specify connect descriptors using the DESCRIPTION parameter. Identify multiple connect descriptors with the DESCRIPTION LIST parameter.

Protocol Addresses

The protocol address section of a tnsnames.ora file specifies listener protocol addresses.

Optional Parameters for Description

Use these parameters to configure connect descriptor containers under the DESCRIPTION parameter.

Connection Data Section

Learn how to configure network connections with protocol addresses.

Security Section

The security section of the tnsnames.ora file specifies these security-related parameters for use with Oracle security features.

Timeout Parameters

The timeout section of the tnsnames.ora file provides the ability to specify timeout and retry configuration through the TNS connect string.

Compression Parameters

The compression section of the tnsnames.ora file provides the ability to enable compression and specify compression levels. These parameters can be set at the DESCRIPTION level of a connect string.



6.1 Overview of Local Naming Parameters

The tnsnames.ora file is a configuration file that contains network service names that are mapped to connect descriptors for the Local Naming method.

A net service name is an alias that is mapped to a database network address that is contained in a connect descriptor. A connect descriptor contains the location of the listener that is accessed through a protocol address and the service name of the database to which to connect. Clients and database servers that are clients of other database servers use the net service name when connecting with applications.

Typically, tools such as Oracle Database Configuration Assistant (DBCA) and Oracle Net Configuration Assistant (NETCA) create the tnsnames.ora file in the <code>ORACLE_HOME/network/admin</code> directory for Oracle Database installations, the <code>GRID_HOME/network/admin</code> directory for Oracle Grid Infrastructure installations, or the corresponding <code>ORACLE_BASE_HOME/network/admin</code> directory for a read-only Oracle home. Note that if you have installed multiple databases, then the file is created in the Oracle home or Grid home where DBCA or NETCA is run (or the Oracle base home for read-only instances).

The order for checking the tnsnames.ora file is:

- 1. The directory specified by the TNS ADMIN environment variable
- 2. If the TNS_ADMIN environment variable is not set or the file is not found in the TNS_ADMIN directory:
 - On Linux and UNIX: The ORACLE_HOME/network/admin directory (or its ORACLE_BASE_HOME/network/admin directory for a read-only Oracle home)
 - On Windows: The ORACLE_HOME\network\admin directory (or its ORACLE_BASE_HOME\network\admin directory for a read-only Oracle home)
- **3.** For a read-only Oracle home, if the file is not found in the Oracle base home:
 - On Linux and UNIX: The ORACLE HOME/network/admin directory
 - On Windows: The ORACLE_HOME\network\admin directory

(i) Note

- On Windows, the ORACLE_HOME location is determined by the ORACLE_HOME\bin\oracle.key file (which contains the name of the Windows Registry key where ORACLE_HOME is defined). Also, the TNS_ADMIN environment variable is used if it is set in the environment of the process. If you do not define the TNS_ADMIN environment variable in the environment or if the process is a service that does not have an environment, then Windows scans the registry for a TNS_ADMIN parameter.
- With Oracle Instant Client, tnsnames.ora is located in the subdirectory of the Oracle Instant Client software. For example, in the <code>/opt/oracle/instantclient</code> <code>release number/network/admin directory.</code>

Related Topics

Oracle Al Database Net Services Administrator's Guide



6.2 General Syntax of thsnames.ora

In this example, you can see the general tnsnames.ora file syntax.

Here, DESCRIPTION contains the connect descriptor, ADDRESS contains the protocol address, and CONNECT DATA contains database service identification information.

Example 6-1 Basic Format of thsnames.ora File

```
net_service_name=
  (DESCRIPTION=
      (ADDRESS=(protocol_address_information))
      (CONNECT_DATA=
            (SERVICE_NAME=service_name)
      )
}
```

6.3 Using Multiple Descriptions in tnsnames.ora Files

In this example, you can see two connect descriptors with multiple addresses.

A tnsnames.ora file can contain net service names with one or more connect descriptors. Each connect descriptor can contain one or more protocol addresses.

Use the thsnames.ora parameter DESCRIPTION_LIST to define the list of connect descriptors.

Example 6-2 Net Service Name with Multiple Connect Descriptors in tnsnames.ora

(i) Note

Oracle Net Manager does not support multiple connect descriptors for a net service name if you use Oracle Connection Manager.

6.4 Multiple Address Lists in tnsnames.ora Files

The tnsnames.ora file supports connect descriptors with multiple lists of addresses, each with its own characteristics. Learn how to configure multiple address lists in tnsnames.ora files.

The following example shows two address lists. The first address list features client load balancing and no connect-time failover. These setting apply only to protocol addresses that are



within its ADDRESS_LIST. The second protocol address list does not enable client load loading balancing, but the list does enable connect-time failover. These settings affect only protocol addresses that are included in its ADDRESS_LIST. The client first tries the first or second protocol address at random, then it tries protocol addresses number three and four, in that order, and so on.

Example 6-3 Multiple Address Lists in tnsnames.ora Files

```
net_service_name=
  (DESCRIPTION=
    (ADDRESS_LIST=
        (LOAD_BALANCE=on)
        (FAILOVER=off)
        (ADDRESS=(protocol_address_information))
        (ADDRESS=(protocol_address_information)))
        (ADDRESS_LIST=
            (LOAD_BALANCE=off)
            (FAILOVER=on)
            (ADDRESS=(protocol_address_information))
            (ADDRESS=(protocol_address_information))
            (CONNECT_DATA=
            (SERVICE_NAME=service_name)))
```

(i) Note

- Oracle Net Manager supports only the creation of one protocol address list for a connect descriptor.
- Oracle Net Services supports the IFILE parameter in the tnsnames.ora file, with
 up to three levels of nesting. You must add the parameter manually to the file. The
 following is an example of the syntax:

```
IFILE=/tmp/listener_em.ora
IFILE=/tmp/listener_cust1.ora
IFILE=/tmp/listener_cust2.ora
```

6.5 Connect-Time Failover and Client Load Balancing with Oracle Connection Managers

When tnsnames.ora connect descriptors have at least two protocol addresses for Oracle Connection Manager, you can also include parameters for connect-time failover and load balancing in the file.

Example 6-4 Multiple Oracle Connection Manager Addresses in tnsnames.ora

This example illustrates the failover of multiple Oracle Connection Manager protocol addresses.



```
(LOAD_BALANCE=off) # 2
  (ADDRESS=(PROTOCOL=tcp)(HOST=host2a)(PORT=1630))
  (ADDRESS=(PROTOCOL=tcp)(HOST=host2b)(PORT=1630)))
  (ADDRESS=(PROTOCOL=tcp)(HOST=host3)(PORT=1521))) # 3
(CONNECT_DATA=(SERVICE_NAME=sales.us.example.com)))
```

The previous syntax does the following:

 The client connects to the protocol address of the first Oracle Connection Manager as indicated by:

```
(ADDRESS=(PROTOCOL=tcp)(HOST=host1)(PORT=1630))
```

2. Oracle Connection Manager connects to the first protocol address of another Oracle Connection Manager. If the first protocol address fails, then it tries to connect to the second protocol address. This sequence is specified with the following configuration:

```
(ADDRESS_LIST=
  (FAILOVER=on)
  (LOAD_BALANCE=off)
  (ADDRESS=(PROTOCOL=tcp)(HOST=host2a)(PORT=1630))
  (ADDRESS=(PROTOCOL=tcp)(HOST=host2b)(PORT=1630)))
```

Oracle Connection Manager connects to the database service using the following protocol address:

```
(ADDRESS=(PROTOCOL=tcp)(HOST=host3)(PORT=1521))
```

Example 6-5 Client Load Balancing in thsnames.ora

This example illustrates client load balancing among two Oracle Connection Managers and two protocol addresses:

```
sample2=
(DESCRIPTION=
  (LOAD_BALANCE=on) # 1
  (FAILOVER=on)
  (ADDRESS_LIST=
      (SOURCE_ROUTE=yes)
      (ADDRESS=(PROTOCOL=tcp)(HOST=host1)(PORT=1630)) # 2
      (ADDRESS=(PROTOCOL=tcp)(HOST=host2)(PORT=1521)))
(ADDRESS_LIST=
      (SOURCE_ROUTE=yes)
      (ADDRESS=(PROTOCOL=tcp)(HOST=host3)(port=1630))
      (ADDRESS=(PROTOCOL=tcp)(HOST=host4)(port=1521)))
      (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))) # 3
```

The previous syntax does the following:

- The client selects an ADDRESS_LIST at random and fails over to the other address if the chosen ADDRESS_LIST fails. This is indicated if you set the LOAD_BALANCE and FAILOVER parameters to on.
- When an ADDRESS_LIST is chosen, the client first connects to Oracle Connection Manager using the Oracle Connection Manager protocol address that uses port 1630 as is indicated for the ADDRESS_LIST.



Oracle Connection Manager then connects to the database service using the protocol address that is indicated for the ADDRESS LIST.

6.6 Connect Descriptor Descriptions

Specify connect descriptors using the DESCRIPTION parameter. Identify multiple connect descriptors with the DESCRIPTION_LIST parameter.

DESCRIPTION LIST

The DESCRIPTION_LIST parameter of the thin the thin the defines a list of connect descriptors for a particular net service name.

DESCRIPTION

Use the tnsnames.ora file DESCRIPTION parameter to specify connect descriptor containers.

6.6.1 DESCRIPTION_LIST

The DESCRIPTION_LIST parameter of the tnsnames.ora file defines a list of connect descriptors for a particular net service name.

Purpose

To define a list of connect descriptors for a particular net service name.

Example 6-6 Example

```
net_service_name=
(DESCRIPTION_LIST=
  (DESCRIPTION=
    (ADDRESS=...)
    (CONNECT_DATA=(SERVICE_NAME=sales.example.com)))
(DESCRIPTION=
```

6.6.2 DESCRIPTION

Use the thsnames.ora file DESCRIPTION parameter to specify connect descriptor containers.

Purpose

To specify a container for a connect descriptor.

Usage Notes

When using more than one DESCRIPTION parameter, place the parameters under the DESCRIPTION_LIST parameter.

Example 6-7 DESCRIPTION Parameter Example

```
net_service_name=
(DESCRIPTION=
   (ADDRESS=...)
   (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com)))
```



6.7 Protocol Addresses

The protocol address section of a tnsnames.ora file specifies listener protocol addresses.

If there is only one listener protocol address, then use the ADDRESS parameter. If there is more than one address, then use the ADDRESS LIST parameter.

ADDRESS

The tnsnames.ora parameter ADDRESS specifies protocol addresses with the ADDRESS_LIST for multiple addresses or with the DESCRIPTION parameter for one listener.

HTTPS PROXY

Learn to use the tnsnames.ora parameter HTTPS_PROXY to specify HTTP proxy host names to tunnel Transport Layer Security (TLS) client connections.

HTTPS PROXY PORT

Learn how to use the tnsnames.ora parameter HTTPS_PROXY_PORT to specify forward HTTP proxy host ports for tunneling Transport Layer Security (TLS) client connections.

ADDRESS LIST

The ADDRESS_LIST networking parameter specifies the number of protocol addresses.

6.7.1 ADDRESS

The thishames.ora parameter ADDRESS specifies protocol addresses with the ADDRESS_LIST for multiple addresses or with the DESCRIPTION parameter for one listener.

Purpose

To specify one listener protocol address.

Usage Notes

Put this parameter under either the ADDRESS LIST parameter or the DESCRIPTION parameter.

ADDRESS Parameter Example

```
net_service_name=
(DESCRIPTION=
   (ADDRESS=(PROTOCOL=tcp)(HOST=sales-svr)(PORT=1521))
(CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))
```

6.7.2 HTTPS_PROXY

Learn to use the tnsnames.ora parameter HTTPS_PROXY to specify HTTP proxy host names to tunnel Transport Layer Security (TLS) client connections.

Purpose

To specify HTTP proxy host names for tunneling your TLS client connections.

Usage Notes

Your clients can tunnel secure connections over HTTP proxy using the HTTP CONNECT method. This helps access the public cloud database service because it eliminates the need to open an outbound port on a client-side firewall. This parameter is applicable only to the connect



descriptors where PROTOCOL=TCPS. This is similar to the web browser setting for intranet users who want to connect to internet hosts. You can increase the forward web proxy read timeout for requests to a higher value depending on client queries. Otherwise, the forward web proxy closes the connection assuming that no requests are made from the client.

A successful connection depends on your specific proxy configurations. The performance of your data transfers depend on the proxy capacity. Oracle recommends against using this feature in production environments where performance is critical.

Configuring tnsnames.ora for an HTTP proxy may not be secure enough, depending your organization's network configuration and security policies. For example, some networks require a user name and password for the HTTP proxy.

Oracle Client versions earlier than 18c does not support connections through HTTP proxy.

Contact your network administrator to open outbound connections to hosts that are in the oraclecloud.com domain by using the relevant port, without going through an HTTP proxy. For example, port 1522.

Default

None

Values

An HTTP proxy host name that can make an outbound connection to internet hosts.

Example

HTTPS_PROXY=www-proxy.example.com

6.7.3 HTTPS PROXY PORT

Learn how to use the tnsnames.ora parameter HTTPS_PROXY_PORT to specify forward HTTP proxy host ports for tunneling Transport Layer Security (TLS) client connections.

Purpose

To specify forward HTTP proxy host port for tunneling TLS client connections.

Usage Notes

It forwards the HTTP proxy host port that receives the HTTP CONNECT method. Use this parameter with https_proxy_port. The value for the https_proxy_port parameter takes effect only when you set SQLNET.USE_HTTPS_proxy=1 set in your sqlnet.ora file.

Default

none

Values

port number

Example

HTTPS_PROXY_PORT=80



6.7.4 ADDRESS_LIST

The ADDRESS_LIST networking parameter specifies the number of protocol addresses.

Purpose

To define a list of protocol addresses.

Usage Notes

If there is only one listener protocol address, then ADDRESS_LIST is not necessary.

Put this parameter either under the DESCRIPTION parameter or the DESCRIPTION_LIST parameter.

Example

```
net_service_name=
  (DESCRIPTION=
    (ADDRESS_LIST=
        (ADDRESS=(PROTOCOL=tcp)(HOST=sales1-svr)(PORT=1521))
        (ADDRESS=(PROTOCOL=tcp)(HOST=sales2-svr)(PORT=1521)))
        (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com)))
```

6.8 Optional Parameters for Description

Use these parameters to configure connect descriptor containers under the DESCRIPTION parameter.

ENABLE

Use the ${\tt ENABLE}$ parameter to enable the keepalive feature on the supported TCP transports.

EXPIRE_TIME

Use the EXPIRE_TIME parameter to specify how often, in minutes, to verify that the remote server connection is alive.

FAILOVER

Use the FAILOVER parameter to enable or disable connect-time failover for multiple protocol addresses.

LOAD BALANCE

Use the LOAD_BALANCE parameter to enable or disable client load balancing for multiple protocol addresses.

RECV BUF SIZE

Use the RECV_BUF_SIZE parameter to specify buffer space for session receive operations.

SDU

Use the SDU parameter to configure the session data unit (SDU) size.

SEND BUF SIZE

Use the SEND_BUF_SIZE parameter to specify buffer space for session send operations.

SOURCE ROUTE

Use the SOURCE_ROUTE parameter to enable routing through multiple protocol addresses.



TYPE OF SERVICE

Use the ${\tt TYPE_OF_SERVICE}$ parameter to specify the type of service to use for an Oracle Rdb database.

USE SNI

Use the USE_SNI parameter to set Server Name Indication (SNI) value using CONNECT_DATA parameters for TLS connections.

6.8.1 ENABLE

Use the ENABLE parameter to enable the keepalive feature on the supported TCP transports.

Purpose

To allow the caller to detect a terminated remote server; typically it takes 2 hours or more to notice.

Usage Notes

The keepalive feature on the supported TCP transports can be enabled for a net service client by putting (ENABLE=broken) under the DESCRIPTION parameter in the connect string. On the client side, the default for tcp_keepalive is off. Operating system TCP configurables, which vary by platform, define the actual keepalive timing details.

Values

broken

Example

```
net_service_name=
  (DESCRIPTION=
    (ENABLE=broken)
    (ADDRESS=(PROTOCOL=tcp)(HOST=sales1-svr)(PORT=1521))
    (ADDRESS=(PROTOCOL=tcp)(HOST=sales2-svr)(PORT=1521)))
    (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))
```

Although the preceding example has multiple addresses, the ADDRESS_LIST parameter was not used. This is because the ADDRESS_LIST parameter is not mandatory.

6.8.2 EXPIRE_TIME

Use the EXPIRE_TIME parameter to specify how often, in minutes, to verify that the remote server connection is alive.

Purpose

To specify time intervals, in minutes, for how often to verify that the remote server connection is alive.

Usage Notes

Oracle Net Services tunes the TCP keepalive parameters so that probes are sent after an idle activity.

Limitations on using the terminated connection detection feature are:

You cannot use it on bequeathed connections.



- Though very small, a probe packet generates additional traffic that may degrade your network performance.
- Depending on your operating system, the server may need to perform additional processing to distinguish the connection probing event from other events. This can also result in a degraded network performance.

Default

0

Minimum Value

Recommended Value

10

Example

```
net service name=
   (DESCRIPTION=
     (EXPIRE TIME=10)
     (ADDRESS=(PROTOCOL=tcp)(HOST=sales1-svr)(PORT=1521)))
     (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))
```

6.8.3 FAILOVER

Use the Failover parameter to enable or disable connect-time failover for multiple protocol addresses.

Purpose

To enable or disable connect-time failover for multiple protocol addresses.

Usage Notes

When you set the parameter to on, yes, or true, Oracle Net fails over at connect time to a different address if the first protocol address fails. When you set the parameter to off, no, or false, Oracle Net tries one protocol address.

Put this parameter under the DESCRIPTION_LIST parameter, the DESCRIPTION parameter, or the ADDRESS_LIST parameter.



(i) Note

Do not set the GLOBAL_DBNAME parameter in the SID_LIST_listener_name section of the listener.ora. A statically configured global database name disables connect-time failover.

Default

on for the DESCRIPTION LIST, DESCRIPTION, and ADDRESS LIST parameters



Values

- yes | on | true
- no | off | false

Example

```
net_service_name=
(DESCRIPTION=
    (FAILOVER=on)
    (ADDRESS_LIST=
         (ADDRESS=(PROTOCOL=tcp)(HOST=sales1-svr)(PORT=1521))
         (ADDRESS=(PROTOCOL=tcp)(HOST=sales2-svr)(PORT=1521)))
(CONNECT_DATA=(SERVICE_NAME=sales.us.example.com)))
```

6.8.4 LOAD_BALANCE

Use the ${\tt LOAD_BALANCE}$ parameter to enable or disable client load balancing for multiple protocol addresses.

Purpose

To enable or disable client load balancing for multiple protocol addresses.

Usage Notes

When you set the parameter to on, yes, or true, Oracle Net goes through the list of addresses in a random sequence, balancing the load on the various listener or Oracle Connection Manager protocol addresses. When you set the parameter to off, no, or false, Oracle Net tries the protocol addresses sequentially until one succeeds.

Put this parameter under the DESCRIPTION_LIST parameter, the DESCRIPTION parameter, or the ADDRESS_LIST parameter.

Default

on for DESCRIPTION LIST

Values

- yes | on | true
- no | off | false

Example

```
net_service_name=
(DESCRIPTION=
  (LOAD_BALANCE=on)
  (ADDRESS_LIST=
        (ADDRESS=(PROTOCOL=tcp)(HOST=sales1-svr)(PORT=1521))
        (ADDRESS=(PROTOCOL=tcp)(HOST=sales2-svr)(PORT=1521)))
        (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com)))
```



6.8.5 RECV_BUF_SIZE

Use the RECV_BUF_SIZE parameter to specify buffer space for session receive operations.

Purpose

To specify, in bytes, the buffer space for receive operations of sessions.

Usage Notes

This parameter is supported by the TCP/IP, TCP/IP with TLS, and SDP protocols.

Put this parameter under the DESCRIPTION parameter or at the end of the protocol address.

Setting this parameter in the connect descriptor for a client overrides the <u>RECV_BUF_SIZE</u> parameter at the client-side sqlnet.ora file.



Additional protocols might support this parameter on certain operating systems. Refer to the operating system-specific documentation for additional information about additional protocols.

Default

The default value for this parameter is specific to the operating system. The default for the Linux 2.6 operating system is 87380 bytes.

Example

```
net_service_name=
(DESCRIPTION=
   (ADDRESS_LIST=
     (ADDRESS=(PROTOCOL=tcp)(HOST=sales1-server)(PORT=1521)
        (RECV_BUF_SIZE=11784))
     (ADDRESS=(PROTOCOL=tcp)(HOST=sales2-server)(PORT=1521)
       (RECV_BUF_SIZE=11784))
   (CONNECT DATA=
     (SERVICE_NAME=sales.us.example.com)))
net_service_name=
 (DESCRIPTION=
   (RECV_BUF_SIZE=11784)
   (ADDRESS_LIST=
     (ADDRESS=(PROTOCOL=tcp)(HOST=hr1-server)(PORT=1521))
     (ADDRESS=(PROTOCOL=tcp)(HOST=hr2-server)(PORT=1521)))
   (CONNECT DATA=
     (SERVICE_NAME=hr.us.example.com)))
```

Related Topics

Oracle Al Database Net Services Administrator's Guide



6.8.6 SDU

Use the SDU parameter to configure the session data unit (SDU) size.

Purpose

To instruct Oracle Net to optimize the transfer rate of data packets being sent across the network with a specified SDU size.

Usage Notes

Put this parameter under the DESCRIPTION parameter.

Setting this parameter in the connect descriptor for a client overrides the DEFAULT_SDU_SIZE parameter at client-side sqlnet.ora file.

Default

8192 bytes (8 KB)

Values

512 to 2097152 bytes

Example

Related Topics

Oracle AI Database Net Services Administrator's Guide

6.8.7 SEND_BUF_SIZE

Use the SEND_BUF_SIZE parameter to specify buffer space for session send operations.

Purpose

To specify, in bytes, the buffer space for send operations of sessions.

Usage Notes

This parameter is supported by the TCP/IP, TCP/IP with TLS, and SDP protocols.

Put this parameter under the DESCRIPTION parameter or at the end of the protocol address.

Setting this parameter in the connect descriptor for a client overrides the <u>SEND_BUF_SIZE</u> parameter at the client-side sqlnet.ora file.





Additional protocols might support this parameter on certain operating systems. Refer to the operating system-specific documentation for information about additional protocols.

Default

The default value for this parameter is operating system specific. The default for the Linux 2.6 operating system is 16 KB.

Example

```
net_service_name=
 (DESCRIPTION=
   (ADDRESS_LIST=
     (ADDRESS=(PROTOCOL=tcp)(HOST=sales1-server)(PORT=1521)
        (SEND_BUF_SIZE=11784))
     (ADDRESS=(PROTOCOL=tcp)(HOST=sales2-server)(PORT=1521)
        (SEND_BUF_SIZE=11784)))
   (CONNECT DATA=
     (SERVICE_NAME=sales.us.example.com)))
net_service_name=
(DESCRIPTION=
   (SEND_BUF_SIZE=11784)
   (ADDRESS_LIST=
     (ADDRESS=(PROTOCOL=tcp)(HOST=hr1-server)(PORT=1521)
     (ADDRESS=(PROTOCOL=tcp)(HOST=hr2-server)(PORT=1521)))
   (CONNECT DATA=
     (SERVICE_NAME=hr.us.example.com)))
```

Related Topics

Oracle Al Database Net Services Administrator's Guide

6.8.8 SOURCE_ROUTE

Use the SOURCE_ROUTE parameter to enable routing through multiple protocol addresses.

Purpose

To enable routing through multiple protocol addresses.

Usage Notes

When you set this parameter to on or yes, Oracle Net uses each address in order until the destination is reached.

To use Oracle Connection Manager, an initial connection from the client to Oracle Connection Manager is required, and a second connection from Oracle Connection Manager to the listener is required.

Put this parameter under either the DESCRIPTION_LIST parameter, the DESCRIPTION parameter, or the ADDRESS_LIST parameter.

Default

off



Values

- yes on
- no | off

Example

```
net_service_name=
  (DESCRIPTION=
        (SOURCE_ROUTE=on)
        (ADDRESS=(PROTOCOL=tcp)(HOST=cman-pc)(PORT=1630))
        (ADDRESS=(PROTOCOL=tcp)(HOST=sales1-svr)(PORT=1521))
        (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))
```

Related Topics

Oracle Al Database Net Services Administrator's Guide

6.8.9 TYPE OF SERVICE

Use the TYPE_OF_SERVICE parameter to specify the type of service to use for an Oracle Rdb database.

Purpose

To specify the type of service to use for an Oracle Rdb database.

Usage Notes

This parameter should only be used if the application supports both an Oracle Rdb and Oracle database service, and you want the application to load balance between the two.

Put this parameter under the DESCRIPTION parameter.

Example

Related Topics

Oracle Al Database Net Services Administrator's Guide



6.8.10 USE_SNI

Use the USE_SNI parameter to set Server Name Indication (SNI) value using CONNECT_DATA parameters for TLS connections.

Purpose

To enable or disable setting of SNI value using CONNECT_DATA parameters for TLS connections through connect descriptor.

Usage Notes

When USE_SNI is set and CONNECT_DATA has any of the supported parameters for SNI, then those parameters are used to set the SNI value. This SNI value is then used by the listener to select the appropriate service handler for servicing the request without having to do a TLS handshake with the client. The supported CONNECT_DATA parameters for setting SNI include SERVICE_NAME, INSTANCE_NAME, SERVER and COLOCATION_TAG.

When USE_SNI is set and CONNECT_DATA doesn't include any of the supported parameters listed above, then SNI value will not be set and the listener will perform the usual TLS handshake with the client to fetch the connect request.

Values

- ON | TRUE | YES to set SNI value using CONNECT DATA
- OFF | FALSE | NO to not set SNI value using CONNECT_DATA

Default Value

OFF

Example



Support for SNI is available in all versions starting 23.7, but not in earlier versions.

Related Topics

Oracle Al Database Net Services Administrator's Guide

6.9 Connection Data Section

Learn how to configure network connections with protocol addresses.



A network object is identified by a protocol address. When a connection is made, the client and the receiver of the request (listener or Oracle Connection Manager) are configured with identical protocol addresses. The client uses this address to send the connection request to a particular network object location, and the recipient "listens" for requests on this address, and grants a connection based on its address information matching the client information.

CONNECT DATA

Use the CONNECT DATA parameter to define the connection service.

- COLOCATION TAG
- CONNECTION ID PREFIX

Use this parameter to add application specific ID to connection identifier.

- FAILOVER MODE
- GLOBAL NAME
- HS
- INSTANCE NAME
- POOL BOUNDARY

Use the POOL_BOUNDARY parameter to enable implicit connection pooling with either Database Resident Connection Pooling (DRCP) or Proxy Resident Connection Pooling (PRCP).

POOL CONNECTION CLASS

Use this parameter to explicitly name the connection class for Database Resident Connection Pooling (DRCP) connections.

POOL NAME

Use the POOL_NAME parameter to specify a pool name for multi-pool Database Resident Connection Pooling (DRCP) connections.

POOL PURITY

Use this parameter to specify if an application needs a new session that is not tainted with any prior session state or to reuse a previous session.

- RDB DATABASE
- SHARDING KEY

Use the ${\tt SHARDING_KEY}$ parameter to route the database connection request to an appropriate shard.

SHARDING KEY ID

Use this parameter to route the database connection request to a shard using the unique SHA-256 ID of a sharding key (instead of a sharding key value).

SUPER SHARDING KEY

Use the SUPER_SHARDING_KEY parameter in the case of composite sharding to route the database request to a collection of shards (shardspace).

- SERVER
- SERVICE NAME
- TUNNEL SERVICE NAME

Set this parameter to identify the client CMAN.



6.9.1 CONNECT_DATA

Use the CONNECT_DATA parameter to define the connection service.

Purpose

To define the service to which you want to connect, such as SERVICE_NAME.

Usage Notes

Put this parameter under the DESCRIPTION parameter. CONNECT_DATA permits additional parameters as listed in Connection Data Section.

Example

6.9.2 COLOCATION_TAG

Purpose

To direct the listener to route all connections with the same <code>colocation_tag</code> to the same database instance.

Usage Notes

Use this parameter with the CONNECT_DATA parameter.

The parameter value must be an alphanumeric string.

Example

① Note

Under certain conditions, such as, when maximum load of an instance is reached or when new instances are added or deleted for a service, the colocation of client connections that have the same <code>colocation_tag</code> to the same database instance may not be consistent.



6.9.3 CONNECTION_ID_PREFIX

Use this parameter to add application specific ID to connection identifier.

Usage Notes

Put this parameter under the CONNECT_DATA parameter.

Example

```
net_service_name=
(DESCRIPTION=
    (ADDRESS_LIST=
         (ADDRESS=...)
         (ADDRESS=...))
(CONNECT_DATA=
         (SERVICE_NAME=sales.us.example.com)
         ((CONNECTION_ID_PREFIX=value)))
```

(i) Note

The CONNECTION_ID_PREFIX value is appended internally to a system generated connection ID value and sent as CONNECTION_ID in connect string. The CONNECTION_ID_PREFIX must be an 8-byte alphanumeric identifier limited to the following [a...z] [A...Z] [0...9] _ character set.

Related Topics

Permitted Listener and Net Service Name Character Set
 Create listener names and net service names for clients that comply with Oracle Net Services character set requirements.

6.9.4 FAILOVER_MODE

Purpose

To instruct Oracle Net to fail over to a different listener if the first listener fails during run time.

Usage Notes

Depending upon the configuration, the session or any SELECT statements which were in progress are automatically failed over.

This type of failover is called Transparent Application Failover (TAF) and should not be confused with the connect-time failover FAILOVER parameter.

Put this parameter under the CONNECT_DATA parameter.

Additional Parameters

FAILOVER MODE supports the following parameters:



- BACKUP: Specifies the failover node by its net service name. A separate net service name must be created for the failover node.
- TYPE: Specifies the type of failover. Three types of Oracle Net failover functionality are available by default to Oracle Call Interface (OCI) applications:
 - SESSION: Fails over the session. For example, if a user's connection is lost, then a new session is automatically created for the user on the backup. This type of failover does not attempt to recover selects.
 - SELECT: Allows users with open cursors to continue fetching them after failure.
 However, this mode involves overhead on the client side in normal select operations.
 - NONE: This is the default, in which no failover functionality is used. This can also be explicitly specified to prevent failover from happening.
- METHOD: Specifies how fast failover is to occur from the primary node to the backup node:
 - BASIC: Establishes connections at failover time. This option requires almost no work on the backup database server until failover time.
 - PRECONNECT: Pre-establishes connections. This provides faster failover but requires that the backup instance be able to support all connections from every supported instance.
- TRANSACTION: Allows the database to complete the current database transaction following a
 recoverable error. This parameter is used with the COMMIT_OUTCOME=TRUE parameter.
- RETRIES: Specifies the number of times to attempt to connect after a failover. If DELAY is specified, then RETRIES defaults to five retry attempts.
- DELAY: Specifies the amount of time in seconds to wait between connect attempts. If RETRIES is specified, then DELAY defaults to one second.

Note

If a callback function is registered, then RETRIES and DELAY parameters are ignored.

Related Topics

Oracle Al Database Net Services Administrator's Guide

6.9.5 GLOBAL_NAME

Purpose

To identify the Oracle Rdb database.

Usage Notes

Put this parameter under the CONNECT_DATA parameter.

Example

```
net_service_name=
(DESCRIPTION=
   (ADDRESS_LIST=
    (ADDRESS=...)
   (ADDRESS=...)
(CONNECT_DATA=
```



```
(SERVICE_NAME=generic)
(RDB_DATABASE=[.mf]mf_personal.rdb)
(GLOBAL_NAME=alpha5)))
```

6.9.6 HS

Purpose

To direct Oracle Net to connect to a non-Oracle system through Heterogeneous Services.

Usage Notes

Put this parameter under the CONNECT_DATA parameter.

Default

None

Values

οk

Example

```
net_service_name=
(DESCRIPTION=
    (ADDRESS_LIST=
         (ADDRESS=...)
         (ADDRESS=...))
    (CONNECT_DATA=
         (SID=sales6)
    )
(HS=ok))
```

Related Topics

Oracle Al Database Net Services Administrator's Guide

6.9.7 INSTANCE_NAME

Purpose

To identify the database instance to access.

Usage Notes

Set the value to the value specified by the INSTANCE_NAME parameter in the initialization parameter file.

Put this parameter under the CONNECT_DATA parameter.

Example

```
net_service_name=
(DESCRIPTION=
   (ADDRESS_LIST=
      (ADDRESS=...)
   (ADDRESS=...)
(CONNECT_DATA=
```



(SERVICE_NAME=sales.us.example.com) (INSTANCE_NAME=sales1)))

(i) See Also

Oracle Database Net Services Administrator's Guide for additional information about the use of INSTANCE NAME

6.9.8 POOL BOUNDARY

Use the POOL BOUNDARY parameter to enable implicit connection pooling with either Database Resident Connection Pooling (DRCP) or Proxy Resident Connection Pooling (PRCP).

Purpose

To enable implicit connection pooling with either DRCP (on the database server side) or PRCP (for Oracle Connection Manager in Traffic Director Mode). This setting specifies a time boundary to release an application session back to the DRCP or PRCP pool. You can set implicit connection pooling at a statement or transaction boundary.

If you omit this parameter setting, then implicit connection pooling is disabled.

Usage Notes

- Specify this parameter under the CONNECT_DATA section of the connect string in the tnsnames.ora file, Easy Connect syntax, or directly as part of the command-line connect string.
- This parameter is applicable to pooled connections only. In the application tier, to configure DRCP or PRCP, the client must specify the server type as POOLED using the SERVER=POOLED setting.
- When set to STATEMENT, a session is released back to the connection pool when the session is implicitly stateless. A session is implicitly stateless when all open cursors in a session have been fetched through to completion and there are no active transactions, temporary tables, or temporary LOBs.
 - Use the STATEMENT value for applications that create minimal session states from partially fetched cursors, temporary LOBs, and global or private temporary tables.
- When set to TRANSACTION, a session is released back to the connection pool when a transaction ends implicitly or explicitly, or when a transaction is not available and the session is stateless. The release to the pool closes any active cursors, temporary tables, and temporary LOBs.
 - Use the TRANSACTION value for applications that create many session states from partially fetched cursors, temporary LOBs, and global or private temporary tables and for applications that have occasional commits or rollbacks of transactions.
- After executing a statement or creating a temporary LOB, if you perform a commit or rollback within the TRANSACTION boundary, then:
 - Subsequent fetch operations may encounter an invalid cursor-related error, such as ORA-01001.
 - Subsequent use of a temporary LOB may encounter an ORA-22922 error.



- Working with a persistent LOB can continue even after an implicit release. However, if an implicit operation lands on a different instance, then an ORA-43887 error may occur. In such cases, you must attempt the operation again.
- If an application uses session pooling APIs along with the POOL_BOUNDARY=STATEMENT or POOL_BOUNDARY=TRANSACTION attribute in the connect string, then the connect string setting takes precedence over the pooling APIs. The session is released back to the connection pool using the statement or transaction boundary directive, overriding the session release API call.

Default

None

Values and Examples

Value	Example
STATEMENT: To set implicit connection pooling at a statement boundary	Easy connect string:
	<pre>sales1-server:1521/sales.us.example.com:pooled?</pre>
	pool_boundary=statement
	Connect descriptor in tnsnames.ora:
	inst1=
	(DESCRIPTION=
	(ADDRESS=(PROTOCOL=tcp)(HOST=sales-server)
	(PORT=1521))
	(CONNECT_DATA=
	(SERVICE_NAME-Sales.us.example.com)
	(POOL BOUNDARY=STATEMENT))
)
TRANSACTION: To set implicit connection pooling at a transaction boundary	Easy connect string:
	<pre>sales1-server:1521/sales.us.example.com:pooled?</pre>
	pool_boundary=transaction
	Connect descriptor in tnsnames.ora:
	inst1=
	(DESCRIPTION=
	(ADDRESS=(PROTOCOL=tcp)(HOST=sales-server)
	(PORT=1521))
	(CONNECT_DATA=
	(SERVICE NAME=sales.us.example.com)
	(SERVER=POOLED)
	· _ · _ · _ · _ · _ ·



The following example of a connect descriptor in the them in the shows how to set implicit connection pooling in different modes:

For the inst1s application instance, POOL_BOUNDARY=STATEMENT specifies that implicit connection pooling applies at a statement boundary. HOST=sales-server and PORT=1521 specify a DRCP connection through the database server.

For the inst1t application instance, POOL_BOUNDARY=TRANSACTION specifies that implicit connection pooling applies at a transaction boundary. HOST=proxy-server and PORT=1522 specify a PRCP connection through Oracle Connection Manager in Traffic Director Mode.

Related Topics

- Oracle Al Database Development Guide
- Oracle Al Database Net Services Administrator's Guide

6.9.9 POOL_CONNECTION_CLASS

Use this parameter to explicitly name the connection class for Database Resident Connection Pooling (DRCP) connections.

Usage Notes

Add this parameter in the connect string under CONNECT_DATA section of the connect identifier. This parameter takes precedence and overrides the properties programmatically set by the application using this connect string.

Example

```
ServerPool =
  (DESCRIPTION=
          (ADDRESS=(PROTOCOL=tcp) (HOST=sales-svr) (PORT=1521))
          (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com)(SERVER=POOLED)
  (POOL_CONNECTION_CLASS=value)))
```



Related Topics

POOL PURITY

Use this parameter to specify if an application needs a new session that is not tainted with any prior session state or to reuse a previous session.

6.9.10 POOL_NAME

Use the POOL_NAME parameter to specify a pool name for multi-pool Database Resident Connection Pooling (DRCP) connections.

Purpose

To specify a pool name for each connection in multi-pool DRCP. This enables client applications or services to establish connections from specific DRCP pools.

With this setting, DRCP marks the connection against the appropriate pooled server. If you do not set this parameter, then the connection is established from the default pool if it is active.

Usage Notes

Use this parameter under the CONNECT_DATA section of the tnsnames.ora file or directly as part of the command-line connect string.

When the client connects with POOL_NAME=pool_name along with the SERVER=POOLED setting, DRCP checks whether a DRCP pool with the given pool name is added in the database:

- If the pool does not exist, then an error is returned.
- If the pool with the given pool name exists and is active, then the connection is established from the specified pooled server.
- If the pool with the given pool name exists but is inactive, then an error is returned for any new connections attempted. If connections are already established and the pool is made inactive, then those connections are handled based on the drainTime parameter used in the stop pool() procedure (called to stop the DRCP pool).

Database administrators add a DRCP pool at the PDB or CDB level. Static data dictionary view DBA_CPOOL_INFO contains information about existing DRCP pools. For example, this query lists all the available active pools:

```
SELECT * FROM DBA_CPOOL_INFO WHERE status='ACTIVE';
```

Value

DRCP pool name

Default

None

Example

```
(DESCRIPTION=
  (ADDRESS=
      (PROTOCOL=TCP)
      (HOST=sales-svr)
      (PORT=1522)
)
```



```
(CONNECT_DATA=
    (SERVICE_NAME=sales.us.example.com)
    (SERVER=POOLED)
    (POOL_NAME=mypool)
)
```

Related Topics

Oracle AI Database Development Guide

6.9.11 POOL PURITY

Use this parameter to specify if an application needs a new session that is not tainted with any prior session state or to reuse a previous session.

Usage Notes

Starting with Oracle Database 21c, you can configure Database Resident Connection Pooling (DRCP) for specific pluggable databases (PDBs). Add this parameter in the connect string under CONNECT_DATA section of the connect identifier to set purity attributes to a DRCP connection request.

This parameter takes precedence and overrides the properties programmatically set by the application using this connect string.

Values

NEW/SELF

Example

```
ServerPool =
  (DESCRIPTION=
      (ADDRESS=(PROTOCOL=tcp) (HOST=sales-svr) (PORT=1521))
      (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com)(SERVER=POOLED)
(POOL_PURITY=value)))
```

Related Topics

POOL CONNECTION CLASS

Use this parameter to explicitly name the connection class for Database Resident Connection Pooling (DRCP) connections.

6.9.12 RDB_DATABASE

Purpose

To specify the file name of an Oracle Rdb database.

Usage Notes

Put this parameter under the CONNECT DATA parameter.



Example

6.9.13 SHARDING KEY

Use the SHARDING_KEY parameter to route the database connection request to an appropriate shard.

Purpose

To specify the value of a sharding key. Based on the value specified during a database connection request, the request is directly routed to the appropriate shard.

Usage Notes

You specify this parameter under the CONNECT_DATA section of a connect string or tnsnames.ora file.

Use the SHARDING_KEY parameter to specify a sharding key in simplified text format. This parameter supports only ASCII character set and not special characters. The following data types are supported for a sharding key:

- NUMBER
- INTEGER
- SMALLINT
- RAW
- NVARCHAR
- NVARCHAR2
- NCHAR
- DATE
- TIMESTAMP

Use the <code>SHARDING_KEY_B64</code> parameter to specify the base64-encoded binary representation of a sharding key. This parameter supports these special characters: " quotation mark , comma () close parenthesis + plus sign)

Values

The fields for base64-encoded values (*_B64) start with a header, which is a sequence of space-separated integer values:

```
(CONNECT_DATA=
  (SHARDING_KEY_B64=
    [version][type][key column 1 type identifier][key column 2 type
identifier] ... ,[base64 string],[base64 string],[base64 string],...))...
```



In the above syntax:

- Parts of the compound key are separated with a comma.
- *version* specifies the version number of base64 representation. Currently, only version 1 is supported, and thus the supported *version* value is 1.
- type specifies the character set string and its encoding information. The supported type values are:

Value	Character Set String	Encoding Scheme
0	String contains hash value.	Character values are encoded in AL32UTF8 (for VARCHAR) and AL16UTF16 (for NVARCHAR).
1	String does not contain hash value.	
2	String does not contain hash value.	Character values are encoded in database encoding, which may be specific for each column.
3	String contains hash value.	
4	String contains only hash value.	

 key column type identifier specifies the data types. The supported key column type identifier values are:

Value	Data Type
1	VARCHAR, NVARCHAR, CHAR, NCHAR
2	NUMBER
6	NUMBER with length in first byte
12	DATE
23	RAW
180	TIMESTAMP

• The header is terminated by a comma and is followed by *base64 string*. *base64 string* is a comma-separated list of the base64-encoded value string. The hash value, if available, is the last value in the list.

Example 6-8

In the following sample connect string, the <code>SHARDING_KEY</code> parameter value is specified in simplified text format:



Example 6-9

In the following sample connect string, the <code>SHARDING_KEY_B64</code> parameter value is encoded to base64 binary representation:

Related Topics

SUPER SHARDING_KEY

Use the SUPER_SHARDING_KEY parameter in the case of composite sharding to route the database request to a collection of shards (shardspace).

SHARDING KEY ID

Use this parameter to route the database connection request to a shard using the unique SHA-256 ID of a sharding key (instead of a sharding key value).

Oracle Al Database Net Services Administrator's Guide

6.9.14 SHARDING_KEY_ID

Use this parameter to route the database connection request to a shard using the unique SHA-256 ID of a sharding key (instead of a sharding key value).

Purpose

If you are using hashing to encrypt sharding keys, then use this parameter to specify the unique SHA256 hash value assigned to a sharding key. Based on the value specified during the database connection request, the request is directly routed to the appropriate shard.

Usage Notes

You use this parameter for directory-based sharding.

Set this parameter under the CONNECT DATA section of a connect string or this names. or a file.

Value

SHA256 hash value of a sharding key in simplified text format. This value supports only the RAW data type.

You must enclose the value in single quotation marks.

Default

None



Example

Related Topics

SHARDING KEY

Use the ${\tt SHARDING_KEY}$ parameter to route the database connection request to an appropriate shard.

SUPER SHARDING KEY

Use the SUPER_SHARDING_KEY parameter in the case of composite sharding to route the database request to a collection of shards (shardspace).

Oracle Al Database Net Services Administrator's Guide

6.9.15 SUPER SHARDING KEY

Use the SUPER_SHARDING_KEY parameter in the case of composite sharding to route the database request to a collection of shards (shardspace).

Purpose

To specify a shardspace key for a collection of shards. A shardspace is set of shards that store data that corresponds to a range or list of key values. Based on the value specified during a database connection request, the request is directly routed to an appropriate shardspace.

Usage Notes

You specify this parameter under the CONNECT_DATA section of a connect string or tnsnames.ora file.

Use the SUPER_SHARDING_KEY parameter to specify a shardspace key for a collection of shards in simplified text format. This parameter supports only ASCII character set and not special characters. The supported data types for a super sharding key are the same as those for a sharding key.

Use the SUPER_SHARDING_KEY_B64 parameter to specify the base64-encoded binary representation of a shardspace key. This parameter supports special characters (such as "quotation mark, comma () close parenthesis + plus sign).



Values

The fields for base64-encoded values (*_B64) start with a header, which is a sequence of space-separated integer values:

```
(CONNECT_DATA=(SUPER_SHARDING_KEY_B64=[version] [type] [integer literal] [integer literal] ... ,[base64 binary],[base64 binary],[base64 binary],...))...
```

For details on each of the base64-encoded header fields, see **SHARDING KEY**.

Example 6-10

In the following sample connect string, the <code>SHARDING_KEY</code> and <code>SUPER_SHARDING_KEY</code> parameter values are specified in simplified text format:

```
net_service_name=
  (DESCRIPTION=
    (ADDRESS_LIST=
        (ADDRESS=(host=sales-east1)(port=1522))
        (ADDRESS=(host=sales-east2)(port=1522))
    )
  (CONNECT_DATA=
        (SERVICE_NAME=sales.us.example.com)
        ((SHARDING_KEY=40598230)(SUPER_SHARDING_KEY=gold))
    )
  )
}
```

Example 6-11

In the following sample connect string, the SHARDING_KEY_B64 and SUPER_SHARDING_KEY_B64 parameter values are encoded to base64 binary representation:

Related Topics

SHARDING KEY

Use the ${\tt SHARDING_KEY}$ parameter to route the database connection request to an appropriate shard.

SHARDING KEY ID

Use this parameter to route the database connection request to a shard using the unique SHA-256 ID of a sharding key (instead of a sharding key value).



Oracle Al Database Net Services Administrator's Guide

6.9.16 SERVER

Purpose

To direct the listener to connect the client to a specific type of service handler.

Usage Notes

Put this parameter under the CONNECT_DATA parameter.

Values

- dedicated to specify whether client requests be served by dedicated server.
- shared to specify whether client requests be served by a dispatcher or shared server.
- pooled to get a connection from the connection pool if database resident connection pooling is enabled on the server.

(i) Note

- Shared server must be configured in the database initialization file in order for the client to connect to the database with a shared server process.
- The <u>USE_DEDICATED_SERVER</u> parameter in the sqlnet.ora file overrides this parameter.

Example

6.9.17 SERVICE_NAME

Purpose

To identify the Oracle Database database service to access.

Usage Notes

Set the value to a value specified by the SERVICE_NAMES parameter in the initialization parameter file.

Put this parameter under the CONNECT_DATA parameter.

Example

```
net_service_name=
  (DESCRIPTION=
```



```
(ADDRESS_LIST=
  (ADDRESS=...)
  (ADDRESS=...))
(CONNECT_DATA=
  (SERVICE_NAME=sales.us.example.com)))
```

Related Topics

Oracle AI Database Net Services Administrator's Guide

6.9.18 TUNNEL_SERVICE_NAME

Set this parameter to identify the client CMAN.

Purpose

The server CMAN listener will route the connection to a gateway that has a tunnel connection to the requested client ID.

Usage Notes

Put this parameter under the CONNECT_DATA parameter.

Example

```
net_service_name=
(DESCRIPTION=
    (ADDRESS_LIST=
        (ADDRESS=...)
        (ADDRESS=...))
(CONNECT_DATA=
        (SERVICE_NAME=sales.us.example.com)
        (TUNNEL_SERVICE_NAME=south)))
```

Related Topics

Oracle Al Database Net Services Administrator's Guide

6.10 Security Section

The security section of the tnsnames.ora file specifies these security-related parameters for use with Oracle security features.

AUTHENTICATION SERVICE

Use the thinnames.ora parameter AUTHENTICATION_SERVICE to enable an authentication service.

AZURE DB APP ID URI

Use the AZURE_DB_APP_ID_URI parameter to specify the application ID URI of the Oracle Database instance, registered with Microsoft Entra ID (previously called Microsoft Azure Active Directory).

CLIENT CERTIFICATE

Use the CLIENT_CERTIFICATE parameter to specify the file system path to a client certificate that authenticates your database client application.



CLIENT ID

Use the CLIENT_ID parameter to specify the ID of the database client Microsoft Entra ID app registration.

IGNORE AND ENCRYPTION FOR TCPS

The IGNORE_ANO_ENCRYPTION_FOR_TCPS parameter specifies if the SQLNET.ENCRYPTION_CLIENT parameter should be ignored for this specific TNS alias.

KERBEROS5 CC NAME

Use the tnsnames.ora parameter KERBEROS5_CC_NAME to specify the complete path name to the Kerberos credentials cache (CC) file.

KERBEROS5 PRINCIPAL

Use the KERBEROS5_PRINCIPAL parameter to set the Kerberos principal name associated with the Kerberos credentials cache (CC) file.

OCI COMPARTMENT

Use the OCI_COMPARTMENT parameter to specify Oracle Cloud Identifier (OCID) of the compartment that holds database instances for client connections.

OCI CONFIG FILE

Use the $\texttt{OCI_CONFIG_FILE}$ parameter to specify the directory location where the Oracle Cloud Infrastructure (OCI) configuration file is stored.

OCI DATABASE

Use the OCI_DATABASE parameter to specify Oracle Cloud Identifier (OCID) of the database that you want to access for the client connection.

OCI IAM URL

Use the OCI_IAM_URL parameter to specify an endpoint URL that the database client must connect with to get the database token for authenticating Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) users on OCI Database as a Service (DBaaS).

OCI PROFILE

Use the OCI_PROFILE parameter to specify the profile name for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) users.

OCI TENANCY

Use the OCI_TENANCY parameter to specify Oracle Cloud Identifier (OCID) of the user's tenancy.

PASSWORD AUTH

REDIRECT URI

Use the REDIRECT_URI parameter to specify the redirect URI, registered for your Microsoft Entra ID client application.

SECURITY

Use the SECURITY parameter to change the security properties of a connection.

SEPS WALLET LOCATION

Use the SEPS_WALLET_LOCATION parameter to specify the wallet location for secure external password store (SEPS) and to enable the use of specified wallet for authentication.

SSL CERTIFICATE ALIAS

Use the sqlnet.ora or thinnames.ora parameter SSL_CERTIFICATE_ALIAS to specify the certificate alias to use in Transport Layer Security (TLS) connections.

SSL CERTIFICATE THUMBPRINT

Use the sqlnet.ora or tnsnames.ora parameter $SSL_CERTIFICATE_THUMBPRINT$ to specify the certificate thumbprint to use in Transport Layer Security (TLS) connections.



SSL CLIENT AUTHENTICATION

Use the SSL_CLIENT_AUTHENTICATION parameter to specify whether the database client is authenticated using Transport Layer Security (TLS).

SSL DISABLE WEAK EC CURVES

Use the SSL_DISABLE_WEAK_EC_CURVES parameter to disable the use of weak Elliptic Curve Cryptography (ECC) curves.

SSL SERVER CERT DN

Use the SSL_SERVER_CERT_DN parameter to specify the distinguished name (DN) of the database server.

SSL SERVER DN MATCH

Use the SSL_SERVER_DN_MATCH parameter to enforce server-side certificate validation through distinguished name (DN) matching.

SSL VERSION

Use the SSL_VERSION parameter to define valid Transport Layer Security (TLS) versions to be used for connections.

TENANT ID

Use the TENANT_ID parameter to specify the ID of your Microsoft Entra ID tenant.

TOKEN AUTH

Use the TOKEN_AUTH parameter to configure token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) or Microsoft Azure users of Microsoft Entra ID (previously called Microsoft Azure Active Directory).

TOKEN LOCATION

Use the TOKEN_LOCATION parameter to specify the directory location where token file is stored for token-based authentication.

TLS KEY EXCHANGE GROUPS

Use the ${\tt TLS_KEY_EXCHANGE_GROUPS}$ parameter to enable or disable post-quantum cryptographic (PQC) ML-KEM algorithms and classical ECDHE groups for TLS connections.

WALLET LOCATION

Use the ${\tt WALLET_LOCATION}$ parameter in the ${\tt tnsnames.ora}$ file to specify different locations where Oracle wallets are stored.

6.10.1 AUTHENTICATION SERVICE

Use the thsnames.ora parameter AUTHENTICATION_SERVICE to enable an authentication service.

Purpose

To enable an authentication service. If you have installed authentication, then Oracle recommends that you set AUTHENTICATION_SERVICE to either NONE or to one of the listed authentication methods.

Usage Notes

 Use this parameter in the SECURITY section of the tnsnames.ora file or directly as part of the connect string.

You can also set this value in the sqlnet.ora file. The AUTHENTICATION_SERVICE parameter is equivalent to the sqlnet.ora parameter SQLNET.AUTHENTICATION_SERVICES. The parameter value specified in the connect string takes precedence.



Note that the AUTHENTICATION_SERVICE parameter can take only a single authentication service, unlike the SQLNET.AUTHENTICATION_SERVICES parameter that can take multiple values.

- When using the AUTHENTICATION_SERVICE=ALL, the server attempts to authenticate using each of the following methods:
 - 1. Authentication based on a service external to the database, such as a service on the network layer, Kerberos, or RADIUS.
 - 2. Authentication based on the operating system user's membership in an administrative operating system group. Group names are platform-specific. This authentication applies to administrative connections only.
 - 3. Authentication performed by the database.
 - 4. Authentication based on credentials stored in a directory server.

The server falls back to the authentication methods that appear further down on the list if attempts to use the authentication methods appearing higher on the list were unsuccessful.

- When using local database password authentication (no external authentication), set AUTHENTICATION_SERVICE=NONE for better client performance.
- Operating system authentication enables access to the database using any user name and any password when an administrative connection is attempted to the CDB root, such as using the AS SYSDBA clause when connecting using SQL*Plus.

An example of a connection to the CDB root is as follows.

sqlplus ignored_username/ignored_password AS SYSDBA

When the operating-system user who issued the preceding command is already a member of the appropriate administrative operating system group, then the connection is successful. This is because Oracle checks the group membership first, and thus the user name and password are ignored by the server.

Default

ALL



When installing Oracle Database with Database Configuration Assistant (DBCA), you can set this parameter to NTS in the sqlnet.ora file.

Values

Authentication methods that are available with Oracle Net Services:

- NONE for no authentication methods, including Microsoft Windows native operating system
 authentication. When you set AUTHENTICATION_SERVICE to NONE, then the user can use a
 valid user name and password to access the database.
- ALL for all authentication methods.
- BEQ for native operating system authentication for operating systems other than Microsoft Windows.
- KERBEROS5 for Kerberos authentication.



- RADIUS for Remote Authentication Dial-In User Service (RADIUS) authentication.
- TCPS for TLS authentication.
- NTS for Microsoft Windows native operating system authentication. In this case, the user must authenticate to the database (CDB root) with OS credentials using Windows native authentication. No external password is needed. NTS checks the group membership for an OS user. For example, if an OS user is a member of the ORA DBA group, then the user can log in to the database as SYSDBA.

(i) Note

With the AUTHENTICATION_SERVICE=NTS setting, if you try to connect through SQL*Plus using NTS authentication and specify an external password (for example, SQL*Plus SYSTEM/password), then the connection fails with an ORA-12638, 00000, "Failed to retrieve credentials for adapter_name. error message. For regular user name and password based authentication, set the value to NONE.

Example

```
net service name=
    (DESCRIPTION=
        (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr)(PORT=1521))
        (SECURITY=(AUTHENTICATION SERVICE=KERBEROS5))
        (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))
    )
```

Related Topics

- Oracle AI Database Security Guide
- SQLNET.AUTHENTICATION SERVICES Use the sqlnet.ora parameter SQLNET.AUTHENTICATION SERVICES to enable one or more authentication services.

6.10.2 AZURE DB APP ID URI

Use the AZURE DB APP ID URI parameter to specify the application ID URI of the Oracle Database instance, registered with Microsoft Entra ID (previously called Microsoft Azure Active Directory).

Purpose

To specify the application ID URI that uniquely identifies your database instance in Entra ID.

This URI value is used to compose the authorization scope (permission) of your database token request during token-based authentication:

```
$Scope = "database_app_id_uri/scope"
```



For example:

```
$Scope = "https://application.example.com/123ab4cd-1a2b-1234-a12b-
aa00123b2cd3/session:scope:connect"
```

Here, the app ID URI https://application.example.com/123ab4cd-1a2b-1234-a12b-aa00123b2cd3 is part of the scope.

Usage Notes

This parameter is mandatory. You must set it along with the TOKEN_AUTH parameter for the AZURE_INTERACTIVE, AZURE_SERVICE_PRINCIPAL, AZURE_MANAGED_IDENTITY, and AZURE_DEVICE_CODE authentication flows.

For the JDBC-thin clients, you can specify this parameter in the connect string, Easy Connect syntax, tnsnames.ora file, or properties. For the thick clients (OCI and Instant Client) and ODP.NET core and managed database clients, you can specify this parameter in the connect string, sqlnet.ora file, Easy Connect syntax, or tnsnames.ora file. The parameter value specified in the connect string takes precedence.

Default

None

Value

You can get the application ID URI value by logging in to the Azure portal. This is listed as the Application ID URI value on the App registrations - Overview page.

Note that this is the value that you specified while registering your Oracle Database instance with the Entra ID tenancy, as shown in *Oracle AI Database Security Guide*.

Examples

```
In the tnsnames.ora file:
```



In the Easy Connect string:

tcps:sales-svr:1521/sales.us.example.com? TOKEN AUTH=AZURE INTERACTIVE&AZURE DB APP ID URI=https:// application.example.com/123ab4cd-1a2b-1234-a12b-aa00123b2cd3

In these examples, the CLIENT_ID, TENANT_ID, and REDIRECT_URI parameters are not specified. CLIENT_ID and TENANT_ID are required parameters when using the thick clients (OCI and Instant Client). These parameters are optional for the JDBC-thin and ODP.NET core and managed database clients, which can automatically get these values from the Azure SDK configuration.

Related Topics

- Oracle Database Security Guide
- TOKEN AUTH

Use the TOKEN_AUTH parameter to configure token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) or Microsoft Azure users of Microsoft Entra ID (previously called Microsoft Azure Active Directory).

6.10.3 CLIENT CERTIFICATE

Use the CLIENT_CERTIFICATE parameter to specify the file system path to a client certificate that authenticates your database client application.

Purpose

File system path to a client certificate that authenticates your database client application in Microsoft Entra ID. A client certificate is the digital certificate of an Azure cloud resource, and the client uses this certificate as a credential to prove its identity when requesting an Entra ID access token. This is used for the AZURE SERVICE PRINCIPAL token-based authentication flow.



(i) Note

Only the JDBC-thin clients and ODP.NET core and managed database clients (and not the thick clients, such as OCI and Instant Client) support certificate-based authentication.

Usage Notes

The Entra ID client uses a client ID and a client secret to retrieve the Entra ID OAuth2 database access token. If a client secret is not configured, then the client driver automatically reads the file system path of a client certificate from the AZURE CLIENT CERTIFICATE PATH environment variable in the Azure SDK configuration. If the application client is public, then it uses only a client ID.

For more information about using certificates with service principals, review Microsoft documentation.

- This parameter is optional. You can set it if you have not configured the SDKs. Note that this parameter is ignored if the client driver is configured with a client secret.
- You can specify this parameter along with the TOKEN_AUTH=AZURE_SERVICE_PRINCIPAL setting in the connect string, Easy Connect syntax, or tnsnames.ora file. The parameter value specified in the connect string takes precedence.



- The supported formats for a certificate file are:
 - pem (Privacy Enhanced Mail)
 - pfx (Personal Information Exchange)

This format is password-protected. If the file is in a .pfx format, then you must also set the corresponding AZURE_CLIENT_CERTIFICATE_PASSWORD parameter.

You cannot store the certificate in an Oracle Wallet or Azure Key Vault.

Because this certificate is a credential for accessing the database, you must protect it on your file system.

Default

None

Value

Full path (including a file name) to the Azure certificate file

Examples

In the tnsnames.ora file:

In the Easy Connect string:

```
tcps:sales-svr:1521/sales.us.example.com?
TOKEN_AUTH=AZURE_SERVICE_PRINCIPAL&AZURE_DB_APP_ID_URI=https://
application.example.com/123ab4cd-1a2b-1234-a12b-
aa00123b2cd3&CLIENT_CERTIFICATE=ORACLE_HOME/.azure/certificates/my-app.pem
```

In these examples, the CLIENT_ID and TENANT_ID parameters are not specified. These parameters are optional for the JDBC-thin and ODP.NET core and managed database clients, which can automatically get these values from the Azure SDK configuration.

Related Topics

- Oracle Database Security Guide
- TOKEN AUTH

Use the TOKEN_AUTH parameter to configure token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) or Microsoft Azure users of Microsoft Entra ID (previously called Microsoft Azure Active Directory).



6.10.4 CLIENT_ID

Use the CLIENT_ID parameter to specify the ID of the database client Microsoft Entra ID app registration.

Purpose

To specify the client ID assigned to your database client during Entra ID app registration. Note that this is not the client ID for the database server. This application is your database client that requests to get an access token for the user during Azure token-based authentication.

Usage Notes

You use this parameter along with the TOKEN_AUTH parameter for the AZURE_INTERACTIVE, AZURE_SERVICE_PRINCIPAL, AZURE_MANAGED_IDENTITY, and AZURE_DEVICE_CODE authentication flows, as follows:

The AZURE_MANAGED_IDENTITY authentication flow is applicable to client-side or server-side
applications hosted on Azure environments, such as Azure App Service or Azure virtual
machine.

When using the JDBC-thin clients and ODP.NET core and managed database clients, the client driver uses a system-assigned managed identity. A system-assigned managed identity is an implicit identity assigned by Entra ID to your application, and is configured in the Azure SDK by default. Optionally, you can set this parameter to explicitly assign the client ID of a user-assigned managed identity to your application.

When using the thick clients (OCI and Instant Client), which do not use the Azure SDKs, you must set this parameter to assign a user-assigned managed identity to your application.

 For other authentication flows, when using the JDBC-thin clients and ODP.NET core and managed database clients, the client driver searches for the client ID in the Azure SDK configuration. In this case, this parameter is optional.

When using the OCI and Instant Clients, you must set this parameter (along with other required parameters, such as <code>TENANT_ID</code>). Otherwise, an error message appears prompting you to configure the required parameters.

Note that this parameter is mandatory for the OCI and Instant Clients. It is optional only when using the JDBC-thin clients and ODP.NET core and managed database clients.

For the JDBC-thin clients, you can specify this parameter in the connect string, Easy Connect syntax, tnsnames.ora file, or properties. For the thick clients (OCI and Instant Client) and ODP.NET core and managed database clients, you can specify this parameter in the connect string, sqlnet.ora file, Easy Connect syntax, or tnsnames.ora file. The parameter value specified in the connect string takes precedence.

Default

None

Value

You can get the client ID value by logging in to the Azure portal. This is listed as the Application (client) ID value on the App registrations - Overview page.



Examples

```
In the tnsnames.ora file:
net_service_name=
    (DESCRIPTION =
       (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr)(PORT=1521))
       (SECURITY=
          (SSL_SERVER_DN_MATCH=TRUE)
          (SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleContext")
          (TOKEN_AUTH=AZURE_INTERACTIVE)
          (AZURE_DB_APP_ID_URI=https://application.example.com/
123ab4cd-1a2b-1234-a12b-aa00123b2cd3)
          (CLIENT_ID=123ab4cd-1a2b-1234-a12b-aa00123b2cd3)
       (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))
In the sqlnet.ora file:
SSL_SERVER_DN_MATCH=TRUE
TOKEN_AUTH=AZURE_INTERACTIVE
AZURE_DB_APP_ID_URI=https://application.example.com/123ab4cd-1a2b-1234-a12b-
aa00123b2cd3
CLIENT_ID=123ab4cd-1a2b-1234-a12b-aa00123b2cd3
In the Easy Connect string:
tcps:sales-svr:1521/sales.us.example.com?
TOKEN_AUTH=AZURE_INTERACTIVE&AZURE_DB_APP_ID_URI=https://
application.example.com/123ab4cd-1a2b-1234-a12b-
aa00123b2cd3&CLIENT_ID=123ab4cd-1a2b-1234-a12b-aa00123b2cd3
```

In these examples, the <code>TENANT_ID</code> and <code>REDIRECT_URI</code> parameters are not specified. <code>TENANT_ID</code> is required when using the thick clients (OCI and Instant Client). This parameter is optional for the JDBC-thin and ODP.NET core and managed database clients, which can automatically get this value from the Azure SDK configuration.

Related Topics

- Oracle Database Security Guide
- TOKEN AUTH

Use the TOKEN_AUTH parameter to configure token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) or Microsoft Azure users of Microsoft Entra ID (previously called Microsoft Azure Active Directory).



6.10.5 IGNORE_ANO_ENCRYPTION_FOR_TCPS

The IGNORE_ANO_ENCRYPTION_FOR_TCPS parameter specifies if the SQLNET.ENCRYPTION_CLIENT parameter should be ignored for this specific TNS alias.

Purpose

To specify if the SQLNET.ENCRYPTION_CLIENT parameter should be ignored for this specific TNS alias.

Usage Notes

If your requirements are that SQLNET.ENCRYPTION_SERVER be set to required, then you can set the IGNORE_ANO_ENCRYPTION_FOR_TCPS parameter in both SQLNET.ENCRYPTION_CLIENT and SQLNET.ENCRYPTION_SERVER to TRUE. This forces the client to ignore the value that is set for the SQLNET.ENCRYPTION_CLIENT parameter for all outgoing TCPS connections.

Default

FALSE

Example 6-12 Example

```
test_ssl=
    (DESCRIPTION =
          (ADDRESS=(PROTOCOL=tcps)(HOST=)(PORT=1750))
          (CONNECT_DATA=(SID=^ORACLE_SID^))
          (SECURITY=(IGNORE_ANO_ENCRYPTION_FOR_TCPS=TRUE))
)
```

6.10.6 KERBEROS5_CC_NAME

Use the tnsnames.ora parameter KERBEROS5_CC_NAME to specify the complete path name to the Kerberos credentials cache (CC) file.

Purpose

To specify the complete path name to the Kerberos CC file.

Usage Notes

 Use this parameter in the SECURITY section of the tnsnames.ora file or directly as part of the connect string.

You can also set this value in the sqlnet.ora file. The KERBEROS5_CC_NAME parameter is equivalent to the sqlnet.ora parameter SQLNET.KERBEROS5_CC_NAME. The parameter value specified in the connect string takes precedence.

 This parameter supports multiple principals for the storage of credentials that are returned by KDC in an encrypted format.

You can use the <code>okinit</code>, <code>oklist</code>, and <code>okdstry</code> utilities to configure encrypted cache files for all Kerberos principals. These utilities work with encrypted cache files only if you specify the cache path using <code>KERBEROS5_CC_NAME</code>.

KERBEROS5_CC_NAME is mandatory for all additional Kerberos users and principals.
 Optionally, you can set the KERBEROS5_PRINCIPAL parameter to specify the Kerberos



principal name associated with the credential cache (specified through KERBEROS5_CC_NAME). You can set KERBEROS5_PRINCIPAL in the connect string, sqlnet.ora file, or this names.ora file.

Oracle Database checks KERBEROS5_PRINCIPAL against the value that is retrieved from the credential cache. If the two values do not match, then the user is not authenticated.

Values and Examples

You can use the following formats to specify a value for KERBEROS5_CC_NAME:

- If the Oracle database is using a directory cache:
 - KERBEROS5_CC_NAME=complete_path_to_cc_file

For example:

```
KERBEROS5_CC_NAME=/tmp/kcache
KERBEROS5_CC_NAME=D:\tmp\kcache
```

KERBEROS5_CC_NAME=FILE:complete_path_to_cc_ file

For example:

```
KERBEROS5_CC_NAME=FILE:/tmp/kcache
```

- If the Oracle database is using the native Windows cache:
 - KERBEROS5_CC_NAME=OSMSFT://
 - KERBEROS5 CC NAME=MSLSA:

The OSMSFT and MSLSA options specify that the file is on Microsoft Windows and is running Microsoft Kerberos Key Distribution Center (KDC).

Default

The default value is operating system-dependent, as follows:

- On Linux and UNIX operating systems: /tmp/krb5cc_userid
- On Microsoft Windows operating systems: c:\tmp\krbcache

Related Topics

KERBEROS5 PRINCIPAL

Use the KERBEROS5_PRINCIPAL parameter to set the Kerberos principal name associated with the Kerberos credentials cache (CC) file.

SQLNET.KERBEROS5 CC NAME

Use the sqlnet.ora parameter $SQLNET.KERBEROS5_CC_NAME$ to specify the complete path name to the Kerberos credentials cache (CC) file.

Oracle AI Database Security Guide

6.10.7 KERBEROS5_PRINCIPAL

Use the KERBEROS5_PRINCIPAL parameter to set the Kerberos principal name associated with the Kerberos credentials cache (CC) file.

Purpose

When you configure Kerberos authentication for an Oracle Database client, you can specify multiple Kerberos principals with a single Oracle Database client.



This is an optional parameter. When specified, it is used to verify if the principal name in the credential cache (specified using KERBEROS5_CCC_NAME) matches the parameter value.

Usage Notes

Use this parameter in the SECURITY section of the tnsnames.ora file, or set it in the sqlnet.ora file. Alternatively, you can set KERBEROS5_PRINCIPAL in the connect string along with the KERBEROS5_CC_NAME parameter to connect as a different Kerberos principal.

The parameter value specified in the connect string takes precedence over the value specified in the sqlnet.ora Or tnsnames.ora file.

Each Kerberos principal must have a valid credential cache. Oracle Database checks KERBEROS5_PRINCIPAL against the value that is retrieved from the credential cache. If the two values do not match, then the user is not authenticated.

Examples

• For a user krbuser1, who is externally authenticated using the Kerberos principal krbprincl@example.com and the credential cache for this principal is located at /tmp/krbuser1/krb.cc, the connect descriptor in the tnsnames.ora file is:

For a user krbuser2, who is externally authenticated using the Kerberos principal krbprinc2@example.com and the credential cache for this principal is located at /tmp/krbuser2/krb.cc, the connect descriptor in the tnsnames.ora file is:



Note

The connection fails if the principal in the /tmp/krbuser1/krb.cc file does not contain the $krbprincl@example.com\ value$.

Related Topics

SQLNET.KERBEROS5 CC NAME

Use the sqlnet.ora parameter SQLNET.KERBEROS5_CC_NAME to specify the complete path name to the Kerberos credentials cache (CC) file.

KERBEROS5 CC NAME

Use the tnsnames.ora parameter KERBEROS5_CC_NAME to specify the complete path name to the Kerberos credentials cache (CC) file.

Oracle Al Database Security Guide

6.10.8 OCI COMPARTMENT

Use the OCI_COMPARTMENT parameter to specify Oracle Cloud Identifier (OCID) of the compartment that holds database instances for client connections.

Purpose

To define the scope of your database token request. This value instructs the database client to initiate a token request to databases within the specified compartment only. You use this parameter while configuring token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) users on OCI Database as a Service (DBaaS).

Usage Notes

The OCI_COMPARTMENT parameter is optional if you have not specified the OCI_DATABASE parameter. If you choose to set OCI_DATABASE, then you must also set OCI_COMPARTMENT to limit your token request to the specified database within that compartment.

If you do not set both the OCI_COMPARTMENT and OCI_DATABASE parameters, then the entire tenancy is the scope of your token request.

You can use this parameter along with the PASSWORD_AUTH and TOKEN_AUTH authentication settings:

- With the PASSWORD_AUTH configuration, the database client can only request an IAM database token using the IAM user name and IAM database password.
- With the TOKEN_AUTH configuration, the database client can request an IAM database token using the API-key, delegation token, security token, resource principal, or instance principal credentials. You can also enable the database client to directly retrieve the dbtoken with IAM Single-Sign On (SSO) credentials by using the OCI_INTERACTIVE, OCI_API_KEY, OCI_INSTANCE_PRINCIPAL, OCI_DELEGATION_TOKEN, and OCI_RESOURCE_PRINCIPAL authentication flows.

Use this parameter under the SECURITY section of the tnsnames.ora file, sqlnet.ora file, Easy Connect syntax, or directly as part of the command-line connect string. The parameter value specified in the connect string takes precedence over the other specified values.

Default

None



Value

OCID for the IAM compartment to allow access for the database token. You can get the OCID value for your compartment from the Compartments information page in the OCI console.

The compartment OCID uses this syntax:

```
OCI_COMPARTMENT=compartment_OCID
```

For details on the syntax options, see Oracle Cloud IDs (OCIDs).

Examples

```
In the tnsnames.ora file:
net_service_name=
  (DESCRIPTION=
     (ADDRESS=(PROTOCOL=tcps)(HOST=salesserver1)(PORT=1522))
     (SECURITY=
        (SSL_SERVER_DN_MATCH=TRUE)
        (SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleContext")
        (PASSWORD_AUTH=OCI_TOKEN)
        (OCI_IAM_URL=https://auth.us-region-1.example.com/v1/actions/
generateScopedAccessBearerToken)
        (OCI_TENANCY=ocid1.tenancy..12345)
        (OCI_COMPARTMENT=ocid1.compartment..12345)
        (OCI_DATABASE=ocid1.autonomousdatabase.oc1.12345))
     (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))
In the sqlnet.ora file:
SSL_SERVER_DN_MATCH=TRUE
PASSWORD_AUTH=OCI_TOKEN
OCI_IAM_URL=https://auth.us-region-1.example.com/v1/actions/
generateScopedAccessBearerToken
OCI_TENANCY=ocid1.tenancy..12345
OCI_COMPARTMENT=ocid1.compartment..12345
OCI_DATABASE=ocid1.autonomousdatabase.oc1.12345
In the Easy Connect syntax:
```

Related Topics

Oracle AI Database Security Guide

tcps:sales-svr:1521/sales.us.example.com?

SE=ocid1.autonomousdatabase.oc1.12345

- PASSWORD AUTH
- TOKEN AUTH

Use the TOKEN_AUTH parameter to configure token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) or Microsoft Azure users of Microsoft Entra ID (previously called Microsoft Azure Active Directory).

TOKEN AUTH=OCI INTERACTIVE&OCI COMPARTMENT=ocid1.compartment..12345&OCI DATABA



OCI DATABASE

Use the OCI_DATABASE parameter to specify Oracle Cloud Identifier (OCID) of the database that you want to access for the client connection.

6.10.9 OCI_CONFIG_FILE

Use the OCI_CONFIG_FILE parameter to specify the directory location where the Oracle Cloud Infrastructure (OCI) configuration file is stored.

Purpose

To specify the directory location of the OCI configuration file. This file stores the client connection information for OCI Identity and Access Management (IAM) users as part of their profile. The SDK, CLI, and other OCI tools use this file to access the IAM user credentials during IAM token-based authentication.

Usage Notes

This is an optional parameter. If you do not set this parameter, then the database client gets the user's profile from the default configuration file located at C:/user-profile/.oci/config. You can use this parameter to override the default configuration file location. In this case, the database client searches for the profile in the location specified by OCI_CONFIG_FILE.

You can use this parameter along with the <code>TOKEN_AUTH</code> parameter for the <code>OCI_API_KEY</code> and <code>OCI_INTERACTIVE</code> authentication flows:

- When using the OCI_INTERACTIVE authentication flow, if this parameter is not set and the configuration file is also not present in the default location, then Oracle Database prompts the user for a region ID, presenting a list of region IDs from which the user can choose.
- When using the OCI_API_KEY authentication flow, if this parameter is not set and the default configuration file is also not present, then an ORA-50109 error message is returned. In this case, you must set this parameter to include the configuration file location.

For JDBC-thin clients, you can specify this parameter in the Easy Connect syntax or tnsnames.ora connect string. For ODP.NET Core classes and ODP.NET Managed Driver classes, you can specify this parameter in the sqlnet.ora file, Easy Connect syntax, or tnsnames.ora connect string. The parameter value specified in the connect string takes precedence.

Default

None

Value

Full path (including a file name) to the OCI configuration file

Examples

In the tnsnames.ora file:

```
net_service_name=
   (DESCRIPTION =
          (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr)(PORT=1521))
          (SECURITY=
                (SSL_SERVER_DN_MATCH=TRUE)
                (SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleContext")
                (TOKEN AUTH=OCI INTERACTIVE)
```



```
(OCI_CONFIG_FILE=/home/dbuser1/config))
    (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))
)

In the sqlnet.ora file:

SSL_SERVER_DN_MATCH=TRUE
TOKEN_AUTH=OCI_INTERACTIVE
OCI_CONFIG_FILE=/home/dbuser1/config

In the Easy Connect string:

tcps:sales-svr:1521/sales.us.example.com?
TOKEN_AUTH=OCI_INTERACTIVE&OCI_CONFIG_FILE=/home/dbuser1/config
```

In these examples, the optional OCI_PROFILE parameter is not specified. Thus, the client automatically gets the DEFAULT profile from the specified configuration file directory.

Related Topics

- Oracle Database Security Guide
- TOKEN AUTH

Use the TOKEN_AUTH parameter to configure token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) or Microsoft Azure users of Microsoft Entra ID (previously called Microsoft Azure Active Directory).

OCI PROFILE

Use the OCI_PROFILE parameter to specify the profile name for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) users.

6.10.10 OCI DATABASE

Use the OCI_DATABASE parameter to specify Oracle Cloud Identifier (OCID) of the database that you want to access for the client connection.

Purpose

To define the scope of your database token request. The database OCID value instructs the database client to initiate a token request to the specified database within your compartment. You use this parameter while configuring token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) users on OCI Database as a Service (DBaaS).

Usage Notes

This is an optional parameter. You can set this parameter to limit the access to only a particular database. If you set <code>OCI_DATABASE</code>, then you must also provide specific compartment identifier using the <code>OCI_COMPARTMENT</code> parameter.

You can use this parameter along with the PASSWORD_AUTH and TOKEN_AUTH authentication settings:

 With the PASSWORD_AUTH configuration, the database client can only request an IAM database token using the IAM user name and IAM database password.



With the TOKEN_AUTH configuration, the database client can request an IAM database token using the API-key, delegation token, security token, resource principal, or instance principal credentials. You can also enable the database client to directly retrieve the dbtoken with IAM Single-Sign On (SSO) credentials by using the OCI_INTERACTIVE, OCI_API_KEY, OCI_INSTANCE_PRINCIPAL, OCI_DELEGATION_TOKEN, and OCI_RESOURCE_PRINCIPAL authentication flows.

Specify this parameter under the SECURITY section of the tnsnames.ora file, sqlnet.ora file, Easy Connect syntax, or directly as part of the command-line connect string. The parameter value specified in the connect string takes precedence.

Default

None

Value

OCID of the database that you want to access for the client connection. You can get the OCID value for your database from the Database details page in the OCI console.

The database OCID uses this syntax:

```
OCI_DATABASE=database_OCID
```

For details on the syntax options, see Oracle Cloud IDs (OCIDs).

Examples

```
In the tnsnames.ora file:
```

```
net service name=
  (DESCRIPTION=
     (ADDRESS=(PROTOCOL=tcps)(HOST=salesserver1)(PORT=1522))
     (SECURITY=
        (SSL SERVER DN MATCH=TRUE)
        (SSL SERVER CERT DN="C=US,O=example,CN=OracleContext")
        (PASSWORD AUTH=OCI TOKEN)
        (OCI_IAM_URL=https://auth.us-region-1.example.com/v1/actions/
generateScopedAccessBearerToken)
        (OCI_TENANCY=ocid1.tenancy..12345)
        (OCI COMPARTMENT=ocid1.compartment..12345)
        (OCI DATABASE=ocid1.autonomousdatabase.oc1.12345))
     (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))
In the sqlnet.ora file:
SSL_SERVER_DN_MATCH=TRUE
PASSWORD_AUTH=OCI_TOKEN
OCI_IAM_URL=https://auth.us-region-1.example.com/v1/actions/
generateScopedAccessBearerToken
OCI_TENANCY=ocid1.tenancy..12345
OCI_COMPARTMENT=ocid1.compartment..12345
OCI_DATABASE=ocid1.autonomousdatabase.oc1.12345
```



In the Easy Connect syntax:

tcps:sales-svr:1521/sales.us.example.com?
TOKEN_AUTH=OCI_INTERACTIVE&OCI_COMPARTMENT=ocid1.compartment..12345&OCI_DATABA
SE=ocid1.autonomousdatabase.oc1.12345

Related Topics

- Oracle AI Database Security Guide
- PASSWORD AUTH
- TOKEN AUTH

Use the TOKEN_AUTH parameter to configure token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) or Microsoft Azure users of Microsoft Entra ID (previously called Microsoft Azure Active Directory).

OCI COMPARTMENT

Use the OCI_COMPARTMENT parameter to specify Oracle Cloud Identifier (OCID) of the compartment that holds database instances for client connections.

6.10.11 OCI IAM URL

Use the OCI_IAM_URL parameter to specify an endpoint URL that the database client must connect with to get the database token for authenticating Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) users on OCI Database as a Service (DBaaS).

Purpose

To specify the IAM URL for your REST API requests. The database client connects to this URL to retrieve the database token from IAM.

Usage Notes

You set the <code>OCI_IAM_URL</code> parameter along with the <code>PASSWORD_AUTH</code> and <code>OCI_TENANCY</code> parameters while configuring IAM token-based authentication (using the IAM user name and IAM database password to retrieve the database token). These parameters are mandatory.

With this configuration, the database client can only request an IAM database token using the IAM user name and IAM database password. The client cannot request an IAM database token for an API-key, delegation token, security token, resource principal, service principal, or instance principal.

You can also set the optional OCI_COMPARTMENT and OCI_DATABASE parameters to specify the scope of your token request.

Use this parameter under the SECURITY section of the tnsnames.ora file, sqlnet.ora file, or directly as part of the command-line connect string. The parameter value specified in the connect string takes precedence over the other specified values.

Default

None



Value

OCI IAM endpoint URL that the database client must connect with to get the database token. This URL is specific to your region and uses this syntax:

<authentication_regional_endpoint>/v1/actions/generateScopedAccessBearerToken

You can derive this value by replacing *<authentication_regional_endpoint>* with the API endpoint URL for your region. To obtain the appropriate API endpoint URL, see <u>Identity and Access Management Data Plane API</u>.

For example, if you want to use the URL as https://auth.us-region-1.example.com, then your OCI IAM URL value is:

```
https://auth.us-region-1.example.com/v1/actions/generateScopedAccessBearerToken
```

Examples

```
In the tnsnames.ora file:
```

```
net service name=
  (DESCRIPTION=
     (ADDRESS=(PROTOCOL=tcps)(HOST=salesserver1)(PORT=1522))
     (SECURITY=
        (SSL_SERVER_DN_MATCH=TRUE)
        (SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleContext")
        (PASSWORD_AUTH=OCI_TOKEN)
        (OCI_IAM_URL=https://auth.us-region-1.example.com/v1/actions/
generateScopedAccessBearerToken)
        (OCI_TENANCY=ocid1.tenancy..12345))
     (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))
In the sqlnet.ora file:
SSL_SERVER_DN_MATCH=TRUE
PASSWORD AUTH=OCI TOKEN
OCI_IAM_URL=https://auth.us-region-1.example.com/v1/actions/
generateScopedAccessBearerToken
OCI_TENANCY=ocid1.tenancy..12345
```

In these examples, the optional <code>OCI_COMPARTMENT</code> and <code>OCI_DATABASE</code> parameters are not specified and thus the entire tenancy is set as the scope of the token request.

Related Topics

- Oracle Al Database Security Guide
- PASSWORD AUTH



6.10.12 OCI_PROFILE

Use the OCI_PROFILE parameter to specify the profile name for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) users.

Purpose

To specify the profile name for IAM users. This profile is the client connection information stored in the OCI configuration file, and is used during IAM token-based authentication.

Usage Notes

- This is an optional parameter. A profile named DEFAULT is already set in the configuration
 file. The database client gets the DEFAULT profile from the OCI configuration file (from either
 the default C:/user-profile/.oci/config directory location or the location specified by
 OCI_CONFIG_FILE).
- You can specify this parameter to override the DEFAULT profile set in the configuration file and assign a new profile name for the IAM user.
 - When this parameter is not set and the profile is also not present in the configuration file, then an error message appears indicating that token-based authentication has failed due to the profile not existing.
- You can use this parameter along with the TOKEN_AUTH parameter for the OCI_API_KEY and OCI_INTERACTIVE authentication flows.

For JDBC-thin clients, you can specify this parameter in the Easy Connect syntax or tnsnames.ora connect string. For ODP.NET Core classes and ODP.NET Managed Driver classes, you can specify this parameter in the sqlnet.ora file, Easy Connect syntax, or tnsnames.ora connect string. The parameter value specified in the connect string takes precedence.

Values

- DEFAULT: This means that no value is explicitly defined for a given profile, and the profile is inherited from the default profile set in the configuration file.
- profile_name: Specify a new configuration profile name (for example, ADMIN_USER) to
 override the DEFAULT profile set in the configuration file.

Default

DEFAULT

Examples

In the tnsnames.ora file:



```
(CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))
```

In the sqlnet.ora file:

```
SSL_SERVER_DN_MATCH=TRUE
TOKEN_AUTH=OCI_INTERACTIVE
OCI_CONFIG_FILE=/home/dbuser1/config
OCI_PROFILE=ADMIN_USER
```

In the Easy Connect string:

```
tcps:sales-svr:1521/sales.us.example.com?
TOKEN_AUTH=OCI_INTERACTIVE&OCI_CONFIG_FILE=/home/dbuser1/
config&OCI_PROFILE=ADMIN_USER
```

Related Topics

- Oracle Database Security Guide
- TOKEN AUTH

Use the TOKEN_AUTH parameter to configure token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) or Microsoft Azure users of Microsoft Entra ID (previously called Microsoft Azure Active Directory).

OCI_CONFIG_FILE
 Use the OCI_CONFIG_FILE parameter to specify the directory location where the Oracle
 Cloud Infrastructure (OCI) configuration file is stored.

6.10.13 OCI_TENANCY

Use the OCI_TENANCY parameter to specify Oracle Cloud Identifier (OCID) of the user's tenancy.

Purpose

To specify OCID of the user's tenancy (root compartment).

Usage Notes

You set this parameter along with the mandatory PASSWORD_AUTH and OCI_IAM_URL parameters while configuring token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) users on OCI Database as a Service (DBaaS).

With this configuration, the database client can only request an IAM database token using the IAM user name and IAM database password. The client cannot request an IAM database token for an API-key, delegation token, security token, resource principal, service principal, or instance principal.

You can also set the optional OCI_COMPARTMENT and OCI_DATABASE parameters to specify the scope of your token request. If you do not set the OCI_COMPARTMENT and OCI_DATABASE parameter values, then the entire tenancy is the scope of your token request.

Use this parameter under the SECURITY section of the tnsnames.ora file, sqlnet.ora file, or directly as part of the command-line connect string. The parameter value specified in the connect string takes precedence over the other specified values.



Default

None

Value

OCID of the user's tenancy. You can get the OCID value for your tenancy from the Tenancy information page in the OCI console.

The tenancy OCID uses this syntax:

```
OCI_TENANCY=tenancy_OCID
```

For details on the syntax options, see Oracle Cloud IDs (OCIDs).

Examples

```
In the tnsnames.ora file:
```

```
net_service_name=
  (DESCRIPTION=
     (ADDRESS=(PROTOCOL=tcps)(HOST=salesserver1)(PORT=1522))
     (SECURITY=
        (SSL_SERVER_DN_MATCH=TRUE)
        (SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleContext")
        (PASSWORD_AUTH=OCI_TOKEN)
        (OCI_IAM_URL=https://auth.us-region-1.example.com/v1/actions/
generateScopedAccessBearerToken)
        (OCI_TENANCY=ocid1.tenancy..12345))
     (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))
In the sqlnet.ora file:
SSL_SERVER_DN_MATCH=TRUE
PASSWORD AUTH=OCI TOKEN
OCI_IAM_URL=https://auth.us-region-1.example.com/v1/actions/
generateScopedAccessBearerToken
OCI_TENANCY=ocid1.tenancy..12345
```

In these examples, the optional OCI_COMPARTMENT and OCI_DATABASE parameters are not specified and thus the entire tenancy is set as the scope of the token request.

Related Topics

- Oracle AI Database Security Guide
- PASSWORD_AUTH

6.10.14 PASSWORD AUTH

Use the Password_auth parameter to configure an authentication method for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) users on OCI Database as a



Service (DBaaS). With this setting, client connections use the IAM user name and IAM database password for logging in users to the database.

Purpose

To configure either IAM database password verifier authentication or IAM token-based authentication, using the IAM user name and IAM database password for the access.

For password verifier authentication, the database server retrieves an IAM database password verifier from IAM. For token-based authentication, the database client requests a database token (db-token) from IAM.

Usage Notes

- Use this parameter under the SECURITY section of the tnsnames.ora file, sqlnet.ora file, or directly as part of the command-line connect string. The parameter value specified in the connect string takes precedence over the other specified values.
- This setting instructs the database client to either use the existing password login process
 with the database server (password verifier authentication) or to get a token with the IAM
 user name and IAM database password (token-based authentication). This IAM database
 password is different from the OCI console password. An IAM user can set this password
 from the OCI console.
 - See <u>Create an OCI IAM password to use for Autonomous Databases User Authentication</u> and Authorization.
- By default, this parameter is set to PASSWORD_VERIFIER. The
 PASSWORD_AUTH=PASSWORD_VERIFIER setting configures IAM database password verifier
 authentication. The database server retrieves an IAM database password verifier (an
 encrypted hash of password) from IAM to authenticate users.
 - When an IAM user logs in with the IAM user name and IAM database password using <code>@connect_identifier</code>, the <code>PASSWORD_AUTH=PASSWORD_VERIFIER</code> setting along with <code>@connect_identifier</code> instructs the database client to follow the existing user name and password login process with the database server.
 - You can use the PASSWORD_AUTH parameter to override the tnsnames.ora or sqlnet.ora setting by specifying a different value in the connect string.
- To configure IAM token-based authentication with the IAM user name and IAM database password, set PASSWORD_AUTH=OCI_TOKEN. The database client requests a database token (db-token) from IAM for the user to access the database.
 - This db-token obtained by the client is a bearer token with an expiration time and scope, and does not come with a private key. These tokens are transmitted over secure channels. You must use only the TCP/IP with Transport Layer Security (TLS) protocol, otherwise an error message appears indicating that non-TLS connections are disallowed.
 - When an IAM user logs in with the IAM user name and IAM database password using / @connect_identifier, the PASSWORD_AUTH=OCI_TOKEN setting along with / @connect_identifier instructs the database client to get the token directly from an OCI IAM endpoint using a REST API request. If the IAM user is mapped to a database schema (exclusively or shared), then the login is completed.

For the database client to retrieve the token from IAM, you must set additional parameters so that the database client can find the IAM endpoint along with additional meta-data. The additional parameters are OCI_IAM_URL and OCI_TENANCY along with the optional OCI_COMPARTMENT and OCI_DATABASE. These values enable the database client to make appropriate calls to the specified endpoint.



The OCI IAM URL parameter specifies the API endpoint URL that the database client must connect with. The OCI TENANCY parameter specifies the OCID (Oracle Cloud Identifier) of the user's tenancy. The optional OCI_COMPARTMENT and OCI_DATABASE parameters limit the scope of your request.

This authentication method is more secure than using a password verifier because a password verifier is considered sensitive. Also, only the database client can retrieve the database token. Applications or tools cannot pass these types of tokens through the database client API.

(i) Note

You can also use other IAM user credentials (such as API-key, security token, resource principal, service principal, instance principal, or delegation token) to get the db-token. This db-token is a proof-of-possession (PoP) token. In this case, you use a different parameter setting (TOKEN AUTH=OCI TOKEN).

Unlike the IAM database password that can only be used by the database client to retrieve the token, these credentials require an application or tool to retrieve the token. See TOKEN AUTH.

Default

PASSWORD_VERIFIER

Values and Examples

Value Example For IAM database password verifier authentication: In the tnsnames.ora file: PASSWORD AUTH=PASSWORD VERIFIER net service name= **Note**: Use of IAM user name and IAM database (DESCRIPTION = password with the IAM database password verifier is the default configuration, and you do not need to (ADDRESS=(PROTOCOL=tcps) set any additional parameters for the client. (HOST=sales-svr)(PORT=1521)) However, if PASSWORD_AUTH is set to OCI_TOKEN (SECURITY= in the client-side sqlnet.ora file, then the client (SSL SERVER DN MATCH=TRUE) tries to connect with OCI IAM to retrieve a database token using the IAM user name and IAM (SSL SERVER CERT DN="C=US,O=example,C database password. In this case, you can override N=OracleContext") this setting for a particular connection using PASSWORD_AUTH=PASSWORD_VERIFIER. (PASSWORD_AUTH=PASSWORD_VERIFIER)) (CONNECT DATA=(SERVICE NAME=sales.us. example.com))) In the sqlnet.ora file: PASSWORD_AUTH=PASSWORD_VERIFIER



Value

For IAM token-based authentication with the IAM user name and IAM database password:

PASSWORD AUTH=OCI TOKEN

Note: You must configure the TCPS protocol (PROTOCOL=tcps) and set the SSL_SERVER_DN_MATCH parameter to TRUE for token-based authentication.

Example

In the tnsnames.ora file:

```
net service name=
  (DESCRIPTION=
     (ADDRESS=(PROTOCOL=tcps)
(HOST=salesserver1)(PORT=1522))
     (SECURITY=
        (SSL_SERVER_DN_MATCH=TRUE)
(SSL_SERVER_CERT_DN="C=US,O=example,C
N=OracleContext")
        (PASSWORD_AUTH=OCI_TOKEN)
        (OCI_IAM_URL=https://auth.us-
region-1.example.com/v1/actions/
generateScopedAccessBearerToken)
(OCI_TENANCY=ocid1.tenancy..12345))
(CONNECT_DATA=(SERVICE_NAME=sales.us.
example.com))
  )
In the sqlnet.ora file:
```

SSL_SERVER_DN_MATCH=TRUE
PASSWORD_AUTH=OCI_TOKEN
OCI_IAM_URL=https://auth.usregion-1.example.com/v1/actions/
generateScopedAccessBearerToken
OCI_TENANCY=ocid1.tenancy..12345

In these examples, the optional OCI_COMPARTMENT and OCI_DATABASE parameters are not specified and thus the entire tenancy is set as the scope of the token request.

Related Topics

- Oracle AI Database Security Guide
- OCI IAM URL

Use the OCI_IAM_URL parameter to specify an endpoint URL that the database client must connect with to get the database token for authenticating Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) users on OCI Database as a Service (DBaaS).

OCI TENANCY

Use the OCI_TENANCY parameter to specify Oracle Cloud Identifier (OCID) of the user's tenancy.

OCI COMPARTMENT

Use the OCI_COMPARTMENT parameter to specify Oracle Cloud Identifier (OCID) of the compartment that holds database instances for client connections.



OCI DATABASE

Use the OCI_DATABASE parameter to specify Oracle Cloud Identifier (OCID) of the database that you want to access for the client connection.

6.10.15 REDIRECT URI

Use the REDIRECT_URI parameter to specify the redirect URI, registered for your Microsoft Entra ID client application.

Purpose

To specify the redirect URI (or reply URL), registered for your Entra ID client application. This is used for the AZURE_INTERACTIVE token-based authentication flow. This URL obtains the authorization code from the Entra authentication endpoint and determines which port to use to receive the authorization code.

Usage Notes

This is an optional parameter. If you do not specify this parameter, then it uses the default value of http://localhost, which is the most common redirect URL.

Specify this parameter only if necessary for your use case. The authorization server redirects the user to your specified address only if you have registered the redirect URI for the client application in the Azure portal, as shown in *Oracle AI Database Security Guide*.

You can specify this parameter along with the <code>TOKEN_AUTH=AZURE_INTERACTIVE</code> setting in the connect string, Easy Connect syntax, or <code>tnsnames.ora</code> file. The parameter value specified in the connect string takes precedence.

Default

The default redirect URI for all clients is:

```
http://localhost
```

Value

You can get a redirect URI value by logging in to the Azure portal. All URI values are listed as Redirect URIs on the App registrations - Authentication page of your Entra ID service.

Note that this is the value that you specified while registering your database client application with Entra ID.

Examples

In the tnsnames.ora file:



```
(CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))
```

In the Easy Connect string:

```
tcps:sales-svr:1521/sales.us.example.com?
TOKEN_AUTH=AZURE_INTERACTIVE&AZURE_DB_APP_ID_URI=https://application.example.com/123ab4cd-1a2b-1234-a12b-aa00123b2cd3&REDIRECT_URI=http://localhost:1575
```

In these examples, the CLIENT_ID and TENANT_ID parameters are not specified. CLIENT_ID and TENANT_ID are required parameters when using the thick clients (OCI and Instant Client). These parameters are optional for the JDBC-thin and ODP.NET core and managed database clients, which can automatically get these values from the Azure SDK configuration.

Related Topics

- Oracle Database Security Guide
- TOKEN AUTH

Use the TOKEN_AUTH parameter to configure token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) or Microsoft Azure users of Microsoft Entra ID (previously called Microsoft Azure Active Directory).

6.10.16 SECURITY

Use the SECURITY parameter to change the security properties of a connection.

Purpose

To change the security properties of a connection.

Usage Notes

Put this parameter under the DESCRIPTION parameter. SECURITY permits additional parameters as listed in <u>Security Section</u>.

Example



6.10.17 SEPS_WALLET_LOCATION

Use the SEPS_WALLET_LOCATION parameter to specify the wallet location for secure external password store (SEPS) and to enable the use of specified wallet for authentication.

Purpose

To specify the directory path of the client-side oracle wallet and to configure the client to use secure external password store for authentication purposes. Setting this parameter causes all CONNECT /@db_connect_string statements to use the information in the SEPS wallet at the specified location to authenticate to databases.

Usage Notes

You can set SEPS WALLET LOCATION in the sqlnet.ora file to specify a common wallet location for all connections. You can also set it in the connect string or tnsnames . ora file to specify a different wallet location for a particular connection.

Use of SEPS_WALLET_LOCATION in the connect string or thinames.ora overrides the sqlnet.ora SEPS_WALLET_LOCATION setting for the specific tnsnames.ora service.

To disable authentication using SEPS, you must unset SEPS_WALLET_LOCATION parameter. You must also unset SQLNET. WALLET OVERRIDE or set it to FALSE in sqlnet.ora file.



(i) Note

If the SEPS WALLET LOCATION parameter is set, the SQLNET. WALLET OVERRIDE parameter is ignored.

Default

None

Examples

If you created the wallet in \$ORACLE_HOME/network/admin and your Oracle home is set to/ private/ora_db, then you need to enter the following into your client sqlnet.ora file.

```
SEPS_WALLET_LOCATION=/private/ora_db/network/admin
```

You can also set this parameter under the SECURITY section of the tnsnames.ora or directly as part of the command-line connect string. The parameter value specified in the connect string take precedence over the other specified values.

```
net service name=
  (DESCRIPTION=
    (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr)(PORT=1521))
    (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))
    (SECURITY=(SEPS WALLET LOCATION=/private/ora db/network/admin)))
```

Related Topics

Oracle AI Database Security Guide



6.10.18 SSL_CERTIFICATE_ALIAS

Use the sqlnet.ora or the thing or a parameter SSL_CERTIFICATE_ALIAS to specify the certificate alias to use in Transport Layer Security (TLS) connections.

Purpose

To specify the alias that you provided when storing the client or server certificate in an Oracle Database wallet.

When encrypting TLS connections, both the database client and database server need to provide a signed certificate. You can store this certificate in an Oracle Database wallet or Microsoft Certificate Store (MCS). If there is more than one certificate that can be used, the user or application settings can specify the particular certificate to connect with. This choice can be made manually by the user via graphical user interface (GUI) or automatically by the application using a thumbprint or alias name. A thumbprint or alias name can uniquely identify the certificate.

This parameter instructs the client or server to automatically select a particular certificate using the specified alias name. Thus, the user does not need to manually select the correct client certificate from the list available in a wallet.

Usage Notes

Use this parameter in the tnsnames.ora file, sqlnet.ora file, or directly as part of the command-line connect string. The parameter values specified in the connect string take precedence over the other specified values.

orapki helps you manage certificates and wallets for Oracle Database. To get the alias name value, run the following command:

```
orapki wallet display -wallet <wallet directory> -pwd <wallet password> -complete
```

Value

Certificate alias name

Default

None

Examples

• In the tnsnames.ora file:

```
net_service_name=
   (DESCRIPTION=
        (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr)(PORT=1521))
        (SECURITY=(SSL_CERTIFICATE_ALIAS=my_cert))
    )
```

In the Easy Connect string:

tcps://salesserver:1521/sales.us.example.com?SSL_CERTIFICATE_ALIAS=my_cert



In the sqlnet.ora file:

SSL_CERTIFICATE_ALIAS=my_cert

Related Topics

Oracle Al Database Security Guide

6.10.19 SSL_CERTIFICATE_THUMBPRINT

Use the sqlnet.ora or this names.ora parameter SSL_CERTIFICATE_THUMBPRINT to specify the certificate thumbprint to use in Transport Layer Security (TLS) connections.

Purpose

To specify the thumbprint signature for an X509 certificate. These thumbprints are automatically generated for certificates.

When encrypting TLS connections, both the database client and database server need to provide a signed certificate. You can store this certificate in an Oracle Database wallet or Microsoft Certificate Store (MCS). If there is more than one certificate that can be used, the user or application settings can specify the particular certificate to connect with. This choice can be made manually by the user via graphical user interface (GUI) or automatically by the application using a thumbprint or alias name. A thumbprint or alias name can uniquely identify the certificate.

This parameter instructs the client or server to automatically select a particular certificate using the specified thumbprint. Thus, the user does not need to manually select the correct certificate from the list available in a certificate store.

Usage Notes

Use this parameter in the tnsnames.ora file, sqlnet.ora file, or directly as part of the command-line connect string. The parameter values specified in the connect string take precedence over the other specified values.

You can specify both the SHA-1 and SHA-256 thumbprint information for the client certificate.

orapki helps you manage certificates and wallets for Oracle Database. To get the thumbprint value, run the following command:

orapki wallet display -wallet <wallet directory> -pwd <wallet password> -complete

Value

SHA-1 or SHA-256 thumbprint of the client certificate, in the <algorithm>:<Hash> format For example:

```
SHA1:1B:11:01:5A:B1:2C:20:B2:12:34:3E:04:7B:83:47:DE:70:2E:4E:11
```

SHA256:B3:8A:5B:1A:03:63:83:92:2B:5D:E1:53:61:EE:03:94:0A:56:B4:56:41:7E:41:24:41:9B:88:EB:C6:1E:11:23



or

SHA1:1B11015AB12C20B212343E047B8347DE702E4E11

SHA256:B38A5B1A036383922B5DE15361EE03940A56B456417E4124419B88EBC61E1123

Default

None

Examples

In the tnsnames.ora file:

In the Easy Connect string:

```
tcps://salesserver:1521/sales.us.example.com?
SSL CERTIFICATE THUMBPRINT=SHA1:1B11015AB12C20B212343E047B8347DE702E4E11
```

• In the sqlnet.ora file:

SSL_CERTIFICATE_THUMBPRINT=SHA256:B38A5B1A036383922B5DE15361EE03940A56B4564 17E4124419B88EBC61E1123

Related Topics

Oracle AI Database Security Guide

6.10.20 SSL CLIENT AUTHENTICATION

Use the SSL_CLIENT_AUTHENTICATION parameter to specify whether the database client is authenticated using Transport Layer Security (TLS).

Purpose

To enable client authentication in a TLS connection. The connection can be one-way or two-way (mutual TLS or mTLS).



Usage Notes

When set to TRUE, a two-way TLS connection is initiated. Both the client and server (including the listener) authenticate each other. For example, if you set this parameter to TRUE in the server configuration (server-side sqlnet.ora), then the server attempts to authenticate the client. If you set it to TRUE in the listener configuration (listener.ora), then the listener attempts to authenticate the client.

When set to FALSE, only the client authenticates the server and listener as a one-way TLS connection. For example, if you set this parameter to FALSE in the server configuration, then the server does not authenticate the client. If you set it to FALSE in the listener configuration, then the listener does not authenticate the client.

When set to OPTIONAL, the server behaves as follows:

- If the client sends a certificate, then the connection is completed as a two-way TLS connection after authenticating the client.
- If the client does not send a certificate, then the connection is completed as a one-way TLS connection.

Ensure that this parameter setting is consistent for the server or listener (on one side) and the client (on the other). Otherwise, the connection may fail. For example, if you enable client authentication in the server or listener configuration, then you must enable it in the client configuration.

Default

TRUE

Values

- TRUE | ON | YES | 1: To enable mTLS
- FALSE | OFF | NO | 0: To enable one-way TLS
- OPTIONAL: To enable both TLS and mTLS

Example

SSL_CLIENT_AUTHENTICATION=FALSE

Related Topics

Oracle Al Database Security Guide

6.10.21 SSL DISABLE WEAK EC CURVES

Use the SSL_DISABLE_WEAK_EC_CURVES parameter to disable the use of weak Elliptic Curve Cryptography (ECC) curves.

Purpose

To disable the use of weak ECC curves with key length less than 256 bits. You can set this parameter in the database server (sqlnet.ora), client (sqlnet.ora or tnsnames.ora connect string), or the listener (listener.ora).



Usage Notes

The Oracle Net Services parameter SSL_DISABLE_WEAK_EC_CURVES is deprecated in Oracle AI Database 26ai.

Elliptic Curve Cryptography (ECC) features in Oracle Net Services, such as those used for secure external password stores, have some curves disabled by default. Oracle and other major vendors disable weak elliptic curves by default to protect systems from known cryptographic vulnerabilities, and to enforce modern security standards. These older, weaker curves can be susceptible to a variety of attacks and may present security risks if used. Because Oracle no longer has ECC curves with key length less than 256 bit enabled, this parameter no longer serves a purpose, and will be removed in a future release. Oracle strongly recommends that you review your configurations to ensure that you follow security best practices.

(i) Note

SSL_DISABLE_WEAK_EC_CURVES is deprecated in favor of TLS_KEY_EXCHANGE_GROUPS parameter starting with Oracle AI Database 26ai.

By default, this parameter is set to FALSE to enable the use of all ECC curves. If you want to enable the use of only Oracle approved curves with ECC curve key size of 256 bits or higher, then set this parameter to TRUE.

When set to TRUE, you can use only the following ECC curves:

- secp256r1
- secp384r1
- secp521r1
- x25519

Values

- TRUE | ON | YES | 1: To enable only the Oracle approved ECC curves with minimum ECC curve key length of 256 bits
- FALSE | OFF | NO | 0: To enable all ECC curves

Default

FALSE

Examples

In the tnsnames.ora file:

```
net_service_name=
  (DESCRIPTION=
      (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr)(PORT=1521))
      (SECURITY=(SSL_DISABLE_WEAK_EC_CURVES=TRUE))
)
```



In the sqlnet.ora file or the listener.ora file:

```
SSL_DISABLE_WEAK_EC_CURVES=TRUE
```

Related Topics

TLS KEY EXCHANGE GROUPS

Use the TLS_KEY_EXCHANGE_GROUPS parameter to enable or disable post-quantum cryptographic (PQC) ML-KEM algorithms and classical ECDHE groups for TLS connections.

6.10.22 SSL SERVER CERT DN

Use the SSL_SERVER_CERT_DN parameter to specify the distinguished name (DN) of the database server.

Purpose

To specify the DN of the database server for DN matching. DN matching adds another clientside check on the listener and server certificates to ensure that the certificates are the correct ones that the client expects.

Usage Notes

- Set this parameter in the tnsnames.ora file or connect string to enforce full DN matching. For partial DN matching, do not include this parameter.
- The value in the SSL_SERVER_CERT_DN parameter is matched to the full DN in the listener and server certificates only when the SSL_SERVER_DN MATCH parameter is set to ON.
 - The client must know the server DN ahead of time to specify the value in SSL_SERVER_CERT_DN. The client uses SSL_SERVER_CERT_DN to check the certificate DN for both the listener and database server that the client wants to connect to.
- Oracle recommends that you use the same certificate for both the listener and server. If you use different certificates with different DNs for the listener and server, then full DN matching fails. In this case, you need to get new certificates with the same DN (for full DN matching) or you need to change your DN matching strategy.
- Starting with Oracle AI Database 26ai, the DN matching behavior is enhanced for better security. Full DN matching checks the complete DN in SSL_SERVER_CERT_DN against the DN in both the listener and server certificates. In earlier releases, full DN matching checked the complete DN only in the server certificate.

If you want to revert to the earlier weaker DN matching behavior (that is, checking only the server certificate), then set SSL_ALLOW_WEAK_DN_MATCH=TRUE. However, note that the SSL_ALLOW_WEAK_DN_MATCH parameter is deprecated and will be removed in a future release. Oracle recommends that you get new certificates or change your DN matching strategy.

Value

Database server DN

Example

```
finance=
  (DESCRIPTION=
     (ADDRESS_LIST=
          (ADDRESS=(PROTOCOL = tcps) (HOST = finance)
```



```
(PORT = 1575)))
(CONNECT_DATA=
  (SERVICE_NAME=finance.us.example.com))
(SECURITY=
  (SSL_SERVER_CERT_DN="cn=finance,cn=OracleContext,c=us,o=example")))
```

Related Topics

SSL SERVER DN MATCH

Use the SSL_SERVER_DN_MATCH parameter to enforce server-side certificate validation through distinguished name (DN) matching.

SSL ALLOW WEAK DN MATCH

Use the sqlnet.ora parameter SSL_ALLOW_WEAK_DN_MATCH to allow the earlier weaker distinguished name (DN) matching behavior during server-side certificate validation.

Oracle AI Database Security Guide

6.10.23 SSL SERVER DN MATCH

Use the SSL_SERVER_DN_MATCH parameter to enforce server-side certificate validation through distinguished name (DN) matching.

Purpose

To enforce server-side certificate validation through DN matching.

The purpose of adding this DN matching parameter for the client is to further improve security on a Transport Layer Security (TLS) connection. A TLS connection relies on the client to verify if the database server certificate is valid and signed by a trusted root certificate. The listener and server certificate DN matching adds another client-side check on the listener and server certificates to ensure that the certificates are the correct ones that the client expects.

Usage Notes

- If you set this parameter to TRUE, then in addition to verifying the server's certificate chain, the client enforces another check against the listener and server through DN matching.
- You can configure either partial DN matching or full DN matching.

Through partial DN matching, the client checks the HOST parameter (in the client sqlnet.ora file or connect string) against a host name in the certificate DN or certificate Subject Alternative Name (SAN) field. The client checks HOST against both the listener and server certificates in this order:

 The client first compares HOST with a host name in the listener certificate's DN. For example, CN part of DN:

```
"c=us,o=examplecorporation,cn=sales.us.example.com"
```

2. If no match is found in the listener certificate's DN, then the client compares HOST with a host name in the listener certificate's SAN field. For example:

```
"DNS:sales.us.example.com"
```

If no match is found in the listener certificate's SAN field, then the client does not try connecting to the server and the connection fails.



- 3. If the listener certificate check succeeds, then the client performs similar checks on the server certificate. That is, the client first compares HOST with a host name in the server certificate's DN.
- 4. If no match is found in the server certificate's DN, then the client compares HOST with a host name in the server certificate's SAN field.

Through full DN matching, the client checks the complete DN in SSL_SERVER_CERT_DN against the certificate DN of both the listener and server certificates. To enforce a full DN match, specify the complete DN using the SSL_SERVER_CERT_DN parameter in the tnsnames.ora file or connect string.

- Oracle recommends that you use the same certificate for both the listener and server.
 - If you use different certificates with different DNs for the listener and server, then full DN matching fails. In this case, you need to get new certificates with the same DN (for full DN matching) or you need to change your DN matching strategy. If you have configured partial DN matching, then it may also fail if ${\tt HOST}$ is not found in the certificate DN or SAN fields of both the listener and server certificates.
- Prior to Oracle AI Database 26ai, partial DN matching checked against host name and SAN only in the server certificate. If a match was not found, then along with the host name and SAN, it also checked the SERVICE_NAME parameter. Similarly, full DN matching checked against the complete DN only in the server certificate.

If you want to revert to the earlier weaker DN matching behavior (that is, checking only the server certificate and allowing a service name check for partial DN matching), then set SSL_ALLOW_WEAK_DN_MATCH=TRUE. However, note that the SSL_ALLOW_WEAK_DN_MATCH parameter is deprecated and will be removed in a future release. Oracle recommends that you get new certificates or change your DN matching strategy.

Default

NO

Values

YES | ON | TRUE | 1:

To enforce partial or full DN matching. If the DN matches the host name or SAN in both the listener and server certificates, then the connection succeeds. If the DN does not match the host name or SAN in the server or listener certificate, then the connection fails.

NO | OFF | FALSE | 0:

To not enforce DN matching. If the DN does not match the host name or SAN in the sever or listener certificate, then the connection is successful, but an error is logged to the sqlnet.log file.

Example

SSL_SERVER_DN_MATCH=YES

Related Topics

SSL SERVER CERT DN

Use the $SSL_SERVER_CERT_DN$ parameter to specify the distinguished name (DN) of the database server.

SSL ALLOW WEAK DN MATCH

Use the sqlnet.ora parameter SSL_ALLOW_WEAK_DN_MATCH to allow the earlier weaker distinguished name (DN) matching behavior during server-side certificate validation.



Oracle Al Database Security Guide

6.10.24 SSL_VERSION

Use the SSL_VERSION parameter to define valid Transport Layer Security (TLS) versions to be used for connections.

Purpose

To define the version of TLS that must run on the systems with which the database server communicates. By default, the database server and client negotiate the strongest security protocol. Oracle does not recommend modifying this parameter, unless your security requirements mandate the usage of certain protocol versions.

Usage Notes

- Clients, listeners, and database servers must use compatible versions. Modify this
 parameter only when necessary to enforce the use of the more secure TLS protocol and
 not allow clients that only work with the older TLS protocols. The current default uses TLS
 1.3, which is the version required for multiple security compliance requirements. If you
 need to specify TLS 1.2, then also include TLS 1.3 to allow more secure connections.
- In addition to sqlnet.ora, listener.ora, and cman.ora, you can specify this parameter
 under the SECURITY section of the the section of the connect string. The
 parameter value specified in the connect string takes precedence over the other specified
 values.
- Starting with Oracle AI Database 26ai, the use of Transport Layer Security protocol versions 1.0 and 1.1 are desupported.
 - In most cases, this change will not have any impact, because the database client and server will negotiate the use of the most secure protocol and cipher algorithm. However, if TLS 1.0 or 1.1 has been specified, then you must either remove it to allow the database server and client to pick the most secure protocol, or you must specify either TLS 1.2, or TLS 1.3, or both, for the protocol. Oracle recommends using the latest, most secure protocol. That protocol is TLS 1.3, which is introduced with Oracle AI Database 26ai.
- Starting with Oracle AI Database 26ai, the Secure Socket Layer v3 protocol (SSLv3) is no longer supported for database server-client connections, and the sqlnet.ora parameter ADD SSLV3 TO DEFAULT has been removed.
 - SSLv3 is a much less secure protocol to secure the database server-to-client connection. Instead of using SSLv3, allow the database server and client to negotiate the most secure protocol that is common between the server and the client. Oracle AI Database 26ai provides TLS 1.2 and TLS 1.3 protocols for certificate-based network encryption.
- If you set SSL_VERSION to undetermined, then the most secure TLS protocol version is used. You can also use the SSL_VERSION=undetermined setting in the connect string for a specific connection to override the SSL_VERSION value configured in the sqlnet.ora, listener.ora, Or cman.ora file.
- If you do not set SSL_VERSION to any value, then all the supported TLS protocol versions are tried starting with the most secure version. This is typically the most common configuration, ensuring that the strongest protocol is chosen during TLS negotiation.

Values

undetermined | TLSv1.2 | TLSv1.3



Default

undetermined

Syntax and Examples

To specify a single protocol version:

```
SSL_VERSION=TLS_protocol_version
```

For example:

```
SSL_VERSION=TLSv1.3
```

 To specify multiple protocol versions, use a comma-separated string of values, enclosed in parenthesis:

```
SSL VERSION=(TLS protocol version1,TLS protocol version2)
```

For example:

```
SSL_VERSION=(TLSv1.2,TLSv1.3)
```

Note

Do not enclose protocol versions in parenthesis while specifying this parameter in the tnsnames.ora file or as part of the connect string, otherwise the setting will not parse correctly. For example:

```
net_service_name=
  (DESCRIPTION=
         (ADDRESS=(PROTOCOL=tcps)(HOST=salesserver)(PORT=1522))
         (SECURITY=(SSL_VERSION=TLSv1.2,TLSv1.3))
)
```

Related Topics

- Set the Required TLS Version on the Server
- Set the Required TLS Version on the Client

6.10.25 TENANT_ID

Use the TENANT_ID parameter to specify the ID of your Microsoft Entra ID tenant.

Purpose

To specify the ID of the Entra ID tenant in which your Entra ID application is registered. This is the Azure tenancy ID that uniquely identifies your database instance in Entra ID.



Usage Notes

- You use this parameter along with the TOKEN_AUTH parameter for the AZURE_INTERACTIVE,
 AZURE_SERVICE_PRINCIPAL, AZURE_MANAGED_IDENTITY, and AZURE_DEVICE_CODE token based authentication flows.
- This parameter is mandatory for the thick clients (OCI and Instant Client). It is optional
 when using the JDBC-thin clients and ODP.NET core and managed database clients.
 - When using the JDBC-thin clients and ODP.NET core and managed database clients, if you have configured the Azure SDKs, then the client driver automatically searches for the tenant ID in the SDK configuration. If you have not configured the SDKs, then you must set this parameter.
 - When using the OCI and Instant Clients (which do not use the Azure SDKs), you must set this parameter (along with other required parameters, such as <code>CLIENT_ID</code>). Otherwise, an error message appears prompting you to configure the required parameters.
- For the JDBC-thin clients, you can specify this parameter in the connect string, Easy Connect syntax, tnsnames.ora file, or properties. For the thick clients (OCI and Instant Client) and ODP.NET core and managed database clients, you can specify this parameter in the connect string, sqlnet.ora file, Easy Connect syntax, or tnsnames.ora file. The parameter value specified in the connect string takes precedence.

Default

None

Value

You can get the tenant ID value by logging in to the Azure portal. This is listed as Tenant ID on the Tenant Properties page.

Examples

```
In the tnsnames.ora file:
```

AZURE DB APP ID URI=https://application.example.com/123ab4cd-1a2b-1234-a12b-

aa00123b2cd3



TENANT_ID=1a123ab1-a1b1-1a2b-a1b2-a12bcdab0123
REDIRECT URI=http://localhost:1575

In the Easy Connect string:

tcps:sales-svr:1521/sales.us.example.com?
TOKEN_AUTH=AZURE_INTERACTIVE&AZURE_DB_APP_ID_URI=https://application.example.com/123ab4cd-1a2b-1234-a12b-aa00123b2cd3&TENANT_ID=1a123ab1-a1b1-1a2b-a1b2-a12bcdab0123&REDIRECT_URI=http://localhost:1575

In these examples, the CLIENT_ID parameter is not specified. CLIENT_ID is required when using the thick clients (OCI and Instant Client). This parameter is optional for the JDBC-thin and ODP.NET core and managed database clients, which can automatically get this value from the Azure SDK configuration.

Related Topics

- Oracle Database Security Guide
- TOKEN AUTH

Use the TOKEN_AUTH parameter to configure token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) or Microsoft Azure users of Microsoft Entra ID (previously called Microsoft Azure Active Directory).

6.10.26 TOKEN AUTH

Use the TOKEN_AUTH parameter to configure token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) or Microsoft Azure users of Microsoft Entra ID (previously called Microsoft Azure Active Directory).

Purpose

Token-based access enforces strong authentication, which enables a more secure access to the database. IAM users can connect to OCI Database as a Service (DBaaS) databases, and Azure users can connect to Oracle Databases (cloud or on-premises).

With this setting, when a / (slash) login is used, the Oracle Database client either looks for a token file or directly gets the token using single-sign on (SSO) credentials.

Use this parameter under the SECURITY section of the tnsnames.ora file, sqlnet.ora file, or directly as part of the command-line connect string. The parameter value specified in the connect string takes precedence over the other specified values.

Usage Notes for IAM

OCI IAM token:

An OCI IAM token (db-token), which is obtained from IAM using Oracle Cloud Infrastructure (OCI) Command Line Interface (CLI) or programmatically from the OCI Software Development Kit (SDK), is a proof-of-possession (PoP) token with an expiration time and scope.

You can use one of the IAM user credentials, such as API-key, security token, resource principal, instance principal, or delegation token to retrieve the db-token and private key from IAM.



These tokens are transmitted over secure channels. You must use only the TCP/IP with Transport Layer Security (TLS) protocol, otherwise an error message appears indicating that non-TLS connections are disallowed.

· Required setting for token-based authentication:

You must configure the TCPS protocol (PROTOCOL=tcps) and set the SSL_SERVER_DN_MATCH parameter to TRUE for token-based authentication.

Use a file location to send the token to Oracle Database:

When an IAM user logs in using <code>/@connect_identifier</code> (and <code>TOKEN_AUTH</code> is set to <code>OCI_TOKEN</code>), the <code>TOKEN_AUTH=OCI_TOKEN</code> setting along with <code>/@connect_identifier</code> instructs the database client to get the <code>db-token</code> and private key from either the default directory or the location specified by <code>TOKEN_LOCATION</code>.

Use the client API to send the token to Oracle Database:

If your client application is updated to retrieve tokens from IAM, then you can override the <code>TOKEN_AUTH=OCI_TOKEN</code> setting. The client application gets the <code>db-token</code> and private key from IAM and sends as attributes to the database client using the client API. In this case, you do not need to specify the <code>TOKEN_AUTH</code> and <code>TOKEN_LOCATION</code> parameters.

General IAM token-based authentication process:

 An IAM user or application in OCI first requests the db-token from IAM by using APIkey, security token, resource principal, service principal, instance principal, or delegation token (delegation token is available only in the Cloud Shell).

To use a security token, you need to generate it by completing the browser authentication process and then request the db-token using that security token. If the IAM policy that authorizes you to be issued the db-token exists, then the db-token is returned.

You request the db-token using OCI CLI (or OCI SDK for applications). For example, run the following OCI CLI command to request the db-token by using an API-key (apikey):

```
$ oci iam db-token get --profile scott
```

The profile option specifies the profile for which you want to access the IAM user credentials and retrieve the db-token.

For more information on using OCI CLI, see the get command details in <u>Oracle Cloud</u> <u>Infrastructure CLI Command Reference</u>.

- 2. OCI CLI references the config file (that stores your IAM user credentials as part of the profile) and makes a call to IAM to get the db-token. The db-token and private key files are written at the default or specified token location.
- 3. You can specify the TOKEN_LOCATION parameter to override the default directory where the db-token and private key files are stored.

The database client gets the <code>db-token</code> and private key from the default token location or the location specified by <code>TOKEN_LOCATION</code>, signs the <code>db-token</code> with the private key and sends it to the database server. The database server verifies the <code>db-token</code> and gets the group membership information for the user. If the IAM user is mapped to a database schema (exclusively or shared), then the login is completed.

Use an Oracle Database client to directly send the token to Oracle Database:

This feature is available in environments that use the JDBC-thin clients and ODP.NET core and managed database clients. For the JDBC-thin clients, you can set this in the



tnsnames.ora or Easy Connect connect string. For the ODP.NET core and managed database clients, you can set this in the sqlnet.ora, tnsnames.ora, or Easy Connect connect string. The parameter value specified in the connect string takes precedence.

To configure this feature for the JDBC-thin clients, see *Oracle Database JDBC Developer's Guide* and for the ODP.NET clients, see *Oracle Data Provider for .NET Developer's Guide*.

The following authentication flows enable the database client to directly retrieve the db-token with IAM SSO credentials:

OCI Interactive:

TOKEN_AUTH=OCI_INTERACTIVE specifies the OCI Interactive flow. This authenticates the token request interactively using a web browser, and is useful for client-side web applications or desktop applications.

The database client gets a default profile (named DEFAULT) from the OCI configuration file, which is stored either in the default directory or at the location specified by the OCI_CONFIG_FILE parameter. After validating the user's region against a list of valid regions, the client launches an authentication request to the user in a web browser, prompting to log in using the IAM user name and password along with any additional factors required by IAM.

Optionally, you can override the DEFAULT profile set in the configuration file by specifying the OCI_PROFILE parameter.

OCI API Key:

TOKEN_AUTH=OCI_API_KEY specifies the OCI API Key flow. This authenticates the token request with IAM using an IAM-recognized API-key.

The database client reads the file system location of the API-key from the user's DEFAULT profile in the OCI configuration file, from either the default configuration file directory or the location specified by OCI_CONFIG_FILE.

Optionally, you can override the user's DEFAULT profile set in the configuration file by specifying the OCI_PROFILE parameter.

OCI Instance Principal:

TOKEN_AUTH=OCI_INSTANCE_PRINCIPAL specifies the OCI Instance Principal flow. This authenticates the token request with IAM as an OCI instance principal for applications running on OCI compute instances.

OCI Delegation Token:

TOKEN_AUTH=OCI_DELEGATION_TOKEN specifies the OCI Delegation Token flow. This authenticates the token request with IAM using a delegation token for applications running in an OCI Cloud Shell.

OCI Resource Principal:

TOKEN_AUTH=OCI_RESOURCE_PRINCIPAL specifies the OCI Resource Principal flow. This authenticates the token request with IAM as an OCI resource principal for applications running in a container (as an OCI function).

Default:

TOKEN_AUTH=OCI_DEFAULT specifies the Default flow. With this setting, the client driver reads the predefined environment variables from the SDK configuration, evaluates each authentication flow in a sequence, and then assigns the most appropriate flow based on the environment where the application is running.

Sequence in which the driver evaluates each authentication flow with OCI_DEFAULT:



- 1. OCI API Key: The driver first checks if a configuration file is present at the location specified by the OCI_CONFIG_FILE parameter or at the default location (\$HOME/.oci/config). The driver then checks if the file contains a profile matching the name configured by the OCI_PROFILE parameter or the default name (DEFAULT). Finally, the driver checks if the profile is configured with an entry named key_file. If all of these checks succeed, then authentication with an API key is used. If any of these checks fail, then the driver proceeds to the next step.
- 2. OCI Delegation Token: The driver first checks if the OCI_CONFIG_FILE environment variable is set. The driver then checks if a file is present at the location configured by the OCI_CONFIG_FILE environment variable. The driver then checks if the file contains a profile named DEFAULT. Finally, the driver checks if the profile is configured with an entry named delegation_token_file. If all of these checks succeed, then authentication with a delegation token is used. If any of these checks fail, then the driver proceeds to the next step.
- 3. OCI Resource Principal: The driver first checks if the OCI_RESOURCE_PRINCIPAL_VERSION environment variable is set. The driver then checks if the variable is set to version 2.2 or 1.1. If the variable is set to 2.2, the driver then checks if the OCI_RESOURCE_PRINCIPAL_PRIVATE_PEM, OCI_RESOURCE_PRINCIPAL_RPST, and OCI_RESOURCE_PRINCIPAL_REGION environment variables are also set. Otherwise, if the variable is set to 1.1, then the driver checks if the OCI_RESOURCE_PRINCIPAL_RPT_ENDPOINT environment variable is also set. If the required variables for a version are set, then authentication as a resource principal is used. If any variable is not set, then the driver proceeds to the next step.
- 4. OCI Instance Principal: The driver requests a certificate from the instance metadata service. The base URL of the service is http:// 169.254.169.254/opc/v2/. However, a fallback URL of http:// 169.254.169.254/opc/v1/ is used if the v2 service request fails. If a request to the v2 or v1 service succeeds, then authentication as an instance principal is used. If the request fails, then the driver proceeds to the next step.
- The driver reports an error indicating that authentication is not possible using any of the authentication flows.

You also need to specify the OCI_DATABASE and OCI_COMPARTMENT parameters for all these authentication flows, if the OCI database token policy limits you to access only a particular database or databases within a compartment.

Note

You can also use another IAM credential, IAM database password, to request the dbtoken from IAM. This db-token is a bearer token and does not come with a private key. You can configure the database client to request this token using your IAM user name and IAM database password. An application cannot pass this type of db-token to the client. In this case, you use a different parameter setting (PASSWORD_AUTH=OCI_TOKEN).

Unlike the API-key, security token, resource principal, service principal, instance principal, and delegation token that require an application or tool to get a token, the IAM database password can only be used by the database client to retrieve the token. See PASSWORD AUTH.



Default Setting for IAM

None

Table 6-1 Values and Examples for IAM

Value	Example
TOKEN_AUTH=OCI_TOKEN	In the tnsnames.ora file:
	<pre>net_service_name= (DESCRIPTION = (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr) (PORT=1521)) (SECURITY= (SSL_SERVER_DN_MATCH=TRUE)</pre>
	<pre>(SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleCont ext")</pre>
	<pre>(CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))</pre>
	In the sqlnet.ora file:
	SSL_SERVER_DN_MATCH=TRUE TOKEN_AUTH=OCI_TOKEN
	In these examples, the optional TOKEN_LOCATION parameter is not specified. Thus, the client automatically gets the db-token and private key from the default token location.



Table 6-1 (Cont.) Values and Examples for IAM

Value	Example
TOKEN_AUTH=OCI_INTERACTIVE	In the tnsnames.ora file:
	<pre>net_service_name= (DESCRIPTION = (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr) (PORT=1521)) (SECURITY= (SSL_SERVER_DN_MATCH=TRUE)</pre>
	<pre>(SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleCont ext")</pre>
	<pre>(CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))</pre>
	In the sqlnet.ora file:
	SSL_SERVER_DN_MATCH=TRUE TOKEN_AUTH=OCI_INTERACTIVE
	In these examples, the optional OCI_CONFIG and OCI_PROFILE parameters are not specified. Thus, the client automatically gets the DEFAULT profile from the default configuration file directory.



Table 6-1 (Cont.) Values and Examples for IAM

Value	Example	
TOKEN_AUTH=OCI_API_KEY	In the tnsnames.ora file:	
	<pre>net_service_name= (DESCRIPTION = (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr) (PORT=1521)) (SECURITY= (SSL_SERVER_DN_MATCH=TRUE)</pre>	
	(SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleContext")	
	(TOKEN_AUTH=OCI_API_KEY))	
	<pre>(CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))</pre>	
	In the sqlnet.ora file:	
	SSL_SERVER_DN_MATCH=TRUE TOKEN_AUTH=OCI_API_KEY	
	In these examples, the optional OCI_CONFIG and OCI_PROFILE parameters are not specified. Thus, the client automatically gets the API-key value from the DEFAULT profile stored in the default configuration file directory.	
TOKEN_AUTH=OCI_INSTANCE_PRI NCIPAL	In the tnsnames.ora file:	
	<pre>net_service_name= (DESCRIPTION = (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr) (PORT=1521)) (SECURITY= (SSL_SERVER_DN_MATCH=TRUE)</pre>	
	(SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleCont ext")	
	(TOKEN_AUTH=OCI_INSTANCE_PRINCIPAL))	
	<pre>(CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))</pre>	
	In the sqlnet.ora file:	
	SSL_SERVER_DN_MATCH=TRUE TOKEN_AUTH=OCI_INSTANCE_PRINCIPAL	



Table 6-1 (Cont.) Values and Examples for IAM

```
Value
                             Example
TOKEN_AUTH=OCI_DELEGATION_T In the tnsnames.ora file:
                             net_service_name=
                                  (DESCRIPTION =
                                     (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr)
                             (PORT=1521))
                                     (SECURITY=
                                        (SSL_SERVER_DN_MATCH=TRUE)
                             (SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleCont
                             ext")
                                        (TOKEN_AUTH=OCI_DELEGATION_TOKEN))
                             (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com)
                             In the sqlnet.ora file:
                             SSL_SERVER_DN_MATCH=TRUE
                             TOKEN_AUTH=OCI_DELEGATION_TOKEN
TOKEN_AUTH=OCI_RESOURCE_PRI In the tnsnames.ora file:
NCIPAL
                             net service name=
                                  (DESCRIPTION =
                                     (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr)
                             (PORT=1521))
                                     (SECURITY=
                                        (SSL_SERVER_DN_MATCH=TRUE)
                             (SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleCont
                             ext")
                                        (TOKEN_AUTH=OCI_RESOURCE_PRINCIPAL))
                             (CONNECT DATA=(SERVICE NAME=sales.us.example.com)
                             In the sqlnet.ora file:
                             SSL_SERVER_DN_MATCH=TRUE
                             TOKEN_AUTH=OCI_RESOURCE_PRINCIPAL
```

Usage Notes for Entra ID

Entra ID access token:



An Entra ID OAuth2 access token is a bearer token with an expiration time and scope. This token follows the OAuth2.0 standard with Entra ID extensions. You can request these tokens from tools and scripts run on Linux, Microsoft PowerShell, or other environments. You can also request these tokens programmatically using the Microsoft SDKs.

These tokens are transmitted over secure channels. You must use only the TCP/IP with Transport Layer Security (TLS) protocol, otherwise an error message appears indicating that non-TLS connections are disallowed.

Required setting for token-based authentication:

You must configure the TCPS protocol (PROTOCOL=tcps) and set the SSL_SERVER_DN_MATCH parameter to TRUE for token-based authentication.

Use a file location to send the token to Oracle Database:

When an Azure user logs in using <code>/@connect_identifier</code> (and <code>TOKEN_AUTH</code> is set to <code>OAUTH</code>), the <code>TOKEN_AUTH=OAUTH</code> setting instructs the database client to get the access token from the directory location specified by <code>TOKEN_LOCATION</code> if the token file is named <code>token</code>. If the token file name is different from <code>token</code>, then you must use the file name along with the directory location while specifying the <code>TOKEN_LOCATION</code> parameter.

The TOKEN_LOCATION parameter is mandatory for Azure token-based authentication. The database client gets the token from this location and sends it to the database server.

Use the client API to send the token to Oracle Database:

If your client application is updated to retrieve tokens from Entra ID, then you can override the TOKEN_AUTH=OAUTH setting. Entra ID directly passes the db-token as an attribute to the database client using the client API. When the client receives this request, the client sends it to the database server.

In this case, you do no need to specify the TOKEN_AUTH and TOKEN_LOCATION parameters.

General Azure token-based authentication process:

1. An Azure user or application first requests the access token from Entra ID using one of the supported authentication flows (resource owner password credentials, authorization code, on-behalf-of (OBO) flow, or client credentials).

An Azure user can connect using any supported utility to retrieve the token and store it in a local file directory.

You can request the token from tools and scripts run on Linux, Microsoft PowerShell, or other environments. You can also request programmatically using the Microsoft SDKs.

For detailed examples on how to retrieve an Entra ID OAuth2 access token, see *Oracle AI Database Security Guide*.

2. The database client then sends the token to the database server. The database server verifies the token (using the Entra ID public key) and extracts various claims from the token, including user name, app roles, and audience. If the Entra ID principal is mapped to a database schema (exclusively or shared), then the login is completed.

Use an Oracle Database client to directly send the token to Oracle Database:

This feature is available in environments that use the JDBC-thin clients, thick clients (Oracle Call Interface (OCI) and Oracle Database Instant Client, JDBC-thick, ODP.NET unmanaged, or Python-thick), ODP.NET Core classes, or ODP.NET Managed Driver classes.

For the thick clients, only the interactive flow is supported (TOKEN_AUTH=AZURE_INTERACTIVE).



For the JDBC-thin clients, you can set this in the tnsnames.ora or Easy Connect connect string. For the thick clients and ODP.NET core and managed database clients, you can set this in the tnsnames.ora, connect string, or sqlnet.ora file (except for REDIRECT_URI and CLIENT_CERTIFICATE). The parameter value specified in the connect string takes precedence.

To configure this feature for the JDBC clients, see *Oracle Database JDBC Developer's Guide*. For the ODP.NET clients, see *Oracle Data Provider for .NET Developer's Guide*. For the OCI and Instant Clients, see *Oracle Call Interface Developer's Guide*.

The following authentication flows enable the database client to directly retrieve an access token with Azure SSO credentials:

Azure OAuth2 Interactive:

TOKEN_AUTH=AZURE_INTERACTIVE specifies the Azure OAuth2 Interactive flow. This authenticates the token request interactively using a web browser, and is useful for client-side web applications or desktop applications.

When an Azure user logs in using /@connect_identifier (and TOKEN_AUTH is set to AZURE_INTERACTIVE), the TOKEN_AUTH=AZURE_INTERACTIVE setting along with / @connect_identifier instructs the database client driver to directly get an access token from Entra ID. This is for human users who are logging in to tools (such as SQLcl) and can also open a browser window in their environment for authentication.

If the user has not already logged in, then the database client launches an authentication request to the user (either in a dialog box if the user is using a web application or as a prompt if the user is working in a command line shell), prompting to log in using the Azure user name and password. After logging in to the Azure account, the user is redirected back to the client application (to its registered redirect URI).

Optionally, you can set the REDIRECT_URI parameter if you want to override the default redirect URI value (http://localhost).

You must set the AZURE_DB_APP_ID_URI parameter to compose the authorization scope of your token request.

The CLIENT_ID and TENANT_ID parameters are optional for the JDBC-thin and ODP.NET core and managed database clients, which can automatically get these values from the Azure SDK configuration. CLIENT_ID and TENANT_ID are required parameters for the OCI and Instant Clients.

Azure Service Principal:

TOKEN_AUTH=AZURE_SERVICE_PRINCIPAL specifies the Azure Service Principal flow. This authenticates the token request as a service principal by using either a client secret or a client certificate, and is useful for server-side applications (for example, microservices or back-end apps).

You must set the $\verb"azure_db_app_id_uri"$ parameter to compose the authorization scope of your token request.

The CLIENT_ID, TENANT_ID, and CLIENT_CERTIFICATE parameters are optional for the JDBC-thin and ODP.NET core and managed database clients, which can automatically get these values from the Azure SDK configuration. CLIENT_ID and TENANT_ID are required parameters for the OCI and Instant Clients.

Azure Managed Identity:

TOKEN_AUTH=AZURE_MANAGED_IDENTITY specifies the Azure Managed Identity flow. This authenticates the token request with Entra ID as an Azure managed identity, and is useful for client-side or server-side applications hosted on Azure environments (for example, Azure App Service or Azure virtual machine).



You must set the AZURE DB APP ID URI parameter to compose the authorization scope of your token request.

You can set the CLIENT ID parameter to configure a user-assigned managed identity for authenticating the token request. This parameter is optional for the JDBC-thin and ODP.NET core and managed database clients, which can automatically get this value from the Azure SDK configuration. CLIENT ID is required for the OCI and Instant Clients.

Azure Device Code:

TOKEN AUTH-AZURE DEVICE CODE specifies the Azure Device Code flow. This authenticates the token request interactively, and is for human users or client-side applications running on platforms with limited or no browser support (for example, command line environments such as SQLcl).

The database client displays a device code and an Entra ID login URL through the standard output of the tool, and prompts the user to enter the device code, Azure user name, and Azure password on any browser-supporting device (for example, cellphone or laptop). After completing the login in a web browser, the Azure SDK returns an access token to the client. The client sends the access token to the database to authorize the database user session.

You must set the AZURE_DB_APP_ID_URI parameter to compose the authorization scope of your token request.

The CLIENT ID and TENANT ID parameters are optional for the JDBC-thin and ODP.NET core and managed database clients, which can automatically get these values from the Azure SDK configuration. CLIENT ID and TENANT ID are required parameters for the OCI and Instant Clients.

(i) Note

You must explicitly enable the Azure OAuth2 Interactive and Azure Device Code flows for your Entra ID app in the Azure portal. To do so, on the App registrations - Authentication page, under Advanced Settings, set Allow public client flows to Yes.

Default:

TOKEN AUTH-AZURE DEFAULT specifies the Default flow. With this setting, the client driver reads the predefined environment variables from the SDK configuration, evaluates each authentication flow in a sequence, and then assigns the most appropriate flow based on the environment where the application is running.

Sequence in which the driver evaluates each authentication flow with AZURE_DEFAULT:

- 1. Azure Service Principal with Client Secret Credentials: The driver checks if client ID and client secret are configured as parameters to the driver or as SDK environment variables. If both are configured, then the driver authenticates as a service principal using a client secret. Otherwise, the driver proceeds to the next step.
- 2. Azure Service Principal with Client Certificate Credentials: The driver checks if client ID and client certificate are configured as parameters to the driver or SDK environment variables. If both are configured, then the driver authenticates as a service principal using a client certificate. Otherwise, the driver proceeds to the next step.



- 3. Azure Username Credentials: The driver checks if client ID, username, and password are configured as parameters to the driver or SDK environment variables. If all are configured, then the driver authenticates as a service principal using the username and password. Otherwise, the driver proceeds to the next step.
- 4. Azure Managed Identity: The driver checks if the MSI_ENDPOINT or IDENTITY_ENDPOINT environment variable is set. If either is set, then the driver authenticates as a managed identity using the configured endpoint. If neither is set, then the driver checks if the AZURE_TENANT_ID and AZURE_FEDERATED_TOKEN_FILE environment variables are set. If both are set, then the driver authenticates as a managed identity using the configured token file. If both are not set, then the driver requests an access token from the Azure Instance Metadata Service (IMDS) endpoint. If the request succeeds, then the driver authenticates as a managed identity. Otherwise, the driver proceeds to the next step.
- 5. Visual Studio Credentials: For ODP.NET Core classes and ODP.NET Managed Driver classes, the driver additionally evaluates the Azure user through Visual Studio Credentials authentication flow. The driver checks if the TENANT_ID parameter or the AZURE_TENANT_ID environment variable is set and if the Azure user is logged in to Visual Studio. If both the checks succeed, then authentication with the Visual Studio credentials is used. Otherwise, the driver proceeds to the next step.
- The driver reports an error indicating that authentication is not possible using any of the authentication flows.

Default Setting for Entra ID

None



Table 6-2 Values and Examples for Entra ID

Value	Example
TOKEN_AUTH=OAUTH	 If the token file is named token, TOKEN_AUTH=OAUTH, and TOKEN_LOCATION="token_file_directory":
	In the tnsnames.ora file:
	<pre>net_service_name= (DESCRIPTION=</pre>
	(HOST=salesserver1)(PORT=1522)) (SECURITY= (SSL_SERVER_DN_MATCH=TRUE)
	(SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleContext")
	(TOKEN_AUTH=OAUTH)
	(TOKEN_LOCATION="/home/dbuser1/access-token"))
	<pre>(CONNECT_DATA=(SERVICE_NAME=sales.us.example.c om)))</pre>
	In the sqlnet.ora file:
	SSL_SERVER_DN_MATCH=TRUE TOKEN AUTH=OAUTH
	TOKEN_LOCATION="/home/dbuser1/access-token"
	In these examples, the token file name is token. Thus, only the directory path (/home/dbuser1/access-token) is specified. The client automatically looks for the token file in the specified path and gets the access token. • If the token file name is different from token,
	TOKEN_AUTH=OAUTH, and
	TOKEN_LOCATION="token_file_directory/
	<pre>token_filename": In the tnsnames.ora file:</pre>
	net service name=
	(DESCRIPTION=
	(ADDRESS=(PROTOCOL=tcps)
	(HOST=salesserver1)(PORT=1522))
	(SECURITY= (SSL_SERVER_DN_MATCH=TRUE)
	(SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleContext")
	(TOKEN_AUTH=OAUTH)
	(TOKEN_LOCATION="/home/dbuser1/



Table 6-2 (Cont.) Values and Examples for Entra ID

Value	Example
	<pre>access-token/mytoken"))</pre>
	<pre>(CONNECT_DATA=(SERVICE_NAME=sales.us.example.c om)))</pre>
	In the sqlnet.ora file:
	SSL_SERVER_DN_MATCH=TRUE TOKEN_AUTH=OAUTH TOKEN_LOCATION="/home/dbuser1/access-token/ mytoken"
	In these examples, the token file name is mytoken. Thus, both the file name and directory path (/home/dbuser1/access-token) are specified. The client gets the access token from the mytoken file in the specified path.



Table 6-2 (Cont.) Values and Examples for Entra ID

Value **Example** In the tnsnames.ora file: TOKEN_AUTH=AZURE_INTERACTIV net_service_name= (DESCRIPTION = (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr) (PORT=1521)) (SECURITY= (SSL_SERVER_DN_MATCH=TRUE) (SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleCont ext") (TOKEN_AUTH=AZURE_INTERACTIVE) (AZURE_DB_APP_ID_URI=https:// application.example.com/123ab4cd-1a2b-1234-a12baa00123b2cd3) (REDIRECT_URI=http://localhost:1575)) (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com) In the sqlnet.ora file: SSL SERVER DN MATCH=TRUE TOKEN_AUTH=AZURE_INTERACTIVE AZURE_DB_APP_ID_URI=https:// application.example.com/123ab4cd-1a2b-1234-a12baa00123b2cd3 REDIRECT_URI=http://localhost:1575 In these examples, the CLIENT_ID and TENANT_ID parameters are not specified. These parameters are optional for the JDBC-thin and ODP.NET core and managed database clients, which can automatically get these values from the Azure SDK configuration. The thick clients (OCI and Instant Client) must specify these parameters.



Table 6-2 (Cont.) Values and Examples for Entra ID

Value **Example** TOKEN_AUTH=AZURE_SERVICE_PR In the tnsnames.ora file: INCIPAL net_service_name= (DESCRIPTION = (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr) (PORT=1521)) (SECURITY= (SSL_SERVER_DN_MATCH=TRUE) (SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleCont ext") (TOKEN_AUTH=AZURE_SERVICE_PRINCIPAL) (AZURE_DB_APP_ID_URI=https:// application.example.com/123ab4cd-1a2b-1234-a12baa00123b2cd3)) (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com)) In the sqlnet.ora file: SSL_SERVER_DN_MATCH=TRUE TOKEN AUTH=AZURE SERVICE PRINCIPAL AZURE_DB_APP_ID_URI=https:// application.example.com/123ab4cd-1a2b-1234-a12baa00123b2cd3 In these examples, the CLIENT_ID, TENANT_ID, and CLIENT CERTIFICATE parameters are not specified. CLIENT ID and TENANT_ID are optional for the JDBC-thin and ODP.NET core and managed database clients, which can automatically get these values from the Azure SDK configuration. The thick clients (OCI and Instant Client) must specify these parameters.



Table 6-2 (Cont.) Values and Examples for Entra ID

Value **Example** TOKEN_AUTH=AZURE_MANAGED_ID In the tnsnames.ora file: net_service_name= (DESCRIPTION = (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr) (PORT=1521)) (SECURITY= (SSL_SERVER_DN_MATCH=TRUE) (SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleCont ext") (TOKEN_AUTH=AZURE_MANAGED_IDENTITY) (AZURE_DB_APP_ID_URI=https:// application.example.com/123ab4cd-1a2b-1234-a12baa00123b2cd3)) (CONNECT_DATA=(SERVICE_NAME=sales.us.example.com)) In the sqlnet.ora file: SSL_SERVER_DN_MATCH=TRUE TOKEN AUTH=AZURE MANAGED IDENTITY AZURE_DB_APP_ID_URI=https:// application.example.com/123ab4cd-1a2b-1234-a12baa00123b2cd3 In these examples, the CLIENT_ID parameter is not specified. This parameter is optional for the JDBC-thin and ODP.NET core and managed database clients, which can automatically get this value from the Azure SDK configuration. The thick clients (OCI and

Instant Client) must specify this parameter.



Table 6-2 (Cont.) Values and Examples for Entra ID

Value	Example	
TOKEN_AUTH=AZURE_DEVICE_COD E	In the tnsnames.ora file:	
	<pre>net_service_name= (DESCRIPTION = (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr) (PORT=1521)) (SECURITY= (SSL_SERVER_DN_MATCH=TRUE)</pre>	
	<pre>(SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleCont ext")</pre>	
	In the sqlnet.ora file: SSL_SERVER_DN_MATCH=TRUE TOKEN_AUTH=AZURE_DEVICE_CODE AZURE_DB_APP_ID_URI=https://	
	application.example.com/123ab4cd-1a2b-1234-a12b-aa00123b2cd3 In these examples, the CLIENT_ID and TENANT_ID parameters are not specified. These parameters are optional for the JDBC-thin and ODP.NET core and managed database clients, which can automatically get these values from the Azure SDK configuration. The thick clients (OCI and Instant Client) must specify these parameters.	

Related Topics

- Authenticating and Authorizing IAM Users for Oracle DBaaS Databases
- Authenticating and Authorizing Microsoft Azure Users for Oracle Databases
- TOKEN LOCATION

Use the TOKEN_LOCATION parameter to specify the directory location where token file is stored for token-based authentication.

OCI CONFIG FILE

Use the <code>OCI_CONFIG_FILE</code> parameter to specify the directory location where the Oracle Cloud Infrastructure (OCI) configuration file is stored.

OCI PROFILE

Use the $\texttt{OCI_PROFILE}$ parameter to specify the profile name for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) users.



OCI DATABASE

Use the OCI_DATABASE parameter to specify Oracle Cloud Identifier (OCID) of the database that you want to access for the client connection.

OCI COMPARTMENT

Use the OCI_COMPARTMENT parameter to specify Oracle Cloud Identifier (OCID) of the compartment that holds database instances for client connections.

AZURE DB APP ID URI

Use the AZURE_DB_APP_ID_URI parameter to specify the application ID URI of the Oracle Database instance, registered with Microsoft Entra ID (previously called Microsoft Azure Active Directory).

REDIRECT URI

Use the REDIRECT_URI parameter to specify the redirect URI, registered for your Microsoft Entra ID client application.

• CLIENT ID

Use the CLIENT_ID parameter to specify the ID of the database client Microsoft Entra ID app registration.

TENANT ID

Use the TENANT ID parameter to specify the ID of your Microsoft Entra ID tenant.

CLIENT CERTIFICATE

Use the CLIENT_CERTIFICATE parameter to specify the file system path to a client certificate that authenticates your database client application.

6.10.27 TOKEN_LOCATION

Use the TOKEN_LOCATION parameter to specify the directory location where token file is stored for token-based authentication.

Purpose

To specify the token file directory location. You use this parameter while configuring token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) or Microsoft Azure users of Microsoft Entra ID. The database client gets the token from this location and sends it to the database server. For Entra ID, you can also specify the token file name along with the directory location.

Use this parameter along with the TOKEN_AUTH parameter in the thinnames.ora file, sqlnet.ora file, or directly as part of the command-line connect string. The parameter values specified in the connect string take precedence over the other specified values.

Usage Notes for IAM

The TOKEN_LOCATION parameter is optional for IAM token-based authentication. You can use this parameter along with the TOKEN_AUTH parameter to override the default directory where the db-token and private key are stored. This location is used by the database client to retrieve the db-token and private key.

When an IAM user initiates a connection using <code>/@connect_identifier</code> (and <code>TOKEN_AUTH</code> is set to <code>OCI_TOKEN</code>), the database client retrieves the <code>db-token</code> and private key from either the default directory or the location specified by <code>TOKEN_LOCATION</code>. The client then signs the <code>db-token</code> using the private key and sends the <code>db-token</code> to the database server.

Default Setting for IAM

On Linux:



/home/username/.oci/db-token

On Windows:

The database client searches for the default directory in this order:

If the USERPROFILE environment variable is set, then the client searches in the USERPROFILE directory (for example, C:\Users\username).

If USERPROFILE is not set, then the client searches in HOMEDRIVE directory (for example, C:) with HOMEPATH (for example, \Users\username).

For example, the default token location directory on Windows is:

C:\Users\username\.oci\db-token

Values and Examples for IAM

Value	Example
TOKEN_LOCATION="token_file_directory"	In the tnsnames.ora file:
	<pre>net_service_name= (DESCRIPTION =</pre>
	(SECURITY=
	(SSL_SERVER_DN_MATCH=TRUE)
	<pre>(SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleContext")</pre>
	<pre>(CONNECT_DATA=(SERVICE_NAME=sales.us.example.com)))</pre>
	In the sqlnet.ora file:
	SSL_SERVER_DN_MATCH=TRUE TOKEN_AUTH=OCI_TOKEN TOKEN_LOCATION="/home/oracle/.oci/db-token"

Usage Notes for Entra ID

The TOKEN_LOCATION parameter is mandatory for Azure token-based authentication. You must use this parameter along with the TOKEN_AUTH parameter to specify the directory location where the Entra ID OAuth2 access token is stored. This location is used by the database client to get the access token.

If your token file is named token, then specify only the directory path. If the token file name is different from token, then you must use the file name along with the directory path.

When an Azure user initiates a connection using <code>/@connect_identifier</code>, the database client retrieves the access token from the location specified by <code>TOKEN_LOCATION</code> and sends the token to the database server.



Default Setting for Entra ID

None

Values and Examples for Entra ID

Value	Example
If the token file is named token:	In the tnsnames.ora file:
TOKEN_LOCATION="token_file_directory"	
	net_service_name=
	(DESCRIPTION=
	(ADDRESS=(PROTOCOL=tcps)(HOST=salesserver1)
	(PORT=1522))
	(SECURITY=
	(SSL_SERVER_DN_MATCH=TRUE)
	(SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleContext")
	(TOKEN_AUTH=OAUTH)(TOKEN_LOCATION="/home/
	dbuser1/access-token"))
	<pre>(CONNECT_DATA=(SERVICE_NAME=sales.us.example.com)))</pre>
	In the sqlnet.ora file:
	SSL SERVER DN MATCH=TRUE
	TOKEN_AUTH=OAUTH
	TOKEN_LOCATION="/home/dbuser1/access-token"
	In these examples, the token file name is token. Thus, only the directory path (/home/dbuser1/access-token) is specified. The client automatically looks for the token file in the specified path and gets the access token.



Value	Example
If the token file name is different from token:	In the tnsnames.ora file:
TOKEN_LOCATION="token_file_directory/	
token_filename"	net_service_name=
	(DESCRIPTION=
	(ADDRESS=(PROTOCOL=tcps)(HOST=salesserver1)
	(PORT=1522))
	(SECURITY=
	(SSL_SERVER_DN_MATCH=ON)
	(SSL_SERVER_CERT_DN="C=US,O=example,CN=OracleContext") (TOKEN AUTH=OAUTH)
	(TOKEN_LOCATION="/home/dbuser1/access-token/
	mytoken"))
	<pre>(CONNECT_DATA=(SERVICE_NAME=sales.us.example.com))</pre>
	In the sqlnet.ora file:
	SSL SERVER DN MATCH=TRUE
	TOKEN AUTH=OAUTH
	TOKEN_LOCATION="/home/dbuser1/access-token/mytoken"
	In these examples, the token file name is mytoken. Thus, both the file name and directory path (/home/dbuser1/access-token) are specified. The client gets the access token from the mytoken file in the specified path.

Related Topics

- Authenticating and Authorizing IAM Users for Oracle DBaaS Databases
- Authenticating and Authorizing Microsoft Azure Users for Oracle Databases
- TOKEN AUTH

Use the TOKEN_AUTH parameter to configure token-based authentication for Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) or Microsoft Azure users of Microsoft Entra ID (previously called Microsoft Azure Active Directory).

6.10.28 TLS_KEY_EXCHANGE_GROUPS

Use the TLS_KEY_EXCHANGE_GROUPS parameter to enable or disable post-quantum cryptographic (PQC) ML-KEM algorithms and classical ECDHE groups for TLS connections.

Purpose

To enable selection of classical or quantum-safe key exchange algorithms for TLS connections. You can set this parameter in the database server (sqlnet.ora), client (sqlnet.ora or tnsnames.ora connect string), or the listener (listener.ora).

Usage Notes

This parameter takes a combination of following values as a comma-separated list:



- ec: If the TLS_KEY_EXCHANGE_GROUPS value contains ec, the Oracle approved ECDHE groups secp256r1, secp384r1, secp521r1, and x25519 are enabled. This is similar to setting the deprecated parameter SSL_DISABLE_WEAK_EC_CURVES to TRUE.
- weak: If the parameter value contains weak, then all ECDHE groups are enabled including
 the weak groups that are disabled when the deprecated parameter
 SSL_DISABLE_WEAK_EC_CURVES is set to TRUE, as well as the Oracle approved ECDHE
 groups. Oracle does not recommend setting the value to weak.

Note

Some groups from the Oracle approved ECDHE list may be moved to the weak groups list in the future, and such changes would be transparent.

• ml-kem: If the TLS_KEY_EXCHANGE_GROUPS value contains ml-kem, ML-KEM TLS groups are enabled.

Note

- ML-KEM refers to the Module-Lattice-based Key Encapsulation Mechanism
 that allows secure exchange of cryptographic keys over insecure channels. It
 is a cryptographic protocol designed for quantum-safe key exchange and is
 part of the NIST Post-Quantum Cryptography (PQC) standardization process.
- ML-KEM is only valid with TLSv1.3, it does not apply to TLSv1.2.

ML-KEM negotiation can happen if both client and server support ML-KEM which is to say both client and server are DB26ai and:

- The server has TLS_KEY_EXCHANGE_GROUPS set to ml-kem and the client has the value set to ml-kem, ec or not have TLS_KEY_EXCHANGE_GROUPS set at all. In this case, the client uses ECDHE to send the key share in its initial handshake message. The server's list does not contain any key shares supported by the client. It finds the common group, which is ml-kem in this case, from the client's list and its own list and sends a retry request with its key share using ML-KEM. The client resends the key share, and the handshake proceeds with ml-kem as the negotiated group.
- The client sets TLS_KEY_EXCHANGE_GROUPS to ml-kem explicitly and the server has the value set to ec,ml-kem or ml-kem or not have TLS_KEY_EXCHANGE_GROUPS set at all. In this case, the client uses ml-kem to send the key share in its initial handshake message. The server supports this group and the handshake proceeds with ml-kem as the negotiated group.

Values

A comma-separated list of one or more of the values below:

- ec: To enable the Oracle approved ECDHE groups
- weak: To enable both the weak and Oracle approved ECDHE groups
- ml-kem: To enable the ML-KEM TLS groups

The following table shows the results of TLS negotiations based on TLS_KEY_EXCHANGE_GROUPS values from both the client and server.



Server-Side Value	Client-Side Value	Result
Not set	Not set	ECDHE
ec,ml-kem	ec,ml-kem	ECDHE
ec,ml-kem	ml-kem	ML-KEM
ml-kem	ec,ml-kem	ML-KEM
ml-kem	ml-kem	ML-KEM
ес	ес	ECDHE

ECDHE is given higher preference compared to ML-KEM. If <code>TLS_KEY_EXCHANGE_GROUPS</code> contains both <code>ml-kem</code> and <code>ec</code>, then ECDHE groups are given higher preference. The order in which the values are specified in <code>TLS_KEY_EXCHANGE_GROUPS</code> parameter does not matter.

Default

ec, weak, and ml-kem are enabled by default, in that order.

Examples

• In the tnsnames.ora file:

```
net_service_name=
  (DESCRIPTION=
        (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr)(PORT=1521))
        (SECURITY=(TLS_KEY_EXCHANGE_GROUPS=ml-kem,ec))
)
```

• In the sqlnet.ora file or the listener.ora file:

```
TLS_KEY_EXCHANGE_GROUPS=ml-kem,ec
```

Related Topics

SSL DISABLE WEAK EC CURVES

Use the SSL_DISABLE_WEAK_EC_CURVES parameter to disable the use of weak Elliptic Curve Cryptography (ECC) curves.

Oracle AI Database Security Guide

6.10.29 WALLET LOCATION

Use the WALLET_LOCATION parameter in the thin the thin file to specify different locations where Oracle wallets are stored.

Purpose

This parameter denotes a connection specific wallet. You can use this parameter when different connections need to use different wallets on the client side.

Usage Notes

 The parameter WALLET_LOCATION is deprecated for use with Oracle AI Database 26ai for the Oracle Database server. It is not deprecated for use with the Oracle Database client or listener.



For Oracle Database server, Oracle recommends that you use the WALLET_ROOT system parameter instead of using WALLET LOCATION.

 The connect string parameter MY_WALLET_DIRECTORY has been deprecated with Oracle Al Database 26ai.

Oracle recommends that you use WALLET_LOCATION in the connect string to override the sqlnet.ora WALLET_LOCATION setting. WALLET_LOCATION has been updated for connect strings so that the same parameter can be used in sqlnet.ora and in this change simplifies the parameters that you need to remember. Oracle recommends that you change your client connect strings to use WALLET_LOCATION instead of MY WALLET DIRECTORY.

Use of WALLET_LOCATION in tnsnames.ora overrides the WALLET_LOCATION in sqlnet.ora for the specific tnsnames.ora service. The tnsnames.ora WALLET_LOCATION setting enables a client connection to have distinct TLS connections that use certificates. This means that the client initiates multiple TLS connections using different TLS certificates, in the same client process.

Use this parameter if you have a single client that must rely on more than one TLS
session. An example would be for a client that requires access to multiple pluggable
databases (PDBs), each with its own identity (certificate). This feature enables you to
configure the client to connect to the correct identity for each PDB. After the configuration
is complete, multi-threaded clients are able to access more than one wallet with different
certificates in simultaneous TLS sessions.

Default

None

Examples

```
net_service_name=
 (DESCRIPTION=
   (ADDRESS LIST=
     (ADDRESS=(PROTOCOL=tcp)(HOST=sales1-svr)(PORT=1521))
     (ADDRESS=(PROTOCOL=tcp)(HOST=sales2-svr)(PORT=1521)))
   (CONNECT_DATA=
     (SERVICE_NAME=sales.us.example.com))
      (SECURITY=(wallet_location=/home/oracle/wallets/databases)))
ssl_certs1 =
    (DESCRIPTION =
       (ADDRESS=(PROTOCOL=tcps)(HOST=shobeen.us.example.com) (PORT=1750))
       (CONNECT_DATA=(SID=sales_pdb))
       (SECURITY=(WALLET_LOCATION=/oracle/wallets/certificates/sales_cert))
ssl_certs2 =
    (DESCRIPTION =
       (ADDRESS=(PROTOCOL=tcps)(HOST=shobeen.us.example.com) (PORT=1750))
       (CONNECT_DATA=(SID=marketing_pdb))
       (SECURITY=(WALLET_LOCATION=/oracle/wallets/certificates/
marketing_cert))
```



Related Topics

- Oracle AI Database Security Guide
- Oracle Al Database Net Services Reference

6.11 Timeout Parameters

The timeout section of the tnsnames.ora file provides the ability to specify timeout and retry configuration through the TNS connect string.

The following parameters can be set at the DESCRIPTION level of a connect string:

CONNECT TIMEOUT

Use the tnsnames.ora parameter CONNECT_TIMEOUT to specify the amount of time, in milliseconds, seconds, or minutes, in which clients must establish Oracle Net connections to database instances.

RETRY COUNT

Use the tnsnames.ora parameter RETRY_COUNT to specify the number of times an ADDRESS list is traversed before terminating the connection attempt.

RETRY DELAY

Use the tnsnames.ora parameter RETRY_DELAY to specify the delay between connection retries.

TRANSPORT CONNECT TIMEOUT

Use the tnsnames.ora parameter TRANSPORT_CONNECT_TIMEOUT to specify the transport connect timeout duration, in milliseconds, seconds, or minutes.

RECV TIMEOUT

Use the tnsnames.ora parameter RECV_TIMEOUT to specify the duration of time that a database client or server should wait for data from a peer after establishing a connection.

6.11.1 CONNECT_TIMEOUT

Use the thinnames.ora parameter CONNECT_TIMEOUT to specify the amount of time, in milliseconds, seconds, or minutes, in which clients must establish Oracle Net connections to database instances.

Purpose

To specify the timeout duration in ms or msec (milliseconds), sec (seconds), or min (minutes) for a client to establish an Oracle Net connection to Oracle Database.

Usage Notes

- Put this parameter under the DESCRIPTION parameter.
- In case, no unit is mentioned, the default unit is sec.

It accepts different timeouts with or without space between the value and the unit. For example:

CONNECT_TIMEOUT=10 ms

or

CONNECT TIMEOUT=10ms



 The timeout interval specified by CONNECT_TIMEOUT is a superset of the TCP connect timeout interval. It includes the time to be connected to the database instance providing the requested service, not just the duration of the TCP connection.

The timeout interval is applicable to each ADDRESS in an ADDRESS_LIST, and each IP address to which a host name is mapped.

• The CONNECT_TIMEOUT parameter is equivalent to the sqlnet.ora parameter SQLNET.OUTBOUND CONNECT TIMEOUT, and overrides it.

Examples

```
net_service_name=
  (DESCRIPTION=
    (CONNECT_TIMEOUT=10 ms)(RETRY_COUNT=3)
    (ADDRESS_LIST=
        (ADDRESS=(PROTOCOL=tcp)(HOST=sales1-svr)(PORT=1521))
        (ADDRESS=(PROTOCOL=tcp)(HOST=sales2-svr)(PORT=1521)))
        (CONNECT_DATA=
        (SERVICE NAME=sales.us.example.com)))
```

Related Topics

SQLNET.OUTBOUND CONNECT TIMEOUT

Use the sqlnet.ora parameter SQLNET.OUTBOUND_CONNECT_TIMEOUT to specify the amount of time, in milliseconds, seconds, or minutes, in which clients must establish Oracle Net connections to database instances.

6.11.2 RETRY_COUNT

Use the tnsnames.ora parameter RETRY_COUNT to specify the number of times an ADDRESS list is traversed before terminating the connection attempt.

Purpose

To specify the number of times an ADDRESS list is traversed before the connection attempt is terminated.

Usage Notes

Put this parameter under the DESCRIPTION parameter.

When a DESCRIPTION_LIST is specified, each DESCRIPTION is traversed multiple times based on the specified number of retries.

Example

```
net_service_name=
(DESCRIPTION_LIST=
(DESCRIPTION=
    (CONNECT_TIMEOUT=10)(RETRY_COUNT=3)
    (ADDRESS_LIST=
         (ADDRESS=(PROTOCOL=tcp)(HOST=sales1a-svr)(PORT=1521))
         (ADDRESS=(PROTOCOL=tcp)(HOST=sales1b-svr)(PORT=1521)))
         (CONNECT_DATA=(SERVICE_NAME=sales1.example.com)))
(DESCRIPTION=
         (CONNECT_TIMEOUT=60)(RETRY_COUNT=1)
         (ADDRESS_LIST=
               (ADDRESS=(PROTOCOL=tcp)(HOST=sales2a-svr)(PORT=1521))
               (ADDRESS=(PROTOCOL=tcp)(HOST=sales2b-svr)(PORT=1521)))
               (CONNECT_DATA=(SERVICE_NAME=sales2.us.example.com))))
```



6.11.3 RETRY_DELAY

Use the tnsnames.ora parameter RETRY_DELAY to specify the delay between connection retries.

Purpose

To specify the delay between subsequent retries for a connection in units of ms or msec (milliseconds), sec (seconds), or min (minutes). This parameter works in conjunction with the RETRY_COUNT parameter.

Usage Notes

Put this parameter under the DESCRIPTION parameter.

When a DESCRIPTION_LIST is specified, each DESCRIPTION is traversed multiple times based on the specified number of retries, and the specific delay for the description.

In case, no unit is mentioned, the default unit is sec.

You can configure it with or without space between the value and the unit. For example:

```
Or

RETRY_DELAY=800 ms

RETRY_DELAY=800ms
```

Example

Related Topics

RETRY COUNT

Use the tnsnames.ora parameter RETRY_COUNT to specify the number of times an ADDRESS list is traversed before terminating the connection attempt.



6.11.4 TRANSPORT_CONNECT_TIMEOUT

Use the tnsnames.ora parameter TRANSPORT_CONNECT_TIMEOUT to specify the transport connect timeout duration, in milliseconds, seconds, or minutes.

Purpose

To specify the transport connect timeout duration in ms or msec (milliseconds), sec (seconds), or min (minutes) for a client to establish an Oracle Net connection to Oracle Database.

Usage Notes

- This parameter is put under the DESCRIPTION parameter.
- The default value is 60 sec. In case, no unit is mentioned, the default unit is sec.

It accepts different timeouts with or without space between the value and the unit.

```
TRANSPORT_CONNECT_TIMEOUT=10 ms

Or

TRANSPORT_CONNECT_TIMEOUT=10ms
```

• The timeout interval is applicable for each ADDRESS in an ADDRESS_LIST description, and each IP address that a host name is mapped. The TRANSPORT_CONNECT_TIMEOUT parameter is equivalent to the sqlnet.ora parameter TCP.CONNECT_TIMEOUT, and overrides it.

Example

```
net_service_name =
  (DESCRIPTION=
    (TRANSPORT_CONNECT_TIMEOUT=10 ms)
  (ADDRESS_LIST=
        (ADDRESS=(PROTOCOL=tcp)(HOST=sales1-svr)(PORT=1521))
        (ADDRESS=(PROTOCOL=tcp)(HOST=sales2-svr)(PORT=1521)))
  (CONNECT_DATA=
        (SERVICE NAME=sales.us.example.com)))
```

Related Topics

TCP.CONNECT TIMEOUT

Use the sqlnet.ora parameter TCP.CONNECT_TIMEOUT to specify the amount of time in which a client must establish TCP connections to database servers.

6.11.5 RECV_TIMEOUT

Use the tnsnames.ora parameter RECV_TIMEOUT to specify the duration of time that a database client or server should wait for data from a peer after establishing a connection.

Purpose

To specify the time duration in ms or msec (milliseconds), sec (seconds), min (minutes), or hr (hours) for a database client or server to wait for data from the peer after establishing a connection. The peer must send data within the time interval that you specify.



Usage Notes

- This parameter is put under the DESCRIPTION parameter.
- If you do not specify a unit of measurement, then the default unit is sec.

It accepts time duration with or without space between the value and the unit. For example:

```
RECV_TIMEOUT=10 ms

or

RECV_TIMEOUT=10ms
```

Setting this parameter for clients ensures that receive operations are not left in a wait state indefinitely or for a long period due to server host being down, server busy state, or network connectivity issues.

If a client does not receive response data in the time specified, then the client logs ORA-12535: TNS:operation timed out and ORA-12609: TNS: Receive timeout occurred messages to the sqlnet.log file.

Default Value

None

Minimum Value

1 ms

Allowed Range

Any number greater than the minimum value of 1 ms up to 4294967295 ms.

Examples

```
net_service_name=
  (DESCRIPTION=
    (CONNECT_TIMEOUT=10ms)(RETRY_COUNT=3)(RECV_TIMEOUT=10ms)
    (ADDRESS_LIST=
       (ADDRESS=(PROTOCOL=tcp)(HOST=sales1-svr)(PORT=1521))
       (ADDRESS=(PROTOCOL=tcp)(HOST=sales2-svr)(PORT=1521)))
       (CONNECT_DATA=
       (SERVICE_NAME=sales.us.example.com)))
```

Related Topics

Oracle Al Database Net Services Administrator's Guide

6.12 Compression Parameters

The compression section of the tnsnames.ora file provides the ability to enable compression and specify compression levels. These parameters can be set at the <code>DESCRIPTION</code> level of a connect string.

COMPRESSION

The tnsnames.ora file's compression parameter enables or disables the data compression.



COMPRESSION LEVELS

The COMPRESSION_LEVELS parameter of the tnsnames.ora file specifies the compression level.

6.12.1 COMPRESSION

The tnsnames.ora file's compression parameter enables or disables the data compression.

Purpose

To enable or disable data compression.

Usage Notes

Put this parameter under the DESCRIPTION parameter.

Setting this parameter in the connect descriptor for a client overrides the SQLNET.COMPRESSION parameter in the client-side sqlnet.ora file.

Default

off

Values

- on to enable data compression.
- off to disable data compression.

Example

Related Topics

SOLNET.COMPRESSION

Use the ${\tt sqlnet.ora}$ parameter ${\tt SQLNET.COMPRESSION}$ to enable or disable data compression.

6.12.2 COMPRESSION_LEVELS

The COMPRESSION_LEVELS parameter of the tnsnames.ora file specifies the compression level.

Purpose

To specify the compression level.

Usage Notes

The compression levels are used at the time of negotiation to verify which levels are used at both ends, and select one level. Put this parameter under the DESCRIPTION parameter.



This parameter is used with the COMPRESSION parameter. Setting this parameter in the connect descriptor for a client overrides the SQLNET.COMPRESSION_LEVELS parameter in the client-side sqlnet.ora file.

Default

low

Values

- low for low CPU usage and a low compression ratio.
- high for high CPU usage and a high compression ratio.

Example

```
net_service_name=
  (DESCRIPTION=
    (COMPRESSION=on)
    (COMPRESSION_LEVELS=(LEVEL=low)(LEVEL=high))
    (ADDRESS_LIST=
         (ADDRESS=(PROTOCOL=tcp)(HOST=sales1-server)(PORT=1521))
         (ADDRESS=(PROTOCOL=tcp)(HOST=sales2-server)(PORT=1521)))
    (CONNECT_DATA=
         (SERVICE_NAME=sales.us.example.com)))
```

Related Topics

SQLNET.COMPRESSION LEVELS

Use the sqlnet.ora parameter SQLNET.COMPRESSION_LEVELS to specify the compression level.

Centralized Configuration Provider Naming Parameters

This chapter describes the parameters for configuring the Centralized Configuration Provider naming method.

- Overview of Centralized Configuration Provider Naming Parameters
 With Centralized Configuration Provider Naming, Azure App Configuration and Oracle
 Cloud Infrastructure (OCI) Object Storage provide services to centrally manage configuration data.
- Allowed Parameter Names and Values in Connect Descriptors
 These are the restrictions on the parameter names and values that can appear in the connect descriptor, when using the Centralized Configuration Provider naming method.
- Authentication Parameters for Azure App Configuration Store
 These are the authentication parameters that you specify in the connect identifier (using the option=value syntax) to access the Azure App Configuration store.
- Authentication Parameters for OCI Object Storage
 These are the authentication parameters that you specify in the connect identifier (using the option=value syntax) to access the Oracle Cloud Infrastructure (OCI) Object Storage JSON file.

7.1 Overview of Centralized Configuration Provider Naming Parameters

With Centralized Configuration Provider Naming, Azure App Configuration and Oracle Cloud Infrastructure (OCI) Object Storage provide services to centrally manage configuration data.

Instead of storing connect descriptors on the database client in a tnsnames.ora file, you can store them in a Centralized Configuration Provider. For example, if a large number of connect descriptors are stored on the client using the Local Naming method (in a tnsnames.ora file) or Easy Connect Naming method, then any modification would require an update to all those client connect descriptors. By storing connect descriptors in a Centralized Configuration Provider, you can centralize network service names and addresses in a single location, facilitating their administration (such as addition, deletion, or modification).

Optionally, you can also store database credentials (such as database user name and database password) and Oracle Call Interface parameters (such as statement_cache_size, prefetch_rows, or session_pool) in a Centralized Configuration Provider. You need to use Azure Key Vault or OCI Vault to store the database password, and then add a reference to that vault in your Centralized Configuration Provider. You can also store an Oracle wallet in Azure Key Vault or OCI Vault, and then add a reference to that vault in your Centralized Configuration Provider.

Azure App Configuration Store:

In the Azure App Configuration store, you organize connect descriptors and other details under a prefix. A Centralized Configuration Provider connect identifier takes this prefix from the Azure App Configuration endpoint and uses it to locate the connect descriptor,



database user name and password, and other Oracle Call Interface configuration parameters.

JSON File in the OCI Object Storage:

In the OCI Object Storage, you organize connect descriptors and other details in a JSON file. A Centralized Configuration Provider connect identifier refers to JSON objects with specific names for resolving connect identifiers to connect descriptors.

Note that you specify only the allowed (naming-restricted) parameters and values in connect descriptors. Also, to access your Centralized Configuration Provider, you specify the authentication method (using the AUTHENTICATION parameter) and corresponding authentication parameters in connect descriptors.

Related Topics

Oracle Al Database Net Services Administrator's Guide

7.2 Allowed Parameter Names and Values in Connect Descriptors

These are the restrictions on the parameter names and values that can appear in the connect descriptor, when using the Centralized Configuration Provider naming method.

Naming-Restricted Parameter Names

This is a list of all left-hand side naming parameters (before =) allowed in a connect_descriptor value, which you specify in the Azure App Configuration store or Oracle Cloud Infrastructure (OCI) Object Storage JSON file.

Naming-Restricted Parameter Values

For some of the naming-restricted parameter names, some values are not allowed on the right-hand side (after =).

7.2.1 Naming-Restricted Parameter Names

This is a list of all left-hand side naming parameters (before =) allowed in a connect_descriptor value, which you specify in the Azure App Configuration store or Oracle Cloud Infrastructure (OCI) Object Storage JSON file.

All parameters that can potentially access the file-system are restricted to avoid errors, especially in multitier and multitenant environments. This is because a tenant may potentially add references to a wallet of another tenant. All the parameters that may cause process-level changes or issues with unintended resource usage are also restricted.

These are the naming-restricted parameters in the <code>connect_descriptor</code> that are allowed on the left-hand side (before =).

- ADDRESS
- ADDRESS LIST
- BACKUP
- COLOCATION TAG
- COMPRESSION
- COMPRESSION_LEVELS
- CONNECT_DATA



- CONNECTION_ID_PREFIX
- CONNECT_TIMEOUT
- DELAY
- DESCRIPTION
- DESCRIPTION_LIST
- ENABLE
- EXPIRE_TIME
- FAILOVER
- FAILOVER_MODE
- GLOBAL_NAME
- HOST
- HS
- HTTPS_PROXY
- HTTPS_PROXY_PORT
- IGNORE_ANO_ENCRYPTION_FOR_TCPS
- INACTIVITY_TIMEOUT
- INCREMENT
- INSTANCE NAME
- LOAD_BALANCE
- LOB_PREFETCH_SIZE
- MAX
- MAX_LIFETIME_SESSION
- MAX_USE_SESSION
- METHOD
- MIN
- OCI
- POOL_BOUNDARY
- POOL_CONNECTION_CLASS
- POOL_NAME
- POOL_PURITY
- PORT
- PREFETCH_ROWS
- PROTOCOL
- RDB_DATABASE
- RECV_BUF_SIZE
- RECV_TIMEOUT
- RESTORE



- RETRIES
- RETRY_COUNT
- RETRY_DELAY
- SDU
- SECURITY
- SEND_BUF_SIZE
- SERVER
- SERVICE_NAME
- SERVICE_TAG
- SESSION_POOL
- SHARDING_KEY
- SID
- SSL_SERVER_CERT_DN
- SSL_SERVER_DN_MATCH
- STATEMENT_CACHE_SIZE
- SUPER_SHARDING_KEY
- TRANSPORT_CONNECT_TIMEOUT
- TYPE_OF_SERVICE
- WALLET_LOCATION

Related Topics

Oracle Al Database Net Services Administrator's Guide

7.2.2 Naming-Restricted Parameter Values

For some of the naming-restricted parameter names, some values are not allowed on the right-hand side (after =).

Note these restrictions on the values that you can specify:

Parameter	Restriction
PROTOCOL	BEQ or Fork capability is not allowed.
	The allowed values are: TCP TCPS WSS EXADIRECT
WALLET_LOCATION	Only SYSTEM is allowed. For the METHOD sub-parameter, the allowed values are: OCIVAULT AZUREVAULT BASIC PRECONNECT





To disable these naming restrictions, set the ${\tt sqlnet.ora}$ parameter or environment variable NAMES.CLOUD_NAMING_RESTRICTIONS to FALSE. The default value for this parameter is TRUE.

Related Topics

Oracle Al Database Net Services Administrator's Guide

7.3 Authentication Parameters for Azure App Configuration Store

These are the authentication parameters that you specify in the connect identifier (using the option=value syntax) to access the Azure App Configuration store.

AUTHENTICATION

Use the AUTHENTICATION parameter to specify the authentication method that you want to use for accessing the Azure App Configuration store.

AZURE CLIENT ID

Use the CLIENT_ID parameter to specify the ID of the Microsoft Entra ID application.

AZURE TENANT ID

Use the AZURE_TENANT_ID parameter to specify the tenant ID associated with the Microsoft Entra ID subscription.

AZURE CLIENT SECRET

Use the AZURE_CLIENT_SECRET parameter to specify a client secret for your Microsoft Entra ID application.

AZURE CLIENT CERTIFICATE PATH

Use the AZURE_CLIENT_CERTIFICATE_PATH parameter to specify a client certificate of the Microsoft Entra ID application.

AZURE MANAGED IDENTITY CLIENT ID

Use the AZURE_MANAGED_IDENTITY_CLIENT_ID parameter to specify a user-assigned managed identity for authentication with Microsoft Entra ID.

HTTPS_PROXY

Use the HTTPS_PROXY parameter to specify the HTTPS proxy host name when the client is behind a corporate HTTPS proxy.

HTTPS PROXY PORT

Use the HTTPS_PROXY_PORT parameter to specify the HTTPS proxy port when the client is behind a corporate HTTPS proxy.

TIMEOUT

Use the TIMEOUT parameter to specify the duration to complete each HTTP call.

7.3.1 AUTHENTICATION

Use the AUTHENTICATION parameter to specify the authentication method that you want to use for accessing the Azure App Configuration store.

Purpose

To control how the Centralized Configuration Provider component authenticates with the Azure App Configuration store.



This is an optional parameter. If you do not set authentication method, then the default setting (AUTHENTICATION=AZURE_DEFAULT) is used to provide the Azure Service Principal flow. Set this parameter only if you want to override this default flow.

Usage Notes

Specify this parameter in the connect identifier string at the command line using the option=value syntax. Depending on the specified authentication method, you must additionally set the corresponding authentication parameters in the same string as given below:

• AZURE_DEFAULT provides the default token credential authentication using the Azure Service Principal (or OAuth 2.0 Client Credential) flow.

This authenticates to Microsoft Entra ID (previously called Microsoft Azure Active Directory) as a service principal using either a client secret or an X509 client certificate assigned during App Registration.

The client driver evaluates the following credential types (if enabled) in an order:

- 1. Azure Service Principal with Client Secret Credentials:
 - a. The driver checks if the AZURE_TENANT_ID, AZURE_CLIENT_ID, and AZURE_CLIENT_SECRET parameters are set at the command line.
 - b. If the preceding parameters are not set, then it tries the AZURE_TENANT_ID, AZURE_CLIENT_ID, and AZURE_CLIENT_SECRET environment variables. If configured, then the driver authenticates as a service principal using client secret. Otherwise, the driver proceeds to the next step.
- 2. Azure Service Principal with Client Certificate Credentials:
 - a. The driver checks if the AZURE_TENANT_ID, AZURE_CLIENT_ID, and AZURE_CLIENT_CERTIFICATE_PATH parameters are set at the command line.
 - b. If the preceding parameters are not set, then it tries the AZURE_TENANT_ID, AZURE_CLIENT_ID, and AZURE_CLIENT_CERTIFICATE_PATH environment variables. If configured, then the driver authenticates as a service principal using client certificate.

Note

For both of these flows, if all the environment variables are set (that is, AZURE_TENANT_ID, AZURE_CLIENT_ID, and AZURE_CLIENT_SECRET, and AZURE_CLIENT_CERTIFICATE_PATH), then the driver first attempts AZURE_TENANT_ID, AZURE_CLIENT_ID and AZURE_SECRET_ID values.

AZURE SERVICE PRINCIPAL provides the Azure Service Principal flow.

Similar to the default flow, this authenticates the request as a service principal using either the client secret or client certificate assigned during App Registration. However, here the driver looks only at the command line parameters, as follows:

- 1. The driver first tries the AZURE_TENANT_ID, AZURE_CLIENT_ID, and AZURE_CLIENT_SECRET parameters set at the command line.
- 2. If client secret is not set, then the driver looks for client certificate by trying the AZURE_TENANT_ID, AZURE_CLIENT_ID, and AZURE_CLIENT_CERTIFICATE_PATH parameters.





(i) Note

If both the AZURE_CLIENT_SECRET and AZURE_CLIENT_CERTIFICATE_PATH parameters are set, then this flow uses client certificate for authentication.

AZURE_MANAGED_IDENTITY provides either the Azure Managed Identity flow or the Azure Managed User Identity flow.

This method works for Azure Virtual Machines, App Service, Azure Functions applications, and the Azure Cloud Shell. This attempts authentication to Entra ID using a managed identity assigned to the deployment environment.

If you want to use a "user-assigned" managed identity for authentication, then you must additionally specify the AZURE MANAGED IDENTITY CLIENT ID authentication parameter.

Values

- AZURE DEFAULT to enable the default token credential authentication flow
- AZURE SERVICE PRINCIPAL to enable authentication using client credentials set at the command line
- AZURE_MANAGED_IDENTITY to enable authentication using managed identity or managed user identity credentials

Default

AZURE_DEFAULT

Example

AUTHENTICATION=AZURE_SERVICE_PRINCIPAL

Related Topics

- Oracle Al Database Net Services Administrator's Guide
- Authentication Parameters for Azure App Configuration Store These are the authentication parameters that you specify in the connect identifier (using the option=value syntax) to access the Azure App Configuration store.

7.3.2 AZURE CLIENT ID

Use the CLIENT_ID parameter to specify the ID of the Microsoft Entra ID application.

Purpose

To specify the client ID associated with App Registration for authenticating to Entra ID.

You use this parameter for the AZURE DEFAULT and AZURE SERVICE PRINCIPAL authentication flows to access the Azure App Configuration store.

Usage Notes

Set this parameter at the command line in the connect identifier using the option=value syntax.



Default

None

Value

Client (application) ID of an App Registration in the tenant. You can get this value from the registered application essentials page in the Azure portal.

Example

AZURE_CLIENT_ID=123ab4cd-1a2b-1234-a12b-aa00123b2cd3

Related Topics

- Oracle Al Database Net Services Administrator's Guide
- AUTHENTICATION

Use the AUTHENTICATION parameter to specify the authentication method that you want to use for accessing the Azure App Configuration store.

7.3.3 AZURE TENANT ID

Use the AZURE_TENANT_ID parameter to specify the tenant ID associated with the Microsoft Entra ID subscription.

Purpose

To specify the tenant ID associated with the Entra ID subscription. Entra ID is trusted to authenticate users, services, and devices for the subscription.

You use this parameter for the AZURE_DEFAULT and AZURE_SERVICE_PRINCIPAL authentication flows to access the Azure App Configuration store.

Usage Notes

Set this parameter at the command line in the connect identifier using the <code>option=value</code> syntax.

Default

None

Value

Tenant ID associated with the Entra ID subscription. You can get this value from the Overview page under Basic information in the Azure portal.

Example

AZURE_TENANT_ID=1a123ab1-a1b1-1a2b-a1b2-a12bcdab0123

Related Topics

Oracle Al Database Net Services Administrator's Guide



AUTHENTICATION

Use the AUTHENTICATION parameter to specify the authentication method that you want to use for accessing the Azure App Configuration store.

7.3.4 AZURE CLIENT SECRET

Use the AZURE_CLIENT_SECRET parameter to specify a client secret for your Microsoft Entra ID application.

Purpose

To specify a client secret associated with App Registration for authenticating to Entra ID. This credential enables confidential applications to identify themselves to the authentication service, when receiving tokens at a web address location (using an HTTPS scheme).

You use this parameter for the AZURE_DEFAULT and AZURE_SERVICE_PRINCIPAL authentication flows to access the Azure App Configuration store.

Usage Notes

Set this parameter at the command line in the connect identifier using the <code>option=value</code> syntax.

Default

None

Value

Client secret generated during App Registration. This value appears on the Certificates and Secrets page when you create a new client secret in the Azure portal.

Example

AZURE_CLIENT_SECRET=alabcdl2abcdlabclabclabcl2a

Related Topics

- Oracle Al Database Net Services Administrator's Guide
- AUTHENTICATION

Use the AUTHENTICATION parameter to specify the authentication method that you want to use for accessing the Azure App Configuration store.

7.3.5 AZURE CLIENT CERTIFICATE PATH

Use the AZURE_CLIENT_CERTIFICATE_PATH parameter to specify a client certificate of the Microsoft Entra ID application.

Purpose

To enable authentication to Entra ID as a service principal, using an X509 certificate assigned during App Registration.

You use this parameter for the AZURE_DEFAULT and AZURE_SERVICE_PRINCIPAL authentication flows to access the Azure App Configuration store.



Usage Notes

Set this parameter at the command line in the connect identifier using the option=value syntax.

Default

None

Value

File system path to a PEM or PKCS12 certificate file including the private key. This certificate file must have a private key without password. Ensure that you protect this certificate with necessary file permissions.

Example

AZURE_CLIENT_CERTIFICATE_PATH=ORACLE_HOME/.azure/certificates/my-app.pem

Related Topics

- Oracle Al Database Net Services Administrator's Guide
- AUTHENTICATION

Use the AUTHENTICATION parameter to specify the authentication method that you want to use for accessing the Azure App Configuration store.

7.3.6 AZURE MANAGED IDENTITY CLIENT ID

Use the AZURE_MANAGED_IDENTITY_CLIENT_ID parameter to specify a user-assigned managed identity for authentication with Microsoft Entra ID.

Purpose

To specify a user-assigned managed identity if you are using the Managed User Identity authentication flow for accessing the Azure App Configuration store. This managed identity acts as a standalone Entra ID resource.

Usage Notes

Set this parameter at the command line in the connect identifier using the option=value syntax, along with the AUTHENTICATION=AZURE_MANAGED_IDENTITY setting.

For example:

sqlplus /@"config-azure://dbclient-appconfig?key=/database/hr/
&authentication=azure_managed_identity&azure_managed_identity_client_id=b1c123
4-1a12-1234-ab12-3a1a1bc12a"

Default

None

Value

Client ID for a user-assigned managed identity. You can get this value from the Managed Identities - Overview page in the Azure portal.



Example

AZURE_MANAGED_IDENTITY_CLIENT_ID=b1c1234-1a12-1234-ab12-3a1a1bc12a

Related Topics

- Oracle Al Database Net Services Administrator's Guide
- Managed Identities for Azure Resources Documentation
- AUTHENTICATION

Use the AUTHENTICATION parameter to specify the authentication method that you want to use for accessing the Azure App Configuration store.

7.3.7 HTTPS_PROXY

Use the HTTPS_PROXY parameter to specify the HTTPS proxy host name when the client is behind a corporate HTTPS proxy.

Purpose

To specify the HTTPS proxy host name for tunneling Transport Layer Security (TLS) client connections, when the client is behind a corporate HTTPS proxy.

Default

None

Value

HTTPS proxy host name

Examples

HTTPS_PROXY=www-proxy.example.com

Related Topics

Oracle Al Database Net Services Administrator's Guide

7.3.8 HTTPS_PROXY_PORT

Use the HTTPS_PROXY_PORT parameter to specify the HTTPS proxy port when the client is behind a corporate HTTPS proxy.

Purpose

To specify the HTTPS proxy port for tunneling TLS client connections, when the client is behind a corporate HTTPS proxy.

Default

None

Value

HTTPS proxy port number



Example

HTTPS_PROXY_PORT=80

Related Topics

Oracle AI Database Net Services Administrator's Guide

7.3.9 TIMEOUT

Use the TIMEOUT parameter to specify the duration to complete each HTTP call.

Purpose

To specify the duration to complete each HTTP call. Set this parameter to avoid long network delays or indefinite waiting for a server's response.

Value

Timeout on each HTTP call, in seconds

Default

None

Example

TIMEOUT=60

Related Topics

Oracle Al Database Net Services Administrator's Guide

7.4 Authentication Parameters for OCI Object Storage

These are the authentication parameters that you specify in the connect identifier (using the option=value syntax) to access the Oracle Cloud Infrastructure (OCI) Object Storage JSON file.

AUTHENTICATION

Use the AUTHENTICATION parameter to specify the authentication method that you want to use for accessing the Oracle Cloud Infrastructure (OCI) Object Storage JSON file.

OCI PROFILE

Use the OCI_PROFILE parameter to specify the profile file section name.

• OCI PROFILE PATH

Use the OCI_PROFILE_PATH parameter to override the default Oracle Cloud Infrastructure (OCI) configuration file location.

OCI TENANCY

Use the OCI_TENANCY parameter to specify the tenant ID associated with Oracle Cloud Infrastructure (OCI) subscription.

OCI USER

Use the $\mathtt{OCI_USER}$ parameter to specify the user ID associated with Oracle Cloud Infrastructure (OCI) subscription.



OCI KEY FILE

Use the OCI_KEY_FILE parameter to specify location of the Oracle Cloud Infrastructure (OCI) private key file.

OCI FINGERPRINT

Use the OCI_FINGERPRINT parameter to specify the fingerprint of the Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) profile key.

HTTPS PROXY

Use the HTTPS_PROXY parameter to specify the HTTPS proxy host name when the client is behind a corporate HTTPS proxy.

HTTPS PROXY PORT

Use the HTTPS_PROXY_PORT parameter to specify the HTTPS proxy port when the client is behind a corporate HTTPS proxy.

TIMEOUT

Use the TIMEOUT parameter to specify the duration to complete each HTTP call.

7.4.1 AUTHENTICATION

Use the AUTHENTICATION parameter to specify the authentication method that you want to use for accessing the Oracle Cloud Infrastructure (OCI) Object Storage JSON file.

Purpose

To control how the Centralized Configuration Provider component authenticates with the OCI Object Storage JSON file.

This is an optional parameter. If you do not set authentication method, then the default setting (AUTHENTICATION=OCI_DEFAULT) is used to provide the OCI API Key flow. Set this parameter only if you want to override this default flow.

Usage Notes

Specify this parameter in the connect identifier using the <code>option=value</code> syntax. Depending on the specified authentication method, you must additionally set the corresponding authentication parameters in the same string as given below:

• OCI_DEFAULT provides the default profile-based OCI authentication using the OCI API Key flow. This flow enables authentication to OCI using API key-related values.

The client driver evaluates the following credential types (if enabled) in an order:

- 1. It first checks if the OCI_TENANCY, OCI_USER, OCI_FINGERPRINT, and OCI_KEY_FILE parameters are set at the command line.
- 2. If the preceding parameters are not set, then it checks for these parameters in the OCI configuration file present at the default location (~/.oci/config) or at the location specified by the OCI_CONFIG_FILE environment variable.

The driver then checks if the file is present at the location configured by the OCI_PROFILE_PATH parameter.

Finally, the driver checks if the file contains a profile matching the name configured by the OCI_PROFILE parameter or the default name (DEFAULT).

- OCI_INSTANCE_PRINCIPAL provides the OCI Instance Principal flow. This flow enables authentication to OCI using VM instance credentials running on OCI.
- OCI_RESOURCE_PRINCIPAL provides the OCI Resource Principal flow. This flow enables authentication to OCI using OCI resource principals.



Default

OCI_DEFAULT

Values

- OCI_DEFAULT to enable the default profile-based OCI authentication using API key-related values
- OCI INSTANCE PRINCIPAL to enable authentication using VM instance credentials
- OCI_RESOURCE_PRINCIPAL to enable authentication using OCI resource principals

Example

AUTHENTICATION=OCI_RESOURCE_PRINCIPAL

Related Topics

- Oracle Al Database Net Services Administrator's Guide
- OCI SDK Authentication Methods
- Authentication Parameters for OCI Object Storage

These are the authentication parameters that you specify in the connect identifier (using the <code>option=value</code> syntax) to access the Oracle Cloud Infrastructure (OCI) Object Storage JSON file.

7.4.2 OCI PROFILE

Use the OCI_PROFILE parameter to specify the profile file section name.

Purpose

To specify the profile file section name. This profile is the client connection information stored in your Oracle Cloud Infrastructure (OCI) configuration file.

You use this parameter for the OCI API Key authentication flow to access the OCI Object Storage JSON file.

Usage Notes

Set this parameter at the command line in the connect identifier using the option=value syntax.

Default

DEFAULT

Value

Profile file section name to use for authentication to OCI.

Example

OCI_PROFILE=ADMIN_USER



Related Topics

- Oracle Cloud Infrastructure Documentation
- Oracle Al Database Net Services Administrator's Guide
- AUTHENTICATION

Use the AUTHENTICATION parameter to specify the authentication method that you want to use for accessing the Oracle Cloud Infrastructure (OCI) Object Storage JSON file.

7.4.3 OCI PROFILE PATH

Use the $OCI_PROFILE_PATH$ parameter to override the default Oracle Cloud Infrastructure (OCI) configuration file location.

Purpose

To override the default OCI configuration file location. You use this parameter for the OCI API Key authentication flow to access the OCI Object Storage JSON file.

Usage Notes

Set this parameter at the command line in the connect identifier using the option=value syntax.

If you do not set this parameter, then the client driver looks for the OCI configuration file either at the default location (~/.oci/config) or at the location specified by the OCI_CONFIG_FILE environment variable.

Default

None

Value

Full path (including a file name) to the OCI configuration file

Example

OCI_PROFILE_PATH=/app/myociprofile/config

Related Topics

- Oracle Cloud Infrastructure Documentation
- Oracle Al Database Net Services Administrator's Guide
- AUTHENTICATION

Use the AUTHENTICATION parameter to specify the authentication method that you want to use for accessing the Oracle Cloud Infrastructure (OCI) Object Storage JSON file.



7.4.4 OCI_TENANCY

Use the OCI_TENANCY parameter to specify the tenant ID associated with Oracle Cloud Infrastructure (OCI) subscription.

Purpose

To specify the tenant ID associated with OCI subscription. OCI ID is trusted to authenticate users, services, and devices for the subscription.

You use this parameter for the OCI API Key authentication flow to access the OCI Object Storage JSON file.

Usage Notes

Set this parameter at the command line in the connect identifier using the <code>option=value</code> syntax.

Default

None

Value

Tenancy's Oracle Cloud Identifier (OCID). You can get this value from the Tenancy Details page under Tenancy Information in the OCI console.

Example

OCI TENANCY=1a123ab1-a1b1-1a2b-a1b2-a12bcdab0123

Related Topics

- Oracle Cloud Infrastructure Documentation
- Oracle Al Database Net Services Administrator's Guide
- AUTHENTICATION

Use the AUTHENTICATION parameter to specify the authentication method that you want to use for accessing the Oracle Cloud Infrastructure (OCI) Object Storage JSON file.

7.4.5 OCI_USER

Use the OCI_USER parameter to specify the user ID associated with Oracle Cloud Infrastructure (OCI) subscription.

Purpose

To specify the user ID associated with OCI subscription. You use this parameter for the OCI API Key authentication flow to access the OCI Object Storage JSON file.

Usage Notes

Set this parameter at the command line in the connect identifier using the <code>option=value</code> syntax.



Default

None

Value

User's Oracle Cloud Identifier (OCID). You can get this value from the User Details page under User Information in the OCI console.

Example

OCI_USER=ocid1.user.oc1..aalabcd12bclabcdlabcdflabcdfg12abcd

Related Topics

- Oracle Cloud Infrastructure Documentation
- Oracle Al Database Net Services Administrator's Guide
- AUTHENTICATION

Use the AUTHENTICATION parameter to specify the authentication method that you want to use for accessing the Oracle Cloud Infrastructure (OCI) Object Storage JSON file.

7.4.6 OCI_KEY_FILE

Use the OCI_KEY_FILE parameter to specify location of the Oracle Cloud Infrastructure (OCI) private key file.

Purpose

To specify location of the OCI private key file. You use this parameter for the OCI API Key authentication flow to access the OCI Object Storage JSON file.

If you want to make API requests, then you must obtain an RSA public key in PEM format (minimum 2048 bits) added to your OCI Identity Access Management (IAM) user profile and sign the API requests with the corresponding private key.

Usage Notes

Set this parameter at the command line in the connect identifier using the option=value syntax.

Default

None

Value

OCI private key file location. This value must be corresponding to the public key added to the IAM user profile.

Example

OCI_KEY_FILE=~/.oci/oci_api_key.pem

Related Topics

Oracle Cloud Infrastructure Documentation



- Oracle AI Database Net Services Administrator's Guide
- AUTHENTICATION

Use the AUTHENTICATION parameter to specify the authentication method that you want to use for accessing the Oracle Cloud Infrastructure (OCI) Object Storage JSON file.

7.4.7 OCI FINGERPRINT

Use the OCI_FINGERPRINT parameter to specify the fingerprint of the Oracle Cloud Infrastructure (OCI) Identity and Access Management (IAM) profile key.

Purpose

To specify the fingerprint of the key added to the OCI IAM profile. You use this parameter for the OCI API Key authentication flow to access the OCI Object Storage JSON file.

Usage Notes

Set this parameter at the command line in the connect identifier using the <code>option=value</code> syntax.

Default

None

Value

Key's fingerprint. You can get this value from the User Details page under API Keys in the OCI console.

Example

OCI FINGERPRINT=a1:12:a1:1a:01:12:23:34:ab:12:ab:0a:12:a1:

Related Topics

- Oracle Cloud Infrastructure Documentation
- Oracle Al Database Net Services Administrator's Guide
- <u>AUTHENTICATION</u>

Use the AUTHENTICATION parameter to specify the authentication method that you want to use for accessing the Oracle Cloud Infrastructure (OCI) Object Storage JSON file.

7.4.8 HTTPS_PROXY

Use the HTTPS_PROXY parameter to specify the HTTPS proxy host name when the client is behind a corporate HTTPS proxy.

Purpose

To specify the HTTPS proxy host name for tunneling Transport Layer Security (TLS) client connections, when the client is behind a corporate HTTPS proxy.

Default

None



Value

HTTPS proxy host name

Examples

HTTPS_PROXY=www-proxy.example.com

Related Topics

Oracle Al Database Net Services Administrator's Guide

7.4.9 HTTPS PROXY PORT

Use the HTTPS_PROXY_PORT parameter to specify the HTTPS proxy port when the client is behind a corporate HTTPS proxy.

Purpose

To specify the HTTPS proxy port for tunneling TLS client connections, when the client is behind a corporate HTTPS proxy.

Default

None

Value

HTTPS proxy port number

Example

HTTPS_PROXY_PORT=80

Related Topics

Oracle AI Database Net Services Administrator's Guide

7.4.10 TIMEOUT

Use the TIMEOUT parameter to specify the duration to complete each HTTP call.

Purpose

To specify the duration to complete each HTTP call. Set this parameter to avoid long network delays or indefinite waiting for a server's response.

Value

Timeout on each HTTP call, in seconds

Default

None



Example

TIMEOUT=60

Related Topics

Oracle Al Database Net Services Administrator's Guide

Oracle Net Listener Parameters in the listener.ora File

This chapter provides a complete listing of the listener.ora file configuration parameters.

- Overview of Oracle Net Listener Configuration File
 Oracle Net Listener configuration, stored in the listener.ora file, consists of these elements.
- Protocol Address Parameters
- Connection Rate Limiter Parameters

The connection rate limiter feature in Oracle Net Listener enables a database administrator to limit the number of new connections handled by the listener. When this feature is enabled, Oracle Net Listener imposes a user-specified maximum limit on the number of new connections handled by the listener every second. Depending on the configuration, the rate can be applied to a collection of endpoints, or to a specific endpoint.

Control Parameters

This section describes the following parameters that control the behavior of the listener:

- ADR Diagnostic Parameters for Oracle Net Listener
 - The diagnostic data for the critical errors is quickly captured and stored in the ADR for Oracle Net listener.
- Non-ADR Diagnostic Parameters for Oracle Net Listener
 - This section lists the parameters used when ADR is disabled. The default value of DIAG_ADR_ENABLED_listener_name is on. Therefore, the DIAG_ADR_ENABLED_listener_name parameter must explicitly be set to off to use non-ADR tracing.
- Class of Secure Transports Parameters
 - The class of secure transports (COST) parameters specify a list of transports that are considered secure for administration and registration of a particular listener.

8.1 Overview of Oracle Net Listener Configuration File

Oracle Net Listener configuration, stored in the listener.ora file, consists of these elements.

- Name of the listener
- Protocol addresses that the listener is accepting connection requests on
- Valid nodes that the listener allows to register with the database
- Database services
- Control parameters

Dynamic service registration, eliminates the need for static configuration of supported services. However, static service configuration is required if you plan to use Oracle Enterprise Manager Cloud Control. For information about static service configuration, see *Oracle Al Database Net Services Administrator's Guide*.



By default, the listener.ora file is located in the <code>ORACLE_HOME/network/admin</code> directory. You can also store the <code>listener.ora</code> in the following locations:

- The directory specified by the TNS_ADMIN environment variable or registry value.
- On Linux and UNIX operating systems, it is the global configuration directory. For example, on the Oracle Solaris operating system, the directory is /var/opt/oracle. See Oracle Al Database Global Data Services Concepts and Administration Guide for information about management of global service. Also refer to Oracle operating system-specific documentation.
- In the read-only Oracle home mode, the default location for the listener.ora file is ORACLE_BASE_HOME/network/admin. If the listener.ora file is not present in the ORACLE_BASE_HOME/network/admin directory, then search for the file in the ORACLE_HOME/network/admin directory.
- In the read-only Oracle home mode, the parameters are stored in the <code>ORACLE_BASE_HOME</code> location by default.

It is possible to configure multiple listeners, each with a unique name, in one listener.ora file. Multiple listener configurations are possible because each of the top-level configuration parameters has a suffix of the listener name or is the listener name itself.

(i) Note

- It is often useful to configure multiple listeners in one listener.ora file. However, Oracle recommends running only one listener for each node in most customer environments.
- Oracle Net Services supports the IFILE parameter in the listener.ora file, with up to three levels of nesting. The parameter is added manually to the file. The following is an example of the syntax:

```
IFILE=/tmp/listener_em.ora
IFILE=/tmp/listener_cust1.ora
IFILE=/tmp/listener_cust2.ora
```

Refer to Oracle Database Reference for additional information.

The following example shows a listener.ora file for a listener named LISTENER, which is the default name of the listener.

Example 8-1 listener.ora File

```
LISTENER=
(DESCRIPTION=
(ADDRESS_LIST=
(ADDRESS=(PROTOCOL=tcp)(HOST=sale-server)(PORT=1521))
(ADDRESS=(PROTOCOL=ipc)(KEY=extproc))))
```

8.2 Protocol Address Parameters

The protocol address section of the listener.ora file defines the protocol addresses on which the listener is accepting connection requests. This section describes the most common parameters used in protocol addresses. The ADDRESS_LIST parameter is also supported. This section lists and describes the following parameters:



ADDRESS

The protocol ADDRESS parameter's networking parameter is in the listener.ora file. It specifies the protocol address under the DESCRIPTION parameter for one listener.

DESCRIPTION

DESCRIPTION networking parameter of the listener.ora file contains listener protocol addresses.

- Firewall
- IF

The protocol address parameter IP determine which IP address the listener listens on when a host name is specified

- QUEUESIZE
- RECV BUF SIZE

Use the RECV_BUF_SIZE parameter to specify buffer space for session receive operations.

SEND BUF SIZE

Use the ${\tt SEND_BUF_SIZE}$ parameter to specify buffer space for session send operations.

8.2.1 ADDRESS

The protocol ADDRESS parameter's networking parameter is in the listener.ora file. It specifies the protocol address under the DESCRIPTION parameter for one listener.

Purpose

Specifies a single listener protocol address in the DESCRIPTION parameter

Usage Notes

Use this parameter to define the protocol, the host, and the port number for the listener.

Example

```
listener_name=
(DESCRIPTION=
  (ADDRESS_LIST=
    (ADDRESS=(PROTOCOL=tcp)(HOST=hr-server)(PORT=1521))
    (ADDRESS=(PROTOCOL=tcp)(HOST=sales-server)(PORT=1521))))
```

8.2.2 DESCRIPTION

DESCRIPTION networking parameter of the listener.ora file contains listener protocol addresses.

Purpose

To contain listener protocol addresses.

Example 8-2 Example

listener_name



8.2.3 Firewall

Purpose

It can be set in endpoint to enable firewall functionality.

Related Topics

Oracle Database Net Services Administrator's Guide

8.2.4 IP

The protocol address parameter IP determine which IP address the listener listens on when a host name is specified

Purpose

To determine which IP address the listener listens on when a host name is specified.

Usage Notes

This parameter is only applicable when the HOST parameter specifies a host name.

Values

first

Listen on the first IP address returned by the DNS resolution of the host name. If the user wants the listener to listen on the first IP to which the specified host name resolves, then the address must be qualified with (IP=first).

v4_only

Listen only on IPv4 addresses.

v6_only

Listen only on IPv6 addresses.

Default

This feature is disabled by default.

Example

```
listener_name=
(DESCRIPTION=
   (ADDRESS=(PROTOCOL=tcp)(HOST=rancode1-vip)(PORT=1522)(IP=v6_only))
```

8.2.5 QUEUESIZE

Purpose

To specify the number of concurrent connection requests that the listener can accept on a TCP/IP or IPC listening endpoint (protocol address).



Usage Notes

The number of concurrent connection requests is dependent on the platform and listener usage scenarios. If the listener is heavily-loaded, then set the parameter to a higher number.

Put this parameter at the end of the protocol address with its value set to the expected number of concurrent connection requests.

Default

The default number of concurrent connection requests is operating system specific.

Example

```
listener_name=
(DESCRIPTION=
  (ADDRESS=(PROTOCOL=tcp)(HOST=hr-server)(PORT=1521)(QUEUESIZE=20)))
```

See Also

Oracle Database Net Services Administrator's Guide for additional information about configuring this parameter

8.2.6 RECV_BUF_SIZE

Use the RECV_BUF_SIZE parameter to specify buffer space for session receive operations.

Purpose

To specify, in bytes, the buffer space for receive operations of sessions.

Usage Notes

Put this parameter under the DESCRIPTION parameter or at the end of the protocol address with its value set to the expected number of bytes.

This parameter is supported by the TCP/IP, TCP/IP with TLS, and SDP protocols.



Additional protocols might support this parameter on certain operating systems. Refer to the operating system-specific documentation for information about additional protocols that support this parameter.

Default

The default value for this parameter is operating system specific. The default for the Linux operating system is 87380 bytes.

Example

listener_name=
(DESCRIPTION=



```
(ADDRESS_LIST=
    (ADDRESS=(PROTOCOL=tcp)(HOST=sales-server)(PORT=1521)
        (RECV_BUF_SIZE=11784))
    (ADDRESS=(PROTOCOL=ipc)(KEY=extproc)
        (RECV_BUF_SIZE=11784))))
listener_name=
(DESCRIPTION=
    (ADDRESS_LIST=
        (RECV_BUF_SIZE=11784))
    (ADDRESS=(PROTOCOL=tcp)(HOST=sales-server)(PORT=1521)
    (ADDRESS=(PROTOCOL=ipc)(KEY=extproc))))
```

Related Topics

Oracle Al Database Net Services Administrator's Guide

8.2.7 SEND BUF SIZE

Use the SEND_BUF_SIZE parameter to specify buffer space for session send operations.

Purpose

To specify, in bytes, the buffer space for send operations of sessions.

Usage Notes

Put this parameter under the DESCRIPTION parameter or at the end of the protocol address.

This parameter is supported by the TCP/IP, TCP/IP with TLS, and SDP protocols.



Additional protocols might support this parameter on certain operating systems. Refer to operating system-specific documentation for additional information about additional protocols that support this parameter.

Default

The default value for this parameter is operating system specific. The default for the Linux operating system is 16 KB.

Example



Related Topics

Oracle Al Database Net Services Administrator's Guide

8.3 Connection Rate Limiter Parameters

The connection rate limiter feature in Oracle Net Listener enables a database administrator to limit the number of new connections handled by the listener. When this feature is enabled, Oracle Net Listener imposes a user-specified maximum limit on the number of new connections handled by the listener every second. Depending on the configuration, the rate can be applied to a collection of endpoints, or to a specific endpoint.

This feature is controlled through the following listener.ora configuration parameters:

CONNECTION RATE listener name

The CONNECTION_RATE_listener_name configuration parameter of thelistener.ora file specifies a global rate that is enforced across all listening endpoints that are rate-limited.

RATE LIMIT

The RATE_LIMIT configuration parameter of the listener.ora file indicates that a particular listening endpoint is rate-limited.

8.3.1 CONNECTION RATE listener name

The CONNECTION_RATE_listener_name configuration parameter of thelistener.ora file specifies a global rate that is enforced across all listening endpoints that are rate-limited.

Purpose

To specify a global rate that is enforced across all listening endpoints that are rate-limited.

Usage Notes

When this parameter is specified, it overrides any endpoint-level numeric rate values that might be specified.

Syntax

CONNECTION_RATE_listener_name=number_of_connections_per_second

8.3.2 RATE_LIMIT

The RATE_LIMIT configuration parameter of the listener.ora file indicates that a particular listening endpoint is rate-limited.

Purpose

To indicate that a particular listening endpoint is rate-limited.

Usage Notes

The parameter is specified in the ADDRESS section of the listener endpoint configuration.

Syntax

LISTENER=

(ADDRESS=(PROTOCOL=tcp)(HOST=)(PORT=1521)(RATE_LIMIT=yes))



- When the RATE_LIMIT parameter is set to yes for an endpoint, that endpoint is included in the enforcement of the global rate configured by the CONNECTION_RATE_listener_name parameter. The global rate limit is enforced individually at each endpoint that has RATE_LIMIT set to yes.
- Dynamic endpoints for listeners managed by Oracle Clusterware have the RATE_LIMIT parameter set to yes.
- When the RATE_LIMIT parameter is set to a value greater than 0, then the rate limit is enforced at that endpoint level.

Examples

The following examples use the CONNECTION_RATE_listener name and RATE_LIMIT parameters.

Example 1

```
CONNECTION_RATE_LISTENER=10

LISTENER=
  (ADDRESS_LIST=
    (ADDRESS=(PROTOCOL=tcp)(HOST=)(PORT=1521)(RATE_LIMIT=yes))
    (ADDRESS=(PROTOCOL=tcp)(HOST=)(PORT=1522)(RATE_LIMIT=yes))
    (ADDRESS=(PROTOCOL=tcp)(HOST=)(PORT=1523)))
```

In the preceding example, the global rate of new connections is enforced separately for each endpoint. Connections through port 1521 are limited at 10 every second, and the connections through port 1522 are also separately limited at 10 every second. Connections through port 1523 are not limited.

Example 2

```
LISTENER= (ADDRESS_LIST=
    (ADDRESS=(PROTOCOL=tcp)(HOST=)(PORT=1521)(RATE_LIMIT=5))
    (ADDRESS=(PROTOCOL=tcp)(HOST=)(PORT=1522)(RATE_LIMIT=10))
    (ADDRESS=(PROTOCOL=tcp)(HOST=)(PORT=1523))
)
```

In the preceding example, the connection rates are enforced at the endpoint level. A maximum of 5 connections are processed through port 1521 every second. The limit for connections through port 1522 is 10 every second. Connections through port 1523 are not limited.

(i) Note

The global CONNECTON_RATE_listener_name parameter is not specified in the preceding configuration. If it is specified, then the limits on ports 1521 and 1522 are ignored, and the global value is used instead.

8.4 Control Parameters

This section describes the following parameters that control the behavior of the listener:



ADMIN RESTRICTIONS listener name

The listener.ora control parameter ADMIN_RESTRICTIONS_listener_name restricts runtime administration of the listener.

ALLOW MULTIPLE REDIRECTS listener name

The *listener.ora* control parameter ALLOW_MULTIPLE_REDIRECTS_listener_name enables multiple redirects of the client.

• CRS NOTIFICATION listener name

CRS_NOTIFICATION_listener_name control parameter of the listener.ora file sets notification to allow or disallow Cluster Ready Services (CRS) to manage the listener in an Oracle Real Application Clusters environment.

DEDICATED THROUGH BROKER LISTENER

DEDICATED_THROUGH_BROKER_LISTENER networking parameter of the listener.ora file enables the server to spawn a thread or process when a connection to the database is requested through the listener.

DEFAULT SERVICE listener name

DEFAULT_SERVICE_listener_name control parameter of the listener.ora file enables users to connect to the database without having to specify a service name from the client side.

- ENABLE EXADIRECT listener name
- INBOUND CONNECT TIMEOUT listener name
- LOCAL REGISTRATION ADDRESS listener name

MAX ALL CONNECTIONS listener name

Use the MAX_ALL_CONNECTIONS_listener_name parameter to specify the maximum number of concurrent registration and client connection sessions.

MAX REG CONNECTIONS listener name

Use the MAX_REG_CONNECTIONS_listener_name parameter to specify the maximum number of concurrent registration connection sessions.

- REGISTRATION EXCLUDED NODES listener name
- REGISTRATION INVITED NODES listener name
- REMOTE REGISTRATION ADDRESS listener name
- SAVE CONFIG ON STOP listener name

SERVICE RATE listener name

The SERVICE_RATE_listener_name control parameter specifies incoming connection rate that is allowed per service for an instance.

SSL CIPHER SUITES

Use the SSL_CIPHER_SUITES parameter to control the combination of authentication, encryption, and data integrity algorithms used by Transport Layer Security (TLS).

SSL CLIENT AUTHENTICATION

Use the SSL_CLIENT_AUTHENTICATION parameter to specify whether the database client is authenticated using Transport Layer Security (TLS).

SSL DISABLE WEAK EC CURVES

Use the SSL_DISABLE_WEAK_EC_CURVES parameter to disable the use of weak Elliptic Curve Cryptography (ECC) curves.

SSL VERSION

Use the SSL_VERSION parameter to define valid Transport Layer Security (TLS) versions to be used for connections.



- SUBSCRIBE FOR NODE DOWN EVENT listener name
- TLS KEY EXCHANGE GROUPS

Use the ${\tt TLS_KEY_EXCHANGE_GROUPS}$ parameter to enable or disable post-quantum cryptographic (PQC) ML-KEM algorithms and classical ECDHE groups for TLS connections.

- USE SID AS SERVICE listener name
- USE SNI listener name

Use the <code>listener.ora</code> parameter <code>USE_SNI</code> to enable or disable the use of Server Name Indication (SNI) value by the listener for fetching <code>CONNECT_DATA</code> parameters and selecting an appropriate service handler to service the connection request without performing TLS negotiation with the client.

• <u>VALID_NODE_CHECKING_REGISTRATION_listener_name</u>
The *listener.ora* control parameter VALID_NODE_CHECKING_REGISTRATION_*listener_name*determines if valid node checking registration is performed, or if the subnet is allowed.

WALLET_LOCATION
 Use the WALLET_LOCATION parameter to specify the location of Oracle wallets.

8.4.1 ADMIN_RESTRICTIONS_listener_name

The listener.ora control parameter ADMIN_RESTRICTIONS_listener_name restricts runtime administration of the listener.

Purpose

To restrict runtime administration of the listener.

Usage Notes

Setting ADMIN_RESTRICTIONS_listener_name=on disables the runtime modification of parameters in listener.ora. That is, the listener refuses to accept SET commands that alter its parameters. To change any of the parameters in listener.ora, including ADMIN_RESTRICTIONS_listener_name itself, modify the listener.ora file manually and reload its parameters using the RELOAD command for the new changes to take effect without explicitly stopping and restarting the listener.

Default

off

Example

ADMIN_RESTRICTIONS_listener=on

Related Topics

SET

Use the Listener Control utility command SET to alter listener parameter values.

RELOAD

Use the Listener Control utility command RELOAD to reload the listener.ora file so that you can add or change statically configured services without stopping the listener.



8.4.2 ALLOW_MULTIPLE_REDIRECTS_listener_name

The *listener.ora* control parameter ALLOW_MULTIPLE_REDIRECTS_listener_name enables multiple redirects of the client.

Purpose

To support multiple redirects of the client.

Usage Notes

This parameter should only be set on the SCAN listener on the Oracle Public Cloud. When set to on, multiple redirects of the client are allowed.

Do not set this parameter for a node listener if that is used as a SCAN listener.

Default

off

Values

on | off

Example

ALLOW_MULTIPLE_REDIRECTS_listener=on

8.4.3 CRS_NOTIFICATION_listener_name

CRS_NOTIFICATION_listener_name control parameter of the listener.ora file sets notification to allow or disallow Cluster Ready Services (CRS) to manage the listener in an Oracle Real Application Clusters environment.

Purpose

To set notification.

Usage Notes

By default, the Oracle Net listener notifies Cluster Ready Services (CRS) when it is started or stopped. These notifications allow CRS to manage the listener in an Oracle Real Application Clusters environment. This behavior can be prevented by setting the CRS_NOTIFICATION_listener_name parameter to off.

Default

on

Values

on | off



8.4.4 DEDICATED_THROUGH_BROKER_LISTENER

DEDICATED_THROUGH_BROKER_LISTENER networking parameter of the listener.ora file enables the server to spawn a thread or process when a connection to the database is requested through the listener.

Purpose

To enable the server to spawn a thread or process when a connection to the database is requested through the listener.

Default

off

Values

on | off

Example 8-3 Example

(Optional) Enter an example to illustrate your reference here.

8.4.5 DEFAULT SERVICE listener name

DEFAULT_SERVICE_listener_name control parameter of the listener.ora file enables users to connect to the database without having to specify a service name from the client side.

Purpose

To enable users to connect to the database without having to specify a service name from the client side.

Usage Notes

When a client tries to connect to the database, the connection request passes through the listener. The listener may be servicing several different databases. If a service name is configured in this parameter, then users may not necessarily need to specify a service name in the connect syntax. If a user specifies a service name, then the listener connects the user to that specific database, otherwise the listener connects to the service name specified by the <code>DEFAULT_SERVICE_listener_name</code> parameter. For container databases, the client must explicitly specify the service name.

Default

There is no default value for the <code>DEFAULT_SERVICE_listener_name</code> parameter. If this parameter is not configured and a user does not specify a fully-qualified service name in the connect syntax, then the connection attempt fails. This parameter only accepts one value.

Example 8-4 Example

DEFAULT_SERVICE_listener=sales.us.example.com



8.4.6 ENABLE_EXADIRECT_listener_name

Purpose

To enable Exadirect protocol.

Usage Notes

The parameter enables Exadirect support.

Default

Off

Values

on | off

Example 8-5 Example

ENABLE EXADIRECT listener=on

8.4.7 INBOUND CONNECT TIMEOUT listener_name

Purpose

To specify the time, in seconds, for the client to complete its connect request to the listener after the network connection had been established.

Usage Notes

If the listener does not receive the client request in the time specified, then it terminates the connection. In addition, the listener logs the IP address of the client and an ORA-12525:TNS: listener has not received client's request in time allowed error message to the listener.log file.

To protect both the listener and the database server, Oracle recommends setting this parameter in combination with the <u>SQLNET.INBOUND_CONNECT_TIMEOUT</u> parameter in the sqlnet.ora file. When specifying values for these parameters, consider the following recommendations:

- Set both parameters to an initial low value.
- Set the value of the INBOUND_CONNECT_TIMEOUT_listener_name parameter to a lower value than the SQLNET.INBOUND_CONNECT_TIMEOUT parameter.

For example, you can set the <code>INBOUND_CONNECT_TIMEOUT_listener_name</code> parameter to 2 seconds and the <code>INBOUND_CONNECT_TIMEOUT</code> parameter to 3 seconds. If clients are unable to complete connections within the specified time due to system or network delays that are normal for the particular environment, then increment the time as needed.

Default

60 seconds

Example

INBOUND_CONNECT_TIMEOUT_listener=2



8.4.8 LOCAL_REGISTRATION_ADDRESS_listener_name

Purpose

To secure registration requests through dedicated secure registration endpoints for local listeners. Service ACLs are accepted by listener only if LOCAL_REGISTRATION_ADDRESS_Isnr alias is configured. The parameter specifies the group that is allowed to send ACLs.

Usage Notes

The local registration endpoint accepts local registration connections from the specified group. All local registration requests coming on normal listening endpoints are redirected to the local registration endpoint. If the registrar is not a part of the group, then it cannot connect to the endpoint.

Default

OFF

Values

ON, OFF, or IPC endpoint address with group

When set to ON, listener defaults the group to oinstall on UNIX and ORA_INSTALL on Windows.

Example 8-6 Example

LOCAL_REGISTRATION_ADDRESS_lsnr_alias = (address=(protocol=ipc)(group=xyz))
LOCAL_REGISTRATION_ADDRESS_lsnr_alias = ON

Related Topics

- Firewall
- DBMS_SFW_ACL_ADMIN

8.4.9 MAX ALL CONNECTIONS_listener_name

Use the ${\tt MAX_ALL_CONNECTIONS_listener_name}$ parameter to specify the maximum number of concurrent registration and client connection sessions.

Purpose

To specify the maximum number of concurrent registration and client connection sessions that can be supported by Oracle Net Listener.

Usage Notes

This number includes registration connections from databases, and ongoing client connection establishment requests. After a connection is established, the clients do not maintain a connection to the listener. This limit only applies to client connections that are in the initial connection establishment phase from a listener perspective.

Default

4096



Example

MAX_ALL_CONNECTIONS_listener=4096

8.4.10 MAX_REG_CONNECTIONS_listener_name

Use the MAX_REG_CONNECTIONS_listener_name parameter to specify the maximum number of concurrent registration connection sessions.

Purpose

To specify the maximum number of concurrent registration connection sessions that can be supported by Oracle Net Listener.

Default

512

Example

MAX_REG_CONNECTIONS_listener=2048

8.4.11 REGISTRATION_EXCLUDED_NODES_listener_name

Purpose

To specify the list of nodes that cannot register with the listener.

Usage Notes

The list can include host names or CIDR notation for IPv4 and IPv6 addresses. The wildcard format (*) is supported for IPv4 addresses. The presence of a host name in the list results in the inclusion of all IP addresses mapped to the host name. The host name should be consistent with the public network interface.

If the <code>REGISTRATION_INVITED_NODES_listener_name</code> parameter and the <code>REGISTRATION_EXCLUDED_NODES_listener_name</code> parameter are set, then the <code>REGISTRATION_EXCLUDED_NODES_listener_name</code> parameter is ignored.

Values

Valid nodes and subnet IP addresses or names.

Example

8.4.12 REGISTRATION_INVITED_NODES_listener_name

Purpose

To specify the list of node that can register with the listener.



Usage Notes

- The list can include host names or CIDR notation for IPv4 and IPv6 addresses. The wildcard format (*) is supported for IPv4 addresses. The presence of a host name in the list results in the inclusion of all IP addresses mapped to the host name. The host name should be consistent with the public network interface.
- If the REGISTRATION_INVITED_NODES_listener_name parameter and the REGISTRATION_EXCLUDED_NODES_listener_name parameter are set, then the REGISTRATION_EXCLUDED_NODES_listener_name parameter is ignored.
- Starting with Oracle Grid Infrastructure 12c, for a SCAN listener, if the VALID_NODE_CHECKING_REGISTRATION_listener_name and REGISTRATION_INVITED_NODES_listener_name parameters are set in the listener.ora file, then the listener agent overwrites these parameters.

Values

Valid nodes and subnet IP addresses or names.

Example

```
REGISTRATION_INVITED_NODES_listener = (10.1.35.*, 10.1.34.0/24, \
2001:DB8:fe38:7303, node1)
```

(i) See Also

Oracle Real Application Clusters Administration and Deployment Guide for information about valid node checking for registration

8.4.13 REMOTE REGISTRATION ADDRESS listener name

Purpose

To secure registration requests through dedicated secure registration endpoints for SCAN listeners.

Usage Notes

The registration endpoint is on a private network within the cluster. All remote registration requests coming in on normal listening endpoints are redirected to the registration endpoint. Any system which is not a part of the cluster cannot connect to the endpoint. This feature is not supported when ADMIN_RESTRICTIONS_listener_name is set to ON as the Cluster Ready Services agent configures the remote_registration_address dynamically at run time.

Default

This parameter is configured internally in listeners managed by Oracle Clusterware to restrict registrations to the private network. The value of this parameter should not be modified or specified explicitly. The only supported explicit setting is for turning this feature off by setting the value to OFF.



Values

off

Example

REMOTE REGISTRATION ADDRESS listener=off

8.4.14 SAVE CONFIG ON STOP listener name

Purpose

To specify whether runtime configuration changes are saved to the listener.ora file.

Usage Notes

When you set the parameter to true, any parameters that were modified while the listener was running using the Listener Control utility <u>SET</u> command are saved to the listener.ora file when the <u>STOP</u> command is issued. When you set the parameter to false, the Listener Control utility does not save the runtime configuration changes to the listener.ora file.

Default

false

Values

true | false

Example

SAVE_CONFIG_ON_STOP_listener=true

8.4.15 SERVICE RATE listener name

The SERVICE_RATE_listener_name control parameter specifies incoming connection rate that is allowed per service for an instance.

Purpose

To specify incoming connection rate that is allowed per service for an instance.

Usage Notes

Any user-specified value greater than 0 sets the maximum limit on the number of new connections per service-instance handled by the proxy listener every second. Listener rejects connections after it reaches the maximum limit. Client side connection failure is reported with the "TNS:listener: rate limit reached" error.

Default

0

Example 8-7 Example

SERVICE_RATE=10



8.4.16 SSL_CIPHER_SUITES

Use the SSL_CIPHER_SUITES parameter to control the combination of authentication, encryption, and data integrity algorithms used by Transport Layer Security (TLS).

Purpose

To control the combination of authentication, encryption, and data integrity algorithms used by TLS. By default, the strongest protocol and cipher are negotiated between the database client and server. Setting this parameter will override the default behavior. You must use this parameter only if you have internal security controls that dictate the usage of certain protocol versions.

Usage Notes

Starting with Oracle AI Database 26ai, the use of Transport Layer Security protocol versions 1.0 and 1.1 are desupported.

In most cases, this change will not have any impact, because the database client and server will negotiate the use of the most secure protocol and cipher algorithm. However, if TLS 1.0 or 1.1 has been specified, then you must either remove it to allow the database server and client to pick the most secure protocol, or you must specify either TLS 1.2, or TLS 1.3, or both, for the protocol. Oracle recommends using the latest, most secure protocol. That protocol is TLS 1.3, which is introduced with Oracle Al Database 26ai.

Enclose the SSL_CIPHER_SUITES parameter value in parentheses. Otherwise, the cipher suite setting does not parse correctly.

Default

None

Values

Approved ciphers compatible with TLS 1.3:

- TLS_AES_256_GCM_SHA384
- TLS_CHACHA20_POLY1305_SHA256 (non-FIPS only)
- TLS AES 128 CCM SHA256
- TLS_AES_128_GCM_SHA256

Approved ciphers compatible with TLS 1.2:

- TLS_ECDHE_RSA_WITH_AES_256_GCM_SHA384
- TLS_ECDHE_RSA_WITH_AES_128_GCM_SHA256
- TLS_ECDHE_ECDSA_WITH_AES_256_GCM_SHA384
- TLS_ECDHE_ECDSA_WITH_AES_128_GCM_SHA256
- TLS_DHE_RSA_WITH_AES_256_GCM_SHA384
- TLS DHE RSA WITH AES 128 GCM SHA256

Deprecated ciphers compatible with TLS 1.2:

- TLS_ECDHE_RSA_WITH_AES_256_CBC_SHA384
- TLS_ECDHE_RSA_WITH_AES_256_CBC_SHA



- TLS_ECDHE_RSA_WITH_AES_128_CBC_SHA256
- TLS_ECDHE_RSA_WITH_AES_128_CBC_SHA
- TLS_ECDHE_ECDSA_WITH_AES_256_CBC_SHA384
- TLS_ECDHE_ECDSA_WITH_AES_256_CBC_SHA
- TLS_ECDHE_ECDSA_WITH_AES_128_CBC_SHA256
- TLS_ECDHE_ECDSA_WITH_AES_128_CBC_SHA
- TLS_RSA_WITH_AES_256_GCM_SHA384
- TLS_RSA_WITH_AES_256_CBC_SHA256
- TLS_RSA_WITH_AES_256_CBC_SHA
- TLS_RSA_WITH_AES_128_GCM_SHA256
- TLS_RSA_WITH_AES_128_CBC_SHA256
- TLS_RSA_WITH_AES_128_CBC_SHA
- TLS_DHE_RSA_WITH_AES_256_CBC_SHA256
- TLS_DHE_RSA_WITH_AES_128_CBC_SHA256
- TLS_DHE_RSA_WITH_AES_256_CBC_SHA

Examples

SSL_CIPHER_SUITES=(TLS_ECDHE_ECDSA_WITH_AES_128_GCM_SHA256)

SSL_CIPHER_SUITES=(TLS_AES_256_GCM_SHA384, TLS_ECDHE_ECDSA_WITH_AES_128_GCM_SHA256)

Related Topics

- Set the TLS Cipher Suites on the Server
- Set the TLS Cipher Suites on the Client

8.4.17 SSL CLIENT AUTHENTICATION

Use the SSL_CLIENT_AUTHENTICATION parameter to specify whether the database client is authenticated using Transport Layer Security (TLS).

Purpose

To enable client authentication in a TLS connection. The connection can be one-way or two-way (mutual TLS or mTLS).

Usage Notes

When set to TRUE, a two-way TLS connection is initiated. Both the client and server (including the listener) authenticate each other. For example, if you set this parameter to TRUE in the server configuration (server-side sqlnet.ora), then the server attempts to authenticate the client. If you set it to TRUE in the listener configuration (listener.ora), then the listener attempts to authenticate the client.



When set to FALSE, only the client authenticates the server and listener as a one-way TLS connection. For example, if you set this parameter to FALSE in the server configuration, then the server does not authenticate the client. If you set it to FALSE in the listener configuration, then the listener does not authenticate the client.

When set to OPTIONAL, the server behaves as follows:

- If the client sends a certificate, then the connection is completed as a two-way TLS connection after authenticating the client.
- If the client does not send a certificate, then the connection is completed as a one-way TLS connection.

Ensure that this parameter setting is consistent for the server or listener (on one side) and the client (on the other). Otherwise, the connection may fail. For example, if you enable client authentication in the server or listener configuration, then you must enable it in the client configuration.

Default

TRUE

Values

- TRUE | ON | YES | 1: To enable mTLS
- FALSE | OFF | NO | 0: To enable one-way TLS
- OPTIONAL: To enable both TLS and mTLS

Example

SSL_CLIENT_AUTHENTICATION=FALSE

Related Topics

Oracle AI Database Security Guide

8.4.18 SSL_DISABLE_WEAK_EC_CURVES

Use the SSL_DISABLE_WEAK_EC_CURVES parameter to disable the use of weak Elliptic Curve Cryptography (ECC) curves.

Purpose

To disable the use of weak ECC curves with key length less than 256 bits. You can set this parameter in the database server (sqlnet.ora), client (sqlnet.ora or tnsnames.ora connect string), or the listener (listener.ora).

Usage Notes

The Oracle Net Services parameter SSL_DISABLE_WEAK_EC_CURVES is deprecated in Oracle AI Database 26ai.

Elliptic Curve Cryptography (ECC) features in Oracle Net Services, such as those used for secure external password stores, have some curves disabled by default. Oracle and other major vendors disable weak elliptic curves by default to protect systems from known cryptographic vulnerabilities, and to enforce modern security standards. These older, weaker curves can be susceptible to a variety of attacks and may present security risks if used. Because Oracle no longer has ECC curves with key length less than 256 bit enabled, this



parameter no longer serves a purpose, and will be removed in a future release. Oracle strongly recommends that you review your configurations to ensure that you follow security best practices.

Note

SSL_DISABLE_WEAK_EC_CURVES is deprecated in favor of TLS_KEY_EXCHANGE_GROUPS parameter starting with Oracle AI Database 26ai.

By default, this parameter is set to FALSE to enable the use of all ECC curves. If you want to enable the use of only Oracle approved curves with ECC curve key size of 256 bits or higher, then set this parameter to TRUE.

When set to TRUE, you can use only the following ECC curves:

- secp256r1
- secp384r1
- secp521r1
- x25519

Values

- TRUE | ON | YES | 1: To enable only the Oracle approved ECC curves with minimum ECC curve key length of 256 bits
- FALSE | OFF | NO | 0: To enable all ECC curves

Default

FALSE

Examples

• In the tnsnames.ora file:

```
net_service_name=
  (DESCRIPTION=
      (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr)(PORT=1521))
      (SECURITY=(SSL_DISABLE_WEAK_EC_CURVES=TRUE))
)
```

• In the sqlnet.ora file or the listener.ora file:

```
SSL_DISABLE_WEAK_EC_CURVES=TRUE
```

Related Topics

TLS KEY EXCHANGE GROUPS

Use the ${\tt TLS_KEY_EXCHANGE_GROUPS}$ parameter to enable or disable post-quantum cryptographic (PQC) ML-KEM algorithms and classical ECDHE groups for TLS connections.



8.4.19 SSL_VERSION

Use the SSL_VERSION parameter to define valid Transport Layer Security (TLS) versions to be used for connections.

Purpose

To define the version of TLS that must run on the systems with which the database server communicates. By default, the database server and client negotiate the strongest security protocol. Oracle does not recommend modifying this parameter, unless your security requirements mandate the usage of certain protocol versions.

Usage Notes

- Clients, listeners, and database servers must use compatible versions. Modify this
 parameter only when necessary to enforce the use of the more secure TLS protocol and
 not allow clients that only work with the older TLS protocols. The current default uses TLS
 1.3, which is the version required for multiple security compliance requirements. If you
 need to specify TLS 1.2, then also include TLS 1.3 to allow more secure connections.
- In addition to sqlnet.ora, listener.ora, and cman.ora, you can specify this parameter
 under the SECURITY section of the the section of the connect string. The
 parameter value specified in the connect string takes precedence over the other specified
 values.
- Starting with Oracle AI Database 26ai, the use of Transport Layer Security protocol versions 1.0 and 1.1 are desupported.
 - In most cases, this change will not have any impact, because the database client and server will negotiate the use of the most secure protocol and cipher algorithm. However, if TLS 1.0 or 1.1 has been specified, then you must either remove it to allow the database server and client to pick the most secure protocol, or you must specify either TLS 1.2, or TLS 1.3, or both, for the protocol. Oracle recommends using the latest, most secure protocol. That protocol is TLS 1.3, which is introduced with Oracle AI Database 26ai.
- Starting with Oracle AI Database 26ai, the Secure Socket Layer v3 protocol (SSLv3) is no longer supported for database server-client connections, and the sqlnet.ora parameter ADD SSLV3 TO DEFAULT has been removed.
 - SSLv3 is a much less secure protocol to secure the database server-to-client connection. Instead of using SSLv3, allow the database server and client to negotiate the most secure protocol that is common between the server and the client. Oracle AI Database 26ai provides TLS 1.2 and TLS 1.3 protocols for certificate-based network encryption.
- If you set SSL_VERSION to undetermined, then the most secure TLS protocol version is
 used. You can also use the SSL_VERSION=undetermined setting in the connect string for a
 specific connection to override the SSL_VERSION value configured in the sqlnet.ora,
 listener.ora, Or cman.ora file.
- If you do not set SSL_VERSION to any value, then all the supported TLS protocol versions are tried starting with the most secure version. This is typically the most common configuration, ensuring that the strongest protocol is chosen during TLS negotiation.

Values

undetermined | TLSv1.2 | TLSv1.3



Default

undetermined

Syntax and Examples

To specify a single protocol version:

```
SSL_VERSION=TLS_protocol_version
```

For example:

```
SSL_VERSION=TLSv1.3
```

 To specify multiple protocol versions, use a comma-separated string of values, enclosed in parenthesis:

```
SSL VERSION=(TLS protocol version1,TLS protocol version2)
```

For example:

```
SSL_VERSION=(TLSv1.2,TLSv1.3)
```

Note

Do not enclose protocol versions in parenthesis while specifying this parameter in the tnsnames.ora file or as part of the connect string, otherwise the setting will not parse correctly. For example:

```
net_service_name=
  (DESCRIPTION=
          (ADDRESS=(PROTOCOL=tcps)(HOST=salesserver)(PORT=1522))
          (SECURITY=(SSL_VERSION=TLSv1.2,TLSv1.3))
)
```

Related Topics

- Set the Required TLS Version on the Server
- Set the Required TLS Version on the Client

8.4.20 SUBSCRIBE_FOR_NODE_DOWN_EVENT_listener_name

Purpose

To subscribe to Oracle Notification Service (ONS) notifications for downed events.

Usage Notes

By default, the listener subscribes to the ONS node down event on startup, if ONS is available. This subscription enables the listener to remove the affected service when it receives node down event notification from ONS. The listener uses asynchronous subscription for the event



notification. Alter this behavior by setting

SUBSCRIBE_FOR_NODE_DOWN_EVENT_listener_name=off in listener.ora.

Default

on

Values

on | off

8.4.21 TLS KEY_EXCHANGE_GROUPS

Use the TLS_KEY_EXCHANGE_GROUPS parameter to enable or disable post-quantum cryptographic (POC) ML-KEM algorithms and classical ECDHE groups for TLS connections.

Purpose

To enable selection of classical or quantum-safe key exchange algorithms for TLS connections. You can set this parameter in the database server (sqlnet.ora), client (sglnet.ora or thsnames.ora connect string), or the listener (listener.ora).

Usage Notes

This parameter takes a combination of following values as a comma-separated list:

- ec: If the TLS_KEY_EXCHANGE_GROUPS value contains ec, the Oracle approved ECDHE groups - secp256r1, secp384r1, secp521r1, and x25519 are enabled. This is similar to setting the deprecated parameter SSL_DISABLE_WEAK_EC_CURVES to TRUE.
- weak: If the parameter value contains weak, then all ECDHE groups are enabled including the weak groups that are disabled when the deprecated parameter SSL_DISABLE_WEAK_EC_CURVES is set to TRUE, as well as the Oracle approved ECDHE groups. Oracle does not recommend setting the value to weak.



(i) Note

Some groups from the Oracle approved ECDHE list may be moved to the weak groups list in the future, and such changes would be transparent.

ml-kem: If the TLS_KEY_EXCHANGE_GROUPS value contains ml-kem, ML-KEM TLS groups are enabled.

(i) Note

- ML-KEM refers to the Module-Lattice-based Key Encapsulation Mechanism that allows secure exchange of cryptographic keys over insecure channels. It is a cryptographic protocol designed for quantum-safe key exchange and is part of the NIST Post-Quantum Cryptography (PQC) standardization process.
- ML-KEM is only valid with TLSv1.3, it does not apply to TLSv1.2.

ML-KEM negotiation can happen if both client and server support ML-KEM which is to say both client and server are DB26ai and:



- The server has TLS_KEY_EXCHANGE_GROUPS set to ml-kem and the client has the value set to ml-kem, ec or not have TLS_KEY_EXCHANGE_GROUPS set at all. In this case, the client uses ECDHE to send the key share in its initial handshake message. The server's list does not contain any key shares supported by the client. It finds the common group, which is ml-kem in this case, from the client's list and its own list and sends a retry request with its key share using ML-KEM. The client resends the key share, and the handshake proceeds with ml-kem as the negotiated group.
- The client sets TLS_KEY_EXCHANGE_GROUPS to ml-kem explicitly and the server has the value set to ec, ml-kem or ml-kem or not have TLS_KEY_EXCHANGE_GROUPS set at all. In this case, the client uses ml-kem to send the key share in its initial handshake message. The server supports this group and the handshake proceeds with ml-kem as the negotiated group.

Values

A comma-separated list of one or more of the values below:

- ec: To enable the Oracle approved ECDHE groups
- weak: To enable both the weak and Oracle approved ECDHE groups
- ml-kem: To enable the ML-KEM TLS groups

The following table shows the results of TLS negotiations based on <code>TLS_KEY_EXCHANGE_GROUPS</code> values from both the client and server.

Server-Side Value	Client-Side Value	Result
Not set	Not set	ECDHE
ec,ml-kem	ec,ml-kem	ECDHE
ec,ml-kem	ml-kem	ML-KEM
ml-kem	ec,ml-kem	ML-KEM
ml-kem	ml-kem	ML-KEM
ес	ec	ECDHE

ECDHE is given higher preference compared to ML-KEM. If TLS_KEY_EXCHANGE_GROUPS contains both ml-kem and ec, then ECDHE groups are given higher preference. The order in which the values are specified in TLS_KEY_EXCHANGE_GROUPS parameter does not matter.

Default

ec, weak, and ml-kem are enabled by default, in that order.

Examples

In the tnsnames.ora file:

```
net_service_name=
  (DESCRIPTION=
       (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr)(PORT=1521))
       (SECURITY=(TLS_KEY_EXCHANGE_GROUPS=ml-kem,ec))
)
```

• In the sqlnet.ora file or the listener.ora file:

TLS KEY EXCHANGE GROUPS=ml-kem,ec



Related Topics

- <u>SSL_DISABLE_WEAK_EC_CURVES</u>
 Use the SSL_DISABLE_WEAK_EC_CURVES parameter to disable the use of weak Elliptic Curve Cryptography (ECC) curves.
- Oracle AI Database Security Guide

8.4.22 USE_SID_AS_SERVICE_listener_name

Purpose

To enable the system identifier (SID) in the connect descriptor to be interpreted as a service name when a user attempts a database connection.

Usage Notes

Database clients with earlier releases of Oracle Database that have hard-coded connect descriptors can use this parameter to connect to a container or pluggable database.

For an Oracle container database, the client must specify a service name in order to connect to it. Setting this parameter to on instructs the listener to use the SID in the connect descriptor as a service name and connect the client to the specified database.

Default

off

Example

USE_SID_AS_SERVICE_listener=on

8.4.23 USE_SNI_listener_name

Use the listener.ora parameter USE_SNI to enable or disable the use of Server Name Indication (SNI) value by the listener for fetching CONNECT_DATA parameters and selecting an appropriate service handler to service the connection request without performing TLS negotiation with the client.

Purpose

To allow listener to use SNI value for selecting appropriate service handler and skip the TLS handshake with the client.

Usage Notes

SNI is enabled by default in the listener. If you do not configure USE_SNI parameter in listener.ora, then by default, the listener processes the SNI. If a valid SNI is found, the listener uses it to fetch the CONNECT_DATA parameters, skips the TLS handshake process with the client and forwards the connection request to an appropriate service handler. If SNI is missing or invalid, then the listener will perform a full TLS handshake with the client to get the connect request.

If you set the $\tt USE_SNI$ to $\tt OFF$, then SNI will not be used by the listener to fetch the $\tt CONNECT_DATA$ parameters and the listener performs the usual TLS handshake with the client to fetch the connect request.



Default Value

ON

Values

- ON | TRUE | YES to enable processing of SNI value by listener
- OFF | FALSE | NO to disable processing of SNI value by listener

Example

USE_SNI_listener = OFF



Support for SNI is available in all versions starting 23.7, but not in earlier versions.

Related Topics

Oracle Al Database Net Services Administrator's Guide

8.4.24 VALID_NODE_CHECKING_REGISTRATION_listener_name

The *listener.ora* control parameter VALID_NODE_CHECKING_REGISTRATION_*listener_name* determines if valid node checking registration is performed, or if the subnet is allowed.

Purpose

To determine whether valid node checking registration is performed, or the subnet is allowed.

Usage Notes

- When set to on, valid node checking registration is performed at the listener for any incoming registration request, and only local IP addresses are allowed.
- Starting with Oracle Grid Infrastructure 12c, for a SCAN listener, if the VALID_NODE_CHECKING_REGISTRATION_listener_name and REGISTRATION_INVITED_NODES_listener_name parameters are set in the listener ora file, then the listener agent overwrites these parameters.

Default

on

Values

- off | 0 to specify valid node checking registration is off, and no checking is performed.
- on | 1 | local to specify valid node checking registration is on, and all local IP addresses can register. If a list of invited nodes is set, then all IP addresses, host names, or subnets in the list as well as local IP addresses are allowed.
- subnet | 2 to specify valid node checking registration is on, and all machines in the local subnets are allowed to register. If a list of invited nodes is set, then all nodes in the local subnets as well as all IP addresses, host names and subnets in the list are allowed.



Example

VALID_NODE_CHECKING_REGISTRATION_listener=on



Oracle Real Application Clusters Administration and Deployment Guide for information about valid node checking for registration

8.4.25 WALLET_LOCATION

Use the WALLET_LOCATION parameter to specify the location of Oracle wallets.

Purpose

To specify the directory path where an Oracle wallet is stored. Wallets securely contain certificates, secrets, private keys, and trust points used by Oracle Database.

Usage Notes

Where to set this parameter:

You can set WALLET_LOCATION in the listener.ora file to specify a common wallet location for all listeners. You can also set WALLET_LOCATION as part of address string of the listener in listener.ora to specify a different wallet location for each listener. For example:

```
net_service_name=
    (DESCRIPTION =
          (ADDRESS=(PROTOCOL=tcps)(HOST=sales-svr)(PORT=1234))
          (SECURITY=(WALLET LOCATION=DIRECTORY))
```

Storage of wallet files:

The password-protected wallet is stored in an <code>ewallet.p12</code> file. The auto-login and local auto-login wallets are stored in a <code>cwallet.sso</code> file.

For example, if an Oracle wallet is stored in the Microsoft Windows registry and the wallet's key (KEY) is SALESAPP, then the storage location of the password-protected wallet is HKEY_CURRENT_USER\SOFTWARE\ORACLE\WALLETS\SALESAPP\EWALLET.P12. The storage location of the auto-login and local auto-login wallets is HKEY_CURRENT_USER\SOFTWARE\ORACLE\WALLETS\SALESAPP\CWALLET.SSO.

Additional Parameters

Use SOURCE to specify the type of storage and storage location for wallets, as follows:

- METHOD: Type of storage
- METHOD_DATA: Storage location:
 - DIRECTORY: Location of wallet on the file system
 - KEY: Wallet type and location in the Microsoft Windows registry



Syntax and Examples

The syntax depends on the wallet as follows:

Wallet on the file system:

Microsoft certificate store:

```
WALLET_LOCATION=
  (SOURCE=
         (METHOD=mcs))
```

The key-value pair for MCS omits the METHOD_DATA parameter because MCS does not use wallets. Instead, Oracle PKI (public key infrastructure) applications obtain certificates, trust points and private keys directly from a user's profile.

Wallet in the Microsoft Windows registry:

Default

None

8.5 ADR Diagnostic Parameters for Oracle Net Listener

The diagnostic data for the critical errors is quickly captured and stored in the ADR for Oracle Net listener.

Since Oracle Database 11g, Oracle Database includes an advanced fault diagnosability infrastructure for preventing, detecting, diagnosing, and resolving problems. The problems are critical errors such as those caused by database code bugs, metadata corruption, and customer data corruption.

When a critical error occurs, it is assigned an incident number, and diagnostic data for the error, such as traces and dumps, are immediately captured and tagged with the incident



number. The data is then stored in the Automatic Diagnostic Repository (ADR), a file-based repository outside the database.

This section includes the parameters used when ADR is enabled. ADR is enabled by default. Non-ADR parameters listed in the listener.ora file are ignored when ADR is enabled.

The following listener.ora parameters are used when ADR is enabled (when DIAG_ADR_ENABLED is set to on):

• ADR BASE listener name

The ADR_BASE_listener_name parameter is a diagnostic parameter specifies the base directory that stores tracing and logging incidents when ADR is enabled.

DIAG ADR ENABLED listener name

The DIAG_ADR_ENABLED_listener_name is a diagnostic parameter of the listener.ora file. It indicates whether ADR is enabled.

LOG FILE NUM listener name

The LOG_FILE_NUM_listener_name is a diagnostic parameter of the listener.ora file that specifies the number of log file segments.

LOG FILE SIZE listener name

The LOG_FILE_SIZE_listener_name diagnostic parameter of thelistener.ora file specifies the size of each log file segment.

LOGGING listener name

The LOGGING_listener_name diagnostic parameter of the listener.ora file turns logging on or off.

TRACE LEVEL listener name

The TRACE_LEVEL_listener_name diagnostic parameter of the listener.ora file turns listener tracing on, at a specific level, or turns it off.

• TRACE TIMESTAMP listener name

The TRACE_TIMESTAMP_listener_name diagnostic parameter of the listener.ora file adds a time stamp to every trace event in the trace file for the listener.

8.5.1 ADR_BASE_listener_name

The ADR_BASE_listener_name parameter is a diagnostic parameter specifies the base directory that stores tracing and logging incidents when ADR is enabled.

Purpose

To specify the base directory that stores tracing and logging incidents when ADR is enabled.

Default

The default is ORACLE BASE, or ORACLE HOME/log if ORACLE BASE is not defined.

Values

Any valid directory path to a directory with write permission.

Example

ADR_BASE_listener=/oracle/network/trace



8.5.2 DIAG_ADR_ENABLED_listener_name

The DIAG_ADR_ENABLED_listener_name is a diagnostic parameter of the listener.ora file. It indicates whether ADR is enabled.

Purpose

To indicate whether ADR tracing is enabled.

Usage Notes

When the DIAG_ADR_ENABLED_listener_name parameter is set to on, then ADR file tracing is used. When the DIAG_ADR_ENABLED_listener_name parameter is set to off, then non-ADR file tracing is used.

Default

on

Values

on off

Example 8-8 Example

DIAG_ADR_ENABLED_listener=on

8.5.3 LOG_FILE_NUM_listener_name

The LOG_FILE_NUM_listener_name is a diagnostic parameter of the listener.ora file that specifies the number of log file segments.

Purpose

To specify the number of log file segments. At any point of time there can be only n log file segments where n is $log_{file_num_listener_name}$. If the log grows beyond this number, then the older segments are deleted.

Default

No default. If you don't specify a value, or set the value to zero, then the number of segments grows indefinitely.

Values

Any integer value.

Example 8-9

LOG_FILE_NUM_listener=3



8.5.4 LOG_FILE_SIZE_listener_name

The LOG_FILE_SIZE_listener_name diagnostic parameter of thelistener.ora file specifies the size of each log file segment.

Purpose

To specify the size of each log file segment. The size is in MB.

Default

300 MB

Values

Any integer value.

Example 8-10 Example

LOG_FILE_SIZE_listener=10

8.5.5 LOGGING_listener_name

The LOGGING_listener_name diagnostic parameter of the listener.ora file turns logging on or off.

Purpose

To turn logging on or off.

Usage Notes

This parameter is also applicable when non-ADR tracing is used.

Default

on

Values

on | off

Example

LOGGING_listener=on

8.5.6 TRACE_LEVEL_listener_name

The TRACE_LEVEL_listener_name diagnostic parameter of the listener.ora file turns listener tracing on, at a specific level, or turns it off.

Purpose

To turn listener tracing on, at a specific level, or to turn it off.



Usage Notes

This parameter is also applicable when non-ADR tracing is used.

Default

off | 0

Values

- off or 0 for no trace output
- user or 4 for user trace information
- admin or 10 for administration trace information
- support or 16 for Oracle Support Services trace information

Example

TRACE_LEVEL_listener=admin

8.5.7 TRACE_TIMESTAMP_listener_name

The TRACE_TIMESTAMP_listener_name diagnostic parameter of the listener.ora file adds a time stamp to every trace event in the trace file for the listener.

Purpose

To add a time stamp in the form of dd-mmm-yyyy hh:mi:ss:mil to every trace event in the trace file for the listener.

Usage Notes

This parameter is used with the <u>TRACE_LEVEL_listener_name</u> parameter. This parameter is also applicable when non-ADR tracing is used.

Default

on

Values

- on | true
- off | false

Example

TRACE_TIMESTAMP_listener=true

8.6 Non-ADR Diagnostic Parameters for Oracle Net Listener

This section lists the parameters used when ADR is disabled. The default value of DIAG_ADR_ENABLED_listener_name is on. Therefore, the DIAG_ADR_ENABLED_listener_name parameter must explicitly be set to off to use non-ADR tracing.



- LOG DIRECTORY listener name
- LOG_FILE_listener_name
- TRACE_DIRECTORY_listener_name
- TRACE FILE listener name
- TRACE FILEAGE listener name
- TRACE_FILELEN_listener_name
- TRACE_FILENO_listener_name

8.6.1 LOG_DIRECTORY_listener_name

Purpose

To specify the destination directory of the listener log file.

Usage Notes

Use this parameter when ADR is not enabled.

Default

ORACLE_HOME/network/log

Example

LOG_DIRECTORY_listener=/oracle/network/admin/log

8.6.2 LOG_FILE_listener_name

Purpose

To specify the name of the log file for the listener.

Usage Notes

Use this parameter when ADR is not enabled.

Default

listener.log

Example

LOG_FILE_listener=list.log

8.6.3 TRACE DIRECTORY listener_name

Purpose

To specify the destination directory of the listener trace file.

Usage Notes

Use this parameter when ADR is not enabled.



Default

ORACLE_HOME/network/trace

Example

TRACE_DIRECTORY_listener=/oracle/network/admin/trace

8.6.4 TRACE FILE *listener_name*

Purpose

To specify the name of the trace file for the listener.

Usage Notes

Use this parameter when ADR is not enabled.

Default

listener.trc

Example

TRACE_FILE_listener=list.trc

8.6.5 TRACE_FILEAGE_listener_name

Purpose

To specify the maximum age of listener trace files in minutes.

Usage Notes

When the age limit is reached, the trace information is written to the next file. The number of files is specified with the <u>TRACE_FILENO_listener_name</u> parameter. Use this parameter when ADR is not enabled.

Default

Unlimited

This is the same as setting the parameter to 0.

Example 8-11 Example

TRACE_FILEAGE_listener=60

8.6.6 TRACE_FILELEN_listener_name

Purpose

To specify the size of the listener trace files in kilobytes (KB).



Usage Notes

When the size is met, the trace information is written to the next file. The number of files is specified using the TRACE_FILENO_listener_name parameter. Use this parameter when ADR is not enabled.

Default

Unlimited

Example

TRACE_FILELEN_listener=100

8.6.7 TRACE_FILENO_listener_name

Purpose

To specify the number of trace files for listener tracing.

Usage Notes

When this parameter is set along with the <u>TRACE_FILELEN_listener_name</u> parameter, trace files are used in a cyclical fashion. The first file is filled first, then the second file, and so on. When the last file has been filled, the first file is re-used, and so on.

The trace file names are distinguished from one another by their sequence number. For example, if the default trace file of listener.trc is used, and this parameter is set to 3, then the trace files would be named listener1.trc, listener2.trc and listener3.trc.

In addition, trace events in the trace files are preceded by the sequence number of the file. Use this parameter when ADR is not enabled.

Default

1

Example

TRACE_FILENO_listener=3

8.7 Class of Secure Transports Parameters

The class of secure transports (COST) parameters specify a list of transports that are considered secure for administration and registration of a particular listener.

The COST parameters identify which transports are considered secure for that installation and whether the administration of a listener requires secure transports. Configuring these parameters is optional.

- SECURE REGISTER listener name
- Using COST Parameters in Combination
- <u>DYNAMIC REGISTRATION listener name</u>
 DYNAMIC_REGISTRATION_listener_name is a class of secure transports (COST) parameter and it enables or disables dynamic registration of a listener.



- SECURE_PROTOCOL_listener_name
- SECURE CONTROL listener name

(i) See Also

Oracle Database Net Services Administrator's Guide for additional information about COST parameters and listener security

8.7.1 SECURE_REGISTER_listener_name

Purpose

To specify the transports on which registration requests are to be accepted.

Usage Notes

If the SECURE_REGISTER_listener_name parameter is configured with a list of transport names, then only the connections arriving on the specified transports are able to register the service with the listener. Connections arriving by other transport protocols are refused. The following is an example:

```
SECURE_REGISTER_listener1 = (TCPS,IPC)
```

In the preceding example, registration requests are accepted only on TCPS and IPC transports.

If no values are entered for this parameter, then the listener accepts registration requests from any transport.

Syntax

```
SECURE_REGISTER_listener_name =
[(]transport1[,transport2, ....,transportn)]
```

In the preceding example, transport1, transport2, and transport are valid, installed transport protocol names.

If this parameter and <u>SECURE_CONTROL_listener_name</u> are configured, then they override the <u>SECURE_PROTOCOL_listener_name</u> parameter.

Example

```
LISTENER1=
(DESCRIPTION=
    (ADDRESS_LIST=
         (ADDRESS=(PROTOCOL=tcp)(HOST=sales-server)(PORT=1521))
         (ADDRESS=(PROTOCOL=ipc)(KEY=extproc))
         (ADDRESS=(PROTOCOL=tcps)(HOST=sales-server)(PORT=1522))))
SECURE REGISTER_listener1=tcps
```

8.7.2 Using COST Parameters in Combination

COST parameters can also be used in combination to further control which transports accept service registration and control commands.

In <u>Example 8-12</u>, control commands are accepted only on the IPC channel and the TCPS transport, and service registrations are accepted only on an IPC channel.



Example 8-12 Combining COST Parameters

```
LISTENER1=
(DESCRIPTION=
  (ADDRESS_LIST=
        (ADDRESS=(PROTOCOL=tcp)(HOST=sales-server)(PORT=1521))
        (ADDRESS=(PROTOCOL=ipc)(KEY=extproc))
        (ADDRESS=(PROTOCOL=tcps)(HOST=sales-server)(PORT=1522))))
SECURE_CONTROL_listener1=(tcps,ipc)
SECURE_REGISTER_listener1=ipc
```

In <u>Example 8-13</u>, control commands are accepted only on the TCPS transport, and service registrations are accepted only on the IPC channel.

Example 8-13 Combining COST Parameters

```
LISTENER1=
(DESCRIPTION=
  (ADDRESS_LIST=
        (ADDRESS=(PROTOCOL=tcp)(HOST=sales-server)(PORT=1521))
        (ADDRESS=(PROTOCOL=ipc)(KEY=extproc))
        (ADDRESS=(PROTOCOL=tcps)(HOST=sales-server)(PORT=1522))))
SECURE_CONTROL_listener1=tcps
SECURE_PROTOCOL_listener1=ipc
```

8.7.3 DYNAMIC_REGISTRATION_listener_name

DYNAMIC_REGISTRATION_listener_name is a class of secure transports (COST) parameter and it enables or disables dynamic registration of a listener.

Purpose

To enable or disable dynamic registration.

Usage Notes

Static registrations are not affected by this parameter.

Default

The default value is on. Unless this parameter is explicitly set to off, all registration connections are accepted.

Values

- on: The listener accepts dynamic registration.
- off: The listener refuses dynamic registration.

Example 8-14 Example

DYNAMIC_REGISTRATION_listener_name=on

8.7.4 SECURE PROTOCOL listener name

Purpose

To specify the transports on which administration and registration requests are accepted.



Usage Notes

If this parameter is configured with a list of transport names, then the control commands and service registration can happen only if the connection belongs to the list of transports.

If this parameter is not present and neither <u>SECURE_CONTROL_listener_name</u> or <u>SECURE_REGISTER_listener_name</u> are configured, then all supported transports accept control and registration requests.

If the <u>SECURE_CONTROL_listener_name</u> and <u>SECURE_REGISTER_listener_name</u> parameters are configured, then they override the <u>SECURE_PROTOCOL_listener_name</u> parameter.

Syntax

```
SECURE_PROTOCOL_listener_name =
[(]transport1[,transport2, ....,transportn)]
```

In the preceding syntax, transport1, transport2, and transportn are valid, installed transport protocol names.

Example

```
LISTENER1=
(DESCRIPTION=
    (ADDRESS_LIST=
          (ADDRESS=(PROTOCOL=tcp)(HOST=sales-server)(PORT=1521))
          (ADDRESS=(PROTOCOL=ipc)(KEY=extproc))
          (ADDRESS=(PROTOCOL=tcps)(HOST=sales-server)(PORT=1522))))
SECURE_PROTOCOL_listener1=tcps
```

8.7.5 SECURE CONTROL listener_name

Purpose

To specify the transports on which control commands are to be serviced.

Usage Notes

If the SECURE_CONTROL_listener_name parameter is configured with a list of transport names, then the control commands are serviced only if the connection is one of the listed transports. Connections arriving by other transport protocols are refused. The following is an example:

```
SECURE_CONTROL_listener1 = (TCPS,IPC)
```

In the preceding example, administration requests are accepted only on TCPS and IPC transports.

If no values are entered for this parameter, then the listener accepts any connection on any endpoint.

Syntax

```
SECURE_CONTROL_listener_name =
[(]transport1[,transport2, ...,transportn)]
```

In the preceding syntax, transport1, transport2, and transportn are valid, installed transport protocol names.



Example

```
LISTENER1=
(DESCRIPTION=
    (ADDRESS_LIST=
         (ADDRESS=(PROTOCOL=tcp)(HOST=sales-server)(PORT=1521))
         (ADDRESS=(PROTOCOL=ipc)(KEY=extproc))
         (ADDRESS=(PROTOCOL=tcps)(HOST=sales-server)(PORT=1522))))
SECURE_CONTROL_LISTENER1=tcps
```

Oracle Connection Manager Parameters

This chapter provides a complete listing of the cman. ora file configuration parameters.

- Overview of Oracle Connection Manager Configuration File
 Oracle Connection Manager configuration information is stored in the cman.ora file.
- Oracle Connection Manager Parameters

This section lists and describes the following cman.ora file parameters:

- Oracle Connection Manager in Traffic Director Mode Parameters
 This section lists and describes the cman.ora file parameters.
- ADR Diagnostic Parameters for Oracle Connection Manager
 The diagnostic data for critical errors is quickly captured and stored in the ADR for Oracle Connection Manager.
- Non-ADR Diagnostic Parameters for Oracle Connection Manager
 This section lists the parameters used when ADR is disabled:
- Oracle Connection Manager Tunneling Parameters
 This section lists the parameters that you must configure to enable tunneling.

9.1 Overview of Oracle Connection Manager Configuration File

Oracle Connection Manager configuration information is stored in the cman.ora file.

Oracle Connection Manager Configuration File

Oracle Connection Manager configuration information consists of the following elements:

- Protocol address of the Oracle Connection Manager listener
- Access control parameters
- Performance parameters

By default, the cman.ora file is located in the <code>ORACLE_HOME/network/admin</code> directory. You can also store the cman.ora file in the following locations:

- The directory specified by the TNS_ADMIN environment variable or registry value.
- On Linux and UNIX operating systems, the global configuration directory. For example, on the Oracle Solaris operating system, this directory is /var/opt/oracle.
- ORACLE_BASE_HOME/network/admin directory.
- ORACLE_HOME/network/admin directory.

Example 9-1 Sample cman.ora File

```
CMAN=
  (CONFIGURATION=
        (ADDRESS=(PROTOCOL=tcp)(HOST=proxysvr)(PORT=1521))
        (RULE_LIST=
              (RULE=(SRC=192.0.2.32/27)(DST=sales-server)(SRV=*)(ACT=accept))
```



```
(ACTION_LIST=(AUT=on)(MCT=120)(MIT=30)))
(RULE=(SRC=foo)(DST=hr-server)(SRV=cmon)(ACT=accept)))
(PARAMETER_LIST=
  (MAX_GATEWAY_PROCESSES=8)
  (MIN_GATEWAY_PRCESSSES=3)
  (DIAG_ADR_ENABLED=ON)
  (ADR_BASE=/oracle/log)))
```

cman.ora File Sections

ASO AUTHENTICATION FILTER={off | on}

- Listening address: Preceded by ADDRESS=, this section contains information pertinent to the listener. The ADDRESS parameter is required.
- Rule list: Preceded by RULE_LIST=, this section contains rule information. TheRULE parameter is listed in the rule list section of the file. The RULE parameter is required.
- Rule Group: Preceded by RULE_GROUP=, this section contains rule_list grouped by service names. You can use either the rule_group syntax or the rule_list syntax.
- Parameter list: Preceded by PARAMETER_LIST=, this section contains all other parameters
 including those listed in "ADR Diagnostic Parameters for Oracle Connection Manager",
 and "Non-ADR Diagnostic Parameters for Oracle Connection Manager".

The following parameters are allowed in the parameter list section of the cman.ora file. The default values are bold. To override the default setting for a parameter, enter the parameter and a nondefault value.

```
ADMIN_GROUP=user_group
CONNECTION STATISTICS={no | yes}
EVENT_GROUP={init_and_term | memory_ops | conn_hdlg | proc_mgmt | reg_and_load
| wake_up | timer | cmd_proc | relay}
IDLE_TIMEOUT=0 or greater
INBOUND CONNECT TIMEOUT=0 or greater. The default value is 60.
LOG_DIRECTORY=log_directory. The default value is ORACLE_HOME/network/log.
LOG_LEVEL={off | user | admin | support}
MAX_CMCTL_SESSIONS= Any positive number. The default value is 4.
MAX CONNECTIONS= A value between 1 and 1024. The default value is 256.
MAX GATEWAY PROCESSES= Any number greater than the minimum number of gateway
processes up to 64. The default value is 16.
MIN GATEWAY PROCESSES= Any positive number less than or equal to 64. Must be less than
or equal to the maximum number of gateway processes. The default value is 2.
OUTBOUND CONNECT TIMEOUT=0 or greater
SESSION_TIMEOUT=0 or greater
{\tt TRACE\_DIRECTORY=trace\_directory}. \ \ {\tt The\ default\ value\ is\ ORACLE\_HOME/network/trace}.
TRACE_FILELEN= Any positive number. The default value is 0 (zero).
TRACE FILENO= Any positive number. The default value is 0 (zero).
TRACE_LEVEL={off | user | admin | support}
```



```
TRACE_TIMESTAMP={off | on}
(PARAMETER_LIST=
      (ASO_AUTHENTICATION_FILTER=ON)
      (ADMIN_GROUP=dba)
      (CONNECTION_STATISTICS=NO)
      (EVENT_GROUP=INIT_AND_TERM, MEMORY_OPS, PROCESS_MGMT)
      (IDLE_TIMEOUT=30)
      (INBOUND_CONNECT_TIMEOUT=30)
      (LOG_DIRECTORY=/home/user/network/admin/log)
      (LOG_LEVEL=SUPPORT)
      (MAX_CMCTL_SESSIONS=6)
      (MAX_CONNECTIONS=512)
      (MAX_GATEWAY_PROCESSES=10)
      (MIN_GATEWAY_PROCESSES=4)
      (OUTBOUND_CONNECT_TIMEOUT=30)
      (SESSION_TIMEOUT=60)
      (TRACE_DIRECTORY=/home/user/network/admin/trace)
      (TRACE_FILELEN=100)
      (TRACE_FILENO=2)
      (TRACE_LEVEL=SUPPORT)
      (TRACE TIMESTAMP=ON)
      (VALID_NODE_CHECKING_REGISTRATION=ON)
      (REGISTRATION_EXCLUDED_NODES = 10.1.26.*)
      (REGISTRATION_INVITED_NODES = 10.1.35.*)
```

9.2 Oracle Connection Manager Parameters

This section lists and describes the following cman.ora file parameters:

ADDRESS

The ADDRESS networking parameter specifies the protocol address of Oracle Connection Manager.

ADMIN GROUP

The ADMIN_GROUP parameter of the cman.ora file specifies the user group that can perform the Oracle Connection Manager (CMAN) administration.

ASO AUTHENTICATION FILTER

It is a networking parameter for Oracle Connection Manager. It instructs Oracle Connection Manager to check the connection requests for Secure Network Services (SNS).

BANDWIDTH

Use the BANDWIDTH parameter to limit all the connections of a service to a specified value in bytes per second.

CLIENT DN RULE MATCH

Use this parameter to enable filtering of Transport Layer Security (TLS) connections using DN_LIST in $RULE_GROUP$.

COMPRESSION

The COMPRESSION parameter of the cman.ora file enables or disables data compression.

COMPRESSION LEVELS

The COMPRESSION_LEVELS networking parameter of the cman.ora file specifies the CPU usage and compression ratio.



COMPRESSION THRESHOLD

The COMPRESSION_THRESHOLD parameter of the cman.ora file specifies the minimum data size for which compression is required.

CONNECTION STATISTICS

 ${\tt CONNECTION_STATISTICS} \ networking \ parameter \ of \ the \ {\tt cman.ora} \ file \ specifies \ whether \ the \\ {\tt SHOW_CONNECTIONS} \ command \ displays \ connection \ statistics.$

DN LIST

Use this parameter to specify a list of common names (CN) that are allowed to connect to a service using Transport Layer Security (TLS).

ENABLE IP FORWARDING

Use the cman.ora parameter ENABLE_IP_FORWARDING to forward client IP address to the database server.

EVENT GROUP

EVENT_GROUP networking parameter of the cman.ora file specifies which event groups are logged.

EXPIRE TIME

The EXPIRE_TIME networking parameter of cman.ora file specifies a time interval, in minutes, to send a check to verify that client/gateway connections are active.

GROUP

Use the GROUP parameter to specify a rule_list for a service.

• IDLE TIMEOUT

The IDLE_TIMEOUT parameter of the cman.ora file specifies the time that an established connection can remain active without transmitting data.

INBOUND CONNECT TIMEOUT

The INBOUND_CONNECT_TIMEOUT parameter of the cman.ora file specifies the time limit that the Oracle Connection Manager listener waits for a valid connection before timing out.

IP RATE COUNT

The IP_RATE_COUNT parameter of the cman.ora file specifies the maximum number of client connections allowed from an IP address in the specified time interval.

IP RATE INTERVAL

The IP_RATE_INTERVAL parameter of the cman.ora file specifies the number of seconds for which Oracle Connection Manager accepts new connections from a single IP address.

IP RATE BLOCK

The IP_RATE_BLOCK parameter of the cman.ora file specifies the time duration, in minutes, for which an IP address is blocked after exceeding the defined IP rate limit.

LOG FILE NUM

The ${\tt LOG_FILE_NUM}$ networking parameter of the ${\tt cman.ora}$ file specifies the number of log file segments.

LOG FILE SIZE

LOG_FILE_SIZE networking parameter of thecman.ora file specifies the size of each log file segment.

LOG SUPPRESS NODES

Use the cman.ora parameter $LOG_SUPPRESS_NODES$ to specify the addresses for which you want to disable logging of health check errors in the Oracle Connection Manager (CMAN) log file.



MAX ALL CONNECTIONS

The MAX_ALL_CONNECTIONS parameter of the cman.ora file specifies the maximum number of concurrent registration and client connection sessions that can be supported by Oracle Connection Manager.

MAX CMCTL SESSIONS

The MAX_CMCTL_SESSIONS parameter of the cman.ora file specifies the maximum number of concurrent local or remote sessions.

MAX BANDWIDTH GROUP

Use the MAX_BANDWIDTH_GROUP parameter to specify the maximum number of services that can be configured.

MAX CONNECTIONS

The MAX_CONNECTIONS parameter of the cman.ora file specifies the maximum number of connection slots that a gateway process can handle.

MAX GATEWAY PROCESSES

The MAX_GATEWAY_PROCESSES parameter of the cman.ora file specifies the maximum number of gateway processes supported by Oracle Connection Manager.

MAX REG CONNECTIONS

The $\mathtt{MAX}_\mathtt{REG}_\mathtt{CONNECTIONS}$ parameter of the $\mathtt{cman.ora}$ file specifies the maximum number of concurrent registration connection sessions that can be supported by Oracle Connection Manager.

MIN GATEWAY PROCESSES

The MIN_GATEWAY_PROCESSES parameter of the cman.ora file specifies the minimum number of gateway processes supported by Oracle Connection Manager.

NEXT HOP

The NEXT_HOP parameter provides static routing of client connections from Oracle Connection Manager (Oracle CMAN).

OUTBOUND CONNECT TIMEOUT

The <code>OUTBOUND_CONNECT_TIMEOUT</code> parameter of the <code>cman.ora</code> file specifies the time limit that the Oracle Connection Manager instance waits for a valid connection to be established before timing out.

REGISTRATION EXCLUDED NODES

The Oracle Connection Manager parameter file (cman.ora)

REGISTRATION_EXCLUDED_NODES specifies the list of nodes that cannot register with the listener.

REGISTRATION_INVITED_NODES

The Oracle Connection Manager parameter file (cman.ora) REGISTRATION_EXCLUDED_NODES parameter specifies the list of node that can register with the listener.

REST ADDRESS

Use the REST_ADDRESS parameter to configure REST endpoint hostname and port. Oracle CMAN listens to tops endpoint based on the specified hostname and port.

RULE

The RULE parameter of the cman.ora file specifies an access control rule list to filter incoming connections.

• SDU

Use the SDU parameter to specify the session data unit (SDU) size for connections.

SERVICE_RATE

The SERVICE_RATE parameter of cman.ora file specifies incoming connection rate that is allowed per service for an instance.



SESSION TIMEOUT

The SESSION_TIMEOUT parameter of the cman.ora file specifies the maximum time in seconds allowed for a user session.

SSL CIPHER SUITES

Use the SSL_CIPHER_SUITES parameter to control the combination of authentication, encryption, and data integrity algorithms used by Transport Layer Security (TLS).

SSL CLIENT AUTHENTICATION

Use the SSL_CLIENT_AUTHENTICATION parameter to specify whether the database client is authenticated using Transport Layer Security (TLS).

SSL VERSION

Use the SSL_VERSION parameter to define valid Transport Layer Security (TLS) versions to be used for connections.

• TRACE FILE

The ${\tt TRACE_FILE}$ parameter of the ${\tt cman.ora}$ file specifies the directory for Oracle Connection Manager trace files.

USE SERVICE AS TNSNAMES ALIAS

Use this parameter for static routing of client connections from Oracle connection manager based on client's service name.

USE SID AS SERVICE

The USE_SID_AS_SERVICE Oracle Connection Manager parameter enables the system identifier (SID) in the connect descriptor to be interpreted as a service name when a user attempts a database connection.

USE SNI

Use cman.ora parameter USE_SNI to enable or disable the use of Service Name Indication (SNI) by the CMAN listener for selecting an appropriate service handler without the TLS negotiation and also to enable or disable the setting of SNI value in outgoing connection by the gateway process.

VALID NODE CHECKING REGISTRATION

The VALID_NODE_CHECKING_REGISTRATION parameter of the cman.ora file specifies whether valid node checking registration is performed.

WALLET LOCATION

Use the WALLET_LOCATION parameter to specify the location of Oracle wallets.

9.2.1 ADDRESS

The ADDRESS networking parameter specifies the protocol address of Oracle Connection Manager.

Purpose

To specify the protocol address of Oracle Connection Manager (CMAN).

Syntax

(ADDRESS=(PROTOCOL=protocol)(HOST=host name)(PORT=port number)

Usage Notes

You can tag CMAN addresses as admin endpoints. This is helpful in cases where you do not want to close all listening endpoints, so that Oracle Connection Manager Control utility



continues to run admin commands using tagged listening endpoints. To do so, set the value of the ADMIN parameter to YES using the following syntax:

```
(ADDRESS=(PROTOCOL=protocol)(HOST=host_name)(PORT=port_number)(ADMIN=YES))
```

You can configure CMAN to receive the client's IP address from a load balancer by enabling the PROXY protocol in CMAN. You must also enable the PROXY protocol in your load balancer to be able to forward the client connection information to the CMAN backend. CMAN supports both PROXY protocol version 1 and version 2 on non-windows platforms. To enable the PROXY protocol in CMAN, add EXPECTED_PROXIES in the listen address for the port that receives the PROXY protocol. The EXPECTED_PROXIES parameter is a comma separated list of load balancer IP addresses from which CMAN will accept the PROXY protocol. The listen address without the EXPECTED_PROXIES must precede the PROXY protocol enabled endpoint address in the cman.ora file.

```
(ADDRESS_LIST=
(ADDRESS=(PROTOCOL=tcp)(HOST=host_name)(PORT=port_number_1))
(ADDRESS=(PROTOCOL=tcp)(HOST=host_name)(PORT=port_number_2)
(EXPECTED_PROXIES=ip_address_1, ip_address_2 . . . ip_address_n)))
```

Note

- Database registration is not supported on the PROXY protocol enabled endpoint.
- If your load balancer supports client IP address preservation, then enabling PROXY protocol in the load balancer may not be required. Review your load balancer documentation for information on configuring the PROXY protocol.

Example

```
(\verb|ADDRESS=(PROTOCOL=tcp)|(HOST=sales-server)|(PORT=1521)|
```

Related Topics

CLOSE NON ADMIN ENDPOINTS

Use the Oracle Connection Manager Control Utility command CLOSE NON_ADMIN_ENDPOINTS to close all non-admin listening endpoints.

• LOG_SUPPRESS_NODES

Use the cman.ora parameter LOG_SUPPRESS_NODES to specify the addresses for which you want to disable logging of health check errors in the Oracle Connection Manager (CMAN) log file.

9.2.2 ADMIN_GROUP

The $ADMIN_GROUP$ parameter of the cman.ora file specifies the user group that can perform the Oracle Connection Manager (CMAN) administration.

Purpose

To allow users of the specified group to perform CMAN administration operations. Users of the group are allowed to run Oracle Connection Manager control utility commands, such as show status, show services, show gateways, show rules, and so on.



Usage Notes

You can include ADMIN_GROUP parameter in the PARAMETER_LIST section of the cman.ora file to specify the group that can run CMAN control utility commands and carry out administration operations.

Default

By default, only CMAN user can perform the connection manager administration operations.

Example

ADMIN GROUP=dba

Related Topics

Oracle Connection Manager Control Utility Commands
 Use Oracle Connection Manager Control utility commands to manage and configure
 Oracle Connection Manager instances.

9.2.3 ASO_AUTHENTICATION_FILTER

It is a networking parameter for Oracle Connection Manager. It instructs Oracle Connection Manager to check the connection requests for Secure Network Services (SNS).

Purpose

To specify whether Oracle Database security authentication settings must be used by the client.

Usage Notes

The global setting can be overridden by a rule-level setting in ACTION LIST.

Values

- on to instruct Oracle Connection Manager to reject connection requests that are not using Secure Network Services (SNS). SNS is part of Oracle Database security.
- off to instruct Oracle Connection Manager not to check for SNS between the client and server. This is the default.

9.2.4 BANDWIDTH

Use the ${\tt BANDWIDTH}$ parameter to limit all the connections of a service to a specified value in bytes per second.

Purpose

To specify a limit on the number of bytes transmitted per second.

Usage Notes

You must include this parameter in the parameter_list section of the cman.ora file.

You must also set the cman.ora parameter MAX_BANDWIDTH_GROUP, which is a mandatory parameter to enable the bandwidth functionality.



Example

BANDWIDTH=524288

Related Topics

MAX BANDWIDTH GROUP

Use the MAX_BANDWIDTH_GROUP parameter to specify the maximum number of services that can be configured.

9.2.5 CLIENT DN RULE MATCH

Use this parameter to enable filtering of Transport Layer Security (TLS) connections using DN_LIST in RULE_GROUP.

Purpose

A TLS connection is allowed only if there is a <code>GROUP</code> specified in <code>RULE_GROUP</code> for the requested service. This <code>GROUP</code> must be configured with <code>DN_LIST</code>.

Values

ON, OFF. By default the value is set to OFF.

Example

CLIENT_DN_RULE_MATCH=ON

9.2.6 COMPRESSION

The COMPRESSION parameter of the cman.ora file enables or disables data compression.

Purpose

To enable or disable data compression. If both the Oracle Connection Manager and the other end (server or client or Oracle Connection Manager) have this parameter set to on, then compression is used for the connection.

Default

off

Values

- on to enable data compression.
- off to disable data compression.

Example

COMPRESSION=on



9.2.7 COMPRESSION_LEVELS

The COMPRESSION_LEVELS networking parameter of the cman.ora file specifies the CPU usage and compression ratio.

Purpose

To specify the compression level.

Usage Notes

The compression levels are used at the time of negotiation to verify which levels are used at both ends, and select one level.

Default

low

Values

- low for low CPU usage and a low compression ratio.
- high for high CPU usage and a high compression ratio.

Example 9-2 Example

COMPRESSION_LEVELS=high, low

9.2.8 COMPRESSION THRESHOLD

The COMPRESSION_THRESHOLD parameter of the cman.ora file specifies the minimum data size for which compression is required.

Purpose

To specify the minimum data size, in bytes, for which compression is required.

Usage Notes

Compression is not be done if the size of the data to be sent is less than this value.

Default

1024 bytes

Example

COMPRESSION THRESHOLD=1024

9.2.9 CONNECTION_STATISTICS

 ${\tt CONNECTION_STATISTICS} \ \ \textbf{networking parameter of the } \ {\tt cman.ora} \ \ \textbf{file specifies whether the } \\ {\tt SHOW_CONNECTIONS} \ \ \textbf{command displays connection statistics}.$

Purpose

To specify whether the SHOW_CONNECTIONS command displays connection statistics.



Usage Notes

The global setting can be overridden by a rule-level setting in ACTION_LIST.

Values

- yes to display statistics.
- no to not display statistics. This is the default.

9.2.10 DN LIST

Use this parameter to specify a list of common names (CN) that are allowed to connect to a service using Transport Layer Security (TLS).

Purpose

An incoming TLS connection is allowed only if the string provided in common name (CN) of the distinguished name (DN) matches with at least one value in the list of values provided in the DN LIST parameter.

Usage Notes

DN_LIST is a comma separated list of common names. The values in the DN_LIST parameter is matched only when the client_dn_rule_match parameter is set to ON.

You must configure DN_LIST inside DESCRIPTION of the GROUP parameter.

Example

```
(GROUP =
          (DESCRIPTION = (NAME = service_name)(DN_LIST = phx,blr))
          (RULE_LIST =
           (RULE=...)
)
```

9.2.11 ENABLE_IP_FORWARDING

Use the cman.ora parameter ENABLE_IP_FORWARDING to forward client IP address to the database server.

Purpose

When set to ON, Oracle Connection Manager (CMAN) forwards the client source address as seen by it to the database server.

Usage Notes

In addition to the <code>ENABLE_IP_FORWARDING</code> parameter, you must set the <code>TCP.ALLOWED_PROXIES</code> parameter in the server-side <code>sqlnet.ora</code> file. The <code>TCP.ALLOWED_PROXIES</code> parameter specifies a list of the CMAN instances that can forward client address.

You can use the SYS_CONTEXT ('USERENV', 'IP_ADDRESS') function to query the forwarded client address details.



Values

- ON | TRUE | YES | 1: To enable client address forwarding
- OFF | FALSE | NO | 0: To disable client address forwarding

Default

OFF

Example

ENABLE_IP_FORWARDING=ON

Related Topics

TCP.ALLOWED PROXIES

Use the sqlnet.ora parameter TCP.ALLOWED_PROXIES to specify a list of the Oracle Connection Manager (CMAN) addresses that can forward client IP address to the database server.

Oracle Al Database SQL Language Reference

9.2.12 EVENT_GROUP

EVENT_GROUP networking parameter of the cman.ora file specifies which event groups are logged.

Purpose

To specify which event groups are logged.

Usage Notes

Multiple events may be designated using a comma-delimited list.

Values

- alert for alert notifications.
- cmd proc for command processing.
- conn_hdlg for connection handling.
- init_and_term for initialization and termination.
- memory_ops for memory operations.
- proc_mgmt for process management.
- reg_and_load for registration and load update.
- relay for events associated with connection control blocks.
- timer for gateway timeouts.
- wake_up for events related to Connection Manager Administration (CMADMIN) wake-up queue.





(i) Note

The event group ALERT cannot be turned off.

9.2.13 EXPIRE TIME

The EXPIRE TIME networking parameter of cman.ora file specifies a time interval, in minutes, to send a check to verify that client/gateway connections are active.

Purpose

To specify a time interval, in minutes, to send a check to verify that client/server connections are active.

Usage Notes

Setting a value greater than 0 ensures that connections are not left open indefinitely, due to an unusual client termination. If the system supports TCP keepalive tuning, then Oracle Net Services automatically uses the enhanced detection model, and tunes the TCP keepalive parameters

If the probe finds a terminated connection, or a connection that is no longer in use, then it returns an error, causing the server process to exit.

This parameter is primarily intended for the database server, which typically handles multiple connections at any one time.

Limitations on using this terminated connection detection feature are:

- It is not allowed on bequeathed connections.
- Though very small, a probe packet generates additional traffic that may downgrade network performance.
- Depending on which operating system is in use, the server may need to perform additional processing to distinguish the connection probing event from other events that occur. This can also result in degraded network performance.

Values

- 0: To disable terminated connection detection.
- Any number greater than 0: To enable terminated connection detection. The number equals the time interval in minutes.

Default

Example 9-3 Example

EXPIRE_TIME=10



9.2.14 GROUP

Use the GROUP parameter to specify a rule_list for a service.

Purpose

This parameter is listed in the $RULE_GROUP$ section of the cman.ora file preceded by $RULE_GROUP=$.

Syntax

```
(GROUP =
    (DESCRIPTION = (NAME = service_name))
    (RULE_LIST =
          (RULE=...)
)
```

Usage Notes

The service name (SRV =) in the rule should match the service_name specified in the NAME parameter. Alternatively, you can specify the service name using an asterisk *.

You can configure a DEFAULT_GROUP in RULE_GROUP. The rules that you specify in this section applies to those services that do not have an explicit GROUP. You do not need to specify DESCRIPTION inside a DEFAULT GROUP.

Example

```
(RULE_GROUP=
     (GROUP =
       (DESCRIPTION = (NAME = sales.us.example.com))
       (RULE_LIST =
         (RULE=
         (SRC=client1-pc)
         (DST=sales-server)
         (SRV=*)
         (ACT=reject))
       )
     (GROUP =
       (DESCRIPTION = (NAME = hr.us.example.com))
       (RULE_LIST =
         (RULE=
           (SRC=192.0.2.45)
           (DST=192.0.2.200)
           (SRV=*)
           (ACT=accept))
       )
     (DEFAULT_GROUP =
       (RULE_LIST=
         (RULE=(SRC=*)(DST=*)(SRV=cmon)(ACT=accept)))
```



)

9.2.15 IDLE_TIMEOUT

The IDLE_TIMEOUT parameter of the cman.ora file specifies the time that an established connection can remain active without transmitting data.

Purpose

To specify the amount of time that an established connection can remain active without transmitting data.

Usage Notes

The global setting can be overridden by a rule-level setting in ACTION_LIST.

Values

- 0 to disable the timeout. This is the default.
- Any number greater than 0 to enable the timeout. The number equals the timeout period in seconds.

9.2.16 INBOUND_CONNECT_TIMEOUT

The INBOUND_CONNECT_TIMEOUT parameter of the cman.ora file specifies the time limit that the Oracle Connection Manager listener waits for a valid connection before timing out.

Purpose

To specify how long, in seconds, the Oracle Connection Manager listener waits for a valid connection from a client or another instance of Oracle Connection Manager.

Values

- 60 sec is the default. Use value 0 to disable timeout.
- Any number greater than ${\tt 0}$ to enable the timeout. The number equals the timeout period in seconds.

Example

INBOUND_CONNECT_TIMEOUT=30

9.2.17 IP RATE COUNT

The IP_RATE_COUNT parameter of the cman.ora file specifies the maximum number of client connections allowed from an IP address in the specified time interval.

Purpose

To enforce IP rate limit on the number of client connections allowed to Oracle Connection Manager (CMAN) from a single IP address. This security feature enables you to protect your database against potential denial-of-service (DoS) attacks.



Usage Notes

Use the IP_RATE_COUNT parameter under the PARAMETER_LIST section of the CMAN configuration. When set to a value greater than 1, the specified IP rate limit is enforced at the CMAN endpoint level.

You can use this parameter along with the optional IP_RATE_INTERVAL and IP_RATE_BLOCK parameters. IP_RATE_INTERVAL allows you to specify the number of seconds for which IP_RATE_COUNT connections are accepted. IP_RATE_BLOCK allows you to specify the duration for which the IP address is blocked after exceeding the defined IP_RATE_COUNT per IP_RATE_INTERVAL limit.

Default

None

Value

Any number greater than 1

Example

```
CMAN=
    (CONFIGURATION=
          (ADDRESS=(PROTOCOL=tcp)(HOST=proxysvr)(PORT=1521))
          (PARAMETER_LIST=(IP_RATE_COUNT=512)))
```

Related Topics

- Oracle Al Database Net Services Administrator's Guide
- IP RATE INTERVAL

The IP_RATE_INTERVAL parameter of the cman.ora file specifies the number of seconds for which Oracle Connection Manager accepts new connections from a single IP address.

IP RATE BLOCK

The IP_RATE_BLOCK parameter of the cman.ora file specifies the time duration, in minutes, for which an IP address is blocked after exceeding the defined IP rate limit.

9.2.18 IP RATE INTERVAL

The IP_RATE_INTERVAL parameter of the cman.ora file specifies the number of seconds for which Oracle Connection Manager accepts new connections from a single IP address.

Purpose

To specify the number of seconds for which IP_RATE_COUNT connections are accepted. This security feature enforces IP rate limit on client connections and thus protects your database against potential denial-of-service (DoS) attacks.

Usage Notes

This is an optional parameter. You can use it under the PARAMETER_LIST section along with the IP_RATE_COUNT parameter. IP_RATE_COUNT allows you to specify the number of connections allowed from an IP address.



You can also set the optional IP_RATE_BLOCK parameter to specify the duration for which the IP address is blocked after exceeding the defined IP RATE COUNT per IP RATE INTERVAL limit.

Default

1 second

Value

Any number less than or equal to 60. The number equals the time duration in seconds.

Example

```
CMAN=
    (CONFIGURATION=
          (ADDRESS=(PROTOCOL=tcp)(HOST=proxysvr)(PORT=1521))
          (PARAMETER LIST=(IP RATE INTERVAL=5)))
```

Related Topics

- Oracle Al Database Net Services Administrator's Guide
- IP RATE COUNT

The IP_RATE_COUNT parameter of the cman.ora file specifies the maximum number of client connections allowed from an IP address in the specified time interval.

IP RATE BLOCK

The IP_RATE_BLOCK parameter of the cman.ora file specifies the time duration, in minutes, for which an IP address is blocked after exceeding the defined IP rate limit.

9.2.19 IP_RATE_BLOCK

The IP_RATE_BLOCK parameter of the cman.ora file specifies the time duration, in minutes, for which an IP address is blocked after exceeding the defined IP rate limit.

Purpose

To specify the time duration for which an IP address is blocked from establishing new connections. This security feature enforces IP rate limit on client connections and thus protects your database against potential denial-of-service (DoS) attacks.

Usage Notes

This is an optional parameter. You can use it under the PARAMETER_LIST section along with the IP_RATE_COUNT parameter. IP_RATE_COUNT allows you to specify the number of connections allowed from an IP address.

You can also set the optional IP_RATE_INTERVAL parameter to specify the number of seconds for which IP_RATE_COUNT connections are accepted. The IP address is blocked after exceeding the defined IP_RATE_COUNT per IP_RATE_INTERVAL limit.

Default

15 minutes

Value

Any number greater than 0. The number equals the time duration in minutes.



Example

CMAN=

```
(CONFIGURATION=
     (ADDRESS=(PROTOCOL=tcp)(HOST=proxysvr)(PORT=1521))
     (PARAMETER_LIST=(IP_RATE_BLOCK=30)))
```

Related Topics

- Oracle Al Database Net Services Administrator's Guide
- IP RATE COUNT

The IP_RATE_COUNT parameter of the cman.ora file specifies the maximum number of client connections allowed from an IP address in the specified time interval.

IP RATE INTERVAL

The IP_RATE_INTERVAL parameter of the cman.ora file specifies the number of seconds for which Oracle Connection Manager accepts new connections from a single IP address.

9.2.20 LOG_FILE_NUM

The LOG_FILE_NUM networking parameter of the cman.ora file specifies the number of log file segments.

Purpose

To specify the number of log file segments. At any point of time there can be only n log file segments where n is LOG_FILE_NUM and if the log grows beyond this number, then the older segments are deleted.

Default

No default. Number of segments grow indefinitely, if not specified or set to zero.

Value

Any integer value up to the maximum integer.

Example

LOG_FILE_NUM=3

9.2.21 LOG_FILE_SIZE

LOG_FILE_SIZE networking parameter of thecman.ora file specifies the size of each log file segment.

Purpose

To specify the size of each log file segment. The size is in MB.

Default

300 MB



Values

Any integer value.

Example 9-4 Example

LOG_FILE_SIZE=10

9.2.22 LOG_SUPPRESS_NODES

Use the cman.ora parameter LOG_SUPPRESS_NODES to specify the addresses for which you want to disable logging of health check errors in the Oracle Connection Manager (CMAN) log file.

Purpose

A CMAN frontend component, such as a load balancer, may perform periodic health checks by connecting to CMAN endpoint at the backend followed by immediately disconnecting from it. These health check operations generate error entries in the CMAN log file and are logged as connect failures. You can set this parameter to disable logging of such errors.

Usage Notes

Set this parameter in the PARAMETER_LIST section of the cman.ora file.

The list of addresses can include host names or CIDR notation for IPv4 and IPv6 addresses. The wildcard format (*) is supported for IPv4 addresses.

The presence of a host name in the list results in the inclusion of all IP addresses mapped to the host name. The host name must be consistent with the public network interface.

Value

LOG SUPPRESS NODES=(list of load balancer addresses)

list of load balancer addresses specifies valid nodes, subnet IP addresses, or names for which you want to disable logging.

Default

None

Example

LOG SUPPRESS NODES=(10.1.35.*, 10.1.34.0/24, 2001:DB8:fe38:7303, node1)

9.2.23 MAX_ALL_CONNECTIONS

The MAX_ALL_CONNECTIONS parameter of the cman.ora file specifies the maximum number of concurrent registration and client connection sessions that can be supported by Oracle Connection Manager.

Purpose

To specify the maximum number of concurrent registration and client connection sessions that can be supported by Oracle Connection Manager.



Usage Notes

This number includes registration connections from databases, and ongoing client connection establishment requests. After a connection is established, the clients do not maintain a connection to the listener. This limit only applies to client connections that are in the initial connection establishment phase from a listener perspective.

Default

Operating system-specific

Example

MAX_ALL_CONNECTIONS=40

9.2.24 MAX_CMCTL_SESSIONS

The MAX_CMCTL_SESSIONS parameter of the cman.ora file specifies the maximum number of concurrent local or remote sessions.

Purpose

To specify the maximum number of concurrent local or remote sessions of the Oracle Connection Manager control utility allowable for a given instance.

Usage Notes

One of the sessions must be a local session.

Value

Any number of sessions can be designated.

Example

MAX_CMCTL_SESSIONS=6

9.2.25 MAX_BANDWIDTH_GROUP

Use the MAX_BANDWIDTH_GROUP parameter to specify the maximum number of services that can be configured.

Purpose

This parameter is mandatory to enable the bandwidth functionality.

Usage Notes

Configure this parameter to a value of maximum services that your system supports. Add this parameter in the parameter section of the cman.ora file.

You can also configure this parameter with an additional 20% to 100% buffer, depending upon how often the services are created and destroyed in the system.

Example

MAX BANDWIDTH GROUP=100



Related Topics

BANDWIDTH

Use the BANDWIDTH parameter to limit all the connections of a service to a specified value in bytes per second.

9.2.26 MAX_CONNECTIONS

The ${\tt MAX_CONNECTIONS}$ parameter of the cman.ora file specifies the maximum number of connection slots that a gateway process can handle.

Purpose

To specify the maximum number of connection slots that a gateway process can handle.

Values

Any number in the range of 1 to 1024.

Default

The default value is 256.

Example

MAX_CONNECTIONS=100

9.2.27 MAX_GATEWAY_PROCESSES

The MAX_GATEWAY_PROCESSES parameter of the cman.ora file specifies the maximum number of gateway processes supported by Oracle Connection Manager.

Purpose

To specify the maximum number of gateway processes that an instance of Oracle Connection Manager supports.

Value

The number designated must be greater than the minimum number of gateway processes. The maximum is 64.

Default

The default value is 16.

Example

MAX_GATEWAY_PROCESSES=8



9.2.28 MAX_REG_CONNECTIONS

The MAX_REG_CONNECTIONS parameter of the cman.ora file specifies the maximum number of concurrent registration connection sessions that can be supported by Oracle Connection Manager.

Purpose

To specify the maximum number of concurrent registration connection sessions that can be supported by Oracle Connection Manager.

Default

512

Example

MAX_REG_CONNECTIONS=20

9.2.29 MIN_GATEWAY_PROCESSES

The MIN_GATEWAY_PROCESSES parameter of the cman.ora file specifies the minimum number of gateway processes supported by Oracle Connection Manager.

Purpose

To specify the minimum number of gateway processes that an instance of Oracle Connection Manager supports.

Value

Any number of sessions can be designated up to 64.

The value can be any positive number less than or equal to 64. Must be less than or equal to the maximum number of gateway processes.

Default

The default value is 2.

Example

MIN_GATEWAY_PROCESSES=4

9.2.30 NEXT_HOP

The NEXT_HOP parameter provides static routing of client connections from Oracle Connection Manager (Oracle CMAN).

Purpose

To specify a fixed address for Oracle CMAN to connect and to relay all client connection requests.



Usage Notes

This parameter contains the next hop address to which Oracle CMAN should connect to, whenever there is a client connection to it. This parameter provides static routing of client connections from Oracle CMAN and does not require service registration.

Values

You must specify this parameter in the CONFIGURATION section. Use description or address list to specify multiple addresses along with other characteristics such as <code>load_balance</code> and <code>failover</code>.

Default

Not enabled.

Example

```
CMAN=
(CONFIGURATION=
    (ADDRESS=(PROTOCOL=tcp)(HOST=proxysvr)(PORT=4555))
    (rule_list=(rule=(src=*)(dst=*)(srv=*)(act=accept)))
    (PARAMETER_LIST=
         (MAX_GATEWAY_PROCESSES=8)
         (MIN_GATEWAY_PRCESSSES=3))
    (NEXT_HOP=(ADDRESS=(PROTOCOL=tcps)(HOST=proxysvr1)(PORT=1555))
    )
```

9.2.31 OUTBOUND_CONNECT_TIMEOUT

The OUTBOUND_CONNECT_TIMEOUT parameter of the cman.ora file specifies the time limit that the Oracle Connection Manager instance waits for a valid connection to be established before timing out.

Purpose

To specify the length of time in seconds that the Oracle Connection Manager instance waits for a valid connection to be established with the database server or with another Oracle Connection Manager instance.

Values

- 60 to disable the timeout. This is the default.
- Any number greater than 0 to enable the timeout. The number equals the timeout period in seconds.

Example

OUTBOUND_CONNECT_TIMEOUT=30



9.2.32 REGISTRATION_EXCLUDED_NODES

The Oracle Connection Manager parameter file (cman.ora)
REGISTRATION_EXCLUDED_NODES specifies the list of nodes that cannot register with the listener.

Purpose

To specify the list of nodes that cannot register with the listener.

Usage Notes

The list can include host names or CIDR notation for IPv4 and IPv6 addresses. The wildcard format (*) is supported for IPv4 addresses. The presence of a host name in the list results in the inclusion of all IP addresses mapped to the host name. The host name should be consistent with the public network interface.

If the REGISTRATION_INVITED_NODES parameter and the REGISTRATION_EXCLUDED_NODES parameter are set, then the REGISTRATION EXCLUDED NODES parameter is ignored.

Values

Valid nodes and subnet IP addresses or names.

Example

9.2.33 REGISTRATION INVITED NODES

The Oracle Connection Manager parameter file (cman.ora) REGISTRATION_EXCLUDED_NODES parameter specifies the list of node that can register with the listener.

Purpose

To specify the list of node that can register with the listener.

Usage Notes

The list can include host names or CIDR notation for IPv4 and IPv6 addresses. The wildcard format (*) is supported for IPv4 addresses. The presence of a host name in the list results in the inclusion of all IP addresses mapped to the host name. The host name should be consistent with the public network interface.

If the REGISTRATION_INVITED_NODES parameter and the REGISTRATION_EXCLUDED_NODES parameter are set, then the REGISTRATION_EXCLUDED_NODES parameter is ignored.

Values

Valid nodes and subnet IP addresses or names.



Example

9.2.34 REST ADDRESS

Use the REST_ADDRESS parameter to configure REST endpoint hostname and port. Oracle CMAN listens to tops endpoint based on the specified hostname and port.

Usage Notes

Add the REST_ADDRESS attribute under the parameter_list of the cman.ora file.

Syntax

REST_ADDRESS=host name:port

Example

REST_ADDRESS=cman_host:1524

9.2.35 RULE

The RULE parameter of the cman.ora file specifies an access control rule list to filter incoming connections.

Purpose

To specify an access control rule list to filter incoming connections.

Usage Notes

A rule list specifies which connections are accepted, rejected, or dropped.

If no rules are specified, then all connections are rejected.

The source and destination can be a host name, IP address, or subnet mask.

There must be at least one rule for client connections and one rule for CMCTL connections. Omitting one or the other results in the rejection of all connections for the rule type omitted. The last rule in the example that follows is a CMCTL rule.

Oracle Connection Manager does not support wildcards for partial IP addresses. If you use a wildcard, then use it in place of a full IP address. The IP address of the client may, for example, be (SRC=*).

Oracle Connection Manager supports only the /nn notation for subnet addresses. In the first rule in Example "Sample cman.ora File", /27 represents a subnet mask that comprises 27 leftmost bits.

Values

This parameter is listed in the rule list section of the cman.ora file preceded by RULE_LIST=.



Syntax

```
(RULE_LIST=
  (RULE=
     (SRC=host)
     (DST=host)
     (SRV=service_name)
     (ACT={accept|reject|drop})
     (ACTION_LIST=AUT={on|off}
     ((CONN_STATS={yes|no})(MCT=time)(MIT=time)(MOCT=time)))
  (RULE=...))
```

Additional Parameters

The RULE parameter filters a connection or group of connections using the following parameters:

SRC: The source host name or IP address of the client.

DST: The destination server host name or IP address of the database server.

SRV: The database service name of Oracle Database obtained from the SERVICE_NAME parameter in the initialization parameter file.

ACT: The action for the connection request. Use accept to accept incoming requests, reject to reject incoming requests, or drop to reject incoming requests without sending an error message.

ACTION_LIST: The rule-level parameter settings for some parameters. These parameters are as follows:

- AUT: Oracle Database security authentication on client side.
- CONN_STATS: Log input and output statistics.
- MCT: Maximum connect time.
- MIT: Maximum idle timeout.
- MOCT: Maximum outbound connect time.

Rule-level parameters override their global counterparts.

Example

```
(RULE_LIST=
  (RULE=
    (SRC=client1-pc)
    (DST=sales-server)
    (SRV=sales.us.example.com)
    (ACT=reject))
  (RULE=
    (SRC=192.0.2.45)
    (DST=192.0.2.200)
    (SRV=db1)
    (ACT=accept))
  (RULE=
    (SRC=sale-rep)
    (DST=sales1-server)
    (SRV=cmon)
    (ACT=accept)))
```



9.2.36 SDU

Use the SDU parameter to specify the session data unit (SDU) size for connections.

Purpose

To specify the SDU size, in bytes, for connections.

Usage Notes

Oracle Connection Manager can negotiate large SDU with client and server when configured. When the configured values of client, database server, and Oracle Connection Manager do not match for a session, the least value of all the three values is used.

Default

65536 bytes (64 KB)

Value

512 to 2097152 bytes

Example

SDU=32768

9.2.37 SERVICE_RATE

The SERVICE_RATE parameter of cman.ora file specifies incoming connection rate that is allowed per service for an instance.

Purpose

To specify incoming connection rate that is allowed per service for an instance.

Usage Notes

Any user-specified value greater than 0 sets the maximum limit on the number of new connections per service-instance handled by the proxy listener every second. Listener rejects connections after it reaches the maximum limit. Client side connection failure is reported with "TNS: listener: rate limit reached".

Values

- 0 to disable service rate limit. This is the default.
- Any number greater than 0 to enable service rate limit.

Example 9-5 Example

SERVICE_RATE=10



9.2.38 SESSION_TIMEOUT

The SESSION_TIMEOUT parameter of the cman.ora file specifies the maximum time in seconds allowed for a user session.

Purpose

To specify the maximum time in seconds allowed for a user session.

Usage Notes

The global setting can be overridden by a rule-level setting in ACTION_LIST.

Values

- 0 to disable the timeout. This is the default.
- Any number greater than 0 to enable the timeout. The number equals the timeout period in seconds.

Example

SESSION TIMEOUT=60

9.2.39 SSL_CIPHER_SUITES

Use the SSL_CIPHER_SUITES parameter to control the combination of authentication, encryption, and data integrity algorithms used by Transport Layer Security (TLS).

Purpose

To control the combination of authentication, encryption, and data integrity algorithms used by TLS. By default, the strongest protocol and cipher are negotiated between the database client and server. Setting this parameter will override the default behavior. You must use this parameter only if you have internal security controls that dictate the usage of certain protocol versions.

Usage Notes

Starting with Oracle AI Database 26ai, the use of Transport Layer Security protocol versions 1.0 and 1.1 are desupported.

In most cases, this change will not have any impact, because the database client and server will negotiate the use of the most secure protocol and cipher algorithm. However, if TLS 1.0 or 1.1 has been specified, then you must either remove it to allow the database server and client to pick the most secure protocol, or you must specify either TLS 1.2, or TLS 1.3, or both, for the protocol. Oracle recommends using the latest, most secure protocol. That protocol is TLS 1.3, which is introduced with Oracle AI Database 26ai.

Enclose the SSL_CIPHER_SUITES parameter value in parentheses. Otherwise, the cipher suite setting does not parse correctly.

Default

None



Values

Approved ciphers compatible with TLS 1.3:

- TLS_AES_256_GCM_SHA384
- TLS_CHACHA20_POLY1305_SHA256 (non-FIPS only)
- TLS_AES_128_CCM_SHA256
- TLS_AES_128_GCM_SHA256

Approved ciphers compatible with TLS 1.2:

- TLS_ECDHE_RSA_WITH_AES_256_GCM_SHA384
- TLS_ECDHE_RSA_WITH_AES_128_GCM_SHA256
- TLS_ECDHE_ECDSA_WITH_AES_256_GCM_SHA384
- TLS_ECDHE_ECDSA_WITH_AES_128_GCM_SHA256
- TLS_DHE_RSA_WITH_AES_256_GCM_SHA384
- TLS_DHE_RSA_WITH_AES_128_GCM_SHA256

Deprecated ciphers compatible with TLS 1.2:

- TLS_ECDHE_RSA_WITH_AES_256_CBC_SHA384
- TLS_ECDHE_RSA_WITH_AES_256_CBC_SHA
- TLS_ECDHE_RSA_WITH_AES_128_CBC_SHA256
- TLS_ECDHE_RSA_WITH_AES_128_CBC_SHA
- TLS_ECDHE_ECDSA_WITH_AES_256_CBC_SHA384
- TLS_ECDHE_ECDSA_WITH_AES_256_CBC_SHA
- TLS_ECDHE_ECDSA_WITH_AES_128_CBC_SHA256
- TLS_ECDHE_ECDSA_WITH_AES_128_CBC_SHA
- TLS_RSA_WITH_AES_256_GCM_SHA384
- TLS_RSA_WITH_AES_256_CBC_SHA256
- TLS_RSA_WITH_AES_256_CBC_SHA
- TLS_RSA_WITH_AES_128_GCM_SHA256
- TLS_RSA_WITH_AES_128_CBC_SHA256
- TLS_RSA_WITH_AES_128_CBC_SHA
- TLS_DHE_RSA_WITH_AES_256_CBC_SHA256
- TLS_DHE_RSA_WITH_AES_128_CBC_SHA256
- TLS_DHE_RSA_WITH_AES_256_CBC_SHA



Examples

SSL_CIPHER_SUITES=(TLS_ECDHE_ECDSA_WITH_AES_128_GCM_SHA256)

SSL_CIPHER_SUITES=(TLS_AES_256_GCM_SHA384, TLS_ECDHE_ECDSA_WITH_AES_128_GCM_SHA256)

Related Topics

- Set the TLS Cipher Suites on the Server
- Set the TLS Cipher Suites on the Client

9.2.40 SSL_CLIENT_AUTHENTICATION

Use the SSL_CLIENT_AUTHENTICATION parameter to specify whether the database client is authenticated using Transport Layer Security (TLS).

Purpose

To enable client authentication in a TLS connection. The connection can be one-way or two-way (mutual TLS or mTLS).

Usage Notes

When set to TRUE, a two-way TLS connection is initiated. Both the client and server (including the listener) authenticate each other. For example, if you set this parameter to TRUE in the server configuration (server-side sqlnet.ora), then the server attempts to authenticate the client. If you set it to TRUE in the listener configuration (listener.ora), then the listener attempts to authenticate the client.

When set to FALSE, only the client authenticates the server and listener as a one-way TLS connection. For example, if you set this parameter to FALSE in the server configuration, then the server does not authenticate the client. If you set it to FALSE in the listener configuration, then the listener does not authenticate the client.

When set to OPTIONAL, the server behaves as follows:

- If the client sends a certificate, then the connection is completed as a two-way TLS connection after authenticating the client.
- If the client does not send a certificate, then the connection is completed as a one-way TLS connection.

Ensure that this parameter setting is consistent for the server or listener (on one side) and the client (on the other). Otherwise, the connection may fail. For example, if you enable client authentication in the server or listener configuration, then you must enable it in the client configuration.

Default

TRUE

Values

- TRUE | ON | YES | 1: To enable mTLS
- FALSE | OFF | NO | 0: To enable one-way TLS



OPTIONAL: To enable both TLS and mTLS

Example

SSL_CLIENT_AUTHENTICATION=FALSE

Related Topics

Oracle AI Database Security Guide

9.2.41 SSL_VERSION

Use the SSL_VERSION parameter to define valid Transport Layer Security (TLS) versions to be used for connections.

Purpose

To define the version of TLS that must run on the systems with which the database server communicates. By default, the database server and client negotiate the strongest security protocol. Oracle does not recommend modifying this parameter, unless your security requirements mandate the usage of certain protocol versions.

Usage Notes

- Clients, listeners, and database servers must use compatible versions. Modify this
 parameter only when necessary to enforce the use of the more secure TLS protocol and
 not allow clients that only work with the older TLS protocols. The current default uses TLS
 1.3, which is the version required for multiple security compliance requirements. If you
 need to specify TLS 1.2, then also include TLS 1.3 to allow more secure connections.
- In addition to sqlnet.ora, listener.ora, and cman.ora, you can specify this parameter under the SECURITY section of the the section of the connect string. The parameter value specified in the connect string takes precedence over the other specified values.
- Starting with Oracle AI Database 26ai, the use of Transport Layer Security protocol versions 1.0 and 1.1 are desupported.
 - In most cases, this change will not have any impact, because the database client and server will negotiate the use of the most secure protocol and cipher algorithm. However, if TLS 1.0 or 1.1 has been specified, then you must either remove it to allow the database server and client to pick the most secure protocol, or you must specify either TLS 1.2, or TLS 1.3, or both, for the protocol. Oracle recommends using the latest, most secure protocol. That protocol is TLS 1.3, which is introduced with Oracle AI Database 26ai.
- Starting with Oracle AI Database 26ai, the Secure Socket Layer v3 protocol (SSLv3) is no longer supported for database server-client connections, and the sqlnet.ora parameter ADD_SSLV3_TO_DEFAULT has been removed.
 - SSLv3 is a much less secure protocol to secure the database server-to-client connection. Instead of using SSLv3, allow the database server and client to negotiate the most secure protocol that is common between the server and the client. Oracle AI Database 26ai provides TLS 1.2 and TLS 1.3 protocols for certificate-based network encryption.
- If you set SSL_VERSION to undetermined, then the most secure TLS protocol version is used. You can also use the SSL_VERSION=undetermined setting in the connect string for a specific connection to override the SSL_VERSION value configured in the sqlnet.ora, listener.ora, or cman.ora file.



• If you do not set SSL_VERSION to any value, then all the supported TLS protocol versions are tried starting with the most secure version. This is typically the most common configuration, ensuring that the strongest protocol is chosen during TLS negotiation.

Values

```
undetermined | TLSv1.2 | TLSv1.3
```

Default

undetermined

Syntax and Examples

To specify a single protocol version:

```
SSL_VERSION=TLS_protocol_version
```

For example:

```
SSL_VERSION=TLSv1.3
```

• To specify multiple protocol versions, use a comma-separated string of values, enclosed in parenthesis:

```
SSL_VERSION=(TLS_protocol_version1,TLS_protocol_version2)
```

For example:

```
SSL_VERSION=(TLSv1.2,TLSv1.3)
```

(i) Note

Do not enclose protocol versions in parenthesis while specifying this parameter in the tnsnames.ora file or as part of the connect string, otherwise the setting will not parse correctly. For example:

```
net_service_name=
  (DESCRIPTION=
         (ADDRESS=(PROTOCOL=tcps)(HOST=salesserver)(PORT=1522))
         (SECURITY=(SSL_VERSION=TLSv1.2,TLSv1.3))
)
```

Related Topics

- Set the Required TLS Version on the Server
- Set the Required TLS Version on the Client



9.2.42 TRACE_FILE

The TRACE_FILE parameter of the cman.ora file specifies the directory for Oracle Connection Manager trace files.

Purpose

To specify the directory for Oracle Connection Manager trace files.

9.2.43 USE_SERVICE_AS_TNSNAMES_ALIAS

Use this parameter for static routing of client connections from Oracle connection manager based on client's service name.

Usage Notes

Oracle connection manager uses the service name specified by the client as an alias. You must configure alias in thinknames.ora file of CMAN home. If an alias is not configured for a service, then the NEXT_HOP parameter in cman.ora acts as a default connect string.

Values

OFF and ON. The default is OFF.

Example

Configuration in CMAN home:

```
cman.ora

USE_SERVICE_AS_TNSNAMES_ALIAS=ON

tnsnames.ora

sales=
  (DESCRIPTION=
        (ADDRESS=(PROTOCOL=TCP)(HOST=sales-server)(port=1521))
        (CONNECT_DATA=(SERVICE_NAMES=sales)))
```

Note

DESCRIPTION_LIST is not supported in the tnsnames.ora file of CMAN home.

Configuration in client home:

```
sales_cman=
  (DESCRIPTION=
```

tnsnames.ora



```
(ADDRESS=(PROTOCOL=TCP)(HOST=cman-server)(port=1523))
(CONNECT_DATA=(SERVICE_NAMES=sales)))
```

In this example, the client is connecting to service sales. CMAN will use the sales alias in tnsnames.ora of the CMAN home for connecting to the next hop.

9.2.44 USE SID AS SERVICE

The USE_SID_AS_SERVICE Oracle Connection Manager parameter enables the system identifier (SID) in the connect descriptor to be interpreted as a service name when a user attempts a database connection.

Purpose

To enable the system identifier (SID) in the connect descriptor to be interpreted as a service name when a user attempts a database connection.

Usage Notes

Database clients with earlier releases of Oracle Database that have hard-coded connect descriptors can use this parameter to connect to a container or pluggable database.

For an Oracle container database, the client must specify a service name in order to connect to it. Setting this parameter to on instructs the Oracle Connection Manager listener to use the SID in the connect descriptor as a service name and connect the client to the specified database.

Values

- off (default value)
- on

Example 9-6 Example

USE_SID_AS_SERVICE=on

9.2.45 USE SNI

Use cman.ora parameter USE_SNI to enable or disable the use of Service Name Indication (SNI) by the CMAN listener for selecting an appropriate service handler without the TLS negotiation and also to enable or disable the setting of SNI value in outgoing connection by the gateway process.

Purpose

To allow CMAN listener to fetch the CONNECT_DATA parameters in SNI without the TLS handshake and also to enable the gateway process to set the SNI value in outbound connections.

Usage Notes

Use the USE_SNI parameter under the PARAMETER_LIST section of the cman.ora file. If you do not configure this parameter, then by default, CMAN listener processes SNI value if available in incoming connection to select an appropriate service handler, but gateway process will not set SNI in the outgoing connection.

If you explicitly set the parameter to ON, then it enables gateway process also to set SNI based on CONNECT DATA in outgoing connection.



If you set the USE_SNI parameter to OFF, then neither the CMAN listener nor the gateway process will process the SNI data.

Default Value

ON for CMAN listener for incoming connections, but OFF for gateways for outgoing connections

Values

ON | TRUE | YES

OFF | FALSE | NO

Example

CMAN=

```
(CONFIGURATION=
     (ADDRESS=(PROTOCOL=tcp)(HOST=proxysvr)(PORT=1521))
     (PARAMETER LIST=(USE SNI=ON)))
```



Support for SNI is available in all versions starting 23.7, but not in earlier versions.

Related Topics

Oracle Al Database Net Services Administrator's Guide

9.2.46 VALID_NODE_CHECKING_REGISTRATION

The VALID_NODE_CHECKING_REGISTRATION parameter of the cman.ora file specifies whether valid node checking registration is performed.

Purpose

To determine whether valid node checking registration is performed, and if the subnet is allowed.

Usage Notes

When set to on, valid node checking registration is performed at the listener for any incoming registration request, and only local IP addresses are allowed.

Default

on

Values

- off | 0 to specify valid node checking registration is off, and no checking is performed.
- on | 1 | local to specify valid node checking registration is on, and all local IP addresses can register. If a list of invited nodes is set, then all IP addresses, host names, or subnets in the list as well as local IP addresses are allowed.



subnet | 2 to specify valid node checking registration is on, and all machines in the local subnets are allowed to register. If a list of invited nodes is set, then all nodes in the local subnets as well as all IP addresses, host names and subnets in the list are allowed.

Example

VALID NODE CHECKING REGISTRATION=on

9.2.47 WALLET LOCATION

Use the WALLET_LOCATION parameter to specify the location of Oracle wallets.

Purpose

To specify the directory path where you want to store an Oracle wallet. Wallets securely contain certificates, secrets, private keys, and trust points used by Oracle Database.

Usage Notes

Where to set this parameter:

You can set WALLET_LOCATION in the cman.ora file to specify a common wallet location for all the Oracle Connection Manager (CMAN) aliases. You can also set it in the connect string to specify a different wallet location for a particular outgoing connection when using the parameters USE SERVICE AS TNSNAMES ALIAS OR NEXT HOP.



(i) Note

Only one WALLET LOCATION configuration is allowed per cman.ora file. Setting this parameter more than once in the cman.ora is invalid.

Setting to use the system default certificate store

If you set WALLET LOCATION=SYSTEM in the outgoing connect string, then the CMAN gateway uses the default certificate store to validate the Oracle Database server certificate for outgoing connections instead of creating a local wallet with root certificate. The default certificate store is located in /etc/pki/tls/cert.pem on Linux and Microsoft Certificate Store (MCS) on Windows. In this case, the server certificate needs to be signed by a trusted root certificate that is already installed in the default certificate store.

- Setting for walletless TLS connections:
 - The WALLET_LOCATION parameter is optional for TLS connections that do not use a client wallet. If you do not include WALLET LOCATION in cman.ora, then the driver automatically picks up common root certificates from the system default certificate store (if the system is Windows or Linux). This is applicable only to the outbound connections from gateway.
- Storage of wallet files:
 - The password-protected wallet is stored in an ewallet.p12 file. The auto-login and local auto-login wallets are stored in a cwallet.sso file.

For example, if an Oracle wallet is stored in the Microsoft Windows registry and the wallet's key (KEY) is SALESAPP, then the storage location of the password-protected wallet is HKEY CURRENT USER\SOFTWARE\ORACLE\WALLETS\SALESAPP\EWALLET.P12. The storage location of the auto-login and local auto-login wallets is

HKEY_CURRENT_USER\SOFTWARE\ORACLE\WALLETS\SALESAPP\CWALLET.SSO.



Additional Parameters

Use SOURCE to specify the type of storage and storage location for wallets, as follows:

- METHOD: Type of storage
- METHOD_DATA: Storage location:
 - DIRECTORY: Location of wallet on the file system
 - KEY: Wallet type and location in the Microsoft Windows registry

Syntax and Examples

The syntax depends on the wallet as follows:

Wallet on the file system:

(DIRECTORY=/etc/oracle/wallets/databases)))

Microsoft certificate store:

```
WALLET_LOCATION=
  (SOURCE=
        (METHOD=mcs))
```

The key-value pair for MCS omits the METHOD_DATA parameter because MCS does not use wallets. Instead, Oracle PKI (public key infrastructure) applications obtain certificates, trust points and private keys directly from a user's profile.

Wallet in the Microsoft Windows registry:

(KEY=SALESAPP)))

Default

None



9.3 Oracle Connection Manager in Traffic Director Mode Parameters

This section lists and describes the cman.ora file parameters.

SERVICE AFFINITY

Use the cman.ora parameter SERVICE_AFFINITY to modify the default load distribution mechanism for Oracle Connection Manager in Traffic Director Mode.

- TDM
- TDM BIND THREAD
- TDM DATATYPE CHECK
- TDM PERPDB PRCP CONNFACTOR

Use the cman.ora parameter TDM_PERPDB_PRCP_CONNFACTOR to configure per-PDB Proxy Resident Connection Pooling (PRCP).

- TDM PRCP MAX CALL WAIT TIME
- TDM PRCP MAX TXN CALL WAIT TIME
- TDM SHARED THREADS MAX
- TDM SHARED THREADS MIN
- TDM STATS FREQUENCY

Use the cman.ora parameter TDM_STATS_FREQUENCY to configure the frequency at which usage statistics are uploaded to PDB for per-PDB Proxy Resident Connection Pooling (PRCP) connections.

TDM THREADING MODE

9.3.1 SERVICE_AFFINITY

Use the cman.ora parameter SERVICE_AFFINITY to modify the default load distribution mechanism for Oracle Connection Manager in Traffic Director Mode.

Purpose

To configure load distribution mechanism for Oracle Connection Manager in Traffic Director Mode. By default, Oracle Connection Manager in Traffic Director Mode uses service affinity to select a gateway for routing incoming connection requests. All new connection requests are routed to the gateways associated with database services.

Usage Notes

If you set this parameter to ON, then all new connection requests are routed to the gateways associated with database services.

If you set this parameter to ${\tt OFF}$, then all new connection requests are routed to the least-loaded gateways.

When using Proxy Resident Connection Pooling (PRCP), Oracle recommends that you set the SERVICE_AFFINITY parameter to OFF for better performance and resource utilization of gateway processes.



Values

ON | OFF

Default

ON

Example

```
SERVICE_AFFINITY = {ON | OFF}
```

Related Topics

- Oracle Al Database Net Services Administrator's Guide
- Oracle Multitenant Administrator's Guide

9.3.2 TDM

Purpose

To configure Oracle Connection Manager to act as Oracle Connection Manager in Traffic Director Mode.

Default

FALSE

Values

- TRUE
- FALSE

Example

tdm = TRUE

9.3.3 TDM_BIND_THREAD

Purpose

To make the application connection hold on to the TDM thread and has different implications with and without PRCP. This parameter only applies when <code>TDM_THREADING_MODE</code> is set to <code>SHARED</code>.

Usage Notes

Without PRCP, setting this parameter to yes makes the application connection hold on the TDM worker thread as long as there is a transaction in progress.

With PRCP, setting this parameter to yes makes the application connection hold on to the TDM thread from the time <code>OCISessionGet</code> is done by the application till it does an <code>OCISessionRelease</code>.



Default

no

Values

- yes
- no

Example

TDM_BIND_THREAD = yes

9.3.4 TDM_DATATYPE_CHECK

Purpose

To validate all the inbound data to the database, of the data type <code>NUMBER</code>, <code>DATE</code>, <code>TIMESTAMP</code>, <code>TIMESTAMP</code> WITH <code>LOCAL TIMEZONE</code>, <code>TIMESTAMP</code> WITH <code>TIMEZONE</code>, <code>BLOB</code>, <code>CLOB</code>, <code>BFILE</code>, <code>UROWID</code> and <code>REF</code>. The following error is received by the application if there is any problem with the data sent to the Oracle Connection Manager in Traffic Director Mode.

ORA-03137: malformed TTC packet from client rejected: [3101]

Usage Notes

Turning ON/OFF this parameter enables or disables the data validation.

Default

OFF

Values

- ON
- OFF

Example

tdm_datatype_check={ON | OFF}

9.3.5 TDM PERPDB_PRCP_CONNFACTOR

Use the cman.ora parameter TDM_PERPDB_PRCP_CONNFACTOR to configure per-PDB Proxy Resident Connection Pooling (PRCP).

Purpose

To configure per-PDB PRCP. This parameter value sets a connection factor, which helps in dynamically determining the maximum size of every per-PDB PRCP pool.

Usage Notes

 The per-PDB PRCP setting determines the maximum size of a per-PDB PRCP pool based on the TDM_PERPDB_PRCP_CONNFACTOR parameter value and the Oracle Compute Unit (OCPU) count allocated to each PDB automatically.



A background process automatically fetches these values and resizes the pool. This derived maximum size value overrides the <session_pool> MAX_SIZE parameter configured in the orangess.xml file.

- PRCP dynamically rereads the TDM_PERPDB_PRCP_CONNFACTOR value and accordingly refreshes the maximum size of a per-PDB pool, if needed. You can change this parameter value using the Oracle Connection Manager Control utility (CMCTL) RELOAD command. There is no need to restart Oracle Connection Manager in Traffic Director Mode for the changes to take effect.
- In addition to TDM_PERPDB_PRCP_CONNFACTOR, you must set the sqlnet.ora parameter TCP.ALLOWED PROXIES on the database server. Otherwise, the connection request fails. TCP.ALLOWED_PROXIES specifies the CMAN instance (IP address or host name) that can fetch the OCPU count from the database server.

Values

- 0 to disable per-PDB PRCP
- Any number equal to or greater than 1 to enable per-PDB PRCP



(i) Note

Ensure that you specify a connection factor value within the maximum connections limit defined by the cman.ora parameter MAX CONNECTIONS.

Default

Example

TDM_PERPDB_PRCP_CONNFACTOR=10

Related Topics

- Oracle Al Database Net Services Administrator's Guide
- TCP.ALLOWED PROXIES

Use the sqlnet.ora parameter TCP.ALLOWED_PROXIES to specify a list of the Oracle Connection Manager (CMAN) addresses that can forward client IP address to the database server.

RELOAD

Use the Oracle Connection Manager Control utility RELOAD command to make the utility dynamically reread parameters and rules.

MAX CONNECTIONS

The MAX_CONNECTIONS parameter of the cman.ora file specifies the maximum number of connection slots that a gateway process can handle.



9.3.6 TDM_PRCP_MAX_CALL_WAIT_TIME

Purpose

To record the maximum time of inactivity, in seconds, for a client after obtaining a session from the PRCP pool. This parameter is applicable when the Oracle Connection Manager in Traffic Director Mode is configured to have Proxy Resident Connection Pool.

Usage Notes

After obtaining a session from the PRCP pool, if the client application does not issue a database call for the time specified by TDM_PRCP_MAX_CALL_WAIT_TIME parameter, then the PRCP session is freed and the client connection is terminated. As a result, if the client application attempts a round trip call on such a connection, then it receives an ORA-3113 or ORA-3115 error.

Default

30 seconds

Values

Any non negative value. However, Oracle recommends not to use a value of 0 as that implies that a connection can acquire a PRCP session for an indefinite amount of time

9.3.7 TDM_PRCP_MAX_TXN_CALL_WAIT_TIME

Purpose

To record the maximum time of inactivity, in seconds, for a client after it obtains a session from the Proxy Resident Connection Pool and starts a transaction. This parameter is applicable when the Oracle Connection Manager in Traffic Director Mode is configured to have PRCP.

Usage Notes

If the client application does not issue a database call for the time specified by TDM_PRCP_MAX_TXN_CALL_WAIT_TIME parameter while in a transaction, the PRCP session is freed, the transaction is rolled back, and the client connection is terminated. As a result, if the client application attempts a round trip call on such a connection, then it receives an ORA-3113 or ORA-3115 error.

Default

0

Values

Any nonnegative value. However, it is recommended not to use a value of 0 as it implies that a connection can acquire a PRCP session for an indefinite amount of time.



9.3.8 TDM_SHARED_THREADS_MAX

Purpose

To configure the maximum number of threads that an Oracle Connection Manager process in Traffic Director Mode should have, when tdm_threading_mode is set to SHARED.

Values

Any number can be designated for the maximum number of threads. For DEDICATED mode, the maximum number of threads is same as the maximum number of connections. In SHARED mode, though there is no fixed upper bound, it should ideally be proportional to the load.

9.3.9 TDM SHARED THREADS MIN

Purpose

To configure the minimum number of threads that an Oracle Connection Manager process in Traffic Director Mode should have, when tdm_threading_mode is set to SHARED.

Values

Any number can be designated for the minimum number of threads. For SHARED mode, there is no limit enforced. However, the number of threads should be proportional to the load.

9.3.10 TDM_STATS_FREQUENCY

Use the cman.ora parameter TDM_STATS_FREQUENCY to configure the frequency at which usage statistics are uploaded to PDB for per-PDB Proxy Resident Connection Pooling (PRCP) connections.

Purpose

To specify the time interval, in minutes, at which usage statistics for Oracle Connection Manager in Traffic Director Mode should be uploaded to PDB if per-PDB PRCP is enabled.

These usage statistics help in monitoring the behavior of your connection pools. PDB administrators can query the dynamic database view V\$TDM_STATS to view this statistical data.

Values

- 0 to disable statistics upload.
- Any number equal to or greater than 1 (up to the maximum value) to enable statistics upload. This value depends on your runtime load and connection pool usage.

Default Value

0

Minimum Value

0

Maximum Value

2800



Example

TDM_STATS_FREQUENCY=300

Related Topics

- Oracle Al Database Net Services Administrator's Guide
- V\$TDM STATS

9.3.11 TDM THREADING MODE

Purpose

To configure the usage of threads by the Oracle Connection Manager in Traffic Director Mode.

Usage Notes

If this parameter is set to <code>DEDICATED</code>, then a worker thread is spawned for each inbound connection and the maximum number of threads is determined by the $max_connections$ parameter

If this parameter is set to SHARED, then a shared pool of worker threads handle all inbound connections. The minimum number of worker threads is specified by the tdm_shared_threads_min setting and the maximum number of worker threads is specified by the tdm_shared_threads_max setting. The thread pool is internally managed within these bounds.

Default

DEDICATED

Values

- DEDICATED
- SHARED

Example

```
tdm_threading_mode={DEDICATED | SHARED}
tdm_shared_threads_min = 4
tdm_shared_threads_max = 5
```

9.4 ADR Diagnostic Parameters for Oracle Connection Manager

The diagnostic data for critical errors is quickly captured and stored in the ADR for Oracle Connection Manager.

Since Oracle Database 11g, Oracle Database includes an advanced fault diagnosability infrastructure for preventing, detecting, diagnosing, and resolving problems. The problems are critical errors such as those caused by database code bugs, metadata corruption, and customer data corruption.

When a critical error occurs, it is assigned an incident number, and diagnostic data for the error, such as traces and dumps, are immediately captured and tagged with the incident



number. The data is then stored in the Automatic Diagnostic Repository (ADR), a file-based repository outside the database.

This section describes the parameters used when ADR is enabled. ADR is enabled by default. Non-ADR parameters listed in the cman.ora file are ignored when ADR is enabled.

ADR BASE

It is a diagnostic parameter in the cman.ora file and it specifies the base directory to store tracing and logging incidents when ADR is enabled.

DIAG ADR ENABLED

 ${\tt DIAG_ADR_ENABLED} \ diagnostic \ parameter \ of \ the \ {\tt cman.ora} \ file \ indicates \ whether \ ADR \ tracing \ is \ enabled.$

- LOG LEVEL
- TRACE LEVEL
- TRACE TIMESTAMP

9.4.1 ADR_BASE

It is a diagnostic parameter in the cman.ora file and it specifies the base directory to store tracing and logging incidents when ADR is enabled.

Purpose

To specify the base directory to store tracing and logging incidents when ADR is enabled.

Default

The default is <code>ORACLE_BASE</code>, or <code>ORACLE_HOME/log</code> if <code>ORACLE_BASE</code> is not defined.

Values

Any valid directory path to a directory with write permission.

Example 9-7 Example

ADR_BASE=/oracle/network/trace

9.4.2 DIAG ADR ENABLED

DIAG_ADR_ENABLED diagnostic parameter of the cman.ora file indicates whether ADR tracing is enabled.

Purpose

To indicate whether ADR tracing is enabled.

Usage Notes

When the DIAG_ADR_ENABLED parameter is set to OFF, then non-ADR file tracing is used.

Values

on | off

Example 9-8 Example

DIAG_ADR_ENABLED=on



9.4.3 LOG_LEVEL

Purpose

To specify the level of logging performed by Oracle Connection Manager.

Usage Notes

This parameter is also applicable when non-ADR logging is used.

The following log files are used with Oracle Connection Manager:

- instance-name_pid.log for the listener.
- instance-name cmadmin pid.log for CMADMIN.
- instance-name_cmgw_pid.log for the gateway processes.

The log files are located in the ORACLE_HOME/network/log directory.

Default

off or 0

Values

- off or 0 for no log output.
- user or 4 for user log information.
- admin or 10 for administration log information.
- support or 16 for Oracle Support Services log information.

Example

LOG_LEVEL=admin

9.4.4 TRACE LEVEL

Purpose

To specify the trace level for the Oracle Connection Manager instance.

Usage Notes

This parameter is also applicable when non-ADR tracing is used.

The following trace files are used with Oracle Connection Manager:

- instance-name pid.trc for the listener.
- instance-name_cmadmin_pid.trc for CMADMIN.
- instance-name_cmgw_pid.trc for the gateway processes.

The log files are located in the ORACLE_HOME/network/log directory.

Default

off



Values

- off for no trace output.
- user for user trace information.
- admin for administration trace information.
- support for Oracle Support Services trace information.

Example

TRACE_LEVEL=admin

9.4.5 TRACE_TIMESTAMP

Purpose

To add a time stamp in the form of dd-mmm-yyyy hh:mi:ss:mil to every trace event in the trace file for the listener.

Usage Notes

This parameter is used with the <u>TRACE_LEVEL</u> parameter. This parameter is also applicable when non-ADR tracing is used.

Default

on

Values

- on or true
- off Or false

Example

TRACE_TIMESTAMP=true

9.5 Non-ADR Diagnostic Parameters for Oracle Connection Manager

This section lists the parameters used when ADR is disabled:

- LOG DIRECTORY
- TRACE_DIRECTORY
- TRACE FILELEN
- TRACE FILENO

9.5.1 LOG_DIRECTORY

Purpose

To specify the location of Oracle Connection Manager log files.



Usage Notes

Use this parameter when ADR is not enabled.

Default

ORACLE_BASE_HOME/network/log

Values

Any valid directory path to a directory with write permission.

Example

LOG_DIRECTORY=/oracle/network/log

9.5.2 TRACE_DIRECTORY

Purpose

To specify the location of the Oracle Connection Manager trace files.

Usage Notes

Use this parameter when ADR is not enabled.

Default

ORACLE_BASE_HOME/network/trace

Values

Any valid directory path to a directory with write permission.

Example

TRACE_DIRECTORY=/oracle/network/admin/trace

9.5.3 TRACE_FILELEN

Purpose

To specify the size, in KB, of the trace file.

Usage Notes

When the size is met, the trace information is written to the next file. The number of files is specified with the TRACE_FILENO parameter. Any size can be designated. Use this parameter when ADR is not enabled.

Default

Unlimited

Example

TRACE_FILELEN=100



9.5.4 TRACE_FILENO

Purpose

To specify the number of trace files for Oracle Connection Manager tracing.

Usage Notes

When this parameter is set along with the <u>TRACE_FILELEN</u> parameter, trace files are used in a cyclical fashion. The first file is filled first, then the second file, and so on. When the last file has been filled, the first file is reused, and so on. Any number of files can be designated.

The trace file names are distinguished from one another by their sequence number. For example, if this parameter is set to 3, then the gateway trace files would be named <code>instance-name_cmgw1_pid.trc</code>, <code>instance_name_cmgw2_pid.trc</code> and <code>instance_name_cmgw3_pid.trc</code>.

In addition, trace events in the trace files are preceded by the sequence number of the file. Use this parameter when ADR is not enabled.

Default

1

Example

TRACE_FILENO=3

9.6 Oracle Connection Manager Tunneling Parameters

This section lists the parameters that you must configure to enable tunneling.

TUNNELING

Set this parameter to start Oracle Connection Manager as server in tunneling mode.

TUNNEL CAPACITY

Use this parameter to specify the number of reverse connections that can be multiplexed over a tunnel.

MAX TUNNELS

Use this parameter to specify the number of tunnels that a client connection manager in tunneling mode can create.

TUNNEL PROBE INTERVAL

Use this parameter in server connection manager to keep the tunnel connection open.

NON TUNNEL GATEWAYS

Use this parameter to specify the number of regular gateways that will not be used for tunneling.

TUNNEL ADDRESS

Set this parameter on the client CMAN to point to the server CMAN that you want to connect to.

• GATEWAY PROCESSES

Use this parameter to specify the number of gateway processes.



9.6.1 TUNNELING

Set this parameter to start Oracle Connection Manager as server in tunneling mode.

Purpose

Set this parameter to on to start Oracle Connection Manager in tunneling mode. You must set this parameter on the server CMAN. When this parameter is set, the CMAN starts processing and accepts tunnel requests.

Usage Notes

Use this parameter with PARAMETER_LIST.

Default

OFF

Example

```
(PARAMETER_LIST= (TUNNELING=ON))
```

9.6.2 TUNNEL_CAPACITY

Use this parameter to specify the number of reverse connections that can be multiplexed over a tunnel.

Purpose

You must set this parameter on the server CMAN. Only the number of connections that you specify for this parameter will be allowed per tunnel.

Usage Notes

Use this parameter with PARAMETER_LIST.

Example

```
(PARAMETER_LIST=
(TUNNELING_CAPACITY=25))
```



9.6.3 MAX_TUNNELS

Use this parameter to specify the number of tunnels that a client connection manager in tunneling mode can create.

Purpose

This parameter creates the specified number of tunnels by each connection manager gateway. You must set this parameter on the client CMAN.

Usage Notes

Use this parameter with PARAMETER_LIST.

Example

```
(PARAMETER_LIST= (MAX_TUNNELS=4))
```

9.6.4 TUNNEL_PROBE_INTERVAL

Use this parameter in server connection manager to keep the tunnel connection open.

Purpose

Specify a time interval in minutes to send small probe packets to keep the tunnel connection open and avoid time out. You must set this parameter on the server CMAN.

Usage Notes

Use this parameter with PARAMETER_LIST.

Example

```
(PARAMETER_LIST= (TUNNEL_PROBE_INTERVAL=7))
```

9.6.5 NON_TUNNEL_GATEWAYS

Use this parameter to specify the number of regular gateways that will not be used for tunneling.

Purpose

Set this parameter at both the server CMAN and the client CMAN to specify the number of regular gateways. Regular gateways handle regular and forward connections. In tunneling mode, all gateways are tunnel gateways by default.



Usage Notes

Use this parameter with PARAMETER_LIST.

Default

0 when tunneling is enabled.

Example

```
(PARAMETER_LIST= (NON_TUNNEL_GATEWAYS=2))
```

9.6.6 TUNNEL_ADDRESS

Set this parameter on the client CMAN to point to the server CMAN that you want to connect to.

Purpose

The gateways connect to the specified server address to create tunnels. You can configure single or multiple addresses using address_list and description.

Usage Notes

Put this parameter under CONFIGURATION.

Example

```
(CONFIGURATION=
  (TUNNEL_ADDRESS=
  (DESCRIPTION=(ADDRESS=(PROTOCOL=TCPS)(HOST=host_name)(PORT=port_number))
  (CONNECT_DATA=(TUNNEL_ID=tunnel_id)))))
```

9.6.7 GATEWAY_PROCESSES

Use this parameter to specify the number of gateway processes.

Usage

Use this parameter with PARAMETER_LIST.

gateway_processes=value

Example





(i) Note

MIN_GATEWAY_PROCESSES parameter and MAX_GATEWAY_PROCESSES parameter are not supported with tunneling option.

Directory Usage Parameters in the Idap.ora File

This chapter provides a complete listing of the ldap.ora file configuration parameters.

Overview of Directory Server Usage File

The ldap.ora file contains directory usage configuration parameters created by Oracle Internet Directory Configuration Assistant, or Oracle Net Configuration Assistant. Do not modify these parameters or their settings.

<u>Directory Usage Parameters</u>

This section lists and describes the following ldap.ora file configuration parameters.

10.1 Overview of Directory Server Usage File

The ldap.ora file contains directory usage configuration parameters created by Oracle Internet Directory Configuration Assistant, or Oracle Net Configuration Assistant. Do not modify these parameters or their settings.

When created with Oracle Internet Directory Configuration Assistant, ldap.ora is located in the <code>ORACLE_HOME/ldap/admin</code> directory. When created with Oracle Net Configuration Assistant, the ldap.ora file is located either in the <code>ORACLE_BASE_HOME/network/admin</code> directory or the <code>ORACLE_HOME/network/admin</code> directory. The ldap.ora file can also be stored in the directory specified by the <code>LDAP_ADMIN</code> or <code>TNS_ADMIN</code> environment variable.

Related Topics

- Oracle Internet Directory
- Oracle Net Configuration Assistant

10.2 Directory Usage Parameters

This section lists and describes the following ldap.ora file configuration parameters.

DEFAULT ADMIN CONTEXT

DEFAULT_ADMIN_CONTEXT ldap.ora file configuration parameter specifies the default directory for the creation, modification, or search of the connect identifiers.

DIRECTORY SERVER TYPE

DIRECTORY_SERVER_TYPE is a networking parameter of the ldap.ora file and it specifies the type of directory server that is being used.

DIRECTORY SERVERS

DIRECTORY_SERVERS is a directory usage parameter and it lists the host names and port number of the primary and alternate LDAP directory servers.



10.2.1 DEFAULT_ADMIN_CONTEXT

DEFAULT_ADMIN_CONTEXT ldap.ora file configuration parameter specifies the default directory for the creation, modification, or search of the connect identifiers.

Purpose

To specify the default directory entry that contains an Oracle Context from which connect identifiers can be created, modified, or looked up.

Values

Valid distinguished name (DN)

Example 10-1 Example

DEFAULT ADMIN CONTEXT="o=OracleSoftware,c=US"

10.2.2 DIRECTORY_SERVER_TYPE

DIRECTORY_SERVER_TYPE is a networking parameter of the ldap.ora file and it specifies the type of directory server that is being used.

Purpose

To specify a value that corresponds to the type of directory server to be used, such as OID for Oracle Internet Directory, Oracle Unified Directory, or OpenLDAP and AD for Microsoft Active Directory.

Values

- OID for Oracle Internet Directory, Oracle Unified Directory, or OpenLDAP
- AD for Microsoft Active Directory

Example 10-2 Example

DIRECTORY_SERVER_TYPE=OID

10.2.3 DIRECTORY_SERVERS

DIRECTORY_SERVERS is a directory usage parameter and it lists the host names and port number of the primary and alternate LDAP directory servers.

Purpose

To list the host names and port number of the primary and alternate LDAP directory servers.

Values

host:port[:sslport]

Example 10-3 Example

DIRECTORY SERVERS=(ldap-server1:389:636, ldap-server2:389:636)

LDAP Parameters in the Connect Identifier

This chapter describes the LDAP parameters that you can directly specify in the database client connect identifier, when using the Directory Naming method.

- About Using LDAP Parameters in the Connect Identifier
 The Directory Naming method provides an alternative method to specify LDAP name lookup, by using LDAP parameters in the database client connection identifier.
- Allowed Parameters in the Connect Identifier
 These are the LDAP parameters that you can use in the connect identifier.

11.1 About Using LDAP Parameters in the Connect Identifier

The Directory Naming method provides an alternative method to specify LDAP name lookup, by using LDAP parameters in the database client connection identifier.

With the Directory Naming method, connect identifiers are mapped to connect descriptors contained in an LDAP-compliant directory server, such as Oracle Internet Directory, Oracle Unified Directory, or Microsoft Active Directory. Instead of specifying the protocol-specific and directory usage parameters in external configuration files (such as ldap.ora and sqlnet.ora), you can directly specify those parameters in the connect identifier. This eliminates the need for external configuration files to connect to the database.

The values that are specified as part of ldap.ora and sqlnet.ora for LDAP name lookup are directly passed in the connect identifier. If ldap.ora or sqlnet.ora is present and you use LDAP parameters in the connect identifier, then the connect identifier values take precedence.

Related Topics

Oracle Al Database Net Services Administrator's Guide

11.2 Allowed Parameters in the Connect Identifier

These are the LDAP parameters that you can use in the connect identifier.

- Protocol-Specific Parameters
 - These connect identifier parameters (PROTOCOL, HOST, PORT, NAME, and CONTEXT) are name-value pairs that define the LDAP connection.
- AUTHENTICATE BIND

The AUTHENTICATE_BIND parameter specifies whether the LDAP naming adapter should use a wallet for authentication.

- AUTHENTICATE BIND METHOD
 - The AUTHENTICATE_BIND_METHOD parameter specifies authentication method for the client LDAP naming adapter.
- DIRECTORY SERVER TYPE
 - The DIRECTORY_SERVER_TYPE parameter specifies the directory server to be used for LDAP-based name lookup.



WALLET LOCATION

The WALLET_LOCATION parameter specifies the directory where an Oracle wallet is stored.

11.2.1 Protocol-Specific Parameters

These connect identifier parameters (PROTOCOL, HOST, PORT, NAME, and CONTEXT) are name-value pairs that define the LDAP connection.

Purpose

To configure name-value pairs that define the LDAP connection.

Usage Notes

Parameter	Description	Required
PROTOCOL	Protocol, either LDAP or LDAPS.	Yes
	The LDAPS protocol uses a Transport Layer Security (TLS) connection.	
HOST	Host name where your LDAP directory server is running.	Yes
PORT	Port number for the LDAP connection.	No
	The default port for the LDAP protocol is 389 and for the LDAPS protocol is 636.	
NAME	LDAP entry to resolve the connect descriptor.	Yes
	This entry must be contained in the OracleContext container of a given context.	
CONTEXT	Directory naming context containing OracleContext.	No
	The default value for this parameter is: cn=OracleContext	
	For example, a context can be:	
	<pre>cn=OracleContext,dc=example,dc=com</pre>	

Example

Here is a sample connect identifier, specified with all the LDAP connection parameters:

```
scott/password@ldaps://ldapserver:636/
cn=orcl,cn=OracleContext,dc=example,dc=com
```

Related Topics

Oracle Al Database Net Services Administrator's Guide

11.2.2 AUTHENTICATE_BIND

The AUTHENTICATE_BIND parameter specifies whether the LDAP naming adapter should use a wallet for authentication.

Purpose

To specify whether the LDAP naming adapter should attempt to authenticate using a specified wallet, when it connects to the LDAP directory to resolve the service name in the connect string.

Usage Notes

When set to FALSE, the LDAP connection is established using an anonymous bind.



When set to TRUE, the LDAP connection is authenticated using an Oracle wallet. You must specify the wallet location using the WALLET LOCATION parameter.

Values

TRUE | FALSE

Default

FALSE

Example

AUTHENTICATE_BIND=TRUE

Related Topics

Oracle Al Database Net Services Administrator's Guide

11.2.3 AUTHENTICATE_BIND_METHOD

The AUTHENTICATE_BIND_METHOD parameter specifies authentication method for the client LDAP naming adapter.

Purpose

To specify the authentication method that the client LDAP naming adapter should use while connecting to the LDAP directory to resolve connect string names.

Usage Notes

The simple authentication method over LDAPS (LDAP over TLS connection) is supported.

You store the directory entry DN and password in an Oracle wallet. When the client connects to the LDAP server, it is authenticated using the credentials stored in this wallet. The wallet trust store must contain root certificates issued by the certificate authority of the LDAP server.

The LDAP naming adapter uses the <code>oracle.ldap.client.dn</code> and <code>oracle.ldap.client.password</code> entries from the wallet for authenticating to the LDAP server. If these entries are not present, then the client attempts an anonymous authentication using LDAPS.

Values

- LDAPS_SIMPLE_AUTH
- NONE

Default

NONE

Example

AUTHENTICATE_BIND_METHOD=LDAPS_SIMPLE_AUTH

Related Topics

Oracle Al Database Net Services Administrator's Guide



11.2.4 DIRECTORY_SERVER_TYPE

The DIRECTORY_SERVER_TYPE parameter specifies the directory server to be used for LDAPbased name lookup.

Purpose

With the Directory Naming method, connect identifiers are mapped to connect descriptors contained in an LDAP-compliant directory server. You can specify a value that corresponds to the type of directory server to be used, such as OID for Oracle Internet Directory, Oracle Unified Directory, or OpenLDAP and AD for Microsoft Active Directory.

Values

- OID for Oracle Internet Directory, Oracle Unified Directory, or OpenLDAP
- AD for Microsoft Active Directory

Default

OID

Example

DIRECTORY_SERVER_TYPE=AD

Related Topics

Oracle AI Database Net Services Administrator's Guide

11.2.5 WALLET LOCATION

The WALLET_LOCATION parameter specifies the directory where an Oracle wallet is stored.

Purpose

To specify the LDAP directory where the client wallet is stored. This wallet is used for making Transport Layer Security (TLS) connections to the LDAP directory.



(i) Note

This is a client-side parameter, and is not applicable to the database connection.

Usage Notes

The database client searches for the client wallet in this order:

- The client first looks for the WALLET_LOCATION parameter value in the connect identifier.
- If no wallet is present, then the client searches for the WALLET_LOCATION parameter value in the sqlnet.ora file.
- If no wallet is present, then the client uses the wallet from the operating system's default certificate store.



Default	
---------	--

None

Example

WALLET_LOCATION=/home/oracle/wallet

Related Topics

Oracle AI Database Net Services Administrator's Guide



Upgrade Considerations for Oracle Net Services

This appendix describes the coexistence and upgrade issues for Oracle Net Services.

Anonymous Access to Oracle Internet Directory
 Typical users of directory naming (LDAP) require anonymous access to the Oracle Internet Directory for name lookup.

A.1 Anonymous Access to Oracle Internet Directory

Typical users of directory naming (LDAP) require anonymous access to the Oracle Internet Directory for name lookup.

Oracle Internet Directory Setting

If you upgrade your Oracle Internet Directory software release 11g or later, then the default setting for Oracle Internet Directory changes to disallow anonymous access to the directory. The directory administrator must configure the directory to enable anonymous binds after upgrading the directory to release 11g. In addition, the way anonymous binds are configured in Oracle Internet Directory changed between Oracle Database 10g and Oracle Database 11g.

LDAP Schema for Oracle Net Services

This appendix describes the Oracle schema object classes and attributes defined in the directory server for Oracle Net Services objects. It does not describe object classes and attributes reserved for future functionality or used by other Oracle products.

Structural Object Classes

The Oracle schema supports the structural object classes for Oracle Net directory naming lookups.

Attributes

It lists the attributes used for the object classes. This list is subject to change.

B.1 Structural Object Classes

The Oracle schema supports the structural object classes for Oracle Net directory naming lookups.

Table B-1 Oracle Net Structural Object Classes

Object Class	Attributes	Description
orclDBServer	orclNetDescNameorclVersion	Defines the attributes for database service entries.
orclNetAddress	orclNetAddressStringorclNetProtocolorclVersion	Specifies a listener protocol address.
orclNetAddressAux1	 orclNetHostname 	Specifies an auxiliary object class to add attributes to an orclNetAddress entry.
orclNetAddressList	 orclNetAddrList orclNetFailover orclNetLoadBalance orclNetSourceRoute orclVersion 	Specifies a list of protocol addresses.
orclNetDescription	 orclNetAddrList orclNetInstanceName orclNetConnParamList orclNetFailover orclNetLoadBalance orclNetSdu orclNetServiceName orclNetSourceRoute orclSid orclVersion 	Specifies a connect descriptor containing the protocol address of the listener and the connect information to the service.



Table B-1 (Cont.) Oracle Net Structural Object Classes

Object Class	Attributes	Description
orclNetDescriptionAux1	 orclNetSendBufSize orclNetReceiveBufSize orclNetFailoverModeString orclNetInstanceRole 	Specifies auxiliary object class to add attributes to an orclNetDescription entry.
orclNetDescriptionList	orclNetDescListorclVersion	Specifies a list of connect descriptors.
orclNetService	orclNetDescNameorclVersion	Defines the attributes for network service name entries.
orclNetServiceAlias	orclNetDescNameorclVersion	Defines the attributes for network service alias entries.

B.2 Attributes

It lists the attributes used for the object classes. This list is subject to change.

Table B-2 LDAP Schema Attributes for Oracle Net Services

Attribute	Description
orclCommonContextMap	Allows the mapping of more than one default Oracle Context in the directory server.
orclNetAddrList	Identifies one or more listener protocol addresses.
orclNetAddressString	Defines a listener protocol address.
orclNetConnParamList	Placeholder for connect data parameters.
orclNetDescList	Identifies one or more connect descriptors.
orclNetDescName	Identifies a connect descriptor or a list of connect descriptors.
orclNetFailover	Turns connect-time failover on for a protocol address list.
orclNetFailoverModeString	Instructs Oracle Net to fail over to a different listener if the first listener fails during runtime. Depending on the configuration, session or any SELECT statements that were in progress are automatically failed over.
orclNetHostname	Specifies the host name.
orclNetInstanceName	Specifies the instance name to access.
orclNetInstanceRole	Specifies a connection to the primary or secondary instance of an Oracle Real Application Clusters (Oracle RAC) configuration.
orclNetLoadBalance	Turns client load balancing on for a protocol address list.
orclNetProtocol	Identifies the protocol used in the orclAddressString attribute.
orclNetReceiveBufSize	Specifies the buffer space limit for receive operations of sessions.



Table B-2 (Cont.) LDAP Schema Attributes for Oracle Net Services

Attribute	Description
orclNetSdu	Specifies the session data unit (SDU) size.
orclNetSendBufSize	Specifies the buffer space limit for send operations of sessions.
orclNetServiceName	Specifies the database service name in the CONNECT_DATA portion.
orclNetSourceRoute	Instructs Oracle Net to use each address in order until the destination is reached.
orclSid	Specifies the Oracle system identifier (SID) in the CONNECT_DATA portion of a connection descriptor.
orclVersion	Specifies the version of software used to create the entry.

Configuring OpenLDAP Server to Use Oracle Net Naming Directory

This appendix describes the steps to configure OpenLDAP server to work with Oracle Net Services LDAP schema.

OpenLDAP is an open source implementation of LDAP. Oracle Database client uses entries created using Oracle Net Services LDAP schema.

- 1. Download, install, and configure OpenLDAP server.
- 2. Add \$ORACLE_HOME/network/ldap/schema/openldap/orclnetnaming.schema to slapd.conf. If \$ORACLE_HOME is /opt/oracle, then include /opt/oracle/network/ldap/ schema/openldap/orclnetnaming.schema in slapd.conf.
- 3. Start OpenLDAP server.
- 4. Add oracleContext in preferred naming context. The following example shows the createorclctx.ldif file contents to add OracleContext, assuming dc=my-domain,dc=com is the chosen naming context.

```
$ cat createorclctx.ldif
dn: cn=oracleContext,dc=my-domain,dc=com
objectclass: orclContext
cn: oracleContext
```

5. Add the entry created in Step 4 to OpenLDAP server using ldapadd.

ldapadd example:

```
$ ldapadd -H <OpenLDAP Server Name and Port> -D <DN of user having
privileges to add> -f createorclctx.ldif <applicable authentication flags>
```

6. Create LDAP entry for storing connection descriptor. The following example shows sales.ldif entry details, assuming oracleContext is created under dc=my-dmain,dc=com.

```
$ cat sales.ldif
dn: cn=sales,cn=oraclecontext,dc=my-domain,dc=com
objectclass: top
objectclass: orclNetService
orclnetdescstring:
(DESCRIPTION=(ADDRESS=(PROTOCOL=TCP)(HOST=databasehost)(PORT=1521))
(CONNECT_DATA=(SERVICE_NAME=mydbservice.us.example.com)))
cn: sales
```

Add the entry created in Step 6 to OpenLDAP server using ldapadd.

ldapadd example:

\$ ldapadd -H <OpenLDAP Server Name and Port> -D <DN of user having privileges to add> -f sales.ldif <applicable authentication flags>



Related Topics

OpenLDAP Quick-Start Guide