

**Oracle® Communications  
Offline Mediation Controller**

Patch Set Release Notes

Release 12.0

**F10054-02**

September 2019

F10054-02

Copyright © 2018, 2019, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

---

---

# Contents

<b>Preface</b> .....	v
Audience .....	v
Downloading Oracle Communications Documentation .....	v
Documentation Accessibility .....	v
Document Revision History .....	v
<b>1 Summary of Customer-Reported Fixes</b>	
Customer-Reported Fixes .....	1-1
<b>2 New Features</b>	
<b>New Features in Offline Mediation Controller 12.0 Patch Set 2</b> .....	2-1
Hostname Now Used for Identifying Mediation Hosts .....	2-1
Additional NMSHELL Command-Line Components .....	2-1
Compiling the NPL Rule File by Using NMSHELL .....	2-2
Checking NMSHELL Command Status .....	2-3
Deleting Nodes .....	2-3
Incremental Import and Export of Specific Nodes .....	2-4
Exporting Node Chain Configuration and Customization by Using GUI .....	2-5
Importing Node Chain Configuration and Customization by Using GUI .....	2-5
Exporting Node Chain Configuration and Customization by Using NMSHELL .....	2-6
Importing Node Chain Configuration or Customization by Using NMSHELL .....	2-7
<b>New Features in Offline Mediation Controller 12.0 Patch Set 1</b> .....	2-8
Configurable Location for Storing ECE Response Records .....	2-9
ECE Distribution Cartridge Can Be Configured for Disaster Recovery .....	2-9
Support for Filtering Delayed Response Records from ECE .....	2-10
Configuring NARComparator and RatedEventsChecker .....	2-11
Filtering Delayed Response Records .....	2-12
Enhanced NMSHELL Command-Line Components .....	2-13
Starting Nodes .....	2-13
Stopping Nodes .....	2-14
Checking Node Status .....	2-15
Offline Mediation Controller Is Now Certified with Oracle Unified Directory 12.2 .....	2-16
Xalan-Java is Not Supported .....	2-16

### **3 Known Problems**

Offline Mediation Controller .....	3-1
------------------------------------	-----

---

---

# Preface

This guide includes information about Oracle Communications Offline Mediation Controller 12.0 patch sets.

## Audience

This guide is intended for all Offline Mediation Controller users.

## Downloading Oracle Communications Documentation

Product documentation is located on Oracle Help Center:

<http://docs.oracle.com>

Additional Oracle Communications documentation is available from the Oracle software delivery Web site:

<https://edelivery.oracle.com>

## Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at

<http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

### Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit

<http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit

<http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

## Document Revision History

The following table lists the revision history for this guide:

Version	Date	Description
F10054-01	September 2018	Initial release. Information about Patch Set 1 features, which are identified by "(Patch Set 1)", is added.
F10054-02	September 2019	Information about Patch Set 2 features, which are identified by "(Patch Set 2)", is added.



---

## Summary of Customer-Reported Fixes

This chapter provides an overview of the customer-reported bug fixes that were introduced in Oracle Communications Offline Mediation Controller.

### Customer-Reported Fixes

Table 1-1 lists the service request (SR) issues reported by external sources and provides a brief description of the resolution. The SRs are grouped by the respective patch sets.

**Table 1-1** Customer-Reported Fixes

SR Number	Bug Number	Description
3-17353094911	28806854 29335774	(Patch Set 2) When the batch insertion mode was enabled in Java Database Connectivity (JDBC) Distribution Cartridge, the performance of the cartridge was affected.  This has been fixed.
3-18539180101	28816188	(Patch Set 2) In a Distribution Cartridge (DC) node, with multithreading configurations, once the configured maximum number of records were reached and the output file was closed for writing, it was observed that the data continued to be written into the closed file.  This has been fixed.
3-18423607891	29023558	(Patch Set 2) In a mediation chain, if any Node Programming Language (NPL) rule file or routing between cartridges was updated, then Local Data Manager (LDM) which transports data from the output directory for one node to the input directory of the other nodes stopped movement of files.  This has been fixed.
3-18455452131	29540813	(Patch Set 2) After submitting a recycle job from the Suspense Management Center, the recycle job was dequeued by the Recycle Cartridge and was handed over to the Recycle Enhancement Processor (EP) cartridge. Even if the Recycle EP has lost the connection to the database, it continued to process the recycle jobs, leaving the status of the jobs as <b>recycling</b> and required a manual intervention to move the status back to <b>suspended</b> .  This has been fixed.

**Table 1–1 (Cont.) Customer-Reported Fixes**

SR Number	Bug Number	Description
3-19350872291	29540828	(Patch Set 2) If the customer data was lost in Oracle Communications Elastic Charging Engine (ECE), the Public User Identities (PUI) information was still intact. Any usage charging requests from ECE Distribution Cartridge (DC) node of Oracle Communications Offline Mediation Controller was always terminated in a delayed response from ECE, causing ECE to slowdown.  This has been fixed.
3-19461861711	30117842	(Patch Set 2) In case of a network issue, the Recycle Cartridge stopped working without automatic retries to connect with time out configurations.  This has been fixed.
NA	27938697	(Patch Set 1) Distribution Cartridge (DC) was displaying the "error processing file" error intermittently.  This has been fixed.
3-17544640231	28076189	(Patch Set 1) Enhancement Processor (EP) did not support more than 20 threads.  This has been fixed.
3-17156499871	28105656	(Patch Set 1) Offline Mediation Controller was not mapping input record types to the suspended usage record type and hence it was not possible to distinguish suspended records.  This has been fixed.
3-15005509201	28105679	(Patch Set 1) The memory utilization was not calculated properly. As a result, the node manager reported the fatal memory error even when the threshold was not reached.  This has been fixed.
3-16707732031	28105692	(Patch Set 1) The performance of Offline Mediation Controller was affected when there were larger number of input files to be processed. A high CPU utilization from EP threads was also observed.  This has been fixed.
3-17688816781	28311166	(Patch Set 1) The Offline Mediation Controller Oracle Communications Elastic Charging Engine (ECE) Distribution Cartridge (DC) node and EP thread configurations were not supported through user interface.  This has been fixed.
NA	28586528	(Patch Set 1) If the same file was sent to Offline Mediation Controller Oracle CDR Format Collection Cartridge (CC) again for processing, the already processed file was removed.  This has been fixed.

---

---

## New Features

This chapter provides an overview of the feature enhancements introduced in Oracle Communications Offline Mediation Controller 12.0 patch sets.

### New Features in Offline Mediation Controller 12.0 Patch Set 2

Offline Mediation Controller 12.0 Patch Set 2 includes the following enhancements:

- [Hostname Now Used for Identifying Mediation Hosts](#)
- [Additional NMSHELL Command-Line Components](#)
- [Incremental Import and Export of Specific Nodes](#)

#### Hostname Now Used for Identifying Mediation Hosts

In previous releases, Offline Mediation Controller was using only the IP addresses specified in the **SystemModel.cfg** file in the Administration Server configuration directory (*OMC\_home/config/adminserver*) to identify mediation hosts. The IP addresses in this file could not be changed directly and the workaround contained more steps.

This process has now been simplified. The **SystemModel.cfg** file contains the details of the node managers and the corresponding nodes for one administration server. If the IP address of the node manager is not provided, Offline Mediation Controller reads the host name of the node manager in this file and derives the IP address for identifying the corresponding mediation host. If you change the host name of a node manager in the **SystemModel.cfg** file, Offline Mediation Controller reads the new host name and derives the IP address of the corresponding mediation host.

#### Additional NMSHELL Command-Line Components

In previous releases, when you edited a node programming language (NPL) rule file in Offline Mediation Controller NPL Editor, there was only the option to compile and validate the NPL rule file by using NPL Editor. Also, you could not delete any nodes by using NMSHELL or check the status of an NMSHELL command.

With this enhancement, you can perform the following by using NMSHELL command-line components:

- Compile and validate the NPL rule file and make changes in the NPL rule file in case of any validation errors.
- Check the status of the command run.
- Delete all nodes or a specific node.

See the following topics for more information:

- [Compiling the NPL Rule File by Using NMSHELL](#)
- [Checking NMSHELL Command Status](#)
- [Deleting Nodes](#)

### Compiling the NPL Rule File by Using NMSHELL

To compile the NPL rule file by using NMSHELL:

1. Start Administration Server and Node Manager daemons. See the discussion about starting component daemons in *Offline Mediation Controller Installation Guide*.
2. Go to `OMC_home/bin/tools` and enter the following command:

```
./NMSHELL
```

The prompt changes to `nmsH>`.

3. Enter the following command:

```
login server_hostname port
```

where:

- `server_hostname` is the IP address or host name of the computer on which Administration Server is running.
  - `port` is the Administration Server port number.
4. When prompted, enter the user name and password.

You are connected to Administration Server.

5. Enter the following command:

```
compileNpl -f npl_file_name -d compiled_npl_class -majorType major_type_of_the_node -minorType minor_type_of_the_node -id node_id
```

where:

- `-f npl_file_name` specifies the absolute path of the NPL file that you want to compile.
- `-d compiled_npl_class` specifies the absolute path of the compiled NPL class after running the command.
- `-majorType major_type_of_the_node` specifies the major type of the node for which the NPL rule file is compiled. This parameter is not applicable if node ID is defined using the ID argument.
- `-minorType minor_type_of_the_node` specifies the minor type of the node for which the NPL rule file is compiled. This parameter is not applicable if node ID is defined using the ID argument.
- `-id node_id` specifies the unique ID assigned to the node for which the NPL rule file is compiled. This parameter is not applicable if `-majorType` and `-minorType` are specified.

The NPL rule file is compiled. If the compilation fails, update the rule file and recompile.

You can store the compiled NPL rule file in the `classpath` directory in the `config` folder of the node and update the `general.cfg` file to use the compiled NPL rule file.

---



---

**Important:** After compiling the NPL rule file, you must start and stop nodes only by using NMSHELL command-line components. Using the GUI to start or stop nodes uses only the attributes and NPL that are defined in GUI components.

---



---

### Checking NMSHELL Command Status

To check the status of the last NMSHELL command run:

1. Start Administration Server and Node Manager daemons. See the discussion about starting component daemons in *Offline Mediation Controller Installation Guide*.
2. Go to `OMC_home/bin/tools` and enter the following command:

```
./NMSHELL
```

The prompt changes to `nmsh>`.

3. Enter the following command:

```
login server_hostname port
```

where:

- `server_hostname` is the IP address or host name of the computer on which Administration Server is running.
  - `port` is the Administration Server port number.
4. When prompted, enter the user name and password.  
You are connected to Administration Server.
  5. Enter the following command:

```
cmd -status
```

This command returns the following results:

- `-1` specifies that the last run command failed or there are no commands run before.
- `0` specifies that the last run command was successful.

---



---

**Note:** When multiple nodes are started or stopped by using NMSHELL, the status of the command can be retrieved only by running the `status` command. See "[Checking Node Status](#)" for more information.

`cmd -status` confirms only whether the last run command was successful or failed.

---



---

### Deleting Nodes

To delete nodes:

1. Start Administration Server and Node Manager daemons. See the discussion about starting component daemons in *Offline Mediation Controller Installation Guide*.
2. Go to `OMC_home/bin/tools` and enter the following command:

```
./NMSHELL
```

The prompt changes to **nms**>.

3. Enter the following command:

```
login server_hostname port
```

where:

- *server\_hostname* is the IP address or host name of the computer on which Administration Server is running.
  - *port* is the Administration Server port number.
4. When prompted, enter the user name and password.  
You are connected to Administration Server.
  5. Do one of the following:

- To delete all the nodes in the mediation host, enter the following command:

```
deleteNodes
```

All the nodes for the currently running mediation host are deleted.

- To delete all the nodes managed by a specific node manager, enter the following command:

```
deleteNode -ip mediation_hostname -p port
```

- *mediation\_hostname* is the mediation host's IP address or host name.
- *port* is the mediation host port number.

All the nodes for the specified mediation host are deleted.

- To delete a specific node, enter the following command:

```
deleteNode node_id_1 node_id_2...
```

All the specified nodes are deleted.

## Incremental Import and Export of Specific Nodes

In previous releases, you had to export or import node configuration and customization from all the mediation hosts configured in Node Manager even if the configuration or customization for only one node chain was modified.

With this enhancement, you can export or import node configuration and customization from one or more node chains under the Node Manager by using the Offline Mediation Controller user interface (GUI) or NMSHELL command-line components.

See the following topics for more information:

- [Exporting Node Chain Configuration and Customization by Using GUI](#)
- [Importing Node Chain Configuration and Customization by Using GUI](#)
- [Exporting Node Chain Configuration and Customization by Using NMSHELL](#)
- [Importing Node Chain Configuration or Customization by Using NMSHELL](#)

---



---

**Important:** If you terminate the export or import process (by using GUI or NMSHELL) or if the system fails or an error occurs repeatedly, intermediate files, data files, and folders are created in the nodes directory in *OMC\_home*. You need to create an offline copy of these files manually and delete the nodes before running the command again.

---



---

### Exporting Node Chain Configuration and Customization by Using GUI

To export the node chain configuration and customization by using GUI:

1. Log on to Offline Mediation Controller Administration Client.  
The Node Hosts & Nodes (logical view) screen appears.
2. In the **Mediation Hosts** table, select a host.
3. In the **Nodes on Mediation Host** section, select a node from which you want to export the configuration and customization.
4. Right-click on the node and select **Export Node Chain** or click **Export Node Chain** on the node host panel.  
The Export Configuration dialog box appears.
5. In the **Directory** field, enter the full path or browse to the directory to which you want to export the node chain configuration and customization.
6. Click **Export**.

The node chain configuration and customization are exported to the **export\_timestamp.xml** and **export\_timestamp.nmx** file respectively.

### Importing Node Chain Configuration and Customization by Using GUI

To import the node chain configuration and customization by using GUI:

1. Log on to Offline Mediation Controller Administration Client.  
The Node Hosts & Nodes (logical view) screen appears.
2. In the **Mediation Hosts** table, select a host.
3. In the **Nodes on Mediation Host** section, right-click and select the following as appropriate or select from the node host panel:
  - **Import Node Chain Customization**
  - **Import Node Chain Configuration**
 The Import Configuration dialog box appears.
4. In the **Import File** field, enter the full path or browse to the **.xml** or **.nmx** file from which you want to import the node chain configuration or customization.  
The node managers display under the Old Node Manager column in the Node Manager mapping pane.
5. Select a Node Manager from the list and click **Map**.  
The Map dialog box appears.
6. Enter **Name**, **IP address** or **host name**, and **Port number** for the new Node Manager.
7. Repeat step 5 and step 6 for the rest of the node managers in the list.

8. Select Regenerate Node id(s) to regenerate the node ID of the nodes for which the configuration or customization is imported.
9. After mapping all node managers, click **Import**.

The node chain configuration and customization is imported into the selected node manager. After the import, backup of existing nodes is created in the `OMC_home/importbackup` directory.

### Exporting Node Chain Configuration and Customization by Using NMSHELL

To export the node chain configuration and customization:

1. Start Administration Server and Node Manager daemons. See the discussion about starting component daemons in *Offline Mediation Controller Installation Guide*.
2. Go to `OMC_home/bin/tools` and enter the following command:

```
./NMSHELL
```

The prompt changes to `nmsh>`.

3. Enter the following command:

```
login server_hostname port
```

where:

- `server_hostname` is the IP address or host name of the computer on which Administration Server is running.
- `port` is the Administration Server port number.

4. When prompted, enter the user name and password.

You are connected to Administration Server.

5. Enter the following command:

```
export [-n mediation_name@host_name:port] -f filename [-c value -nc y -id node_id]
```

where:

- `-n mediation_name@mediation_hostname:port` exports the mediation host's node configuration or node customization.

where:

- `mediation_name` is the mediation host's name configured in Node Manager.
- `mediation_hostname` is the mediation host's IP address or host name.
- `port` is the port number at which the mediation host communicates with Node Manager.

To export multiple hosts, enter the mediation hosts separated by comma (,).

- `-f filename` specifies the name and path of the output files. Do not include the file extension.
- `-c value` specifies whether to export both the node configuration and customization or only the node configuration.

where `value` is:

- **Y** to export both the node configuration and node customization. Two files are generated; a *filename.xml* file with the node configuration and a *filename.nmx* file with the node customization. This is default.
- **N** to export only the node configuration. One file is generated: a *filename.xml* file with the node configuration.
- **-nc y** specifies to export only the node chain configuration and customization.
- **-id *node\_id*** specifies to export the node chain configuration and customization for the specified *node\_id*. *node\_id* is the unique ID assigned to the node when the node configuration is saved. You can add one or more *node\_ids* as comma separated values.

For example:

```
export -n abc@localhost:55109 -f ../testnodechain/test/exportfile -c y -nc y
-id 31a80o-16it-jrzysls9
```

The node configuration and customization from the **31a80o-16it-jrzysls9** node chain in the mediation host (**abc@localhost:55109**) are exported successfully to the specified file.

## Importing Node Chain Configuration or Customization by Using NMSHELL

To import the node chain configuration or customization:

1. Start Administration Server and Node Manager daemons. See the discussion about starting component daemons in *Offline Mediation Controller Installation Guide*.

---



---

**Note:** Ensure that Administration Server and Node Manager are available in the same *OMC\_home* directory. If Node Manager is in a different directory, the node IDs are regenerated during the import by default and a backup of the old node chain is not created.

---



---

2. Go to *OMC\_home/bin/tools* and enter the following command:

```
./NMSHELL
```

The prompt changes to **nmsh>**.

3. Enter the following command:

```
login server_hostname port
```

where:

- *server\_hostname* is the IP address or host name of the computer on which Administration Server is running.
  - *port* is the Administration Server port number.
4. When prompted, enter the user name and password.

You are connected to Administration Server.

---



---

**Note:** Ensure that you stop the nodes for which you want to import the customization or configuration before importing the node chain configuration or customization. See "[Stopping Nodes](#)" for more information.

---



---

5. Enter the following command:

```
import -n mediation_name@mediation_hostname:port -f filename -c value -nc y -r y
```

where:

- **-n mediation\_name@mediation\_hostname:port** specifies the mediation host configured in Node Manager.

where:

- *mediation\_name* is the mediation host's name configured in Node Manager.
- *mediation\_hostname* is the IP address or host name of the mediation host you are importing to.
- *port* is the port number at which the mediation host you are importing to communicates with Node Manager.

The command verifies whether the mediation host exists in Node Manager. If the mediation host does not exist, the command generates an error.

- **-f filename** specifies the name and path of the input file. Use *filename.xml* file to import the node configuration and use *filename.nmx* file to import the node customization.
- **-c value** specifies whether to import the node customization or the node configuration.

where *value* is:

- **Y** to import only the node customization. Use this value with the *filename.nmx* file.
- **N** to import only the node configuration. Use this value with the *filename.xml* file.

- **-nc y** specifies to import only the node chain customization or configuration.
- **-r y** specifies to regenerate the *node\_id* of the nodes for which the configuration or customization is imported. This value must be set if you importing node chain configuration or customization.

The node chain configuration or customization is imported into the specified mediation host. After the import, backup of existing nodes is created in the *OMC\_home/importbackup* directory.

For example:

```
import -n linux1@10.10.10.111:55109 -f import.xml -c N -nc y -r y
```

The node chain configuration is imported from the **import.xml** file into the specified mediation hosts (**linux1@10.10.10.111:55109**).

After importing the node chain configuration or customization, you need to manually map the nodes that are not part of the imported node chain and delete undesired nodes.

## New Features in Offline Mediation Controller 12.0 Patch Set 1

Offline Mediation Controller 12.0 Patch Set 1 includes the following enhancements:

- [Configurable Location for Storing ECE Response Records](#)

- [ECE Distribution Cartridge Can Be Configured for Disaster Recovery](#)
- [Support for Filtering Delayed Response Records from ECE](#)
- [Enhanced NMSHELL Command-Line Components](#)
- [Offline Mediation Controller Is Now Certified with Oracle Unified Directory 12.2](#)
- [Xalan-Java is Not Supported](#)

## Configurable Location for Storing ECE Response Records

By default, the Offline Mediation Controller Oracle Communications Elastic Charging Engine (ECE) Distribution Cartridge (DC) node writes the ECE response records to the files in the default output directory of the ECE DC node; for example, the success response records are written to the file in the *OMC\_home/ocomc/output/ecedc\_NodeID/success* directory, where:

- *OMC\_home* is the directory in which you installed Offline Mediation Controller.
- *ecedc\_NodeID* is the unique identifier of the ECE DC node.

With this enhancement, you can configure a custom location for storing the ECE response records. If a custom location is not configured, the ECE DC node writes the records to the files in the default output directory of the ECE DC node.

You can configure the location for storing the ECE response records by using the following options in the **Output Directory Configuration** tab in the **Node Configuration** section:

Field	Description
<b>Duplicate request directory</b>	Enter the path to the directory where all the files containing the duplicate response records must be stored.
<b>Success response directory</b>	Enter the path to the directory where all the files containing the success response records must be stored.
<b>Suspense directory</b>	Enter the path to the directory where all the files containing the suspense response records must be stored.
<b>No-response directory</b>	Enter the path to the directory where all the files containing the no response records must be stored.
<b>Delayed response directory</b>	Enter the path to the directory where all the files containing the delayed response records must be stored.

For more information on the ECE DC node, see the discussion about the ECE cartridge pack in *Offline Mediation Controller Cartridge Packs*.

## ECE Distribution Cartridge Can Be Configured for Disaster Recovery

The ECE DC node creates usage requests based on the call detail record (CDR) input stream, which are then submitted to ECE for rating. In case if the node manager or system fails during this process, you might lose the input CDR data and may not be able to create the usage requests.

To recover input CDRs and to allow failover in case of system failure, you can now configure the ECE DC for disaster recovery. This ensures that the CDR files are retained in the system until the ECE DC node receives the success response from ECE.

To configure the ECE DC node for disaster recovery:

1. Open the `OMC_home/web/htdocs/AdminServerImpl.properties` file in a text editor.
2. Set the following entry to **true**:  

```
com.nt.udc.admin.server.AdminServerImpl.disasterRecovery true
```
3. Save and close the file.
4. Restart Administration Server and Administration Client.

In this case, when the node manager or system fails, the CDRs for which the response has not been received from ECE are stored in the recovery (`.archdel`) files. The recovery files are stored in the input directory of the ECE DC node (which is the `OMC_home/ocomc/input/ecedc_NodeID` directory). You can use the **RatedEventsChecker** utility to reprocess the recovery files. For more information, see "[Support for Filtering Delayed Response Records from ECE](#)".

After you restart the system, you can copy the NAR files from the `outputdir` directory of the **RatedEventsChecker** utility to the input directory of the ECE DC node for reprocessing the records.

## Support for Filtering Delayed Response Records from ECE

In the previous releases, the ECE DC node was reprocessing all the delayed response records from ECE irrespective of the response received, such as success or failure.

With this enhancement, you can avoid the reprocessing of the delayed response records which are already processed by ECE by filtering the delayed response records based on the response received. You can perform this by using the **NARComparator** and **RatedEventsChecker** utilities.

The **NARComparator** utility compares the network accounting records (NARs) in `delayedresponsedir` and `noresponsedir` directories:

- If the session ID of the NAR in the `delayedresponsedir` directory matches the session ID of the NAR in the `noresponsedir` directory, **NARComparator** writes the NAR to the file in the `filteroutdir/success` directory.
- If no match is found, **NARComparator** writes the NAR to the file in the `filteroutdir/reprocess` directory.
- If any error occurs during this process, **NARComparator** writes the NAR to the file in the `filteroutdir/error` directory.

The **RatedEventsChecker** utility checks if the `narfield` values in the `inputdir` directory exist in the Oracle Communications Billing and Revenue Management (BRM) database. This utility compares the `narfield` values of the NARs in the `inputdir` directory with the values stored in the `columnname` in the BRM database. If no match is found, the NAR is copied to the file in the `outputdir/reprocess` directory for reprocessing the records.

---

**Important:** After running the **RatedEventsChecker** utility, you must copy the files in the *outputdir/reprocess* directory to the input directory of the NAR CC node (which is the *OMC\_Home/suspense* directory) for reprocessing the response records. And, ensure the following:

- The InputRec block of the NAR CC Node Programming Language (NPL) is compatible with NAR fields specified in the output file generated by **RatedEventsChecker**.
  - The OutputRec block of NAR CC NPL is compatible with the InputRec block of the ECE DC NPL.
- 

You can configure the **NARComparator** and **RatedEventsChecker** utilities by using the *OMC\_home/ocomc/web/htdocs/NarComparator.properties* and *OMC\_home/ocomc/web/htdocs/RatedEventsChecker.properties* files respectively.

For more information, see the following:

- [Configuring NARComparator and RatedEventsChecker](#)
- [Filtering Delayed Response Records](#)

### Configuring NARComparator and RatedEventsChecker

To configure the **NARComparator** and **RatedEventsChecker** utilities:

1. Open the *OMC\_home/ocomc/web/htdocs/NarComparator.properties* file.
2. Edit the configuration entries listed in [Table 2-1](#):

**Table 2-1** *NARComparator Configuration Entries*

Entry	Description
<b>norespondedir</b>	Specify the path to the directory in which you want to store the no response records.
<b>delayedrespondedir</b>	Specify the path to the directory in which you want to store the delayed response records.
<b>filteroutdir</b>	Specify the path to the directory in which you want to store the response records filtered by <b>NARComparator</b> .
<b>narfilesuffix</b>	Specify the string to append at the end of the NAR file name; for example, .arch,.archdel.

3. Save and close the file.
4. Open the *OMC\_home/ocomc/web/htdocs/RatedEventsChecker.properties* file.
5. Edit the configuration entries listed in [Table 2-2](#):

**Table 2-2** *RatedEventsChecker Configuration Entries*

Entry	Description
<b>dbuser</b>	Specify the name of the BRM database user.
<b>dbhost</b>	Specify the host name or IP address of the BRM database user.
<b>dbport</b>	Specify the number for the Oracle database port.
<b>dbsid</b>	Specify the Oracle database alias.

**Table 2–2 (Cont.) RatedEventsChecker Configuration Entries**

Entry	Description
<b>db servicename</b>	Specify the BRM database service name.
<b>JDBCUrl</b>	Specify the Oracle JDBC URL to use to connect to the BRM database. <b>jdbcUrl="jdbc:oracle:thin://hostname:port:sid"</b> where <i>hostname</i> and <i>port</i> are the host name and port number for the computer on which the database queue resides, and <i>sid</i> is the name of the BRM database service.
<b>JDBCdriver</b>	Specify the Oracle JDBC driver to use to connect to the BRM database; for example, <code>oracle.jdbc.driver.OracleDriver</code> .
<b>inputdir</b>	Specify the path to the directory in which you want to store the NAR files from the <i>filteroutdir/reprocess</i> directory filtered by <b>NARComparator</b> .
<b>outputdir</b>	Specify the path to the directory in which you want to store the response records filtered by <b>RatedEventsChecker</b> .
<b>inputfilesuffix</b>	Specify the string to append at the end of the input file name; for example, <code>.arch,.archdel</code> .
<b>tablename</b>	Specify the name of the BRM database table in which the NAR session IDs are stored; for example, <code>EVENT_T</code> .
<b>columnname</b>	Specify the name of the column in the BRM database table that must be used for comparing NAR session IDs; for example, <code>NETWORK_SESSION_ID</code> .
<b>narfield</b>	Specify the name of the NAR field that must be used for comparing NAR session IDs; for example, <code>session_id</code> .

6. Save and close the file.

### Filtering Delayed Response Records

To filter the delayed response records received from ECE:

1. Copy the NAR files from the no response directory of the ECE DC node into the *norespondedir* directory specified in the `OMC_home/ocomc/web/htdocs/NarComparator.properties` file.
2. Copy the NAR files from the delayed response directory of the ECE DC node into the *delayedrespondedir* directory specified in the `OMC_home/ocomc/web/htdocs/NarComparator.properties` file.
3. Go to the `OMC_home/bin/tools` directory.
4. Enter the following command, which compares the NARs in the *norespondedir* and *delayedrespondedir* directories:  

```
./NARComparator
```
5. Verify that the success, error, and reprocess response records are written to the NAR files in the respective subdirectories of the *filteroutdir* directory.  
The location of the *filteroutdir* directory is specified in the `OMC_home/ocomc/web/htdocs/NarComparator.properties` file.
6. Copy the `ojdbc-version.jar` into the `OMC_home/ocomc/3rdparty_jars/` directory; where *version* is the latest version of Java certified with Offline Mediation Controller.

See the discussion about Offline Mediation Controller system requirements in the *Offline Mediation Controller Installation Guide* for the Java version.

7. Copy the NAR files from the *filteroutdir/reprocess* directory into the *inputdir* directory specified in the *OMC\_home/ocomc/web/htdocs/RatedEventsChecker.properties* file.
8. Go to the *OMC\_home/bin/tools* directory.
9. Enter the following command, which compares the NARs in the directories of the ECE DC node:

```
./RatedEventsChecker -p BRMdbPassword
```

where *BRMdbPassword* is the password of the BRM database user.

10. Verify that the response records are written to the reprocess directory in the *outputdir* directory specified in the *OMC\_home/ocomc/web/htdocs/RatedEventsChecker.properties* file.

## Enhanced NMSHELL Command-Line Components

In previous releases, you could only start or stop all the nodes in the currently running mediation host by using the NMSHELL command-line components.

Offline Mediation Controller now allows you to perform the following tasks by using NMSHELL:

- Start or stop all nodes in the mediation host.
- Start or stop all nodes for a specific node manager.
- Start or stop specific nodes by using the node ID.
- Check the status of a node; for example, stopped, running, and suspended.

For more information, see:

- [Starting Nodes](#)
- [Stopping Nodes](#)
- [Checking Node Status](#)

### Starting Nodes

To start nodes:

1. Start Administration Server and Node Manager daemons. See the discussion about starting component daemons in *Offline Mediation Controller Installation Guide*.
2. Go to *OMC\_home/bin/tools* and enter the following command:

```
./NMSHELL
```

The prompt changes to **nmsh>**.

3. Enter the following command:

```
login server_hostname port
```

where:

- *server\_hostname* is the IP address or host name of the computer on which Administration Server is running.
- *port* is the Administration Server port number.

4. When prompted, enter the user name and password.  
You are connected to Administration Server.
5. Do one of the following:
  - To start all nodes in the mediation host, enter the following command:  
**startNodes**  
  
All the nodes for the currently running mediation host are started.
  - To start all nodes managed by a specific node manager, enter the following command:  
**startNode -ip mediation\_hostname -p port**
    - *mediation\_hostname* is the mediation host's IP address or host name.
    - *port* is the mediation host port number.All the nodes for the specified mediation host are started.
  - To start a specific node, enter the following command:  
**startNode node\_id\_1 node\_id\_2...**  
  
All the specified nodes are started.

### Stopping Nodes

To stop nodes:

1. Start Administration Server and Node Manager daemons. See the discussion about starting component daemons in *Offline Mediation Controller Installation Guide*.
2. Go to *OMC\_home/bin/tools* and enter the following command:  
**./NMShell**  
  
The prompt changes to **nmsh>**.
3. Enter the following command:  
**login server\_hostname port**  
  
where:
  - *server\_hostname* is the IP address or host name of the computer on which Administration Server is running.
  - *port* is the Administration Server port number.
4. When prompted, enter the user name and password.  
You are connected to Administration Server.
5. Do one of the following:
  - To stop all the nodes in the mediation host, enter the following command:  
**stopNodes**  
  
All the nodes for the currently running mediation host are stopped.
  - To stop all the nodes managed by a specific node manager, enter the following command:

```
stopNode -ip mediation_hostname -p port
```

- *mediation\_hostname* is the mediation host's IP address or host name.
- *port* is the mediation host port number.

All the nodes for the specified mediation host are stopped.

- To stop a specific node, enter the following command:

```
stopNode node_id_1 node_id_2...
```

All the specified nodes are stopped.

### Checking Node Status

To check the status of nodes:

1. Start Administration Server and Node Manager daemons. See the discussion about starting component daemons in *Offline Mediation Controller Installation Guide*.
2. Go to *OMC\_home/bin/tools* and enter the following command:

```
./NMShell
```

The prompt changes to **nmsh>**.

3. Enter the following command:

```
login server_hostname port
```

where:

- *server\_hostname* is the IP address or host name of the computer on which Administration Server is running.
  - *port* is the Administration Server port number.
4. When prompted, enter the user name and password.  
You are connected to Administration Server.
  5. Do one of the following:

- To check the status of all the nodes in the mediation host, enter the following command:

```
status
```

The status of all the nodes for the currently running mediation host is displayed.

- To check the status of all the nodes managed by a specific node manager, enter the following command:

```
status -ip mediation_hostname -p port
```

- *mediation\_hostname* is the mediation host's IP address or host name.
- *port* is the mediation host port number.

The status of all the nodes for the specified mediation host is displayed.

- To check the status of a specific node, enter the following command:

**status** *node\_id\_1 node\_id\_2...*

The status for all the specified nodes is displayed.

## **Offline Mediation Controller Is Now Certified with Oracle Unified Directory 12.2**

Offline Mediation Controller 12.0 is now certified with Oracle Unified Directory 11.1.2.3.0 and 12.2.

## **Xalan-Java is Not Supported**

Currently, Offline Mediation Controller 12.0 is certified with Xalan-Java 2.7.2.

With this patch, Xalan-Java is not supported in Offline Mediation Controller 12.0.

---

---

## Known Problems

This chapter provides an overview of the known problems in Oracle Communications Offline Mediation Controller 12.0 Patch Set 1.

### Offline Mediation Controller

There are no known problems in Offline Mediation Controller 12.0 Patch Set 1.

