

# Oracle® Tuxedo

## Mainframe Adapter for TCP Gateway User's Guide



Release 22c  
F84948-02  
October 2023

The Oracle logo, consisting of a solid red square with the word "ORACLE" in white, uppercase, sans-serif font centered within it.

ORACLE®

Oracle Tuxedo Mainframe Adapter for TCP Gateway User's Guide, Release 22c

F84948-02

Copyright © 1996, 2023, Oracle and/or its affiliates.

Primary Author: Priya Pathak

Contributing Authors: Tulika Das

Contributors: Maggie Li

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, and MySQL are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

# Contents

<b>1</b>	<b>Introducing Oracle Tuxedo Mainframe Adapter for TCP Gateway</b>	
1.1	What You Need to Know	1-1
1.2	Oracle TMA TCP Gateway and the Oracle Tuxedo Architecture	1-2
1.3	Operational Considerations	1-3
1.4	Oracle TMA TCP Functionality	1-4
1.4.1	Domains-based Gateway Connectivity	1-4
1.4.2	Security	1-4
1.4.3	Connection Multiplexing	1-4
1.4.4	Domain Name Server Support	1-5
1.5	GWIDOMAIN Gateway Component	1-5
1.6	How TMA TCP Gateway Affects Oracle Tuxedo Application Programs	1-5
1.6.1	VIEW Definitions	1-6
1.6.2	FML Buffer Support	1-6
1.7	How TMA TCP Gateway Affects Oracle Tuxedo Administration	1-6
<b>2</b>	<b>Understanding How Oracle TMA TCP Gateway Works</b>	
2.1	Planning Your Configuration	2-1
2.2	Initializing TMA TCP Gateway	2-2
2.3	Processing Local Service Requests	2-2
2.3.1	Step 1: Receiving a Service Request from Oracle Tuxedo Software	2-3
2.3.2	Step 2: Connecting to a Remote System	2-3
2.3.3	Step 3: Converting Input Buffer Types	2-3
2.3.4	Step 4: Translating Input Data	2-3
2.3.5	Step 5: Transmitting the Service Request	2-4
2.3.6	Step 6: Receiving a Reply	2-4
2.3.7	Step 7: Translating the Reply	2-4
2.3.8	Step 8: Converting Output Data	2-4
2.3.9	Step 9: Sending the Reply to the Caller	2-4
2.4	Processing Remote Service Requests	2-5
2.5	Processing Shut Down Requests	2-5
2.6	Programming Considerations	2-5
2.6.1	Input and Output Issues	2-5

2.6.1.1	Preparing Input and Output Data with TMA TCP Gateway	2-6
2.6.1.2	Service Request Parameters	2-6
2.6.1.3	Output Data Considerations	2-7
2.6.2	Limitations on the Use of Certain ATMI Functions	2-7
2.6.2.1	Conversational Communication Functions	2-7
2.6.2.2	Non-Transactional Communications	2-8
2.6.2.3	The tpsprio( ) and tpgprio( ) Functions	2-8
2.6.2.4	The tpbroadcast() and tnotify() Functions	2-8
2.6.3	Error Handling	2-8
2.6.3.1	Gateway Errors	2-9
2.6.3.2	Remote System Failures	2-9
2.6.3.3	Application Errors	2-9

### 3 Configuring Oracle TMA TCP Gateway for Data Mapping

---

3.1	Converting Input and Output Data	3-1
3.1.1	Buffers and Records	3-2
3.1.2	Buffers Received from Local Programs	3-2
3.1.3	Records Received from Remote Programs	3-2
3.2	Managing Parameters for Buffer and Record Conversion	3-3
3.2.1	Parameters for Locally Originated Calls	3-3
3.2.1.1	Guidelines for Mapping Input Buffers to Input Records	3-4
3.2.1.2	Guidelines for Mapping Output Records to Output Buffers	3-5
3.2.2	Parameters for Remotely Originated Calls	3-5
3.2.2.1	Guidelines for Mapping Input Records to Input Buffers	3-6
3.2.2.2	Guidelines for Mapping Output Buffers to Output Records	3-7
3.3	Mapping Buffers to Records	3-8
3.3.1	Setting the INBUFTYPE and INRECTYPE Parameters	3-8
3.4	Mapping Records to Buffers	3-10
3.4.1	Setting the OUTRECTYPE and OUTBUFTYPE Parameters	3-10
3.4.2	Creating VIEW Definitions to Facilitate Buffer Conversion	3-12
3.4.2.1	Preparing VIEW Definitions	3-12
3.4.3	Translating Data	3-13
3.4.3.1	Data Translation Rules	3-13
3.4.3.2	NULL Characters in String Length Calculations (C Programs)	3-14
3.4.3.3	NULL Characters in String Length Calculations (COBOL Programs)	3-14
3.4.3.4	Converting Numeric Data	3-15
3.5	Encoding COBOL Data Types	3-15
3.5.1	Using the COBOL Data Encoding Library	3-16
3.5.1.1	Encoding for All Services	3-16
3.5.1.2	Encoding Messages To and From a Specific Host	3-16

3.6	Using Code Page Translation Tables	3-16
3.6.1	Specifying a Translation Table	3-17
3.6.2	How the Translation Tables Work	3-18
3.6.3	Troubleshooting Translation Table Errors	3-18
3.6.4	Sample DMCONFIG Definition for ASCII to EBCDIC Translations	3-19
3.7	Using Multibyte Character Set (MBCS) Translations	3-19
3.7.1	Sample DMCONFIG Definition for MBCS Translations	3-20

## 4 Setting Up Security for Oracle TMA TCP Gateway

---

4.1	Security Checking from Tuxedo to Mainframe	4-1
4.2	Security Checking from Mainframe to Tuxedo	4-2
4.3	Setting Up Security	4-2
4.3.1	Tuxedo Security Plug-in	4-3
4.3.2	Built-in Tuxedo Security	4-3
4.4	Sample Security Files	4-3
4.4.1	User Files	4-3
4.4.2	Group File	4-4
4.4.3	ACL File	4-4
4.5	Data Area Security	4-5
4.5.1	Enabling Data Area Security	4-5
4.5.2	Format	4-5
4.6	Using TLS Encryption	4-6

## 5 Configuring Oracle TMA TCP Gateway

---

5.1	Updating the Oracle Tuxedo UBBCONFIG File	5-1
5.1.1	Updating the GROUPS Section to Establish a Server Group	5-1
5.1.1.1	Syntax	5-2
5.1.1.2	Example	5-2
5.1.2	Updating the SERVERS Section	5-2
5.1.2.1	Syntax	5-3
5.1.2.2	Using the Request Logging Option	5-3
5.1.2.3	Other Options for Configuring Servers	5-4
5.2	Specifying Parameters in the GWICONFIG File	5-4
5.2.1	Defining the GLOBAL Section of the GWICONFIG File	5-6
5.2.2	Defining the NATIVE Section of the GWICONFIG File	5-8
5.2.3	Defining the FOREIGN Section of the GWICONFIG File	5-9
5.2.4	Defining the LOCAL_SERVICES Section of the GWICONFIG File	5-11
5.2.5	Defining the REMOTE_SERVICES Section of the GWICONFIG File	5-13
5.3	Defining Domain Configurations in the DMCONFIG File	5-14

5.3.1	DM_LOCAL_DOMAINS Section	5-14
5.3.2	DM_REMOTE_DOMAINS Section	5-17
5.3.3	DM_ACCESS_CONTROL Section	5-19
5.3.4	DM_LOCAL_SERVICES Section	5-20
5.3.5	DM_REMOTE_SERVICES Section	5-21
5.3.6	DM_ROUTING Section	5-23
5.3.7	Sample DMCONFIG File	5-24

## 6 Starting Oracle TMA TCP Gateway

---

6.1	Setting Environment Variables	6-1
6.2	Invoking TMA TCP Gateway	6-1
6.3	Administering the Gateways	6-1

## 7 Error and Information Messages

---

## 8 Code Page Translation Tables

---

8.1	Modifying a Code Page Translation Table	8-1
8.2	Default Tuxedo	8-2
8.3	United States (00819x00037)	8-3
8.4	Germany (00819x00273)	8-4
8.5	Finland/Sweden (00819x00278)	8-5
8.6	Spain (00819x00284)	8-6
8.7	Great Britain (00819x00285)	8-7
8.8	France (00819x00297)	8-8
8.9	Belgium (00819x00500)	8-9
8.10	Portugal (00819x00860)	8-10
8.11	Latin-1 (00819x01047)	8-12
8.12	Latin-2 (00912x00870)	8-13

# 1

## Introducing Oracle Tuxedo Mainframe Adapter for TCP Gateway

The Oracle Tuxedo Mainframe Adapter for TCP Gateway (hereafter referenced as TMA TCP Gateway) is a domains-based gateway connectivity feature that allows application programs on Oracle Tuxedo systems to perform non-transactional tasks with application programs in other OLTP systems that support TMA TCP, which include:

- CICS on IBM MVS systems
- IMS/TM on IBM MVS systems

The TMA TCP Gateway is designed to provide transparent access to services that reside outside an Oracle Tuxedo region. In addition, TMA TCP Gateway can provide remote application programs with access to local services.

This chapter provides information about the following topics:

- [What You Need to Know](#)
- [Oracle TMA TCP Gateway and the Oracle Tuxedo Architecture](#)
- [Operational Considerations](#)
- [Oracle TMA TCP Functionality](#)
- [GWIDOMAIN Gateway Component](#)
- [How TMA TCP Gateway Affects Oracle Tuxedo Application Programs](#)
- [How TMA TCP Gateway Affects Oracle Tuxedo Administration](#)

### 1.1 What You Need to Know

This document is intended for system administrators who will configure and administer TMA TCP Gateway. In addition, programmers will find useful pointers for developing client programs and service routines that send data through TMA TCP Gateway.

This document describes the TMA TCP Gateway component and gives instructions for using the tools for building TMA TCP Gateway applications.

This guide explains how to configure and administer TMA TCP Gateway and how TMA TCP Gateway fits into the Oracle Tuxedo environment. In addition, this guide:


- Explains how TMA TCP Gateway processes service requests, those that originate locally and those that originate on remote systems
- Explains how TMA TCP Gateway affects Oracle Tuxedo application programs
- Provides conceptual and procedural information that will help you configure and administer TMA TCP Gateway

## 1.2 Oracle TMA TCP Gateway and the Oracle Tuxedo Architecture

An Oracle Tuxedo region consists of client and server programs that operate across a network of Oracle Tuxedo systems or compatible systems. Any client program can request services that are offered by any server program running on any computer in the region. The location of server programs is kept transparent through use of a directory that maps services to servers.

The following figure shows, TMA TCP Gateway extends this transparent access by sending requests to and receiving requests from remote regions and systems through TCP/IP network software.

**Figure 1-1 Routing Service Calls through Oracle TMA TCP Gateway**



As above figure illustrates, inside a single region, TMA TCP Gateway fits between the Oracle Tuxedo software and TCP/IP.

- When local client programs send requests to remote systems, TMA TCP Gateway transforms those requests into messages formatted appropriately for transmission



to the remote system. Also, when remote systems respond, TMA TCP Gateway transforms these responses into replies that local client programs can process.

- When remote client programs send request messages, TMA TCP Gateway transforms those messages into requests that local service routines can process. Also, when local service routines send replies, TMA TCP Gateway transforms those replies into messages that remote services can process.

The TMA TCP Gateway product is implemented as a Tuxedo domain gateway. It accepts standard Oracle Tuxedo service requests and returns standard replies.

One TMA TCP Gateway gateway connects to multiple communications targets, also referred to as gateways. Each communications target, or gateway, is a unique network endpoint.

Although remote systems are identified in the TMA TCP Gateway configuration, they remain unknown to Oracle Tuxedo software. For example, remote systems that are accessible through TMA TCP Gateway are not identified in the `MACHINES` section of the `UBBCONFIG` file.

The TMA TCP Gateway gateway maintains its own control information in shared memory, in much the same way that Oracle Tuxedo software itself maintains the Bulletin Board. Although TMA TCP Gateway accesses the Oracle Tuxedo Bulletin Board, Oracle Tuxedo does not access TMA TCP Gateway control information.

## 1.3 Operational Considerations

Operational considerations are permanent limitations on using a feature. The following operational considerations apply to TMA TCP Gateway:

### Note:

In the following discussion, a local application program is one that resides within the immediate Oracle Tuxedo administrative region. A remote application program is one that resides outside the immediate Oracle Tuxedo administrative region.

- The TMA TCP Gateway software does not support conversational communication.
- The TMA TCP Gateway software supports only nontransactional communication.
- Local client and server programs which use the `tpsprio()` function set the priority where service requests are dequeued by TMA TCP Gateway. This process does not affect any prioritization on the remote system.
- Local client programs cannot use the `tpbroadcast()` function to send unsolicited messages to remote client programs (and the reverse).
- Local services cannot use the `tpbroadcast()` or `tpnotify()` functions to send messages to remote client programs (and the reverse).
- When local client and server programs use the `tpgprio()` function to determine the priority of a remote service, the priority of a local TMA TCP Gateway requester is returned.

For background information about these operational considerations, see [Understanding How Oracle TMA TCP Gateway Works](#)

## 1.4 Oracle TMA TCP Functionality

The following functionality is available in this version of TMA TCP.

- [Domains-based Gateway Connectivity](#)
- [Security](#)
- [Connection Multiplexing](#)
- [Domain Name Server Support](#)

### 1.4.1 Domains-based Gateway Connectivity

The TMA TCP product has a domains-based architecture supporting bidirectional communications, request/response support, and support for MVS Open Transaction Manager Access (OTMA) interfaces.

### 1.4.2 Security

The TMA TCP Gateway product grants access to Oracle Tuxedo services based on a user name that the remote gateway supplies.

The TMA TCP for CICS product can initiate transactions or link to programs. Oracle Tuxedo security provides the user ID value to the TMA TCP product to test for appropriate security prior to initiating the transactions.

The TMA TCP for IMS product has an OTMA interface that supports enhanced security. This interface allows an Oracle Tuxedo requester to pass a user ID through the OTMA server interface for authorization through a third-party security package, such as RACF.

TMA TCP Gateway supports TLS encryption when communicating with TMA TCP for CICS or TMA TCP for IMS.

### 1.4.3 Connection Multiplexing

The TMA TCP Gateway allows multiple requests to process simultaneously over a single connection. This feature is known as connection multiplexing. Two connecting gateways determine a multiplex count that is acceptable to both sides at connection time. After establishing the connection, clients can send multiple requests (up to the number in the multiplex count) to the server gateway. Connection multiplexing allows for more efficient use of sockets and other system resources by the TMA TCP gateways.

 **Note:**

Each connection is one-directional, which means clients on opposing platforms cannot use the same connection to communicate with remote servers.

## 1.4.4 Domain Name Server Support

The TMA TCP product supports domain name server (DNS) resolution of IP addresses. This support allows you to change the IP address at the Domain Name Server to implement address changes without reconfiguring the TMA TCP gateway.

## 1.5 GWIDOMAIN Gateway Component

The TMA TCP product consists of a single component, the `GWIDOMAIN` gateway. This gateway is responsible for mediating both incoming and outgoing requests. It also maintains connections with all remote gateways.

## 1.6 How TMA TCP Gateway Affects Oracle Tuxedo Application Programs

The TMA TCP Gateway product preserves the high degree of location transparency that Oracle Tuxedo software provides. In fact, in virtually all cases, programmers do not need to know that particular services are provided by remote systems.

The TMA TCP Gateway product supports the main Oracle Tuxedo communication paradigm: request/reply communications (either synchronous or asynchronous).

All Oracle Tuxedo buffer types can be employed for data exchange. These include:

- X/Open standard XATMI buffer types
  - `X_OCTET`
  - `X_C_TYPE`
  - `X_COMMON`
- Oracle Tuxedo ATMI buffers
  - `CARRAY`
  - `STRING`
  - `FML`
  - `VIEW`

Each of the three X/Open buffer types is equivalent to an Oracle Tuxedo ATMI buffer type. The following information provides these equivalencies.

- `X_OCTET` is equivalent to `CARRAY`
- `X_C_TYPE` is equivalent to `VIEW`
- `X_COMMON` is equivalent to `VIEW`, but represents only the subset of field types that are common to both the C and COBOL languages
- [VIEW Definitions](#)
- [FML Buffer Support](#)

## 1.6.1 VIEW Definitions

In some circumstances, you must convert typed buffers to formats that are acceptable to target systems. The standard Oracle Tuxedo system `VIEW` definition mechanism is employed for this purpose.

`VIEW` definitions make it possible to map input data and output data between different programming environments (such as C and COBOL). They also enable TMA TCP Gateway to convert data representations automatically between different systems.

`VIEW` definitions can be created by programmers or system administrators. See [Configuring Oracle TMA TCP Gateway for Data Mapping](#) for details. For more detailed information about programming considerations, see the [Understanding How Oracle TMA TCP Gateway Works](#).

## 1.6.2 FML Buffer Support

When communicating with systems or regions that do not support FML buffers directly, the TMA TCP Gateway can convert FML buffers to or from user-defined record layouts in a manner transparent to the FML application. Thus, once a `VIEW` definition that describes the remote application's record layout is created, it can be used to convert the record to or from an FML buffer. The `GWICONFIG` (TMA TCP Gateway configuration file) and `DMCONFIG` files contain `VIEW` specifications as part of the service description.

Through this conversion between ATMI buffers and record structures, TMA TCP Gateway supports sending fielded buffers containing FML data between regions. The TMA TCP Gateway software converts the data from FML buffers to user-defined records using the `VIEW` definitions and field descriptions at the originating region.

You can use an alternate data mapping tool to map FML buffers to formats that mainframe applications can use. For more information about how to configure TMA TCP Gateway to work with an alternate data mapping tool, see the [Configuring Oracle TMA TCP Gateway for Data Mapping](#) and [Configuring Oracle TMA TCP Gateway](#).

## 1.7 How TMA TCP Gateway Affects Oracle Tuxedo Administration

The TMA TCP Gateway administration tools and features are thoroughly integrated with Oracle Tuxedo administration tools and features. Here are some specific examples:

- System administrators define TMA TCP Gateway in the Oracle Tuxedo configuration as a regular Tuxedo domain gateway.
- The TMA TCP Gateway domain configuration file (`DMCONFIG`) specifies how local Oracle Tuxedo service names are mapped to remote service names. Also, the `GWICONFIG` file identifies `VIEW` definitions that TMA TCP Gateway uses to convert and translate input and output data.
- At runtime, system administrators use Oracle Tuxedo subcommands to manage TMA TCP Gateway and related processes.

For more detailed information about configuring TMA TCP Gateway, see [Configuring Oracle TMA TCP Gateway](#). For detailed information about commands for

administering TMA TCP Gateway, see the *Oracle Tuxedo Administrator's Guide* and the *Oracle Tuxedo Domain User Guide*.

# 2

## Understanding How Oracle TMA TCP Gateway Works

To understand how Tuxedo Mainframe Adapter for TCP Gateway (hereafter referenced as TMA TCP Gateway) works, you need to understand how it performs the following tasks. These tasks are described in the following topics:

- [Planning Your Configuration](#)
- [Initializing TMA TCP Gateway](#)
- [Processing Local Service Requests](#)
- [Processing Remote Service Requests](#)
- [Processing Shut Down Requests](#)
- [Programming Considerations](#)

### 2.1 Planning Your Configuration

One of the major benefits of using Tuxedo Mainframe Adapter for TCP Gateway to connect dissimilar systems is the degree to which different programming environments can be isolated. Oracle Tuxedo programmers rarely need to know that services are handled by dissimilar systems or by systems in remote regions. Application programs do not need to be developed in any special way.

The key to this high degree of transparency is the TMA TCP Gateway configuration. Through TMA TCP Gateway configuration, environmental differences, such as naming conventions and data formats, are concealed from programmers and programs.

Three kinds of environmental differences are isolated in the TMA TCP Gateway configuration files (`GWICONFIG` and `DMCONFIG`). They are:

- **Service names**  
Different systems have different rules for naming services. Service names can differ in length, allowable characters, and even conventions as to how they are constructed or chosen.
- **Input and output data formats**  
Different systems have different conventions for formatting input and output data (such as structure, character set, and so forth).
- **Error handling**  
Different systems report application errors in different ways.

The technique that hides these differences is called mapping. Generally, when you map things, you associate local values or entities with values or entities that are meaningful to programs on remote systems.

The procedure for mapping service names is self-explanatory; you create a configuration file record in which a local name for a service is paired with a remote name for that service. On

the other hand, procedures for mapping input data, output data, and application errors are more complex. Conceptual information and other background information are required.

For detailed information about updating the TMA TCP Gateway configuration files (`GWICONFIG` and `DMCONFIG`), see the [Configuring Oracle TMA TCP Gateway](#)

 **Note:**

All TMA TCP Gateway configuration parameters are described in the [Configuring Oracle TMA TCP Gateway](#). This document focuses on complex parameters that require a separate introduction. The task of configuring data mappings could be considered a programming activity because it requires knowledge of the Oracle Tuxedo programming environment. However, because configuration parameters affect many application programs, configuration is usually an administrator's responsibility.

## 2.2 Initializing TMA TCP Gateway

When you boot Oracle Tuxedo software using the `tmboot` command, TMA TCP Gateway initializes in the following manner.

1. The TMA TCP Gateway software parses the `GWICONFIG` configuration file and initializes all parameters. If syntax errors are encountered during parsing, TMA TCP Gateway writes a message to the `ULOG` file and initialization fails.
2. After reading the `GWICONFIG` file, TMA TCP Gateway advertises remote services that are named in the file dynamically. These services includes services for all remote gateways.

## 2.3 Processing Local Service Requests

When TMA TCP Gateway receives an Oracle Tuxedo service request from a local client program, it processes the request in the following manner.

- [Step 1: Receiving a Service Request from Oracle Tuxedo Software](#)
- [Step 2: Connecting to a Remote System](#)
- [Step 3: Converting Input Buffer Types](#)
- [Step 4: Translating Input Data](#)
- [Step 5: Transmitting the Service Request](#)
- [Step 6: Receiving a Reply](#)
- [Step 7: Translating the Reply](#)
- [Step 8: Converting Output Data](#)
- [Step 9: Sending the Reply to the Caller](#)

## 2.3.1 Step 1: Receiving a Service Request from Oracle Tuxedo Software

When a client program sends a request for a remote service that is accessible through TMA TCP Gateway, Oracle Tuxedo forwards the request to the gateway pending the requested service.

## 2.3.2 Step 2: Connecting to a Remote System

The TMA TCP Gateway will determine which remote system will process each request. Data-dependent routing rules may be used to determine the desired remote system.

If no connection to the target remote system exists or an existing connection has been broken, the TMA TCP Gateway opens a new connection at this time.

If the remote system returns a connection failure indication, the Oracle Tuxedo service request fails and an error is returned to the caller. The actual error value returned depends on the timing of the connection failure. Information about failures is written to the `ULOG` file.

## 2.3.3 Step 3: Converting Input Buffer Types

In some circumstances, typed buffers associated with service requests must be converted before service requests can be sent to remote systems. Type conversion involves changing the layout of a buffer to a format that is acceptable to a remote service.

For example, if a local client program places user input in an FML buffer that a remote service cannot process, the buffer must be converted into the structure the remote service expects.

In situations where input type conversion is required, programmers or administrators must perform the following tasks:

- Determine the format of the input data the remote service expects.
- If necessary, create a `VIEW` definition that describes the format of the input data. `VIEW` definitions are descriptions of data structures that are used for input and output in the Oracle Tuxedo environment.
- Specify this information in the TMA TCP Gateway configuration files (`GWICONFIG` and `DMCONFIG`).

Once these tasks have been completed, TMA TCP Gateway performs all necessary type conversions automatically.

For information about creating `VIEW` definitions to facilitate type conversion, see [Configuring Oracle TMA TCP Gateway for Data Mapping](#). For information about the TMA TCP Gateway configuration file, see [Configuring Oracle TMA TCP Gateway](#).

## 2.3.4 Step 4: Translating Input Data

The TMA TCP Gateway software automatically translates data as required. Translation refers to a change in how intrinsic data types are represented with respect to word length, byte ordering, and character encoding.

To facilitate data translation, administrators must specify certain parameters in the `GWICONFIG` configuration file. For detailed information about how TMA TCP Gateway translates data, see [Configuring Oracle TMA TCP Gateway for Data Mapping](#)



## 2.3.5 Step 5: Transmitting the Service Request

The TMA TCP Gateway product constructs a request message. This message includes the following items and is sent to the remote system:

- The remote service name
- The input data record that TMA TCP Gateway has converted and translated, as required
- An indication of whether the remote service should return a reply to the caller

## 2.3.6 Step 6: Receiving a Reply

After sending a request message, TMA TCP Gateway performs a receive operation. If the TMA TCP Gateway receive timeout expires before a message arrives from the remote system, a `TPETIME` error is returned to the caller.

## 2.3.7 Step 7: Translating the Reply

After TMA TCP Gateway receives a reply, data representations are translated as needed, in the reverse of the input translation. For details, see the [Step 4: Translating Input Data](#)

## 2.3.8 Step 8: Converting Output Data

If the format of the reply is not suitable for the local client program, TMA TCP Gateway converts the reply into an appropriate buffer format.

In situations where output conversion is required, programmers or administrators must do the following:

- Determine the type and the format of the output buffer the local client program expects
- If necessary, create a `VIEW` definition that describes the format of the output buffer
- Specify this information in the TMA TCP Gateway configuration files (`GWICONFIG` and `DMCONFIG`)

Once these tasks have been completed, TMA TCP Gateway performs all necessary conversions automatically.

For information about creating `VIEW` definitions to facilitate type conversion, see the [Configuring Oracle TMA TCP Gateway for Data Mapping](#). For information about the TMA TCP Gateway configuration file, see the [Configuring Oracle TMA TCP Gateway](#).

## 2.3.9 Step 9: Sending the Reply to the Caller

The Oracle Tuxedo buffer resulting from output type conversion and output data translation is returned to the caller with a `TPSUCCESS` or `TPFAIL` indication.

## 2.4 Processing Remote Service Requests

The TMA TCP Gateway software processes remote service requests (those which originate on remote systems) in much the same way that it processes local requests. The following list offers a brief summary.

1. The TMA TCP Gateway receives the service request and, if necessary, the input record associated with the request is translated and converted into the specified input buffer format.
2. Acting as a client program, the gateway passes the service request to Oracle Tuxedo software.
3. When the service routine is complete, the output buffer is converted into the specified output record format and/or translated, when required.
4. Finally, the output is sent to the requester on the remote system.

For more detailed information about record and buffer conversion, and data translation, see the [Processing Local Service Requests](#)

## 2.5 Processing Shut Down Requests

When you send a shutdown request to TMA TCP Gateway using the `tmshutdown` command, TMA TCP Gateway performs the following tasks:

1. Completes outstanding requests
2. Drops all open connections
3. Terminates

## 2.6 Programming Considerations

In general, Oracle Tuxedo application programs that send requests through TMA TCP Gateway are developed the same as other Oracle Tuxedo application programs.

The TMA TCP Gateway product supports all request/reply communications functions that are included in the ATMI and XATMI interfaces. In addition, all supported functions can be used in the standard manner documented in the Oracle Tuxedo documentation.

- All XATMI and ATMI buffer types are supported.
- All system errors are reported in the standard manner as documented in the Oracle Tuxedo documentation.
- [Input and Output Issues](#)
- [Limitations on the Use of Certain ATMI Functions](#)
- [Error Handling](#)

### 2.6.1 Input and Output Issues

This subsection describes several input and output issues that programmers need to consider when developing application programs that use TMA TCP Gateway.

- [Preparing Input and Output Data with TMA TCP Gateway](#)

- [Service Request Parameters](#)
- [Output Data Considerations](#)

### 2.6.1.1 Preparing Input and Output Data with TMA TCP Gateway

The [Processing Local Service Requests](#) topic describes many circumstances that require conversion of input and output parameters into formats acceptable to remote systems or regions and the local system.

The TMA TCP Gateway product provides powerful configuration capabilities that make it possible for you to convert or map parameters easily rather than requiring you to program in a different way.

The TMA TCP Gateway configuration files (`GWICONFIG` and `DMCONFIG`) are a centralized mechanism that you can use to define and maintain relationships between the local system and remote systems or regions. In addition to input and output parameter mappings, these relationships include service name mappings (where remote service names are mapped to local service names) and error record mappings.

For more information about the `GWICONFIG` configuration file, see the [Configuring Oracle TMA TCP Gateway](#)

### 2.6.1.2 Service Request Parameters

Oracle Tuxedo application programs can request the following two categories of remote services through TMA TCP Gateway:

- Existing application programs that were originally developed for traditional OLTP environments and have been adapted for use with Oracle Tuxedo.
- Services that were developed specifically for the XATMI or ATMI (Oracle Tuxedo) environments. Included in this category are services that reside in remote Oracle Tuxedo regions.

If a remote service was developed specifically for the Oracle Tuxedo environment, the input it requires is shaped by three factors:

- Application-specific requirements
- Normal ATMI or XATMI requirements for defining and sending input
- Machine-specific requirements for how input is formatted (such as those described in [Processing Local Service Requests](#))

On the other hand, if a remote service is an existing OLTP application program, additional requirements for input are often required. For example, many systems require input that includes terminal data.

Often, by creative use of the TMA TCP Gateway configuration capabilities previously introduced, you can eliminate the need to include control information, such as terminal data, in the Oracle Tuxedo application source code that you develop. For instance, you can include terminal control codes in `VIEW` definitions that are associated with the TMA TCP Gateway configuration.

For information about the normal input requirements of Oracle Tuxedo services, see *Oracle Tuxedo Programmer's Guide*.

### 2.6.1.3 Output Data Considerations

To maintain the location transparency of the Oracle Tuxedo environment, TMA TCP Gateway does not preserve data from Oracle Tuxedo input buffers in the associated output buffers. Hence, the consequences of using the same buffer for input and output must be understood to avoid problems.

In particular, some existing Oracle Tuxedo applications may use FML buffers to accumulate results or to maintain application context across service requests. Developers adding TMA TCP Gateway to such an application must do one of the following:

- Maintain a copy of the necessary data in the client program (or service routine) that makes requests.
- Ensure that the remote service returns input data with the output record.

This requirement is no different from the requirement that existed before the use of TMA TCP Gateway. That is, application programs that accumulate output data in FML buffers must ensure that services return replies in original FML input buffers (with output data added)—not in new or re-initialized buffers.

### 2.6.2 Limitations on the Use of Certain ATMI Functions

The ATMI interface includes several features and functions—related primarily to conversations, transactions and client identities—that application programs cannot propagate to other application programs through TMA TCP Gateway.

In this guide, permanent limitations of this sort are referred to as operational considerations. Specific operational considerations are described in the following sections:



#### Note:

In this discussion, a local application program is one that resides within the immediate Oracle Tuxedo region. A remote application program is one that resides outside the immediate Oracle Tuxedo region.

- [Conversational Communication Functions](#)
- [Non-Transactional Communications](#)
- [The `tpsprio\(\)` and `tpgprio\(\)` Functions](#)
- [The `tpbroadcast\(\)` and `tpnotify\(\)` Functions](#)

#### 2.6.2.1 Conversational Communication Functions

Conversational communication functions are subject to the following operational considerations:

- Local client and server programs cannot use the `tpconnect()` function to establish conversations with remote services.
- Remote client and server programs cannot use the `tpconnect()` function to establish conversations with local services.

- Similarly, the `tpsend()`, `tprecv()`, and `tpdiscon()` functions may not be used for communication through TMA TCP Gateway.

### 2.6.2.2 Non-Transactional Communications

The TMA TCP Gateway product supports only non-transactional communications. Therefore, all communications via TMA TCP Gateway are subject to the following operational considerations:

- Remote services called by local client or server programs are always invoked outside the boundaries of any local transaction.
- Local services called by remote client or server programs are always invoked outside the boundaries of any local transaction.
- Local client or server programs calling remote services should invoke the `tpcall()` function, or the `tpacall()` and `tpgetrply()` functions, outside the boundaries of any local transaction, such as `tx_begin()/tx_commit()` or `tpbegin()/tpcommit()` pair.
- If local client or server programs must call remote services within the boundaries of a local transaction, `TPNOTRAN` must be specified as one of the flags to the `tpcall()` or `tpacall()` function.

### 2.6.2.3 The `tpsprio()` and `tpgprio()` Functions

The `tpsprio()` and `tpgprio()` functions are subject to the following operational considerations:

- Local client and server programs cannot use the `tpsprio()` function to set the priority at which remote services are processed. Instead, a call to the `tpsprio()` function causes the priority of a local TMA TCP Gateway to be set.
- Remote client and server programs cannot use the `tpsprio()` function to set the priority at which local services are processed.
- When local client or server programs use the `tpgprio()` function to determine the priority of a remote service, the priority of a local TMA TCP Gateway is returned.

### 2.6.2.4 The `tpbroadcast()` and `tpnotify()` Functions

The `tpbroadcast()` and `tpnotify()` functions are subject to the following operational considerations:

- Local client programs cannot use the `tpbroadcast()` function to send unsolicited messages to remote client programs (and the reverse).
- Local services cannot use the `tpbroadcast()` or `tpnotify()` functions to send messages to remote client programs (and the reverse).

## 2.6.3 Error Handling

Three kinds of errors can be encountered by local application programs when they send requests through TMA TCP Gateways. The following topics explain how TMA TCP Gateway handles these different kinds of errors.

- [Gateway Errors](#)

- [Remote System Failures](#)
- [Application Errors](#)

### 2.6.3.1 Gateway Errors

When local or remote gateway errors occur, they are logged in the Oracle Tuxedo `ULOG` file and associated service requests fail. Also, appropriate error codes are returned to callers.

### 2.6.3.2 Remote System Failures

When remote systems encounter problems, service requests may fail or time out. The exact outcome depends on whether the remote system provides a means for TMA TCP Gateway to detect failure.

If the remote target system does not make it possible for TMA TCP Gateway to detect particular types of failure, the TMA TCP Gateway blocking timeout parameter can be tuned to provide timely detection of the problem.

For more information about the blocking timeout parameter, see the [Configuring Oracle TMA TCP Gateway](#)

### 2.6.3.3 Application Errors

Application errors are similar to remote system failures. Remote systems may or may not use error indicators to pass information back to the local TMA TCP Gateway resulting in the generation of error messages. If no such error indicators exist, service routines typically use their own mechanisms to report failures to callers.

When application errors occur, some service routines may not return their usual output records at all. Instead, they may return some other data indicating that there has been an error, such as a string that contains a failure message.

When TMA TCP Gateway receives a service failure message from a remote system, it:

- Converts the output buffer as required based on instructions it finds in the `GWICONFIG` file
- Writes an error record in the `ULOG` file if the configuration directs it to do so
- Returns the appropriate type of Oracle Tuxedo buffer to the caller

#### Note:

When Oracle Tuxedo applications detect service failures, they should not assume that returned buffers are the expected type. Oracle Tuxedo application programs may ignore return buffers when failures occur. If you need to check a buffer type, use the Oracle Tuxedo `tpypes()` function. When the type is known, the buffer can be handled accordingly (for example, by displaying a window containing an error string).

# 3

## Configuring Oracle TMA TCP Gateway for Data Mapping

The key to the high degree of transparency between systems is the Tuxedo Mainframe Adapter for TCP Gateway (hereafter referenced as TMA TCP Gateway) configuration. Environmental differences, such as data formats, are concealed from programmers and programs through this mechanism.

This document also provides information about creating `VIEW` definitions. `VIEW` definitions are descriptions of data structures that are used for input and output in the Oracle Tuxedo environment. The TMA TCP Gateway product uses `VIEW` definitions to determine how to convert input data and output data into formats that are acceptable to target systems.

For detailed information about updating the TMA TCP Gateway configuration files (`GWICONFIG` and `DMCONFIG`), see the [Configuring Oracle TMA TCP Gateway](#)



### Note:

The task of configuring data mappings could be considered a programming activity because it requires knowledge of the Oracle Tuxedo programming environment. However, because configuration parameters affect many application programs, configuration is usually an administrator's responsibility.

This chapter provides information about the following topics:

- [Converting Input and Output Data](#)
- [Managing Parameters for Buffer and Record Conversion](#)
- [Mapping Buffers to Records](#)
- [Mapping Records to Buffers](#)
- [Encoding COBOL Data Types](#)
- [Using Code Page Translation Tables](#)
- [Using Multibyte Character Set \(MBCS\) Translations](#)

### 3.1 Converting Input and Output Data

This section introduces procedures that TMA TCP Gateway follows to process and convert input and output data.

- [Buffers and Records](#)
- [Buffers Received from Local Programs](#)
- [Records Received from Remote Programs](#)

## 3.1.1 Buffers and Records

In this guide, the following terms are used to describe input and output data.

### **Buffer**

Input or output data as it exists inside the local Oracle Tuxedo region. This definition includes all the buffer types that Oracle Tuxedo software supports—both Oracle Tuxedo ATMI buffer types and X/Open XATMI buffer types.

### **Record**

Input or output data as it exists outside the local Oracle Tuxedo region—on different kinds of systems.

These terms make it easier to understand how TMA TCP Gateway handles input and output data.

## 3.1.2 Buffers Received from Local Programs

The TMA TCP Gateway processes buffers from local programs in the following manner.

1. When TMA TCP Gateway receives a buffer from a local program, it automatically determines the buffer's type.  
The TMA TCP Gateway product automatically “types” input buffers that local client programs send to remote services.  
The TMA TCP Gateway product automatically “types” output buffers that local services return to remote client programs.
2. After TMA TCP Gateway determines a buffer's type, it consults the configuration file (`GWICONFIG`) to determine whether the buffer needs to be converted to a different format.  
Client requests sent to remote services may need to be converted to record formats that are meaningful to those services.  
Server responses returned to remote client programs may need to be converted to record formats that are meaningful to those programs.
3. If the configuration indicates that conversion is required, TMA TCP Gateway transforms the buffer into the record format that is specified in the configuration.

## 3.1.3 Records Received from Remote Programs

The TMA TCP Gateway processes buffers from remote programs in the following manner.

1. When TMA TCP Gateway receives a record from a remote system, it consults the configuration file (`GWICONFIG`) to determine the record's type.
2. Gateway determines a record's type, it consults the domain configuration (`DMCONFIG`) to determine whether the record needs to be converted to a different format.  
Client requests from remote client programs may need to be converted to buffer formats that are acceptable to local service routines.  
Server responses returned from remote services may need to be converted to buffer formats that are acceptable to local client programs.



3. If the configuration indicates that conversion is required, TMA TCP Gateway transforms the record into the buffer format that is specified in the configuration.

## 3.2 Managing Parameters for Buffer and Record Conversion

The TMA TCP Gateway product provides four configuration parameters you can use to map buffers and records. For more information about buffers and records, see the [Buffers and Records](#)

Specify the following buffer configuration parameters in the domain configuration file (DMCONFIG).

### **INBUFTYPE**

Identifies the type, and in some cases the format, of a buffer received from a Tuxedo client or server

### **OUTBUFTYPE**

Identifies the type, and in some cases the format, of a buffer to be sent to a Tuxedo client or server

Specify the following record configuration parameters in the gateway configuration file (GWICONFIG).

### **INRECTYPE**

Identifies the type, and in some cases the format, of a buffer to be sent to a remote gateway

### **OUTRECTYPE**

Identifies the type, and in some cases the format, of a buffer received from a remote gateway

Each of these four parameters has two possible meanings or interpretations—one for service requests that originate locally, and one for service requests that originate on remote systems.

The following topics, [Parameters for Locally Originated Calls](#) and [Parameters for Remotely Originated Calls](#), explore these different meanings in detail.

- [Parameters for Locally Originated Calls](#)
- [Parameters for Remotely Originated Calls](#)


### 3.2.1 Parameters for Locally Originated Calls

This section takes a closer look at how TMA TCP Gateway handles service calls that originate locally, within the immediate Oracle Tuxedo region. Also, it explains how the `INBUFTYPE`, `INRECTYPE`, `OUTRECTYPE`, and `OUTBUFTYPE` parameters can be used to manage the conversion of buffers and records that flow between local client programs and remote services.

Oracle Tuxedo client program issues a service call that a local TMA TCP Gateway routes to a remote server through TMA TCP Gateway.

In this situation, the four configuration parameters that are shown in the figure have the following meanings:

**Figure 3-1 How Parameters Are Mapped During Locally Originated Calls**



- The `INBUFTYPE` parameter describes the Oracle Tuxedo input buffer that the local client program provides to the TMA TCP Gateway through Oracle Tuxedo software.
- The `INRECTYPE` parameter describes the input record that is sent to the service on the remote system.
- The `OUTRECTYPE` parameter describes the output record that is received from the service on the remote system.
- The `OUTBUFTYPE` parameter describes the Oracle Tuxedo output buffer that is returned to the local client program.
- [Guidelines for Mapping Input Buffers to Input Records](#)
- [Guidelines for Mapping Output Records to Output Buffers](#)

### 3.2.1.1 Guidelines for Mapping Input Buffers to Input Records

The following sections provide detailed information explaining how to use the `INBUFTYPE` and `INRECTYPE` parameters for service calls that originate locally (where local client programs call remote services).

#### `INBUFTYPE`

The `INBUFTYPE` parameter is used to specify the request buffer type that is provided to a local TMA TCP Gateway when a local client program issues a service request.

Because the gateway determines the type of client request buffers automatically at runtime, this parameter is described here for conceptual completeness only.

#### `INRECTYPE`

The `INRECTYPE` parameter is used to specify the type, and in some cases the format, of the request record that a particular remote service requires. The TMA TCP Gateway uses this information to convert Oracle Tuxedo request buffers into records that remote services can process.

You must specify the `INRECTYPE` parameter when one of the circumstances described in the following table is true.

Circumstance	Explanation
The remote service uses an input record that is structured differently than the client program's request buffer.	In this circumstance, the remote service uses a record that is structured differently than the client program's VIEW, X_C_TYPE, or X_COMMON buffer. For example, the remote service may expect structure members to be sequenced differently.
The remote service uses a request record that differs from the client program's request buffer in both type and structure.	In this case, the client program uses an Oracle Tuxedo FML buffer and the remote service expects a corresponding record with an appropriate structure.

The `INRECTYPE` parameter may be omitted if the request buffer is identical, in type and structure, to the request record the remote service expects.

### 3.2.1.2 Guidelines for Mapping Output Records to Output Buffers

The following sections provide detailed information explaining how to use the `OUTRECTYPE` and `OUTBUFTYPE` parameters for service calls that originate locally (where local client programs call remote services and receive output from those services).

#### OUTBUFTYPE

The `OUTBUFTYPE` parameter is used to specify the type, and in some cases the structure, of the reply buffer that a local client program expects. The TMA TCP Gateway uses this information to map reply records from remote services to the appropriate kinds of reply buffers.

#### OUTRECTYPE

The `OUTRECTYPE` parameter is used to specify the type, and in some cases the format, of the reply record that a particular remote service returns to the local TMA TCP Gateway.

You must specify the `OUTRECTYPE` parameter when one of the circumstances described in the following table is true.

Circumstance	Explanation
The remote service returns a reply record that is structured differently than the reply buffer the local client program expects.	In this circumstance, the remote service returns a record that is structured differently than the client program's VIEW, X_C_TYPE, or X_COMMON buffer. For example, the structure members of the output record may be sequenced differently than the structure members of the output buffer.
The remote service returns a reply record that differs in both type and structure from the reply buffer the client program expects.	In this case, the remote service returns a particular record and the local client program expects a corresponding Oracle Tuxedo FML buffer.

The `OUTRECTYPE` parameter may be omitted if the remote service returns a reply record that is identical, in type and structure, to the reply buffer the local client program expects.

## 3.2.2 Parameters for Remotely Originated Calls


This section takes a closer look at how TMA TCP Gateway handles service calls that originate on remote computers, outside the local Oracle Tuxedo region. Also, it explains how

the `INRECTYPE`, `INBUFTYPE`, `OUTBUFTYPE`, and `OUTRECTYPE` parameters can be used to manage the conversion of buffers and records that flow between remote client programs and local services.

A remote client program issues a service request that a remote TMA TCP gateway routes to the local TMA TCP Gateway. The gateway receives the request from the network and passes the request to a local Oracle Tuxedo server.

In the following figure, a remote client program issues a service request that a remote TMA TCP gateway routes to the local TMA TCP Gateway. The gateway receives the request from the network and passes the request to a local Oracle Tuxedo server.

**Figure 3-2 How Parameters Are Mapped During Remotely Originated Calls**



- The `OUTRECTYPE` parameter describes the output record that the remote client sends to the TMA TCP Gateway.
- The `OUTBUFTYPE` parameter describes the Oracle Tuxedo output buffer that is provided to the local server.
- The `INBUFTYPE` parameter describes the Oracle Tuxedo input buffer that the local server returns to the TMA TCP Gateway.
- The `INRECTYPE` parameter describes the input record that the local TMA TCP Gateway returns to the remote client program.
- [Guidelines for Mapping Input Records to Input Buffers](#)
- [Guidelines for Mapping Output Buffers to Output Records](#)

### 3.2.2.1 Guidelines for Mapping Input Records to Input Buffers

The following sections provide detailed information explaining how to use the `INRECTYPE` and `INBUFTYPE` parameters for service calls that originate on remote systems (where remote client programs call local services).

#### `INBUFTYPE`

The `INBUFTYPE` parameter is used to specify the type, and in some cases the structure, of the reply buffer that the TMA TCP Gateway expects from a local server. The TMA

TCP Gateway uses this information to map reply buffers from local server programs to the appropriate kind of reply records.

Because the gateway determines the type of incoming buffers automatically at runtime, this parameter is described here for conceptual completeness only.

**INRECTYPE**

The **INRECTYPE** parameter is used to specify the type, and in some cases the format, of the reply record that the local TMA TCP Gateway sends to the remote client.

You must specify the **INRECTYPE** parameter when one of the circumstances described in the following table is true.

Circumstance	Explanation
The remote client program requires a reply record that is structured differently than the reply buffer the local service provides.	In this circumstance, the remote client program sends a record that is structured differently than the local service's <code>VIEW</code> , <code>X_C_TYPE</code> , or <code>X_COMMON</code> buffer. For example, the structure members of the input record may be sequenced differently than the structure members of the input buffer.
The remote client program requires a reply record that differs in both type and structure from the reply buffer the local service provides.	In this case, the remote client program requires a particular record and the local service provides a corresponding Oracle Tuxedo FML buffer.

You can omit the **INRECTYPE** parameter if the local server program sends a reply buffer that is identical in type and structure to the reply record the remote client expects.

### 3.2.2.2 Guidelines for Mapping Output Buffers to Output Records

The following sections provide detailed information explaining how to use the **OUTBUFTYPE** and **OUTRECTYPE** parameters for service calls that originate on remote computers (where remote client programs call local services and receive output from those services).

**OUTBUFTYPE**

The **OUTBUFTYPE** parameter specifies the request buffer type that the local TMA TCP Gateway provides to the local server.

**OUTRECTYPE**

The **OUTRECTYPE** parameter is used to specify the type, and in some cases the format, of the request record a particular remote client program sends to the TMA TCP Gateway. The TMA TCP Gateway uses this information to convert request records from remote clients into buffers that local server programs can process.

You must specify the **OUTRECTYPE** parameter when one of the circumstances described in the following table is true.

Circumstance	Explanation
The remote client program provides a request record that is structured differently than the local service's request buffer.	In this circumstance, the remote client program provides a record that is structured differently than the local service's <code>VIEW</code> , <code>X_C_TYPE</code> , or <code>X_COMMON</code> buffer. For example, the local server program may expect structure members to be sequenced differently.


Circumstance	Explanation
The remote client program provides an request record that differs from the local service's request buffer in both type and structure.	In this case, the remote client outputs a record and the local client program expects a corresponding Oracle Tuxedo FML buffer.

The `OUTRECTYPE` parameter may be omitted if the local service's request buffer is identical, in type and structure, to the request record the remote client program provides.

### 3.3 Mapping Buffers to Records

The following figure shows all the possibilities for mapping buffers to records. The TMA TCP Gateway is responsible for mapping buffers to records, based on information it finds in the TMA TCP Gateway configuration. This mapping occurs for Tuxedo client requests and Tuxedo server responses.


Figure 3-3 Buffer to Record Mappings



- [Setting the INBUFTYPE and INRECTYPE Parameters](#)

#### 3.3.1 Setting the INBUFTYPE and INRECTYPE Parameters

The following table lists some of the mapping possibilities that are shown in the previous figure and some suggestions for setting the `INBUFTYPE` and `INRECTYPE` parameters.


No	INBUFTYPE and INRECTYPE Parameters
1	<p>Oracle Tuxedo CARRAY input buffers can be copied to CARRAY input records. A CARRAY buffer contains raw data that is not converted or translated. Set the INBUFTYPE parameter to CARRAY, and omit the INRECTYPE parameter.</p> <p>CARRAY input buffers can also be copied to STRING input records. This creates a string that goes through no conversion and no translation. The resultant buffer is the length of the original CARRAY buffer. Since all characters are copied, if the CARRAY buffer contains null characters, it affects the buffer when later handled as a STRING. The INBUFTYPE parameter should be set to CARRAY and the INRECTYPE parameter should be set to STRING.</p>
2	<p>Oracle Tuxedo STRING input buffers can be mapped to CARRAY input records. No data conversion or translation is performed. The STRING buffer is copied through the leftmost null character only. Set the INBUFTYPE parameter to STRING and the INRECTYPE parameter to CARRAY.</p>
3	<p>Oracle Tuxedo STRING input buffers can be mapped to STRING input records. The buffer goes through data type translation (such as ASCII to EBCDIC). Set the INBUFTYPE parameter to STRING, and omit the INRECTYPE parameter.</p>
4	<p>Oracle Tuxedo VIEW input buffers can be mapped to identical Oracle Tuxedo VIEW input records. In this situation, the data structure that the remote service expects is identical to the data structure the client program uses. There is no need to create a new VIEW definition. Instead, specify the input record type (VIEW) and the name of the existing VIEW definition (the one the client program currently uses) for both the INBUFTYPE parameter, and omit the INRECTYPE parameter.</p>
5	<p>Oracle Tuxedo VIEW input buffers can be mapped to VIEW input records—in any combination. However, in this situation, the data structure that the remote service expects (designated as VIEW 'B' mapping possibilities in the <a href="#">Mapping Buffers to Records</a> ) differs from the data structure the client program uses (designated as VIEW 'A' in <a href="#">Mapping Buffers to Records</a>). Consequently, you must</p> <ol style="list-style-type: none"> <li>1. Create a VIEW definition for the data structure that the remote service expects.</li> <li>2. Specify the desired record type and the name of this VIEW definition with the INRECTYPE parameter.</li> <li>3. Set the INBUFTYPE parameter to <code>VIEW: original-viewname</code></li> </ol>
6	<p>Before an Oracle Tuxedo FML input buffer can be sent to a remote service that does not support FML, it must be mapped to one of the following input record types: VIEW, X_C_TYPE, or X_COMMON. Also, you must create a VIEW definition for the input data structure that the remote service expects. Set INBUFTYPE to FML and INRECTYPE to <code>VIEW:viewname</code>.</p> <div style="border: 1px solid #0070C0; padding: 10px; margin-top: 20px;"> <p> <b>Note:</b></p> <p>In the DMCONFIG file, if FML or FML32 are specified as INBUFTYPE or OUTBUFTYPE, the type must be followed by a colon (:). (Example:  <code>INBUFTYPE="FML32: "</code>)</p> </div>



## 3.4 Mapping Records to Buffers

The following figure shows all the possibilities for mapping records to buffers. The TMA TCP Gateway is responsible for mapping records to buffers, based on information it finds in the TMA TCP Gateway configuration. This mapping occurs for remote client requests and remote server responses.

Figure 3-4 Record to Buffer Mappings




- [Setting the OUTRECTYPE and OUTBUFTYPE Parameters](#)
- [Creating VIEW Definitions to Facilitate Buffer Conversion](#)
- [Translating Data](#)

### 3.4.1 Setting the OUTRECTYPE and OUTBUFTYPE Parameters

The following table lists some of the mapping possibilities that are shown in the previous figure and some suggestions for setting the `OUTRECTYPE` and `OUTBUFTYPE` parameters (for service calls that originate locally).



No	OUTRECTYPE and OUTBUFTYPE Parameters
1	<p>Oracle Tuxedo CARRY output records can be copied to CARRY output buffers. A CARRY buffer contains raw data that is not converted or translated. Set the OUTBUFTYPE parameter to CARRY. The OUTRECTYPE parameters need not be set.</p> <p>Oracle Tuxedo CARRY output records can also be copied to STRING output buffers. This creates a string that goes through no conversion and no translation. The resultant buffer is the length of the original CARRY buffer. Since all characters are copied, if the CARRY buffer contains null characters, it affects the buffer when later handled as a STRING. The OUTRECTYPE should be set to CARRY and OUTBUFTYPE should be set to STRING.</p>
2	<p>Oracle Tuxedo STRING output records can be mapped to CARRY output buffers. There is no data conversion or translation performed. The STRING buffer is copied through the leftmost null characters only. Set OUTRECTYPE to STRING and OUTBUFTYPE to CARRY.</p>
3	<p>Oracle Tuxedo STRING output records can be mapped to STRING output buffers. The buffer goes through datatype translation (such as ASCII to EBCDIC). OUTBUFTYPE and OUTRECTYPE parameters are set to STRING.</p>
4	<p>Oracle Tuxedo VIEW output records can be mapped to identical Oracle Tuxedo VIEW output buffers. In this situation, the data structure that the remote service returns is identical to the data structure the local client program expects. There is no need to create a new VIEW definition. Instead, specify the VIEW buffer type and the name of the existing VIEW definition with the OUTBUFTYPE parameter. The OUTRECTYPE parameter can be set to VIEW: <i>viewname</i> , but it is not mandatory.</p>
5	<p>Oracle Tuxedo VIEW output records can be mapped to VIEW output buffers—in any combination. However, in this situation, the data structure that the remote service returns (designated as VIEW 'B' in Figure 3-4) differs from the data structure the client program expects (designated as VIEW 'A' in Figure 3-4). To facilitate the conversion process, perform the following tasks.</p> <ol style="list-style-type: none"> <li>1. Create a VIEW definition for the data structure that the remote service returns.</li> <li>2. If the name given to the VIEW definition is different than the name that the remote service returns (that is, ATMI buffer subtype), specify the output record type and the name of VIEW 'B' with the OUTRECTYPE parameter. (By doing this, you override the value the TMA TCP Gateway requester automatically detects.)</li> <li>3. Specify the output buffer type and the name of an existing view (VIEW 'A' in the figure) specified in the OUTBUFTYPE parameter.</li> </ol>

No	OUTRECTYPE and OUTBUFTYPE Parameters
6	<p>Oracle Tuxedo <code>VIEW</code> output records can be mapped to FML output buffers. To facilitate the conversion process, you must perform the following tasks.</p> <ol style="list-style-type: none"> <li>1. Create a <code>VIEW</code> definition that describes the data structure that the remote service returns.</li> <li>2. If the name given to the <code>VIEW</code> definition is different than the name that the remote service returns (that is, the ATMI buffer subtype), specify the output record type and the name of your <code>VIEW</code> definition with the <code>OUTRECTYPE</code> parameter. (By doing this, you override the value the TMA TCP Gateway requester automatically detects.)</li> <li>3. Set the <code>OUTBUFTYPE</code> parameter to FML.</li> </ol> <div style="border: 1px solid #0070C0; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>In the <code>DMCONFIG</code> file, if FML or FML32 are specified as <code>INBUFTYPE</code> or <code>OUTBUFTYPE</code>, the type must be followed by a colon (:). (Example: <code>INBUFTYPE="FML32:"</code>)</p> </div>

## 3.4.2 Creating `VIEW` Definitions to Facilitate Buffer Conversion

`VIEW` definitions are used to describe input and output records that are sent to and received from remote systems. They describe data elements and indicate how data elements are typed and sequenced. Based on these descriptions, TMA TCP Gateway translates field data types as required to maintain transparency between dissimilar systems.

You should create `VIEW` definitions before you configure TMA TCP Gateway. For complete information about `VIEW` definitions and related topics, see Oracle Tuxedo documentation.

The TMA TCP Gateway buffer and record conversion capabilities are extremely powerful and flexible. The key to maximizing these capabilities is to thoroughly understand the Oracle Tuxedo `VIEW` definition mechanism.

`VIEW` definitions make it possible to specify composite data structures that can be used:

- On different kinds of machines
- With different programming languages
- [Preparing `VIEW` Definitions](#)

### 3.4.2.1 Preparing `VIEW` Definitions

After determining the input and output record layouts for the remote application programs you are working with, you need to prepare `VIEW` definitions and specify these definitions in the configuration files.

 **Note:**

FML fields must be specified for all `VIEW`s that TMA TCP Gateway converts. In other words, any `VIEW` that you specify as an `INRECTYPE`, `OUTRECTYPE`, `INBUFTYPE`, or `OUTBUFTYPE` must be defined with appropriate FML fields (no dashes in the `FNAME` column of the `VIEW` definition). For the FML fields to match, you must compile these `VIEW`s without the `-n` option specified.

1. Create standard Oracle Tuxedo `VIEW` definitions in files.
2. Run the `viewc` or `viewc32` `VIEW` compiler.
3. Set the `VIEWFILES`, `VIEWDIR`, `FLDFTBLS`, and `FLDTBLDIR` environment variables, using a Oracle Tuxedo `ENVFILE` if necessary (so that TMA TCP Gateway servers can locate binary `VIEW` files and field table files at runtime).
4. After these tasks are complete, you can specify `VIEW` definitions in the `GWICONFIG` and `DMCONFIG` files (by associating names of `VIEW` definitions with the `INRECTYPE`, `OUTRECTYPE`, `INBUFTYPE`, and `OUTBUFTYPE` parameters, as required).

For detailed information about configuring TMA TCP Gateway, see the [Configuring Oracle TMA TCP Gateway](#)

### 3.4.3 Translating Data

When a local client program sends data to (or receives data from) a service routine on a different kind of computer, TMA TCP Gateway automatically translates data as required. Translation involves changing the representation of intrinsic data types by changing attributes such as word length and byte order.

The TMA TCP Gateway automatically translates input and output data as required, following rules that are described in the following section. Read the information carefully before you create `VIEW` definitions (to facilitate buffer conversion) and configure TMA TCP Gateway.

Basic rules for how TMA TCP Gateway translates data are described in the following subsection. For detailed information about how TMA TCP Gateway handles string and numeric data, refer to the [NULL Characters in String Length Calculations \(C Programs\)](#).

- [Data Translation Rules](#)
- [NULL Characters in String Length Calculations \(C Programs\)](#)
- [NULL Characters in String Length Calculations \(COBOL Programs\)](#)
- [Converting Numeric Data](#)

#### 3.4.3.1 Data Translation Rules

The following information outlines the data translation rules that TMA TCP Gateway follows:

- `CARRAY` fields are passed untranslated as sequences of bytes.
- `STRING` and `CHAR` fields undergo SBCS (ASCII-to-EBCDIC) translation, if needed.
- `SHORT` and `LONG` fields are translated to `S9(4) COMP` and `S9(9) COMP`, respectively.
- `FLOAT` and `DOUBLE` fields translate to `COMP-1` and `COMP-2`, respectively.

- XML fields undergo SBCS (ASCII-to-EBCDIC) translation, if needed.

**WARNING:** `dec_t` cannot be used with `VIEW` translations.



**Note:**

Oracle Tuxedo provides a field type named `dec_t` that supports decimal values within `VIEWS`. The TMA TCP Gateway translates these fields into machine independent representations of packed decimals. For example, `dec_t(m,n)` becomes

The following table summarizes the relationships.

Remote Data Type	Description	View Field Type/ Length
PIC X(n)	Alphanumeric characters	string / n
PIC X	Single alphanumeric character	char
PIC X(n)	Raw bytes	carray / n
PIC 9	Single numeric byte	carray / 1
PIC S9(4) COMP	16-bit integer	short
PIC S9(9) COMP	32-bit integer	long
COMP-1	Single-precision floating point	float
COMP-2	Double-precision floating point	double
PIC S9((m+(n+1))/2)V9(n) COMP-3	Packed decimal	dec_t / m,n

### 3.4.3.2 NULL Characters in String Length Calculations (C Programs)

When you create `VIEW` definitions for input and output buffers that are used by C language applications, you must specify extra characters for terminating NULL characters that are used in string fields.

For example, when a local application program expects a 10-byte string in an output buffer, you would specify 11 for that field—10 for the string plus 1 for the terminating NULL character.

### 3.4.3.3 NULL Characters in String Length Calculations (COBOL Programs)

When you create `VIEW` definitions for input and output buffers that are used by COBOL language applications, do not specify extra characters for terminating NULL characters that are used in string fields.

For example, when a remote COBOL application program expects 10 characters in an input record, you would specify 10 for that field, not 10 plus 1 (for the terminating NULL character).

 **Note:**

Although TMA TCP Gateway does not require strings to be NULL-terminated, it respects NULL termination. Therefore, when TMA TCP Gateway detects a NULL (zero) character within a string, it does not process any subsequent characters. To pass full 8-bit data that contains embedded NULL values, use a `CARRAY` type field or buffer.

The TMA TCP Gateway product provides standard character translation from ASCII-to-EBCDIC and EBCDIC-to-ASCII. TMA TCP Gateway automatically performs this translation on the `STRING` data type.

### 3.4.3.4 Converting Numeric Data

Numeric data can easily be converted into different data types, provided that you have enough range in the intermediate and destination types to handle the maximum value you need to represent.

For example, you can convert numeric values into strings (and the reverse). For example, while FML buffers do not directly support the `dec_t` type, you can place decimal values in `STRING` fields and map these to `dec_t` fields within `VIEW` definitions.

## 3.5 Encoding COBOL Data Types

An additional encoding library, `ConvMVSC`, has been included for Tuxedo clients using COBOL data types. This library, `ConvMVSC`, is similar to the default library, `ConvMVS`, but differs in the following ways:

- For the `STRING` data type, both `ConvMVSC` and `ConvMVS` perform ASCII-to-EBCDIC and EBCDIC-to-ASCII translation.
  - For strings sent to a remote gateway, both libraries perform ASCII-to-EBCDIC conversion, and forward the string to the mainframe.
  - For strings received from a remote gateway, the `ConvMVS` library performs EBCDIC-to-ASCII translation, truncates any trailing space characters and adds a NULL terminator. The `ConvMVSC` library performs the translation, but does not truncate spaces or add the terminator.
- For the `VIEW` data type, the `ConvMVS` and `ConvMVSC` libraries treat all field types except `STRING` the same.
  - For `STRING` fields within a view sent to a remote gateway, `ConvMVS` performs ASCII-to-EBCDIC conversion and appends space to 'pad' the string with space characters to the size of the field. `ConvMVSC` performs the character conversion, but does not perform any 'padding'.
  - For `STRING` fields within a view received from a remote gateway, `ConvMVS` performs EBCDIC-to-ASCII conversion, truncates any trailing space characters, and adds a NULL terminator. The `ConvMVSC` library performs the character conversion, but does not truncate spaces or add the terminator.
- [Using the COBOL Data Encoding Library](#)

## 3.5.1 Using the COBOL Data Encoding Library

There are two methods for enabling the COBOL data encoding library:

- [Encoding for All Services](#)
- [Encoding Messages To and From a Specific Host](#)

### 3.5.1.1 Encoding for All Services

To enable COBOL data encoding for every service in the gateway, set the parameter `DFLTTYPE="MVSC"` in the `GLOBAL` section of the `GWICONFIG` file.

#### Listing 3-1 Encoding for All Services

```
*GLOBAL  
  
DFLTTYPE="MVSC"
```

### 3.5.1.2 Encoding Messages To and From a Specific Host

To enable COBOL data encoding for messages to and from a specific host, set the parameter `TYPE="MVSC"` for that host's `FOREIGN` entry in the `GWICONFIG` file.

#### Listing 3-2 Encoding for Messages To and From a Specific Host


```
*FOREIGN  
  
HOST_NAME  
TYPE="MVSC"
```

## 3.6 Using Code Page Translation Tables

The TMA TCP software includes translation tables which enable conversions of single byte character sets (SBCS) between ASCII and EBCDIC. These tables are based on IBM-defined code sets and include the default Tuxedo code page, which is the default code page translation table used in previous releases of TMA TCP.

Each translation table consists of two mapping tables, one for outbound conversions (Tuxedo to mainframe) and one for inbound conversions (mainframe to Tuxedo). You do not have to specify the direction of a translation; however, you must determine the national language in which the host application is written. The following figure illustrates code page translation.

Figure 3-5 TMA TCP Code Page Translation



The figure demonstrates how a Tuxedo application using the Latin-1 ASCII code page CP-00819 character set operates with a host application using German EBCDIC code page CP-00273. The TMA TCP translation table 00819x00273 provides both the inbound and outbound conversions.

- [Specifying a Translation Table](#)
- [How the Translation Tables Work](#)
- [Troubleshooting Translation Table Errors](#)
- [Sample DMCONFIG Definition for ASCII to EBCDIC Translations](#)

### 3.6.1 Specifying a Translation Table

To designate the translation table for your applications, make an entry in the `DMCONFIG` file definition for each remote domain. Use the `CODEPAGE` parameter in the `DM_REMOTE_DOMAINS` section of the `DMCONFIG` file. Specify the translation table to use.

To specify a default code page translation for remote hosts to use, specify the translation table filename in the `CODEPAGE` parameter for the local gateway entry in the `DM_LOCAL_DOMAINS` section of the `DMCONFIG` file.

The following table lists the SBCS translation tables provided with the TMA TCP software.

Country	File Name	ASCII Code Set	EBCDIC Code Set
Tuxedo default	TUXEDO	TUXEDO-ASCII	TUXEDO-EBCDIC
United States	00819x00037	CP-00819	CP-00037
Great Britain	00819x00285	CP-00819	CP-00285

Country	File Name	ASCII Code Set	EBCDIC Code Set
France	00819x00297	CP-00819	CP-00297
Portugal	00819x00860	CP-00819	CP-00860
Spain	00819x00284	CP-00819	CP-00284
Belgium	00819x00500	CP-00819	CP-00500
Germany	00819x00273	CP-00819	CP-00273
Finland	00819x00278	CP-00819	CP-00278
Sweden	00819x00278	CP-00819	CP-00278
Latin-1	00819x01047	CP-00819	CP-01047
Latin-2	00912x00870	CP-00912	CP-00870

**Note:**

The Tuxedo default ASCII and EBCDIC code pages differ slightly from CP-00819 and CP-00037.

## 3.6.2 How the Translation Tables Work

At start up, the TMA TCP Gateway loads a translation table for each remote domain.

You can modify any of the tables to suit your application translation needs, except the default Tuxedo tables, which are hard-coded. You must restart the gateway to change any translation table definitions. The TMA TCP translation tables are located in `$TUXDIR/udataobj/codepage`. For table contents, refer to the [Code Page Translation Tables](#)

If no `CODEPAGE` specification is made for a remote domain, the TMA TCP Gateway software uses the Tuxedo default translation tables.

Note: Copies of the default Tuxedo translation tables are included with your product software in `$TUXDIR/udataobj/codepage`. These copies are provided for you to apply modifications if necessary for your applications. These copies are not the actual default tables used by the gateway. You cannot modify the default Tuxedo tables because they are hard-coded.

## 3.6.3 Troubleshooting Translation Table Errors

The following information assists you in resolving errors associated with translation tables that cause the gateway to fail. The gateway issues the following message when encountering an error associated with the specified translation table.

```
1072:ERROR Cannot read CODEPAGE <filename> for <LOCAL | REMOTE> DOMAIN
<domainname>
```

For a description of error messages, refer to the [Error and Information Messages](#). The following causes may be responsible for the gateway issuing the previous error.

- The gateway cannot find the translation table file.



Verify that you specified the correct codepage name in the `CODEPAGE` parameter in the `DM_REMOTE_DOMAIN` section of the `DMCONFIG` file and that the file resides in `$TUXDIR/udataobj/codepage`.

- The software cannot read the translation table file.  
Verify that the file name specified for the `CODEPAGE` parameter is valid. Also, verify that the specified file is not corrupt.
- The software cannot read the translation table file because of access permissions.  
Verify that the specified translation table file in the `$TUXDIR/udataobj/codepage` directory has read permissions.

### 3.6.4 Sample DMCONFIG Definition for ASCII to EBCDIC Translations

The following listing shows entries defining one local domain (`CIXA`) and two remote domains (`CISA` and `IMSA`). In the following example, it is assumed that the local domain uses ASCII code page `CP-00819` and the two remote domains use the German and French EBCDIC code pages `CP-00273` and `CP-00297`, respectively.

#### Listing 3-3 Code Page Definition Example

```
# DMCONFIG
*DM_LOCAL_DOMAINS
CIXA
TYPE=IDOMAIN
*DM_REMOTE_DOMAINS
CISA
TYPE=IDOMAIN
CODEPAGE=00819X00273
IMSA
TYPE=IDOMAIN
CODEPAGE="00819X00297"
```

## 3.7 Using Multibyte Character Set (MBCS) Translations

Besides SBCS character set translation, TCP `GWIDOMAIN` supports multibyte character set (MBCS) translation to meet Asian customer's requirement. This translation does not depend on translation tables under directory `$TUXDIR/udataobj/codepage`, instead, it is based on ICU libraries, which contains more than 200 different SBCS and MBCS character sets.

To use this translation, specify the `CODEPAGE` parameter in `DMCONFIG DM_REMOTE_DOMAINS` in the following format:

```
CODEPAGE="ASCII_CHAR_SET:EBCDIC_CHAR_SET"
```

You can specify a default translation for remote hosts to use in this `CODEPAGE` parameter in `DMCONFIG DM_LOCAL_DOMAINS`

`ASCII_CHAR_SET` is for local domain and `EBCDIC_CHAR_SET` is for remote domain. They are separated by a colon.

Both `ASCII_CHAR_SET` and `EBCDIC_CHAR_SET` must be available character sets known by ICU. A utility `uconv` can be used to retrieve relevant information of these character sets.

For example, when you want to translate MBCS to a remote domain, define `CODEPAGE="utf-8:ibm-1388"`. Consequently, for outbound calls, `GWIDOMAIN` translates the

client input from UTF-8 to ibm-1388; on the other hand, the inbound calls are translated from ibm-1388 to UTF-8.

For more information, see [DM\\_LOCAL\\_DOMAINS](#) and [DM\\_REMOTE\\_DOMAINS](#)

- [Sample DMCONFIG Definition for MBCS Translations](#)

### 3.7.1 Sample DMCONFIG Definition for MBCS Translations

The following listing shows entries defining one local domain (CIXA) and two remote domains (CISA and IMSA). In the following example, it is assumed that the local domain uses UTF-8 and the both the two remote domains use Simplified Chinese Mixed EBCDIC ibm-1388.

#### Listing 3-4 Sample DMCONFIG Definition for MBCS Translations

```
# DMCONFIG
*DM_LOCAL_DOMAINS
CIXA
TYPE=IDOMAIN
CODEPAGE="UTF-8:ibm-1388"

*DM_REMOTE_DOMAINS
CISA
TYPE=IDOMAIN
CODEPAGE="UTF-8:ibm-1388"
IMSA
TYPE=IDOMAIN
CODEPAGE="UTF-8:ibm-1388"
```

# 4

## Setting Up Security for Oracle TMA TCP Gateway

The Tuxedo Mainframe Adapter for TCP Gateway (hereafter referenced as TMA TCP Gateway) component supports security features that allows a requester from Tuxedo to pass a user ID requirement through the OTMA or CICS server interfaces for verification through system security, such as RACF.


This chapter explains the following security topics:

- [Security Checking from Tuxedo to Mainframe](#)
- [Security Checking from Mainframe to Tuxedo](#)
- [Setting Up Security](#)
- [Sample Security Files](#)
- [Data Area Security](#)
- [Using TLS Encryption](#)

### 4.1 Security Checking from Tuxedo to Mainframe

The following figure illustrates the process flow for security verifications from TMA TCP Gateway to a mainframe.

**Figure 4-1 Security Checking for Tuxedo to Mainframe Transactions**



1. When the client program performs a `tpinit()`, the user's Tuxedo identity is validated against the `tpusr` file.
2. When the client program issues a `tpcall()` or `tpacall()`, Tuxedo verifies (against the `tpacl` file) that the user is authorized to invoke the gateway service.
3. When the gateway establishes the initial connection, connection security information (specified as `RMTNAME` and `PASSWORD` in the `GWICONFIG` file) is passed from the TMA TCP Gateway to the remote gateway. If the `RMTNAME` and `PASSWORD` values match the values configured on the remote gateway, the connection is established.

With each request, the TMA TCP Gateway passes the user's Tuxedo identity to the remote gateway.

 **Note:**


To pass authority checking, the user's Tuxedo identity must match the mainframe user ID exactly.

4. The remote mainframe gateway initiates a proxy to act on behalf of the specified user ID.
5. The proxy calls the specified service using system security to check authorization.

## 4.2 Security Checking from Mainframe to Tuxedo

The following figure illustrates the process flow for security verifications from a mainframe to TMA TCP Gateway.

**Figure 4-2 Security Checking for Mainframe to Tuxedo Transactions**



1. The user ID, established at mainframe log in, is checked by system security to verify that the user has permission to start a client transaction.
2. The user ID is checked by system security to verify that the user has permission to send a request to the gateway.
3. With each request, the gateway passes the user ID to the Tuxedo gateway.

 **Note:**

To pass authority checking, the user's Tuxedo identity must match the mainframe user ID exactly.

4. The TMA TCP Gateway maps the mainframe user ID to a Tuxedo user ID and issues the service request on behalf of that user.
5. The Tuxedo server performs access checks (based on the `tpacl` file) to verify that the user has access to the requested service.

## 4.3 Setting Up Security

The TMA TCP Gateway product supports two methods for providing security:

- [Tuxedo Security Plug-in](#)
- [Built-in Tuxedo Security](#)

### 4.3.1 Tuxedo Security Plug-in

The Tuxedo security plug-in enables the customization of the security functions, including the use of alternate implementations. The Tuxedo security plug-in is set up during Tuxedo plug-in configuration. Refer to the Tuxedo documentation for specific information about this feature.

### 4.3.2 Built-in Tuxedo Security

Built-in Tuxedo security is used when custom security plug-ins are not implemented.

To enable the built-in Tuxedo security feature, complete the following tasks.

1. Code `SECURITY` in the Oracle Tuxedo `UBBCONFIG` file. Refer to the *Oracle Tuxedo Administration Guide* for more information.
2. Set up user, group, and `ACL` files. Refer to the *Oracle Tuxedo Administrator's Guide* for more information.

 **Note:**

The user information in these files must match in the Oracle Tuxedo and the mainframe environments or a security violation occurs.

3. Code the security parameter in your TMA TCP Gateway configuration file (`GWICONFIG`). For `GWICONFIG` syntax and parameter definitions, refer to the [Configuring Oracle TMA TCP Gateway](#)

## 4.4 Sample Security Files

Part of the process for setting up security for TMA TCP requires you to have user, group, and `ACL` files. The following sections include these sample files.

- [User Files](#)
- [Group File](#)
- [ACL File](#)

### 4.4.1 User Files

The following sample is a user file that includes user names, encrypted passwords, a user ID number, group number, and a client name.

**Listing 4-1 Sample User (tpusr) File**

```
#illen:w2ZMOKeJmiU0M:1:0:TPCLTNM,someguy::  
#illen:0YzvQeqzcNz56:1:0:TPCLTNM,*::  
#eke:x3vG37eOqh0XE:2:0:TPCLTNM,*::  
#illen:0YzvQeqzcNz56:1:1:TPCLTNM,*::  
#illen:0YzvQeqzcNz56:1:2:TPCLTNM,*::
```

```
john:x3vG37eOqh0XE:2:1:TPCLTNM,*::  
jim:0YzvQeqzcNz56:1:1:TPCLTNM,*::  
richard:IxqosKHu5Q3BA:3:1:TPCLTNM,*::  
JDOE:zBMWVUBNNBVgo:4:0:TPCLTNM,*::  
smith:ULfRJzAeyGAD2:5:0:TPCLTNM,*::  
#
```

Lines that begin with the pound sign (#) are users that have been changed or deleted by `tpusrmod` or `tpusrdel`.

## 4.4.2 Group File

The following sample is a group file that specifies the names and indexes of groups.



### Note:

The `tpgrp` file is only necessary when specifying `ACL` or `MANDATORY_ACL` modes for security. If you specify `USER_AUTH` for security, you can assign users to groups, but they do not correlate to the groups used for security by the remote system.

### Listing 4-2 Sample Group (`tpgrp`) File

```
good::1:  
bad::2:
```

## 4.4.3 ACL File

The `tpacl` file correlates a group and the services to which that group has access. In the `tpacl` file, the first field specifies what is protected, the second field specifies the type of object being protected (specified in the first field), and the third field specifies the group that has access to the object.

In the following example, only users in group 1 (john, jim, richard) can access `TOLOWER`, and only users in group 2 can access `TOUPPER`.



### Note:

The `tpacl` file is only necessary when specifying `ACL` or `MANDATORY_ACL` modes for security.

### Listing 4-3 Sample ACL (`tpacl`) File

```
TOLOWER:SERVICE:1:  
TOUPPER:SERVICE:2:
```

## 4.5 Data Area Security

The TMA TCP Gateway provides data area security which is a specialized security protocol for the following cases:

- User information is propagated across multiple Tuxedo domain boundaries
- A remote or local service requires a user's LTERM information

In these cases, a client's user ID, group name, and LTERM can be specified in the data area of a request. For Tuxedo clients, user information specified in the data area is verified by the remote gateway in the usual manner. For remote clients, remote user information is placed in the data area fields by the local gateway to be used by Tuxedo services. In this case, the remote client does not have to populate these fields, but must allocate space for them in the data area.

- [Enabling Data Area Security](#)
- [Format](#)

### 4.5.1 Enabling Data Area Security

Complete the following tasks to enable data area security.

1. Add fields to the user's data area on the local and remote hosts. These fields are passed to and from the mainframe host. For the field formats, refer to the listing in topic [Format](#)
2. Set WRAP=TPSD in the FOREIGN section corresponding to the remote host in the GWICONFIG file. For syntax and parameter definitions for the FOREIGN section of the GWICONFIG file, refer to [Defining the FOREIGN section of the GWICONFIG File](#)
3. Populate the data area with the user information before sending a request to a remote service.
4. The remote user's information is populated into the data area when a request is received for a local service. If using a VIEW data format, allocate the extra fields before the application data as defined in refer to the listing in topic [Format](#). If using the STRING data format, allocate 24 additional bytes at the beginning of the string to be used for the security fields.

### 4.5.2 Format

The user data area fields in C use the following format:

#### Listing 4-4 Syntax for C User Data Area Fields

```
struct da_security {
char uname[8]; /*user name*/
char group[8]; /*user group*/
char lterm[8]; /*terminal id*/
/*user data is appended here*/
}
```

## 4.6 Using TLS Encryption

TMA TCP Gateway supports TLS encryption when communicating with TMA TCP for CICS or TMA TCP for IMS.

Command line parameter `-p` must be specified for `GWIDOMAIN` to identify the network protocol between TMA TCP Gateway and TMA TCP for CICS or TMA TCP for IMS. The following values are supported in the `-p` command line parameter:

- `SSL`: means the network communication is TLS/SSL enabled.
- `SSL_ONE_WAY`: same as `SSL`, except using one way authenticate, that is, client authenticate is not enabled. This is the default value.
- `TCP`: No encryption is enabled in the network communication. When TLS/SSL is enabled, parameters `SEC_PRINCIPAL_NAME`, `SEC_PRINCIPAL_LOCATION`, and `SEC_PRINCIPAL_PASSVAR` must be specified for TMA TCP Gateway. This may be done in the `*RESOURCES`, `*MACHINES`, `*GROUPS`, or `*SERVERS` sections in `UBBCONFIG`.

Refer to Oracle Tuxedo reference guide [Oracle Tuxedo Reference Guide](#) for the details of these three parameters. Refer to [Creating an Oracle Wallet](#) on how to create an Oracle Wallet to store the keys and certificates.

When TLS/SSL is enabled, TLS v1.2 is used and the minimum asymmetric key length is 2048. Below is a list of supported cipher suites:

- `TLS_RSA_WITH_AES_256_CBC_SHA256`
- `TLS_RSA_WITH_AES_256_GCM_SHA384`
- `TLS_RSA_WITH_AES_128_CBC_SHA256`
- `TLS_RSA_WITH_AES_128_GCM_SHA256`
- `TLS_ECDHE_ECDSA_WITH_AES_256_GCM_SHA384`
- `TLS_ECDHE_ECDSA_WITH_AES_128_GCM_SHA256`
- `TLS_ECDHE_RSA_WITH_AES_128_GCM_SHA256`

For Elliptic Curve Cryptography (ECC) based cipher suites, for example, `TLS_ECDHE_ECDSA_WITH_AES_256_GCM_SHA384` and `TLS_ECDHE_ECDSA_WITH_AES_128_GCM_SHA256`, the corresponding TLS certificates must also be ECC based, and the environment variable `TM_MIN_PUB_KEY_LENGTH` must be set to 0.

To enable TLS hostname validation, set environment variable `TUX_SSL_HOSTNAME_VALIDATE` to `Y`.



# 5

## Configuring Oracle TMA TCP Gateway

The following configuration files must be set up prior to running Oracle Tuxedo Mainframe Adapter for TCP Gateway (hereafter referenced as TMA TCP Gateway):

- `UBBCONFIG`
- `GWICONFIG`
- `DMCONFIG`

This document explains the following tasks for configuring TMA TCP Gateway:

- [Updating the Oracle Tuxedo UBBCONFIG File](#)
- [Specifying Parameters in the GWICONFIG File](#)
- [Defining Domain Configurations in the DMCONFIG File](#)

### 5.1 Updating the Oracle Tuxedo UBBCONFIG File

As with any Tuxedo server, you must establish a server group for TMA TCP Gateway by adding entries for TMA TCP Gateway in the `UBBCONFIG` file for the local region. Specifically, you must add records to:

- The `GROUPS` section
- The `SERVERS` section
- The `SERVICES` section

See the *Oracle Tuxedo Administrator's Guide* for more information about the `UBBCONFIG` file. See [UBBCONFIG\(5\)](#) for more information about the `UBBCONFIG` file. For information about the `UBBCONFIG` file specific to the gateway, refer to the [Updating the GROUPS Section to Establish a Server Group](#) and [Updating the SERVERS Section](#)



#### Note:

Lines beginning with an asterisk (\*) indicate the beginning of a specification section. Each such line contains the name of the section immediately following the \*. The asterisk is required when specifying a section name.

- [Updating the GROUPS Section to Establish a Server Group](#)
- [Updating the SERVERS Section](#)

#### 5.1.1 Updating the GROUPS Section to Establish a Server Group

To establish a server group for TMA TCP Gateway, you must add the following items to the `GROUPS` section of the Oracle Tuxedo `UBBCONFIG` file:

- A name for the TMA TCP Gateway server group using the *groupname* variable
- The logical machine name for the system on which TMA TCP Gateway is installed using the *LMID* parameter

 **Note:**

For Windows NT, the *LMID* must be in uppercase

- A group number for the TMA TCP Gateway server group using the *GROUPNO* parameter
- [Syntax](#)
- [Example](#)

### 5.1.1.1 Syntax

The syntax of the configuration file entry is as follows:

**Listing 5-1 Syntax for GROUPS Section of UBBCONFIG File**

```
groupname LMID=logical_machine_identifier
GROUPNO=group_number
```

The variable definitions follow.

Variable	Description
<i>groupname</i>	Specifies the name you select for the TMA TCP Gateway server group.
<i>logical_machine_identifier</i>	Specifies the logical machine identifier for the system on which TMA TCP Gateway is installed.
<i>group_number</i>	Specifies the number you assign to the TMA TCP Gateway server group.

### 5.1.1.2 Example

Here is an example of a UBBCONFIG entry that establishes a server group.

**Listing 5-2 Establishing a Server Group**

```
NODE2GATE LMID=NODE2
GROUPNO=1
```

## 5.1.2 Updating the SERVERS Section

This section explains how to specify TMA TCP Gateway servers in the Oracle Tuxedo configuration.

The TMA TCP Gateway product provides the gateway you need to list in the *SERVERS* section of the Oracle Tuxedo UBBCONFIG configuration file.

For each TMA TCP Gateway server group, you can specify one gateway. There must also be entries for domain administration (DMADM) and gateway administration (GWADM) servers.

- [Syntax](#)
- [Using the Request Logging Option](#)
- [Other Options for Configuring Servers](#)

### 5.1.2.1 Syntax

The syntax of each configuration file entry is as follows.

**Listing 5-3 Syntax for SERVER Section of UBBCONFIG File**

```
DMADM SVRGRP=groupname SRVID=integer
GWADM SVRGRP=groupname SRVID=integer
GWIDOMAIN SVRGRP=groupname SRVID=integer
CLOPT="-A -- -r -p <protocol>"
```

The following table describes the parts of the syntax.

Part	Description
GWIDOMAIN	Specifies the name of the TMA TCP Gateway.
DMADM	Specifies the name of the Oracle Tuxedo supplied domain administration server.
GWADM	Specifies the name of the Oracle Tuxedo supplied gateway administration server.
<i>groupname</i>	Specifies the name you select for the TMA TCP Gateway server group. This is the group with which the server in question is associated.
<i>integer</i>	Specifies the number you assign to the TMA TCP Gateway server.
CLOPT="-A -- -r -p <protocol>"	-A specifies the command line option string that is used to initialize TMA TCP Gateway when it is invoked. This is the default for Oracle Tuxedo server processes. -r after the double dashes specifies that the server should record, in its standard error file, a log of services performed. This log may be analyzed by the <code>txrpt</code> command. When using this option, ensure that the <code>ULOGDEG</code> variable is not set to "y". -p after the double dashes specified the network protocol used between TMA TCP Gateway and TMA TCP for CICS or TMA TCP for IMS. The supported values are: <ul style="list-style-type: none"> <li>• TCP</li> <li>• SSL</li> <li>• SSL_ONE_WAY.</li> </ul>

For more information about Oracle Tuxedo servers and related configuration parameters, see *Oracle Tuxedo Administrator's Guide* documentation.

### 5.1.2.2 Using the Request Logging Option

Output from the -r command line option should be capable of being processed by `txrpt` command. The `txrpt` command analyzes the standard error output of a Oracle Tuxedo

server and provides a summary of service processing time within the server. The report shows the number of times each service was dispatched and the average amount of time it took for each service to process a request during the specified period. `txrpt` takes its input from the standard input or from a standard error file redirected as input.

**Note:**

The process of gathering statistics creates overhead. Use this option selectively. The `-r` option applies to servers but does not apply to GWIDOMAIN because it is a Gateway.

### 5.1.2.3 Other Options for Configuring Servers

As with other Tuxedo servers, you can use some of Oracle Tuxedo system server boot options with TMA TCP Gateway servers. Boot options must be specified with `CLOPT` parameter (before the `CLOPT` double-dash separator).

**Note:**

Because TMA TCP Gateway dynamically advertises services that are listed in its initialization file, you should not advertise services by using the `-s` option.

For more information about these and other boot options, see `servopts(5)` in *Oracle Tuxedo Administrator's Guide*.

## 5.2 Specifying Parameters in the GWICONFIG File

The `GWICONFIG` file is the mechanism that system administrators use to configure TMA TCP Gateway. The particular file the gateway uses is determined by the environment variable `GWICONFIG`. The configuration file is similar to the Tuxedo Transaction Manager `UBBCONFIG` file, both in structure and in composition. This makes it possible for experienced Oracle Tuxedo administrators to configure TMA TCP Gateway without extensive training.

**Note:**

`GWICONFIG` is a generic filename. You are free to choose other filenames just as with the Tuxedo `UBBCONFIG` file and `DMCONFIG` file. Be sure that the name of the `GWICONFIG` file is specified in the `GWICONFIG` environment variable. Also, the `GWICONFIG` file should be saved to the application directory.

The `GWICONFIG` file is divided into the following required sections:

Section	Description
GLOBAL	Describes certain general characteristics of all TMA TCP Gateways.
NATIVE	Describes all native systems. Use the gateway name, specified in the <code>GWI_GWNAME</code> environment variable, to distinguish different gateways in the same configuration file.
FOREIGN	Describes all foreign systems.
LOCAL_SERVICES	Describes local services that are accessible in the Oracle Tuxedo domain through the TMA TCP Gateway. Each local service is linked to a native system using the <code>NATIVE</code> parameter. For each local service, TMA TCP Gateway uses the TCP port number and IP address of the corresponding native system to establish a TCP listening endpoint.
REMOTE_SERVICES	Describes remote services that are accessible from the Oracle Tuxedo domain. Each remote service describes a TCP service on a foreign system. For each remote service, the <code>FOREIGN</code> parameter defines the name of the foreign system. TMA TCP Gateway uses the TCP port number and IP address of the foreign system to connect to the remote TCP service.

**WARNING:** The `GWICONFIG` file *must* contain the required sections in the order shown in Listing below. Each section requires the asterisk (\*) in the name.

#### Listing 5-4 Sample `GWICONFIG` File

```
*GLOBAL
NWDEVICE="/dev/tcp"
CONNECT_TIME=20
OUTREQ_TIME=20
LATENCY=-2
SECURE=N
MULTIPLY=2
DFLTWRAP="TPS"
DFLTTYPE="MVS"
*NATIVE
LOCAL_IPADDR="//hostname1"
TCP_PORT=9002
IDLE_TIME=20

*FOREIGN
RIGHTY_WRAP="TPS"
TYPE="MVS"
IPADDR="//hostname2"
TCP_PORT=9004
MULTIPLY=2
IDLE_TIME=30
RMTACCT="zeke"
PASSWORD="maple"

MIKE_WRAP="TPS"
TYPE="MVS"
IPADDR="//dalvs3"
TCP_PORT=9001
MULTIPLY=6

*LOCAL_SERVICES
```

```
TUXTOUPPER

ECHO

*REMOTE_SERVICES
TUXTOLOWER
OUTREQ_TIME=20

BEASVR07
OUTRECTYPE="VIEW:weird"

TST1V
```

**Note:**

Changes to the `GWICONFIG` file must be made when upgrading from previous releases of TMA TCP. See the Oracle Tuxedo Mainframe Adapter for TCP Release Notes for specific upgrade information.

- [Defining the GLOBAL Section of the GWICONFIG File](#)
- [Defining the NATIVE Section of the GWICONFIG File](#)
- [Defining the FOREIGN Section of the GWICONFIG File](#)
- [Defining the LOCAL\\_SERVICES Section of the GWICONFIG File](#)
- [Defining the REMOTE\\_SERVICES Section of the GWICONFIG File](#)

## 5.2.1 Defining the GLOBAL Section of the GWICONFIG File

The following sections describe parameters that are associated with the `GLOBAL` section of the `GWICONFIG` file. These parameters describe global characteristics for the gateway.

The format of the `GLOBAL` section of the `GWICONFIG` file is shown in the following listing.

### Listing 5-5 Syntax for GLOBAL Section of GWICONFIG File

```
[ # A comment (from "#" to end of line)]

*GLOBAL
[ NWDEVICE=TCP_device ]
[ CONNECT_TIME=n]
[ IDLE_TIME=n]
[ OUTREQ_TIME=n]
[ LATENCY=n|1 ]
[ SECURE=Y|N ]
[ MULTIPLEX=n|1 ]
[ DFLTWRAP=wrapper name ]
[ DFLTTYPE=translation type ]
```

The following table describes the parameters that are set in the `GLOBAL` section.

Parameter	Required/ Optional	Default	Description
NWDEVICE=" <i>TCP_device</i> "	Optional	"/dev/tcp"	Specifies the network device to be used for communication with remote gateways.
CONNECT_TIME= <i>n</i> seconds	Optional	No timeout	Specifies the number of seconds the gateway waits to establish a connection.
IDLE_TIME= <i>n</i> seconds	Optional	No idle timeout	Specifies the number of seconds a connection can be idle before timing out.
OUTREQ_TIME= <i>n</i> seconds	Optional	None	Specifies the default timeout value, in seconds, for requests sent to foreign gateways.
LATENCY= <i>n</i> seconds	Optional	1	Specifies the number of seconds to be deducted from the timeout value sent to a remote gateway for a Tuxedo client request. This increases the likelihood that the remote gateway detects a timeout before the local gateway.
SECURE=Y   N	Optional	N	Specifies whether the TMA TCP Gateway supplies user information to local and remote services. If SECURE=Y, then the TMA TCP Gateway supplies user information to remote services and applies remote user information to local services using the <code>appkey</code> . If SECURE=N, then the TMA TCP Gateway does not supply user information to remote services and does not apply remote user information to local services using the <code>appkey</code> . If SECURE=N and the Tuxedo domain is set with SECURITY=ACL in the UBBCONFIG file, a request to a local service can fail even if ACLs are in place.
MULTIPLY= <i>n</i>	Optional	1	Specifies the maximum number of outstanding requests per connection that the local gateway can support.
DFTWRAP= <i>wrapper name</i>	Optional	TPS	Specifies the name of the default wrapping library to use for wrapping and unwrapping messages for machines without a FOREIGN section or without a WRAP parameter in the FOREIGN section. A corresponding wrapper object WRAP< <i>wrapper name</i> > must exist. The wrapper name TPS is used in most cases. Specify TPSD if data area security is used. For more information about data area security, refer to <a href="#">Setting Up Security for Oracle TMA TCP Gateway</a>

Parameter	Required/Optional	Default	Description
DFLTYPE=system type	Optional	DFLTYPE=MVS	Specifies the default foreign system type for encoding and decoding message buffers. If you specify TYPE in the FOREIGN section, that TYPE definition overrides this default value. For normal C-to-COBOL encoding, specify DFLTYPE="MVSC" to enable COBOL data encoding. For more information about DFLTYPE values MVS and MVSC, refer to <a href="#">Configuring Oracle TMA TCP Gateway for Data Mapping</a>

## 5.2.2 Defining the NATIVE Section of the GWICONFIG File

The following sections describe parameters that are associated with the NATIVE section of the GWICONFIG file. These parameters are specific to the local system. You can specify multiple native systems in the same configuration file allowing multiple gateway processes to access the same configuration file. This makes a single repository of connectivity services. The link between the gateway process and the native system entry is made through the GWINAME environment variable.

The format of the NATIVE section of the GWICONFIG file is illustrated in the following listing.

### Listing 5-6 Syntax for NATIVE Section of GWICONFIG File

```
[ # A comment (from "#" to end of line)]
*NATIVE
<GATEWAY_NAME>
[ IPADDR=ip_address ]
[ TCP_PORT=port number ]
[ IDLE_TIME=n]
[ MULTIPLEX=n]
[ POLL_TIME=n]
[ MAXCONNECT=n]
```

The following table describes for each local system that are specified in the NATIVE section.

Parameter	Required/Optional	Default	Description
< GATEWAY_NAME >	Required	None	This parameter is a 1-78 alphanumeric character string that represents the gateway identification passed in the GWINAME environment variable. The GATEWAY_NAME parameter must match an entry in the DM_LOCAL_DOMAINS section of the DMCONFIG file.



Parameter	Required/Optional	Default	Description
IPADDR= <i>ip_address</i>	Optional	IP address of the local host machine	Specifies the IP address for the local system. The IPADDR can be in the hexadecimal format 0xaaaaaaaa, the dotted decimal format // #.#.#.#, or the DNS format // host[.domainname].
TCP_PORT= <i>port number</i>	Optional	None	Specifies the local port number used for listening for services. This parameter is optional if no local services are advertised. If you do not specify TCP_PORT, a listener port is not created.
IDLE_TIME= <i>n</i>	Optional	No idle time value	Specifies the number of seconds a connection can remain idle before being disconnected.
MULTIPLY= <i>n</i>	Optional	1	Specifies the number of outstanding requests per connection that the local gateway can support.
POLL_TIME= <i>n</i>	Optional	250,000 micro seconds	Specifies the polling timeout (in microseconds) to be used in polling for Tuxedo messages. The range of values for this parameter is 100,000-10,000,000.
MAXCONNECT= <i>n</i>	Optional	No maximum	Specifies the number of connections into the gateway from remote hosts. If the remote system attempts more connections than this parameter specifies, the remote systems are disconnected.

### 5.2.3 Defining the FOREIGN Section of the GWICONFIG File

The FOREIGN section of the GWICONFIG file contains parameters that collectively describe foreign systems.

The format of the FOREIGN section of the GWICONFIG file is illustrated in the following listing.

#### Listing 5-7 Syntax for FOREIGN Section of GWICONFIG File

```
[ # A comment (from "#" to end of line)]
*FOREIGN
<SYSTEM_NAME>
IPADDR=ip_address
[TYPE=system_type]
[WRAP=wrapper name]
[TCP_PORT=port number]
[MULTIPLY=n sessions]
[IDLE_TIME=n seconds]
[RMTACCT="userid"]
[PASSWORD="password"]
[CICS=Y | N]
[CICSHAND=<name>]
[MAXCONNECT=n]
[CONNSYNC=Y|N]
```

```
[CONNECT_TIME=n]
[CICSDATA="string"]
```

The following table describes the parameters that are set for the each foreign system that you specify in the `FOREIGN` section.

The following table describes the parameters that are specified in the `FOREIGN` section.

Parameter	Required/Optional	Default	Description
< <i>SYSTEM_NAME</i> >	Required	None	This parameter is a 1-78 alphanumeric character string that represents the foreign system name. The <i>SYSTEM_NAME</i> parameter must match an entry in the <code>DM_REMOTE_DOMAINS</code> section of the <code>DMCONFIG</code> file.
<code>IPADDR= ip_address</code>	Required	None	Specifies the IP address for the remote system. The <code>IPADDR</code> can be in the hexadecimal format <code>0xaaaaaaaa</code> , the dotted decimal format <code>//#. #. #. #</code> , or the DNS format <code>//host[.domainname]</code> .
<code>TYPE= system type</code>	Optional	"MVS"	Specifies the foreign system type for encoding and decoding the Tuxedo buffers (application data). <code>TYPE</code> values of <code>MVS</code> and <code>MVSC</code> support C-to-COBOL or COBOL data encoding. If you do not specify <code>TYPE</code> , the value in <code>DFLTYPE</code> in the <code>GLOBAL</code> section is used. For more information about <code>MVS</code> and <code>MVSC</code> <code>TYPE</code> values, refer to <a href="#">Configuring Oracle TMA TCP Gateway for Data Mapping</a> .
<code>WRAP= wrapper name</code>	Optional	"TPS"	Specifies the name of the wrapping entry to use for wrapping and unwrapping messages for this host. A corresponding wrapper object <code>wrap&lt;wrapper name&gt;</code> must exist. The wrapper name <code>TPS</code> is used in most cases. Specify <code>TPSD</code> if data area security is used. For more information about data area security, refer to <a href="#">Setting Up Security for Oracle TMA TCP Gateway</a> . If <code>WRAP</code> is not specified in the <code>FOREIGN</code> section, the value for <code>DFLTPWRAP</code> in the <code>GLOBAL</code> section is used.
<code>TCP_PORT= port number</code>	Optional	No port number	Specifies the port number of the foreign gateway. This parameter is optional if remote services are not defined for this foreign system.

Parameter	Required/ Optional	Default	Description
MULTIPLY= <i>n</i> sessions per connection	Optional	1 session per connection	Specifies the maximum number of sessions per connection that the local gateway can support.
IDLE_TIME= <i>n</i> seconds	Optional	No idle timeout	Specifies the number of seconds a connection can remain idle before being disconnected.
CICS=Y   N	Optional	N	Specifies whether to send control information to the IBM TCP/IP listener for use with the TMA TCP for CICS gateway. If CICS=Y and you are not using IBM TCP/IP or your remote gateway is not TMA TCP for CICS, the transaction does not process correctly.
CICSHAND= < <i>name</i> >	Optional	BEAH	Specifies the name of the handler transaction to be passed to the IBM TCP/IP listener for use with TMA TCP for CICS.
RMTACCT= " <i>userid</i> "	Optional	""	Specifies the user ID for gateway-level security on the foreign system. The user ID for connection validation is obsolete.
PASSWORD= " <i>password</i> "	Optional	""	Specifies the password associated with the user ID for gateway-level security on the foreign system. The password for connection validation is obsolete.
MAXCONNECT= <i>n</i>	Optional	No limit	Specifies the maximum number of connections to the specified host.
CONNSYNC=Y N	Optional	N	Specifies whether to force the gateway to establish connections to the specified host in a synchronous manner.
CONNECT_TIME= <i>n</i>	Optional	Value from GLOBAL section	Specifies the number of seconds the gateway waits to establish a connection. If you do not specify this parameter, the value of CONNECT_TIME in the GLOBAL section is used.
CICSDATA= " <i>string</i> "	Optional	""	Specifies a string to be passed to the IBM TCP/IP listener for use with the TMA TCP for CICS gateway.

## 5.2.4 Defining the LOCAL\_SERVICES Section of the GWICONFIG File

The LOCAL\_SERVICES section of the GWICONFIG file contains parameters for each local service specified in the DMCONFIG file. Each service entry name matches the remote name of the service in the DM\_LOCAL\_SERVICES section.

The format of the LOCAL\_SERVICES section of the GWICONFIG file is illustrated in the following listing.

**Listing 5-8 Syntax for LOCAL\_SERVICES Section of GWICONFIG File**

```
[ # A comment (from "#" to end of line)]
*LOCAL_SERVICES
<SERVICE_NAME>
[INRECTYPE="foreign_incoming_buffer_type"]
[OUTRECTYPE="foreign_outgoing_buffer_type"]
[SECURE=Y | N]
[CONV=Y | N]
```

The following section describes the parameters set for each service you specify in the LOCAL\_SERVICES section.

Parameter	Required/Optional	Default	Description
< SERVICE_NAME >	Required	None	This parameter is a 1-78 alphanumeric character string that represents the local service name that matches the service name value in the DM_LOCAL_SERVICES section of the DMCONFIG file.
INRECTYPE= "foreign_incoming_buffer_type"	Optional	None	Specifies the foreign buffer type for replies to remote clients. If you do not specify INRECTYPE, the default is no type. In this case, the type of buffer is unchanged.
OUTRECTYPE= "foreign_outgoing_buffer_type"	Optional	Match the INRECTYPE value	Specifies the foreign buffer type for requests from remote clients. If you do not specify OUTRECTYPE, the default is to match the INRECTYPE value.
SECURE=Y   N	Optional	N	Specifies whether the TMA TCP Gateway applies remote user information to local services. If SECURE=Y, then the TMA TCP Gateway applies remote user information to local services using the appkey. If SECURE=N, then the TMA TCP Gateway does not apply remote user information to local services using the appkey. If SECURE=N and the Tuxedo domain is set with SECURITY=ACL in the UBBCONFIG file, a request to a local Tuxedo service can fail even if ACLs are in place.
CONV=Y   N	Optional	N	Specifies whether service is conversational. Conversational mode is not currently supported, so Y returns an error message and the gateway does not start.

## 5.2.5 Defining the REMOTE\_SERVICES Section of the GWICONFIG File

The `REMOTE_SERVICES` section of the `GWICONFIG` file contains parameters for each remote service specified in the `DMCONFIG` file. Each service entry name matches the remote name of the service in the `DM_REMOTE_SERVICES` section.

The format of the `REMOTE_SERVICES` section of the `GWICONFIG` file is illustrated in the following listing.

**Listing 5-9 Syntax for REMOTE\_SERVICES Section of GWICONFIG File**

```
[ # A comment (from "#" to end of line)]
*REMOTE_SERVICES
<SERVICE_NAME>
[INRECTYPE="foreign_outgoing_buffer_type"]
[OUTRECTYPE="foreign_incoming_buffer_type"]
[OUTREQ_TIME=n]
[SECURE=Y | N]
[CONV=Y | N]
```

The following table describes the parameters set for each service you specify in the `REMOTE_SERVICES` section.

Parameter	Required/Optional	Default	Description
< SERVICE_NAME >	Required	-	This parameter is a 1-78 alphanumeric character string that represents the local service name that matches the <code>RNAME</code> value in the <code>DM_REMOTE_SERVICES</code> section of the <code>DMCONFIG</code> file. If <code>RNAME</code> is not specified, this name matches the Tuxedo service name.
<code>INRECTYPE= "foreign_outgoing_buffer_type"</code>	Optional	None	Specifies the foreign buffer type for requests to remote servers. If you do not specify <code>INRECTYPE</code> , the default is no type. In this case, the type of buffer is changed.
<code>OUTRECTYPE= "foreign_incoming_buffer_type"</code>	Optional	Match the <code>OUTBUFTYPE</code> value	Specifies the foreign buffer type for replies from remote servers. If you do not specify <code>OUTRECTYPE</code> , the default is no type. In this case, the type of buffer is unchanged.
<code>OUTREQ_TIME= n</code>	Optional	Value from <code>GLOBAL</code> section	Specifies the timeout value, in seconds, for requests sent to this service. If you do not specify this parameter, the value for <code>OUTREQ_TIME</code> in the <code>GLOBAL</code> section is used. If <code>OUTREQ_TIME</code> is not specified in this section or the <code>GLOBAL</code> section, an error message occurs.

Parameter	Required/Optional	Default	Description
SECURE=Y   N	Optional	N	Specifies whether the TMA TCP Gateway supplies local user information to remote services. If SECURE=Y, then the TMA TCP Gateway supplies user information to remote services. If SECURE=N, then the TMA TCP Gateway does not supply user information to remote services.
CONV=Y   N	Optional	N	Specifies whether the service is conversational. Conversational mode is not currently supported, so Y returns an error message and the gateway does not start.

## 5.3 Defining Domain Configurations in the DMCONFIG File

The domain configuration file (`DMCONFIG`) is made up of specification sections. Lines beginning with an asterisk (\*) indicate the beginning of a specification section. Each such line contains the name of the section immediately following the \*. The asterisk is required when specifying a section name. Allowable section names are:

`DM_LOCAL_DOMAINS`, `DM_REMOTE_DOMAINS`, `DM_LOCAL_SERVICES`, `DM_REMOTE_SERVICES`, `DM_ROUTING`, and `DM_ACCESS_CONTROL`.



### Note:

The `DM_LOCAL_DOMAINS` section must precede the `DM_REMOTE_DOMAINS`

The following paragraphs describe the significant parameters within specific sections of the `DMCONFIG` file that define new gateway configurations.

- [DM\\_LOCAL\\_DOMAINS Section](#)
- [DM\\_REMOTE\\_DOMAINS Section](#)
- [DM\\_ACCESS\\_CONTROL Section](#)
- [DM\\_LOCAL\\_SERVICES Section](#)
- [DM\\_REMOTE\\_SERVICES Section](#)
- [DM\\_ROUTING Section](#)
- [Sample DMCONFIG File](#)

### 5.3.1 DM\_LOCAL\_DOMAINS Section

This section identifies local domains and their associated gateway groups. The section must have an entry for each gateway group (local domain). Each entry specifies the parameters required for the domain gateway processes running in that group.

The format of the `DM_LOCAL_DOMAINS` section of the `DMCONFIG` file is illustrated in the following listing.

**Listing 5-10 Syntax for `DM_LOCAL_DOMAINS` Section of `DMCONFIG` File**

`LDM required parameters [optional parameters]`

`LDM` is an *identifier* value used to name each local domain and must be unique within a particular configuration. In the description of the `DM_LOCAL_SERVICES` section, `LDM` is the identifier that connects local services with a particular gateway group.

The following table describes the parameters that are set in the `DM_LOCAL_SERVICES` section.

Parameter	Required/Optional	Default	Description
<code>GWGRP = identifier</code>	Required	None	Specifies the name of the gateway server group (the name provided in the <code>TUXCONFIG</code> file) representing this local domain. A one-to-one relationship must exist between a <code>DOMAINID</code> and the name of the gateway server group; each <code>GWGRP</code> must have its own unique <code>DOMAINID</code> .
<code>TYPE = identifier</code>	Required	None	Is used for grouping local domain into classes. <code>TYPE</code> can be set to <code>TDOMAIN</code> or any other domain gateway type. The <code>TDOMAIN</code> value indicates that this local domain can only communicate with another Tuxedo System/Domain. For use with TMA TCP Gateway, specify <code>TYPE=IDOMAIN</code> . Domain types must be defined in the <code>\$TUXDIR/udataobj/DMTYPE</code> file.
<code>DOMAINID = string</code>	Required	None	Is used to identify the local domain. <code>DOMAINID</code> must be unique across both local and remote domains. The value of <i>string</i> can be a sequence of characters (for example, "BA.CENTRAL01"), or a sequence of hexadecimal digits preceded by "0x" (for example, "0x0002FF98C000B9D6"). <code>DOMAINID</code> must be 32 octets or fewer in length. If the value is a string, it must be 31 characters or fewer.
<code>AUDITLOG = string</code>	Optional	None	Specifies the name of the audit log file for this local domain. The audit log feature is activated from the <code>dmadmin</code> command and records all the operations within this local domain. If the audit log feature is active and this parameter is not specified, the file <code>DMmmddy.LOG</code> (where <i>mm</i> =month, <i>dd</i> =day, and <i>yy</i> =year) is created in the directory specified by the <code>\$APPDIR</code> environment variable or the <code>APPDIR</code> keyword of the <code>MACHINES</code> section of the <code>TUXCONFIG</code> file.
<code>BLOCKTIME = numeric</code>	Optional	The value of <code>BLOCKTIME</code> parameter specified in the <code>TUXCONFIG</code> file	Specifies the maximum wait time allowed for a blocking call. The value sets a multiplier of the <code>SCANUNIT</code> parameters specified in the <code>TUXCONFIG</code> file. The value <code>SCANUNIT * BLOCKTIME</code> must be greater than or equal to <code>SCANUNIT</code> and less than 32,768 seconds. A timeout always implies a failure of the affected request. Notice that the timeout specified for transactions in the <code>TUXCONFIG</code> is always used when the request is issued within a transaction.

Parameter	Required/Optional	Default	Description
CODEPAGE = <i>table-identifier</i>	Optional	None	<p>Specifies the mapping to use with remote hosts that are not specified in the DMCONFIG file. CODEPAGE designates a bidirectional translation table for SBCS (ASCII to EBCDIC) conversion or designates multibyte character set (MBCS) encoding or decoding between a local Tuxedo application and a remote mainframe application. The <i>table-identifier</i> describes a file containing a translation table. The name of the file, located in the \$TUXDIR/udatajobj/codepage directory, is a composite of the code page numbers used for the translation. This parameter specifies the mapping to use with remote hosts that are not specified in the DMCONFIG file.</p> <p>For SBCS (ASCII to EBCDIC), for example, specifying CODEPAGE=00819x00297 designates the translation table for converting ASCII CP-00819 characters to French EBCDIC CP-00297 characters, and vice versa. The translation tables can be modified. For complete character listings, refer to "Code Page Translation Tables."</p> <p>For MBCS, for example, specifying CODEPAGE="UTF-8:ibm-1388" designates MBCS encoding or decoding for converting UTF-8 characters to Simplified Chinese Mixed EBCDIC ibm-1388 characters, and vice versa. For more information, see Using Multibyte Character Set (MBCS) Translations.</p>
DMTLOGDEV = <i>string</i>	Optional	None	<p>Specifies the Tuxedo file system that contains the Domain transaction log (DMTLOG) for this machine. The DMTLOG is stored as a Tuxedo System VTOC table on the device. If this parameter is not specified, the domain gateway group is not allowed to process requests in transaction mode. Local domains running on the same machine can share the same DMTLOGDEV file system, but each local domain must have its own log (a table in the DMTLOGDEV) named as specified by the DMTLOGNAME keyword.</p>
DMTLOGNAME = <i>identifier</i>	Optional	"DMTLOG"	<p>Specifies the name of the domain transaction log for this domain. This name must be unique when the same DMTLOGDEV is used for several local domains. The name must be 30 characters or less.</p>
DMTLOGSIZE = <i>numeric</i>	Optional	100 pages	<p>Specifies the numeric size, in pages, of the Domain transaction log for this machine. It must be greater than 0 and less than the amount of available space on the Tuxedo file system. If not specified, the default is 100 pages.</p>
MAXDATALEN = <i>numeric</i>	Optional	None	<p>Specifies a maximum amount of data (in bytes) that can be sent to or from any services advertised by this local domain. There is no limit if this parameter is not specified.</p>
MAXRDOM = <i>numeric</i>	Optional	None	<p>Specifies the maximum number of connections (or dialogs if the domain is of type OS/TP) allowed per gateway. There is no limit if this parameter is not specified.</p>
MAXRDTRAN = <i>numeric</i>	Optional	16	<p>Specifies the maximum number of domains that can be involved in a transaction. It must be greater than 0 and less than 32,768. If not specified, the default is 16.</p>
MAXTRAN = <i>numeric</i>	Optional	The value of MAXGTT	<p>Specifies the maximum number of simultaneous global transactions allowed on this local domain. It must be greater than or equal to 0 and less than or equal to the MAXGTT parameter specified in the TUXCONFIG file. If not specified, the default is the value of MAXGTT.</p>



Parameter	Required/Optional	Default	Description
MAXSEN DLEN = <i>numeric</i>	Optional	None	Specifies the maximum length (in bytes) of messages sent or received by this local domain. If this parameter is set, all messages sent or received are broken up into packets of no more than MAXSENLEN bytes. There is no limit if this parameter is not specified.

### 5.3.2 DM\_REMOTE\_DOMAINS Section

This section identifies the known set of remote domains and their characteristics.

The format of the DM\_REMOTE\_DOMAINS section of the DMCONFIG file is illustrated in the following listing.

**Listing 5-11 Syntax for DM\_REMOTE\_DOMAINS Section of DMCONFIG**

```

RDOM required parameters [optional
parameters]

```

*RDOM* is an *identifier* value used to identify each remote domain known to this configuration and must be unique within the configuration.

The following table describes the parameters that are set in the DM\_REMOTE\_DOMAINS section.

Parameter	Required/Optional	Default	Description
TYPE = <i>identifier</i>	Required	None	Is used for grouping remote domain into classes. TYPE can be set to TDOMAIN or any other domain gateway type. The TDOMAIN value indicates that this remote domain can only communicate with another Tuxedo System/Domain. The OSITP value indicates that this remote domain communicates with another TP domain via the OSI-TP protocol. For use with TMA TCP Gateway, specify TYPE=IDOMAIN.

Parameter	Required/Optional	Default	Description
DOMAINID = <i>string</i>	Required	None	Is used to identify a remote domain. DOMAINID must be 32 octets or fewer in length. If the value is a string, it must be 31 characters or fewer. DOMAINID must be unique across remote domains. The value of <i>string</i> can be a sequence of characters or a sequence of hexadecimal digits preceded by "0x".

Parameter	Required/Optional	Default	Description
CODEPAGE = <i>table-identifier</i>	Optional	None	Is used to designate a bidirectional translation table for SBCS (ASCII to EBCDIC) conversion or designate multibyte character set (MBCS) encoding or decoding between a local Tuxedo application and a remote mainframe application. The <i>table-identifier</i> describes a file containing a translation table. The name of the file, located in the \$TUXDIR/ udataajobj/codepage directory, is a composite of the code page numbers used for the translation. For SBCS (ASCII to EBCDIC), for example, specifying CODEPAGE=00819x00297 designates the translation table for converting ASCII CP-00819 characters to French EBCDIC CP-00297 characters, and vice versa. The translation tables can be modified. For complete character listings, refer to "Code Page Translation Tables." For MBCS, for example, specifying CODEPAGE="UTF-8:ibm-1388" designates MBCS encoding or decoding for converting UTF-8 characters to Simplified Chinese Mixed EBCDIC ibm-1388 characters, and vice versa. For more information, see Using Multibyte Character Set (MBCS) Translations.

### 5.3.3 DM\_ACCESS\_CONTROL Section

This section is optional in the DMCONFIG file and specifies the access control lists used by local domain.

The format of the `DM_ACCESS_CONTROL` section of the `DMCONFIG` file is illustrated in the following listing.

**Listing 5-12 Syntax for `DM_ACCESS_CONTROL` Section of `DMCONFIG`**

`ACL_NAME` required parameters

`ACL_NAME` is a name (*identifier*) used to identify a particular access control list; it must be 15 characters or less in length.

Parameter	Required/Optional	Default	Description
<code>ACLIST = <i>identifier</i> [,<i>identifier</i>]</code>	Required	None	An <code>ACLIST</code> is composed of one or more remote domain names ( <code>RDOM</code> ) separated by commas. The wildcard character ( <code>*</code> ) can be used to specify that all the remote domains defined in the <code>DM_REMOTE_DOMAINS</code> section can access a local domain.

### 5.3.4 `DM_LOCAL_SERVICES` Section

This section provides information on the services exported by each local domain. This section is optional and if it is not specified then all local domains defined in the `DM_LOCAL_DOMAINS` section accept requests to all of the services advertised by the Tuxedo System/Domain application. If this section is defined then it should be used to restrict the set of local services that can be requested from a remote domain.

The format of the `DM_LOCAL_SERVICES` section of the `DMCONFIG` file is illustrated in the following listing.

**Listing 5-13 Syntax for `DM_LOCAL_SERVICES` Section of `DMCONFIG` File**

`service` [optional parameters]

`service` is the local name (*identifier*) of the exported service, and it must be 15 characters or fewer in length.

This name corresponds to a name advertised by one or more servers running with the local Tuxedo System/Domain application. Notice that exported services inherit the default or special properties specified for the service in an entry in the `SERVICES` section of the `TUXCONFIG` file. Some of these parameters are: `LOAD`, `PRIO`, `AUTOTRAN`, `ROUTING`, `BUFTYPE`, and `TRANTIME`.

Parameter	Required/Optional	Default	Description
<code>ACL = <i>identifier</i></code>	Optional	None	Specifies the name of the access control list ( <code>ACL</code> ) to be used by the local domain to restrict requests made to this service by remote domains. The name of the <code>ACL</code> is defined in the <code>DM_ACCESS_CONTROL</code> section. If this parameter is not specified, then access control is not performed for requests to this service.

Parameter	Required/Optional	Default	Description
LDOM = <i>identifier</i>	Optional	None	Specifies the name identifying the local domain exporting this service. If this keyword is not specified, then all the local domains defined in the DM_LOCAL_DOMAINS section accept requests to this local service.
RNAME = <i>string</i>	Optional	The service name in the GWICONFIG	Specifies the name exported to remote domains. The remote domains use this name for request to this service. If this parameter is not specified, the local service name is supposed to be the name used by any remote domain. For TMA TCP, this should match the service name in the GWICONFIG.
INBUFTYPE = "type:subtype   FML:servername"	Optional	None	Specifies the Tuxedo buffer type for replies from local servers. To use an alternate data mapping product, specify FML as the buffer type (regardless of the actual Tuxedo buffer type being passed) and the encoding service name as the subtype. Because the gateway does not do the encoding, the FML buffer type in the DMCONFIG file is a flag for alternate data mapping only. The Tuxedo server and the alternate data mapping product should be configured with the actual Tuxedo buffer type.
OUTBUFTYPE = "type:subtype   FML:servername"	Optional	None	Specifies the Tuxedo buffer type for requests to local servers.  To use an alternate data mapping product, specify FML as the buffer type (regardless of the actual Tuxedo buffer type being passed) and the decoding service name as the subtype. Because the gateway does not do the decoding, the FML buffer type in the DMCONFIG file is a flag for alternate data mapping only. The Tuxedo server and the alternate data mapping product should be configured with the actual Tuxedo buffer type.

### 5.3.5 DM\_REMOTE\_SERVICES Section

This section provides information on services "imported" and available on remote domains. The format of the DM\_REMOTE\_SERVICES section of the DMCONFIG file is illustrated in the following listing.

**Listing 5-14 Syntax for DM\_REMOTE\_SERVICES Section of DMCONFIG**

```
service [optional parameters]
```

*service* is the name (*identifier*) used by the local Tuxedo System/Domain application for a particular remote service. Remote services are associated with a particular remote domain.

Parameter	Required/Optional	Default	Description
CONV = {Y   N}	Optional	N	Specifies whether the remote service is a conversational service. Use Y to specify the remote service is a conversational service. Use N to specify the remote service is not a conversational service.

Parameter	Required/Optional	Default	Description
LDOM = <i>identifier</i>	Optional	None	Specifies the name of a local domain in charge of routing requests to this remote service. The gateway group associated with the local domain advertises <i>service</i> in the Tuxedo System/Domain Bulletin Board. If this parameter is not specified, then all the local domains are able to accept requests to this remote service. The service request is redirected to a remote domain of the same type (see the following definition for RDOM keyword).
RDOM = <i>identifier</i>	Optional	None	Specifies the name of the remote domain responsible for the actual execution of this service. If this parameter is not specified and a routing criteria (see the following definition for ROUTING keyword) is not specified, then the local domain assumes that any remote domain of the same type accepts this service and it selects a known domain (a domain to which a connection already exists) or remote domain from the DM_REMOTE_DOMAINS section.
RNAME = <i>string</i>	Optional	The service name in the GWICONFIG	Specifies the actual service name expected by the remote domain. If this parameter is not specified, the remote service name is the same as the name specified in <i>service</i> . For TMA TCP, this name should match the service name in the GWICONFIG file.
ROUTING = <i>identifier</i>	Optional	None	When more than one remote domain offers the same service, a local domain can perform data-dependent routing if this optional parameter is specified. The <i>identifier</i> specifies the name of the routing criteria used for this data-dependent routing. If not specified, data-dependent routing is not done for this service. <i>identifier</i> must be 15 characters or less in length. If multiple entries exist for the same service name but with different RDOM parameters, the ROUTING parameter should be the same for all of these entries.
TRANSTIME = <i>integer</i>	Optional	30 seconds	Specifies the default time-out value in seconds for a transaction automatically started for the associated service. The value must be greater than or equal to 0 and less than 2147483648. A value of 0 implies the maximum time-out value for the machine.
INBUFTYPE="type: subtype   FML: servicename"	Optional	None	Specifies the Tuxedo buffer type for requests from local clients. To use an alternate data mapping product, specify FML as the buffer type (regardless of the actual Tuxedo buffer type being passed) and the encoding service name as the subtype. Because the gateway does not do the encoding, the FML buffer type in the DMCONFIG file is a flag for alternate data mapping only. The Tuxedo application and the alternate data mapping product should be configured with the actual Tuxedo buffer type.
OUTBUFTYPE="type: subtype   FML: servicename"	Optional	None	Specifies the Tuxedo buffer type for replies to local clients. To use an alternate data mapping product, specify FML as the buffer type (regardless of the actual Tuxedo buffer type being passed) and the decoding service name as the subtype. Because the gateway does not do the decoding, the FML buffer type in the DMCONFIG file is a flag for alternate data mapping only. The Tuxedo application and the alternate data mapping product should be configured with the actual Tuxedo buffer type.

## 5.3.6 DM\_ROUTING Section

This section is optional in the DMCONFIG file and provides information for data-dependent routing of service requests using FML, VIEW, X\_C\_TYPE, and X\_COMMON typed buffers.

The format of the DM\_ROUTING section of the DMCONFIG file is illustrated in the following listing.

### Listing 5-15 Syntax for DM\_ROUTING Section of DMCONFIG File

CRITERION\_NAME required parameters

CRITERION\_NAME is the (*identifier*) name of the routing entry that was specified on the services entry. CRITERION\_NAME must be 15 characters or less in length.

Parameter	Required/Optional	Default	Description
FIELD = <i>identifier</i>	Required	None	Specifies the name of the routing field. It must be 30 characters or less. This field is assumed to be a field name that is identified in an FML field table (for FML buffers) or an FML view table (for VIEW, X_C_TYPE, or X_COMMON buffers). The FLDTBLDIR and FIELDTBLS environment variables are used to locate FML field tables, and the VIEWDIR and VIEWFILES environment variables are used to locate FML view tables.
RANGES = <i>string</i>	Required	None	Specifies the ranges and associated remote domain names (RDOM) for the routing field. <i>string</i> must be enclosed in double quotes. The format of <i>string</i> is a comma-separated ordered list of range/RDOM pairs. A range is either a single value (signed numeric value or character string in single quotes), or a range of the form "lower - upper" (where lower and upper are both signed numeric values or character strings in single quotes). Note that "lower" must be less than or equal to "upper." To embed a single quote in a character string value (as in O'Brien, for example), it must be preceded by two backslashes ('O\\Brien'). The value MIN can be used to indicate the minimum value for the data type of the associated FIELD; for strings and arrays, it is the null string; for character fields, it is 0; for numeric values, it is the minimum numeric value that can be stored in the field. The value MAX can be used to indicate the maximum value for the data type of the associated FIELD; for strings and arrays, it is effectively an unlimited string of octal-255 characters; for a character field, it is a single octal-255 character; for numeric values, it is the maximum numeric value that can be stored in the field.

Parameter	Required/Optional	Default	Description
-	-	-	<p>Thus, MIN - -5" is all numbers less than or equal to -5 and ' 6 - MAX' " is all numbers greater than or equal to 6. The meta-character "*" (wildcard) in the position of a range indicates any values not covered by the other ranges previously seen in the entry; only one wildcard range is allowed per entry and it should be last (ranges following it are ignored).</p> <p>The routing field can be of any data type supported in FML. A numeric routing field must have numeric range values and a string routing field must have string range values.</p> <p>String range values for string, array, and character field types must be placed inside a pair of single quotes and cannot be preceded by a sign. Short and long integer values are a string of digits, optionally preceded by a plus or minus sign. Floating point numbers are of the form accepted by the C compiler or <code>atof()</code>: an optional sign, then a string of digits optionally containing a decimal point, then an optional e or E followed by an optional sign or space, followed by an integer.</p> <p>When a field value matches a range, the associated RDOM value specifies the remote domain to which the request should be routed. A RDOM value of "*" indicates that the request can go to any remote domain known by the gateway group.</p> <p>Within a range/RDOM pair, the range is separated from the RDOM by a ".".</p>
BUFTYPE = ~type1[: subtype1[, subtype2 . . . ] ] [: type2[: subtype3[, . . . ]]] . . . ~	Required	None	<p>Is a list of types and subtypes of data buffers for which this routing entry is valid. The types are restricted to be either FML, VIEW, X_C_TYPE, or X_COMMON. No subtype can be specified for type FML and subtypes are required for the other types ("*" is not allowed). Duplicate type/subtype pairs cannot be specified for the same routing criterion name; more than one routing entry can have the same criterion name as long as the type/subtype pairs are unique.</p> <p>If multiple buffer types are specified for a single routing entry, the data types of the routing field for each buffer type must be the same.</p> <p>If the field value is not set (for FML buffers), or does not match any specific range and a wildcard range has not been specified, an error is returned to the application process that requested the execution of the remote service.</p>

### 5.3.7 Sample DMCONFIG File

The following listing is a sample DMCONFIG file and must be set up prior to running the TMA TCP Gateway product. For a sample DMCONFIG file that uses alternate data mapping tools, refer to the ["Configuring Oracle TMA TCP Gateway for Data Mapping"](#)

#### Listing 5-16 Sample DMCONFIG File

```
#
# Copyright (c) 2023 Oracle Systems, Inc
# All Rights Reserved

*DM_LOCAL_DOMAINS
LOCAL GWGRP=GROUP
```



```
TYPE=IDOMAIN
DOMAINID="LOCAL"

#
*DM_REMOTE_DOMAINS
REMOTE TYPE=IDOMAIN
DOMAINID="REMOTE"

#
*DM_LOCAL_SERVICES
ECHOX RNAME="ZECHOSV4"
TOLOWER RNAME="TUXTOLOWER"
INBUFTYPE=string
OUTBUFTYPE=string

#
*DM_REMOTE_SERVICES
TOUPPER RDOM=REMOTE
LDOM=LOCAL
RNAME="TUXTOUPPER"

ECHO FAR RDOM=REMOTE
LDOM=LOCAL
RNAME="BEASVR07"
INBUFTYPE="VIEW:myview"
OUTBUFTYPE="FML"

NORMAL RDOM=REMOTE
LDOM=LOCAL
RNAME="TST1V"
```

# 6

## Starting Oracle TMA TCP Gateway

The following topics provide information about starting the Oracle Tuxedo Mainframe Adapter for TCP Gateway (hereafter referenced as TMA TCP Gateway) product:

- [Setting Environment Variables](#)
- [Invoking TMA TCP Gateway](#)
- [Administering the Gateways](#)

### 6.1 Setting Environment Variables

Before you attempt to use TMA TCP Gateway, you must set the `TUXDIR` and `PATH` environment variables as the following example illustrates.

#### Listing 6-1 Setting `ROOTDIR` and `PATH` Environment Variables

```
TUXDIR=/usr/tuxedo; export TUXDIR
PATH=$PATH:$TUXDIR/bin; export PATH
GWICONFIG=$APPDIR/gwiconfig;export GWICONFIG
BDMCONFIG=$APPDIR/bdmconfig;export BDMCONFIG
TUXCONFIG=$APPDIR/tuxconfig;export TUXCONFIG
```

You should set `TUXDIR` to the actual path where your Oracle Tuxedo and TMA TCP Gateway software is installed. Set `APPDIR` to the application directory, similar to the `UBBCONFIG` file. You may also need to set the `LANG` environment variable if you have generated custom mapping tables or message catalogs. Some platforms may require that `LANG` always is set. Consult your operating system documentation for the appropriate `LANG` value.

### 6.2 Invoking TMA TCP Gateway

Perform a `tmloadcf` and `dmloadcf` to load the `UBBCONFIG` and the `DMCONFIG` files. Invoke TMA TCP Gateway using the `tmboot` command to boot the Oracle Tuxedo system. Be sure to configure TMA TCP Gateway prior to using the `tmboot` command. For details, see the “Configuring Oracle TMA TCP Gateway” section.

#### Listing 6-2 Invoking TMA TCP Gateway Using `tmboot`

```
tmboot
```

### 6.3 Administering the Gateways

Oracle Tuxedo has a set of `tmadmin` and `dmadmin` commands for the administration of the TMA TCP Gateways. For detailed information about these commands, refer to the *Oracle Tuxedo Administrator's Guide* and the *Oracle Tuxedo Domain User Guide*.

# 7

## Error and Information Messages

There are several ways that local client programs can learn about application errors that occur on remote systems. For example:

- Application failures can be communicated through error indicators that remote systems send to the local Tuxedo Mainframe Adapter for TCP Gateway.
- Service routines can include information about failures in output records that are returned to client programs.

This document contains a description of error and informational messages that can be encountered while using Oracle Tuxedo Mainframe Adapter for TCP Gateway (hereafter referenced as TMA TCP Gateway).

Error	Description	
<b>1000:ERROR</b>	<b>Memory allocation error</b>	
-	<b>DESCRIPTION</b>	An attempt to allocate memory failed.
-	<b>ACTION</b>	Check available memory.
<b>1001:ERROR</b>	<b>Cannot load shared module &lt;text&gt;: &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	An attempt to load the listed shared library failed. The reason is noted in the error text.
-	<b>ACTION</b>	Verify that the shared library exists.
<b>1002:ERROR</b>	<b>Cannot get symbol &lt;text&gt; in module &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The listed symbol was not found in the listed shared module.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1003:ERROR</b>	<b>No encoding type defined for &lt;text&gt;. No encoding done</b>	
-	<b>DESCRIPTION</b>	The gateway configuration file does not specify a <code>TYPE</code> parameter for the listed <code>FOREIGN</code> gateway or a <code>DFLTTYPE</code> parameter in the <code>GLOBAL</code> section.
-	<b>ACTION</b>	Correct the gateway configuration file.
<b>1004:ERROR</b>	<b>Encoding type '&lt;text&gt;:&lt;text&gt;' for type '&lt;text&gt;' failed.</b>	
-	<b>DESCRIPTION</b>	Allocating a typed buffer for encoding output failed.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1005:ERROR</b>	<b>Decode failed due to allocation error</b>	
-	<b>DESCRIPTION</b>	The output data buffer was not created correctly with <code>tpalloc( )</code> .

Error	Description	
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1006:ERROR</b>	<b>No encoding type defined for &lt;text&gt;. No decoding done</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software does not have an encoding type defined in shared memory for the listed gateway.
-	<b>ACTION</b>	Verify the <code>TYPE</code> parameter for the gateway in the gateway configuration file.
<b>1007:ERROR</b>	<b>Decoding type &lt;text&gt;:&lt;text&gt; for type &lt;text&gt; failed</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software detected an error while getting decoding information for the listed type, subtype, and remote type.
-	<b>ACTION</b>	Previous logged error messages should provide the exact reasons for the failure. Contact your Tuxedo System Technical Support.
<b>1008:ERROR</b>	<b>GWICONFIG env var not found!</b>	
-	<b>DESCRIPTION</b>	Retrieving the environment variable <code>GWICONFIG</code> failed.
-	<b>ACTION</b>	Set and export the <code>GWICONFIG</code> environment variable.
<b>1009:ERROR</b>	<b>&lt;text&gt; config file not found!</b>	
-	<b>DESCRIPTION</b>	The named configuration file cannot be found.
-	<b>ACTION</b>	Verify that the file which the <code>GWICONFIG</code> environment variable points to exists.
<b>1010:ERROR</b>	<b>Parse of &lt;text&gt; failed, exiting</b>	
-	<b>DESCRIPTION</b>	An attempt to parse the gateway configuration file failed.
-	<b>ACTION</b>	Verify the format of the gateway configuration file.
<b>1011:ERROR</b>	<b>&lt;number&gt; errors found while parsing &lt;text&gt;, exiting</b>	
-	<b>DESCRIPTION</b>	Errors occurred while parsing the gateway configuration file.
-	<b>ACTION</b>	Verify the format of the gateway configuration file
<b>1012:INFO</b>	<b>Dumping configuration to stdout</b>	
-	<b>DESCRIPTION</b>	The current configuration is dumped to the standard output.
-	<b>ACTION</b>	<b>No action required.</b>
<b>1013:ERROR</b>	<b>Sending error to &lt;text&gt;:\n&lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The error condition described is being sent to the listed gateway.

Error	Description	
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1014:ERROR</b>	<b>Invalid action detected &lt;number&gt;</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software detected an invalid action while trying to encode a buffer.
-	<b>ACTION</b>	This is an internal error with no associated user action. If the error persists, contact your Tuxedo System Technical Support with the exact error message.
<b>1015:ERROR</b>	<b>Data encoding failed</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software detected an error encoding data.
-	<b>ACTION</b>	Previous logged error messages should provide the exact reasons for the failure. Contact your Tuxedo System Technical Support.
<b>1016:ERROR</b>	<b>Invalid wrap switch index</b>	
-	<b>DESCRIPTION</b>	The wrap switch index in shared memory is not valid.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1017:ERROR</b>	<b>Buffer wrapping failed</b>	
-	<b>DESCRIPTION</b>	The buffer wrapping function returned an error.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1018:ERROR</b>	<b>Bad wrapping protocol</b>	
-	<b>DESCRIPTION</b>	The wrapping protocol in shared memory is not <code>GWI_PROTOCOL</code> .
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1019:ERROR</b>	<b>Cannot unwrap buffer</b>	
-	<b>DESCRIPTION</b>	The buffer unwrapping function returned an error.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1020:ERROR</b>	<b>Unable to obtain local service (&lt;text&gt;) information from shared memory</b>	
-	<b>DESCRIPTION</b>	Information about the local service could not be found in shared memory.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1021:ERROR</b>	<b>Request for unknown service '&lt;text&gt;' from &lt;text&gt;</b>	

Error	Description	
-	<b>DESCRIPTION</b>	Information about the listed service could not be found in shared memory.
-	<b>ACTION</b>	Verify the DMCONFIG file and ensure dmloadcf has been run on it.
<b>1022:ERROR</b>	<b>Reply received for invalid session</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway received a reply for an invalid session.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1023:ERROR</b>	<b>Reply received for inactive session</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway received a reply for an inactive session.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1024:ERROR</b>	<b>Unable to obtain remote service (&lt;text&gt;) information from shared memory</b>	
-	<b>DESCRIPTION</b>	Information about the remote service could not be found in shared memory.
-	<b>ACTION</b>	Verify the DMCONFIG file and insure dmloadcf has been run on it.
<b>1025:ERROR</b>	<b>Data decoding failed</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software detected an error while decoding a received message buffer.
-	<b>ACTION</b>	Previous logged error messages should provide the exact reasons for the failure. Contact your Tuxedo System Technical Support.
<b>1026:INFO</b>	<b>&lt;text&gt; : &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The field name and its value in a fielded buffer are logged.
-	<b>ACTION</b>	No action required.
<b>1027:INFO</b>	<b>Type &lt;number&gt; : &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The field type and its value in a fielded buffer are logged.
-	<b>ACTION</b>	<b>No action required.</b>
<b>1028:ERROR</b>	<b>Cannot open &lt;text&gt;:&lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	Could not find the listed view file.
-	<b>ACTION</b>	Verify the VIEWDIR and VIEWFILES environment variables.
<b>1029:ERROR</b>	<b>FML incompatible field in &lt;text&gt;:&lt;text&gt;</b>	

Error	Description	
-	<b>DESCRIPTION</b>	The listed view contains the packed decimal data type. Views containing this type cannot be used for FML-to-view or view-to-view conversions.
-	<b>ACTION</b>	Remove packed decimal fields from the input FML or view, or send the same view structure to the local gateway that is sent to the remote gateway.
<b>1030:ERROR</b>	<b>tpalloc for &lt;text&gt; failed</b>	
-	<b>DESCRIPTION</b>	Allocation of a Tuxedo typed buffer failed.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1031:ERROR</b>	<b>Fvstof failed for &lt;text&gt;:&lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The conversion of a C structure to a fielded buffer failed.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1033:ERROR</b>	<b>tpalloc for &lt;text&gt;:&lt;text&gt; failed</b>	
-	<b>DESCRIPTION</b>	Allocating a typed buffer for the listed view failed.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1036:ERROR</b>	<b>Unable to obtain network descriptor; error code = &lt;number&gt;</b>	
-	<b>DESCRIPTION</b>	This is an internal error code, indicating a network initialization failure.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1037:ERROR</b>	<b>Unable to determine RDOM for request</b>	
-	<b>DESCRIPTION</b>	This is an internal error code, indicating a shared memory lookup failure.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1038:ERROR</b>	<b>Unable to connect to &lt;text&gt;; return code &lt;number&gt;</b>	
-	<b>DESCRIPTION</b>	The gateway detected an error while trying to open a connection on a socket.
-	<b>ACTION</b>	Verify that the network address information for the desired FOREIGN entry is correct.
<b>1039:ERROR</b>	<b>Connection failed to &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software detected an error while trying to connect to the listed gateway.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.

Error	Description	
<b>1048:ERROR</b>	<b>Unable to send service request</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software detected an error while trying to send a message to the network.
-	<b>ACTION</b>	This is an internal error with no associated user action. If the error persists, contact your Tuxedo System Technical Support with the exact error message.
<b>1049:ERROR</b>	<b>Unable to send service request \"&lt;text&gt;\"</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software detected an error while trying to send a message to the network.
-	<b>ACTION</b>	This is an internal error with no associated user action. If the error persists, contact your Tuxedo System Technical Support with the exact error message.
<b>1050:ERROR</b>	<b>Unable to get remote service information from shared memory</b>	
-	<b>DESCRIPTION</b>	Information about the remote service could not be found in shared memory.
-	<b>ACTION</b>	Verify the DMCONFIG file and insure dmloadcf has been run on it.
<b>1052:ERROR</b>	<b>Can't get remote service name for &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The remote service name for the listed service could not be found in shared memory.
-	<b>ACTION</b>	Verify the DMCONFIG file and insure dmloadcf has been run on it.
<b>1053:ERROR</b>	<b>No remote service entry for &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	No remote service entry for the listed service was found in shared memory.
-	<b>ACTION</b>	Correct the gateway configuration file.
<b>1054:ERROR</b>	<b>Cannot suspend action</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software was unable to suspend the action while trying to set up a network connection.



Error	Description	
-	<b>ACTION</b>	This is an internal error with no associated user action. If the error persists, contact your Tuxedo System Technical Support with the exact error message.
<b>1055:WARN</b>	<b>CICS init string failed for &lt;text&gt;.</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software detected an error while trying to send a CICS initialization string to the listed gateway.
-	<b>ACTION</b>	This is an internal error with no associated user action. If the error persists, contact your Tuxedo System Technical Support with the exact error message.
<b>1056:INFO</b>	<b>Connection &lt;number&gt; initialized to &lt;text&gt;, ID:\n\t&lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software successfully initialized a connection to the gateway.
-	<b>ACTION</b>	No action required.
<b>1057:INFO</b>	<b>Multiplex count for connection &lt;number&gt; is &lt;number&gt;</b>	
-	<b>DESCRIPTION</b>	The multiplex count for the listed connection is given.
-	<b>ACTION</b>	No action required.
<b>1058:INFO</b>	<b>Listen port &lt;number&gt; (&lt;text&gt;) established</b>	
-	<b>DESCRIPTION</b>	The listen port for the gateway has been established.
-	<b>ACTION</b>	No action required.
<b>1059:ERROR</b>	<b>Cannot change action into msg_failure</b>	
-	<b>DESCRIPTION</b>	The action cannot be changed to msg_failure.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1060:ERROR</b>	<b>Cannot change action into msg_reply</b>	
-	<b>DESCRIPTION</b>	The action cannot be changed to msg_failure.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1062:ERROR</b>	<b>Unexpected action state &lt;number&gt;</b>	
-	<b>DESCRIPTION</b>	This message should never occur. The program code or defines are wrong if it does.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1063:WARN</b>	<b>Conversation not found - closing connection</b>	
-	<b>DESCRIPTION</b>	The ID of the connection was not found in the shared memory conversation table.

Error	Description	
-	<b>ACTION</b>	No action required.
<b>1064:ERROR</b>	<b>No more actions</b>	
-	<b>DESCRIPTION</b>	Trying to create an action to time out a conversation failed.
-	<b>ACTION</b>	No action required.
<b>1066:ERROR</b>	<b>Cannot allocate appropriate array for poll</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software was unable to allocate the <code>pollfd</code> array.
-	<b>ACTION</b>	This is an internal error with no associated user action. If the error persists, contact your Tuxedo System Technical Support with the exact error message.
<b>1067:ERROR</b>	<b>Run-time environment setting failure</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software was unable to initialize the run-time environment.
-	<b>ACTION</b>	Previous logged error messages should provide the exact reasons for the failure. Contact your Tuxedo System Technical Support.
<b>1068:ERROR</b>	<b>No free listen structures available</b>	
-	<b>DESCRIPTION</b>	Obtaining a free listen structure failed.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1069:ERROR</b>	<b>Cannot listen for host &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software was unable to resolve the IP address of the listed gateway.
-	<b>ACTION</b>	Previous logged error messages should provide the exact reasons for the failure. Contact your Tuxedo System Technical Support.
<b>1070:ERROR</b>	<b>Gateway fails to complete connection</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software was unable to open a socket connection.
-	<b>ACTION</b>	Verify that the address of the remote host is configured correctly.
<b>1071:ERROR</b>	<b>Unable to establish listen port &lt;number&gt; (&lt;text&gt;)</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software was unable to establish a listen socket.

Error	Description	
-	<b>ACTION</b>	Verify that the configured listen port is not in use by another process. Contact your Tuxedo System Technical Support.
<b>1072:ERROR</b>	<b>Can't read CODEPAGE '&lt;text&gt;' for &lt;text&gt; DOMAIN &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The codepage file specified in the DMCONFIG file cannot be opened.
-	<b>ACTION</b>	Verify that the specified file is available and that the file protections are set correctly.
<b>1073:ERROR</b>	<b>&lt;text&gt; '&lt;text&gt;' not found in domain configuration</b>	
-	<b>DESCRIPTION</b>	A FOREIGN or NATIVE entry does not have a corresponding entry in the domain configuration (dmconfig) file.
-	<b>ACTION</b>	Verify that each FOREIGN and NATIVE entry in the gwiconfig file has a corresponding entry in the dmconfig file.
<b>1075:ERROR</b>	<b>Cannot alloc conv switch</b>	
-	<b>DESCRIPTION</b>	Creating a conversation switch in shared memory failed.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1076:ERROR</b>	<b>Cannot alloc wrap switch</b>	
-	<b>DESCRIPTION</b>	Creating a wrap switch in shared memory failed.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1077:ERROR</b>	<b>Couldn't load configuration</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software was unable to load the configuration.
-	<b>ACTION</b>	Verify the format of the gateway configuration file.
<b>1078:ERROR</b>	<b>No gateway defined in config file</b>	
-	<b>DESCRIPTION</b>	The gateway configuration file does not contain a gateway definition.
-	<b>ACTION</b>	Correct the gateway configuration file.
<b>1079:ERROR</b>	<b>Couldn't find &lt;text&gt; gateway (GWINAME) in NATIVE section</b>	
-	<b>DESCRIPTION</b>	The listed gateway was not found in the NATIVE section of the gateway configuration file.
-	<b>ACTION</b>	Correct the gateway configuration file.
<b>1080:ERROR</b>	<b>Couldn't find env var GWINAME. Cannot guess which gateway.</b>	

Error	Description	
-	<b>DESCRIPTION</b>	The gateway configuration file contains more than one gateway entry and the environment variable <code>GWINAME</code> is not set.
-	<b>ACTION</b>	Set the <code>GWINAME</code> environment variable.
<b>1081:ERROR</b>	<b>Couldn't find host name. Cannot guess gateway address.</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software detected an error while trying to get the name of the current host.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1082:ERROR</b>	<b>Service &lt;text&gt; is SECURE, Tuxedo security disabled</b>	
-	<b>DESCRIPTION</b>	The listed service requires security, but Tuxedo security is disabled.
-	<b>ACTION</b>	Either turn on Tuxedo security with the <code>SECURITY</code> resource, or remove the <code>SECURE</code> parameter from the gateway configuration file for this service.
<b>1083:ERROR</b>	<b>Network initialization fails; error code = &lt;number&gt;</b>	
-	<b>DESCRIPTION</b>	Initialization of the network protocol has failed.
-	<b>ACTION</b>	Verify that the underlying TCP product is installed and configured correctly.
<b>1084:ERROR</b>	<b>Universal callback setup fails; error code = &lt;number&gt;</b>	
-	<b>DESCRIPTION</b>	This is an internal error code, indicating a library setup failure.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1085:ERROR</b>	<b>Unable to register protocol; error code = &lt;number&gt;</b>	
-	<b>DESCRIPTION</b>	This is an internal error code, indicating a library setup failure.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1086:ERROR</b>	<b>Unable to set network device; error code = &lt;number&gt;</b>	
-	<b>DESCRIPTION</b>	The configured network device cannot be found.
-	<b>ACTION</b>	Verify that the <code>NWDEVICE</code> field in the <code>LOCAL</code> section of the <code>GWICONFIG</code> file is correct (usually <code>/dev/tcp</code> ).
<b>1087:ERROR</b>	<b>Can't get remote address</b>	
-	<b>DESCRIPTION</b>	Could not convert the remote internet address to a binary address.

Error	Description	
-	<b>ACTION</b>	Previous logged error messages should provide the exact reasons for the failure. Contact your Tuxedo System Technical Support.
<b>1088:INFO</b>	<b>Accepted new connection &lt;number&gt; from &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	A new connection from the remote gateway has been accepted.
-	<b>ACTION</b>	No action required.
<b>1089:ERROR</b>	<b>Poll returned error (num_cnx=&lt;number&gt;)</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software detected an error while polling the connection for events.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1090:ERROR</b>	<b>No free sessions available</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software was unable to allocate shared memory for a new session structure.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1091:ERROR</b>	<b>Unable to get new action: gpnd &lt;number&gt;</b>	
-	<b>DESCRIPTION</b>	This is an internal error, indicating that the Domain Gateway is unable to allocate a new action.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1092:ERROR</b>	<b>Invalid ses_idx &lt;number&gt; for act &lt;number&gt;</b>	
-	<b>DESCRIPTION</b>	The action structure references an invalid session index.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1093:ERROR</b>	<b>Unable to allocate a receive buffer</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway is unable to allocate memory for a receive buffer.
-	<b>ACTION</b>	Verify that system memory requirements are met. If problems persist, contact your Tuxedo System Technical Support.
<b>1094:WARN</b>	<b>Deleting late reply from local service '&lt;text&gt;'</b>	
-	<b>DESCRIPTION</b>	A late reply has arrived from a Tuxedo service. Because the request has already timed out, the reply is discarded.

Error	Description	
-	<b>ACTION</b>	No action is required. If an excessive number of timeouts occur, adjustments may be needed in the configuration.
<b>1097:ERROR</b>	<b>Error message from &lt;text&gt;:\n\tTuxedo code &lt;number&gt; (&lt;text&gt;):\n\t&lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	Received an error message from the remote gateway.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1098:WARN</b>	<b>Late response received for freed session &lt;number&gt;/&lt;number&gt;</b>	
-	<b>DESCRIPTION</b>	Received a response on a file descriptor which had timed out.
-	<b>ACTION</b>	No action required.
<b>1099:INFO</b>	<b>Stale message found</b>	
-	<b>DESCRIPTION</b>	Received a message on a session with no associated action.
-	<b>ACTION</b>	No action required.
<b>1100:ERROR</b>	<b>Data conversion failed for local request '&lt;text&gt;'</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software detected an error while trying to decode a message.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1101:ERROR</b>	<b>Unexpected diagnostic &lt;number&gt; returned from server</b>	
-	<b>DESCRIPTION</b>	An unexpected diagnostic flag was returned from the server.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1102:ERROR</b>	<b>Data conversion failed for local service '&lt;text&gt;'</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software detected an error while trying to encode a message.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1103:INFO</b>	<b>Connection &lt;number&gt; initialized from &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software received a connection request from the remote gateway.
-	<b>ACTION</b>	No action required
<b>1104:ERROR</b>	<b>Unable to identify local service, rname '&lt;text&gt;'</b>	
-	<b>DESCRIPTION</b>	The service requested by the listed remote service was not found in shared memory.
-	<b>ACTION</b>	Verify the DMCONFIG file and insure dmloadcf has been run on it.
<b>1105:ERROR</b>	<b>Unable to map local service RNAME &lt;text&gt;</b>	

Error	Description	
-	<b>DESCRIPTION</b>	The service requested by the listed service name was not found in shared memory.
-	<b>ACTION</b>	Verify the DMCONFIG file and insure dmloadcf has been run on it.
<b>1106:ERROR</b>	<b>Unable to identify user &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The listed user is not authorized for the requested service.
-	<b>ACTION</b>	Verify the tpusr file in APPDIR.
<b>1107:ERROR</b>	<b>Protocol error: server cannot use GWI_OP_DISCON</b>	
-	<b>DESCRIPTION</b>	A remote service is sending a disconnect.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1108:ERROR</b>	<b>Invalid opcode on receive</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software received an invalid opcode.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1110:INFO</b>	<b>Closing connection &lt;number&gt;</b>	
-	<b>DESCRIPTION</b>	The listed connection is being closed.
-	<b>ACTION</b>	No action required.
<b>1111:ERROR</b>	<b>gwi_mk_error called with bad act_idx!</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software detected that an error occurred between a send and receive. The connection closes.
-	<b>ACTION</b>	No action required.
<b>1112:ERROR</b>	<b>Too many unrecoverable errors occurred - deleting action</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software detected more than 2 errors while trying to complete the action.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1113:ERROR</b>	<b>Unrecoverable error occurred on send of reply request - deleting action</b>	
-	<b>DESCRIPTION</b>	Cannot send a reply to a call made with TPNOREPLY.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1114:ERROR</b>	<b>Local request '&lt;text&gt;' timed out, returning error response</b>	
-	<b>DESCRIPTION</b>	The request for the local service timed out.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1115:WARN</b>	<b>Deleting timed out session index %d for connection %d</b>	

Error	Description	
-	<b>DESCRIPTION</b>	The request for the local service timed out.
-	<b>ACTION</b>	No action required.
<b>1116:ERROR</b>	<b>Local request '&lt;text&gt;' failed, returning error response</b>	
-	<b>DESCRIPTION</b>	The request for the local service failed.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1117:ERROR</b>	<b>Error on receive from &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software detected an error when receiving a request from a remote gateway.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1118:ERROR</b>	<b>Unrecoverable error occurred on unknown receipt(2) - deleting action</b>	
-	<b>DESCRIPTION</b>	The current action has no associated session.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1119:ERROR</b>	<b>No FOREIGN entry for REMOTE_DOMAIN '&lt;text&gt;'</b>	
-	<b>DESCRIPTION</b>	There is no FOREIGN entry in the GWICONFIG file corresponding to the specified REMOTE_DOMAIN.
-	<b>ACTION</b>	Create a FOREIGN entry in the GWICONFIG file for each REMOTE_DOMAIN that is available through the gateway.
<b>1120:ERROR</b>	<b>Unrecoverable error occurred - deleting GWEV_MSG_FAILURE action (type &lt;number&gt;)</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software detected an unrecoverable error.
-	<b>ACTION</b>	Previous logged error messages should provide more information. Contact your Tuxedo System Technical Support.
<b>1121:ERROR</b>	<b>Unrecoverable error occurred - changing action (type &lt;number&gt;) into GWEV_MSG_FAILURE</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software detected an unrecoverable error.
-	<b>ACTION</b>	Previous logged error messages should provide more information. Contact your Tuxedo System Technical Support.
<b>1122:ERROR</b>	<b>Unrecoverable error occurred - deleting action (type &lt;number&gt;)</b>	



Error	Description	
-	<b>DESCRIPTION</b>	The Domain Gateway library software detected an unrecoverable error.
-	<b>ACTION</b>	Previous logged error messages should provide more information. Contact your Tuxedo System Technical Support.
<b>1123:INFO</b>	<b>Request id not found</b>	
-	<b>DESCRIPTION</b>	The action with the given request ID was not found in shared memory.
-	<b>ACTION</b>	No action required.
<b>1124:ERROR</b>	<b>convid not found</b>	
-	<b>DESCRIPTION</b>	The session with the given conversation ID was not found in shared memory.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1125:ERROR</b>	<b>Invalid network address &lt;&lt;text&gt;&gt;</b>	
-	<b>DESCRIPTION</b>	The given network address is not valid.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1126:ERROR</b>	<b>Invalid host name &lt;&lt;text&gt;&gt;</b>	
-	<b>DESCRIPTION</b>	Could not get the network address for the listed host.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1127:ERROR</b>	<b>Bad ip adress format &lt;&lt;text&gt;&gt;</b>	
-	<b>DESCRIPTION</b>	The format of the listed ip address is invalid.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1128:ERROR</b>	<b>Input string too long &lt;&lt;text&gt;&gt;</b>	
-	<b>DESCRIPTION</b>	The address is too long to fit in the memory allocated for it.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1129:ERROR</b>	<b>Timeout on local service &lt;text&gt;, returning error to &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software detected a timeout on the listed remote service.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1130:ERROR</b>	<b>Timeout on local service &lt;text&gt;, returning error to &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software detected a timeout on the listed local service.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.

Error	Description	
<b>1131:ERROR</b>	<b>Connect time-out on connection &lt;number&gt; to &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software detected a timeout while attempting to connect to the remote gateway.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1132:ERROR</b>	<b>Idle time-out on connection &lt;number&gt; to &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software detected a timeout on the listed connection to the remote gateway.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1133:ERROR</b>	<b>Parse error: &lt;text&gt; line &lt;number&gt; column &lt;number&gt; (after &lt;&lt;text&gt;&gt;) at &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The Domain Gateway library software encountered an error while parsing the gateway configuration file.
-	<b>ACTION</b>	Correct the gateway configuration file.
<b>1134:ERROR</b>	<b>No NWDEVICE specified</b>	
-	<b>DESCRIPTION</b>	There was no <code>NWDEVICE</code> specified in the gateway configuration file.
-	<b>ACTION</b>	Correct the gateway configuration file.
<b>1135:ERROR</b>	<b>NATIVE name &lt;text&gt; already in use</b>	
-	<b>DESCRIPTION</b>	The listed gateway name is specified more than once in the <code>NATIVE</code> section of the gateway configuration file.
-	<b>ACTION</b>	Correct the gateway configuration file.
<b>1136:WARN</b>	<b>Unreasonable POLL_TIME &lt;number&gt; ignored for NATIVE &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The gateway configuration file specifies a poll time which is less than 100,000 or greater than 10,000,000.
-	<b>ACTION</b>	No action required. The poll time is set to 250,000.
<b>1137:ERROR</b>	<b>REMOTE_SERVICE &lt;text&gt; has no OUTREQ_TIME, no default in GLOBAL</b>	
-	<b>DESCRIPTION</b>	The gateway configuration file does not have an <code>OUTREQ_TIME</code> specified for a remote service.
-	<b>ACTION</b>	Correct the gateway configuration file.
<b>1138:ERROR</b>	<b>FOREIGN name &lt;text&gt; already in use</b>	

Error	Description	
-	<b>DESCRIPTION</b>	The listed gateway name is specified more than once in the FOREIGN section of the gateway configuration file.
-	<b>ACTION</b>	Correct the gateway configuration file.
<b>1139:ERROR</b>	<b>Missing mandatory TYPE param for FOREIGN &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The gateway configuration file does not have a TYPE parameter for the listed gateway.
-	<b>ACTION</b>	Correct the gateway configuration file.
<b>1140:ERROR</b>	<b>Missing mandatory WRAP param for FOREIGN &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The gateway configuration file does not have a WRAP parameter for the listed gateway.
-	<b>ACTION</b>	Correct the gateway configuration file.
<b>1141:ERROR</b>	<b>Missing mandatory IP_ADDR param for FOREIGN &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The gateway configuration file does not have an IP_ADDR parameter for the listed gateway.
-	<b>ACTION</b>	Correct the gateway configuration file.
<b>1142:ERROR</b>	<b>LOCAL_SERVICE name &lt;text&gt; already in use</b>	
-	<b>DESCRIPTION</b>	The listed service name is specified more than once in the LOCAL_SERVICE section of the gateway configuration file.
-	<b>ACTION</b>	Correct the gateway configuration file.
<b>1145:ERROR</b>	<b>REMOTE_SERVICE name &lt;text&gt; already in use</b>	
-	<b>DESCRIPTION</b>	The listed service name is specified more than once in the REMOTE_SERVICE section of the gateway configuration file.
-	<b>ACTION</b>	Correct the gateway configuration file.
<b>1149:ERROR</b>	<b>Mandatory &lt;text&gt; section missing</b>	
-	<b>DESCRIPTION</b>	The gateway configuration file must contain the GLOBAL, FOREIGN, NATIVE, LOCAL_SERVICES, and REMOTE_SERVICES sections.
-	<b>ACTION</b>	Correct the gateway configuration file.
<b>1150:ERROR</b>	<b>Duplicate &lt;text&gt; section</b>	
-	<b>DESCRIPTION</b>	The gateway configuration file contains multiple entries for the listed section.

Error	Description	
-	<b>ACTION</b>	Correct the gateway configuration file.
<b>1151:ERROR</b>	<b>Section &lt;text&gt; out of order</b>	
-	<b>DESCRIPTION</b>	The listed section is not in the proper order in the gateway configuration file.
-	<b>ACTION</b>	Correct the gateway configuration file.
<b>1152:INFO</b>	<b>Section order must be *GLOBAL then *NATIVE/*FOREIGN then *LOCAL_SERVICES/*REMOTE_SERVICES</b>	
-	<b>DESCRIPTION</b>	The gateway configuration file must have the following order of sections: GLOBAL, NATIVE/FOREIGN LOCAL_SERVICES/REMOTE_SERVICES.
-	<b>ACTION</b>	No action required.
<b>1153:WARN</b>	<b>Bad subtype &lt;text&gt; truncated to &lt;number&gt; characters</b>	
-	<b>DESCRIPTION</b>	The gateway configuration file specifies a subtype name which is too long.
-	<b>ACTION</b>	Correct the gateway configuration file.
<b>1154:WARN</b>	<b>Bad type &lt;text&gt; truncated to &lt;number&gt; characters</b>	
-	<b>DESCRIPTION</b>	The gateway configuration file specifies a type name which is too long.
-	<b>ACTION</b>	Correct the gateway configuration file.
<b>1155:WARN</b>	<b>SECURE= accepts Y or N, not &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The gateway configuration file contains an invalid entry for the SECURE parameter.
-	<b>ACTION</b>	Correct the gateway configuration file.
<b>1156:</b>	<b>DSECURITY= accepts Y or N, not &lt;parameter&gt;</b>	
-	<b>DESCRIPTION</b>	The gateway configuration file contains an invalid entry for the DSECURITY parameter.
-	<b>ACTION</b>	Correct the gateway configuration file.
<b>1157:WARN</b>	<b>DUMP= accepts Y or N, not &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The gateway configuration file contains an invalid entry for the DUMP parameter.
-	<b>ACTION</b>	Correct the gateway configuration file.
<b>1158:WARN</b>	<b>CONNSYNC= accepts Y or N, not &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The gateway configuration file contains an invalid entry for the CONNSYNC parameter.

Error	Description	
-	<b>ACTION</b>	Correct the gateway configuration file.
<b>1159:WARN</b>	<b>CICS= accepts Y or N, not &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The gateway configuration file contains an invalid entry for the CICS parameter.
-	<b>ACTION</b>	Correct the gateway configuration file.
<b>1160:ERROR</b>	<b>Remove obsolete line in &lt;text&gt; : \"REPLY = &lt;text&gt;\"</b>	
-	<b>DESCRIPTION</b>	The gateway configuration file contains a REPLY parameter, which is obsolete.
-	<b>ACTION</b>	Remove the REPLY parameter from the gateway configuration file.
<b>1161:ERROR</b>	<b>CONV=Y, conversational mode not supported</b>	
-	<b>DESCRIPTION</b>	The gateway configuration file specifies CONV=Y for a local service. This is currently not supported.
-	<b>ACTION</b>	Correct the gateway configuration file.
<b>1162:WARN</b>	<b>CONV= accepts Y or N, not &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	The gateway configuration file contains an invalid entry for the CONV parameter.
-	<b>ACTION</b>	Correct the gateway configuration file.
<b>1163:ERROR</b>	<b>Bad unwrapping protocol</b>	
-	<b>DESCRIPTION</b>	The unwrapping protocol in shared memory is not GWI_PROTOCOL.
-	<b>ACTION</b>	Contact your Tuxedo System Technical Support.
<b>1164:INFO</b>	<b>External encode/decode enabled, type '&lt;text&gt;'</b>	
-	<b>DESCRIPTION</b>	The external encoding command line option has been specified on the gateway, with the given encoding type.
-	<b>ACTION</b>	None required.
<b>1165:ERROR</b>	<b>External encode/decode service returned error:\n\tTuxedo code &lt;number&gt; (&lt;text&gt;)</b>	
-	<b>DESCRIPTION</b>	An external encode or decode request has resulted in an error. The Tuxedo code and a descriptive message are supplied.
-	<b>ACTION</b>	Verify that the encode/decode service is running and that the DMCONFIG and GWICONFIG files are configured properly.

Error	Description	
<b>1166:ERROR</b>	<b>TCP-IP Listener Error Received: &lt;text&gt;</b>	
-	<b>DESCRIPTION</b>	An error has been reported by the TCP/IP listener on the remote system.
-	<b>ACTION</b>	Examine the logs on the remote system to determine the cause of the TCP/IP failure.
<b>1167:INFO</b>	<b>Mainframe buffer length checking disabled</b>	
-	<b>DESCRIPTION</b>	The gateway has been configured to allow copybook buffers from the remote host that are not as large as the desired VIEW buffer.
-	-	-
<b>1168:INFO</b>	<b>Mainframe padding disabled</b>	
-	<b>DESCRIPTION</b>	The gateway has been configured to not align copybook members sent to and received from the remote host.
-	-	-
<b>1169:INFO</b>	<b>Request logging enabled</b>	
-	<b>DESCRIPTION</b>	The gateway has been configured to log each request to standard error output.
-	-	-
<b>1170:INFO</b>	<b>CODPEPAGE '&lt;Code page name&gt;' for 'LOCAL' DOMAIN &lt;Domain name&gt;</b>	
-	<b>DESCRIPTION</b>	This displays the code page used by the Local Domain.
-	-	-
<b>1171:INFO</b>	<b>CODPEPAGE '&lt;Code page name&gt;' for 'LOCAL' DOMAIN &lt;Domain name&gt;</b>	
-	<b>DESCRIPTION</b>	This displays the code page used by the Remote Domain.
<b>1173:ERROR</b>	<b>Invalid network protocol value</b>	
-	<b>DESCRIPTION</b>	Invalid domain network protocol is used.
-	<b>ACTION</b>	Use correct network protocol value.
<b>1174: ERROR</b>	<b>SSL handshake failed, errno=%d</b>	
-	<b>DESCRIPTION</b>	The Gateway failed to shake hands with SSL peer.
-	<b>ACTION</b>	Contact Oracle Customer Support.
<b>1175: ERROR</b>	<b>Get SSL Data failed</b>	
-	<b>DESCRIPTION</b>	The Gateway failed to get SSL data.
-	<b>ACTION</b>	Contact Oracle Customer Support.
<b>1176:ERROR</b>	<b>Message Buffer Invalid</b>	

---

<b>Error</b>	<b>Description</b>	
-	<b>DESCRIPTION</b>	The Gateway failed to get message buffer.
-	<b>ACTION</b>	Contact Oracle Customer Support.

# 8

## Code Page Translation Tables

This document provides the code page translation tables distributed with the Oracle Tuxedo Mainframe Adapter for TCP Gateway (hereafter referenced as TMA TCP Gateway) product. The files containing these translation tables are located in `$TUXDIR/udataobj/codepage` on the product CDROM.

- [Modifying a Code Page Translation Table](#)
- [Default Tuxedo](#)
- [United States \(00819x00037\)](#)
- [Germany \(00819x00273\)](#)
- [Finland/Sweden \(00819x00278\)](#)
- [Spain \(00819x00284\)](#)
- [Great Britain \(00819x00285\)](#)
- [France \(00819x00297\)](#)
- [Belgium \(00819x00500\)](#)
- [Portugal \(00819x00860\)](#)
- [Latin-1 \(00819x01047\)](#)
- [Latin-2 \(00912x00870\)](#)

### 8.1 Modifying a Code Page Translation Table

The tables provide conversions between the ASCII Latin-1 character set and representative national language EBCDIC character sets. In most cases, you do not need to modify them. Simply choose the appropriate translation table for a selected language and enter its file name in the `CODEPAGE` specification, as explained in the [Using Code Page Translation Tables](#)

However, if you must modify a translation table, be aware of the following:

- You must have valid character mapping information. This information is available from a number of sources and is not provided in this documentation. A good source is the *IBM National Language Support Reference Manual*
- If you modify a character code in an outbound table, you must also modify its inbound counterpart.
- It is not recommended that you build tables from scratch.
- The tables have a common format that contains comment lines and required lines. The format must be maintained to ensure proper table operation. Comment lines begin with the `#` character.



 **Note:**

Do *not* alter the following required lines:

- `version (100)` specifies the format of the rest of the file.
- `table (256)` specifies the size of the table and the min/max number of bytes composing each character code.

To modify a table, perform the following steps.

1. With a text editor, open the file you want to modify. The following command opens the translation table file for Germany (00819x00273) in a text editor.  
`edit $TUXDIR/udataobj/codepage/00819x00273`
2. Using the editor functions, modify the character code in the outbound table.
3. Using the editor functions, modify the counterpart character code in the inbound table.
4. Repeat Steps 2 and 3 until you have completed the modifications.
5. Using the editor functions, save the file with a new name. Do not save the modified file using the original file name.  
**WARNING:** Do *not* save modifications to any of the original files provided with your product CDROM.
6. Exit the editor.
7. To use the file you modified for code page translations, make sure you specify its name using the `CODEPAGE` option in the `DM_REMOTE_DOMAINS` section of the gateway `DMCONFIG` file.

## 8.2 Default Tuxedo

### Listing B-1 Default Tuxedo Translation Table

```
#=====
# tuxedo
# Default Tuxedo ASCII/EBCDIC character translation tables.
#
# Local: "TUXEDO-ASCII"
# Remote: "TUXEDO-EBCDIC"
#-----

# Header
version 100;

# Outbound (local -> remote) table
table 256 1 1;
00 01 02 03 37 2D 2E 2F 16 05 25 0B 0C 0D 0E 0F # 00-0F
10 11 12 13 3C 3D 32 26 18 19 3F 27 1C 1D 1E 1F # 10-1F
40 5A 7F 7B 5B 6C 50 7D 4D 5D 5C 4E 6B 60 4B 61 # 20-2F
F0 F1 F2 F3 F4 F5 F6 F7 F8 F9 7A 5E 4C 7E 6E 6F # 30-3F
7C C1 C2 C3 C4 C5 C6 C7 C8 C9 D1 D2 D3 D4 D5 D6 # 40-4F
D7 D8 D9 E2 E3 E4 E5 E6 E7 E8 E9 AD E0 BD 5F 6D # 50-5F
79 81 82 83 84 85 86 87 88 89 91 92 93 94 95 96 # 60-6F
```

```

97 98 99 A2 A3 A4 A5 A6 A7 A8 A9 C0 6A D0 A1 07 # 70-7F
20 21 22 23 24 15 06 17 28 29 2A 2B 2C 09 0A 1B # 80-8F
30 31 1A 33 34 35 36 08 38 39 3A 3B 04 14 3E E1 # 90-9F
41 42 43 44 45 46 47 48 49 51 52 53 54 55 56 57 # A0-AF
58 59 62 63 64 65 66 67 68 69 70 71 72 73 74 75 # B0-BF
76 77 78 80 8A 8B 8C 8D 8E 8F 90 9A 9B 9C 9D 9E # C0-CF
9F A0 AA AB AC 4A AE AF B0 B1 B2 B3 B4 B5 B6 B7 # D0-DF
B8 B9 BA BB BC 4F BE BF CA CB CC CD CE CF DA DB # E0-EF
DC DD DE DF EA EB EC ED EE EF FA FB FC FD FE FF # F0-FF

```

```

# Inbound (remote -> local) table
table 256 1 1;
00 01 02 03 9C 09 86 7F 97 8D 8E 0B 0C 0D 0E 0F # 00-0F
10 11 12 13 9D 85 08 87 18 19 92 8F 1C 1D 1E 1F # 10-1F
80 81 82 83 84 0A 17 1B 88 89 8A 8B 8C 05 06 07 # 20-2F
90 91 16 93 94 95 96 04 98 99 9A 9B 14 15 9E 1A # 30-3F
20 A0 A1 A2 A3 A4 A5 A6 A7 A8 D5 2E 3C 28 2B E5 # 40-4F
26 A9 AA AB AC AD AE AF B0 B1 21 24 2A 29 3B 5E # 50-5F
2D 2F B2 B3 B4 B5 B6 B7 B8 B9 7C 2C 25 5F 3E 3F # 60-6F
BA BB BC BD BE BF C0 C1 C2 60 3A 23 40 27 3D 22 # 70-7F
C3 61 62 63 64 65 66 67 68 69 C4 C5 C6 C7 C8 C9 # 80-8F
CA 6A 6B 6C 6D 6E 6F 70 71 72 CB CC CD CE CF D0 # 90-9F
D1 7E 73 74 75 76 77 78 79 7A D2 D3 D4 5B D6 D7 # A0-AF
D8 D9 DA DB DC DD DE DF E0 E1 E2 E3 E4 5D E6 E7 # B0-BF
7B 41 42 43 44 45 46 47 48 49 E8 E9 EA EB EC ED # C0-CF
7D 4A 4B 4C 4D 4E 4F 50 51 52 EE EF F0 F1 F2 F3 # D0-DF
5C 9F 53 54 55 56 57 58 59 5A F4 F5 F6 F7 F8 F9 # E0-EF
30 31 32 33 34 35 36 37 38 39 FA FB FC FD FE FF # F0-FF

# End

```

## 8.3 United States (00819x00037)

### Listing B-2 Translation Table for United States

```

Listing B-2 Translation Table for United States
#=====
# 00819x00037
# Character code page mapping tables for US (USA).
#
# Local: "IBM-CP00819", ISO-8859-1 Latin-1
# Remote: "IBM-CP00037", EBCDIC Latin-1, US
#-----

# Header
version 100;

# Outbound (local -> remote) table
table 256 1 1;
00 01 02 03 37 2D 2E 2F 16 05 15 0B 0C 0D 0E 0F # 00-0F
10 11 12 13 3C 3D 32 26 18 19 3F 27 1C 1D 1E 1F # 10-1F
40 5A 7F 7B 5B 6C 50 7D 4D 5D 5C 4E 6B 60 4B 61 # 20-2F
F0 F1 F2 F3 F4 F5 F6 F7 F8 F9 7A 5E 4C 7E 6E 6F # 30-3F

```

```

7C C1 C2 C3 C4 C5 C6 C7 C8 C9 D1 D2 D3 D4 D5 D6 # 40-4F
D7 D8 D9 E2 E3 E4 E5 E6 E7 E8 E9 BA E0 BB B0 6D # 50-5F
79 81 82 83 84 85 86 87 88 89 91 92 93 94 95 96 # 60-6F
97 98 99 A2 A3 A4 A5 A6 A7 A8 A9 C0 4F D0 A1 07 # 70-7F
04 06 08 09 0A 14 17 1A 1B 20 21 22 23 24 25 28 # 80-8F
29 2A 2B 2C 30 31 33 34 35 36 38 39 3A 3B 3E FF # 90-9F
41 AA 4A B1 9F B2 6A B5 BD B4 9A 8A 5F CA AF BC # A0-AF
90 8F EA FA BE A0 B6 B3 9D DA 9B 8B B7 B8 B9 AB # B0-BF
64 65 62 66 63 67 9E 68 74 71 72 73 78 75 76 77 # C0-CF
AC 69 ED EE EB EF EC BF 80 FD FE FB FC AD AE 59 # D0-DF
44 45 42 46 43 47 9C 48 54 51 52 53 58 55 56 57 # E0-EF
8C 49 CD CE CB CF CC E1 70 DD DE DB DC 8D 8E DF # F0-FF

```

```

# Inbound (remote -> local) table
table 256 1 1;
00 01 02 03 80 09 81 7F 82 83 84 0B 0C 0D 0E 0F # 00-0F
10 11 12 13 85 0A 08 86 18 19 87 88 1C 1D 1E 1F # 10-1F
89 8A 8B 8C 8D 8E 17 1B 8F 90 91 92 93 05 06 07 # 20-2F
94 95 16 96 97 98 99 04 9A 9B 9C 9D 14 15 9E 1A # 30-3F
20 A0 E2 E4 E0 E1 E3 E5 E7 F1 A2 2E 3C 28 2B 7C # 40-4F
26 E9 EA EB E8 ED EE EF EC DF 21 24 2A 29 3B AC # 50-5F
2D 2F C2 C4 C0 C1 C3 C5 C7 D1 A6 2C 25 5F 3E 3F # 60-6F
F8 C9 CA CB C8 CD CE CF CC 60 3A 23 40 27 3D 22 # 70-7F
D8 61 62 63 64 65 66 67 68 69 AB BB F0 FD FE B1 # 80-8F
B0 6A 6B 6C 6D 6E 6F 70 71 72 AA BA E6 B8 C6 A4 # 90-9F
B5 7E 73 74 75 76 77 78 79 7A A1 BF D0 DD DE AE # A0-AF
5E A3 A5 B7 A9 A7 B6 BC BD BE 5B 5D AF A8 B4 D7 # B0-BF
7B 41 42 43 44 45 46 47 48 49 AD F4 F6 F2 F3 F5 # C0-CF
7D 4A 4B 4C 4D 4E 4F 50 51 52 B9 FB FC F9 FA FF # D0-DF
5C F7 53 54 55 56 57 58 59 5A B2 D4 D6 D2 D3 D5 # E0-EF
30 31 32 33 34 35 36 37 38 39 B3 DB DC D9 DA 9F # F0-FF

# End

```

## 8.4 Germany (00819x00273)

### Listing B-3 Translation Table for Germany

```

#=====
# 00819x00273
# Character code page mapping tables for Germany (Deutschland).
#
# Local: "IBM-CP00819", ISO-8859-1 Latin-1
# Remote: "IBM-CP00273", EBCDIC Latin-1, Germany
#-----

# Header
version 100;

# Outbound (local -> remote) table
table 256 1 1;
00 01 02 03 37 2D 2E 2F 16 05 15 0B 0C 0D 0E 0F # 00-0F
10 11 12 13 3C 3D 32 26 18 19 3F 27 1C 1D 1E 1F # 10-1F

```

```

40 4F 7F 7B 5B 6C 50 7D 4D 5D 5C 4E 6B 60 4B 61 # 20-2F
F0 F1 F2 F3 F4 F5 F6 F7 F8 F9 7A 5E 4C 7E 6E 6F # 30-3F
B5 C1 C2 C3 C4 C5 C6 C7 C8 C9 D1 D2 D3 D4 D5 D6 # 40-4F
D7 D8 D9 E2 E3 E4 E5 E6 E7 E8 E9 63 EC FC 5F 6D # 50-5F
79 81 82 83 84 85 86 87 88 89 91 92 93 94 95 96 # 60-6F
97 98 99 A2 A3 A4 A5 A6 A7 A8 A9 43 BB DC 59 07 # 70-7F
04 06 08 09 0A 14 17 1A 1B 20 21 22 23 24 25 28 # 80-8F
29 2A 2B 2C 30 31 33 34 35 36 38 39 3A 3B 3E FF # 90-9F
41 AA B0 B1 9F B2 CC 7C BD B4 9A 8A BA CA AF BC # A0-AF
90 8F EA FA BE A0 B6 B3 9D DA 9B 8B B7 B8 B9 AB # B0-BF
64 65 62 66 4A 67 9E 68 74 71 72 73 78 75 76 77 # C0-CF
AC 69 ED EE EB EF E0 BF 80 FD FE FB 5A AD AE A1 # D0-DF
44 45 42 46 C0 47 9C 48 54 51 52 53 58 55 56 57 # E0-EF
8C 49 CD CE CB CF 6A E1 70 DD DE DB D0 8D 8E DF # F0-FF

```

```

# Inbound (remote -> local) table
table 256 1 1;
00 01 02 03 80 09 81 7F 82 83 84 0B 0C 0D 0E 0F # 00-0F
10 11 12 13 85 0A 08 86 18 19 87 88 1C 1D 1E 1F # 10-1F
89 8A 8B 8C 8D 8E 17 1B 8F 90 91 92 93 05 06 07 # 20-2F
94 95 16 96 97 98 99 04 9A 9B 9C 9D 14 15 9E 1A # 30-3F
20 A0 E2 7B E0 E1 E3 E5 E7 F1 C4 2E 3C 28 2B 21 # 40-4F
26 E9 EA EB E8 ED EE EF EC 7E DC 24 2A 29 3B 5E # 50-5F
2D 2F C2 5B C0 C1 C3 C5 C7 D1 F6 2C 25 5F 3E 3F # 60-6F
F8 C9 CA CB C8 CD CE CF CC 60 3A 23 A7 27 3D 22 # 70-7F
D8 61 62 63 64 65 66 67 68 69 AB BB F0 FD FE B1 # 80-8F
B0 6A 6B 6C 6D 6E 6F 70 71 72 AA BA E6 B8 C6 A4 # 90-9F
B5 DF 73 74 75 76 77 78 79 7A A1 BF D0 DD DE AE # A0-AF
A2 A3 A5 B7 A9 40 B6 BC BD BE AC 7C AF A8 B4 D7 # B0-BF
E4 41 42 43 44 45 46 47 48 49 AD F4 A6 F2 F3 F5 # C0-CF
FC 4A 4B 4C 4D 4E 4F 50 51 52 B9 FB 7D F9 FA FF # D0-DF
D6 F7 53 54 55 56 57 58 59 5A B2 D4 5C D2 D3 D5 # E0-EF
30 31 32 33 34 35 36 37 38 39 B3 DB 5D D9 DA 9F # F0-FF

# End

```

## 8.5 Finland/Sweden (00819x00278)

### Listing B-4 Translation Table for Sweden/Finland

```

#=====
# 00819x00278
# Character code page mapping tables for Finland/Sweden.
#
# Local: "IBM-CP00819", ISO-8859-1 Latin-1
# Remote: "IBM-CP00278", EBCDIC Latin-1, Finland/Sweden
#-----

# Header
version 100;

# Outbound (local -> remote) table
table 256 1 1;

```

```

00 01 02 03 37 2D 2E 2F 16 05 15 0B 0C 0D 0E 0F # 00-0F
10 11 12 13 3C 3D 32 26 18 19 3F 27 1C 1D 1E 1F # 10-1F
40 4F 7F 63 67 6C 50 7D 4D 5D 5C 4E 6B 60 4B 61 # 20-2F
F0 F1 F2 F3 F4 F5 F6 F7 F8 F9 7A 5E 4C 7E 6E 6F # 30-3F
EC C1 C2 C3 C4 C5 C6 C7 C8 C9 D1 D2 D3 D4 D5 D6 # 40-4F
D7 D8 D9 E2 E3 E4 E5 E6 E7 E8 E9 B5 71 9F 5F 6D # 50-5F
51 81 82 83 84 85 86 87 88 89 91 92 93 94 95 96 # 60-6F
97 98 99 A2 A3 A4 A5 A6 A7 A8 A9 43 BB 47 DC 07 # 70-7F
04 06 08 09 0A 14 17 1A 1B 20 21 22 23 24 25 28 # 80-8F
29 2A 2B 2C 30 31 33 34 35 36 38 39 3A 3B 3E FF # 90-9F
41 AA B0 B1 5A B2 CC 4A BD B4 9A 8A BA CA AF BC # A0-AF
90 8F EA FA BE A0 B6 B3 9D DA 9B 8B B7 B8 B9 AB # B0-BF
64 65 62 66 7B 5B 9E 68 74 E0 72 73 78 75 76 77 # C0-CF
AC 69 ED EE EB EF 7C BF 80 FD FE FB FC AD AE 59 # D0-DF
44 45 42 46 C0 D0 9C 48 54 79 52 53 58 55 56 57 # E0-EF
8C 49 CD CE CB CF 6A E1 70 DD DE DB A1 8D 8E DF # F0-FF

```

```

# Inbound (remote -> local) table
table 256 1 1;
00 01 02 03 80 09 81 7F 82 83 84 0B 0C 0D 0E 0F # 00-0F
10 11 12 13 85 0A 08 86 18 19 87 88 1C 1D 1E 1F # 10-1F
89 8A 8B 8C 8D 8E 17 1B 8F 90 91 92 93 05 06 07 # 20-2F
94 95 16 96 97 98 99 04 9A 9B 9C 9D 14 15 9E 1A # 30-3F
20 A0 E2 7B E0 E1 E3 7D E7 F1 A7 2E 3C 28 2B 21 # 40-4F
26 60 EA EB E8 ED EE EF EC DF A4 C5 2A 29 3B 5E # 50-5F
2D 2F C2 23 C0 C1 C3 24 C7 D1 F6 2C 25 5F 3E 3F # 60-6F
F8 5C CA CB C8 CD CE CF CC E9 3A C4 D6 27 3D 22 # 70-7F
D8 61 62 63 64 65 66 67 68 69 AB BB F0 FD FE B1 # 80-8F
B0 6A 6B 6C 6D 6E 6F 70 71 72 AA BA E6 B8 C6 5D # 90-9F
B5 FC 73 74 75 76 77 78 79 7A A1 BF D0 DD DE AE # A0-AF
A2 A3 A5 B7 A9 5B B6 BC BD BE AC 7C AF A8 B4 D7 # B0-BF
E4 41 42 43 44 45 46 47 48 49 AD F4 A6 F2 F3 F5 # C0-CF
E5 4A 4B 4C 4D 4E 4F 50 51 52 B9 FB 7E F9 FA FF # D0-DF
C9 F7 53 54 55 56 57 58 59 5A B2 D4 40 D2 D3 D5 # E0-EF
30 31 32 33 34 35 36 37 38 39 B3 DB DC D9 DA 9F # F0-FF

# End

```

## 8.6 Spain (00819x00284)

### Listing B-5 Translation Table for Spain

```

#=====
# 00819x00284
# Character code page mapping tables for Spain (España).
#
# Local: "IBM-CP00819", ISO-8859-1 Latin-1
# Remote: "IBM-CP00284", EBCDIC Latin-1, Spain
#-----

# Header
version 100;

```

```
# Outbound (local -> remote) table
table 256 1 1;
00 01 02 03 37 2D 2E 2F 16 05 15 0B 0C 0D 0E 0F # 00-0F
10 11 12 13 3C 3D 32 26 18 19 3F 27 1C 1D 1E 1F # 10-1F
40 BB 7F 69 5B 6C 50 7D 4D 5D 5C 4E 6B 60 4B 61 # 20-2F
F0 F1 F2 F3 F4 F5 F6 F7 F8 F9 7A 5E 4C 7E 6E 6F # 30-3F
7C C1 C2 C3 C4 C5 C6 C7 C8 C9 D1 D2 D3 D4 D5 D6 # 40-4F
D7 D8 D9 E2 E3 E4 E5 E6 E7 E8 E9 4A E0 5A BA 6D # 50-5F
79 81 82 83 84 85 86 87 88 89 91 92 93 94 95 96 # 60-6F
97 98 99 A2 A3 A4 A5 A6 A7 A8 A9 C0 4F D0 BD 07 # 70-7F
04 06 08 09 0A 14 17 1A 1B 20 21 22 23 24 25 28 # 80-8F
29 2A 2B 2C 30 31 33 34 35 36 38 39 3A 3B 3E FF # 90-9F
41 AA B0 B1 9F B2 49 B5 A1 B4 9A 8A 5F CA AF BC # A0-AF
90 8F EA FA BE A0 B6 B3 9D DA 9B 8B B7 B8 B9 AB # B0-BF
64 65 62 66 63 67 9E 68 74 71 72 73 78 75 76 77 # C0-CF
AC 7B ED EE EB EF EC BF 80 FD FE FB FC AD AE 59 # D0-DF
44 45 42 46 43 47 9C 48 54 51 52 53 58 55 56 57 # E0-EF
8C 6A CD CE CB CF CC E1 70 DD DE DB DC 8D 8E DF # F0-FF

# Inbound (remote -> local) table
table 256 1 1;
00 01 02 03 80 09 81 7F 82 83 84 0B 0C 0D 0E 0F # 00-0F
10 11 12 13 85 0A 08 86 18 19 87 88 1C 1D 1E 1F # 10-1F
89 8A 8B 8C 8D 8E 17 1B 8F 90 91 92 93 05 06 07 # 20-2F
94 95 16 96 97 98 99 04 9A 9B 9C 9D 14 15 9E 1A # 30-3F
20 A0 E2 E4 E0 E1 E3 E5 E7 A6 5B 2E 3C 28 2B 7C # 40-4F
26 E9 EA EB E8 ED EE EF EC DF 5D 24 2A 29 3B AC # 50-5F
2D 2F C2 C4 C0 C1 C3 C5 C7 23 F1 2C 25 5F 3E 3F # 60-6F
F8 C9 CA CB C8 CD CE CF CC 60 3A D1 40 27 3D 22 # 70-7F
D8 61 62 63 64 65 66 67 68 69 AB BB F0 FD FE B1 # 80-8F
B0 6A 6B 6C 6D 6E 6F 70 71 72 AA BA E6 B8 C6 A4 # 90-9F
B5 A8 73 74 75 76 77 78 79 7A A1 BF D0 DD DE AE # A0-AF
A2 A3 A5 B7 A9 A7 B6 BC BD BE 5E 21 AF 7E B4 D7 # B0-BF
7B 41 42 43 44 45 46 47 48 49 AD F4 F6 F2 F3 F5 # C0-CF
7D 4A 4B 4C 4D 4E 4F 50 51 52 B9 FB FC F9 FA FF # D0-DF
5C F7 53 54 55 56 57 58 59 5A B2 D4 D6 D2 D3 D5 # E0-EF
30 31 32 33 34 35 36 37 38 39 B3 DB DC D9 DA 9F # F0-FF

# End
```

## 8.7 Great Britain (00819x00285)

### Listing B-6 Translation Table for Great Britain

```
#####
# 00819x00285
# Character code page mapping tables for Great Britain (UK).
#
# Local: "IBM-CP00819", ISO-8859-1 Latin-1
# Remote: "IBM-CP00285", EBCDIC Latin-1, UK
#-----
# Header
```

```

version 100;

# Outbound (local -> remote) table
table 256 1 1;
00 01 02 03 37 2D 2E 2F 16 05 15 0B 0C 0D 0E 0F # 00-0F
10 11 12 13 3C 3D 32 26 18 19 3F 27 1C 1D 1E 1F # 10-1F
40 5A 7F 7B 4A 6C 50 7D 4D 5D 5C 4E 6B 60 4B 61 # 20-2F
F0 F1 F2 F3 F4 F5 F6 F7 F8 F9 7A 5E 4C 7E 6E 6F # 30-3F
7C C1 C2 C3 C4 C5 C6 C7 C8 C9 D1 D2 D3 D4 D5 D6 # 40-4F
D7 D8 D9 E2 E3 E4 E5 E6 E7 E8 E9 B1 E0 BB BA 6D # 50-5F
79 81 82 83 84 85 86 87 88 89 91 92 93 94 95 96 # 60-6F
97 98 99 A2 A3 A4 A5 A6 A7 A8 A9 C0 4F D0 BC 07 # 70-7F
04 06 08 09 0A 14 17 1A 1B 20 21 22 23 24 25 28 # 80-8F
29 2A 2B 2C 30 31 33 34 35 36 38 39 3A 3B 3E FF # 90-9F
41 AA B0 5B 9F B2 6A B5 BD B4 9A 8A 5F CA AF A1 # A0-AF
90 8F EA FA BE A0 B6 B3 9D DA 9B 8B B7 B8 B9 AB # B0-BF
64 65 62 66 63 67 9E 68 74 71 72 73 78 75 76 77 # C0-CF
AC 69 ED EE EB EF EC BF 80 FD FE FB FC AD AE 59 # D0-DF
44 45 42 46 43 47 9C 48 54 51 52 53 58 55 56 57 # E0-EF
8C 49 CD CE CB CF CC E1 70 DD DE DB DC 8D 8E DF # F0-FF

# Inbound (remote -> local) table
table 256 1 1;
00 01 02 03 80 09 81 7F 82 83 84 0B 0C 0D 0E 0F # 00-0F
10 11 12 13 85 0A 08 86 18 19 87 88 1C 1D 1E 1F # 10-1F
89 8A 8B 8C 8D 8E 17 1B 8F 90 91 92 93 05 06 07 # 20-2F
94 95 16 96 97 98 99 04 9A 9B 9C 9D 14 15 9E 1A # 30-3F
20 A0 E2 E4 E0 E1 E3 E5 E7 F1 24 2E 3C 28 2B 7C # 40-4F
26 E9 EA EB E8 ED EE EF EC DF 21 A3 2A 29 3B AC # 50-5F
2D 2F C2 C4 C0 C1 C3 C5 C7 D1 A6 2C 25 5F 3E 3F # 60-6F
F8 C9 CA CB C8 CD CE CF CC 60 3A 23 40 27 3D 22 # 70-7F
D8 61 62 63 64 65 66 67 68 69 AB BB F0 FD FE B1 # 80-8F
B0 6A 6B 6C 6D 6E 6F 70 71 72 AA BA E6 B8 C6 A4 # 90-9F
B5 AF 73 74 75 76 77 78 79 7A A1 BF D0 DD DE AE # A0-AF
A2 5B A5 B7 A9 A7 B6 BC BD BE 5E 5D 7E A8 B4 D7 # B0-BF
7B 41 42 43 44 45 46 47 48 49 AD F4 F6 F2 F3 F5 # C0-CF
7D 4A 4B 4C 4D 4E 4F 50 51 52 B9 FB FC F9 FA FF # D0-DF
5C F7 53 54 55 56 57 58 59 5A B2 D4 D6 D2 D3 D5 # E0-EF
30 31 32 33 34 35 36 37 38 39 B3 DB DC D9 DA 9F # F0-FF

# End

```

## 8.8 France (00819x00297)

### Listing B-7 Translation Table for France

```

#=====
# 00819x00297
# Character code page mapping tables for France.
#
# Local: "IBM-CP00819", ISO-8859-1 Latin-1
# Remote: "IBM-CP00297", EBCDIC Latin-1, France
#-----

```

```

# Header
version 100;

# Outbound (local -> remote) table
table 256 1 1;
00 01 02 03 37 2D 2E 2F 16 05 15 0B 0C 0D 0E 0F # 00-0F
10 11 12 13 3C 3D 32 26 18 19 3F 27 1C 1D 1E 1F # 10-1F
40 4F 7F B1 5B 6C 50 7D 4D 5D 5C 4E 6B 60 4B 61 # 20-2F
F0 F1 F2 F3 F4 F5 F6 F7 F8 F9 7A 5E 4C 7E 6E 6F # 30-3F
44 C1 C2 C3 C4 C5 C6 C7 C8 C9 D1 D2 D3 D4 D5 D6 # 40-4F
D7 D8 D9 E2 E3 E4 E5 E6 E7 E8 E9 90 48 B5 5F 6D # 50-5F
A0 81 82 83 84 85 86 87 88 89 91 92 93 94 95 96 # 60-6F
97 98 99 A2 A3 A4 A5 A6 A7 A8 A9 51 BB 54 BD 07 # 70-7F
04 06 08 09 0A 14 17 1A 1B 20 21 22 23 24 25 28 # 80-8F
29 2A 2B 2C 30 31 33 34 35 36 38 39 3A 3B 3E FF # 90-9F
41 AA B0 7B 9F B2 DD 5A A1 B4 9A 8A BA CA AF BC # A0-AF
4A 8F EA FA BE 79 B6 B3 9D DA 9B 8B B7 B8 B9 AB # B0-BF
64 65 62 66 63 67 9E 68 74 71 72 73 78 75 76 77 # C0-CF
AC 69 ED EE EB EF EC BF 80 FD FE FB FC AD AE 59 # D0-DF
7C 45 42 46 43 47 9C E0 D0 C0 52 53 58 55 56 57 # E0-EF
8C 49 CD CE CB CF CC E1 70 6A DE DB DC 8D 8E DF # F0-FF

# Inbound (remote -> local) table
table 256 1 1;
00 01 02 03 80 09 81 7F 82 83 84 0B 0C 0D 0E 0F # 00-0F
10 11 12 13 85 0A 08 86 18 19 87 88 1C 1D 1E 1F # 10-1F
89 8A 8B 8C 8D 8E 17 1B 8F 90 91 92 93 05 06 07 # 20-2F
94 95 16 96 97 98 99 04 9A 9B 9C 9D 14 15 9E 1A # 30-3F
20 A0 E2 E4 40 E1 E3 E5 5C F1 B0 2E 3C 28 2B 21 # 40-4F
26 7B EA EB 7D ED EE EF EC DF A7 24 2A 29 3B 5E # 50-5F
2D 2F C2 C4 C0 C1 C3 C5 C7 D1 F9 2C 25 5F 3E 3F # 60-6F
F8 C9 CA CB C8 CD CE CF CC B5 3A A3 E0 27 3D 22 # 70-7F
D8 61 62 63 64 65 66 67 68 69 AB BB F0 FD FE B1 # 80-8F
5B 6A 6B 6C 6D 6E 6F 70 71 72 AA BA E6 B8 C6 A4 # 90-9F
60 A8 73 74 75 76 77 78 79 7A A1 BF D0 DD DE AE # A0-AF
A2 23 A5 B7 A9 5D B6 BC BD BE AC 7C AF 7E B4 D7 # B0-BF
E9 41 42 43 44 45 46 47 48 49 AD F4 F6 F2 F3 F5 # C0-CF
E8 4A 4B 4C 4D 4E 4F 50 51 52 B9 FB FC A6 FA FF # D0-DF
E7 F7 53 54 55 56 57 58 59 5A B2 D4 D6 D2 D3 D5 # E0-EF
30 31 32 33 34 35 36 37 38 39 B3 DB DC D9 DA 9F # F0-FF

# End

```

## 8.9 Belgium (00819x00500)

### Listing B-8 Translation Table for Belgium

```

#=====
# 00819x00500
# Character code page mapping tables for Belgium (Belgique).
#
# Local: "IBM-CP00819", ISO-8859-1 Latin-1

```



```
# Remote: "IBM-CP00500", EBCDIC Latin-1, Belgium
#-----

# Header
version 100;

# Outbound (local -> remote) table
table 256 1 1;
00 01 02 03 37 2D 2E 2F 16 05 15 0B 0C 0D 0E 0F # 00-0F
10 11 12 13 3C 3D 32 26 18 19 3F 27 1C 1D 1E 1F # 10-1F
40 4F 7F 7B 5B 6C 50 7D 4D 5D 5C 4E 6B 60 4B 61 # 20-2F
F0 F1 F2 F3 F4 F5 F6 F7 F8 F9 7A 5E 4C 7E 6E 6F # 30-3F
7C C1 C2 C3 C4 C5 C6 C7 C8 C9 D1 D2 D3 D4 D5 D6 # 40-4F
D7 D8 D9 E2 E3 E4 E5 E6 E7 E8 E9 4A E0 5A 5F 6D # 50-5F
79 81 82 83 84 85 86 87 88 89 91 92 93 94 95 96 # 60-6F
97 98 99 A2 A3 A4 A5 A6 A7 A8 A9 C0 BB D0 A1 07 # 70-7F
04 06 08 09 0A 14 17 1A 1B 20 21 22 23 24 25 28 # 80-8F
29 2A 2B 2C 30 31 33 34 35 36 38 39 3A 3B 3E FF # 90-9F
41 AA B0 B1 9F B2 6A B5 BD B4 9A 8A BA CA AF BC # A0-AF
90 8F EA FA BE A0 B6 B3 9D DA 9B 8B B7 B8 B9 AB # B0-BF
64 65 62 66 63 67 9E 68 74 71 72 73 78 75 76 77 # C0-CF
AC 69 ED EE EB EF EC BF 80 FD FE FB FC AD AE 59 # D0-DF
44 45 42 46 43 47 9C 48 54 51 52 53 58 55 56 57 # E0-EF
8C 49 CD CE CB CF CC E1 70 DD DE DB DC 8D 8E DF # F0-FF

# Inbound (remote -> local) table
table 256 1 1;
00 01 02 03 80 09 81 7F 82 83 84 0B 0C 0D 0E 0F # 00-0F
10 11 12 13 85 0A 08 86 18 19 87 88 1C 1D 1E 1F # 10-1F
89 8A 8B 8C 8D 8E 17 1B 8F 90 91 92 93 05 06 07 # 20-2F
94 95 16 96 97 98 99 04 9A 9B 9C 9D 14 15 9E 1A # 30-3F
20 A0 E2 E4 E0 E1 E3 E5 E7 F1 5B 2E 3C 28 2B 21 # 40-4F
26 E9 EA EB E8 ED EE EF EC DF 5D 24 2A 29 3B 5E # 50-5F
2D 2F C2 C4 C0 C1 C3 C5 C7 D1 A6 2C 25 5F 3E 3F # 60-6F
F8 C9 CA CB C8 CD CE CF CC 60 3A 23 40 27 3D 22 # 70-7F
D8 61 62 63 64 65 66 67 68 69 AB BB F0 FD FE B1 # 80-8F
B0 6A 6B 6C 6D 6E 6F 70 71 72 AA BA E6 B8 C6 A4 # 90-9F
B5 7E 73 74 75 76 77 78 79 7A A1 BF D0 DD DE AE # A0-AF
A2 A3 A5 B7 A9 A7 B6 BC BD BE AC 7C AF A8 B4 D7 # B0-BF
7B 41 42 43 44 45 46 47 48 49 AD F4 F6 F2 F3 F5 # C0-CF
7D 4A 4B 4C 4D 4E 4F 50 51 52 B9 FB FC F9 FA FF # D0-DF
5C F7 53 54 55 56 57 58 59 5A B2 D4 D6 D2 D3 D5 # E0-EF
30 31 32 33 34 35 36 37 38 39 B3 DB DC D9 DA 9F # F0-FF

# End
```

## 8.10 Portugal (00819x00860)

### Listing B-9 Translation Table for Portugal

```
#####
# 00819x00860
# Character code page mapping tables for Portugal.
```

```

#
# Local: "IBM-CP00819", ISO-8859-1 Latin-1
# Remote: "IBM-CP00860", ASCII IBM-PC graphics, Portugal
#
# Caveats
# The mapping between the two code pages is inexact, because some
# characters do not exist in both code sets.
#-----

# Header
version 100;

# Outbound (local -> remote) table
table 256 1 1;
00 01 02 03 04 05 06 07 08 09 0A 0B 0C 0D 0E 0F # 00-0F
10 11 12 13 9E B0 16 17 18 19 1A 1B 1C 1D 1E 1F # 10-1F
20 21 22 23 24 25 26 27 28 29 2A 2B 2C 2D 2E 2F # 20-2F
30 31 32 33 34 35 36 37 38 39 3A 3B 3C 3D 3E 3F # 30-3F
40 41 42 43 44 45 46 47 48 49 4A 4B 4C 4D 4E 4F # 40-4F
50 51 52 53 54 55 56 57 58 59 5A 5B 5C 5D 5E 5F # 50-5F
60 61 62 63 64 65 66 67 68 69 6A 6B 6C 6D 6E 6F # 60-6F
70 71 72 73 74 75 76 77 78 79 7A 7B 7C 7D 7E 7F # 70-7F
B1 B2 B3 B4 B5 B6 B7 B8 B9 BA BB BC BD BE BF C0 # 80-8F
C1 C2 C3 C4 C5 C6 C7 C8 C9 CA CB CC CD CE CF D0 # 90-9F
FF AD 9B 9C D1 D2 D3 15 D4 D5 A6 AE AA D6 D7 D8 # A0-AF
F8 F1 FD D9 DA E6 14 FA DB DC A7 AF AC AB DD A8 # B0-BF
91 86 8F 8E DE DF E0 80 92 90 89 E2 98 8B E3 E4 # C0-CF
E5 A5 A9 9F 8C 99 E7 E9 E8 9D 96 EA 9A EC EE E1 # D0-DF
85 A0 83 84 EF F0 F2 87 8A 82 88 F3 8D A1 F4 F5 # E0-EF
EB A4 95 A2 93 94 F7 F6 ED 97 A3 F9 81 FB FC FE # F0-FF

# Inbound (remote -> local) table
table 256 1 1;
00 01 02 03 04 05 06 07 08 09 0A 0B 0C 0D 0E 0F # 00-0F
10 11 12 13 B6 A7 16 17 18 19 1A 1B 1C 1D 1E 1F # 10-1F
20 21 22 23 24 25 26 27 28 29 2A 2B 2C 2D 2E 2F # 20-2F
30 31 32 33 34 35 36 37 38 39 3A 3B 3C 3D 3E 3F # 30-3F
40 41 42 43 44 45 46 47 48 49 4A 4B 4C 4D 4E 4F # 40-4F
50 51 52 53 54 55 56 57 58 59 5A 5B 5C 5D 5E 5F # 50-5F
60 61 62 63 64 65 66 67 68 69 6A 6B 6C 6D 6E 6F # 60-6F
70 71 72 73 74 75 76 77 78 79 7A 7B 7C 7D 7E 7F # 70-7F
C7 FC E9 E2 E3 E0 C1 E7 EA CA E8 CD D4 EC C3 C2 # 80-8F
C9 C0 C8 F4 F5 F2 DA F9 CC D5 DC A2 A3 D9 14 D3 # 90-9F
E1 ED F3 FA F1 D1 AA BA BF D2 AC BD BC A1 AB BB # A0-AF
15 80 81 82 83 84 85 86 87 88 89 8A 8B 8C 8D 8E # B0-BF
8F 90 91 92 93 94 95 96 97 98 99 9A 9B 9C 9D 9E # C0-CF
9F A4 A5 A6 A8 A9 AD AE AF B3 B4 B8 B9 BE C4 C5 # D0-DF
C6 DF CB CE CF D0 B5 D6 D8 D7 DB F0 DD F8 DE E4 # E0-EF
E5 B1 E6 EB EE EF F7 F6 B0 FB B7 FD FE B2 FF A0 # F0-FF

# End

```

## 8.11 Latin-1 (00819x01047)

### Listing B-10 Latin-1 Translation Table

```
#####
# 00819x01047
# Character code page mapping tables.
#
# Local: "IBM-CP00819", ISO-8859-1 Latin-1
# Remote: "IBM-CP01047", EBCDIC Latin-1
#-----

# Header
version 100;

# Outbound (local -> remote) table
table 256 1 1;
00 01 02 03 37 2D 2E 2F 16 05 15 0B 0C 0D 0E 0F # 00-0F
10 11 12 13 3C 3D 32 26 18 19 3F 27 1C 1D 1E 1F # 10-1F
40 5A 7F 7B 5B 6C 50 7D 4D 5D 5C 4E 6B 60 4B 61 # 20-2F
F0 F1 F2 F3 F4 F5 F6 F7 F8 F9 7A 5E 4C 7E 6E 6F # 30-3F
7C C1 C2 C3 C4 C5 C6 C7 C8 C9 D1 D2 D3 D4 D5 D6 # 40-4F
D7 D8 D9 E2 E3 E4 E5 E6 E7 E8 E9 AD E0 BD 5F 6D # 50-5F
79 81 82 83 84 85 86 87 88 89 91 92 93 94 95 96 # 60-6F
97 98 99 A2 A3 A4 A5 A6 A7 A8 A9 C0 4F D0 A1 07 # 70-7F
04 06 08 09 0A 14 17 1A 1B 20 21 22 23 24 25 28 # 80-8F
29 2A 2B 2C 30 31 33 34 35 36 38 39 3A 3B 3E FF # 90-9F
41 AA 4A B1 9F B2 6A B5 BB B4 9A 8A B0 CA AF BC # A0-AF
90 8F EA FA BE A0 B6 B3 9D DA 9B 8B B7 B8 B9 AB # B0-BF
64 65 62 66 63 67 9E 68 74 71 72 73 78 75 76 77 # C0-CF
AC 69 ED EE EB EF EC BF 80 FD FE FB FC BA AE 59 # D0-DF
44 45 42 46 43 47 9C 48 54 51 52 53 58 55 56 57 # E0-EF
8C 49 CD CE CB CF CC E1 70 DD DE DB DC 8D 8E DF # F0-FF

# Inbound (remote -> local) table
table 256 1 1;
00 01 02 03 80 09 81 7F 82 83 84 0B 0C 0D 0E 0F # 00-0F
10 11 12 13 85 0A 08 86 18 19 87 88 1C 1D 1E 1F # 10-1F
89 8A 8B 8C 8D 8E 17 1B 8F 90 91 92 93 05 06 07 # 20-2F
94 95 16 96 97 98 99 04 9A 9B 9C 9D 14 15 9E 1A # 30-3F
20 A0 E2 E4 E0 E1 E3 E5 E7 F1 A2 2E 3C 28 2B 7C # 40-4F
26 E9 EA EB E8 ED EE EF EC DF 21 24 2A 29 3B 5E # 50-5F
2D 2F C2 C4 C0 C1 C3 C5 C7 D1 A6 2C 25 5F 3E 3F # 60-6F
F8 C9 CA CB C8 CD CE CF CC 60 3A 23 40 27 3D 22 # 70-7F
D8 61 62 63 64 65 66 67 68 69 AB BB F0 FD FE B1 # 80-8F
B0 6A 6B 6C 6D 6E 6F 70 71 72 AA BA E6 B8 C6 A4 # 90-9F
B5 7E 73 74 75 76 77 78 79 7A A1 BF D0 5B DE AE # A0-AF
AC A3 A5 B7 A9 A7 B6 BC BD BE DD A8 AF 5D B4 D7 # B0-BF
7B 41 42 43 44 45 46 47 48 49 AD F4 F6 F2 F3 F5 # C0-CF
7D 4A 4B 4C 4D 4E 4F 50 51 52 B9 FB FC F9 FA FF # D0-DF
5C F7 53 54 55 56 57 58 59 5A B2 D4 D6 D2 D3 D5 # E0-EF
30 31 32 33 34 35 36 37 38 39 B3 DB DC D9 DA 9F # F0-FF
```

```
# End
```

## 8.12 Latin-2 (00912x00870)

### Listing B-11 Latin-2 Translation Table

```
#####
# 00912x00870
# Character code page mapping tables for Latin-2 character sets.
#
# Local: "IBM-CP00912", ISO-8859-2 Latin-2
# Remote: "IBM-CP00870", EBCDIC Latin-2
# -----

# Header
version 100;

# Outbound (local -> remote) table
table 256 1 1;
00 01 02 03 37 2D 2E 2F 16 05 15 0B 0C 0D 0E 0F # 00-0F
10 11 12 13 3C 3D 32 26 18 19 3F 27 1C 1D 1E 1F # 10-1F
40 4F 7F 7B 5B 6C 50 7D 4D 5D 5C 4E 6B 60 4B 61 # 20-2F
F0 F1 F2 F3 F4 F5 F6 F7 F8 F9 7A 5E 4C 7E 6E 6F # 30-3F
7C C1 C2 C3 C4 C5 C6 C7 C8 C9 D1 D2 D3 D4 D5 D6 # 40-4F
D7 D8 D9 E2 E3 E4 E5 E6 E7 E8 E9 4A E0 5A 5F 6D # 50-5F
79 81 82 83 84 85 86 87 88 89 91 92 93 94 95 96 # 60-6F
97 98 99 A2 A3 A4 A5 A6 A7 A8 A9 C0 6A D0 A1 07 # 70-7F
04 06 08 09 0A 14 17 1A 1B 20 21 22 23 24 25 28 # 80-8F
29 2A 2B 2C 30 31 33 34 35 36 38 39 3A 3B 3E FF # 90-9F
41 B1 80 BA 9F 77 AA B5 BD BC AF FD B9 CA B8 B4 # A0-AF
90 A0 9E 9A BE 57 8A 70 9D 9C 8F DD B7 64 B6 B2 # B0-BF
ED 65 62 66 63 78 69 68 67 71 72 73 DA 75 76 FA # C0-CF
AC BB AB EE EB EF EC BF AE 74 FE FB FC AD B3 59 # D0-DF
CD 45 42 46 43 58 49 48 47 51 52 53 DF 55 56 EA # E0-EF
8C 9B 8B CE CB CF CC E1 8E 54 DE DB DC 8D 44 B0 # F0-FF

# Inbound (remote -> local) table
table 256 1 1;
00 01 02 03 80 09 81 7F 82 83 84 0B 0C 0D 0E 0F # 00-0F
10 11 12 13 85 0A 08 86 18 19 87 88 1C 1D 1E 1F # 10-1F
89 8A 8B 8C 8D 8E 17 1B 8F 90 91 92 93 05 06 07 # 20-2F
94 95 16 96 97 98 99 04 9A 9B 9C 9D 14 15 9E 1A # 30-3F
20 A0 E2 E4 FE E1 E3 E8 E7 E6 5B 2E 3C 28 2B 21 # 40-4F
26 E9 EA EB F9 ED EE B5 E5 DF 5D 24 2A 29 3B 5E # 50-5F
2D 2F C2 C4 BD C1 C3 C8 C7 C6 7C 2C 25 5F 3E 3F # 60-6F
B7 C9 CA CB D9 CD CE A5 C5 60 3A 23 40 27 3D 22 # 70-7F
A2 61 62 63 64 65 66 67 68 69 B6 F2 F0 FD F8 BA # 80-8F
B0 6A 6B 6C 6D 6E 6F 70 71 72 B3 F1 B9 B8 B2 A4 # 90-9F
B1 7E 73 74 75 76 77 78 79 7A A6 D2 D0 DD D8 AA # A0-AF
FF A1 BF DE AF A7 BE BC AE AC A3 D1 A9 A8 B4 D7 # B0-BF
7B 41 42 43 44 45 46 47 48 49 AD F4 F6 E0 F3 F5 # C0-CF
7D 4A 4B 4C 4D 4E 4F 50 51 52 CC FB FC BB FA EC # D0-DF
```

```
5C F7 53 54 55 56 57 58 59 5A EF D4 D6 C0 D3 D5 # E0-EF  
30 31 32 33 34 35 36 37 38 39 CF DB DC AB DA 9F # F0-FF  
# End
```