Oracle® Communications Cloud Native Unified Data Repository Installation and Upgrade Guide



Release 1.7.1 F32752-03 August 2020

ORACLE

Oracle Communications Cloud Native Unified Data Repository Installation and Upgrade Guide, Release 1.7.1

F32752-03

Copyright © 2019, 2020, Oracle and/or its affiliates.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software" or "commercial computer software documentation" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

# Contents

### <u>1</u> Introduction

1-1
1-2
1-2
1-3

### 2 Installing Unified Data Repository

Planning Your Installation	2-1
Installation Sequence	2-4
Installation Preparation	2-4
OCUDR Namespace Creation	2-7
Service Account, Role and RoleBinding Creation	2-8
Kubernetes Secret Creation - DBName, Username, Password and Encryption Key	2-9
Kubernetes Secret Creation - Private Keys and Certificates for IngressGateway	2-10
ocudr-custom-values.yaml File Configuration	2-12
Unified Data Repository Deployment	2-13
Post Installation Sanity Check - Helm Test	2-14

### 3 Customizing and Configuring Unified Data Repository

Customizing Unified Data Repository	3-1
Configuring User Parameters	3-16

### 4 Upgrading an Existing Unified Data Repository Deployment

### 5 Troubleshooting Unified Data Repository

Generic Checklist	5-1
Verifying UDR Registration with NRF	5-3
Verifying Container Logs	5-4



Verifying OCUDR Microservices Logs	5-4
Debugging Errors from Egress Gateway	5-9
Debugging Errors from Ingress Gateway	5-9
Debugging Helm Test Issues	5-11
Debugging HPA Issues	5-12
Debugging HTTPS Support related Issues	5-12
Debugging Notification Issues	5-14
Debugging Pod Creation Failure	5-14
Debugging UDR Registration with NRF Failure	5-18
Debugging UDR with Service Mesh Failure	5-20
Using Logs	5-22

# 6 Uninstalling Unified Data Repository

# A ASM Specific Configuration



### List of Figures

5-1	Sample Output: UDR Pods Status	5-2
5-2	Sample Output: UDR Pods Status	5-2
5-3	Sample Output: Verifying Table Entries in Database	5-3
5-4	Container Logs	5-4
5-5	NRF-Client-Service Logs	5-5
5-6	NUDR-NOTIFY-SERVICE Logs	5-6
5-7	NUDR-CONFIG-SERVICE Logs	5-7
5-8	Enabling Egress Traffic using HTTPS	5-9
5-9	Snapshot of Values.yaml file	5-10
5-10	503 Error Code	5-10
5-11	Helm Test Pod	5-11
5-12	Helm Test in Pending State	5-11
5-13	Pod Readiness Failed	5-11
5-14	metrics-server yaml file	5-12
5-15	CPU Usage Update	5-12
5-16	HTTPS Port Exposed	5-13
5-17	Configuration Info under Ingressgateway	5-13
5-18	config initssl	5-13
5-19	Commands to check Secrets	5-14
5-20	Config Server Container Status	5-14
5-21	Service Availability in CNE	5-18
5-22	Verifying Istio-Proxy	5-20
5-23	Global Section - Istio-Proxy Info	5-21
5-24	Annotation to Configure Port	5-21
5-25	Annotation to View UDR Metrics	5-22



### List of Tables

2-1 ocudr-custom-values-1.7.1.yaml Parameters

2-12



# My Oracle Support

My Oracle Support (https://support.oracle.com) is your initial point of contact for all product support and training needs. A representative at Customer Access Support can assist you with My Oracle Support registration.

Call the Customer Access Support main number at 1-800-223-1711 (toll-free in the US), or call the Oracle Support hotline for your local country from the list at http:// www.oracle.com/us/support/contact/index.html. When calling, make the selections in the sequence shown below on the Support telephone menu:

- 1. Select 2 for New Service Request.
- 2. Select 3 for Hardware, Networking and Solaris Operating System Support.
- 3. Select one of the following options:
  - For Technical issues such as creating a new Service Request (SR), select 1.
  - For Non-technical issues such as registration or assistance with My Oracle Support, select **2**.

You are connected to a live agent who can assist you with My Oracle Support registration and opening a support ticket.

My Oracle Support is available 24 hours a day, 7 days a week, 365 days a year.



# What's New in This Guide

This section shares the list of new features introduced in every OCUDR release. For more release specific information, you can refer to its release notes.

#### Patch Release 1.7.1

In this patch release, UDR can be deployed with service mesh like Aspen. This helps in controlling and monitoring the data flow within UDR microservices and outside as well.

#### Release 1.7

The following new features are introduced in this release:

- Extension of SLF provisioning with SLFGroupName on both UDR and ProvGw
- Supports enablement of various features of UDR
- Supports Helm test for NF deployment
- Supports customized labels and annotations in the Helm charts
- Supports CSAR packaging
- Integrated with Egress API gateway
- Integrated with CNC-Console for configuration of UDR
- Supports 4G policy data storage
- Support Diameter Sh interface for subscriber profile



# 1 Introduction

This documents provides information for installing Cloud Native Unified Data Repository product.

# **Overview**

The 5G Unified Data Repository (UDR) is one of the main key component of the 5G Service Based Architecture. It is implemented as a cloud native function and offers a unified database for storing application, subscription, authentication, service authorization, policy data, session binding and Application state information. It provides a HTTP2 based RESTful interface for other NF's and provisioning clients to access the stored data.

Oracle's 5G UDR:

- Leverages a common Oracle Communications Cloud Native Framework
- Is compliant to 3GPP 29.505 Release 15 specification UDM
- Is compliant to 3GPP 29.519 Release 16 (backward compatible with Release 15) specification for PCF
- Has tiered architecture providing separation between the connectivity, business logic and data layers
- Uses Oracle MySQL NDB Cluster CGE Edition as backend database in the Data Tier.
- Registers with NRF in the 5G network so that the other NFs in the network can discover UDR through NRF.
- Registers UDR with services like DR-SERVICE and GROUP-ID-MAP.

As per 3GPP, UDR supports following functionality:

- Storage and retrieval of subscription data by the UDM.
- Storage and retrieval of policy data by the PCF.
- Storage and retrieval of structured data for exposure.
- Storage and retrieval of SLF information, consumed by NRF.
- Application data (including Packet Flow Descriptions (PFDs) for application detection, AF request information for multiple UEs), by the NEF.
- Subscription and Notification feature.

**Unstructured Data Storage Function (UDSF)** is a part of Oracle's 5G UDR solution. It supports storage and retrieval of unstructured data by any 5G NF. The specifications of UDSF are presently not defined by 3GPP.

5G SLF functionality is also a part of Oracle's 5G UDR solution. It:

- Supports Nudr-groupid-map service as defined by 3GPP
- Registers with NRF for Nudr-groupid-map service



- Is complaint with 3GPP Release 16 for APIs to be consumed by 5G NRF
- Supports REST/JSON based provisioning APIs for SLF data

## Architecture

The Cloud Native Unified Data Repository architecture has following three tiers:

#### **Connectivity Tier**

- Ingress API Gateway (Spring Cloud Gateway [SCG] based) is used as an API gateway that receives all requests and forwards them to the Nudr-drservice service of Business Tier.
- It load balances the traffic and provides required authentication.
- It provides TLS support.
- It runs on Kubernetes/OCCNE as a microservice.
- It uses Egress API Gateway for Egress traffic arising from UDR (notifications and NRF management APIs).

#### **Business Tier**

- Provides the business logic of 5G Unified Data Repository.
- It has following micro services:
  - nudr-drservice: The core service that handles flexible URI support, runtime schema validation and connects to Data Tier for DB operations. It provides SLF lookup functionality.
  - nudr-nrf-client-service: Handles registration, heartbeat, update and deregistration with Network Repository Function (NRF).
  - nudr-notify-service: Handles notification messages to Policy Control Function (PCF) and Unified Data Management (UDM) for data subscriptions.
  - nudr-config: Handles all request from CNC-Console and redirects all requests to appropriate REST API of the config server. It allows users to configure UDR for all micro services.
  - nudr-config-server: Handles all the requests from nudr-config and updates the database.
  - nudr-diameterproxy service: Supports Diameter Sh interface for 4G policy data for the subscriber profile.

#### Data Tier

- Uses Oracle MySQL NDB Cluster, CGE edition as backend database in the DB tier. This provides HA and geo-redundcancy capabilities.
- Users can build database on either Bare metal, virtualized or on kubernetes platform (kubevirt based).

# References

You can refer to the following documents for better understanding of Unified Data Repository and its related network functions.

Unified Data Repository User's Guide



- Provisioning Gateway Guide
- CNE Installation Guide
- Policy Installation Guide
- NRF Installation Guide

# Acronyms

The following table provides information about the acronyms used in the document.

Field	Description
5G-AN	5G Access Network
5GC	5G Core Network
5G-GUTI	5G Globally Unique Temporary Identifier
5GS	5G System
AMF	Access and Mobility Management Function
ASM	Aspen Service Mesh
AUSF	Authentication Server Function
NEF	Network Exposure Function
NF	Network Function
NRF	Network Repository Function
NSI ID	Network Slice Instance Identifier
NSSAI	Network Slice Selection Assistance Information
NSSF	Network Slice Selection Function
NSSP	Network Slice Selection Policy
PCF	Policy Control Function
REST	Representational State Transfer
SEPP	Security Edge Protection Proxy
SLF	Subscriber Location Function
SMF	Session Management Function
UDM	Unified Data Management
UDR	Unified Data Repository
UDSF	Unstructured Data Storage Function



# 2 Installing Unified Data Repository

This section provides instructions on installing Unified Data Repository.

# **Planning Your Installation**

Before installing UDR, perform the following pre-installation tasks:

- Checking the software requirements
- Checking the environment setup

#### **Checking the Software Requirements**

Before installing Unified Data Repository (UDR), install the following softwares on your system.

Software	Version
Kubernetes	v1.13.3
HELM	v2.12.3

Additional softwares that needs to be deployed as per the requirement of the services are:

Software	Version	Notes
elasticsearch	1.21.1	Needed for Logging Area
elastic-curator	1.2.1	Needed for Logging Area
elastic-exporter	1.1.2	Needed for Logging Area
logs	2.0.7	Needed for Logging Area
kibana	1.5.2	Needed for Logging Area
grafana	2.2.0	Needed for Metrics Area
prometheus	8.8.0	Needed for Metrics Area
prometheus-node-exporter	1.3.0	Needed for Metrics Area
metallb	0.8.4	Needed for External IP
metrics-server	2.4.0	Needed for Metric Server
tracer	0.8.3	Needed for Tracing Area

#### Note:

The above softwares are available in the **Oracle Communications Cloud Native Environment (OCCNE)**. If you are deploying UDR in any other environment, then the above softwares must be installed before installing UDR.

To check the installed software items, execute the following command:

ORACLE

helm ls

Some systems may need to use helm command with **admin.conf** file as follows:

helm --kubeconfig admin.conf

#### Note:

Some of the above mentioned software(s) are updated frequently. Their later versions than those listed above should work with UDR 1.7. Some UDR features and services work differently depending on the software being used

#### **Checking the Environment Setup**

Before installing UDR, the system environment should have the following:

- Access to OpenStack Environment: User should have access to an existing OpenStack environment including the OpenStack Desktop. This environment is configured with appropriate resource flavors and network resources that allows its users to allocate resources to the virtual machines created via this procedure.
- OCUDR Software: User must install Kubernetes v1.13.3 and HELM v2.12.3. UDR consists of:
  - Helm Charts that reflect the OCUDR software version. It is a zipped tar file that you need to unzip.
  - Docker images of the micro-services that are shared as tar file. You need to untar it.

#### Note:

For more details about OCUDR Software, see Checking the Software Requirements.

 Create Database User/Group: The Database administrator should create a user in the MYSQL DB using MySQL NDB cluster. UDR uses an NDB MySQL database to store the subscriber information. NDB MySQL database provides HA and geo-redundancy capabilities.

The database administrator should also provide user with necessary permissions to access the tables in the NDB cluster. The steps to create a user and assign permissions are as follows:

- 1. Login to the server where the ssh keys are stored and SQL nodes are accessible.
- 2. Connect to the SQL nodes.
- 3. Login to the Database as a root user.



 Create a user on all sql nodes and assign it to a group having necessary permissions to access the tables on all sql nodes. Also, create a database on only one sql node.

```
CREATE USER '<username>'@'%' IDENTIFIED BY '<password>';
DROP DATABASE if exists <db_name>;
CREATE DATABASE <db_name> CHARACTER SET utf8;
CREATE DATABASE udr_release CHARACTER SET utf8;
```

#### Note:

DB Name used in the above command should be same as releaseDbName configuration under global section in values.

GRANT SELECT, INSERT, CREATE, ALTER, DROP, LOCK TABLES, CREATE TEMPORARY TABLES, DELETE, UPDATE, EXECUTE, INDEX, REFERENCES ON <db\_name>.\* TO '<user>'@'%'; GRANT SELECT, INSERT, CREATE, ALTER, DROP, LOCK TABLES, CREATE TEMPORARY TABLES, DELETE, UPDATE, EXECUTE, INDEX, REFERENCES ON udr\_release.\* TO '<user>'@'%'; USE <db\_name>;

#### Note:

You need this database name, username and password at the time of creating Kubernetes secrets.

- Network Access: The Kubernetes cluster hosts must have network access to:
  - Local docker image repository where the Oracle Communications Unified Data Repository images are available.
     To check if the Kubernetes cluster hosts has network access to the local docker image repository, try to pull any image with tag name to check connectivity by executing:

```
docker pull <docker-repo>/<image-name>:<image-tag>
```

Local helm repository where the Oracle Communications Unified Data Repository helm charts are available.
To check if the Kubernetes cluster hosts has network access to the local helm repository, execute:

helm repo update

#### Note:

Some of the systems may need to use helm command with helm --kubeconfig admin.conf



#### Note:

All the kubectl and helm commands (used in this document) must be executed on a system depending on the infrastructure of the deployment. It can be any client machine like virtual machine, server, local desktop and so on.

- Laptop/Desktop Client Software: A laptop/desktop where the user executes deployment commands should have:
  - Network access to the helm repository and docker image repository
  - Configuration of Helm repository on the client
  - Network access to the Kubernetes cluster
  - Necessary environment settings to run the kubectl commands. The environment should have privileges to create namespace in the Kubernetes cluster.
  - Helm client installed with the **push** plugin. The environment should be configured so that the 'helm install' command deploys the software in the Kubernetes cluster.

#### Note:

All the kubectl and helm commands (used in this document) must be executed on a system depending on the infrastructure of the deployment. It can be any client machine like virtual machine, server, local desktop and so on.

# **Installation Sequence**

The installation sequence of UDR is as follows:

- 1. Installation Preparation
- 2. OCUDR Namespace Creation
- 3. Service Account, Role, and RoleBinding Creation
- 4. Creating Kubernetes Secrets for storing:
  - DBName, Username, Password and EncryptionKey
  - Private Keys and Certificate for IngressGateway
- 5. ocudr-custom-values.yaml File Configuration
- 6. UDR Deployment
- 7. Post Installation Sanity Check Helm Test

### Installation Preparation

This phase of installation includes downloading and loading the required files to the system.



 Download the following UDR package file from Oracle Software Delivery Cloud (OSDC).

<nfname>-pkg-<marketing-release-number>.tgz

For example:ocudr-pkg-1.7.1.tgz

2. Untar the UDR Package File. Execute the following command to untar UDR Package File.

tar -xvf ocudr-pkg-1.7.1.tgz

This command results into ocudr-pkg-1.7.1 directory. The directory consists of following:

- UDR Docker Images File: ocudr-images-1.7.1.tar
- Helm File: ocudr-1.7.1.tgz
- **Readme txt File:** The Readme.txt contains cksum and md5sum of tarballs.
- Verify the checksums of tarballs in the following file. Readme.txt
- 4. Load the tarballs to docker images. Execute the following command: # docker load --input /root/ocudr-images-1.7.1.tar
- 5. Check if all the images are loaded. Execute the following command: docker images | grep ocudr
- Tag the docker images to docker registry. Execute the following command: docker tag <image-name>:<image-tag> <docker-repo>/<image-name>:<image-tag>
- 7. Push the docker images to docker registry. Execute the following command: docker push <docker-repo>/<image-name>:<image-tag>

#### Sample Tag and Push Commands:

# docker tag ocudr/nudr\_datarepository\_service:1.7.1 <customer repo>/nudr\_datarepository\_service:1.7.1

# docker push <customer repo>/nudr\_datarepository\_service:1.7.1

# docker tag ocudr/nudr\_nrf\_client\_service:1.7.1 <customer repo>/
nudr\_nrf\_client\_service:1.7.1

# docker push <customer repo>/nudr\_nrf\_client\_service:1.7.1

# docker tag ocudr/nudr\_notify\_service:1.7.1 <customer repo>/
nudr\_notify\_service:1.7.1

# docker push <customer repo>/nudr\_notify\_service:1.7.1

# docker tag ocudr/nudr\_diameterproxy:1.7.1 <customer repo>/
nudr\_diameterproxy:1.7.1

# docker push <customer repo>/nudr\_diameterproxy:1.7.1

# docker tag ocudr/nudr\_prehook:1.7.1 <customer repo>/
nudr\_prehook:1.7.1



# docker push <customer repo>/nudr\_prehook:1.7.1 # docker tag ocudr/nudr\_config:1.7.1 <customer repo>/ nudr\_config:1.7.1 # docker push <customer repo>/nudr\_config:1.7.1 # docker tag ocudr/ocingress\_gateway:1.7.7 <customer repo>/ ocingress\_gateway:1.7.7 # docker push <customer repo>/ocingress\_gateway:1.7.7 # docker tag ocudr/ocegress\_gateway:1.7.7 <customer repo>/ ocegress\_gateway:1.7.7 # docker push <customer repo>/ocegress\_gateway:1.7.7 # docker tag ocudr/configurationinit:1.2.0 <customer repo>/ configurationinit:1.2.0 # docker push <customer repo>/configurationinit:1.2.0 # docker tag ocudr/configurationupdate:1.2.0 <customer repo>/ configurationupdate:1.2.0 # docker push <customer repo>/configurationupdate:1.2.0 # docker tag ocudr/ocpm\_config\_server:1.7.0 <customer repo>/ ocpm\_config\_server:1.7.0 # docker push <customer repo>/ocpm\_config\_server:1.7.0 # docker tag ocudr/readiness-detector:latest <customer repo>/ readiness-detector:latest # docker push <customer repo>/readiness-detector:latest # docker tag ocudr/nf\_test:1.7.1 <customer repo>/nf\_test:1.7.1 # docker push <customer repo>/nf\_test:1.7.1 8. Untar Helm Files. Execute the following command: tar -xvzf ocudr-1.7.1.tgz 9. Download the Unified Data Repository (UDR) Custom Template ZIP file from OHC. The steps are as follows: a. Go to the URL, docs.oracle.com b. Navigate to Industries->Communications->Cloud Native Core. c. Click the Unified Data Repository (UDR) Custom Template link to download

- d. Unzip the template to get ocudr-custom-configTemplates-1.7.1 file that contains the following:
  - UDR\_Dashboard.json: This file is used by grafana.



- ocudr-custom-values-1.7.1.yaml: This file is used during installation.
- ProvGw\_Dashboard.json
- provgw-custom-values-1.7.1.yaml

Following are the OCUDR Images.

Pod	Image
<helm_release_name>-nudr-drservice</helm_release_name>	ocudr/nudr_datarepository_service
<helm_release_name>-nudr-notify -service</helm_release_name>	ocudr/nudr_notify_service
<helm_release_name>-nudr-nrf-client-service</helm_release_name>	ocudr/nudr_nrf_client_service
<helm_release_name>-ingressgateway</helm_release_name>	ocudr/ocingress_gateway ocudr/configurationinit ocudr/configurationupdate
<helm_release_name>-egressgateway</helm_release_name>	ocudr/ocegress_gateway ocudr/configurationinit ocudr/configurationupdate
<helm_release_name>-nudr-config</helm_release_name>	ocudr/nudr_config
<helm_release_name>-nudr-config-server</helm_release_name>	ocudr/ocpm_config_server ocudr/readiness-detector
<helm_release_name>-nudr-diameterproxy- service</helm_release_name>	ocudr/nudr_diameterproxy
<helm_release_name>-test</helm_release_name>	ocudr/nf_test
<helm_release_name>-nudr-preinstall</helm_release_name>	ocudr/nudr_prehook

#### Note:

<helm\_release\_name>-nudr-notify-service and <helm\_release\_name>nudr-diameterproxy-service are not required for SLF deployment. So, set its flag value as 'enabled - false' in the values.yaml file. For more details, see User Configurable Parameterocudr-custom-values.yaml File Configuration.

### **OCUDR** Namespace Creation

In this section, you will learn to verify the existence of a required namespace in the system. If a namespace does not exist, you must create it. The steps to verify and create a namespace are as follows:

**1.** Execute the following command to verify the existence of required namespace in system:

kubectl get namespace

2. If the required namespace does not exist, then execute the following command to create a namespace:

kubectl create namespace <required namespace>

For example: kubectl create namespace ocudr



#### Note:

This is an optional step. In case required namespace already exists, proceed with next procedures.

### Service Account, Role and RoleBinding Creation

In this section, you will learn to create a service account, role and rolebinding resources.

A sample command to create the resources is as follows:

```
kubectl -n <ocudr-namespace> create -f ocudr-sample-resource-template.yaml
```

A sample template to create the resources is as follows:

#### Note:

You need to update the <helm-release> and <namespace> values with its respective ocudr namespace and ocudr helm release name.

```
#
# Sample template start
#
apiVersion: v1
kind: ServiceAccount
metadata:
 name: <helm-release>-serviceaccount
 namespace: <namespace>
___
apiVersion: rbac.authorization.k8s.io/v1
kind: Role
metadata:
 name: <helm-release>-role
 namespace: <namespace>
rules:
- apiGroups:
  - "" # "" indicates the core API group
  resources:
  - services
  - configmaps
  - pods
  - secrets
  - endpoints
  verbs:
  - get
  - watch
  - list
```



```
apiVersion: rbac.authorization.k8s.io/v1beta1
kind: RoleBinding
metadata:
  name: <helm-release>-rolebinding
  namespace: <namespace>
roleRef:
  apiGroup: rbac.authorization.k8s.io
  kind: Role
  name: <helm-release>-role
subjects:
- kind: ServiceAccount
  name: <helm-release>-serviceaccount
  namespace: <namespace>
#
# Sample template end
#
```

# Kubernetes Secret Creation - DBName, Username, Password and Encryption Key

In this section, you will learn to create a secret to store database name, username, password, and encryption key.

To create a Kubernetes secret:

1. Create a yaml file with dbname, dbusername, dbpassword, encryptionKey using the syntax given below:

```
ocudr-secret.yaml
apiVersion: v1
kind: Secret
metadata:
   name: ocudr-secrets
type: Opaque
data:
   dbname: dWRyZGI=
   dsusername: dWRydXNlcg==
   dspassword: dWRycGFzc3dk
   encryptionkey: TXkgc2VjcmV0IHBhc3NwaHJhc2U=
```

#### Note:

The **name** used to define a secret above should be same as given in the **dbCredSecretName** configuration under global section in values.yaml.

The values of dbname, dsusername, dspassword, encryptionKey are base64 encoded. These are created by executing the following commands:

```
echo -n "<db name>" | base64
echo -n "<db username>" | base64
```



```
echo -n "<db password>" | base64
echo -n "<encryptionKey string>" | base64
```

#### Note:

You will create a secret using this yaml file.

2. Execute the following command to create a namespace where deployment is done.

kubectl create namespace <namespace>

#### Note:

To create a secret, you need a namespace where deployment is done.

- 3. Execute the following command to create a secret: kubectl create -f <secret File Name> -n <namespace>
- 4. Execute the following command to verify a secret creation: kubectl describe secret <secret name> -n <namespace>

## Kubernetes Secret Creation - Private Keys and Certificates for IngressGateway

In this section, you will learn to create a secret to store private keys and certificates for IngressGateway.

#### Note:

It is a user or operator discretion to create the private keys and certificates for IngressGateway and it is not in the scope of UDR. This section shares only samples to create them.

To create a secret to store private keys and certificate for IngressGateway:

- 1. Generate RSA private key by executing the following command: openssl reg -x509 -nodes -sha256 -days 365 -newkey rsa:2048 -keyout rsa\_private\_key -out rsa\_certificate.crt -config ssl.conf -passin pass:"keystorepasswd" -passout pass:"keystorepasswd"
- 2. Convert the private key to .pem format by executing the following command: openssl rsa -in rsa\_private\_key -outform PEM -out rsa\_private\_key\_pkcsl.pem -passin pass:"keystorepasswd" -passout pass:"keystorepasswd"
- 3. Generate certificate using the private key by executing the following command: openssl req -new -key rsa\_private\_key -out apigatewayrsa.csr -config ssl.conf -passin pass:"keystorepasswd" -passout pass:"keystorepasswd"



Note:

You can use **ssl.conf** to configure default entries along with storage area network (SAN) details for your certificate.

A sample ssl.conf file is given below:

```
ssl.conf
#ssl.conf
[req]
default_bits = 4096
distinguished name = reg distinguished name
req extensions = req ext
[ req_distinguished_name ]
countryName = Country Name (2 letter code)
countryName_default = IN
stateOrProvinceName = State or Province Name (full name)
stateOrProvinceName default = Karnataka
localityName = Locality Name (eq, city)
localityName_default = Bangalore
organizationName = Organization Name (eg, company)
organizationName_default = Oracle
commonName = Common Name (e.q. server FQDN or YOUR name)
commonName max = 64
commonName default = localhost
[ req ext ]
subjectAltName = @alt_names
[alt names]
IP = 127.0.0.1
DNS.1 = localhost
```

 Create a root Certificate Authority (CA) by executing the following set of commands:

openssl req -new -keyout cakey.pem -out careq.pem -config ssl.conf passin pass:"keystorepasswd" -passout pass:"keystorepasswd"

openssl x509 -signkey cakey.pem -req -days 3650 -in careq.pem -out caroot.cer -extensions v3\_ca -passin pass:"keystorepasswd" echo 1234 > serial.txt

 Sign the server certificate with root CA private key by executing the following command:

```
openssl x509 -CA caroot.cer -CAkey cakey.pem -CAserial serial.txt -
req -in apigatewayrsa.csr -out apigatewayrsa.cer -days 365 -extfile
ssl.conf -extensions req_ext -passin pass:"keystorepasswd"
```

6. Generate ECDSA private key by executing the following set of commands: openssl ecparam -genkey -name prime256v1 -noout -out ecdsa\_private\_key.pem

openssl pkcs8 -topk8 -in ecdsa\_private\_key.pem -inform pem -out ecdsa\_private\_key\_pkcs8.pem -outform pem -nocrypt

**7.** Generate certificate using the private key by executing the following set of commands:



openssl req -new -key ecdsa\_private\_key\_pkcs8.pem -x509 -nodes -days 365 -out ecdsa\_certificate.crt -config ssl.conf

openssl req -new -key ecdsa\_private\_key\_pkcs8.pem -out apigatewayecdsa.csr -config ssl.conf -passin pass:"keystorepasswd" passout pass:"keystorepasswd"

8. Sign the server certificate with root CA private key by executing the following command:

openssl x509 -CA caroot.cer -CAkey cakey.pem -CAserial serial.txt -req -in apigatewayecdsa.csr -out apigatewayecdsa.cer -days 365 -extfile ssl.conf -extensions req\_ext -passin pass:"keystorepasswd"

- 9. Create a key.txt file by entering any password. Example: echo "keystorepasswd" > key.txt
- **11.** Create a Secret by executing the following set of commands: kubectl create ns NameSpace

kubectl create secret generic ocudr-gateway-secret
--from-file=apigatewayrsa.cer --from-file=caroot.cer --fromfile=apigatewayecdsa.cer --from-file=rsa\_private\_key\_pkcs1.pem -from-file=ecdsa\_private\_key\_pkcs8.pem --from-file=key.txt --fromfile=trust.txt -n <Namespace>

### ocudr-custom-values.yaml File Configuration

In this section, you will learn to configure docker Registry path, DB connectivity service fqdn and port details and UDR details based on deployment.

UDR uses MySQL database to store the configuration and run time data. Before deploying the UDR in Kubernetes Cluster, update the following parameters in the **ocudr-custom-values-1.7.1.yaml** file:

Section	Parameter	Services
Global	mysql	<ul> <li>dbServiceName : mysql-connectivity- service.occne-infra.</li> <li>port: "<port>".</port></li> </ul>
	<b>dockerRegistry</b> : allows to configure docker Registry from where the images are pulled.	ocudr- registry.us.oracle.com:5000

Table 2-1 ocudr-custom-values-1.7.1.yaml Parameters



Section	Parameter	Services
nrfclient	host:	baseurl: " <to connect<br="">to Network Repository Function (NRF) for registration&gt;".</to>
		<ul> <li>proxy: "<proxy setting<br="">if anyone connects to NRF&gt;". Default value is NULL.</proxy></li> </ul>
		<ul> <li>capacityMultiplier: "<capacity multiplier="">". Default value is 500.</capacity></li> </ul>
		<ul> <li>supirange: "<supi rang<br="">for UDR&gt;". Default value is [{\"start\": \"1000000000\", \"end" \"2000000000\"}]</supi></li> </ul>
		• <b>priority</b> : " <priority>". Default value is 10.</priority>
		<ul> <li>fqdn: "FQDN of nudr- drservice for NRF to us while sending request. is carried in registration request to NRF".</li> </ul>
		<ul> <li>gpsirange: "<gpsi rang<br="">for UDR&gt;"</gpsi></li> </ul>
		<ul> <li>plmnvalues: "<plmn values that supports&gt;"</plmn </li> </ul>

#### Table 2-1 (Cont.) ocudr-custom-values-1.7.1.yaml Parameters

## Unified Data Repository Deployment

In this section, you will learn to deploy Unified Data Repository.

You can deploy UDR either with **HELM repository** or with **HELM tar**. To deploy UDR in Kubernetes cluster:

1. Use ocudr-custom-values-1.7.1.yaml file, which is modified in the ocudr-custom-values.yaml section. Execute the following command to deploy UDR: helm install <helm chart> [--version <OCUDR version>] --name <release> --namespace <k8s namespace> -f <ocudr-custom-values-1.7.1.yaml>

In the above command:

- <helm chart> is the name of the chart, which is of the form <helm repo>/ ocudr.
- <OCUDR version> is the software version (helm chart version) of the OCUDR. This is optional. If omitted, the default is **latest** version available in helm repository.
- <release> is a name of user's choice to identify the helm deployment. From 1.7.1 release onwards, all pod names, service name, deployment name are prepended by this release name.



- <k8s namespace> is a name of user's choice to identify the kubernetes namespace of the Unified Data Repository. All the Unified Data Repository micro services are deployed in this kubernetes namespace.
- <ocudr-custom-values-1.7.1.yaml> is the customized ocudr-custom-values-1.7.1.yaml file. The ocudr-custom-values-1.7.1.yaml file is a part of customer documentation. Users needs to download the file and modify it as per the user site.

#### Note:

If helm3 is used, execute the following command for installation: helm install -name <release> --namespace <k8s namespace> f <ocudr-custom-values-1.7.1.yaml> <helm chart> [--version <OCUDR version>]

2. (Optional) Customize the Unified Data Repository by overriding the default values of various configurable parameters. See Customizing Unified Data Repository

#### Verifying UDR Deployment

After deploying UDR, you need to verify whether all the services and pods are up and running.

### Post Installation Sanity Check - Helm Test

**Helm Test** is a feature that validates successful installation of UDR along with its readiness (Readiness probe url configured is checked for success) of all the pods. The pods that are checked are based on the namespace and label selector configured for the helm test configurations.

This test also checks for all the PVCs to be in bound state under the Release namespace and label selector configured.

Note: You can use Helm Test feature only if you have Helm3.

To execute the Helm test functionality:

#### Note:

Before executing the Hem Test command, it is important to do the following configurations.

 Configure the helm test configurations under the Global section of the values.yaml file as follows:

```
global:
    # Helm test related configurations
    test:
        nfName: ocudr
        image:
            name: ocudr/nf_test
            tag: 1.7.1
```



```
config:
  logLevel: WARN
  timeout: 40
```

For more details, refer to the Configuring User Parameters

 Ensure the label given below is part of all microservice deployments. The Helm Test feature takes the labelSelector internally, along with the helm release namespace, to select the pods and pvcs for verification.
 app.kubernetes.io/instance: {{ .Release.Name }}

Usually, it is one of the Engineering labels present in the template of all NF charts. If it is not present, you need to add this label so that the helm test can work on specific helm release.

 Execute the following Helm Test command: helm test <helm\_release\_name> -n <k8s namespace>

Wait for the helm test job to complete. Check the output whether the test job is successful or not.

#### Note:

Readiness probe for all kubernetes deployment defined under the umbrella chart should be configured with **httpGet** parameter with proper url. If it is not configured, helm test for that pod is considered success. And if the Pod/PVC list to be verified, is fetched based on namespace and labelSelector is empty, then the Helm Test is success. If the Helm Test fails with errors, then you can refer to the Troubleshooting Unified Data Repository



# S Customizing and Configuring Unified Data Repository

This section provides information on customizing and configuring Unified Data Repository.

# **Customizing Unified Data Repository**

You can customize the Unified Data Repository deployment by overriding the default values of various configurable parameters.

In the ocudr-custom-values.yaml File Configuration section, MySQL host is customized.

The **ocudr-custom-values.yaml** file can be prepared by hand to customize the parameters.

Following is an example of Unified Data Repository customization file.

#### Note:

All the configurable parameters are mentioned in the Configuring User Parameters

# Copyright 2019 (C), Oracle and/or its affiliates. All rights reserved.

```
global:
    dockerRegistry: ocudr-registry.us.oracle.com:5000
    mysql:
        dbServiceName: "mysql-connectivity-service.occne-infra"
        a read only parameter. Use the default value.
        port: "3306"
        udrTracing:
        enable: false
        host: "occne-tracer-jaeger-collector.occne-infra"
```

udrTracing: enable: false host: "occne-tracer-jaeger-collector.occne-infra" port: 14268 dbenc: shavalue: 256 serviceAccountName: egress: enabled: true # Configurations for Config-Server configServerEnable: true initContainerEnable: false dbCredSecretName: 'ocudr-secrets'



#This is

```
releaseDbName: 'udr_release'
 configServerFullNameOverride: nudr-config-server
 # Configuration to decide the Service the deployment will provide
 udrServices: "nudr-group-id-map"
 # Enable to register with NRF for UDSF service
 udsfEnable: false
 # Helm test related configurations
 test:
   nfName: ocudr
   image:
     name: ocudr/nf_test
     tag: 1.7.1
   config:
     logLevel: WARN
     timeout: 120
 # Pre Hook Install configurations
 preInstall:
   image:
     name: ocudr/nudr_prehook
     tag: 1.7.1
   config:
     logLevel: WARN
 # Resources for Hooks
 hookJobResources:
   limits:
     cpu: 2
     memory: 2Gi
   requests:
     cpu: 1
     memory: 1Gi
                           #******
* * *
 # ******* Sub-Section Start: Custom Extension Global Parameters
******
* * *
 customExtension:
   allResources:
     labels: {}
     annotations:
       sidecar.istio.io/inject: "\"false\""
   lbServices:
     labels: {}
     annotations: {}
```

```
lbDeployments:
    labels: {}
    annotations:
      sidecar.istio.io/inject: "\"true\""
      oracle.com/cnc: "\"true\""
   nonlbServices:
    labels: {}
    annotations: {}
   nonlbDeployments:
    labels: {}
    annotations:
      sidecar.istio.io/inject: "\"true\""
      oracle.com/cnc: "\"true\""
 # ******** Sub-Section End: Custiom Extensions Global Parameters
******
* * *
 # ******* Sub-Section Start: Prefix/Suffix Global Parameters
* * * * * * * * * * * *
* * *
 k8sResource:
   container:
    prefix:
    suffix:
 # ******* Sub-Section End: Prefix/Suffix Global Parameters
*****
* * *
nudr-drservice:
# nameOverride: "nudr-drservice"
 image:
   name: ocudr/nudr_datarepository_service
   tag: 1.7.1
   pullPolicy: Always
 service:
   http2enabled: "true"
   type: ClusterIP
   port:
    http: 5001
    https: 5002
    management: 9000
   customExtension:
```



```
labels: {}
      annotations: {}
  tracingEnabled: false
  notify:
   port:
      http: 5001
      https: 5002
  deployment:
    replicaCount: 2
    customExtension:
      labels: {}
      annotations: {}
  logging:
    level:
      root: "WARN"
  subscriber:
    autocreate: "true"
  validate:
    smdata: "false"
  vsaLevel: "smpolicy"
  resources:
    limits:
      cpu: 4
      memory: 4Gi
    requests:
      cpu: 4
      memory: 4Gi
    target:
      averageCpuUtil: 80
  hikari:
   poolsize: "25"
  minReplicas: 2
  maxReplicas: 8
nudr-notify-service:
# nameOverride: "nudr-notify-service"
  enabled: false
  image:
    name: ocudr/nudr_notify_service
    tag: 1.7.1
   pullPolicy: Always
  service:
   http2enabled: "true"
```



```
type: ClusterIP
   port:
     http: 5001
     https: 5002
      management: 9000
    customExtension:
      labels: {}
      annotations: {}
  tracingEnabled: false
 deployment:
   replicaCount: 2
   customExtension:
      labels: {}
      annotations: {}
 notification:
   retrycount: "3"
   retryinterval: "5"
   retryerrorcodes: "400,429,500,503"
 hikari:
   poolsize: "10"
 logging:
   level:
      root: "WARN"
 resources:
   limits:
      cpu: 3
      memory: 3Gi
   requests:
      cpu: 3
      memory: 3Gi
    target:
      averageCpuUtil: 80
 minReplicas: 2
 maxReplicas: 4
 # for egress port
 http:
   proxy:
     port: 8080
nudr-config:
# nameOverride: "nudr-configuration-service"
 enabled: true
  image:
   name: ocudr/nudr_config
    tag: 1.7.1
   pullPolicy: Always
 service:
   http2enabled: "true"
```



```
type: ClusterIP
   port:
     http: 5001
     https: 5002
      management: 9000
    customExtension:
      labels: {}
      annotations: {}
 deployment:
    replicaCount: 1
    customExtension:
      labels: {}
      annotations: {}
  logging:
    level:
      root: "WARN"
 resources:
    limits:
      cpu: 2
      memory: 2Gi
   requests:
      cpu: 2
      memory: 2Gi
    target:
      averageCpuUtil: 80
 minReplicas: 1
 maxReplicas: 1
config-server:
 enabled: true
 global:
   nfName: nudr
    imageServiceDetector: ocudr/readiness-detector:latest
    envJaegerAgentHost: ''
    envJaegerAgentPort: 6831
 replicas: 1
  envLoggingLevelApp: WARN
 resources:
    limits:
      cpu: 2
      memory: 2Gi
   requests:
      cpu: 2
      memory: 512Mi
  service:
    type: ClusterIP
  fullnameOverride: udr-config-server
  installedChartVersion: ''
```



```
nudr-nrf-client-service:
# nameOverride: "nudr-nrf-client-service"
  enabled: true
 host:
   baseurl: "http://ocnrf-ingressgateway.mynrf.svc.cluster.local/nnrf-
nfm/v1/nf-instances"
   proxy:
 ssl: "false"
 logging:
    level:
     root: "WARN"
  image:
   name: ocudr/nudr_nrf_client_service
    tag: 1.7.1
   pullPolicy: Always
 heartBeatTimer: "90"
 udrGroupId: "udr-1"
 capacityMultiplier: "500"
  supirange: "[{\"start\": \"1000000000\", \"end\": \"2000000000\"}]"
 priority: "10"
 udrMasterIpv4: "10.0.0.0"
 gpsirange: "[{\"start\": \"1000000000\", \"end\": \"2000000000\"}]"
  #endpointLabelSelector : "ocudr-ingressgateway"
 plmnvalues: "[{\"mnc\": \"14\", \"mcc\": \"310\"}]"
  scheme: "http"
 livenessProbeMaxRetry: 5
 # this is for egress port
 http:
   proxy:
     host:
     port: 8080
 # The below 2 configuration will change based on site k8s name
resolution settings, Also note the changes with namespace used for udr
installation
  #livenessProbeUrl: "http://nudr-notify-
service.myudr.svc.cluster.local:9000/actuator/health,http://nudr-
drservice.myudr.svc.cluster.local:9000/actuator/health"
  fqdn: "ocudr-ingressgateway.myudr.svc.cluster.local"
 resources:
    limits:
      cpu: 1
     memory: 2Gi
   requests:
      cpu: 1
     memory: 2Gi
  service:
    customExtension:
      labels: {}
     annotations: {}
 deployment:
    customExtension:
     labels: {}
```

```
annotations:
        traffic.sidecar.istio.io/excludeOutboundPorts:
"\"9000,9090\"" #Should be configured with the management ports used
for UDR microservices and actutorPort used for IGW/EGW
ingressgateway:
 global:
   # Docker registry name
   # dockerRegistry: reg-1:5000
   # Specify type of service - Possible values are :- ClusterIP,
NodePort, LoadBalancer and ExternalName
   type: ClusterIP
   # Enable or disable IP Address allocation from Metallb Pool
   metalLbIpAllocationEnabled: true
   # Address Pool Annotation for Metallb
   metalLbIpAllocationAnnotation: "metallb.universe.tf/address-pool:
signaling"
   # Set to true if constant node port needs to be assigned when
Servicetype is LoadBalancer or NodePort
   staticNodePortEnabled: false
   # port on which UDR's API-Gateway service is exposed
   # If httpsEnabled is false, this Port would be HTTP/2.0 Port
(unsecured)
   # If httpsEnabled is true, this Port would be HTTPS/2.0 Port
(secured SSL)
   publicHttpSignalingPort: 80
   publicHttpsSignallingPort: 443
 image:
   # image name
   name: ocudr/ocingress_gateway
   # tag name of image
   tag: 1.7.7
   # Pull Policy - Possible Values are:- Always, IfNotPresent, Never
   pullPolicy: Always
 initContainersImage:
   # inint Containers image name
   name: ocudr/configurationinit
   # tag name of init Container image
   tag: 1.2.0
   # Pull Policy - Possible Values are:- Always, IfNotPresent, Never
   pullPolicy: Always
 updateContainersImage:
   # update Containers image name
   name: ocudr/configurationupdate
   # tag name of update Container image
   taq: 1.2.0
   # Pull Policy - Possible Values are:- Always, IfNotPresent, Never
```



```
pullPolicy: Always
deployment:
  customExtension:
     labels: {}
     annotations: {}
service:
  customExtension:
     labels: {}
     annotations: {}
  ssl:
    tlsVersion: TLSv1.2
    privateKey:
      k8SecretName: ocudr-gateway-secret
      k8NameSpace: ocudr
      rsa:
        fileName: rsa_private_key_pkcs1.pem
      ecdsa:
        fileName: ecdsa_private_key_pkcs8.pem
    certificate:
      k8SecretName: ocudr-gateway-secret
      k8NameSpace: ocudr
      rsa:
        fileName: apigatewayrsa.cer
      ecdsa:
        fileName: apigatewayecdsa.cer
    caBundle:
      k8SecretName: ocudr-gateway-secret
      k8NameSpace: ocudr
      fileName: caroot.cer
    keyStorePassword:
      k8SecretName: ocudr-gateway-secret
      k8NameSpace: ocudr
      fileName: key.txt
    trustStorePassword:
      k8SecretName: ocudr-gateway-secret
      k8NameSpace: ocudr
      fileName: trust.txt
    initialAlgorithm: RSA256
cncc:
  enabled: false
  enablehttp1: true
# Resource details
resources:
  limits:
    cpu: 5
```



```
memory: 4Gi
   initServiceCpu: 1
   initServiceMemory: 1Gi
   updateServiceCpu: 1
   updateServiceMemory: 1Gi
  requests:
   cpu: 5
   memory: 4Gi
   initServiceCpu: 1
    initServiceMemory: 1Gi
   updateServiceCpu: 1
   updateServiceMemory: 1Gi
  target:
   averageCpuUtil: 80
log:
  level:
   root: WARN
    ingress: INFO
   oauth: INFO
# enable jaeger tracing
jaegerTracingEnabled: false
openTracing :
  jaeger:
   udpSender:
      # udpsender host
     host: "occne-tracer-jaeger-agent.occne-infra"
      # udpsender port
      port: 6831
   probabilisticSampler: 0.5
# Number of Pods must always be available, even during a disruption.
minAvailable: 2
# Min replicas to scale to maintain an average CPU utilization
minReplicas: 2
# Max replicas to scale to maintain an average CPU utilization
maxReplicas: 5
# label to override name of api-gateway micro-service name
#fullnameOverride: ocudr-endpoint
# To Initialize SSL related infrastructure in init/update container
initssl: false
# Cipher suites to be enabled on server side
ciphersuites:
  - TLS_ECDHE_ECDSA_WITH_AES_256_GCM_SHA384
  - TLS_ECDHE_RSA_WITH_AES_256_GCM_SHA384
  - TLS_ECDHE_RSA_WITH_CHACHA20_POLY1305_SHA256
  - TLS_DHE_RSA_WITH_AES_256_GCM_SHA384
  - TLS_DHE_RSA_WITH_AES_256_CCM
```

- TLS\_ECDHE\_ECDSA\_WITH\_AES\_128\_GCM\_SHA256

```
- TLS_ECDHE_RSA_WITH_AES_128_GCM_SHA256
#OAUTH CONFIGURATION
oauthValidatorEnabled: false
nfType: SMF
nfInstanceId: 6faf1bbc-6e4a-4454-a507-a14ef8e1bc11
producerScope: nsmf-pdusession,nsmf-event-exposure
allowedClockSkewSeconds: 0
nrfPublicKeyKubeSecret: nrfpublickeysecret
nrfPublicKeyKubeNamespace: ingress
validationType: strict
producerPlmnMNC: 123
producerPlmnMCC: 346
#Server Configuration for http and https support
#Server side http support
enableIncomingHttp: true
#Server side https support
enableIncomingHttps: false
#Client side https support
enableOutgoingHttps: false
maxRequestsQueuedPerDestination: 5000
maxConnectionsPerIp: 10
#Service Mesh (Istio) to take care of load-balancing
serviceMeshCheck: true
# configuring routes
routesConfig:
- id: traffic_mapping_http
  uri: http://{{ .Release.Name }}-nudr-drservice:5001
  path: /nudr-dr/**
  order: 1
- id: traffic_mapping_http_prov
  uri: http://{{ .Release.Name }}-nudr-drservice:5001
  path: /nudr-dr-prov/**
  order: 2
- id: traffic_mapping_http_mgmt
  uri: http://{{ .Release.Name }}-nudr-drservice:5001
  path: /nudr-dr-mgm/**
  order: 3
- id: traffic_mapping_http_udsf
  uri: http://{{ .Release.Name }}-nudr-drservice:5001
  path: /nudsf-dr/**
  order: 4
- id: traffic_mapping_http_group
  uri: http://{{ .Release.Name }}-nudr-drservice:5001
  path: /nudr-group-id-map/**
  order: 5
- id: traffic_mapping_http_group_prov
  uri: http://{{ .Release.Name }}-nudr-drservice:5001
  path: /nudr-group-id-map-prov/**
  order: 6
- id: traffic_mapping_http_slf_group_prov
  uri: http://{{ .Release.Name }}-nudr-drservice:5001
```

```
path: /slf-group-prov/**
   order: 7
egressgateway:
  enabled: true
  #fullnameOverride : 'ocudr-egress-gateway'
 nfType: UDR
  #global:
  # dockerRegistry: reg-1:5000
 deploymentEgressGateway:
    image: ocudr/ocegress_gateway
    imageTag: 1.7.7
   pullPolicy: Always
  initContainersImage:
    # inint Containers image name
   name: configurationinit
    # tag name of init Container image
    tag: 1.2.0
    # Pull Policy - Possible Values are:- Always, IfNotPresent, Never
   pullPolicy: Always
  updateContainersImage:
    # update Containers image name
    name: configurationupdate
    # tag name of update Container image
    tag: 1.2.0
    # Pull Policy - Possible Values are:- Always, IfNotPresent, Never
   pullPolicy: Always
  # enable jagger tracing
  jaegerTracingEnabled: false
  openTracing :
    jaeger:
      udpSender:
        # udpsender host
        host: "occne-tracer-jaeger-agent.occne-infra"
        # udpsender port
        port: 6831
      probabilisticSampler: 0.5
  # ---- Oauth Configuration - BEGIN ----
  oauthClientEnabled: false
 nrfAuthority: 10.75.224.7:8085
 nfInstanceId: fe7d992b-0541-4c7d-ab84-c6d70b1b01b1
  consumerPlmnMNC: 345
  consumerPlmnMCC: 567
  # ---- Oauth Configuration - END ----
 minReplicas: 1
 maxReplicas: 4
 minAvailable: 1
```



```
# ---- HTTPS Configuration - BEGIN ----
initssl: false
enableOutgoingHttps: false
# Resource details
resources:
  limits:
    cpu: 3
    memory: 4Gi
    initServiceCpu: 1
    initServiceMemory: 1Gi
    updateServiceCpu: 1
    updateServiceMemory: 1Gi
  requests:
    cpu: 3
    memory: 4Gi
    initServiceCpu: 1
    initServiceMemory: 1Gi
    updateServiceCpu: 1
    updateServiceMemory: 1Gi
  target:
    averageCpuUtil: 80
deployment:
  customExtension:
    labels: {}
    annotations: {}
service:
  type: ClusterIP
  customExtension:
    labels: {}
    annotations: {}
  ssl:
    tlsVersion: TLSv1.2
    initialAlgorithm: RSA256
    privateKey:
      k8SecretName: ocudr-gateway-secret
      k8NameSpace: ocudr
      rsa:
        fileName: rsa_private_key_pkcs1.pem
      ecdsa:
        fileName: ecdsa_private_key_pkcs8.pem
    certificate:
      k8SecretName: ocudr-gateway-secret
      k8NameSpace: ocudr
      rsa:
        fileName: apigatewayrsa.cer
      ecdsa:
        fileName: apigatewayecdsa.cer
    caBundle:
      k8SecretName: ocudr-gateway-secret
```



```
k8NameSpace: ocudr
        fileName: caroot.cer
      keyStorePassword:
        k8SecretName: ocudr-gateway-secret
        k8NameSpace: ocudr
        fileName: key.txt
      trustStorePassword:
        k8SecretName: ocudr-gateway-secret
        k8NameSpace: ocudr
        fileName: trust.txt
  # ---- HTTPS Configuration - END ----
  #Enable this if loadbalancing is to be done by egress instead of K8s
  K8ServiceCheck: false
  #Set the root log level
  loq:
    level:
      root: WARN
      egress: INFO
      oauth: INFO
nudr-diameterproxy:
  enabled: false
  image:
    name: ocudr/nudr_diameterproxy
    taq: 1.7.1
    pullPolicy: Always
  service:
   http2enabled: "true"
    type: ClusterIP
    diameter:
      type: LoadBalancer
    port:
      http: 5001
      https: 5002
      management: 9000
      diameter: 6000
    customExtension:
      labels: {}
      annotations: {}
  deployment:
    replicaCount: 2
    customExtension:
      labels: {}
      annotations: {}
  logging:
    level:
      root: "WARN"
```




```
resources:
   limits:
      cpu: 3
      memory: 4Gi
   requests:
      cpu: 3
      memory: 4Gi
    target:
      averageCpuUtil: 80
 minReplicas: 2
 maxReplicas: 4
 drservice:
   port:
      http: 5001
      https: 5002
 diameter:
   realm: "oracle.com"
    identity: "nudr.oracle.com"
    strictParsing: false
                          #strict parse message and AVP
    IO:
      threadCount: 0
                          # should not go beyond 2*CPU
      queueSize: 0
                          # range [2048-8192] should be power of 2
   messageBuffer:
                          # should not go beyond 2*CPU
      threadCount: 0
                          # range [1024-4096] and default 1024/Low,
      queueSize: 0
2048/Medium, 4096/High. should be power of 2
   peer:
      setting: |
         reconnectDelay: 3
         responseTimeout: 4
         connectionTimeOut: 3
         watchdogInterval: 6
         transport: 'TCP'
         reconnectLimit: 50
      nodes: |
       - name: 'seagull'
         responseOnly: false
         namespace: 'seagull1'
         host: '10.75.185.158'
         domain: 'svc.cluster.local'
         port: 4096
         realm: 'seagull1.com'
         identity: 'seagull1a.seagull1.com'
      clientNodes:
       - identity: 'seagull1a.seagull1.com'
         realm: 'seagull1.com'
       - identity: 'seagull1.com'
         realm: 'seagull1.com'
```



## **Configuring User Parameters**

The UDR micro services have configuration options. The user should be able to configure them via deployment values.yaml.



## Default Helm Release Name:- ocudr

**Global Configuration:** These values are suffixed to all the container names of OCNRF. These values are useful to add custom annotation(s) to all non-Load Balancer Type Services that OCNRF helm chart creates.

Parameter Description Default value Range or Notes **Possible Values** (If applicable) dockerRegistry Docker registry ocudr-Not applicable from where the registry.us.oracle. images will be com:5000 pulled mysql.dbService DB service to Not applicable This is a CNE mysql-Name connect connectivityservice used for service.occnedb connection. infra Default name used on CNE is the same as configured. Port for DB 3306 mysql.port Not applicable Service Connection udrTracing.enabl Flag to enable false true/false е udr tracing on Jaeger Jaegar Service udrTracing.host occne-tracer-Not applicable Name installed in jaeger-CNE collector.occneinfra

Following table provides the parameters for global configurations.



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
udrTracing.port	Jaegar Service Port installed in CNE	14268	Not applicable	
dbenc.shavalue	Encryption Key size	256	256 or 512	
serviceAccountN ame	Service account name	null	Not Applicable	The serviceaccount, role and rolebindings required for deployment should be done prior installation. Use the created serviceaccountna me here.
egress.enabled	Flag to enable outgoing traffic through egress gateway	true	true/false	
configServerEna ble	Flag to enable config-server	true	true/false	
initContainerEna ble	Flag to disable init container for config-server. This is not required because the pre install hooks take care of DB tables creation and connectivity is also verified	false	true/false	
dbCredSecretNa me	DB Credentioal Secret Name	ocudr-secrets	Not Applicable	
releaseDbName	Release Db Name	udr_release	Not Applicable	
configServerFull NameOverride	Config Server Full Name Override	nudr-config- server	Not Applicable	
udrServices	Services supported on the UDR deployment, This config will decide the schema execution on the udrdb which is done by the nudr- preinstall hook pod.	nudr-group-id- map	All/nudr-dr/nudr- group-id-map	This release is specifically for SLF, so default value is nudr- group-id-map



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
udsfEnable	Flag to enable UDSF services on the deployment	false	true/false	
test.nfName	NF name on which the helm test is performed. For UDR the default value is UDR. Will be used in container name as suffix	ocudr	Not applicable	
test.image.name	Image name for the helm test container image	ocudr/nf_test	Not Applicable	
test.image.tag	Image version tag for helm test	1.7.1	Not Applicable	
test.config.logLev el	Log level for helm test pod	WARN	Possible Values - WARN INFO DEBUG	
test.config.timeou t	Timeout value for the helm test operation. If exceeded helm test will be considered as failure	120	Range: 1-300 Unit:seconds	
preinstall.image.n ame	Image name for the nudr-prehook pod which will take care of DB and table creation for UDR deployment.	ocudr/prehook	Not Applicable	
preinstall.image.t ag	Image version for nudr-prehook pod image	1.7.1	Not Applicable	
preinstall.config.l ogLevel	Log level for preinstall hook pod	WARN	Possible Values - WARN INFO DEBUG	
hookJobResourc es.limits.cpu	CPU limit for pods created kubernetes hooks/jobs created as part of UDR installation. Applicable for helm test job as well.	2	Not Applicable	



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
hookJobResourc es.limits.memory	Memory limit for pods created kubernetes hooks/jobs created as part of UDR installation. Applicable for helm test job as well.	2Gi	Not Applicable	
hookJobResourc es.requests.cpu	CPU requests for pods created kubernetes hooks/jobs created as part of UDR installation. Applicable for helm test job as well.	1	Not Applicable	The cpu to be allocated for hooks during deployment
hookJobResourc es.requests.mem ory	Memory requests for pods created k8s hooks/jobs created as part of UDR installation. Applicable for helm test job as well.	1Gi	Not Applicable	The memory to be allocated for hooks during deployment
customExtension .allResources.lab els	Custom Labels that needs to be added to all the OCUDR kubernetes resources	null	Not Applicable	This can be used to add custom label(s) to all k8s resources that will be created by OCUDR helm chart.
customExtension .allResources.an notations	Custom Annotations that needs to be added to all the OCUDR kubernetes resources	null	Not Applicable Note: ASM related annotations needs to be added under ASM Specific Configuration section	This can be used to add custom annotation(s) to all k8s resources that will be created by OCUDR helm chart.
customExtension .lbServices.labels	Custom Labels that needs to be added to OCUDR Services that are considered as Load Balancer type	null	Not Applicable	This can be used to add custom label(s) to all Load Balancer Type Services that will be created by OCUDR helm chart.



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
customExtension .lbServices.annot ations		null	Not Applicable	This can be used to add custom annotation(s) to all Load Balancer Type Services that will be created by OCUDR helm chart.
customExtension .lbDeployments.l abels	Custom Labels that needs to be added to OCUDR Deployments that are associated to a Service which is of Load Balancer type	null	Not Applicable	This can be used to add custom label(s) to all Deployments that will be created by OCUDR helm chart which are associated to a Service which if of Load Balancer Type.
customExtension .lbDeployments.a nnotations	Custom Annotations that needs to be added to OCUDR Deployments that are associated to a Service which is of Load Balancer type	null	Not Applicable Note: ASM related annotations needs to be added under ASM Specific Configuration section	This can be used to add custom annotation(s) to all Deployments that will be created by OCUDR helm chart which are associated to a Service which if of Load Balancer Type.
customExtension .nonlbServices.la bels	Custom Labels that needs to be added to OCUDR Services that are considered as not Load Balancer type	null	Not Applicable	This can be used to add custom label(s) to all non-Load Balancer Type Services that will be created by OCUDR helm chart.
customExtension .nonlbServices.a nnotations	Custom Annotations that needs to be added to OCUDR Services that are considered as not Load Balancer type	null	Not Applicable	This can be used to add custom annotation(s) to all non-Load Balancer Type Services that will be created by OCUDR helm chart.



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
customExtension .nonlbDeploymen ts.labels	Custom Labels that needs to be added to OCUDR Deployments that are associated to a Service which is not of Load Balancer type	null	Not Applicable	This can be used to add custom label(s) to all Deployments that will be created by OCUDR helm chart which are associated to a Service which if not of Load Balancer Type.
customExtension .nonlbDeploymen ts.annotations	Custom Annotations that needs to be added to OCUDR Deployments that are associated to a Service which is not of Load Balancer type	null	Not Applicable Note: ASM related annotations to be added under ASM Specific Configuration section	This can be used to add custom annotation(s) to all Deployments that will be created by OCUDR helm chart which are associated to a Service which if not of Load Balancer Type.
k8sResource.con tainer.prefix	Value that will be prefixed to all the container names of OCUDR.	null	Not Applicable	This value will be used to prefix to all the container names of OCUDR.
k8sResource.con tainer.suffix	Value that will be suffixed to all the container names of OCUDR.	null	Not Applicable	This value will be used to prefix to all the container names of OCUDR.

Following table provides the parameters for **nudr-drservice micro service**.

Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
image.name	Docker Image name	ocudr/ nudr_datareposit ory_service	Not applicable	
image.tag	Tag of Image	1.7.1	Not applicable	
image.pullPolicy	This setting will tell if image need to be pulled or not		Possible Values - Always IfNotPresent Never	



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
subscriber.autocr eate	Flag to enable auto creation of subscriber	true	true/false	This flag will enable auto creation of subscriber when creating data for a non existent subscriber.
validate.smdata	Flag to enable correlation feature for smdata	false	true/false	This flag will control the correlation feature for smdata. This flag must be false if using v16.2.0 for PCF data.
logging.level.root	Log Level	WARN	Possible Values - WARN INFO DEBUG	Log level of the nudr-drservice pod
deployment.replic aCount	Replicas of nudr- drservice pod	2	Not applicable	Number of nudr- drservice pods to be maintained by replica set created with deployment
minReplicas	Minimum Replicas	2	Not applicable	Minimum number of pods
maxReplicas	Maximum Replicas	8	Not applicable	Maximum number of pods
service.http2enab led	Enabled HTTP2 support flag for rest server	true	true/false	Enable/Disable HTTP2 support for rest server
service.type	UDR service type	ClusterIP	Possbile Values- ClusterIP NodePort LoadBalancer	The kubernetes service type for exposing UDR deployment Note: Suggested to be set as ClusterIP (default value) always
service.port.http	HTTP port	5001	Not applicable	The http port to be used in nudr- drservice service
service.port.https	HTTPS port	5002	Not applicable	The https port to be used for nudr- drservice service
service.port.man agement	Management port	9000	Not applicable	The actuator management port to be used for nudr-drservice service



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
resources.reques ts.cpu	Cpu Allotment for nudr-drservice pod	3	Not applicable	The cpu to be allocated for nudr-drservice pod during deployment
resources.reques ts.memory	Memory allotment for nudr-drservice pod	4Gi	Not applicable	The memory to be allocated for nudr-drservice pod during deployment
resources.limits.c pu	Cpu allotment limitation	3	Not applicable	
resources.limits. memory	Memory allotment limitation	4Gi	Not applicable	
resources.target. averageCpuUtil	CPU utilization limit for autoscaling	80	Not Applicable	CPU utilization limit for creating HPA
notify.port.http	HTTP port on which notify service is running	5001	Not applicable	
notify.port.https	HTTPS port on which notify service is running	5002	Not applicable	
hikari.poolsize	Mysql Connection pool size	25	Not applicable	The hikari pool connection size to be created at start up
vsaLevel	The data level where the vsa which holds the 4G Policy data is added.	smpolicy	Not applicable	
tracingEnabled	Flag to enable/ disable jaeger tracing for nudr- drservice		true/false	
service.customEx tension.labels	Custom Labels that needs to be added to nudr- drservice specific Service.	null	Not Applicable	This can be used to add custom label(s) to nudr- drservice Service.
service.customEx tension.annotatio ns	Custom Annotations that needs to be added to nudr- drservice specific Services.	null	Not Applicable	This can be used to add custom annotation(s) to nudr-drservice Service.



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
deployment.custo mExtension.label s	Custom Labels that needs to be added to nudr- drservice specific deployment.		Not Applicable	This can be used to add custom label(s) to nudr- drservice Deployment.
deployment.custo mExtension.anno tations	Custom Annotations that needs to be added to nudr- drservice specific deployment.	null	Not Applicable	This can be used to add custom annotation(s) to nudr-drservice deployment.

Following table provides the parameters for **nudr-notify-service micro service**.

Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
enabled	flag for enabling or disabling nudr- notify-service	false	true or false	For SLF deployment, this micro service must be disabled.
image.name	Docker Image name	ocudr/ nudr_notify_servi ce	Not applicable	
image.tag	Tag of Image	1.7.1	Not applicable	
image.pullPolicy	This setting will tell if image need to be pulled or not	Always	Possible Values - Always IfNotPresent Never	
notification.retryc ount	Number of notifications to be attempted	3	Range: 1 - 10	Number of notification attempts to be done in case of notification failures.
				Whether retry should be done will be based on notification.retrye rrorcodes configuration.

Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
notification.retryin terval		5	Range: 1 - 60 Unit: Seconds	The retry interval for notifications in case of failure. Unit is in seconds. Whether retry should be done will be based on notification.retrye rrorcodes configuration.
notification.retrye rrorcodes	Notification failures eligible for retry	"400,429,500,503 "	Valid HTTP status codes comma seperated	Comma separated error code should be given. These error codes will be eligible for retry notifications in case of failures.
hikari.poolsize	Mysql Connection pool size	25	Not applicable	The hikari pool connection size to be created at start up
tracingEnabled	Flag to enable/ disable jaeger tracing for nudr- notify-service	false	true/false	
http.proxy.port	Port to connect to egress gateway	8080	Not applicable	
logging.level.root	Log Level	WARN	Possible Values - WARN INFO DEBUG	Log level of the notify service poo
deployment.replic aCount	Replicas of nudr- notify-service pod	2	Not applicable	Number of nudr- notify-service pods to be maintained by replica set created with deployment
minReplicas	Minimum Replicas	2	Not applicable	Minimum number of pods
maxReplicas	Maximum Replicas	4	Not applicable	Maximum number of pods
service.http2ena bled	Enabled HTTP2 support flag	true	true/false	This is a read only parameter. Do not change this value



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
service.type	UDR service type	ClusterIP	Possbile Values- ClusterIP NodePort LoadBalancer	The kubernetes service type for exposing UDR deployment
				Note: Suggested to be set as ClusterIP (default value) always
service.port.http	HTTP port	5001	Not applicable	The http port to be used in notify service to receive signals from nudr-notify- service pod.
service.port.https	HTTPS port	5002	Not applicable	The https port to be used in notify service to receive signals from nudr-notify- service pod.
service.port.man agement	Management port	9000	Not applicable	The actuator management port to be used for notify service.
resources.reques ts.cpu	Cpu Allotment for nudr-notify- service pod	3	Not applicable	The cpu to be allocated for notify service pod during deployment
resources.reques ts.memory	Memory allotment for nudr-notify- service pod	3Gi	Not applicable	The memory to be allocated for nudr-notify- service pod during deployment
resources.limits.c pu	Cpu allotment limitation	3	Not applicable	
resources.limits. memory	Memory allotment limitation	3Gi	Not applicable	
resources.target. averageCpuUtil	CPU utilization limit for autoscaling	80	Not Applicable	CPU utilization limit for creating HPA
service.customEx tension.labels	Custom Labels that needs to be added to nudr- notify-service specific service.	null	Not Applicable	This can be used to add custom label(s) tonudr- notify-service Service.



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
service.customEx tension.annotatio ns	Custom Annotations that needs to be added to nudr- notify-service specific services.	null	Not Applicable	This can be used to add custom annotation(s) to nudr-notify- service Service.
deployment.custo mExtension.label s	Custom Labels that needs to be added to nudr- notify-service specific deployment.	null	Not Applicable	This can be used to add custom label(s) to nudr- notify-service deployment.
deployment.custo mExtension.anno tations	Custom Annotations that needs to be added to nudr- notify-service specific deployment.	null	Not Applicable	This can be used to add custom annotation(s) to nudr-notify- service deployment.

Following table provides the parameters for **nudr-nrf-client-service micro service**.

Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
enabled	flag for enabling or disabling nudr- nrf-client-service	true	true/false	
host.baseurl	NRF url for registration	http://ocnrf- ingressgateway. mynrf.svc.cluster. local/nnrf- nfm/v1/nf- instances	Not applicable	Url used for udr to connect and register with NRF
host.proxy	Proxy Setting	NULL	nrfClient.host	Proxy setting if required to connect to NRF
ssl	SSL flag	false	true/false	SSL flag to enable SSL with udr nrf client pod
logging.level.root	Log Level	WARN	Possible Values - WARN INFO DEBUG	Log level of the UDR nrf client pod
image.name	Docker Image name	ocudr/ nudr_nrf_client_s ervice	Not applicable	
image.tag	Tag of Image	1.7.1	Not applicable	



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
image.pullPolicy	This setting will tell if image need to be pulled or not	Always	Possible Values - Always IfNotPresent Never	
heartBeatTimer	Heart beat timer	90	Unit: Seconds	
udrGroupId	Group ID of UDR	udr-1	Not applicable	
capacityMultiplier	Capacity of UDR	500	Not applicable	Capacity multiplier of UDR based on number of UDR pods running
supirange	Supi Range supported with UDR	[{\"start\": \"1000000000\", \"end\": \"20000000000\"} ]	Valid start and end supi range	
priority	Priority	10	Priority to be sent in registration request	Priority to be sent in registration request
fqdn	UDR FQDN	ocudr- ingressgateway. myudr.svc.cluster .local	Not Applicable	FQDN to used for registering in NRF for other NFs to connect to UDR. Note: Be cautious in updating this value. Should consider helm release name, namespace used for udr deployment and name resolution setting in k8s.
gpsirange	Gpsi Range supported with UDR	[{\"start\": \"1000000000\", \"end\": \"20000000000\"} ]	Valid start and end gpsi range	
livenessProbeMa xRetry	Max retries of liveness proble failed	5	This should be changed based on how many times do you want to retry	This should be changed based on how many times do you want to retry if liveness fails
udrMasterIpv4	Master IP of which we deployed	10.0.0.0	This should be changed with the master ip which we deployed	udrMasterIpv4 is used to send the ipv4 address to the nrf while registration.



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
plmnvalues	Plmn values range that it supports	[{\"mnc\": \"14\", \"mcc\": \"310\"}]	This values can be changed that the range it supports	Plmn values are sent to nrf during regisration from UDR.
scheme	scheme in which udr supports	http	This can be changed to https.	scheme which we send to NRF during registration
resources.reques ts.cpu	Cpu Allotment for nudr-notify- service pod	1	Not applicable	The cpu to be allocated for nrf client service pod during deployment
resources.reques ts.memory	Memory allotment for nudr-notify- service pod	2Gi	Not applicable	The memory to be allocated for nrf client service pod during deployment
resources.limits.c pu	Cpu allotment limitation	1	Not applicable	
resources.limits. memory	Memory allotment limitation	2Gi	Not applicable	
http.proxy.port	Port to connect egress gateway	8080	Not applicable	
service.customEx tension.labels	Custom Labels that needs to be added to nudr- nrf-client specific service.	null	Not Applicable	This can be used to add custom label(s) to nudr- nrf-client service.
service.customEx tension.annotatio ns	Custom Annotations that needs to be added to nudr- nrf-client specific services.	null	Not Applicable	This can be used to add custom annotation(s) to nudr-nrf-client service.
deployment.custo mExtension.label s	Custom Labels that needs to be added to nudr- nrf-client specific deployment.	null	Not Applicable	This can be used to add custom label(s) to nudr- nrf-client deployment.
deployment.custo mExtension.anno tations		null	Not Applicable Note: ASM related annotations to be added under ASM Specific Configuration section	This can be used to add custom annotation(s) to nudr-nrf-client deployment.

Following table provides the parameters for **nudr-config micro service**.



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
deployment.custo mExtension.anno tations	Custom Annotations that needs to be added to nudr- config specific Deployment.	null	Not applicable	This can be used to add custom annotation(s) to nudr-config Deployment.
deployment.custo mExtension.label s	Custom Labels that needs to be added to nudr- config specific Deployment.	null	Not applicable	This can be used to add custom label(s) to nudr- config Deployment.
deployment.replic aCount	Replicas of nudr- config pod	1	Not applicable	Number of nudr- config pods to be maintained by replica set created with deployment
image.name	Docker Image name	ocudr/ nudr_config	Not applicable	
image.pullPolicy	This setting indicates whether image needs to be pulled or not	Always	Possible Values - Always IfNotPresent Never	
image.tag	Tag of Image	1.7.1	Not applicable	
logging.level.root	Log Level	WARN	Possible Values - WARN INFO DEBUG	Log level of the nudr-config pod
maxReplicas	Maximum Replicas	1	Not applicable	Maximum number of pods
minReplicas	Minimum Replicas	1	Not applicable	Minimum number of pods
resources.limits.c pu	Cpu allotment limitation	2	Not applicable	
resources.limits. memory	Memory allotment limitation	2Gi	Not applicable	
resources.reques ts.cpu	Cpu Allotment for nudr-drservice pod	2	Not applicable	The cpu to be allocated for nudr-config pod during deployment
resources.reques ts.memory	Memory allotment for nudr-drservice pod	2Gi	Not applicable	The memory to be allocated for nudr-config pod during deployment



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
resources.target. averageCpuUtil	CPU utilization limit for autoscaling	80	Not Applicable	CPU utilization limit for creating HPA
service.customEx tension.annotatio ns	Custom Annotations that needs to be added to nudr- config specific Services.	null	Not applicable	This can be used to add custom annotation(s) to nudr-config Service.
service.customEx tension.labels	Custom Labels that needs to be added to nudr- config specific Service.	null	Not applicable	This can be used to add custom label(s) to nudr- config Service.
service.http2ena bled	Enabled HTTP2 support flag for rest server	true	true/false	Enable/Disable HTTP2 support for rest server
service.port.http	HTTP port	5001	Not applicable	The http port to be used in nudr- config service
service.port.https	HTTPS port	5002	Not applicable	The https port to be used for nudr- config service
service.port.man agement	Management port	9000	Not applicable	The actuator management port to be used for nudr-config service
service.type	UDR service type	ClusterIP	Possbile Values- ClusterIP NodePort	The kubernetes service type for exposing UDR deployment
			LoadBalancer	<b>Note:</b> Suggested to be set as ClusterIP (default value) always

Following table provides the parameters for **nudr-config-server Micro service**.

Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
envLoggingLevel App	Log Level	WARN	Possible Values - WARN INFO DEBUG	Log level of the nudr-config- server pod



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
replicas	Replicas of nudr- config-server pod	1	Not applicable	Number of nudr- config-server pods to be maintained by replica set created with deployment
resources.reques ts.cpu	Cpu Allotment for nudr-drservice pod	2	Not applicable	The cpu to be allocated for nudr-config- server pod during deployment
service.type	UDR service type	ClusterIP	Possbile Values- ClusterIP NodePort LoadBalancer	The kubernetes service type for exposing UDR deployment Note: Suggested to be set as ClusterIP (default value) always
resources.reques ts.memory	Memory allotment for nudr-drservice pod	512Mi	Not applicable	The memory to be allocated for nudr-config- server pod during deployment
enabled	Flag to enable/ disable nudr- config-server service	true	true/false	
global.nfName	It is NF name used to add with config server service name.	nudr	Not applicable	
global.imageServ iceDetector	Image Service Detector for config-server init container	ocudr/readiness- detector:latest	Not Applicable	
global.envJaeger AgentHost	Host FQDN for Jaeger agent service for config-server tracing		Not Applicable	
global.envJaeger AgentPort	Port for Connection to Jaeger agent for config-server tracing	6831	Valid Port	
resources.limits.c pu	Cpu allotment limitation	2	Not applicable	
resources.limits. memory	Memory allotment limitation	2Gi	Not applicable	



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
global.type	ocudr- ingressgateway service type	ClusterIP	Possbile Values- ClusterIP NodePort LoadBalancer	
global.metalLblp AllocationEnable d	Enable or disable Address Pool for Metallb	true	true/false	
global.metalLblp AllocationAnnotat ion	Address Pool for Metallb	metallb.universe.t f/address-pool: signaling	Not applicable	
global.staticNode PortEnabled	If Static node port needs to be set, then set staticNodePortEn abled flag to true and provide value for staticNodePort	false	Not applicable	
global.publicHttp SignalingPort	Port used on which ingressgateway listens for incoming http requests.	80	Valid Port	
global.publicHttp sSignallingPort	Port used on which ingressgateway listens for incoming https requests.	443	Valid Port	
image.name	Docker image name	ocudr/ ocingress_gatew ay	Not applicable	
image.tag	Image version tag	1.7.7	Not applicable	
image.pullPolicy	This setting will tell if image need to be pulled or not	Always	Possible Values - Always IfNotPresent Never	
initContainersIma ge.name	Docker Image name	ocudr/ configurationinit	Not applicable	
initContainersIma ge.tag	Image version tag	1.2.0	Not applicable	
initContainersIma ge.pullPolicy	This setting will tell if image need to be pulled or not	Always	Possible Values - Always IfNotPresent Never	

Following table provides parameters for **ocudr-ingressgateway micro service (API Gateway)** 



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
updateContainer sImage.name	Docker Image name	ocudr/ configurationupd ate	Not applicable	
updateContainer sImage.tag	Image version tag	1.2.0	Not applicable	
updateContainer sImage.pullPolicy	This setting will tell if image need to be pulled or not	Always	Possible Values - Always IfNotPresent Never	
service.ssl.tlsVer sion	Configuration to take TLS version to be used	TLSv1.2	Valid TLS version	These are service fixed parameters
service.ssl.privat eKey.k8SecretNa me	name of the secret which stores keys and certificates	ocudr-gateway- secret	Not applicable	
service.ssl.privat eKey.k8NameSp ace	namespace in which secret is created	ocudr	Not applicable	
service.ssl.privat eKey.rsa.fileNam e	rsa private key stored in the secret	rsa_private_key_ pkcs1.pem	Not applicable	
service.ssl.privat eKey.ecdsa.fileN ame	ecdsa private key stored in the secret	ecdsa_private_ke y_pkcs8.pem	Not applicable	
service.ssl.certifi cate.k8SecretNa me	name of the secret which stores keys and certificates	ocudr-gateway- secret	Not applicable	
service.ssl.certifi cate.k8NameSpa ce	namespace in which secret is created	ocudr	Not applicable	
service.ssl.certifi cate.rsa.fileName	rsa certificate stored in the secret	apigatewayrsa.ce r	Not applicable	
service.ssl.certifi cate.ecdsa.fileNa me	ecdsa certificate stored in the secret	apigatewayecdsa .cer	Not applicable	
service.ssl.caBun dle.k8SecretNam e	name of the secret which stores keys and certificates	ocudr-gateway- secret	Not applicable	
service.ssl.caBun dle.k8NameSpac e	namespace in which secret is created	ocudr	Not applicable	
service.ssl.caBun dle.fileName	ca Bundle stored in the secret	caroot.cer	Not applicable	



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
service.ssl.keySt orePassword.k8S ecretName	name of the secret which stores keys and certificates	ocudr-gateway- secret	Not applicable	
service.ssl.keySt orePassword.k8N ameSpace	namespace in which secret is created	ocudr	Not applicable	
service.ssl.keySt orePassword.file Name	keyStore password stored in the secret	key.txt	Not applicable	
service.ssl.trustSt orePassword.k8S ecretName	name of the secret which stores keys and certificates	ocudr-gateway- secret	Not applicable	
service.ssl.trustSt orePassword.k8N ameSpace	namespace in which secret is created	ocudr	Not applicable	
service.ssl.trustSt orePassword.file Name	trustStore password stored in the secret	trust.txt	Not applicable	
service.initialAlgo rithm	Algorithm to be used ES256 can also be used, but corresponding certificates need to be used.	RSA256	RSA256/ES256	
resources.limits.c pu	Cpu allotment limitation	5	Not applicable	
resources.limits. memory	Memory allotment limitation	4Gi	Not applicable	
resources.limits.i nitServiceCpu	Maximum amount of CPU that Kubernetes will allow the ingress-gateway init container to use.	1	Not Applicable	
resources.limits.i nitServiceMemor y	Memory Limit for ingress-gateway init container	1Gi	Not Applicable	
resources.limits.u pdateServiceCpu	Maximum amount of CPU that Kubernetes will allow the ingress-gateway update container to use.	1	Not Applicable	



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
resources.limits.u pdateServiceMe mory	Memory Limit for ingress-gateway update container	1Gi	Not Applicable	
resources.reques ts.cpu	Cpu allotment for ocudr-endpoint pod	5	Not Applicable	
resources.reques ts.memory	Memory allotment for ocudr-endpoint pod	4Gi	Not Applicable	
resources.reques ts.initServiceCpu	The amount of CPU that the system will guarantee for the ingress-gateway init container, <b>and K8s</b> will use this value to decide on which node to place the pod		Not Applicable	
resources.reques ts.initServiceMe mory	The amount of memory that the system will guarantee for the ingress-gateway init container, and Kubernetes will use this value to decide on which node to place the pod		Not Applicable	
resources.reques ts.updateService Cpu	The amount of CPU that the system will guarantee for the ingress-gateway update container, and Kubernetes will use this value to decide on which node to place the pod.		Not Applicable	
resources.reques ts.updateService Memory	The amount of memory that the system will guarantee for the ingress-gateway update container, and Kubernetes will use this value to decide on which node to place the pod.		Not Applicable	



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
resources.target. averageCpuUtil	CPU utilization limit for autoscaling	80	Not Applicable	
minAvailable	Number of pods always running	2	Not Applicable	
minReplicas	Min replicas to scale to maintain an average CPU utilization	2	Not applicable	
maxReplicas	Max replicas to scale to maintain an average CPU utilization	5	Not applicable	
log.level.root	Logs to be shown on ocudr- endpoint pod	WARN	valid level	
log.level.ingress	Logs to be shown on ocudr- ingressgateway pod for ingress related flows	INFO	valid level	
log.level.oauth	Logs to be shown on ocudr- ingressgateway pod for oauth related flows	INFO	valid level	
initssl	To Initialize SSL related infrastructure in init/update container	false	Not Applicable	
jaegerTracingEna bled	Enable/Disable Jaeger Tracing	false	true/false	
openTracing.jaeg er.udpSender.hos t	Jaeger agent service FQDN	occne-tracer- jaeger- agent.occne-infra	Valid FQDN	
openTracing.jaeg er.udpSender.por t	Jaeger agent service UDP port	6831	Valid Port	
openTracing.jaeg er.probabilisticSa mpler	Probablistic Sampler on Jaeger	0.5	Range: 0.0 - 1.0	Sampler makes a random sampling decision with the probability of sampling. For example, if the value set is 0.1, approximately 1 in 10 traces will be sampled



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
	Supported cipher suites for ssl	- TLS_ECDHE_EC DSA_WITH_AES _256_GCM_SHA 384 - TLS_ECDHE_RS A_WITH_AES_2 56_GCM_SHA38 4 - TLS_ECDHE_RS A_WITH_CHACH A20_POLY1305 _SHA256 - TLS_DHE_RSA_ WITH_AES_256 _ GCM_SHA384 - TLS_DHE_RSA_ WITH_AES_256 _ CCM - TLS_ECDHE_RSA_ WITH_AES_256 _ CCM - TLS_ECDHE_RSA_ WITH_AES_256 _ CCM - TLS_ECDHE_RSA_ WITH_AES_256 _ TLS_ECDHE_RS A_WITH_AES _128_GCM_SHA 256 - TLS_ECDHE_RS A_WITH_AES_1 28_GCM_SHA25 6	Not applicable	
oauthValidatorEn abled	OAUTH Configuration	false	Not Applicable	
enableIncomingH ttp	Enabling for accepting http requests	true	Not Applicable	
enableIncomingH ttps	Enabling for accepting https requests	false	true or false	
enableOutgoingH ttps	Enabling for sending https requests	false	true or false	
maxRequestsQu euedPerDestinati on	Queue Size at the ocudr- endpoint pod	5000	Not Applicable	



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
maxConnections Perlp	Connections from endpoint to other microServices	10	Not Applicable	
serviceMeshChe ck	Load balancing will be handled by Ingress gateway, if true it would be handled by serviceMesh	true	true/false	



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
routesConfig	Routes configured to connect to different micro services of UDR	<pre>- id: traffic_mapp ing_http uri: http://{{ .R elease.Name }}-nudr- drservice:50 01 path: / nudr-dr/** order: 1 - id: traffic_mapp ing_http_pro v uri: http://{{ .R elease.Name }}-nudr- drservice:50 01 path: / nudr-dr- prov/** order: 2 - id: traffic_mapp ing_http_mgm t uri: http://{{ .R elease.Name }}-nudr- drservice:50 01 path: / nudr-dr- prov/** order: 2 - id: traffic_mapp ing_http_mgm t uri: http://{{ .R elease.Name }}-nudr- drservice:50 01 path: / nudr-dr- mgm/** order: 3 - id: traffic_mapp ing_http_uds f uri: http://{{ .R elease.Name }}-nudr- drservice:50</pre>	Not Applicable	



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
		drservice:50		
		01		
		path: /		
		nudsf-dr/**		
		order: 4		
		- id:		
		traffic_mapp		
		ing_http_gro		
		up		
		uri:		
		http://{{ .R		
		elease.Name		
		}-nudr-		
		drservice:50		
		01		
		path: /		
		nudr-group-		
		id-map/**		
		order: 5		
		- id:		
		traffic_mapp		
		ing_http_gro		
		up_prov		
		uri:		
		http://{{ .R		
		elease.Name		
		}}-nudr-		
		drservice:50		
		01		
		path: /		
		nudr-group-		
		id-map-		
		prov/**		
		order: 6		
		- id:		
		traffic_mapp		
		ing_http_slf		
		_group_prov		
		uri:		
		http://{{ .R		
		elease.Name		
		}}-nudr-		
		drservice:50		
		01		
		path: /slf-		
		group-		
		prov/**		
		order: 7		



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
service.customEx tension.labels	Custom Labels that needs to be added to ingressgateway specific service.	null	Not Applicable	This can be used to add custom label(s) to ingressgateway service.
service.customEx tension.annotatio ns	Custom Annotations that needs to be added to ingressgateway specific services.	null	Not Applicable	This can be used to add custom annotation(s) to ingressgateway service.
deployment.custo mExtension.label s	Custom Labels that needs to be added to ingressgateway specific deployment.	null	Not Applicable	This can be used to add custom label(s) to ingressgateway deployment.
deployment.custo mExtension.anno tations	Custom Annotations that needs to be added to ingressgateway specific deployment.	null	Not Applicable	This can be used to add custom annotation(s) to ingressgateway deployment.

Following table provides parameters for **ocudr-egressgateway micro service (API Gateway)** 

Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
enabled	Configuration flag to enable/disable egress gateway	true	true/false	
image.name	Docker image name	ocudr/ ocegress_gatewa y	Not applicable	
image.tag	Image version tag	1.7.7	Not applicable	
image.pullPolicy	This setting will tell if image need to be pulled or not	Always	Possible Values - Always IfNotPresent Never	
initContainersIma ge.name	Docker Image name	ocudr/ configurationinit	Not applicable	
initContainersIma ge.tag	Image version tag	1.2.0	Not applicable	



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
initContainersIma ge.pullPolicy	This setting will tell if image need to be pulled or not	Always	Possible Values - Always IfNotPresent Never	
updateContainer sImage.name	Docker Image name	ocudr/ configurationupd ate	Not applicable	
updateContainer sImage.tag	Image version tag	1.2.0	Not applicable	
updateContainer sImage.pullPolicy	This setting will tell if image need to be pulled or not	Always	Possible Values - Always IfNotPresent Never	
resources.limits.c pu	Cpu allotment limitation	3	Not applicable	
resources.limits. memory	Memory allotment limitation	4Gi	Not applicable	
resources.limits.i nitServiceCpu	Maximum amount of CPU that Kubernetes will allow the egress-gateway init container to use.	1	Not applicable	
resources.limits.i nitServiceMemor y	Memory Limit for egress-gateway init container	1Gi	Not applicable	
resources.limits.u pdateServiceCpu	Maximum amount of CPU that Kubernetes will allow the egress-gateway update container to use.	1	Not applicable	
resources.limits.u pdateServiceMe mory	Memory Limit for egress-gateway update container	1Gi	Not applicable	
resources.reques ts.cpu	Cpu allotment for ocudr- egressgateway pod	3	Not applicable	
resources.reques ts.memory	Memory allotment for ocudr- egressgatewaypo d	4Gi	Not applicable	



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
resources.reques ts.initServiceCpu	The amount of CPU that the system will guarantee for the egress-gateway init container, and Kubernetes will use this value to decide on which node to place the pod		Not Applicable	
resources.reques ts.initServiceMe mory	The amount of memory that the system will guarantee for the egress-gateway init container, and Kubernetes will use this value to decide on which node to place the pod		Not Applicable	
resources.reques ts.updateService Cpu	The amount of CPU that the system will guarantee for the egress-gateway update container, and Kubernetes will use this value to decide on which node to place the pod.		Not Applicable	
resources.reques ts.updateService Memory	The amount of memory that the system will guarantee for the egress-gateway update container, and Kubernetes will use this value to decide on which node to place the pod.		Not Applicable	
resources.target. averageCpuUtil	CPU utilization limit for autoscaling	80	Not applicable	
service.ssl.tlsVer sion	Configuration to take TLS version to be used	TLSv1.2	Valid TLS version	These are service fixed parameters

Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
service.initialAlgo rithm	Algorithm to be used ES256 can also be used, but corresponding certificates need to be used.	RSA256	RSA256/ES256	
service.ssl.privat eKey.k8SecretNa me	name of the secret which stores keys and certificates	ocudr-gateway- secret	Not applicable	
service.ssl.privat eKey.k8NameSp ace	namespace in which secret is created	ocudr	Not applicable	
service.ssl.privat eKey.rsa.fileNam e	rsa private key stored in the secret	rsa_private_key_ pkcs1.pem	Not applicable	
service.ssl.privat eKey.ecdsa.fileN ame	ecdsa private key stored in the secret	ecdsa_private_ke y_pkcs8.pem	Not applicable	
service.ssl.certifi cate.k8SecretNa me	name of the secret which stores keys and certificates	ocudr-gateway- secret	Not applicable	
service.ssl.certifi cate.k8NameSpa ce	namespace in which secret is created	ocudr	Not applicable	
service.ssl.certifi cate.rsa.fileName	rsa certificate stored in the secret	apigatewayrsa.ce r	Not applicable	
service.ssl.certifi cate.ecdsa.fileNa me	ecdsa certificate stored in the secret	apigatewayecdsa .cer	Not applicable	
service.ssl.caBun dle.k8SecretNam e	name of the secret which stores keys and certificates	ocudr-gateway- secret	Not applicable	
service.ssl.caBun dle.k8NameSpac e	namespace in which secret is created	ocudr	Not applicable	
service.ssl.caBun dle.fileName	ca Bundle stored in the secret	caroot.cer	Not applicable	
service.ssl.keySt orePassword.k8S ecretName	name of the secret which stores keys and certificates	ocudr-gateway- secret	Not applicable	
service.ssl.keySt orePassword.k8N ameSpace	namespace in which secret is created	ocudr	Not applicable	



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
service.ssl.keySt orePassword.file Name	keyStore password stored in the secret	key.txt	Not applicable	
service.ssl.trustSt orePassword.k8S ecretName	name of the secret which stores keys and certificates	ocudr-gateway- secret	Not applicable	
service.ssl.trustSt orePassword.k8N ameSpace	namespace in which secret is created	ocudr	Not applicable	
service.ssl.trustSt orePassword.file Name	trustStore password stored in the secret	trust.txt	Not applicable	
minAvailable	Number of pods always running	1	Not Applicable	
minReplicas	Min replicas to scale to maintain an average CPU utilization	1	Not applicable	
maxReplicas	Max replicas to scale to maintain an average CPU utilization	4	Not applicable	
log.level.root	Logs to be shown on ocudr- egressgateway pod	WARN	valid level	
log.level.egress	Logs to be shown on ocudr- egressgateway pod for egress related flows	INFO	valid level	
log.level.oauth	Logs to be shown on ocudr- egressgateway pod for oauth related flows	INFO	valid level	
fullnameOverride	Name to be used for deployment	ocudr- egressgateway	Not applicable	This config is commented by default.
initssl	To Initialize SSL related infrastructure in init/update container	false	Not Applicable	
jaegerTracingEna bled	Enable/Disable Jaeger Tracing	false	true/false	
openTracing.jaeg er.udpSender.hos t	Jaeger agent service FQDN	occne-tracer- jaeger- agent.occne-infra	Valid FQDN	



Parameter	er Description Default value Range or Possible Values (If applicable)		Notes	
openTracing.jaeg er.udpSender.por t	Jaeger agent service UDP port	6831	Valid Port	
openTracing.jaeg er.probabilisticSa mpler	Probablistic Sampler on Jaeger	0.5	5 Range: 0.0 - 1.0	
enableOutgoingH ttps	Enabling for sending https requests	false	true or false	
oauthClientEnabl ed	Enable if oauth is required	false	true or false	Enable based on Oauth configuration
nrfAuthority	Nrf Authoriy configuration	10.75.224.7:8085	Not Applicable	
nfInstanceId	Nrf Instance Id	fe7d992b-0541-4 c7d-ab84- c6d70b1b01b1	Not Applicable	
consumerPlmnM NC	plmnmnc	345	Not Applicable	
consumerPlmnM CC	plmnmcc	567	Not Applicable	
k8sServiceCheck	Enable this if loadbalancing is to be done by egress instead of K8s	false	true/false	
service.customEx tension.labels	Custom Labels that needs to be added to egressgateway specific Service.	null	Not applicable	This can be used to add custom label(s) to egressgateway Service.
service.customEx tension.annotatio ns	Custom Annotations that needs to be added to egressgateway specific Services.	null	Not applicable	This can be used to add custom annotation(s) to egressgateway Service.
deployment.custo mExtension.label s	Custom Labels that needs to be added to egressgateway specific Deployment.	null	III Not applicable	



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
deployment.custo mExtension.anno tations		null	Not applicable	This can be used to add custom annotation(s) to egressgateway deployment.

Following table provides parameters for **nudr-diameterproxy micro service**.

Parameter			Range or Possible Values (If applicable)	Notes
enabled	To enable service.	false	Not applicable	Used to enable or disable service.
image.name	Docker Image name	ocudr/ nudr_diameterpr oxy	Not applicable	
image.tag	Tag of Image	1.7.1	Not applicable	
image.pullPolicy	This setting will tell if image need to be pulled or not	Always	Possible Values - Always IfNotPresent Never	
logging.level.root	Log Level	WARN	Possible Values - WARN INFO DEBUG	The log level of the nudr- diameterproxy server pod
deployment.replic aCount	Replicas of the nudr- diameterproxy pod	2	Not applicable	Number of nudr- config-server pods to be maintained by replica set created with deployment
minReplicas	min replicas of nudr- diameterproxy	2	Not applicable	Minimum number of pods
maxReplicas	max replicas of nudr- diameterproxy	4	Not applicable	Maximum number of pods
service.http2ena bled	Enabled HTTP2 support flag for rest server	true	true/false	Enable/Disable HTTP2 support for rest server



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
service.type	UDR service type	ClusterIP	Possible Values- ClusterIP NodePort LoadBalancer	The Kubernetes service type for exposing UDR deployment Note: Suggested to be set as ClusterIP (default value) always
service.diameter.t ype	Diameter service type	LoadBalancer	Possible Values- ClusterIP NodePort LoadBalancer	The Kubernetes service type for exposing UDR deploymentdiame ter traffic goes via diameter- endpoint, not via ingress-gateway
service.port.http	HTTP port	5001	Not applicable	The HTTP port to be used in nudr- diameterproxy service
service.port.https	HTTPS port	5002	Not applicable	The https port to be used for nudr- diameterproxy service
service.port.man agement	Management port	9000	Not applicable	The actuator management port to be used for nudr- diameterproxy service
service.port.diam eter	Diameter port	6000	Not applicable	The diameter port to be used for nudr- diameterproxy service
resources.reques ts.cpu	Cpu Allotment for nudr- diameterproxy pod	3	Not applicable	The CPU to be allocated for nudr- diameterproxy pod during deployment
resources.reques ts.memory	Memory allotment for nudr- diameterproxy pod	4Gi	Not applicable	The memory to be allocated for nudr- diameterproxy pod during deployment
resources.limits.c pu	Cpu allotment limitation	3	Not applicable	The CPU to be max allocated for nudr- diameterproxy pod



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
resources.limits. memory	Memory allotment limitation	4Gi	Not applicable	The memory to be max allocated for nudr- diameterproxy pod
resources.target. averageCpuUtil	CPU utilization limit for autoscaling	80	Not Applicable	CPU utilization limit for creating HPA
drservice.port.htt p	HTTP port on which dr service is running	5001	Not Applicable	dr-service port is required in diameterproxy application
drservice.port.htt ps	HTTPS port on which dr service is running	5002	Not Applicable	dr-service port is required in diameterproxy application
diameter.realm	Realm of the diameterproxy microservice	oracle.com	String value	Host realm of diameterproxy
diameter.identity	FQDN of the diameterproxy in diameter messages	nudr.oracle.com	String value	identity of the diameterproxy
diameter.strictPar sing	Strict parsing of Diameter AVP and Messages	false	Not Applicable	strict parsing
diameter.IO.threa dCount	Number of thread for IO operation	0	0 to 2* CPU	Number of threads to handle IO operations in diameterproxy pod
				if threadcount is 0 then application choose the threadCount based on pod profile size
diameter.IO.queu eSize	Queue size for IO	0	2048 to 8192	the count should be the power of 2 if queueSize is 0 then application choose the queueSize based on pod profile size

Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
diameter.messag eBuffer.threadCo unt	Number of threads for process the message	0	0 to 2* CPU	Number of threads to handle meassages in diameterproxy pod if threadcount is 0 then application choose the threadCount based on pod profile size
diameter.peer.set ting	Diameter peer setting	reconnectDelay: 3 responseTimeout : 4 connectionTimeO ut: 3 watchdogInterval: 6 transport: 'TCP' reconnectLimit: 50	Not Applicable	<ol> <li>reconnect delay for diameter reonnect (in seconds).</li> <li>total turnaround time for process the diameter messages. (in sec)</li> <li>TCP connection timeout time. (in sec)</li> <li>DWR and DWA messages every number of time (in sec)</li> <li>Transport layer</li> <li>reconnect the number of time if diameter peer is down</li> </ol>



Parameter	Description	Default value	Range or Possible Values (If applicable)	Notes
diameter.peer.no des	diameter server peer nodes list	- name: 'seagull' responseOnly: false namespace: 'seagull1' host: '10.75.185.158' domain: 'svc.cluster.local' port: 4096 realm: 'seagull1.com' identity: 'seagull1a.seagul 11.com'	Not applicable	the diameter server peer node information *it should be yaml list *default values are template , how to add peer nodes.
diameter.peer.clie ntNodes	diameter client peers	<ul> <li>identity:</li> <li>'seagull1a.seagul</li> <li>l1.com'</li> <li>realm:</li> <li>'seagull1.com'</li> <li>identity:</li> <li>'seagull1.com'</li> <li>realm:</li> <li>'seagull1.com'</li> </ul>	Not applicable	the diameter client node information *it should be yaml list *default values is template, how to add peer nodes.
service.customEx tension.labels	Custom Labels that needs to be added to nudr- diameterproxy specific Service.	null	Not applicable	This can be used to add custom label(s) to nudr- diameterproxy Service.
service.customEx tension.annotatio ns	Custom Annotations that needs to be added to nudr- diameterproxy specific Services.	null	Not applicable	This can be used to add custom annotation(s) to nudr- diameterproxy Service.
deployment.custo mExtension.label s	Custom Labels that needs to be added to nudr- diameterproxy specific Deployment.	null	Not applicable	This can be used to add custom label(s) to nudr- diameterproxy Deployment.
deployment.custo mExtension.anno tations	Custom Annotations that needs to be added to nudr- diameterproxy specific Deployment.	null	Not applicable	This can be used to add custom annotation(s) to nudr- diameterproxy Deployment.

# 4 Upgrading an Existing Unified Data Repository Deployment

### Note:

IF YOU HAVE ENABLED SERVICE MESH THEN YOU HAVE TO INSTALL UDR. YOU CANNOT UPGRADE FROM UDR 1.7.0 TO UDR 1.7.1. HOWEVER, IF THE SERVICE MESH IS NOT ENABLED THEN YOU CAN UPGRADE FROM UDR 1.7.0 TO UDR 1.7.1 BY FOLLOWING THE HELM UPGRADE SECTION DIRECTLY. WHILE UPGRADING, YOU CAN SKIP THE DB SCHEMA UPGRADE SECTION.

To upgrade an existing UDR deployment, first upgrade the DB schema and then, perform the helm upgrade.

User should stop the Provisioning traffic while performing the upgrade procedure.

### Note:

For SLF, upgrade feature is not supported from 1.7.0 to 1.7.1. Hence, these instructions are not applicable for the same.

#### **DB Schema Upgrade**

You should install <code>mysql-connector</code> and <code>Python3</code> before upgrading the DB schema. If <code>Python3</code> is not available, then execute the commands given below on one of the sql nodes for dbschema upgrade.

```
yum install gcc openssl-devel bzip2-devel sqlite-devel
cd /usr/src/
wget https://www.python.org/ftp/python/3.6.10/Python-3.6.10.tgz
tar xzf Python-3.6.10.tgz
cd Python-3.6.10
./configure --enable-optimizations
make altinstall
python3.6 -V (To check if installation is OK)
```

To install  ${\tt mysql-connector}$  using pip, execute the following commands on the sql node.

```
python3.6 -m pip install -U setuptools
python3.6 -m pip install -U wheel
python3.6 -m pip install -U mysql-connector-python-rf
```



Modify username, password and db name in the script as per requirement.

#### Note:

You can refer to the Oracle Help Center for **upgrade.py** script to upgrade to 1.7.0 schema.

For db upgrade, execute the following command:

python3.6 upgrade.py

#### **Helm Upgrade**

Upgrading an existing deployment replaces the running containers and pods with new containers and pods. If there is no change in the pod configuration, it is not replaced. Unless there is a change in the service configuration of a micro service, the service endpoints remain unchanged. For example, ClusterIP.

- To upgrade, follow instructions given in the Deploying OCUDR section to extract the required OCUDR software components. If required, re-tag and push the images to customer's repository. For more information, see UDR Deployment.
- Take a backup of 1.6.0 version's ocudr-custom-values.yaml file before changing any configuration.
- Modify the ocudr-custom-values-1.7.0.yaml file parameters as per site requirement. For more information on updating the ocudr-customvalues-1.7.0.yaml file, see ocudr-custom-values.yaml File Configuration.

Execute the following command to upgrade an existing Unified Data Repository deployment. For the parameters that are configurable, see . Customizing Unified Data Repository

\$ helm upgrade <release> <helm chart> [--version <OCUDR version>] -f
<ocudr-custom-values-1.7.0.yaml>

<release> could be found in the output of 'helm list' command <chart> is the name of the chart in the form of <repository/ocudr> e.g. reg-1/ocudr or cne-repo/ocudr

#### **Rollback Instructions**

Execute the following command to check if the pods are successfully started.

kubectl get pods -n <namespace\_name>

If there are issues that a user cannot recover on checking logs and describe on pods, rollback using the steps below:

#### Schema Rollback:

- **1.** Rollback schema to 1.6.0.
- Use the rollback.py script to downgrade to 1.6.0 schema, modify username, password and db name as per requirement. python rollback.py



### Note:

You can refer to the Oracle Help Center site for the rollback.py script.

#### Image Rollback using Helm:

- **1.** Use the backed up customized 1.6.0 version's **ocudr-values.yaml** file to rollback to previous version.
- 2. Execute the helm rollback command. helm rollback <helm release name> <revision\_no>

To obtain the revision number, execute the following command : helm history <helm release name>



# 5 Troubleshooting Unified Data Repository

In this chapter, you will learn about the known issues that you may encounter while installing or working on Unified Data Repository and the techniques to troubleshoot these issues. It covers:

- Generic Checklist
- Verifying UDR Registration with NRF
- Verifying Container Logs
- Verifying OCUDR Micro Services Logs
- Debugging Errors from Egress Gateway
- Debugging Errors from Ingress Gateway
- Debugging Helm Test Issues
- Debugging HPA Issues
- Debugging HTTPS Support related Issues
- Debugging Notification Issues
- Debugging Pod Creation Failure
- Debugging UDR Registration with NRF Failure

## **Generic Checklist**

The following generic checklist helps you to ensure that your system is configured properly and there is no issue with basic system setup:

Execute the following command to check the installation of kubectl.
 \$ kubect1

If Kubectl is not installed, you can visit https://kubernetes.io/docs/tasks/tools/ install-kubectl/

Execute the following command to check the installation of helm.
 \$ helm ls

If helm is not installed, execute the following set of commands one after another to install helm:

- 1. curl -o /tmp/helm.tgz https://storage.googleapis.com/kubernetes-helm/helm-v2.9.1linux-amd64.tar.gz. Replace with appropriate http link.
- 2. tar -xzvf /tmp/helm.tgz -C /usr/local/bin --strip-components=1
  linux-amd64/helmrm -f /tmp/helm.tgz
- 3. kubectl create serviceaccount --namespace kube-system tiller
- 4. kubectl create clusterrolebinding tiller-cluster-rule -clusterrole=cluster-admin --serviceaccount=kube-system:tiller
- 5. helm init --service-account tiller



- 6. kubectl get po -n kube-system # Wait for tiller pod to be up
- helm ls # Does not return an error. Try again if returns an error as tiller pod may be coming up.
- 8. helm install. If this command fails immediately with syntax error, check the syntax and values in the values.yaml file. [If values.yaml file is used in helm install command, else contact the UDR development team.]
- Execute the following command to check the installation of UDR.
   \$ kubectl get pods -n <ocudr-namespace>

### Figure 5-1 Sample Output: UDR Pods Status

NAME	READY	STATUS	RESTARTS	AGE
ocudr-egressgateway-79fcffcd6b-2x85v	1/1	Running		13h
ocudr-ingressgateway-b48cc8bc4-qzstd	1/1	Running		13h
ocudr-nudr-config-64b8d8b9db-zzc7w	1/1	Running		13h
ocudr-nudr-config-server-cbd98d94f-pq8pf	1/1	Running		13h
ocudr-nudr-diameterproxy-f5f6494c6-lsx2d	1/1	Running		13h
ocudr-nudr-drservice-894f8f857-qvxrk	1/1	Running		13h
ocudr-nudr-notify-service-55db555984-bm5w5	1/1	Running		13h
ocudr-nudr-nrf-client-service-5986795678-vxd18	1/1	Running		13h

In the figure given above, the STATUS of all the pods is 'Running'.

 Execute the following command to view all the events related to a particular namespace.

kubectl get events -n <ocudr-namespace>

 Verify UDR Pods: Execute the following command to verify whether UDR specific pods are working as expected:

#### Figure 5-2 Sample Output: UDR Pods Status

[root@master ocudr]# kubectl get pods -n udr1-1				
NAME	READY	STATUS	RESTARTS	AGE
ocudr-ingressgateway-57b576cb94-wrmb4	1/1	Running		9m56s
ocudr-nudr-drservice-799484d597-dckwr	1/1	Running		9m56s
ocudr-nudr-notify-service-76f54c64bd-w5wtl	1/1	Running		9m56s
ocudr-nudr-nrf-client-service-65567975c4-vc6ps	1/1	Running		9m56s

In the figure given above, you can see that the status of all the pods is 'Running'.

### Note:

The number of pods for each service depends on helm configuration. In addition, all pods should be in ready state and you need to ensure that there are no continuous restarts.

 Verify Database Connectivity: After verifying UDR pods, login to NDB cluster and verify the creation of udrdb with all the tables. To check the entries in the database tables, you need to execute following command: select count(\*) from RESOURCE\_MAP



<sup>\$</sup> kubectl get pods -n <ocudr-namespace>

It ensures that the connection is fine and the database is created successfully. This count differs based on the **udrServices** option selected under global section in values. But this table cannot be empty.

Figure 5-3 Sample Output: Verifying Table Entries in Database



- Verify Subscribers: To verify UDR subscribers, you need to verify the provisioning flow on UDR. You can use the following provisioning URL supported on UDR to verify the provisioning flow:
  - If you use external tools like postman and http2 curl, then follow this URL: http://<ocudr-ingress-gateway-ip>:<http-external-port>/nudr-drprov/v1/profile-data/msisdn-1111111113

In case of curl, the client should support a http2 curl utility.

If https is enabled in UDR ingress gateway, then follow this URL: https://<ocudr-ingress-gateway-ip>:<https-external-port>/nudr-drprov/v1/profile-data/msisdn-1111111113

Verifying provisioning flow on UDR also confirms udrdb status on the NDB cluster.

- Verify Logs: Check the logs of nudr-nrf-client-service for no 503 errors. This helps to find out if all the fqdn configured, as part of helm configurations, in values are resolvable.
- Verify NRF registration: Once the deployment has passed the above checks, verify the udr\_nrf\_registration\_success\_total metric on prometheus after couple of minutes of UDR deployment.

### Verifying UDR Registration with NRF

Execute the following commands to verify whether UDR is registered with NRF.

#### • With HTTP1 messaging

curl -v -X GET --url 'http://<FQDN:PORT of NRF-API\_Gateway>/nnrfnfm/v1/nf-instances?nf-type=UDR'

**Example:** curl -v --http2-prior-knowledge -X GET --url 'http://ocnrfingressgateway.ocnrf/nnrf-nfm/v1/nf-instances?nf-type=UDR'

#### With HTTP2 messaging

curl -v --http2-prior-knowledge -X GET --url 'http://<FQDN:PORT of NRF-API\_Gateway>/nnrf-nfm/v1/nf-instances?nf-type=UDR'

**Example:** curl -v --http2-prior-knowledge -X GET --url 'http://ocnrfingressgateway.ocnrf/nnrf-nfm/v1/nf-instances?nf-type=UDR'





### Verifying Container Logs

You can check the container logs in the *lvar/log/containers* location on the appropriate nodes where the pods are running.

#### Figure 5-4 Container Logs

```
[root@olslave2'containers]# ls | grep nudr
ocudr-nudr-notify-service-74dddf64b5-46d7b_default_ocudr-nudr-notify-service-3f99b648224db59ff5d2b5af15a2c125d5d107092a66a85a3
5eff2817bb8009.log
ocudr-nudr-nrf-client-service-9c59d9f7b-ckt8j_default_ocudr-nudr-nrf-client-service-7ac9715d072d204a3969b17e90b44067316cb673ff
86b0843902472e42444c70.log
[root@olslave2 containers]# pwd
/var/log/containers
[root@olslave1 containers]# containers]#
[root@olslave1 containers]#
[root@olslave1 containers]#
[root@olslave1 containers]# ls | grep nudr
ocudr-nudr-drservice-646495555d-q7mlf_default_ocudr-nudr-drservice-d17386177f17dba7d4756f98d49779327b1be2bd2cdc88eebbad43c54a9
a5bce.log
```

### Verifying OCUDR Microservices Logs

In this section, you will learn to check logs of the following microservices:

- OCUDR-NUDR-DRSERVICE
- NRF-CLIENT-SERVICE
- NUDR-NOTIFY-SERVICE
- NUDR-CONFIG-SERVICE
- NUDR-CONFIG-SERVER
- NUDR-DIAMETERPROXY Service

Checking Logs in OCUDR-NUDR-DRSERVICE

**OCUDR-NUDR-DRSERVICE** dumps all the header while processing messages. User should search for "Before Request/After Request" header in the messages. If nudr-drservice requests are failing, check the count of **udr\_schema\_operations\_failure\_total measurement**. If this count is increasing:

- · Check the content of incoming requests
- Ensure that the incoming json data blob is proper
- Connectivity between microservices are mysql DB nodes
- Try not to insert duplicate keys
- Ensure DB nodes have enough resources available

To view logs, execute the following command: kubectl logs -f <nudr-drservice pod> -n <ocudr-namespace>

To check logs directly on the pods, execute the following command:



kubectl exec -it ocudr-nudr-drservice-779c67b9f-sjcmv bash

To change logging level in the ocudr-nudr-drservice using helm:

- Open the latest ocudr\_value.yaml file that is used at the time of ocudr installation/ upgrade.
- 2. Change the value of "logging level root" attribute under "ocudr" to "INFO".

```
Note:
```

OCUDR supports logging level values: DEBUG, INFO, WARN and ERROR.

3. Execute the following helm upgrade command to change the log level: helm upgrade ocudr ocudr-helm-repo/ocudr -f <updated values.yaml with logging level as INFO> --version <helm version>

#### Checking Logs in NUDR-NRF-CLIENT-SERVICE

If the count of **udr\_nrf\_livenessProbe\_failure\_total measure** increases, you need to ensure that helm charts configuration for "nudr-nrf-client-service" is correct and NRF server is up and running fine.

If nudr-nrf-client-service is not able to register with NRF and there is a difference between "udr\_nrf\_registration\_requests\_total" and "udr\_nrf\_registration\_success\_total", then you need to ensure that helm charts configuration for "nudr-nrf-client-service" are correct.

If nudr-nrf-client-service is not able to de-register with NRF and there is a difference between "udr\_nrf\_deregistration\_requests\_total" and "udr\_nrf\_deregistration\_success\_total", then you need to ensure that helm charts configuration for "nudr-nrf-client-service" are correct.

To view the NUDR-NRF-CLIENT-SERVICE logs, execute the following command:

kubectl logs <nrf-client-pod pod> -n <ocudr-namespace>

To check logs directly on the pods, refer to the screen given below:

#### Figure 5-5 NRF-Client-Service Logs

[admusr@olmaster ~]\$ kubectl	get poo	is	gre	ep nud	r			
ocudr-nudr-drservice-779c67b9	f-sjcmv	7			1/1	Running	0	157m
ocudr-nudr-notify-service-77f	74ffbc-	-v771	4		1/1	Running	0	157m
ocudr-nudr-nrf-client-service	-6d9854	fbd4	-2n	ahmp	1/1	Running	0	157m
<pre>[admusr@olmaster ~]\$ kubectl bash-4.2\$ cd /home/udruser/ bash-4.2\$ ls -1 total 908</pre>	exec -j	it oc	udı	r-nudr-	-nrf-client	-service-60	19854fb	d4-2mhmp bash
drwxr-xr-x 1 udruser udruser	36	Oct	7	09:27	app			
-rw-rr 1 udruser udruser	906279	Oct	9	08:20	application	n.log		
-rwxrwxr-x 1 root root	219	Oct	7	09:21	healthchec	k.sh		
-rwxrwxr-x 1 root root	222	Oct	7	09:21	runService	.sh		

To change logging level in the nrf-client-service using helm:

 Open the latest ocudr\_value.yaml file that is used at the time of ocudr installation/ upgrade.



2. Change the value of "logging level root" attribute under "nrfclient" to "INFO".

Note:

nudr-nrf-client-service supports logging level values: DEBUG, INFO, WARN and ERROR.

3. Execute the following helm upgrade command to change the log level: helm upgrade ocudr ocudr-helm-repo/ocudr -f <updated values.yaml with logging level as INFO> --version <helm version>

#### Checking Logs in NUDR-NOTIFY-SERVICE

Measurements like nudr\_notif\_notifications\_ack\_2xx\_total, nudr\_notif\_notifications\_ack\_4xx\_total, and nudr\_notif\_notifications\_ack\_5xx\_total gives information about the response code returned in the notification response. If the count of nudr\_notif\_notifications\_send\_fail\_total measurement increases, then you need to ensure that the notification server mentioned in the NOTIFICATION\_URI during subscription request is up and running.

To view the NUDR-NOTIFY-SERVICE logs, execute the following command:

kubectl logs <nudr-notify-service pod> -n <ocudr-namespace>

To check logs directly on the pods, refer to the screen given below:

#### Figure 5-6 NUDR-NOTIFY-SERVICE Logs

```
[admusr@olmaster ~]$ kubectl get pods | grep nudr
ocudr-nudr-drservice-779c67b9f-sjcmv
                                                                 1/1
                                                                           Running 0
                                                                                                     161m
ocudr-nudr-notify-service-77f74ffbc-v7714
                                                                 1/1
                                                                           Running 0
Running 0
                                                                                                     161m
ocudr-nudr-nrf-client-service-6d9854fbd4-2mhmp
                                                                 1/1
                                                                           Running
                                                                                                     161m
[admusr@olmaster ~]$ kubectl exec -it ocudr-nudr-notify-service-77f74ffbc-v77l4 bash
bash-4.2$ cd /home/udruser/
bash-4.2$ ls -1
total 16
drwxr-xr-x 1 udruser udruser 37 Oct 7 09:25 app
-rw-r--r-- 1 udruser udruser 5955 Oct 9 05:45 application.log
-rw-rw-r-- 1 root root 219 Oct 7 09:21 healthcheck.sh
-rwxrwxr-x_1 root root 378 Oct 7 09:21 runService.sh
```

To change logging level in the nudr-notify-service using helm:

- Open the latest ocudr\_value.yaml file that is used at the time of ocudr installation/ upgrade.
- 2. Change the value of "logging level root" attribute under "ocudr" to "INFO".

Note:

nudr-notify-service supports logging level values: DEBUG, INFO, WARN and ERROR.

3. Execute the following helm upgrade command to change the log level: helm upgrade ocudr ocudr-helm-repo/ocudr -f <updated values.yaml with logging level as INFO> --version <helm version>



#### Checking Logs in NUDR-CONFIG-SERVICE

To view logs, execute the following command: kubectl logs <nudr-config pod> -n <ocudr-namespace>

To check logs directly on the pods, refer to the screen given below:

#### Figure 5-7 NUDR-CONFIG-SERVICE Logs

[root@master ~] # kubectl get pods -n myudr				
NAME	READY	STATUS	RESTARTS	AGE
ocudr-egressgateway-79fcffcd6b-2x85v	1/1	Running	0	14h
ocudr-ingressgateway-b48cc8bc4-qzstd	1/1	Running	0	14h
ocudr-nudr-config-64b8d8b9db-zzc7w	1/1	Running	0	14h
ocudr-nudr-config-server-cbd98d94f-pq8pf	1/1	Running	0	14h
ocudr-nudr-diameterproxy-f5f6494c6-lsx2d	1/1	Running	0	14h
ocudr-nudr-drservice-894f8f857-qvxrk	1/1	Running	0	14h
ocudr-nudr-notify-service-55db555984-bm5w5	1/1	Running	0	14h
ocudr-nudr-nrf-client-service-5986795678-vxdl8	1/1	Running	0	14h
[root@master ~] # kubectl exec ocudr-nudr-config	-64b8d8b	9db-zzc7w	-it bash -	n myudr
bash-4.2\$ cd home/udruser/				
bash-4.2\$ ls				
app application.log runService.sh				

To change logging level in the ocudr-nudr-config service using helm:

- Open the latest ocudr\_value.yaml file that is used at the time of ocudr installation/ upgrade.
- 2. Change the value of "logging level root" attribute under "ocudr" to "INFO".



3. Execute the following helm upgrade command to change the log level: helm upgrade ocudr ocudr-helm-repo/ocudr -f <updated values.yaml with logging level as INFO> --version <helm version>

#### Checking Logs in NUDR-CONFIG-SERVER

To view logs, execute the following command: kubectl logs <nudr-config-server pod> -n <ocudr-namespace>

To change logging level in the ocudr-nudr-config-server service using helm:

- Open the latest ocudr\_value.yaml file that is used at the time of ocudr installation/ upgrade.
- 2. Change the value of "logging level root" attribute under "ocudr" to "INFO".

#### Note:

OCUDR supports logging level values: DEBUG, INFO, WARN and ERROR.



3. Execute the following helm upgrade command to change the log level: helm upgrade ocudr ocudr-helm-repo/ocudr -f <updated values.yaml with logging level as INFO> --version <helm version>

#### Checking Logs in NUDR-DIAMETERPROXY Service

Debug errors from ocudr-nudr-diameterproxy:

- If diameterproxy rejects any request or you are not able to send any request from seagull machines, it means the dictionary file is not loaded correctly to the application. You need to check the dictionary path and change it, if required and redeploy the diameterproxy service. (The dictionary file path should be "/home/udruser/app/diameter").
- If diameterproxy answers CEA message with DIAMETER\_UNKNOWN\_PEER, it means client peer is not configured correctly. To resolve this, configure client peer of nudr-diameterproxy service.
- If diameterproxy answers CEA message success and other SH message response as DIAMETER\_UNABLE\_TO\_COMPLY, it means the dr-service pod is not up and running or sent sh message is invalid. You can check dr-service failure using nudr\_diameterproxy\_rest\_failure\_res\_msgs\_total metrics name and invalid sh message, if nudr\_diameterproxy\_total\_requests\_total metric is not increasing.
- If there are many error logs in diameterproxy micro service stating connection refused with some IP Address and port, it means specified server peer in helm charts is not running and diameterproxy retries to connect with that peer.
- If you are not getting any PNR messages then check whether dr-service and notify-service is up and running. You need to ensure that server peer configuration is correct.

To view NUDR-DIAMETERPROXY service logs, execute the following command: kubectl logs <nudr-diameterproxy pod> -n <ocudr-namespace>

To change logging level in the ocudr-nudr-diameterproxy service using helm:

- 1. Open the latest ocudr\_value.yaml file that is used at the time of ocudr installation/ upgrade.
- 2. Change the value of "logging level root" attribute under "ocudr" to "INFO".

### Note:

OCUDR supports logging level values: DEBUG, INFO, WARN and ERROR.

3. Execute the following helm upgrade command to change the log level: helm upgrade ocudr ocudr-helm-repo/ocudr -f <updated values.yaml with logging level as INFO> --version <helm version>

### Note:

You can use kibana also to view logs.



# Debugging Errors from Egress Gateway

If the traffic is not routed via Egress Gateway, you need to check the following:

- Check whether Egress Gateway is enabled or not from global values file.
- Check whether Egress pod is running from kubectl. To check, execute the following command: kubectl get pods -n <Release.name>
- To enable the outgoing traffic using HTTPS, you need to make the following configuration as true:

Figure 5-8 Enabling Egress Traffic using HTTPS



 Create certs and keys uniquely for all Egress and respective Ingress NF's. For more details, check the IngressGateway Container Stuck section in Init State/ Failed. It is same as Ingress debugging.


# **Debugging Errors from Ingress Gateway**

The possible errors that you may encounter from Ingress Gateway are:

• Check for 500 Error: If the request fails with 500 status code without Problem Details information, it means that the flow ended in ocudr-ingressgateway pod without route. You can confirm the same in the errors/exception section of the ocudr-ingressgateway pod logs. You also need to check the values.yaml file for the essential route configuration as shown below:







 Check for 503 Error: If the request fails with 503 status code with "SERVICE\_UNAVAILABLE" in Problem Details, then it means that the nudrdrservice pod is not reachable due to some reason.

Figure 5-10 503 Error Code

ody Coo	okies He	eaders (11)	Test Results			Status: 503 Service Unavailab
Pretty	Raw	Preview	Visualize	JSON	•	
1	{					
2	"ty	pe": null,				
3	"ti	tle": null,				
4	"st	atus": 503,				
5	"de	tail": "SER	VICE_UNAVAILA	ABLE",		
6	"in	stance": nu	11,			
7	"ca	use": null,				
8	"in	validParams	": null			
9	5					

You can confirm the same in the errors/exception logs of the ocudringressgateway pod. Check for ocudr-nudr-drservice pod status and fix the issue.



# **Debugging Helm Test Issues**

To debug Helm Test issues:

- Execute the following command to get the Helm Test pod name. kubectl get pods -n <deployment-namespace>
- Check for the Helm Test pod that is in error state.

Figure 5-1	1 Holm	Test Dod
Figure 5-L	т неш	Test Pou

[root@master ~]# kubectl get pods -n ocudr				
NAME	READY	STATUS	RESTARTS	AGE
ocudr-egressgateway-595d796-n99r9	1/1	Running		2m7s
ocudr-ingressgateway-74c94967c5-kmcfz	1/1	Running	0	2m7s
ocudr-nudr-config-65d8946986-pm561	1/1	Running		2m7s
ocudr-nudr-config-server-5c9fb996c7-nwj7h	1/1	Running		2m7s
ocudr-nudr-diameterproxy-6bf67d8d8d-6mlkb	1/1	Running	0	2m7s
ocudr-nudr-drservice-595bf9877d-jg58b	0/1	Pending	0	2m7s
ocudr-nudr-notify-service-65cf544955-dgxgq	1/1	Running	0	2m7s
ocudr-nudr-nrf-client-service-64774d996-6s64s	1/1	Running	0	2m7s
ocudr-test-twjqh	0/1	Error	0	82s

 Execute the following command to check the Helm Test pod: kubectl logs <helm\_test\_pod\_name> -n <deployment\_namespace>

In the logs, concentrate on ERROR and WARN level logs. There can be multiple reasons for failure. Some of hem are shown below:

Figure 5-12 Helm Test in Pending State



In this case, check for CPU and Memory availabality in the kubernetes cluster.

Figure 5-13 Pod Readiness Failed

<pre>(     "thread" : "main",</pre>	
"level": "ERROR",	
"loggerName" : "com.oracle.ocudr.udr.services.client.MyNFClient\$\$EnhancerBySpringCGLIB\$\$c5eed3d4",	
"message" : "Liveness check failed for URL: http://10.244.2.62:9000/actuator/health, PodName: ocudr-nudr-	notify
service-65cf544955-dgxgg",	
"endOfBatch" : false,	
"loggerFqcn" : "org.apache.logging.slf4j.Log4jLogger",	
"instant" : {	
"epochSecond" : 1594631490,	
"nano0fSecond" : 287018000	
3 ·	
"threadId" : 1,	
<pre>"contextMap" : { },</pre>	
"threadPriority" : 5	
}^M	

In this case, check for readiness proble url correctness in the particular microservice helm charts under charts folder. In the above case, check for charts



of notify service [OR] check if the pod is crashing for some reason when the url configured for readiness probe is correct.

 There are few other cases where the httpGet parameter is not configured for Readiness probe. In this case, Helm Test is considered as success for that pod. And if the Pod/PVC list is fetched based on namespace and labelSelector is empty, the helm test is considered as success.

# **Debugging HPA Issues**

There can be scenarios where HPA running on nudr-drservice deployment and nudr\_notify\_service might not get the CPU metrics successfully from the pods. Execute the following command to view the HPA details:

kubectl get hpa

In this scenario, you need to check the following:

 Check whether metrics server is running on the kubernetes cluster. If it is running, even then the CPU usage pod might not be accessible. In this case, you need to check the metrics-server values yaml file for the args passed as shown below:

#### Figure 5-14 metrics-server yaml file

```
args:
- --kubelet-preferred-address-types=InternalIP
- --kubelet-insecure-tls
```

If it requires any update, then do the same and restart the metrics server pod. You
have to wait for couple of minutes after starting the metrics server to see the CPU
usage update. For this, execute the kubectl get hpa command.

#### Figure 5-15 CPU Usage Update

[admusr@olmaster templates]	\$ kubectl get hpa					
NAME	REFERENCE	TARGETS	MINPODS	MAXPODS	REPLICAS	AGE
ocudr-nudr-drservice	Deployment/ocudr-nudr-drservice	0%/80%	1	1	1	18h
ocudr-nudr-notify-service	Deployment/ocudr-nudr-notify-service	42%/80%	1	1	1	18h

### Debugging HTTPS Support related Issues

UDR supports HTTPS and its validations are done at Ingress Gateway of UDR. You may encounter issues related to HTTPS when:

 HTTPS port is not exposed: Execute the following command to figure out whether HTTPS port is exposed or not: kubectl get svc --n <ocudr-namespace>



[root@master ocudr]# kubectl ge	et svc -n ocudr			
NAME	TYPE	CLUSTER-IP	EXTERNAL-IP	PORT (S)
AGE				
ocudr-ingressgateway	LoadBalancer	10.102.65.118	<pending></pending>	80:32659/TCP,443:30500/TCP
5701:30245/TCP 42s				
ocudr-nudr-drservice	ClusterIP	None	<none></none>	5002/TCP,9000/TCP,5001/TCP
42s				
ocudr-nudr-notify-service	ClusterIP	None	<none></none>	9000/TCP,5001/TCP,5002/TCP
42s				
ocudr-nudr-nrf-client-service	ClusterIP	None	<none></none>	9000/TCP
42s				
udrdbservice	ClusterIP	10.111.252.140	<none></none>	3306/TCP

Figure 5-16 HTTPS Port Exposed

Note:

In the above screen, the secure port is 443.

If the HTTPS port is not exposed, then enable the configuration information highlighted in the following screen under the ingressgateway section of the values.yaml file.

#### Figure 5-17 Configuration Info under Ingressgateway



- **IngressGateway Container is stuck in Init State/Failed:**The IngressGateway Container can stuck due to any one of the following reasons:
  - When config initssl is enabled under ingressgateway section of the values.yaml file.

#### Figure 5-18 config initssl

# To Initialize SSL related infrastructure in init/update container
initssl: false

 If config initssl is enabled, then you need to check whether secrets are created with all required certificates. The following screenshot shows the commands that you need to execute to check whether secrets are present and have all the required data.



[root@master ocudr]# kubectl NAME	TYPE	DATA	AGE
default-token-g75q7	kubernetes.io/service-account-token	3	13d
ocudr-secrets	Opaque	4	3m35s
ocudr-serviceaccount-token-lw	h8k kubernetes.io/service-account-token	3	2m44s
ocudrgateway-secret	Opaque	7	43m
[root@master ocudr]# kubect1	describe secret ocudrgateway-secret -n ocud	dr	
Name: ocudrgateway-se	cret		
Namespace: ocudr			
Labels: <none></none>			
Annotations: <none></none>			
Type: Opaque			
Type: Opaque			
Data			
Data			
apigatewayecdsa.cer:	1277 bytes		
apigatewayrsa.cer:	1554 bytes		
caroot.cer:	1858 bytes		
ecdsa private key pkcs8.pem:	241 bytes		
key.txt:	15 bytes		
rsa private key pkcsl.pem:	1679 bytes		
trust.txt:	17 bytes		

Figure 5-19 Commands to check Secrets

• **Config-Server Container Stuck in Hooks Init State:** The UDR installation stucks in Hooks Init state when there is database connection failure.

Figure 5-20 Config Server Container Status

Every 2.0s: kubectl get pods -n myudr			Wed Jun 17 05:20:20 2	020
NAME ocudr-ocpm-config-pre-install-47mpc	STATUS CreateContainerConfigError	RESTARTS 0	AGE 10m	

# **Debugging Notification Issues**

If UDR does not generate any notification, check the notify service port configuration in the values.yaml file. These ports should be same as ports on which notify service is running.

```
nudr-drservice:
...
...
notify:
    port:
        http: 5001
        https: 5002
```

## **Debugging Pod Creation Failure**

A pod creation can fail due to various reasons. Some of the possible scenarios are explained below:

- Verifying pod image correctness: To verify pod image correctness:
  - Verify whether any of the pod is in ImagePullBackOff state.
  - To check whether the image name used for any pod is not correct, verify the values given below in the values.yaml file.

```
nudr-drservice:
```



```
image:
               repository: reg-1:5000/ocudr/
nudr_datarepository_service
               tag: 1.6.0
      nudr-nrf-client-service:
      . . .
           image:
                repository: reg-1:5000/ocudr/nrf_client_service
                taq: 1.6.0
      nudr-notify-service:
      . . .
           image:
                repository: reg-1:5000/ocudr/nudr_notify_service
                tag: 1.6.0
      nudr-config:
      . . .
           image:
               repository: reg-1:5000/ocudr/nudr_config
                tag: 1.6.0
      nudr-config-server:
      . . .
           image:
                repository: reg-1:5000/ocudr/ocpm_config_server
                tag: 1.6.0
```

 After updating the values.yaml file, execute the following command for helm upgrade:

helm upgrade <helm chart> [--version <OCUDR version>] --name
<release> --namespace <ocudr-namespace> -f <ocudr\_values.yaml>

- Verifying Resource Allocation Failure: To verify resource allocation failure:
  - Verify whether any of the pod is in Pending state. If it is there, execute the following command:
     kubectl describe <nudr-drservice pod id> --n <ocudr-namespace>
    - Verify whether any warning on Insufficient CPU exists in the describe output
  - of the respective pod. If it exists, it means there are insufficient CPU for the pods to start. You have to either fix the hardware issue or reduce the number of CPUs alloted to a pod in the values.yaml file.

```
nudr-drservice:
...
...
resources:
limits:
```

ORACLE

```
cpu: 3
memory: 4Gi
requests:
cpu: 3
memory: 4Gi
```

nudr-notify-service:

••• •••

• • •

resources:

limits:

cpu: 3

memory: 4Gi

requests:

cpu: 3

memory: 4Gi

nudr-config:

· · ·

. . .

resources:

limits:

cpu: 3

memory: 4Gi

requests:

cpu: 3

memory: 4Gi



```
nudr-config-server:
. . .
. . .
. . .
resources:
  limits:
    cpu: 2
    memory: 2Gi
  requests:
    cpu: 2
    memory: 512Mi
ingress-gateway:
. . .
. . .
. . .
resources:
  limits:
    cpu: 3
    memory: 4Gi
  requests:
    cpu: 3
    memory: 4Gi
```

 After updating the values.yaml file, execute the following command for helm upgrade:

```
helm upgrade <helm chart> [--version <OCUDR version>] --name
<release> --namespace <ocudr-namespace> -f <ocudr_values.yaml>
```

- Verifying SQL Exception Failures with nudr-prehook pod: nudr-prehook pod is added as part of 1.7 release. It creates UDR DB along with the tables required. If it does not creates the DB, then to debug the pod failure perform the following steps:
  - Verify whether helm install command hangs for longer time or fails with BackOffLimit exceeded error.
  - Watch the **kubectl get pods** command based on the release namespace.
  - Check whether **nudr-preinstall** pod is going to error state. This means the DB creation has failed or connection to DB is not successful.



- Execute the following command on logs:
   kubectl logs <nudr-prehook pod id> --n <ocudr-namespace>
- Check the log output of the pods for any warning or SQL exceptions using above command continuously. If any warning or SQL exception is found, it means there is an issue with the SQL connection or the SQL Node. Examine each exception thoroughly to find the root caue.
- Verify the following information in the values.yaml file.

```
global:
...
mysql:
dbServiceName: "mysql-connectivity-service.occne-infra" #This
is a read only parameter. Use the default value.
port: "3306"
```

Ensure that the following service is available in the CNE.

#### Figure 5-21 Service Availability in CNE

[root@master ocudr]# kubectl get svc -n occne-infra NAME TYPE CLUSTER-IP EXTERNAL-IP PORT(S) AGE mysql-connectivity-service ClusterIP 10.109.123.205 <none> 3306/TCP 3h49m

- Check whether kubernetes secrets are present. If secrets exist, then check its encrypted details like username, password and DB name. If these details does not exist, then update the secrets.
- After making any changes, execute the following command to upgrade helm. helm upgrade <helm chart> [--version <OCUDR version>] --name <release> --namespace <ocudr-namespace> -f <ocudr\_values.yaml>

For more details, you can refer to Kubernetes Secret Creation - DBName, Username, Password and Encryption Key.

## Debugging UDR Registration with NRF Failure

UDR registration with NRF may fail due to various reasons. Some of the possible scenarios are as follows:

- Verify pod status: Verify whether all the pods are running or not. Ensure atleast one replica for each microservice is up and running. If it is not running, check for possible reasons. Once the issue resolves, UDR registers successfully with NRF.
- Verify NRF url correctness: Execute the following command to check the logs of the ocudr-nudr-nrf-client-service pod:

kubectl logs <nrf-client-service pod id> --n <ocudr-namespace>

If the logs state that the connection with NRF fails as shown below:

```
10:07:01.335 [scheduling-1] WARN
ocudr.udr.services.client.RestClient
- Got error response
{nfInstanceId=3fd8556a-7804-4abd-8143-640904042d89,
answerStr=java.net.UnknownHostException: ocnrf-
```



```
ingressgateway.mynrf.svc.cluster.local,
response=<503, java.net.UnknownHostException: ocnrf-
ingressgateway.mynrf.svc.cluster.
local,[]>, nrfBaseUrl=http://ocnrf-
ingressgateway.mynrf.svc.cluster.local/nnrf-nfm/
v1/nf-instances, header={Content-Type=[application/json]},
uri=http://ocnrf-ingressgateway.mynrf.svc.cluster.local/nnrf-nfm/v1/
nf-instances/3fd8556a-7804-4abd-8143-640904042d89}
10:07:01.340 [scheduling-1] WARN
ocudr.udr.services.client.RestClient -
Got error response {answerStr=java.net.UnknownHostException: ocnrf-
ingressgateway.
mynrf.svc.cluster.local, headerMap={Content-Type=[application/
json]}, response=<503,
java.net.UnknownHostException: ocnrf-
ingressgateway.mynrf.svc.cluster.local,[]>,
profile={"nfInstanceId":"3fd8556a-7804-4abd-8143-640904042d89","nfTy
pe":"UDSF",
"nfStatus": "REGISTERED", "fqdn": "ocudr-
ingressgateway.myudr.svc.cluster.local",
"udrInfo":{"supiRanges":[{"start":"100000000
```

Then, verify the baseurl used for NRF in the values.yaml file (as shown below), which is used for connection with NRF.

```
nudr-nrf-client-service:
...
...
host:
baseurl: "http://ocnrf-ingressgateway.mynrf.svc.cluster.local/
nnrf-nfm/v1/nf-instances"
```

 Verify UDR fqdn correctness: Execute the following command to check the logs of the nrf-client-service pod:

kubectl logs <nrf-client-service pod id> --n <ocudr-namespace>

If the logs state that the FQDN used is not correct then the UDR registration with NRF fails. You need to check the FQDN used in the values.yaml file as follows:

```
nudr-nrf-client-service:
...
...
fqdn: "ocudr-ingressgateway.myudr.svc.cluster.local"
```

This helps to connect with NRF.

Check for livenessProbeFailure: Execute the following command to check the logs of the nrf-client-service pod.

kubectl logs <nrf-client-service pod id> --n <ocudr-namespace>



If the logs state that the livenessProbe failed, check for similar logs as shown below:

19:38:42.770 [scheduling-1] ERROR o.u.s.c.NRFRegistrationScheduler -NFService liveness probe failed, ignore registration/update operation {livenessProbeRetry=19}

```
19:39:12.772 [scheduling-1] WARN ocudr.udr.services.client.RestClient
- Got error response {answerStr=java.net.UnknownHostException:
nudr-drservice.myudr.svc.cluster.local: Temporary
failure in name resolution, uri=http://nudr-
drservice.myudr.svc.cluster.local:9000/actuator/health, url=http://
nudr-drservice.myudr.svc.cluster.local:9000/actuator/health,
headerMap=null, response=<503,java.net.UnknownHostException: nudr-
drservice.myudr.svc.cluster.local: Temporary failure in name
resolution,[]>}
```

In the values.yaml file, check the livenessProbeUrl, which is used for connection with NRF.

```
nudr-nrf-client-service:
...
...
livenessProbeUrl: ""
```

### Debugging UDR with Service Mesh Failure

There are some known failure scenarios that you may encounter while installing UDR with service mesh. The scenarios along with their solutions are as follows:

• Istio-Proxy side car container not attached to Pod: This particular failure arise when istio injection is not enabled on the NF installed namespace. Execute the following command to verify the same:

kubectl get namespace -L istio-injection

IrootAmaster	oguda 1 7 01#	kubeat1	get namespace -L istio-injection
NAME	STATUS	AGE	ISTIO-INJECTION
default	Active	28d	
istio-system	Active	20d	
kube-node-lea	ase Active	28d	
kube-public	Active	28d	
kube-system	Active	28d	
myudr	Active	18d	enabled
myudr1	Active	18d	enabled
occne-infra	Active	27d	
ocnrf	Active	20d	enabled
ocudr	Active	26d	disabled
ocudr1	Active	14d	
provgw	Active	19d	enabled
vnnrf	Active	4d12h	enabled

Figure 5-22 Verifying Istio-Proxy

To enable the istio injection, execute the following command:

kubectl label --overwrite namespace <nf-namespace> istioinjection=enabled



Other possible reason for this error could be that the below highlighted annotation is missing from the deployment.

Figure 5-23 Global Section - Istio-Proxy Info

sustomExtension:
allResources:
labels: ()
annotations:
<pre>sidecar.istio.io/inject: "\"false\""</pre>
lbServices:
labels: ()
annotations: {}
lbDeployments:
labels: ()
annotations:
<pre>sidecar.istio.io/inject: "\"true\""</pre>
oracle.com/cnc: "\"true\""
nonlbServices:
labels: {}
annotations: ()
nonlbDeployments:
labels: {}
annotations:
<pre>sidecar.istio.io/inject: "\"true\""</pre>
oracle.com/cnc: "\"true\""

You need to add the highlighted annotation as shown above to the global section for **IbDeployments** and **nonIbDeployments** parameters.

• UDR registration with NRF failed: This can be due to NF liveness probe failure. You can confirm this on nudr-nrf-client-service pod logs. In this case, you need to ensure that the management port of all UDR microservices are excluded from side car envoy usage. You have to configure proper port as suggested in the below annotation under nudr-nrf-client-service section.

#### Figure 5-24 Annotation to Configure Port



• If there are issues in viewing UDR metrics on OSO prometheus then you have to add the annotation given below to all the deployments for the NF.





Figure 5-25 Annotation to View UDR Metrics

## Using Logs

The following table helps you to understand the logs you need to look into, to handle different UDR debugging issues:

SNO	Scenarios	Pod	Logs to be searched	Log Level
1	Registration with NRF Successful	nrf-client-service	Register completed successfully / "nfServiceStatus":"RE GISTERED"	INFO
2	Heartbeat message log	nrf-client-service	Update completed successfully	INFO
3	NRF configurations reloading	nrf-client-service	NRF client config reloaded	INFO
4	Check for exiting NF Instance Entry	nrf-client-service	No registered NF instance exists	WARN
5	Started Application	nrf-client-service	Successful application start	INFO
6	Started Application	nudr-drservice	Successful application start	INFO
7	NRF Client Config Initialized	nrf-client-service	Initialize NRF client configuration	INFO
8	FQDN/BASEURL/ livenessProbeUrl Improper	nrf-client-service	response=<503,java.n et.UnknownHostExce ption	WARN



SNO	Scenarios	Pod	Logs to be searched	Log Level
9	nudr-drservice liveness probe failure	nrf-client-service	NFService liveness probe failed	WARN
10	SQL Exception during start up	nudr-drservice	java.sql.SQLExceptio n	WARN
11	DB connection pool Established	nudr-drservice	HikariPool-1 - Start completed	INFO
12	Error Code Mapping configurations loaded	nudr-drservice	Loaded Error Code Mapping Configuration	INFO
13	Error Code Mapping configurations loaded	nudr-drservice	Loaded Error Reason Mapping Configuration	INFO
14	Error Code Mapping configurations loaded	nudr-drservice	Loaded Error Title Mapping Configuration	INFO
15	Error Code Mapping configurations loaded	nudr-drservice	Loaded Error Type Mapping Configuration	INFO
16	Check if Ports successfully listening	nudr-drservice	Undertow started on port(s)	INFO
17	Check for message received	nudr-drservice	Before request [uri= <uri-sent excluding ip and port&gt;</uri-sent 	DEBUG
18	Check for message processed	nudr-drservice	After request [uri= <uri-sent excluding ip and port&gt;</uri-sent 	DEBUG
19	URI Pattern not supported	nudr-drservice	None match pattern found for URL	WARN
20	Check if Ports successfully listening	nrf-client-service	Undertow started on port(s)	INFO
21	Pod exit	nudr-drservice	HikariPool-1 - Shutdown completed	INFO
22	DB username/ DB password invalid	nudr-drservice	Access denied for user	WARN
23	Registration with NRF failed	nrf-client-service	Register failed	ERROR
24	De registration with NRF successful	nrf-client-service	Deregister completed successfully	INFO
25	De registration with NRF failed	nrf-client-service	Deregister failed	ERROR
26	NF Profile update failed	nrf-client-service	Update failed	ERROR



# 6 Uninstalling Unified Data Repository

To uninstall or completely delete the Unified Data Repository (UDR) deployment, execute the following command: helm del --purge <helm\_release\_name\_for\_ocudr>

### Note:

In case you are using helm3, execute the following command to uninstall UDR:

helm uninstall <helm\_release\_name\_for\_ocudr> --namespace
<ocudr\_namespace>



# A ASM Specific Configuration

To configure ASM, you have to:

• Add the following annotation under Global section of UDR deployment.

```
# ******* Sub-Section Start: Custom Extension Global Parameters
******
******
global:
 customExtension:
   allResources:
    labels: {}
    annotations:
      sidecar.istio.io/inject: "\"false\""
   lbServices:
    labels: {}
    annotations: {}
   lbDeployments:
    labels: {}
    annotations:
      sidecar.istio.io/inject: "\"true\""
      oracle.com/cnc: "\"true\""
   nonlbServices:
    labels: {}
    annotations: {}
   nonlbDeployments:
    labels: {}
    annotations:
      sidecar.istio.io/inject: "\"true\""
      oracle.com/cnc: "\"true\""
 # ******* Sub-Section End: Custiom Extensions Global Parameters
*******
******
Enable Service Mesh Flag under ingressgateway section.
```

```
ingressgateway:
    # Mandatory: This flag needs to set it "true" is Service Mesh
would be present
```



•

```
where UDR will be deployed serviceMeshCheck: true
```

Change Ingress Gateway Service Type to ClusterIP under ingressgateway section.

```
ingressgateway:
global:
    # Service Type
    type: ClusterIP
```

 Exclude actuator ports from Aspen Mesh to avoid traffic through side car. These ports are used as actuator ports (used for readiness/liveness checks) for Ingress Gateway and UDR microservices. The default actuator port (service.port.management) used for UDR microservices is 9000 and Ingress/ Egress Gateway is 9090 (ingressgateway.ports.actuatorPort). If there is no change in default ports, you can use the annotation given below.

```
nudr-nrf-client-service:
  deployment:
    customExtension:
    labels: {}
    annotations:
    traffic.sidecar.istio.io/excludeOutboundPorts:
    "\"9000,9090\""
```

 Create a destination rule and service entry to enable MYSQL connectivity service to establish a connection between UDR/SLF and NDB cluster. This is outside ASM. The sample templates are as follows: Creating a Service for External MySQL instance

```
apiVersion: v1
kind: Endpoints
metadata:
 name: mysql-connectivity-service-headless
 namespace: <ocudr-namespace>
subsets:
- addresses:
  - ip: <sql-nodel-ip>
  - ip: <sql-node2-ip>
ports:
  - port: 3306
   protocol: TCP
apiVersion: v1
kind: Service
metadata:
 name: mysql-connectivity-service-headless
 namespace: <ocudr-namespace>
spec:
 clusterIP: None
 ports:
  - port: 3306
   protocol: TCP
```

```
targetPort: 3306
sessionAffinity: None
type: ClusterIP
---
apiVersion: v1
kind: Service
metadata:
    name: mysql-connectivity-service
    namespace: <ocudr-namespace>
spec:
    externalName: mysql-connectivity-service-headless.<ocudr-
namespace>.svc.cluster.local
    sessionAffinity: None
    type: ExternalName
```

#### Creation of Service Entry and DestinationRule for External DB instance

```
apiVersion: networking.istio.io/vlalpha3
kind: ServiceEntry
metadata:
  name: mysql-external-se
  namespace: <ocudr-namespace>
spec:
  hosts:
  - mysql-connectivity-service-headless.<ocudr-
namespace>.svc.cluster.local
 ports:
  - number: 3306
   name: mysql
    protocol: MySQL
  location: MESH_EXTERNAL
apiVersion: networking.istio.io/vlalpha3
kind: DestinationRule
metadata:
  name: mysql-external-dr
  namespace: <ocudr-namespace>
spec:
  host: mysql-connectivity-service-headless.<ocudr-
namespace>.svc.cluster.local
  trafficPolicy:
    tls:
      mode: DISABLE
```

