Oracle® Retail Inventory Planning
Optimization Cloud Service-Demand
Forecasting / Inventory Planning
Optimization Cloud Service-Lifecycle
Allocation and Replenishment
User Guide





Oracle Retail Inventory Planning Optimization Cloud Service-Demand Forecasting / Inventory Planning Optimization Cloud Service-Lifecycle Allocation and Replenishment User Guide, Release 24.1.201.0

F95845-02

Copyright © 2024, Oracle and/or its affiliates.

Primary Author: Melissa Artley

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, MySQL and NetSuite are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

Audience		xiii
Documentation Ac	cessibility	xiii
Customer Support		xiii
Improved Process	for Oracle Retail Documentation Corrections	xiii
Oracle Retail Docu	mentation on the Oracle Help Center (docs.oracle.com)	xiv
Conventions		xiv
Send Us You	r Comments	
Introduction:	Demand Forecasting	
Forecasting Challe	nges and IPOCS-Demand Forecasting Solutions	1-1
Selecting the E	Best Forecasting Method	1-2
Overcoming D	ata Sparsity Through Escalation and Pooling Levels	1-2
Forecasting De	emand for New Products and Locations	1-2
Managing Fore	ecasting Results Through Automated Exception Reporting	1-2
Incorporating t Demand	he Effects of Promotions and Other Event-Based Challenges on	1-3
53 Week Cale	ndar	1-3
Forecasting Proces	SS	1-4
Process Sumn	nary	1-4
User Experience a	nd Workflow	1-5
Dashboard Vie	ews and Workspaces	1-5
Forecast Engir	ne	1-6
Demand Fore	ecasting Dashboard	
Overview Dashboa	ard	2-2
Forecast Scorecar	d Dashboard	2-4
Approval Alerts		2-5



Navigations Alerts 2-6

3 New Item & Locations Task

New Item & Locations Workspaces, Steps, and Views	3-1
New Item Maintenance Workspace	3-2
New Item Settings Step	3-5
New Item Basic Parameters View	3-5
Like Item - Select and Approve Step	3-7
New Item Forecast View	3-8
New Item Statistics View	3-8
Select and Approve View	3-9
New Store Maintenance Workspace	3-12
Like Store Assignment Step	3-14
Product Like Store Assignment View	3-14
New Item Management Workspace	3-15
Settings Step	3-16
New Item Basic Parameters View	3-16
Manage Step	3-19
New Item Attributes View	3-19
New Item Statistics View	3-19
Select and Approve View	3-20
New Item Forecast View	3-23
View Step	3-24
Attribute Value View	3-24
Similarity Score View	3-25
Forecast Setup Task	
Forecast Setup Workspaces, Steps, and Views	4-1
Forecast Setup Workspace	4-1
General Step	4-2
Basic Parameters View	4-4
Advanced Parameters View	4-5
Intermediate Level View	4-7
Final Level View	4-9
Exception Management Step	4-11
Basic Parameters View	4-11
Intermediate Level View	4-13
Final Level View	<i>1</i> -1/



4

5 Forecast Review Task

	Forecast Review Workspaces, Steps, and Views	5-1
	Forecast Review Workspace	5-1
	Approve Step	5-4
	Forecast Results View	5-4
	Approve Information View	5-7
	Forecast Results Chart View	5-10
	What-if Parameters View	5-12
	Preprocessing Details View	5-14
6	IPOCS-Demand Forecasting Administration Task	
	Batch Flow Administration Workspace, Step, and View	6-1
	Batch Flow Administration Workspace	6-1
	Batch Flow Control Step	6-2
	Batch Flow Control View	6-2
7	Business Rule Engine	
	Attributes Task	7-1
	Attributes Workspaces, Steps, and Views	7-1
	Attributes Workspace	7-1
	Review Step	7-4
	Location Attributes View	7-4
	Product Attributes View	7-5
	Enable Prod/Loc View	7-6
	Business Rule Group Admin Task	7-7
	Business Rule Group Admin Workspaces, Steps, and Views	7-7
	Business Rule Group Admin Workspace	7-7
	Setup Step	7-8
	Rule Group Info View	7-9
	Rule Group Active Attribute View	7-10
	Rule Group Scope (Weekly Forecast) View	7-10
	Business Rule Setup Task	7-11
	Business Rule Setup Workspaces, Steps, and Views	7-11
	Business Rule Setup Weekly Forecast Workspace	7-11
	Setup Step	7-15
	Rule Enable View	7-15
	Rule Condition Setup View	7-16
	Rule Membership View	7-19
	Parameters for Approval View	7-19
	• •	



Parameters for Navigation View	7-21
Offer Analysis Task	
Offer Analysis Workspaces, Steps, and Views	8-1
Offer Analysis Workspace	8-1
Offer Analysis Step	8-2
Summary View	8-5
Detailed View	8-6
Attribute Review Task	
Attribute Review Workspaces, Steps, and Views	9-1
Attributes Review Workspace	9-1
Label and Setup Step	9-4
Enable Prod/Loc View	9-4
Label & Setup View	9-5
Review Step	9-6
Location Attributes View	9-6
Product Attributes View	9-7
Product/Location Attributes View	9-7
Edit Step	9-8
Location Attributes View	9-9
Product Attributes View	9-9
Product/Location Attributes View	9-10
Introduction: Lifecycle Allocation and Replenishment	
Key Features	10-2
User Experience and Workflow	10-3
Lifecycle Allocation and Replenishment Dashboard	
Overview Dashboard	11-3
Setup Exceptions Dashboard	11-4
Replenishment Exceptions	11-5
Assortment Administration Task	
7.0001tmone 7.tammon autori Taok	
Assortment Administration Workspace, Steps, and Views	12-1
	12-1 12-2



	Actual Data View	12-6
	Assortment View	12-7
	Assortment Parameters View	12-10
	Filter View	12-12
	Review Assortment Step	12-14
	Location View	12-14
	Variant View	12-17
	Variant-Location View	12-20
	Variant-Location-Week View	12-23
	Product-Location View	12-24
	Product-Location-Week View	12-28
	Assortment Admin Action Buttons	12-29
13	Manage Alert Parameters	
	Manage Alert Parameters Workspace, Steps, and Views	13-1
	Manage Alert Parameters Workspace	13-2
	Label & Review Step	13-5
	Label & Review View	13-5
	Alert Parameters Step	13-8
	Item-Location Alert Parameters View	13-9
	Parent-Location Alert Parameters View	13-9
	Class-Region Alert Parameters View	13-10
	Partition-Location Alert Parameters View	13-11
	Global Alert Parameters View	13-12
	Alert Details Step	13-12
	Item Alerts View	13-13
	Item-Location Alerts View	13-14
	Alert Details View	13-15
14	Manage Scaling Parameters	
	Manage Scaling Parameters Workspace, Steps, and Views	14-1
	Manage Scaling Parameters Workspace	14-1
	Manage Scaling Parameters Step	14-4
	Constraint Groups View	14-4
	Constraints View	14-6
	Constraints PROD-LOC Association View	14-7



15 Manage Databags

Manage Databags Workspace, Steps, and Views	15-3
Databag Scope and Review Workspaces	15-4
Setup Step	15-9
Setup View	15-9
Product Group Scope View	15-10
Location Group Scope View	15-10
Source Group Scope View	15-11
Alerts Scope View	15-12
Attributes Scope View	15-13
Enable & Publish Step	15-14
Enable & Setup View: Databag Review	15-15
Filter Conditions View	15-18
Today & Parameters View	15-21
Review Databags Details Step	15-21
Associated PROD View	15-22
Associated LOC View	15-22
Associated SLOC View	15-23
Associated WEEK View	15-24
Associated Alerts View	15-25
Associated Attributes View	15-25
Associated PROD-LOC View	15-26
Review Attributes & Alerts Step	15-27
PROD Attributes View	15-27
LOC Attributes View	15-28
PROD-LOC Attributes View	15-28
PROD-LOC Alerts View	15-29
Manage Databag Action Buttons	15-29
Manage Rule Groups	
Manage Rule Groups Workspace, Steps, and Views	16-1
Manage Rule Groups Workspace	16-1
Setup & Publish Step	16-6
Enable & Setup View: Rule Groups	16-6
Statistics View	16-7
Today View	16-9
Product Group Scope View: Rule Group	16-10
Location Group Scope View: Rule Group	16-10
Source Scope View	16-11
Attribute Scope View	16-12



16

Manage Rule Groups Action Buttons	16-13
Manage Packs	
Manage Packs Workspace, Steps, and Views	17-1
Manage Packs Workspace	17-2
Pack Setup Step	17-4
Enable View: Manage Packs	17-4
Pack-SKU View	17-4
Packs View	17-5
Manage Packs Action Buttons	17-6
Manage Allowed Transfer	
Manage Allowed Transfer Workspace, Steps, and Views	18-3
Manage Allowed Transfer Workspace	18-3
Allowed Transfer Step	18-4
Allowed Transfer View	18-4
Supply Chain Network	
Supply Chain Network Workspace, Steps, and Views	19-:
Supply Chain Network Workspace	19-2
Overview Step	19-
Statistics View	19-
Location Scope View	19-
Product Scope View	19-8
Bill of Distributions Step	19-9
Bill of Distributions View	19-10
Valid Source Locations View	19-12
Planning Calendars Step	19-13
Planning Calendars View	19-14
Day of Week View	19-17
Daily Exceptions View	19-17
Lifecycle Calendars Step	19-19
Lifecycle Calendars View	19-20
Lifecycle Phases View	19-23
Rules Step	19-25
Rules View	19-27
Conditions View	19-33
SKU-LOC View	19-34
SKU-LOC-Week View	19-40



SKU-LOC-Phases View	19-41
Filter Step	19-42
Filter Parameters View	19-42
Calendar Filter View	19-44
Supply Chain Network Action Buttons	19-44
Replenishment Parameters	
Replenishment Parameters Workspace, Steps, and Views	20-1
Replenishment Parameters Workspace	20-2
Overview Step	20-5
Statistics View	20-5
Location Scope View	20-7
Product Scope View	20-8
Replenishment Parameters Step	20-9
Replenishment Parameters View	20-13
Replenishment Change Parameters Concept	20-18
Replenishment Change Parameters View	20-19
Default Replenishment Parameters View	20-21
Inventory Plan Parameters Step	20-22
Inventory Planning Parameters Key Concept	20-22
Inventory Plan Parameters View	20-23
Constraint Parameters Step	20-27
Replenishment Constraint Parameters Concept	20-27
Constraint Parameter View	20-28
Default Store Priority View	20-33
Rules Step	20-32
Rules Concept for the Replenishment Parameters Task	20-32
Rules View	20-34
Conditions View	20-39
SKU-LOC View	20-42
Filter Step	20-50
Filter Parameters View	20-50
Replenishment Parameters Action Buttons	20-52
Review and Approve	
Review and Approve Workspace, Steps, and Views	21-2
Review and Approve Workspace	21-4
Overview Step	21-8
·	



10-D0 List view	21-9
Today View	21-10
User Filter View	21-11
Review & Approve Step	21-12
SKU Level (R & A) View	21-13
SKU-LOC Level (R & A) View	21-41
SKU-Source LOC Level (R & A) View	21-71
VAR-LOC Level (R & A) View	21-73
VAR-Source LOC Level (R & A) View	21-75
LOC Level (R & A) View	21-76
LOC-SKU Level (R & A) View	21-76
LOC-VAR Level (R & A) View	21-77
Source LOC-SKU Level (R & A) View	21-77
Source LOC-VAR Level (R & A) View	21-78
Display Space by LOC (R & A) View	21-78
Display Space by SKU (R & A) View	21-80
Stockroom Space by LOC (R & A) View	21-81
Stockroom Space by SKU (R & A) View	21-82
OTB (R & A) View	21-83
Inventory Plan Step	21-85
Horizon (InvPlan) View	21-86
SKU-LOC Level (InvPlan) View	21-87
SKU-LOC-DAY Level (InvPlan) View	21-93
SKU-LOC-WEEK Level (InvPlan) View	21-94
SKU-Source LOC-WEEK Level (R & A) View	21-99
Rebalancing Step	21-99
Item-Location View	21-100
Items View	21-104
Locations View	21-108
Parameters View	21-112
Item-Location View	21-114
Items View	21-117
Links View	21-121
Locations View	21-122
Parameters View	21-126
Plan Transfer Step	21-128
Allowed Transfer View	21-128
Transfer Deficit Analysis View	21-129
Transfer Surplus Analysis View	21-130
Transfer by Destination View	21-131
Transfer by Product View	21-133



	Transfer Deficit From-To View	21-135
	Transfer Surplus From-To View	21-137
	Filter Step	21-137
	Attribute Filter Setup View	21-138
	Calendar Filter Setup View	21-138
	Filter Setup View	21-139
	Filter Statistics View	21-142
	Quick Filter View	21-142
	Review & Approve Action Buttons	21-144
	User Filter View	21-146
Α	Appendix: Forecast Approval Exceptions	
	Forecast versus Recent Sales	A-2
	Adjusted versus Approved	A-2
	Forecast versus Last Year Sales	A-3
	Promo Peaks	A-4
В	Appendix: Forecast Errors in the Forecast Score	card Dashboard
	Mean Absolute Percent Error	B-1
	Root Mean Squared Error	B-1
	Mean Absolute Error	B-2
	Forecast Bias	B-2
	Percent Adjusted	B-2
С	Appendix: Business Rule Engine	
D	Appendix: IPOCS-Lifecycle Allocation and Replenishment Exceptions & Alerts	
_	Appendix Trouble besting	
Е	Appendix: Troubleshooting	



Preface

The Oracle Retail Inventory Planning Optimization Cloud Service-Demand Forecasting/ Inventory Planning Optimization Cloud Service-Lifecycle Allocation and Replenishment User Guide describes the IPOCS-Demand Forecasting and IPOCS-Lifecycle Allocation and Replenishment module's user interfaces and how to navigate through each module.

Audience

This document is intended for the users and administrators of Oracle Retail Inventory Planning Optimization Cloud Service-Demand Forecasting. This may include merchandisers, buyers, and business analysts.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info or Visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs if you are hearing impaired.

Customer Support

To contact Oracle Customer Support, access My Oracle Support at the following URL:

https://support.oracle.com

When contacting Customer Support, please provide the following:

- Product version and program/module name
- Functional and technical description of the problem (include business impact)
- Detailed step-by-step instructions to re-create
- Exact error message received
- Screen shots of each step you take

Improved Process for Oracle Retail Documentation Corrections

To more quickly address critical corrections to Oracle Retail documentation content, Oracle Retail documentation may be republished whenever a critical correction is needed. For critical corrections, the republication of an Oracle Retail document may at times not be



attached to a numbered software release; instead, the Oracle Retail document will simply be replaced on the Oracle Help Center (docs.oracle.com), or, in the case of Data Models, to the applicable My Oracle Support Documentation container where they reside.

This process will prevent delays in making critical corrections available to customers. For the customer, it means that before you begin installation, you must verify that you have the most recent version of the Oracle Retail documentation set. Oracle Retail documentation is available on the Oracle Help Center (docs.oracle.com) at the following URL:

https://docs.oracle.com/en/industries/retail/index.html

An updated version of the applicable Oracle Retail document is indicated by Oracle part number, as well as print date (month and year). An updated version uses the same part number, with a higher-numbered suffix. For example, part number E123456-02 is an updated version of a document with part number E123456-01.

If a more recent version of a document is available, that version supersedes all previous versions.

Oracle Retail Documentation on the Oracle Help Center (docs.oracle.com)

Oracle Retail product documentation is available on the following web site:

https://docs.oracle.com/en/industries/retail/index.html

(Data Model documents are not available through Oracle Help Center. These documents are packaged with released code, or you can obtain them through My Oracle Support.)

Conventions

The following text conventions are used in this document:

Convention	Meaning	
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.	
italic	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.	
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.	



Send Us Your Comments

Oracle Retail Inventory Planning Optimization Cloud Service-Demand Forecasting/ Inventory Planning Optimization Cloud Service-Lifecycle Allocation and Replenishment User Guide, Release 24.1.201.0.

Oracle welcomes customers' comments and suggestions on the quality and usefulness of this document.

Your feedback is important, and helps us to best meet your needs as a user of our products. For example:

- Are the implementation steps correct and complete?
- Did you understand the context of the procedures?
- · Did you find any errors in the information?
- Does the structure of the information help you with your tasks?
- Do you need different information or graphics? If so, where, and in what format?
- Are the examples correct? Do you need more examples?

If you find any errors or have any other suggestions for improvement, then please tell us your name, the name of the company who has licensed our products, the title and part number of the documentation and the chapter, section, and page number (if available).



Before sending us your comments, you might like to check that you have the latest version of the document and if any concerns are already addressed. To do this, access the Online Documentation available on the Oracle Help Center Web site. It contains the most current Documentation Library plus all documents revised or released recently.

Send your comments to us using the electronic mail address: retail-doc_us@oracle.com

Please give your name, address, electronic mail address, and telephone number (optional).

If you need assistance with Oracle software, then please contact your support representative or Oracle Support Services.

If you require training or instruction in using Oracle software, then please contact your Oracle local office and inquire about our Oracle University offerings. A list of Oracle offices is available on our Web site at http://www.oracle.com.



1

Introduction: Demand Forecasting

Oracle Retail Inventory Planning Optimization Cloud Service-Demand Forecasting (IPOCS-Demand Forecasting) provides accurate forecasts that enable retailers to coordinate demand-driven outcomes that deliver connected customer interactions. With a single view of demand, IPOCS-Demand Forecasting provides pervasive value across retail processes, including driving optimal strategies in planning, increasing inventory productivity in supply chains, decreasing operational costs and driving customer satisfaction from engagement to sale to fulfillment. IPOCS-Demand Forecasting is a comprehensive solution that maximizes the forecast accuracy for the entire product lifecycle, the ability to adapt to recent trends, seasonality, out-of-stocks and promotions, and reflect the unique demand drivers of each retailer. Today's progressive retail organizations know that store-level demand drives the supply chain. The ability to forecast consumer demand productively and accurately is vital to a retailer's success. The business requirements for consumer responsiveness mandate a forecasting system that more accurately forecasts at the point of sale, handles difficult demand patterns, forecasts promotions and other causal events, processes large numbers of forecasts, and minimizes the cost of human and computer resources. Forecasting drives the business tasks of planning, replenishment, purchasing, and allocation. As forecasts become more accurate, businesses run more efficiently by buying the right inventory at the right time. This ultimately lowers inventory levels, improves safety stock requirements, improves customer service, and increases the company's profitability.

This guide contains these chapters and appendices for the IPOCS-Demand Forecasting module:

- Demand Forecasting Dashboard
- New Item & Locations Task
- Forecast Setup Task
- Forecast Review Task
- IPOCS-Demand Forecasting Administration Task
- Business Rule Engine
- Offer Analysis Task
- Appendix: Forecast Approval Exceptions
- Appendix: Forecast Errors in the Forecast Scorecard Dashboard
- Appendix: Business Rule Engine
- Appendix: Troubleshooting

Forecasting Challenges and IPOCS-Demand Forecasting Solutions

A number of challenges affect the ability of forecast demand accurately including:

Selecting the Best Forecasting Method

- Overcoming Data Sparsity Through Escalation and Pooling Levels
- Forecasting Demand for New Products and Locations
- Managing Forecasting Results Through Automated Exception Reporting
- Incorporating the Effects of Promotions and Other Event-Based Challenges on Demand
- 53 Week Calendar

Selecting the Best Forecasting Method

One challenge to accurate forecasting is the selection of the best model to account for level, trending, seasonal, and spiky demand. Oracle Retail's automatic evaluation of several methods eliminates this complexity. The automated approach can pick the best fit method among a large selection, like Simple Exponential Smoothing, Holt Exponential Smoothing, Additive and Multiplicative Winters Exponential Smoothing, Croston's Intermittent Demand Model, and Seasonal Regression forecasting.

Another approach is to combine the output of the competing methods to create a more robust forecast and minimize the risk of overfitting.

Overcoming Data Sparsity Through Escalation and Pooling Levels

Demand at low levels, such as item/store, is usually too noisy to identify clear selling patterns, both for baseline and promotional sales. In such cases, generating a reliable forecast requires analyzing historical data at a higher level (escalation or pooling levels) in the hierarchy in which demand patterns can be consistently detected. The forecasting components estimated at these high levels, like seasonality curves and promotion effects, are combined with low level information, like base demand and trend, to create the low level forecast that is needed to drive the supply chain.

Forecasting Demand for New Products and Locations

IPOCS-Demand Forecasting also forecasts demand for new products and locations for which no sales history exists. There are several options for new products. First, there is the option to go on auto mode, and the user does not have to do anything. Another option is model the new product's demand based on that of an existing similar product for which you do have a history. The existing item selection can be automatically done by matching item attributes. There is also the option to manually select the item. Forecasts for the new products are copied from one item or can be a combination of multiple items. The level for the new products are copied from Like Item, the seasonal curve, and the promotional effects are from escalation.

Managing Forecasting Results Through Automated Exception Reporting

The IPOCS-Demand Forecasting end user is typically responsible for managing the forecast results for thousands of items, at hundreds of stores, across many weeks at a time. The Oracle Retail Predictive Application Server Cloud Edition (RPASCE) platform provides users with an automated exception reporting process that indicates to you where a forecast value may lie above or below an established threshold, thereby reducing the level of interaction needed from you. The framework for exception management is implemented using multiple features.



First, there are the approval exceptions, where the forecasts are run through business rules to determine if forecasts need review. For the forecasts that need review, a second layer of exceptions is available, to determine the priority in which the review should happen. This is implemented using the rules in the Business Rules Engine. In the exception dashboard profile, a user can filter down to different levels of merchandise/locations to view a hit count and the variance from the desired value of the forecast. She can then go to the Navigation exceptions tiles and launch in a workspace where she can review the exceptions sorted in order of priority as defined by business rules.

In the exception dashboard profile, the user can filter down to different levels of merchandise/locations to view a hit count and the variance from the desired value of the forecast. The user then goes to the Navigation exceptions tiles and launches in a workspace to review the exceptions sorted in order of priority as defined by business rules.

Once in the workspace, the user navigates to flagged positions using the workspace alerts which are synchronized with the exception dashboards. When an exception is resolved, the result is committed to the domain, and the dashboard exception count— upon refresh—reflects the change.

Incorporating the Effects of Promotions and Other Event-Based Challenges on Demand

Promotions, non-regular holidays, and other causal events create another significant challenge to accurate forecasting. Promotions such as advertised sales and free gifts with purchase might have a significant impact on a product's sales history, as can fluctuating holidays such as Easter. The causal forecasting functionality estimates the effects that such events have on demand. The results are used to predict future sales when conditions in the selling environment are similar. This type of advanced forecasting identifies the behavioral relationship of the variable you want to forecast (sales) to both its own past and explanatory variables such as promotion and advertising. Suppose that your company has a large promotional event during the Back To School season each year. The exact date of Back To School varies from year to year; as a result, the standard time-series forecasting model often has difficulty representing this effect in the seasonal profile. The Promotional Forecasting module allows you to identify the Back To School season in all years of your sales history, and then define the upcoming Back To School date. By doing so, you can causally forecast the Back To School-related demand pattern shift.

53 Week Calendar

For the majority of retailers, the business is managed using a calendar (364 days organized into 13 week quarters) that periodically includes an extra 53rd week so that the year end stays in about the same time of the year. It is useful to have some control over how this 53rd week will be managed within the forecasting system's time dimension. Management of this issue causes customers the pain, time and cost of configuring their data every few years that this happens.

The problem described has two implications. The first case is when two years—each with 52 weeks—of historical sales are available, and the retailer needs to forecast for the following year, which has 53 weeks. In this case, the retailer needs to have a forecast for that period, but also preserving the seasonality for the other periods. The second case is when one of the years of historical sales has 52 weeks, and the other has 53 weeks. In this case, the retailer needs to have a forecast where the 53 week history is mapped to 52 seasonality indices. There is a third case, when the 53rd week is outside the dates considered for the forecast generation. If this is the case, nothing needs to be done.



There is no special setup for handling the 53rd week. It is only the calendar file that has 53 fiscal weeks in one of the years If the 53rd week is in history, the value for that week is not taken into account when calculating time-phased metrics. Specifically for seasonality, the sales of the 53rd week are not used to calculate the 52 seasonal indices. However, for the base demand calculation, which does not have a time component, the value of the 53 week is used. If the 53rd week is in the forecast region, the seasonality for the upcoming 53rd week is the average of the week 52 and the first week of the following year.

Forecasting Process

The forecasting process represents a next generation approach engineered to provide transparency, responsiveness and accuracy through the application of retail sciences using the scale of our modern Retail Cloud Platform.

- Transparency enables analytical processes and end-users to understand and
 engage with the forecast. This is accomplished by representing the demand model
 as the decomposition of intuitive components that include base rate of demand,
 seasonality and causal effects. The forecasting process provides transparency to
 the final results, individual model components and underlying decisions by the
 system and end-user.
- Responsiveness enables the coordination and simulation of demand-driven outcomes using forecasts that adapt immediately to new information and without a dependency on batch processes. This is accomplished by separating the calculation of the forecast from the analytical processes that determine components within the forecasting model.
- Accuracy enables retailers to deliver connected customer interactions while
 driving efficiencies to increase profits. Maximizing forecast accuracy is paramount
 to IPOCS-Demand Forecasting. This is accomplished through the application of
 best-fit sciences throughout the forecasting process.

The forecast engine powering IPOCS-Demand Forecasting is the same that powers all solutions in the Retail AI Foundation Cloud Service platform. The separation of the workflow in IPOCS-Demand Forecasting and the forecast engine, allows much more flexibility in evolving the two pieces separately.

Process Summary

Following is a summary of the forecasting process:

1. Prepare Reference Data

The purpose of this step is to prepare reference data for subsequent estimation, pruning and escalation processes. The emphasis in the preparation processes is to treat anomalies in historical data, such as out-of-stock, outliers and promotions, where the objective is to increase reliability of the reference data.

2. Estimated Demand Parameters

The purpose of this step is to estimate all demand parameters and at all possible escalation levels. An escalation level represents a grouping of items and locations for robust parameter estimation to overcome sparsity and sensitivity. Escalation levels can be tied to explicit hierarchy levels (for example, subclass/region) or flexible item/location groupings (for example, optimized analytical clusters). As each demand parameter is estimated, multiple machine learning methods are



applied, individually optimized and evaluated for accuracy. The final model can represent the best-fit method or a robust method calculated as an intelligent blending of multiple methods weighted by accuracy.

3. Prune

The purpose of this step is to prune escalation levels that do not pass analytical quality checks. These include data, estimation and correlation quality checks. The result is a candidate pool of high quality parameter estimates for the escalation process.

4. Escalate

The purpose of this step is to select the demand parameter estimate for each component of the forecast model using the candidate pool of escalation levels. The escalation process reflects the optimal balance of richness and reliability.

5. Forecast

The purpose of this step is to calculate the forecast through the application of demand parameter estimates from the analytical processes in conjunction with the known demand drivers and user-overrides. The demand model is completely responsive to changes in demand drivers and updates to the demand model itself (for example, user-defined override). This step also includes support for responsive new-item forecasting, with tailored approaches for new-item scenarios, such as dynamic, repeatable and similar assortments.

User Experience and Workflow

The user experience is delivered on our experience-inspired RPAS Cloud Edition (RPASCE) user interface (UI). RPASCE provides end-users with a next generation cloud-native UI that is purpose-built to accelerate intent into action for planners and forecasters. This includes interactive and visual dashboards to assess priorities, responsive and flexible workspaces to implement decisions and a coordinated exceptions framework that ties business process all the way from dashboard to cell.

The business process is engineered to maximize the productivity of end-users through exception-driven processes and emphasis on workflow simplification. The day-in-the-life processes begin with dashboard views that enable the end-user to assess the effectiveness and quality of their forecasts and prioritize exceptions. From the dashboards, the end-user is able to contextually launch into the appropriate workspace. For exception-driven processes, the end-user is guided to the point-of-resolution, with visibility to progress and the ability to iteratively work through forecasting priorities throughout the day.

Dashboard Views and Workspaces

The dashboard views and workspaces that support day-in-the-life forecasting workflows are summarized as follows:

Forecast Overview Dashboard

This dashboard leads with Key Performance Indicators (KPIs) that provide macro-level insight into forecasting priorities and the effectiveness of the forecasts in driving demand-driven outcomes. This enables end-users to assess forecasting complexity drivers, such as frequent promotions, and forecasting performance towards business objectives, such as fill rates.

Forecast Scorecard Dashboard



This dashboard provides insight to forecast accuracy (for example, MAPE, Bias) along with clear visibility to system performance and the impact of end-user contributions to the forecasting process. This enables forecast analysts and managers to identify forecast process improvement priorities.

Exception Dashboards

The exception dashboards represent the primary starting point for day-in-the-life processes. The approval and navigation exceptions each have a dedicated dashboards that enables end-users to efficiently drive decisions through focused exception-driven processes. From here, end-users can define the scope of exceptions to be managed through dashboard filters and launch directly to workspace views tailored for resolution. As exceptions are resolved, the dashboard is updated to enable end-users to iteratively work through forecasting priorities.

Forecast Review Workspaces

The forecast approval workspaces represent the primary point of interaction with the demand forecasts. The navigation exceptions and their workspace counterparts allow you to review forecast information guided by priorities that are dynamically implemented in the Business Rule Engine. This is supported by a rich set of decision support metrics and the ability to responsively simulate forecast updates.

Forecast Engine


Not visible to the end user is the forecast engine, and all the tasks happening behind the scenes. The forecast engine produces a single version of forecast that is used in IPOCS-Demand Forecasting, all Retail AI Foundation Cloud Service solutions, as well as planning and merchandising. The batch is split between estimation and forecasting. Estimation consists of the heavy data mining of historical demand to generate the necessary forecast parameters like seasonality, price and promo effects. Following are tasks which comprise the estimation workflow within the Retail AI Foundation Cloud Service.

Refer to the *Oracle Retail AI Foundation User Guide* for details on the methodology used for forecast generation.



Figure 1-1 IPOCS-Demand Forecasting Estimation

IPOCS-Demand Forecasting: Estimation



After estimation is run, the forecast parameters are computed, and everything is available to generate the forecast.

The forecast generation is happening in the forecast engine, while all the workflow-related activities are happening in the IPOCS-Demand Forecasting solution.



Override Defaults Generate by **Forecasts** Product / Location Auto Approval Manual Approval **Approve** Set by Alert Review NO **Forecast Dashboard** Default YES Review Legend **Exceptions** Approved **Export** Daily / Weekly Tasks What-If **Forecasts Approve** Ad Hoc Tasks **Forecasts Automated Tasks**

IPOCS-Demand Forecasting: Forecasting

Figure 1-2 Forecasting for IPOCS-Demand Forecasting



Demand Forecasting Dashboard

The IPOCS-Demand Forecasting Dashboard is the workspace that is seen upon login. You can use the dashboard to quickly analyze the health of the business. The dashboard will need to be refreshed periodically as new products, locations, and demand-related data are added. This typically happens weekly, but depends on your administrator's settings. The measure data of existing products and locations in the dashboard can be refreshed at any time to view updated changes.



For additional information about the user interface, dashboard, and workspaces, click **Application Help** from the Help icon on the dashboard.

IPOCS-Demand Forecasting has two dashboard profile types and includes two profiles for each type:

- Metric profile type
 - Overview Dashboard
 - Forecast Scorecard Dashboard
- Exception profile type
 - Approval Alerts
 - Navigations Alerts

Figure 2-1 Dashboard Profiles






The information in the metric and exception profiles is summarized in tiles, which can be filtered on the product, location, or any other hierarchy that makes sense as shown in Figure 2-2 and Figure 2-3.

Figure 2-2 Product Filter



Figure 2-3 Location Filter



The information that is presented condensed in the tile metrics, is also presented in a chart with more detail.

In addition there is the Administration dashboard which gives information about scheduled OAT tasks, or workspace build information. More about the Administration dashboard can be found in the *Oracle Retail Predictive Application Server Cloud Edition User Guide*.

Overview Dashboard

There are five GA tiles in the Overview dashboard.






Figure 2-4 Overview Dashboard

Note:

This view has a dual Y-axis and the scales of the Y-axes could be different from each other.

Current and Historical In-stock Rates

The first tile displays information about how often stockouts occurred. If every four weeks, a stockout is registered, the in-stock rate would be 75%. This information is driven by how often stockouts occur. The tile displays current and historical fill rates.

The in-stock calculations are:

In-stock% = (total number of periods - periods with outage) / total number of periods number of periods for the Current version of the metric: given by Current Period Window in Forecast Setup/Exception Management step number of periods for Historic version of the metric: given by Historic Period Window in the Forecast Setup/Exception Management step.

Stockouts

The second tile displays information about the current and historical fill rates, which are related to service levels. This information is directly tied to the amount of lost sales caused by total or partial stockouts.

Breakdown of Sales

The third tile shows the breakdown of sales. The total sales are the sum of regular, promotional and markdown sales. The promotional and markdown sales are displayed as secondary metrics to gauge the amount of sales driven by these extraordinary events.



Promotional and Markdown Sales

The last two tiles display information about promotional and markdown sales. Besides the total units, additional information is displayed as secondary metrics. For instance, the tiles display how often the merchandise are promoted or marked down, as the promo or markdown frequency. Also, it shows the effectiveness of how promoting or marking down merchandise is increasing demand as compared to regular demand.

The calculations for the Markdown Effectiveness and Frequency are:

Markdown Effectiveness = (sum of markdown units) / (sum of regular units)

Markdown Frequency = (number of periods with markdown sales) / (total number of periods)


The number of periods used for these calculations is given by Recent Sales Window in Forecast Setup/Exception Management step.

It may seem a little confusing to introduce yet another time window, but if we are using just the current period window, all the periods may have markdown sales, which may not be a complete picture of the business. This is why markdown has its own controls.

Forecast Scorecard Dashboard

The information displayed in this dashboard helps the forecast analyst or forecast manager determine how accurate the forecasts are.

Figure 2-5 Forecast Scorecard Dashboard



Error Metrics

These are the error metrics:

- Mean Absolute Percentage Error
- Root Mean Squared Error
- Mean Absolute Error
- Forecast Bias
- Percent Adjusted

The error metrics are detailed in Appendix: Forecast Errors in the Forecast Scorecard Dashboard. They are calculated for both the user-adjusted, as well as for the system-generated forecasts, allowing a fair evaluation of the performance of the analyst versus the system.



Forecast Bias

Another tile is dedicated to the forecast bias, a useful metric in determining if the forecast is consistently over or under the actual demand.

Percent Adjusted and Adjusted Volume

Finally, there is the Percent Adjusted tile, with the Adjusted Volume as the secondary metric. Here is displayed the percent of adjusted forecasts, and the volume resulted as the result of the adjustments. For instance, if the percent adjustment is high, but the adjusted volume is not significant, the analyst may want to spent time and effort on other areas of the merchandise.

Approval Alerts

This is the exception profile that shows the result of the approval business rules.




Figure 2-6 Approval Exceptions

Exceptions

The information displayed in the tiles is based on exceptions, or business rules defined to check if the forecasts are within bounds with respect to some thresholds. The exceptions definitions and expressions are detailed in Appendix: Forecast Approval Exceptions.

Number of Hits Count

The main metric in the tiles is the number of hits count which is based on the product and location filter settings. If the filter settings range products and locations to a narrower selection than, *All Product* and *All Location*, then the number should be reflected in the tile; that is, it should decrease.

Number of Subclass and Districts

The secondary metric on the tiles display the number of subclass and districts that are affected. Note that the dimensions are configurable.

Charts

Each tile comes with a set of charts where the hit count information is broken down to lower levels and sorted based on hit count, or average variance.





The average variance represents how much off the forecast is versus its target. For example we compare the forecast against last year sales. If the sales are 10 units and the forecast is 15 units, the variance is 5 units. The average variance is the average of all the differences between forecast and last year sales.

The hit count represents how many times the forecast did not pass the configured business rules. The average variance represents by how much the forecasts were off. This is useful, because if a subclass is heavily alerted, but the forecasts only barely miss the threshold, the user may want to concentrate on other merchandise, potentially less alerted, but where the forecasts were off by a larger amount.

Navigations Alerts

The approval exceptions are very helpful in deciding what product/locations are approved and which ones need review. However, reviewing unapproved product/locations in order of critically, makes the reviewing process much more efficient. You can start reviewing Urgent items, then move on to Required, and if time permits you can review Optional and then Informational.




Figure 2-7 Navigation Exceptions

Exceptions

The product/locations presented in this dashboard are virtually the same as the ones in the Approval Exceptions. The difference is that the product locations are sorted in order of priority, which is a proxy for the importance to the business. The rules to determine the priorities are set up in the Business Rule Engine, as detailed in the Appendix: Business Rule Engine.



Forecast Review Workspace

Finally, when a user makes a decision as to which merchandise and locations to review, the user can launch directly in the Forecast Review workspace by clicking **Open in Workspace**, with the locations and product ranged down to the desired selection. Once in the workspace, you can choose to use the navigation alerts to navigate to product/locations. Every navigation exception can have a workspace counterpart. Using these exceptions you are guided to the exact product, location, and time period that needs your attention.

The **Open in Workspace** button is located in the right corner above the top chart



Alternatively, you can right-click on any exception chart and select **Open in Workspace**



New Item & Locations Task

This chapter describes the capabilities around forecasting New Items and New Stores. Forecast generation for New Items can be fully automated, while for New Stores the process is manual.

In general, an item is eligible to be considered new if it satisfies the following condition:

 Forecast start date override is in the future or Sales history length is less than the time series duration parameter

An item is eligible to be considered a Like Item if it satisfies these conditions:

- Its recent sales density needs to be larger than a threshold or zero for a special case.
- Its sales history needs to be longer than the time series duration parameter.
- Finally, we provide the Like Item exclusion mask measure, which can be populated by custom rules through which the implementer can include any other eligibility conditions.

Once a New Item is assigned a system recommended Like Item, it is not processed it in the next New Item batch because it is considered already taken care of.

If you set up the New Item to do manual approve first, all the New Items in the system are handled as manual approval.

In general, if auto approval is turned on, and batch is ran, the items already processed will be skipped in the batch as we only look at *refresh New Item* in each batch.

These workspaces help you achieve this task:

- New Item Maintenance Workspace
- New Store Maintenance Workspace
- New Item Management Workspace

New Item & Locations Workspaces, Steps, and Views

The following table lists the workspaces, steps, and views for the New Item & Locations task.

Table 3-1 New Item & Locations Workspaces, Steps, and Views

Workspace	Steps	Views
New Item	New Item Settings Step	New Item Basic Parameters View
Maintenance Workspace	Like Item - Select and Approve Step	New Item Forecast View New Item Statistics View Select and Approve View
New Store Maintenance Workspace	Like Store Assignment Step	Product Like Store Assignment View

Table 3-1 (Cont.) New Item & Locations Workspaces, Steps, and Views

Workspace	Steps	Views
New Item Management Workspace	Settings Step	New Item Basic Parameters View
	Manage Step	New Item Attributes View New Item Statistics View Select and Approve View New Item Forecast View
	View Step	Attribute Value View Similarity Score View

New Item Maintenance Workspace



There are two workspaces that can help you with setting up New Items for forecast generation:

- New Item Maintenance Workspace—Use when item attributes are not available and you need to manually select Like Items from the New Item Maintenance workspace.
- New Item Management Workspace —Use when item attributes are available, the Like Item selection can be automated using the New Item Management workspace.

It is recommended to use only one of the two workspace options, depending on whether or not attributes are available. The other workspace can be easily hidden using Access Rights.

The workflow in the New Item Maintenance workspace starts by selecting the New Items. An item is defined as new if it has a forecast startdate override that is in the future, that is later than the RPAS_TODAY date. The date can be loaded in the measure if available. If not, the date can be entered manually. Once you identified the New Item and the forecast startdate override is populated, you can select the substitution method. Depending on your selection, you may need to enter additional information. The workflow message measure guides you through the process. For instance, if you choose the Like Item option, you need to specify a Like Item. If you do not specify a Like Item, the workflow message warns you and displays *User Specified Like Item Not Set*. You have successfully set up a New Item for forecasting when the workflow message is cleared and the Approval flag is selected. You finish by running the Approve New Items custom menu.






You can work on multiple New Items and run the custom menu after you have set them all up.

Another helpful tool in the process of setting up New Items is the Workflow Message Count measure. It displays the number of item/store combinations that have been flagged as new, but have not yet been successfully set up. If setting up the New Items was successful, then the measure displays a count of zero.

To build the New Item Maintenance workspace, perform these steps:

1. From the left sidebar menu, click the Task Module to view the available tasks.






- 2. Click the **New Item/Store** activity to access the available workspaces.
- 3. Click **New Item Maintenance**. The New Item Maintenance wizard opens.

You can open an existing workspace, but to create a new workspace, click **Create New Workspace**.



Figure 3-2 New Item Maintenance Wizard



4. Enter a name for your new workspace in the label text box and click **OK**.

Figure 3-3 Enter Workspace Label



The Workspace wizard opens. Select the products you want to work with and click Next.


Figure 3-4 Workspace Wizard: Select Products

Select Products Levels & Positions Company Label ⊡ Level ■ Label 1312Casual* Company 1322Casual* Division $\overline{\mathbf{v}}$ Coffee Group Coffee Maker Department $\overline{\mathbf{z}}$ Missy Sweaters Class Missy Tops Subclass Grandparent Item




6. Select the locations you want to work with and click **Finish**.

Figure 3-5 Workspace Wizard: Select Locations



7. The wizard notifies you that your workspace is being prepared. Successful workspaces are available from the Dashboard.

Figure 3-6 Successful Workspace Build



New Item Settings Step


This step contains the New Item Basic Parameters View.

New Item Basic Parameters View

The New Item Basic Parameters view allows you to set default values for some parameters related to the New Item functionality.



Figure 3-7 New Item Basic Parameters View



Measures: New Item Basic Parameters View

The New Item Basic Parameters view contains the following measures.

Adjustment Factor

The only demand component needed to generate forecast for New Items is base demand. If the Like Item substitution method is selected, the adjustment factor specifies what percent of a Like Item's base demand will be copied to the New Item.

Auto-approve

You decide if automatic Like Item recommendations are automatically approved by selecting this measure. If the automatic Like Item recommendations are not automatically approved, the system suggested Like Items are still displayed, but not used in forecast generation.

Substitute Method

This measure displays a list where you can select the substitute method. When a substitute method is used to forecast, the method set for an intersection is cleared once the Default Forecast Start Date is greater than the Forecast Start Date Override plus the Like TS Duration for the intersection. Valid substitute method options are:

None

No forecast is created for the New Item.

Like Item

The forecast is created using the base demand of a Like Item. The Like Item is selected in the User Selected Like Item measure in the Like Item - Select and Approve view. The forecast of the New Item is given by:

Base demand New Item = base demand Like Item * Adjustment Factor



Forecast at time t = base demand New Item * seasonality at time t (comingfrom escalation level) * promo and price effects (coming from pooling level)

Base Rate of Demand

IPOCS-Demand Forecasting calculates the escalated base rate of demand. The forecast for the new item is given by::

Forecast at time t = base rate of demand (coming from escalation level) * seasonality attime t (coming from escalation level) * promo and price effects (coming from pooling level)

User Input

This method is very similar to Base Rate of Demand, with the difference that you have to manually specify a base rate of demand. The forecast is then generated using the same formula as for Base Rate of Demand.

Threshold Recent Sales Density

In this measure, you enter the threshold for the data density. If the actual density is larger than the threshold, the time series qualifies to serve as Like Item/location for a new/item/ location. The data density is calculated as:

data density = number of periods with demand larger than zero / total length of demand

For a time series with the following demand values:

0,1,0,1,0,today

The data density is 2/4 = 50%

History Time Series Duration

In this measure you can enter the threshold for the historical demand duration to determine if a time series is considered. If the demand history is less than the threshold, the forecast of the new time series is generated using the New Item/store functionality. If the demand length is larger than the threshold, the time series is not considered new anymore, and its own demand is used to generate the forecast.



Tip:

Consider the threshold is set to five periods, and the first week of sales is 10 weeks ago, In this case, the item is not considered new anymore. Whatever Like Item strategy was selected for the item is not applied anymore and the forecast is generated based on its own demand.

Like Item - Select and Approve Step

This step contains views that allow you to set up the forecasting strategy for New Items.

The available views are:


- **New Item Forecast View**
- New Item Statistics View
- Select and Approve View



New Item Forecast View

In this view you are able to view the forecast of the New Item based on the selected strategy.

Figure 3-8 New Item Forecast View



Measures: New Item Forecast View

The New Item Forecast view contains the following measures.

New Item Forecast Weekly Forecast

This measure displays the forecast resulting from a What-if action performed in the workbook.


Current New Item Forecast Weekly Forecast

This measure displays the approved forecast calculated in batch. If no new item strategy has been selected prior to the batch run, this measure is empty.

New Item Statistics View

The measures in this view are supporting the New Item setup process that happens mainly in the Figure 3-10.

Figure 3-9 New Item Statistics View





Measures: New Item Statistics View

The New Item Statistics view contains the following measures.

Workflow Message Count

This measure displays the count of the Workflow Message measure in the Select and Approve view. The workflow messages are guiding you in the New Item setup process. If the count is zero, you have set up correctly all New Items. The count corresponds to the number of New Item/store combinations that you still have to finish setting up.


Store Count

This measure displays the number of stores that a New Items has been set up for.

Select and Approve View

This view enables you to set up your New Items for forecasting. Depending on the strategy you select in the Substitution Method, you can choose a fully automated process, or you may need to enter additional information. The workflow messages are guiding you through the process.

Figure 3-10 Select and Approve View



Measures: Select and Approve View

The Select and Approve view contains the following measures.



Substitute Method

This measure displays a list where you can select the substitute method. When a substitute method is used to forecast, the method set for an intersection is cleared once the Default Forecast Start Date is greater than the Forecast Start Date Override plus the Like TS Duration for the intersection. Valid substitute method options are:

None

No forecast is created for the New Item.

Like Item

The forecast is created using the base demand of a Like Item. The Like Item is selected in the User Selected Like Item measure in the Like Item - Select and Approve view. The forecast of the New Item is given by:

Base demand New Item = base demand Like Item * Adjustment Factor

Forecast at time t = base demand New Item * seasonality at time t (coming from escalation level) * promo and price effects (coming from pooling level)

Base Rate of Demand

IPOCS-Demand Forecasting calculates the escalated base rate of demand. The forecast for the new item is given by::

Forecast at time t = base rate of demand (coming from escalation level) * seasonality at time t (coming from escalation level) * promo and price effects (coming from pooling level)

User Input

This method is very similar to Base Rate of Demand, with the difference that you have to manually specify a base rate of demand. The forecast is then generated using the same formula as for Base Rate of Demand.

User Provided Base Demand

If the User Input substitution method was selected, you have to enter here the base rate of demand that is going to be used for the New Item when generating forecast.

User Selected Like Item

If the Like Item substitution method was selected, you have to select here the Like Item whose base demand is going to be used for the New Item when generating forecast.

Like Item Average Sales

If you selected the Like Item substitution method, and have chosen a Like Item from the picklist, this measures displays the average sales of the Like Item. This is useful because it gives you an idea of the base rate of demand that is going to be used when generating the forecast for the New Item. It is not the exact value because it is recalculated every time the forecasting batch is run, but it is likely be very close.

Forecast Startdate Override

This is a very important measure because it identifies an item as being new. It can be loaded if the information can be interfaced from another system. If not available, you can manually set it.

Approve Flag



When the set up process for forecasting the New Item was successful, this measure becomes True and the measure displays a check mark. You are now ready to run the Approve New Items custom menu to approve the New Item forecast strategy.

Approve Date

This measure displays the date when the Like Item recommendation was approved by running the custom menu.

Adjustment Factor

The only demand component needed to generate forecast for New Items is base demand. If the Like Item substitution method is selected, the adjustment factor specifies what percent of a Like Item's base demand will be copied to the New Item.

Workflow Message

The information in this measure guides you through the forecast setup process for New Items. It informs you on the next steps depending on the substitution method that you selected.

Table 3-2 Workflow Message

Message	Cause	Action
Substitution Method Not Set	You have identified a New Item and set the Forecast Startdate Override, but did not select a substitution method.	Select a Substitution Method
User Specified Like Item Not Set	You have identified a New Item and selected Like Item as substitution method, but you did not select a Like Item.	Select a User Selected Like Item
Base Demand Not Input By User	You have identified a New Item and selected Base Rate of Demand as substitution method, but you did not input a User Provided Base Demand.	Input a User Provided Base Demand
Existing Item	You have entered a Forecast Startdate Override for an item that is not new	Either clear the date to avoid confusion. Even if you do not, no action is taken for the item with respect to New Item forecast setup.

Custom Menus

There are a two custom menus relevant to this view.

Approve New Items

After you set up the strategy to forecast New Items, then running the custom menu approves the strategy. The setup includes selecting a substitution method, Like Items, and percent contribution, among others. After running the **Approve New Items** custom menu, the Approve Date measure is populated with the current date.

Recalculate Eligible Like Items

When the workbook is built, the set of eligible Like Items is calculated using the last committed threshold values. You can change some threshold values in the workspace. For instance, lowering the Threshold Recent Sales Density will likely increase the number of eligible Like Items. To see the result of the threshold change, the **Recalculate Eligible Like Items** custom menu needs to be run.



New Store Maintenance Workspace


Use this workspace to assign like stores to handle forecasting for New Stores. The like store assignment is manual and there is a good reason for it. New stores have a large financial impact, so it makes sense having a business person making the like store selection.

It is probably more appropriate than going with an automatic selection based on something like store attributes. Also, new store introductions are infrequent compared to New Item introductions, so manually handling New Stores is not a significant overhead activity.

To build the New Store Maintenance workspace, perform these steps:

1. From the left sidebar menu, click the Task Module to view the available tasks.






- Click the New Item/Store activity and then click New Item/Location again to access the available workspaces.
- Click New Store Maintenance. The New Store Maintenance wizard opens.
 You can open an existing workspace, but to create a new workspace, click Create New Workspace.




Figure 3-12 New Store Maintenance Wizard



4. Enter a name for your new workspace in the label text box and click **OK**.

Figure 3-13 Enter Workspace Label



5. Select the locations you want to work with and click **Finish**.


Figure 3-14 Workspace Wizard: Select Locations

Select Locations Levels & Positions Company Label Level Label 11 Southeastern US Company 12 Northeastern US Chain 13 Midwest US Area 14 Northcentral US \sim Region 15 Southwestern US District 31 Eastern Canada Store 32 Canadian Lakes 33 Western Canada

6. The wizard notifies you that your workspace is being prepared. Successful workspaces are available from the Dashboard.



Figure 3-15 Successful Workspace Build




Like Store Assignment Step

This step contains the Product Like Store Assignment View.

Product Like Store Assignment View

The Product Like Store Assignment view is at the intersection of prod/location, so all parameters can vary by product. For example, a new store opening in the Midwest can have a Like Store from Alaska for items in the Shovels department. However, for summer items, the Like Store is picked from the Northeast region.

Figure 3-16 Product Like Store Assignment View



Measures: Product Like Store Assignment View

The Product Like Store Assignment view contains the following measures.

Like Store

In this measure, you can specify the like store. Note how the like store can be different by product. In IPOCS-Demand Forecasting, a different like store selection can be made for every subclass.

Adjustment Factor

This measure is relevant to the Like Store Substitution method. It determines how much of the base rate of demand of a like store is applied to the new store. For instance, if the adjustment factor is 1.25, the base rate of demand of the new store is 1.25 times the base rate of demand of the like store.

Substitute Method

This measure displays a list where you can select the substitute method. When a substitute method is used to forecast, the method set for an intersection is cleared once the Default Forecast Start Date is greater than the Forecast Start Date Override plus the Like TS Duration for the intersection. Valid substitute method options are:

None

No forecast is created for the time series.

Like Store

If you select Like Store as strategy to generate forecast for the new store, the base demand of the new store is the base demand of the like store times the Adjustment Factor.

Base demand new store = base demand like store * Adjustment Factor

The forecast for the new store is calculated as:

Forecast at time t = base demand new store * seasonality at time t (coming from escalation level) * promo and price effects (coming from pooling level)

Forecast Start

This measure specifies the first date for which forecast is generated for the new store.

New Item Management Workspace

Note:

There are two workspaces that can help you with setting up New Items for forecast generation:

- New Item Maintenance Workspace—Use when item attributes are not available and you need to manually select Like Items from the New Item Maintenance workspace.
- New Item Management Workspace —Use when item attributes are available, the Like Item selection can be automated using the New Item Management workspace.

It is recommended to use only one of the two workspace options, depending on whether or not attributes are available. The other workspace can be easily hidden using Access Rights.

The workflow in the New Item Management workspace starts by selecting the New Items. An item is defined as new if it has a forecast startdate override that is in the future, that is., past RPAS_TODAY. The date can be loaded in the measure if available. If not, the date can be entered manually. Once you identified the New Item and the forecast startdate override is

populated, you can select the substitution method. Depending on your selection, you may need to enter additional information. The workflow message measure will guide you through the process. For instance, if you choose *User Input*, you need to provide the *User Provided Base Demand*. If you do not provide the *User Provided Base Demand*, the workflow message warns you and displays *Base Demand Not Input By User*. You have successfully set up a New Item for forecasting when the workflow message is cleared and the Approval flag is selected. You finish by running the Approve New Items custom menu.



You can work on multiple New Items and run the custom menu after you have set them all up.

Another helpful tool in the process of setting up New Items is the Workflow Message Count measure. It displays the number of item/store combinations that have been flagged as new, but have not yet been successfully set up. When setting up the New Items was successful the measure will display a count of zero.

There are a few key features that are available in the New Item Management that are not included in New Item Maintenance:

- System Recommended Like Item based on the similarity between new and existing items
- Ability to display a User Selected Like Item picklist that is sorted by the similarity between new and existing items
- Ability to control how many items are included in the User Selected Like Item picklist
- Ability to edit attribute weights and immediately see the updated Like Item recommendations

Settings Step


This step contains the New Item Basic Parameters View.

New Item Basic Parameters View

The New Item Basic Parameters view is used to set default values for some parameters related to the New Item functionality.



Figure 3-17 New Item Basic Parameters View



Measures: New Item Basic Parameters View

The New Item Basic Parameters view contains the following measures.

Adjustment Factor

The only demand component needed to generate forecast for New Items is base demand. If the Like Item substitution method is selected, the adjustment factor specifies what percent of a Like Item's base demand will be copied to the New Item.

Auto-approve

You decide if automatic Like Item recommendations are automatically approved by selecting this measure. If the automatic Like Item recommendations are not automatically approved, the system suggested Like Items are still displayed, but not used in forecast generation.

Substitute Method

This measure displays a list where you can select the substitute method. When a substitute method is used to forecast, the method set for an intersection is cleared once the Default Forecast Start Date is greater than the Forecast Start Date Override plus the Like TS Duration for the intersection. Valid substitute method options are:

None

No forecast is created for the New Item

Like Item

The forecast is created using the base demand of a Like Item. The Like Item is selected in the User Selected Like Item measure in the Like Item - Select and Approve view. The forecast of the New Item is given by:

Base demand New Item = base demand Like Item * Adjustment Factor

Forecast at time t = base demand New Item * seasonality at time t (coming from escalation level) * promo and price effects (coming from pooling level)



Base Rate of Demand

IPOCS-Demand Forecasting calculates a base rate of demand based on items in the same class (dimension is configurable). The forecast for the New Item is given by:

Forecast at time t = base rate of demand * seasonality at time t (coming from escalation level) * promo and price effects (coming from pooling level)

User Input

This method is very similar to Base Rate of Demand, with the difference that you have to manually specify a base rate of demand. The forecast is then generated using the same formula as for Base Rate of Demand

Threshold Recent Sales Density

In this measure, you enter the threshold for the data density. If the actual density is larger than the threshold, the time series qualifies to serve as Like Item/location for a new/item/location. The data density is calculated as:

data density = number of periods with demand larger than zero / total length of demand

For a time series with the following demand values:

0,1,0,1,0,today

The data density is 2/4 = 50%

If the value for the threshold is zero, an item that is not actively selling can also be eligible as Like Item if it has an approved base demand.

This can be useful when the item to be introduced is a replacement or similar to an item that sold last season. In this case the base demand of the New Item will be modeled after the approved base demand of the item that it replaced.

History Time Series Duration

In this measure you can enter the threshold for the historical demand duration to determine if a time series is considered. If the demand history is less than the threshold, the forecast of the new time series is generated using the New Item/store functionality. If the demand length is larger than the threshold, the time series is not considered new anymore, and its own demand is used to generate the forecast.



Tip:

Consider the threshold is set to five periods, and the first week of sales is 10 weeks ago, In this case, the item is not considered new anymore. Whatever Like Item strategy was selected for the item is not applied anymore and the forecast is generated based on its own demand.

Recommended Number of Like ItemsIn this measure you specify how many item you want to see in the User Selected Like Item picklist, in the Select and Approve view. If you change the value, by clicking the Calculate custom menu, the picklist is regenerated to reflect the new setting. The items in the picklist are sorted by similarities, which are calculated using item attributes and their weights.



Manage Step

This step contains views that allow you to set up the forecasting strategy for New Items.

The available views are:

- New Item Attributes View
- New Item Statistics View
- Select and Approve View
- New Item Forecast View

New Item Attributes View

In this view you can view item attributes as well as their weights. The weights can be edited, and they are managed at an intersection higher than SKU. For instance, for the coffee class the Roast attribute has a weight of 0.4. Once you change the value of any attribute weight, the similarity matrix is recalculated. This also triggers the regeneration of the user Like Item picklist. The items in the picklist are sorted by similarities, which are calculated using item attributes and their weights.

Figure 3-18 New Item Attributes View



Measures: New Item Attributes View

The New Item Attributes view contains the following measure.

Attribute Weight

This measure displays the current weight by item attributes.

New Item Statistics View

The measures in this view are supporting the New Item setup process that happens mainly in the Select and Approve view.



Figure 3-19 New Item Statistics View



Measures: New Item Statistics View

The New Item Statistics view contains the following measures.

Workflow Message Count

This measure displays the count of the Workflow Message measure in the Like Item – Select and Approve view. The workflow messages are guiding you in the New Item setup process. If the count is zero, you have set up correctly all New Items. The count corresponds to the number of New Item/store combinations that you still have to finish setting up.

Store Count

This measure displays the number of stores that a New Items has been set up for.

Select and Approve View

This view enables you to set up your New Items for forecasting. Depending on the strategy you select in the Substitution Method, you can choose a fully automated process, or you may need to enter additional information. The workflow messages are guiding you through the process.



Select and Approve 品 П Location Product 品 \Box Measure (Default) < 1234768 - PL -1057 Green Bay 1006 Chicago Location Measure Substitute Method Base Rate of None User Provided Base Demand 0.00 0.00 User Selected Like Item Like Item Average Sales Forecast Start Date Override П Approve Flag Approve Date Adjustment Factor 1.00 1.00 Workflow Message Existing Item

Figure 3-20 Select and Approve View

Measures: Select and Approve View

The Select and Approve view contains the following measures.

Substitute Method

This measure displays a list where you can select the substitute method. When a substitute method is used to forecast, the method set for an intersection is cleared once the Default Forecast Start Date is greater than the Forecast Start Date Override plus the Like TS Duration for the intersection. Valid substitute method options are:

None

No forecast is created for the New Item.

Like Item

The forecast is created using the base demand of a Like Item. The Like Item is selected in the User Selected Like Item measure in the Like Item - Select and Approve view. The forecast of the New Item is given by:

Base demand New Item = base demand Like Item * Adjustment Factor

Forecast at time t = base demand New Item * seasonality at time t (coming from escalation level) * promo and price effects (coming from pooling level)

Base Rate of Demand

IPOCS-Demand Forecasting calculates the escalated base rate of demand. The forecast for the new item is given by:



Forecast at time t = base rate of demand (coming from escalation level) * seasonality at time t (coming from escalation level) * promo and price effects (coming from pooling level)

User Input

This method is very similar to Base Rate of Demand, with the difference that you have to manually specify a base rate of demand. The forecast is then generated using the same formula as for Base Rate of Demand

User Provided Base Demand

If the User Input substitution method was selected, you have to enter here the base rate of demand that is going to be used for the New Item when generating forecast.

Forecast Startdate Override

This is a very important measure because it identifies an item as being new. It can be loaded if the information can be interfaced from another system. If not available, you can manually set it.

Approve Date

This measure displays the date when the Like Item recommendation was approved by running the custom menu.

Adjustment Factor

The only demand component needed to generate forecast for New Items is base demand. If the Like Item substitution method is selected, the adjustment factor specifies what percent of a Like Item's base demand will be copied to the New Item.

Workflow Message

The information in this measure guides you through the forecast setup process for New Items. It informs you on the next steps depending on the substitution method that you selected.

Message	Cause	Action
Substitution Method Not Set	You have identified a New Item and set the Forecast Startdate Override, but did not select a substitution method.	Select a Substitution Method
User Specified Like Item Not Set	You have identified a New Item and selected Like Item as substitution method, but you did not select a Like Item.	Select a User Selected Like Item
Base Demand Not Input By User	You have identified a New Item and selected Base Rate of Demand as substitution method, but you did not input a User Provided Base Demand.	Input a User Provided Base Demand
Existing Item	You have entered a Forecast Startdate Override for an item that is not new	Either clear the date to avoid confusion. Even if you do not, no action is taken for the item with respect to New Item forecast setup.



Approved Like Item

This measure is relevant if you selected the Like item substitution method. If you go through the process to set up the New Item, and use the System Recommended Like Item or override by selecting another Like Item from the User Selected Like Item picklist, the Approval Flag is checked. Running the Approve New Items custom menu populates this measure.

System Recommended Like Item

This measure is relevant if you selected the Like item substitution method. Your environment needs to have item attributes and attributes weights, so similarities between new and existing items are calculated. In this case, the potential Like Items are sorted by their similarity scores, and the item with the highest score is displayed as the system recommendation.

Note how the Like Items are not displaying just the item label. First, you see a percentage. This represents how similar the Like Items are to the New Items. A value closer to 100% means high similarity. The second value shows the average demand of the Like Item. This is useful in selecting a Like Item, because it is an indication of forecast magnitude. This value is recalculated to reflect the latest data point, so what you see here may be outdated by a week. Finally the third element is the item label.

User Selected Like Item

This measure is relevant if you selected the Like item substitution method. It shows a picklist with items that you can select to override the system recommendation. The number of items displayed in the picklist is set in the Recommended Number of Like Items measure in the Settings step.

Note how the Like Items are not displaying just the item label. First, you see a percentage. This represents how similar the Like Items are to the New Items. A value closer to 100% means high similarity. The second value shows the average demand of the Like Item. This is useful in selecting a Like Item, because it is an indication of forecast magnitude. This value is recalculated to reflect the latest data point, so what you see here may be outdated by a week. Finally the third element is the item label.

Approve Flag

When the set up process for forecasting the New Item was successful, this measure becomes True and the measure displays a check mark. You are now ready to run the Approve New Items custom menu to approve the New Item forecast strategy.

User Forecast

This measure displays the adjusted forecast calculated in batch. If no new item strategy has been selected prior to the batch run, this measure is empty.

New Item Forecast

This measure displays the forecast resulting from a What-if action performed in the workbook.

Current New Item Forecast


This measure displays the approved forecast calculated in batch. If no new item strategy has been selected prior to the batch run, this measure is empty.

New Item Forecast View

In this view you are able to view the forecast of the New Item based on the selected strategy.



Figure 3-21 New Item Forecast View



Measures: New Item Forecast View

The New Item Forecast view contains the following measures.

User Forecast

This measure displays the adjusted forecast calculated in batch. If no new item strategy has been selected prior to the batch run, this measure is empty.

New Item Forecast

This measure displays the forecast resulting from a What-if action performed in the workbook.

Current New Item Forecast

This measure displays the approved forecast calculated in batch. If no new item strategy has been selected prior to the batch run, this measure is empty.

View Step

This step contains views that allow you to view item attributes and how attributes define similarities among items.

The available views are:


- Attribute Value View
- Similarity Score View

Attribute Value View

This view displays attributes by product.



Figure 3-22 Attribute Value View



Measures: Attribute Value View

The Attribute Value view contains the following measure.


Product Attribute

This measure displays the attributes of an item.

Similarity Score View

In this view you can review the similarity scores between new and existing items. This view is Position Query (PQD) defined, so you can filter the Product hierarchy to show only positions corresponding to New Items.

Figure 3-23 Similarity Score View





Measures: Similarity Score View

The Similarity Score view contains the following measures.

Similarity Scores

This measure displays the similarity scores among new and existing items.

What-if Similarity Scores

Similarity Scores are based on an item's attribute assignment and attribute weights and calculated in AI Foundation. The higher the number between two items the more similar the two items are. .



4

Forecast Setup Task

This chapter describes the Forecast Setup task for IPOCS-Demand Forecasting.

Forecast Setup Workspaces, Steps, and Views

The following table lists the workspaces, steps, and views for the Forecast Setup task.

Table 4-1 Forecast Setup Workspaces, Steps, and Views

Workspace	Step	Views
Forecast Setup Workspace	General Step	Basic Parameters View Advanced Parameters View Intermediate Level View Final Level View
	Exception Management Step	Basic Parameters View Intermediate Level View Final Level View

Forecast Setup Workspace

The Forecast Setup workspace allows you access to all of the views listed in Forecast Setup Workspace.


The workspace is intended for the business user, who sets high level forecast parameters such as forecast length, start, or end. It is also the place to select adjustment and approval strategies through the exception management capabilities provided by RPAS.

For details on forecasting algorithms and how to tune analytical parameters, refer to the *Oracle Retail AI Foundation Cloud Service User Guide*.

To build the Forecast Setup workspace, perform these steps:

1. From the left sidebar menu, click the Task Module to view the available tasks.

Figure 4-1 Task Module



- 2. Click the **IPO Administration** activity and then click **Demand Forecast** to access the available workspaces.
- 3. Click Setup Weekly Forecast. The wizard opens.

You can open an existing workspace, but to create a new workspace, click ${\bf Create}$ ${\bf New Workspace}.$

Figure 4-2 Weekly Forecast Wizard




4. Enter a name for your new workspace in the label text box and click **OK**.

Figure 4-3 Enter Workspace Label



5. The Workspace wizard opens. Select the products you want to work with and click **Next**.

Figure 4-4 Workspace Wizard: Select Products



6. Select the locations you want to work with and click **Finish**.


Figure 4-5 Workspace Wizard: Select Locations

Select Locations Levels & Positions Label Company □ Level ■ Label 11 Southeastern US Company 12 Northeastern US Chain 13 Midwest US \sim 14 Northcentral US 15 Southwestern US District 31 Eastern Canada □ Store 32 Canadian Lakes 33 Western Canada

7. The wizard notifies you that your workspace is being prepared. Successful workspaces are available from the Dashboard.



Figure 4-6 Successful Workspace Build



The Forecast Setup workspace is built. This workspace contains these steps:

- General Step
- Exception Management Step

General Step


The available views are:

- Basic Parameters View
- Advanced Parameters View
- Intermediate Level View
- Final Level View

Basic Parameters View

The Basic Parameters view allows you to view and set high level information. For instance, you can set the approval policy or determine the time frame for which forecast is required.

Figure 4-7 Basic Parameters View



Measures: Basic Parameters View

The Basic Parameters view contains the following measures.



Forecast Start Date

This is the starting date of the forecast. If no value is specified at the time of forecast generation, the system uses the data/time at which the batch is executed as the default value. If a value is specified in this field and it is used to successfully generate the batch forecast, this value is cleared.

Forecast Length

The Forecast Length is used with the Forecast Start Date to determine forecast horizon. The forecast length is based on the calendar dimension of the final-level. For example, if the forecast length is to be 10 weeks, the setting for a final-level at day is 70 (10 x 7 days).

Approval Method

This field is a list from which you select the default automatic approval policy for forecast items. Valid values are:

Manual

The system-generated forecast is not automatically approved. Forecast values must be manually approved by accessing and amending the Forecast Review view

Auto

The system-generated quantity is automatically approved as is.

By Alert


This list of values may also include any Forecast Approval alerts that have been configured for use in the forecast approval process. Alerts are configured during the implementation and can be enabled to be used for Forecast Approval in the Enable Alert for Forecast Approval view. Refer to the *Oracle Retail Predictive Application Server Configuration Tools User Guide* for more information on alerts. The Alert Parameters view contains a list and descriptions of available alerts, and for which level (causal/baseline) that they are designed for.

Advanced Parameters View

The Advanced Parameters view allows you to set default values for parameters that are less frequently accessed, such as History length or measures affecting cumulative interval calculations.



Figure 4-8 Advanced Parameters View



Measures: Advanced Parameters View

The Advanced Parameters view contains the following measures.

Updating Last Week Forecast

This field is a list from which you can select the method for updating the Approved Forecast for the last specified number of weeks of the forecast horizon. This option is valid only if the Approval Method Override is set to Manual or Approve by alert, and the alert was rejected. The choices are:

No Change

When using this method, the last week in the forecast horizon does not have an Approved Forecast value. The number of weeks is determined number of weeks elapsed between the forecast start date and the last approval date.

Replicate

When using this method the last weeks in the forecast horizon are forecast using the Approved Forecast for the week corresponding to the last approval date.

Use Forecast

When using this method, the System Forecast for the last weeks in the forecast horizon is approved.

Interval Lower Ratio

The value entered in this field multiplied by the forecast represents the lower bound of the confidence interval for a given period in the forecast horizon.

Interval Upper Ratio

The value entered in this filed multiplied by the forecast represents the upper bound of the confidence interval for a given period in the forecast horizon.

Adjust Forecast Method

This measure allows you to choose how to automatically adjust the system generated forecast. The options are:



No Adjustment

No adjustment is made to the system generated forecast

Keep Last Change

If any adjustments were done to the forecast in the previous runs, they are reflected in the Adjusted Forecast measure. In this use case, the total forecast is retained.

Keep Last Baseline

If any adjustments were done in the Adjusted Baseline in the previous runs, they are retained. In this use case, the system calculated peaks are applied on the Adjusted Baseline

Keep Last Peak

If any adjustments were done in the Adjusted Peak measure in the previous runs, they are retained. In this use case, the adjusted peaks are applied on the system calculated baseline.

Run Forecast

This field let's you specify if the forecast should be run for this final level. This is useful if multiple final levels are available, and the need is to forecast only a subset of them.

Periods Kept for Approval

This measure lets you specify how many periods before today you want to keep for the approved forecast. For instance if the number you enter is **5**, the approved forecast will be populated for the forecast horizon in the future and for five weeks in the past.

History Prerange Length

This measure lets you control how many calendar positions are showed in the wizard prior to RPAS_TODAY when building the Forecast Review workbook.

The historical positions (before RPAS_TODAY/forecast start date) displayed in the wizard are decided by the number entered here, and the history length used to forecast the level.

If the number displayed here is 10 and the history length is 17, the number of positions before today, are pre-ranged in the wizard to:

```
MAX (History Prerange Length, History Length) = MAX (10, 17) = 17
```

History Length


This measure lets you control how many periods are used by the forecast engine when calculating the base demand.

Intermediate Level View

It allows you to view and set high level information, but below the global settings. For instance, you can select the approval policy or determine the history length used to calculate base demand.



Figure 4-9 Intermediate Level View



Measures: Intermediate Level View

The Intermediate Level view contains the following measures.

Forecast Length at Intermediate

The Forecast Length is used with the Forecast Start Date to determine forecast horizon. The forecast length is based on the calendar dimension of the final-level. For example, if the forecast length is to be 10 weeks, the setting for a final-level at day is $70 (10 \times 7 \text{ days})$.

If the final level is at day, and the forecast length override is specified, it can happen that the week level forecast is generated for an additional week in the future. However, when spread to day, the forecast length is respected.

The previous circumstance covers for the following case. The forecast is generated on a Tuesday, and the forecast length override 14. If a week is starting Monday, the forecast generated at week level is going to be three weeks long. However, it is going to be spread to day for only the desired 14 days.

Approve Method at Intermediate

This field is a list from which you select the default automatic approval policy for forecast items. Valid values are:

Manual

The system-generated forecast is not automatically approved. Forecast values must be manually approved by accessing and amending the Forecast Review view.

Automatic

The system-generated quantity is automatically approved as is.

By Alert

This list of values may also include any Forecast Approval alerts that have been configured for use in the forecast approval process. Alerts are configured during



the implementation and can be enabled to be used for Forecast Approval in the Enable Alert for Forecast Approval view. Refer to the *Oracle Retail Predictive Application Server Configuration Tools User Guide* for more information on alerts. The Alert Parameters view contains a list and descriptions of available alerts, and for which level (causal/baseline) that they are designed for.

Adjust Forecast Method at Intermediate

This measure allows you to automatically adjust the system generated forecast.

The options are:

No Adjustment

No adjustment is made to the system generated forecast

Keep Last Change

If any adjustments were done to the forecast in the previous runs, they are reflected in the Adjusted Forecast measure. In this use case, the total forecast is retained.

Keep Last Baseline

If any adjustments were done in the Adjusted Baseline in the previous runs, they are retained. In this use case, the system calculated peaks are applied on the Adjusted Baseline

Keep Last Peak

If any adjustments were done in the Adjusted Peak measure in the previous runs, they are retained. In this use case, the adjusted peaks are applied on the system calculated baseline.

History Length at Intermediate


This is the override of the History Length in Basic Parameters.

Final Level View

The Final Level view allows you to override some default measures, such as forecast start and end dates, or override the approval policy.



Figure 4-10 Final Level View



Measures: Final Level View

The Final Level view contains the following measures.

Forecast Start Date at Final

This is the override of the Forecast Start Date in Basic Parameters.

If the final level is at day, and the forecast length override is specified, it can happen that the week level forecast is generated for an additional week in the future. However, when spread to day, the forecast length is respected.

The previous circumstance covers for the following case. The forecast is generated on a Tuesday, and the forecast length override 14. If a week is starting Monday, the forecast generated at week level is going to be three weeks long. However, it is going to be spread to day for only the desired 14 days.

Forecast End Date at Final

This is the override of the Forecast End Date in Basic Parameters.

Approval Method at Final

Set only at the final-level, the Approval Method at Final is a list from which you select the approval policy for individual product/location combinations. The options are:

No Override

The default approval policy is used

Manual

The system-generated forecast is not automatically approved. Forecast values must be manually approved by accessing and amending the Forecast Review view



Auto

The system-generated quantity is automatically approved as is.

By Alert

This list of values may also include any Forecast Approval alerts that have been configured for use in the forecast approval process. Alerts are configured during the implementation and can be enabled to be used for Forecast Approval in the Enable Alert for Forecast Approval view. Refer to the *Oracle Retail Predictive Application Server Configuration Tools User Guide* for more information on alerts. The Alert Parameters view contains a list and descriptions of available alerts, and for which level (causal/baseline) that they are designed for.

Adjust Forecast Method at Final

This is the override of the Adjust Forecast Method in Advanced Parameters .

History Length at Final

This is the override of the History Length in Basic Parameters.

Assortment Start Date

If the Lifecycle Allocation and Replenishment solution is implemented, this measure displays the Assortment Start Date from the solution. This date can serve as the Forecast Start Date for the item/store combination.

Assortment End Date

If the Lifecycle Allocation and Replenishment solution is implemented, this measure displays the Assortment End Date from the solution. This date can serve as the Forecast End Date for the item/store combination. Note that the actual end date is given by the Assortment End Date or the end of the forecast horizon, whichever comes first.

Exception Management Step

The available views are:


- Basic Parameters View
- Intermediate Level View
- Final Level View

Basic Parameters View

The Basic Parameters view allows you to view and edit threshold for approval exceptions.



Figure 4-11 Basic Parameters View



Measures: Basic Parameters View

The Basic Parameters view contains the following measures.

Alert - Calculation Periods

The number stored in this field defines the number of calculations periods used in generating exceptions.

Alert - Error Threshold

This field stores the value that determines if a forecast error is acceptable, or if it needs to be flagged as exception.

Alert - Average Sales Threshold

Threshold used in deciding if average sales are high or low, depending on how they compare against the value.

Alert - Causal Peak Factor

This measure is relevant for promotional forecasting. The current forecast values are divided by the maximum historical demand. If the result is larger than the value of this measure, the forecast may be too large and an exception is triggered

Recent Sales Window

This field determines the time frame over which recent sales are considered in the exception calculations.

Current Period Window

This field stores the number of periods, going back from today, used to calculate various key metrics, such as service level or number of out-of-stock units. This is meant to be for the current periods, so the value should be something reflecting the



current state. For instance the current service level could be calculated for the past week, so four or five periods

Historic Period Window

This field stores the number of periods, going back from today, used to calculate various key metrics, such as service level or number of out-of-stock units. This is meant to be for the historic level, so the value should be something reflecting a longer past period. For instance the current service level could be calculated for the past year or half year, so twenty six or fifty two periods.

Intermediate Level View

The Intermediate Level view allows you to view and edit threshold for approval exceptions at a level lower than in the Basic Parameters view. A typical level is subclass/region.

2. Intermediate Level Product Location \Box & 品 Measure (Default) 0 **Great Lakes Region** Ground Instant Product Measure Alert - Calculation Periods at Intermediate Alert - Error Threshold at Intermediate Alert - Average Sales Threshold at Intermediate Recent Sales Window at Intermediate Current Period Window at Intermediate Historic Period Window at Intermediate Alert - Causal Peak Factor at Intermediate

Figure 4-12 Intermediate Level View

Measures: Intermediate Level View

The Intermediate Level View contains the following measures.

Alert - Calculation Periods at Intermediate

The number stored in this field defines the number of calculations periods used in generating exceptions.

Alert - Error Threshold at Intermediate

This field stores the value that determines if a forecast error is acceptable, or if it needs to be flagged as exception.

Alert - Average Sales Threshold at Intermediate



Threshold used in deciding if average sales are high or low, depending on how they compare against the value.

Recent Sales Window at Intermediate

This field determines the time frame over which recent sales are considered in the exception calculations.

Current Period Window at Intermediate

This field stores the number of periods, going back from today, used to calculate the service level. This is meant to be for the current level, so the value should be something reflecting the current state. For instance the current service level could be calculated for the past week, so four or five periods.

Historic Period Window at Intermediate

This field stores the number of periods, going back from today, used to calculate the service level. This is meant to be for the historic level, so the value should be something reflecting a longer past period. For instance the current service level could be calculated for the past year or half year, so twenty six or fifty two periods.

Alert - Causal Peak Factor at Intermediate


This measure is relevant for promotional forecasting. The current forecast values are divided by the maximum historical demand. If the result is larger than the value of this measure, the forecast may be too large and an exception is triggered.

Final Level View

The Final Level view allows you to view and edit threshold for approval exceptions at a levels typically lower than in both the Basic Parameters as well as Intermediate Level views. The intersection may be as low as item/store.



Figure 4-13 Final Level View





Forecast Review Task

This chapter describes the Forecast Review for IPOCS-Demand Forecasting.

Forecast Review Workspaces, Steps, and Views

The following table lists the workspaces, steps, and views for the Forecast Review task.

Table 5-1 Forecast Review Workspaces, Steps, and Views

Workspace	Step	Views
Forecast Review Workspace	Approve Step	Forecast Results View
		Approve Information View
		Forecast Results Chart View
		What-if Parameters View
		Preprocessing Details View


Forecast Review Workspace

The Forecast Review workspace allows you access to all of the views listed in Forecast Review Workspaces, Steps, and Views.

To build the Forecast Review workspace, perform these steps:

1. From the left sidebar menu, click the Task Module to view the available tasks.


Figure 5-1 Task Module



- 2. Click the **Review and Approve** activity to access the available workspaces.
- 3. Click **Demand Weekly Forecast**. The wizard opens.

You can open an existing workspace, but to create a new workspace, click **Create New Workspace**.

Figure 5-2 Weekly Forecast



4. Enter a name for your new workspace in the label text box and click **OK**.


Figure 5-3 Enter Workspace Label



5. The Workspace wizard opens. Select the products you want to work with and click **Next**.

Figure 5-4 Workspace Wizard: Select Products


Select Products



6. The Workspace wizard opens. Select the locations you want to work with and click **Next**.

Figure 5-5 Workspace Wizard: Select Locations


Select Locations



7. Select the time periods you want to work with and click Finish.

Figure 5-6 Workspace Wizard: Select Available Calendar Positions


Select Calendar





8. The wizard notifies you that your workspace is being prepared. Successful workspaces are available from the Dashboard.

Figure 5-7 Successful Workspace Build



Approve Step

The available views are:

- Forecast Results View
- Approve Information View
- Forecast Results Chart View
- What-if Parameters View
- · Preprocessing Details View

Forecast Results View

The Forecast Results view shows all information related to forecast generation. It shows the forecast with its components, baseline and promotional peaks. It also shows sales of last year, and cumulative interval information.


The navigation of this worksheet is very conveniently driven by real time or workbook alerts.



There is a duplicate of this view - Forecast Results Chart View- that is intended to show the information in chart form.

If not already in chart mode, you need to change the view type from pivot table to chart and save the format. This is a one-time action.

Figure 5-8 Forecast Results View



Measures: Forecast Results View

The Forecast Results view contains the following measures.

Adjusted Forecast

This is a read-only measures that equals the adjusted baseline plus the adjusted peaks.

Adjusted Baseline

The value in this field initially defaults to the System Baseline if the forecast is automatically approved by the system or through a Forecast Approval Alert. Otherwise, the value in the Adjusted Baseline is different than the System Baseline if:

- Adjusted Baseline has been updated by you.
- Keep Last Changes is selected.
- Update Last Weeks Forecast is set to Replicate.



- Changes to the Adjusted Baseline are automatically approved. The Approval view updates with the date of the adjustment and the name of the user who made the adjustment.
- Demand transference is selected as the adjustment method in forecast setup and significant demand transference effects are available.

Approved Forecast

The Approved Forecast is the forecast quantity that was approved at the time of the task build. The values contained in this measure are read-only. If changes are made to the Adjusted Forecast, then click Calculate to show the new value in the Approved Forecast.

Approved System Forecast

The Approved System Forecast is populated with the last System Forecast approved for a time series:

- 1. Approval Method set to Automatic Approval
- 2. Approval Method set to a Forecast Approval Alert and the alert is not triggered
- 3. Update Last Weeks Forecast is set to Use Forecast

Preprocessed Sales

This read-only measure is the demand data used to generate the forecast. This allows you to compare Actuals to forecast values. The preprocessed sales are based on the historical sales which are undergoing several rounds corrections.

Last Year Sales

Event

This measure displays at the item, location, and week level if one or more offers were active. This usually goes together with the Discount measure.

Discount

This is the discount from the full price for which a product was sold at a given location for a given time period.

Last Last Year Sales

System Forecast

This is a read-only measures that equals the system baseline plus the system peaks.

System Baseline

The System Baseline displays the system generated baseline forecast. The values contained in this field are read-only. The system baseline incorporates level, trend, seasonality, but no causal-related information.

What-if Baseline

In the What-if Parameters view you can change some forecast parameters and see how they impact the forecast. The resulting forecast is stored in this measure. If you like the change, you can run the Copy What-if custom menu, and the forecast is copied in the Adjusted Forecast measure

Adjusted Cumint



Cumulative Intervals are used in safety stock calculation within allocation and replenishment systems. Its value is similar to a running total of a percentage of the actual forecast and is read-only.

Approved Cumint

Cumulative Intervals are used in safety stock calculation within allocation and replenishment systems. Its value is similar to a running total of a percentage of the actual forecast and is read-only.

Error Metrics

To assist the forecast analyst in deciding which forecasts to review, there are several error metrics that can be reviewed.

When the accuracy is good with only a small error, the analyst may decide to move on and review other forecasts. When an item performs poorly, the analyst may want to spend some time to adjust the forecast values.

The error metrics are:

- Weighted Absolute Percentage Error
- Mean Absolute Error
- Root Mean Squared Error
- Forecast Bias

Figure 5-9 shows the error metrics calculations. Note that they are calculated for each time period

Figure 5-9 Error Metrics Calculations

Weighted Absolute Percentage Error
$$WAPE = \frac{1}{n} \frac{\sum_{today-1}^{today-n} |F_t - A_t|}{\sum_{today-1}^{today-n} A_t}$$
 Mean Absolute Error
$$MAE = \frac{1}{n} \sum_{today-1}^{today-n} |F_t - A_t|$$
 Root Mean Squared Error
$$RMSE = \sqrt{\frac{\sum_{today-1}^{today-n} (F_t - A_t)^2}{n}}$$
 Forecast Bias
$$BIAS = \frac{1}{n} \sum_{today-1}^{today-n} (F_t - A_t)$$

Approve Information View

The Approve Information view shows information around the approval process, like which user approved the forecast, when it was approved and potential notes.

2. Approve Information All Dimensions B \Box Measure (Default) 1234773 -Measure Approve By system Approval Comment refused by frairt01 Violated Exceptions Forecast vs Recent Approval Date 03/31/2019 Approve Active Forecast Items LLC Indicator Mean Absolute Error 210.00 Root Mean Squared Error 246.39 Weighted Absolute Percentage Error 20.00% Forecast Bias -210.00

Figure 5-10 Approve Information View

Measures: Approve Information View

The Approve Information view contains the following measures.

Adjust Forecast Method

This measure displays the adjustment method used to programmatically adjust the system forecast. The options are:

No Adjustment

No adjustment is made to the system generated forecast

Keep Last Change

If any adjustments were done to the forecast in the previous runs, they are reflected in the Adjusted Forecast measure. In this use case, the total forecast is retained.

Keep Last Baseline

If any adjustments were done in the Adjusted Baseline in the previous runs, they are retained. In this use case, the system calculated peaks are applied on the Adjusted Baseline

Keep Last Peak



If any adjustments were done in the Adjusted Peak measure in the previous runs, they are retained. In this use case, the adjusted peaks are applied on the system calculated baseline.

Approve By

Approved By is a read-only field that displays the name of the user to approve forecasts for an item/location. This field may be populated with **Sys** if the system was set to automatically approve forecasts during the batch forecast process.

Approval Comment

Approval Comment is a field in which notes may be entered regarding the forecast values or any pertinent information for specified product/location combinations.

Violated Exceptions

This field displays which (if at all) approval exception business rule was violated.

Approval Date

Approval Date is a read-only field that displays the date that the forecast quantity is approved either automatically during the batch forecast process or when changes are made to the Adjusted Forecast. This information is necessary for IPOCS-Demand Forecasting to carry out any subsequent processes, such as replenishment procedures.

Approve

This field may be selected if you want to accept the System Forecast quantity for a time series that has yet to be approved. The flag is also activated when a change is made to the Adjusted Forecast and Calculate occurs. When this flag is activated, the time series for an item/location are approved and both the Approval Date and Approved By fields are updated.

Active Forecast Items

This field indicates if an item/store qualifies to have a forecast generated.

Error Metrics

To assist the forecast analyst in deciding which forecasts to review, there are several error metrics that can be reviewed.

When the accuracy is good with only a small error, the analyst may decide to move on and review other forecasts. When an item performs poorly, the analyst may want to spend some time to adjust the forecast values.

The error metrics are:

- Weighted Absolute Percentage Error
- Mean Absolute Error
- Root Mean Squared Error
- Forecast Bias

Figure 5-11 shows the error metrics calculations. The errors are calculated using total adjusted sales (preprocessed) and approved forecast values in history. The time periods used in the calculation are given by the Error Calculation Window measure in the Forecast Setup workspace.



Figure 5-11 Error Metrics Calculations

Weighted Absolute Percentage Error
$$WAPE = \frac{1}{n} \frac{\sum_{today-1}^{today-1} |F_t - A_t|}{\sum_{today-1}^{today-n} A_t}$$
 Mean Absolute Error
$$MAE = \frac{1}{n} \sum_{today-1}^{today-n} |F_t - A_t|$$
 Root Mean Squared Error
$$RMSE = \sqrt{\frac{\sum_{today-1}^{today-n} (F_t - A_t)^2}{n}}$$
 Forecast Bias
$$BIAS = \frac{1}{n} \sum_{today-1}^{today-n} (F_t - A_t)$$

Forecast Results Chart View

The Forecast Results view shows all information related to forecast generation. It shows the forecast with its components, baseline and promotional peaks. It also shows sales of last year, and cumulative interval information.

The navigation of this worksheet is very conveniently driven by real time or workbook alerts.



There is a duplicate of this view - Forecast Results View- that is intended to show the information in table form.

If not already in chart mode, you need to change the view type from pivot table to chart and save the format. This is a one-time action.




Figure 5-12 Forecast Results Chart View

Measures: Forecast Results Chart View

The Forecast Results Chart view contains the following measures.

Adjusted Forecast

This is a read-only measures that equals the adjusted baseline plus the adjusted peaks.

Adjusted Baseline

The value in this field initially defaults to the System Baseline if the forecast is automatically approved by the system or through a Forecast Approval Alert. Otherwise, the value in the Adjusted Baseline is different than the System Baseline if:

- Adjusted Baseline has been updated by you.
- Keep Last Changes is selected.
- Update Last Weeks Forecast is set to Replicate.
- Changes to the Adjusted Baseline are automatically approved. The Approval view updates with the date of the adjustment and the name of the user who made the adjustment.
- Demand transference is selected as the adjustment method in forecast setup and significant demand transference effects are available.

Approved Forecast

The Approved Forecast is the forecast quantity that was approved at the time of the task build. The values contained in this measure are read-only. If changes are made to the Adjusted Forecast, then click Calculate to show the new value in the Approved Forecast.

Approved System Forecast

The Approved System Forecast is populated with the last System Forecast approved for a time series:



- 1. Approval Method set to Automatic Approval
- 2. Approval Method set to a Forecast Approval Alert and the alert is not triggered
- Update Last Weeks Forecast is set to Use Forecast

Preprocessed Sales

This read-only measure is the demand data used to generate the forecast. This allows you to compare Actuals to forecast values. The preprocessed sales are based on the historical sales which are undergoing several rounds corrections.

Last Year Sales

Event

This measure displays at the item, location, and week level if one or more offers were active. This usually goes together with the Discount measure.

Discount

This is the discount from the full price for which a product was sold at a given location for a given time period.

Last Last Year Sales

System Forecast

This is a read-only measures that equals the system baseline plus the system peaks.

System Baseline

The System Baseline displays the system generated baseline forecast. The values contained in this field are read-only. The system baseline incorporates level, trend, seasonality, but no causal-related information.

What-if Baseline

In the What-if Parameters view you can change some forecast parameters and see how they impact the forecast. The resulting forecast is stored in this measure. If you like the change, you can run the Copy What-if custom menu, and the forecast is copied in the Adjusted Forecast measure

Adjusted Cumint

Cumulative Intervals are used in safety stock calculation within allocation and replenishment systems. Its value is similar to a running total of a percentage of the actual forecast and is read-only.

Approved Cumint

Cumulative Intervals are used in safety stock calculation within allocation and replenishment systems. Its value is similar to a running total of a percentage of the actual forecast and is read-only.

What-if Parameters View

The What-if Parameters view allows you to adjust some forecast parameters and immediately view the effects on the forecast in the Forecast Results view.


If you like the new adjusted forecast, you first have to Approve the forecast to get the forecast in the approved forecast measure. Next you have to Commit to update the



database with the approved forecast as well as with the What-if forecast parameters settings. These parameters are used the next time the forecast batch is run.

Parameters that can be adjusted will affect base demand as well as total forecast.

Figure 5-13 What-if Parameters View



Measures: What-if Parameters View

The What-if Parameters view contains the following measures.

What-if Forecast Start Date

This measure lets you specify a different forecast start date then the default used in batch, which is RPAS_TODAY.

What-if Forecast Length

This measure lets you specify a forecast length, which is likely not the default forecast end date less forecast start date used in batch. The value used will be reflected in the Forecast End Date measure.

What-if Forecast End Date

This measure displays the date based on the entries in the Forecast Start Date and Forecast Length. Forecast End Date = Forecast Start Date + Forecast Length.

What-if History Length

This measure lets you specify the number of periods used to calculate the base demand.

What-if



This Boolean measures specifies if the user can perform what-if. If it is unchecked, no what-if is triggered. To perform what-if you need to select at least one of the following measures:

- What-if Forecast Length
- What-if Forecast Start Date
- · What-if History Length

If the What-if flag is on, you can run it by clicking on the What-if custom menu.

What-if Base Demand

This measure displays the value for the base demand based on the new history length.

What-if Forecast Length Requested

This measure displays the requested forecast length. This is useful, because after running the What-if custom menu, the What-if Forecast Length measure will be blanked out. It is this measure where you keep track of the latest forecast length used.

What-if Forecast Start Date Requested

This measure displays the requested forecast start date. This is useful, because after running the What-if custom menu, the What-if Forecast Start Date measure will be blanked out. It is this measure where you keep track of the latest forecast stare date used.

What-if History Length Requested

This measure displays the requested history length. This is useful, because after running the What-if custom menu, the What-if History Length measure will be blanked out. It is this measure where you keep track of the latest history length used.

Copy to Adjusted

After you finish adjusting the parameters, you can either return to reviewing the forecast or you can apply the changes. Enable this measure by selecting the Boolean measure value to true.

Preprocessing Details View

The Preprocessing Details view shows all necessary information to determine how the loaded sales were transformed into unconstrained demand. You can review the numbers after each step, and also have the possibility to override the total demand. Unconstrained demand is what an item would have sold at a location without the influence of any outside factor. These factors can include:

- Out of stock situations where an item would have likely sold more
- Outliers like fatty fingers or Software bugs
- Promotions that can boost sales
- Weather that can boost or lower sales. Examples include hurricanes for water bottles, or rain for barbecue items.

For details on how the corrections are made refer to the *Oracle Retail Al Foundation Cloud Service User Guide*.



5. Preprocessing Details Calendar 8 0 **All Dimensions** Location 8 0 Product & 1 Measure (Default) 0 > 1234768 - PL - 100% Columbian Non-Flavored 1006 Chicago 2/23/2019 Calendar 2/9/2019 2/16/2019 3/2/2019 3/9/2019 1 Measure Depromote Adjustment 0.00 0.00 0.00 0.00 0.00 0.00 0.00 0.00 0.00 0.00 Outage Adjustment 0.00 0.00 0.00 0.00 Outlier Adjustment 0.00 Outage Indicator \checkmark Promotion Indicaor 212.00 225.00 192.00 180.00 Baseline Sales 156.00 Historical Discount 0.00 0.00 0.00 0.00 0.00 Historical Event Outlier Indicator 212.00 225.00 180.00 Raw Sales 192.00 156.00 212.00 225.00 192.00 156.00 180.00 Preprocessed Sales

-1.00

-1.00

-1.00

-1.00

Figure 5-14 Preprocessing Details View

Measures: Preprocessing Details View

The Preprocessing Details view contains the following measures.

-1.00

Depromote Adjustment

User Override

This measure displays the units that were removed from the historical sales, because they were caused by the lift in demand due to one or more offers.

Outage Adjustment

This measure displays the units that were added to the historical sales, because they were caused by the artificial drop in demand due to stockouts.

Outlier Adjustment

This measure displays the units that were added to the historical sales, because they were caused by the artificial drop in demand due unusual events, like human error, or extreme bottle water sales during a hurricane.

Outage Indicator

This measure is either loaded or calculated by the rules in the custom menu. It is used during the pre-processing run that corrects sales for lost sales.

Promotion Indicator

This measure is usually calculated as the *OR* of all available offers that are active for a product/location/calendar combination. It is used during the preprocessing run that removes promotional sales.

Baseline Sales



This measure represents the demand that was sold at a location without the influence of any outside factor.

Historical Discount

This measure displays the units that were removed from the historical sales, because they were caused by the lift in demand due to one or more offers.

When the Historical Discount or Historical Event measures are not blank, it is likely that the Promotion Indicator is On, and the Depromote Adjustment will also have a non-zero value.

Historical Event

When the Historical Discount or Historical Event measures are not blank, it is likely that the Promotion Indicator is On, and the Depromote Adjustment will also have a non-zero value.

Outlier Indicator

This measure is either loaded or calculated by the rules in the custom menu. It is used during the pre-processing run that corrects the sales for outliers.

Raw Sales

This measure is loaded and it represents the historical sales at a product/location/calendar period level. It is different from demand because it may be constrained by stockouts, outliers, weather, and so on.

Preprocessed Sales

This measure represents the demand – including promotion and offer data that was sold at a product/location/calendar. If configured properly, the stockout and outliers impact is removed.

User Override

After reviewing all the above measures, this is the place to override the demand at the product/location/calendar level. This can be useful for special cases (introduction of key items) as well as extreme situations when entire departments were hurt by natural events, like a pandemic.



6

IPOCS-Demand Forecasting Administration Task

This chapter describes the IPOCS-Demand Forecasting batch flow management for IPOCS-Demand Forecasting.

Batch Flow Administration Workspace, Step, and View

The following table lists the workspace, step, and view for the IPOCS-Demand Forecasting Administration task.

Table 6-1 Batch Flow Administration Workspace, Step, and View

Workspace	Step	View
Batch Flow Administration Workspace	Batch Flow Control Step	Batch Flow Management View


Batch Flow Administration Workspace

The Batch Flow Administration workspace allows you access to all of the views listed in Batch Flow Administration Workspace, Step, and View.

To build the Batch Flow Administration workspace, perform these steps:

1. From the left sidebar menu, click the Task Module to view the available tasks.

Figure 6-1 Task Module



2. Click the IPO Administration activity and then click Batch Flow Administration.

This workbook does not have a wizard. A workbook is being prepared. Successful workspaces are available from the Dashboard.

The Batch Flow Administration workspace is built. This workspace contains this step: Batch Flow Control Step.

Batch Flow Control Step

This step includes the Batch Flow Control View.

Batch Flow Control View

This view contains measures that control what steps should be run doing batch. It is information that is passed to the Oracle Administration Task (OAT) within IPOCS. For instance, if in the OAT you select to run forecast, by default the task runs forecast for all available final levels. However, if in the Batch Flow Management you enable Run Forecast 01, and disable Run Forecast for other levels - like 03, the OAT will only run forecast for final level 01

The reason why some steps may be skipped has to do with the tuning of the system during the implementation. If one step is fine-tuned, for instance selecting the forecast strategy for new items, for the sake of saving time, the implementer may want to skip non-relevant steps, like running forecast for established items.



 Batch Flow Management \Box Measure (Default) -Measure Run Newltem Batch ~ Import Inventory Data Replenish Warehouse ~ Import Assortment Period from AP Import Initial Allocation from Export Purchase Orders and Transfers To RMS Get Purchase Order Numbers from RMS Get Transfer Order Numbers from RMS Recalculate Sales Start Index

Figure 6-2 Batch Flow Control View

Measures: Batch Flow Control

Calculate Total Sales from Pos

Run Forecast 01

Include New Item

Eligibility 01

Dates

Recommendation 01

Enable GA Business Rules

Copy Assortment Start/End

The Batch Flow Control view contains the following measures.

Export Purchase Order and Transfers to RMS

If selected, proposed Purchase Orders and Transfers are sent to RMS using web-service calls.

~

~

~

~

Get Purchase Order Numbers from RMS



If selected, Purchase Order Numbers are retrieved from RMS using web-service calls.

Get Transfer Order Numbers from RMS

If selected, Transfer Order Numbers are retrieved from RMS using web-service calls.

Run New Item Batch

If selected, this step calculates the New Item setup. For example, similarities, New Item recommendations, and so on.

Run Forecast

If selected, the forecast for the selected final levels is generated.

Include New Item Recommendation

If selected, the forecast for New Items is generated.

Include New Item Eligibility

Enable GA Business Rules Eligibility

If selected, this makes sure that only forecastable items are handled by the business rule engine in the approval process. If deselected, the approval rules set up in the business rule engine become invalid. However, you can write custom rules to decide what items should go through the approval process. For instance a rule can be; *Any item with average sales of less than 1 unit per month is automatically approved*. The result of the rule should be stored in the Eligible MASK per Rule Group measure. The measure name is: rulgeligmask_CF. For additional details, refer to the *Oracle Retail Inventory Planning Optimization Cloud Service-Demand Forecasting/ Inventory Planning Optimization Cloud Service-Lifecycle Allocation and Replenishment Implementation Guide*.

Primary App to Load Common Data

This measure indicates which application's batch job should load the common hierarchies like Product, Location and Calendar.



7

Business Rule Engine

This chapter describes the tasks that comprise the Business Rule Engine for IPOCS-Demand Forecasting, including:

- Attributes Task
- Business Rule Group Admin Task
- Business Rule Setup Task

Attributes Task

This section describes the Attributes task for IPOCS-Demand Forecasting.

Attributes Workspaces, Steps, and Views

The following table lists the workspaces, steps, and views for the Attributes task.

Table 7-1 Attributes Workspaces, Steps, and Views

Workspace	Step	Views
Attributes Workspace	Review Step	Location Attributes View
		Product Attributes View
		Product/Location Attributes View

Attributes Workspace

The Attributes workspace allows you access to all of the views listed in Attributes Workspaces, Steps, and Views.

The Attributes workspace allows you to review attributes that you can use in rules using the Business Rule engine. The attributes can be product specific, like brand or class. They can also be location specific, like store format, or number of stores an item is sold in. Finally, they can be product/location specific, like average sales, or the vendor from where the products were sourced for a specific store.

The attribute data types are:

- String examples are brand, region
- Date examples are store open date, forecast end date
- Numeric examples are historical average sales, coefficient of variance


The sources of the attribute information can come from various source. They can be loaded or calculated. IPOCS-Demand Forecasting GA has a set of calculated attributes that can be easily expanded to including any retailer-relevant attributes. For additional technical information on how the attributes are managed, refer to the *Oracle Retail Inventory Planning*

Optimization Cloud Service-Demand Forecasting / Inventory Planning Optimization Cloud Service-Lifecycle Allocation and Replenishment Implementation Guide.

To build the Attributes workspace, perform these steps:

1. From the left sidebar menu, click the Task Module to view the available tasks.

Figure 7-1 Task Module




- 2. Click the **IPO Administration** activity and then click **Attributes Review** to access the available workspaces.
- 3. Click Weekly Forecast. The wizard opens.

You can open an existing workspace, but to create a new workspace, click **Create New Workspace**.




Figure 7-2 Weekly Forecast Wizard



4. Enter a name for your new workspace in the label text box and click **OK**.

Figure 7-3 Enter Workspace Label



5. The Workspace wizard opens. Select the locations you want to work with and click **Next**.

Figure 7-4 Workspace Wizard: Select Locations

Select Locations Levels & Positions Company Label Level 11 Southeastern US Company 12 Northeastern US Chain Area 13 Midwest US 14 Northcentral US Region 15 Southwestern US District Store 31 Eastern Canada 32 Canadian Lakes 33 Western Canada




6. Select the products you want to work with and click Finish.

Figure 7-5 Workspace Wizard: Select Products



7. The wizard notifies you that your workspace is being prepared. Successful workspaces are available from the Dashboard.

Figure 7-6 Successful Workspace Build



The Attributes workspace is built. This workspace contains this step:

Review Step

Review Step


The available views are:

- Location Attributes View
- Product Attributes View
- Product/Location Attributes View

Location Attributes View

The Location Attributes View view allows you to review attributes and their values that are location specific.

Figure 7-7 Location Attributes View



Measures: Location Attributes View

The Location Attributes View view contains the following measures.

Location Based Attribute String

This measure displays location based attributes that have a string value, such as region, or store format.

Location Based Attribute Number

This measure displays location based attributes that have a numeric value, such as number of products carried in a location, or average sales per store.

Location Based Attribute Date


This measure displays location based attributes that have a date value, such as a store open date.

Product Attributes View

The Product Attributes view allows you to review attributes and their values that are product specific.



Figure 7-8 Product Attributes View



Measures: Product Attributes View

The Product Attributes view contains the following measures.

Product Based Attribute String

This measure displays product based attributes that have a string value, such as brand, or class.

Product Based Attribute Number

This measure displays product based attributes that have a numeric value, such as number of locations carrying an item, or average sales per item.


Product Based Attribute Date

This measure displays product based attributes that have a date value, such as item start date.

Enable Prod/Loc View

The Enable Prod/Loc view allows you to enable at the product/location levels.

Figure 7-9 Enable Prod/Loc View





Measures: Enable Prod/Loc View

The Enable Prod/Loc view contains the following measure.

Product-Location Attribute Mask

This measure allows you to select product and locations that have relevant attributes. The attributes are displayed and can be edited in the next two steps.

Business Rule Group Admin Task

This section describes the Business Rule Group Admin task for IPOCS-Demand Forecasting.

Business Rule Group Admin Workspaces, Steps, and Views

The following table lists the workspaces, steps, and views for the Business Rule Group Admin task.

Table 7-2 Business Rule Group Admin Workspaces, Steps, and Views

Workspace	Step	Views
Business Rule Group Admin Workspace		Rule Group Info View Rule Group Active Attribute View
		Rule Group Scope View

Business Rule Group Admin Workspace

The Business Rule Group Admin workspace allows you access to all of the views listed in Business Rule Group Admin Workspaces, Steps, and Views.

The Business Rule Group Admin sets up the framework to efficiently use the Business Rule Engine. Here you can enable or disable Rule Groups, or can assign attributes to certain rule groups. The workspace is not intended to be used by the forecast analyst on a regular basis. It is more for the Administrator of the solution.


The rule groups can have associated certain types of items to them. For instance, Spring fashion items. For these items, you may not want to enable rule groups.

To build the Business Rule Group Admin workspace, perform these steps:

1. From the left sidebar menu, click the Task Module to view the available tasks.




Figure 7-10 Task Module



- 2. Click the **IPO Administration** activity and then click **Demand Forecast** to access the available workspace.
- 3. Click Business Rule Group Admin.
- 4. There is no wizard for this task. Successful workspaces are available from the Dashboard.

Figure 7-11 Successful Workspace Build



The Business Rule Group Admin workspace is built. This workspace contains this step:

Setup Step

Setup Step

The available views are:

- Rule Group Info View
- Rule Group Active Attribute View




Rule Group Scope (Weekly Forecast) View

Rule Group Info View

The Rule Group Info View view allows you to review attributes and their values that are location specific.

Figure 7-12 Rule Group Info View



Measures: Rule Group Info View

The Rule Group Info View view contains the following measures.

Rule Group Type

In this measure you can assign a type to your rule groups. Available options in GA are:

- Approval— assigns business rules to the approval rule groups to decide what product/ locations are approved and which need to be reviewed
- **Navigation** the product/locations that were not approved are assigned to Navigation rule groups and you decide on the priority that they need to be reviewed.
- Custom— Approval and Navigation are very useful in the approval workflow of the solution. However, the scope of the rule groups in the context of the Business Rule Engine can be expanded to many areas.

Rule Group Description

This measure allows you to type a meaningful description for each rule group, depending on its purpose.

Priority Lowerbound

The rules inside a rule group need to have a priority assigned to them in case of conflicts. This measure sets the lower bound for rule priorities.

Priority Upperbound

The rules inside a rule group need to have a priority assigned to them in case of conflicts. This measure sets the upper bound for rule priorities.

Enable Rule Group

This measure allows you to enable rule groups, or disable them if they became out of scope.




Rule Group Active Attribute View

The Rule Group Active Attribute view allows you to enable attributes for rule groups. The number of attributes can be very high and not all attributes are relevant for all types of merchandise. For instance, you have little use of the flavor attribute when it comes to fashion, or *Neckline* when it comes to hard-line merchandise.

Once you know what type of merchandise is associated with every rule group, you can decide what attributes is relevant to each rule group. This makes the workflow around the business rules more efficient and user friendlier.

Figure 7-13 Rule Group Active Attribute View



Measures: Rule Group Active Attribute View

The Rule Group Active Attribute view contains the following measure.

Rule Group Active Attribute


This measure allows you to select the attributes relevant for every rule group.

Rule Group Scope (Weekly Forecast) View

The Rule Group Scope (Weekly Forecast) view allows you to define the scope of a rule group in terms of what product/locations may be associated with it.



Figure 7-14 Rule Group Scope (Weekly Forecast) View



Measures: Rule Group Scope View

The Rule Group Active Attribute view contains the following measure.

Rule Group Scope

In this measure you can assign products and locations to certain rule groups.

Business Rule Setup Task

This section describes the Business Rule Setup for IPOCS-Demand Forecasting.

Business Rule Setup Workspaces, Steps, and Views

The following table lists the workspaces, steps, and views for the Business Rule Setup task.

Table 7-3 Business Rule Setup Workspaces, Steps, and Views

Workspace	Step	Views
Business Rule Setup Weekly	Setup Step	Rule Enable View
Forecast Workspace		Rule Condition Setup View
		Rule Membership View
		Parameters for Approval View
		Parameters for Navigation View

Business Rule Setup Weekly Forecast Workspace


The Business Rule Setup sets up the framework to efficiently use the Business Rule Engine. Here you can enable or disable Rule Groups, or can assign attributes to certain rule groups. The workspace is not intended to be used by the forecast analyst on a regular basis. It is intended for an Administrator for br-engine.fm.

To build the Business Rule Setup workspace, perform these steps:



1. From the left sidebar menu, click the Task Module to view the available tasks.

Figure 7-15 Task Module



- 2. Click the **Business Rule Setup** activity to access the available workspaces.
- 3. Click **Rule Setup**. The wizard opens.

You can open an existing workspace, but to create a new workspace, click **Create New Workspace**.

Figure 7-16 Wizard



4. Enter a name for your new workspace in the label text box and click **OK**.


Figure 7-17 Enter Workspace Label



5. The Workspace wizard opens. Select the Business Rule Group type you want to work with. It is important to click only one of the available options, otherwise you will get a warning and cannot proceed to the next step. Click **Next**.

Figure 7-18 Workspace Wizard: Select Business Rule Group Type






6. Select the Business Rule Groups you want to work with and click **Next**.


Figure 7-19 Workspace Wizard: Select Business Rule Groups

Select Business Rule Group




7. Select the products you want to work with and click **Next**.

Figure 7-20 Workspace Wizard: Select Products




8. Select the locations you want to work with and click **Finish**.

Figure 7-21 Workspace Wizard: Select Locations



9. The wizard notifies you that your workspace is being prepared. Successful workspaces are available from the Dashboard.

Figure 7-22 Successful Workspace Build



The Business Rule Group Admin workspace is built. This workspace contains this step:



Setup Step

Setup Step

The available views are:

- Rule Enable View
- Rule Condition Setup View
- Rule Membership View
- Parameters for Approval View
- Parameters for Navigation View

Rule Enable View

The Rule Enable view allows you to review attributes and their values that are location specific.

Figure 7-23 Rule Enable View



Measures: Rule Enable View

The Rule Enable view contains the following measures.

Enable

In this measure you can enable or disable the rule. Note that although you decide to enable the rule, other factors also need to hold true. For instance the time you want to enable the rule needs to be within the start and end dates.

Priority

The rule conditions used to assign product/locations may result in product/locations been assigned to more than one rule. The rule priority decides which rule takes precedence. A lower number denotes a higher priority.

Start Date

The date when the rule becomes active. Rarely used in IPOCS-Demand Forecasting, but may be very helpful for planning or replenishment solutions.

End Date

The date when the rule stops being active. Rarely used in IPOCS-Demand Forecasting, but may be very helpful for planning or replenishment solutions.



Rule Description

Here you can enter a description for a rule. For instance if a rule condition is to check for high sellers with stable demand, the rule description could be: *High demand / low variability*.

Rule On/Off

This measure displays the status of a rule.

Rule Condition Setup View

The Rule Condition Setup view allows you to assign items to business based on the conditions you specify.

For the purpose of reviewing the forecast, you may want to group together key items as well as high sellers.

Examples of rule conditions can include:

- If an item is a key item and recent sales are larger than 50 items per week, then group together
- Group all coffee items together, except for private label.
- If class is Coffee and brand is not Private Label, then group together.

IPOCS-Demand Forecasting GA has up to four conditions per rule. How to change this, and for more examples and technical details, refer to the *Oracle Retail Inventory Planning Optimization Cloud Service-Demand Forecasting / Inventory Planning Optimization Cloud Service-Lifecycle Allocation and Replenishment Implementation Guide*, as well as the Appendix: Business Rule Engine.

Figure 7-24 Rule Condition Setup View



Measures: Rule Condition Setup View

The Rule Condition Setup view contains the following measures.

Attribute Selected

This measure allows you to select the attribute for the condition. The attributes for the rule are assigned in the Attributes workspace.

Condition Group

Condition groups allow you to refine the criteria that define a rule. Conditions inside the groups are evaluated first. Finally, the rule is the result of the evaluation of all groups that make it up.

Figure 7-25 shows an example of how Condition Orders and Condition Groups are evaluated to create a rule.

The rule is made up of four conditions, which belong to the two groups. The evaluation occurs in the following sequence:



- Condition Group 1 is the result of Condition 1 AND Condition 2
- Condition Group 2 is the result of Condition 3 AND Condition 4
- The Rule is the evaluation of the results of Condition Group 1 AND Condition Group 2

The operator between groups is given by the between Condition of Condition 2, which in this case links the two groups.

Figure 7-25 Example of How Condition Orders and Condition Groups are Evaluated to Create a Rule

Dula	Condition	Condition	Between
Rule	Group	Order	Condition
Condition 1	1	1	AND
Condition 2	1	2	AND
Condition 3	2	3	OR
Condition 4	2	4	

Between Condition AND/OR

If multiple conditions are set up for a rule, this measure allows you to specify if the operator is **AND**, or **OR**.

Condition Operator

This measure compares the attribute value with a condition value.

Table 7-4 Condition Operators

Possible Operators	Descriptions	Example
==	Checks if the attribute value is equal with the Condition Value	brand == Private Label
!=	Checks if the attribute value is different from the Condition Value	average sales != 0
>	Checks if the attribute value is larger than the Condition Value	Average sales >5
>=	Checks if the attribute value is larger or equal to the Condition Value	
<	Checks if the attribute value is less than the Condition Value	Standard deviation of sales <6
<=	Checks if the attribute value is less or equal to the Condition Value	
contain		
not contain		
match		
not match		



Condition Order

The condition order specifies in which sequence to evaluate conditions to create a rule.

Condition Value (string)

This measure is used when the type of the attribute is a string. Example: brand == Private Label

Condition Value (numeric)

This measure is used when the type of the attribute is numeric. Example: average sales > 10

Condition Value (Date)

This measure is used when the type of the attribute is a date. Example: today >= 02/30/2024"

Condition Value (Measure)

This measure is used when you want to refine the condition value. For instance, for coffee items, except Private Label, you want to assign items to the rule that sell more than 50 per week. For Private Label items you may want the value to be 100.

You need to populate your Condition measure with a value of 100 for all Private Label items, and the rest of the coffee items with 100.

Condition Error String

In case an error occurs, this measure displays the reason. For instance, an attribute was of type string, and was compared to a Condition Value of type date.

Total Eligible Items

Total number of items that are brought in the workspace and are eligible to be managed using business rules.

Condition Count

Number of items that are attached to each condition.

Rule Count

Number of items that are filtered to each rule.

Business Rule Process

Perform the following steps to run the business rules.

- Once the conditions are setup, click Calculate. Then run the custom menu
 Validate Rule Setup. If any rules were set up incorrectly, a message appears in
 the Condition Error measure.
- 2. Correct the conditions until the error message no longer appears.
- 3. Run the **Assign Membership** custom menu. This runs the conditions in the rules, and assigns product/locations to the designated rules.
- To make sure that conditions and assignments are successful, check the Condition Count and Rule Count measures. They show you how many product/




locations are assigned to each rule. Once you see the count and membership you can commit and after running the batch the business rules will take effect.

Rule Membership View

The Rule Membership view displays the condition and rule a product/location is assigned to.

Figure 7-26 Rule Membership View



Measures: Rule Membership View

The Rule Membership view contains the following measures.

Rule Membership

This measure displays what rule a certain product/location is assigned to.

Condition Membership


This measure displays what condition a certain product/location is assigned to.

Parameters for Approval View

The Parameters for Approval view allows you to manage the approval exception setting based on the business rules you set up. For instance, if a rule has assigned high margin items, you may want to tighten the Error threshold, to make sure the forecast is in line with your expectations.



Figure 7-27 Parameters for Approval View



Measures: Parameters for Approval View

The Parameters for Approval view contains the following measures.

Approval Method at Rule

This field is a list from which you select the default automatic approval policy for forecast items. Valid values are:

Manual

The system-generated forecast is not automatically approved. Forecast values must be manually approved by accessing and amending the Forecast Review view

Automatic

The system-generated quantity is automatically approved as is.

By Alert

This list of values may also include any Forecast Approval alerts that have been configured for use in the forecast approval process. Alerts are configured during the implementation and can be enabled to be used for Forecast Approval in the Enable Alert for Forecast Approval view. Refer to the *Oracle Retail Predictive Application Server Configuration Tools User Guide* for more information on alerts. The Alert Parameters view contains a list and descriptions of available alerts, and for which level (causal/baseline) that they are designed for.

Alert - Average Sales Threshold at Rule

Threshold used in deciding if average sales are high or low, depending on how they compare against the value. It overrides the values set up in the Forecast Setup workspace.

Alert - Calculation Periods at Rule

The number stored in this field defines the number of calculations periods used in generating exceptions. It overrides the values set up in the Forecast Setup workspace.

Alert - Error Threshold at Rule

This field stores the value that determines if a forecast error is acceptable, or if it needs to be flagged as exception. It overrides the values set up in the Forecast Setup workspace.

Alert - Causal Peak Factor at Rule



This measure is relevant for promotional forecasting. The current forecast values are divided by the maximum historical demand. If the result is larger than the value of this measure, the forecast may be too large and an exception is triggered. It overrides the values set up in the Forecast Setup workspace.

Parameters for Navigation View

The Parameters for Navigation view allows setup for what forecasts are approved and which ones need review

The forecast approval process is two prong.

 First, you set up business to decide what forecasts are approved and which ones need review.

The setup occurs in the Rule Condition Setup View and the Parameters for Navigation View. After the batch is run, there will be a pool of approved product/locations, and a pool of product/locations that need review. However, not all product/locations in this pool have the same criticality.

Secondly, navigation exceptions come in the picture.

The unapproved product/locations are run thru the business rules for navigations and assigned to different navigation buckets.

For instance, key items and high margin items will always be *Urgent*. High sellers, but lower value can be *Required*. The next tier can be *Optional*.

Finally, unapproved product/locations that are not as important for the business as the ones already assigned to the top tiers can be assigned to *Informational*.




Figure 7-28 Parameters for Navigation View

Measures: Parameters for Navigation View

The Parameters for Navigation view contains the following measure.

Navigation Buckets at Rule



In this measure you assign the product/locations assigned to the navigation business rules to the Navigation Buckets, which represent the urgency they need review.



8

Offer Analysis Task

This chapter describes the Offer Analysis task for IPOCS-Demand Forecasting.

Offer Analysis Workspaces, Steps, and Views

The following table lists the workspaces, steps, and views for the Offer Analysis task.

Table 8-1 Offer Analysis Workspaces, Steps, and Views

Workspace	Step	Views
Offer Analysis Workspace	Offer Analysis Step	Summary View
		Detailed View

Offer Analysis Workspace

The Offer Analysis workspace allows you access to all of the views listed in Offer Analysis Workspaces, Steps, and Views.

It allows you to review how certain events have performed historically. The current promotion model consists of campaigns, which are a collection of promotions. Each promotion has one or more active offers.

Examples of this event structure are listed in the following table.


Campaign	Promotions	Offers
Winter 2024	TV Ad December	Multiple Buys
		Gift with purchase
	Price Discount February	Buy One Get One
		20% off any collection

The information is useful to review at any of these levels, but it is at the offer level where the impact on demand is quantified inside the forecast engine. It is then aggregated across offers to present the data per promotion, and across promotions to see how well the campaign did. All information in this workbook is historical. Offer information for the forecast (as it impacts future demand) is presented in the Forecast Review workbook. When reviewing the forecast, you can select how similar offers performed in the past and include additional information for the approval process in addition to the business rules set up for exception management.

To build the Offer Analysis workspace, perform these steps:

1. From the left sidebar menu, click the Task Module to view the available tasks.


Figure 8-1 Task Module



- 2. Click the **Review and Approve** activity and then click **Promotion Analysis** to access the available workspaces.
- 3. Click **Promotion Analysis**. The wizard opens.


You can open an existing workspace, but to create a new workspace, click **Create New Workspace**.

Figure 8-2 Offer Analysis Wizard



4. Enter a name for your new workspace in the label text box and click **OK**.


Figure 8-3 Enter Workspace Label



5. The Workspace wizard opens. Select the items you want to work with and click **Next**.

Figure 8-4 Workspace Wizard: Select Items


Select Offer



6. The Workspace wizard opens. Select the locations you want to work with and click Next.

Figure 8-5 Workspace Wizard: Select Locations


Select Locations



7. Select the offers you want to work with and click **Finish**.




Figure 8-6 Workspace Wizard: Select Offers



8. The wizard notifies you that your workspace is being prepared. Successful workspaces are available from the Dashboard.

Figure 8-7 Successful Workspace Build



The Offer Analysis workspace is built. This workspace contains this step:

Offer Analysis Step

Offer Analysis Step

The available views are:

Summary View



Detailed View

Summary View

The Summary view allows you to review campaign/promo/offer data at a level in the product and location hierarchies that is higher than item/store. For a more detailed look, the same measures presented in this view can be reviewed in the Detailed View.

Figure 8-8 Summary View



Measures: Summary View

The Summary view contains the following measures.

Baseline Sales Units

This measure displays the sales units that would have been sold during the offer period if no reward was active.

Markdown Sales Units

This measure displays clearance units sold during the offer period.

Offer Sales Units

This measure displays the additional sales units sold during the offer period due to the offer reward.

Reward Type

This measure displays the mechanism used during the offer period to drive additional demand. The reward types available are:

- Percent off: Price discount from the original price. Let's say the original price is \$9.99, and the discount is 15%. During the offer the price at which items were sold is \$8.49
- **Amount off**: Amount off from the original price. Let's say the original price is \$9.99 and the amount off is \$2. During the offer the price at which items were sold is \$7.99.
- **Fixed price**: The price at which an item was sold. No matter what the original price is, the fixed price is what the items were sold for.

Effective Discount

This measure displays the actual discount offered during the offer period, no matter what the reward type was. This is a very important metric, since it is probably the main driver of the additional demand produced during an offer. It is also not always trivial to calculate. For example, for a Buy One Get One Free offer one would think the discount is 50%. However, not everybody buys an even number of items, even when this offer is active. This will actually lower the effective discount to be less than 50%.

Offer Start Date



This measure displays the date when the offer period started. This measure is displayed at an aggregate level, and let us say that some stores have different offer start dates, due to different weather in their geographic location. The date displayed is the earliest of the available dates.

Offer End Date

This measure displays the date when the offer period ended. This measure is displayed at an aggregate level, and let us say that some stores have different offer start dates, due to different weather in their geographic location. The date displayed is the latest of the available dates.

Offer Length

This measure displays the number of dates the offer was active. It is the number of days between the offer end and start dates.

Product Count

This measure displays how many items were part of the offer.

Location Count

This measure displays how many stores were part of the offer.

Detailed View

The Detailed view has the exact same metrics as the Summary View. The difference is that the Detailed view has the information displayed at the item/store level, while the Summary View shows it at a higher level in the product and location hierarchies.



9

Attribute Review Task

This chapter describes the Attribute Review task for IPOCS-Demand Forecasting and IPOCS-Lifecycle Allocation and Replenishment.

Attribute Review Workspaces, Steps, and Views

The following table lists the workspaces, steps, and views for the Attribute Review task.

Table 9-1 Attribute Review Workspaces, Steps, and Views

Workspace	Steps	Views
Attributes Review Workspace	Label & Setup Step	Enable Prod/Loc View Label & Setup View
	Review Step	Location Attributes View Product Attributes View Product/Location Attributes View
	Edit Step	Location Attributes View Product Attributes View Product/Location Attributes View

Attributes Review Workspace

The Attributes Review workspace allows you access to all of the views listed in Attributes Review Workspaces, Steps, and Views.

The Attribute Review workspace allows you to review attributes that you can use in rules using the Business Rule engine. The attributes can be product specific, like brand or class. They can also be location specific, like store format, or number of stores an item is sold in. Finally, they can product/location specific, like average sales, or the vendor from where the products were sourced for a specific store.

The attribute data types are:


- String examples are brand, region
- Date examples are store open date, forecast end date
- Numeric examples are historical average sales, coefficient of variance

The sources of the attribute information can come from various source. They can be loaded or calculated. IPOCS-Demand Forecasting GA has a set of calculated attributes that can be easily expanded to including any retailer-relevant attributes. For additional technical information on how the attributes are managed, refer to the *Oracle Retail Inventory Planning Optimization Cloud Service-Demand Forecasting / Inventory Planning Optimization Cloud Service-Lifecycle Allocation and Replenishment Implementation Guide*.

To build the Attribute Review workspace, perform these steps:

1. From the left sidebar menu, click the Task Module to view the available tasks.


Figure 9-1 Task Module



- 2. Click the **IPO Administration** activity and then click **Attributes Review** to access the available workspaces.
- 3. Click Weekly Forecast. The wizard opens.

You can open an existing workspace, but to create a new workspace, click **Create New Workspace**.

Figure 9-2 Weekly Forecast Wizard






4. Enter a name for your new workspace in the label text box and click **OK**.

Figure 9-3 Enter Workspace Label




5. The Workspace wizard opens. Select the locations you want to work with and click Next.

Figure 9-4 Workspace Wizard: Select Locations



6. Select the products you want to work with and click **Finish**.


Figure 9-5 Workspace Wizard: Select Products



7. The wizard notifies you that your workspace is being prepared. Successful workspaces are available from the Dashboard.



Figure 9-6 Successful Workspace Build



The Attributes Review workspace is built. This workspace contains this step:

- Label & Setup
- Review Step
- Edit Step

Label and Setup Step


The available views are:

- Enable Prod/Loc View
- · Label and Setup View

Enable Prod/Loc View

The Enable Prod/Loc view allows you to enable attributes at the product/location levels.

Figure 9-7 Enable Prod/Loc View



Measures: Enable Prod/Loc View

The Enable Prod/Loc view contains the following measure.

Product-Location Attribute Mask


This measure allows you to select product and location that have relevant attributes. The attributes are displayed and can be edited in the next two steps.



Label & Setup View

The Label & Setup view allows you to enable attributes for the IPOCS-Lifecycle Allocation and Replenishment solution and to potentially give attributes a more meaningful description.

Figure 9-8 Label & Setup View



Measures: Label & Setup View

The Label & Setup view contains the following measures.

Attribute Description

This measure allows to give attributes a more meaningful description.

Lifecycle Active Attributes

This measure allows to select attributes to be used in the Lifecycle Allocation and Replenishment solution. Some of the available attributes may not be relevant for the solution, and here is where you can specify which should be used and which not.

Attribute to View



Review Step


The available views are:

- Location Attributes View
- Product Attributes View
- Product/Location Attributes View

Location Attributes View

The Location Attributes view allows you to manually enter attribute values that are location specific.

Figure 9-9 Location Attributes View



Measures: Location Attributes View

The Location Attributes view contains the following measures.

Loaded Location Attribute String

This measure allows editing location attributes that have a string value, such as region, or store format.

Loaded Location Attribute Number

This measure allows editing location attributes that have a numeric value, such as number of products carried in a location, or average sales per store.

Loaded Location Attribute Date



This measure allows editing location attributes that have a date value, such as a store open date.

Product Attributes View

The Product Attributes view allows you to review attributes and their values that are product specific.

Figure 9-10 Product Attributes View



Measures: Product Attributes View

The Product Attributes view contains the following measures.

Product Attribute String

This measure displays product attributes that have a string value, such as brand, or class.

Product Attribute Number

This measure displays product attributes that have a numeric value, such as number of locations carrying an item, or average sales per item.

Product Attribute Date


This measure displays product attributes that have a date value, such as item start date.

Product/Location Attributes View

The Product/Location Attributes view allows you to review attributes and their values that are product/location specific.



Figure 9-11 Product/Location Attributes View



Measures: Product/Location Attributes View

The Product/Location Attributes view contains the following measures.

Product-Location Attribute String

This measure displays product/location attributes that have a string value, such as brand, or price tier.

Product-Location Attribute Number

This measure displays product/location attributes that have a numeric value, such as average sales or error variance.

Product-Location Attribute Date

This measure displays product/location attributes that have a date value, such as item start or end dates.

Edit Step

The available views are:




- Location Attributes View
- Product Attributes View
- Product/Location Attributes View

Location Attributes View

The Location Attributes view allows you to manually enter attribute values that are location specific.

Figure 9-12 Location Attributes View



Measures: Location Attributes View

The Location Attributes view contains the following measures.

Loaded Location Attribute String

This measure allows editing location attributes that have a string value, such as region, or store format.

Loaded Location Attribute Number

This measure allows editing location attributes that have a numeric value, such as number of products carried in a location, or average sales per store.

Loaded Location Attribute Date

This measure allows editing location attributes that have a date value, such as a store open date.

Product Attributes View



The Product Attributes view allows you to manually edit attribute values that are product specific.

Figure 9-13 Product Attributes View



Measures: Product Attributes View

The Product Attributes view contains the following measures.

Loaded Product Attribute String

This measure allows editing product attributes that have a string value, such as brand, or class.

Loaded Product Attribute Number

This measure allows editing product attributes that have a numeric value, such as number of locations carrying an item, or average sales per item.

Loaded Product Attribute Date


This measure allows editing product attributes that have a date value, such as item start date.

Product/Location Attributes View

The Product/Location Attributes view allows you to manually edit attribute values that are product/location specific.



Figure 9-14 Product/Location Attributes View



Measures: Product/Location Attributes View

The Product/Location Attributes view contains the following measures.

Loaded Product-Location Attribute String

This measure allows editing product/location attributes that have a string value, such as brand, or price tier.

Loaded Product-Location Attribute Number

This measure allows editing product/location attributes that have a numeric value, such as average sales or error variance.

Loaded Product-Location Attribute Date

This measure allows editing product/location attributes that have a date value, such as item start or end dates.



10

Introduction: Lifecycle Allocation and Replenishment

Oracle Retail Inventory Planning Optimization Cloud Service-Lifecycle Allocation and Replenishment (IPOCS-Lifecycle Allocation and Replenishment) is an automated allocation and replenishment planning system that constantly monitors inventory conditions and based on these conditions creates point in time replenishment orders or transfers to consumer demand, while considering various constraints. Inventory movement varies from Warehouse to Store, Warehouse to Third Party, Customer Order Fulfillment, and Store to Store.


Figure 10-1 Orders and Transfers Overview



IPOCS-Lifecycle Allocation and Replenishment is appropriate for retailers where:

- Lead time is longer than the product lifecycle
- Items have low weekly sales by location
- Over the product's life it goes through a cycle of Initial Allocation (Product Introduction), Replenishment (Product Growth and Maturity) and Final Allocation (Product End of Life/ Decline), as depicted in the following image.

Figure 10-2 Lifecycle Overview



This guide contains these chapters and appendices for the IPOCS-Lifecycle Allocation and Replenishment module:

- Lifecycle Allocation and Replenishment Dashboard
- Assortment Administration Task
- Manage Alert Parameters
- Manage Scaling Parameters
- Manage Databags
- Manage Rule Groups
- Manage Packs
- Manage Allowed Transfer
- Supply Chain Network
- Replenishment Parameters
- Review & Approve
- Appendix: IPOCS-Lifecycle Allocation and Replenishment Exceptions & Alerts
- Appendix: Troubleshooting

Key Features

IPOCS-Lifecycle Allocation and Replenishment key features include:

- A pre-defined set of business processes, measures and rules used to support the customer requirements and business process
- Rule-based replenishment parameters management
- Assignment of replenishment parameters at item location based on rules
- User parameters focus by exception only
- Forecast-based location Target Stock (TS) level calculation



- TS can be calculated through different methods, ranging from a simple Fixed Units
 quantity to more sophisticated methods based on demand volatility and service level,
 to fit different product types and demand behaviors throughout the product lifecycle
- Analysis Capabilities
 - Ability to analyze supply chain performance indicators such as days of stock at any level of the location/Merchandise hierarchies combined with product and/or location attributes
- Product Lifecycle Recognition
 - Lifecycles are used to rule the replenishment approach over time, based on the item lifecycle phase

Supported Replenishment

Supported Replenishment (pull) activities include:

- Predict how much stores will sell
- Determine how much inventory stores should carry, for example, store Target Stock (TS) level
- Predict how much the warehouse will ship to stores
- Distribution of constrained stock
- Determine how much inventory the warehouse should carry
- Generate/Review/Approve orders for all locations

Supported Allocation

Supported Allocation (push) activities include:

- Post-distribute goods housed in warehouses to stores (end-of-life management).
- Management of store-to-store transfers when supply is limited or for stock re-balancing across stores.

User Experience and Workflow


The user experience is delivered on our experience inspired Retail Predictive Application Server Cloud Edition (RPASCE) user interface (UI). RPASCE provides end-users with a next-generation cloud-native UI that is purpose-built to accelerate intent into action for planners and forecasters. This includes interactive and visual dashboards to assess priorities, responsive and flexible workspaces to implement decisions and a coordinated exceptions framework that ties business processes all the way from dashboard to mobile phone.



11

Lifecycle Allocation and Replenishment Dashboard

The IPOCS-Lifecycle Allocation and Replenishment dashboard is the workspace that opens on login. You can use the dashboard to quickly analyze the health of the business. The dashboard needs to be refreshed periodically as new products, locations, and replenishment-related data are added. This typically happens weekly but depends on your administrator's settings. The measure data of existing products and locations in the dashboard can be refreshed at any time to view updated changes.



IPOCS-Lifecycle Allocation and Replenishment has two dashboard profile types and includes the following profiles for each type:

- Metric profile type
 - Overview
- Exception profile type
 - Setup Exceptions
 - Replenishment Exceptions

Figure 11-2 Dashboard Profiles



The information in the metric and exception profiles is summarized in tiles, which can be filtered, for example, on the product, location, or any other hierarchy that makes sense as shown in the following image.

Figure 11-3 Merchandise Filter







Figure 11-4 Location Filter



The information presented is condensed in the tile metrics, which is also shown in a chart that is broken down into more detail.

In addition, there is the Administration dashboard which provides information about scheduled OAT tasks, or workspace build information. More information about the Administration dashboard can be found in the *Oracle Retail Predictive Application Server Cloud Edition User Guide*.

Overview Dashboard

There is one GA tile in the Overview dashboard.






Figure 11-5 Overview Dashboard

Actual Stock on Hand Units

This tile displays information about the current and historical on-hand stock in units and retail value.

Setup Exceptions Dashboard

This is the first of the exception profile types available in IPOCS-Lifecycle Allocation and Replenishment. It is relevant to identify merchandise and location with set up issues such as, missing replenishment parameters/methods or supply chain network models.






Figure 11-6 Setup Exceptions Dashboard

The hit count represents the number of products in the subclass and location, within the store group, that are missing set up rules according to the configured business rules.

Exceptions

The information displayed in the tiles is based on exceptions, or business rules defined to check if the replenishment parameters and supply network model are set up for all product and location combinations that are expecting a replenishment plan recommended by IPOCS-Lifecycle Allocation and Replenishment. The exception definitions and expressions are detailed in the Appendix: IPOCS-Lifecycle Allocation and Replenishment Exceptions & Alerts .

Number of Hits Count

The main metric in the tiles is the number of hit counts which are based on the product and location filter settings. If the filter settings range products and locations to a narrower selection than, **All Product** and **All Location**, then the number should be reflected in the tile; that is, it should decrease.

Number of Subclass and Store Group

The secondary metric on the tiles displays the number of subclass and districts that are affected. Note that the dimensions are configurable.

Charts

Each tile comes with a set of charts where the hit count information is broken down to lower levels and sorted based on hit count.

Replenishment Exceptions



This is the second of the exception profile types available in IPOCS-Lifecycle Allocation and Replenishment. It is relevant to identify merchandise and location where the suggested replenishment needs the user's attention. For example, a particular product and location might be in an overstock situation and may need the replenishment plan overriden by the user and a potential review of the replenishment parameters to reduce the overstock.




Figure 11-7 Replenishment Exceptions

Exceptions

The information displayed in the tiles is based on exceptions, or business rules defined to identify the outliers that need the replenishment plan recommended by IPOCS-Lifecycle Allocation and Replenishment reviewed. The exception definitions and expressions are detailed in the Appendix: IPOCS-Lifecycle Allocation and Replenishment Exceptions & Alerts .



Assortment Administration Task

This chapter describes the functionality that allows you to review and maintain the assortment within IPOCS-Lifecycle Allocation and Replenishment.

In IPOCS-Lifecycle Allocation and Replenishment assortment information is used during the replenishment calculation. Replenishment should only be suggested for valid product and location combinations rather than for all product and location combinations. It is during this process where the assortment information is very important to allow IPOCS-Lifecycle Allocation and Replenishment to replenish only valid combinations, it also improves calculation performance by reducing the amount of product and location combinations.

Based on the assortment information IPOCS-Lifecycle Allocation and Replenishment identifies valid product and location combinations if the following conditions are met:

- If the product and location combination is active when the system runs the replenishment calculations. In other words, if the system date (today's date) is within the Assortment Start and Assortment End Dates for the product and location combination
- There are historical sales for the product and location combination.
- There is allocation information for the product and location combination.
- If users have overridden the assortment information and have created an exception to force a particular product and location combination to be valid (assorted)

Assortment Administration Workspace, Steps, and Views

The following table lists the workspaces, steps, and views for the Assortment Administration task.

Table 12-1 Assortment Admin Workspace, Steps and Views

Workspace	Step	Tab	Views
Assortment Admin	Review Parameters Step	Assortment Summary	Actual Data View
Workspace			Assortment View
		Assortment Parameters	Assortment Parameters View
			Filter View
	Review Assortment Step	By Parent	Location View
			Variant View
			Variant-Location View
			Variant-Location-Week View
		By Item	Location View



Table 12-1 (Cont.) Assortment Admin Workspace, Steps and Views


Workspace	Step	Tab	Views
			Product-Location View
		Actual Data	Product-Location-Week View

Assortment Admin Workspace

The Assortment Admin workspace allows you to access all the views listed in Assortment Administration Workspace, Steps, and Views. To build the Assortment Admin workspace, perform these steps:

1. From the left sidebar menu, click the **Task Module** to view the available tasks.

Figure 12-1 Task Module



- **2.** Click the **Assortment Management** activity to access the available workspaces.
- Click Assortment Admin. The Assortment Admin wizard opens. You can open an existing workspace, but to create a new workspace, click Create New Workspace.

Assortment Admin

Select Plan

□ | Filter...

My Plans

Sort by ▼

Assortment Admin

Figure 12-2 Assortment Admin Wizard

4. Enter a name for your new workspace in the label text box and click **OK**.

Cancel

Open in new tab Open

Figure 12-3 Enter Workspace Label



Create New Plan


5. The Workspace wizard opens. Select the products you want to work with and click **Next**.

Assortment Admin: Assortment Admin Product Levels & Positions P08 View ▼ Search... ☐ Label 1 S/C 0001 □ P08 S/C 0002 POP S/C 0003 □ P06 S/C 0004 P05 S/C 0005 POG S/C 0006 S/C 0007 ☐ P03 S/C 0007 Pack P02 S/C 0008 ✓ POV S/C 0008 Pack S/C 0009 S/C 0010 S/C 0011 S/C 0011 Pack S/C 0012 Cancel Previous Next > Finish

Figure 12-4 Workspace Wizard: Select Product

6. Select the locations you want to work with and click **Next**.






7. Select the calendar period you want to work with and click **Finish**.

Figure 12-6 Workspace Wizard: Select Calendar

8. The wizard notifies you that your workspace is being prepared. Successful workspaces are available from the Dashboard.

Figure 12-7 Successful Workspace Build



Review Parameters Step

This step contains these views:




- Actual Data View
- Assortment View
- Assortment Parameters View
- Filter View

Actual Data View

The **Actual Data View**, under the **Assortment Summary tab**, allows you to review high-level actuals that are relevant for the assortment administration. For example, what is the date of the first sale within the workspace's scope.

Figure 12-8 Actual Data View



Measures: Actual Data View

Note:

In this view, there are no hierarchies in the axis, all the measures in this view are shown aggregated based on all product and all location (and calendar where relevant). It is applicable to the scope loaded into the workspace.

Today Date

This is a loaded read-only measure to display the system date that is calculated by the IPOCS-Lifecycle Allocation and Replenishment batch.

Has Sales Count



This is a calculated measure used to indicate the total number of loaded product and location combinations for which IPOCS-Lifecycle Allocation and Replenishment has sales data.

First Sales Date

This is a calculated measure used to indicate the first sales date for the workbook scope based on the loaded product and location daily sales. The first sales date is the earliest date of all products sold in all locations.

Last Sales Date

This is a calculated measure used to indicate the last sales date for the location based on the loaded product and location daily sales. The last sales date is the later date of all products sold in all locations.

Sales Span Dur (Weeks)

This is a calculated measure to show the number of week's sales across the calendar.

Actual Sales Units

This is a calculated measure used to indicate the total sales units considering the daily sales of the product and location combination.

Actual Sales Count

This is a calculated measure used to indicate the total number of product and location combinations with sales units (greater than 0 units).

Has Stock Count

This is a calculated measure used to indicate the total number of product and location combinations for which IPOCS-Lifecycle Allocation and Replenishment has stock data.

First Stock Date

This is a calculated measure used to indicate the first inventory date for the workbook scope based on the loaded product and location inventory. The first inventory date is the earliest date of all products and location inventories.

Last Stock Date

This is a calculated measure used to indicate the last inventory date for the workbook scope based on the loaded product and location inventory. The last inventory date is the later date of all products and location inventories.

Actual EOP Units

This is a calculated measure used to indicate the end-of-period inventory in units considering the actual inventory position for product and location combinations loaded into the workspace.

Actual EOP Count


This is a calculated measure used to indicate the total number of product and location combinations with end-of-period inventory (greater than 0 units).

Assortment View

The **Assortment View**, under the **Assortment Summary tab**, allows you to see a high-level overview of the assortments.



Figure 12-9 Assortment View



Measures: Assortment View

The Assortment view contains the following measures.

Asst. Loc Valid Count

This is a calculated measure used to indicate the total number of locations with at least one valid product and location combination assorted. In this view, the measure contains the total number for the workspace scope.

Asst. Loc Start Date

This is a calculated measure used to indicate the earliest populated location start date within the [Validation] Location Step.

Asst. Loc End Date

This is a calculated measure used to indicate the last populated location end date within the [Validation] Location Step.

Asst. Var Start Date

This is a calculated measure used to indicate the earliest populated Variant start date within the [Validation] Variant Step.

Asst. Var End Date

This is a calculated measure used to indicate the last populated Variant end date within the [Validation] Variant Step.

Asst. Var-Loc Def. Count

This is a calculated measure used to indicate the total number of variance and location combinations assorted. In this view, the measure contains the total number for the workspace scope.



Asst. Var-Loc Exc. Count

This is a calculated measure used to indicate the number of exceptions that are being used at the Var-Loc level.

Asst. Var-Loc Exc. End Count

This is a calculated measure used to indicate the number of populated end date exceptions at the Variant Location level.

Asst. Var-Loc Exc. Start Count

This is a calculated measure used to indicate the number of populated start date exceptions at the Variant Location level.

Asst. Prod-Loc Exc. Count

This is a calculated measure used to indicate the number of exceptions that are being used at the Prod-Loc level.

Asst. Prod-Loc Exc. End Count

This is a calculated measure used to indicate the number of populated end date exceptions at the Product Location level.

Asst. Prod-Loc Exc. Start Count

This is a calculated measure used to indicate the number of populated start date exceptions at the Product Location level.

Plan Asst. Prod-Loc Start Date

This is a calculated measure used to indicate the earliest plan assortment start dates for all item / location.

Plan Asst. Prod-Loc End Date

This is a calculated measure used to indicate the last plan assortment end dates for all item / location.

Asst. Prod-Loc Count

This is a calculated measure used to indicate the total number of product and location combinations assorted. In this view, the measure contains the total number for the workspace scope.

Asst. Prod-Loc Active Count

This is a calculated measure used to indicate the total number of product and location combinations assorted and still active. If the assortment end date has not been reached yet, then it is active. Otherwise, it is inactive meaning that the assortment has already stopped. In this view, the measure contains the total number for the workspace scope.

Asst. Var-Loc Count

This is a calculated measure used to indicate the total number of variance and location combinations assorted. In this view, the measure contains the total number for the workspace scope.

Asst. Var-Loc Active Count

This is a calculated measure used to indicate the total number of variance and location combinations assorted and still active. If the assortment end date has not been reached yet,



for all products within the variance, then it is active. Otherwise, it is inactive meaning that the assortment has already stopped. In this view, the measure contains the total number for the workspace scope.

Lfc. Prod-Loc Def. Count

This is a calculated measure used to indicate the total number of product and location combinations with a default valid lifecycle. In this view, the measure contains the total number for the workspace scope.


Lfc. Prod-Loc Count

This is a calculated measure used to indicate the total number of product and location combinations with a valid lifecycle considering the user-defined lifecycle exceptions. In this view, the measure contains the total number for the workspace scope.

Assortment Parameters View

The **Assortment Parameters View**, under the **Assortment Parameters tab**, allows you to set up assortment rules to be considered by the IPOCS-Lifecycle Allocation and Replenishment assortment calculation functionality.

Figure 12-10 Assortment Parameters View



Measures: Assortment Parameters View

The Assortment Parameters view contains the following measures.

Asst. Start Rule

Plan Start Date



The assortment start date loaded into IPOCS-Lifecycle Allocation and Replenishment is used. If there is an exception forced by you then the exception takes priority.

First Sales after Plan Start Date

If the first sale occurs after the planned start date, then the assortment start date is the first sales date. Otherwise, the assortment start date is the planned start date.

First Stock after Plan Start Date

If the first inventory has been received after the planned start date, then the assortment start date is the date that the first inventory was received. Otherwise, the assortment start date is the planned start date.

Min {Plan Start Date - First Sales}

The assortment start date is the oldest date between the first sale date and the planned assortment start date loaded into IPOCS-Lifecycle Allocation and Replenishment.

Min {Plan Start Date - First Stock}

The assortment start date is the oldest date between the first inventory date and the planned assortment start date loaded into IPOCS-Lifecycle Allocation and Replenishment.

Min {Plan Start Date - First Sales/Stock}

The assortment start date is the oldest date between the first inventory date, the first sales date and the planned assortment start date loaded into IPOCS-Lifecycle Allocation and Replenishment.

First Sales

The first sales date is used for the assortment start date.

First Stock

The first inventory date is used for the assortment start date.

First Stales/Stock

The assortment start date is the oldest date between the first inventory date and the first sales date.

Asst. End Rule

This is an editable measure to define how IPOCS-Lifecycle Allocation and Replenishment should calculate the assortment end date. Valid values are:

Plan End Date

The assortment end date loaded into IPOCS-Lifecycle Allocation and Replenishment. If there is an exception forced by you, then the exception takes priority.

Max {Plan End Date - Last Sales}

The assortment end date is the date that comes last between the last sale date and the planned assortment end date loaded into IPOCS-Lifecycle Allocation and Replenishment. Please note that when the loaded assortment end date is empty IPOCS-Lifecycle Allocation and Replenishment assumes the latest calendar day available as the assortment end date calculation.

Max {Plan End Date - Last Stock}

The assortment end date is the date that comes last between the last inventory date and the planned assortment end date loaded into IPOCS-Lifecycle Allocation and Replenishment. Please note that when the loaded assortment end date is empty IPOCS-



Lifecycle Allocation and Replenishment assumes the latest calendar day available as the assortment end date calculation.

Max {Plan End Date - Last Sales/Stock}

The assortment end date is the date that comes last between the last sale date, the last inventory date and the planned assortment end date loaded into IPOCS-Lifecycle Allocation and Replenishment. Please note that when the loaded assortment end date is empty IPOCS-Lifecycle Allocation and Replenishment assumes the latest calendar day available as the assortment end date calculation.

Min {Plan End Date - Last Stock}

The assortment end date is the date that comes first between the last inventory date and the planned assortment end date loaded into IPOCS-Lifecycle Allocation and Replenishment. Please note that when the loaded assortment end date is empty IPOCS-Lifecycle Allocation and Replenishment assumes the latest calendar day available as the assortment end date calculation.

Min {Plan Start Date - Last Sales/Stock}

The assortment end date is the date that comes first between the last sale date, last inventory date and the planned assortment end date loaded into IPOCS-Lifecycle Allocation and Replenishment. Please note that when the loaded assortment end date is empty IPOCS-Lifecycle Allocation and Replenishment assumes the latest calendar day available as the assortment end date calculation.

Last Sales

The last sales date is used for the assortment end date.

Last Stock

The last inventory date is used for the assortment last date.

Last Stales/Stock

The assortment end date is date that comes last between the last inventory date and the last sales date.

Asst. End Lag Dur (days)


This is an editable measure to define the number of lag days that the system considers for the sales and inventory for the assortment calculations. When the assortment is calculated based on the sales or inventory data and if the data from today's date is older than the lag days indicated then the product and location combination is not assorted. For example, if the product does not sell for more than 30 days in a particular location, then it is removed from the assortment of that location.

Filter View

The **Filter View**, under the **Assortment Parameters tab**, allows you to set up a filter to work the assortment. For example, you can use the filter to display product and location combinations where the assortment is valid.



Figure 12-11 Filter View



Measures: Filter View

The Filter view contains the following measures.

Filter Type

This is an editable measure to define what type of filter should be applied to the views within the Assortment Admin workspace. Valid values are:

All

No filter is applied. All information is displayed.

Default Asst

Only valid assortments, by default, are displayed. The product and location combinations are filter based on the value of the measure Asst. Var-Loc Def. If the measure is selected, then the combination is captured the filter. Otherwise, it is excluded by the filter.

Valid Asst

Only valid assortments are displayed. The product and location combinations are filtered based on the measure Asst. Var-Loc Def. value. If the measure is selected, then the combination is captured by the filter. Otherwise, it is excluded by the filter.

Asst Active

Only active assortments are displayed. The product and location combinations are filtered based on the measure Asst. Prod-Loc value. If the measure is selected, then the combination is captured by the filter. Otherwise, it is excluded by the filter.

Default Lfc

Only a valid lifecycle, by default, is displayed. The product and location combinations are filtered based on the measure Lfc. Prod-Loc Def. value. If the measure is selected, then the combination is captured by the filter. Otherwise, it is excluded by the filter.

Valid Lfc

Only the valid lifecycle is displayed. The product and location combinations are filtered based on the measure Lfc. Prod-Loc value. If the measure is selected, then the combination is captured by the filter. Otherwise, it is excluded by the filter.

Review Assortment Step


This step contains these views:

- Location View
- Variant View
- Variant-Location View
- Variant-Location-Week View
- Product-Location View
- Product-Location-Week View

Location View

The **Location View**, under the **Review Assortment tab** and **By Parent tabs**, allows you to review and/or manage the assortment but at the location level only. The analysis is kept at location level without products.

Figure 12-12 Location View



Measures: Location View

The Location view contains the following measures.



Note:

The measures displayed in this view are supported by their counterparts defined at the product and location level. Therefore, the calculated measures in this view are the result of aggregating the ones at the product and location intersection.

User Valid Prod-Loc Filter

This is an editable measure to select locations to be filtered. The views display only the selected locations.

Asst. Loc Valid

This is a calculated measure to identify whether the location has a valid assortment or not. The location has a valid assortment when it contains a valid product assortment, or you have populated the location assortment start date or end date.

Asst. Loc Start Date

This is an editable measure to enter the location's assortment start date.

Asst. Loc End Date

This is an editable measure to enter the location's assortment end date.

Has Sales

This is a calculated measure used to indicate whether a location has sales data within IPOCS-Lifecycle Allocation and Replenishment or not. When selected, at least one product within the location would have sales, otherwise, there are no sales in IPOCS-Lifecycle Allocation and Replenishment.

First Sales Date

This is a calculated measure used to indicate the first sales date for the location based on the loaded product and location daily sales. In this view the location first sales date is the earliest date of all products sold in the location.

Last Sales Date

This is a calculated measure used to indicate the last sales date for the location based on the loaded product and location daily sales. In this view, the location last sales date is the later date of all products sold in the location.

Has Stock

This is a calculated measure used to indicate whether a location has inventory data within IPOCS-Lifecycle Allocation and Replenishment or not. When selected, then at least one product within the location would have sales, otherwise, there are no sales in IPOCS-Lifecycle Allocation and Replenishment.

First Stock Date

This is a calculated measure used to indicate the first inventory date for the location based on the loaded product and location inventory. The location first inventory date is the earliest date of all product inventory in the location.

Last Stock Date



This is a calculated measure used to indicate the last inventory date for the location based on the loaded product and location inventory. The location last inventory date is the later date of all product inventory in the location.

Asst. Prod-Loc Count

This is a calculated measure used to indicate the total number of product and location combinations assorted. In this view, the measure displays the total number of products for the location.

Asst. Prod-Loc Active Count

This is a calculated measure used to indicate the total number of product and location combinations assorted and still active. If the assortment end date has not been reached yet, then it is active. Otherwise, it is inactive, meaning that the assortment has already stopped. In this view, the measure displays the total number of products for the location.

Asst. Var-Loc Count

This is a calculated measure used to indicate the total number of variance and location combinations assorted. In this view, the measure displays the total number of variants for the location.

Asst. Var-Loc Active Count

This is a calculated measure used to indicate the total number of variance and location combinations assorted and still active. If the assortment end date has not been reached yet, for all products within the variance, then it is active. Otherwise, it is inactive, meaning that the assortment has already stopped. In this view, the measure displays the total number of variants for the location.

Asst. Var-Loc Start Date

This is a calculated measure used to indicate the assortment start date for the assorted variance and location combinations. In this view, the measure displays the earliest date from all the variances assorted for the location.

Asst. Var-Loc End Date

This is a calculated measure used to indicate the assortment end date for the assorted variance and location combinations. In this view, the measure displays the later date from all the variances assorted for the location.

Asst. Var-Loc From Start Dur (weeks)

This is a calculated measure used to indicate the number of elapsed weeks since the assortment started date indicated in the measure Asst. Var-Loc Start Date. The number of weeks is calculated until the IPOCS-Lifecycle Allocation and Replenishment today's week.

Lfc. Loc Valid

This is a calculated measure to identify whether the location has valid lifecycle products or not. The location has a valid lifecycle when it contains at least one valid lifecycle product.

Lfc. Prod-Loc Exc.

This is an editable measure to set a lifecycle exception for all products within the location. Valid values are:



Default

This value ignores the lifecycle exception and keeps the default lifecycle result.

On

This value enables the exception and uses the exception dates for the lifecycle calculation.

Off

This value enables the exception and disables all of the products in the location for the lifecycle calculation.

Lfc. Prod-Loc Count

This is a calculated measure used to indicate the total number of product and location combinations with a valid lifecycle. In this view, the measure displays the total number of valid lifecycles for all the products in the location.

Variant View

The **Variant View**, under the **Review Assortment tab**, and **By Parent tab**, allows you to review and manage the assortment but at the variant level only. The analysis is kept at variant level without locations.




Figure 12-13 Variant View

Measures: Variant View

The Variant view contains the following measures.



Note:

The measures displayed in this view are supported by their counterparts defined at the product and location level. Therefore, the calculated measures in this view are the result of aggregating the ones at the product and location intersection.

User Valid Prod-Loc Filter

This is an editable measure to select a variant to be filtered. The views display only the selected variants.

Asst. Var Start Date

This is an editable measure to enter the variant's assortment start date.

Asst. Var End Date

This is an editable measure to enter the variant's assortment end date.

Has Sales

This is a calculated measure used to indicate whether a variant has sales data within IPOCS-Lifecycle Allocation and Replenishment or not. When selected, then at least one product within the variant would have sales, otherwise, there are no sales in IPOCS- Lifecycle Allocation and Replenishment for the variant.

First Sales Date

This is a calculated measure used to indicate the date of the first sale for the variant based on the loaded product and location daily sales. In this view, the variant's first sales date is the earliest date of all products, within the variant, sold in all the locations.

Last Sales Date

This is a calculated measure used to indicate the last sales date for the variant based on the loaded product and location daily sales. In this view, the variant's last sales date is the later date of all products, within the variant, sold in all the locations.

Has Stock

This is a calculated measure used to indicate whether a variant has inventory data within IPOCS-Lifecycle Allocation and Replenishment or not. When selected, then at least one product within the variant would have inventory in one location, otherwise, there is no inventory in IPOCS- Lifecycle Allocation and Replenishment for the variant.

First Stock Date

This is a calculated measure used to indicate the first inventory date for the variant based on the loaded product and location inventory. In this view, the variant's first inventory date is the earliest date of all the variant's products from all location inventories.

Last Stock Date



This is a calculated measure used to indicate the last inventory date for the location based on the loaded product and location inventory. In this view, the variant's last inventory date is the later date of all the variant's products from all location inventories.

Asst. Prod-Loc Count

This is a calculated measure used to indicate the total number of product and location combinations assorted. In this view, the measure displays the total number of locations assorted for all the products within the variant.

Asst. Prod-Loc Active Count

This is a calculated measure used to indicate the total number of product and location combinations assorted and still active. If the assortment end date has not been reached yet, then it is active. Otherwise, it is inactive, meaning that the assortment has already stopped. In this view, the measure displays the total number of locations assorted for all the products within the variant.

Asst. Var-Loc Count

This is a calculated measure used to indicate the total number of variant and location combinations assorted. In this view, the measure displays the total number of locations for the variant.

Asst. Var-Loc Active Count

This is a calculated measure used to indicate the total number of variant and location combinations assorted and still active. If the assortment end date has not been reached yet, for all products within the variance, then it is active. Otherwise, it is inactive meaning, that the assortment has already stopped. In this view, the measure displays the total number of locations for the variant.

Asst. Var-Loc Start Date

This is a calculated measure used to indicate the assortment start date for the assorted variance and location combinations. In this view, the measure displays the earliest date from all the locations assorted for the variance.

Asst. Var-Loc End Date

This is a calculated measure used to indicate the assortment end date for the assorted variance and location combinations. In this view, the measure displays the earliest date from all the locations assorted for the variance.

Asst. Var-Loc from Start Dur (weeks)

This is a calculated measure used to indicate the number of elapsed weeks since the assortment start date indicated in the measure Asst. Var-Loc Start Date. The number of weeks is calculated until the IPOCS-Lifecycle Allocation and Replenishment today's week.

Lfc. Prod-Loc Exc.

This is an editable measure to set a lifecycle exception for the variant (all products within) in all locations. Valid values are:

Default

This value ignores the lifecycle exception and keeps the default lifecycle result.

On



This value enables the exception and uses the exception dates for the lifecycle calculation.

Off

This value enables the exception and disables the variant for all products in all locations for the lifecycle calculation.


Lfc. Prod-Loc Count

This is a calculated measure used to indicate the total number of product and location combinations with a valid lifecycle. In this view, the measure displays the total number of valid lifecycles for all the products, within the variant, in all locations.

Variant-Location View

The Variant-Location View, under the Review Assortment tab, and By Parent tab, allows you to review and manage the assortment but at the variant and location level only. The analysis is kept at variant level without the products within.

Figure 12-14 Variant-Location View



Measures: Variant-Location View

The Variant-Location view contains the following measures.



The measures displayed in this view are supported by their counterparts defined at the product and location level. Therefore, the calculated measures in this view are the result of aggregating the ones at the product and location intersection.

User Valid Prod-Loc Filter



This is an editable measure to select variant and location combinations to be filtered. The views display only the selected variant and location combinations.

Asst. Var-Loc Def

This is a calculated measure used to indicate if the variant and location combinations are valid by default.

Asst. Var-Loc Exc.

This is an editable measure to set an assortment exception for the variant and location combinations. Valid values are:

Default

This value ignores the assortment exception and keeps the default assortment result.

Or

This value enables the exception and uses the exception dates for the assortment calculation.

Off

This value enables the exception and disables the variant and location combination for the assortment calculation.

Asst. Var-Loc Exc. Start Date

This is an editable measure to enter the assortment start date for the variant and location combination exception. When the exception is set to Default or On, this is the date used by the assortment calculation.

Asst. Var-Loc Exc. End Date

This is an editable measure to enter the assortment end date for the variant and location combination exception. When the exception is set to Default or On, this is the date used by the assortment calculation.

Plan Asst. Prod-Loc Start Date

This is a calculated measure used to indicate the planned assortment start date for the product and location combination. When there is an assortment start date exception the planned assortment start date is the exception. Otherwise, it is the assortment start date loaded from the external system. In this view, the measure displays the earliest date of all the products within the variant for the location.

Plan Asst. Prod-Loc End Date

This is a calculated measure used to indicate the planned assortment end date for the product and location combination. When there is an assortment end date exception the planned assortment end date is the exception. Otherwise, it is the assortment end date loaded from the external system. In this view, the measure displays the later date of all the products within the variant for the location.

Has Sales

This is a calculated measure used to indicate whether a variant and location combination has sales data within IPOCS-Lifecycle Allocation and Replenishment or not. When selected then at least one product, within the variant, has sales for the location. Otherwise, there are no sales in IPOCS-Lifecycle Allocation and Replenishment for the variant and location combination.



First Sales Date

This is a calculated measure used to indicate the first sales date for the variant and location combination based on the loaded product and location daily sales. In this view, the variant and location combination's first sales date is the earliest date of all products within the variant sold in the location.

Last Sales Date

This is a calculated measure used to indicate the last sales date for the variant and location combination based on the loaded product and location daily sales. In this view, the variant and location combination's last sales date is the later date of all products within the variant sold in the location.

Has Stock

This is a calculated measure used to indicate whether a variant and location combination has inventory data within IPOCS-Lifecycle Allocation and Replenishment or not. When selected then at least one product, within the variant, has inventory in the location. Otherwise, there is no inventory in IPOCS-Lifecycle Allocation and Replenishment for the variant and location combination.

First Stock Date

This is a calculated measure used to indicate the first inventory date for the variant and location combination based on the loaded product and location inventory. In this view, the variant and location combination's first inventory date is the earliest date of all products within the variant with inventory in the location.

Last Stock Date

This is a calculated measure used to indicate the last inventory date for the variant and location combination based on the loaded product and location inventory. In this view, the variant and location combination's last inventory date is the later date of all products within the variant with inventory in the location.

Asst. Prod-Loc Count

This is a calculated measure used to indicate the total number of product and location combinations assorted. In this view, the measure displays the total number of assorted products, within the variant, for the location.

Asst. Prod-Loc Active Count

This is a calculated measure used to indicate the total number of product and location combinations assorted and still active. If the assortment end date has not been reached yet then it is active. Otherwise, it is inactive, meaning that the assortment has already stopped. In this view, the measure displays the total number of active assorted products, within the variant, for the location.

Asst. Var-Loc

This is a calculated measure used to indicate whether the variant and location combinations are assorted or not. A variant and location combination is assorted if at least one product, within the variant, is assorted in the location.

Asst. Var-Loc Active

This is a calculated measure used to indicate whether the variant and location combinations are assorted and still active or not. If the assortment end date has not



been reached yet, then it is active. A variant and location combination is assorted and active if at least one product, within the variant, is assorted and active in the location.

Asst. Var-Loc Start Date

This is a calculated measure used to indicate the assortment start date for the assorted variance and location combinations. In this view, the measure displays the earliest assortment start date of all assorted products, within the variant, for the location.

Asst. Var-Loc End Date

This is a calculated measure used to indicate the assortment end date for the assorted variance and location combinations. In this view, the measure displays the later assortment end date of all assorted products, within the variant, for the location.

Asst. Var-Loc from Start Dur (weeks)

This is a calculated measure used to indicate the number of elapsed weeks since the assortment started date indicated in the measure Asst. Var-Loc Start Date. The number the weeks are calculated until the IPOCS-Lifecycle Allocation and Replenishment today's week.

Lfc. Prod-Loc Exc.

This is an editable measure to set a lifecycle exception for the variant (all products within) and location combination. Valid values are:

Default

This value ignores the lifecycle exception and keeps the default lifecycle result.

On

This value enables the exception and uses the exception dates for the lifecycle calculation.

Off

This value enables the exception and disables the variant (all products within) and location combination for the lifecycle calculation.

Lfc. Prod-Loc Count


This is a calculated measure used to indicate the total number of product and location combinations with a valid lifecycle. In this view, the measure displays the total number of valid lifecycles for all the products, within the variant, in the location.

Variant-Location-Week View

The **Variant-Location-Week View**, under the **By Parent tab**, allows you to review the assortment week by week at the variant and location level.



Figure 12-15 Variant-Location-Week View



Measures: Variant-Location-Week View

The Variant-Location-Week view contains the following measures.

Asst. Var-Loc-Week

This is a calculated measure used to indicate for each week whether the variant and location combinations are assorted or not. A variant and location combination is assorted, for a particular week, if at least one product within the variant is assorted in the location for that same week.

Asst. Var-Loc-Week Count

This is a calculated measure used to indicate the total number of variant and location combinations assorted for each week.


Asst. Var-Loc-Week

This is a calculated measure, not visible but available in the view for selection, to display the variant image and help you by having a visual assortment.

Product-Location View

The **Product-Location View**, under the **By Item** tab, allows you to review and manage the assortment at the lowest level - product and location level.

Figure 12-16 Product-Location View





Measures: Product-Location View

The Product-Location view contains the following measures.

User Valid Prod-Loc Filter

This is an editable measure to select product and location combinations to be filtered. The views display only the selected product and location combinations.

Ext Asst. Prod-Loc

This is a measure loaded into IPOCS-Lifecycle Allocation and Replenishment to indicate whether a product and location combination is assorted or not. Valid values are:

Default

If the assortment dates are empty, but IPOCS-Lifecycle Allocation and Replenishment has sales or inventory data for the product and location combination, then IPOCS-Lifecycle Allocation and Replenishment assumes the product and location combination as assorted.

On

This value assumes the product and location combination as assorted and use the loaded assortment dates to assign the assortment start and end dates.

Off

This value assumes the product and location combination as not assorted even if there are assortment dates loaded.

Ext Asst. Prod-Loc Start Date

This is a measure loaded into IPOCS-Lifecycle Allocation and Replenishment to indicate the assortment start date for the product and location combination.

Ext Asst. Prod-Loc End Date

This is a measure loaded into IPOCS-Lifecycle Allocation and Replenishment to indicate the assortment end date for the product and location combination.

Asst. Var-Loc Exc.

This is an editable measure to override the loaded assortment for the product and location combinations. Valid values are:

Default

This value ignores the assortment exception and keeps the loaded assortment.

On

This value overrides the loaded value. It forces the product and location combination to be assorted and uses the assortment exception dates to assign the assortment start and end dates. If no exception dates are entered by you and a loaded date exists, then IPOCS-Lifecycle Allocation and Replenishment uses the loaded assortment dates to assign the assortment start and end dates.

Of

This value overrides the loaded value. It forces the product and location combination to be not assorted.

Asst. Var-Loc Exc. Start Date



This is an editable measure to enter the assortment start date exception for the product and location combination. When the exception is set to Default or On, this is the date used by the assortment calculation.

Asst. Var-Loc Exc. End Date

This is an editable measure to enter the assortment end date exception for the product and location combination. When the exception is set to Default or On, this is the date used by the assortment calculation.

Plan Asst. Prod-Loc Start Date

This is a calculated measure used to indicate the planned assortment start date for the product and location combination. When there is an assortment start date exception the planned assortment start date is the exception. Otherwise, it is the assortment start date loaded from the external system.

Plan Asst. Prod-Loc End Date

This is a calculated measure used to indicate the planned assortment end date for the product and location combination. When there is an assortment end date exception the planned assortment end date is the exception. Otherwise, it is the assortment end date loaded from the external system.

Has Sales

This is a calculated measure used to indicate whether a product and location combination has sales data within IPOCS-Lifecycle Allocation and Replenishment or not. When selected then there are sales. Otherwise, there are no sales in IPOCS-Lifecycle Allocation and Replenishment for the product and location combination.

First Sales Date

This is a calculated measure used to indicate the first sales date for the product and location combination based on the loaded product and location daily sales. The product and location combination's first sales date is the earliest date from the product and location combination sales.

Last Sales Date

This is a calculated measure used to indicate the last sales date for the product and location combination based on the loaded product and location daily sales. The product and location combination's last sales date is the later date from the product and location combination sales.

Has Stock

This is a calculated measure used to indicate whether a product and location combination has inventory data within IPOCS-Lifecycle Allocation and Replenishment or not. When selected then there is inventory. Otherwise, there is no inventory in IPOCS-Lifecycle Allocation and Replenishment for the product and location combination.

First Stock Date

This is a calculated measure used to indicate the first inventory date for the product and location combination based on the loaded product and location inventory. The product and location combination's first inventory date is the earliest date from the product and location combination inventory.

Last Stock Date



This is a calculated measure used to indicate the last inventory date for the product and location combination based on the loaded product and location inventory. The product and location combination's last inventory date is the later date from the product and location combination inventory.

Fixed TS Units 1

This is a measure loaded into IPOCS-Lifecycle Allocation and Replenishment to indicate the initial allocation, in units, for the product and location combination.

Fixed TS Units 2

This is an editable measure used to indicate a manual allocation for the product and location combination.

Fixed TS Units 3

This is an editable/loadable measure that is a placeholder to indicate other allocations for the product and location combination. It can be loaded from another source system.

Asst. Prod-Loc

This is a calculated measure used to indicate whether the product and location combinations are assorted or not.

Asst. Prod-Loc Active

This is a calculated measure used to indicate whether the product and location combinations are assorted and still active or not. If the assortment end date has not been reached yet, then it is active. Otherwise, the product and location combination is assorted, but not active.

Asst. Prod-Loc Start Date

This is a calculated measure used to indicate the assortment start date for the assorted product and location combinations. The date is calculated based on the option selected in the Assortment Parameters view.

Asst. Prod-Loc End Date

This is a calculated measure used to indicate the assortment end date for the assorted product and location combinations. The date is calculated based on the option selected in the Assortment Parameters view.

Lfc. Prod-Loc Def.

This is a calculated measure to identify whether the product and location combination has a valid lifecycle by default or not.

Lfc. Prod-Loc Exc.

This is an editable measure to set a lifecycle exception for the product and location combination. Valid values are:

Default

This value ignores the lifecycle exception and keeps the default lifecycle result.

Or

This value enables the exception and uses the lifecycle exception dates for the lifecycle calculation.

Off



This value enables the exception and disables the product and location combination for the lifecycle calculation.

Lfc. Prod-Loc Validity Start Date

This is an editable measure to enter the lifecycle start date exception for the product and location combination. This date overrides the lifecycle start date calculated in the Allocation & Replenishment Supply Chain Network workspace.

Lfc. Prod-Loc Validity End Date

This is an editable measure to enter the lifecycle end date exception for the product and location combination. This date overrides the lifecycle end date calculated in the Allocation & Replenishment Supply Chain Network workspace.

Lfc. Prod-Loc

This is a calculated measure to identify whether the product and location combination has a valid lifecycle or not. This measure takes into consideration the lifecycle exceptions. The exception takes priority over the Lfc. Prod-Loc Def.

Lfc. Anchor Exc. Date

This is an editable measure to enter the lifecycle anchor date exception for the product and location combination. This date overrides the lifecycle anchor date calculated in the Allocation & Replenishment Supply Chain Network workspace.

Lfc. End Exc. Date

This is an editable measure to enter the lifecycle's exception end date for the product and location combination. This date overrides the lifecycle anchor date calculated in the Allocation & Replenishment Supply Chain Network workspace.

Product-Location-Week View

The **Product-Location-Week View**, under the **Actual Data tab**, allows you to review the sales and inventory actual data at the product, location, and week level.






Figure 12-17 Product-Location-Week View

Measures: Product-Location-Week View

The Product-Location-Day view contains the following measures.

Actual Loc. Sales Units

This is a loaded measure used to indicate the total sales units for the day, product, and location combination.

Loc. On Hand EOP Day

This is a loaded measure used to indicate the closing inventory units for the day, product and location combination.

Assortment Admin Action Buttons

The Assortment Admin workspace has the following action buttons available:

- Load Actual Data
- Calc Sales Span
- Calc Assortment
- Calc Lifecycle
- Publish Data



Complete Retail Applications

| Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications | Complete Retail Applications |

Figure 12-18 Assortment Admin Action Buttons

Load Actual Data

This action button is responsible for loading the actual sales and actual inventory data. It populates the measures available in the Product-Location-Day view.

Calc Sales Span

This action button is responsible for the calculation of the first and last selling dates of the item/location. The assortment calculation can use this information to get the start and end dates of the assortment.

Calc Assortment

This action button is responsible for the assortment calculation. This action calculates the assortment start and end dates, using the rule selected by you in the view Assortment Parameters, and if the product and location combination is assorted or not.

Calc Lifecycle

This action button is responsible for the lifecycle calculation. The measure Lfc. Prod-Loc, in the Product-Location view, is calculated and populated by this action button.

Publish Data

This action button is responsible for committing all the measures managed within this workspace to be used by other IPOCS-Lifecycle Allocation and Replenishment processes and workspaces.



Manage Alert Parameters

This chapter describes the functionality that allows you to review alerts and set up replenishment watch lists.

Alerts Concept

Alerts are classified into two different types:

- Critical Alerts
- Non-Critical Alerts

IPOCS-Lifecycle Allocation and Replenishment uses the type of alert to know whether the generated orders can be auto-approved or should be reviewed or fixed by a user. When a product and location has an alert hit and that alert is a critical alert, then IPOCS-Lifecycle Allocation and Replenishment does not auto-approve the orders. You must review or fix the critical alert and then manually approve the orders, if needed. When a product and location combination has an alert hit and that alert is a non-critical alert, then it does not affect the approval of the orders. It is just an information to the users.

Additionally, alerts are also used to filter, within the Allocation and Replenishment Admin and Manage Databags workspaces, based on the product and location hits of the alert.

These alerts are available in IPOCS-Lifecycle Allocation and Replenishment:

- Replenishment Watch List
- SKU in Shortage
- Max Stockroom Min Display Max Display
- Future Promotions Maturity to EOL Recent Item Launch New SKU
- Shortage (Current) Overstock (Current) No Replenishment
- No Replenishment Method

Manage Alert Parameters Workspace, Steps, and Views

The Manage Alert Parameters workspace allows you to maintain the description and type of each alert and review the alerts that have been triggered. You can also maintain the alert parameters in this workspace such as the Replenishment Watch-List.

The following table lists the workspaces, steps, and views of the Manage Alert Parameters task.

Table 13-1 Manage Alert Parameters Workspace, Steps, and Views

Workspace	Steps	Tab	Views
Manage Alert Parameters Workspace	Label & Review Step	Label & Review	Label & Review View



Table 13-1 (Cont.) Manage Alert Parameters Workspace, Steps, and Views


Workspace	Steps	Tab	Views
	Alert Parameters Step	Item-Location	Item-Location Alert Parameters View
		Parent- Location	Parent-Location Alert Parameters View
		Class-Region	Class-Region Alert Parameters View
		Partition- Location	Partition-Location Alert Parameters View
		Global	Global Alert Parameters View
	Alert Details Step	Alert by Item	Item Alerts View
		Alert by Item- Location	Item-Location Alerts View
		Alert Details	Alert Details View

Manage Alert Parameters Workspace

To build the Manage Alert Parameters workspace, perform these steps:

1. From the left sidebar menu, click **Task Module** to view the available tasks.


Figure 13-1 Task Module



- 2. Click the IPO Administration activity and then click Lifecycle Allocation and Replenishment to access the available workspaces.
- 3. Click Manage Alert Parameters. The Manage Alert Parameters wizard opens.

You can open an existing workspace, but to create a new workspace, click Create New Workspace.

Figure 13-2 Create New Workspace



5. Enter a name for your new workspace in the label text box and click **OK**.



6. The Workspace wizard opens. Select the alerts you want to work with and click Next.





Figure 13-3 Workspace Wizard: Select Alerts

The Workspace wizard opens. Select the products you want to work with and click Next.





8. Select the locations you want to work with and click Finish.

Location

Levels & Positions

Company

Level

Level

Company

AK

Catalog

Chain

Chain

Channel

Franchise

Franchise

Great Lakes Region

Great Pains

Guif States

HI

Mid-Attantic

Mississippi Valley

Mobile

Mobile

None


Padific Northwest

Padific Southwest

Figure 13-5 Workspace Wizard: Select Location

9. The wizard notifies you that your workspace is being prepared. Successful workspaces are available from the Dashboard.

Figure 13-6 Successful Workspace Build: Manage Alert Parameters



Label & Review Step


This step contains the Label & Review View.

Label & Review View



The **Label & Review View**, under the **Label & Review tab**, allows you to set the alert as a critical or non-critical alert. Additionally, you can set a description for the alert and review alert details and hit counts per alert.

Figure 13-7 Label & Review View



Label & Review - Default Profile Measures

The Label & Review view contains the following measures.

Alert Description

This is an editable measure to define an alternative description for the alert. This Alert Description can be set as a Visible Attribute for the Alert hierarchy in all workspaces where the hierarchy is available.

Alert Short Descr. (Description)

This is an editable measure to define an alternative shortened description for the alert. This is the description that is displayed to you in the Replenishment workspaces and when reviewing the alerts.

Critical Alert

This is an editable measure to set an alert as a critical alert type. When selected, the alert is set as critical. Otherwise, the alert is non-critical.

Enable RTA

This is an editable measure to use the alert as an RPAS Real Time Alert (RTA) available in the workspace - **PROD Highlighted Alert** and **PROD-LOC Highlighted Alert**. If defined as RTA, the RPAS alert navigation mode for the RTA mentioned previously is possible and is based on the alert hits for the selected alert.



Note:

When multiple alerts are selected for the Enable RTA, the RPAS Real Time Alert (RTA) considers all alerts that are enabled as RTA within the generic RTA available in the workspace. There is a measure available for each RTA to indicate what alerts are being captured by RTA.

PROD Highlighted Alert

When using the alert navigation mode, the alert uses the view PROD Alerts to navigate and the measure PROD Alerts displays with the list of alerts with hits for the product, PROD-LOC Highlighted Alert. When using alert navigation mode, this alert uses the view, PROD-LOC Alerts to navigate and the measure PROD-LOC Alerts displays with the list of alerts with hits for the product and location.

Alert Type

This is a calculated measure that indicates the alert type. The alert type is provided in the Alert hierarchy. By default, alerts are a Replenishment Alert Type.

Alert Priority

This is a calculated measure that indicates the priority of the alert. The alert priority is provided in the Alert hierarchy.

Alert Class

This is a calculated measure that indicates the alert class. The alert class is provided in the Alert hierarchy.

Alert PROD-LOC Count

This is a calculated measure that indicates the total number of products and locations with hits for the selected alert. For example, for the Shortage alert, the count represents the total number of products and locations with a stock shortage.

Alert PROD-LOC %

This is a calculated measure that indicates in percentage how much the alerted product and location represent in the total number of the assorted products and locations.

$$100 * \frac{PROD - LOCCount}{AssortedPROD - LOCCount}$$

Alert To-Be-Rev PROD-LOC Count

This is a calculated measure that indicates the total number of products and locations with alert hits, out of the Alert PROD-LOC Count, that still need to be reviewed by you.

Alert To-Be-Rev PROD-LOC %



This is a calculated measure that indicates in percentages how much the alerted products and locations have yet to be reviewed and represents the total of the assorted products and locations.

$$100 * AlertTo - Be - RevPROD - LOCCount$$

$$AssortedPROD - LOCCount$$

Alert VAR-LOC Count

This is a calculated measure that indicates the total number of variant and location with hits for the selected alert.

Alert To-Be-Rev VAR-LOC Count

This is a calculated measure that indicates the total number of variant and location with alert hits, out of the Alert VAR-LOC Count, that still need to be reviewed by you.

Alert VAR Count

This is a calculated measure that indicates the total number of variants with hits for the selected alert. For example, for a Shortage alert, the count represents the total number of variant with stock shortage (if it has a shortage in at least one location, then it counts).

Alert To-Be-Rev VAR Count

This is a calculated measure that indicates the total number of variants with alert hits, out of the Alert VAR Count, that still need to be reviewed by you.

Alert LOC Count

This is a calculated measure that indicates the total number of locations with hits for the selected alert. For example, for a Shortage alert, the count represents the total number of locations with a stock shortage (if it has a shortage in at least one assorted product, then it counts).

Alert To-Be-Rev LOC Count

This is a calculated measure that indicates the total number of locations with alert hits, out of the Alert LOC Count, that still need to be reviewed by you.

Alert Parameters Step

In this step you can set up and review the alert parameters. This step contains the following views:

- Item-Location Alert Parameters View
- Parent-Location Alert Parameters View




- Class-Region Alert Parameters View
- Partition-Location Alert Parameters View

Item-Location Alert Parameters View

The Item-Location Alert Parameters View, under the Item-Location tab, allows you to review and set up the replenishment watch list alert for the product-location combinations.

Figure 13-8 Item-Location Alert Parameters View



Item-Location Alert Parameters - Default Profile Measures

The Item-Location Alert Parameters view contains the following measure.

Repl Watch List


This is an editable measure used to indicate the product-location combinations that should be included or removed from the replenishment watch list. This information is used by the Repl Watch List alert to notify you of the product-location if it generates orders. If the measure is selected, it means that the product-location combination is included in the watch list. Otherwise, the product-location combination is excluded from the watch list.

Parent-Location Alert Parameters View

The Parent-Location Alert Parameters View, under the Parent-Location tab, allows you to review and set up the forecast watch list for the parent-location combinations.



Figure 13-9 Parent-Location Alert Parameters View



Parent-Location Alert Parameters - Default Profile Measures

The Parent-Location Alert Parameters view contains the following measure.


Fcst Watch List

The Forecast Watch List is an editable measure used to indicate the product-location combinations that should be included or removed from the forecast watch list. This information is used by the Forecast Watch List alert to notify you of the product-location if they generate orders. If the measure is selected, it means that the product-location combination is included in the watch list. Otherwise, the product-location combination is excluded from the watch list.

Class-Region Alert Parameters View

The Class-Region Alert Parameters View, under the Class-Region tab, allows you to review and set up the thresholds to be used by the stock alerts. You can set up thresholds in both percentage and units. These values are considered when triggering the shortage and overstock alerts.

Figure 13-10 Class-Region Alert Parameters View





Class-Region Alert Parameters - Default Profile Measures

The Class-Region Alert Parameters view contains the following measures.

Shortage (Current) Threshold %

This is an editable measure used to define the threshold in percentage to be considered by the stock shortage alert calculations.

Shortage (Current) Threshold Units

This is an editable measure used to define the threshold in units to be considered by the stock shortage alert calculations.

Overstock (Current) Threshold %

This is an editable measure used to define the threshold in percentage to be considered by the overstock alert calculations.


Overstock (Current) Threshold Units

This is an editable measure used to define the threshold in units to be considered by the overstock alert calculations.

Partition-Location Alert Parameters View

The Partition-Location Alert Parameter View, under the Partition-Location tab, allows you to set up and review the parameters to be used by the min display, max display, and max stockroom thresholds.

Figure 13-11 Partition-Location Alert Parameters View



Partition-Location Alert Parameters - Default Profile Measures

The Partition-Location Alert Parameters view contains the following measures.

Min Display Space Count



This is an editable measure used to enter the minimum amount of products, for the merchandise level, that should be in the display at the location. This value is then used by the alerts to alert you if locations are not reaching their minimum display for certain merchandise.

Max Display Space Count

This is an editable measure used to enter the maximum amount of products, for the merchandise level, that can be in the display at the location. This value is then used by the alerts to alert you if locations are exceeding their maximum display for certain merchandise.

Max Stockroom Space

This is an editable measure used to enter the maximum inventory units, for the merchandise level, that can be stocked at the location. This value is then used by the alerts to alert you if locations are reaching or exceeding their maximum stock capacity for certain merchandise.

Global Alert Parameters View

The **Global Alert Parameters View**, under the **Global tab** allows you to review and set up all alert measure parameters that have no dimension attached, however, this function is no longer available and has been deprecated in this release.




Figure 13-12 Global Alert Parameters View

Alert Details Step

In this step, you can review the alert hits by product and by product and location. This step contains these views:

- Item-Alerts-View
- Item-Location-Alerts-View
- Alert-Details-View




Item Alerts View

The **Item Alerts View**, under the **Alert by Item tab**, allows you to review at the product level what alerts are being triggered for each product. The alert short description is used to display to you the alerts being triggered.

The navigation of this view is very conveniently driven by the real-time alerts or workspace alerts.





Item Alerts View - Default Profile Measures

The Item Alerts view contains the following measures.

PROD Alerts

This is a calculated measure that contains the alert that was triggered for the product. It uses the alert short description to display the triggered alert. If multiple alerts are triggered for the same product then this measure displays all the alerts triggered.



If no short description is provided in the Label & Review view for the alert, then the alert does not display in this measure. Because the alert short description is empty, you are unable to see the alert even if it is triggered.

PROD Real Time Alert

This is a calculated measure used to identify the product with triggered alerts where the option Real Time Alert (RTA) is enabled in the Label & Review view. When the alert has the option RTA active, this measure is populated with the keyword highlighted to identify the products that should be considered by the RTA. If the RTA is unavailable for the alert, this measure is empty.



VAR Real Time Alert

This is a calculated measure used to identify the product at the variant level with triggered alerts where the option Real Time Alert (RTA) is enabled in the Label & Review view. When the alert has the option RTA active, this measure is populated with the keyword highlighted to identify the products that should be considered by RTA. If the RTA is unavailable, this measure is empty.




When the view is not displaying the variant level or higher, this measure displays "-" to indicate you that the measure is not available at that level. You will need to modify the base intersection level displayed to view the value.

Item-Location Alerts View

The Item-Location Alerts View, under the Alert by Item-Location tab, allows you to review at the product and location levels what alerts are being triggered for that combination. The alert short description is the one used to display to you what alert is being triggered. The navigation of this view is conveniently driven by the real-time alerts or workspace alerts.

Figure 13-14 Item-Location Alerts View



Item-Location Alerts - Default Profile Measures

The Item-Location Alerts view contains the following measures.

Revwd PROD - LOC

This is an editable measure used to indicate that the product-location combination has been reviewed. When selected, IPOCS-Lifecycle Allocation and Replenishment assumes the combination as reviewed. Otherwise, it assumes the combination is still to be reviewed.

VAR-LOC Real Time Alert



This is a calculated measure used to identify the variant-location combination with triggered alerts where the option Real Time Alert (RTA) is enabled in the Label & Review view. When the alert has the option RTA active, this measure is populated with the keyword highlighted to identify the variant-location combinations that should be considered by the RTA. If the RTA is unavailable for the alert, this measure is empty.

PROD-LOC Real Time Alert

This is a calculated measure used to identify the product-location combination with triggered alerts where the option Real Time Alert (RTA) is enabled in the Label & Review view. When the alert has the option RTA active, this measure is populated with the keyword highlighted to identify the product-location combinations that should be considered by the RTA. If the RTA is unavailable for the alert, this measure is empty.

PROD-LOC Alerts

This is a calculated measure that contains the alert that was triggered for the product-location combination. It uses the alert short description to display the triggered alert. If multiple alerts are triggered for the same product-location combination, this measure displays all of the triggered alerts.

Alert Details View

The **Alert Details View**, under the **Alert Details tab**, allows you to review per alert what product-location combinations are triggered. You can also check what product-locations are still pending review.




Figure 13-15 Alert Details View

Alert Details View - Default Profile Measures

The Alert Details view contains the following measures.

Alert PROD-LOC

This is a calculated measure that indicates what product-locations have been triggered for the alert.

Alert To-Be-Rev PROD-LOC



This is a calculated measure that indicates what product-locations have been triggered by an alert and still need to be reviewed by you. When selected, you still need to review the product-location combination. When clear, you have reviewed the product-location combination already or the product-location combination has not been triggered by an alert.



14

Manage Scaling Parameters

This chapter describes the functionality that allows users to manage scaling parameters.

Manage Scaling Parameters Workspace, Steps, and Views

The Manage Scaling Parameters workspace allows you to adjust or expand inventory levels to meet changing demands or business needs.

The following table lists the workspaces, steps, and views of the Manage Scaling Parameters task.

Table 14-1 Manage Scaling Parameters Workspace, Steps, and Views


Workspace	Steps	Tab	Views
Manage Scaling	Manage Scaling	Manage Scaling	Constraint Groups View
Parameters Workspace Parameters Step	Parameters	Constraints View	
			Constraints PROD-LOC Association View

Manage Scaling Parameters Workspace

To build the Manage Scaling Parameters workspace, perform these steps:


1. From the left sidebar menu, click **Task Module** to view the available tasks.

Figure 14-1 Task Module



- 2. Click the IPO Administration activity and then click Lifecycle Allocation and Replenishment to access the available workspaces.
- 3. Click Manage Scaling Parameters. The Manage Scaling Parameters wizard opens.
- **4.** You can open an existing workspace, but to create a new workspace, click **Create New Workspace**.

Figure 14-2 Create New Workspace






5. Enter a name for your new workspace in the label text box and click **OK**.




6. The Workspace wizard opens. Select the databags you want to work with and click Next.

Figure 14-3 Workspace Wizard: Select Databags




7. The Workspace wizard opens. Select the products you want to work with and click Next.

Figure 14-4 Workspace Wizard: Select Product




8. Select the locations you want to work with and click **Finish**.

Figure 14-5 Workspace Wizard: Select Location



9. The wizard notifies you that your workspace is being prepared. Successful workspaces are available from the Dashboard.

Figure 14-6 Successful Workspace Build: Manage Scaling Parameters



Manage Scaling Parameters Step

The Manage Scaling Parameters workspace consists of these views:

- · Constraint Groups View
- Constraints View
- Constraint PROD-LOC Association View

Constraint Groups View

The **Constraint Groups View**, under the **Scaling tab**, allows you to define a constraint group to be set up to configure constraints to be applied to product and location combinations.






Figure 14-7 Constraint Groups View

Constraint Groups View - Default Profile Measures

The default measure profile available in the Constraint Groups view contains the following measures.

Cstr. Group Enabled

Constraint Group Enabled is an editable measure to enable or disable a constraint group. Each row (or list) represents a different constraint group.

Cstr. Group Descr.

Constraint Group Description is an editable measure to enter a user-defined constraint group description.

Cstr. Active Count

Constraint Active Count is a calculated measure to display the total number of constraints in use (active) for the constraint group.

Cstr. Active PROD-LOC Count

Constraint Active PROD-LOC Count is a calculated measure that displays the total number of product and location combinations that are associated with an active constraints within the constraint group. For example, if the constraint group has two active constraints being applied to product and location combinations then this value is the total of both.

Cstr. Object User Filter

Constraint Object User Filter is an editable measure to select the constraint group to filter the views within the Allocation and Replenishment workspace. When selected, and after the workspace calculation (either **Calculate** or **F9**) is run, the views in the Allocation and




Replenishment workspace are filtered based on the product and locations associated with active constraints within the selected constraint groups.

Constraints View

The **Constraints View**, under the **Scaling tab**, allows you to define the constraints, within a constraint group, that is used by the scaling process. This is the view where the constraint parameters are set (for example, a minimum order quantity of 500 units).

Figure 14-8 Constraints View



Constraints View - Default Profile Measures

The default measure profile available in the Constraints view contains the following measures.

Cstr. Active

Constraint Active is an editable measure to enable or disable a constraint within the constraint group. Each row (or list) represents a different constraint.

Cstr. Descr.

Constraint Description is an editable measure to enter a user-defined constraint description.

Cstr. Type

Constraint Type is an editable measure to select the type of constraint being defined. Valid values are:

- Min
 - When the constraint is for minimum order quantity.
- Multiple

When the constraint is for multiple order quantity.

Cstr. Descr.



Constraint Description is an editable measure to enter the value for the constraint related to the selected type (Cstr. Type). For example, if the constraint is for a minimum order quantity, then this measure holds the number of units (for example, 500).

Cstr. Rounding Thres. %

Constraint Rounding Threshold Percentage is an editable measure to enter the threshold percentage to be used in the scaling calculation to know if the suggested order is either scaled up or scaled down.

Cstr. Active PROD-LOC Count

Constraint Active Product-Location Count is a calculated measure to display the total number of product and location combinations that are associated with the constraint.

Cstr. Object User Filter

Constraint Object User Filter is an editable measure to select the constraint to filter the views within the Allocation and Replenishment workspace. When selected, and after the workspace calculation (either **Calculate** or **F9**) is run, the views in the Allocation and Replenishment workspace are filtered based on the product and locations associated within the selected constraints.

Constr. Order

Constraint Order is a calculated measure to display the total order, in the selected Unit of Measurement (UOM), for the items associated with the constraint. By default IPOCS-Lifecycle Allocation and Replenishment uses units and the value displayed is the suggested replenishment units calculated by IPOCS-Lifecycle Allocation and Replenishment. When you select a different UOM, then the UOM conversion factor is used to convert the suggested replenishment units into the selected UOM.

Constr. Scaled Order

Constraint Scaled Order is a calculated measure to display the total order after the scaling is run for the selected UOM and for the items associated with the constraint. By default, IPOCS-Lifecycle Allocation and Replenishment uses units and the value displayed is the result of the scaling applied to the suggested replenishment units calculated by IPOCS-Lifecycle Allocation and Replenishment. When you select a different UOM, then the UOM conversion factor is used to convert into the selected UOM the result of the scaling applied to the suggested replenishment units.

Constraints PROD-LOC Association View

The **Constraints PROD-LOC Association View**, under the **Scaling tab**, allows you to select the product and location combinations to be included in each constraint that is used by the scaling process.



Figure 14-9 Constraints PROD-LOC Association View

Constraints PROD-LOC Association View - Default Profile Measures

The default measure profile available in the Constraints PROD-LOC Association view contains the following measure.

Cstr. Active PROD-LOC

Constraint Active Product-Location is an editable measure to associate a product and location combination to the constraint. When selected, the product and location combination is associated with the constraint and is used by the scaling process. When not selected, the product and location combination is not associated.



15

Manage Databags

This chapter describes the Databag concept and the functionality that allow users to create and update Databags.

Databag Concept

A Databag is a collection of Product, Location, Source Location, Attributes, and Alert positions that are used to facilitate the selection process when using the Replenishment Admin workspaces. The databag is the scope of a user's work. When working in the replenishment workspace, you only need to select the databag that you want to work with and the wizard process loads automatically all products, locations, attributes, and alerts linked to the selected databag. This way you do not need to go through the selection process every time. You only need to create a new Replenishment Admin workspace.

The following image illustrates different databags with different scopes and users. Each databag has its own scope with the assigned products, locations, calendar, attributes, and alerts.






Figure 15-1 Different Databags with Different Scopes and Users

Additionally, a databag scope can also be defined using attribute-based values to identify what positions should be part of the databag scope. The following images illustrate two databags scope by attribute conditions.


Figure 15-2 Databag Containing Only Alerted Products and Locations





Databag scope based on the Lifecycle value.

Figure 15-3 Databag Scope Based on the Lifecycle Value



Manage Databags Workspace, Steps, and Views

The following table lists the workspaces, steps, and views of the Manage Databag task.

Table 15-1 Manage Databags Workspace, Steps, and Views

Workspace	Steps	Tab	Views
Databag Scope Workspace	Setup	Setup	Setup View
		Product Group Scope	Product Group ScopeView
		Location Group Scope	Location Group Scope View
		Source Group Scope	Source Group Scope View
		Alert Scope	Alert Scope View
		Attributes Scope	Attributes Scope View
Databag Review Workspace	Enable & Publish	Enable & Setup	Enable & Setup View
		Filter Conditions	Filter Conditions View
		Today & Parameters	Today & Parameters View

Table 15-1 (Cont.) Manage Databags Workspace, Steps, and Views


Workspace	Steps	Tab	Views
	Review Databag Details	Products	Associated PROD View
		Locations	Associated LOC View
		Sources	Associated SLOC View
		Weeks	Associated WEEK View
		Alerts	Associated Alerts View
		Attributes	Associated Attributes View
		Product- Locations	Associated PROD- LOC View
	Review Attributes & Alerts	Product	PROD Attributes View
		Location	LOC Attributes
		Product- Location	PROD-LOC Attributes
		Alerts	PROD-LOC Alerts

Databag Scope and Review Workspaces

To build the Databag Scope or Databag Review workspaces, perform these steps:

1. From the left sidebar menu, click the **Task Module** to view the available tasks.


Figure 15-4 Task Module



2. Click the IPO Administration activity and then click Lifecycle Allocation and Replenishment to access the available workspaces.

3. Click either Databag Scope or Databag Review. The Databags wizard opens.


Figure 15-5 Databags Wizard



You can open an existing workspace, but to create a new workspace, click Create New Workspace.



Figure 15-6 Create New Workspace



5. Enter a name for your new workspace in the label text box and click **OK**.

Figure 15-7 Enter Workspace Label



The Workspace wizard opens. Select the databags you want to work with and click Next.






Figure 15-8 Workspace Wizard: Select Databags

7. Select the products you want to work with and click **Next**.





8. Select the locations you want to work with and click **Next**.







Figure 15-10 Workspace Wizard: Select Location


9. Select the source locations you want to work with and click Finish.





10. The wizard notifies you that your workspace is being prepared. Successful workspaces are available from the Dashboard.

Figure 15-12 Successful Workspace Build: Manage Databags



Setup Step


This step contains these views:

- Setup View
- Product Group Scope View
- Location Group Scope View
- Source Group Scope View
- Alerts Scope View
- Attributes Scope View

Setup View

The **Setup View**, under the **Setup tab**, allows you to set a meaningful label to the databag that can be used as dimension attribute in the databag hierarchy.

Figure 15-13 Setup View



Setup View - Default Profile Measures

The Setup view contains the following measures.

Databag User Descr.




Databag User Description is an editable measure used to modify the description of a databag. This databag description can be set as a Visible Attribute for the databag hierarchy in any other workspace.

Product Group Scope View

The **Product Group Scope View**, under the **Product Scope tab**, allows you to select specific products to include in the scope of the databag if the databag level defined in the **Enable & Setup view** is either Local or All Prod.

Figure 15-14 Product Group Scope View



Product Group Scope View - Default Profile Measures

The Product Group Scope view contains the following measure.

PROD Group Scope


Product Group Scope is a checkbox measure used to select which products should be assigned to the databag.

Location Group Scope View

The Location Group Scope View, under the Location Group Scope tab, allows you to select specific locations to include in the scope of the databag if the databag level is defined in the Enable & Setup view as either Local or All Loc.



Figure 15-15 Location Group Scope View



Location Group Scope View - Default Profile Measures

The Location Group Scope view contains the following measure.


LOC Group Scope

Location Group Scope is a checkbox measure used to select which locations should be assigned to the databag.

Source Group Scope View

The **Source Group Scope View**, under the **Source Group Scope tab**, allows you to select specific source locations, at the location group level, to be included in the scope of the databag.

Figure 15-16 Source Group Scope View





Source Group Scope View - Default Profile Measures

The Source Group Scope view contains the following measure.


SLOC Group Scope

Source Location Group Scope is a checkbox measure used to select which source locations should be assigned to the databag.

Alerts Scope View

The **Alerts Scope View**, under the **Alerts Scope tab**, allows you to select specific alerts to be included in the scope of the databag.

Figure 15-17 Alerts Scope View



Alerts Scope View - Default Profile Measures

The Alerts Scope view contains the following measure.

Alert Scope

This measure allows you to select the alerts to be included in the databag scope and for which purpose they are used.

The valid values are:

•

This empty value indicates that the alert should not be included in the databag.



View

This value indicates that the alert should be included in the databag. The alert is then available in the Replenishment workspaces to aid in analysis and navigation. .

Filter

This value indicates that the alert should be included in the databag scope and the alert is then available in the Replenishment workspace. Additionally, when the Filter values are selected, the scope of the databag is recalculated based on the product and alerts that match the alert.

Note:

For example, if the alert **New SKU** is included in the databag scope and set as a Filter value, the databag is recalculated and only the products associated with the **New SKU** alert, within the defined product scope, are included in the databag. The remaining items are filtered out.

Attributes Scope View

The **Attributes Scope View**, under the **Attributes Scope tab**, allows you to select all or any specific product, location, or product-location attributes to be included in the scope of the databag.



Attributes Scope Databag 品 Measure (Default) Business Rule Attribute 🖁 ATTR Scope Databag 01.01 🗘 Databag 01.02 Databag Business Rule Attribute → all [Business Rule Attribute] \checkmark ~ Assortment End Date ~ ~ Assortment Start Date \checkmark Brand **Brand Tier** \checkmark \checkmark Class \checkmark Collar ~ Color \checkmark \checkmark ~ Department HighPriority Item 01 ~ Historic Average Sales 01 \checkmark Historic Sales Coefficient Of Variation 01 Item Status ~ \checkmark Life Cycle Phase \checkmark \sim

Figure 15-18 Attributes Scope View

Attributes Scope View - Default Profile Measures

The Attributes Scope view contains the following measure.

ATTR Scope

Attribute Scope allows you to select which attributes should be included in the databag scope.



By default, if none of the attributes are selected for the databag then the calculation assumes that all attributes are available for the databag. If you select at least one attribute, then only the selected attributes are available for the databag.

Enable & Publish Step




This step contains these views:

- Enable & Setup View
- Filter Conditions View
- Today & Parameters View

Enable & Setup View: Databag Review

The **Enable & Setup View**, under the **Enable & Setup tab**, allows you to select specific alerts to view databag statistics and enable or disable the databag. You can also set a meaningful label to the databag that can be used as a dimension attribute in the databag hierarchy.

Figure 15-19 Enable & Setup View: Databag Review



Enable & Setup View: Databag Review - Default Profile Measures

The Enable & Setup view contains the following measures.

Databag Manual Filter

This is a checkbox measure that you can select or clear to filter all views of the workspace by the databags that are selected as manual filters. When selected, only the selected databags are available. In order to see all databags, no databag should be selected (This is the default behavior).

Databag Type

This measure allows you to enable or disable the databag. The valid values for this measure are:

- **Replenishment**: The databag is used to open a Replenishment workspaces.
- Off: The databag is unavailable.

Databag Level

This measure allows you to choose the level of PROD-LOC at which the databag is defined. The valid values for this measure are:



- **Local**: The Product and Location scope of this databag is based on the set up of the scope defined in the Product Group Scope and Location Group Scope views.
- All Prod: The Product scope of this databag is all Products and it ignores the set up of the scope defined in the Product Group Scope view. While the Location is based on the set up of the scope defined in the Location Group Scope view.
- **All Loc**: The Product scope of this databag is based on the set up of the scope defined in the Product Group Scope view. While the Location scope is all Location, it ignores the set up of the scope defined in the Location Group Scope view.
- Global: The Product and Location scope is based on all Products and all Locations and it ignores the set up of the scopes defined in the Product Group Scope and Location Group Scope views.

Databag User Descr.

Databag User Description is an editable measure used to modify the description of a databag. This databag description can be set as a Visible Attribute for databag hierarchy in any other workspace.

Databag Mask

This measure allows you to select additional filters for the Product and Location scope. The valid values for this measure are:

- All: The Product and Location scope is based on the scope defined by you in the Product Group Scope and Location Group Scope views. No additional filtering is applied.
- Ass. Valid: The Product and Location scopes defined by you in the Product Group Scope and Location Group Scope views are filtered out if the product and location combination is not assorted. This way, only valid assortment combinations is part of the databag.
- Lfc. Valid: The Product and Location scopes defined by you in the Product Group Scope and Location Group Scope views are filtered out if the product and location combination does not have a valid lifecycle. For example, typically, warehouses are not assorted. Therefore they are excluded by the Assorted Valid mask. However, as warehouses source assorted products for one or more stores, then they have a valid lifecycle for the products.

Matching PROD-LOC Cond

Matching Product-Location Condition is a calculated measure that indicates the filter condition defined in the Filter Conditions view. If there is no condition defined, it displays All. Otherwise, it displays the string with the conditions defined in the Filter Conditions view.

PROD Scope Count

Product Scope Count is a calculated measure that indicates the number of products based on the product groups selected in the Product Group Scope view and the databag mask value.

PROD Assoc. Count

Product Association Count is a calculated measure that indicates the number of products based on the product groups selected in the Product Group Scope view with the filter conditions applied and the databag mask value.

PROD Assoc. %



Product Association Percentage is a calculated measure that indicates the percentage of products that are being considered for the databag. It is calculated as:

Figure 15-20 Calculation

$$100 \frac{PRODAssoc.Count}{PRODScopeCount}$$

LOC Scope Count

Location Scope Count is a calculated measure that indicates the number of locations based on the location groups selected in the Location Group Scope view and the databag mask value.

LOC Assoc. Count

Location Association Count is a calculated measure that indicates the number of locations based on the location groups selected in the Location Group Scope view with the filter conditions applied and the databag mask value.

LOC Assoc. %

Location Association Percentage is a calculated measure that indicates the percentage of locations that are being considered for the databag. It is calculated as:

Figure 15-21 Calculation

$$100 \frac{LOCAssoc.Count}{LOCScopeCount}$$

SLOC Assoc. Count

Source Location Association Count is a calculated measure that indicates the number of source locations based on the location groups selected in the Source Location Group Scope view with the filter conditions applied and the databag mask value.

Past Dur Weeks (weeks)

Past Duration Weeks is an editable measure used to input the number of weeks in the past that should be included in the databag scope.

Future Dur Weeks (weeks)

Future Duration Weeks is an editable measure used to input the number of weeks in the future that should be included in the databag scope.

WEEK Assoc. Count

WEEK Association Count is a calculated measure that indicates the number of weeks included in the databag scope.



Alerts Assoc. Count

Alerts Association Count is a calculated measure that indicates the number of alerts included in the databag scope.

ATTR Assoc. Count

ATTRIBUTE Association Count is a calculated measure that indicates the number of attributes (product, location or/and product-location attributes) included in the databag scope.

Last Databag Publish User ID

This is a calculated measure that audits the databag **Publish Data** button. It is populated with the user ID that last ran the **Publish Data** button.

Last Databag Publish Date

This is a calculated measure that audits the **Publish Data** button. It is populated with the date and time that last ran the **Publish Data** button.

Filter Conditions View

This view allows you to define the conditions for the rules based in product, location, and product-location attributes. A rule condition is what allows the engine to find the product and location combinations where the rule is applicable.

Figure 15-22 Filter Conditions View



Filter Conditions View - Default Profile Measures

The Filter Conditions view contains the following measures.

Condition Attribute

The Condition Attribute measure allows you to select the attribute for the condition, The attributes for the rules are assigned in the Attribute Review workspace.

Within Cond Op

The Within Cond Op measure allows you to specify the operator to be used inside the condition.



Table 15-2 Within Cond Op Measure Available Operators

Possible Operators	Descriptions	Example
==	Checks if the attribute value is equal with the Condition Value	brand == Private Label
!=	Checks if the attribute value is different from the Condition Value	average sales != 0
>	Checks if the attribute value is larger than the Condition Value	Average sales >5
>=	Checks if the attribute value is larger or equal to the Condition Value	
<	Checks if the attribute value is less than the Condition Value	Standard deviation of sales <6
<=	Checks if the attribute value is less or equal to the Condition Value	
contain		
not contain		
match		
not match		

Cond Value

The Cond Value measure is used when the type of the attribute is numeric. Example: average sales > 10

Cond Value String

The Cond Value String measure is used when the type of the attribute is a string. Example: brand == Private Label

Cond Value Measure

The value of the Cond Value measure is a measure name, which is populated by an expression that let's you refine the condition value. For instance private label versus non-private label.

This measure is used when you want to refine the condition value.

For instance, for the coffee items, except Private Label, you want to assign items to the rule that sell more than 50 per week. For Private Label items you may want the value to be 100. You need to populate your Condition measure with a value of 100 for all Private Label items, and the rest of the coffee items with 50.

Cond Value Date

The Cond Value Date measure is used when the type of the attribute is a date. Example: $today \ge 02/30/2024$ "

Between Cond Op

Within a rule there can be multiple conditions and also multiple condition groups. This is specified in the Cond Group measure. Conditions with the same Cond Group value belong to the same group.



For example, if a rule has four conditions, Conditions 1 and 2 can belong to Condition group 1, and Conditions 3 and 4 can belong to the Condition group 2. Also, the Cond Order measure gives the ranking of the conditions inside the group.

The following table is an assumed use case:

Table 15-3 Between Cond Op Assumed Use Case

Condition	Between Con Op	Cond Order	Cond Group
Condition 1	AND	1	1
Condition 2	OR	2	1
Condition 3	OR	3	2
Condition 4		4	2

The value for the Between Cond Op can be the logical operators AND or OR.

The conditions are evaluated first inside a condition group and then between groups. In the previous case, the resulting condition is:

(Condition 1 AND Condition 2) OR (Condition 3 OR Condition 4)

Here is an example where all conditions belong to the same condition group:

Table 15-4 Example: All Conditions Belong to the Same Condition Group

Condition	Between Con Op	Cond Order	Cond Group
Condition 1	AND	1	1
Condition 2	OR	2	1
Condition 3	OR	3	1
Condition 4		4	1

The resulting condition for the rule is given by:

Condition 1 AND Condition 2 OR Condition 3 OR Condition 4

Note that the conditions are evaluated in the order given by the values in the Cond Order measure.

Cond Order

The Cond Order measure displays the order in which conditions are evaluated, wither independently or inside a condition group.

Cond Group

The Cond Group measure allows you to group conditions. This is useful when you want to evaluate conditions in a two-step process. First, the conditions are evaluated inside groups. In the second step, the group results are evaluated .

Validation Result

The Validation Result measure displays the condition expressions that are validated.

Invalid Flag

The Invalid Flag measure indicates if a condition is invalid.




Valid Flag

The Valid Flag measure indicates if a condition is valid.

Today & Parameters View

The **Today & Parameters View**, under the **Today & Parameters tab**, allows you to review the system date and to maintain the maximum number of positions that can be loaded into the condition value measures in the Filter Condition view.

Figure 15-23 Today & Parameters View



Today & Parameters View - Default Profile Measures

The Today & Parameters view contains the following measure.

Max Picklist Values

Maximum Picklist Values allows you to set the maximum number of values that can be loaded into the condition values measure (picklist measures) in the Filter Condition view. The default value is 500.

Review Databags Details Step

This step provides you with all the databag details as a result of the databag set up from the Enable & Publish step. This step contains these views:

- Associated PROD View
- Associated LOC View
- Associated SLOC View
- Associated WEEK View
- Associated Alerts View
- Associated Attributes View




Associated PROD-LOC View

Associated PROD View

The **Associated PROD View** ,under the **Products tab** , allows you to review the products that are in scope and associated with the databag based on the databag set up.

Figure 15-24 Associated PROD View



Associated PROD View - Default Profile Measures

The Associated PROD view contains the following measures.

PROD Scope

Product Scope indicates if a product is in the databag scope. When selected, the product is in the databag scope. This indicates that the product met the filter conditions defined in the previous step. When clear, the product is not in the databag scope.

PROD Assoc.


Product Associated indicates if a product is associated with the databag. When selected, the product is associated with the databag. This indicates that the product was evaluated within the databag but does not meet the conditions of the filter evaluation. When clear, the product is not associated with the databag.

Associated LOC View

The **Associated LOC View**, under the **Locations tab**, allows you to review the locations that are in scope and associated with the databag based on the databag set up.



Figure 15-25 Associated LOC View



Associated LOC View - Default Profile Measures

The Associated LOC view contains the following measures.

LOC Scope

Location Scope indicates if a location is in the databag scope. This indicates that the location met the filter conditions defined in the previous step. When selected, the location is in the databag scope. When clear, the location is not in the databag scope.

LOC Assoc.


Location Associated indicates if a location is associated with the databag. When selected, the location is associated with the databag. This indicates that the location was evaluated within the databag but does not meet the conditions of the filter evaluation. When clear, the location is not associated with the databag.

Associated SLOC View

The **Associated SLOC View**, under the **Sources tab**, allows you to review the source locations that are in scope and associated with the databag based on the databag set up.



Figure 15-26 Associated SLOC View



Associated SLOC View - Default Profile Measures

The Associated SLOC view contains the following measure.


SLOC Assoc.

Source Location Associated indicates if a source location is associated with the databag. When selected, the source location is associated with the databag. This indicates that the source location was evaluated within the databag but does not meet the conditions of the filter evaluation. When clear, the source location is not associated with the databag.

Associated WEEK View

The **Associated WEEK View**, under the **Weeks tab**, allows you to review the weeks that are associated with the databag based on the past and the future number of weeks entered in the databag set up.

Figure 15-27 Associated WEEK View





Associated WEEK View - Default Profile Measures

The Associated WEEK view contains the following measure.


WEEK Assoc.

WEEK Associated indicates if a week is associated with the databag. When selected, the week is associated with the databag. When clear, the week is not associated with the databag.

Associated Alerts View

The **Associated WEEK View**, under the **Alerts tab**, allows you to review the alerts that are associated with the databag based on the databag alert scope.

Figure 15-28 Associated Alerts View



Associated Alerts View - Default Profile Measures

The Associated Alerts view contains the following measure.

Alerts Assoc.


Alerts Associated indicates if an alert is associated with the databag. When selected, the alert is associated with the databag. When clear, the alert is not associated with the databag.

Associated Attributes View

The **Associated Attributes View**, under the **Attributes tab**, allows you to review the attributes associated with the databag based on the databag attributes scope.



Figure 15-29 Associated Attributes View



Associated Attributes View - Default Profile Measures

The Associated Attributes view contains the following measure.


ATTR Assoc.

Attribute Associated indicates if an attribute is associated with the databag. When selected, the attribute is associated with the databag. When clear, the attribute is not associated with the databag.

Associated PROD-LOC View

The **Associated PROD-LOC View**, under the **Product-Locations tab**, allows you to review product-location combinations that are associated with the databag based on the databag set up.

Figure 15-30 Associated PROD-LOC View





Associated PROD-LOC View - Default Profile Measures

The Associated PROD-LOC view contains the following measure.

PROD-LOC Assoc.

Product-Location Associated indicates if a product-location combination is associated with the databag. When selected, the product-location combination is associated with the databag. When clear, the product-location combination is not associated with the databag.

Review Attributes & Alerts Step


This step provides you with all the required views to review the product, location, and product-location attribute values. This step contains these views:

- PROD Attributes View
- LOC Attributes View
- PROD-LOC Attributes View
- PROD-LOC Alerts View

PROD Attributes View

The **PROD Attributes View**, under the **Product tab**, allows you to review the product attribute values.

Figure 15-31 PROD Attributes View



PROD Attributes View - Default Profile Measures

The PROD Attributes view contains the following measure.

Attribute Product Value


This measure displays the product attribute values.



LOC Attributes View

The **LOC Attributes View**, under the **Location tab**, allows you to review location attribute values.

Figure 15-32 LOC Attributes View



LOC Attributes View - Default Profile Measures

The LOC Attributes view contains the following measure.


Attribute Location Value

This measure displays the location attribute values.

PROD-LOC Attributes View

The **PROD-LOC Attributes View**, under the **Product-Location tab**, allows you to review product-location attribute values.

Figure 15-33 PROD-LOC Attributes View





PROD-LOC Attributes View - Default Profile Measures

The PROD-LOC Attributes view contains the following measure.


Attribute Prod-Loc Value

This measure displays the product-location attribute values.

PROD-LOC Alerts View

The **PROD-LOC Alerts View**, under the **Alerts tab**, allows you to review which alerts are assigned per product-location.

Figure 15-34 PROD-LOC Alerts View



PROD-LOC Alerts View - Default Profile Measures

The PROD-LOC Alerts view contains the following measure.

This measure displays the product-location attribute values.

Manage Databag Action Buttons

The Manage Databag workspace has the following action buttons available:

Calc Databags


Use the **Calculation Databags** action button to calculate the databag scope based on all the set up you created. The result is the Boolean measure that is used by the Replenishment workspace to load the correct scope of products, locations, source locations, attributes and alerts.

Publish Data

Use the **Publish Data** action button to commit the changes made in the Manage Databag workspace. It also saves the audit information of the update and commits the measures

Last Databag Publish User ID and **Last Databag Publish Date** based on who and when the Publish Data was last run.

Figure 15-35 Manage Databag Action Buttons





Manage Rule Groups

This chapter describes the rule groups concept and the functionality that allows you to create and update the rule groups.

About Rule Groups

A Rule Group is a collection of Product, Location, Source Location and Attribute positions that are used to facilitate your selection process when setting up the supply chain network and replenishment rules. The application works with two types of Rule Groups:

- Setup Rule Group
- Parameters Rule Group

While the Setup rule group is used to set up the supply chain network model (for example, bill of distribution, planning calendar, and so on.), the Parameter rule group is used to set up the replenishment methods and replenishment parameters (for example, target stock method with a re-order level of 50%). By default, IPOCS-Lifecycle Allocation and Replenishment should be configured with at least two rule groups containing all positions. One for Setup and one for Parameters.

Manage Rule Groups Workspace, Steps, and Views

The following table lists the workspaces, steps, and views for the Manage Rule Groups task.

Table 16-1 Manage Rule Groups Workspace, Steps, and Views


Workspace	Step	Tab	Views
Manage Rule Groups Workspace	Setup & Publish	Enable & Setup	Enable & Setup View
			Statistics View
			Today View
		Product Scope	Product Group Scope View
		Location Scope	Location Group Scope View
		Source Scope	Source Scope View
		Attribute Scope	Attribute Scope View

Manage Rule Groups Workspace

To build the Manage Rule Groups workspace, perform these steps:

1. From the left sidebar menu, click **Task Module** to view the available tasks.

Figure 16-1 Task Module



- 2. Click the IPO Administration activity and then click Lifecycle Allocation and Replenishment to access the available workspaces.
- 3. Click Manage Rule Groups. The Manage Rule Groups wizard opens.
- **4.** You can open an existing workspace, but to create a new workspace, click **Create New Workspace**.






Figure 16-2 Create New Workspace

5. Enter a name for your new workspace in the label text box and click **OK**.



Create New Workspace

6. The Workspace wizard opens. Select the rule groups you want to work with and click **Next**.

Cancel

Open in new tab

Open





Figure 16-3 Workspace Wizard: Select Rule Groups

The Workspace wizard opens. Select the products you want to work with and click Next.





8. Select the locations you want to work with and click **Next**.





Figure 16-5 Workspace Wizard: Select Location

9. Select the source locations you want to work with and click **Finish**.

Figure 16-6 Workspace Wizard: Select Source Location



10. The wizard notifies you that your workspace is being prepared. Successful workspaces are available from the Dashboard.

Last 7 days ast Edited 10/25/2023 reated 10/25/2023 Γ Edit Dashboard Databag Scope Initial Last Edited 3/31/2019 Created 9/19/2023 Ø All (6) Scheduled (3) In Progress (0) Completed (3) Databag Review Last 24 hours ▼ All Submitters ▼ All Task Types Initial Last Edited 3/31/2019 Created 9/19/2023 Ø Actions View Z Z Detach Muto-Refresh L Download Log Watch Live Log Download Rej MNG ASSRTMNT Description ✓ Status
 ○ Task Type
 ○ Submitter by Started/Schedured Completed
 ○ R Success WbBatch Build oci.admin 10/25/23, 2:... 10/25/23, 2:... -Ø Success WbBatch Build oci.admin 10/25/23, 2:... 10/25/23, 2:... - Manage Databage Inventory Planning Opti... RG

Figure 16-7 Successful Workspace Build: Manage Rule Groups

Setup & Publish Step


This step contains these views:

- Enable & Setup View: Rule Groups
- Statistics View
- Today View
- Product Group Scope View: Rule Groups
- Location Group Scope View: Rule Groups
- Source Scope View
- Attribute Scope View

Enable & Setup View: Rule Groups

The **Enable & Setup View**, under the **Enable & Setup tab**, allows you to review who published the rule groups and when they were published. Within this view, you can set up the rule group type and a user-friendly description for the rule group.

Figure 16-8 Enable & Setup View: Rule Groups





Enable & Setup View: Rule Groups - Default Profile Measures

The Enable & Setup view contains the following measures.

Rule Group Manual Filter

This is a checkbox measure that you can select or clear to filter all the views in the workspace by the rule groups selected as manual filters. Only the selected rule groups are available in the workspace. To see all rule groups, all of the rule groups should be cleared. (This is the default behavior).

Rule Group Type

This is a writeable measure used to define the rule group type. Valid values are:

- **Setup**: The rule group is enabled and its purpose is to be available in the Replenishment Supply Chain Network workspace to set up the supply chain network model.
- **Parameters**: The rule group is enabled and its purpose is to be available in the Replenishment Rules workspace to set up the replenishment method and parameters.
- _: Empty space indicates that the rule group is unavailable.

Rule Group User Descr.

Rule Group User Description is an editable measure used to define an alternative description of the rule group. This Rule Group User Description can be set as a Visible Attribute for the Rule Group hierarchy in all the workspaces where the hierarchy is available.

Last Rule Group Publish User ID

This is a calculated measure used to audit the rule group's **Publish Data** button. It is populated with the user ID that last ran the **Publish Data** button.

Last Rule Group Publish Date


This is a calculated measure used to audit the rule group's **Publish Data** button. It is populated with the date and time that last ran the **Publish Data** button.

Statistics View

The **Statistics View**, under the **Enable & Setup tab**, allows you to review how many products, locations, and source locations are in scope and associated with each of the Rule Groups.



Figure 16-9 Statistics View



Statistics View - Default Profile Measures

The Statistics view contains the following measures.

Rule Group Valid

This is a calculated measure that indicates if a rule group has a valid set up. It is selected when the set up is valid. It is clear when the set up is invalid. An example of an invalid set up is when the rule group is unavailable.

PROD Assoc. Count

The Product Association Count is a calculated measure that indicates the number of products associated with the rule group based on the product groups selected in the Product Group Scope view.

LOC Assoc. Count

The Location Association Count is a calculated measure that indicates the number of locations associated with the rule group based on the location groups selected in the Location Group Scope view.

SLOC Assoc. Count

The Source Location Association Count is a calculated measure that indicates the number of source locations associated with the rule group based on the source location groups selected in the Source Scope view.

Attribute Assoc. Count

The Attribute Association Count is a calculated measure that indicates the number of attributes associated with the rule group based on the attributes selected in the Attribute Scope view.

Week Assoc. Count

The Week Association Count is a calculated measure that indicates the number of weeks associated with the rule group.

All PROD-LOC Count



The All Product-Location Count is a calculated measure that indicates the number of product-location combinations associated with the rule group based on the product and location scopes.

PROD-LOC Valid Count

The Product-Location Valid Count is a calculated measure that indicates the number of product-location combinations associated with the rule group based on the product and location scopes and the combination is assorted.

PROD-LOC Valid %

The Product-Location Valid Percentage is a calculated measure that indicates the percentage of assorted products and locations associated with the rule group, compared to the total of the product and location combinations. This measure is calculated as:


Figure 16-10 Calculation

$$100*\frac{AllPROD-LOCCount}{PROD-LOCValidCount}$$

Today View

The **Today View**, under the **Today tab**, allows you to check today's date.

Figure 16-11 Today View



Today View - Default Profile Measures

The Today view contains the following measure.

Today Date




This is a read-only measure that displays the system date calculated by the batch.

Product Group Scope View: Rule Group

The **Product Group Scope View**, under the **Product Scope tab**, allows you to select specific products to be included in the rule group.

Figure 16-12 Product Group Scope View: Rule Group



Product Group Scope View: Rule Group - Default Profile Measures

The Product Group Scope view: Rule Group contains the following measures.

PROD Group Scope

The Product Group Scope is a checkbox measure used to select which products should be assigned to the rule group.

PROD Group Assoc.

The Product Group Associated is a calculated measure that indicates whether the product groups are associated with the rule group or not. The measure is selected if the product groups are associated. If the product groups are not associated, it is clear.

Location Group Scope View: Rule Group

The Location Group Scope View, under the Location Group Scope tab, allows you to select the specific locations to be included in the rule group.



Figure 16-13 Location Group Scope View: Rule Group

Location Group Scope View: Rule Group - Default Profile Measures

The Location Group Scope view contains the following measures.

LOC Group Scope

Location Group Scope is a checkbox measure used to select which locations should be assigned to the databag.

LOC Group Assoc.


Location Group Associated is a calculated measure that indicates whether the location groups are associated with the rule group or not. The measure is selected if the location groups are associated. If the location groups are not associated, it is clear.

Source Scope View

The **Source Scope View**, under the **Source Scope tab**, allows you to select specific source locations to be included in the rule group.



Figure 16-14 Source Scope View



Source Scope View - Default Profile Measures

The Source Scope view contains the following measures.

SLOC Scope

Source Location Scope is a checkbox measure used to select which source locations should be assigned to the rule group.


SLOC Assoc.

Source Location Associated is a calculated measure that indicates whether the source locations are associated with the rule group or not. The measure is selected if the source locations are associated. If the source locations are not associated, it is clear.

Attribute Scope View

The **Attribute Scope View**, under the **Attribute Scope tab**, allows you to select specific attributes to be included in the rule group.

Figure 16-15 Attribute Scope View





Attribute Scope View - Default Profile Measures

The Attribute Scope view contains the following measures.

Attribute Scope

Attribute Scope allows you to select which attributes should be assigned to the rule group.

Attribute Assoc.

Attribute Assoc. is a calculated measure that indicates whether the attributes are associated with the rule group or not. The measure is selected if the attributes are associated. The measure is clear if the attributes are not associated.

Manage Rule Groups Action Buttons

The Manage Rule Group workspace has the following action buttons available:


Calc Rule Groups

Use the **Calculation Rule Groups** action button to calculate the rule group's scope based on all setups created by you. The result is a Boolean measure that is used by the Replenishment Setup Rules and Replenishment Parameters Rules workspaces to load the correct scope of products, locations, source locations and attributes.

Publish Data

Use the **Publish Data** action button to commit the changes made in the Manage Rule Groups workspace. It also saves the audit information by updating and committing the measures **Last Rule Group Publish User ID** and **Last Rule Group Publish Date** based on who and when the **Publish Data** was last run.

Figure 16-16 Manage Rule Groups Action Buttons





17

Manage Packs

This chapter describes the functionality that allows you to manage Packs.

Manage Packs Workspace, Steps, and Views

The following table lists the workspaces, steps, and views of the Manage Packs task.

Table 17-1 Manage Rule Groups Workspace, Steps, and Views


Workspace	Steps	Tab	Views
Manage Packs Workspace	Pack Setup	Pack Setup	Enable View: Manage Packs
			Pack-SKU View
			Packs View

Manage Packs Workspace

To build the Manage Packs workspace, perform these steps:


1. From the left sidebar menu, click **Task Module** to view the available tasks.

Figure 17-1 Task Module



- 2. Click the IPO Administration activity and then click Lifecycle Allocation and Replenishment to access the available workspaces.
- 3. Click Manage Packs. The Manage Packs wizard opens.
- **4.** You can open an existing workspace, but to create a new workspace, click **Create New Workspace**.

Figure 17-2 Create New Workspace



5. Enter a name for your new workspace in the label text box and click **OK**.



6. The Workspace wizard opens. Select the products you want to work with and click **Next**.



Manage Packs

Levels & Positions

Company

Level

Company

Pantry

Pantry


Group

Women's Fashion

Figure 17-3 Workspace Wizard: Select Product

7. Select the locations you want to work with and click Finish.

Figure 17-4 Workspace Wizard: Select Location



8. The wizard notifies you that your workspace is being prepared. Successful workspaces are available from the Dashboard.



Dishboard

Dishboard

Task Status

Eat Dishboard

Task Status

Eat Dishboard

Task Status

Eat Dishboard

Task Status

Eat Dishboard

Seed Bushboard

Seed Bushboard

Seed Bushboard

Eat Dishboard

Seed Bushboard

Seed Bush

Figure 17-5 Successful Workspace Build: Manage Packs

Pack Setup Step


This step contains the following views:

- Enable View: Manage Packs
- Pack-SKU View
- Packs View

Enable View: Manage Packs

The **Enable View**, under the **Pack Setup tab**, allows you to enable packs in the solution. This is a global setting.


Figure 17-6 Enable View: Manage Packs



Pack-SKU View

The **Pack-SKU View**, under the **Pack Setup tab**, allows you to review the pack composition. In this view you can select what items are part of the pack and how many units of each assigned item make up the pack.


Figure 17-7 Pack-SKU View



Packs View

The **Packs View**, under the **Pack Setup tab**, allows you to review the pack information for each product. For example, the pack type and the number of products within the pack.

Figure 17-8 Packs View



Packs View - Default Profile Measures

The Packs view contains the following measures.

Pack Type

This is a loaded measure used to indicate the product's pack type. Either simple or complex.

Size Desc.



The Size Description is a loaded measure used to indicate the product's pack description.

Pack SKU Ass. Count

This is a calculated measure used to indicate the total number of products (SKU) in the pack.

Pack SKU Ass. Unit

This is an editable measure used to indicate the total number of component units (SKU) that belong to the pack.

Pack User Filter

This is an editable measure used to apply a filter to the Pack-SKU view by the selected packs. When the packs are selected, and after the workspace calculation (**Calculate** or **F9**) is run, the Pack-SKU view is filtered based on the selected packs.


Manage Packs Action Buttons

The Manage Packs workspace has the following action button available:

Pack Setup

This action button is responsible to calculate the pack information based on the available pack set up.

Figure 17-9 Manage Packs Action Button





18

Manage Allowed Transfer

This chapter describes the functionality that allows you to manage allowed transfers.

Manage Allowed Transfer Workspace, Steps, and Views

The Manage Allowed Transfer workspace allows you to manage what locations are allowed to have transfers. You can manage a location matrix where to select if a transfer between the locations in the matrix are allowed or not. The columns in the view represent the transfers' destination location and the rows represent the transfer's source location.

The following table lists the workspaces, steps, and views of the Manage Allowed Transfer task.

Table 18-1 Manage Allowed Transfer Workspace, Steps, and Views


Workspace	Steps	Tab	Views
Manage Allowed Transfer Workspace	Allowed Transfer	Allowed Transfer	Allowed Transfer View

Manage Allowed Transfer Workspace

To build the Manage Allowed Transfer workspace, perform these steps:


1. From the left sidebar menu, click **Task Module** to view the available tasks.

Figure 18-1 Task Module



- 2. Click the IPO Administration activity and then click Lifecycle Allocation and Replenishment to access the available workspaces.
- 3. Click Manage Allowed Transfer. The Manage Allowed Transfer wizard opens.
- 4. You can open an existing workspace, but to create a new workspace, click **Create New Workspace**.

Figure 18-2 Create New Workspace




5. Enter a name for your new workspace in the label text box and click **OK**.




6. Select the locations you want to work with and click **Next**.

Figure 18-3 Workspace Wizard: Select Location



7. Select the source locations you want to work with and click Finish.

Figure 18-4 Workspace Wizard: Select Source Location



8. The wizard notifies you that your workspace is being prepared. Successful workspaces are available from the Dashboard.



Manage Workspaces Manage Allowed Transfers Last 7 days Last Edited 10/27/2023 Created 10/27/2023 Edit Dashboard MNG Transfers Initial Last Edited 9/14/2023 Created 9/14/2023 In Progress (0) Completed (1) Replenishment Parameters Last 24 hours ▼ All Submitters ▼ Initial Last Edited 9/21/2023 **Task Status** Created 9/21/2023 View 🔻 ಿ Detach 🔲 Auto-Refresh 😃 Download Log 🚱 Watch Live Log 🕦 Download Rej ≎ Status ≎ Task Type Submitter by Started/Scheduled Completed Initial Manage Allowed Transfers WbBatch Build oci.admin 10/27/23, 1:... 10/27/23, 1:...

Figure 18-5 Successful Workspace Build: Manage Allowed Transfer

Allowed Transfer Step

This step contains the Allowed Transfer View.

Allowed Transfer View

The **Allowed Transfer View**, under the **Allowed Transfer tab**, allows you to manage which locations are allowed to have transfers. You can manage a location matrix to select if a transfer between the locations in the matrix is allowed or not. The columns in the view represent the transfers' destination location and the rows represent the transfers' source location.

Figure 18-6 Allowed Transfer View

Allowed Transfer View - Default Profile Measures

The Allowed Transfer view contains the following measure.

Transfer Enable



This is an editable measure for you to allow or disallow transfers between source locations and destination locations. When selected, transfers are allowed. A transfer that is clear is not allowed.



19

Supply Chain Network

This chapter describes the functionality that allows you to set up and review the supply chain network model to be used by the IPOCS-Lifecycle Allocation and Replenishment calculations.

The Supply Chain Network Workspace is where you can set up the Bill of Distribution, Planning Calendars, and Lifecycle Calendars. Once they are defined you can configure rules and conditions to specify where they should be applied. The IPOCS-Lifecycle Allocation and Replenishment Rule Engine does the heavy work for you and calculates the correct Bill of Distribution, Planning Calendars, Assortment Calendars, and Lifecycle Calendars at the product and location level using the available assortment and lifecycle information.

You can further leverage the IPOCS-Lifecycle Allocation and Replenishment Rules Engine and specify the period where the rule should apply (start and end date if applicable) and the priority of the rule to allow IPOCS-Lifecycle Allocation and Replenishment to pick the most suitable rule based on the priority.

Prod / Loc Scope
Prod: OEM - Apple Handset
Loc: UK

Prod / Loc Scope
Prod: OEM - Apple Handset
Loc: UK

Rule Start / End Date
Start Date: Jan, 2
End Date: .

Rule Priority
Priority 10

Plan Clnd 2

Plan Clnd 3

Plan Clnd 2

Life Clnd 2

Life Clnd 2

Life Clnd 3

Life Clnd 3

Plan Clnd 2

Rule Start / End Date
Start Date: Jan, 2
End Date: .

Rule Priority
Priority 10

Priority 10

Figure 19-1 IPOCS-Lifecycle Allocation and Replenishment Setup Rules Illustration

Legend

BOD = Bill of Distribution Plan Clnd = Planning Calendar Life Clnd = Lifecycle Calendar OEM = Original Equipment Manufacturer

Supply Chain Network Workspace, Steps, and Views



The following table lists the workspaces, steps, and views for the Supply Chain Network task.

Table 19-1 Supply Chain Network Workspace, Steps, and Views

Workspace	Steps	Tab	Views
Supply Chain Network Workspace	Overview	Overview	Statistics View
		Scope	Location Scope View
			Product Scope View
	Bill of Distributions	Bill of Distributions	Bill of Distributions View
			Valid Source Locations View
	Planning Calendars	Planning Calendars	Planning Calendars View
			Day of Week View
			Daily Exceptions View
	Lifecycle Calendars	Lifecycle Calendars	Lifecycle Calendars View
			Lifecycle Phases View
	Rules	Setup	Rule Views
			Conditions View
		Review	SKU-LOC View
			SKU-LOC-Week View
			SKU-LOC-Phases View
	Filter	Filter	Calendar Filter View
			Filter Parameters View


Supply Chain Network Workspace

The Supply Chain Network workspace allows you to access all the views listed in the Supply Chain Network Workspaces, Steps, and Views. To build the Supply Chain Network workspace, perform these steps:

1. From the left sidebar menu, click **Task Module** to view the available tasks.




Figure 19-2 Task Module



- 2. Click the **Business Rules Setup** activity to access the available workspaces.
- 3. Click Supply Chain Network. The Supply Chain Network wizard opens.
- You can open an existing workspace, but to create a new workspace, click Create New Workspace.

Figure 19-3 Supply Chain Network Wizard: Create New Workspace



5. Enter a name for your new workspace in the label text box and click **OK**.




6. The Workspace wizard opens. Select the rule group you want to work with and click **Finish**.



Only the rule groups that are from the Setup rule group type are available for selection. The rule group type value is managed in the Manage Rule Groups workspace.

Figure 19-4 Workspace Wizard: Select Rule Group



7. The wizard notifies you that the workspace is being prepared. Successful workspaces are available from the Dashboard.



The workspace is built using the selected rule group scope. The products, locations, source locations and attributes available in the workspace are the ones in the rule group scope that is managed in the Manage Rule Groups workspace.






Figure 19-5 Successful Workspace Build: Supply Chain Network

Overview Step

This step contains these views:


- Statistics View
- Location Scope View
- Product Scope View

Statistics View

The **Statistics View**, under the **Overview tab**, allows you to check the statistics of the Supply Chain Network. The view has statistical information regarding the number of valid counts for each set up (for example, Bill of Distribution, Planning Calendar) and rules. It also provides the number of product and location combinations and the number of Network Loop errors.



Figure 19-6 Statistics View



Statistics View - Default Profile Measures

The Statistics View contains the following measures.

Rule Group Type

The Rule Group Type is a loaded read-only measure to display the rule group type that was set up for the rule group in the Manage Rule Group workspace.

Valid values are:

- Setup: The rule group is enabled and its purpose is to be available in the Replenishment Supply Chain Network workspace to set up the supply chain network model.
- Parameters: The rule group is enabled and its purpose is to be available in the Replenishment Rules workspace to set up the replenishment method and parameters.
- _: Empty space indicates that the rule group is unavailable.

Rule Group User Desc.

The Rule Group User Description is a loaded read-only measure to display your description that was set up for the rule group in the Manage Rule Group workspace.

Last Rule Group Publish User ID

The Last Rule Group Publish User ID is a loaded read-only measure to display you identifier that performed the last rule group's change in the Manage Rule Group workspace.

Last Rule Group Publish Date



The Last Rule Group Publish Date is a loaded read-only measure to display the date and time when the last rule group's change was performed in the Manage Rule Group workspace.

BOD Valid Count

The Bill of Distributions Valid Count is a calculated measure to display the total number of valid bills of distributions (BOD) that are set up for the rule group.

Plc. Valid Count

The Planning Calendar's Valid Count is a calculated measure to display the total number of valid planning calendars (Plc) that are set up for the rule group.

Lfc. Valid Count

The Lifecycle Calendar's Valid Count is a calculated measure to display the total number of valid lifecycle calendars (Lfc) that are set up for the rule group.

Rule Valid Count

The Rule Valid Count is a calculated measure to display the total number of valid rules that are set up for the rule group.

All PL Count

The All Product and Location Count is a calculated measure to display the total number of product and location combinations that have a lifecycle phase value.

PL Valid Count

The Product and Location Valid Count is a calculated measure to display the total number of product and location combinations that have a valid rule assigned.

PL Valid %

The Product and Location Valid Percentage is a calculated measure used to indicate, in percentage, how much the product and location combinations with a valid rule assigned represent the total of product and location combinations with a lifecycle phase value. The value of this measure is the result of the formula:

Figure 19-7 Calculation

$$100 * \frac{PL \ Valid \ Count}{All \ PL \ Count}$$

Network Loop @ Today Count

The Network Loop @ Today Count is a calculated measure to display the total number of Network Loop errors caused by the BOD set up for the rule group.

Location Scope View

The **Location Scope View**, under the **Scope tab**, allows you to check what specific locations are in the scope of a rule group and loaded into the workspace.



Figure 19-8 Location Scope View

Location Scope View - Default Profile Measures

The Location Scope View contains the following measure.

LOC Group Assoc.


The Location Group Associated is a loaded read-only measure used to indicate the location groups that are associated with the rule group. This measure is managed in the Manage Rule Groups workspace.

Product Scope View

The **Product Scope View**, under the **Scope tab**, allows you to check what specific products are in the scope of a rule group and loaded into the workspace.



Figure 19-9 Product Scope View



Product Scope View - Default Profile Measures

The Product Scope View contains the following measure.

PROD Group Assoc.

The Product Group Associated is a loaded read-only measure used to indicate the products groups that are associated with the rule group.

Bill of Distributions Step

This step contains these views:

- Bill of Distributions View
- Valid Source Locations View

In IPOCS-Lifecycle Allocation and Replenishment, the Bill of Distribution (BOD) defines the lead time for all supplying sources available throughout the supply chain network. Lead time is defined as the number of days a shipment takes to arrive between the source and the target.



Figure 19-10 IPOCS-Lifecycle Allocation and Replenishment Bill of Distributions Illustration




Source	Lead Time
Supplier A	3
Supplier B	2
Supplier B	5
Warehouse 1	1
Warehouse 2	2
Warehouse 2	1

Bill of Distributions View

The **Bill of Distributions View**, under the **Bill of Distributions tab**, allows you to perform all possible setups for the source of supply chain network. The setup is then used in the rules and based on the rule set up it is associated with, down to item and location level (lowest level of Prod-Loc).

Figure 19-11 Bill of Distributions View



Bill of Distributions View - Default Profile Measures

The Bill of Distributions View contains the following measures.

BOD Enable

The Bill of Distributions Enable is an editable measure to enable or disable a bill of distribution. Each row (or list) represents a different BOD.

BOD Valid

The Bill of Distributions Valid is a calculated measure used to indicate if the set up of the BOD is valid or not. For example, if the primary source is missing then the BOD is not valid for IPOCS-Lifecycle Allocation and Replenishment.

BOD Desc

The Bill of Distributions Description is a calculated measure used to indicate the BOD description. The description is calculated based on the BOD user-defined description and the BOD set up. The pattern applied is the following:

When no Reserved source is set up:

[BOD User Desc]+ +[Primary Source]+.+[Lead Time]

When only Reserved source 1 is set up:

[BOD User Desc]+ +[Primary Source]+.+[Lead Time]+.R1

When only Reserved source 2 is set up:

[BOD User Desc]+ +[Primary Source]+.+[Lead Time]+.R2

When both Reserved source are set up:

[BOD User Desc]+ +[Primary Source]+.+[Lead Time]+.R1.R2

BOD User Desc

The Bill of Distributions User Description is an editable measure to input a user-defined BOD description. The final BOD description takes into consideration your defined description. The entered value must not contain a colon punctuation mark (:).

Primary Source

The Primary Source is an editable measure to select, from a picklist, a primary source for the BOD. The list of sources presented to you in the picklist are the sources that are enabled as a valid location source in the Valid Source Locations view.

Lead Time

The Lead Time is an editable measure to define the lead time, in number of days, for the BOD.

Reserved Source 1

The Reserved Source 1 is an editable measure to select, from a picklist, a reserved source for the BOD. The list of sources presented to you in the picklist are the sources that are enabled as valid reserved sources in the Valid Source Locations view.

Reserved Source 2

The Reserved Source 2 is an editable measure to select, from a picklist, an additional reserved source for the BOD. The list of sources presented in the picklist are the sources that are enabled as valid reserved sources in the Valid Source Locations view.

Alternative Source

The Alternative Source is an editable measure to select, from a picklist, an alternative source to the primary source for the BOD. The list of sources presented in the picklist are the sources that are enabled as Valid Source Locations in the Valid Source Locations view.

Rule BOD Count

The Rule Bill of Distributions Count is a calculated measure to display the total number of rules that are using the BOD.

PL BOD Count



The Product and Location Bill of Distributions Count is a calculated measure to display the total number of product and location combinations that are associated with the BOD.

PL BOD %

The Product and Location Bill of Distributions Percentage is a calculated measure used to indicate, in percentages, how much the product and location combinations associated with the BOD represent in the total of product and location combinations with a lifecycle phase value. The value of this measure is the result of the formula:

Figure 19-12 Calculation

$$100* \frac{PL\ BOD\ App.\ Count}{All\ PL\ Count}$$


BOD User Filter

The Bill of Distributions User Filter is an editable measure to select the BOD to filter the views by the selected BOD. This measure is used by the **Run Filter** action button responsible to calculate the filters applied to the views within the Supply Chain Network workspace.

Valid Source Locations View

The **Valid Source Locations View**, under the **Valid Sources tab**, allows you to select which locations are primary sources or reserved sources. This set up is used by the Primary Source and Reserved Source measures in the Bill of Distributions view to display the correct source location to you.

Figure 19-13 Valid Source Locations View





Valid Source Locations View - Default Profile Measures

The Valid Source Locations View contains the following measures.

Valid Primary Source

The Valid Primary Source is an editable measure to define a location possible location to be used by the bill of distributions as the primary source or alternate source.

Valid Reserved Source

The Valid Reserved Source is an editable measure to define a possible location to be used by the bill of distributions as a reserved source.

Planning Calendars Step

This step contains these views:

- · Planning Calendars View
- Day of Week View
- Daily Exceptions View

In IPOCS-Lifecycle Allocation and Replenishment the Planning Calendar (Plc) is used to specify the location's ordering/receiving patterns along with the associated planning horizon that IPOCS-Lifecycle Allocation and Replenishment should plan for. IPOCS-Lifecycle Allocation and Replenishment works with two types of calendars:

- Review Calendar: Use this calendar for point-in-time replenishments
- Receipt Calendar: Use this calendar for time-phased replenishments

Both calendars allow for two methods to set up a Planning Calendar:

- **Day of Week**: Main method to select the review or receipt dates, by selecting a day of the week, (for example, Monday) regardless of the dates
- **Exception**: Method to configure exceptions by selecting specific dates (days) that are an exception to the day of week set up.




Figure 19-14 Planning Calendar Day of Week Setup Illustration (Review & Receipt)

Day of Week	Monday	Tuesday	Wednesday	Thursday	Friday	Saturday	Sunday
Review	\checkmark		\checkmark		$\overline{\checkmark}$		
Review	\checkmark	$\overline{\mathbf{V}}$	$\overline{\checkmark}$	V	$\overline{\checkmark}$		
Review			$\overline{\checkmark}$				

Day of Week	Monday	Tuesday	Wednesday	Thursday	Friday	Saturday	Sunday
Receipt	$\overline{\checkmark}$		$\overline{\checkmark}$		$\overline{\mathbf{V}}$		
Receipt	$\overline{\checkmark}$	$\overline{\checkmark}$	\checkmark	$\overline{\checkmark}$	V		
Receipt			$\overline{\checkmark}$				

Figure 19-15 Planning Calendar Exception Setup Illustration (Review & Receipt)




Day of Week	Receipt Exception	Receipt Active
2019.02.03	Default	
2019.02.04	Default	$\overline{\mathbf{V}}$
2019.02.05	Off	
2019.02.06	On	$\overline{\checkmark}$

The planning calendar set up is used in the rules and based on the rule set up it is associated with down to the item and location levels (lowest level of Prod-Loc). This set up is also used by the IPOCS-Lifecycle Allocation and Replenishment Engine to plan what the next review day or receipt day is.

Planning Calendars View

The **Planning Calendars View**, under the **Planning Calendars tab**, allows you to set up a planning calendar and specify the time horizon to be used. The set up of the planning calendar is completed by the set up in the views Day of Week and Daily Exceptions.

Figure 19-16 Planning Calendars View



Planning Calendars View - Default Profile Measures

The Planning Calendars View contains the following measures.

Plc. Enable

The Plc. Enable is an editable measure to enable or disable a planning calendar. Each row (or list) represents a different planning calendar.

Plc. Valid

The Plc. Valid is a calculated measure that indicates if the set up of the planning calendar is valid or not. IPOCS-Lifecycle Allocation and Replenishment assumes that a planning calendar valid if it is enabled.

Plc. Desc

The Plc. Desc is a calculated measure used to indicate the planning calendar description. The description is calculated based on the planning calendar user-defined description and the planning calendar set up. The pattern applied is the following:

[Plc. User Desc]+ +[List of selected Review Days separated by .]

Plc. User Desc

The Plc. User Desc is an editable measure to input a user-defined planning calendar description. The final planning calendar description takes into consideration the user-defined description. The entered value must not contain a colon punctuation mark (:).

Plc. Horizon Dur (d)

The Plc. Horizon Dur (d) is an editable measure to input the time horizon for the planning calendar. The time horizon is a numeric value expressed in a number of days.

Rule Plc. Count

The Rule Plc. Count is a calculated measure to display the total number of rules that are using the planning calendar.



PL Plc. Count

The PL Plc. Count is a calculated measure to display the total number of product and location combinations that associated with the planning calendar.

PL Plc. %

The PL Plc. % is a calculated measure used to indicate, in percentage, how much the product and location combinations associated with the planning calendar represent the total of product and location combinations with a lifecycle phase value. The value of this measure is the result of the formula:

Figure 19-17 Calculation

$$100 * \frac{PL\ Plc.\ Count}{All\ PL\ Count}$$

Daily Ex. Copy & Paste

The Daily Ex. Copy & Paste is an editable measure to select whether the planning calendar is the source or destination for the copy/paste exception functionality (**Copy-Paste Exceptions** action button). Valid values are:

Copy

The option selected in the planning calendar used as a source of the copy for the daily exception. The copy copies all information in the view Daily Exceptions.

Paste

The option selected in the planning calendar used as a destination of the copy for the daily exception. The paste overrides all the information in the view Daily Exceptions.

• .

The option selected to clear the measure. An example of this would be to select a copy of the planning calendar 01 and then select paste to the planning calendar 02. Then when the **Copy-Paste Exception** action button runs all daily exceptions from Planning Calendar 01, it is copied to Planning Calendar 02. The results can be selected in the view Daily Exceptions.



Only one planning calendar should be selected as a source (**Copy**) but multiple planning calendar can be selected as a destination (**Paste**).

Plc. User Filter


The Plc. User Filter is an editable measure to select the planning calendar to filter the views by the selected planning calendar. This measure is used by the **Run Filter** action button responsible to calculate the filters applied to the views within the Supply Chain Network workspace.



Day of Week View

The **Day of Week View**, under the **Day of Week tab**, allows you to set up what the week must be in terms of the review and receipt days for the planning calendar. This set up is also used by IPOCS-Lifecycle Allocation and Replenishment Engine to know what the next review day is, or what the next receipt day is.

Figure 19-18 Day of Week View



Day of Week View - Default Profile Measures

The Day of Week View contains the following measures.

Review Day of Week

This is an editable measure to select the days of the week, in the planning calendar, to be used for the replenishment days.

Receipt Day of Week


This is an editable measure to select the days of the week, in the planning calendar, to be used as received deliveries days.

Daily Exceptions View

The **Daily Exceptions View**, under the **Daily Exceptions tab**, allows you to set up exception days on top of the set up already completed for the days of week. For example, if Fridays are selected as review days but there is a specific Friday where the review can not be completed, then you can use this view to override the particular Friday date to be a no-review day. By default, all dates assume the set up from the Day of Week view.



Figure 19-19 Daily Exceptions View



Daily Exceptions View - Default Profile Measures

The Daily Exceptions View contains the following measures.

Review Excp. (Dy)

The Review Exception (Day) is an editable measure to set up a review day exception, in the planning calendar, for a particular date. Valid values are:

Default

This option assumes the review day set up from the Day of Week view.

Or

This option overrides the review day set up from the Day of Week and forces the date to be a review day.

Off

This option overrides the review day set up from the Day of Week and forces the date to be a no-review day.

Review Active (Dy)

The Review Active (Day) is a calculate measure used to indicate whether the date is a review day or not (might be a forced exception or the default day from the Day of Week view). When selected, the date is a review day. When clear, the date is not a review day.

Receipt Excp. (Dy)

The Receipt Exception (Day) is an editable measure to set up a receipt day exception, in the planning calendar, for a particular date. Valid values are:

Default

This option assumes the receipt day set up from the Day of Week view.

On

This option overrides the receipt day set up from the Day of Week and forces the date to be a receipt day.

Off

This option overrides the receipt day set up from the Day of Week and forces the date to be a no-receipt day.

Review Active (Dy)

The Review Active (Day) is a calculated measure used to indicate whether the date is a receipt day or not (might be a forced exception or the default day from the Day of Week view). When selected the date is a receipt day. When clear, the date is not a receipt day.

Lifecycle Calendars Step

This step contains these views:

- Lifecycle Calendars View
- Lifecycle Phases View

In IPOCS-Lifecycle Allocation and Replenishment the Lifecycle represents all the phases that every item goes through during its lifetime. A full lifecycle is when an item goes from discovery to maturity and then end of life.

Figure 19-20 IPOCS-Lifecycle Allocation and Replenishment Lifecycle Illustration



The IPOCS-Lifecycle Allocation and Replenishment Lifecycle calendar defines the timing of the lifecycle phases, and it is linked to an item assortment plan at the location. The assortment start date is used as an Anchor Date to trigger the start of the lifecycle assortment. The end date defines when an item should stop selling and stop being replenished.

The IPOCS-Lifecycle Allocation and Replenishment approaches for replenishment may vary throughout the different lifecycle phases:

Discovery

This rule measures how long the sales forecast takes to stabilize during the initial sales period. Sales are generally highly volatile.

- Example: Setting 3-4 weeks after (end of) initial allocation or 2% Sell Through of Total Initial Inventory
- Setting the end of Discovery too early could misdiagnose poor sales for an item
- Setting the end of Discovery too early could misdiagnose poor sales for an item

Maturity

Item sales growth is continuous and forecasting in general is less volatile and more reliable.



End of Life

The item is close to the planned assortment end date and typically sales begin to diminish. In some cases, the item is sold at a Clearance Price during the end of life.


- Example: Set as 80% Sell Through of Total Initial Inventory or for a specific date
- The total forecast from the beginning of the end of life to the assortment end date is the key driver for replenishment for this phase of the lifecycle

The end of replenishment may be linked to the Assortment End Date, to a userdefined end of replenishment date or calculated by the system based on an elapsed time starting from the anchor date.

Lifecycle Calendars View

The **Lifecycle Calendars View**, under the **Lifecycle Calendars tab**, allows you to set up a lifecycle calendar where the start and end dates and the number of phases are specfied. The Phases setup is completed in the Lifecycle Phases view.

Figure 19-21 Lifecycle Calendars View



Lifecycle Calendars View - Default Profile Measures

The Lifecycle Calendars View contains the following measures.

Lfc. Enable

The Lifecycle Enable is an editable measure to enable or disable a lifecycle calendar. Each row (or list) represents a different lifecycle calendar.

Lfc. Valid

The Lifecycle Valid is a calculated measure used to indicate if the set up of the lifecycle calendar is valid or not. IPOCS-Lifecycle Allocation and Replenishment assumes a lifecycle calendar is valid if the total number of phases for the lifecycle calendar has a valid set up in the Lifecycle Phases view. For example, if a lifecycle calendar is set up to have four phases and only three of them are valid, then the



lifecycle calendar is not valid. The lifecycle calendar is only valid when all four out of the four of four phases are valid.

Lfc. Desc

The Lifecycle Description is a calculated measure used to indicate the lifecycle calendar description. The description is calculated based on the lifecycle calendar user-defined description and the lifecycle calendar set up. The pattern applied is the following:

[Lfc. User Desc]+ + #START# + -> + #END#, where:

- #START# value is as follows
 - If the measure Lfc. Anchor is set to assortment start date then it is the text Ast. Start.
 - If the measure Lfc. Anchor is set to Default and the anchor date exists (measure Lfc. Default Anchor Date is not empty) then it is the date indicated in the measure Lfc. Default Anchor Date.
 - If the measure Lfc. Anchor is set to Default and the anchor date does not exist (measure Lfc. Default Anchor Date is empty) then it is the text -inf (infinite).
- #END# value is as follows
 - If the measure Lfc. End is set to assortment start date then it is the text Ast. End.
 - If the measure Lfc. End is set to Default Date and the default end date exist (measure Lfc. Default End Date is not empty) then it is the date indicated in the measure Lfc. Default End Date.
 - If the measure Lfc. End is set to Default Date and the default end date does not exists (measure Lfc. Default End Date is empty) then it is the text +inf (infinite).
 - If the measure Lfc. End is set to Default then it is the value indicated in the measure Lfc. Default End Dur (d).

Lfc. User Desc

The Lifecycle User Description is an editable measure to input a user-defined lifecycle calendar description. The final lifecycle calendar description takes into consideration the user-defined description. The entered value must not contain a colon punctuation mark (:).

Lfc. Anchor Method

The Lifecycle Anchor Method is an editable measure to select how IPOCS-Lifecycle Allocation and Replenishment should calculate the lifecycle calendar start date. Valid values are:

Default

This option sets the lifecycle calendar start date to the date indicated in the measure Lfc. Default Anchor Date. If the measure Lfc. Default Anchor Date is empty, then the start date is assumed as $-\infty$ (infinite).

Ast. Start

This option sets the lifecycle calendar start date to the same date as the assortment start date.

Lfc. Default Anchor Date

The Lifecycle Default Anchor Date is an editable measure to define a default start date for the lifecycle calendar when the Lfc. Anchor measure is set up as default.

Lfc. End Method



The Lifecycle End Method is an editable measure to select how IPOCS-Lifecycle Allocation and Replenishment should calculate the lifecycle calendar end date. Valid values are:

Def. Date

This option sets the lifecycle calendar end date to the date indicated in the measure Lfc. Default End Date. If the measure Lfc. End Anchor Date is empty then the end date is assumed as $-\infty$ (infinite).

Def. Dur.

This option sets the lifecycle calendar end date to the lifecycle start date plus the number of days indicated in the measure Lfc. Default End Dur (d). If the measure Lfc. Default End Dur (d) is empty then 0 days is assumed.

Ast. End

This option sets the lifecycle calendar end date to the same date as the assortment end date.

Lfc. Default End Date

The Lifecycle Default End Date is an editable measure to define a default end date for the lifecycle calendar when the Lfc. End measure is set up as Def. Date.

Lfc. Default End Dur (d)

The Lifecycle Default End Duration (day) is an editable measure to defined default duration in days for the lifecycle calendar when the Lfc. End measure is set up as Def. Dur.

Lfc. Number of Phases

The Lifecycle Number of Phases is an editable measure to define how many phases the lifecycle calendar has. The number of phases indicated in this measure is the number of rows (phases) available in the view Lifecycle Phases to set up the phases.

Rule Lfc. Count

The Rule Lifecycle Count is a calculated measure to display the total number of rules that are using the lifecycle calendar.

PL Lfc. Count

Product and Location Lifecycle Count is a calculated measure to display the total number of product and location combinations that are associated with the lifecycle calendar.

PL Lfc. %

The Product and Location Lifecycle Percentage is a calculated measure used to indicate, in percentages, how many product and location combinations associated with the lifecycle calendar are represented in the total of product and location combinations with a lifecycle phase value. The value of this measure is the result of the formula:

Figure 19-22 Calculation

$$100 * \frac{PL \, Lfc. \, Count}{All \, PL \, Count}$$



Lfc Duplicate Phases

The Lifecycle Duplicate Phases is an editable measure to select whether the lifecycle calendar is the source or destination for the copy/paste lifecycle functionality (**Copy-Paste LFC** action button). Valid values are:

Copy

The option selected in the lifecycle calendar to be used as the source of the copy.

Paste

The option selected in the planning calendar to be used as destination of the copy.

•

The empty option selected to clear the measure.



Only one lifecycle calendar should be selected as a source (**Copy**) but multiple lifecycle calendars can be selected as a destination (**Paste**).

Lfc. User Filter

The Lifecycle User Filter is an editable measure to select the lifecycle calendar to filter the views by the selected lifecycle calendar. This measure is used by the **Run Filter** action button responsible to calculate the filters applied to the views within the Supply Chain Network workspace.

Lifecycle Phases View


The **Lifecycle Phases View**, under the **Lifecycle Phases tab**, allows you to configure each one of the phases for the total of phases specified in the lifecycle calendar. In this view, you can name the phases and set up the start and duration of each phase.

The lifecycle phases are considered as Prod-Loc Attributes in IPOCS-Lifecycle Allocation and Replenishment that can be used to set up replenishment parameter rules based on lifecycle phases.

This allows the IPOCS-Lifecycle Allocation and Replenishment to work on associating the correct replenishment parameters down to the item-location level (lowest level) based on the lifecycle phase. Using lifecycle phases simplifies the replenishment parameter management by completing it at the lifecycle phase level.



Figure 19-23 Lifecycle Phases View



Lifecycle Phases View - Default Profile Measures

The Lifecycle Phases View contains the following measures.

Phase Valid

The Phase Valid is a calculated measure used to indicate if the set up of the lifecycle phase is valid or not. IPOCS-Lifecycle Allocation and Replenishment assumes a lifecycle phase is valid when the Phase and Phase Start measures are populated.

Phase

The Phase is an editable measure to input a user-defined lifecycle phase description or name.

Phase Start Method

The Phase Start Method is an editable measure to select how the IPOCS-Lifecycle Allocation and Replenishment calculates the phase start date. Valid options are:

Offset versus Anchor

In this option the phase start date is calculated based on the lifecycle start date plus the number of days indicated in the measure Phase Anchor Offset (d).

Offset versus End

In this option the phase start date is calculated based on the lifecycle end date plus the number of days indicated in the measure Phase End Offset (d).

Date

In this option the phase start date is set to the date indicated in the measure Phase Start Date.

Seas. Sales %

In this option the phase starts on the date that the sales reached the percentage indicated in the measure Phase Min Sales %.

First



In this option the phase starts first before all other phases in the lifecycle calendar. Based on the previously listed options, the lifecycle phase is assigned to the item and location combination when the IPOCS-Lifecycle Allocation and Replenishment system date reaches the start date assigned to the phase.

Phase Anchor Offset (d)

The Phase Anchor Offset (day) is an editable measure to define the number of days to offset from the lifecycle calendar start date. This value is only used when the Phase Start is set to Offset vs Anchor. Negative values can also be used if the offset days need to be moved backward to the past.

Phase End Offset (d)

The Phase End Offset (day) is an editable measure to define the number of days to offset from the lifecycle calendar end date. This value is only used when the Phase Start is set to Offset versus End. Negative values can also be used if the offset days need to be moved backward to the past.

Phase Start Date

The Phase Start Date is an editable measure for you define a specific date to start the lifecycle phase. This value is only used when the Phase Start is set to Date.

Phase Min Sales %

The Phase Min Sales % is an editable measure to define the minimum sales percentage that IPOCS-Lifecycle Allocation and Replenishment uses to identify the lifecycle phase start date. This value is only used when the Phase Start is set to Seas. Sales %.

Rules Step

This step contains these views:

- Rules View
- Conditions View
- SKU-LOC View
- SKU-LOC-Phases View
- SKU-LOC-Week View

IPOCS-Lifecycle Allocation and Replenishment Rules Concept for the Supply Chain Network Task

IPOCS-Lifecycle Allocation and Replenishment provides a powerful engine that enables you to create a set of rules to apply all set up completed, within the Setup Task (BOD, Planning Calendar, and lifecycle calendar), down to the item and location levels. You can define multiple rules at a higher level using product, location and product-location attributes and then allow the IPOCS-Lifecycle Allocation and Replenishment Rule Engine to calculate at the lowest level, product and location combinations, and define the correct set up to be applied.

IPOCS-Lifecycle Allocation and Replenishment rules allows you to specify the period when the rule should be applied (if applicable) and the rules' priority. The rule priority allows IPOCS-Lifecycle Allocation and Replenishment to choose the correct rule to be applied if a product and location combination fits in more than one set up rule (the higher the number, the higher the priority). The rule start and end date are used by IPOCS-Lifecycle Allocation and



Replenishment to determine if the rule should be considered or discarded. If the IPOCS-Lifecycle Allocation and Replenishment system date falls within the start date and end date (or rule dates are empty) then it is considered. Otherwise, it is discarded.

Following are two examples and illustrations of rules for the set up task:

Rule 1

This rule should be configured to apply the Bill of distribution BOD1, the planning calendar PLC1 and the lifecycle calendar Clnd1.

- The scope of the rule is the scope of the rule group where it is being configured (for example, Apple Handset products and the country UK).
- The condition where the rule applies is for all items in the scope and for all locations which type is STORE.

Rule 2


This rule should be configured to apply the Bill of distribution BOD2, the planning calendar PLC2 and the lifecycle calendar Clnd2.

- The scope of the rule is the scope of the rule group where it is being configured (for example, Apple Handset products and the country UK).
- The condition where the rule applies is for all items in the scope and for all locations where the type is STORE.



The condition is used by the IPOCS-Lifecycle Allocation and Replenishment Rule Engine to apply the set up to the product and location combinations that match the condition within the rule scope. The rule scope is defined by the Product Groups and Location Groups associated with the rule's rule group.

Figure 19-24 Illustration for Rule 1





Plan Clnd 1

Plan Clnd 2

Plan Clnd 3

Prod / Loc Scope
Prod: OEM - Apple Handset Loc: UK

Prod / Loc Scope
Prod: OEM - Apple Handset Loc: UK

Rule Start / End Date
Start Date: Jan, 2
End Date:
Rule Priority
Priority 10

Rule Condition
Location Type = Warehouse

Rule 2

Figure 19-25 Illustration for Rule 2

Rules View

The **Rules View**, under the **Rules tab**, allows you to configure the rules by enabling them and defining the rule start date, end date and priority for each one. Once configured you can set up the rule by selecting the bill of distribution, the planning calendar, and the lifecycle calendar that the rule uses. The product and locations that apply the rule set up are based on the scope of the rule's rule group (Product Scope and Location Scope views) and the rule's condition that is set up and managed in the Conditions view.

ORACLE* Oracle Retail Applications Rules * Rules Consistens SKU-LOC SKU-LOC-Week SKU-LOC-Phases Statistics **≣ 4 ⊡ ±** + Rule Condition Rule Level v (LOG == Store Group (Q) AN 1 5 R.01.03 + (LDS == Store Group Web) R,01.06 R01.08 - (LDS -- Store Group Web) AND (POS -- SKU 0002) 07/01/2019 07/90/2019 2.00 D R.01.09 3.00 07/30/2019 + (LDG == Store Group 01) AND (PDG == Subdess 01) 2.00 8.01.12 y (LDL == Supplier New 01 OR == Supplier New 02 OR == Supplier New 03) v (100 == Store 013) R01.15 + (LDL == Store 028) 4.00 +

Figure 19-26 Rules View

Rules View - Measure Profiles

The Rules View contains the following profiles to change the measures that are visible in the view:



Default

This profile is used as default by the view. All the available or visible measures are listed and described in the section Measure: Default Profile.

BOD

This profile displays a subset of measures from the default profile. It focuses on the rule and on the BOD measures only. The Planning Calendar and Lifecycle calendar-related measures are left out of the visible measures.

Calendars

This profile displays a subset of measures from the default profile. It focuses on the rule and in the Planning Calendar measures only. BOD and Lifecycle calendarrelated measures are left out of the visible measures.

Lifecycle

This profile displays a subset of measures from the default profile. It focuses on the rule and on the lifecycle calendar only. The BOD and Planning calendarrelated measures are left out of the visible measures.

Rules View - Default Profile Measures

The Rules View contains the following measures.

Rule User Filter

The Rule User Filter is an editable measure to select the rule to filter the views by the selected rule. This measure is used by the **Run Filter** action button responsible to calculate the filters applied to the views within the Supply Chain Network workspace.

Rule Enable

The Rule Enable is an editable measure to enable or disable a rule. Each row (or list) represents a different rule.

Rule Condition

The Rule Condition is a calculated measure used to indicate the condition for which the rule is valid. The condition is the result of the set up completed in the Conditions view.

Rule Start Date

The Rule Start Date is an editable measure for you define a start date for the rule (when the rule should become active). When the rule is valid and the start date is empty, then IPOCS-Lifecycle Allocation and Replenishment applies it. When the rule is valid, and the start date is populated, IPOCS-Lifecycle Allocation and Replenishment starts to apply it only when the start date is reached.

Rule End Date

The Rule End Date is an editable measure for you define an end date for the rule (when the rule should become inactive). When empty IPOCS-Lifecycle Allocation and Replenishment assumes that the rule has no end date and if it is valid then IPOCS-Lifecycle Allocation and Replenishment applies it. When the rule is valid, and the end date is populated, IPOCS-Lifecycle Allocation and Replenishment stops applying it starting from the defined date.

Rule Priority



The Rule Priority is an editable measure for you define the rule's priority. The higher that the number is, then the higher the priority of the rule. This rule priority is important to IPOCS-Lifecycle Allocation and Replenishment as it is used when rules overlap each other. IPOCS-Lifecycle Allocation and Replenishment uses the rule priority to select which one to apply.

Rule Valid

The Rule Valid is a calculated measure used to indicate if the set up of the rule is valid or not. For example, if the BOD, Planning Calendar, and Lifecycle Calendar are missing then the rule is not valid for IPOCS-Lifecycle Allocation and Replenishment. IPOCS-Lifecycle Allocation and Replenishment needs at least one of them to be assigned for the rule to be considered valid.

PL Ass. Count

The Product and Location Associated Count is a calculated measure to display the total number of product and location combinations that are associated with the rule based on the rule's condition.

PL Ass. %

The Product and Location Associated Percentage is a calculated measure used to indicate, in percentage, how much the product and location combinations, where the rule is applicable, represent the total of product and location combinations within the rule group scope. The value of this measure is the result of the formula:

Figure 19-27 Calculation

$$100 * \frac{PL \ Ass. \ Count}{All \ PL \ Count}$$

Rule BOD

The Rule Bill of Distributions is an editable measure to select the bill of distribution to be applied by the rule. This measure is a picklist populated with all valid BODs that were set up in the Bill of Distributions view.

PL BOD App. Count

The Product and Location Bill of Distributions Applied Count is a calculated measure to display the total number of product and location combinations that apply this rule's BOD. The calculations take into account all the valid rules where the product and location combinations fall into and based on the priority calculates the count of product and location that applies the selected BOD.

PL BOD App. %

The Product and Location Bill of Distributions Applied Percentage is a calculated measure used to indicate, in percentage, how much the product and location combinations, where the rule's BOD is applicable, represent the total of product and location combinations within the rule group scope. The value of this measure is the result of the formula:



Figure 19-28 Calculation

$$100 * \frac{PL\ BOD\ App.\ Count}{All\ PL\ Count}$$

Rule Plc.

The Rule Planning Calendar is an editable measure to select the planning calendar to be applied by the rule. This measure is a picklist populated with all valid planning calendars that were set up in the Planning Calendars view.

PL Plc. App. Count

The PL Planning Calendar Applied Count is a calculated measure to display the total number of product and location combinations that apply this rule's planning calendar. The calculations take into account all the valid rules where the product and location combinations fall into and based on the priority calculates the count of product and location that apply to the selected planning calendar.

PL Plc. App. %

The PL Planning Calendar Applied Percentage is a calculated measure used to indicate, in percentage, how much the product and location combinations, where the rule's planning calendar is applicable, represent the total of product and location combinations within the rule group scope. The value of this measure is the result of the formula:

Figure 19-29 Calculation

$$100 * \frac{PL\ Plc.\ App.\ Count}{All\ PL\ Count}$$

Rule Lfc.

The Rule Lifecycle Calendar is an editable measure to select the lifecycle calendar to be applied by the rule. This measure is a picklist populated with all valid lifecycle calendars that were set up in the Lifecycle Calendars view.

PL Lfc. App. Count

The Product and Location Lifecycle Calendar Applied Count is a calculated measure to display the total number of product and location combinations that apply this rule's lifecycle calendar. The calculations take into account all the valid rules where the product and location combinations fall into and based on the priority calculates the count of product and location that apply to the selected lifecycle calendar.

PL Lfc. App. %

The Product and Location Lifecycle Calendar Applied Percentage is a calculated measure used to indicate, in percentage, how many of the product and location combinations, where the rule's lifecycle calendar is applicable, represent the total of product and location combinations within the rule group scope. The value of this measure is the result of the formula:



Figure 19-30 Calculation

$$100 * \frac{PL Lfc. App. Count}{All PL Count}$$

Copy and Paste

The Copy and Paste is an editable measure to select whether the rule is the source or destination for the copy and paste rules functionality (**Copy-Paste Rules** action button). Valid values are:

Copy

Option to select in the rule to be used as the source of the copy.

Paste

Option to select in the rule to be used as the destination of the copy.

.

Option selected to clear the measure.



Only one rule should be selected as a source (**Copy**) but multiple rules can be selected as a destination (**Paste**).

Conditions View

This view allows you to define the conditions for the rules based in product, location, and product-location attributes. A rule condition is what allows the engine to find the product and location combinations where the rule is applicable.

Figure 19-31 Conditions View



Conditions View - Default Profile Measures

The Conditions view contains the following measures.

Condition Attribute

The Condition Attribute measure allows you to select the attribute for the condition, The attributes for the rules are assigned in the Attribute Review workspace.

Within Cond Op



The Within Cond Op measure allows you to specify the operator to be used inside the condition.

Table 19-2 Within Cond Op Measure Available Operators

Possible Operators	Descriptions	Example
==	Checks if the attribute value is equal with the Condition Value	brand == Private Label
!=	Checks if the attribute value is different from the Condition Value	average sales != 0
>	Checks if the attribute value is larger than the Condition Value	Average sales >5
>=	Checks if the attribute value is larger or equal to the Condition Value	
<	Checks if the attribute value is less than the Condition Value	Standard deviation of sales <6
<=	Checks if the attribute value is less or equal to the Condition Value	
contain		
not contain		
match		
not match		

Cond Value

The Cond Value measure is used when the type of the attribute is numeric. Example: average sales > 10

Cond Value String

The Cond Value String measure is used when the type of the attribute is a string. Example: brand == Private Label

Cond Value Measure

The value of the Cond Value measure is a measure name, which is populated by an expression that let's you refine the condition value. For instance private label versus non-private label.

This measure is used when you want to refine the condition value.

For instance, for the coffee items, except Private Label, you want to assign items to the rule that sell more than 50 per week. For Private Label items you may want the value to be 100. You need to populate your Condition measure with a value of 100 for all Private Label items, and the rest of the coffee items with 50.

Cond Value Date

The Cond Value Date measure is used when the type of the attribute is a date. Example: today >= 02/30/2024"

Between Cond Op



Within a rule there can be multiple conditions and also multiple condition groups. This is specified in the Cond Group measure. Conditions with the same Cond Group value belong to the same group.

For example, if a rule has 4 conditions, Conditions 1 and 2 can belong to condition group 1, and conditions 3 and 4 can belong to the condition group 2. Also, the Cond Order measure gives the ranking of the conditions inside the group.

The following table is an assumed use case:

Table 19-3 Between Cond Op Assumed Use Case

			2 12	
Condition	Between Con Op	Cond Order	Cond Group	
Condition 1	AND	1	1	
Condition 2	OR	2	1	
Condition 3	OR	3	2	
Condition 4		4	2	

The value for the Between Cond Op can be the logical operators AND or OR.

The conditions are evaluated first inside a condition group and then between groups. In the previous case, the resulting condition is:

(Condition 1 AND Condition 2) OR (Condition 3 OR Condition 4)

Here is an example where all conditions belong to the same condition group:

Table 19-4 Example: All Conditions Belong to the Same Condition Group

Condition	Between Con Op	Cond Order	Cond Group
Condition 1	AND	1	1
Condition 2	OR	2	1
Condition 3	OR	3	1
Condition 4		4	1

The resulting condition for the rule is given by:

Condition 1 AND Condition 2 OR Condition 3 OR Condition 4

Note that the conditions are evaluated in the order given by the values in the Cond Order measure.

Cond Order

The Cond Order measure displays the order in which conditions are evaluated, wither independently or inside a condition group.

Cond Group

The Cond Group measure allows you to group conditions. This is useful when you want to evaluate conditions in a two-step process. First, the conditions are evaluated inside groups. In the second step, the group results are evaluated.

Validation Result



The Validation Result measure displays the condition expressions that are validated.

Invalid Flag

The Invalid Flag measure indicates if a condition is invalid.


Valid Flag

The Valid Flag measure indicates if a condition is valid.

SKU-LOC View

The **SKU-LOC View**, under the **SKU-LOC tab**, allows you to review the results of the IPOCS-Lifecycle Allocation and Replenishment Rule Engine calculation based on the rules set up in the workspace. In this view, you have to review to the results at the lowest level, item, and location levels, and you can also create exceptions, at the item-location level, to overwrite the replenishment set up calculated by the IPOCS-Lifecycle Allocation and Replenishment Rule Engine (for example, a particular item and location that should apply a different planning calendar from all the other item locations in the same rule).

Figure 19-32 SKU-LOC View



SKU-LOC View - Measure Profiles

The SKU-LOC View contains the following profiles to change the measures that are visible in the view:

Default

This profile is used as default by the view. All the available or visible measures are listed and described in **SKU-LOC View - Default Profile Measures**.

BOD

This profile displays a subset of measures from the default profile. It focuses on the rule and in the BOD measures only. Planning Calendar and Lifecycle calendarrelated measures are left out of the visible measures.



Planning

This profile displays a subset of measures from the default profile to focus on the Planning Calendar measures. BOD and Lifecycle calendar-related measures are left out of the visible measures.

Lifecycle

This profile displays a subset of measures from the default profile. It focuses on the rule and in the lifecycle calendar only. BOD and Planning calendar-related measures are left out of the visible measures.

SKU-LOC View - Default Profile Measures

The SKU-LOC View contains the following measures.

PL User Filter

The Product and Location User Filter is an editable measure to select the product and location combinations to filter the views by the selected product and location combinations. This measure is used by the **Run Filter** action button responsible to calculate the filters applied to the views within the Supply Chain Network workspace.

All PL

The All Product and Location is a calculated measure used to indicate if a product and location combination is valid or not. A selected measure indicates the combination is valid, meaning it has a lifecycle phase value. A clear measure indicates that it is not valid.

PL Valid

The Product and Location Valid is a calculated measure used to indicate if a product and location combination has a valid rule from where the IPOCS-Lifecycle Allocation and Replenishment Rule Engine calculates the replenishment set up. The measure is selected when the item and location combinations have at least one valid rule that applies. A clear measure indicates that it does not have at least one valid rule that applies.

PL BOD

The Product and Location Bill of Distribution is a calculated measure used to indicate that the bill of distribution is applied to the product and location combination. The bill of distribution displayed is the one calculated by the IPOCS-Lifecycle Allocation and Replenishment Rule Engine using the rules set up.

Ovr BOD

The Override Bill of Distributions is an editable measure that allows you to create exceptions at the item-location level. You can select the bill of distribution to override the assigned bill of distribution (measure PL BOD). This measure is a picklist populated with all valid BODs that were set up in the Bill of Distributions view.

PL BOD Prio

The Product and Location Bill of Distributions Priority is a calculated measure used to indicate the priority of the rule from where the bill of distribution was calculated for the product and location combination.

PL BOD End Date

The Product and Location Bill of Distributions End Date is a calculated measure used to indicate the end date of the rule from where the bill of distribution was calculated for the product and location combination.



PL BOD Rule Count

Product and Location Bill of Distributions Rule Count is a calculated measure used to indicate the total number of BOD that are assigned to the product and location combination based on the set up rules. Note that a product and location combination can only have one BOD active. The active one is the one from the rule with the highest priority or has an exception override.

PL Plc.

The Product and Location Planning Calendar is a calculated measure used to indicate the planning calendar applied to the product and location combination. The planning calendar displayed is the one calculated by the IPOCS-Lifecycle Allocation and Replenishment Rule Engine using the rules set up.

Ovr Plc.

The Override Planning Calendar is an editable measure that allows you to create exceptions at the item-location level. You can select the planning calendar to override the assigned planning calendar (measure PL Plc.). This measure is a picklist populated with all valid planning calendars that were set up in the Planning Calendars view.

PL Plc. Prio

The Product and Location Planning Calendar Priority is a calculated measure used to indicate the priority of the rule from where the planning calendar was calculated for the product and location combination.

PL Plc. End Date

Product and Location Planning Calendar End Date is a calculated measure used to indicate the end date of the rule from where the planning calendar was calculated for the product and location combination.

PL Plc. Rule Count

The Product and Location Planning Calendar Rule Count is a calculated measure used to indicate the total number of PLC that are assigned to the product and location combination based on the set up rules. Note that a product and location combination can only have one PLC active. The active one is the one from the rule with the highest priority or has an exception override.

PL Lfc.

The Product and Location Lifecycle Calendar is a calculated measure used to indicate the lifecycle calendar applied to the product and location combination. The lifecycle calendar displayed is the one calculated by the IPOCS-Lifecycle Allocation and Replenishment Rule Engine using the rules set up.

Ovr Lfc.

The Override Lifecycle Calendar. is an editable measure that allows you to create exceptions at the item-location level. You can select the lifecycle calendar to override the assigned lifecycle calendar (measure PL Lfc.). This measure is a picklist populated with all valid lifecycle calendars that were set up in the Lifecycle Calendars view.

PL Lfc. Prio



The Product and Location Lifecycle Calendar Priority is a calculated measure used to indicate the priority of the rule from where the lifecycle calendar was calculated for the product and location combination.

PL Lfc. End Date

The Product and Location Lifecycle Calendar End Date is a calculated measure used to indicate the end date of the rule from where the lifecycle calendar was calculated for the product and location combination.

PL Lfc. Rule Count

The Product and Location Lifecycle Calendar Rule Count is a calculated measure used to indicate the total number of lifecycle calendars that are assigned to the product and location combination based on the set up rules. Note that a product and location combination can only have one lifecycle calendar active. The active one is the one from the rule with the highest priority or has an exception override.

Primary Source @ Today

The Primary Source at Today is a calculated measure used to indicate the applied primary source for the product and location combination at the system date. The primary source is calculated from the current BOD assigned to the product and location combination.

Lead Time @ Today Dur (d)

The Lead Time at Today Duration (day) is a calculated measure used to indicate the applied lead time, in days, for the product and location combination at the system date. The lead time is calculated from the current BOD assigned to the product and location combination.

Reserved Source 1 @ Today

The Reserved Source 1 at Today is a calculated measure used to indicate the applied reserved source 1 for the product and location combination at the system date. The reserved source 1 is calculated from the current BOD assigned to the product and location combination.

Reserved Source 2 @ Today

The Reserved Source 2 at Today is a calculated measure used to indicate the applied reserved source 2 for the product and location combination at the system date. The reserved source 2 is calculated from the current BOD assigned to the product and location combination.

Alternative Source @ Today

The Alternative Source at Today is a calculated measure used to indicate the applied alternative source for the product and location combination at the system date. The alternative source is calculated from the current BOD assigned to the product and location combination.

LLC @ Today

The Low-level Code at Today is a calculated measure used to indicate the low-level code applied to the product and location combination at the system date. The low-level code is calculated from the current BOD assigned to the product and location combination and the valid values are:

- 0: The location is a store
- 1: The location is a warehouse



- 2: The location is a supplier
- -1: The location is invalid

Network Loop @ Today

The Network Loop at Today is a calculated measure used to indicate if there are Network Loop errors caused by the BOD set up for the rule group at the system date. When selected, there are Network Loop errors. Otherwise, there are no errors.

Revw @ Today

The Review at Today is a calculated measure used to indicate if today (current system date) is a review day for the product and location combination. The review day is calculated from the current planning calendar assigned to the product and location combination.

Next Revw @ Today Date

The Next Review at Today Date is a calculated measure used to indicate the next review date for the product and location combination. The next review date is calculated from the current planning calendar assigned to the product and location combination.

Next Revw @ Today Dur (d)

The Next Review at Today Duration (day) is a calculated measure used to indicate the number of days to the next review date for the product and location combination. The calculation of the number of days uses the current system date and the Next Revw @ Today Date.

Avg Revw Time @ Today Dur (d)

The Average Review Time at Today Duration (day) is a calculated measure used to indicate the average number of days between each review period (planning period) for the product and location combination. The value is calculated using the review periods from the current planning calendar assigned to the product and location combination.

Asst. Prod-Loc

The Assorted Product and Location is a loaded measure used to indicate whether the product and location combinations are assorted or not.

Asst. Prod-Loc Start Date

The Assorted Product and Location Start Date is a loaded measure used to indicate the assortment start date for the assorted product and location combinations.

Asst. Prod-Loc End Date

The Assorted Product and Location End Date is a loaded measure used to indicate the assortment end date for the assorted product and location combinations.

Asst. Prod-Loc Active

Assorted Product and Location Active is a loaded measure used to indicate whether the product and location combinations are assorted and still active or not. If the assortment end date has not been reached yet then it is active. Otherwise, the product and location combination is assorted but not active.

Lfc. Prod-Loc Def.



The Lifecycle Calendar Product and Location Default is a loaded measure to identify whether the product and location combination has a valid lifecycle by default or not.

Lfc. Prod-Loc Exc.

The Lifecycle Calendar Product and Location Exception is a loaded measure used to indicate whether the lifecycle is an exception for the product and location combination. Check the measure Lfc. Prod-Loc Exc. in the Assortment Admin workspace for more detail on the valid values.

Lfc. Prod-Loc Validity Start Date

The Lifecycle Calendar Product and Location Validity Start Date is a loaded measure used to indicate the lifecycle start date exception for the product and location combination when there is an exception.

Lfc. Prod-Loc Validity End Date

The Lifecycle Calendar Product and Location Validity End Date is a loaded measure used to indicate the lifecycle end date exception for the product and location combination when there is an exception.

Lfc. Prod-Loc

The Lifecycle Calendar Product and Location is a loaded measure to identify whether the product and location combination has a valid lifecycle or not.

Lfc. Anchor Exc. Date

The Lifecycle Calendar Anchor Exception Date is a loaded measure to identify the lifecycle anchor date exception for the product and location combination when there is an exception.

Lfc. End Exc. Date

The Lifecycle Calendar End Exception Date is a loaded measure to identify the lifecycle's exception end date for the product and location combination when there is an exception.

Actual Loc. Sales Units

The Actual Location Sales Units is a loaded measure to display the actual sales for the product and location combination. The value displayed for the product and location combination is the aggregation of all the weeks that are in the scope of the workspace.

Tot. Init. Fcst Units

The Total Initial Forecast Units is a loaded measure to display the total initial forecast for the product and location combination. The value displayed for the product and location combination is the aggregation of all the weeks from the current week up to the forecast horizon.

Lfc. Active @ Today

The Lifecycle Calendar Active at Today is a loaded measure used to indicate whether the product and location combination has a valid lifecycle or not at the system date.

Lfc. Active @ Today


The Lifecycle Calendar Active at Today is a loaded measure used to indicate the lifecycle phase string for the product and location combination when the product and location combination has a valid lifecycle at the system date.



SKU-LOC-Week View

The **SKU-LOC-Week View**, under the **Review tab**, allows you to review and overwrite the review weeks and receipt weeks. Any overrides are on top of the review weeks and receipt weeks that the IPOCS-Lifecycle Allocation and Replenishment calculates using the planning calendar set up for the product and location combination.

Figure 19-33 SKU-LOC-Week View



SKU-LOC-Week View - Default Profile Measures

The SKU-LOC-Week View contains the following measures.

Revw Cal. (Wk) @ Today

The Review Calendar (Week) at Today is an editable measure used to indicate whether the week is a review week or not based on the planning calendar set up for the product and location combination at the system date. You can override the calculated value.

Rcpt Cal. (Wk) @ Today

The Receipt Calendar (Week) at Today is an editable measure used to indicate whether the week is a receipt week or not based on the planning calendar set up for the product and location combination at the system date. You can override the calculated value.

Asst. Var-Loc-Wk

The Assorted Variant-Location-Week is a calculated measure used to indicate whether a Var-Location is assorted or not for the given week. (Note if one item under the Variant is assorted then this is indicated as true).


Asst. Var-Loc-Wk Count



The Assorted Variant-Location-Week Count is a calculated measure used to indicate whether a Var-Location is assorted or not for the given week. (Note if one item under the Variant is assorted then this is indicated as true).

Asst. Var-Loc-Wk


The Assorted Variant-Location-Week is an image measure that aligns with the Asst. Var-Loc-Wk Count.



SKU-LOC-Phases View

The **SKU-LOC-Phases View**, under the **Review tab**, allows you to review the lifecycle phases for the product and location combinations. In addition, you are allowed to overwrite the start date of each lifecycle phase at the product and location combination level.

Figure 19-35 SKU-LOC-Phases View





SKU-LOC-Phases View - Default Profile Measures

The SKU-LOC-Phases View contains the following measures.

Lfc. Phase @ Today

The Lifecycle Calendar Phase at Today is a loaded measure used to indicate the list of lifecycle phases for the product and location combination based on the lifecycle calendar set up at the system date. The phase names are prefixed and suffixed to provide you with additional information, the logic is as follows:

<>

When the phase name is prefixed and suffixed this way, it means that the phase is the current lifecycle phase (for example, <Maturity>

• ()

When the phase name is prefixed and suffixed this way, it means that the phase is an elapsed/previous lifecycle phase (for example, (Discovery)

When the phase name has no prefix and suffix, it means the lifecycle phase has not been reached yet (for example, **EOL**)

Lfc. Phase Excp. Start Date

The Lifecycle Calendar Phase Exception Start Date is an editable measure that allows you to override the phase start date set up in the lifecycle calendar assigned to the product and location combination.

Filter Step

This step contains these views:


- Filter Parameters View
- Calendar Filter View

Filter Parameters View

The **Filter Parameters View**, under the **Filter tab**, allows you to set up the filter that can change the scope of the products and locations displayed in all relevant views under the Rules Step within the Supply Chain Network Workspace.



Figure 19-36 Filter Parameters View



Filter Parameters View - Default Profile Measures

The Filter Parameters View contains the following measures.

Filter Not Valid

The Filter Not Valid is an editable measure to change the scope of the products and locations displayed in all relevant views under the Rules Step. If the measure is selected the **Run Filter** action button is responsible to calculate the filters only displayed as non-valid product and location combinations. When clear the filter only displays valid product and location combinations. By default, the measure is clear. The measure PL Valid identifies whether a product and location combination is valid or not.

Rule -> PL Filter

Rule -> Product and Location Filter is an editable measure to select how the filter should work in the SKU- LOC view. Valid values are:

Associated

The view is filtered to display the product and location combinations that are associated with the rules selected in the Rules view (measure Rule User Filter). Note that product and location combinations can fit within more than one rule. When they fit into a rule, they are associated regardless of whether that rule is the actual one to be applied.

Applied

The view is filtered to display the product and location combinations that apply the rules selected in the Rules view (measure Rule User Filter). The rule is considered applied when the IPOCS-Lifecycle Allocation and Replenishment Rule Engine sets the replenishment set up for the product and location combination based on the rule (for example, BOD, PLC, and so on.).

PL -> Rule Filter

The Product and Location -> Rule Filter is an editable measure to select how the filter should work in the Rules view. Valid values are:



Associated

The view is filtered to display rules that are associated with the product and location combinations selected in the SKU-LOC view (measure PL User Filter). Note that product and location combinations can fit into more than one rule. When they fit in a rule they are associated regardless of whether that rule is the actual one to be applied.


Applied

The view is filtered to display rules that are associated with the product and location combinations selected in the SKU-LOC view (measure PL User Filter). The rule is considered applied when the IPOCS-Lifecycle Allocation and Replenishment Rule Engine sets the replenishment set up for the product and location combination based on the rule (for example, BOD, PLC, and so on.).

Calendar Filter View

The Calendar Filter View, under the SKU-LOC-Week tab and Statistics tab, allows you to choose the number of weeks to filter based on the weeks displayed in the SKU-LOC view- Week. This view is the same as the Calendar Filter view under the Planning Calendar Step. For more details on the measures, check the Calendar Filter view measures in the Planning Calendar Step.

Figure 19-37 Calendar Filter View



Supply Chain Network Action Buttons

The Supply Chain Network workspace has the following action buttons available:

Copy-Paste Exceptions

Use the **Copy-Paste Exceptions** action button to copy the planning daily exceptions from the planning calendar selected as the source of the copy and paste into all planning calendars selected as the destination of the copy. This



action only copies the daily exceptions. It does not copy any other planning calendar (for example, weekdays).

Copy-Paste LFC

Use the **Copy-Paste Lifecycle Calendar** action button to copy the lifecycle calendar information from the lifecycle calendar selected as the source of the copy and paste it into all the lifecycle calendars selected as the destination of the copy. This action copies all the information in the lifecycle calendar view and lifecycle phase view.

Copy-Paste Rules

Use the **Copy-Paste Rules** action button to copy all rule information from the rule selected as the source of the copy and paste it into all rules selected as the destination of the copy. This action copies all the information in the Rules view and Conditions view.

Rule Conditions

Use the **Rule Conditions** action button for the calculation of the rule's conditions based on the set up completed in the Conditions view. The result of the calculation is written into the measure Rule Condition in the Rules view.

Rule Engine

Use the **Rule Engine** action button for running the IPOCS-Lifecycle Allocation and Replenishment Rules Engine to calculate which rule's replenishment set up would be applied to the product and location combination level. The results of the run are visible in the statistic measures of the Rules view as they are updated with the run results. To ensure that the IPOCS-Lifecycle Allocation and Replenishment Rules Engine is run with the right conditions for all the rules, this action button runs the Rule Conditions first, as part of its process.

Rule Apply

Use the **Rule Apply** action button for applying the rule's replenishment set up, from the last Rule Engine run, down to the product and location combination level. The results of the run are visible in the SKU-LOC view as the measures are updated with the run results.

Rule Engine + Apply

Use the **Rule Engine + Apply** action button to run the **Rule Engine** action button followed by the run of the **Rule Apply** action button. As a result, the IPOCS-Lifecycle Allocation and Replenishment Rule Engine is run, and the results are applied down to the product and location combination level immediately.

Clear Filter

Use the **Clear Filter** action button to remove all filters applied in the Supply Chain Network view and clear all User Filter measures within the workspace.

Run Filter

Use the **Run Filter** action button to apply the filters in the Supply Chain Network views based on the filter set up completed within the workspace. For example, the calendar horizon or check the filtered measures.

Reload Attributes

Use the **Reload Attributes** action button to load the product, location, and product-location attributes from the domain into the workspace. It refreshes the measures available for all the views under the Attributes Step.

Commit Attributes



Use the **Commit Attributes** action button to save the domain, product, location, and product-location attributes. This functionally ensures that any user changes to the attributes within the workspace are saved and committed to the domain.

Note:

When product, location and product-location attributes are interfaced into IPOCS-Lifecycle Allocation and Replenishment your changes are overridden by the interface values during the batch run.

Calc. Visual Assort.

Use the **Calculate Visual Assortment** action button to display a visual representation of your assortment.

Reload Valid Intersections

Use the **Reload Valid Intersections** action button to load the assortment information from the domain into the workspace. It refreshes all assortment and lifecycle related information. You can use this option when changes are performed in the Assortment Admin workspace and should be refreshed in the Supply Chain Network workspace.

Figure 19-38 Supply Chain Network Action Buttons



Replenishment Parameters

This chapter describes the functionality that allows you to set up and review the replenishment and inventory parameters that are used within the Allocation & Replenishment calculations. The Replenishment Parameters Workspace is where you can set up the replenishment parameters, change parameters, constraint parameters and inventory planning parameters. Once they are defined you can configure rules and conditions to specify where they should be applied. In a similar way to the Supply Chain Network workspace, the rule engine does the heavy work for you and calculates the right parameters at the product and location level using the available assortment and lifecycle information.

You can further specify the priority and the period where the rule should apply (start and end date if applicable). Based on the set up, the rules engine determines the most appropriate rule and then distributes the parameter to each item and location.

Rpl. | Rpl.2 | Rpl.3 | Prod / Loc Scope | Prod : All Items | Loc: All Locations | Loc: All Locations | Rule Start / End Date | Start Date: Jan, 2 | End Date: . | Rule Priority | Priority 10 | Rule Priority | Rule Priority | Priority 10 | Rule Priority | Rule Priority | Priority 10 | Rule Priority | Priority 10 | Rule Priority | Rule Priority | Rule Priority | Priority 10 | Rule Priority | Rule Priority | Priority 10 | Rule Priority | Priority | Priority | Priority | Rule Priority | P

Figure 20-1 Rules Engine Process

Replenishment Parameters Workspace, Steps, and Views

The following table lists the workspaces, steps, and views of the Replenishment Parameters task.

Table 20-1 Replenishment Parameters Workspace, Steps, and Views

Workspace	Steps	Tab	Views
Replenishment Parameters Workspace	Overview	Overview	Statistics View
		Scope	Location Scope View
			Product Scope View



Table 20-1 (Cont.) Replenishment Parameters Workspace, Steps, and Views

Workspace	Steps	Tab	Views
	Replenishment Parameters	Replenishment Parameters	Replenishment Parameters View
			Replenishment Change Parameters View
			Default Replenishment Parameters View
	Inventory Plan Parameters	Inventory Plan Parameters	Inventory Plan Parameters View
	Constraint Parameters	Constraint Parameters	Constraint Parameters View
			Default Store Priority View
	Rules	Setup	Conditions View
			Rules View
		Review	SKU-LOC View
	Filter	Filter	Filter Parameters View


Replenishment Parameters Workspace

The Replenishment Parameters workspace allows you to access all the views listed in the Replenishment Parameters Workspace, Steps, and Views. To build the Replenishment Parameters workspace, perform these steps:

1. From the left sidebar menu, click the **Task Module** to view the available tasks.




Figure 20-2 Task Module



- 2. Click the **Business Rule Setup** activity to access the available workspaces.
- 3. Click Replenishment Parameters.
- **4.** The Replenishment Parameters wizard opens. You can open an existing workspace, but to create a new workspace, click **Create New Workspace**.

Figure 20-3 Replenishment Parameters Wizard




5. Enter a name for your new workspace in the label text box and click **OK**.

Figure 20-4 Enter Workspace Label



6. Select the rule groups you want to work with and click **Finish**.

Figure 20-5 Workspace Wizard: Rule Groups





Only the rule groups that are from the Replenishment rule group type are available for selection. The rule group type value is managed in the Manage Rule Groups workspace.

7. The wizard notifies you that your workspace is being prepared. Successful workspaces are available from the Dashboard.

Dashboard

Dashboard

Dashboard

Dashboard

Task Status

Administration

Edit Dashboard

Task Status

Edit Opened

Task Status

Edit O

Figure 20-6 Successful Workspace Build

Note:

The workspace is built using the selected rule group scope. The products, locations, source locations and attributes available in the workspace are the ones in the rule group scope that is managed in the Manage Rule Groups workspace.

Overview Step

This step contains these views:


- Statistics View
- Location Scope View
- Product Scope View

Statistics View

The **Statistics View**, under the **Overview tab**, allows you to review the statistics of the Replenishment Parameters. The view has statistical information regarding the number of valid counts for each set up (for example, Replenishment Parameters, Change Parameters) and rules. It also provides the number of product and location combinations within the workspace.



Figure 20-7 Statistics View



Statistics View - Default Profile Measures

The Statistics view contains the following measures.

Rule Group Type

Rule Group Type is a loaded read-only measure used to display the rule group type that was set up for the rule group in the Manage Rule Group workspace.

Rule Group User Descr.

Rule Group User Description is a loaded read-only measure used to display the user-description that was set up for the rule group in the Manage Rule Group workspace.

Last Rule Group Publish User ID

Last Rule Group Publish User ID is a loaded read-only measure used to display the user-identifier that performed the last rule group's change in the Manage Rule Group workspace.

Last Rule Group Publish Date

Last Rule Group Publish Date is a loaded read-only measure used to display the date and time when the last rule group's change was performed in the Manage Rule Group workspace.

Repl. Valid Count

Replenishment Valid Count is a calculated measure used to display the total number of valid replenishment parameters that are set up for the rule group.

Chg. Valid Count

Change Valid Count is a calculated measure used to display the total number of valid change parameters that are set up for the rule group.

Cstr. Valid Count

Constraint Valid Count is a calculated measure used to display the total number of valid constraint parameters that are set up for the rule group.



Inv. Plan. Valid Count

Inventory Plan Valid Count is a calculated measure used to display the total number of valid inventory plan parameters that are set up for the rule group.

Rule Valid Count

Rule Valid Count is a calculated measure used to display the total number of valid rules that are set up for the rule group.

All PL Count

All Product and Location Count is a calculated measure used to display the total number of product and location combinations that have a lifecycle phase value.

PL Valid Count

Product and Location Valid Count is a calculated measure used to display the total number of product and location combinations that have a valid rule assigned.

PL Valid %

Product and Location Valid Percentage is a calculated measure used to indicate, in percentage, how much the product and location combinations with a valid rule assigned represent in the total of product and location combinations with a lifecycle phase value. The measure is calculated as:

Figure 20-8 Calculation


$$100*\frac{PLValidCount}{AllPLCount}$$

Location Scope View

The **Location Scope View**, under the **Scope tab**, allows you to review what specific locations are in the scope of a rule group and loaded into the workspace.



Figure 20-9 Location Scope View



Location Scope View - Default Profile Measures

The Location Scope view contains the following measure.


LOC Group Assoc.

Location Group Associated is a loaded read-only measure used to indicate the location groups that are associated with the rule group. This measure is managed in the Manage Rule Groups workspace.

Product Scope View

The **Product Scope View**, under the **Scope tab**, allows you to review what specific products are in the scope of a rule group and loaded into the workspace.

Figure 20-10 Product Scope View





Product Scope View - Default Profile Measures

The Product Scope view contains the following measure.

PROD Group Assoc.

Product Group Associated is a loaded read-only measure used to indicate the products groups that are associated with the rule group. This measure is managed in the Manage Rule Groups workspace.

Replenishment Parameters Step

This step contains these views:

- Replenishment Parameters View
- Replenishment Change Parameters View
- Default Replenishment Parameters View

Replenishment Key Concepts

Replenishment parameters are used to specify the Reorder Level (ROL) and the Reorder Up to Level (RUTL) methods along with the associated parameters that is used in generating point in time planned orders.

Reorder Level (ROL) is the inventory level that determines whether an order for replenishment should be placed at the time of review or not. At the time of review, if the stock levels are less than the ROL, then an order for replenishment is placed, otherwise it is ignored until the next cycle.

Reorder Up to Level (RUTL) is level that must be maintained to meet expected service levels for demand fulfilment.

Figure 20-11 ROL and RUTL



The replenishment is a point in time replenishment. In another words, it calculates the replenishment units, for a particular product and location combination, to fulfil the demand from the system date until the next planning day in the planning calendar plus the lead time.



Planning Today Calendar **Evaluate Execution Order** From Today to Next Planning Calendar Day Plus Lead time X X Today **Total Need** Total Inventory (100Units) 150 Units Total Need (150Units) Total X Inventory Today 100 Units Generate Next Order 50Units

Figure 20-12 Point in Time Replenishment

Point in Time Replenishment Methods

Lifecycle Inventory Planning has the following replenishment methods for the ROL and RUTL calculations.

ROL Methods

- Statistical SS (Statistical Safety Stock): This replenishment method calculates the ROL taking into account the cumulated demand forecast from current date up to the number of days set as Lead Time plus Next Review Time. It considers the Target Service Level (Tgt SL %) and Volatility (Volatility %) in the calculation too
- Min Time Supply (Minimum Time Supply): This replenishment method
 calculates the ROL taking into account the cumulated demand forecast from
 current date up to the number of days defined as minimum time to supply (in
 days).
- **Min Quantity (Minimum Quantity)**: This replenishment method calculates the ROL taking into account the value defined as the minimum quantity units.
- Min Safety Time (Minimum Safety Time): This replenishment method calculates
 the ROL to the cumulated demand forecast from the first forecast date up to the
 number of days set to Lead Time plus Next Review Time plus the number of days
 to shift set in Min Safety Time (days).
- **Min (Minimum)**: This replenishment method calculates the ROL to the minimum of the active ROL methods.
- Max (Maximum): This replenishment method calculates the ROL to the maximum
 of the active ROL methods.
- Sum (Sum): This replenishment method calculates the ROL to the sum of the active ROL methods.

RUTL Methods



- Max Quantity (Maximum Quantity): This replenishment method calculates the RUTL taking into account the value defined as the maximum quantity units.
- Max Time Supply (Minimum Time Supply): This replenishment method calculates the RUTL taking into account the cumulated demand forecast from current date up to the number of days defined as maximum time to supply (in days).
- Target DOS (Days Of Supply): This replenishment method calculates the RUTL taking into account the cumulated demand forecast from current date up to the number of days defined as days of supply or up to the number of days of Lead Time plus Next Review Time. The application picks the highest number of days between the two options.
- Target Stock: This replenishment method more suitable to the short lifecycle products.
 The replenishment engine calculates the RUTL based on a target stock quantity. The target stock quantity can be calculated using the following options.
 - Fixed 1: This method sets the target stock to the initial allocation quantity (loaded from external sources).
 - Fixed 2: This method sets the target stock to an user-entered allocation quantity (managed within IPOCS-Lifecycle Allocation and Replenishment).
 - Fixed 3: This method sets the target stock to any other potential source for the initial allocation (this is a placeholder than can be used by customers).
 - Ssn Perc: This method sets the target stock a percentage of the total season sales.
 Used to define percentage to calculate the value from the total initial forecast for the season.
 - Sft. Time: This method sets the target stock to the cumulated demand forecast from the first forecast date in the future up to the number of days set to Lead Time plus Next Review Time plus the number of days to shift.
 - Stat SS (Statistical Safety Stock): This method sets the target stock to the cumulated demand forecast from current date up to the number of days set as Lead Time plus Next Review Time. It considers the Target Service Level (Tgt SL %) and Volatility (Volatility %) in the calculation too.
 - EOL (End of Life): This method sets the target stock to the cumulated demand forecast from current date up to the end of life date. It considers the Target Service Level (Tgt SL %) and Volatility (Volatility %) in the calculation too.
- **Min (Minimum)**: This method sets the target stock to the minimum of the active Target Stock methods (excluding End of Life).
- **Max (Maximum)**: This method sets the target stock to the maximum of the active Target Stock methods (excluding End of Life).
- **Sum (Sum)**: This method sets the target stock to the sum of the active Target Stock methods (excluding End of Life).
- **Min (Minimum)**: This replenishment method calculates the RUTL to the minimum of the active RUTL methods.
- Max (Maximum): This replenishment method calculates the RUTL to the maximum of the active RUTL methods.
- Sum (Sum): This replenishment method calculates the RUTL to the sum of the active RUTL methods.



Target Stock Fixed (initial, store, user, etc.) % of Total Season Sales Target DOS Inventory Classic Methods RUTL Level **Max Time Supply** Safety Time order Up To-Level Statistical SS **Max Quantity** Min / Max / Sum of active above Min / Max / Sum Unconstrained Replenishment End of Life + Service Level % Min Quantity ROL Min Time Supply Reorder Statistical SS Availability Min Safety Time

Min / Max / Sum

Figure 20-13 Point in Time Replenishment Methods

Figure 20-14 ROL and RUTL Method Details

Today







Figure 20-15 ROL and RUTL Method: Target Stock Details



Replenishment Parameters View

The Replenishment Parameters View, under the Replenishment Parameters tab, allows you to set up of all possible Replenishment Parameters that can be used by the replenishment parameters rules to be applied on products and locations for the Replenishment (Point-In-Time) calculation. Each list (row) in the view represents a different replenishment parameter set up.

Figure 20-16 Replenishment Parameters View



Replenishment Parameters View - Default Profile Measures

The Replenishment Parameters view contains the following measures.

Repl. Enable

Replenishment Enable is an editable measure used to enable or disable a replenishment parameter. Each row (or list) represents a different replenishment parameter.

Repl. Valid



Replenishment Valid is a calculated measure used to indicate if the set up of the replenishment parameter is valid or not. For example, if the ROL and RUTL methods are missing then the replenishment parameter is not valid for the rule engine.

Repl. Desc.

Replenishment Description is a calculated measure used to indicate the replenishment parameter description. The description is calculated based on the replenishment parameter user-defined description and the replenishment parameter set up selected by you.

Repl. User Desc.

Replenishment User Description is an editable measure used to enter a user-defined replenishment parameter description. The final replenishment parameter description takes the user-defined description into consideration. The entered value must not contain a colon punctuation mark (:).

Min Cred. Qty Units

Minimum Credit Quantity Units is an editable measure used to define the minimum amount of stock desired to have on hand for sales purposes.

ROL Meth.

Reorder Level Method is an editable measure to select the method to be used by the replenishment engine to calculate the ROL. Valid values are:

.

Option to clear the ROL Method.

Min Qty

Option to set up the ROL Method as the Minimum Quantity method. When selected the ROL is calculated to the value set in the measure Min Quantity Units.

Min TS

Option to set up the ROL Method as the Minimum Time Supply method. When selected the ROL is calculated value of the cumulated demand forecast from current date up to the number of days set in the measure Min TS Dur (d).

Stat SS

Option to set up the ROL Method as the Statistical Safety Stock method. When selected the ROL calculation uses the lead time, the next review time in the planning calendar, the service level set in the measure Tgt. SL % and the volatility set in the measure Volatility %.



When the RUTL method is set to Tgt Stk the RUTL and ROL will have the same value. No need to select the ROL method in this case.

Min Qty Units

Minimum Quantity Units is an editable measure used to fix the minimum amount of stock desired when the ROL method is set to Min Quantity.



Min TS Dur (day)

Minimum Time Supply Duration (d) is an editable measure used to fix the number of days to use to calculate the ROL value from the cumulative demand forecast. This measure is used when the ROL method is set to Min TS.

Tgt. SL %

Target Service Level Percentage is an editable measure used to define the service level. This value is used in the ROL and RUTL calculation when the statistical safety stock method is used.

Volatility %

Volatility Percentage is an editable measure used to define the volatility. This value is used in the ROL and RUTL calculation when the statistical safety stock method is used.

ROL Sft. Time Dur (d) RUTL Meth.

Reorder Level Sft. Time Duration (day) Reorder Up to Level Method is an editable measure to select the method to be used by the replenishment engine to calculate the RUTL. The valid values are:

•

Option to clear the RUTL Method.

Max Qty

Option to set up the RUTL Method as the Maximum Quantity method. When selected the RUTL is calculated to the value set in the measure Max Quantity Units.

Max TS

Option to set up the RUTL Method as the Maximum Time Supply method. When selected the RUTL is calculated to the value of the cumulated demand forecast from current date up to the number of days set in the measure Max TS Dur (d).

Tgt. DoS

Option to set up the RUTL Method as the Target Days of Supply method. When selected the RUTL is calculated to the value of the cumulated demand forecast from current date up to the highest number of days from the following options.

- Number of days fixed in the measure Tgt. DoS Dur (d)
- Number of days of lead time plus number of days to the next review time

Tgt Stk

Option to set up the RUTL Method as the Target Stock method. When selected the RUTL is calculated using the method selected in the measure TS Meth.



When the RUTL method is set to Tgt Stk the RUTL and ROL will have the same value. No need to select the ROL method in this case.

Tgt. DoS Dur (d)



Target Days of Supply Duration (day) is an editable measure used to fix the number of days to use to calculate the RUTL value from the cumulative demand forecast. This measure is used when the RUTL method is set to Tgt DoS.

TS Meth.

Target Stock Method is an editable measure to select the target stock method to be used by the replenishment engine when the RUTL method is Tgt Stk. The valid values are:

•

Option to clear the target stock Method.

Fixed 1

When selected the target stock is calculated to the value set in the measure TS Fixed 1 (initial allocation).

Fixed 2

When selected the target stock is calculated to the value set in the measure TS Fixed 2 (manual allocation).

Fixed 3

When selected the target stock is calculated to the value set in the measure TS Fixed 3 (placeholder for other source of allocation).

Ssn Perc

When selected the target stock is calculated as a percentage of the total forecast sales for the season. The percentage used in the calculation is the one set in the measure TS Seas. Fcst %.

Sft Time

When selected the target stock is calculated to the value of the cumulated demand forecast from current date up to the number of days of the lead time plus the number of days to the next review time plus the number of days for the Target Stock Safety Time Duration (measure TS Sft. Time Dur (d)).

Stat SS

When selected the target stock is calculated to the value of the cumulated demand forecast plus the safety stock from current date up to the number of days of the Lead Time plus the number of days for the next review time plus the number of days for the Target Stock Safety Time Duration (measure TS Sft. Time Dur (d)). It also considers the service level set in the measure Tgt. SL % and the volatility set in the measure Volatility % when calculating the target stock.

• EOL

When selected the target stock is calculated to the value of the cumulated demand forecast plus the safety stock from current date up to the number of days to reach the end-of-life date. It also considers the service level set in the measure Tgt. SL % and the volatility set in the measure Volatility % when calculating the target stock.

Min

When selected the target stock is the minimum value from the methods of Fixed, % of Total Season Sales, Safety Time and Statistical SS.

Max



When selected the target stock is the maximum value from the methods of Fixed, % of Total Season Sales, Safety Time and Statistical SS.

TS Sft. Time Dur (d)

Target Stock Sft. Time Duration (day) is an editable measure used to set the number of days for the stock safety. This value is used in the target stock calculations when the RUTL method (RUTL Meth.) is set to Tgt Stk and the target stock method (TS Meth.) is set either to Sft Time or to Stat SS.

TS Seas. Fcst %

Target Stock Seasonal Forecast Percentage is an editable measure used to set the percentage of the Seasonal Forecast that should be used to calculate the target stock. This value is used when the RUTL method (RUTL Meth.) is set to Tgt Stk and the target stock method (TS Meth.) is set Ssn Perc.

Max Qty Units

Max Quantity Units is an editable measure used to fix the maximum amount of stock desired when the RUTL method is set to Max Quantity.

Max TS Dur (d)

Max Target Stock Duration (day) is an editable measure used to fix the number of days to use to calculate the RUTL value from the cumulative demand forecast. This measure is used when the RUTL method is set to Max TS.

Order Round

Order Round is an editable measure used to set the percentage on when to round up the orders if the pack size is greater than 1.

Rule Rpl. Count

Rule Replenishment Count is a calculated measure used to display the total number of rules that are using the replenishment parameter.

PL Rpl. Count

Product and Location Replenishment Count is a calculated measure used to display the total number of product and location combinations that associated with the replenishment parameter.

PL Rpl. %

Product and Location Replenishment Percentage is a calculated measure used to indicate, in percentage, how much the product and location combinations associated with the replenishment parameter represents in the total of product and location combinations with a lifecycle phase value. The measure is calculated as:

Figure 20-17 Calculation

$$100 * \frac{PLRplCount}{AllPLCount}$$



Rpl. User Filter

Rpl. User Filter is an editable measure used to select the replenishment parameter to filter the views by the selected replenishment parameter. This measure is used by the **Run Filter** action button responsible to calculate the filters applied to the views within the Replenishment Parameters workspace.

Replenishment Change Parameters Concept

Replenishment change parameters allows you to set up parameters to override the system calculated Re-Order Level (ROL) and the Re-Order Up to Level (RUTL) values (calculated from the replenishment parameters set up).

The change replenishment parameters provide the following capabilities. You can:


- Define a percentage to increase or decrease the system calculated ROL and RUTL.
- Override the replenishment parameters status. When a replenishment parameter status is enabled, the change parameter can force the replenishment parameter status to disable and the other way around.

As an example, the replenishment change parameters can be leveraged to prepare for an upcoming event by incising the RUTL providing the adequate stock to cover the upcoming demand.

Following are some examples of a set up for the change parameters:

- ON Overrides replenishment parameters status to Enable OFF Overrides replenishment parameters status to Disable
- RUTL +10% Overrides the system calculated receipt up to level to increase it by 10%
- RUTL +25 % Overrides the system calculated receipt up to level to increase it by 25%
- RUTL -10 % Overrides the system calculated receipt up to level to decrease it by 10%
- RUTL -25 % Overrides the system calculated receipt up to level to decrease it by 25%

Figure 20-18 Replenishment Change Parameters RUTL +10%










Figure 20-19 Replenishment Change Parameters RUTL +10% & ROL +10%






Replenishment Change Parameters View

The Replenishment Change Parameters View, under the Replenishment Parameters tab, allows you to set up changes to the existing replenishment set up. The change parameters allows you to increase or decrease the calculated RUTL and ROL values and also allows you to override the replenishment status by enabling or disabling it.

Figure 20-20 Replenishment Change Parameters View



Replenishment Change Parameters View - Default Profile Measures

The Replenishment Change Parameters view contains the following measures.

Chg. Enable

Change Enable is an editable measure used to enable or disable a replenishment change parameter. Each row (or list) represents a different replenishment change parameter.

Chg. Valid

Change Valid is a calculated measure used to indicate if the set up of the replenishment change parameter is valid or not. For example, if the replenishment status is kept as default

and no ROL and/or RUTL change percentage are indicated then the replenishment change parameter is not valid for the engine.

Chg. Desc.

Change Description is a calculated measure used to indicate the replenishment change parameter description. The description is calculated based on the replenishment change parameter user-defined description and the replenishment change parameter set up selected by you.

Chg. User Desc.

Change User Description is an editable measure used to enter a user-defined replenishment change parameter description. The final replenishment change parameter description takes the user-defined description into consideration. The entered value must not contain a colon punctuation mark (:).

Repl. Status

Replenishment Status is an editable measure that allows you to override the replenishment status. The valid values are: Default: Option to not change the replenishment status and keep the system generated replenishment status.

- On Option to force the replenishment to turn on the replenishment
- Off— Option to force the replenishment to turn off the replenishment

ROL Chng %

Reorder Level Change Percentage is an editable measure used that allows you to increase or decrease the system generated ROL value by the percentage value set in this measure. When the ROL should be increase then enter a positive value. When the ROL should be decreased then enter a negative value.

RUTL Chng %

Reorder Up to Level Change Percentage is an editable measure used that allows you to increase or decrease the system generated RUTL value by the percentage value set in this measure. When the RUTL should be increase then enter a positive value. When the RUTL should be decreased then enter a negative value.

Rule Chg. Count

Rule Change Count is a calculated measure used to display the total number of rules that are using the replenishment change parameter.

PL Change Count

Product and Location Change Count is a calculated measure used to display the total number of product and location combinations that associated with the replenishment change parameter.

PL Change %

Product and Location Change Percentage is a calculated measure used to indicate, in percentage, how much the product and location combinations associated with the replenishment change parameter represents in the total of product and location combinations with a lifecycle phase value. The measure is calculated as:



Figure 20-21 Calculation

$$100*\frac{PLChangeCount}{AllPLCount}$$


Chg. User Filter

Change User Filter is an editable measure used to select the replenishment change parameter to filter the views by the selected replenishment change parameter. This measure is used by the **Run Filter** action button responsible to calculate the filters applied to the views within the Replenishment Parameters Rules workspace.

Default Replenishment Parameters View

The Default Replenishment Parameters view allows you to set up the default replenishment strategies.

Figure 20-22 Default Replenishment Parameters View



Default Replenishment Parameters View - Default Profile Measures

The Default Replenishment Parameters view contains the following measures.

Default MCQ Units

Default Minimum Credible Quantity Units an editable measure used to define the default Minimum Credible Quantity for the product and location combination.

Default Min Qty Units



Default Minimum Quantity Units is an editable measure used to define the default the minimum amount of stock desired when the ROL method is set to Min Quantity.

Default Max Qty Units

Default Max Quantity Units is an editable measure used to define the default maximum amount of stock desired when the RUTL method is set to Max Quantity.

Inventory Plan Parameters Step

This step contains this view, Inventory Plan Parameters View.

Inventory Planning Parameters Key Concept

Use Inventory planning parameters to generate the time-phased inventory planning. Inventory parameters specify the System Minimum (which is the reorder level) and the System Maximum (which is the reorder up to level) methods along with the associated parameters is used in generating the time phased plans.

- System Minimum (ROL) is the inventory level that determines whether an order
 for replenishment should be placed at point of receipting week. At the point of
 receipting week, if the stock levels are less than the System Minimum, then an
 order for replenishment is placed, otherwise it is ignored until the next cycle.
- System Maximum (RUTL) is the target inventory level. While the replenishment
 point in time generates the orders at the system date. The time-phased inventory
 planning provides you with a weekly view on the inventory and the orders to be
 placed (the inventory plan is a projection based on current point in time network
 and product lifecycle status).

Time-Phased Replenishment Methods

IPOCS-Lifecycle Allocation and Replenishment has the following replenishment methods for the System Minimum (ROL) and System Maximum (RUTL) calculations.

System Minimum (ROL)

Fixed

This method uses the point-in-time replenishment values and does not calculate at every receipt opportunity. Either the ROL or RUTL values can be chosen from the point in time replenishment.

Forward Cover

This method calculates the value to cover the demand for the minimum number of days that should set by you in this method.

Min

This method uses the calculated value from the Fixed and Forward Cover methods and results is the lowest value between the two.

Max

This method uses the calculated value from the Fixed and Forward Cover methods and the result is the highest value between the two.

Sum



This method uses the calculated value from the Fixed and Forward Cover methods and the result is the sum both values.

System Maximum (RUTL)

Fixed

This method sets the value to a fixed user-defined value.

Forward Cover

This method calculates the value to cover the demand for the maximum number of days that should set by you in this method.

Min

This method uses the calculated value from the Fixed and Forward Cover methods and results is the lowest value between the two.

Max

This method uses the calculated value from the Fixed and Forward Cover methods and the result is the highest value between the two.

Sum

This method uses the calculated value from the Fixed and Forward Cover methods and the result is the sum both values.

Fixed Foward Cover Min Inventory System Max Leve Level Reorder-Up-To-Level Max Sum Unconstrained Replenishment Fixed System Min Level Reorder Level Foward Cover Availability Min Max Sum


Figure 20-23 Time-Phased Replenishment Methods

Inventory Plan Parameters View

The Inventory Plan Parameters View, under the Inventory Plan Parameters tab, allows you to set up all the possible Minimum and Maximum Level Methods for the Inventory Plan

that can be used to set up the replenishment rules that will then be used by the engine to generate the time-phased replenishment.

Figure 20-24 Inventory Plan Parameters View



Inventory Plan Parameters View - Default Profile Measures

The Inventory Plan Parameters view contains the following measures.

Inv. Plan. Enable

Inventory Planning Enable is an editable measure used to enable or disable an inventory planning parameter. Each row (or list) represents a different inventory planning parameter.

Inv. Plan. Valid

Inventory Planning Valid is a calculated measure used to indicate if the set up of the inventory planning parameter is valid or not. An inventory planning parameter is considered valid if it is enabled.

Inv. Plan. Desc.

Inventory Planning Description is a calculated measure used to indicate the inventory planning parameter description. The description is calculated based on the inventory planning parameter user-defined description and the inventory planning parameter set up selected by you.

Inv. Plan. User Desc.

Inventory Planning User Description is an editable measure used to enter a userdefined inventory planning parameter description. The final inventory planning parameter description takes the user-defined description into consideration. The entered value must not contain a colon punctuation mark (:).

Min Method

Minimum Method is an editable measure used to select the method to calculate the System Minimum (which is the reorder level) value. The valid values are:

Fixed



When this option is selected, then the point-in-time replenishment is used for the calculation and in the measure Min Fixed.

Forward Cover

When this option is selected, then the calculation calculates the demand to cover the amount of stock required for the number of days indicated in the measure Min Fwd Cov. Dur (d).

Min

When this option is selected, then the calculation sets the value to the minimum value resulted from the Fixed and Forward Cover methods.

Max

When this option is selected, then the calculation sets the value to the maximum value resulted from the Fixed and Forward Cover methods.

Sum

When this option is selected, then the calculation sets the value to the sum of the values resulted from the Fixed and Forward Cover methods.

Min Fixed

Minimum Fixed is an editable measure used to select how the Fixed method calculates the System Minimum (which is the reorder level) value. The valid values are:

.

When this option is selected the result is set to the value in the measure Min Fixed Units.

ROI

When this option is selected the result is set to the ROL value from the point-in-time replenishment.

RUTL

When this option is selected the result is set to the RUTL value from the point-in-time replenishment.

Min Fixed Units

Minimum Fixed Units is an editable measure used to define the minimum fixed quantity to be used when the Min Method is Fixed and the Min Fixed is -.

Min Fwd Cov. Dur (d)

Minimum Fwd Cover Duration (day) is an editable measure used to define the minimum number of days of cover to be used when the Min Method is Forward Cover.

Max Method

Maximum Method is an editable measure used to select the method to calculate the System Maximum (which is the reorder up-to level) value. The valid values are:

Fixed

When this option is selected the calculation sets it to the value in the measure Max Fixed Units.

Forward Cover



When this option is selected, then the calculation calculates the demand to cover the amount of stock required for the number of days indicated in the measure Max Fwd Cov. Dur (d).

Min

When this option is selected, then the calculation sets the value to the minimum value resulted from the Fixed and Forward Cover methods.

Max

When this option is selected, then the calculation sets the value to the maximum value resulted from the Fixed and Forward Cover methods.

Sum

When this option is selected, then the calculation sets the value to the sum of the values resulted from the Fixed and Forward Cover methods.

Max Fixed Units

Maximum Fixed Units is an editable measure used to define the maximum fixed quantity to be used when the Max Method is Fixed.

Max Fwd Cov. Dur (d)

Maximum Fwd Cover Duration (day) is an editable measure used to define the maximum number of days of cover to be used when the Max Method is Forward Cover.

Rule lvp. Count

Rule Inventory Planning Count is a calculated measure used to display the total number of rules that are using the inventory planning parameter.

PL lvp. Count

Product and Location Inventory Planning Count is a calculated measure used to display the total number of product and location combinations that associated with the inventory planning parameter.

PL Ivp. %

Product and Location Inventory Planning Percentage is a calculated measure used to indicate, in percentage, how much the product and location combinations associated with the inventory planning parameter represents in the total of product and location combinations with a lifecycle phase value. The measure is calculated as:

Figure 20-25 Calculation

$$100*\frac{PLIvp.Count}{AllPLCount}$$

lvp. User Filter

Inventory Planning User Filter is an editable measure used to select the inventory planning parameter to filter the views by the selected inventory planning parameter.

This measure is used by the **Run Filter**action button responsible to calculate the filters applied to the views within the Replenishment Parameters workspace.

Constraint Parameters Step


This step contains these views:

- Constraint Parameters View
- Default Store Priority View

Replenishment Constraint Parameters Concept

Replenishment Constraint Parameters allows you to set up parameters to indicate to the replenishment engine how to ration the stock when there is a stock constraint (for example, shortage). When facing stock shortages, the engine needs to adapt and fulfil the remaining stock to the stores in a way that ensures that the highest probability of sales is covered.

Figure 20-26 Example of a Replenishment Constraint



Rationing constrained stock is not solely based on store priority; allocating to the biggest (most important) stores can create missed sales. The replenishment engine approaches rationing based on the concept of layers. It tries to fulfill the most important on all stores requiring stock (using the store priority) before moving to the next layer. In this manner, the replenishment engine maximizes both service levels and the ability to sell.

The following available layers within IPOCS-Lifecycle Allocation and Replenishment are listed from the highest priority to the lowest priority:

- Customer Orders
- Display Quantity
- Minimum Credible Quantity
- Target Stock Reorder Level (ROL)
- Target Stock Reorder Up-To Level (RUTL)
- Target Stock Pack
- Target Stock Push





Figure 20-27 Example of Rationing based on Layers

As illustrated in the previous image the engine prioritizes the Store 3 despite the fact it is not the store with the higher priority. However, the Store 3 is where the layer with the higher priority needs to be fulfilled first. Once that layer is fulfilled, the engine moves to the stores the next layer with more priority needs to be fulfilled and so on until the available stock is distributed. Note that if there are two stores for the same layer priority to be fulfilled then the store priority is used.

Constraint Parameter View

The replenishment engine utilizes constraint parameters to define the allocation of stock by changing the priorities of the destination location and/or changing the layer of allocation to fulfill. You may also set the destination location to active or not and the source location to constrained or unconstrained.




Figure 20-28 Constraint Parameters View



Constraint Parameters View - Default Profile Measures

The Constraint Parameters view contains the following measures.

Cstr. Enable

Constraint Enable is an editable measure used to enable or disable a replenishment constraint parameter. Each row (or list) represents a different replenishment constraint parameter.

Cstr. Valid

Constraint Valid is a calculated measure used to indicate if the set up of the replenishment constraint parameter is valid or not. A replenishment constraint parameter is considered valid if it is enabled.

Cstr. Desc.

Constraint Description is a calculated measure used to indicate the replenishment constraint parameter description. The description is calculated based on the replenishment constraint parameter user-defined description and the replenishment constraint parameter set up selected by you.

Cstr. User Desc.

Constraint User Description is an editable measure used to enter a user-defined replenishment constraint parameter description. The final replenishment constraint parameter description takes the user-defined description into consideration. The entered value must not contain a colon punctuation mark (:).

Avail. Constr. (Src)

Avail. Constraint (Source) is an editable measure used to enable or disable the constraint for the source location.

Src. Avail. (Src)

Source Avail. (Source) is an editable measure to select which stock units are used from the source locations. The valid values are:

OH

Option to use stock on hand as the available stock.

OH+IT

Option to use stock on hand plus the stock in transit as the available stock. OH+IT+OO: Option to use stock on hand plus the stock in transit plus the stock on-order as the available stock.

Src. Avail. (Src) Dur (d)

Source Avail. (Source) Duration (day) is an editable measure used to define the number of days to get the in-transit and on-order stock. This number of days is used to calculate the available stock at the source location, measure Src. Avail. (Src), when the in-transit and/or on-order option is selected.

Rpl. Active (Dst)

Replenishment Active (Distribute) is an editable measure used to enable or disable the replenishment for the destination location.



Fulfill Till Layer (Dst)

Fulfill Till Layer (Distribute) is an editable measure used to select the layer until which the engine should fulfill the demand at the destination location. You should select one of the following options:

- 1st layer = Customer Order
- 2nd layer = Display Quantity
- 3rd layer = Min Credible Quantity
- 4th layer = Reorder Level
- 5th layer = Reorder Up to Level
- 6th layer = Pack
- 7th layer = Push

SubLayer (Dst)

SubLayer (Distribute) is an editable measure used to define the sublayer at the destination location for each of the layers until the selected layer in the measure FulFill Till Layer (Dst). Use the | character to separate the number of sublayers between layers. For example, if the layer selected in the measure FulFill Till Layer (Dst) is the 5th layer = Reorder Up-To Level and the sublayers are as follows:

- Customer Order has one layer
- Display Quantity has two layers
- Min Cred Quantity has two layers
- ROL has two layers
- RUTL has two layers

Then the value for this measure is: 1|2|2|2|2

Ration. Prio (Dst)

Ration Priority (Distribute) is an editable measure used to define a rationing priority for the destination locations.

Assign Pack (Dst)

Assign Pack (Distribute) is an editable measure to define pack types assigned for the destination locations. The valid values are:

Complex

Option to select pack which type is complex

Simple

Option to select pack which type is complex

Both

Option to select all pack types – simple and complex

Min Pack Fill Rate 1 (Dst) %

Minimum Pack Fill Rate 1 (Distribute) Percentage is an editable measure used to define the minimum pack fill rate percentage for first round of complex pack assignment.



Min Pack Fill Rate 2 (Dst) %

Minimum Pack Fill Rate 2 (Distribute) Percentage is an editable measure used to define the minimum pack fill rate percentage for second round of complex pack assignment.

Rule Cst. Count

Rule Constraint Count is a calculated measure used to display the total number of rules that are using the replenishment constraint parameter.

PL Cst. Count

Product and Location Constraint Count is a calculated measure used to display the total number of product and location combinations that associated with the replenishment constraint parameter.

PL Cst. %

Product and Location Constraint Percentage is a calculated measure used to indicate, in percentage, how much the product and location combinations associated with the replenishment constraint parameter represents in the total of product and location combinations with a lifecycle phase value. The measure is calculated as:

Figure 20-29 Calculation

$$100*\frac{PLCst.Count}{AllPLCount}$$

Cst. User Filter


Constraint User Filter is an editable measure used to select the replenishment constraint parameter to filter the views by the selected replenishment constraint parameter. This measure is used by the **Run Filter** action button responsible to calculate the filters applied to the views within the Replenishment Parameters workspace.

Default Store Priority View

The **Default Store Priority View**, under the **Constraint Parameters tab**, allows you to set up the locations priority by product partition to be used by the rationing process.



Figure 20-30 Default Store Priority View



Default Store Priority View - Default Profile Measures

The Default Store Priority view contains the following measure.

Default Ration. Prio

Default Rationing Priority is an editable measure used to define the location's priority, for the selected product partition, to be used by the engine for the rationing.

Rules Step

This step contains these views:

- Rules View
- Conditions View
- SKU-LOC View

Rules Concept for the Replenishment Parameters Task

In a similar way to the Supply Chain Network workspace, IPOCS-Lifecycle Allocation and Replenishment provides a powerful engine that enables you to create a set of rules to apply all the set up completed, within the Replenishment Parameters Task (replenishment parameters, replenishment change parameters, replenishment constraint parameters and inventory planning parameters), down to the item and location levels. You can define multiple rules at higher-levels using product, location, and product-location combinations. The rule engine determines the correct set to apply a the lowest level of product and location combinations.

Rules allow you to specify the time frame for the rule (if applicable) and the rule priority. The rule priority allows the rule engine to choose the correct rule to be applied if a product and location combination fits in more than one replenishment parameter rule (higher the number, higher the priority). The rule start and end date are used by the engine to know if the rule should be considered or discarded. If the system date



falls in the start date and end date (or rule dates are empty) then it is considered. Otherwise, it is discarded.

Following are two examples and illustrations of rules for the Replenishment Parameters task.

Rule 1

Should be configured to apply the Repl. Param 1, Change Param 1, Constraint Param 1, and Inv. Plan Param 1.

- The scope of the rule group where it is being configured (for example, Sport Bag products and the country France).
- The condition where the rule applies is for all locations and products in the scope where the product-location lifecycle phase attribute is *Discovery*.

Rule 2


Should be configured to apply the Repl. Param 2, Change Param 2, Constraint Param 2, and Inv. Plan Param 2.

- The scope of the rule group where it is being configured (for example, Sport Bag products and the country France).
- The condition where the rule applies is for all locations and products in the scope where the product-location lifecycle phase attribute is *Maturity*.

Note:

The condition is used by the rule engine to apply the set up to the product and location combinations that match the condition within the rule scope. The rule scope is defined by the Product Groups and Location Groups associated with the rule's rule group.

Figure 20-31 Illustration for a Rule 1






Prod / Loc Scope Prod: Sports Bag Loc: France Rule Start / End Date Start Date: Jan,2 End Date: . Start Date: Jan,2 End Date: . **Rule Priority** Priority 10 Priority 10 **Rule Condition** Lifecycle Phase = Maturity Lifecycle Phase = Maturity Rule 2

Figure 20-32 Illustration for a Rule 2

Rules View

The Rules View, under the Setup tab, allows you to configure the rules by enabling them and defining the rule start date, end date and priority for each one. Once configured you can set up the rule by selecting the replenishment parameters, replenishment change parameters, replenishment constraint parameters and inventory planning parameters that the rule uses. The product and locations that applies the rule set up is based on the scope of the rule's rule group (Product Scope and Location Scope views) and the rule's condition that is set up and managed in the Conditions view.

Rules V Setup Review B 9 E



Rules View - Measure Profiles

Figure 20-33 Rules View

The Rules View contains the following profiles to change the measures that are visible in the view:



Default

This profile is used as default by the view. All the available or visible measures are listed and described in the section Measure: Default Profile.

Change

This profile displays a subset of measures from the default profile. It focuses on the rule and in the replenishment change parameters measures only. All other parameter related measures are left out of the visible measures.

Constraint

This profile displays a subset of measures from the default profile. It focuses on the rule and in the replenishment constraint parameters measures only. All other parameter related measures are left out of the visible measures.

Inventory Plan

This profile displays a subset of measures from the default profile. It focuses on the rule and in the inventory planning parameters measures only. All other parameter related measures are left out of the visible measures.

Replenishment

This profile displays a subset of measures from the default profile. It focuses on the rule and in the replenishment parameters measures only. All other parameter related measures are left out of the visible measures.

Rules View - Default Profile Measures

The Rules View contains the following measures.

Rule User Filter

Rule User Filter is an editable measure used to select the rule to filter the views by the selected rule. This measure is used by the **Run Filter** action button responsible to calculate the filters applied to the views within the Replenishment Parameters workspace.

Rule Enable

Rule Enable is an editable measure used to enable or disable a rule. Each row (or list) represents a different rule.

Rule Level

Rule Level an editable measure used to select the level at what the engine will run the rule. The valid options are:

Global

In this option the rule engine will fully override the rule group scope that was set up in the Manage Rule Groups workspace and applies the rule to all valid product and location combinations.

All Prod

In this option the rule engine will partially override the rule group scope that was set up in the Manage Rule Groups workspace. The rule engine applies the rule to all valid product but for the locations in the rule group location's scope only.

All Loc



In this option, the rule engine will fully override the rule group scope that was set up in the Manage Rule Groups workspace. The rule engine applies the rule only to the products in the rule group product's scope and all valid locations.

Local

In this option the rule engine applies the rule to products and locations in the rule group scope defined in the Manage Rule Groups workspace.

Rule Condition

Rule Condition is a calculated measure used to indicate the condition for which the rule is valid. The condition is the result of the set up completed in the Conditions view.

Rule Start Date

Rule Start Date is an editable measure used to define a start date for the rule (when the rule should become active). When the rule is valid, and the start date is empty then the rule engine applies it. When the rule is valid, and the start date is populated the rule engine will start to apply it only when the start date is reached.

Rule End Date

Rule End Date is an editable measure used to define an end date for the rule (when the rule should become inactive). When empty, the rule engine assumes that the rule has no end date and if it is valid, then the rule engine applies it. When the rule is valid, and the end date is populated, the rule engine stops applying it starting from the defined date.

Rule Prio

Rule Priority is an editable measure used to define the rule's priority. The higher the number the higher the priority of the rule is. This rule priority is important to the rule engine as it is used when rules overlap each other. The rule engine uses the rule priority to select which one to apply.

Rule Valid

Rule Valid is a calculated measure used to indicate if the set up of the rule is valid or not. For example, if all replenishment parameters are missing then the rule is not valid for the rule engine. The engine needs at least one of them to be assigned for the rule to be considered as valid.

PL Ass. Count

Product and Location Associated Count is a calculated measure used to display the total number of product and location combinations that are associated with the rule based on the rule's condition.

PL Ass. %

Product and Location Associated Percentage is a calculated measure used to indicate, in percentage, how much the product and location combinations, where the rule is applicable, represent in the total of product and location combinations within the rule group scope. The measure is calculated as:



Figure 20-34 Calculation

$$100*\frac{PLAss.Count}{AllPLCount}$$

Rule Rpl.

Rule Replenishment is an editable measure for the you to select the replenishment parameter to be applied by the rule. This measure is a picklist populated with all valid replenishment parameters that were set up in the Replenishment Parameters view.

PL Rpl. App. Count

Product and Location Replenishment Applied Count is a calculated measure used to display the total number of product and location combinations that applies this rule's replenishment parameter. The calculation takes into account all the valid rules where the product and location combinations fall into and based on the priority calculates the count of product and location that applies the selected replenishment parameter.

PL Rpl. App. %

Product and Location Replenishment Applied Percentage is a calculated measure used to indicate, in percentage, how much the product and location combinations, where the rule's replenishment parameter is applicable, represent in the total of product and location combinations within the rule group scope. The measure is calculated as:

Figure 20-35 Calculation

$$100*\frac{PLRpl.\,App.\,Count}{AllPLCount}$$

Rule Cst.

Rule Constraint is an editable measure used to select the replenishment constraint parameter to be applied by the rule. This measure is a picklist populated with all valid replenishment constraint parameters that were set up in the Constraint Parameters view.

PL Cst. App. Count

Product and Location Constraint Applied Count is a calculated measure used to display the total number of product and location combinations that applies this rule's replenishment constraint parameter. The calculation takes into account all the valid rules where the product and location combinations fall into and based on the priority calculates the count of product and location that applies the selected replenishment constraint parameter.

PL Cst. App. %

Product and Location Constraint Applied Percentage is a calculated measure used to indicate, in percentage, how much the product and location combinations, where the rule's replenishment constraint parameter is applicable, represent in the total of product and location combinations within the rule group scope. The measure is calculated as:



Figure 20-36 Calculation

$$100 * \frac{PLCst. App. Count}{AllPLCount}$$

Rule Chg.

Rule Change is an editable measure used to select the replenishment change parameter to be applied by the rule. This measure is a picklist populated with all valid replenishment change parameters that were set up in the Replenishment Change Parameters.

PL Chg App. Count

Product and Location Change Applied Count is a calculated measure used to display the total number of product and location combinations that applies this rule's replenishment change parameter. The calculation takes into account all the valid rules where the product and location combinations fall into and based on the priority calculates the count of product and location that applies the selected replenishment change parameter.

PL Chg App. %

Product and Location Change Applied Percentage is a calculated measure used to indicate, in percentage, how much the product and location combinations, where the rule's replenishment change parameter is applicable, represent in the total of product and location combinations within the rule group scope. The measure is calculated as:

Figure 20-37 Calculation

$$100 * \frac{PLChg. App. Count}{AllPLCount}$$

Rule lvp.

Rule Inventory Planning is an editable measure used to select the inventory planning parameter to be applied by the rule. This measure is a picklist populated with all valid inventory planning parameters that were set up in the Inventory Plan Parameters view.

PL Ivp. App. Count

Product and Location Inventory Planning Applied Count is a calculated measure used to display the total number of product and location combinations that applies this rule's inventory planning parameter. The calculation takes into account all the valid rules where the product and location combinations fall into and based on the priority calculates the count of product and location that applies the selected inventory planning parameter.

PL Ivp. App. %



Product and Location Inventory Planning Applied Percentage is a calculated measure used to indicate, in percentage, how much the product and location combinations, where the rule's inventory planning parameter is applicable, represent in the total of product and location combinations within the rule group scope. The measure is calculated as:

Figure 20-38 Calculation

$$100 * \frac{PLIvp. App. Count}{AllPLCount}$$

Copy & Paste

Copy and Paste is an editable measure to select whether the rule is the source or destination for the copy paste rules functionality (Copy-Paste Rules). Valid values are:

Copy

Option to select in the rule to be used as the source of the copy.

Paste

Option to select in the rule to be used as destination of the copy.

•

Option selected to clear the measure.



Only one rule should be selected as a source, **Copy** but multiple rules can be selected as a destination, **Paste**.

Conditions View

This view allows you to define the conditions for the rules based in product, location, and product-location attributes. A rule condition is what allows the engine to find the product and location combinations where the rule is applicable.

Figure 20-39 Conditions View





Conditions View - Default Profile Measures

The Conditions view contains the following measures.

Condition Attribute

The Condition Attribute measure allows you to select the attribute for the condition, The attributes for the rules are assigned in the Attribute Review workspace.

Within Cond Op

The Within Cond Op measure allows you to specify the operator to be used inside the condition.

Table 20-2 Within Cond Op Measure Available Operators

Possible Operators	Descriptions	Example
==	Checks if the attribute value is equal with the Condition Value	brand == Private Label
!=	Checks if the attribute value is different from the Condition Value	average sales != 0
>	Checks if the attribute value is larger than the Condition Value	Average sales >5
>=	Checks if the attribute value is larger or equal to the Condition Value	
<	Checks if the attribute value is less than the Condition Value	Standard deviation of sales <6
<=	Checks if the attribute value is less or equal to the Condition Value	
contain		
not contain		
match		
not match		

Cond Value

The Cond Value measure is used when the type of the attribute is numeric. Example: average sales > 10

Cond Value String

The Cond Value String measure is used when the type of the attribute is a string. Example: brand == Private Label

Cond Value Measure

The value of the Cond Value measure is a measure name, which is populated by an expression that let's you refine the condition value. For instance private label versus non-private label.

This measure is used when you want to refine the condition value.



For instance, for the coffee items, except Private Label, you want to assign items to the rule that sell more than 50 per week. For Private Label items you may want the value to be 100. You need to populate your Condition measure with a value of 100 for all Private Label items, and the rest of the coffee items with 50.

Cond Value Date

The Cond Value Date measure is used when the type of the attribute is a date. Example: $today \ge 02/30/2024$ "

Between Cond Op

Within a rule there can be multiple conditions and also multiple condition groups. This is specified in the Cond Group measure. Conditions with the same Cond Group value belong to the same group.

For example, if a rule has 4 conditions, Conditions 1 and 2 can belong to condition group 1, and conditions 3 and 4 can belong to the condition group 2. Also, the Cond Order measure gives the ranking of the conditions inside the group.

The following table is an assumed use case:

Table 20-3 Between Cond Op Assumed Use Case

Condition	Between Con Op	Cond Order	Cond Group	
Condition 1	AND	1	1	
Condition 2	OR	2	1	
Condition 3	OR	3	2	
Condition 4		4	2	

The value for the Between Cond Op can be the logical operators AND or OR.

The conditions are evaluated first inside a condition group and then between groups. In the previous case, the resulting condition is:

(Condition 1 AND Condition 2) OR (Condition 3 OR Condition 4)

Here is an example where all conditions belong to the same condition group:

Table 20-4 Example: All Conditions Belong to the Same Condition Group

Condition	Between Con Op	Cond Order	Cond Group	
Condition 1	AND	1	1	
Condition 2	OR	2	1	
Condition 3	OR	3	1	
Condition 4		4	1	

The resulting condition for the rule is given by:

Condition 1 AND Condition 2 OR Condition 3 OR Condition 4

Note that the conditions are evaluated in the order given by the values in the Cond Order measure.

Cond Order



The Cond Order measure displays the order in which conditions are evaluated, wither independently or inside a condition group.

Cond Group

The Cond Group measure allows you to group conditions. This is useful when you want to evaluate conditions in a two-step process. First, the conditions are evaluated inside groups. In the second step, the group results are evaluated .

Validation Result

The Validation Result measure displays the condition expressions that are validated.

Invalid Flag

The Invalid Flag measure indicates if a condition is invalid.

Valid Flag

The Valid Flag measure indicates if a condition is valid.

SKU-LOC View

The **SKU-LOC View**, under the **Review tab**, allows you to review the results of running the rule engine calculation based on the rules set up in the workspace. In this view you can review to the results at the lowest level, item and location levels, and can also create exceptions, at the item-location level, to overwrite the replenishment set up calculated by the rule engine (for example, a particular item and location that should apply a different replenishment parameter from all the other item locations in the same rule).

| Solution | Service | Servic

Figure 20-40 SKU-LOC View

SKU-LOC View - Measure Profiles

The SKU-LOC View contains the following profiles to change the measures that are visible in the view:

Default



This profile is used as default by the view. All the available/visible measures are listed and described in the section Measure: Default Profile.

Change

This profile displays a subset of measures from the default profile. It focuses on the replenishment change parameters measures only. All other parameter related measures are left out of the visible measures.

Constraint

This profile displays a subset of measures from the default profile. It focuses on the replenishment constraint parameters measures only. All other parameter related measures are left out of the visible measures.

Inv Plan

This profile displays a subset of measures from the default profile. It focuses on the inventory planning parameters measures only. All other parameter related measures are left out of the visible measures. Replenishment: This profile displays a subset of measures from the default profile. It focuses on the replenishment parameters measures only. All other parameter related measures are left out of the visible measures.

SKU-LOC View - Default Profile Measures

The SKU-LOC View contains the following measures.

PL User Filter

Product and Location User Filter is an editable measure used to select the product and location combinations to filter the views by the selected the product and location combinations. This measure is used by the **Run Filter** action button is responsible to calculate the filters applied to the views within the Supply Chain Network workspace.

All PL

All Product and Location is a calculated measure used to indicate if a product and location combination is valid or not. If the combination is valid for a lifecycle phase, it displays as selected.

PL Valid

Product and Location Valid is a calculated measure used to indicate if a product and location combination has a valid rule from where the rule engine calculates the replenishment parameters. If the product-location combination is valid, it displays as selected.

PL Rpl.

Product and Location Replenishment is a calculated measure used to indicate the replenishment parameter applied to the product and location combination. The replenishment parameter displayed is the one calculated by the rule engine using the replenishment rules set up.

Ovr Rpl.

Over Replenishment is an editable measure that allows you to create exceptions at the itemlocation level. You can select the replenishment parameter to override the assigned replenishment parameter (measure PL Rpl.). This measure is a picklist populated with all valid replenishment parameter that were set up in the Replenishment Parameters view.

PL Rpl. Rule Count



Product and Location Replenishment Rule Count is a calculated measure used to indicate the total number of replenishment parameters that are assigned to the product and location combination based on the Rules set up. Note that a product and location combination can only have one replenishment parameter active. The one that is active is the one from the rule with the highest priority or the user-exception override.

PL Rpl. Prio

Product and Location Replenishment Priority is a calculated measure used to indicate the priority of the rule from where the replenishment parameter was calculated for the product and location combination.

PL Rpl. End Date

Product and Location Replenishment End Date is a calculated measure used to indicate the end date of the rule from where the replenishment parameter was calculated for the product and location combination.

PL Change

Product and Location Change is a calculated measure used to indicate the replenishment change parameter applied to the product and location combination. The replenishment change parameter displayed is the one calculated by the rule engine using the replenishment rules set up.

Ovr Change

Over Change is an editable measure used that allows you to create exceptions at the item-location level. You can select the replenishment change parameter to override the assigned replenishment change parameter (measure PL Change). This measure is a picklist populated with all valid replenishment change parameters that were set up in the Replenishment Change Parameters view.

PL Chq. Rule Count

Product and Location Change Rule Count is a calculated measure used to indicate the total number of Replenishment change parameters that are assigned to the product and location combination based on the Rules set up. Note that a product and location combination can only have one replenishment change parameter active. The active Replenishment change parameter is either the one from the rule with the highest priority or the user-exception override.

PL Chg. Prio

Product and Location Change Priority is a calculated measure used to indicate the priority of the rule from where the replenishment change parameter was calculated for the product and location combination.

PL Chg. End Date

Product and Location Change End Date is a calculated measure used to indicate the end date of the rule from where the replenishment change parameter was calculated for the product and location combination.

PL Cst.

Product and Location Constraint is a calculated measure used to indicate the replenishment constraint parameter applied to the product and location combination. The replenishment change parameter displayed is the one calculated by the rule engine using the replenishment rules set up.



Ovr Cst.

Over Constraint is an editable measure used that allows you to create exceptions at the itemlocation level. You can select the replenishment constraint parameter to override the assigned replenishment constraint parameter (measure PL Cst.). This measure is a picklist populated with all valid replenishment constraint parameters that were set up in the Constraint Parameters view.

PL Cst. Rule Count

Product and Location Constraint Rule Count is a calculated measure used to indicate the total number of replenishment constraint parameters that are assigned to the product and location combination based on the Rules set up. Note that a product and location combination can only have one replenishment constraint parameter active. The active Replenishment constraint parameter is either the one from the rule with the highest priority or the user-exception override.

PL Cst. Prio

Product and Location Constraint Priority is a calculated measure used to indicate the priority of the rule from where the replenishment constraint parameter was calculated for the product and location combination.

PL Cst. End Date

Product and Location Constraint End Date is a calculated measure used to indicate the end date of the rule from where the replenishment constraint parameter was calculated for the product and location combination.

PL lvp.

Product and Location Inventory Planning is a calculated measure used to indicate the inventory planning parameter applied to the product and location combination. The inventory planning parameter displayed is the one calculated by the rule engine using the replenishment rules set up.

Ovr lvp.

Over Inventory Planning is an editable measure used that allows you to create exceptions at the item-location level. You can select the inventory planning parameter to override the assigned inventory planning parameter (measure PL Ivp.). This measure is a picklist populated with all valid inventory planning parameters that were set up in the Inventory Plan Parameters view.

PL lvp. Rule Count

Product and Location Inventory Planning Rule Count is a calculated measure used to indicate the total number of inventory planning parameters that are assigned to the product and location combination based on the Rules set up. Note that a product and location combination can only have one inventory planning parameter active. The active inventory planning parameter is either the one from the rule with the highest priority or the user-exception override.

PL lvp. Prio

Product and Location Inventory Planning Priority is a calculated measure used to indicate the priority of the rule from where the inventory planning parameter was calculated for the product and location combination.

PL Ivp. End Date



Product and Location Inventory Planning End Date is a calculated measure used to indicate the end date of the rule from where the inventory planning parameter was calculated for the product and location combination.

Default MCQ Units

Default Minimum Credible Quantity Units is an editable measure used to define the default Minimum Credible Quantity for the product and location combination.

Min Cred. Qty @ Today Units

Minimum Credible Quantity at Today Units is a calculated measure used to indicate the Minimum Credible Quantity applied to the product and location combination at the system date. The Minimum Credible Quantity displayed is the one calculated by the rule engine using the replenishment rules set up. In case there is no Minimum Credible Quantity from the replenishment rule set up the value from the measure Default MCQ Units is used instead.

ROL Meth. @ Today

Reorder Level Method at Today is a calculated measure used to indicate the ROL method applied to the product and location combination at the system date. The ROL method displayed is the one calculated by the rule engine using the replenishment rules set up.

Default Min Qty Units

Default Minimum Quantity Units is an editable measure used to define the default the minimum amount of stock desired when the ROL method is set to Min Quantity.

Min Qty @ Today Units

Minimum Quantity at Today Units is a calculated measure used to indicate the ROL minimum quantity units applied to the product and location combination at the system date. The minimum quantity units displayed is the one calculated by the rule engine using the replenishment rules set up.

Min TS @ Today Dur (d)

Minimum Target Stock at Today Duration (day) is a calculated measure used to indicate the ROL minimum time supply (in days) applied to the product and location combination at the system date. The minimum time supply displayed is the one calculated by the rule engine using the replenishment rules set up.

Volatility @ Today %

Volatility at Today Percentage is a calculated measure used to indicate the Volatility % applied to the product and location combination at the system date. The Volatility % displayed is the one calculated by the rule engine using the replenishment rules set up.

Tgt. SL @ Today %

Target Service Level at Today Percentage is a calculated measure used to indicate the Target Service Level % applied to the product and location combination at the system date. The Target Service Level % displayed is the one calculated by the rule engine using the replenishment rules set up.

ROL Sft. Time @ Today Dur (d)



Reorder Level Safety Time at Today Duration (day) details the Reorder level safety time duration applicable today based on rules association and used in replenishment calculations where RUTL method is not Target Stock. The ROL level is determined as lead time + review time + ROL Sft Time @ Today Dur (d).

RUTL Meth. @ Today

Reorder Up to Level Method at Today is a calculated measure used to indicate the RUTL method applied to the product and location combination at the system date. The RUTL method displayed is the one calculated by the rule engine using the replenishment rules set up.

Default Max Qty Units

Default Maximum Quantity Units is an editable measure used to define the default maximum amount of stock desired when the RUTL method is set to Max Quantity.

Max Qty @ Today Units

Maximum Quantity at Today Units is a calculated measure used to indicate the RUTL maximum quantity units applied to the product and location combination at the system date. The maximum quantity units displayed is the one calculated by the rule engine using the replenishment rules set up.

Max TS @ Today Dur (d)

Maximum Target Stock at Today Duration (day) is a calculated measure used to indicate the RUTL maximum time supply (in days) applied to the product and location combination at the system date. The maximum time supply displayed is the one calculated by the rule engine using the replenishment rules set up.

Tgt. DoS @ Today Dur (d)

Tgt. DoS at Today Duration (day) is a calculated measure used to indicate the Target Days of Supply (in days) applied to the product and location combination at the system date. The Target Days of Supply displayed (and used by the Tgt DoS RUTL method) is the one calculated by the rule engine using the replenishment rules set up.

TS Meth. @ Today

Target Stock Method at Today is a calculated measure used to indicate the target stock method applied to the product and location combination at the system date (when the RUTL method is target stock). The target stock method displayed is the one calculated by the rule engine using the replenishment rules set up.

TS Sft. Time @ Today Dur (d)

Target Stock Safety Time at Today Duration (day) is a calculated measure used to indicate the number of days for the stock safety applied to the product and location combination at the system date (to be used when the RUTL method is target stock). The value displayed is the one calculated by the rule engine using the replenishment rules set up.

TS Seas. Fcst @ Today %

Target Stock Seasonal Forecast at Today Percentage is a calculated measure used to indicate the percentage of the Seasonal Forecast applied to the product and location combination at the system date (to be used when the RUTL method is target stock). The value displayed is the one calculated by the rule engine using the replenishment rules set up.

Order Rounding Threshold @ Today %



Order Rounding Threshold at Today Percentage is a calculated measure used to indicate the percentage to round up the orders applied to the product and location combination at the system date. The value displayed is the one calculated by the rule engine using the replenishment rules set up.

Repl. Status @ Today

Replenishment Status at Today is a calculated measure used to indicate whether product and location combination at the system date is replenished or not. The value displayed is the one calculated by the rule engine using the replenishment rules set up.

ROL Chng @ Today %

Reorder Level Change at Today Percentage is a calculated measure used to indicate the percentage to increase or decrease the system generated ROL value applied to the product and location combination at the system date. The value displayed is the one calculated by the rule engine using the replenishment rules set up.

RUTL Chng @ Today %

Reorder Up to Level Change at Today Percentage is a calculated measure used to indicate the percentage to increase or decrease the system generated RUTL value applied to the product and location combination at the system date. The value displayed is the one calculated by the rule engine using the replenishment rules set up.

Avail. Constr. (Src) @ Today

Available Constraint (Source) at Today is a calculated measure used to indicate whether a constraint is enable or disable (at the source location) for the product and location combination at the system date. The value displayed is the one calculated by the rule engine using the replenishment rules set up.

Src. Avail. (Src) @ Today

Source Available (Source) at Today is a calculated measure used to indicate which stock units to be used from the source locations is applied to the product and location combination at the system date. The value displayed is the one calculated by the rule engine using the replenishment rules set up.

Src. Avail. (Src) @ Today Dur (d)

Source Available (Source) at Today Duration (day) is a calculated measure used to indicate the number of days to get the in-transit and on-order stock is applied to the product and location combination at the system date. The value displayed is the one calculated by the rule engine using the replenishment rules set up.

Rpl. Active (Dst) @ Today

Replenishment Active (Distribution) at Today is a calculated measure used to indicate for the product and location combination at the system date if the location has the replenishment active or not. The value displayed is the one calculated by the rule engine using the replenishment rules set up.

Fulfill Till Layer (Dst) @ Today

Fulfill Till Layer (Distribution) at Today is a calculated measure used to indicate the layer applied to the product and location combination at the system date (layer until



which the engine should fulfill the demand). The value displayed is the one calculated by the rule engine using the replenishment rules set up.

SubLayer (Dst) @ Today

SubLayer (Distribution) at Today is a calculated measure used to indicate the sublayers applied to the product and location combination at the system date. The value displayed is the one calculated by the rule engine using the replenishment rules set up.

Default Ration, Prio

Default Rationing Priority is an editable measure used to define the default rationing priority for the product and location combination.

Ration. Prio (Dst) @ Today

Rationing Priority (Distribution) at Today is a calculated measure used to indicate the rationing priority applied to the product and location combination at the system date. The value displayed is the one calculated by the rule engine using the replenishment rules set up. In case there is no rationing priority from the replenishment rule set up the value from the measure Default Ration Prio. is used instead.

Assign Pack (Dst) @ Today

Assign Pack (Distribution) at Today is a calculated measure used to indicate the pack types' assignment applied to the product and location combination at the system date. The value displayed is the one calculated by the rule engine using the replenishment rules set up.

Min Pack Fill Rate 1 (Dst) @ Today %

Minimum Pack Fill Rate 1 (Distribution) at Today Percentage is a calculated measure used to indicate the minimum pack fill rate percentage for first round of complex pack assignment applied to the product and location combination at the system date. The value displayed is the one calculated by the rule engine using the replenishment rules set up.

Min Pack Fill Rate 2 (Dst) @ Today %

Minimum Pack Fill Rate 2 (Distribution) at Today Percentage is a calculated measure used to indicate the minimum pack fill rate percentage for second round of complex pack assignment applied to the product and location combination at the system date. The value displayed is the one calculated by the rule engine using the replenishment rules set up.

Min Method @ Today

Minimum Method at Today is a calculated measure used to indicate the inventory planning method, to calculate the System Minimum value, applied to the product and location combination at the system date. The inventory planning method displayed is the one calculated by the rule engine using the replenishment rules set up.

Min Fixed @ Today

Minimum Fixed at Today is a calculated measure used to indicate how the Fixed inventory planning method calculates the System Minimum value for the product and location combination at the system date. The value displayed is the one calculated by the rule engine using the replenishment rules set up.

Min Fixed @ Today Units

Minimum Fixed at Today Units is a calculated measure used to indicate the minimum fixed quantity applied to the product and location combination at the system date (used when the



Min Method @ Today is Fixed and the Min Fixed @ Today is -). The value displayed is the one calculated by the rule engine using the replenishment rules set up.

Min Fwd Cov. @ Today Dur (d)

Minimum Forward Cover at Today Duration (day) is a calculated measure used to indicate the minimum number of days of cover applied to the product and location combination at the system date (used when the Min Method @ Today is Forward cover). The value displayed is the one calculated by the rule engine using the replenishment rules set up.

Max Method @ Today

Maximum Method at Today is a calculated measure used to indicate the inventory planning method, to calculate the System Maximum value, applied to the product and location combination at the system date. The inventory planning method displayed is the one calculated by the rule engine using the replenishment rules set up.

Max Fixed @ Today Units

Maximum Fixed at Today Units is a calculated measure used to indicate the maximum fixed quantity applied to the product and location combination at the system date (used when the Max Method @ Today is Max). The value displayed is the one calculated by the rule engine using the replenishment rules set up.

Max Fwd Cov. @ Today Dur (d)

Maximum Forward Cover at Today Duration (day) is a calculated measure used to indicate the maximum number of days of cover applied to the product and location combination at the system date (used when the Max Method @ Today is Forward cover). The value displayed is the one calculated by the rule engine using the replenishment rules set up.

Filter Step


This step contains this view, Filter Parameters View.

Filter Parameters View

The **Filter Parameters View**, under the **Filter tab**, allows you to set up the filter that can change the scope of the products and locations displayed in all relevant views under the Rules Step within the Repl. Param. Rules Workspace.



Figure 20-41 Filter Parameters View



Filter Parameters View - Default Profile Measures

The Filter Parameters view contains the following measures.

Filter Not Valid

Filter Not Valid is an editable measure to change the scope of the products and locations displayed in all relevant views under the Rules Step. If the measure is selected, the **Run Filter** action button is responsible to calculate the filters that only display non-valid product and location combinations. When clear the filter only displays valid product and location combinations. By default, the measure is clear. The measure PL Valid identifies whether or not a product and location combination is valid.

Rule -> PL Filter

Rule -> PL Filter is an editable measure to select how the filter should work in the SKU- LOC view. Valid values are:

Associated

The view is filtered to display the product and location combinations that are associated with the rules selected in the Rules view (measure Rule User Filter). Note that a product and location combination can fit in more than one rule. When they fit in a rule they are associated regardless, if that rule is the actual one to be applied.

Applied

The view is filtered to display the product and location combinations that apply the rules selected in the Rules view (measure Rule User Filter). The rule is consider as applied when the LIP CS Rule Engine sets the replenishment set up for the product and location combination based on the rule (for example, BOD, PLC, and so on).

PL -> Rule Filter

Product and Location -> Rule Filter is an editable measure to select how the filter should work in the Rules view. Valid values are:

Associated



The view is filtered to display rules that are associated with the product and location combinations selected in the SKU-LOC view (measure PL User Filter). Note that a product and location combinations can fit in more than one rule. When they fit in a rule they are associated regardless, if that rule is the actual one to be applied.

Applied

The view is filtered to display rules that are associated with the product and location combinations selected in the SKU-LOC view (measure PL User Filter). The rule is consider as applied when the LIP CS Rule Engine sets the replenishment set up for the product and location combination based on the rule (for example, BOD, PLC, and so on).

Note:

In the same way as in the Supply Chain Network workspace, the measure in this view is used by the **Replenishment Parameters Run Filter** action button to filter the relevant views within the Replenishment Parameters workspace.

Replenishment Parameters Action Buttons

The Replenishment Parameters workspace has the following action buttons available:

Run Filter

Use the **Run Filter** action button for applying the filters in the Rules views based on the filter set up completed within the workspace. For example, filter based on the User Filter measures.

Clear Filter

Use the **Copy-Paste Exceptions** action button for removing all filters applied in the Rules views and clears all the User Filter measures within the workspace.

Calculate Rules

Use the **Calculate Rules** action button for running the rules engine to calculate which rule's replenishment and inventory planning parameters set up would be applied to the product and location combination level and applying the rule's replenishment and inventory planning parameters set up down to the product and location combination level.

Duplicate Rule

Use the **Duplicate Rule** action button to copy all the rules information from the rule selected as the source of the copy and paste it into all the rules selected as the destination of the copy. This action copies all the information in the Rules view and Conditions view.



21

Review and Approve

This chapter describes the functionality that allows you to review and approve the latest system-calculated point-in-time orders and time-phased orders. This is the workspace where you analyze the suggested replenishment and allocations and perform the necessary actions. The following are some examples of typical tasks to perform in this workspace.

- Future store opening or store closing impacts
- · What-if scenarios to simulate changes in the replenishment parameters
- Review critical alerts and do the necessary amendments
- Approve orders that are not approved automatically due to critical alerts






Figure 21-1 Review and Approve Task

Review and Approve Workspace, Steps, and Views

The following table lists the workspaces, steps, and views of the Review and Approve task.

Table 21-1 Review and Approve Workspace, Steps, and Views

Workspace	Step	Tab	Views
Review and	Overview	To-Do List	Approval Status View
Approve Workspace			To-Do List View
·			Today View
			User Filter View



Table 21-1 (Cont.) Review and Approve Workspace, Steps, and Views

Workspace	Step	Tab	Views
	Review and	By Prod	SKU Level (R and A) View
	Approve		SKU-LOC Level (R and A) View
			SKU-Source LOC Level (R and A) View
			VAR-LOC Level (R and A) View
			VAR-Source LOC Level (R and A) View
		By Location	LOC Level (R and A) View
			LOC-SKU Level (R and A) View
			LOC-VAR Level (R and A) View
			Source LOC-SKU Level (R and A) View
			Source LOC-VAR Level (R and A) View
		Space	Display Space by LOC (R and A) View
			Display Space by SKU (R and A) View
			Stockroom Space by LOC (R and A) View
			Stockroom Space by SKU (R and A) View
		OTB	OTB View
	Inventory Plan	Inventory	Horizon - InvPlan View
		Plan	SKU-LOC Level (InvPlan) View
			SKU-LOC-DAY Level (InvPlan) View
			SKU-LOC-WEEK Level (InvPlan) View
			SKU-Source LOC-WEEK Level (R and A) View
	Rebalancing	Summary	Item-Location View
			Items View
			Locations View
			Parameters View
		Transfers	Item-Location View
			Items View
			Links View
			Locations View
			Parameters View
	Manual Transfer	Allowed Transfer	Allowed Transfer View



Table 21-1 (Cont.) Review and Approve Workspace, Steps, and Views


Workspace	Step	Tab	Views
		Deficit	Transfer Deficit Analysis View
		Surplus Analysis	Transfer Surplus Analysis View
		Plan	Transfer by Destination View
	Transfer	Transfer by Product View	
			Transfer Deficit From-To View
			Transfer Surplus From- To View
	Filter	Filter	Attribute Filter Setup View
			Calendar Filter Setup View
			Filter Setup View
			Filter Statistics View
		Quick Filter View	
			User Filter View

Review and Approve Workspace

The Review and Approve workspace allows you to access all views listed in the Review and Approve Workspace, Steps, and Views. To build the Review and Approve workspace, perform these steps:

1. From the left sidebar menu, click the **Task Module** to view the available tasks.


Figure 21-2 Task Module





- 2. Click the **Review and Approve** activity to access the available workspaces.
- 3. Click Lifecycle Allocation and Replenishment. The wizard opens. You can open an existing workspace, but to create a new workspace, click Create New Workspace.

Figure 21-3 Lifecycle Review and Approve Wizard



4. Enter a name for your new workspace in the label text box and click **OK**.

Figure 21-4 Enter Workspace Label



5. The workspace wizard opens. Select the databag you want to work with and click **Next**.

Cancel Next > Finish





Figure 21-5 Workspace Wizard: Databag


6. Select the product you want to work with and click Next.






7. Select the locations you want to work with and click Finish.

Figure 21-7 Workspace Wizard: Locations



3. The wizard notifies you that your workspace is being prepared. Successful workspaces are available from the Dashboard.

Figure 21-8 Successful Workspace Build



Note:

The workspace is built using the selected databag scope. The products, locations, source locations, alerts, and attributes available in the workspace are in the databag scope that is managed in the Manage Databag workspace.

Overview Step


This step contains these views:

- Approval Status View
- To-Do List View
- Today View
- User Filter View

Approval Status View

The **Approval Status View**, under the **To-Do List tab**, allows you to review approval statistics like the number of product and location combinations that were automatically approved and the ones that still require your approval.

Figure 21-9 Approval Status View



Approval Status View - Default Profile Measures

The Approval Status view contains the following measures.

Rpl TBA Count

The Rpl TBA Count is a calculated measure used to indicate the total number of assorted product and location combinations that need the orders to be approved manually.

Appr. Rpl. Plan Count

The Approved Rpl. Plan Count is a calculated measure used to indicate the total number of assorted product and location combinations with approved orders.

Appr. Plan (Wk) Count



The Approved Plan (Week) Count is a calculated measure used to indicate the total number of assorted product and location combinations with approved orders for the current week.

TBA Plan (Wk) Count

The TBA Plan (Week) Count is a calculated measure used to indicate the total number of assorted product and location combinations that need the orders to be approved manually for the current week.

To-Do List View

The **To-Do List View**, under the **To-Do List tab**, allows you to review the number of alert hits that have been triggered as well as their types (all alerts available in IPOCS-Lifecycle Allocation and Replenishment). Within this view, you can also select the alerts to focus the review and leverage IPOCS-Lifecycle Allocation and Replenishment filter capabilities. If alerts are used as a filter, then the views under the Review & Approve steps are filtered based on the alert hits only. The alerts can be added or removed as a filter at any time by you.




Figure 21-10 To-Do List View

To-Do List View - Default Profile Measures

The To-Do List view contains the following measures.

Filter By Alert

The Filter By Alert is an editable measure used to select what alerts should be used to filter the views under the Review & Approve Step. When alerts are selected, IPOCS-Lifecycle Allocation and Replenishment uses the calculated alert hits for the selected alerts to filter the views. The views are filtered as soon as you run the workspace calculation, (either **Calculate** or **F9**). In order to disable the alert as a filter you need to clear the alerts and re-run the workspace calculation (either **Calculate** or **F9**).

Seed User

The Seed User is an editable measure used to select which alerts should be used to populate the User-filtered Boolean measure. You can use this alert to first seed the User-filtered



measure and then either add additional positions or reduce the positions by simply selecting or clearing the item/location combination. This is used for the filtering functionality.

Enable RTA

The Enable Real-Time Alerts is an editable measure used to select alerts that should be used as Real-Time Alerts (RTA) within the workspace. When alerts are selected, IPOCS-Lifecycle Allocation and Replenishment uses the calculated alert hits for the selected alerts to enable the RTA. The RTA hits and navigation capabilities are available as soon as you run the workspace calculation (either **Calculate** or **F9**). To disable the alert as RTA you need to clear the alert and re-run the workspace calculation (either **Calculate** or **F9**).

Alert Priority

The Alert Priority is a calculated measure used to indicate the alert's priority.

Alert VAR Count

The Alert Variant Count is a calculated measure used to indicate the total number of variants that have hits for the alert. For example, if 12 different variants were added to the replenishment watch list, regardless of the stores, then this measure indicates the number 12 in the replenishment watch list alert.

Alert To-Be-Rev VAR Count

The Alert To-Be-Reviewed Variant Count is a calculated measure used to indicate the number of variants that have not been reviewed yet, out of the total number of variants that have hits for the alert.

Alert VAR-LOC Count

The Alert Variant-Location Count is a calculated measure used to indicate the total number of variant and location combinations that have hits for the alert. For example, if 12 different variants are added to the replenishment watch list, for only two stores, then this measure indicates the number 24 in the replenishment watch list alert.

Alert To-Be-Rev VAR-LOC Count

The Alert To-Be-Reviewed Variant-Location Count is a calculated measure used to indicate the number of variant and location combinations that have not been reviewed yet, out of the total number of variant and location combinations that have hits for the alert.

Alert LOC Count

The Alert Location Count is a calculated measure used to indicate the total number of locations that have hits for the alert. For example, if 12 different variants were added to the replenishment watch list, for only two stores, then this measure indicates the number 2 in the replenishment watch list alert.

Alert To-Be-Rev LOC Count


The Alert To-Be-Reviewed Location Count is a calculated measure used to indicate the number of locations that have not been reviewed yet, out of the total number of locations that have hits for the alert.

Today View



The **Today View**, under the **Today View List tab**, allows you to check IPOCS-Lifecycle Allocation and Replenishment's Today date.

Figure 21-11 Today View



Today View - Default Profile Measures

The Today view contains the following measure.

Today Date


The Today Date is a loaded read-only measure to display the system date that is calculated by IPOCS-Lifecycle Allocation and Replenishment batch.

User Filter View

The **User Filter View**, under the **To-Do List tab**, allows you to configure the filter to be applied to the views within the Review & Approve workspace. In this view you can configure the filter to be applied to the product and location hierarchies. Once a change is performed it is applied after running the workspace calculation (either **Calculate** or **F9**).



Figure 21-12 User Filter View



User Filter View - Default Profile Measures

The User Filter view contains the following measure.

User Filter PROD-LOC

User Filter Product and Location is an editable measure to restrict the filter by the product and location combinations when the measure User Filter PROD-LOC is selected.

Review & Approve Step

In this step you can review at different levels, the orders calculated by IPOCS-Lifecycle Allocation and Replenishment and approve them. This step contains these views:

By Prod Tab

- SKU Level (R & A) View
- SKU-LOC Level (R & A) View
- SKU-Source LOC Level (R & A) View
- VAR-LOC Level (R & A) View
- VAR-Source LOC Level (R & A) View

By Location Tab

- LOC Level (R & A) View
- LOC-SKU Level (R & A) View
- LOC-VAR Level (R & A) View
- Source LOC-SKU Level (R & A) View
- Source LOC-VAR Level (R & A) View

Space Tab



- Display Space by LOC (R & A) View
- Display Space by SKU (R & A) View
- Stockroom Space by LOC (R & A) View
- Stockroom Space by SKU (R & A) View

OTB Tab


OTB (R & A) View

SKU Level (R & A) View

The **SKU Level (R & A) View**, under the **By Prod tab**, allows you to review the replenishment and allocation calculated values at the product level only (no location). Additionally, the sales and forecast for the previous and forthcoming four weeks are also available.

The navigation of this view is driven by real-time alerts or workspace alerts. To leverage the real-time alert navigation in this workspace the desired alerts should be enabled as RTA (measure Enable RTA) in the To-Do List view.

Figure 21-13 SKU Level (R & A) View



Note:

The measures being displayed in this view, regardless of the measure profile, are supported by their counterparts defined at the product and location level. Therefore, the calculated measures in this view are the result of aggregating the ones at the product and location intersection.

SKU Level (R & A) View - Default Profile Measures

The Default measure profile available in the SKU Level (R & A) view contains the following measures.



User Filter PROD - LOC

The User Filter PROD - LOC is an editable measure used to include specific product and location combinations into the quick filter. When selected, by clicking the **Run Filters** action menu, the quick filter restricts the condition to search only for the product and location combinations selected. When clear, the product and location combinations are not included in the filter condition.

Revwd PROD - LOC

The Revwd PROD - LOC is an editable measure used to indicate that the product and location combination alerts have been reviewed.

PROD Alerts

The PROD Alerts is a calculated measure used to display the Alert Short Descr. of all alerts that were triggered for the product.

Actual Sales W-4 Units

The Actual Sales W-4 Units is a calculated measure used to display the accumulated daily sales units at the system date week - 4 weeks. The system date is available in the Today view.

Actual Sales W-3 Units

The Actual Sales W-3 Units is a calculated measure used to display the accumulated daily sales units at the system date week - 3 weeks. The system date is available in the Today view.

Actual Sales W-2 Units

The Actual Sales W-2 Units is a calculated measure used to display the accumulated daily sales units at the system date week - 2 weeks. The system date is available in the Today view.

Actual Sales W-1 Units

The Actual Sales W-1 Units is a calculated measure used to display the accumulated daily sales units at the system date week - 1 week. The system date is available in the Today view.

Actual Lost Sales W-4 to W-1 Units

The Actual Lost Sales W-4 to W-1 Units is a calculated measure used to display the accumulated lost sales units from the system date week – 4 until the previous week (from the system date week). The system date is available in the Today view.

Actual Sales W+0 Units

The Actual Sales W+0 Units is a calculated measure used to display the accumulated daily sales units for the current system date week. The system date is available in the Today view.

Fcst W+0 Units

The Fcst W+0 Units is a calculated measure used to display forecast units for the current system date week. The system date is available in the Today view.

Fcst W+1 Units



The Fcst W+1 Units is a calculated measure used to display forecast units at the system date week +1 week. The system date is available in the Today view.

Fcst W+2 Units

The Fcst W+2 Units is a calculated measure used to display forecast units at the system date week +2 weeks. The system date is available in the Today view.

Fcst W+3 Units

The Fcst W+3 Units is a calculated measure used to display forecast units at the system date week + 3 weeks. The system date is available in the Today view.

Lifecycle Sales To-Date %

The Lifecycle Sales To-Date % is a calculated measure used to indicate the percentage of actual sales up to date against the total initial forecast.

Figure 21-14 Calculation

$$100* \frac{\sum_{firstweek}^{currentweek} Actual Loc. Sales Units}{Tot. Init. FcstUnits}$$

Lifecycle Sales To-Go %

The Lifecycle Sales To-Go % is a calculated measure used to indicate the percentage of sales to complete the total initial forecast.

Figure 21-15 Calculation

$$100* \frac{\sum_{currentweek}^{horizon} Actual Loc. Sales Units + SellOutFcst(Wk)Units}{Tot. Init. FcstUnits}$$

Asst. Prod-Loc Start Date

The Asst. Prod-Loc Start Date is a loaded measure used to indicate the assortment start date for the assorted product and location combinations.

Asst. Prod-Loc End Date

The Asst. Prod-Loc End Date is a loaded measure used to indicate the assortment end date for the assorted product and location combinations.

Asst. Prod-Loc Active Count

The Asst. Prod-Loc Active Count is a calculated measure used to indicate the total number of product and location combinations assorted and still active. If the assortment end date has not been reached yet then, it is active. Otherwise, it is inactive; meaning that the assortment has stopped already.



RUTL @Today Units

The RUTL @Today Units is a calculated measure used to indicate the Reorder Up-to Level (RUTL) value in units for the product and location combination at the system date. In this view, the value is the total of all locations for the product.

Tot. Dest. Avail. Units

The Tot. Dest. Avail. Units is a calculated measure used to indicate the total quantity of units available at the destination location. In this view, the value is the total of all locations where there is available inventory for the product.

Unc Need Total Units

The Unc Need Total Units is a calculated measure used to indicate the total unconstrained quantity, in units, needed for the location. In this view, the value is the total of all locations for the product.

Sys. Rpl. Plan In Units

The Sys. Rpl. Plan In Units is a calculated measure used to indicate the order quantity for the location based on the location's needs. This value is calculated based on the replenishment rules and the location forecast. In this view, the value is the total of all locations for the product.

Sys. Rpl. Plan In Pack Units

The Sys. Rpl. Plan In Pack Units is a calculated measure used to indicate the order quantity, in pack order quantity, for the location based on the location needs. This value is calculated based on the replenishment rules and the location forecast. In this view, the value is the total of all locations for the product.

Rpl. TBA Count

The Rpl. TBA Count is a calculated measure used to indicate the total number of assorted product and location combinations that need the orders to be approved manually. In this view, the value is the total of all locations for the product.

Tot. Deficit Units

The Tot. Deficit Units is a calculated measure used to indicate the product inventory deficit using the total available inventory and Reorder Up-to Level (RUTL) value.

Figure 21-16 Calculation

$$Max(\sum_{alllocations} (RUTL@TodayUnits - Tot. Avail. Units), 0)$$

Tot. Surplus Units

The Tot. Surplus Units is a calculated measure used to indicate the product inventory surplus using the total available inventory and Reorder Up-to Level (RUTL) value.



Figure 21-17 Calculation

$$Max(\sum_{alllocations} (Tot. Avail. Units - RUTL@TodayUnits), 0)$$

SKU Level (R & A) View - Actuals Profile Measures

The Actuals measure profile available in the SKU Level (R & A) view contains the following measures.

User Filter PROD - LOC

The User Filter PROD - LOC is the same as the one in the default profile. Refer to the measure User Filter PROD-LOC in the Default Profile Measures.

Actual PL Sales Wk Units

The Actual PL Sales Wk Units is a calculated measure used to indicate the weekly sales, aggregated from the daily sales, for the product and location combination. In this view, the value is the total of all locations and all weeks for the product.

Actual Loc. Sales Units

The Actual Loc. Sales Units is a calculated measure used to indicate the weekly sales, aggregated from the daily sales, for the product and location combinations. In this view, the value is the total of all locations and all weeks for the product.

Actual Loc.Recpt Units

The Actual Loc.Recpt Units is a calculated measure used to indicate the weekly receipts for the product and location combination. In this view, the value is the total of all locations and all weeks for the product.

Actual Loc. Shipmt Units

The Actual Loc. Shipmt Units is a calculated measure used to indicate the weekly shipments for the product and location combinations. In this view, the value is the total of all locations and all weeks for the product.

Actual Sales W-4 Units

The Actual Sales W-4 Units is the same as the one in the default profile. Refer to the measure, Actual Sales W-4 Units, in the Default Profile Measures.

Actual Sales W-3 Units

The Actual Sales W-3 Units is the same as the one in the default profile. Refer to the measure, Actual Sales W-3 Units in the Default Profile Measures.

Actual Sales W-2 Units

The Actual Sales W-2 Units is the same as the one in the default profile. Refer to the measure, Actual Sales W-2 Units, in the Default Profile Measures.

Actual Sales W-1 Units

The Actual Sales W-1 Units is the same as the one in the default profile. Refer to the measure, Actual Sales W-1 Units, in the Default Profile Measures.



Actual Sales W+0 Units

Actual Sales W+0 Units is the same as the one in the default profile. Refer to the measure, Actual Sales W+0 Units, in the Default Profile Measures.

Actual Sales W-1 + W+0 Units

The Actual Sales W-1 + W+0 Units is a calculated measure used to display the accumulated sales units from the system date week -1 until the system current week. The system date is available in the Today view.

Actual Sales W-2 + W+0 Units

The Actual Sales W-2 + W+0 Units is a calculated measure used to display the accumulated sales units from the system date week – 2 until the system current week. The system date is available in the Today view.

Actual Sales W-3 + W+0 Units

The Actual Sales W-3 + W+0 Units is a calculated measure used to display the accumulated sales units from the system date week – 3 until the system current week. The system date is available in the Today view.

Actual Sales W-4 + W+0 Units

The Actual Sales W-4 + W+0 Units is a calculated measure used to display the accumulated sales units from the system date week – 4 until the system current week. The system date is available in the Today view.

Actual Lost Sales W-4 to W-1 Units

Actual Lost Sales W-4 to W-1 Units is the same as the one in the default profile. Refer to the measure, Actual Lost Sales W-4 to W-1 Units, in the Default Profile Measures.

Actual Sales D-7 Units

The Actual Sales D-7 Units is a calculated measure used to display the accumulated daily sales units for the last 7 days (from the system date - 7 days until system date). The system date is available in the Today view.

Actual Sales D-15 Units

The Actual Sales D-15 Units is a calculated measure used to display the accumulated daily sales units for the last 15 days (from the system date - 15 days until system date). The system date is available in the Today view.

Actual Sales D-30 Units

The Actual Sales D-30 Units is a calculated measure used to display the accumulated daily sales units for the last 30 days (from the system date - 30 days until system date). The system date is available in the Today view.

Actual Avg Inv. W-1 Units

The Actual Avg Inv. W-1 Units is a calculated measure used to display the average inventory units at the previous week (system date week - 1 week). The system date is available in the Today view.

Actual Avg Inv. W-2 Units



The Actual Avg Inv. W-2 Units is a calculated measure used to display the average inventory units at the system date week - 2 weeks. The system date is available in the Today view.

Actual Avg Inv. W-3 Units

The Actual Avg Inv. W-3 Units is a calculated measure used to display the average inventory units at the system date week - 3 weeks. The system date is available in the Today view.

Actual Avg Inv. W-4 Units

The Actual Avg Inv. W-4 Units is a calculated measure used to display the average inventory units at the system date week - 4 weeks. The system date is available in the Today view.

Actual PL Avg Inv. Wk Units

The Actual PL Avg Inv. Wk Units is a calculated measure to display the average holding inventory of the assortment period.

SKU Level (R & A) View - Availability Profile Measures

The Availability measure profile available in the SKU Level (R & A) view contains the following measures.

User Filter PROD - LOC

The User Filter PROD - LOC is the same as the one in the default profile. Refer to the measure User Filter PROD-LOC in the Default Profile Measures.

RUTL Mask

The RUTL Mask is a calculated measure used to indicate whether the product and location combination is eligible for replenishment. When selected, then it is eligible. When clear, it is not eligible. In this view, if at least one location is eligible then the product is eligible.

Rpl. Dest. Mask

The Rpl. Dest. Mask is a calculated measure used to indicate whether the product and location combination is eligible for replenishment and the constraint parameter at the system date indicates that replenishment is enabled (measure Rpl. Active (Dst) @ Today). When selected, then it is eligible. When clear, it is not eligible. In this view, if at least one location is eligible then the product is eligible.

Rpl. Src. Mask

The Rpl. Src. Mask is a calculated measure used to indicate whether the product and source location combination is eligible for replenishment. When selected, then it is eligible. When clear, it is not eligible. In this view, if at least one location is eligible then the product is eligible.

Tot. On Hand Units

The Tot. On Hand Units is a calculated measure used to indicate the total on-hand inventory units. The total on-hand units include the on-hand inventory loaded into IPOCS-Lifecycle Allocation and Replenishment plus the on-hand inventory units for the replacement or phase-out product, if any.

In Transit over LT+RT Units

The In Transit over LT+RT Units is a calculated measure used to indicate the total in transit units over the lead time plus the review time.

On Order (in) over LT+RT Units



The On Order (in) over LT+RT Units is a calculated measure used to indicate the total on orders (in) units over the lead time plus the review time.

Exp. Rpl. Plan In Units

The Exp. Rpl. Plan In Units is a calculated measure used to indicate the replenishment planned units to be exported from the batch for the product and location combination. In this view, the value is the total of all destination locations for the product.

Appr. Rpl. Plan In Units

The Appr. Rpl. Plan In Units is a calculated measure used to indicate the approved replenishment planned units for the product and location combination. In this view, the value is the total of all destination locations for the product.

Appr. Rpl. Plan In Pack Units

The Appr. Rpl. Plan In Pack Units is a calculated measure used to indicate the approved replenishment planned packs units for the product and location combination. In this view, the value is the total of all destination locations for the product.

Sys. Rpl. Plan In Units

The Sys. Rpl. Plan In Units is the same as the one in the default profile. Refer to the measure, Sys. Rpl. Plan In Units, in the Default Profile Measures.

Transfer Plan In Units

The Transfer Plan In Units is a calculated measure used to indicate the transfer units planned for the product and location combination. In this view, the value is the total of all destination locations for the product.

Appr. Transfer In Units

The Appr. Transfer In Units is a calculated measure used to indicate the transfer units approved for the product and location combination. In this view, the value is the total of all destination locations for the product.

Exp. Transfer Plan In Units

The Exp. Transfer Plan In Units is a calculated measure used to indicate the transfer units to be exported from the batch for the product and location combination. In this view, the value is the total of all destination locations for the product.

On Order (out) over LT+RT Units

The On Order (out) over LT+RT Units is a calculated measure used to indicate the total on orders (out) units over the lead time plus the review time.

Exp. Rpl. Plan Out Units

The Exp. Rpl. Plan Out Units is a calculated measure used to indicate the source location (for example, warehouse) replenishment planned units to be exported from the batch for the product and location combination. In this view, the value is the total of all source locations for the product.

Appr. Rpl. Plan Out Units

Appr. Rpl. Plan Out Units is a calculated measure used to indicate the source location approved replenishment units for the product and location combination. In this view, the value is the total of all source locations for the product.



Sys. Rpl. Plan Out Units

The Sys. Rpl. Plan Out Units is a calculated measure used to indicate the order quantity for the source location based on the source location needs. This value is calculated based on the replenishment rules and the source location demand. In this view, the value is the total of all source locations for the product.

Transfer Plan Out Units

The Transfer Plan Out Units is a calculated measure used to indicate the source location's transfer units planned for the product and location combination. In this view, the value is the total of all locations for the product.

Appr. Transfer Out Units

The Appr. Transfer Out Units is a calculated measure used to indicate the source location's transfer units approved for the product and location combination. In this view, the value is the total of all locations for the product.

Exp. Transfer Plan Out Units

The Exp. Transfer Plan Out Units is a calculated measure used to indicate the source location's transfer units to be exported from the batch for the product and location combination. In this view, the value is the total of all locations for the product.

Tot. Dest. Avail. Units

The Tot. Dest. Avail. Units is the same as the one in the default profile. Refer to the measure, Tot. Dest. Avail. Units, in the Default Profile Measures.

Tot. Dest. Avail Dur (w)

The Tot. Dest. Avail Dur (w) is a calculated measure used to indicate the number of weeks that the Tot. Dest. Avail. Units can cover the demand for the product and location combination.

Tot. Physical Avail. Units

The Tot. Physical Avail. Units is a calculated measure used to indicate the total quantity of units' physically available at the destination location. The physically available units differ from the available units as the booked inventory is taken into consideration. In this view, the value is the total of all locations for the product.

Figure 21-18 Calculation

Tot. Dest. Avail. Units - Tot. BookedUnits

Tot. Physical Avail. Dur (w)

The Tot. Physical Avail. Dur (w) is a calculated measure used to indicate the number of weeks that the Tot. Physical Avail. Units can cover the demand for the product and location combination.

Up To Dest. Avail Units

The Up To Dest. Avail Units is the same as Tot. Dest. Avail Units grouped by source.



Up To Dest. Avail Dur (w)

The Up To Dest. Avail Dur (w) is the same as Tot. Dest. Avail Units grouped by source displayed by duration (weeks).

Tot. Src. Avail. Units

The Tot. Src. Avail. Units is a calculated measure used to indicate the total quantity of units available at the source location.

Tot. Src. Avail. Pack Units

The Tot. Src. Avail. Pack Units is a calculated measure used to indicate the total quantity of pack units available at the source location.

Tot. Dest. Avail. (incl. Rpl. & Trsf. Out)

The Tot. Dest. Avail. (incl. Rpl. & Trsf. Out) is the Total Destination Available stock, which is calculated as the sum of all inbound deliveries following replenishment, plus stock on hand but excluding all planned and approved outbound shipments – this measure provides the location net inventory following replenishment calculation.

Tot. Avail. Units

The Tot. Avail. Units is a calculated measure used to indicate the total quantity of units available for the product considering all inventory (booked, on-hand, transit, and on-order) plus all orders (approved, planned, and exported) plus all transfers (approved, planned, and exported).

Tot. Avail. Dur (w)

The Tot. Avail. Dur (w) is a calculated measure used to indicate the number of weeks that the Tot. Avail. Units can cover the demand for the product and location combination.

SKU Level (R & A) View - Forecast Profile Measures

The Forecast measure profile available in the SKU Level (R & A) view contains the following measures.

User Filter PROD - LOC

The User Filter PROD - LOC is the same as the one in the default profile. Refer to the measure User Filter PROD-LOC in the Default Profile Measures.

Fcst W+0 Units

The Fcst W+0 Units is the same as the one in the default profile. Refer to the measure, Fcst W+0 Units, in the Default Profile Measures.

Fcst W+1 Units

The Fcst W+1 Units is the same as the one in the default profile. Refer to the measure, Fcst W+1 Units, in the Default Profile Measures.

Fcst W+2 Units

The Fcst W+2 Units is the same as the one in the default profile. Refer to the measure, Fcst W+2 Units, in the Default Profile Measures.

Fcst W+3 Units



The Fcst W+3 Units is the same as the one in the default profile. Refer to the measure, Fcst W+3 Units, in the Default Profile Measures.

Fcst W+0 to W+1 Units

The Fcst W+0 to W+1 Units is a calculated measure used to display the accumulated forecast from the current system date week until the system current week + 1. The system date is available in the Today view.

Fcst W+0 to W+2 Units

The Fcst W+0 to W+2 Units is a calculated measure used to display the accumulated forecast from the current system date week until the system current week + 2. The system date is available in the Today view.

Fcst W+0 to W+3 Units

The Fcst W+0 to W+3 Units is a calculated measure used to display the accumulated forecast from the current system date week until the system current week + 3. The system date is available in the Today view.

Forecast Overt LT+RT Units

The Forecast Overt LT+RT Units is a calculated measure used to display the daily Forecast Demand, in units, from the system date up to number of days of Lead Time plus Review Time. The system date is available in the Today view.

Final Fcst PL Wk Units

The Final Fcst PL Wk Units is a calculated measure used to display the final weekly forecast after being spread from the variant level.

Sell-Out Fcst (Wk) Units

The Sell-Out Fcst (Wk) Units is an editable measure used to enter product demand at the destination locations. In this view, the measure is aggregated and when changed, the value is spread proportionally across the locations and weeks within the workspace (you can check the spread value in the SKU-LOC-WEEK Level (InvPlan) view).

Sell-In Fcst (Wk) Units

The Sell-In Fcst (Wk) Units is an editable measure used to enter the weekly demand at the source location for the product and location combination.

Tot. Demand (Wk) Units

The Tot. Demand (Wk) Units is a calculated measure used to indicate the total weekly demand for the product. In this view, the measure is aggregated (you can check the weekly value in the SKU-LOC-WEEK Level (InvPlan) view).

Up To Sell-Out Fcst Units

The Up To Sell-Out Fcst Units is a calculated measure used to indicate the sell-out Forecast from the source location perspective for the products.

SKU Level (R & A) View - Inventory Profile Measures

The Inventory measure profile available in the SKU Level (R & A) view contains the following measures.

User Filter PROD - LOC



The User Filter PROD - LOC is the same as the one in the default profile. Refer to the measure User Filter PROD-LOC in the Default Profile Measures.

Tot. On Hand Units

The Tot. On Hand Units is the same as the one in the availability profile. Refer to the measure, Tot. On Hand Units, in the in the Availability Profile Measures.

Tot. Booked Units

The Tot. Booked Units is a calculated measure used to indicate the total inventory booked in units.

In Transit over LT+RT Units

The In Transit over LT+RT Units is the same as the one in the availability profile. Refer to the measure, In Transit over LT+RT Units, in the Availability Profile Measures.

Tot. In Transit Units

The Tot. In Transit Units is a calculated measure used to indicate the total inventory units in transit.

Tot. In Transit

The Tot. In Transit is a calculated measure used to display your comment for the intransit inventory and your comment for the phase-out item's inventory, if any.

Tot. On Order (in) Units

The Tot. On Order (in) Units is a calculated measure used to indicate the total on-order inventory units. The total on-order units include the on-order inventory loaded into IPOCS-Lifecycle Allocation and Replenishment plus the on-order inventory units for the replacement/phase-out product, if any.

On Order (in) over LT+RT Units

The On Order (in) over LT+RT Units is the same as the one in the availability profile. Refer to the measure, On Order (in) over LT+RT Units, in the Availability Profile Measures.

In Transit + On Order (in) Units

The In Transit + On Order (in) Units is a calculated measure used to indicate the accumulated on-order and in-transit inventory units at the locations for the product.

Tot. on Order (out) Units

The Tot. on Order (out) Units is a calculated measure used to indicate the total onorder inventory units out from the source locations (for example, warehouse. The total on-order (out) units include the on-order inventory loaded into IPOCS-Lifecycle Allocation and Replenishment plus the on-order (out) inventory units for the replacement/phase-out product, if any.

On Order (out) over LT+RT Units

The On Order (out) over LT+RT Units is the same as the one in the availability profile. Refer to the measure, On Order (out) over LT+RT Units, in the Measures: Availability Profile in the Default Profile Measures.

Tot. Cust. Order Units



The Tot. Cust. Order Units is a calculated measure used to indicate the total customer orders units. The total customer orders include the customer orders loaded into IPOCS-Lifecycle Allocation and Replenishment plus the customer orders for the replacement/phase-out product, if any.

Loc. On Hand Units

The Loc. On Hand Units is a loaded measure used to indicate the on-hand inventory units for the product and location combinations. In this view, the displayed value is for the product considering all locations.

Loc. Booked Units

The Loc. Booked Units is a loaded measure used to indicate the booked or reserved inventory units for the product and location combinations. In this view, the displayed value is for the product considering all locations.

Loc. In Transit Units

The Loc. In Transit Units is a loaded measure used to indicate the in-transit inventory units for the product and location combinations. In this view, the displayed value is for the product considering all locations.

Loc In Transit

vLoc In Transit is a loaded measure used to indicate whether the product and location combination has in-transit inventory or not. When selected, there is in-transit inventory. When clear, there is no in-transit inventory. In this view, a product has in-transit inventory if there is at least one location with in-transit inventory.

Loc. On Order (in) Units

The Loc. On Order (in) Units is a loaded measure used to indicate the in-transit inventory units for the product and location combinations. In this view, the displayed value is for the product considering all locations.

Loc. On Order (out) Units

The Loc. On Order (out) Units is a loaded measure used to indicate the on-order inventory units (into the destination locations) for the product and location combinations. In this view, the displayed value is for the product considering all locations.

Cust. Order Units

The Cust. Order Units is a loaded measure used to indicate the on-order inventory units (out from source locations) for the product and location combinations. In this view, the displayed value is for the product considering all locations.

Ph. Out On Hand Units

The Ph. Out On Hand Units is a calculated measure used to indicate the on-hand inventory units for the phased-out item, if any.

Ph. Out Booked Units

The Ph. Out Booked Units is a calculated measure used to indicate the booked or reserved inventory units for the phased-out item, if any.

Ph. Out In Transit Units

The Ph. Out In Transit Units is a calculated measure used to indicate the in-transit inventory units for the phased-out item, if any.



Ph. Out In Transit

The Ph. Out In Transit is a calculated measure used to indicate whether the phasedout item has in-transit inventory or not. When selected, there is in-transit inventory. When clear, there is no in-transit inventory.

Ph. Out On Order (in) Units

The Ph. Out On Order (in) Units is a calculated measure used to indicate the on-order inventory units (into the destination locations) for the phased-out item, if any.

Ph. Out On Order (out) Units

The Ph. Out On Order (out) Units is a calculated measure used to indicate the onorder inventory units (out from source locations) for the phased-out item, if any.

Ph. Out Cust. Order Units

The Ph. Out Cust. Order Units is a calculated measure used to indicate the customer orders for the phased-out item, if any.

Pack Type

The Pack Type is a loaded measure used to indicate the product's pack type. Either simple or complex.

Pack Desc.

The Pack Desc. is a loaded measure used to indicate the product's pack description.

Pack - SKU Ass. Count

The Pack - SKU Ass. Count is a calculated measure used to indicate the total number of products (SKU) in the pack.

Pack - SKU Ass. Units

The Pack - SKU Ass. Units is an editable measure used to indicate the total number of units that the product (SKU) has in the pack.

SKU Level (R & A) View - Parameters Profile Measures

The Parameters measure profile available in the SKU Level (R & A) view contains the following measures.

User Filter PROD - LOC

The User Filter PROD - LOC is the same as the one in the default profile. Refer to the measure User Filter PROD-LOC in the Default Profile Measures.

Asst. Prod-Loc

The Asst. Prod-Loc is a loaded measure used to indicate whether the product and location combinations are assorted or not. For more details, refer to the same measure in the Product-Location view within the Manage Assortment workspace.

Asst. Prod-Loc Count

The Asst. Prod-Loc Count is a loaded measure used to indicate the total number of product and location combinations assorted. For more details, refer to the same measure in the Product-Location view within the Manage Assortment workspace.

Asst. Prod-Loc Active



The Asst. Prod-Loc Active is a loaded measure used to indicate whether the product and location combinations are assorted and still active or not. For more details check the same measure in the view Product- Location within the Manage Assortment workspace.

Asst. Prod-Loc Active Count

The Asst. Prod-Loc Active Count is a loaded measure used to indicate the total number of product and location combinations assorted and still active. For more details, refer to the same measure in the Product-Location view within the Manage Assortment workspace.

Asst. Prod-Loc Start Date

The Asst. Prod-Loc Start Date is a loaded measure used to indicate the assortment start date for the assorted product and location combinations. For more details, refer to the same measure in the Product-Location view within the Manage Assortment workspace.

Asst. Prod-Loc End Date

The Asst. Prod-Loc End Date is a loaded measure used to indicate the assortment end date for the assorted product and location combinations. For more details, refer to the same measure in the Product-Location view within the Manage Assortment workspace.

Lfc. Prod-Loc

The Lfc. Prod-Loc is a loaded measure used to indicate whether the product and location combination has a valid lifecycle or not. For more details, refer to the same measure in the Product-Location view within the Manage Assortment workspace.

Lfc. Prod-Loc Count

The Lfc. Prod-Loc Count is a calculated measure used to indicate the number of locations where the product has a valid lifecycle.

Lfc. Active @ Today

The Lfc. Active @ Today is a loaded measure used to indicate whether the product and location combination has a valid lifecycle or not at the system date. In this view, the product has an active lifecycle if there is at least one location with an active lifecycle.

Lfc. Active @ Today

The Lfc. Active @ Today is a loaded measure used to indicate the lifecycle phase string for the product and location combination when the product and location combination has a valid lifecycle at the system date. In this view, the values are aggregated to the product level only using the ambig aggregation.

Display Qty Units

The Display Quantity Units is a loaded measure used to indicate the Display Quantity for the product and location combination used by IPOCS-Lifecycle Allocation and Replenishment for the RUTL calculation. In this view, the value is the total for the product.

Min Order Qty Units

The Min Order Quantity Units is an editable measure used to indicate the minimum order quantity for the product and location combination. In this view, the value is the total for the product.

Mult. Order Qty Units



The Mult. Order Quantity Units is an editable measure used to indicate the number of multiple order quantities for the product and location combination. In this view, the value is the total for the product.

Fixed TS 1 Units

The Fixed TS 1 Units is a loaded measure used to indicate the initial allocation for the product and location combination. For more details, refer to the same measure in the Product-Location view within the Manage Assortment workspace.

Fixed TS 2 Units

The Fixed TS 2 Units is an editable measure used to indicate an initial allocation for the product and location combination. For more details, refer to the same measure in the Product-Location view within the Manage Assortment workspace.

Fixed TS 3 Units

The Fixed TS 3 Units is an editable measure used to indicate an initial allocation for the product and location combination. For more details, refer to the same measure in the Product-Location view within the Manage Assortment workspace.

Tot. Init. Fcst Units

The Tot. Init. Fcst Units is a loaded measure used to display the total initial forecast for the product and location combination.

Conversion UOM 1

The Conversion UOM 1 is an editable measure used to indicate a value to be used when converting units into a specific unit of measure based on the Constraint UOM 1 for scaling. In this view, the value is the total for the product.

Conversion UOM 2

The Conversion UOM 2 is an editable measure used to indicate a value to be used when converting units into a specific unit of measure based on the Constraint UOM 1 for scaling. In this view, the value is the total for the product.

Conversion UOM 3

The Conversion UOM 3 is an editable measure used to indicate a value to be used when converting units into a specific unit of measure based on the Constraint UOM 1 for scaling. In this view, the value is the total for the product.

Avg. Cost €

The Avg. Cost € is an editable measure used to indicate the average cost for the product and location combination. In this view, the value is the average for the product considering all the locations.

Price (excl.VAT) €

The Price (excl.VAT) € is an editable measure used to indicate the price excluding VAT for the product and location combination. In this view, the value is the average for the product considering all the locations.

Primary Source @ Today

The Primary Source @ Today is a loaded measure used to indicate the applied primary source for the product and location combination at the system date and can be



overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Reserved Source 1 @ Today

The Reserved Source 1 @ Today is a calculated measure used to indicate the applied reserved source 1 for the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Reserved Source 2 @ Today

The Reserved Source 2 @ Today is a calculated measure used to indicate the applied reserved source 2 for the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Alternative Source @ Today

The Alternative Source @ Today is a calculated measure used to indicate the applied alternative source for the product and location combination at the system date and can be overridden. .

LLC @ Today

The LLC @ Today is a calculated measure used to indicate the low level code applied to the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Lead Time @ Today Dur (d)

The Lead Time @ Today Dur (d) is a calculated measure used to indicate the applied lead time, in days, for the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Revw @ Today

The Revw @ Today is a calculated measure used to indicate if Today (current system date) is a review day for the product and location combination and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Next Revw @ Today Date

The Next Revw @ Today Date is a calculated measure used to indicate the next review date for the product and location combination. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Next Revw @ Today Dur (d)

The Next Revw @ Today Dur (d) is a calculated measure used to indicate the number of days to the next review date for the product and location combination. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Avg Revw Time @ Today Dur (d)



The Avg Revw Time @ Today Dur (d) is a calculated measure used to indicate the average number of days between each review period (planning period) for the product and location combination. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

RUTL Mask

The RUTL Mask is the same as the one in the availability profile. Refer to the measure, RUTL Mask, in the Availability Profile Measures.

Min Cred. Qty @ Today Units

The Min Cred. Quantity @ Today Units is a calculated measure used to indicate the Minimum Credible Quantity applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

ROL Meth. @ Today

The ROL Meth. @ Today is a calculated measure used to indicate the ROL method applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Min Qty @ Today Units

The Min Quantity @ Today Units is a calculated measure used to indicate the ROL minimum quantity units applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Min TS @ Today Dur (d)

The Min TS @ Today Dur (d) is a calculated measure used to indicate the ROL minimum time supply (in days) applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Tgt. SL @ Today %

The Tgt. SL @ Today % is a calculated measure used to indicate the Target Service Level % applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Volatility @ Today %

The Volatility @ Today % is a calculated measure used to indicate the Volatility % applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

ROL Sft. Time @ Today Dur (d)

The ROL Sft. Time @ Today Dur (d) details the Reorder level safety time duration applicable today based on rules association and used in replenishment calculations where RUTL method is not Target Stock. The ROL level is determined as lead time + review time + ROL Sft Time @ Today Dur (d).

RUTL Meth. @ Today



The RUTL Meth. @ Today is a calculated measure used to indicate the RUTL method applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Max Qty @ Today Units

The Max Quantity @ Today Units is a calculated measure used to indicate the RUTL maximum quantity units applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Max TS @ Today Dur (d)

The Max TS @ Today Dur (d) is a calculated measure used to indicate the RUTL maximum time supply (in days) applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Tgt. DoS @ Today Dur (d)

The Tgt. DoS @ Today Dur (d) is a calculated measure used to indicate the Target Days of Supply (in days) applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

TS Meth. @ Today

The TS Meth. @ Today is a calculated measure used to indicate the target stock method applied to the product and location combination at the system date (when the RUTL method is target stock). For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

TS Seas. Fcst @ Today %

TS Seas. Fcst @ Today % is a calculated measure used to indicate the percentage of the Seasonal Forecast applied to the product and location combination at the system date (to be used when the RUTL method is target stock). For more details about the measure, refer to the same measure description in the view SKU- LOC within the Supply Chain Network workspace.

TS Sft. Time @ Today Dur (d)

The TS Sft. Time @ Today Dur (d) is a calculated measure used to indicate the number of days for the stock safety applied to the product and location combination at the system date (to be used when the RUTL method is target stock). For more details about the measure, refer to the same measure description in the view SKU- LOC within the Supply Chain Network workspace.

Order Rounding Threshold @ Today

The Order Rounding Threshold @ Today is a calculated measure used to indicate the percentage to round up the orders applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Repl. Status @ Today

The Repl. Status @ Today is a calculated measure used to indicate whether the product and location combination at the system date is replenishable or not. For more details about the



measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

ROL Chng @ Today %

The ROL Chng @ Today % is a calculated measure used to indicate the percentage to increase or decrease the system-generated ROL value applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

RUTL Chng @ Today %

The RUTL Chng @ Today % is a calculated measure used to indicate the percentage to increase or decrease the system-generated RUTL value applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Rpl. Dest. Mask

The Rpl. Dest. Mask is the same as the one in the availability profile. Refer to the measure, Rpl. Dest. Mask, in the Measures: Availability Profile in the Default Profile Measures.

Rpl. Src. Mask

The Rpl. Src. Mask is the same as the one in the availability profile. Refer to the measure, Rpl. Src. Mask, in the Measures: Availability Profile in the Default Profile Measures.

Avail. Constr. (Src) @ Today

The Avail. Constr. (Src) @ Today is a calculated measure used to indicate whether a constraint is enabled or disabled (at the source location) for the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Src. Avail. (Src) @ Today

The Src. Avail. (Src) @ Today is a calculated measure used to indicate which stock units to be used from the source locations are applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Src. Avail. (Src) @ Today Dur (d)

The Src. Avail. (Src) @ Today Dur (d) is a calculated measure used to indicate the number of days to get the in-transit and on-order stock applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Rpl. Active (Dst) @ Today

The Rpl. Active (Dst) @ Today is a calculated measure used to indicate for the product and location combination at the system date if the location has the replenishment



active or not. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Fulfill Till Layer (Dst) @ Today

The Fulfill Till Layer (Dst) @ Today is a calculated measure used to indicate the layer applied to the product and location combination at the system date (layer until which IPOCS-Lifecycle Allocation and Replenishment should fulfill the demand). For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Ration. Prio (Dst) @ Today

The Ration. Prio (Dst) @ Today is a calculated measure used to indicate the rationing priority applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

SubLayer (Dst) @ Today

The SubLayer (Dst) @ Today is a calculated measure used to indicate the sublayers applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Assign Pack (Dst) @ Today

The Assign Pack (Dst) @ Today is a calculated measure used to indicate the pack types assignment applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Min Pack Fill Rate 1 (Dst) @ Today %

The Min Pack Fill Rate 1 (Dst) @ Today % is a calculated measure used to indicate the minimum pack fill rate percentage for the first round of complex pack assignments applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Min Pack Fill Rate 2 (Dst) @ Today %

The Min Pack Fill Rate 2 (Dst) @ Today % is a calculated measure used to indicate the minimum pack fill rate percentage for the second round of complex pack assignments applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

SKU Level (R & A) View - Plan Profile Measures

The Plan measure profile available in the SKU Level (R & A) view contains the following measures.

User Filter PROD - LOC

The User Filter PROD - LOC is the same as the one in the default profile. Refer to the measure User Filter PROD-LOC in the Default Profile Measures.

RUTL Mask



The RUTL Mask is the same as the one in the availability profile. Refer to the measure, RUTL Mask, in the Availability Profile Measures.

Rpl. Dest. Mask

The Rpl. Dest. Mask is the same as the one in the availability profile. Refer to the measure, Rpl. Dest. Mask, in the Availability Profile Measures.

Rpl. Src. Mask

The Rpl. Src. Mask is the same as the one in the availability profile. Refer to the measure, Rpl. Src. Mask, in the Availability Profile Measures.

Pack Partition

The Pack Partition is a calculated measure used to indicate a partition (identifier) for the products that belong to the same pack. For example, if pack 001 has sku001, sku002 and sku003 then all 3 SKUs have the same pack partition value.

Tot. Physical Avail. Units

The Tot. Physical Avail. Units is the same as the one in the availability profile. Refer to the measure, Tot. Physical Avail. Units, in the Availability Profile Measures.

Tot. Physical Avail. Dur (w)

The Tot. Physical Avail. Dur (w) is the same as the one in the availability profile. Refer to the measure, Tot. Physical Avail. Dur (w), in the Availability Profile Measures.

Tot. Dest. Avail. Units

The Tot. Dest. Avail. Units is the same as the one in the default profile. Refer to the measure, Tot. Dest. Avail. Units, in the Default Profile Measures.

Tot. Dest. Avail. Dur (w)

Tot. Dest. Avail. Dur (w) is a calculated measure used to indicate the number of weeks that the Tot. Dest. Avail. Units can cover the demand for the product and location combination.

Tot. Src. Avail. Units

The Tot. Src. Avail. Units is a calculated measure used to indicate the total quantity of units available at the source location for the product and location combination. In this view, the value is the total for the product.

Tot. Src. Avail Pack Units

The Tot. Src. Avail Pack Units is a calculated measure used to indicate the total quantity of pack units available at the source location for the product and location combination. In this view, the value is the total for the product.

User Tot. Src. Avail. Units

The User Tot. Src. Avail. Units is an editable measure you can use to enter the total quantity of units available at the source location for the product. The value of this measure overrides the measure Tot. Src. Avail. Unit.

Manual Push Units

The Manual Push Units is an editable measure you can use to enter the total quantity of units to be manually pushed from the source location to the destination locations for



the product. The value is spread proportionally between all the product's destination locations.

ROL @ Today Units

The ROL @ Today Units is a calculated measure used to indicate the Reorder level (ROL) value in units for the product and location combination at the system date. In this view, the value is the total of all locations for the product.

RUTL @ Today Units

The RUTL @ Today Units is the same as the one in the default profile. Refer to the measure, RUTL @ Today Units, in the Default Profile Measures.

Forecast Over LT+RT Units

The Forecast Over LT+RT Units is the same as the one in the forecast profile. Refer to the measure, Forecast Over LT+RT Units, in the Forecast Profile Measures.

Unc. Need Total Units

The Unc. Need Total Units is the same as the one in the default profile. Refer to the measure, Unc. Need Total Units, in the Default Profile Measures.

Min Unc. Need Pack Units

The Min Unc. Need Pack Units is a measure that indicates the minimum unit of Packs needed regardless of Pack Fill Rate.

Max Unc. Need Pack Units

The Max Unc. Need Pack Units is a measure that indicates the maximum unit of Packs needed regardless of Pack Fill Rate.

User Rpl. Fix Locked Units

The User Rpl. Fix Locked Units is an editable measure you can use to enter fixed replenishment units (order quantity) for the product. This measure overrides the product's system-calculated replenishment units. The entered value is spread proportionally between all the product's destination locations.

Sys. Rpl. Plan In Units

The Sys. Rpl. Plan In Units is the same as the one in the default profile. Refer to the measure, Sys. Rpl. Plan In Units, in the Default Profile Measures.

Sys. Rpl. Plan In Pack Units

The Sys. Rpl. Plan In Pack Units is the same as the one in the default profile. Refer to the measure, Sys. Rpl. Plan In Pack Units, in the Default Profile Measures.

Unc. Req. Total Units

The Unc. Req. Total Units is a calculated measure used to indicate the total unconstrained quantity, in units, needed for the source location (for example, warehouse). In this view, the value is the total for the product.

Sys. Rpl. Plan Out Units

The Sys. Rpl. Plan Out Units is the same as the one in the default profile. Refer to the measure, Sys. Rpl. Plan Out Units, in the Default Profile Measures.

Sys. Rpl Plan Out Pack Units



The Sys. Rpl Plan Out Pack Units is a calculated measure used to indicate the pack order quantity (either simple or complex packs) for the source location based on the source location needs. This value is calculated based on the replenishment rules and the source location demand. In this view, the value is the total of all source locations for the product.

Tot. Avail Units

The Tot. Avail Units is the same as the one in the availability profile. Refer to the measure, Tot. Avail. Units, in the Availability Profile Measures.


Tot. Avail Dur (w)

The Tot. Avail Dur (w) is the same as the one in the availability profile. Refer to the measure, Tot. Avail. Dur (w), in the Availability Profile Measures.

Tot. Regular Units

The Tot. Regular Units is a calculated measure used to indicate the total regular units for the product. The calculation is based on the deficit and surplus units.

Figure 21-19 Calculation



Tot. Deficit Units

The Tot. Deficit Units is the same as the one in the default profile. Refer to the measure, Tot. Deficit Units, in the Default Profile Measures.

Tot. Deficit %

The Tot. Deficit % is a calculated measure used to indicate the percentage that the deficit units represent in the RUTL units.

Figure 21-20 Calculation

$$100*\frac{Tot.\,DeficitUnits}{RUTL@TodayUnits}$$

Tot. Surplus Units

The Tot. Surplus Units is the same as the one in the default profile. Refer to the measure, Tot. Surplus Units, in the Default Profile Measures.

Tot. Surplus %

The Tot. Surplus % is a calculated measure used to indicate the percentage that the surplus units represent in the RUTL units.

Figure 21-21 Calculation

$$100*\frac{Tot.\,SurplusUnits}{RUTL@TodayUnits}$$

Tot. Fulfil. %

The Tot. Fulfil. % is a calculated measure used to indicate the percentage that the total available stock fulfills the RUTL.

Rpl. TBA

The Rpl. TBA is a calculated measure used to indicate whether the product and location combination needs the order to be approved manually. In this view, the value is the total of all locations for the product.

Appr. Rpl. Plan

The Appr. Rpl. Plan is an editable measure used to indicate whether the product's order should or should not be approved by the approval process. The **Replenishment Approval** action button approves all orders when this measure is selected.

Appr. Rpl Plan User ID

The Appr. Rpl Plan User ID is a calculated measure used to audit the **Replenishment Approval** action button. It is populated with the user-identifier that last ran the Replenishment Approval.

Appr. Rpl. Plan Date

Appr. Rpl. Plan Date is a calculated measure used to audit the **Replenishment Approval** action button. It is populated with the date and time that the replenishment approval was last run.

Appr. Rpl. Plan In Units

The Appr. Rpl. Plan In Units is the same as the one in the availability profile. Refer to the measure, Appr. Rpl. Plan In Units, in the Availability Profile Measures.



Appr. Rpl. Plan In Pack Units

The Appr. Rpl. Plan In Pack Units is the same as the one in the availability profile. Refer to the measure, Appr. Rpl. Plan In Pack Units, in the Availability Profile Measures.

Appr. Rpl. Plan Out Units

The Appr. Rpl. Plan Out Units is the same as the one in the availability profile. Refer to the measure, Appr. Rpl. Plan Out Units, in the Measures: Availability Profile in the Default Profile Measures.

Exp. Rpl. Plan Date

The Exp. Rpl. Plan Date is a calculated measure used to audit the replenishment export. It is populated with the date and time that the replenishment was exported by the batch, if exported by the last batch run. Otherwise, it is empty.

Exp Rpl. Plan In Units

The Exp Rpl. Plan In Units is the same as the one in the availability profile. Refer to the measure, Exp. Rpl. Plan In Units, in the Availability Profile Measures.

Exp. Rpl. Plan Out Units

The Exp. Rpl. Plan Out Units is the same as the one in the availability profile. Refer to the measure, Exp. Rpl. Plan Out Units, in the Availability Profile Measures.

SKU Level (R & A) View - Replacement Profile Measures

The Replacement measure profile available in the SKU Level (R & A) view contains the following measures.

User Filter PROD - LOC

The User Filter PROD - LOC is the same as the one in the default profile. Refer to the measure User Filter PROD-LOC in the Default Profile Measures.

Phs. Out PROD

The Phs. Out PROD is an editable measure used to select the phase-out product for the current product. You can select the product from a picklist populated with all available products within the workspace.

Phs. Out Subst. Date

The Phs. Out Subst. Date is an editable measure used to select the substitution date for the phased-out product.

Tot. On Hand Units

The Tot. On Hand Units is the same as the one in the availability profile. Refer to the measure, Tot. On Hand Units, in the Availability Profile Measures.

Tot. Booked Units

The Tot. Booked Units is the same as the one in the inventory profile. Refer to the measure, Tot. Booked Units, in the Inventory Profile Measures.

Tot. In Transit Units



The Tot. In Transit Units is the same as the one in the inventory profile. Refer to the measure, Tot. In Transit Units, in the Inventory Profile Measures.

Tot. In Transit

The Tot. In Transit is the same as the one in the inventory profile. Refer to the measure, Tot. In Transit, in the Inventory Profile Measures.

Tot. On Order (in) Units

The Tot. On Order (in) Units is the same as the one in the inventory profile. Refer to the measure, Tot. On Order (out) Units, in the Inventory Profile Measures.

Tot. On Order (out) Units

The Tot. On Order (out) Units is the same as the one in the inventory profile. Refer to the measure, Tot. On Order (out) Units, in the Inventory Profile Measures.

Tot. Cust. Order Units

The Tot. Cust. Order Units is the same as the one in the inventory profile. Refer to the measure, Tot. Cust. Order Units, in the Inventory Profile Measures.

Loc. On Hand Units

The Loc. On Hand Units is the same as the one in the inventory profile. Refer to the measure, Loc. On Hand Units, in the Inventory Profile Measures.

Loc. Booked Units

The Loc. Booked Units is the same as the one in the inventory profile. Refer to the measure, Loc. Booked Units, in the Inventory Profile Measures.

Loc. In Transit Units

The Loc. In Transit Units is the same as the one in the inventory profile. Refer to the measure, Loc. In Transit Units, in the Inventory Profile Measures.

Loc. In Transit

The Loc. In Transit is the same as the one in the inventory profile. Refer to the measure, Loc. In Transit in the Inventory Profile Measures.

Loc. On Order (in) Units

The Loc. On Order (in) Units is the same as the one in the inventory profile. Refer to the measure, Loc. On Order (in) Units, in the Inventory Profile Measures.

Loc. On Order (out) Units

Loc. On Order (out) Units is the same as the one in the inventory profile. Refer to the measure, Loc. On Order (out) Units, in the Inventory Profile Measures.

Cust. Order Units

The Cust. Order Units is the same as the one in the inventory profile. Refer to the measure, Cust. Order Units, in the Inventory Profile Measures.

Ph. Out On Hand Units

The Ph. Out On Hand Units is the same as the one in the inventory profile. Refer to the measure, Ph. Out On Hand Units, in the Inventory Profile Measures.



Ph. Out Booked Units

The Ph. Out Booked Units is the same as the one in the inventory profile. Refer to the measure, Ph. Out Booked Units, in the Inventory Profile Measures.

Ph. Out In Transit Units

The Ph. Out In Transit Units is the same as the one in the inventory profile. Refer to the measure, Ph. Out In Transit Units, in the Inventory Profile Measures.

Ph. Out In Transit

The Ph. Out In Transit is the same as the one in the inventory profile. Refer to the measure, Ph. Out In Transit in the Inventory Profile Measures.

Ph. Out On Order (in) Units

The Ph. Out On Order (in) Units is the same as the one in the inventory profile. Refer to the measure, Ph. Out On Order (in) Units, in the Inventory Profile Measures.

Ph. Out On Order (out) Units

The Ph. Out On Order (out) Units is the same as the one in the inventory profile. Refer to the measure, Ph. Out On Order (out) Units, in the Inventory Profile Measures.

Ph. Out Cust. Order Units

The Ph. Out Cust. Order Units is the same as the one in the inventory profile. Refer to the measure, Ph. Out Cust. Order Units, in the Inventory Profile Measures.

SKU Level (R & A) View - YTDYTG Profile Measures

The Year-To-Date Year-To-Go (YTDYTG) measure profile available in the SKU Level (R & A) view contains the following measures.

User Filter PROD - LOC

The User Filter PROD - LOC is the same as the one in the default profile. Refer to the measure User Filter PROD-LOC in the Default Profile Measures.

Tot. Init. Fcst Units

The Tot. Init. Fcst Units is the same as the one in the parameters profile. Refer to the measure, Tot. Init. Fcst Units, in the Parameters Profile Measures.

Actual Loc. Sales Units

The Actual Loc. Sales Units is the same as the one in the actuals profile. Refer to the measure, Actual Loc. Sales Units, in the Actuals Profile Measures.

Sell-Out Fcst (Wk) Units

The Sell-Out Fcst (Wk) Units is the same as the one in the forecast profile. Refer to the measure, Sell-Out Fcst (Wk) Units, in the Forecast Profile Measures.

Lifecycle Sales To-Date %

The Lifecycle Sales To-Date % is the same as the one in the default profile. Refer to the measure, Lifecycle Sales To-Date %, in the Default Profile Measures.

Lifecycle Sales To-Go %



The Lifecycle Sales To-Go % is the same as the one in the default profile. Refer to the measure, Lifecycle Sales To-Go %, in the Default Profile Measures.

Actual Loc. Recpt Units

The Actual Loc. Recpt Units is the same as the one in the actuals profile. Refer to the measure, Actual Loc. Recpt Units, in the Actuals Profile Measures.

Actual Loc. Shipmt Units

The Actual Loc. Shipmt Units is the same as the one in the actuals profile. Refer to the measure, Actual Loc. Shipmt Units, in the Actuals Profile Measures.

Lifecycle Receipt To-Date %

The Lifecycle Receipt To-Date % is a calculated measure used to indicate the percentage of actual receipts up to date against the total initial forecast.

Figure 21-22 Calculation

$$100* \frac{\sum_{firstweek}^{currentweek} Actual Loc.\, RecptUnits}{Tot.\, Init.\, FcstUnits}$$

Lifecycle Sell-Thru %

The Lifecycle Sell-Thru % is a calculated measure used to indicate the percentage of lifecycle product's sell-through.

Figure 21-23 Calculation

$$100* \frac{\sum_{firstweek}^{currentweek} Actual Sales Units}{\sum_{firstweek}^{currentweek} Actual Loc. \, Recpt Units}$$


SKU-LOC Level (R & A) View

The **SKU-LOC Level (R & A) View**, under the **By Prod tab**, is similar to the view SKU Level (R & A) but allows you to do the review at the product and location levels.

The navigation of this view is driven by real-time alerts or workspace alerts. To leverage the real-time alert navigation in this workspace the desired alerts should be enabled as RTA (measure Enable RTA) in the To-Do List view.



Figure 21-24 SKU-LOC Level (R & A) View



SKU-LOC Level (R & A) View - Default Profile Measures

The Default measure profile available in the SKU-LOC Level (R & A) view contains the following measures.

User Filter PROD-LOC

The User Filter PROD-LOC is an editable measure used to include specific product and location combinations into the quick filter. When selected, the quick filter restricts the condition to search only for the product and location combinations selected. When clear, the product and location combinations are not included in the filter condition.

Revwd PROD - LOC

The Revwd PROD - LOC is an editable measure used to indicate that the product and location combination alerts have been reviewed.

PROD - LOC Alerts

The PROD - LOC Alerts is a calculated measure used to display the Alert Short Descr. for all alerts that were triggered for the product and location combination.

Tot. Dest. Avail. Units

The Tot. Dest. Avail. Units is a calculated measure used to indicate the total quantity of units available at the location for the product and location combination.

Tot. Dest. Avail. Dur (w)

The Tot. Dest. Avail. Dur (w) is a calculated measure used to indicate the number of weeks that the Tot. Dest. Avail. Units can cover the demand for the product and location combination.

Forecast Over LT+RT Units

The Forecast Over LT+RT Units is a calculated measure to display the daily Forecast Demand for the product and location combination, in units, from the system date up to the number of days of Lead Time plus Review Time. The system date is available in the Today view.

RUTL @ Today Units



The RUTL @ Today Units is a calculated measure used to indicate the Reorder Up-to Level (RUTL) value in units for the product and location combination at the system date.

Unc. Need Total Units

The Unc. Need Total Units is a calculated measure used to indicate the total unconstrained quantity, in units, needed at the location for the product and location combination.

User Rpl. Fix Locked Units

The User Rpl. Fix Locked Units is an editable measure used to enter fixed replenishment units (order quantity) for the product and location combination. This measure overrides the product's system-calculated replenishment units.

Sys. Rpl. Plan In Units

The Sys. Rpl. Plan In Units is a calculated measure used to indicate the order quantity for the product and location combination based on the location needs. This value is calculated based on the replenishment rules and the available forecast.

Sys. Rpl. Plan In Pack Units

The Sys. Rpl. Plan In Pack Units is a calculated measure used to indicate the pack order quantity for the product and location combination based on the location needs. This value is calculated based on the replenishment rules and the available forecast.

Rpl. TBA

The Rpl. TBA is a calculated measure used to indicate whether the product and location combination needs the order to be approved manually.

Appr. Rpl. Plan

The Appr. Rpl. Plan is an editable measure used to indicate whether the product and location combination order should be approved or not by the approval process. The **Replenishment Approval** action button approves all orders when this measure is selected.

Appr. Rpl. Plan In Units

The Appr. Rpl. Plan In Units is a calculated measure used to indicate the approved replenishment planned units for the product and location combination.

Tot. Avail. Units

The Tot. Avail. Units is a calculated measure used to indicate the total quantity of units available for the product and location combination taking into consideration all inventory (booked, on-hand, transit and on-order) plus all orders (approved, planned, and exported) plus all transfers (approved, planned, and exported).

Tot. Avail. Dur (w)


The Tot. Avail. Dur (w) is a calculated measure used to indicate the number of weeks that the Tot. Avail. Units can cover the demand for the product and location combination.

Tot. Regular Units

The Tot. Regular Units is a calculated measure used to indicate the total regular units for the product. The calculation is based on the deficit and surplus units for the product and location combination.



Figure 21-25 Calculation



Tot. Deficit Units

The Tot. Deficit Units is a calculated measure used to indicate the inventory deficit using the total available inventory and Reorder Up-to Level (RUTL) value for the product and location combination.

Figure 21-26 Calculation

Max(RUTL@TodayUnits - Tot. Avail. Units, 0)

Tot Deficit %

The Tot Deficit % is a calculated measure used to indicate the percentage that the deficit units represent in the RUTL units for the product and location combination.

Figure 21-27 Calculation

$$100*\frac{Tot.\,DeficitUnits}{RUTL@TodayUnits}$$

Tot. Surplus Units



The Tot. Surplus Units is a calculated measure used to indicate the inventory surplus using the total available inventory and Reorder Up-to Level (RUTL) value for the product and location combination.

Figure 21-28 Calculation

$$Max(\sum_{alllocations}(Tot.\,Avail.\,Units-RUTL@TodayUnits),0)$$

Tot. Surplus %

The Tot. Surplus % is a calculated measure used to indicate the percentage that the surplus units represent in the RUTL units for the product and location combination.

Figure 21-29 Calculation

$$100*\frac{Tot.\,SurplusUnits}{RUTL@TodayUnits}$$

Tot. Fulfil. %

The Tot. Fulfil. % is a calculated measure used to indicate the percentage that the total available stock fulfills the RUTL for the product and location combination.

Figure 21-30 Calculation

$$100*\frac{Tot.\,Avail.\,Units}{RUTL@TodayUnits}$$

Lifecycle Sales To-date %

The Lifecycle Sales To-date % is a calculated measure used to indicate the percentage of actual sales up to date against the total initial forecast for the product and location combination.

Figure 21-31 Calculation

$$100* \frac{\sum_{firstweek}^{currentweek} Actual Loc. Sales Units}{Tot. Init. FcstUnits}$$



Lifecycle Sales To-Go %

The Lifecycle Sales To-Go % is a calculated measure used to indicate the percentage of sales to complete the total initial forecast for the product and location combination.

Figure 21-32 Calculation

$$100* \frac{\sum_{currentweek}^{horizon} Actual Loc. Sales Units + SellOutFcst(Wk)Units}{Tot. Init. FcstUnits}$$

SKU-LOC Level (R & A) - Measures: Actuals Profile

The Actuals measure profile available in the SKU-LOC Level (R & A) view contains the following measures.

User Filter PROD - LOC

The User Filter PROD - LOC is the same as the one in the default profile. Refer to the measure User Filter PROD-LOC in the Default Profile Measures.

Actual PL Sales Wk Units

The Actual PL Sales Wk Units is a calculated measure used to indicate the weekly sales, aggregated from the daily sales, for the product and location combination.

Actual Loc. Sales Units

The Actual Loc. Sales Units is a calculated measure used to indicate the weekly sales, aggregated from the daily sales, for the product and location combination.

Actual Loc. Recpt Units

The Actual Loc. Recpt Units is a calculated measure used to indicate the weekly receipts for the product and location combination.

Actual Loc. Shipmt Units

The Actual Loc. Shipmt Units is a calculated measure used to indicate the weekly shipments for the product and location combination.

Actual Sales W-4 Units

The Actual Sales W-4 Units is a calculated measure used to display the accumulated daily sales units at the system date week - 4 weeks for the product and location combination. The system date is available in the Today view.

Actual Sales W-3 Units

The Actual Sales W-3 Units is a calculated measure used to display the accumulated daily sales units at the system date week - 3 weeks for the product and location combination. The system date is available in the Today view.

Actual Sales W-2 Units

The Actual Sales W-2 Units is a calculated measure used to display the accumulated daily sales units at the system date week - 2 weeks for the product and location combination. The system date is available in the Today view.



Actual Sales W-1 Units

The Actual Sales W-1 Units is a calculated measure used to display the accumulated daily sales units at the system date week - 1 weeks for the product and location combination. The system date is available in the Today view.

Actual Sales W+0 Units

The Actual Sales W+0 Units is a calculated measure used to display the accumulated daily sales units for the current system date week for the product and location combination. The system date is available in the Today view.

Actual Sales W+1 Units

The Actual Sales W+1 Units is a calculated measure used to display the accumulated daily sales units for the current system date week + 1 week for the product and location combination. The system date is available in the Today view

Actual Sales W+2 Units

The Actual Sales W+2 Units is a calculated measure used to display the accumulated daily sales units for the current system date week + 2 weeks for the product and location combination. The system date is available in the Today view.

Actual Sales W+3 Units

The Actual Sales W+3 Units is a calculated measure used to display the accumulated daily sales units for the current system date week + 3 weeks for the product and location combination. The system date is available in the Today view.

Actual Sales W-1 to W+0 Units

The Actual Sales W-1 to W+0 Units is a calculated measure used to display the accumulated sales units from the system date week -1 until the system current week for the product and location combination. The system date is available in the Today view.

Actual Sales W-2 to W+0 Units

The Actual Sales W-2 to W+0 Units is a calculated measure used to display the accumulated sales units from the system date week – 2 until the system current week for the product and location combination. The system date is available in the Today view.

Actual Sales W-3 to W+0 Units

The Actual Sales W-3 to W+0 Units is a calculated measure used to display the accumulated sales units from the system date week – 3 until the system current week for the product and location combination. The system date is available in the Today view.

Actual Sales W-4 to W+0 Units

The Actual Sales W-4 to W+0 Units is a calculated measure used to display the accumulated sales units from the system date week – 4 until the system current week for the product and location combination. The system date is available in the Today view.

Actual Lost Sales W-4 to W-1 Units

The Actual Lost Sales W-4 to W-1 Units is a calculated measure used to display the accumulated lost sales units from the system date week -4 until the previous week (from the system date week) for the product and location combination. The system date is available in the Today view.

Actual Sales D-7 Units



The Actual Sales D-7 Units is a calculated measure used to display the accumulated daily sales units for the last 7 days (from the system date - 7 days until system date) for the product and location combination. The system date is available in the Today view.

Actual Sales D-15 Units

The Actual Sales D-15 Units is a calculated measure used to display the accumulated daily sales units for the last 15 days (from the system date - 15days until system date) for the product and location combination. The system date is available in the Today view.

Actual Sales D-30 Units

The Actual Sales D-30 Units is a calculated measure used to display the accumulated daily sales units for the last 30 days (from the system date - 30days until system date) for the product and location combination. The system date is available in the Today view.

Actual Avg Inv. W-1 Units

The Actual Avg Inv. W-1 Units is a calculated measure used to display the average inventory units at the previous week (system date week - 1 week) for the product and location combination. The system date is available in the Today view.

Actual Avg Inv. W-2 Units

The Actual Avg Inv. W-2 Units is a calculated measure used to display the average inventory units at the system date week - 2 weeks for the product and location combination. The system date is available in the Today view.

Actual Avg Inv. W-3 Units

The Actual Avg Inv. W-3 Units is a calculated measure used to display the average inventory units at the system date week - 3 weeks for the product and location combination. The system date is available in the Today view.

Actual Avg Inv. W-4 Units

The Actual Avg Inv. W-4 Units is a calculated measure used to display the average inventory units at the system date week - 4 weeks for the product and location combination. The system date is available in the Today view.

Actual PL Avg Inv. Wk Units

The Actual PL Avg Inv. Wk Units is a calculated measure used to display the average holding inventory of the assortment period.

SKU-LOC Level (R & A) - Measures: Availability Profile

The Availability measure profile available in the SKU-LOC Level (R & A) view contains the following measures.

User Filter PROD-LOC

The User Filter PROD-LOC is the same as the one in the default profile. Refer to the measure User Filter PROD-LOC in the Default Profile Measures.

RUTL Mask



The RUTL Mask is a calculated measure used to indicate whether the product and location combination is eligible for replenishment. When selected, then it is eligible. When clear, then it is ineligible.

Rpl. Dest. Mask

The Rpl. Dest. Mask is a calculated measure used to indicate whether the product and location combination is eligible for replenishment and the constraint parameter at the system date indicates that replenishment is enable too (measure Rpl. Active (Dst) @ Today). When selected, then it is eligible. When clear, then it is ineligible.

Rpl. Src. Mask

The Rpl. Src. Mask is a calculated measure used to indicate whether the product and source location combination is eligible to be used for replenishment. When selected, then it is eligible. When clear, then it is ineligible.

Tot. On Hand Units

The Tot. On Hand Units is a calculated measure used to indicate the total on-hand inventory units for the product and location combination. The total on-hand units includes the on-hand inventory loaded into IPOCS-Lifecycle Allocation and Replenishment plus the on-hand inventory units for the replacement/phase-out product, if any.

In Transit over LT+RT Units

In Transit over LT+RT Units is a calculated measure used to indicate the total in transit units over the lead time plus the review time for the product and location combination.

On Order (in) over LT+RT Units

The On Order (in) over LT+RT Units is a calculated measure used to indicate the total on order (in) units over the lead time plus the review time for the product and location combination.

Exp. Rpl. Plan In Units

The Exp. Rpl. Plan In Units is a calculated measure used to indicate the replenishment planned units to be exported from the batch for the product and location combination.

Appr. Rpl. Plan In Units

The Appr. Rpl. Plan In Units is the same as the one in the default profile. Refer to the measure, Appr. Rpl. Plan In Units, in the Default Profile Measures.

Appr. Rpl. Plan In Pack Units

The Appr. Rpl. Plan In Pack Units is a calculated measure used to indicate the approved replenishment planned packs units for the product and location combination.

Sys. Rpl. Plan In Units

The Sys. Rpl. Plan In Units is the same as the one in the default profile. Refer to the measure, Sys. Rpl. Plan In Units, in the Default Profile Measures.

Transfer Plan In Units

The Transfer Plan In Units is a calculated measure used to indicate the transfer units planned for the product and location combination.

Appr. Transfer In Units



The Appr. Transfer In Units is a calculated measure used to indicate the transfer units approved for the product and location combination.

Exp. Transfer Plan In Units

The Exp. Transfer Plan In Units is a calculated measure used to indicate the transfer units to be exported from the batch for the product and location combination.

On Order (out) over LT+RT Units

The On Order (out) over LT+RT Units is a calculated measure used to indicate the total on orders (out) units over the lead time plus the review time for the product and location combination.

Exp. Rpl. Plan Out Units

The Exp. Rpl. Plan Out Units is a calculated measure used to indicate the source location (for example, warehouse) replenishment planned units to be exported from the batch for the product and location combination.

Appr. Rpl. Plan Out Units

The Appr. Rpl. Plan Out Units is a calculated measure used to indicate the source location approved replenishment units for the product and location combination.

Sys. Rpl. Plan Out Units

The Sys. Rpl. Plan Out Units is a calculated measure used to indicate the order quantity for the source location based on the source location needs. This value is calculated based on the replenishment rules and the source location demand.

Transfer Plan Out Units

The Transfer Plan Out Units is a calculated measure used to indicate the source location's transfer units planned for the product and location combination.

Appr. Transfer Out Units

Appr. Transfer Out Units is a calculated measure used to indicate the source location's transfer units approved for the product and location combination.

Exp. Transfer Plan Out Units

The Exp. Transfer Plan Out Units is a calculated measure used to indicate the source location's transfer units to be exported from the batch for the product and location combination.

Tot. Dest. Avail. Units

The Tot. Dest. Avail. Units is the same as the one in the default profile. Refer to the measure, Tot. Dest. Avail. Units, in the Default Profile Measures.

Tot. Dest. Avail. Dur (w)

The Tot. Dest. Avail. Dur (w) is the same as the one in the default profile. Refer to the measure, Tot. Dest. Avail. Dur (w), in the Default Profile Measures.

Tot. Physical Avail. Units

The Tot. Physical Avail. Units is a calculated measure used to indicate the total quantity of units' physically available at the location for the product and location



combination. The physically available units differ from the available units as the booked inventory is taken into consideration.

Figure 21-33 Calculation

Tot. Dest. Avail, Units - Tot. BookedUnits

Tot. Physical Avail. Dur (w)

The Tot. Physical Avail. Dur (w) is a calculated measure used to indicate the number of weeks that the Tot. Physical Avail. Units can cover the demand for the product and location combination.

Up To Dest. Avail Units

The Up To Dest. Avail Units is the same as Tot. Dest. Avail Units grouped by source.

Up To Dest. Avail Dur (w)

The Up To Dest. Avail Dur (w) is the same as Tot. Dest. Avail Units grouped by source displayed by duration (weeks).

Tot. Src. Avail. Units

The Tot. Src. Avail. Units is a calculated measure used to indicate the total quantity of units available at the source location for the product and location combination.

Tot. Src. Avail Pack Units

The Tot. Src. Avail Pack Units is a calculated measure used to indicate the total quantity of pack units available at the source location. Tot. Dest. Avail (incl. Rpl. & Trsf. Out) Units Tot. Avail. Units This measure is the same as the one in the default profile. Refer to the measure, Tot. Avail. Units. in the Default Profile Measures.

Tot. Avail. Dur (w)

The Tot. Avail. Dur (w) is the same as the one in the default profile. Refer to the measure, Tot. Avail. Dur (w), in the Default Profile Measures.

SKU-LOC Level (R & A) - Measures: Forecast Profile

The Forecast measure profile available in the SKU-LOC Level (R & A) view contains the following measures.

User Filter PROD - LOC

The User Filter PROD - LOC is the same as the one in the default profile. Refer to the measure User Filter PROD-LOC in the Default Profile Measures.

Fcst W+0 Units

The Fcst W+0 Units is a calculated measure used to display forecast units for the current system date week for the product and location combination. The system date is available in the Today view.

Fcst W+1 Units



The Fcst W+1 Units is a calculated measure used to display forecast units at system date week +1 week for the product and location combination. The system date is available in the Today view.

Fcst W+2 Units

The Fcst W+2 Units is a calculated measure to display forecast units at system date week +2 weeks for the product and location combination. The system date is available in the Today view.

Fcst W+3 Units

The Fcst W+3 Units is a calculated measure used to display forecast units at system date week +3 weeks for the product and location combination. The system date is available in the Today view.

Fcst W+0 to W+1 Units

The Fcst W+0 to W+1 Units is a calculated measure used to display the accumulated forecast from the current system date week until the system current week + 1 for the product and location combination. The system date is available in the Today view.

Fcst W+0 to W+2 Units

The Fcst W+0 to W+2 Units is a calculated measure used to display the accumulated forecast from the current system date week until the system current week + 2 for the product and location combination. The system date is available in the Today view.

Fcst W+0 to W+3 Units

The Fcst W+0 to W+3 Units is a calculated measure used to display the accumulated forecast from the current system date week until the system current week + 3 for the product and location combination. The system date is available in the Today view.

Forecast Over LT+RT Units

The Forecast Over LT+RT Units is the same as the one in the default profile. Refer to the measure, Forecast Over LT+RT Units, in the Default Profile Measures.

Final Fcst PL Wk Units

The Final Fcst PL Wk Units measure is not applicable.

Sell-Out Fcst (Wk) Units

The Sell-Out Fcst (Wk) Units is an editable measure that is used to enter the demand at the location (destination location) for the product and location combination. In this view, the measure is aggregated and when changed the value is spread proportionally across weeks within the workspace (you can check the spread value in the SKU-LOC-WEEK Level (InvPlan) view).

Sell-In Fcst (Wk) Units

The Sell-In Fcst (Wk) Units is an editable measure to enter the weekly demand at the source location for the product and location combination.

Tot. Demand (Wk) Units

The Tot. Demand (Wk) Units is a calculated measure used to indicate the total weekly demand for the product and location combination. In this view, the measure is aggregated and when changed the value is spread proportionally across weeks within



the workspace (you can check the spread value in the SKU- LOC-WEEK Level (InvPlan) view).

Up To Sell_Out Fcst Units

The Up To Sell_Out Fcst Units is a calculated measure used to indicate the sell-out Forecast from the source location perspective for the product and location combination.

SKU-LOC Level (R & A) - Measures: Inventory Profile

The Inventory measure profile available in the SKU-LOC Level (R & A) view contains the following measures.

User Filter PROD - LOC

The User Filter PROD - LOC is the same as the one in the default profile. Refer to the measure User Filter PROD-LOC in the Default Profile Measures.

Tot. On Hand Units

The Tot. On Hand Units is the same as the one in the availability profile. Refer to the measure, Tot. On Hand Units, in the Availability Profile Measures.

Tot. Booked Units

The Tot. Booked Units is a calculated measure used to indicate the total inventory booked in units for the product and location combination.

In Transit over LT+RT Units

The In Transit over LT+RT Units is the same as the one in the availability profile. Refer to the measure, Availability Profile Measures.

Tot. In Transit Units

The Tot. In Transit Units is a calculated measure used to indicate the total inventory units in transit for the product and location combination.

Tot. In Transit

The Tot. In Transit is a calculated measure used to display comments for the in-transit inventory and for the phase-out item's inventory, if any, for the product and location combination.

Tot. On Order (in) Units

The Tot. On Order (in) Units is a calculated measure used to indicate the total on-order inventory units for the product and location combination. The total on-order units include the on-order inventory loaded into IPOCS-Lifecycle Allocation and Replenishment plus the on-order inventory units for the replacement or phase-out product, if any.

On Order (in) over LT+RT Units

The On Order (in) over LT+RT Units is the same as the one in the availability profile. Refer to the measure, On Order (in) over LT+RT Units, in the Availability Profile Measures.

In Transit + On Order (in) Units

The In Transit + On Order (in) Units is a calculated measure used to indicate the accumulated on order and in-transit inventory units for the product and location combination.

Tot. On Order (out) Units



The Tot. On Order (out) Units is a calculated measure used to indicate the total onorder inventory units out from the source locations (for example, warehouse) for the product and location combination. The total on-order (out) units includes the on-order inventory loaded into IPOCS-Lifecycle Allocation and Replenishment plus the on-order (out) inventory units for the replacement/phase-out product, if any.

On Order (out) over LT+RT Units

The On Order (out) over LT+RT Units is the same as the one in the availability profile. Refer to the measure, On Order (out) over LT+RT Units, in the Availability Profile Measures.

Tot. Cust. Order Units

The Tot. Cust. Order Units is a calculated measure used to indicate the total customer order units for the product and location combination. The total customer orders include the customer orders loaded into IPOCS-Lifecycle Allocation and Replenishment plus the customer orders for the replacement or phase-out product, if any.

Loc. On Hand Units

The Loc. On Hand Units is a loaded measure used to indicate the on-hand inventory units for the product and location combination.

Loc. Booked Units

The Loc. Booked Units is a loaded measure used to indicate the booked or reserved inventory units for the product and location combination.

Loc. In Transit Units

The Loc. In Transit Units is a loaded measure used to indicate the in-transit inventory units for the product and location combination.

Loc. In Transit

The Loc. In Transit is a loaded measure used to indicate whether the product and location combination has in-transit inventory or not. When selected, there is in-transit inventory. When clear, there is no in-transit inventory.

Loc. On Order (in) Units

The Loc. On Order (in) Units is a loaded measure used to indicate the on-order inventory units (into the destination locations) for the product and location combination.

Loc. On Order (out) Units

The Loc. On Order (out) Units is a loaded measure used to indicate the on-order inventory units (out from source locations) for the product and location combination.

Cust. Order Units

The Cust. Order Units is a loaded measure used to indicate customer orders units for the product and location combination.

Ph. Out On Hand Units

The Ph. Out On Hand Units is a calculated measure used to indicate the product and location combination on-hand inventory units for the phased-out item, if any.

Ph. Out Booked Units



The Ph. Out Booked Units is a calculated measure used to indicate the product and location combination booked or reserved inventory units for the phased-out item, if any.

Ph. Out In Transit Units

The Ph. Out In Transit Units is a calculated measure used to indicate the product and location combination in-transit inventory units for the phased-out item, if any.

Ph. Out In Transit

The Ph. Out In Transit is a calculated measure used to indicate for product and location combination whether the phased-out item has in-transit inventory or not. When selected there is in-transit inventory. When clear, there is no in-transit inventory.

Ph. Out On Order (in) Units

The Ph. Out On Order (in) Units is a calculated measure used to indicate the product and location combination on-order inventory units (into the destination locations) for the phased-out item, if any.

Ph. Out On Order (out) Units

Ph. Out On Order (out) Units is a calculated measure used to indicate the product and location combination on-order inventory units (out from source locations) for the phased-out item, if any.

Ph. Out Cust. Order Units

The Ph. Out Cust. Order Units is a calculated measure used to indicate the product and location combination customer orders for the phased-out item, if any.

Pack Type

The Pack Type is a loaded measure used to indicate the product's pack type. Either simple or complex.

Pack Desc.

The Pack Desc. is a loaded measure used to indicate the product's pack description.

Pack - SKU Ass. Count

The Pack - SKU Ass. Count is a calculated measure used to indicate the total number of products (SKU) in the pack.

Pack - SKU Ass. Units

The Pack - SKU Ass. Units is an editable measure to indicate the total number of units the product (SKU) has in the pack.

SKU-LOC Level (R & A) - Measures: Parameters Profile

The Parameters measure profile available in the SKU-LOC Level (R & A) view contains the following measures.

User Filter PROD - LOC

The User Filter PROD - LOC is the same as the one in the default profile. Refer to the measure User Filter PROD-LOC in the Default Profile Measures.

Asst. Prod-Loc



The Asst. Prod-Loc is a loaded measure used to indicate whether the product and location combinations are assorted or not. For more details, refer to the same measure in the Product-Location view within the Manage Assortment workspace.

Asst. Prod-Loc Count

The Asst. Prod-Loc Count is a loaded measure used to indicate the total number of product and location combinations assorted. For more details, refer to the same measure in the Product-Location view within the Manage Assortment workspace.

Asst. Prod-Loc Active

The Asst. Prod-Loc Active is a loaded measure used to indicate whether the product and location combinations are assorted and still active or not. For more details check the same measure in the view Product- Location within the Manage Assortment workspace.

Asst. Prod-Loc Active Count

The Asst. Prod-Loc Active Count is a loaded measure used to indicate the total number of product and location combinations assorted and still active. For more details check the same measure in the view Product-Location within the Assortment Admin workspace.

Asst. Prod-Loc Start Date

The Asst. Prod-Loc Start Date is a loaded measure used to indicate the assortment start date for the assorted product and location combinations. For more details, refer to the same measure in the Product-Location view within the Manage Assortment workspace.

Asst. Prod-Loc End Date

The Asst. Prod-Loc End Date is a loaded measure used to indicate the assortment end date for the assorted product and location combinations. For more details, refer to the same measure in the Product-Location view within the Manage Assortment workspace.

Lfc. Prod-Loc

The Lfc. Prod-Loc is a loaded measure used to indicate whether the product and location combination has a valid lifecycle or not. For more details, refer to the same measure in the Product-Location view within the Manage Assortment workspace.

Lfc Prod-Loc Count

The Lfc Prod-Loc Count is a calculated measure used to indicate the number of locations where the product has a valid lifecycle. If this view is at the product and location level, then the count is not higher than one at the view's lowest level.

PL Lfc.

The PL Lfc. is a loaded measure used to indicate whether the product and location combination has a valid lifecycle or not at the system date.

Lfc. Active @ Today

The Lfc. Active @ Today is a loaded measure used to indicate whether the product and location combination has a valid lifecycle or not at the system date.

Display Qty Units



The Display Quantity Units is a loaded measure used to indicate the Display Quantity for the product and location combination used by IPOCS-Lifecycle Allocation and Replenishment for the RUTL calculation.

Min Order Qty Units

The Min Order Quantity Units is an editable measure used to indicate the minimum order quantity for the product and location combination.

Mult. Order Qty Units

The Mult. Order Quantity Units is an editable measure used to indicate the number of multiple order quantities for the product and location combination.

Fixed TS 1 Units

The Fixed TS 1 Units is a loaded measure used to indicate the initial allocation for the product and location combination. For more details, refer to the same measure in the Product-Location view within the Manage Assortment workspace.

Fixed TS 2 Units

The Fixed TS 2 Units is an editable measure used to indicate an initial allocation for the product and location combination. For more details, refer to the same measure in the Product-Location view within the Manage Assortment workspace.

Fixed TS 3 Units

The Fixed TS 3 Units is an editable measure used to indicate an initial allocation for the product and location combination. For more details, refer to the same measure in the Product-Location view within the Manage Assortment workspace.

Tot. Init. Fcst Units

The Tot. Init. Fcst Units is a loaded measure to display the total initial forecast for the product and location combination. For more details check the same measure in the SKU-LOC view within the Supply Chain Network workspace.

Conversion UOM 1

The Conversion UOM 1 is an editable measure used to indicate a value when converting units into a specific unit of measure based on the Constraint UOM 1 for scaling.

Conversion UOM 2

The Conversion UOM 2 is an editable measure used to indicate a value when converting units into a specific unit of measure based on the Constraint UOM 1 for scaling.

Conversion UOM 3

The Conversion UOM 3 is an editable measure used to indicate a value when converting units into a specific unit of measure based on the Constraint UOM 1 for scaling.

Avg. Cost €

The Avg. Cost € is an editable measure used to indicate the average cost for the product and location combination.

Price (excl.VAT) €

The Price (excl.VAT) € is an editable measure used to indicate the price excluding VAT for the product and location combination.



PL BOD

The PL BOD is a loaded measure used to indicate the bill of distribution applied to the product and location combination. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Primary Source @ Today

The Primary Source @ Today is a loaded measure used to indicate the applied primary source for the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Reserved Source 1 @ Today

The Reserved Source 1 @ Today is a calculated measure used to indicate the applied reserved source 1 for the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Reserved Source 2 @ Today

The Reserved Source 2 @ Today is a calculated measure used to indicate the applied reserved source 2 for the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Alternate Source @ Today

The Alternate Source @ Today is a calculated measure used to indicate the applied alternative source for the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKULOC view within the Supply Chain Network workspace.

LLC @ Today

The LLC @ Today is a calculated measure used to indicate the low-level code applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Lead Time @ Today Dur (d)

vLead Time @ Today Dur (d) is a calculated measure used to indicate the applied lead time, in days, for the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

PL Plc.

The PL Plc. is a loaded measure used to indicate the planning calendar applied to the product and location combination. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Revw @ Today

The Revw @ Today is a calculated measure used to indicate if Today (current system date) is a review day for the product and location combination. For more details about



the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Next Revw @ Today Date

The Next Revw @ Today Date is a calculated measure used to indicate the next review date for the product and location combination. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Next Revw @ Today Dur (d)

The Next Revw @ Today Dur (d) is a calculated measure used to indicate the number of days to the next review date for the product and location combination and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Avg Revw Time @ Today Dur (d)

The Avg Revw Time @ Today Dur (d) is a calculated measure used to indicate the average number of days between each review period (planning period) for the product and location combination. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

RUTL Mask

The RUTL Mask is the same as the one in the availability profile. Refer to the measure, RUTL Mask, in the Availability Profile Measures.

PL Rpl.

The PL Rpl. is a loaded measure used to indicate the replenishment parameter applied to the product and location combination. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Replenishment Parameters workspace.

Min Cred. Qty @ Today Units

The Min Cred. Quantity @ Today Units is a calculated measure used to indicate the Minimum Credible Quantity applied to the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

ROL Meth. @ Today

The ROL Meth. @ Today is a calculated measure used to indicate the ROL method applied to the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Min Qty @ Today Units

The Min Quantity @ Today Units is a calculated measure used to indicate the ROL minimum quantity units applied to the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Min TS @ Today Dur (d)

The Min TS @ Today Dur (d) is a calculated measure used to indicate the ROL minimum time supply (in days) applied to the product and location combination at the system date and can



be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Tgt. SL @ Today %

The Tgt. SL @ Today % is a calculated measure used to indicate the Target Service Level % applied to the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Volatility @ Today %

The Volatility @ Today % is a calculated measure used to indicate the Volatility % applied to the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

ROL Sft. Time @ Today Dur (d)

The ROL Sft. Time @ Today Dur (d) details the Reorder level safety time duration applicable today based on rules association and used in replenishment calculations where the RUTL method is not Target Stock. The ROL level is determined as lead time + review time + ROL Sft Time @ Today Dur (d).

RUTL Meth. @ Today

The RUTL Meth. @ Today is a calculated measure used to indicate the RUTL method applied to the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Max Qty @ Today Units

The Max Quantity @ Today Units is a calculated measure used to indicate the RUTL maximum quantity units applied to the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Max TS @ Today Dur (d)

The Max TS @ Today Dur (d) is a calculated measure used to indicate the RUTL maximum time supply (in days) applied to the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Tgt. DoS @ Today Dur (d)

The Tgt. DoS @ Today Dur (d) is a calculated measure used to indicate the Target Days of Supply (in days) applied to the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

TS Meth. @ Today

The TS Meth. @ Today is a calculated measure used to indicate the target stock method applied to the product and location combination at the system date (when the RUTL method is target stock) and can be overridden. For more details about the



measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

TS Seas. Fcst @ Today %

The TS Seas. Fcst @ Today % is a calculated measure used to indicate the percentage of the Seasonal Forecast applied to the product and location combination at the system date (to be used when the RUTL method is target stock) and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

TS Sft. Time @ Today Dur (d)

The TS Sft. Time @ Today Dur (d) is a calculated measure used to indicate the number of days for the stock safety applied to the product and location combination at the system date (to be used when the RUTL method is target stock) and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Order Rounding Threshold @ Today %

The Order Rounding Threshold @ Today % is a calculated measure used to indicate the percentage to round up the orders applied to the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

PL Change

The PL Change is a loaded measure used to indicate the change parameter applied to the product and location combination. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Replenishment Parameters workspace.

Repl. Status @ Today

The Repl. Status @ Today is a calculated measure used to indicate whether the product and location combination at the system date is replenishable or not and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

ROL Chng @ Today %

The ROL Chng @ Today % is a calculated measure used to indicate the percentage to increase or decrease the system-generated ROL value applied to the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

RUTL Chng @ Today %

The RUTL Chng @ Today % is a calculated measure used to indicate the percentage to increase or decrease the system-generated RUTL value applied to the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Rpl. Dest. Mask

The Rpl. Dest. Mask is the same as the one in the availability profile. Refer to the measure, Rpl. Dest. Mask, in the Availability Profile Measures.

Rpl. Src. Mask



The Rpl. Src. Mask is the same as the one in the availability profile. Refer to the measure, Rpl. Dest. Mask, in the Availability Profile Measures.

PL Cst.

The PL Cst. is a loaded measure used to indicate the constraint parameter applied to the product and location combination. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Replenishment Parameters workspace.

Avail. Constr. (Src) @ Today

The Avail. Constr. (Src) @ Today is a calculated measure used to indicate whether a constraint is enabled or disabled (at the source location) for the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Src. Avail. (Src) @ Today

The Src. Avail. (Src) @ Today is a calculated measure used to indicate which stock units to be used from the source locations are applied to the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Src. Avail. (Src) @ Today Dur (d)

The Src. Avail. (Src) @ Today Dur (d) is a calculated measure used to indicate the number of days to get the in-transit and on-order stock is applied to the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Rpl. Active (Dst) @ Today

The Rpl. Active (Dst) @ Today is a calculated measure used to indicate the product and location combination at the system date if the location has the replenishment active or not and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Fulfill Till Layer (Dst) @ Today

The Fulfill Till Layer (Dst) @ Today is a calculated measure used to indicate the layer applied to the product and location combination at the system date (layer until which IPOCS-Lifecycle Allocation and Replenishment should fulfill the demand) and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Ration. Prio (Dst) @ Today

Ration. Prio (Dst) @ Today is a calculated measure used to indicate the rationing priority applied to the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

SubLayer (Dst) @ Today



The SubLayer (Dst) @ Today is a calculated measure used to indicate the sublayers applied to the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Assign Pack (Dst) @ Today

The Assign Pack (Dst) @ Today is a calculated measure used to indicate the pack types' assignment applied to the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Min Pack Fill Rate 1 (Dst) @ Today %

The Min Pack Fill Rate 1 (Dst) @ Today % is a calculated measure used to indicate the minimum pack fill rate percentage for first round of complex pack assignment applied to the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Min Pack Fill Rate 2 (Dst) @ Today %

The Min Pack Fill Rate 2 (Dst) @ Today % is a calculated measure used to indicate the minimum pack fill rate percentage for second round of complex pack assignment applied to the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

SKU-LOC Level (R & A) - Measures: Plan Profile

The Plan measure profile available in the SKU-LOC Level (R & A) view contains the following measures.

User Filter PROD - LOC

The User Filter PROD - LOC is the same as the one in the default profile. Refer to the measure User Filter PROD-LOC in the Default Profile Measures.

RUTL Mask

The RUTL Mask is the same as the one in the availability profile. Refer to the measure, RUTL Mask, in the Availability Profile Measures.

Rpl. Dest. Mask

The Rpl. Dest. Mask is the same as the one in the availability profile. Refer to the measure, Rpl. Dest. Mask, in the Availability Profile Measures.

Rpl. Src. Mask

The Rpl. Src. Mask is the same as the one in the availability profile. Refer to the measure, Rpl. Dest. Mask, in the Availability Profile Measures.

Pack Partition

The Pack Partition is the same as the one in the Plan profile for the view SKU Level (R & A) but available at the product and location level. Refer to the measure, Pack Partition, in the view SKU Level (R & A) Measures: Plan Profile in the Default Profile Measures.

Tot. Physical Avail. Units



The Tot. Physical Avail. Units is the same as the one in the availability profile. Refer to the measure, Tot. Physical Avail. Units, in the Availability Profile Measures.

Tot. Physical Avail. Dur (w)

The Tot. Physical Avail. Dur (w) is the same as the one in the availability profile. Refer to the measure, Tot. Physical Avail. Dur (w), in the Availability Profile Measures.

Tot. Dest. Avail. Units

The Tot. Dest. Avail. Units is the same as the one in the default profile. Refer to the measure, Tot. Dest. Avail. Units, in the Default Profile Measures.

Tot. Dest. Avail. Dur (w)

The Tot. Dest. Avail. Dur (w) is a calculated measure used to indicate the number of weeks that the Tot. Dest. Avail. Units can cover the demand for the product and location combination.

Tot. Src. Avail. Units

The Tot. Src. Avail. Units is a calculated measure used to indicate the total quantity of units available at the source location for the product and location combination. In this view, the value is the total for the product.

Tot. Src. Avail. Pack Units

The Tot. Src. Avail. Pack Units is a calculated measure used to indicate the total quantity of pack units available at the source location for the product and location combination. In this view, the value is the total for the product.

User Tot. Src. Avail. Units

The User Tot. Src. Avail. Units is an editable measure user can use to enter the total quantity of units available at the source location for the product. The value of this measure overrides the measure Tot. Src. Avail. Unit.

Manual Push Units

The Manual Push Units is an editable measure used to enter the total quantity of units to be manually pushed from the source location to the destination locations for the product. The value is spread proportionally between all the product's destination locations.

ROL @ Today Units

The ROL @ Today Units is a calculated measure used to indicate the Reorder level (ROL) value in units for the product and location combination at the system date.

RUTL @ Today Units

The RUTL @ Today Units is the same as the one in the default profile. Refer to the measure, RUTL @ Today Units, in the Default Profile Measures.

User RUTL Override Units

The User RUTL Override Units is an editable measure used to enter the Reorder Upto Level (RUTL) value in units for the product and location combination. The value of this measure overrides the measure RUTL @ Today Units.

User RUTL Override End Date



The User RUTL Override End Date is an editable measure used to enter the date when IPOCS-Lifecycle Allocation and Replenishment should stop using the user-defined RUTL units (measure User RUTL Override Units) and start using the system calculated RUTL units (measure RUTL @ Today Units).

Forecast Over LT+RT Units

The Forecast Over LT+RT Units is the same as the one in the forecast profile. Refer to the measure, Forecast Over LT+RT Units, in the Forecast Profile Measures.

Unc. Need Total Units

The Unc. Need Total Units is the same as the one in the default profile. Refer to the measure, Unc. Need Total Units, in the Default Profile Measures.

Min Unc. Need Pack Units

The Min Unc. Need Pack Units indicates the minimum unit of Packs needed regardless of Pack Fill Rate.

Max Unc. Need Pack Units

The Max Unc. Need Pack Units indicates the maximum unit of Packs needed regardless of Pack Fill Rate.

User Rpl. Fix Locked Units

The User Rpl. Fix Locked Units is an editable measure you can use to enter fixed replenishment units (order quantity) for the product and location combination. This measure overrides the product's system-calculated replenishment units.

Sys. Rpl. Plan In Units

The Sys. Rpl. Plan In Units is the same as the one in the default profile. Refer to the measure, Sys. Rpl. Plan In Units, in the Default Profile Measures.

Sys. Rpl. Plan In Pack Units

The Sys. Rpl. Plan In Pack Units is the same as the one in the default profile. Refer to the measure, Sys. Rpl. Plan In Pack Units, in the Default Profile Measures.

Unc. Req. Total Units

The Unc. Req. Total Units is a calculated measure used to indicate the total unconstrained quantity, in units, needed for the source location (for example, warehouse) for the product.

Sys. Rpl. Plan Out Units

The Sys. Rpl. Plan Out Units is the same as the one in the availability profile. Refer to the measure, Sys. Rpl. Plan Out Units, in the Availability Profile Measures.

Sys. Rpl. Plan Out Pack Units

The Sys. Rpl. Plan Out Pack Units is a calculated measure used to indicate the pack order quantity (either simple or complex packs) for the source location based on the source location needs. This value is calculated based on the replenishment rules and the source location demand.

Tot. Avail. Units

The Tot. Avail. Units is the same as the one in the default profile. Refer to the measure, Tot. Avail. Units, in the Default Profile Measures.



Tot. Avail. Dur (w)

The Tot. Avail. Dur (w) is the same as the one in the default profile. Refer to the measure, Tot. Avail. Dur (w), in the Default Profile Measures.

Tot. Regular Units

The Tot. Regular Units is the same as the one in the default profile. Refer to the measure, Tot. Regular Units, in the Default Profile Measures.

Tot. Deficit Units

The Tot. Deficit Units is the same as the one in the default profile. Refer to the measure, Tot. Deficit Units, in the Default Profile Measures.

Tot. Deficit %

The Tot. Deficit % is the same as the one in the default profile. Refer to the measure, Tot. Deficit %, in the Default Profile Measures.

Tot. Surplus Units

The Tot. Surplus Units is the same as the one in the default profile. Refer to the measure, Tot. Surplus Units, in the Default Profile Measures.

Tot. Surplus %

The Tot. Surplus % is the same as the one in the default profile. Refer to the measure, Tot. Surplus %, in the Default Profile Measures.

Tot. Fulfil. %

The Tot. Fulfil. % is the same as the one in the default profile. Refer to the measure, Tot. Fulfil. %, in the Default Profile Measures.

Rpl. TBA

The Rpl. TBA is the same as the one in the default profile. Refer to the measure, Rpl. TBA, in the Default Profile Measures.

Appr. Rpl. Plan

The Appr. Rpl. Plan is an editable measure used to indicate whether the product and location order should be approved or not by the approval process. The **Replenishment Approval** action button approves all orders when this measure is selected.

Appr. Rpl. Plan User ID

The Appr. Rpl. Plan User ID is a calculated measure used to audit the **Replenishment Approval** action button. It is populated with the user-identifier that last ran the Replenishment Approval.

Appr. Rpl. Plan Date

The Appr. Rpl. Plan Date is a calculated measure to audit the **Replenishment Approval** action button. It is populated with the date and time that the replenishment approval was last run.

Appr. Rpl. Plan In Units

The Appr. Rpl. Plan In Units is the same as the one in the default profile. Refer to the measure, Appr. Rpl. Plan In Units, in the Default Profile Measures.



Appr. Rpl. Plan In Pack Units

The Appr. Rpl. Plan In Pack Units is the same as the one in the availability profile. Refer to the measure, Appr. Rpl. Plan In Pack Units, in the Availability Profile Measures.

Appr. Rpl. Plan Out Units

The Appr. Rpl. Plan Out Units is the same as the one in the availability profile. Refer to the measure, Appr. Rpl. Plan Out Units, in the Availability Profile Measures.

Exp. Rpl. Plan Date

The Exp. Rpl. Plan Date is a calculated measure to audit the replenishment export for the product and location combination. It is populated with the date and time that the replenishment was exported by the batch, if exported by the last batch run. Otherwise, it is empty.

Exp. Rpl. Plan In Units

The Exp. Rpl. Plan In Units is the same as the one in the availability profile. Refer to the measure, Exp. Rpl. Plan In Units, in the Availability Profile Measures.

Exp. Rpl. Plan In (details)

The Exp. Rpl. Plan In (details) is a calculated measure used to indicate the breakdown of exported plan in units per batch cycle.

Exp. Rpl. Plan Out Units

The Exp. Rpl. Plan Out Units is the same as the one in the availability profile. Refer to the measure, Exp. Rpl. Plan Out Units, in the Availability Profile Measures.

Exp. Rpl. Plan Out (details)

The Exp. Rpl. Plan Out (details) is a calculated measure used to indicate the breakdown of exported plan out units per batch cycle.



When the view has a lower intersection than the displayed measure, then the measure displays "-" to inform you that the measure is not available at that level.

SKU-LOC Level (R & A) - Measures: Replacement Profile

The Replacement measure profile available in the SKU-LOC Level (R & A) view contains the following measures.

User Filter PROD - LOC

The User Filter PROD - LOC is the same as the one in the default profile. Refer to the measure User Filter PROD-LOC in the Default Profile Measures.

Phs. Out PROD

vPhs. Out PROD is an editable measure used to select the phase-out product for the current product. You can select the product from a picklist populated with all available products within the workspace. It is not possible to have different values per location.

Phs. Out Subst. Date



The Phs. Out Subst. Date is an editable measure used to select the substitution date for the phased out product. It is not possible to have different values per location.

Tot. On Hand Units

The Tot. On Hand Units is the same as the one in the inventory profile. Refer to the measure, Tot. On Hand Units, in the Inventory Profile Measures.

Tot. Booked Units

The Tot. Booked Units is the same as the one in the inventory profile. Refer to the measure, Tot. Booked Units, in the Inventory Profile Measures.

Tot. In Transit Units

The Tot. In Transit Units is the same as the one in the inventory profile. Refer to the measure, Tot. In Transit Units, in the Inventory Profile Measures.

Tot. In Transit

The Tot. In Transit is the same as the one in the inventory profile. Refer to the measure, Tot. In Transit, in the Inventory Profile Measures.

Tot. On Order (in) Units

The Tot. On Order (in) Units is the same as the one in the inventory profile. Refer to the measure, Tot. On Order (in) Units, in the Inventory Profile Measures.

Tot. On Order (out) Units

The Tot. On Order (out) Units is the same as the one in the inventory profile. Refer to the measure, Tot. On Order (out) Units, in the Inventory Profile Measures.

Tot. Cust. Order Units

The Tot. Cust. Order Units is the same as the one in the inventory profile. Refer to the measure, Tot. Cust. Order Units, in the Inventory Profile Measures.

Loc. On Hand Units

The Loc. On Hand Units is the same as the one in the inventory profile. Refer to the measure, Loc. On Hand Units, in the Inventory Profile Measures.

Loc. Booked Units

The Loc. Booked Units is the same as the one in the inventory profile. Refer to the measure, Loc. Booked Units, in the Inventory Profile Measures.

Loc. In Transit Units

The Loc. In Transit Units is the same as the one in the inventory profile. Refer to the measure, Loc. In Transit Units, in the Inventory Profile Measures.

Loc. In Transit

The Loc. In Transit is the same as the one in the inventory profile. Refer to the measure, Loc. In Transit, in the Inventory Profile Measures.

Loc. On Order (in) Units

The Loc. On Order (in) Units is the same as the one in the inventory profile. Refer to the measure, Loc. On Order (in) Units, in the Inventory Profile Measures.



Loc. On Order (out) Units

The Loc. On Order (out) Units is the same as the one in the inventory profile. Refer to the measure, Loc. On Order (out) Units, in the Inventory Profile Measures.

Cust. Order Units

The Cust. Order Units is the same as the one in the inventory profile. Refer to the measure, Cust. Order Units, in the Inventory Profile Measures.

Ph. Out On Hand Units

The Ph. Out On Hand Units is the same as the one in the inventory profile. Refer to the measure, Ph. Out On Hand Units, in the Inventory Profile Measures.

Ph. Out Booked Units

The Ph. Out Booked Units is the same as the one in the inventory profile. Refer to the measure, Ph. Out Booked Units, in the Inventory Profile Measures.

Ph. Out In Transit Units

The Ph. Out In Transit Units is the same as the one in the inventory profile. Refer to the measure, Ph. Out In Transit Units, in the Inventory Profile Measures.

Ph. Out In Transit

The Ph. Out In Transit is the same as the one in the inventory profile. Refer to the measure, Ph. Out In Transit, in the Inventory Profile Measures.

Ph. Out On Order (in) Units

The Ph. Out On Order (in) Units is the same as the one in the inventory profile. Refer to the measure, Ph. Out On Order (in) Units, in the Inventory Profile Measures.

Ph. Out On Order (out) Units

The Ph. Out On Order (out) Units is the same as the one in the inventory profile. Refer to the measure, Ph. Out On Order (out) Units, in the Inventory Profile Measures.

Ph. Out Cust. Order Units

The Ph. Out Cust. Order Units is the same as the one in the inventory profile. Refer to the measure, Ph. Out Cust. Order Units, in the Inventory Profile Measures.



When the view has a lower intersection than the displayed measure, then the measure displays "-" to inform you that the measure is not available at that level.

SKU-LOC Level (R & A) - Measures: YTDYTG Profile

The Year-To-Date Year-To-Go (YTDYTG) measure profile available in the SKU-LOC Level (R & A) view contains the following measures.

User Filter PROD - LOC

The User Filter PROD - LOC is the same as the one in the default profile. Refer to the measure User Filter PROD-LOC in the Default Profile Measures.



Tot. Init. Fcst Units

The Tot. Init. Fcst Units is the same as the one in the parameters profile. Refer to the measure, Tot. Init. Fcst Units, in the Parameters Profile Measures.

Actual Loc. Sales Units

The Actual Loc. Sales Units is the same as the one in the actuals profile. Refer to the measure, Actual Loc. Sales Units, in the Actuals Profile Measures.

Sell-Out Fcst (Wk) Units

The Sell-Out Fcst (Wk) Units is the same as the one in the forecast profile. Refer to the measure, Sell-Out Fcst (Wk) Units, in the Forecast Profile Measures.

Lifecycle Sales To-Date %

The Lifecycle Sales To-Date % is the same as the one in the default profile. Refer to the measure, Lifecycle Sales To-Date %, in the Default Profile Measures.

Lifecycle Sales To-Go %

The Lifecycle Sales To-Go % is the same as the one in the default profile. Refer to the measure, Lifecycle Sales To-Go %, in the Default Profile Measures.

Actual Loc. Recpt Units

The Actual Loc. Recpt Units is the same as the one in the actuals profile. Refer to the measure, Actual Loc. Recpt Units, in the Actuals Profile Measures.

Actual Loc. Shipmt Units

The Actual Loc. Shipmt Units is the same as the one in the actuals profile. Refer to the measure, Actual Loc. Shipmt Units, in the Actuals Profile Measures.

Lifecycle Receipt To-Date %

The Lifecycle Receipt To-Date % is a calculated measure used to indicate the percentage of actual receipts up to date against the total initial forecast for the product and location combination.

Figure 21-34 Calculation

$$100* \frac{\sum_{firstweek}^{currentweek} Actual Loc.\, RecptUnits}{Tot.\, Init.\, FcstUnits}$$

Lifecycle Sell-Thru %

The Lifecycle Sell-Thru % is a calculated measure used to indicate the percentage of lifecycle product's sell-through for the product and location combination.




Figure 21-35 Calculation

$$100* \frac{\sum_{firstweek}^{currentweek} Actual Sales Units}{\sum_{firstweek}^{currentweek} Actual Loc. \, Recpt Units}$$

SKU-Source LOC Level (R & A) View

The SKU-Source LOC Level (R & A) View, under the By Prod tab, allows you to review the replenishment and allocation calculated values at the product level from the source location perspective.

Figure 21-36 SKU-Source LOC Level (R & A) View



SKU-Source LOC Level (R & A) View - Default Profile Measures

The Default measure profile available in the SKU-Source LOC Level (R & A) view contains the following measures.

PROD - LOC Alerts

The PROD - LOC Alerts is a calculated measure used to display the Alert Short Descr. of all the alerts that got triggered for the product and location combination.

Src. Avail. (Src) @ Today

The Src. Avail. (Src) @ Today is a calculated measure used to indicate which stock units to be used from the source locations are applied to the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Src. Avail. (Src) @ Today Dur (d)

The Src. Avail. (Src) @ Today Dur (d) is a calculated measure used to indicate the number of days to get the in-transit and on-order stock is applied to the product and location



combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Tot. On Hand Units

The Tot. On Hand Units is a calculated measure used to indicate the total on-hand inventory units for the product and location combination. The total on-hand units includes the on-hand inventory loaded into IPOCS-Lifecycle Allocation and Replenishment plus the on-hand inventory units for the replacement/phase-out product, if any.

In Transit + On Order (in) Units

The In Transit + On Order (in) Units is a calculated measure used to indicate the accumulated on-order and in-transit inventory units for the product and location combination.

Tot. Src. Avail. Units

The Tot. Src. Avail. Units is a calculated measure used to indicate the total quantity of units available at the source location for the product. (This considers the inventory buckets defined by the Src. Avail. (Src) @ Today measure).

Tot. Src. Avail. Pack Units

The Tot. Src. Avail. Pack Units is a calculated measure used to indicate the total quantity of pack units available at the source location.

User Tot. Src. Avail. Units

The User Tot. Src. Avail. Units is an editable measure you can use to enter the total quantity of units available at the source location for the product. The value of this measure overrides the measure Tot. Src. Avail. Unit

Manual Push Units

The Manual Push Units is an editable measure used to input the total quantity of units to be manually pushed from the source location to the destination locations for the product. The value is spread proportionally between all the product's destination locations.

Unc. Req. Total Units

The Unc. Req. Total Units is a calculated measure used to indicate the total unconstrained quantity, in units, needed for the source location (for example, warehouse) for the product.

Sys. Rpl. Plan Out Units

The Sys. Rpl. Plan Out Units is a calculated measure used to indicate the order quantity for the source location based on the source location needs. This value is calculated based on the replenishment rules and the source location demand.

Sys. Rpl. Plan Out Pack Units

The Sys. Rpl. Plan Out Pack Units is a calculated measure used to indicate the pack order quantity (either simple or complex packs) for the source location based on the source location needs. This value is calculated based on the replenishment rules and the source location demand.



Appr. Rpl. Plan Out Units

The Appr. Rpl. Plan Out Units is a calculated measure used to indicate the source location approved replenishment units for the product and location combination.

Tot. Avail. Units

The Tot. Avail. Units is a calculated measure used to indicate the total quantity of units available for the product and location combination considering all inventory (booked, on-hand, transit and on-order) plus all orders (approved, planned and exported) plus all transfers (approved, planned and exported).

Tot. Avail. Dur (w)

The Tot. Avail. Dur (w) is a calculated measure used to indicate the number of weeks that the Tot. Avail. Units can cover the demand for the product and location combination.

VAR-LOC Level (R & A) View

The VAR-LOC Level (R & A) View, under the By Prod tab, is similar to the view SKU-LOC Level (R & A) but allows you to review the variant and location levels.

The navigation of this view is very conveniently driven by real-time alerts or workspace alerts. To leverage the real-time alert navigation in this workspace the desired alerts should be enabled as RTA (measure Enable RTA) in the To-Do List view.




Figure 21-37 VAR-LOC Level (R & A) View

VAR-LOC Level (R & A) View - Default Profile Measures

The Default measure profile available in this view contains the same measures as the Default measure profile in the SKU-LOC Level (R & A) view. The only difference is that in this view, the data is aggregated from SKU to the VARIANT level. For more information regarding the measures in this profile, refer to the Measures: Default Profile under the SKU-LOC Level (R & A) view.



VAR-LOC Level (R & A) - Measures: Actuals Profile

The Actuals measure profile available in this view contains the same measures as the Actuals measure profile in the SKU-LOC Level (R & A) view. The only difference is that In this view, the data is aggregated from SKU to the VARIANT level. For more information regarding the measures in this profile refer to the Measures: Actuals Profile under the SKU-LOC Level (R & A) view.

VAR-LOC Level (R & A) - Measures: Availability Profile

The Availability measure profile available in this view contains the same measures as the Availability measure profile in the SKU-LOC Level (R & A) view. The only difference is that In this view, the data is aggregated from SKU to the VARIANT level. For more information regarding the measures in this profile refer to the Measures: Availability Profile under the SKU-LOC Level (R & A) view.

VAR-LOC Level (R & A) - Measures: Forecast Profile

The Forecast measure profile available in this view contains the same measures as the Forecast measure profile in the SKU-LOC Level (R & A) view. The only difference is that In this view, the data is aggregated from SKU to the VARIANT level. For more information regarding the measures in this profile refer to the Measures: Forecast Profile under the SKU-LOC Level (R & A) view.

VAR-LOC Level (R & A) - Measures: Inventory Profile

The Inventory measure profile available in this view contains the same measures as the Inventory measure profile in the SKU-LOC Level (R & A) view. The only difference is that in this view the data is aggregated from SKU to the VARIANT level. For more information regarding the measures in this profile refer to the Measures: Inventory Profile under the SKU-LOC Level (R & A) view.

VAR-LOC Level (R & A) - Measures: Parameters Profile

The Parameters measure profile available in this view contains the all the measures as in the Parameters measure profile in the SKU-LOC Level (R & A) view plus some additional variant measures. The only difference is that in this view the data is aggregated from SKU to the VARIANT level. For more information regarding the measures in this profile refer to the Measures: Parameters Profile under the SKU-LOC Level (R & A) view.

Following are the additional measures in this profile.

Asst. Var-Loc

The Asst. Var-Loc is a loaded measure used to indicate whether the variant and location combinations are assorted or not. For more details check the same measure in the view Variant-Location within the Manage Assortment workspace.

Asst. Var-Loc Count

The Asst. Var-Loc Count is a loaded measure used to indicate the total number of variant and location combinations assorted.

Asst. Var-Loc Active

The Asst. Var-Loc Active is a loaded measure used to indicate whether the variant and location combinations are assorted and still active or not. For more details check the



same measure in the view Variant- Location within the Manage Assortment workspace.

Asst. Var-Loc Active Count

The Asst. Var-Loc Active Count is a loaded measure used to indicate the total number of variant and location combinations assorted and still active.

Asst. Var-Loc Start Date

The Asst. Var-Loc Start Date is a loaded measure used to indicate the assortment start date for the assorted variant and location combinations. For more details check the same measure in the view Variant-Location within the Manage Assortment workspace.

Asst. Var-Loc End Date

The Asst. Var-Loc End Date is a loaded measure used to indicate the assortment end date for the assorted variant and location combinations. For more details check the same measure in the view Variant-Location within the Manage Assortment workspace.

Asst. Var-Loc From Start Dur (weeks)

The Asst. Var-Loc From Start Dur (weeks) is a calculated measure used to indicate the number of elapsed weeks since the assortment started date indicated in the measure Asst. Var-Loc Start Date. The number the weeks is calculated until IPOCS-Lifecycle Allocation and Replenishment today's week.

VAR-LOC Level (R & A) - Measures: Plan Profile

The Plan measure profile available in this view contains the same measures as the Plan measure profile in the SKU-LOC Level (R & A) view. The only difference is that in this view the data is aggregated from SKU to the VARIANT level. For more information regarding the measures in this profile refer to the Measures: Plan Profile under the SKU-LOC Level (R & A) view.

VAR-LOC Level (R & A) - Measures: Replacement Profile

The Replacement measure profile available in this view contains the same measures as the Replacement measure profile in the SKU-LOC Level (R & A) view. The only difference is that in this view the data is aggregated from SKU to the VARIANT level. For more information regarding the measures in this profile refer to the Measures: Replacement Profile under the SKU-LOC Level (R & A) view.

VAR-LOC Level (R & A) - Measures: YTDYTG Profile

The YTDYTG measure profile available in this view contains the same measures as the YTDYTG measure profile in the SKU-LOC Level (R & A) view. The only difference is that in this view the data is aggregated from SKU to the VARIANT level. For more information regarding the measures in this profile refer to the Measures: YTDYTG Profile under the SKU-LOC Level (R & A) view.

VAR-Source LOC Level (R & A) View

The VAR-Source LOC Level (R & A) View, under the By Prod tab, is similar to the view SKU-Source LOC Level (R & A) but allows you to perform the review at the variant level rather than SKU. For more details regarding the measures, refer to the SKU-Source LOC Level (R & A) view.



Figure 21-38 VAR-Source LOC Level (R & A) View

LOC Level (R & A) View

The **LOC Level (R & A) View**, under the **By Location tab**, is similar to the SKU Level (R & A) view but the data is presented in a different layout. This view is driven by the location analysis rather than the SKU analysis. For more details regarding the available profiles and the measures within each profile, refer to the SKU Level (R & A) view.

Figure 21-39 LOC Level (R & A) View

LOC-SKU Level (R & A) View

The LOC-SKU Level (R & A) View, under the By Location tab, is similar to the SKU-LOC Level (R & A) view but the data is presented in a different layout. This view is driven by the location analysis rather than the SKU analysis. For more details regarding the available profiles and the measures within each profile, refer to the SKU-LOC Level (R & A) view.



Review & Approve * By Prod By Location Space Product / PROD - LOC Alerts 2000003 - KT5 Low "Home" MaxStk MinDsp MaxStk MinDso 2000010 - 2020 Summer MaxStk MinDsp 4.7 w 2.6 w 2000014 - "Have Fun" 2020 34.94 MaxStk MinDsp 4.17 Calculate (F9) Reload Parameters Synchronize Forecast Calculate Plan Replenishment Approval Run Filters Within Day Exp. Refresh Clear Filters

Figure 21-40 LOC-SKU Level (R & A) View

LOC-VAR Level (R & A) View

The LOC-VAR Level (R & A) View, under the By Location tab, is similar to the VAR-LOC Level (R & A) view but the data is presented in a different layout. This view is driven by the location analysis rather than the VAR analysis. For more details regarding the available profiles and the measures within each profile the VAR-LOC Level (R & A) view.




Figure 21-41 LOC-VAR Level (R & A) View

Source LOC-SKU Level (R & A) View

The **Source LOC-SKU Level (R & A) View**, under the **By Location tab**, is similar to the SKU-Source LOC Level (R & A) view but the data is presented in a different layout. This view is driven by the source location analysis rather than the SKU analysis. For more details

regarding the available profiles and the measures within each profile, refer to the SKU-Source LOC Level (R & A) view.

Figure 21-42 Source LOC-SKU Level (R & A) View

Source LOC-VAR Level (R & A) View

The **Source LOC-VAR Level (R & A) View**, under the **By Location tab**, is similar to the VAR-Source LOC Level (R & A) view but the data is presented in a different layout. This view is driven by the source location analysis rather than the Variant analysis. For more details regarding the available profiles and the measures within each profile, refer to the VAR-Source LOC Level (R & A) view.




Figure 21-43 Source LOC-VAR Level (R & A) View


Display Space by LOC (R & A) View

The **Display Space by LOC (R & A) View**, under the **Space tab**, allows you to manage the display space parameters that is used by IPOCS-Lifecycle Allocation and

Replenishment to alert you for replenishment plan situations where merchandise reached the maximum display count or the minimum display count is not reached at a location or locations. The parameters managed in this view are:

- Min Display Space: Refers to the minimum display stock. It is based only on active items.
- Max Display Space: Refers to the available space for display stock. It is based only on active items.

Figure 21-44 Display Space by LOC (R & A) View



Display Space by LOC (R & A) View - Default Profile Measures

The Default measure profile available in the Display Space by LOC (R & A) view contains the following measures.

Display Space Count

The Display Space Count is a calculated measure used to indicate the total number of products, for the merchandise level (for example, Brand), that have available inventory units at the location.

Min Display Space Count

The Min Display Space Count is an editable measure used to enter the minimum amount of products, for the merchandise level, that should be in the display at the location. This value is then used by IPOCS-Lifecycle Allocation and Replenishment alerts to alert you if locations are not reaching their minimum display for certain merchandise.

Min Display Space %

The Min Display Space % is a calculated measure used to indicate the percentage of minimum display fulfilled using the minimum display count entered by you and the display count available at the location. If the percentage is lower than 100% then the minimum display has not been reached. If the percentage is greater than 100% then the location has more products than the minimum specified. The value of this measure is the result of the formula:



Figure 21-45 Calculation

$$100*\frac{DisplaySpaceCount}{MinDisplaySpaceCount}$$

Max Display Space Count

The Max Display Space Count is an editable measure used to enter the maximum amount of products, for the merchandise level, that can be in the display at the location. This value is then used by IPOCS-Lifecycle Allocation and Replenishment alerts to alert you if locations are exceeding their maximum display for certain merchandise.

Max Display Space %

The Max Display Space % is a calculated measure used to indicate the percentage of maximum display fulfilled using the maximum display count entered by you and the display count available at the location. If the percentage is lower than 100% then the maximum display has not been reached. If the percentage is greater than 100% then the location is exceeding the maximum number of products specified. The value of this measure is the result of the formula:

Figure 21-46 Calculation

$$100*\frac{DisplaySpaceCount}{MaxDisplaySpaceCount}$$

Display Space by SKU (R & A) View

The **Display Space by SKU (R & A) View,** under the **Space tab**, is similar to the Display Space by LOC (R & A) view but the data is presented in a different layout. This view is driven by the SKU analysis rather than the Location analysis. For more details regarding the available profile and the measures within the profile, refer to the Display Space by Loc (R & A) view.



Review & Approve * By Prod By Location Space OTB Menu 🔡 🔍 🚡 Display Space by SKU (R&A) Location / Display Space Count 15 Min Display Space Count 15 15 15 Min Display Space % 73.3 % 73.3 % 73.3 % 73.3 % 73.3 % 73.3 % 73.3 %

Figure 21-47 Display Space by SKU (R & A) View

Stockroom Space by LOC (R & A) View

The **Stockroom Space by LOC (R & A) View**, under the **Space tab**, allows you to manage the stockroom space parameters that is used by IPOCS-Lifecycle Allocation and Replenishment to alert you for replenishment plan situations where merchandise reached the maximum stockroom available at a location or locations. The parameter managed in this view is:

 Max Stockroom Space: The available space to keep the stock. It is based on total inventory.




Figure 21-48 Stockroom Space by LOC (R & A) View

Stockroom Space by LOC (R & A) View - Default Profile Measures

The Default measure profile available in the Stockroom Space by LOC (R & A) view contains the following measures.

Tot. Avail. Units

The Tot. Avail. Units is a calculated measure used to indicate the total available inventory units, for the merchandise level (for example, Brand), at the location. The total available inventory for the merchandise level is the sum of all products available inventory units belonging to that merchandise level. The total available inventory includes on-hand, in-transit and on-order inventory.

Max Stockroom Space

The Max Stockroom Space is an editable measure used to enter the maximum inventory units, for the merchandise level, that can be stocked at the location. This value is then used by IPOCS-Lifecycle Allocation and Replenishment alerts to alert you if locations are reaching/exceeding their maximum stock capacity for certain merchandise.

Max Stockroom Space UOM

The Max Stockroom Space UOM is an editable measure used to enter the unit of measure (UOM) for the max stockroom space entered in the measure Max Stockroom Space. By default the unit of measure Units is used by IPOCS-Lifecycle Allocation and Replenishment.

Max Stockroom Space %

The Max Stockroom Space % is a calculated measure used to indicate the percentage of stock room fulfilled using the maximum stockroom entered by you and the available inventory at the location. If the percentage is lower than 100% then the maximum stockroom has not been reached. If the percentage is greater than 100% then the location is exceeding the maximum stockroom capacity. The value of this measure is the result of the formula:

Figure 21-49 Calculation

$$100*\frac{DisplaySpaceCount}{MaxDisplaySpaceCount}$$

Stockroom Space by SKU (R & A) View

The **Stockroom Space by SKU (R & A) View**, under the **Space tab**, is similar to the Stockroom Space by LOC (R & A) view but the data is presented in a different layout. This view is driven by the SKU analysis rather than the Location analysis. For more details regarding the available profile and the measures within the profile, refer to the Stockroom Space by Loc (R & A) view.



Figure 21-50 Stockroom Space by SKU (R & A) View

OTB (R & A) View

The **OTB** (R & A) View, under the **OTB** tab, allows you to review the open to buy values and take the necessary action to amend the system suggested replenishment, if needed. IPOCS-Lifecycle Allocation and Replenishment has the following open-to-buy concepts:


- Open-to-Buy Residual (OTB Residual) is the remaining under-budget OTB available based on the replenishment plan value and the OTB Value
- Open-to-Buy Exceed (OTB Exceed) would be the out-of-budget OTB based on the replenishment plan value and the OTB Value.

Figure 21-51 Open-to-Buy Concept





Figure 21-52 OTB (R & A) View



OTB (R & A) View - Default Profile Measures

The Default measure profile available in the OTB (R & A) view contains the following measures.

OTB Value

The OTB Value is a loaded measure, from an external system, used to indicate the open-to-buy budget value for the merchandise and location combination.

Rpl. Plan In Value

The Rpl. Plan In Value is a calculated measure used to indicate suggested replenishment plan in value based on the system recommended replenishment units and the loaded open-to-buy price for the merchandise and location combination. The value of this measure is the result of the formula:

Figure 21-53 Calculation

Sys. Rpl. PlanInUnits * OTBPriceValue

OTB Residual Value

The OTB Residual Value is a calculated measure used to indicate the open-to-buy value remaining from the OTB Value assuming the suggested replenishment plan (Rpl. Plan in Value). If the suggested replenishment plan exceeds the available open-to-buy value then this measure is empty. The value of this measure is the result of the formula:

Figure 21-54 Calculation

OTBValue-Rpl. PlanInValue



OTB Residual %

The OTB Residual % is a calculated measure used to indicate in percentage how much of the open-to-buy values is remaining. If the suggested replenishment plan exceeds the available open-to-buy value then this measure is empty. The value of this measure is the result of the formula:

Figure 21-55 Calculation

$$100*\frac{OTBResidualValue}{OTBValue}$$

OTB Exceed Value

The OTB Exceed Value is a calculated measure used to indicate the value that is exceeded from the open-to-buy value (OTB Value) assuming the suggested replenishment plan (Rpl. Plan in Value). If the suggested replenishment plan does not exceed the available open-to-buy value then this measure is empty. The value of this measure is the result of the formula:

Figure 21-56 Calculation

$$Rpl. Plan In Value - OTB Value$$

OTB Exceed %

The OTB Exceed % is a calculated measure used to indicate in percentage how much of the open-to-buy value is exceeded in comparison to the open-to-buy value (OTB Value). If the suggested replenishment plan does not exceed the available open-to-buy value, then this measure is empty. The value of this measure is the result of the formula:

Figure 21-57 Calculation

$$100*\frac{OTBExceedValue}{OTBValue}$$

Inventory Plan Step

In this step, you can review weekly inventory plans calculated by IPOCS-Lifecycle Allocation and Replenishment and approve them. The calculated weekly inventory plans are based on the frozen inbound units, weekly demand, and the Inventory Plan Parameters. This step contains these views:




- · Horizon (InvPlan) View
- SKU-LOC Level (InvPlan) View
- SKU-LOC-DAY Level (InvPlan) View
- SKU-LOC-WEEK Level (InvPlan) View
- SKU-Source LOC-WEEK Level (R & A) View

Horizon (InvPlan) View

The Horizon (InvPlan) View, under the Inventory Plan tab, allows you to manage the time horizon that the inventory plan calculation should consider. For example, if the plan horizon is 10 then IPOCS-Lifecycle Allocation and Replenishment calculates the Inventory Plan for the next 10 weeks (from today) only.

Figure 21-58 Horizon (InvPlan) View



Horizon (InvPlan) View - Default Profile Measures

The Default measure profile available in the Horizon (InvPlan) view contains the following measures.

Today Date

The Today Date is a loaded read-only measure used to display the system date that is calculated by IPOCS-Lifecycle Allocation and Replenishment batch.

Inv. Plan Horizon (w)

The Inv. Plan Horizon (w) is an editable measure used to enter the number of weeks, in the future, that should have inventory plan calculated.

Clear Sell-In

The Clear Sell-In is an editable measure used to define whether the inventory calculation should clear the sell- in forecast or not before starting the inventory plan calculations.

Appr. Plan (Wk) Count



The Appr. Plan (Wk) Count is a calculated measure used to indicate the total number of assorted product and location combinations with approved orders for the current week.


TBA Plan (Wk) Count

The TBA Plan (Wk) Count is a calculated measure used to indicate the total number of assorted product and location combinations that need the orders to be approved manually for the current week.

SKU-LOC Level (InvPlan) View

The **SKU-LOC Level (InvPlan) View**, under the **Inventory Plan tab**, allows you to review and adjust the calculated inventory plan at the product and location levels.

Figure 21-59 SKU-LOC Level (InvPlan) View



SKU-LOC Level (InvPlan) View - Default Profile Measures

The Default measure profile available in the SKU-LOC Level (InvPlan) view contains the following measures.

User Filter PROD-LOC

The User Filter PROD-LOC is an editable measure used to apply a filter to the views within the Review & Approve workspace by the selected product and location combinations. When a product and location combination is selected, and after the workspace calculation (either **Calculate** or **F9**) is run, the views in the Review & Approve workspace is filtered based on the selected product and locations combinations.

Revwd PROD - LOC

The Revwd PROD - LOC is an editable measure used to indicate that the product and location combination alerts have been reviewed.

PROD - LOC Alerts

The PROD - LOC Alerts is a calculated measure used to display the Alert Short Descr. of all the alerts that got triggered for the product and location combination.



Tot. Cust. Order Units

The Total Customer Order Units is the same as the one in the inventory profile under the SKU-LOC Level (R & A) view. Refer to the measure, Tot. Cust. Order Units, in the Measures: Inventory Profile under the SKU-LOC Level (R & A) view in the Default Profile Measures.

Tot. On Order (out) Units

The Tot. On Order (out) Units is the same as the one in the inventory profile under the SKU-LOC Level (R & A) view. Refer to the measure, Tot. On Order (out) Units, in the Measures: Inventory Profile under the SKU-LOC Level (R & A) view in the Default Profile Measures.

Tot. Demand (Wk) Units

The Tot. Demand (Wk) Units is the same as the one in the default profile under the SKU-LOC-WEEK Level (InvPlan) view. Refer to the measure, Tot. Demand (Wk) Units, in the Default Profile Measures under the SKU-LOC-WEEK Level (InvPlan) view in the Default Profile Measures.

External Order Out Units

The External Order Out Units is an editable measure used to enter the weekly order data coming outside of IPOCS-Lifecycle Allocation and Replenishment. In this view, the measure is aggregated and when changed the value is spread proportionally across the weeks within the workspace (you can check the spread value in the SKU-LOC-WEEK Level(InvPlan) view).

Sell-In Fcst (Wk) Units

The Sell-In Fcst (Wk) Units is the same as the one in the default profile under the SKU-LOC-WEEK Level (InvPlan) view. Refer to the measure, Sell-In Fcst (Wk) Units, in the Default Profile Measures under the SKU-LOC-WEEK Level (InvPlan) view in the Default Profile Measures.

Sell-Out Fcst (Wk) Units

The Sell-Out Fcst (Wk) Units is the same as the one in the default profile under the SKU-LOC-WEEK Level (InvPlan) view. Refer to the measure, Sell-Out Fcst (Wk) Units, in the Default Profile Measures under the SKU-LOC-WEEK Level (InvPlan) view in the Default Profile Measures.

Initial Avail. Units

The Initial Avail. Units is a calculated measure used to indicate the initial quantity of units available for the product and location combination considering on-hand and booked inventory plus in and out transfers (approved and exported).

Tot. On Hand Units

The Tot. On Hand Units is the same as the one in the availability profile under the SKU-LOC Level (R & A) view. Refer to the measure, Tot. On Hand Units, in the Measures: Availability Profile under the SKU-LOC Level (R & A) view in the Default Profile Measures.

Tot. Booked Units

The Tot. Booked Units is the same as the one in the inventory profile under the SKU-LOC Level (R & A) view. Refer to the measure, Tot. Booked Units, in the Measures:



Inventory Profile under the S KU- LOC Level (R & A) view in the Default Profile Measures.

Exp. Rpl. Plan In Units

The Exp. Rpl. Plan In Units is the same as the one in the availability profile under the SKU-LOC Level (R & A) view. Refer to the measure, Exp. Rpl. Plan In Units, in the Measures: Availability Profile under the SKU-LOC Level (R & A) view in the Default Profile Measures.

Exp. Rpl. Plan Out Units

The Exp. Rpl. Plan Out Units is the same as the one in the availability profile under the SKU-LOC Level (R & A) view. Refer to the measure, Exp. Rpl. Plan Out Units, in the Measures: Availability Profile under the SKU-LOC Level (R & A) view in the Default Profile Measures.

Appr. Rpl. Plan In Units

The Appr. Rpl. Plan In Units is the same as the one in the default profile under the SKU-LOC Level (R & A) view. Refer to the measure, Appr. Rpl. Plan In Units under the SKU-LOC Level (R & A) view, in the Default Profile Measures.

Appr. Rpl. Plan Out Units

The Appr. Rpl. Plan Out Units is the same as the one in the availability profile under the SKU-LOC Level (R & A) view. Refer to the measure, Appr. Rpl. Plan Out Units, in the Measures: Availability Profile under the SKU-LOC Level (R & A) view in the Default Profile Measures.

Appr. Transfer In Units

The Appr. Transfer In Units is the same as the one in the availability profile under the SKU-LOC Level (R & A) view. Refer to the measure, Appr. Transfer In Units, in the Measures: Availability Profile under the SKU-LOC Level (R & A) view in the Default Profile Measures.

Appr. Transfer Out Units

The Appr. Transfer Out Units is the same as the one in the availability profile under the SKU-LOC Level (R & A) view. Refer to the measure, Appr. Transfer Out Units, in the Measures: Availability Profile under the SKU-LOC Level (R & A) view in the Default Profile Measures.

Frozen Inbound Units

The Frozen Inbound Units is the total committed inbound inventory given to a destination location. In this view, the measure is aggregated (you can check the weekly value in the SKU-LOC-WEEK Level (InvPlan) View).

Tot. In Transit Units

The Tot. In Transit Units is the same as the one in the inventory profile under the SKU-LOC Level (R & A) view. Refer to the measure, Tot. In Transit Units, in the Measures: Inventory Profile under the SKU-LOC Level (R & A) view in the Default Profile Measures.

Tot. On Order (in) Units

The Tot. On Order (in) Units is the same as the one in the inventory profile under the SKU-LOC Level (R & A) view. Refer to the measure, Tot. On Order (in) Units, in the Measures: Inventory Profile under the SKU-LOC Level (R & A) view in the Default Profile Measures.

User Locked Plan (Wk) Units

The User Locked Plan (Wk) Units is an editable measure used to adjust the plan by entering a new value. In this view, the measure is aggregated and when changed the value is spread proportionally across the weeks within the workspace (you can check the spread value in the SKU-LOC-WEEK Level (InvPlan) view).



Sys. Plan (Wk) Units

The Sys. Plan (Wk) Units is a calculated measure used to indicate the proposed quantity that the system has calculated to fulfil the Sell-Out forecast while maintaining the inventory at the Sys Min Level at EOP (week). In this view, the measure is aggregated (you can check the weekly value in the SKU-LOC-WEEK Level (InvPlan) view).

Shortage (Wk) Units

The Shortage (Wk) Units is a calculated measure used to indicate the shortage in units to fulfil the demand. In this view, the measure is aggregated (you can check the weekly value in the S KU-LOC-WEEK Level (InvPlan) view).

Primary Source @ Today

The Primary Source @ Today is a loaded measure used to indicate the applied primary source for the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Lead Time @ Today Dur (d)

The Lead Time @ Today Dur (d) is a calculated measure used to indicate the applied lead time, in days, for the product and location combination at the system date. The lead time is calculated from the current BOD assigned to the product and location combination.

LLC @ Today

The LLC @ Today is a calculated measure used to indicate the low-level code applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

Min Order Qty Units

The Min Order Quantity Units is the same as the one in the parameters profile under the SKU-LOC Level (R & A) view. Refer to the measure, Min Order Quantity Units, in the Measures: Parameters Profile under the SKU-LOC Level (R & A) view in the Default Profile Measures.

Mult. Order Qty Units

The Mult. Order Quantity Units is the same as the one in the parameters profile under the SKU-LOC Level (R & A) view. Refer to the measure, Mult. Order Quantity Units, in the Measures: Parameters Profile under the SKU-LOC Level (R & A) view in the Default Profile Measures.

Order Rounding Threshold @ Today %

The Order Rounding Threshold @ Today % is a calculated measure used to indicate the percentage to round up the orders applied to the product and location combination at the system date and can be overridden. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Replenishment Parameters workspace.

Min Method @ Today

The Min Method @ Today is a calculated measure used to indicate the inventory planning method, to calculate the System Minimum value, applied to the product and



location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Replenishment Parameters workspace.

Min Method Change

The Min Method Change is an editable measure to override the assigned inventory plan method to calculate the System Minimum value (you can review or manage the weekly value in the SKU-LOC- WEEK Level (InvPlan) View). For more details about the possible values check the measure Min Method in the SKU-LOC view within the Replenishment Parameters workspace.

Min Fixed @ Today

The Min Fixed @ Today is a calculated measure used to indicate how the Fixed inventory planning method calculates the System Minimum value for the product and location combination at the system date. For more details about the measure, refer to the same measure description in the view SKU- LOC within the Replenishment Parameters workspace.

Min Fixed @ Today Units

The Min Fixed @ Today Units is a calculated measure used to indicate the minimum fixed quantity applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Replenishment Parameters workspace.

ROL @ Today Units

The ROL @ Today Units is the same as the one in the plan profile under the SKU-LOC Level (R & A) view. Refer to the measure, ROL @ Today Units, in the Measures: Plan Profile under the SKU-LOC Level (R & A) view in the Default Profile Measures.

RUTL @ Today Units

The RUTL @ Today Units is the same as the one in the default profile under the SKU-LOC Level (R & A) view. Refer to the measure, RUTL @ Today Units, in the Default Profile Measures under the SKU-LOC Level (R & A) view in the Default Profile Measures.

Min Fixed Change Units

The Min Fixed Change Units is an editable measure used to override the minimum quantity used when the Fixed method is applied. This value is used in the calculation instead of the Min Fixed @ Today Units, the RUTL @ Today Units or the ROL @ Today Units if the method to calculate the System Minimum value is Fixed. You can review or manage the weekly value in the SKU-LOC-WEEK Level (InvPlan) view.

Min Fwd Cov. @ Today Dur (d)

The Min Fwd Cov. @ Today Dur (d) is a calculated measure used to indicate the minimum number of days of cover applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Replenishment Parameters workspace.

Min Fwd Cov. Change Dur (d)

The Min Fwd Cov. Change Dur (d) is an editable measure used to override the minimum number of days of cover (Min Fwd Cov. @ Today Dur (d)) applied to the product and location combination at the system date.

Max Method @ Today



The Max Method @ Today is a calculated measure used to indicate the inventory planning method, to calculate the System Maximum value, applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Replenishment Parameters workspace.

Max Method Change

The Max Method Change is an editable measure to override the assigned inventory plan method to calculate the System Maximum value. For more details about the possible values check the measure the Max Method in the SKU-LOC view within the Replenishment Parameters workspace.

Max Fwd Cov. @ Today Dur (d)

The Max Fwd Cov. @ Today Dur (d) is a calculated measure used to indicate the maximum number of days of cover applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Replenishment Parameters workspace.

Max Fixed @ Today Units

The Max Fixed @ Today Units is a calculated measure used to indicate the maximum fixed quantity applied to the product and location combination at the system date. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Replenishment Parameters workspace.

Max Fixed Change Units

The Max Fixed Change Units is an editable measure used to override the maximum quantity to be used when the Fixed method is applied. This value is used in the calculation instead of the Max Fixed @ Today Units if the method to calculate the System Maximum value is Fixed.

Max Fwd Cov. Change Dur (d)

The Max Fwd Cov. Change Dur (d) is an editable measure to override the maximum number of days of cover (Max Fwd Cov. @ Today Dur (d)) applied to the product and location combination at the system date.

SKU-LOC Level (InvPlan) - Measures: InOutBound Profile

The InOutBound measure profile available in this view contains a subset of the measures in the Default measure profile. For more information regarding the description of the measure, review the Default Profile Measures in this view. This profile contains the following measure that is not in the Default profile.

Inv. PL Mask

The Inv. PL Mask is a calculated measure used to indicate whether the product and location combination is eligible for the inventory plan. When selected, it is eligible. When clear, it is ineligible.

SKU-LOC Level (InvPlan) - Measures: Parameters Profile

The Parameters measure profile available in this view contains a subset of the measures in the Default measure profile. For more information regarding the measures description check the Default Profile Measures in this view. This profile contains the following measures that are not in the Default profile.



Inv. PL Mask

The Inv. PL Mask is a calculated measure used to indicate whether the product and location combination is eligible for the inventory plan. When selected, it is eligible. When clear, it is ineligible.

PL BOD

The PL BOD is a loaded measure used to indicate the bill of distribution applied to the product and location combination. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Supply Chain Network workspace.

PL lvp.

The PL Ivp. is a loaded measure used to indicate the inventory planning parameter applied to the product and location combination. For more details about the measure, refer to the same measure description in the SKU-LOC view within the Replenishment Parameters workspace.

SKU-LOC-DAY Level (InvPlan) View

The **SKU-LOC-DAY Level (InvPlan) View**, under the **Inventory Plan tab**, allows you to review approved and the exported inventory plan at the product and location levels by date (day).




Figure 21-60 SKU-LOC-DAY Level (InvPlan) View

SKU-LOC-DAY Level (InvPlan) View - Default Profile Measures

The Default measure profile available in the SKU-LOC-DAY Level (InvPlan) view contains the following measures.

Tot. In Transit Units

The Tot. In Transit Units is the same as the one in the default profile under the SKU-LOC-WEEK Level (InvPlan) view. Refer to the measure, Tot. In Transit Units, in the Default Profile Measures under the SKU-LOC-WEEK Level (InvPlan) view in the Default Profile Measures.

Tot. On Order (in) Units



The Tot. On Order (in) Units is the same as the one in the default profile under the SKU-LOC-WEEK Level (InvPlan) view. Refer to the measure, Tot. On Order (in) Units, in the Default Profile Measures under the SKU-LOC-WEEK Level (InvPlan) view in the Default Profile Measures.

Tot. Cust. Order Units

The Tot. Cust. Order Units is the same as the one in the default profile under the SKU-LOC-WEEK Level (InvPlan) view. Refer to the measure, Tot. Cust. Order Units, in the Default Profile Measures under the SKU-LOC-WEEK Level (InvPlan) view in the Default Profile Measures.

Tot. On Order (out) Units

The Tot. On Order (out) Units is the same as the one in the default profile under the SKU-LOC-WEEK Level (InvPlan) view. Refer to the measure, Tot. On Order (out) Units, in the Default Profile Measures under the SKU-LOC-WEEK Level (InvPlan) view in the Default Profile Measures.

Appr. Rpl. Plan Out (day) Units

The Appr. Rpl. Plan Out (day) Units is the same as the one in the default profile under the SKU-LOC-WEEK Level (InvPlan) view. Refer to the measure, Appr. Rpl. Plan Out (day) Units, in the Default Profile Measures under the SKU-LOC-WEEK Level (InvPlan) view in the Default Profile Measures.

Exp. Rpl. Plan Out (day) Units

The Exp. Rpl. Plan Out (day) Units is the same as the one in the default profile under the SKU-LOC-WEEK Level (InvPlan) view. Refer to the measure, Exp. Rpl. Plan Out (day) Units, in the Default Profile Measures under the SKU-LOC-WEEK Level (InvPlan) view in the Default Profile Measures.

Appr. Rpl. Plan In (day) Units

The Appr. Rpl. Plan In (day) Units is the same as the one in the default profile under the SKU-LOC-WEEK Level (InvPlan) view. Refer to the measure, Appr. Rpl. Plan In (day) Units, in the Default Profile Measures under the SKU-LOC-WEEK Level (InvPlan) view in the Default Profile Measures.

Exp. Rpl. Plan In (day) Units

The Exp. Rpl. Plan In (day) Units is the same as the one in the default profile under the SKU-LOC-WEEK Level (InvPlan) view. Refer to the measure, Exp. Rpl. Plan In (day) Units, in the Default Profile Measures under the SKU-LOC-WEEK Level (InvPlan) view in the Default Profile Measures.

SKU-LOC-WEEK Level (InvPlan) View

The **SKU-LOC-WEEK Level (InvPlan) View**, under the **Inventory Plan tab**, allows you to review, adjust and approve the calculated inventory plan at the product and location levels by week. You can for example review week-by-week orders that are coming into the warehouses and then sent from warehouses to stores.



Inventory Plan

The Manual Response of the Control of the Control

Figure 21-61 SKU-LOC-WEEK Level (InvPlan) View

SKU-LOC-WEEK Level (InvPlan) View - Default Profile Measures

The Default measure profile available in the SKU-LOC-WEEK Level (InvPlan) view contains the following measures.

Calculate (F9) Reload Plan Parameters Visual Asso

Tot. Cust. Order Units

6/30/2018

The Tot. Cust. Order Units is a calculated measure used to indicate the total customer order units for the product and location combination. The total customer orders include the customer orders loaded into IPOCS-Lifecycle Allocation and Replenishment plus the customer orders for the replacement/phase-out product, if any.

Tot. On Order (out) Units

The Tot. On Order (out) Units is a calculated measure used to indicate the total on-order inventory units out from the source locations (for example, warehouse). The total on-order (out) units includes the on-order inventory loaded into IPOCS-Lifecycle Allocation and Replenishment plus the on-order (out) inventory units for the replacement/phase-out product, if any.

Tot.Demand (Wk) Units

The Tot.Demand (Wk) Units is a calculated measure used to indicate the total weekly demand for the product and location combination.

External Order Out Units

The External Order Out Units is an editable measure used to enter the weekly order data coming outside of IPOCS-Lifecycle Allocation and Replenishment.

Appr. Rpl. Plan Out (day) Units

The Appr. Rpl. Plan Out (day) Units is a calculated measure used to indicate the source location (for example, warehouse) approved replenishment units for the product and location combination, per day.

Exp. Rpl. Plan Out (day) Units



The Exp. Rpl. Plan Out (day) Units is a calculated measure used to indicate the source location (for example, warehouse) replenishment planned units, per day, to be exported from the batch for the product and location combination.

Sell-In Fcst (Wk) Units

This is an editable measure used to enter the weekly demand at the source location for the product and location combination.

Sell-Out Fcst (Wk) Units

The Sell-In Fcst (Wk) Units is a calculated measure used to indicate the weekly demand at the source location for the product coming from the location's demand (destination location).

Frozen Inbound Units

The Frozen Inbound Units is the total committed inbound inventory to a given destination location.

Tot. In Transit Units

The Tot. In Transit Units is a calculated measure used to display your comment for the in-transit inventory and your comment for the phase-out item's inventory, if any.

Tot. On Order (in) Units

The Tot. On Order (in) Units is a calculated measure used to indicate the total on-order inventory units. The total on-order units include the on-order inventory loaded into IPOCS-Lifecycle Allocation and Replenishment plus the on-order inventory units for the replacement/phase-out product, if any.

Appr. Rpl. Plan In (day) Units

The Appr. Rpl. Plan In (day) Units is a calculated measure used to indicate the approved replenishment units for the product and location combination, per day.

Exp. Rpl. Plan In (day) Units

The Exp. Rpl. Plan In (day) Units is a calculated measure used to indicate the replenishment planned units, per day, to be exported from the batch for the product and location combination.

BOP (Wk) Units

The BOP (Wk) Units is a calculated measure used to indicate the beginning of period inventory units. In this view you can review the available inventory units at the beginning of each week.

Revw Cal. (Wk) @ Today

The Revw Cal. (Wk) @ Today is a loaded measure used to indicate whether the week is a review week or not. You can override the loaded value. For more details about the measure, refer to the same measure description in the SKU-LOC view-Week within the Supply Chain Network workspace.

Rcpt Cal. (WK) @ Today

The Rcpt Cal. (WK) @ Today is a loaded measure used to indicate whether the week is a receipt week or not. You can override the loaded value. For more details about the measure, refer to the same measure description in the SKU-LOC view-Week within the Supply Chain Network workspace.



User Locked Plan (Wk) Units

The User Locked Plan (Wk) Units is an editable measure used to adjust the weekly inventory plan by entering a new value for the weeks that need to be adjusted.

Sys. Plan (Wk) Units

The Sys. Plan (Wk) Units is a calculated measure used to indicate the proposed quantity that the system has calculated, week by week, to fulfill the Sell-Out forecast while maintaining the inventory at the Sys Min Level at EOP (week).

Sys. Action

The Sys. Action is a calculated measure used to indicate the action that is triggered by the system for the inventory plan calculation. Valid values are:

FZR

Frozen—the system does not consider the week for proposal or any action, as it considers the item has not started yet.

TBA

To Be Approved—the system is suggesting a proposal for replenishment that needs to be approved by you.

TBA Plan (Wk)

The TBA Plan (Wk) is a calculated measure used to indicate that the plan suggested by the system needs to be approved for the product, location, and week combination.

Appr. Plan (Wk)

The Appr. Plan (Wk) is a calculated measure used to indicate if the plan is approved for the product, location, and week combination.

Appr. Plan (Wk) Units

The Appr. Plan (Wk) Units is a calculated measure used to indicate the order in units that is approved for the product, location, and week combination.

Appr. Plan (Wk) User ID

The Appr. Plan (Wk) User ID is a calculated measure used to audit the **Plan Approval** action button. It is populated with the user-identifier that last ran the Inventory Plan Approval action.

Appr. Plan (Wk) Date

Appr. Plan (Wk) Date is a calculated measure used to audit the **Plan Approval** action button. It is populated with the user-identifier that last ran the Inventory Plan Approval action.

Exp. Plan (Wk) Units

The Exp. Plan (Wk) Units indicate the Exported Replenishment Orders from the Inventory Plan.

Exp. Plan (Wk) Date

The Exp. Plan (Wk) Date indicates the date when the corresponding replenishment orders from the Inventory Plan were exported (following batch run).

EOP (WK) Units



The EOP (WK) Units is a calculated measure used to indicate the end-of-period inventory units. In this view, you can review the available inventory units at the end of each week.

Shortage (Wk) Units

The Shortage (Wk) Units is a calculated measure used to indicate shortage in units for the product, location, and week combination.

Sys. Min Level (Wk) Units

The Sys. Min Level (Wk) Units is a calculated measure used to indicate the minimum target inventory in units that was calculated by the system for the product, location, and week combination.

Sys. Max Level (Wk) Units

The Sys. Max Level (Wk) Units is a calculated measure used to indicate the maximum target inventory in units that was calculated by the system for the product, location, and week combination.

Min Method Change

The Min Method Change is an editable measure to override the assigned inventory plan method to calculate the System Minimum value at the product, location, and week level. For more details about the possible values check the measure the Min Method in the SKU-LOC view within the Replenishment Parameters workspace.

Min Fixed Change Units

The Min Fixed Change Units is an editable measure used to override the minimum quantity to be used when the Fixed method is applied at the product, location, and week level. This value is used in the calculation instead of the 2Min Fixed @ Today Units2, the RUTL @ Today Units or the ROL @ Today Units if the method to calculate the System Minimum value is Fixed.

Min Fwd Cov. Change Dur (d)

The Min Fwd Cov. Change Dur (d) is an editable measure used to override the minimum number of days of cover applied to the product, location, and week.

Max Method Change

The Max Method Change is an editable measure used to override the assigned inventory plan method to calculate the System Maximum value at the product, location, and week level. For more details about the possible values check the measure the Max Method in the SKU-LOC view within the Replenishment Parameters workspace.

Max Fixed Change Units

The Max Fixed Change Units is an editable measure used to override the maximum quantity to be used when the Fixed method is applied at the product, location, and week level. This value is used in the calculation instead of the Max Fixed @ Today Units if the method to calculate the System Maximum value is Fixed.

Max Fwd Cov. Change Dur (d)

The Max Fwd Cov. Change Dur (d) is an editable measure used to override the maximum number of days of cover applied to the product, location, and week.



SKU-Source LOC-WEEK Level (R & A) View

The SKU-Source LOC-WEEK Level (R & A) View, under the Inventory Plan tab, is similar to the view SKU-LOC-WEEK Level (InvPlan), but allows you to review from the source location perspective rather than the destination location perspective. For more details regarding the measures, refer to the SKU-LOC-WEEK Level (InvPlan) view.

Figure 21-62 SKU-Source LOC-WEEK Level (R & A) View

Rebalancing Step

In this step you can adjust inventory levels to maintain optimal stock levels. Usually this is achieved by moving products from locations with surplus to locations with deficit.

This may also involve increasing orders for items that are selling well or reducing orders for slow-moving items. This step contains these views:

- Summary Tab
 - Item-Location View
 - Items View
 - Locations View
 - Parameters View
- Transfers Tab
 - Item-Location View
 - Items View
 - Links View
 - Locations View
 - Parameters View




Item-Location View

This **Item-Location View** is located under the **Summary** tab. In this view, you can review the store transfer summary at the item location level.



Figure 21-63 Item-Location View





Item-Location View - Default Profile Measures

The Default measure profile available in the Item-Location view contains the following measures.

Product-location Alerts

This measure indicates if an alert was triggered for an item-location.

Reviewed Product-Location

By using this measure, a user indicates that the system plan has been reviewed

Total Available Units

This measure displays the total available units at an item-location.

Receipt Up to Level @ Today Units

This measure displays the Receipt Up To Level units as set up in the Replenishment Parameters workspace.

Initial Need Units

This measure displays the units needed for an item-location combination.

Final Need Units

This measure displays the units needed for an item-location after the transfer.

System Transfer in Units

This measure displays the number of units to be transferred in calculated by the system.

System Transfer In

This measure displays the list of source locations after rebalancing is calculated by the system.

System Transfer Out Units

This measure displays the number of units to be transferred out calculated by the system.

System Transfer Out

This measure displays the list of destination locations after rebalancing is calculated by the system.

Transfers To Be Approved

This measure is used to approve the transfers.

Ignore Replenishment Plan to Be Approved

This measure allows you to approve rebalancing without approving the replenishment system plan.

Approved

This measure allows the user to approve the rebalancing transfers.



Approved Transfer in Units

This measure displays the approved number of units to be transferred in for an item-location.

Approved Transfer In

This measure displays the list of source locations after rebalancing is approved.

Approved Transfer Out Units

This measure displays the approved number of units to be transferred out for an itemlocation.

Approved Transfer Out

This measure displays the list of destination locations after rebalancing is approved.

Approved UserID

This measure displays the user ID of the user who approved the transfers.

Export Transfer in Units

This measure displays the exported number of units of the destination location after the batch is run.

Export Transfer In

This measure displays the list of source locations after the batch is run.

Export Transfer Out Units

This measure displays the list of destination locations after the batch is run.

Export Transfer Out

This measure displays the exported number of units of the source location after the batch is run.

Total Deficit Units

This measure displays the total deficit units for an item-location combination.

Total Deficit %

This measure displays the percentage deficit relative to the total units needed for an itemlocation combination.

Total Surplus Units

This measure displays the total surplus units for an item-location combination.

Total Surplus %

This measure displays the percentage surplus relative to the total units needed for an itemlocation combination.

In Transit over Lead Time+Review Time Units

This measure displays the units in transit over lead and review time for an item-location.

On Order (In) over Lead Time+Review Time Units

This measure displays the units on order over lead and review time for an item-location.



Items View

This **Items View** is located under the **Summary** tab. In this view, you can review the change in KPIs, such as lost sales, as a result of the transfers, with the focus on products.



Figure 21-64 Items View

Source Mask	
Destination Mask	
Item Mask	
Unit Price €	0.00
Availability Units	11,000
Approved Transfer In Units	
Approved Transfer Out Units	
Initial Availability Units	
Receipt Up To Level Units	13,355
System Transfer In Units	
System Transfer In €	0.00
System Transfer Out Units	
Approved	
Approved UserID	
Approved Date	
Final Availability Units	
Initial Need Units	
Final Need Units	%
Final Need %	
Initial Surplus Units	
Final Surplus Units	%



Items View - Default Profile Measures

The Default measure profile available in the Items view contains the following measures.

Source Mask

This measure Is used to decide which products can be transferred out.

Destination Mask

This measure Is used to decide which products can be transferred in.

Item Mask

This measure displays if an item is eligible for transfer.

Unit Price

This measure displays the unit price.

Available Units

This measure displays the available units considering replenishment, manual transfers, and rebalancing.

Approved Transfer in Units

This measure displays the approved number of units to be transferred in.

Approved Transfer Out Units

This measure displays the approved number of units to be transferred out for an itemlocation.

Initial Availability Units

This measure displays the available number of units in the destination location before rebalancing.

Receipt Up to Level Units

This measure displays the Receipt Up To Level units as set up in the Replenishment Parameters workspace

System Transfer in Units

This measure displays the number of units to be transferred in calculated by the system.

System Transfer In

This measure displays the list of source locations after rebalancing as calculated by the system.

System Transfer Out Units

This measure displays the number of units to be transferred out calculated by the system.

Approved

This measure allows the user to approve the rebalancing transfers.



Approved UserID

This measure displays the user ID of the user who approved the transfers.

Approved Date

This measure displays the date of the approval of transfers.

Final Availability Units

This measure displays the available number of units in the destination location after rebalancing.

Initial Need Units

This measure displays the units needed for a product.

Final Need Units

This measure displays the units needed for a product after the transfer.

Final Need %

This measure displays the percentage of the need after rebalancing relative to the need before rebalancing.

Initial Surplus Units

This measure displays the initial surplus units for a product.

Final Surplus Units

This measure displays the surplus units for a product after the transfers.

Final Surplus %

This measure displays the percentage surplus after rebalancing relative to the surplus before rebalancing. This measure displays the percentage surplus after the transfer relative to the total units needed.

Forecast Daily Rate of Sale Units

This measure displays the forecasted daily rate of sales in units.

Initial DOS Duration (Days)

This measure displays the initial days of supply based on the forecast.

Final DOS Duration (Days)

This measure displays the days of supply after the transfers.

Initial DOS MAD Duration (Days)

This measure displays the mean absolute deviation of the days of stock before rebalancing.

Final DOS MAD Duration (Days)

This measure displays the mean absolute deviation of the days of stock before rebalancing.

Final DOS MAD %

This measure displays the mean absolute deviation of the days of stock after rebalancing relative to the mean absolute deviation of the days of stock before rebalancing.



Initial Lost Sales Units

This measure displays the initial lost sales units for a product calculated based on deficit units.

Final Lost Sales Units

This measure displays the lost sales units for a product calculated based on deficit units after the transfers.

Initial Lost Sales \$

This measure displays the initial lost sales value for a product calculated based on deficit units.

Final Lost Sales \$

This measure displays the lost sales value for a product calculated based on deficit units after the transfers.

Final Lost Sales %

This measure displays the percentage lost sales relative to the total units needed.

System Additional Sales \$

Locations View

This **Locations View** is located under the **Summary tab**. In this view, you can review the change in KPIs, such as lost sales, as a result of the transfers, with the focus on locations.



Figure 21-65 Locations View

Source Mask	
Destination Mask	
Location Mask	
Availability Units	
Approved Transfer In Units	
Approved Transfer Out Units	
Initial Availability Units	
Receipt Up To Level Units	24,884
System Transfer In Units	
System Transfer In €	0.00
System Transfer Out Units	
Approved	
Approved UserID	
Approved Date	
Final Availability Units	
Initial Need Units	
Final Need Units	
Final Need %	%
Initial Surplus Units	
Final Surplus Units	
Final Surplus %	%
Forecast Daily Rate Of Sale Units	



Locations View - Default Profile Measures

The Default measure profile available in the Locations view contains the following measures.

Source Mask

This measure is used to decide which stores can transfer products out.

Destination Mask

This measure is used to decide which stores can have products transferred in.

Location Mask

This measure displays if a store is eligible for stock rebalancing.

Availability Units

This measure displays the available units considering replenishment, manual transfers, and rebalancing.

Approved Transfer in Units

This measure displays the approved number of units to be transferred in for a location.

Approved Transfer Out Units

This measure displays the approved number of units to be transferred out from a location.

Initial Availability Units

This measure displays the available number of units in the destination location before rebalancing.

Receipt Up to Level Units

This measure displays the Receipt Up To Level units as set up in the Replenishment Parameters workspace.

System Transfer in Units

This measure displays the number of units to be transferred into a location calculated by the system.

System Transfer In \$

This measure displays the value of products be transferred into a location calculated by the system.

System Transfer Out Units

This measure displays the number of units to be transferred out of a location calculated by the system.

Approved

This measure allows the user to approve the rebalancing transfers.

Approved UserID

This measure displays the user ID of the user who approved the transfers.



Approved Date

This measure displays the date of the approval of transfers.

Final Availability Units

This measure displays the available number of units in the destination location after rebalancing.

Initial Need Units

This measure displays the units needed for a location.

Final Need Units

This measure displays the units needed for a location after the transfers.

Final Need %

This measure displays the percentage of the need after rebalancing relative to the need before rebalancing.

Initial Surplus Units

This measure displays the initial surplus units at a location.

Final Surplus Units

This measure displays the initial surplus units at a location.

.Final Surplus %

This measure displays the percentage surplus after the transfer relative to the total units needed at a location.

Forecast Daily Rate of Sale Units

This measure displays the forecasted daily rate of sales in units at a location.

Initial DOS Duration (Days)

This measure displays the initial days of supply based on the forecast.

Final DOS Duration (Days)

This measure displays the initial days of supply based on the forecast.

Initial Lost Sales Units

This measure displays the initial lost sales units at a location calculated based on deficit units.

Final Lost Sales Units

This measure displays the initial lost sales units at a location calculated based on deficit units after the transfers.

Initial Lost Sales \$

This measure displays the initial lost sales value at a location calculated based on deficit units.

Final Lost Sales \$



This measure displays the initial lost sales value at a location calculated based on deficit units after the transfers.

Final Lost Sales %

This measure displays the lost sales at a location calculated based on deficit units after the transfers relative to the total need at the location.


System Additional Sales \$

This measure displays the difference between lost sales before and after rebalancing.

Parameters View

This **Parameters View** is located under the **Summary tab**. In this view, you can review the parameters that are setup for the store transfers.

Figure 21-66 Parameters View





Parameters View - Default Profile Measures

The Default measure profile available in the Parameters view contains the following measures.

Rebalancing Type

Use this measure to select how the stock is rebalanced:

- **Need/Surplus** looks at the deficit need of the destination location and surplus at the source location.
- DOS tries to balance the Days of Stock (DOS) at every location.
- Need/Surplus+DOS tries to balance the need/surplus and after it runs the DOS balancing.

Surplus Above Layer

This measure allows you to select what portion of stock is considered surplus. For instance, if you select Layer 3, the surplus units include all units that are in Layers 4 and 5. Units in the Layers 3 and less can not be transferred.

Post Optimization

This measure allows you to determine if optimization should run during rebalancing when the rebalancing type is **Need/Surplus+DOS**.

Destination Sorting Key 1

Destination Sorting Key 2

Destination Sorting Key 3

Destination Sorting Key 4

In the Destination Sorting Key measures, you can specify the sorting attributes for destinations. Key 1 has the highest priority and the measures decrease in priority from Key 1 to Key 4. The attributes can be:

- Layer The destination location is sorted based on demand layer priority (Customer Order, Display, Minimum Crdible Quantity, Reorder Point, Reorder Up To Level).
- Priority User defined priority in the transfer link.
- Layer percentage Fill rate percentage on the demand layer.
- Coverage Days Of Stock.

Source Sorting Key 1

Source Sorting Key 2

Source Sorting Key 3

Source Sorting Key 4

In the Source Sorting Key measures, you can specify the sorting attributes for source locations. Key 1 has the highest priority and the measures decrease in priority from Key 1 to Key 4. The attributes can be:

- Cost Prioritizes the lowest cost.
- Lead time Prioritizes the fastest lead time.




- User Out User defined Transfer Out.
- **Priority** User defined priority in the transfer link.
- Surplus Prioritizes the highest surplus.

Item-Location View

This **Item-Location View** is located under the **Transfers tab**. In this view, you can set up the store transfers at the item location level.



Figure 21-67 Item-Location View



Item-Location View - Default Profile Measures

The Default measure profile available in the Item-Location view contains the following measures.



User Filter Product-Location

Product-Location Alerts

This measure indicates if an alert was triggered for an item-location.

Reviewed Product-Location

Total Available Units

This measure displays the total available units at an item-location.

Receipt Up to Level @ Today Units

Initial Need Units

This measure displays the units needed for an item-location combination.

Final Need Units

This measure displays the units needed for an item-location after the transfer.

System Transfer in Units

This measure displays the number of units to be transferred in calculated by the system.

System Transfer In

System Transfer Out Units

This measure displays the number of units to be transferred out calculated by the system.

System Transfer Out

Transfers To Be Approved

This measure is used to approve the transfers.

Ignore Replenishment Plan to Be Approved

Approved

This measure allows you to approve the rebalancing transfers.

Approved Transfer in Units

This measure displays the approved number of units to be transferred in for an itemlocation.

Approved Transfer In

This measure displays the list of source locations after rebalancing is approved.

Approved Transfer Out Units

This measure displays the approved number of units to be transferred out for an itemlocation.



Approved Transfer Out

Approved UserID

This measure displays the user ID of the user who approved the transfers.

Export Transfer in Units

This measure displays the exported number of units of the destination location after the batch is run.

Export Transfer In

This measure displays the list of source locations after the batch is run.

Export Transfer Out Units

This measure displays the exported number of units of the source location after the batch is run.

Export Transfer Out

This measure displays the list of destination locations after the batch is run.

Total Deficit Units

This measure displays the total deficit units for an item-location.

Total Deficit %

This measure displays the percentage deficit relative to the total units needed for an itemlocation.

Total Surplus Units

This measure displays the total surplus units for an item-location.

Total Surplus %

This measure displays the percentage surplus relative to the total units needed for an itemlocation.

In Transit over Lead Time+Review Time Units

This measure displays the units in transit over lead and review time for an item-location.

On Order (In) over Lead Time+Review Time Units

This measure displays the units on order over lead and review time for an item-location.

Items View

This **Items View** is located under the **Transfers tab**. In this view, you can review the change in KPIs, such as lost sales, as a result of the transfers, with the focus on products.



Figure 21-68 Items View

Source Mask	
Destination Mask	
ltem Mask	
Unit Price €	0.00
Availability Units	11,000
Approved Transfer In Units	
Approved Transfer Out Units	
Initial Availability Units	
Receipt Up To Level Units	13,355
System Transfer In Units	
System Transfer In €	0.00
System Transfer Out Units	
Approved	
Approved UserID	
Approved Date	
Final Availability Units	
Initial Need Units	%
Final Need Units	
Final Need %	
Initial Surplus Units	%



Items View - Default Profile Measures

The Default measure profile available in the Items view contains the following measures.

Source Mask

This measure is used to decide which products can be transferred out.

Destination Mask

This measure is used to decide which products can be transferred in.

Item Mask

This measure displays if an item is eligible for transfer.

Unit Price \$

This measure displays the unit price.

Availability Units

This measure displays the available units considering replenishment, manual transfers, and rebalancing.

Approved Transfer in Units

This measure displays the approved number of units to be transferred in.

Approved Transfer Out Units

This measure displays the approved number of units to be transferred out for an itemlocation.

Initial Availability Units

This measure displays the available number of units in the destination location before rebalancing.

Receipt Up to Level Units

This measure displays the Receipt Up To Level units as set up in the Replenishment Parameters workspace.

System Transfer in Units

This measure displays the number of units to be transferred in calculated by the system.

System Transfer In \$

This measure displays the value of the units transferred in for a product.

System Transfer Out Units

This measure displays the number of units to be transferred out calculated by the system.

Approved

This measure allows you to approve the rebalancing transfers.

Approved UserID

This measure displays the user ID of the user who approved the transfers.



Approved Date

This measure displays the date of the approval of transfers.

Final Availability Units

This measure displays the available number of units in the destination location after rebalancing.

Initial Need Units

This measure displays the units needed for a product.

Final Need Units

This measure displays the units needed for a product after the transfer.

Final Need %

This measure displays the percentage of the need after rebalancing relative to the need before rebalancing.

Initial Surplus Units

This measure displays the initial surplus units for a product.

Final Surplus Units

This measure displays the surplus units for a product after the transfers.

Final Surplus %

This measure displays the percentage of surplus units relative to the total need.

Forecast Daily Rate of Sale Units

This measure displays the forecasted daily rate of sales in units.

Initial DOS Duration (Days)

This measure displays the initial days of supply based on the forecast.

Final DOS Duration (Days)

This measure displays the days of supply after the transfers.

Initial DOS MAD Duration (Days)

This measure displays the mean absolute deviation of the days of stock before rebalancing.

Final DOS MAD Duration (Days)

This measure displays the mean absolute deviation of the days of stock after rebalancing.

Final DOS MAD %

This measure displays the mean absolute deviation of the days of stock after rebalancing relative to the mean absolute deviation of the days of stock before rebalancing.

Initial Lost Sales Units



This measure displays the initial lost sales units for a product calculated based on deficit units.

Final Lost Sales Units

This measure displays the lost sales units for a product calculated based on deficit units after the transfers.

Initial Lost Sales \$

This measure displays the initial lost sales value for a product calculated based on deficit units.

Final Lost Sales \$

This measure displays the lost sales value for a product calculated based on deficit units after the transfers.


Final Lost Sales %

This measure displays the percentage lost sales relative to the total units needed.

Links View

This **Links View** is located under the **Transfers tab**. In this view, you can manage metrics that define relationships between source and destination locations.

Figure 21-69 Links View



Links View - Default Profile Measures

The Default measure profile available in the Links view contains the following measures.

Lead Time Duration (Days)

Use this measure to enter the transfer duration from source to destination.

Rebalancing Cost \$

Use this measure to enter the transfer cost from source to destination.



Link Priority


Use this measure to enter the routing transfer priority

Locations View

This **Locations View** is located under the **Transfers tab**. In this view, you can review the change in KPIs, such as lost sales, as a result of the transfers, with the focus on locations.



Figure 21-70 Locations View



Locations View - Default Profile Measures

The Default measure profile available in the Locations view contains the following measures.

Source Mask



This measure Is used to decide which stores can transfer products out.

Destination Mask

This measure is used to decide which stores can have products transferred in.

Location Mask

This measure displays if a store is eligible for stock rebalancing.

Availability Units

This measure displays the available units considering replenishment, manual transfers, and rebalancing.

Approved Transfer in Units

This measure displays the approved number of units to be transferred in for a location.

Approved Transfer Out Units

This measure displays the approved number of units to be transferred out from a location.

Initial Availability Units

This measure displays the available number of units in the destination location before rebalancing.

Receipt Up to Level Units

This measure displays the Receipt Up To Level units as set up in the Replenishment Parameters workspace.

System Transfer in Units

This measure displays the number of units to be transferred into a location calculated by the system.

System Transfer In \$

This measure displays the value of products be transferred into a location calculated by the system.

System Transfer Out Units

This measure displays the number of units to be transferred out of a location calculated by the system.

Approved

This measure allows you to approve the rebalancing transfers.

Approved UserID

This measure displays the user ID of the user who approved the transfers.

Approved Date

This measure displays the date of the approval of transfers.

Final Availability Units



This measure displays the available number of units in the destination location after rebalancing.

Initial Need Units

This measure displays the units needed for a location.

Final Need Units

This measure displays the units needed for a location after the transfers.

Final Need %

This measure displays the percentage of the need after rebalancing relative to the need before rebalancing.

Initial Surplus Units

This measure displays the initial surplus units at a location.

Final Surplus Units

This measure displays the initial surplus units at a location.

Final Surplus %

This measure displays the percentage surplus after the transfer relative to the total units needed at a location.

Forecast Daily Rate of Sale Units

This measure displays the forecasted daily rate of sales in units at a location.

Initial DOS Duration (Days)

This measure displays the initial days of supply based on the forecast.

Final DOS Duration (Days)

This measure displays the initial days of supply based on the forecast.

Initial Lost Sales Units

This measure displays the initial lost sales units at a location calculated based on deficit units.

Final Lost Sales Units

This measure displays the lost sales units at a location calculated based on deficit units after the transfers.

Initial Lost Sales \$

This measure displays the initial lost sales value at a location calculated based on deficit units.

Final Lost Sales \$

This measure displays the lost sales value at a location calculated based on deficit units after the transfers.

Final Lost Sales %




This measure displays the lost sales at a location calculated based on deficit units after the transfers relative to the total need at the location.

Parameters View

This **Parameters View** is located under the **Transfers tab**. In this view, you can set the parameters that are used during rebalancing process.

Figure 21-71 Parameters View



Parameters View - Default Profile Measures

The Default measure profile available in the Parameters view contains the following measures.

Rebalancing Type

Use this measure to select how the stock is rebalanced:

 Need/Surplus - looks at the deficit need of the destination location and surplus at the source location.



- DOS tries to balance the Days of Stock (DOS) at every location.
- Need/Surplus+DOS tries to balance the need/surplus and after it runs the DOS balancing.

Surplus Above Layer

This measure allows you to select what portion of stock is considered surplus. For instance, if you select Layer 3, the surplus units include all units that are in Layers 4 and 5. Units in the Layers 3 and less can not be transferred.

Post Optimization

This measure allows you to determine if optimization should run during rebalancing when the rebalancing type is **Need/Surplus+DOS**.

Destination Sorting Key 1

Destination Sorting Key 2

Destination Sorting Key 3

Destination Sorting Key 4

In the Destination Sorting Key measures, you can specify the sorting attributes for destinations. Key 1 has the highest priority and the measures decrease in priority from Key 1 to Key 4. The attributes can be:

- Layer The destination location is sorted based on demand layer priority (Customer Order, Display, Minimum Crdible Quantity, Reorder Point, Reorder Up To Level).
- Priority User defined priority in the transfer link.
- Layer percentage Fill rate percentage on the demand layer.
- Coverage Days Of Stock.

Source Sorting Key 1

Source Sorting Key 2

Source Sorting Key 3

Source Sorting Key 4

In the Source Sorting Key measures, you can specify the sorting attributes for source locations. Key 1 has the highest priority and the measures decrease in priority from Key 1 to Key 4. The attributes can be:

- Cost Prioritizes the lowest cost.
- Lead time Prioritizes the fastest lead time.
- User Out User defined Transfer Out.
- Priority User defined priority in the transfer link.
- Surplus Prioritizes the highest surplus.

Rebalancing Action Buttons

This view includes these action buttons:

Calculate Rebalancing

This action button initiates the rebalancing calculations.



Clear Rebalancing

This action button resets the numbers generated by the Calculate Rebalancing action.

Approve

This action button approves the store transfers calculated by clicking the Calculate Rebalancing action.

Undo Approve

This action button clears the Approved measure, and the approved transfers measures

Plan Transfer Step

In this step, you can identify deficit and surplus inventory across locations and plan inventory transfers between locations when necessary/required. This step contains these views:


- Allowed Transfer View
- Transfer Deficit Analysis View
- Transfer Surplus Analysis View
- Transfer by Destination View
- · Transfer by Product View
- Transfer Deficit From-To View
- Transfer Surplus From-To View

Allowed Transfer View

The **Allowed Transfer View**, under the **Allowed Transfer tab**, shows you what locations are allowed to have transfers. You can manage a location matrix using the Manage Allowed Transfer workspace under the Administration activity where you can select if a transfer between the locations in the matrix is allowed or not. The columns in the worksheet represent the transfers' destination location and the rows represent the transfers' source location.



Figure 21-72 Allowed Transfer View



Allowed Transfer View - Default Profile Measures

The Default measure profile available in the Allowed Transfer view contains the following measure.

Transfer Enable


The Transfer Enable allows or disallows transfers between source locations and destination locations. When selected, transfers are allowed. When clear, transfers are not allowed. The Transfer Enable measure can be edited and managed using the Manage Allowed Transfer workspace under the Administration activity.

Transfer Deficit Analysis View

The **Transfer Deficit Analysis View**, under the **Deficit Surplus Analysis tab**, allows you to review what stores and products have an inventory deficit. This provides you with the necessary information to support planning of transfers between locations to balance the inventory levels across the locations.



Figure 21-73 Transfer Deficit Analysis View



Transfer Deficit Analysis View - Default Profile Measures

The Default measure profile available in the Transfer Deficit Analysis view contains the following measure.


Tot. Deficit Units

The Tot. Deficit Units is a calculated measure used to indicate the amount of deficit units for the product and location combination. The values are calculated based on the RUTL calculated at the system date and the available inventory. When the available inventory is not enough for the RUTL then there is a deficit.

Transfer Surplus Analysis View

The **Transfer Surplus Analysis View**, under the **Deficit Surplus Analysis tab**, allows you to review what stores and products have an inventory excess/surplus. This provides you with the necessary information to support planning of transfers between locations to balance the inventory levels across the locations.

Figure 21-74 Transfer Surplus Analysis View





Transfer Surplus Analysis View - Default Profile Measures

The Default measure profile available in the Transfer Surplus Analysis view contains the following measures.

Tot. Surplus Units

The Tot. Surplus Units is a calculated measure used to indicate the number of surplus units for the product and location combination. The values are calculated based on the RUTL calculated at the system date and the available inventory. When there is more available inventory than necessary to fulfill the RUTL then there is a surplus.

PROD SLOC Man. Filter

The PROD SLOC Man. Filter is an editable measure used to apply a filter to the Transfer Surplus From-To view by the selected product and source location combination. When a product and location combination is selected and after the workspace calculation (either **Calculate** or **F9**) is run, the views are filtered based on the selected product and location combinations.

Transfer by Destination View

The Transfer by **Destination View**, under the **Manual Transfer tab**, allows you to review replenishment and transfers from a destination location perspective. This view provides approved and exported replenishment and transfers to support the review. Inventory information is also available.




Figure 21-75 Transfer by Destination View

Transfer by Destination View - Default Profile Measures

The Default measure profile available in the Transfer by Destination view contains the following measures.

Appr. Rpl. Plan In Units



The Appr. Rpl. Plan In Units is the same as the one in the default profile under the SKU-LOC Level (R & A) view. Refer to the measure, Appr. Rpl. Plan In Units under the SKU-LOC Level (R & A) view, in the Default Profile Measures.

Exp. Rpl. Plan In Units

The Exp. Rpl. Plan In Units is the same as the one in the availability profile under the SKU-LOC Level (R & A) view. Refer to the measure, Exp. Rpl. Plan In Units, in the Measures: Availability Profile under the SKU-LOC Level (R & A) view in the Default Profile Measures.

Appr. Transfer In Units

The Appr. Transfer In Units is a calculated measure used to indicate the transfer units approved for the product and destination location combination.

Exp. Transfer Plan In Units

The Exp. Transfer Plan In Units is a calculated measure used to indicate the transfer units to be exported from the batch for the product and location combination. In this view, the value is the total of all destination locations for the product.

Tot. On Order (in) Units

The Tot. On Order (in) Units is the same as the one in the inventory profile under the SKU-LOC Level (R & A) view. Refer to the measure, Tot. On Order (in) Units, in the Measures: Inventory Profile under the SKU-LOC Level (R & A) view in the Default Profile Measures.

Appr. Rpl. Plan Out Units

The Appr. Rpl. Plan Out Units is the same as the one in the availability profile under the SKU-LOC Level (R & A) view. Refer to the measure, Appr. Rpl. Plan Out Units, in the Measures: Availability Profile under the SKU-LOC Level (R & A) view in the Default Profile Measures.

Exp. Rpl. Plan Out Units

The Exp. Rpl. Plan Out Units is the same as the one in the availability profile under the SKU-LOC Level (R & A) view. Refer to the measure, Exp. Rpl. Plan Out Units, in the Measures: Availability Profile under the SKU-LOC Level (R & A) view in the Default Profile Measures.

Appr. Transfer Out Units

The Appr. Transfer Out Units is a calculated measure used to indicate the source location's transfer units approved for the product and location combination.

Exp. Transfer Plan Out Units

The Exp. Transfer Plan Out Units is a calculated measure used to indicate the source location's transfer units to be exported from the batch for the product and location combination. In this view, the value is the total of all locations for the product.

Tot. On Order (out) Units

The Tot. On Order (out) Units is the same as the one in the inventory profile under the SKU-LOC Level (R & A) view. Refer to the measure, Tot. On Order (out) Units, in the Measures: Inventory Profile under the SKU-LOC Level (R & A) view in the Default Profile Measures.



Tot. Avail. Units

The Tot. Avail. Units is the same as the one in the default profile under the SKU-LOC Level (R & A) view. Refer to the measure, Tot. Avail. Units, in the Default Profile Measures under the SKU-LOC Level (R & A) view in the Default Profile Measures.

Tot. Avail. Dur (w)

The Tot. Avail. Dur (w) is a calculated measure used to indicate the number of weeks that the Tot. Avail. Unit can cover the demand for the product and location combination.

RUTL @ Today Units

The RUTL @ Today Units is the same as the one in the default profile under the SKU-LOC Level (R & A) view. Refer to the measure, RUTL @ Today Units, in the Default Profile Measures under the SKU-LOC Level (R & A) view in the Default Profile Measures.

Tot. Deficit Units

The Tot. Deficit Units is the same as the one in the default profile under the Transfer Deficit Analysis view. Refer to the measure, Tot. Deficit Units, in the Default Profile Measures under the Transfer Deficit Analysis view in the Default Profile Measures.

Tot. Surplus Units

The Tot. Surplus Units is the same as the one in the default profile under the Transfer Surplus Analysis view. Refer to the measure, Tot. Surplus Units, in the Default Profile Measures under the Transfer Surplus Analysis view, for more details.

Transfer Plan In Units

The Transfer Plan In Units is a calculated measure used to indicate the transfer units planned for the product and destination location combination (for example, populated when a deficit location has a transfer planned to receive inventory from another location).

Transfer Plan Out Units

The Transfer Plan Out Units is a calculated measure used to indicate the transfer units planned for the product and source location combination (for example, populated when a surplus location has a transfer planned to send inventory to another location).

Transfer Avail. Alert


The Transfer Avail. Alert is a calculated measure used to indicate that an alert was triggered by the transfer.

Transfer by Product View

The **Transfer by Product View**, under the **Manual Transfer tab**, allows you to review transfers from a product perspective. This view provides you with planned and approved transfer information.



Figure 21-76 Transfer by Product View



Transfer by Product View - Default Profile Measures

The Default measure profile available in the Transfer by Product view contains the following measures.

Transfer Avail. Units

The Transfer Avail. Units is a calculated measure used to indicate the total inventory quantity available at the location, for the product, that is available after the planned transfers. This calculation takes into account the available inventory at the location plus the planned transfers, in and out, for the location.

Transfer Deficit Units

The Transfer Deficit Units is a calculated measure used to indicate the amount of deficit units for the product and location combination. The values are calculated based on the RUTL calculated at the system date and the available inventory. When the available inventory is not enough for the RUTL then there is a deficit.

Transfer Surplus Units

The Transfer Surplus Units is a calculated measure used to indicate the number of surplus units for the product and location combination. The values are calculated based on the RUTL calculated at the system date and the available inventory. When there is more available inventory than necessary to fulfill the RUTL then there is a surplus.

Transfer Plan In Units

The Transfer Plan In Units is a calculated measure used to indicate the transfer units planned for the product and destination location combination (for example, populated when a deficit location has a transfer planned to receive inventory from another location).

Transfer Plan Out Units

The Transfer Plan Out Units is a calculated measure used to indicate the transfer units planned for the product and source location combination (for example, populated when a surplus location has a transfer planned to send inventory to another location).



Appr. Transfer In Units

The Appr. Transfer In Units is a calculated measure used to indicate the transfer units approved for the product and destination location combination.

Appr. Transfer Out Units

The Appr. Transfer Out Units is a calculated measure used to indicate the source location's transfer units approved for the product and location combination.

Exp. Transfer Plan In Units

The Exp. Transfer Plan In Units is a calculated measure used to indicate the transfer units to be exported from the batch for the product and location combination. In this view, the value is the total of all destination locations for the product.

Exp. Transfer Plan Out Units

The Exp. Transfer Plan Out Units is a calculated measure used to indicate the source location's transfer units to be exported from the batch for the product and location combination. In this view, the value is the total of all locations for the product.

Transfer Deficit From-To View

The **Transfer Deficit From-To View**, under the **Manual Transfer tab**, allows you to review and manage, from the destination locations perspective, the transfers from surplus locations to deficit locations.




Figure 21-77 Transfer Deficit From-To View

Transfer Deficit From-To View - Default Profile Measures

The Default measure profile available in the Transfer Deficit From-To view contains the following measures.

Assort. @ Dst.

The Assort. @ Dst. is a calculated measure used to indicate if the transfer is allowed between the locations for the product and the destination location has the product assorted. When



selected, the transfer is allowed and the product and location is assorted. When clear, either the transfer is not allowed between the locations or the product is not assorted at the destination location.

Avail. @ Dst. Units

The Avail. @ Dst. Units is a calculated measure used to indicate the total inventory units available for the product at the destination location.

Deficit @ Dst. Units

The Deficit @ Dst. Units is a calculated measure used to indicate a deficit of units for the product at the destination location.

Tot. Src. Avail. Units

The Tot. Src. Avail. Units is a calculated measure used to indicate the total inventory units available for the product at the source location.

Surplus @ Src. Units

The Surplus @ Src. Units is a calculated measure used to indicate a surplus of units for the product at the source location.

Transfer Action

The Transfer Action is an editable measure used to indicate, for product and location combinations, the transfer method for the calculation. Valid values are:

Avail

When this option is selected all available inventory at the source location is transferred.

Avail + End

When this option is selected all available inventory at the source location is transferred and the system stops the assortment at the source location.

Spls -> Dfct

When this option is selected the destination location deficit is fulfilled (or reduced) with the surplus inventory from the source location.

Avail -> Dfct

When this option is selected the destination location deficit is fulfilled (or reduced) with the available inventory from the source location.

Spis

When this option is selected only the surplus inventory from the source location is moved to the destination location.

Undo

When this option is selected, the last action or transfer is undone.

Sys. Transfer Plan Units

The Sys. Transfer Plan Units is a calculated measure used to indicate the transfer of units between the source location and the destination location when there is a surplus that can be transferred from the source location to the destination location. This measure is also recalculated by the **Transfers** action button.



Transfer Plan Units

The Transfer Plan Units is an editable measure used to enter manually the number of units to be transferred from the source location to the destination location. This measure can also be overridden or calculated by the **Calculate Transfer Plan** action button. It populates or overrides the measure with the number of units to be transferred from the source location to the destination location by taking into account the transfer method selected in the measure Transfer Action.

Appr. Transfer Units

The Appr. Transfer Units is a calculated measure used to indicate the planned transfers that were approved. The Transfer Plan Units value is copied to this measure by the **Approve Transfers** action button.

Exp. Transfer Plan Units

The Exp. Transfer Plan Units indicates the exported manual location transfers order (in units).

Transfer Surplus From-To View

The **Transfer Surplus From-To View**, under the **Manual Transfer tab**, allows you to review and manage, from the source locations perspective, the transfers from surplus locations to deficit locations. This view contains the same measures as the deficit view. For more details regarding the measures description, refer to the Transfer Deficit From-To view.




Figure 21-78 Transfer Surplus From-To View

Filter Step

In this step you can set up filters to filter the views within the Review & Approved workspace. This step contains these views:

- Attribute Filter Setup View
- Calendar Filter Setup View




- Filter Setup View
- Filter Statistics View
- Quick Filter View
- User Filter View

Attribute Filter Setup View

The Attribute Filter Setup View, under the Filter tab, is similar to the Filter Attribute view within the Manage Alert Parameters workspace. The difference is that the filter, in this step, is applied to the Review & Approved workspace views in a similar way to how they are described in the Manage Alert Parameters workspace. For more details regarding the view and the measures, refer to the Filter Attribute view in the Filters step within the Manage Alert Parameters workspace.

Figure 21-79 Attribute Filter Setup View




Calendar Filter Setup View

The **Calendar Filter View**, under the **Filter tab**, is similar to the Filter Calendar view within the Manage Alert Parameters workspace. The difference is that the filter, in this step, is applied to the Review & Approve workspace views in a similar way to how they are described in the Manage Alert Parameters workspace. For more details regarding the view and the measures, refer to the Filter Calendar view in the Filters step within the Manage Alert Parameters workspace.



Figure 21-80 Calendar Filter Setup View



Filter Setup View

This view allows you to define the conditions for the rules based in product, location, and product-location attributes. A rule condition is what allows the engine to find the product and location combinations where the rule is applicable.

Figure 21-81 Filter Setup View



Filter Setup View - Default Profile Measures

The Filter Setup view contains the following measures.

Condition Attribute

The Condition Attribute measure allows you to select the attribute for the condition, The attributes for the rules are assigned in the Attribute Review workspace.

Within Cond Op

The Within Cond Op measure allows you to specify the operator to be used inside the condition.



Table 21-2 Within Cond Op Measure Available Operators

Possible Operators	Descriptions	Example
==	Checks if the attribute value is equal with the Condition Value	brand == Private Label
!=	Checks if the attribute value is different from the Condition Value	average sales != 0
>	Checks if the attribute value is larger than the Condition Value	Average sales >5
>=	Checks if the attribute value is larger or equal to the Condition Value	
<	Checks if the attribute value is less than the Condition Value	Standard deviation of sales <6
<=	Checks if the attribute value is less or equal to the Condition Value	
contain		
not contain		
match		
not match		

Cond Value

The Cond Value measure is used when the type of the attribute is numeric. Example: average sales > 10

Cond Value String

The Cond Value String measure is used when the type of the attribute is a string. Example: brand == Private Label

Cond Value Measure

The value of the Cond Value measure is a measure name, which is populated by an expression that let's you refine the condition value. For instance private label versus non-private label.

This measure is used when you want to refine the condition value.

For instance, for the coffee items, except Private Label, you want to assign items to the rule that sell more than 50 per week. For Private Label items you may want the value to be 100. You need to populate your Condition measure with a value of 100 for all Private Label items, and the rest of the coffee items with 50.

Cond Value Date

The Cond Value Date measure is used when the type of the attribute is a date. Example: today >= 02/30/2024"

Between Cond Op

Within a rule there can be multiple conditions and also multiple condition groups. This is specified in the Cond Group measure. Conditions with the same Cond Group value belong to the same group.



For example, if a rule has 4 conditions, Conditions 1 and 2 can belong to condition group 1, and conditions 3 and 4 can belong to the condition group 2. Also, the Cond Order measure gives the ranking of the conditions inside the group.

The following table is an assumed use case:

Table 21-3 Between Cond Op Assumed Use Case

Condition	Between Con Op	Cond Order	Cond Group	
Condition 1	AND	1	1	
Condition 2	OR	2	1	
Condition 3	OR	3	2	
Condition 4		4	2	

The value for the Between Cond Op can be the logical operators AND or OR.

The conditions are evaluated first inside a condition group and then between groups. In the previous case, the resulting condition is:

(Condition 1 AND Condition 2) OR (Condition 3 OR Condition 4)

Here is an example where all conditions belong to the same condition group:

Table 21-4 Example: All Conditions Belong to the Same Condition Group

Condition	Between Con Op	Cond Order	Cond Group
Condition 1	AND	1	1
Condition 2	OR	2	1
Condition 3	OR	3	1
Condition 4		4	1

The resulting condition for the rule is given by:

Condition 1 AND Condition 2 OR Condition 3 OR Condition 4

Note that the conditions are evaluated in the order given by the values in the Cond Order measure.

Cond Order

The Cond Order measure displays the order in which conditions are evaluated, wither independently or inside a condition group.

Cond Group

The Cond Group measure allows you to group conditions. This is useful when you want to evaluate conditions in a two-step process. First, the conditions are evaluated inside groups. In the second step, the group results are evaluated.

Validation Result

The Validation Result measure displays the condition expressions that are validated.

Invalid Flag



The Invalid Flag measure indicates if a condition is invalid.


Valid Flag

The Valid Flag measure indicates if a condition is valid.

Filter Statistics View

The **Filter Statistics View**, under the **Filter tab**, is similar to the Filter Statistics view within the Manage Alert Parameters workspace. The difference is that the filter, in this step, is applied to the Review & Approve workspace views in a similar way to how they are described in the Manage Alert Parameters workspace. For more details regarding the view and the measures, refer to the Filter Statistics view in the Filters step within the Manage Alert Parameters workspace

Figure 21-82 Filter Statistics View




Quick Filter View

The **Quick Filter View**, under the **Filter tab**, allows you to review and configure the filter to be applied to the views within the Review & Approve workspace. In this view, you can check filter statistics and configure the filter to be applied to the product, location, and calendar hierarchies (for example, calendar horizon, string search in product attributes, and so on). Once that a change is performed it is applied after running the workspace calculation (either **Calculate** or **F9**).



Figure 21-83 Quick Filter View



Quick Filter View - Default Profile Measures

The Quick Filter view contains the following measures.

All PROD-LOC Count

The All PROD-LOC Count is a calculated measure used to indicate the total number of product and location combinations assorted.

Main Filter PROD - LOC Count

The Main Filter PROD - LOC Count is a calculated measure used to indicate the total number of product and location combinations that were filtered by the filter configured in this view.

Main Filter PROD - LOC %

The Main Filter PROD - LOC % is a calculated measure used to indicate, in percentage, how much the filtered product and location combinations represent on the total count of product and location combinations assorted

User Filter PROD-LOC

The User Filter PROD-LOC is an editable measure used to restrict the filter by the product and location combinations when the measure User Filter PROD-LOC is selected.

PROD SLOC Man. Filter

The PROD SLOC Man. Filter is an editable measure used to filter the relevant product and location in the manual transfer view.

Filter To-Be-Revwd

The Filter To-Be-Revwd is an editable measure used to add in the filter a condition to display only product and location combinations with alert hits that still need to be reviewed by you.

Filter By Pack Type

The Filter By Pack Type is an editable measure used to define the type of packs that the filter should include in the condition. Valid values are:



Both

When selected, the filter includes all pack products – Simple and Complex pack types.

Simple

When selected, the filter only includes simple pack type products.

Complex

When selected, the filter only includes complex pack type products.

PROD Search All

The PROD Search All is an editable measure used to define the string to search in all product attributes. Note that the label is a product attribute.

LOC Search All

The LOC Search All is an editable measure used to define the string to search in all location attributes. Note that the label is a location attribute.

PROD-LOC Search All

The PROD-LOC Search All is an editable measure used to define the string to search in all product-location-attributes (for example, lifecycle).

Filter Horizon Past Weeks Dur (weeks)

The Filter Horizon Past Weeks Dur (weeks) is an editable measure used to indicate the number of past weeks that should be displayed in the views where the calendar is available (for example, Inventory planning views). The relevant views are filtered by based on the number of weeks specified here.

Filter Horizon Future Weeks Dur (weeks)

The Filter Horizon Future Weeks Dur (weeks) is an editable measure used to indicate the number of future weeks that should be displayed in the views where the calendar is available (for example, Inventory planning views). The relevant views are filtered by based on the number of weeks specified here.



Once the workspace calculation is run (either **Calculate** or **F9**), the relevant views are filtered based on the filter set up completed in this view.

Review & Approve Action Buttons

The Review & Approve workspace has the following action buttons available:

Seed User Filter

Use the **Seed User Filter** action button to seed the User Filter from a specified alert which populates the Boolean User Filter measure.

Run Filters



Use the **Run Filters** action button for applying the filters in the Review & Approve workspace based on the filter set up completed in the Filter step. For example, filter based on the User Filter measures.

Clear Filters

Use the **Clear Filters** action button for to remove all filters applied to the views within the Review & Approve workspace.

Reload Parameters

Use the **Reload Parameters** action button to reload, from the domain into the workspace, all the replenishment parameters that are managed in the Replenishment Parameters workspace.

Synchronize Forecast

Use the **Synchronize Forecast** action button to reload the latest adjusted forecast from the domain into the workspace and re-calculate the forecast aggregation measures (for example, Fcst W+0 to W+2 Units). It is primarily used when 'what if' scenarios are being worked on.

Calculate Plan

Use the **Calculate Plan** action button to calculate the replenishment for all the products and locations in the workspace's scope using the set up and parameters available within the Review & Approve workspace. Using this action button you can change the replenishment parameters, by overriding the original values, and complete a what-if scenario to check the impact on replenishment results.

Replenishment Approval

Use the **Replenishment Approval** action button to approve all product and location replenishments that are selected to be approved. When the product and location combination is selected to be approved (measure Appr. Rpl. Plan) then the system replenishment is copied to the approved replenishment.

Within Day Exp. Refresh

Use the **Within Day Exp. Refresh** action button to refresh the exported transfers and inventory plan measures by pulling the values from the domain. Typically, this action is run after the intra-day batch to export transfers and inventory plan is run.

Visual Assortment

Use the **Visual Assortment** action button to calculate the images across the planning calendar in the workspace's scope. This provides you with a visual for the assortment across the calendar.

Calculate Inventory Plan

Use the **Calculate Inventory Plan** action button to calculate the weekly inventory plan for all the products and locations in the workspace's scope using the inventory plan parameters available within the A & R workspace. Using this action button, you can, for example, change the inventory plan parameters, by overriding the original values, and complete a what-if scenario to check the impact in the weekly inventory plan results.

Plan Approval

Use the **Plan Approval** action button to approve all the products, locations and weeks' inventory plans that are selected to be approved. When the product, location, and week combination is selected to be approved (measure Appr. Plan (Wk)) then the system inventory plan is copied to the approved inventory plan. This action button also populates the audit measures that allows you to know when the action was taken and by whom.



Calculate Transfer Plan

Use the **Calculate Transfer Plan** action button to calculate the transfers from the source locations to the destination locations based on the transfer set up completed in the Transfer Step views (for example, allowed transfer locations matrix, units of deficit or surplus).

Approve Transfers

Use the **Approve Transfers** action button to approve all the calculated transfers from the source locations to the destination locations. Specific transfers cannot be chosen by you. All planned transfers within the workspace scope are approved.

Clear Transfers

Use the **Clear Transfers** action button to clear all the planned transfers. It cleans the transfer action and the in and out planned transfer units.

User Filter View

The **User Filter View**, under the **Filter tab**, is similar to the User Filter view within the Manage Alert Parameters workspace. The difference is that the filter, in this step, is applied to the Review & Approve workspace views in a similar way to how they are described in the Manage Alert Parameters workspace. For more details regarding the view and the measures, refer to the User Filter view in the Filters step within the Manage Alert Parameters workspace.




Figure 21-84 User Filter View



A

Appendix: Forecast Approval Exceptions

This appendix provides the details on approval and navigation exceptions defined for the GA version of IPOCS-Demand Forecasting.

The exception management framework available in RPASCE works on several levels. First, the users refines the approval and navigation rules in the Business Rule Engine.

The forecast approval method is one of the following options:

Manual

The system-generated forecast is not automatically approved. Forecast values must be manually approved by accessing and possibly amending values in the Forecast Review workspace.

Automatic

The system-generated forecast is automatically approved as is.

By exception

This list contains the exceptions that were configured for use in the forecast approval process. They should match the dashboard exceptions and workspace alerts.

The unapproved product/locations are then assigned in order of priority to one of the following buckets:

- Urgent
- Required
- Optional
- Informational

Both the approval and navigation features can be configured to fit retailers' needs.

Then, the batch is run and the approval and navigation exceptions are worked out. Now it is time to review them and take actions. First there is the dashboard. You can review the approval exception tiles and see which business rules had a larger impact. The navigation exception profile displays how many production/locations are in each of the navigation buckets. This helps you plan your work when reviewing forecasts in order of priorities, assigned using business rules. From here you can open the Forecast Review workspace. Once in the workspace, you can decide how to review the forecasts. Every dashboard exception can have a workspace alert counterpart. You can navigate to product/locations that are flagged as exceptions, or you can use the workspace exceptions, that point you to cells where the business rules have been violated. This is possible because the workspace alerts have the time dimension while dashboard exceptions are at the production/location intersection, pointing you to the time series that needs attention.

The following details the GA approval alerts calculations.

Forecast versus Recent Sales

Usually it is not expected that demand values differ very much period to period. This also implies that the forecast magnitude generally is in line with the magnitude of the most recent sales. There are cases when this is not the case. For instance when an item enters a season, the forecast is probably higher than the sales in periods leading to the season. Or when an item is towards the end of the season, the forecast will be lower than sales in peak periods. For these cases, the user can be alerted to review the forecast, rather than auto approving it.

The following is the alert expression:

$$\sum_{today-alert\ window\ length-1}^{today-1} baseline\ demand(t) > 0$$

$$&\& \\ \frac{\sum_{today+alert\ window\ length}^{today+alert\ window\ length}\ adjusted\ baseline(t)}{alert\ window\ length} > threshold1$$

$$&\& \\ \frac{\sum_{today+alert\ window\ length}^{today+alert\ window\ length}\ adjusted\ baseline(t)}{\sum_{today-1}^{today-1}\ baseline\ demand(t)} - 1 > threshold2$$

Where length, threshold1, and threshold2 are adjustable parameters.

Note how the calculations are not performed for the entire forecast horizon, but rather by the number of periods determined by the length parameter. The reason is that the forecast horizon can sometimes be very long; for example, 52 weeks, and average demand over such a long time period cannot be used as in-season versus out of season rate of sales.

Adjusted versus Approved

IPOCS-Demand Forecasting is typically set up to generate forecast weekly. Every week, new sales data is loaded, the forecast is regenerated. While the latest data points are expected to make the forecast more accurate, it is not expected that the difference in forecasts generated in two consecutive weeks to vary too much. If the forecasts differ, the user is alerted to review the forecasts.

The following is the alert expression:



$$\left|\frac{\sum_{today+forecast\ length-1}^{today+forecast\ length-1}adjusted\ forecast(t)}{\sum_{today}^{today+forecast\ length-1}lappf(t)}-1\right|>threshold1$$

$$\frac{\sum_{today+forecast\ length-1}^{today+forecast\ length-1} adjusted\ forecast(t)}{forecast\ length-1} > threshold2$$

Where threshold1 and threshold2 are adjustable parameters.

Note how summation of forecasts is not performed over the entire forecast length. It is stopped one period prior the forecast horizon ends, because this is the last populated period of the last approved forecast.

Forecast versus Last Year Sales

The most reliable forecasts are generated from data that has a repeatable pattern year over year. However, this is not always the case. A change in business strategy, merchandise reclassifications, New Items can all lead to changing selling patterns over time.

To detect possible changes in selling patterns, the following alert will compare the last year's sales volume with the forecasted sales volume. If they are different by an adjustable percent, the alert is triggered.

The following is the alert expression:

$$\frac{\sum_{today}^{today+alert\ window\ length}\ adjusted\ baseline(t)}{alert\ window\ length} > threshold1$$

$$\frac{\sum_{today}^{today+alert\ window\ length}\ baseline\ demand\ LY(t)}{alert\ window\ length} > threshold1$$

$$\frac{\sum_{today}^{today+alert\ window\ length}\ adjusted\ baseline(t)}{\sum_{today}^{today+alert\ window\ length}\ baseline\ demand\ LY(t)} - 1 > threshold2$$

Where threshold1 and threshold2 are adjustable parameters.

First we check if the forecast is close to the sales LY. If it is, no alert is triggered. If it is not, we check the rate of sales of the item. If the item is selling consistently, we trigger an alert. If the sales and forecast are different, but the rate of sales of the item is not significant - defined by threshold2, no alert is triggered. This way we avoid prompting the user to review forecasts for low selling items.



Promo Peaks

The purpose of this alert is to check how large the forecast peaks are compared to historical demand. The peaks can come from various effects like promotions, price discount, demand transference due to assortment changes, and so on. The most common, though, are due to price changes and promotions.

The following is the alert expression:

Adjusted Peak > Max Sales History * Causal Peak Factor

Where the Causal Peak Factor is an adjustable parameter.

The business case this addresses is to alert you when the peaks in the forecast region are larger than any observed sales in the past. There may be valid justification for this, for instance, several events are active in the same time period, thus creating a huge spike in demand. You can review the alert and take action.

Enabling GA Approval Alerts

The process around enabling GA approval alerts is as follows:

- 1. GA alerts to be used in the approval process are configured in the IPO-DF plug-in
- 2. Only alerts enabled in the plug-in can be selected for the approval method in the Forecast Setup workspace.
- The Forecast Approval process is limited to only the alerts selected in the Forecast Setup workbook. It calculates all of the enabled alerts for the unapproved sku/ store combinations.
- 4. The dashboard then displays all of the enabled alerts for the unapproved sku/stor. However, the approval process is limited to only whatever was selected as the approval method.
- Forecast vs. Last Year Sales Batch Alert is the same as Forecast versus Last Year Sales.



B

Appendix: Forecast Errors in the Forecast Scorecard Dashboard

This appendix provides background and formulas for the error metrics used in the Forecast Scorecard dashboard. The errors are always calculated at the lowest level - typically item/ store/week, and then averaged at the intersection of the dashboard tiles. For GA this intersection is subclass/district, but it can be configured at implementation time. The evaluation of the forecast is done over a window starting today and looking back a configurable number of periods. All errors are calculated for the system-generated forecast as well as the user adjusted forecast.

The following are the error metrics:

- Mean Absolute Percent Error
- Root Mean Squared Error
- Mean Absolute Error
- Forecast Bias
- Percent Adjusted

Mean Absolute Percent Error

The percentage error of a forecast observation is the difference between the actual POS value and the forecast value, divided by the actual POS value. The result of this calculation expresses the forecast error as a percentage of the actual value. The Mean Absolute Percentage Error statistic measures forecast accuracy by taking the average of the sum of the absolute values of the percentage error calculations across all observations. This method is useful when comparing the accuracy of forecasts for different volume products (it normalizes error by volume).

$$MAPE = \frac{100\%}{n} \sum_{t=1}^{n} \left| \frac{demand(t) - forecast(t)}{demand(t)} \right|$$

Root Mean Squared Error

This is the square root of the Mean Squared Error. The Root Mean Squared Error is one of the most commonly used measures of forecast accuracy because of its similarity to the basic statistical concept of a standard deviation. It evaluates the magnitude of errors in a forecast on a period-by-period basis, and it is best used to compare alternative forecasting models for a given series.

$$RMSE = \sqrt{\frac{\sum_{t=1}^{n}(demand(t) - forecast(t))^{2}}{n}}$$

Mean Absolute Error

The absolute error of a forecast observation is the absolute value of the difference between the forecast value and the actual POS value. The Mean Absolute Error statistic is a measure of the average absolute error. This is calculated by summing the absolute errors for all observations and then dividing by the number of observations to obtain the average. Mean Absolute Error gives you a better indication of how the forecast performed period by period because the absolute value function ensures that negative errors in one period are not canceled out by positive errors in another. Mean Absolute Error is most useful for comparing two forecast methods for the same series.

$$MAE = \frac{\sum_{t=1}^{n} |demand(t) - forecast(t)|}{n}$$

Forecast Bias

Forecast BIAS is described as a tendency to either:

- over-forecast (meaning, more often than not, the forecast is more than the actual)
- under-forecast (meaning, more often than not, the forecast is less than the actual).

A desired property of a forecast is that it is not biased.

$$BIAS = \frac{100\%}{n} \sum_{t=1}^{n} \frac{demand(t) - forecast(t)}{demand(t)}$$

Percent Adjusted

This number represents the count of adjusted forecast values divided by the total count of forecast values. A high percentage indicates that the users heavily adjust the forecasts.



C

Appendix: Business Rule Engine


Oracle Retail has designed the Business Rule Engine (BRE) to help IPOCS-Demand Forecasting users set up business strategies to manage parameters used in the forecast approval and navigation processes. Parameters include alert thresholds, alert calculation window, as well as navigation criteria. These parameters can be set up manually in the forecast setup workbook at the global, intermediate, and final levels (override). With the business rule engine, the parameter values at final level can be dynamically adjusted based on business requirements. No patching of the environment is required. For example, a business strategy can be to set the alert error threshold to 10% for all product/locations combos with average sales larger than 10 units per week. For product/locations with average sales less than 10 units per week, the threshold can be relaxed to 20%. This way high sellers have a tighter error threshold because they are more important for the business, and the analysts may want to review their forecasts more rigorously. Using this approach, the parameter values were assigned to product/locations based on business strategy rather than hierarchy positions.

The BRE is used in br-engine.fm mainly in the approval process. This has been refined to include multiple stages. At a high level these are:

- Automatically adjust the system forecast
- Run the approval exceptions
- Assign the unapproved product/locations to navigation buckets based on business priorities you have set up
- Finally, in the Forecast Review workspace, review/adjust/approve product/locations being guided by the navigation exceptions.

Figure C-1 depicts the overall approval process


Figure C-1 Approval Workflow



Notice how the work done in the BRE is mentioned as an infrequent task. You only need to access it when you want to change business rules regarding approval and/or navigation strategies.

The interaction with the BRE is depicted in Figure C-2.

Figure C-2 Business Rule Engine



You start with the rules conditions, then adjust the approval exceptions requirement, and finally the navigation strategies.

Examples of how approval rule conditions can be used:

High margin items: tighten approval criteria

- Key items: never approve, too important
- Product/locations not in season: approve automatically
- Low sellers: Loosen approval criteria

After the approval exception process is run, there will be a pool of product/locations that are approved and a pool of product/locations that are not approved. However, not all product/locations in this pool have the same criticality.

This is where the navigation exceptions come in the picture. The unapproved product/ locations are run through the business rules for navigations and assigned to different navigation buckets. Let say we have four buckets for navigation: *Urgent*, *Required*, *Optional*, and *Informational*. You can set conditions to achieve the following assignments on unapproved product/locations to navigation buckets (or tiers).

- Urgent- key items, high sellers
- Required- decent sellers and high navigation variance
- Optional- high navigation variance
- Informational- all other unapproved items

Note:

The navigation variance is calculated during the approval exception process and it records by how much the forecast was off from the measure it was compared to.

Figure C-3 illustrates the concepts of approval and navigation conditions, as well as how they support the approval workflow for the previous example.

Figure C-3 Rule Conditions




Figure C-4 and Figure C-5 show images of the Rule Condition Setup views in the UI for approval and navigation.

Figure C-4 Approval Conditions





Figure C-5 Navigation Conditions





D

Appendix: IPOCS-Lifecycle Allocation and Replenishment Exceptions & Alerts

This appendix provides the complete list of alerts defined for the GA version of IPOCS-Lifecycle Allocation and Replenishment. The list of alerts includes alerts for the IPOCS-Lifecycle Allocation and Replenishment set up validation and alerts for IPOCS-Lifecycle Allocation and Replenishment data validation (for example, generated orders).

The exception management framework available in RPASCE works on different levels. Starting with the dashboard component, the exception profiles allow you to view the hit count for every exception. Once in the workspace, you can use the workspace alerts to navigate to the product/location combination (or product/location/weeks) that have been flagged. Every dashboard exception has a workspace alert counterpart. The calculation expressions are not identical, because the dashboard exceptions are at the production/location intersection, while the workspace alerts also have the time dimension.

Finally, every defined exception can be used in the approval logic. Order approval can be controlled by the alerts:

Manual

The system-generated orders are not automatically approved. Order values must be manually approved by accessing and possibly amending values in the A & R Admin workspace.

Automatic

The system-generated orders are automatically approved as is (no blocking alerts triggered).

By Exception

This list contains the exceptions that were configured for use in the replenishment approval process. They should match the dashboard exceptions and workspace alerts.

There are two types of Exception Alerts:

Setup Exceptions

Replenishment Exceptions

Setup Exceptions

The Setup exceptions are used to alert you for potential set up issues in the supply chain network. The following are all set up exceptions available in IPOCS-Lifecycle Allocation and Replenishment.

BOD Exception Count

This exception indicates what ranged products and locations are currently with no Bill of Distributions (BOD)s assigned.

Lifecycle Phase Exception Count

This exception indicates what ranged products and locations are currently with no lifecycle phase defined.

Planning Calendar Exception Count

This exception indicates what ranged products and locations are currently with no planning calendar assigned.

Replenishment Exceptions

Use the replenishment exceptions to alert you for potential issues in the replenishment parameters set up and for specific exceptions that might need to be looked at, for example, a replenishment watch list.

During the batch, IPOCS-Lifecycle Allocation and Replenishment calculates the system proposed order after which the alerts are calculated. Once calculated the alerts are used by IPOCS-Lifecycle Allocation and Replenishment to let the system know if the proposed orders can be approved or not. If for specific item/location combinations, there are critical alerts (alerts classified as critical are within the Review Alerts workspace) then IPOCS-Lifecycle Allocation and Replenishment does not autoapprove the orders and you must review them before approving manually within the system. Following are all the replenishment exceptions available in IPOCS-Lifecycle Allocation and Replenishment.

Future Promotions

This exception indicates what ranged item/location combinations have promotions flagged in the future. You can then review the replenishment and take the necessary action in preparation for the promotion (for example, increment the replenishment values before the start of the promotion).

Replenishment Watch-List

This exception indicates what items/location combination are in the replenishment watch list. This alert allows you to keep track of replenishment for specific item/location combinations. This exception is not automatically calculated by IPOCS-Lifecycle Allocation and Replenishment. You are able to include or exclude item/location combinations from the replenishment watch list within the Review Alerts workspace. IPOCS-Lifecycle Allocation and Replenishment uses those values to calculate this exception.

Lifecycle Mat to EOL

This exception indicates what ranged item/location combinations have a lifecycle phase change from Maturity to EOL. The alert is valid for 7 days so you can review item/location combinations that changed from Lifecycle Mat to EOL for the last 7 days.

No Replenishment

This exception indicates the ranged item/location combinations with valid lifecycles that have an unconstrained need but have no system, approved, or exported plan.

No Replenishment Method

This exception indicates the ranged item/location combinations with valid lifecycles and no replenishment method (parameters) assigned to them. The replenishment parameters need to be reviewed for these item/location combinations.

Overstock (current)

This exception indicates the ranged item/location combinations that have surplus quantity based on the next run order (point-in-time replenishment). The surplus



quantity is only considered if it is higher than a defined threshold, which can be specified in units or percentages. The calculation is as follows (the assumption to apply the calculations is that there is a surplus. Otherwise, the alert is not triggered):

Figure D-1 Units Calculation

Tot. Dest. Avail. Units > (RUTL@ Today Units + Overstock (Current) Threshold Units)

Figure D-2 Percentage Calculation

$$Tot. \, Dest. \, Avail. \, Units \\ > \left(RUTL@ \, Today \, Units \right. \\ \left. + \left(RUTL@ \, Today \, Units * \, \frac{Overstock \, (Current) \, Threshold \, \%}{100} \right) \right)$$

Shortage (current)

This exception indicates the ranged item/location combinations that have a deficit quantity based on the next execution order (point-in-time replenishment). The deficit quantity is only considered if it is less than a defined threshold, which can be specified in units or percentages. The calculation is as follows (the assumption to apply the calculations is that there is a deficit. Otherwise, the alert is not triggered):

Figure D-3 Units Calculation

Tot.Dest.Avail.Units < (RUTL@ Today Units - Shortage (Current) Threshold Units)

Figure D-4 Percentage Calculation

$$Tot. Dest. Avail. Units $$ < \left(RUTL@ Today Units - \left(RUTL@ Today Units * \frac{Shortage (Current)Threshold \%}{100} \right) \right) $$$$

Forecast Watch-List

This exception indicates what item/location combinations are in the forecast watch list. This alert allows you to keep track of specific item/location combinations forecast. This exception is not automatically calculated by IPOCS-Lifecycle Allocation and Replenishment. You can include or exclude item/location combinations from the forecast watch list within the Review Alerts workspace. IPOCS-Lifecycle Allocation and Replenishment uses those values to calculate this exception.



New SKU

This exception indicates the new items that were introduced into IPOCS-Lifecycle Allocation and Replenishment. The way IPOCS-Lifecycle Allocation and Replenishment identifies the new items is by using the assortment start date. If the assortment start date is in the future, then the item/location combinations triggers this alert. When the system reaches the assortment start date, then the item/location combinations no longer trigger the alert.

Recent Item Launch

This exception keeps track of ranged item/location combinations that were recently assorted. To trigger the alert, IPOCS-Lifecycle Allocation and Replenishment uses the assortment start date plus a Recent Item Launch X Dur (weeks) parameter. If the assortment start date plus the X weeks defined in the parameter did not reach the system date, then the item/location combinations trigger the alert.



Appendix: Troubleshooting

This appendix provides details that you can use to identify and resolve problems.

Accessing Multiple RPASCE Applications

A user may need to access multiple RPASCE applications, such as MFP, AP, and IPOCS-Demand Forecasting, at the same time. In this case it is necessary to launch each application URL in a separate browser window, in the following way.

Launch one application in a browser window, then launch every other application in an incognito window (Chrome) or in a private window (Firefox). Launching multiple applications using regular browser windows of the same type (for example, Chrome/Firefox) can lead to unexpected UI errors, such as logging out of one application causing a logout across all applications.

