

The software described in this documentation is either no longer supported or is in extended support.  
Oracle recommends that you upgrade to a current supported release.

# Spacewalk for Oracle® Linux

## Installation Guide for Release 2.6

**ORACLE®**

E85212-14  
August 2020

The software described in this documentation is either no longer supported or is in extended support.  
Oracle recommends that you upgrade to a current supported release.

---

## Oracle Legal Notices

Copyright © 2020, Oracle and/or its affiliates.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software" or "commercial computer software documentation" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

### About this document

This document describes how to install Spacewalk 2.6 servers and proxies.

Document generated on: 2020-08-21 (revision: 556)

---

## Table of Contents

Preface .....	v
1 Installing and Upgrading Spacewalk Servers .....	1
1.1 Oracle Linux Requirements .....	1
1.2 Storage Requirements for a Spacewalk Server .....	1
1.3 Networking Requirements for a Spacewalk Server .....	2
1.4 Database Requirements .....	3
1.4.1 Database Sizing Requirements .....	4
1.4.2 Oracle Database Installation Requirements .....	4
1.4.3 Oracle Database Configuration .....	4
1.5 Installing a Spacewalk Server .....	5
1.6 Configuring a Newly Installed Spacewalk Server .....	11
1.6.1 Replacing a Self-Signed SSL Certificate .....	11
1.6.2 Configuring a Spacewalk Administrator and an Initial Organization .....	17
1.6.3 Replacing the jabberd/osa Database on Spacewalk Servers or Spacewalk Proxies .....	17
1.6.4 Configuring a Web Proxy for a Spacewalk Server .....	19
1.7 Upgrading a Spacewalk Server .....	19
1.8 Troubleshooting Spacewalk Server Problems .....	22
1.8.1 Managing Spacewalk Logging .....	23
1.8.2 osa-dispatcher Reports a Certificate Verification Failure .....	23
1.8.3 osa-dispatcher Reports an Invalid Password .....	24
1.8.4 Tomcat Does Not Start .....	24
1.8.5 Tomcat Runs Out of Memory .....	25
2 Installing and Upgrading Spacewalk Proxies .....	27
2.1 Spacewalk Proxy Requirements .....	27
2.2 Storage Requirements for a Spacewalk Proxy .....	27
2.3 Networking Requirements for a Spacewalk Proxy .....	27
2.4 Installing a Spacewalk Proxy .....	29
2.5 Upgrading a Spacewalk Proxy .....	33
2.6 Troubleshooting Spacewalk Proxy Installation Problems .....	34
2.6.1 Clearing the Proxy Cache .....	35
3 Configuring Inter-Server Synchronization for Spacewalk Servers .....	37
3.1 Enabling or Disabling Worker Synchronization Support for a Spacewalk Server .....	37
3.2 Configuring Primary and Worker Spacewalk Servers With the spacewalk-sync-setup Command .....	38
3.3 Configuring a Primary Spacewalk Server by Using the Spacewalk Web Interface .....	38
3.4 Configuring a Worker Spacewalk Server by Using the Spacewalk Web Interface .....	39
3.5 Mapping a Local Organization to an Exported Organization by Using the Spacewalk Web Interface .....	40
3.6 Synchronizing Software Channels on a Spacewalk Worker Server .....	41



## Preface

[Spacewalk for Oracle® Linux: Installation Guide for Release 2.6](#) describes how to install Spacewalk 2.6 servers and proxies.

## Audience

This document is written for system administrators who want to use Spacewalk to manage Oracle Linux systems. It is assumed that readers have a general understanding of the Linux operating system.

## Related Documents

The documentation for this product is available at:

[Spacewalk for Oracle® Linux Documentation](#)

## Conventions

The following text conventions are used in this document:

Convention	Meaning
<b>boldface</b>	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
<code>monospace</code>	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.



## Chapter 1 Installing and Upgrading Spacewalk Servers

This chapter describes how to install and upgrade Spacewalk servers and proxies.

### 1.1 Oracle Linux Requirements

Oracle supports Spacewalk servers that are running on Oracle Linux 6 ([x86\\_64](#)) or Oracle Linux 7 ([x86\\_64](#)). Oracle recommends that you update Oracle Linux with the latest packages that are available on the Oracle Linux yum server.



#### Note

Do not register a Spacewalk server or client with ULN. You can register a Spacewalk server as a client of itself to receive updates.

You should install Oracle Linux 6 or Oracle Linux 7 by using either the **Minimal** or **Basic Server** software set. If you select additional package groups during installation, remove the `jta` package before installing Spacewalk, as this package causes Spacewalk services to fail to start.

Install Spacewalk by using only the packages that are provided by Oracle from the Oracle Linux yum server at <https://yum.oracle.com>.

No third-party package repositories are required to install Spacewalk on Oracle Linux 6 or Oracle Linux 7. All of the required packages are available in the Spacewalk repositories on the Oracle Linux yum server.

### 1.2 Storage Requirements for a Spacewalk Server

A Spacewalk server should have a minimum of 8 GB of memory. If the Spacewalk server also runs the database that stores the Spacewalk repository, this memory requirement is *in addition to* what is required to run the database.

To preserve errata mapping, by default, Spacewalk maintains all available versions of all available packages in each software channel that you configure. As a result, the storage requirements for a Spacewalk server can be significant, depending on the number of major versions and architectures that you choose to support. Typically, the Oracle Linux binary repositories require approximately 60 GB for each combination of Oracle Linux release and architecture. An extra 40 GB is required for source packages and 80 GB is required for Ksplice updates for each combination of Oracle Linux release and architecture.



#### Note

With Spacewalk 2.6, you can reduce the storage requirements considerably by specifying the `--latest` option to the `spacewalk-repo-sync` command, which causes the server to synchronize only the latest packages that are available at the time of synchronization. It does not remove older packages from the channel. If the synchronization interval is large, you might miss a particular version of a package, which can have implications for errata handling, where errata are associated with specific package versions. If errata consistency is important to you, Oracle recommends that you do *not* use `--latest`. However, using `--latest` with a Ksplice channel is an exception because its packages are always cumulative.



### Caution

Packages are never removed from Oracle Linux repositories, so the space that is required for each repository only ever increases. You should actively monitor the available disk space on the Spacewalk server.

A Spacewalk server stores the packages that it hosts under the `/var/satellite/redhat` directory hierarchy. You should plan how best to configure the `/var` file system before you install Spacewalk. For example, if you set up `/var` as an `ext4` or `XFS` file system by using Logical Volume Manager (LVM), you can expand the storage when required.

## 1.3 Networking Requirements for a Spacewalk Server

Prior to installing a Spacewalk server, refer to the following networking requirements and configuration information:

- **Configure a fully qualified domain name**

You must configure a fully qualified domain name (FQDN) for the Spacewalk server. Note that Spacewalk does not consider `.local` and `.localdomain` to be valid domain names.



### Caution

The Spacewalk server and clients *must* be able to resolve the Spacewalk server's FQDN for both forward and reverse lookups in DNS. If these conditions are not met, neither certificate validation nor PXE booting work. In addition, clients cannot register with the Spacewalk server. In particular, a lack of reverse DNS lookup causes Inter-Server Synchronization (ISS) to fail.

Also, verify that the host name that is returned by the `hostname` command and the value of `HOSTNAME` that is defined in the `/etc/hostname` file (for Oracle Linux 7) or the `/etc/sysconfig/network` file (for Oracle Linux 5 and Oracle Linux 6) are identical.

As shown in the following example, the host name must be consistent with the FQDN that is defined for the system in DNS, for both forward and reverse lookups:

```
# hostname
swksvr.mydom.com
# grep HOSTNAME /etc/sysconfig/network
HOSTNAME=swksvr.mydom.com
```

You can also use the `host` command to verify this information on systems that are running Oracle Linux 5 and Oracle Linux 6:

```
# host swksvr.mydom.com
swksvr.mydom.com has address 192.168.1.3
# host 192.168.1.3
3.1.168.192.in-addr.arpa domain name pointer swksvr.mydom.com.
```

You will need to edit the `/etc/hosts` file and configure the actual IP address for the FQDN and host name, but not the loopback address (`127.0.0.1`), as shown in the following example:

```
127.0.0.1    localhost localhost.localdomain localhost4 localhost4.localdomain4
::1        localhost localhost.localdomain localhost6 localhost6.localdomain6
192.168.1.3 swksvr.mydom.com swksvr
```

- **Port numbers for a Spacewalk server**

The following table describes the network ports that a Spacewalk server uses, depending on its configuration.

Port/ Protocol	Direction	Purpose
69/udp	Inbound	TFTP (if PXE provisioning support is required)
80/tcp	Inbound and outbound	HTTP access
443/tcp	Inbound and outbound	HTTPS access
5222/tcp	Inbound	Push support to Spacewalk clients (if required)
5269/tcp	Inbound	Push support to Spacewalk proxies (if required)

- **Configure network time synchronization**

Configure the Spacewalk server, proxies, and clients to use a network time synchronization mechanism such as the Network Time Protocol (NTP) or the Precision Time Protocol (PTP). In order to establish a Secure Socket Layer (SSL) based connection, Spacewalk requires that the system time on these systems be consistent to within 120 seconds. Furthermore, if the system times (corrected for time zone difference) of the server and a client differ by more than 120 seconds, authentication of the `osad` service on the client by the `jabberd` service on the server fails.

For more information, see [Oracle® Linux 6: Administrator's Guide](#) or [Oracle® Linux 7: Administrator's Guide](#).

## 1.4 Database Requirements

You can use the following database solutions to store Spacewalk data:

- Oracle Database
- Oracle Database Express Edition (Oracle Database XE)
- PostgreSQL

However, note that Oracle supports *only* Oracle Database for use with Spacewalk and provides a restricted-use license for the use of Oracle Database 12c Enterprise Edition for Oracle Linux support customers. For more information, see [Oracle® Linux 6: Licensing Information User Manual](#) or [Oracle® Linux 7: Licensing Information User Manual](#).



### Note

Oracle Database XE (Oracle Database Express Edition) and PostgreSQL are not supported and their use is not described in this document. Note also that Oracle does not provide any tools for migrating from an unsupported database.

## 1.4.1 Database Sizing Requirements

When determining the amount of space the Spacewalk database requires, be sure to include sizing estimates for the following in your overall calculation: number of client systems that will be served by the Spacewalk server, number of channels allocated to each client system, as well as the number of packages that each channel will contain.

To more accurately determine how much space the Spacewalk database requires, use the following calculation:

- 250 KiB per client system.
- 500 KiB per channel, plus an additional 230 KiB per package in the channel (a channel with 5000 packages would require 1.1 GiB).

For example, if you have a large Spacewalk server that is serving 10,000 systems, and each system has four channels that contain 12,000 packages per-channel, then 2.5 GiB would be required for the clients and 11 GiB would be required for the channels.

## 1.4.2 Oracle Database Installation Requirements

You must install an Oracle Database server and make this server available *before* you install Spacewalk.

Supported Oracle Database releases include the following:

- Oracle Database 12c.

You can download the software from the Oracle Technology Network (OTN) at <https://www.oracle.com/technetwork/database/enterprise-edition/downloads/index.html>.

- Oracle Database 11gR2, release 11.2.0.3 or later (requires an active Oracle Database license).

To obtain the correct Oracle Database 11gR2 release, download the software from My Oracle Support (MOS) at <https://support.oracle.com>.

Consult with your Oracle database administrator for specific details about any prerequisite tasks, as well as specific installation options for your environment. For complete instructions, refer to the Oracle Database documentation at <https://docs.oracle.com/en/database/database.html>.

## 1.4.3 Oracle Database Configuration

The following are general guidelines for configuring Oracle Database. These steps can be performed during or after the installation. Consult with your Oracle database administrator to obtain any additional configuration instructions for your particular environment.

- The database must use the [AL32UTF8](#) character set that supports Unicode.



### Note

You can select the [AL32UTF8](#) character set if you select **Advanced install** in the Installation GUI, but not if you select the **Typical install** option.

If you installed the 12cR2 version of Oracle Database, the [AL32UTF8](#) character set is the default.

- The database must have a Spacewalk user. You create this user by using SQL\*Plus commands, as described in the steps that follow. You can use any name that you choose for the Spacewalk user.

For example, you could create a user named `spacewalk` for Oracle Database 11gR2. For Oracle Database 12c, if the database is a pluggable database, you might create a user named `c##spacewalk`. Note that if the database is not a pluggable database, the `c##` prefix does not need to be part of the user name.

- If several Spacewalk servers will share the same database server, you must create a separate Spacewalk user for each server. For example, if you intend to set up two Spacewalk servers that share the same database, you could create two users for Oracle Database 11gR2 with the following names: `spacewalk` and `spacewalk2`. For Oracle Database 12c, you could create the `c##spacewalk` and `c##spacewalk2` users.
- The Spacewalk user must have the `CONNECT` and `RESOURCE` roles.
- The Spacewalk user must have the following system privileges:
  - `ALTER SESSION`
  - `CREATE SYNONYM`
  - `CREATE TABLE`
  - `CREATE TRIGGER`
  - `CREATE VIEW`
  - `UNLIMITED TABLESPACE`

## Creating a Spacewalk User

Create a Spacewalk user as follows:

1. Log in to the system as a database administrator (typically, `SYS` or `SYSDBA`) on the database server.

```
$ sqlplus / as SYSDBA
```

2. Set up the Spacewalk user by running the following SQL\*Plus commands:

```
SQL> create user sw_user identified by sw_passwd;  
SQL> grant connect,resource to sw_user;  
SQL> grant alter session, create synonym, create table, create trigger, create view to sw_user;  
SQL> grant unlimited tablespace to sw_user;
```

where `sw_user` and `sw_passwd` are the user name and password that you will use to administer Spacewalk.

Repeat these steps for each Spacewalk user that you need to set up.

## 1.5 Installing a Spacewalk Server

Before you install the Spacewalk server software, you must do the following:

- Install the Oracle Database and ensure that it is up and running.

For specific instructions on installing and configuring Oracle Database, consult with your Oracle database administrator. See also the product documentation at <https://docs.oracle.com/en/database/database.html>.

## Installing a Spacewalk Server

- Meet all of the requirements and perform any of the prerequisite tasks that are described in this document, as well as those that are specified in the product documentation.

In particular, make sure you have met the following networking requirements:

Configure a FQDN for the Spacewalk server, as described in [Section 1.3, “Networking Requirements for a Spacewalk Server”](#). The `/etc/hosts` file should have an FQDN entry for the Spacewalk server.



### Caution

The Spacewalk server and clients *must* be able to resolve the Spacewalk server's FQDN for both forward and reverse lookups in DNS. If these conditions are not met, neither certificate validation nor PXE booting work. In addition, clients cannot register with the Spacewalk server. In particular, a lack of reverse DNS lookup on the Spacewalk server or the clients causes Inter-Server Synchronization (ISS) to fail.

Follow these steps to install the Spacewalk server software:

1. Install Oracle Instant Client release 11.2.0.4 or later.
  - a. Download the following Instant Client packages. You can find out more about the Instant Client from:

<https://www.oracle.com/database/technologies/instant-client.html>

- Instant Client Package (Basic)
- Instant Client Package (SQL\*Plus)



### Note

Do not download the packages for release 12.1 or later, as these releases are not supported.

- b. Install the Instant Client packages.

```
# rpm -ihv oracle-instantclient11.2-basic-11.2.0.4.0-1.x86_64.rpm \  
oracle-instantclient11.2-sqlplus-11.2.0.4.0-1.x86_64.rpm
```

- c. Add the library path to `ldconfig`.

```
# echo /usr/lib/oracle/11.2/client64/lib > /etc/ld.so.conf.d/oracle-instantclient11.2.conf  
# ldconfig
```



### Caution

The Spacewalk server configuration fails if the Instant Client is missing. Oracle recommends that you install the latest 11.2.0.4 release of the Instant Client.

2. Ensure that the `jta` package is not installed and prevent it from being installed when you install Spacewalk.

Check whether the `jta` package is installed as followed:

```
# yum list installed | grep jta
```

To remove the `jta` package:

```
# yum remove jta
```

To prevent the `jta` package from being installed later, do one of the following:

- Disable the Oracle Linux 6 or Oracle Linux 7 `addons` channels (`[ol6_addons]` or `[ol7_addons]`).
- Add the `jta` package to the `exclude` directive in the `/etc/yum.conf` file as follows:

```
exclude=jta*
```

### 3. Configure the system firewall.

For Oracle Linux 6, you would configure the system firewall as follows:

```
# iptables -I INPUT -p udp -m udp --dport 69 -j ACCEPT
# iptables -I INPUT -p tcp -m state --state NEW -m tcp --dport 80 -j ACCEPT
# iptables -I INPUT -p tcp -m state --state NEW -m tcp --dport 443 -j ACCEPT
# iptables -I INPUT -p tcp -m state --state NEW -m tcp --dport 5222 -j ACCEPT
# iptables -I INPUT -p tcp -m state --state NEW -m tcp --dport 5269 -j ACCEPT
# iptables -I OUTPUT -p tcp -m state --state NEW -m tcp --dport 80 -j ACCEPT
# iptables -I OUTPUT -p tcp -m state --state NEW -m tcp --dport 443 -j ACCEPT
# service iptables save
```

For Oracle Linux 7, you would configure the system firewall as follows:

```
# firewall-cmd --permanent --add-port=69/udp
# firewall-cmd --permanent --add-port=80/tcp
# firewall-cmd --permanent --add-port=443/tcp
# firewall-cmd --permanent --add-port=5222/tcp
# firewall-cmd --permanent --add-port=5269/tcp
# firewall-cmd --reload
```

### 4. Enable access to the repositories that contain the Spacewalk Server and dependent packages on the Oracle Linux yum server at <https://yum.oracle.com>.

For Oracle Linux 6, do the following:

- a. Ensure that your system is up to date and that you have transitioned to use the modular yum repository configuration by installing the `oraclelinux-release-el6` package and running the `/usr/bin/ol_yum_configure.sh` script.

```
# yum install oraclelinux-release-el6
```

## Installing a Spacewalk Server

---

```
# /usr/bin/ol_yum_configure.sh
```

- b. Install the `oracle-spacewalk-server-release-el6` release package to install appropriate yum repository configuration.

```
# yum install oracle-spacewalk-server-release-el6
```

- c. Disable the disable `ol6_spacewalk27_client` and `ol6_spacewalk27_server` repositories:

```
# yum-config-manager --disable ol6_spacewalk27_server ol6_spacewalk27_client
```

- d. Enable the `ol6_spacewalk26_server` and `ol6_spacewalk26_client` repositories in the repository configuration file:

```
# yum-config-manager --enable ol6_spacewalk26_server ol6_spacewalk26_client
```

For Oracle Linux 7, do the following:

- a. Install the `oraclelinux-release-el7` package and run the `/usr/bin/ol_yum_configure.sh` script:

```
# yum install oraclelinux-release-el7  
# /usr/bin/ol_yum_configure.sh
```

- b. Install the `oracle-spacewalk-server-release-el7` release package to install appropriate yum repository configuration:

```
# yum install oracle-spacewalk-server-release-el7
```

- c. Disable the disable `ol7_spacewalk27_server` and `ol7_spacewalk27_client` repositories:

```
# yum-config-manager --disable ol7_spacewalk27_server ol7_spacewalk27_client
```

- d. Enable the `ol7_spacewalk26_server` and `ol7_spacewalk26_client` repositories in the repository configuration file.

```
# yum-config-manager --enable ol7_spacewalk26_server ol7_spacewalk26_client
```

- e. Enable the `ol7_optional_latest` repository, which is included in the `oraclelinux-release-el7` package:

```
# yum-config-manager --enable ol7_optional_latest
```

5. Install the Spacewalk Server packages that are configured to use Oracle Database.

```
# yum install spacewalk-oracle
```



### Note

As part of the Spacewalk installation process, all of the Oracle Linux yum server configuration, as well as ULN configuration, is disabled because Spacewalk handles this configuration going forward.

If you need to re-enable yum repository configuration after an installation, but *before* you have configured any repositories in Spacewalk, you can temporarily

rename any affected yum repository configuration files to enable them again, for example:

```
# mv /etc/yum.repos.d/oracle-linux-ol7.repo.rpmsave /etc/yum.repos.d/oracle-linux-ol7
```

Remember to disable the yum repository configuration files again after you have configured repositories within Spacewalk.

6. (Optional) Install the `spacecmd` and `spacewalk-utils` packages if you want to use commands such as `spacecmd`, `spacewalk-common-channels`, `spacewalk-hostname-rename`, and `spacewalk-sync-setup`.

```
# yum install spacecmd spacewalk-utils
```

<code>spacecmd</code>	Enables you to administer Spacewalk from the command line. You can manage activation keys, configuration channels, kickstarts, software channels, systems, and users.
<code>spacewalk-common-channels</code>	Enables you to configure the software channels, public yum repositories, GNU Privacy Guard (GPG) keys, and activation keys for Oracle Linux from the command line.
<code>spacewalk-hostname-rename</code>	Enables you to regenerate the SSL certificate if you change the system's host name.
<code>spacewalk-sync-setup</code>	Enables you configure a primary-worker (master-slave) relationship between two Spacewalk servers that you want to use in ISS configuration. See <a href="#">Chapter 3, Configuring Inter-Server Synchronization for Spacewalk Servers</a> .



#### Note

You can safely ignore any SELinux `restorecon` messages that are displayed when the packages are installed.

Alternatively, you can install the additional packages at a later time if you register the Spacewalk server as a client of itself and then subscribe it to the appropriate Spacewalk Server 2.6 channel.

7. Configure Spacewalk to use the Oracle Database by running the `spacewalk-setup --external-oracle` command.

The `--external-oracle` option is used because all Oracle databases are external to Spacewalk's setup, regardless of whether the database is running on the same system.

The following example shows how to run the command to initiate an interactive session where you provide the information that is required to complete the Spacewalk setup.

When configuring Spacewalk, keep the following key points in mind:

- The `sw_user` and `sw_passwd` are the Spacewalk user name and password that you specified when you configured the Oracle Database, per [Section 1.4.3, "Oracle Database Configuration"](#).
- The value that is expected for the database service name (SID) is the global database name and *not* the value of `ORACLE_SID`.
- The `Database hostname [localhost]?` prompt is bypassed if the setup tool detects that the Oracle Database and Spacewalk are co-located on the same host. You are only prompted for this information during the setup if the Oracle Database is on a host other than the host on which Spacewalk is installed.
- The value that you specify for the Organization Unit must be the same as the FQDN of the server in DNS. Also, this value must match the system's host name.

```
# spacewalk-setup --external-oracle
* Setting up SELinux..
* Setting up Oracle environment.
* Setting up database.
** Database: Setting up database connection for Oracle backend.
Global Database Name or SID (requires tnsnames.ora)? company.mydom.com
Database hostname [localhost]? spacewalk-db.mydom.com
Username? sw_user
Password? sw_passwd
Database: Testing database connection.
** Database: Populating database.
*** Progress: #####
* Configuring tomcat.
* Setting up users and groups.
** GPG: Initializing GPG and importing key.
** GPG: Creating /root/.gnupg directory
You must enter an email address.
Admin Email Address? my.email@mydom.com
* Performing initial configuration.
* Activating Spacewalk.
** Loading Spacewalk Certificate.
** Verifying certificate locally.
** Activating Spacewalk.
* Enabling Monitoring.
* Configuring apache SSL virtual host.
Should setup configure apache's default ssl server for you
(saves original ssl.conf) [Y]? y
** /etc/httpd/conf.d/ssl.conf has been backed up to ssl.conf-swsave
* Configuring jabberd.
* Creating SSL certificates.
CA certificate password? cert_passwd
Re-enter CA certificate password? cert_passwd
Organization? Company Demo
Organization Unit [swksvr.mydom.com]? swksvr.mydom.com
Email Address [your.email@domain.com]? my.email@mydom.com
City? Redwood Shores
```

## Configuring a Newly Installed Spacewalk Server

```
State? CA
Country code (Examples: "US", "JP", "IN", or type "?" to see a list)? US
** SSL: Generating CA certificate.
** SSL: Deploying CA certificate.
** SSL: Generating server certificate.
** SSL: Storing SSL certificates.
* Deploying configuration files.
* Update configuration in database.
* Setting up Cobbler..
Cobbler requires tftp and xinetd services be turned on for PXE provisioning functionality.
Enable these services [Y]? y
* Restarting services.
Installation complete.
Visit https://swksvr.mydom.com to create the Spacewalk administrator account.
```

8. Verify that the Spacewalk services are running.

```
# /usr/sbin/spacewalk-service status
router (pid 5097) is running...
sm (pid 5105) is running...
c2s (pid 5113) is running...
s2s (pid 5121) is running...
tomcat6 (pid 5193) is running... [ OK ]
httpd (pid 5303) is running...
osa-dispatcher (pid 5331) is running...
rhn-search is running (5353).
cobblerd (pid 5392) is running...
RHN Taskomatic is running (5419).
```

The process IDs on your system are likely to be different from those shown in this example.

9. Note the Spacewalk server URL that is mentioned in the output.

You will need the Spacewalk server URL to create the main Spacewalk administrator account and an initial organization, as described in [Section 1.6.2, “Configuring a Spacewalk Administrator and an Initial Organization”](#).

After completing the Spacewalk server installation, perform any required or optional post-installation tasks. For instructions, see [Section 1.6, “Configuring a Newly Installed Spacewalk Server”](#),

## 1.6 Configuring a Newly Installed Spacewalk Server

After installing a Spacewalk server, perform the following tasks. Some tasks, although recommended, are optional.

### 1.6.1 Replacing a Self-Signed SSL Certificate

When you install a Spacewalk server or Spacewalk proxy, you can create a self-signed SSL certificate to use with Spacewalk clients. The following procedure describes how to replace self-signed certificates or expired CA-signed certificates with certificates that have been signed by a Certificate Authority (CA).

You can use certificates for individual Spacewalk servers or Spacewalk proxies, or wildcard certificates for all Spacewalk servers or Spacewalk proxies in the domains that the wildcard certificates cover.

Replace the existing certificate on a Spacewalk server or Spacewalk proxy as follows:

1. Create a backup of the system's existing SSL configuration.

```
# tar -cvf SSLconfig.tar \
/etc/httpd/conf/ssl.* \
/etc/pki/spacewalk/jabberd/server.pem \
```

```
/root/ssl-build \  
/var/www/html/pub
```

2. Obtain a server certificate by using one of the following methods:

- Obtain a server certificate from a CA and install this certificate in the SSL build hierarchy on the system as follows:
  - a. Send the Certificate Signing Request (CSR) file `/root/ssl-build/swksvr/server.csr` to the CA.



**Note**

`swksvr` is the name of the Spacewalk server or Spacewalk proxy that you used to set up the existing SSL configuration, with the domain name removed.

After validating your request, the CA returns a signed server certificate file.

- b. Create a backup of the signed server certificate file.
- c. If necessary, convert the certificate to Privacy Enhanced Mail (PEM) format.

A PEM-formatted certificate file is a text file that contains a Base64 encoded certificate section between the BEGIN/END markers, as shown in the following output:

```
-----BEGIN CERTIFICATE-----  
MIIF7DCCBNSgAwIBAgIQbsx6pacDIAm4zrz06VLukTANBgkqhkiG9w0BAQUFADCB  
...  
Rs/iGAZeqa6ogZpHFt4MKGwlJ7net4RYxh84HqTEy2Y=
```

```
-----END CERTIFICATE-----
```

A PEM-formatted certificate file usually has a file extension of `.crt` or `.pem`. However, binary DER-formatted certificate files also sometimes have a `.crt` extension.

A DER-formatted certificate file is a binary file that usually has a file extension of `.cer` or `.der`, but can also have the extension `.cert` or `.crt`.

Test whether a certificate file is in DER format by typing the following command:

```
# openssl x509 -inform der -text -in certificate_file
```

- d. If a certificate file is in DER format, convert the file to a PEM-formatted certificate file by typing the following command:

```
# openssl x509 -inform der -in server.cer -out server.pem
```

- e. If a PEM-formatted certificate file was not generated on a UNIX or a Linux system, the file might contain `^M` carriage return characters. Use either of the following commands to remove these characters:

```
# sed -i -e 's/\r//' server.pem
```

```
# dos2unix server.pem
```

Note that the `dos2unix` command is available in the `dos2unix` package.

- f. Copy the PEM-formatted server certificate file to `/root/ssl-build/swksvr/server.crt`.

```
# cp server.pem /root/ssl-build/swksvr/server.crt
```

- Obtain a server certificate using an external tool as follows:
  - a. Obtain both the private key and the signed certificate from the external tool in PEM format, then copy both to `/root/ssl-build/swksvr`.
  - b. If the private key has an existing password, remove it, then replace the key as follows:

```
# openssl rsa -in keyfilewithpasswd.key -out /root/ssl-build/swksvr/server.key
```

This step ensures that the Spacewalk services can start unattended.

## Replacing a Self-Signed SSL Certificate

3. Add the CA public certificate to the `/root/ssl-build` directory as the `RHN-ORG-TRUSTED-SSL-CERT` file by using one of the following methods:

- If available, obtain the CA chain certificate from the CA that issued the server certificate. Copy this certificate file to `/root/ssl-build/RHN-ORG-TRUSTED-SSL-CERT`:

```
# cp ca_chain.pem /root/ssl-build/RHN-ORG-TRUSTED-SSL-CERT
```

- If the CA chain certificate is not available from the issuing CA, create the CA chain certificate as follows:
  - a. Obtain the root CA public certificate and the intermediate CA public certificates from the issuing CA.
  - b. Concatenate the chain of CA public certificate files starting with the public certificate file of the CA that issued your server certificate down to the public certificate file of the root CA to `/root/ssl-build/RHN-ORG-TRUSTED-SSL-CERT`:

```
# cat intermediate_ca.pem root_ca.pem > /root/ssl-build/RHN-ORG-TRUSTED-SSL-CERT
```

where `intermediate_ca.pem` is the public certificate file of the intermediate CA that signed your server certificate, and `root_ca.pem` is the public certificate file of the root CA that signed the intermediate certificate.



### Caution

The order in which the public certificates in a CA chain certificate file appear is critical. The CA chain certificate does not work if its component certificates are not in the correct order.

- If a root CA signed your server certificate directly (which is unlikely nowadays), only the public certificate of the root CA is required. Copy the root CA public certificate file to `/root/ssl-build/RHN-ORG-TRUSTED-SSL-CERT`:

```
# cp root_ca.pem /root/ssl-build/RHN-ORG-TRUSTED-SSL-CERT
```

4. Validate the server certificate against the CA public certificate by typing the following command:

```
# openssl verify -CAfile /root/ssl-build/RHN-ORG-TRUSTED-SSL-CERT \  
/root/ssl-build/swksvr/server.crt  
/root/ssl-build/swksvr/server.crt: OK
```

If the command returns an error, verify that you correctly created `RHN-ORG-TRUSTED-SSL-CERT` and also verify that the date and time on the server are configured correctly.

5. Store the CA public certificate in the Spacewalk database so that it is available for use in provisioning client systems:

```
# rhn-ssl-dbstore -v --ca-cert=/root/ssl-build/RHN-ORG-TRUSTED-SSL-CERT  
Public CA SSL certificate: /root/ssl-build/RHN-ORG-TRUSTED-SSL-CERT
```

If the command returns an error, run the command again, specifying a higher level of debugging, such as `-vvv`, to gather more information about the problem.

## Replacing a Self-Signed SSL Certificate

### 6. Generate and install the web server SSL package as follows:

#### a. Generate the web server SSL package.

```
# rhn-ssl-tool --gen-server --rpm-only --dir /root/ssl-build
...working...

Generating web server's SSL key pair/set RPM:
  /root/ssl-build/swksvr/rhn-org-httpd-ssl-key-pair-swksvr-1.0-rev.src.rpm
  /root/ssl-build/swksvr/rhn-org-httpd-ssl-key-pair-swksvr-1.0-rev.noarch.rpm

The most current Spacewalk Proxy Server installation process against RHN hosted
requires the upload of an SSL tar archive that contains the CA SSL public
certificate and the web server's key set.

Generating the web server's SSL key set and CA SSL public certificate archive:
  /root/ssl-build/swksvr/rhn-org-httpd-ssl-archive-swksvr-1.0-rev.tar

Deploy the server's SSL key pair/set RPM:
(NOTE: the Red Hat Satellite or Proxy installers may do this step for you.)
The "noarch" RPM needs to be deployed to the machine working as a
web server, or Red Hat Satellite, or Spacewalk Proxy.
Presumably 'swksvr.mydom.com'.
```

Run the `rpm` command to list the files that the packages install.

```
# rpm -qlp /root/ssl-build/swksvr/rhn-org-httpd-ssl-key-pair-swksvr-1.0-rev.src.rpm
rhn-org-httpd-ssl-key-pair-swksvr-1.0.tar.gz
rhn-org-httpd-ssl-key-pair-swksvr.spec
# rpm -qlp /root/ssl-build/swksvr/rhn-org-httpd-ssl-key-pair-swksvr-1.0-rev.noarch.rpm
/etc/httpd/conf/ssl.crt/server.crt
/etc/httpd/conf/ssl.csr/server.csr
/etc/httpd/conf/ssl.key/server.key
/etc/pki/spacewalk/jabberd/server.pem
```

#### b. Install the web server SSL `noarch` package.

```
# rpm -Uhv /root/ssl-build/swksvr/rhn-org-httpd-ssl-key-pair-swksvr-1.0-rev.noarch.rpm
Preparing... ##### [100%]
 1:rhn-org-httpd-ssl-key-p##### [100%]
```

### 7. Generate the public CA certificate package and make both the package and the CA public certificate file available to clients.

#### a. Generate the public CA certificate package.

```
# rhn-ssl-tool --gen-ca --dir=/root/ssl-build --rpm-only
...working...

Generating CA public certificate RPM:
  /root/ssl-build/rhn-org-trusted-ssl-cert-1.0-rev.src.rpm
  /root/ssl-build/rhn-org-trusted-ssl-cert-1.0-rev.noarch.rpm

Make the public CA certificate publicly available:
(NOTE: the Red Hat Satellite or Proxy installers may do this step for you.)
The "noarch" RPM and raw CA certificate can be made publicly accessible
by copying it to the /var/www/html/pub directory of your Red Hat Satellite or
Proxy server.
```

Run the `rpm` command to list the files that the packages install.

```
# rpm -qlp /root/ssl-build/rhn-org-trusted-ssl-cert-1.0-rev.src.rpm
```

## Replacing a Self-Signed SSL Certificate

```
rhn-org-trusted-ssl-cert-1.0.tar.gz
rhn-org-trusted-ssl-cert.spec
# rpm -qlp /root/ssl-build/rhn-org-trusted-ssl-cert-1.0-rev.noarch.rpm
/usr/share/rhn/RHN-ORG-TRUSTED-SSL-CERT
```

- b. If a Spacewalk server or proxy is also configured as a client, install the public CA certificate `noarch` package on this system.

```
# rpm -Uhv /root/ssl-build/pub/rhn-org-trusted-ssl-cert-1.0-rev.noarch.rpm
Preparing... ##### [100%]
 1:rhn-org-trusted-ssl-cer##### [100%]
```

The public CA certificate is installed as `/usr/share/rhn/RHN-ORG-TRUSTED-SSL-CERT`.

- c. Copy the `rhn-org-trusted-ssl-cert-1.0-rev.noarch.rpm` package and CA public certificate file to `/var/www/html/pub` for access by clients.

```
# cp /root/ssl-build/rhn-org-trusted-ssl-cert-1.0-rev.noarch.rpm /var/www/html/pub
# cp /root/ssl-build/RHN-ORG-TRUSTED-SSL-CERT /var/www/html/pub
```



### Note

If you do not copy the updated `RHN-ORG-TRUSTED-SSL-CERT` to `/var/www/html/pub`, the `osa-dispatcher` service fails to start.

Verify that the installed copies of `RHN-ORG-TRUSTED-SSL-CERT` are identical by comparing their digest values as follows:

```
# shasum /root/ssl-build/RHN-ORG-TRUSTED-SSL-CERT \
/usr/share/rhn/RHN-ORG-TRUSTED-SSL-CERT \
/var/www/html/pub/RHN-ORG-TRUSTED-SSL-CERT
74380a372bfa55d8ab7579bf01502c874b8aae84
    /root/ssl-build/RHN-ORG-TRUSTED-SSL-CERT
74380a372bfa55d8ab7579bf01502c874b8aae84
    /usr/share/rhn/RHN-ORG-TRUSTED-SSL-CERT
74380a372bfa55d8ab7579bf01502c874b8aae84
    /var/www/html/pub/RHN-ORG-TRUSTED-SSL-CERT
```

The `rhn-org-trusted-ssl-cert-1.0-rev.src.rpm` package is usually not made available to clients.

8. On a Spacewalk server, stop the Spacewalk services, clear the `jabberd` database, then restart Spacewalk.

```
# /usr/sbin/spacewalk-service stop
# rm -Rf /var/lib/jabberd/db/*
# /usr/sbin/spacewalk-service start
```

On a Spacewalk proxy, restart the Spacewalk proxy services.

```
# /usr/sbin/rhn-proxy restart
```

9. On the remaining Spacewalk clients, download and install the public CA certificate package.

```
# wget https://swksvr.mydom.com/pub/rhn-org-trusted-ssl-cert-1.0-rev.noarch.rpm
--2015-06-05 15:15:44-- https://swksvr.mydom.com/pub/rhn-org-trusted-ssl-cert-1.0-rev.noarch.rpm
Resolving swksvr.mydom.com... 192.168.1.3
Connecting to swksvr.mydom.com|192.168.1.3|:443... connected.
HTTP request sent, awaiting response... 200 OK
Length: 4840 (4.7K) [application/x-rpm]
Saving to: "rhn-org-trusted-ssl-cert-1.0-2.noarch.rpm"
```

```
100%[=====] 4,840 --.-K/s in 0s
2015-06-05 15:15:44 (57.5 MB/s) - "rhn-org-trusted-ssl-cert-1.0-rev.noarch.rpm" saved [4840/4840]
# rpm -Uhv /root/ssl-build/pub/rhn-org-trusted-ssl-cert-1.0-rev.noarch.rpm
Preparing... ##### [100%]
 1:rhn-org-trusted-ssl-cer##### [100%]
```



#### Note

If you subsequently replace the server certificate because it is revoked or expired, you do not need to update the public CA certificate on the clients unless you change the CA that signs the server certificate.

## 1.6.2 Configuring a Spacewalk Administrator and an Initial Organization

After installing a Spacewalk server and connecting to the Oracle Database, you must create the main Spacewalk administrator account and an initial organization. Follow these steps:

1. Point a browser at the URL that is specified in the Step of 7 of in [Section 1.5, "Installing a Spacewalk Server"](#).

For example, the server that is shown in the following output ([swksvr.mydom.com](https://swksvr.mydom.com)) matches the host name that you provided when you configured the Oracle Database:

```
Installation complete.
Visit https://swksvr.mydom.com to create the Spacewalk administrator account.
```

Because Spacewalk uses a self-signed certificate by default, you will be prompted to trust this certificate the first time you launch the Spacewalk user interface by using a web browser, unless you have replaced the SSL certificate. See [Section 1.6.1, "Replacing a Self-Signed SSL Certificate"](#).

2. On the Create Organization page (located under Create First User), enter the required values in the appropriate fields.
3. Accept any of the default values that are provided for you.
4. If you are prompted to provide additional configuration details, click the link to be taken to a General Configuration page, where you can enter any additionally required values.
5. Save the changes and then log in to the Spacewalk web interface.

The Overview page for the Spacewalk web interface is displayed

See *About the Spacewalk Web Interface* in [Spacewalk for Oracle® Linux: Client Life Cycle Management Guide for Release 2.6](#).

## 1.6.3 Replacing the jabberd/osa Database on Spacewalk Servers or Spacewalk Proxies

You might need to replace the `jabberd/osa` database on a Spacewalk server or proxy if you encounter any of the following errors:

- OSA status shows "offline as of unknown" for client servers.
- `osa-dispatcher` errors in `/var/log/mesages` on the Spacewalk server or proxy.

- "db: corruption detected! close all jabberd processes and run db\_recover" message in `/var/log/messages` on the Spacewalk server or proxy.

This problem occurs because the default Berkeley database format does not support transactions, and as a result, can become damaged when too many clients attempt to update at the same time. Switching to SQLite provides transactional support for the `jabberd` database and can handle significantly more downstream clients.

Follow these steps to resolve the problem:

1. Stop the `osa-dispatcher` and `jabberd` services.

If you are running Oracle Linux 7, use the `systemctl` command:

```
# systemctl stop osa-dispatcher
# systemctl stop jabberd
```

If you are running Oracle Linux 6, use the `service` command:

```
# service osa-dispatcher stop
# service jabberd stop
```

2. Edit the `/etc/jabberd/sm.xml` file and change "`<driver>db</driver>`" to "`<driver>sqlite</driver>`".
3. Edit the `/etc/jabberd/c2s.xml` file and change "`<module>db</module>`" to "`<module>sqlite</module>`".
4. Create the SQLite database as follows:

```
# sqlite3 /var/lib/jabberd/db/sqlite.db < /usr/share/jabberd/db-setup.sqlite
# chown jabber:jabber /var/lib/jabberd/db/sqlite.db
```

5. Start the `jabberd` and `osa-dispatcher` services again.

For Oracle Linux 7, type the following commands:

```
# systemctl start jabberd
# systemctl start osa-dispatcher
```

For Oracle Linux 6, type the following commands:

```
# service jabberd start
# service osa-dispatcher start
```

6. Check `/var/log/messages` to ensure that SQLite is being used.

```
# cat /var/log/messages | grep sqlite
Feb 24 12:46:18 sw24 jabberd/sm[15196]: loading 'sqlite' storage module
Feb 24 12:46:18 sw24 jabberd/sm[15196]: initialised storage driver 'sqlite'
Feb 24 12:46:18 sw24 c2s: Fri Feb 24 12:46:18 2017 [info] loading 'sqlite' authreg module
Feb 24 12:46:18 sw24 c2s: Fri Feb 24 12:46:18 2017 [notice] initialized auth module 'sqlite'
Feb 24 12:46:18 sw24 jabberd/c2s[15199]: [sirius.lot209.com] configured; realm=, authreg=sqlite, registr
```

7. Reset and restart the `osad` service on the client servers.

If you previously registered client servers and installed the `osad` service on those servers, you will need to remove the `osad-auth.conf` file and then restart the `osad` service on these systems after the database has been switched.

For Oracle Linux 7, type the following commands:

```
# systemctl stop osad
# rm -f /etc/sysconfig/rhn/osad-auth.conf
# systemctl start osad
```

For Oracle Linux 6, type the following commands:

```
# service osad stop
# rm -f /etc/sysconfig/rhn/osad-auth.conf
# service osad start
```

Running these commands triggers the `osad` client on each server to re-authenticate to `jabberd`.

## 1.6.4 Configuring a Web Proxy for a Spacewalk Server

If the Spacewalk server needs to connect through a web proxy, you can configure the web proxy by using one of the following methods *after* you have installed Spacewalk:

- Edit the `/etc/rhn/rhn.conf` file and provide the web proxy configuration settings for the `server.satellite.http_proxy`, `server.satellite.http_proxy_username`, and `server.satellite.http_proxy_password` parameters, as shown in the following example:

```
server.satellite.http_proxy = webproxy.mydom.com:80
server.satellite.http_proxy_username = another
server.satellite.http_proxy_password = examplepass
```

- In the Spacewalk web interface, do the following:
  1. Select the **Admin** tab, then **Spacewalk Configuration**, and then **General**.
  2. Provide the web proxy configuration settings in the fields **HTTP proxy**, **HTTP proxy username**, **HTTP proxy password**, and **Confirm HTTP proxy password**, and then click **Update**.

## 1.7 Upgrading a Spacewalk Server

Upgrade a Spacewalk 2.2 or 2.4 server to Spacewalk 2.6 as follows:

1. Back up the all of the Spacewalk configuration files in the following directories:
  - `/etc/jabberd`
  - `/etc/rhn`
  - `/etc/sysconfig/rhn`
  - Server SSL build directory, typically `/root/ssl-build`

For example, you could use the `tar` command to create a backup as follows:

```
# tar -cvf preSWupgrade.tar /etc/jabberd /etc/rhn /etc/sysconfig/rhn /root/ssl-build
```

2. Back up the Spacewalk database.

For more information about using the Recovery Manager (RMAN) to create a backup, refer to the following documents:

- [Getting Started with RMAN](#) (Oracle Database 11gR2)

- [Getting Started with RMAN](#) (Oracle Database 12c)
3. Disable access to the Spacewalk 2.2 or 2.4 Server packages and enable access to the Spacewalk 2.6 Server packages.
    - If the Spacewalk server is registered as a client of itself, do the following:
      - a. Create a Spacewalk Server 2.6 channel as a child of the Oracle Linux 6 base channel.
      - b. Create a Spacewalk Server 2.6 repository that accesses the Spacewalk Server 2.6 channel on the Oracle Linux yum server ([https://yum.oracle.com/repo/OracleLinux/OL6/spacewalk26/server/x86\\_64/](https://yum.oracle.com/repo/OracleLinux/OL6/spacewalk26/server/x86_64/)), using the same GPG settings as for Oracle Linux 6.
      - c. Associate the Spacewalk Server 2.6 repository with the Spacewalk server 2.6 channel and synchronize the repository's packages from the Oracle Linux yum server.
      - d. Change the channel subscription of the Spacewalk server in Spacewalk from the previous version to the Spacewalk Server 2.6 channel.
    - If the Spacewalk server is configured to obtain Spacewalk Server 2.2 or 2.4 packages from the Oracle Linux yum server, do the following:
      - a. Disable the Spacewalk Server 2.2 or 2.4 repository in the Oracle Linux yum server repository configuration file. Or, delete your Spacewalk Server 2.2 or 2.4 `.repo` file.
      - b. Ensure that your system is up to date and that you have transitioned to use the modular yum repository configuration by installing the `oraclelinux-release-el6` or `oraclelinux-release-el7` package and running the `/usr/bin/ol_yum_configure.sh` script. For example, on Oracle Linux 6, do:

```
# yum install oraclelinux-release-el6
# /usr/bin/ol_yum_configure.sh
```
      - c. Install the `oracle-spacewalk-server-release-el6` or release `oracle-spacewalk-server-release-el7` package to install appropriate yum repository configuration. For example, on Oracle Linux 6, do:

```
# yum install oracle-spacewalk-server-release-el6
```
      - d. Disable the `ol6_spacewalk27_server` and the `ol6_spacewalk27_client` (or `ol7_spacewalk27_server` and `ol7_spacewalk27_client`) repositories in the repository configuration file. For example, for Oracle Linux 6, do:

```
# yum-config-manager --disable ol6_spacewalk27_client
# yum-config-manager --disable ol6_spacewalk27_client
```
      - e. Enable the `ol6_spacewalk26_server` and the `ol6_spacewalk26_client` (or `ol7_spacewalk26_server` and `ol7_spacewalk26_client`) repositories in the repository configuration file. For example, for Oracle Linux 6, do:

```
# yum-config-manager --enable ol6_spacewalk26_client
# yum-config-manager --enable ol6_spacewalk26_client
```
  4. Lock the versions of any third-party libraries by running the following commands:

```
# yum install yum-versionlock
```

```
# yum versionlock cglib
```

This step is necessary because Spacewalk requires a specific version of `cglib`, which must be locked prior to upgrading.

5. Upgrade the Spacewalk packages.

```
# yum upgrade
```

6. Stop the Spacewalk services.

```
# /usr/sbin/spacewalk-service stop
Shutting down spacewalk services...
Stopping RHN Taskomatic...
Stopped RHN Taskomatic.
Stopping cobbler daemon:                [ OK ]
Stopping rhn-search...
Stopped rhn-search.
Shutting down osa-dispatcher:           [ OK ]
Stopping httpd:                          [ OK ]
Stopping tomcat6:                        [ OK ]
Terminating jabberd processes ...
Stopping s2s:                            [ OK ]
Stopping c2s:                            [ OK ]
Stopping sm:                             [ OK ]
Stopping router:                         [ OK ]
Done.
```

You can safely ignore any SELinux `restorecon` messages that are displayed when the packages are installed.

7. (Optional) Install the `rpmconf` package and then run the `rpmconf` command to copy any customizations you want to preserve to the upgraded configuration files.

```
# yum install rpmconf
# rpmconf -a
```



#### Note

Accept the default option, `keep your currently-installed version`, for each configuration file unless directed by Oracle support to do otherwise.

8. Upgrade the Spacewalk database schema by typing the following command on the Spacewalk server:

```
# /usr/bin/spacewalk-schema-upgrade
```

The output of the `spacewalk-schema-upgrade` command confirms whether or not the schema upgrade was successful.

In the event of a failure, do the following:

- Check the log files in the `/var/log/spacewalk/schema-upgrade` directory to determine the cause.
- Restore the database from backup.
- Fix the cause of the problem, for example, by extending the tablespaces if there is insufficient space.
- Upgrade the database schema.

- Upgrade the Spacewalk configuration for the Oracle Database.

```
# spacewalk-setup --external-oracle --upgrade
```



#### Note

This step resets the `jabberd-dispatcher/osa-dispatcher` configuration back to the default. If you have switched to using SQLite, you will need to manually edit the configuration.

- Restart the Spacewalk services.

```
# /usr/sbin/spacewalk-service start
Starting spacewalk services...
Initializing jabberd processes ...
Starting router:          [ OK ]
Starting sm:              [ OK ]
Starting c2s:             [ OK ]
Starting s2s:             [ OK ]
Starting tomcat6:         [ OK ]
Waiting for tomcat to be ready ...
Starting httpd:           [ OK ]
Starting osa-dispatcher:  [ OK ]
Starting rhn-search...
Starting cobbler daemon:  [ OK ]
Starting RHN Taskomatic...
Done.
```

- Perform any necessary post-installation tasks.

Review the information in [Section 1.6, “Configuring a Newly Installed Spacewalk Server”](#).

## 1.8 Troubleshooting Spacewalk Server Problems

The following information describes how to diagnose and fix problems that you might encounter on a Spacewalk server. For information about other known issues and possible workarounds, see [Spacewalk for Oracle® Linux: Release Notes for Release 2.6](#).

Use the `/usr/sbin/spacewalk-service status` command to verify whether any Spacewalk services are not running correctly. If a service does not start correctly, the problem is usually caused by incorrect configuration information being provided during installation.

Check the following log files for errors:

<code>/var/log/httpd/*</code>	Are <code>httpd</code> service log files.
<code>/var/log/rhn_satellite_install.log</code>	Is the installation log file.
<code>/var/log/rhn/reposync/*</code>	Are the repository synchronization log files.
<code>/var/log/rhn/rhn_server_satellite.log</code>	Is the synchronization log file.
<code>/var/log/rhn/rhn_server_xmlrpc.log</code>	Is the XML-RPC transaction log file.
<code>/var/log/rhn/rhn_taskomatic_daemon.log</code>	Is the Red Hat Network (RHN) Task Engine (Taskomatic) log messages.

<code>/var/log/tomcat6</code>	Is the Tomcat log messages for Oracle Linux 6.
<code>/var/log/tomcat</code>	Is the Tomcat log messages for Oracle Linux 7.
<code>/var/log/yum.log</code>	Is the yum log file.

## 1.8.1 Managing Spacewalk Logging

Spacewalk generates large numbers of log messages, particularly under the `/var/log/httpd` directory. To avoid running out of disk space, you might need to adjust the `logrotate` settings to implement more active rotation, compression, and archival of log files.

For more information, see [Oracle® Linux 6: Administrator's Guide](#) and [Oracle® Linux 7: Administrator's Guide](#).

## 1.8.2 osa-dispatcher Reports a Certificate Verification Failure

If the `osa-dispatcher` service does not start, an error similar to the following might be displayed if you attempt to start the service manually with the `service osa-dispatcher start` command on Oracle Linux 6 or the `systemctl start osa-dispatcher` command on Oracle Linux 7:

```
Starting osa-dispatcher: Spacewalk 10611 2015/05/26 17:11:22 +01:00: ('Traceback caught:',)
Spacewalk 10611 2015/05/26 17:11:22 +01:00: ('Traceback (most recent call last):\n
  File "/usr/share/rhn/osad/jabber_lib.py", line 631, in connect\n
    ssl.do_handshake()\nError: [(\\"SSL routines\\", \\"SSL3_GET_SERVER_CERTIFICATE\\",
  \\'certificate verify failed\\')]\n',)
                                     [FAILED]
```

This error usually indicates that the system's host name does not match its FQDN in DNS, or that you specified an incorrect FQDN for name of the Organization Unit when you installed Spacewalk.

1. To regenerate the SSL certificate, run the `spacewalk-hostname-rename` command, which is available in the `spacewalk-utils` package.
2. If the host name has changed, the `spacewalk-hostname-rename` command prompts you to type the same certificate password that you used when you created the existing certificate. To verify that you know the correct password before running `spacewalk-hostname-rename`, run the following command, which returns the base64-encoded private key if the password is correct or the `unable to load Private Key` error otherwise:

```
# openssl rsa -in /root/ssl-build/RHN-ORG-PRIVATE-SSL-KEY
Enter pass phrase for /root/ssl-build/RHN-ORG-PRIVATE-SSL-KEY: cert_passwd
writing RSA key
-----BEGIN RSA PRIVATE KEY-----
MIIEowIBAAKCAQEAvYQ/Enqo+T3WByuXiOQCpIh7eBFdqWt/e+cm3pfvGYBqi/1g
...
+rEslZK2mCoofnPzg2o097oPj5v4IHYh8Bmlssbk9BHvQ2ZQckSA
-----END RSA PRIVATE KEY-----
```

3. Run the `spacewalk-hostname-rename` command, specifying the IP address and FQDN of the server as arguments to the command, as shown in the following example:

```
# /usr/sbin/spacewalk-hostname-rename IP_address --ssl-orgunit=FQDN
```

4. After regenerating the SSL certificate, stop the `jabberd` and `osa-dispatcher` services, clear the `jabberd` database, and restart the `jabberd` and `osa-dispatcher` services.

For Oracle Linux 6, type the following commands:

```
# service jabberd stop
# service osa-dispatcher stop
# rm -Rf /var/lib/jabberd/db/*
# service jabberd start
# service osa-dispatcher start
```

For Oracle Linux 7, type the following commands:

```
# systemctl stop jabberd
# systemctl stop osa-dispatcher
# rm -Rf /var/lib/jabberd/db/*
# systemctl start jabberd
# systemctl start osa-dispatcher
```

5. On every client that is registered with the server, verify that the value of `serverURL` in `/etc/sysconfig/rhn/up2date` is configured with the correct server host name or IP value, for example:

```
serverURL=https://swksvr.mydom.com/XMLRPC
```

### 1.8.3 osa-dispatcher Reports an Invalid Password

If the `osa-dispatcher` service starts correctly, but later stops unexpectedly, you might see a log error similar to the following:

```
Spacewalk 2316 2015/06/05 20:38:47 +01:00: ('Invalid password',)
```

This error can occur if the `jabberd` database contains invalid entries.

To clear the error, stop the `jabberd` and `osa-dispatcher` services, clear the `jabberd` database, then restart the `jabberd` and `osa-dispatcher` services.

For Oracle Linux 6, type the following commands:

```
# service jabberd stop
# service osa-dispatcher stop
# rm -Rf /var/lib/jabberd/db/*
# service jabberd start
# service osa-dispatcher start
```

For Oracle Linux 7, type the following commands:

```
# systemctl stop jabberd
# systemctl stop osa-dispatcher
# rm -Rf /var/lib/jabberd/db/*
# systemctl start jabberd
# systemctl start osa-dispatcher
```



#### Note

To avoid problems with OSA, you should clear the `jabberd` database at regular intervals.

To avoid database corruption, follow the instructions in [Section 1.6.3, “Replacing the jabberd/osa Database on Spacewalk Servers or Spacewalk Proxies”](#).

### 1.8.4 Tomcat Does Not Start

If the Tomcat service does not start, most likely the `jta` package was installed instead of the `geronimo-jta-1.1-api` package.

The software described in this documentation is either no longer supported or is in extended support.  
Oracle recommends that you upgrade to a current supported release.

## Tomcat Runs Out of Memory

---

To resolve the issue, remove the `jta` package and install the `geronimo-jta-1.1-api` package.

Restart the Spacewalk services.

```
# /usr/sbin/spacewalk-service restart
```

### 1.8.5 Tomcat Runs Out of Memory

If you see messages such as `OutOfMemoryError: Java heap space` in the Tomcat logs, increase the maximum amount of memory that is available to the Tomcat service for its heap as follows:

1. Edit the `/etc/sysconfig/tomcat6` (Oracle Linux 6) or `/etc/sysconfig/tomcat` (Oracle Linux 7) file and increase the argument to `-Xmx` in the `JAVA_OPTS` setting. For example, `-Xmx1024m` increases the maximum size of the heap to 1 GB.
2. Restart the Spacewalk services.

```
# /usr/sbin/spacewalk-service restart
```



## Chapter 2 Installing and Upgrading Spacewalk Proxies

A Spacewalk proxy acts as an intermediary between Spacewalk clients and a Spacewalk server. The main purposes of a Spacewalk proxy are to mitigate the loading on the Spacewalk server and to reduce the download times for Spacewalk clients.

This chapter describes how to install or upgrade a Spacewalk proxy.

### 2.1 Spacewalk Proxy Requirements

Oracle supports Spacewalk proxies that are running on Oracle Linux 6 ([x86\\_64](#)) or Oracle Linux 7 ([x86\\_64](#)). Oracle recommends that you update Oracle Linux with the latest packages that are available on the Oracle Linux yum server.



#### Note

Do not register a Spacewalk proxy with ULN. You can register a Spacewalk proxy as a client of itself or as a client of a Spacewalk server to receive updates.

Note the following additional requirements:

- You can install Oracle Linux 6 or Oracle Linux 7 by using the **Minimal** or **Basic Server** software set. If you select additional package groups during installation, remove the `jta` package before installing Spacewalk, as this package causes Spacewalk services to fail to start.
- Install Spacewalk by using only those packages that are provided by Oracle from the Oracle Linux yum server at <https://yum.oracle.com>.
- No third-party package repositories are required to install Spacewalk on Oracle Linux 6 or Oracle Linux 7. All of the required packages are available in the Spacewalk repository on the Oracle Linux yum server.

### 2.2 Storage Requirements for a Spacewalk Proxy

The following are the storage requirements for a Spacewalk proxy:

- A Spacewalk proxy should have a minimum of 4 GB of memory.
- Typically, the proxy cache requires 10 GB of storage for each combination of Oracle Linux release and architecture.
- By default, a Spacewalk proxy caches packages under the `/var/spool/squid` directory hierarchy and is limited to using up to 60% of the free space in the file system that contains this directory hierarchy.

### 2.3 Networking Requirements for a Spacewalk Proxy

The following are the networking requirements for a Spacewalk proxy:

- **Configure a fully qualified domain name**

You must configure a fully qualified domain name (FQDN) for the Spacewalk proxy. Spacewalk does not consider `.local` and `.localdomain` to be valid domain names. Spacewalk clients must be able to resolve the Spacewalk proxy's FQDN for both forward and reverse lookups in DNS. If these conditions are not met, certificate validation and PXE booting do not work and clients cannot register with the Spacewalk server.

Verify that the host name returned by the `hostname` command and the value of `HOSTNAME` defined in `/etc/sysconfig/network` are identical and that this host name is consistent with the FQDN defined for the system in DNS for both forward and reverse lookups, as shown in the following example

```
# hostname
swkproxy.us.mydom.com
# grep HOSTNAME /etc/sysconfig/network
HOSTNAME=swkproxy.us.mydom.com
```

For Oracle Linux 6, you can also use the `host` command to verify this information:

```
# host swkproxy.us.mydom.com
swkproxy.us.mydom.com has address 10.0.0.24
# host 10.0.0.24
24.0.0.10.in-addr.arpa domain name pointer swkproxy.us.mydom.com.
```

Edit the `/etc/hosts` file and configure the actual IP address for the FQDN and host name and not the loopback address (`127.0.0.1`), as shown in the following example:

```
127.0.0.1    localhost localhost.localdomain localhost4 localhost4.localdomain4
::1         localhost localhost.localdomain localhost6 localhost6.localdomain6
10.0.0.24   swkproxy.us.mydom.com swkproxy
```

- **Port numbers for a Spacewalk proxy**

The following table shows the network ports that a Spacewalk proxy uses, depending on its configuration.

Port/ Protocol	Direction	Purpose
80/tcp	Inbound and outbound	HTTP access
443/tcp	Inbound and outbound	HTTPS access
5222/tcp	Inbound	Push support to Spacewalk clients (if required)
5269/tcp	Inbound	Push support to Spacewalk proxies (if required)

- **Configure a web proxy**

If the Spacewalk proxy needs to connect through a web proxy, you can configure the web proxy during installation.

- **Configure network time synchronization**

Configure the Spacewalk server, proxies, and clients to NTP or PTP. Spacewalk requires that the system time on these systems are consistent to within 120 seconds in order to establish an SSL-based connection.

## 2.4 Installing a Spacewalk Proxy



### Note

A Spacewalk Proxy should be configured with the full Spacewalk client and be registered to the Spacewalk server.

Install the Spacewalk Proxy software as follows:

1. Ensure that the `jta` package is not installed and prevent it from being installed when you install Spacewalk.

Check whether the `jta` package is installed:

```
# yum list installed | grep jta
```

Remove the `jta` package:

```
# yum remove jta
```

To prevent the `jta` package from being installed later, either disable the Oracle Linux 6 or Oracle Linux 7 Add-ons channel (`[ol6_addons]` or `[ol7_addons]`), or add the `jta` package to the `exclude` directive in the yum configuration file, `/etc/yum.conf`, for example:

```
exclude=jta*
```

2. Configure the system firewall.

The following example shows how you might configure the system firewall for Oracle Linux 6:

```
# iptables -I INPUT -p tcp -m state --state NEW -m tcp --dport 80 -j ACCEPT
# iptables -I INPUT -p tcp -m state --state NEW -m tcp --dport 443 -j ACCEPT
# iptables -I INPUT -p tcp -m state --state NEW -m tcp --dport 5222 -j ACCEPT
# iptables -I INPUT -p tcp -m state --state NEW -m tcp --dport 5269 -j ACCEPT
# iptables -I OUTPUT -p tcp -m state --state NEW -m tcp --dport 80 -j ACCEPT
# iptables -I OUTPUT -p tcp -m state --state NEW -m tcp --dport 443 -j ACCEPT
# iptables -I OUTPUT -p tcp -m state --state NEW -m tcp --dport 4545 -j ACCEPT
# service iptables save
```

For Oracle Linux 7, you would configure the system firewall as follows:

```
# firewall-cmd --permanent --add-port=80/tcp
# firewall-cmd --permanent --add-port=443/tcp
# firewall-cmd --permanent --add-port=5222/tcp
# firewall-cmd --permanent --add-port=5269/tcp
# systemctl reload firewalld
```

3. If not already present on the Spacewalk server, create software channels for the Spacewalk client and the Spacewalk server, then subscribe the Spacewalk proxy system to these channels as follows:
  - a. Create a Spacewalk client channel as a child of either the Oracle Linux 6 or Oracle Linux 7 base channel, for the installed version of Oracle Linux.
  - b. Create a Spacewalk client repository that accesses the appropriate Spacewalk client channel on the Oracle Linux yum server ([https://yum.oracle.com/repo/OracleLinux/OL6/spacewalk26/client/x86\\_64/](https://yum.oracle.com/repo/OracleLinux/OL6/spacewalk26/client/x86_64/) or [https://yum.oracle.com/repo/OracleLinux/OL7/spacewalk26/client/x86\\_64/](https://yum.oracle.com/repo/OracleLinux/OL7/spacewalk26/client/x86_64/)) by using the same GPG settings as for Oracle Linux 6 or Oracle Linux 7.

## Installing a Spacewalk Proxy

---

- c. Associate the Spacewalk client repository with the Spacewalk client channel and synchronize the repository's packages from the Oracle Linux yum server.
  - d. Create a Spacewalk server channel as a child of either the Oracle Linux 6 or Oracle Linux 7 base channel for the installed version of Oracle Linux.
  - e. Create a Spacewalk server repository that accesses the appropriate Spacewalk server channel on the Oracle Linux yum server ([https://yum.oracle.com/repo/OracleLinux/OL6/spacewalk26/server/x86\\_64/](https://yum.oracle.com/repo/OracleLinux/OL6/spacewalk26/server/x86_64/) or [https://yum.oracle.com/repo/OracleLinux/OL7/spacewalk26/server/x86\\_64/](https://yum.oracle.com/repo/OracleLinux/OL7/spacewalk26/server/x86_64/)), by using the same GPG settings as for Oracle Linux 6 or Oracle Linux 7.
  - f. Associate the Spacewalk server repository with the Spacewalk server channel and synchronize the repository's packages from the Oracle Linux yum server.
  - g. Change the channel subscription of the Spacewalk server in Spacewalk from the previous version to the Spacewalk Server 2.6 channel.
  - h. Subscribe the Spacewalk proxy to the Spacewalk client and server channels.
4. Install the Spacewalk Client software and the `openssh-clients` packages as follows:

```
# yum install rhn-client-tools rhn-check rhn-setup rhnsd \  
m2crypto yum-rhn-plugin openssh-clients
```

5. Register the system as a client of the Spacewalk server for which it will act as a Spacewalk proxy.



### Note

Before you can register a server, you must have already created a client activation key. If enabled, a universal default key can be used. However, using a specific activation key is better.

The following steps use SSL to encrypt all communication between the client and the Spacewalk server. This configuration is *mandatory*. The Proxy must use SSL to communicate to the server. Otherwise, `jabberd` will not work.

- a. Download the CA certificate file `RHN-ORG-TRUSTED-SSL-CERT` to the server.

In a browser tab, navigate to [http://swksvr\\_FQDN/pub](http://swksvr_FQDN/pub), where `swksvr_FQDN` is the fully qualified domain name of the Spacewalk server, and download the CA certificate file `RHN-ORG-TRUSTED-SSL-CERT` to `/usr/share/rhn`.

Alternatively, you can use `wget` from the command line, for example:

```
# wget -q -O /usr/share/rhn/RHN-ORG-TRUSTED-SSL-CERT \  
http://swksvr_FQDN/pub/RHN-ORG-TRUSTED-SSL-CERT
```

- b. Register the system with Spacewalk by using the `rhnreg_ks` command, with the `--sslCAcert` option to specify the path of the CA certificate.

```
# rhnreg_ks --sslCAcert=/usr/share/rhn/RHN-ORG-TRUSTED-SSL-CERT \  

```

## Installing a Spacewalk Proxy

```
--serverUrl=https://swksvr_FQDN/XMLRPC --activationkey=activation_key
```

Specify the Spacewalk server or proxy by its fully qualified domain name.

- c. Verify that the settings in the `/etc/sysconfig/rhn/up2date` file that are used to access the Spacewalk server are correct.
  - i. Verify that `serverURL` is set to the Spacewalk server's URL, for example `https://swksvr.mydom.com/XMLRPC`:

```
# grep ^serverURL= /etc/sysconfig/rhn/up2date
serverURL=https://swksvr.mydom.com/XMLRPC
```

- ii. Verify that `sslCACert` is set to the correct CA certificate file, for example `/usr/share/rhn/RHN-ORG-TRUSTED-SSL-CERT`:

```
# grep ^sslCACert= /etc/sysconfig/rhn/up2date
sslCACert=/usr/share/rhn/RHN-ORG-TRUSTED-SSL-CERT
```



### Note

If the settings are not correct, you most likely made a mistake when registering the system by using the `rhnreg_ks` command. Run the `rhnreg_ks` command again, checking that you correctly specify the path of the CA certificate and the Spacewalk server's URL. Also, make sure to specify the `--force` option to override the previous settings.

6. Install the Spacewalk Proxy installer package.

```
# yum -y install spacewalk-proxy-installer
```

7. Create the `/root/ssl-build` directory.

```
# mkdir /root/ssl-build
```

8. Copy the Spacewalk server's CA key and public certificate files to `/root/ssl-build`.

```
# scp 'root@spacewalk_server:/root/ssl-build/{RHN-ORG-PRIVATE-SSL-KEY, \
RHN-ORG-TRUSTED-SSL-CERT,rhn-ca-openssl.cnf}' /root/ssl-build
RHN-ORG-PRIVATE-SSL-KEY          100% 1751 1.7KB/s   00:00
RHN-ORG-TRUSTED-SSL-CERT        100% 5316 5.2KB/s   00:00
rhn-ca-openssl.cnf              100% 2186 2.1KB/s   00:00
```

9. Configure the Spacewalk proxy by running the `/usr/sbin/configure-proxy.sh` script.

The following example shows an interactive configuration:

```
# /usr/sbin/configure-proxy.sh
Using RHN parent (from /etc/sysconfig/rhn/up2date): swksvr.mydom.com
Using CA Chain (from /etc/sysconfig/rhn/up2date): /usr/share/rhn/RHN-ORG-TRUSTED-SSL-CERT
HTTP Proxy []: [Enter]
Proxy version to activate [2.6]: [Enter]
Traceback email []: my.email@mydom.com
Use SSL [Y/n]: Y
Regardless of whether you enabled SSL for the connection to the Spacewalk Parent
Server, you will be prompted to generate an SSL certificate.
This SSL certificate will allow client systems to connect to this Spacewalk Proxy
securely. Refer to the Spacewalk Proxy Installation Guide for more information.
Organization []: Company Demo
Organization Unit [swkproxy.us.mydom.com]: [Enter]
Common Name [swkproxy.us.mydom.com]: [Enter]
```

## Installing a Spacewalk Proxy

```
City []: Redwood Shores
State []: CA
Country code []: US
Email [my.email@mydom.com]: [Enter]
Cname aliases (separated by space) []: [Enter]
Spacewalk Proxy successfully activated.
Loaded plugins: rhnplugin
This system is receiving updates from RHN Classic or Red Hat Satellite.
Setting up Install Process
Resolving Dependencies
--> Running transaction check
---> Package spacewalk-proxy-management.noarch... will be installed
...
Transaction Summary
=====
Install      42 Package(s)

Total download size: 13 M
Installed size: 32 M
Is this ok [y/N]: y
Downloading Packages:
(1/42): apr... | 122 kB    00:00
...
Using CA key at /root/ssl-build/RHN-ORG-PRIVATE-SSL-KEY.
Generating distributable RPM for CA public certificate:
Copying CA public certificate to /var/www/html/pub for distribution to clients:
Generating SSL key and public certificate:
CA password: cert_passwd
Installing SSL certificate for Apache and Jabberd:
Preparing packages for installation...
rhn-org-httpd-ssl-key-pair-swkproxy-1.0-1
Create and populate configuration channel rhn_proxy_config_1000010000? [Y/n]: Y
Spacewalk username: []: sw_user
Password: sw_passwd
Using server name swksvr.mydom.com
Creating config channel rhn_proxy_config_1000010000
Config channel rhn_proxy_config_1000010000 created
Using server name swksvr.mydom.com
Pushing to channel rhn_proxy_config_1000010000:
Local file /etc/httpd/conf.d/ssl.conf -> remote file /etc/httpd/conf.d/ssl.conf
Local file /etc/rhn/rhn.conf -> remote file /etc/rhn/rhn.conf
Local file /etc/squid/squid.conf -> remote file /etc/squid/squid.conf
Local file /etc/httpd/conf.d/cobbler-proxy.conf -> remote file /etc/httpd/conf.d/cobbler-proxy.conf
Local file /etc/httpd/conf/httpd.conf -> remote file /etc/httpd/conf/httpd.conf
Local file /etc/jabberd/c2s.xml -> remote file /etc/jabberd/c2s.xml
Local file /etc/jabberd/sm.xml -> remote file /etc/jabberd/sm.xml
Enabling Spacewalk Proxy.
Shutting down rhn-proxy...
Terminating jabberd processes ...
Stopping s2s: [FAILED]
Stopping c2s: [FAILED]
Stopping sm: [FAILED]
Stopping router: [FAILED]
Stopping httpd: [FAILED]
Stopping squid: [FAILED]
Done.
Starting rhn-proxy...
init_cache_dir /var/spool/squid... Starting squid: . [ OK ]
Starting httpd: [ OK ]
Initializing jabberd processes ...
Starting router: [ OK ]
Starting sm: [ OK ]
Starting c2s: [ OK ]
Starting s2s: [ OK ]
Done.
```

## Upgrading a Spacewalk Proxy

```
There were some answers you had to enter manually.  
Would you like to have written those into file  
formatted as answers file? [Y/n]: Y  
Writing proxy-answers.txt.NtM1Y
```

The Spacewalk user name and password (*sw\_user* and *sw\_passwd*) are the Spacewalk server administrator's user name and password.



### Note

The information that you provide is optionally recorded in a file named `proxy-answers.txt.UID`, where *UID* is a unique identifier. You can use this file to automate the configuration of a Spacewalk proxy, as shown in the following example:

```
# configure-proxy.sh --non-interactive --answer-file=proxy-answers.txt.NtM1Y
```

10. If you want to use third-party CA-signed SSL certificate instead of the self-signed SSL certificate, follow the procedure described in [Section 1.6.1, “Replacing a Self-Signed SSL Certificate”](#).



### Note

Oracle recommends that you replace the self-signed SSL certificate before registering any clients. Otherwise, you must log on separately to each existing client and configure it to use the new SSL certificate. You cannot do this from the Spacewalk server.

11. To check that the Spacewalk proxy is running correctly, specify the URL of the proxy when registering a Spacewalk client, as shown in the following example

```
rhnreg_ks --sslCACert=/usr/share/rhn/RHN-ORG-TRUSTED-SSL-CERT \  
--serverUrl=https://swkproxy_FQDN/XMLRPC --activationkey=activation_key
```

After registering the client, subscribe it to software channels on the server and verify that you can update packages from the client.

## 2.5 Upgrading a Spacewalk Proxy

Upgrade a Spacewalk proxy as follows:

1. If not already present on the Spacewalk server, create software channels for the Spacewalk 2.6 Client and the Spacewalk 2.6 Server, then subscribe the Spacewalk proxy system to these channels as follows:
  - a. Create a Spacewalk client channel as a child of either the Oracle Linux 6 base channel.
  - b. Create a Spacewalk client repository that accesses the Spacewalk client channel on the Oracle Linux yum server ([https://yum.oracle.com/repo/OracleLinux/OL6/spacewalk26/client/x86\\_64/](https://yum.oracle.com/repo/OracleLinux/OL6/spacewalk26/client/x86_64/)), using the same GPG settings as for Oracle Linux 6.
  - c. Associate the Spacewalk client repository with the Spacewalk client channel and synchronize the repository's packages from the Oracle Linux yum server.
  - d. Create a Spacewalk server channel as a child of the Oracle Linux 6 base channel.

- e. Create a Spacewalk server repository that accesses the Spacewalk server channel on the Oracle Linux yum server ([https://yum.oracle.com/repo/OracleLinux/OL6/spacewalk26/server/x86\\_64/](https://yum.oracle.com/repo/OracleLinux/OL6/spacewalk26/server/x86_64/)), using the same GPG settings as for Oracle Linux 6.
  - f. Associate the Spacewalk server repository with the Spacewalk server channel and synchronize the repository's packages from the Oracle Linux yum server.
  - g. Change the channel subscription of the Spacewalk server in Spacewalk from the previous release to the Spacewalk Server 2.6 channel.
  - h. Subscribe the Spacewalk proxy to the Spacewalk Client 2.6 and Spacewalk Server 2.6 channels instead of the Spacewalk 2.2 or 2.4 Server and Client channels.
2. Back up the CA key, SSL certificate and the openSSL configuration file in `/root/ssl-build`.

For example, you could use the `tar` command as follows to create a backup:

```
# cd /root/ssl-build
# tar -cvf /tmp/sslcerts.tar RHN-ORG-PRIVATE-SSL-KEY RHN-ORG-TRUSTED-SSL-CERT rhn-ca-openssl.cnf
```

3. Run the `yum update` command to update all of the packages on the system.

```
# yum update
```

4. If necessary, extract the CA key, SSL certificate, and openSSL configuration file from your backup file to `/root/ssl-build`:

```
# cd /root/ssl-build
# tar -xvf /tmp/sslcerts.tar
```

5. Configure the Spacewalk proxy by running the `configure-proxy.sh` script.

The following example uses the `proxy-answers.txt.UID` file that was saved from a previous installation to perform the configuration:

```
# configure-proxy.sh --non-interactive --answer-file=proxy-answers.txt.NtMlY
```

You can also run this command interactively by omitting any command-line options.

## 2.6 Troubleshooting Spacewalk Proxy Installation Problems

The following information describes how to diagnose and fix problems that you might encounter on a Spacewalk proxy.

For information about other known issues and possible workarounds, see [Spacewalk for Oracle® Linux: Release Notes for Release 2.6](#).

Use the `rhn-proxy status` command to find out which Spacewalk proxy services are not running correctly. If a service does not start correctly, the problem is usually caused by incorrect configuration information being provided during installation.

Verify that the `/etc/sysconfig/rhn/systemid` file is owned by `root:apache` and that its mode is set to 640.

Check the following log files for errors:

<code>/var/log/httpd/*</code>	Are the <code>httpd</code> service log files.
<code>/var/log/rhn/ rhn_proxy_broker.log</code>	Is the proxy brokering service log file.
<code>/var/log/rhn/ rhn_proxy_redirect.log</code>	Is the proxy SSL redirection service log file.
<code>/var/log/squid/*</code>	Are the squid proxy log files.
<code>/var/log/yum.log</code>	Is the yum log file.

## 2.6.1 Clearing the Proxy Cache

If required to clear up package provisioning problems, you can clear the proxy cache as follows:

1. Stop the `httpd` and `squid` services.

For Oracle Linux 6, type the following commands:

```
# service httpd stop
# service squid stop
```

For Oracle Linux 7, type the following commands:

```
# systemctl stop httpd
# systemctl stop squid
```

2. Delete the contents of the cache as follows:

```
# rm -Rf /var/cache/rhn/*
```

3. Restart the `squid` and `httpd` services.

For Oracle Linux 6, type the following commands:

```
# service squid start
# service httpd start
```

For Oracle Linux 7, type the following commands:

```
# systemctl start squid
# systemctl start httpd
```



## Chapter 3 Configuring Inter-Server Synchronization for Spacewalk Servers

You can configure ISS to synchronize channel content, channel permissions, and organizational trust settings between Spacewalk servers. The configuration of local non-content settings for users and organizations is not affected. One Spacewalk server acts as a *primary* server to provide content to any number of *worker* Spacewalk servers.

Typical use cases include the following:

- Content on the worker servers is regularly synchronized with the primary server to obtain the latest maintenance releases.
- Content is developed and tested on the primary server before distribution to the worker servers.
- worker servers have local content that is additional to that synchronized from the primary server.

You can configure primary servers that are themselves workers of a higher-level primary Spacewalk server. The usual ISS topology is a tree-like hierarchy, where there is one top-level primary server and each worker has only one primary server, rather than a directed graph, where there might be several top-level primary servers and each worker can have more than one primary. If a worker has more than one primary server, you can designate one to be the default primary server with which the worker synchronizes.

You can use the `spacewalk-sync-setup` command to set up the relationships between primary and worker Spacewalk servers, or you can use the Spacewalk web interface to configure each server independently.

### 3.1 Enabling or Disabling Worker Synchronization Support for a Spacewalk Server

By default, a Spacewalk server is configured so that it can act as a primary server. Any worker servers that you configure for the primary server will be able to synchronize from it. The following steps are not usually necessary unless you want to disable this feature on a Spacewalk server that acts only as a worker server.

Enable or disable support for worker synchronization on a Spacewalk server as follows:

1. To disable ISS support, edit `/etc/rhn/rhn.conf` and set the value of `disable_iss` to 1:

```
disable_iss=1
```

To enable ISS support, edit `/etc/rhn/rhn.conf` and set the value of `disable_iss` to 0:

```
disable_iss=0
```

2. Restart the `httpd` service.

For Oracle Linux 6, type the following command:

```
# service httpd restart
```

For Oracle Linux 7, type the following command:

```
# systemctl restart httpd
```

## 3.2 Configuring Primary and Worker Spacewalk Servers With the `spacewalk-sync-setup` Command



### Note

Before you can configure ISS, Spacewalk must be installed and running on both the primary and worker servers.

The `spacewalk-sync-setup` command is available in the `spacewalk-utils` package.

On either of the Spacewalk servers, run the `spacewalk-sync-setup` command.

```
# spacewalk-sync-setup --apply --create-templates \  
  --ms=primary_swksvr_FQDN --ml=primary_swadm --mp=primary_swadm_passwd \  
  --ss=worker_swksvr_FQDN --sl=worker_swadm --sp=worker_swadm_passwd
```

where `primary_swksvr_FQDN` is the fully qualified domain name of the Spacewalk server that will act as the primary server and the `primary_swadm` and `primary_swadm_passwd` values specify the Spacewalk administrator's user name and password for that server.

The `worker_swksvr_FQDN` value is the fully qualified domain name of the Spacewalk server that will act as the worker server and the `worker_swadm` and `worker_swadm_passwd` values specify the Spacewalk administrator's user name and password for that server.

The following is the typical output that is displayed when running this command:

```
# spacewalk-sync-setup --apply --create-templates \  
  --ms=swksvr.mydom.com --ml=swadm --mp=swpass \  
  --ss=swksvr2.mydom.com --sl=swadm2 --sp=swpass2  
INFO: Connecting to swadmin@swksvr.mydom.com  
INFO: Connecting to swadmin@swksvr2.mydom.com  
INFO: Generating master-setup file /root/.spacewalk-sync-setup/master.txt  
INFO: Generating slave-setup file /root/.spacewalk-sync-setup/slave.txt  
INFO: About to wget master CA cert: [wget -q -O  
/usr/share/rhn/swksvr.mydom.com_RHN-ORG-TRUSTED-SSL-CERT  
http://swksvr.mydom.com/pub/RHN-ORG-TRUSTED-SSL-CERT]  
INFO: Applying master-setup /root/.spacewalk-sync-setup/master.txt  
INFO: Applying slave-setup /root/.spacewalk-sync-setup/slave.txt
```

A copy of the primary server's CA certificate is stored on the worker as `/usr/share/rhn/swksvr.mydom.com_RHN-ORG-TRUSTED-SSL-CERT`.

You can then map local organizations on the worker server to organizations that the primary server exports. See [Section 3.5, "Mapping a Local Organization to an Exported Organization by Using the Spacewalk Web Interface"](#).

## 3.3 Configuring a Primary Spacewalk Server by Using the Spacewalk Web Interface

Configure a primary Spacewalk server as follows:

1. Go to **Admin**, select **ISS Configuration**, and then select the **Master Setup** tab.
2. On the Known Slave Instances page, click **+ Add new slave**.

3. On the Edit Slave Details page, type the FQDN of the worker server and select or deselect the check boxes that configure worker and organization synchronization.

For example, you might want to enable the worker to synchronize from the primary server, but not want to synchronize all organizations to the worker.

4. Click Create.

When the page refreshes, you are able to select which organizations can be exported. By default, no organizations are selected.

5. Select the organizations that you want to enable to be exported to the worker, then click **Allow Orgs**.

## 3.4 Configuring a Worker Spacewalk Server by Using the Spacewalk Web Interface

Configure a worker Spacewalk server as follows:

1. In a browser tab, navigate to [http://primary\\_swksvr\\_FQDN/pub](http://primary_swksvr_FQDN/pub), where *primary\_swksvr\_FQDN* is the FQDN of the primary Spacewalk server, and download the CA certificate file `RHN-ORG-TRUSTED-SSL-CERT` as `RHN-ORG-TRUSTED-SSL-CERT-MASTER`.

Alternatively, you can use the `wget` command as follows:

```
# wget -q -O /usr/share/rhn/RHN-ORG-TRUSTED-SSL-CERT-MASTER \  
http://primary_swksvr_FQDN/pub/RHN-ORG-TRUSTED-SSL-CERT
```

2. In the Spacewalk web interface, go to **Admin**, select **ISS Configuration** and then select the **Slave Setup** tab.
3. On the Known Master Instances page, click **+ Add new master**.
4. On the Details for new Master page, type the FQDN of the primary server and the absolute path name of the primary server's CA certificate that you downloaded (`RHN-ORG-TRUSTED-SSL-CERT-MASTER`), then select whether the primary server will be the default one with which the worker synchronizes.
5. Click **Add new master**.

The page refreshes to display a Configure Master-to-Slave Org Mappings section that enables you to configure local names for the organizations that the primary server exports. When you synchronize content, access permissions that you have configured for channels on the primary server propagate to the worker server. You can choose which organizations, and any associated channel permissions, to map to a worker server.

If necessary, create the local organizations to be mapped to the organizations that the primary server exports as follows:

- a. Go to **Admin**, select **Organizations** and click **+ create new organization**.
- b. On the Create New Organization page, provide the details for the organization, including its name and the login details of its administrator.



### Note

You must create a new user to act as the organization's administrator, as the Spacewalk administrator cannot perform this role.

- c. Click **Create Organization**.
  - d. To return to the Configure Master-to-Slave Org Mappings section for the primary server instance, go to **Admin**, select **ISS Configuration**. Then, select the **Slave Setup** tab and click the name of the primary server instance.
6. In the Configure Master-to-Slave Org Mappings section, select the local organizations that map to the organizations that the primary server exports.
  7. For each exported organization in the Master Org Name column, use the pull-down menu in the Matching Local Org column to select the local organization that should map to the export organization.  
  
If you do not want to import an organization, select **NOT MAPPED**.
8. Click **Update**.

## 3.5 Mapping a Local Organization to an Exported Organization by Using the Spacewalk Web Interface

Map local organizations on a worker server to organizations exported by a primary server as follows:

1. On the worker server, to view the organizations that a primary server exports, go to **Admin**, select **ISS Configuration**, select the **Slave Setup** tab, and click the name of the primary server instance.
2. On the worker server, create the local organizations that you want to map to the organizations that the primary server exports.

Create a local organization as follows:

- a. Go to **Admin**, select **Organizations** and click **+ create new organization**.
- b. On the Create New Organization page, provide the details for the organization, including its name and the login details of its administrator.



### Note

You must create a new user to act as the organization's administrator, as the Spacewalk administrator cannot perform this role.

- c. Click **Create Organization**.
  - d. To return to the Configure Master-to-Slave Org Mappings section for the primary server instance, go to **Admin**, select **ISS Configuration**. Then, select the **Slave Setup** tab and click the name of the primary server instance.
3. In the Configure Master-to-Slave Org Mappings section, select the local organizations that map to the organizations that the primary server exports.

For each exported organization in the Master Org Name column, use the pull-down in the Matching Local Org column to select the local organization that should map to the export organization. If you do not want to import the organization, select **NOT MAPPED**.

4. Click **Update**.

## 3.6 Synchronizing Software Channels on a Spacewalk Worker Server

You synchronize a software channel by running the `satellite-sync` command on the worker server as follows:

```
# satellite-sync [--iss-parent=primary_swksvr_FQDN] [--orgid=N] -c channel_label
```

where `channel_label` specifies the label of the software channel to synchronize from the primary server.

The argument to the `--orgid` option specifies the ID of the organization on the worker into which the channel is synchronized. If not specified, the Spacewalk Default Organization with ID 1 is assumed.

The `primary_swksvr_FQDN` value specifies the FQDN of the primary Spacewalk server. If not specified, and the worker server has more than one primary server, the default primary server is assumed.

Output that is similar to the following is displayed when you perform an initial synchronization of a software channel on a worker server from the Spacewalk Default Organization on the default primary server:

```
# satellite-sync -c oraclelinux6-x86_64-patch
16:16:52 Spacewalk - live synchronization
16:16:52 url: https://swksvr.mydom.com
16:16:52 debug/output level: 1
16:16:52 db: c##spacewalk2/<password>@//odbsvr.mydom.com/company.mydom.com
16:16:52
16:16:52 Retrieving / parsing orgs data
16:16:52 orgs data complete
16:16:52
16:16:52 Retrieving / parsing channel-families data
16:16:52 channel-families data complete
16:16:52
16:16:52 Retrieving / parsing product names data
16:16:52 product names data complete
16:16:52
16:16:52 Retrieving / parsing arches data
16:16:53 arches data complete
16:16:53
16:16:53 Retrieving / parsing additional arches data
16:16:53 additional arches data complete
16:16:53
16:16:53 Retrieving / parsing channel data
16:16:54 p = previously imported/synced channel
16:16:54 . = channel not yet imported/synced
16:16:54 base-channels:
16:16:54 NONE RELEVANT
16:16:54 oraclelinux6-x86_64:
16:16:54 . oraclelinux6-x86_64-patch 1367 full import from Fri Jul 10 13:02:52 2015
16:16:54
16:16:54 Channel data complete
16:16:54
16:16:54 Retrieving short package metadata (used for indexing)
16:16:54 Retrieving / parsing short package metadata: oraclelinux6-x86_64-patch (1367)
16:17:01 Diffing package metadata (what's missing locally?): oraclelinux6-x86_64-patch
-----
Diffing: ##### - complete
16:17:04
16:17:04 Downloading package metadata
16:17:04 Retrieving / parsing *relevant* package metadata: oraclelinux6-x86_64-patch (1357)
16:17:04 * WARNING: this may be a slow process.
-----
Downloading:##### - complete
```

```
16:42:30
16:42:30 Downloading rpm packages
16:42:30   Fetching any missing RPMs: oraclelinux6-x86_64-patch (1357)
16:42:53   Total size: 5.31 GiB
16:47:53 Processing rpm packages complete
16:47:53
16:47:53 Importing package metadata
16:47:53   Importing *relevant* package metadata: oraclelinux6-x86_64-patch (1357)
_____
Importing: ##### - complete
18:06:44
18:06:44 Linking packages to channels
18:07:02
18:07:02 Downloading errata data
18:07:02   Retrieving / parsing errata data: oraclelinux6-x86_64-patch (216)
_____
Downloading:##### - complete
18:07:06 Downloading errata data complete
18:07:06
18:07:06 Downloading kickstartable trees metadata
18:07:06   Retrieving / parsing kickstart data: oraclelinux6-x86_64-patch (NONE RELEVANT)
18:07:06
18:07:06 Downloading kickstartable trees files
18:07:06   Retrieving / parsing kickstart tree files: oraclelinux6-x86_64-patch (NONE RELEVANT)
18:07:06
18:07:06 Importing channel errata
18:07:13   Importing *relevant* errata: oraclelinux6-x86_64-patch (468)
_____
Downloading:##### - complete
18:07:31   No new kickstartable tree to import
  Import complete:
    Begin time: Fri Jul 10 16:16:51 2015
    End time:   Fri Jul 10 18:07:31 2015
    Elapsed:   1 hours, 50 minutes, 40 seconds
```