

Oracle® Fusion Middleware

FMW Composer Online Help

12c (12.2.1.2)

E67071-01

September 2016

Copyright © 2016, Oracle and/or its affiliates. All rights reserved.

Primary Author: Phil Stubbs

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

Preface	v
Audience	v
Documentation Accessibility	v
Related Resources	v
Conventions	v
1 Overview of FMW Composer	
1.1 File Menu Commands	1-2
1.2 Edit Menu Commands	1-3
1.3 Help Menu Commands	1-3
1.4 About the FMW Composer Toolbar	1-3
1.5 Topology Properties	1-4
1.5.1 Directory	1-5
1.6 Blueprint	1-7
1.7 Domain Profile	1-7
1.8 About the Elements of a Topology File	1-8
1.8.1 Host	1-9
1.8.2 Oracle Home	1-10
1.8.3 Domain	1-11
1.8.4 Server	1-14
1.8.5 Node Manager	1-15
1.8.6 Cluster	1-17
1.8.7 Database	1-18
1.8.8 Data Source	1-20
1.8.9 Schema	1-21
1.8.10 Web Tier	1-22
1.9 Tuning Parameter Settings	1-23
1.10 Validation Panel	1-24

Preface

The *FMW Composer Online Help* provides information about using the various features of FMW Composer.

[Audience](#)

[Documentation Accessibility](#)

[Related Resources](#)

[Conventions](#)

Audience

This document is intended for administrators who use FMW Composer to configure and manage Oracle Fusion Middleware.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Related Resources

For more information, see the Oracle Fusion Middleware documentation library.

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.

Convention	Meaning
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

Overview of FMW Composer

FMW Composer is a client application that provides a graphical user interface for describing the elements of a Fusion Middleware topology, such as the hosts, Oracle homes, domains, servers, and so on.

With FMW Composer, you can create a topology from scratch, as well as make edits and updates to an existing topology. Once you finish creating or updating a topology, you can save your topology to a topology file, which can be a XML or JSON file. You can use this file as input with the Oracle Lifecycle Management (LCM) Tools to configure and manage your Fusion Middleware environment. To learn more about what you can do with the LCM Tools, see *About the Lifecycle Management Tools in Oracle Fusion Middleware Configuring Oracle Fusion Middleware Using Lifecycle Management Tools*.

The following help topics provide information on using the menus, toolbar, panels, and other features in Composer:

[File Menu Commands](#)

The **File** menu includes commands for creating a file, opening a file, saving a file, displaying the Settings page, and quitting FMW Composer.

[Edit Menu Commands](#)

The **Edit** menu includes commands for adding, assigning, removing, and deleting elements. This menu is context sensitive (the menu options that you can choose from are related to the selected element on the screen).

[Help Menu Commands](#)

Use the **Help** menu to get help using the various features of the Oracle Lifecycle Management (LCM) Tools. You can also use this menu to obtain and verify the version number for FMW Composer.

[About the FMW Composer Toolbar](#)

The FMW Composer toolbar appears at the top of the window. You can use the toolbar to create a new file, save a file, add an element to the topology, delete an element, and more.

[Topology Properties](#)

The Topology Properties panel allows you to specify information about the topology file you are editing, such as the name and version of the file.

[Blueprint](#)

A blueprint file lists and defines the configuration templates required to create a domain.

[Domain Profile](#)

You can use the domain profile file type to specify information about a domain, such as server, cluster, template, and server group information.

About the Elements of a Topology File

You can use FMW Composer to create, define, and edit the elements of your topology. Specifically, FMW Composer has a context-sensitive panel located on the right side of the screen with fields where you can specify information about each element.

Tuning Parameter Settings

Tuning parameters allow you to customize or tune additional configuration settings for various elements.

Validation Panel

The validation panel allows you to quickly see and correct any errors that occur while you are editing a topology, blueprint, or domain profile.

1.1 File Menu Commands

The **File** menu includes commands for creating a file, opening a file, saving a file, displaying the Settings page, and quitting FMW Composer.

Command	Description
New	<p>Creates a new, empty file.</p> <p>The following file types are available:</p> <ul style="list-style-type: none"> • Topology: Use this file type to define the topology of a Fusion Middleware environment (hosts, Oracle homes, domains, etc.). • Blueprint: Use this file type to define the configuration templates required to create a domain. • Domain Profile: Use this file type to specify information about a domain in a separate file outside of the topology. <p>Shortcut: </p>
Open File...	<p>Opens an existing file.</p> <p>Shortcut: </p>
Save	<p>Saves the current page to a file. If the current page is already associated with a file, the page will be saved to that file.</p> <p>If the current page is not associated with a file, you will be prompted to specify a directory location on your system. The file name is automatically generated using the <i>id-version.xml</i> or <i>id-version.json</i> format.</p> <p>Shortcut: </p>
Save As...	<p>Saves the current page to a file. You can save the file either as a XML file or JSON file. You will be prompted to specify a directory location on your system. The file name is automatically generated using the <i>id-version.xml</i> or <i>id-version.json</i> format.</p> <p>Shortcut: </p>
Settings	<p>Displays the Settings page. Use the Settings page to display and set Composer settings, such as the directory path of the Oracle home and the wallet file for environment credentials. On the Settings page, you can:</p> <ul style="list-style-type: none"> • Assign an existing wallet to a topology. • Create a new wallet for a topology. • Specify the location of an Oracle home directory for a topology.

Command	Description
Exit	Exits Composer. Any unsaved changes will be discarded.

1.2 Edit Menu Commands

The **Edit** menu includes commands for adding, assigning, removing, and deleting elements. This menu is context sensitive (the menu options that you can choose from are related to the selected element on the screen).

You can invoke these commands using one of the following methods:

- From the **Edit** menu itself.
- From the right-click (context) menu.

Note that this menu will only list the actions that you can perform on the selected element.

1.3 Help Menu Commands

Use the **Help** menu to get help using the various features of the Oracle Lifecycle Management (LCM) Tools. You can also use this menu to obtain and verify the version number for FMW Composer.

Command	Description
About the Life Cycle Tools	Provides an introduction to the Oracle LCM Tools.
Getting Started	Provides information on how to get started using the LCM Tools, such as locating the LCM Tools in an Oracle home, using the LCM Tools tutorial, and getting help with Composer.
Tutorial	Displays a tutorial that shows you step-by-step how to use the LCM Tools to configure a sample Oracle SOA Suite topology.
About	Displays the version number and build information for Composer.

1.4 About the FMW Composer Toolbar

The FMW Composer toolbar appears at the top of the window. You can use the toolbar to create a new file, save a file, add an element to the topology, delete an element, and more.

Some of the toolbar buttons might appear grayed out. These options are context sensitive and become enabled only after you select an element on the current page. For example, if you select a host, then only the buttons related to that host are enabled.



Button	Description	Menu Location
	<p>Creates a new, empty file.</p> <p>The following file types are available:</p> <ul style="list-style-type: none"> • Topology: Use this file type to define the topology of a Fusion Middleware environment (hosts, Oracle homes, domains, etc.). • Blueprint: Use this file type to define the configuration templates required to create a domain. • Domain Profile: Use this file type to specify information about a domain in a separate file outside of the topology. 	Select File and then New
	Opens an existing file.	Select File and then Open...
	<p>Saves the current page to a file. If the current page is already associated with a file, the page will be saved to that file.</p> <p>If the current page is not associated with a file, you will be prompted to specify a directory location on your system. The file name is automatically generated using the <i>id-version.xml</i> or <i>id-version.json</i> format.</p>	Select File and then Save
	<p>Adds a new element (host, Oracle home, etc.) to the active file. This button is only available for the Topology and Domain Profile file types.</p> <p>This button is context-sensitive (the elements you can choose from are related to the selected element on the screen).</p>	Edit
	<p>Assigns or maps an existing element to another element. For example, you might use this button to assign an Oracle home to a host.</p> <p>This button is context-sensitive (the elements you can assign are related to the selected element on the screen).</p>	Edit
	<p>Removes or unassigns an existing element from another element. For example, you might use this button to remove an Oracle home from an assigned host.</p> <p>You must select the element you want to remove.</p>	Edit
	<p>Deletes an existing element from the active file. This button is only available for the Topology and Domain Profile file types.</p> <p>You must select the element you want to delete.</p>	Edit
	<p>Use this option to get help for an element on the screen.</p> <p>After you click this button, select an element (for example, a host) on the screen to open the online help for that element.</p>	N/A

1.5 Topology Properties

The Topology Properties panel allows you to specify information about the topology file you are editing, such as the name and version of the file.

Property	Description
ID	A unique name for the topology file used to identify this file from other files.

Property	Description
Version	<p>The version number of this topology file. For example, 1.0, 2.0, 3.0, and so on.</p> <p>If you need to make an update to the topology, this property allows you to create multiple versions of the file and distinguish them from one another.</p>
FMW Version Range	<p>This field identifies the minimum or exact Fusion Middleware version of the file. For example, [12.1.3 ,) means any version starting from and including 12.1.3.</p>
Variables	<p>Use this field to define any variables you want to use when setting values in the topology file. A variable represents an actual value in your environment. A variable includes two parts:</p> <ul style="list-style-type: none"> • The Name of the variable. The name can contain alphanumeric characters. The % character should not be used in the variable name. • The Value of the variable. This is an actual value from your environment that the variable name represents.
Directories	<p>To add a LDAP directory component to the topology, click . A dialog box will appear where you can specify information about a directory.</p> <p>To remove a directory component from the topology, select the name of the directory and click .</p> <p>To edit the information for an existing directory component, select the name of the directory and click .</p>
Miscellaneous Properties	<p>Use this field to add additional property settings for a topology.</p> <ul style="list-style-type: none"> • To add a property setting to the topology, click . A dialog box will appear where you can define a Name and Value for the property. • To remove a property from the topology, select the name of the property and click . • To edit the value of an existing property, select the name of the property and click .

Directory

The Directory panel contains fields that you can use to specify information (or attributes) for a LDAP directory.

1.5.1 Directory

The Directory panel contains fields that you can use to specify information (or attributes) for a LDAP directory.

Attribute	Description
ID	A unique name used to identify the directory. The default ID is dir.
Type	Use the drop-down list to specify the directory type of the LDAP server. Valid types include: <ul style="list-style-type: none">• OID• OID_LDAP• AD• LBR_OUD• LBR_OID• ODSEE_LDAP
Port	The port number of the LDAP server.
RCU Connect String	The connect string used by RCU to connect to the database: <i>db_host:db_port:service_name</i> Where <i>db_host</i> is the host name of the machine on which the database resides, <i>db_port</i> is the listener port of the database, and <i>service_name</i> is the service name identified for the database.
Credential	The password used to connect to the LDAP server. Click select to select the password from the wallet or to add the password to the wallet. When you click select , a dialog box will appear with a list of credentials to choose from only if you have provided the path to a wallet on the Composer Settings page (located in the File menu). <ul style="list-style-type: none">• If the credential exists in the wallet, select the credential from the list and click OK.• If the credential does not exist, click New to add the credential to the wallet.
Search Base	The search base for the LDAP server in DN format.
User Search Base	The user search base for the LDAP server in DN format.
Group Search Base	The group or enterprise search base for the LDAP server in DN format.
LBR URL	Load balancer URL

Attribute	Description
Miscellaneous Config	<p>Use this field to add additional configuration property settings for a directory.</p> <ul style="list-style-type: none"> To add a configuration setting for a directory, click . A dialog box will appear where you can define a Name and Value for a property. To remove a property, select the name of the property and click . To edit the value of an existing property, select the name of the property and click .

1.6 Blueprint

A blueprint file lists and defines the configuration templates required to create a domain.

Attributes Tab

Use the Attributes tab to specify information about the blueprint file.

Attribute	Description
ID	A unique name for the blueprint used to identify this blueprint file from other files.
Version	<p>The version number of this blueprint. For example, 1.0, 2.0, 3.0, and so on.</p> <p>If you need to make an update to the blueprint, this property allows you to create multiple versions of the file and distinguish them from one another.</p>
FMW Version Range	This field identifies the minimum or exact Fusion Middleware version of the file. For example, [12.1.3 ,) means any version starting from and including 12.1.3.
Referenced Blueprints	Use this field to add a blueprint to the current file, edit an existing blueprint, or remove a blueprint.

Templates Tab

Use the Templates tab to add or remove domain templates from the blueprint.

1.7 Domain Profile

You can use the domain profile file type to specify information about a domain, such as server, cluster, template, and server group information.

Attributes Tab

Use the Attributes tab to specify information about the file.

Attributes	Description
ID	A unique name for the domain profile file used identify this domain profile from other files.
Version	The version number of this file. For example, 1 . 0, 2 . 0, 3 . 0, and so on. If you need to make an update to the file, this property allows you to create multiple versions of the file and distinguish them from one another.
FMW Version Range	This field identifies the minimum or exact Fusion Middleware version of the file. For example, [12 . 1 . 3 ,) means any version starting from and including 12.1.3.
External Profile	Use this field to add a domain profile to the current file.

Blueprints Tab

Use the Blueprints tab to define the blueprints for the domain.

- Click  to add a blueprint to the domain.
If you have not provided the path to the Oracle home directory on the Composer Settings page (located in the File menu), you will be prompted to specify the path to the Oracle home.
- To edit a blueprint, select the blueprint from the list and click .
This will open the blueprint file in a new tab.
- To remove a blueprint from the domain, select the blueprint from the list and click .

Server Groups Tab

The Server Groups tab displays a list of server groups only if at least one of the templates in a selected blueprint defines a server group. You can assign a server group to a server or cluster.

1.8 About the Elements of a Topology File

You can use FMW Composer to create, define, and edit the elements of your topology. Specifically, FMW Composer has a context-sensitive panel located on the right side of the screen with fields where you can specify information about each element.

You can access a panel by selecting an element on the screen.

For more information about each element panel, see the following topics:

Host

The Host panel contains fields that you can use to specify information (or attributes) for a host in the topology.

Oracle Home

The Oracle Home panel contains fields that you can use to specify information (or attributes) for an Oracle home in the topology.

Domain

The Domain panel contains an Attributes tab that you can use to specify information (or attributes) for a domain in the topology. The Blueprints and Server Groups tabs allow you to add domain templates and server groups, respectively.

Server

The Server panel contains an Attributes tab that you can use to specify information (or attributes) for a server in the topology. The Server Groups tab allows you to select and assign server groups to the selected server.

Node Manager

The Node Manager panel contains fields that you can use to specify information (or attributes) for a Node Manager in the topology.

Cluster

The Cluster panel contains an Attributes tab that you can use to specify information (or attributes) for a cluster in the topology. The Server Groups tab allows you to select and assign server groups to the selected cluster.

Database

The Database panel contains fields that you can use to specify information (or attributes) for a database associated with the topology.

Data Source

The Data Source panel contains fields that you can use to specify information (or attributes) for a data source.

Schema

The Schema panel contains fields that you can use to specify information (or attributes) for a schema.

Web Tier

The Web Tier panel contains fields that you can use to specify information (or attributes) for a web tier component within the topology.

1.8.1 Host

The Host panel contains fields that you can use to specify information (or attributes) for a host in the topology.

Attribute	Description
ID	A unique name for the host used to identify this host from other elements. When you add a new host, the default ID is host1. If host1 is already used in the topology, FMW Composer will default to host2, then host3, and so on.
Address	The primary IP address or DNS name of the host.

Attribute	Description
Credential	<p>The credential from the wallet that will be used to connect to the host.</p> <p>Click select to select the credential for the host from the wallet or add the credential to the wallet. When you click select, a dialog box will appear with a list of credentials to choose from only if you have provided the path to a wallet on the Composer Settings page (located in the File menu).</p> <ul style="list-style-type: none"> • If the credential exists in the wallet, select the credential from the list and click OK. • If the credential does not exist, click New to add the credential to the wallet.
LCM Listen Port	The port that the LCM Agent on this host is listening for REST requests on.
Directory	<p>Use this field to add a directory to this host.</p> <p>Click change to select a directory for the host. A dialog box will appear with a list of directories only if you added and defined at least one directory on the Topology Properties panel.</p> <p>After you add a directory to this host, you can click edit to edit the information for that directory.</p>
Additional Addresses	Use this field to specify additional IP addresses or DNS names for a host.

1.8.2 Oracle Home

The Oracle Home panel contains fields that you can use to specify information (or attributes) for an Oracle home in the topology.

Attribute	Description
ID	<p>A unique name for the Oracle home used to identify the Oracle home from other elements.</p> <p>When you add a new Oracle home, the default ID is home1. If home1 is already used in the topology, FMW Composer will default to home2, then home3, and so on.</p>
Type	<p>Indicates whether the Oracle home is on a local file system (and disk) or on a shared file system (and disk). Valid values are local or shared.</p>
Path	The full path to a directory on the file system. This is the path to the directory where the Oracle home is (or will be) installed on your system.
Java Home	<p>The full path to a directory on the file system. This is the path to a directory where a JDK is installed on your system.</p> <p>For example, /home/Oracle/products/jdk1.8.0_101.</p>

Attribute	Description
Inventory Location	<p>The location where you want to create your central inventory.</p> <p>This field is required if you are installing any Oracle product for the first time on a host that is running UNIX or Linux system software. For more information, see About the Oracle Central Inventory in <i>Oracle Fusion Middleware Installing Software with the Oracle Universal Installer</i>.</p>
Installations	<p>Installation data required to create an Oracle home and install a product.</p> <ul style="list-style-type: none"> • ID: Enter a unique name to identify the distribution you are installing. For example, you might enter <code>infra</code> for Fusion Middleware Infrastructure or <code>soa</code> for Oracle SOA Suite. • Install Type: Specify the type of install you want to perform. This value will differ depending on your product distribution. For example, for the Fusion Middleware Infrastructure distribution, the following install types are valid: <ul style="list-style-type: none"> – Fusion Middleware Infrastructure – Fusion Middleware Infrastructure With Examples • Installer: The full path and file name of the distribution installer file. For example, to install Fusion Middleware Infrastructure: <pre>path_to_infrastructure_jar_file/ fmw_12.2.1.2.0_infrastructure_generic.jar</pre>
Patches	<p>List of patches to be applied to the Oracle home.</p> <ul style="list-style-type: none"> • Click  to add a patch to this list. • To remove a patch, select the patch from the list and click . • To edit a patch, select the patch from the list and click .

1.8.3 Domain

The Domain panel contains an Attributes tab that you can use to specify information (or attributes) for a domain in the topology. The Blueprints and Server Groups tabs allow you to add domain templates and server groups, respectively.

Attributes Tab

Attribute	Description
ID	<p>A unique name for the domain used to identify this domain from other elements.</p> <p>When you add a new domain, the default ID is domain1. If domain1 is already used in the topology, FMW Composer will default to domain2, then domain3, and so on.</p>
Name	The name of the domain.
Type	<p>Indicates whether the domain directory is on a local file system (and disk) or on a shared file system (and disk). Valid values are local or shared.</p>
Path	The full path to a directory on the file system. This is the directory where the domain is (or will be) located on your system.
Application Path	The full path to a directory on the file system. This is the directory where selected applications related to the domains you configure will be created.
Admin Credential	<p>The administrative credential from the wallet that will be used to access the domain's WebLogic Administration Server.</p> <p>Click select to select the credential from the wallet or add the credential to the wallet. When you click select, a dialog box will appear with a list of credentials to choose from only if you have provided the path to a wallet on the Composer Settings page (located in the File menu).</p> <ul style="list-style-type: none"> • If the credential exists in the wallet, select the credential from the list and click OK. • If the credential does not exist, click New to add the credential to the wallet.
Admin Server Url	<p>The URL used to connect to the domain's Administration Server in the following format:</p> <p><code>http://adminserver_host:adminserver_port</code></p> <p>Where:</p> <ul style="list-style-type: none"> • <code>adminserver_host</code> is the host name or IP address of the host where the Administration Server resides. • <code>adminserver_port</code> is the port number used by the Administration Server.
External Profile	Use this field to select a domain profile for the domain.
defaultCoherencePort	The port of the Coherence cluster.

Attribute	Description
Tuning Parameter Variables	<p>Use this field to define any variables you want to use when setting values for tuning parameters. A variable represents an actual value in your environment. A variable includes two parts:</p> <ul style="list-style-type: none"> • The Name of the variable. The name can contain alphanumeric characters. The % character should not be used in the variable name. • The Value of the variable. This is an actual value from your environment that the variable name represents. <p>The following reserved variables are fixed and cannot be changed:</p> <ul style="list-style-type: none"> • %ADMINSERVER%, which will always resolve to the name of the Administration Server. • %DOMAIN%, which will always resolve to the name of the domain.
Tuning Parameter Imports	<p>Use this field to import tuning parameter settings from a separate tuning parameter XML or JSON file.</p>
Tuning Parameter Settings	<p>Composer provides a predefined list of tuning parameter settings that you can apply to a domain.</p> <ul style="list-style-type: none"> • To add a new tuning parameter, click  to display a dialog box with a drop-down menu of available tuning parameters you can set. • To edit a value for an existing tuning parameter, select that parameter from the list of settings and click . • To remove a tuning parameter, select that parameter from the list of settings and click .
Tuning Parameter External Settings	<p>Use this field to add, remove, or edit an external tuning parameter setting (either MBean or WLST).</p> <ul style="list-style-type: none"> • Click  to add a MBean or WLST setting. • To remove an external tuning parameter setting, select that setting from the list and click . • To edit an existing external tuning parameter setting, select that setting from the list and click .

Blueprints Tab

Use the Blueprints tab to define the blueprints for the domain.

- Click  to add a blueprint to the domain.

If you have not provided the path to the Oracle home directory on the Composer Settings page (located in the File menu), you will be prompted to specify the path to the Oracle home.

- To edit a blueprint, select the blueprint from the list and click . This will open the blueprint file in a new tab.
- To remove a blueprint from the domain, select the blueprint from the list and click .

Server Groups Tab

The Server Groups tab displays a list of server groups only if at least one of the templates in a selected blueprint defines a server group. You can assign a server group to a server or cluster in this domain.

1.8.4 Server

The Server panel contains an Attributes tab that you can use to specify information (or attributes) for a server in the topology. The Server Groups tab allows you to select and assign server groups to the selected server.

Attributes Tab

Attribute	Description
ID	A unique name for the server used to identify this server from other elements in a domain. When you add a new server to a domain, the default ID is server1. If server1 is already used in the domain, FMW Composer will default to server2, then server3, and so on.
Is Admin Server	Select this option if this server is the Administration Server.
Name	Name of the server.
Listen Address	The IP address or DNS name this server uses to listen for incoming connections.
Listen Port	The port that this server uses to listen for regular (non-SSL) incoming connections.
SSL Listen Port	The port that this server uses to listen for SSL incoming connections.

Attribute	Description
Tuning Parameter Variables	<p>Use this field to define any variables you want to use when setting values for tuning parameters. A variable represents an actual value in your environment. A variable includes two parts:</p> <ul style="list-style-type: none"> • The Name of the variable. The name can contain alphanumeric characters. The % character should not be used in the variable name. • The Value of the variable. This is an actual value from your environment that the variable name represents. <p>The following reserved variables are fixed and cannot be changed:</p> <ul style="list-style-type: none"> • %ADMINSERVER%, which will always resolve to the name of the Administration Server. • %DOMAIN%, which will always resolve to the name of the domain. • %SERVER%, which will always resolve to the name of the server.
Tuning Parameter Imports	<p>Use this field to import tuning parameter settings from a separate tuning parameter XML or JSON file.</p>
Tuning Parameter Settings	<p>Composer provides a predefined list of tuning parameter settings that you can apply to a server.</p> <ul style="list-style-type: none"> • To add a new tuning parameter, click  to display a dialog box with a drop-down menu of available tuning parameters you can set. • To edit a value for an existing tuning parameter, select that parameter from the list of settings and click . • To remove a tuning parameter, select that parameter from the list of settings and click .

Server Groups Tab

The Server Groups tab displays the server groups assigned to the server.

- Click  to select server group(s) to assign to the server. A dialog box will appear with a list of server groups only if at least one of the templates in a selected blueprint defines a server group.
- Click  to remove or unassign the selected server groups from the server.

1.8.5 Node Manager

The Node Manager panel contains fields that you can use to specify information (or attributes) for a Node Manager in the topology.

Attribute	Description
ID	<p>A unique name for the Node Manager used to identify this Node Manager from other elements.</p> <p>When you add a new Node Manager, the default ID is nm1. If nm1 is already used in the topology, FMW Composer will default to nm2, then nm3, and so on.</p>
Name	Name of the Node Manager.
Credential	<p>The credential from the wallet that will be used to connect to the Node Manager.</p> <p>Click select to select the credential from the wallet or add the credential to the wallet. When you click select, a dialog box will appear with a list of credentials to choose from only if you have provided the path to a wallet on the Composer Settings page (located in the File menu).</p> <ul style="list-style-type: none"> • If the credential exists in the wallet, select the credential from the list and click OK. • If the credential does not exist, click New to add the credential to the wallet.
Tuning Parameter Variables	<p>Use this field to define any variables you want to use when setting values for tuning parameters. A variable represents an actual value in your environment. A variable includes two parts:</p> <ul style="list-style-type: none"> • The Name of the variable. The name can contain alphanumeric characters. The % character should not be used in the variable name. • The Value of the variable. This is an actual value from your environment that the variable name represents. <p>The following reserved variable is fixed and cannot be changed:</p> <ul style="list-style-type: none"> • %NODEMANAGER%, which will always resolve to the name of the Node Manager.
Tuning Parameter Imports	Use this field to import tuning parameter settings from a separate tuning parameter XML or JSON file.
Tuning Parameter Settings	<p>Composer provides a predefined list of tuning parameter settings that you can apply to a Node Manager, such as the Node Manager port.</p> <ul style="list-style-type: none"> • To add a new tuning parameter, click  to display a dialog box with a drop-down menu of available tuning parameters you can set. • To edit a value for an existing tuning parameter, select that parameter from the list of settings and click . • To remove a tuning parameter, select that parameter from the list of settings and click .

Attribute	Description
Tuning Parameter External Settings	<p>Use this field to add, remove, or edit an external tuning parameter setting (either MBean or WLST).</p> <ul style="list-style-type: none"> Click  to add a MBean or WLST setting. To remove an external tuning parameter setting, select that setting from the list and click . To edit an existing external tuning parameter setting, select that setting from the list and click .

1.8.6 Cluster

The Cluster panel contains an Attributes tab that you can use to specify information (or attributes) for a cluster in the topology. The Server Groups tab allows you to select and assign server groups to the selected cluster.

Attributes Tab

Attribute	Description
ID	<p>A unique name for the cluster used to identify this cluster from other elements in a domain.</p> <p>When you add a new cluster to a domain, the default ID is cluster1. If cluster1 is already used in the domain, FMW Composer will default to cluster2, then cluster3, and so on.</p>
Name	The name of the cluster.
Tuning Parameter Variables	<p>Use this field to define any variables you want to use when setting values for tuning parameters. A variable represents an actual value in your environment. A variable includes two parts:</p> <ul style="list-style-type: none"> The Name of the variable. The name can contain alphanumeric characters. The % character should not be used in the variable name. The Value of the variable. This is an actual value from your environment that the variable name represents. <p>The following reserved variables are fixed and cannot be changed:</p> <ul style="list-style-type: none"> <code>%ADMINSERVER%</code>, which will always resolve to the name of the Administration Server. <code>%DOMAIN%</code>, which will always resolve to the name of the domain. <code>%CLUSTER%</code>, which will always resolve to the name of the cluster.

Attribute	Description
Tuning Parameter Imports	Use this field to import tuning parameter settings from a separate tuning parameter XML or JSON file.
Tuning Parameter Settings	<p>Composer provides a predefined list of tuning parameter settings that you can apply to a cluster, such as the cluster address.</p> <ul style="list-style-type: none"> • To add a new tuning parameter, click  to display a dialog box with a drop-down menu of available tuning parameters you can set. • To edit a value for an existing tuning parameter, select that parameter from the list of settings and click . • To remove a tuning parameter, select that parameter from the list of settings and click .
Tuning Parameter External Settings	<p>Use this field to add, remove, or edit an external tuning parameter setting (either MBean or WLST).</p> <ul style="list-style-type: none"> • Click  to add a MBean or WLST setting. • To remove an external tuning parameter setting, select that setting from the list and click . • To edit an existing external tuning parameter setting, select that setting from the list and click .

Server Groups Tab

The Server Groups tab displays the server groups assigned to the cluster.

- Click  to select server group(s) to assign to the cluster. A dialog box will appear with a list of server groups only if at least one of the templates in a selected blueprint defines a server group.
- Click  to remove or unassign the selected server groups from the cluster.

1.8.7 Database

The Database panel contains fields that you can use to specify information (or attributes) for a database associated with the topology.

Attribute	Description
ID	<p>A unique name for the database used to identify the database from other elements.</p> <p>When you add a new database, the default ID is database1. If database1 is already used in the topology, FMW Composer will default to database2, then database3, and so on.</p>
Vendor	<p>The type of database server.</p> <p>Valid values are ORACLE, EBR, SQLSERVER, IBMDB2, or MYSQL.</p>
Driver Class	<p>The fully qualified Java class name of the non-XA JDBC driver.</p>
XA Driver Class	<p>The fully qualified Java class name of the XA JDBC driver.</p>
RCU Connect String	<p>The connect string used by RCU to connect to the database:</p> <p><i>db_host:db_port/service_name</i></p> <p>Where <i>db_host</i> is the host name of the machine on which the database resides, <i>db_port</i> is the listener port of the database, and <i>service_name</i> is the service name identified for the database.</p>
DBA Credential	<p>The credential from the wallet that will be used for actions that require DBA privileges.</p> <p>Click select to select the credential from the wallet or add the credential to the wallet. When you click select, a dialog box will appear with a list of credentials to choose from only if you have provided the path to a wallet on the Composer Settings page (located in the File menu).</p> <ul style="list-style-type: none"> • If the credential exists in the wallet, select the credential from the list and click OK. • If the credential does not exist, click New to add the credential to the wallet.
DBA Role	<p>Select the database user role from the drop-down list:</p> <ul style="list-style-type: none"> • SYSDBA (for the SYS user on Oracle databases) • Normal

Node

The Node panel contains fields that you can use to specify information (or attributes) for a node assigned to a database.

1.8.7.1 Node

The Node panel contains fields that you can use to specify information (or attributes) for a node assigned to a database.

Attribute	Description
ID	<p>A unique name for the node element used to identify the node from other elements.</p> <p>When you add a new node to a database, the default ID is node1. If node1 is already used within a database, FMW Composer will default to node2, then node3, and so on.</p>
Connect String	<p>The JDBC URL that is used to connect to the database repository.</p> <p>For example, for Oracle databases:</p> <pre>jdbc:oracle:thin:@db_host:db_port/service_name</pre> <p>Where <i>db_host</i> is the host name of the machine on which the database resides, <i>db_port</i> is the listener port of the database, and <i>service_name</i> is the service name identified for the database.</p>

1.8.8 Data Source

The Data Source panel contains fields that you can use to specify information (or attributes) for a data source.

Attribute	Description
Type	<p>The data source type. Valid types include:</p> <ul style="list-style-type: none"> • Generic: generic data source • Multi: multi data source
XA	<p>Specifies whether an XA driver must be used for the data source.</p>
Tuning Parameter Variables	<p>Use this field to define any variables you want to use when setting values for tuning parameters. A variable represents an actual value in your environment. A variable includes two parts:</p> <ul style="list-style-type: none"> • The Name of the variable. The name can contain alphanumeric characters. The % character should not be used in the variable name. • The Value of the variable. This is an actual value from your environment that the variable name represents. <p>The following reserved variables are fixed and cannot be changed:</p> <ul style="list-style-type: none"> • %ADMINSERVER%, which will always resolve to the name of the Administration Server. • %DOMAIN%, which will always resolve to the name of the domain.
Tuning Parameter Imports	<p>Use this field to import tuning parameter settings from a separate tuning parameter XML or JSON file.</p>

Attribute	Description
Tuning Parameter Settings	<p>Composer provides a predefined list of tuning parameter settings that you can apply to a data source, such as a timeout on a data source.</p> <ul style="list-style-type: none"> To add a new tuning parameter, click  to display a dialog box with a drop-down menu of available tuning parameters you can set. To edit a value for an existing tuning parameter, select that parameter from the list of settings and click . To remove a tuning parameter, select that parameter from the list of settings and click .
Tuning Parameter External Settings	<p>Use this field to add, remove, or edit an external tuning parameter setting (either MBean or WLST).</p> <ul style="list-style-type: none"> Click  to add a MBean or WLST setting. To remove an external tuning parameter setting, select that setting from the list and click . To edit an existing external tuning parameter setting, select that setting from the list and click .

1.8.9 Schema

The Schema panel contains fields that you can use to specify information (or attributes) for a schema.

Attribute	Description
Shared	<p>Use the drop-down list to specify whether the schema is shared with other domains. Valid values are No, Primary, or Yes.</p> <ul style="list-style-type: none"> No: The schema is not shared. Primary: The schema is owned by the current domain but shared with other domains. Yes: The schema is owned by another primary domain.
Credential	<p>The password for the schema.</p> <p>Click select to select the password from the wallet or add the password to the wallet. When you click select, a dialog box will appear with a list of credentials to choose from only if you have provided the path to a wallet on the Composer Settings page (located in the File menu).</p> <ul style="list-style-type: none"> If the credential exists in the wallet, select the credential from the list and click OK. If the credential does not exist, click New to add the credential to the wallet.

Attribute	Description
Prefix	Prefix for your schema.
Component Info	Full path to the location of the <code>ComponentInfo.xml</code> file. The default location is <code>ORACLE_HOME/oracle_common/rcu/config</code> .
Storage Location	Full path to the location of the <code>StorageInfo.xml</code> file. The default location is <code>ORACLE_HOME/oracle_common/rcu/config</code> .
Tablespace	Tablespace name of the component.
Temp Tablespace	TEMP tablespace name of the component.
Auxiliary Schema Credentials	The schema passwords for auxiliary schemas.

1.8.10 Web Tier

The Web Tier panel contains fields that you can use to specify information (or attributes) for a web tier component within the topology.

Attribute	Description
ID	A unique name used for the web tier component. When you add a new web tier, the default ID is tier1. If tier1 is already used in the topology, FMW Composer will default to tier2, then tier3, and so on.
Name	Name of the web tier component.
Type	Use the drop-down list to specify the component type: <ul style="list-style-type: none"> • OHS: Oracle HTTP Server • OTD: Oracle Traffic Director
Address	The listen address to use for this component.
Admin Credential	Click select to select the password from the wallet or add the password to the wallet. When you click select , a dialog box will appear with a list of credentials to choose from only if you have provided the path to a wallet on the Composer Settings page (located in the File menu). <ul style="list-style-type: none"> • If the credential exists in the wallet, select the credential from the list and click OK. • If the credential does not exist, click New to add the credential to the wallet.

Virtual Host

The Virtual Host panel contains fields that you can use to specify information (or attributes) for a virtual host.

1.8.10.1 Virtual Host

The Virtual Host panel contains fields that you can use to specify information (or attributes) for a virtual host.

Attribute	Description
ID	A unique name used for the virtual host. When you add a new virtual host to a web tier component, the default ID is host1. If host1 is already used within a web tier, FMW Composer will default to host2, then host3, and so on.
Name	Name of the virtual host.
Server Address	The server address for this virtual host.
Server Admin	The email address for the server administrator. This is displayed on error pages to help the user contact technical support.
Protocol	The protocol to use (HTTP or HTTPS).

Location

1.8.10.1.1 Location

Attribute	Description
ID	A unique name for the Location element. When you add a new location element to a virtual host, the default ID is loc1. If loc1 is already used within a virtual host element, FMW Composer will default to loc2, then loc3, and so on.
WebLogic Host	The host name for the Administration Server.
WebLogic Port	The port for the Administration Server.
WebLogic Cluster	List of Oracle WebLogic clusters that can be used for load balancing.
Handler	weblogic-handler
WL Proxy SSL	Valid values are ON or OFF .
WL Proxy SSL Pass Through	Valid values are ON or OFF .

1.9 Tuning Parameter Settings

Tuning parameters allow you to customize or tune additional configuration settings for various elements.

FMW Composer provides a predefined list of parameters that you can edit for the following elements:

- Domain
- Server
- Cluster

- Node Manager
- Data Source

To add a tuning parameter for an element, select that element on the current page.

Then, in the **Attributes** panel, click  under **Tuning Parameter Settings**. This will display a dialog box with a drop-down menu of available tuning parameters you can set.

1.10 Validation Panel

The validation panel allows you to quickly see and correct any errors that occur while you are editing a topology, blueprint, or domain profile.

To locate an error in FMW Composer, select the error message from the list, and then click . You can also double-click the error message to go straight to the panel that contains the error.

After you correct the errors, click  to refresh the list and verify that the errors have been resolved.