

User Defined Events User Guide

**Oracle FLEXCUBE Universal Banking**

Release 12.0.3.0.0

**Part No. E53393-01**

April 2014

User Defined Events User Guide  
April 2014  
Oracle Financial Services Software Limited

Oracle Park

Off Western Express Highway  
Goregaon (East)  
Mumbai, Maharashtra 400 063  
India

Worldwide Inquiries:

Phone: +91 22 6718 3000

Fax: +91 22 6718 3001

[www.oracle.com/financialservices/](http://www.oracle.com/financialservices/)

Copyright © 2007, 2014, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

---

# Contents

<b>1. Preface .....</b>	<b>1-1</b>
1.1 Introduction.....	1-1
1.2 Documentation Accessibility.....	1-1
1.3 Organization .....	1-1
1.4 Glossary of Icons.....	1-1
1.5 Related Documents .....	1-1
<b>2. User Defined Events .....</b>	<b>2-1</b>
2.1 Introduction.....	2-1
2.2 Indicating the Event Details .....	2-1
2.2.1 <i>Specifying Default Details</i> .....	2-3
2.2.2 <i>Value Date Derivation</i> .....	2-4
2.2.3 <i>Event Processing</i> .....	2-5
2.2.4 <i>Calculating the Commission on the Highest Outstanding Balance</i> .....	2-5
2.3 Maintaining Accounting Roles and Heads.....	2-6
2.3.1 <i>Amount Tag Tab</i> .....	2-6
2.3.2 <i>Accounting Roles Tab</i> .....	2-10
2.4 Triggering User Defined Events Automatically .....	2-11
<b>3. Contract Events .....</b>	<b>3-1</b>
3.1 Introduction.....	3-1
3.2 Viewing Event Details.....	3-1
3.2.1 <i>Viewing Accounting Entries</i> .....	3-1
3.2.2 <i>Viewing Messages</i> .....	3-3
<b>4. Function ID Glossary .....</b>	<b>4-1</b>

---

# 1. Preface

## 1.1 Introduction

This manual is intended as a guide to help you define Events in FLEXCUBE. Besides this User Manual, you can find answers to specific features and procedures in the Online Help, which can be invoked, by choosing 'Help Contents' from the *Help* Menu of the software. You can further obtain information specific to a particular field by placing the cursor on the relevant field and striking <F1> on the keyboard.

## 1.2 Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

## 1.3 Organization

This manual is organized as follows:

<b>Chapter 1</b>	<i>About this Manual</i> gives information on the intended audience. It also lists the various chapters covered in this User Manual.
<b>Chapter 2</b>	<i>User Defined Events</i> explains how to define events in Oracle FLEXCUBE either for your own convenience or to suit the requirements of your bank.
<b>Chapter 3</b>	Contract events explains how you can trigger an event at appropriate stages of a contract lifecycle.
<b>Chapter 4</b>	<i>Function ID Glossary</i> has alphabetical listing of Function/Screen ID's used in the module with page references for quick navigation.

## 1.4 Glossary of Icons

This User Manual may refer to all or some of the following icons.

Icons	Function
	Exit
	Add row
	Delete row
	Option List

## 1.5 Related Documents

For further information on procedures discussed in the manual, refer to the Oracle FLEXCUBE manuals on:

- Core Services
- Common Procedures

## 2. User Defined Events

### 2.1 Introduction

A User Defined Event explains how to define events in Oracle FLEXCUBE either for your own convenience or to suit the requirements of your bank.

### 2.2 Indicating the Event Details

You can define the events through the 'User defined Events' screen. You can invoke this screen by typing 'UDDEVMNT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

You can define events for a new module and also for existing modules in this screen.

The screenshot shows the 'Main Screen' interface for defining user-defined events. The window title is 'Main Screen'. At the top, there are buttons for 'New' and 'Enter Query'. The main area contains the following fields and sections:

- Report Module \***: A dropdown menu with a list icon.
- Event Code \***: A text input field.
- Event Description**: A text input field.
- Accounting Entries Definition**: A dropdown menu set to 'No'.
- Advice Definition**: A dropdown menu set to 'No'.
- UDE Advices Definition**: A dropdown menu set to 'No'.
- Association**: A section with two dropdown menus: 'Allow Charge' (set to 'No') and 'Allow Transaction Tax' (set to 'No').
- Application**: A section with two dropdown menus: 'Allow Charge' (set to 'No') and 'Allow Transaction Tax' (set to 'No').
- Liquidation**: A section with two dropdown menus: 'Allow Charge' (set to 'No') and 'Allow Transaction Tax' (set to 'No').

At the bottom, there is a 'Fields | Default' section with a legend for 'Authorized' (represented by a square) and 'Open' (represented by a square).

User defined events will be linked to a product and is triggered in the life cycle of a contract, which is processed under that product.

#### Report Module

Specify the module for which you want to set up a user-defined event. The adjoining option list contains all the module codes available in the system. Select the appropriate one.

#### Event Code

Specify the event code that you want to set up for the module.

#### Event Description

Give a brief description of the event that you are defining. The description that you enter is for information purposes.

#### Accounting Entries Definition

Specify the accounting entries definition. You have the following options:

- Yes

- No

### **Advice Definition**

Specify the advice entries definition. You have the following options:

- Yes
- No

### **UDE Advices Definition**

Specify the UDE advice definition. You have the following options:

- Yes
- No

### **Association**

Indicate your preferences.

#### **Allow Charge**

Specify the association allow charge. You have the following options:

- Yes
- No

#### **Allow Transaction Tax**

Specify the association allow transaction tax. You have the following options:

- Yes
- No

### **Application**

Indicate your preferences. Note that these fields will not be applicable if you have specified any one of the following in the 'Report Module' field:

- CL
- CI
- LE
- MO

#### **Allow Charge**

Specify the application allow charge. You have the following options:

- Yes
- No

#### **Allow Transaction Tax**

Specify the application allow transaction tax. You have the following options:

- Yes
- No

### **Liquidation**

Indicate your preferences. Note that these fields will not be applicable if you have specified any one of the following in the 'Report Module' field:

- CL

- CI
- LE
- MO

**Allow Charge**

Specify the liquidation allow charge. You have the following options:

- Yes
- No


**Allow Transaction Tax**

Specify the liquidation allow transaction tax. You have the following options:

- Yes
- No

**2.2.1 Specifying Default Details**

Click 'Default' button in the 'User Defined Events' screen to define the triggering parameters for the configured event.



In this screen you can enter the following details below:

**Module Code**

The system displays the module code here.

**Event Code**

The system displays the event code here.

**Event Trigger**

The event, which you are defining, can be triggered in either of the following ways:

- Automatic – This means that the event should be triggered automatically during EOD.

- Manual - This means that the event should be triggered manually from the 'User Defined Event' triggering screen.

**Value Date Derivation**

Check this box to indicate that the value date derivation is defined for a particular event.

**Event Processing**


Check this box to indicate the event processing is defined for a particular event.

**Execution Query**

Enter the query condition to select the list of accounts for the execution of the event during EOD. Input to this field will be mandatory if you choose 'Automatic' triggering of the event.

**2.2.2 Value Date Derivation**

Click 'Value Date Derivation' button on the 'Event Trigger' screen and invoke the 'Derivation Rule' screen to specify the value date derivation logic.



In this screen you can enter the following details:

**Module Code**

The system displays module code here.

**Event Code**

The system displays event code here.

**Value Date Derivation Rule**


Enter description about the value date derivation rule. You need to assign a value to 'L\_VAL\_DT'. For instance, 'L\_VAL\_DT:=global.application\_date'.

**Error**

Click 'X' button to execute the code. The derivation code will be validated by the system. If any checks fail, you must alter the statement so that the validation can be made successfully. Click 'E' button to view the errors.

## 2.2.3 Event Processing

Click 'Event Processing' button on the 'Event Trigger' screen and invoke the 'Derivation Rule' screen to assign values for processing of the event.



In this screen you can enter the following details:

### **Module Code**

The system displays module code here.

### **Event Code**

The system displays event code here.

### **Errors**

Click 'X' button to execute the code. The derivation code will be validated by the system. If any checks fail, you must alter the statement so that the validation can be made successfully. Click 'E' button to view the errors.

## 2.2.4 **Calculating the Commission on the Highest Outstanding Balance**

System uses UDE to calculate the commission on the highest outstanding balance of the loan and the mortgage Accounts.

You can define a UDE Highest Debit Balance Commission Event (HDBC) for computation of commission with following parameters:

- Event Trigger can be either Auto or Manual
- Apply Charge should be Yes
- Execution Query should be all accounts which satisfy the following criteria:
  - Account Status is Active
  - Outstanding Principal is greater than 0.00
- Value Date derivation rule to return the date as month-end
- This event is available at Loan and Mortgage product level.

## 2.3 Maintaining Accounting Roles and Heads

You can define the amount tags for accounting roles through the 'Accounting Role and Head Maintenance' screen. You can invoke this screen by typing 'UDDRLTAG' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

You can specify the following parameters for the module:

- Amount Tag
- Accounting Roles

### 2.3.1 Amount Tag Tab

This tab is displayed by default when you invoke the screen.

#### **Amount Tag**

Specify the amount tag.

#### **Description**

Enter the brief description for amount tag.

#### **Charge**

Indicate whether the amount tag pertains to a charge or not by choosing one of the following options:

- Yes

- No

### Accounting

Indicate whether accounting entries are required or not by choosing one of the following options:

- Yes
- No

### Transaction Tax

Indicate whether transaction tax is applicable or not by choosing one of the following options:

- Yes
- No

### Local Currency

Indicate the local currency preference by choosing one of the following options:

- Average
- Equivalent

### Local Currency Eq. Tag

Specify the amount tag for the local currency equivalent amount.

Click 'Derivation' button and invoke the 'Derivation Rule Details' screen to derive the amount and currency for the amount tag.

Here you can specify derivation logic for the following:

- Amount Rule
- Currency Rule

### **Module Code**

The system displays module code here.

### **Amount Tag**

The system displays the amount tag here.

### **Amount Rule Derivation**

You can specify the following details.

#### **Amount Rule Type**

Check this box if the amount has to be derived based on a specified condition. The amount for a particular tag can be derived based on a condition.

#### **Derivation Amount Rule**

If you have checked against the option 'Amount Rule Type', the system will derive the amount for the amount tag that is being defined. You can use the following as variables while creating the derivation rule:

- Account Level UDF
- SDE

You can use any of the following SDEs:

- CUSTOMER\_CATEGORY - Category of the customer of the loan
- CUSTOMER\_ID - Customer ID
- LOAN\_STATUS - Status
- ACCOUNT\_CCY - Loan account's currency
- TODAY - Today
- NEXT\_WORKDAY - Date of next workday
- PAYMENT\_VALUE\_DATE - Payment value date
- LAST\_PAYMENT\_DATE - Last payment date for the customer
- DAYS\_FOR\_NEXT\_PMNT - Days for next payment
- AMOUNT\_DISBURSED - Current disbursement amount
- COMMITMENT\_UTILIZED - Utilized part of commitment
- EMI\_AMOUNT - EMI AMOUNT
- NET\_PRINCIPAL - Non-funded amount for which the loan is applied
- TOTAL\_DUE\_AMOUNT - Sum of all the Outstanding Balances for the Customer
- LAST\_PAYMENT\_AMOUNT - Last Payment Amount for the Customer
- CURRENT\_PAYMENT\_AMOUNT - Current Amount which is Due
- PAID\_INTEREST\_AMOUNT - Total Interest Amount Paid
- INTEREST\_ACCRUED\_AMOUNT - Sum of all the Accrued Amounts for Interest
- AMOUNT\_NOT\_DISBURSED - Amount Not Disbursed
- COMMITMENT\_UNUTILIZED - Unutilized part of commitment
- TOTAL\_PRINCIPAL - Amount for which the loan is applied
- TENOR - Duration for which the loan is applied
- LOAN\_PRINCIPAL - Principal
- PRINCIPAL - Amount disbursed
- PRINCIPAL\_OUTSTAND - Principal amount outstanding
- OVERDUE\_MONTHS - OverDue Months

- TOTAL\_OVERDUE\_AMOUNT - Total Overdue amount for all components
- INS\_TENOR - INSTALLMENT TENOR
- NO\_OF\_RPMNT\_SCHS - Number of Non-Moratorium repayment schedules
- MORA\_OUTSTANDING - Moratorium Outstanding Amount
- COMPOUND\_VALUE - Amount Compounded
- TOTAL\_MORA\_AMOUNT - Total Moratorium Amount
- \_OVR\_DAYS - <Component> overdue days
- \_EXPECTED - <Component> expected amount
- \_OUTSTAND - <Component> outstanding amount
- \_CCY - <Component> currency
- \_OVERDUE - <Component> overdue amount
- \_FN\_NO\_REPAY\_SCH - <Component> number of schedules for a component if periodic
- \_NET\_PRINCIPAL - <Component> amount financed
- PROJECTED\_AMOUNT - Projected Amount
- UIDB\_DIFFERENTIAL - UIDB Differential
- BALLOON\_AMOUNT - Balloon Amount
- RESIDUAL\_AMOUNT - Residual Amount
- CAPITAL\_AMOUNT - Capital Amount
- CLOSURE\_AMOUNT - Closure Amount
- NET\_MORTGAGE - Net Mortgage Amount

Assume that you have an account-level UDF called 'OSCHGRATE'.

The derivation rule using the SDEs and UDF may be given as under.

DECLARE

l\_osprin\_amt number;

rate number;

BEGIN

l\_osprin\_amt:=(@SDE\_VAL#PRINCIPAL\_OUTSTAND);

rate:=(@UDF\_UD#OSCHGRATE);

l\_amount:=rate \* l\_osprin\_amt;

END

### **Amount Rule Error Description**

Enter a brief description about amount rule error that should be displayed in case the derivation fails.

### **Currency Rule Derivation**

The currency can either be derived from the existing account currency or can be maintained as a UDF field in the account or it can be hard-coded in the 'Currency Rule Definition' screen.

### Currency Rule Type

Check this box if the currency for a particular amount tag has to be derived based on the derivation rule.

### Derivation Currency Rule

Specify the rule based on which the system should derive the currency for the amount tag. Note that you need to assign a value to 'L\_CCY'. For instance, the rule may be given as under.

```
BEGIN

SELECT currency

INTO    l_ccy

FROM    cltb_account_master

WHERE  account_number = p_acc_no

AND    branch_code=p_branch;


END;
```

### Currency Rule Error Description

Enter a brief description about currency rule error that should be displayed in case the derivation fails.

## 2.3.2 Accounting Roles Tab

Click 'Accounting Roles' tab in the 'Accounting Role and Head Maintenance' screen.



The screenshot displays the 'Accounting Role and Head Maintenance' window. At the top, there are 'New' and 'Enter Query' buttons. Below them are input fields for 'Module Code \*' and 'Description'. A tabbed interface shows 'Amount Tag' and 'Accounting Roles' tabs, with 'Accounting Roles' selected. Underneath is the 'Account Rule Details' section, which contains a table with columns for 'Role Code', 'Description', and 'Role Type'. The 'Role Type' column has a dropdown menu currently set to 'Asset'. At the bottom of the window, there are fields for 'Input By', 'Authorized By', and 'Modification Number', each with a 'Date Time' field. There are also checkboxes for 'Authorized' and 'Open'.

In this screen you can enter the following details:

#### Role Code

Specify the role code.

## Description

Enter a brief description about role code.

## Role Type

Select the role type from the adjoining drop-down list. The following values are available:

- Asset
- Liability
- Income
- Expense
- C Asset
- C Liability
- Customer

## 2.4 Triggering User Defined Events Automatically

You can add the user defined event batch to the mandatory programs to be run for the module, using the 'Mandatory Batch Program Maintenance' screen. You can invoke this screen by typing 'EIDMANPE' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Mandatory Batch Program Maintenance' window. It features several input fields and radio buttons for configuration. The 'Branch' field is set to '000'. The 'End of Cycle Group' has radio buttons for 'Txn Input', 'End of Txn Input', 'End of Fin Input', 'End of Day', and 'Beginning of Day'. The 'Error Handling' section has radio buttons for 'Stop Automatic End of Day and Run Emergency Program' and 'Continue with Automatic End of Day'. The 'Frequency' is set to 'Daily' and the 'Holiday Rule' is 'Do Not Execute'. The 'Execution Layer' has radio buttons for 'Database' and 'Application'. The 'Sub Stage' is set to '1'. The 'Predecessors' section shows '1 Of 1' and a 'Go' button. The bottom of the screen has a 'Fields' section with 'Maker', 'Checker', 'Mod No', 'Date Time', 'Record Status', 'Authorization Status', and an 'Exit' button.

## Module

Choose the module code from the adjoining option list.

**Function Identification**

Specify 'UDBATEVT' as the batch that needs to be run. You can also select this value from the adjoining option list.

**End Of Cycle Group**

Select the option 'End Of Transaction Input'.

**Predecessors**

You need to add the following batches as predecessors to the 'UDBATEVT' batch:

- CL batch (CLBATCH)
- Islamic CL batch (CIDBATCH)
- Leasing batch (LEDBATCH)
- Mortgage batch (MODBATCH)

*For further details about this screen, refer the chapter 'Setting- up Mandatory Programs for EOD' in the AEOD User Manual.*

This batch fetches the list of user defined events of the following modules for which the event triggering is set as 'Automatic':

- CL
- Islamic Financing
- Mortgages
- Leasing

It fetches valid accounts associated with the event by the executing the query defined for the event in the 'Event Trigger' screen. The settlement account and branch are defaulted from the settlement details maintained for the account. If these details are not maintained, they will be defaulted from the settlement details maintained for the 'Principal' component.

The system triggers the derivation rule maintained for the event to arrive at the value date of the event. The system then posts accounting entries to the respective GLs using the value date derived. The system also derives the amount and currency for each amount tag of the accounting entries defined for the event. The system allows you to link only payment advice 'CR\_ADV, DR\_ADV' to the user defined event. So if linked to an account, this advice will be generated.

---


## 3. Contract Events

### 3.1 Introduction

A contract that you process in Oracle FLEXCUBE goes through different stages during its life cycle. These stages are defined as Events. Every new module that you maintain has to be associated with a set of events, which will be triggered at appropriate stages during the lifecycle of the contract.

### 3.2 Viewing Event Details

You can view the event details under 'Events' screen of a contract screen. To invoke the 'Events' screen type 'CSDEVENT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



#### **Reference Number**

Specify the reference number.

The system displays the following details:

- Event Number
- Event code
- Description
- Event Date
- Authorization Status
- Maker Id
- Checker Id

#### 3.2.1 Viewing Accounting Entries

You can view the accounting entries maintained for an event in the 'Accounting Entries' screen by selecting an event and clicking on 'Accounting Entries' button in the 'Events'

screen. To invoke the screen type 'CSDACENT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows the 'Accounting Entries' application window. At the top, there is a title bar with the text 'Accounting Entries'. Below the title bar is a search area labeled 'Enter Query' containing three input fields: 'Reference Number \*', 'Event \*', and 'Event Number \*'. A checkbox labeled 'See Position Entries' is checked. Below the search area is a tabbed interface with two tabs: 'Accounting Entries' (selected) and 'Overrides'. The main content area displays a table with the following columns: Event, Branch, Account, Account Description, Dr/Cr, Amount Tag, Account Ccy, Foreign Currency Amount, Rate, Local Currency Amount, and Date. The table is currently empty. At the bottom right corner, there is an 'Exit' button.

### Reference Number

Specify the transaction reference number

### See Position Entries

Check this box to view currency position of the entries.

### Event

Specify the event.

### Event Number


The system displays the event number.

The following details are displayed in the Accounting Entries:

- Event
- Branch
- Account
- Account Description
- Dr/Cr
- Amount Tag
- Account Ccy
- Foreign Currency Amount
- Rate
- Local Currency Amount
- Date
- Value Date
- Txn Code


## Override Details

Click on 'Overrides' button to view the override details of the accounting entries.



### 3.2.2 Viewing Messages

You can view the messages by selecting an event and clicking on 'Messages' button in the 'Events' screen. To invoke the screen type 'CSDMSGVW' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.




The system displays the following details:

- Contract Reference
- ESN
- Event
- Message Type
- SWIFT Message Type
- Medium
- Message Status
- Authorization Status
- Receiver

- Receiver Name
- DCN

### **Message Details**

You can view the details of a message by selecting a message from the 'Message' screen and clicking on 'Message Details' button.



The screenshot shows a web application window titled "Message". At the top, there is a search bar labeled "Enter Query". Below the search bar, there are several input fields for filtering messages:

Reference Number	<input type="text"/>	Receiver/Sender	<input type="text"/>
DCN *	<input type="text"/>	Message Type	<input type="text"/>
Version Number	<input type="text"/>	SWIFT Message Type	<input type="text"/>

Below the filters, there is a table with a header "Message" and a single entry. The table is currently empty, showing "1 Of 1" results. At the bottom right of the window, there is an "Exit" button.

---

## 4. Function ID Glossary

### E

EIDMANPE .....2-11

### U

UDDEVMNT .....2-1

UDDRLTAG .....2-6