

Core Services User Guide

Oracle FLEXCUBE Universal Banking

Release 14.3.0.1.1

Part No. F18207-01

December 2019

Core Services User Guide
Oracle Financial Services Software Limited
Oracle Park

Off Western Express Highway
Goregaon (East)
Mumbai, Maharashtra 400 063
India

Worldwide Inquiries:

Phone: +91 22 6718 3000

Fax: +91 22 6718 3001

<https://www.oracle.com/industries/financial-services/index.html>

Copyright © 2007, 2019, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Contents

1. Preface	1-1
1.1 Introduction	1-1
1.2 Audience	1-1
1.3 Documentation Accessibility	1-1
1.4 Organization	1-1
1.5 Related Documents	1-3
1.6 Glossary of Icons	1-3
2. Bank Parameters	2-1
2.1 Bank Parameters Maintenance	2-1
2.1.1 <i>Defining Bank Level Parameters</i>	2-1
2.1.2 <i>Financial Preferences Tab</i>	2-2
2.1.3 <i>General Preferences Tab</i>	2-5
2.1.4 <i>FATCA Tab</i>	2-7
2.1.5 <i>Regulatory Limits</i>	2-9
2.1.6 <i>Preferences Button</i>	2-10
2.1.7 <i>Account Mask Button</i>	2-18
2.2 Confirmation/Affirmation Type Maintenance	2-28
2.2.1 <i>Invoking Confirmation/ Affirmation Type Maintenance</i>	2-28
2.2.2 <i>Viewing Confirmation/ Affirmation Type Summary Details</i>	2-29
2.3 Branch Restriction Maintenance	2-29
2.3.1 <i>Placing User Restrictions on Data Entry Batches</i>	2-30
2.3.2 <i>Fields Button</i>	2-34
2.4 Maintaining Global Intermediary Identification Number	2-34
2.5 Maintaining Charge Transaction Codes	2-35
3. Ramadan Maintenance	3-1
3.1 Maintaining Ramadan Day	3-1
4. Dealer Maintenance	4-1
4.1 Defining Dealer	4-1
5. Branch Parameters	5-1
5.1 Branch Parameter Maintenance	5-1
5.1.1 <i>Creating Branches</i>	5-1
5.1.2 <i>System Features</i>	5-2
5.1.3 <i>Creating Reporting Structure</i>	5-2
5.1.4 <i>Maintaining Branch Parameters</i>	5-3
5.1.5 <i>General Details Tab</i>	5-4
5.1.6 <i>Account Financial Details Tab</i>	5-9
5.1.7 <i>Duplication Check Details Tab</i>	5-14
5.1.8 <i>International Bank Account Number Details Tab</i>	5-15
5.1.9 <i>SWIFT Address Button</i>	5-17
5.1.10 <i>Account Mask Button</i>	5-18
5.1.11 <i>CIF Range Button</i>	5-19
5.1.12 <i>Global Interdict Functions Button</i>	5-22
5.1.13 <i>Preferences Button</i>	5-23
5.1.14 <i>Fields Button</i>	5-30

5.1.15	<i>Tax Button</i>	5-31
5.1.16	<i>Branch Currency Button</i>	5-32
5.1.17	<i>Account Statement Handoff</i>	5-33
5.1.18	<i>Account Statement Generation</i>	5-33
5.2	Maintaining Tax Cycle	5-33
5.3	Branch Level Role to Head Mapping	5-34
5.3.1	<i>Maintaining Role to Head Mapping at Branch Level</i>	5-34
5.3.2	<i>Viewing Accounting Role to Head Mapping Details</i>	5-35
6.	Account Branch Transfer	6-1
6.1	Maintaining Branch Transfer Parameters	6-1
6.2	Customer Account Branch Transfer	6-2
6.2.1	<i>Transferring Customer Account Branch</i>	6-2
6.2.2	<i>Viewing Account Branch Transfer Details</i>	6-5
6.3	Transferring Account Class Branch	6-6
6.4	Processing Account Branch Transfer Batch	6-7
7.	Web Service Maintenance	7-1
7.1	Maintaining Web Service	7-1
7.2	Mapping of Web Service	7-2
7.3	Web Service Details	7-3
7.4	WebService Maintenance	7-4
8.	Accounts for Inter-Branch Transactions	8-1
8.1	Defining Accounts for Inter-Branch Transactions	8-1
8.1.1	<i>System Features</i>	8-2
8.2	Defining Accounts for Inter-Branch Fund Transactions	8-4
8.3	Defining Accounts for Inter-Branch Currency Transactions	8-5
8.4	Querying on Netting Batch	8-7
9.	Error Queue Definition and Accounting Referral Queue	9-1
9.1	Maintaining Error Queue	9-1
9.1.1	<i>Error Code List</i>	9-2
9.2	Viewing Accounting Referral Queue	9-4
10.	Product Restrictions Maintenance	10-1
10.1	Product Restriction	10-1
10.1.1	<i>Maintaining Product Restrictions</i>	10-1
10.1.2	<i>Viewing Product Restrictions</i>	10-3
11.	Restriction Maintenance at Customer Level	11-1
11.1	Restriction Code Maintenance	11-1
11.1.1	<i>Maintaining Restriction Codes</i>	11-1
11.1.2	<i>Viewing Restriction Codes</i>	11-5
11.2	Restriction Code- Customer/Customer Category Linkage	11-6
11.3	Customer Restriction Inquiry	11-7
11.4	Restriction Utilization Tracking	11-9
12.	Sanction Check Maintenance	12-1
12.1	Sanction Check System Maintenance	12-1
12.1.1	<i>Maintaining Sanction Check System Details</i>	12-1
12.1.2	<i>Status Mapping</i>	12-3
12.1.3	<i>Viewing Sanction Check System Details</i>	12-3
12.2	Sanction Check Branch Parameters	12-4
12.2.1	<i>Maintaining Sanction Check Branch Parameters</i>	12-4
12.3	Sanction Check Queue	12-5

12.3.1	<i>Viewing Sanction Check Queue Details</i>	12-5
12.3.2	<i>Viewing Status Change Details</i>	12-6
12.3.3	<i>Viewing Sanction Check Status Change History</i>	12-8
12.3.4	<i>Authorizing Sanction Check Status Change</i>	12-8
12.4	Sanction Check Request Process	12-9
12.4.1	<i>Processing Sanction Check Request for a New Entity</i>	12-10
12.4.2	<i>Processing Sanction Check Request for an Existing Entity</i>	12-10
12.4.3	<i>Processing Sanction Check Request for Reopen of an Existing Entity..</i>	12-10
12.4.4	<i>Sanction Check Notification to External System</i>	12-10
12.4.5	<i>Periodic Sanction Check Request</i>	12-11
13.	Currency Maintenance	13-1
13.1	Handling Euro	13-1
13.1.1	<i>Maintaining Euro Related Information</i>	13-1
13.1.2	<i>Maintaining Limits Type</i>	13-8
13.1.3	<i>Maintaining Transaction Limits</i>	13-8
13.2	Maintaining Sequence Generation Format	13-12
13.3	Maintaining Corporate Deposits Currency Limits	13-15
14.	Currency Denomination	14-1
14.1	Currency Denomination Maintenance	14-1
14.1.1	<i>Maintaining Currency Denomination Details</i>	14-1
14.1.2	<i>Operations Allowed in the Currency Denomination Screen</i>	14-2
14.2	Maintaining Denomination-wise Variance	14-2
15.	Maintaining Limits for Cross Currency Transactions	15-1
15.1	Specifying Limits for Cross Currency Transactions	15-1
16.	Limit Revaluation	16-1
16.1	Limits Revaluation Input	16-1
16.1.1	<i>Maintaining Limits Revaluation Details</i>	16-1
16.1.2	<i>Viewing Limit Revaluation Details</i>	16-3
17.	Maintaining Currency Spread for Customer	17-1
17.1	Currency Spread Maintenance	17-1
17.1.1	<i>Maintaining Customer Spread Details</i>	17-1
17.1.2	<i>Maintaining Currency Margins for Customer</i>	17-3
18.	Cluster Deposits	18-1
18.1	Cluster Deposit Maintenance	18-1
18.1.1	<i>Invoking the Deposit Cluster Maintenance Screen</i>	18-1
18.1.2	<i>Viewing Corporate Deposits Cluster Details</i>	18-2
19.	Period Code Maintenance	19-1
19.1	Period Code Maintenance	19-1
19.1.1	<i>Maintaining Period Code</i>	19-1
19.1.2	<i>System Functions</i>	19-3
20.	Status Code Maintenance	20-1
20.1	Status Codes Maintenance	20-1
20.1.1	<i>Invoking Status Maintenance Screen</i>	20-2
20.1.2	<i>Maintaining Status Codes for OD Account</i>	20-3
20.2	Maintaining Dormancy Parameter Details	20-3
20.3	Maintaining Central Bank Dormancy Details	20-5
21.	Transaction Code	21-1
21.1	Transaction Code Maintenance	21-1
21.1.1	<i>Invoking Transaction Code Screen</i>	21-1

21.1.2	Transactions Tax Button.....	21-9
22.	Transaction Tax	22-1
22.1	Transaction Tax Maintenance	22-1
22.1.1	Invoking Transaction Tax Maintenance Screen	22-1
22.1.2	Viewing Transaction Tax Details	22-2
23.	City Code	23-1
23.1	City Code Maintenance	23-1
23.1.1	Invoking the City Code Maintenance Screen	23-1
23.1.2	Viewing City Code Details	23-2
24.	Employment Details	24-1
24.1	Employment Detail	24-1
24.1.1	Invoking the Employment Details Screen.....	24-1
24.1.2	Viewing Employment Details	24-2
25.	Employment Detail Maintenance	25-1
25.1	Employment Detail Maintenance	25-1
25.1.1	Invoking the Employment Detail Maintenance Screen.....	25-1
25.1.2	Viewing Employment Type Details	25-2
26.	Account Revaluation Maintenance	26-1
26.1	Account Revaluation Setup	26-1
26.1.1	Maintaining Account Revaluation	26-1
27.	Maintaining Branch Holidays	27-1
27.1	Branch Holiday Maintenance.....	27-1
27.1.1	Designating Unexpected Holidays for Branch.....	27-1
28.	Holiday File Upload	28-1
28.1	Uploading Holiday File.....	28-1
29.	Maintaining Clearing Holidays	29-1
29.1	Clearing House Holiday Maintenance	29-1
29.1.1	Maintaining Clearing House Holidays.....	29-2
29.1.2	Steps to Define Clearing House Holidays	29-2
29.1.3	Defining Clearing House Holidays.....	29-3
29.1.4	Designating Unexpected Holidays for Clearing House.....	29-3
30.	Document Maintenance	30-1
30.1	Document Type Maintenance.....	30-1
30.1.1	Maintaining Document Type.....	30-1
30.1.2	Viewing Document Type Details.....	30-2
30.2	Document Checklist Maintenance	30-2
30.2.1	Maintaining Document Checklist Details	30-3
30.2.2	Viewing Document Type Details.....	30-4
31.	Configuring Overrides	31-1
31.1	Types of Overrides	31-1
31.2	Override Maintenance	31-2
31.2.1	Maintaining Overrides.....	31-2
31.2.2	Maintaining Error Messages.....	31-3
31.3	Maintaining Conversion Overrides	31-4
32.	Other Maintenances	32-1
32.1	Feature ID Maintenance	32-1
32.1.1	Maintaining Feature ID	32-2
32.1.2	Fields Button.....	32-4

32.1.3	Viewing Feature ID Summary.....	32-4
32.2	Feature Maintenance.....	32-5
32.2.1	Maintaining Feature.....	32-6
32.2.2	Fields Button.....	32-6
32.3	Category Maintenance	32-6
32.4	Exposure Type Maintenance.....	32-7
32.5	Group Maintenance	32-8
32.6	Haircut Maintenance.....	32-9
32.7	Location Maintenance	32-10
32.8	Static Type Maintenance	32-11
32.9	Unique Identifier Maintenance	32-12
32.10	Replication Mode Maintenance	32-13
32.11	Local Collateral Maintenance	32-15
32.11.1	Linkage tab.....	32-17
32.12	Customer Limit Details	32-18
32.13	Product UDF Mapping	32-19
32.14	GL Mask Maintenance for Multitenant Deployment.....	32-20
32.14.1	Viewing Multi Tenant Parameter Summary.....	32-21
33.	Support 24x7	33-1
33.1	Gateway Messaging	33-1
33.2	Web Branch.....	33-1
33.3	Batch Processing	33-1
33.4	Processing Different Categories During EOD	33-2
34.	Purging Data	34-1
34.1	Data Purging.....	34-1
34.1.1	Module Purging	34-1
34.1.2	Maintaining Purge Details.....	34-2
34.1.3	Entity Purging	34-3
34.1.4	Defining Subsystem Purging	34-4
34.2	Purge Parameter Configuration.....	34-5
34.2.1	Configuring Purge Parameters	34-5
34.2.2	Branch Restrictions Button	34-7
34.2.3	Viewing Purge Parameter Configuration Details	34-7
34.3	Processing Ad-hoc Purge.....	34-8
34.4	Inquiring Purge Log	34-10
35.	Tanking of Maintenance Records	35-1
35.1	Tanking Records	35-1
35.1.1	Tanking New and Modified Maintenance Records	35-1
35.1.2	Tanking New Records	35-2
35.1.3	Tanking Modified Records.....	35-2
35.1.4	Closing a Record.....	35-2
35.1.5	Re-opening a Record	35-3
35.1.6	Authorizing a Record	35-3
35.1.7	Deleting a Record	35-3
35.1.8	Viewing Summary of Records	35-3
35.1.9	Modifying Tanking Preferences.....	35-3
36.	External Deal Maintenance	36-1
36.1	Maintaining External Deal Linkage.....	36-1
37.	Multilevel Authorization of Contract	37-1

37.1	Invoke Multilevel Authorization Detailed screen	37-1
37.1.1	<i>Authorize All Button</i>	37-2
37.1.2	<i>Role Details Button</i>	37-3
38.	Annexure A - File Formats	38-1
38.1	Upload File Formats	38-1
39.	Anti-Money Laundering	39-1
39.1	Anti-Money Laundering Reporting	39-1
39.1.1	<i>Guarding Against Money Laundering</i>	39-1
39.1.2	<i>Creating Product Categories in Oracle FLEXCUBE</i>	39-1
39.1.3	<i>Maintaining Limit Codes</i>	39-3
39.1.4	<i>Maintaining Anti Money Laundering Customer Groups</i>	39-4
39.1.5	<i>Linking Product Category with Customer Group</i>	39-6
39.2	Monitoring AML Accounting	39-7
40.	Developer and Developer Project Maintenance	40-1
40.1	Developer Maintenance	40-1
40.1.1	<i>Maintaining Developer Details</i>	40-1
40.1.2	<i>Project Button</i>	40-2
40.1.3	<i>Fields Button</i>	40-3
40.1.4	<i>Viewing Developer Maintenance Summary</i>	40-3
40.2	Developer Project Maintenance	40-4
40.2.1	<i>Maintaining Developer Project Details</i>	40-4
40.2.2	<i>Fields Button</i>	40-5
40.2.3	<i>Viewing Developer Project Maintenance Summary</i>	40-6
41.	Project Financing	41-1
41.1	Processing Finance for Project	41-1
41.2	Project Details Maintenance	41-4
41.2.1	<i>Maintaining Project Financing Transaction</i>	41-4
41.2.2	<i>Main Tab</i>	41-7
41.2.3	<i>Milestones Tab</i>	41-8
41.2.4	<i>Venture Details Tab</i>	41-9
41.2.5	<i>PPC Limits Tab</i>	41-11
41.2.6	<i>Non PPC Limits Tab</i>	41-13
41.3	Maintaining PPC	41-14
41.4	Maintaining PPC Liquidation	41-17
41.5	Dashboard Details	41-18
41.5.1	<i>Viewing Dashboard Details</i>	41-18
41.5.2	<i>PPC Details Tab</i>	41-19
41.5.3	<i>Limit Details Tab</i>	41-20
41.5.4	<i>Commitment Details Tab</i>	41-20
41.5.5	<i>Loan Details Tab</i>	41-21
41.5.6	<i>Querying Dashboard Details</i>	41-22
41.6	Querying Accounting Entries	41-22
41.7	Error and Error Codes for Project Financing	41-25
42.	Reports	42-1
42.1	Deleted Transaction Listing Report	42-1
42.1.1	<i>Generating List of Deleted Transactions Report</i>	42-2
42.1.2	<i>Contents of Report</i>	42-3
42.2	Accounting Journal Report	42-4
42.2.1	<i>Generating Accounting Journal Report</i>	42-5

42.2.2	<i>Contents of Report</i>	42-6
42.3	Cash Flow Report	42-7
42.3.1	<i>Generating Cash Flow Report</i>	42-7
42.3.2	<i>Contents of Report</i>	42-9
42.3.3	<i>Cash Flow (Summary) Report</i>	42-9
42.4	Future Dated Account Balance Report	42-10
42.4.1	<i>Generating Future Dated Contracts Report</i>	42-10
42.4.2	<i>Contents of the Report</i>	42-11
42.5	Current Rates Report	42-11
42.5.1	<i>Generating Currency Rate Report</i>	42-12
42.5.2	<i>Contents of Report</i>	42-12
42.6	Rate History Report	42-13
42.6.1	<i>Generating Currency Rate History Report</i>	42-13
42.6.2	<i>Contents of the Report</i>	42-13
42.7	Customer Account Opening Confirmation Report	42-14
42.7.1	<i>Generating Customer Account Opening Confirmation Report</i>	42-14
42.7.2	<i>Contents of the Report</i>	42-15
42.8	Account Closing Confirmation Report	42-16
42.8.1	<i>Generating Account Closing Confirmation Report</i>	42-16
42.8.2	<i>Contents of Report</i>	42-16
42.9	Activity Journal Report	42-17
42.9.1	<i>Generating Activity Journal Report</i>	42-17
42.9.2	<i>Contents of Report</i>	42-18
42.10	Core Exception Report	42-18
42.10.1	<i>Generating Core Exception Report</i>	42-18
42.10.2	<i>Contents of Report</i>	42-19
42.11	Uncollected Funds Report	42-20
42.11.1	<i>Generating Uncollected Funds Report</i>	42-20
42.11.2	<i>Contents of Report</i>	42-21
42.12	Account Revaluation Report	42-21
42.12.1	<i>Generating Account Revaluation Report</i>	42-22
42.12.2	<i>Contents of Report</i>	42-22
42.13	Accounts Movement Report	42-23
42.13.1	<i>Generating Accounts Movement Report</i>	42-23
42.13.2	<i>Contents of Report</i>	42-24
42.14	Customer Details Report	42-25
42.14.1	<i>Generating Customer Details Report</i>	42-25
42.14.2	<i>Contents of Report</i>	42-25
42.15	Customer Accounts Report	42-30
42.15.1	<i>Generating Customer Accounts Report</i>	42-30
42.15.2	<i>Contents of Report</i>	42-30
42.16	Document Check List Report	42-33
42.16.1	<i>Generating Document Check List Report</i>	42-33
42.16.2	<i>Contents of the Report</i>	42-34
42.17	Memo Revaluation Report	42-35
42.17.1	<i>Generating Memo Revaluation Report</i>	42-35
42.17.2	<i>Contents of Report</i>	42-36
42.18	Black Listed During Contract Booking Report	42-36
42.18.1	<i>Generating Black Listed During Contract Booking Report</i>	42-37
42.18.2	<i>Contents of the Report</i>	42-37

42.19	Black List Report During File Upload Report.....	42-38
42.19.1	<i>Generating Black List Report During File Upload Report.....</i>	<i>42-38</i>
42.19.2	<i>Contents of the Report</i>	<i>42-39</i>
42.20	Cheque Book Issued Report	42-39
42.20.1	<i>Generating Cheque Book Issued Report.....</i>	<i>42-39</i>
42.20.2	<i>Contents of the Report</i>	<i>42-40</i>
42.21	Demand Draft Issued Report.....	42-41
42.21.1	<i>Generating Demand Draft Issued Report.....</i>	<i>42-41</i>
42.21.2	<i>Contents of the Report</i>	<i>42-42</i>
42.22	PDC Input Report	42-43
42.22.1	<i>Generating PDC Input Report</i>	<i>42-43</i>
42.22.2	<i>Contents of the Report</i>	<i>42-44</i>
42.23	Temporary Overdraft Report	42-45
42.23.1	<i>Generating Temporary Overdraft Report.....</i>	<i>42-45</i>
42.23.2	<i>Contents of the Report</i>	<i>42-46</i>
42.24	Daily Sales Report.....	42-47
42.24.1	<i>Generating Daily Sales Report.....</i>	<i>42-48</i>
42.24.2	<i>Contents of the Report</i>	<i>42-48</i>
42.25	Customer Restriction Utilization Report.....	42-49
42.25.1	<i>Generating Customer Restriction Utilization Report.....</i>	<i>42-50</i>
42.25.2	<i>Contents of the Report</i>	<i>42-50</i>
42.26	Integrating Oracle Business Intelligence Enterprise Edition.....	42-51
43.	Function ID Glossary	43-1

1. Preface

1.1 Introduction

This manual is designed to help you quickly get acquainted with the Core Services module of Oracle FLEXCUBE.

This user manual is a supplement to the Common Core - Core Entities and Services User Manual and contains only specific functionalities and information related to Oracle FCUBS Core Services. Hence, this document should be read in conjunction with the Common Core - Core Entities and Services User Manual from the perspective of completeness in flow and understanding.

You can further obtain information specific to a particular field by placing the cursor on the relevant field and striking <F1> on the keyboard.

1.2 Audience

This manual is intended for the following User/User Roles:

Role	Function
Back office clerk	Input functions for contracts
Back office managers/officers	Authorization functions
Product Managers	Product definition and authorization
End of day operators	Processing during end of day/ beginning of day
Financial Controller/Product Managers	Generation of reports

1.3 Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

1.4 Organization

The manual is organized in the following manner:

Chapter	Description
Chapter 1	<i>About this Manual</i> gives a brief introduction of the module, the audience it addresses and the organization of the various chapters. It also includes the list of related documents to be referred, if any, and the conventions used in the document
Chapter 2	<i>Bank Parameters</i> explains the maintenance of various basic details about your bank

Chapter 3	<i>Ramadan Maintenance</i> explains maintenance of <i>Ramadan</i> year.
Chapter 4	<i>Dealer Maintenance</i> explains how you can capture profiles of dealers involved in buying and selling of foreign exchange
Chapter 5	<i>Branch Parameters</i> explains the process of creating and maintaining branches of your bank, with all necessary details
Chapter 6	<i>Account Branch Transfer</i> explains how you can maintain and process account transfers from one branch of the bank to another.
Chapter 7	<i>Web Service Maintenance</i> explains the process of WebService Mapping and other details regarding maintenance of external WebService.
Chapter 8	<i>Restriction Maintenance at Customer Level</i> explains customer level restrictions which can be utilized during various transactions.
Chapter 9	<i>Accounts for Inter-Branch Transactions</i> explains how you can maintain internal accounts for branches involved in inter-branch transactions
Chapter 10	<i>Currency Maintenance</i> explains the process of maintaining currencies in the system, with all necessary static attributes
Chapter 11	<i>Currency Denomination</i> explains the maintenance of standard currency denominations for each currency
Chapter 12	<i>Maintaining Limits for Cross Currency Transactions</i> explains the maintenance of cross currencies.
Chapter 13	<i>Maintaining Currency Spread for a Customer</i> explains the maintenance of currency spread and margin details for a customer
Chapter 14	<i>Cluster Deposits</i> explains the corporate deposit cluster maintenances.
Chapter 15	<i>Period Code Maintenance</i> explains the maintenance of financial periods into which each financial cycle is to be divided
Chapter 16	<i>Status Code Maintenance</i> explains the maintenance of codes that you can assign to the different statuses that a contract or a customer account can attain
Chapter 17	<i>Transaction Code</i> explains the maintenance of codes that you can use to represent different types of transactions
Chapter 18	<i>Account Revaluation Maintenance</i> explains the maintenance of parameters for account revaluation
Chapter 19	<i>Maintaining Branch Holidays</i> explains the maintenance of the holiday calendar for the different branches of your bank
Chapter 20	<i>Holiday File Upload</i> explains details on uploading holiday file.
Chapter 21	<i>Maintaining Clearing Holidays</i> explains the maintenance of the holiday calendar for the different clearing houses with which your bank transacts





Chapter 22	<i>Document Maintenance</i> explains about the type of documents to be submitted before opening an account and the document checklist to be maintained.
Chapter 23	<i>Configuring Overrides</i> details on configuring overrides of the system.
Chapter 24	<i>Other Maintenances</i> explains the method of installing features in a branch to improve the performance of the system during online or batch processes.
Chapter 25	Support 24x7 explains about the 24x7 support features in FCUBS.
Chapter 26	<i>Purging Data</i> explains the details of purging data.
Chapter 27	<i>Tanking of Maintenance Records</i> explains the process of tanking maintenance records.
Chapter 28	<i>External Deal Maintenance</i> explains the process of capturing deals booked in an external system.
Chapter 29	<i>Annexure A – File Formats</i> contains a list of file formats.
Chapter 30	<i>Anti-Money Laundering Reporting</i> explains the process of guarding against money laundering, a facility provided by Oracle FLEXCUBE
Chapter 31	<i>Developer and Developer Project Maintenance</i> explains how you can maintain details of the real-estate developer and developer projects.
Chapter 32	<i>Project Financing</i> explains the process of maintaining the project finance transaction in a bank using the Project Detail and Maintenance screen.
Chapter 33	<i>Reports</i> explains the procedure of generating Reports.
Chapter 34	<i>Function ID Glossary</i> has alphabetical listing of Function/Screen ID's used in the module with page references for quick navigation.

1.5 Related Documents

- Procedures User Manual
- Settlements User Manual
- Common Core - Core Entities and Services

1.6 Glossary of Icons

This User Manual may refer to all or some of the following icons:

Icons	Function
	Exit
	Add row
	Delete row
	Option List

2. Bank Parameters

This chapter contains the following sections:

- [Section 2.1, "Bank Parameters Maintenance"](#)
- [Section 2.2, "Confirmation/Affirmation Type Maintenance"](#)
- [Section 2.3, "Branch Restriction Maintenance"](#)
- [Section 2.4, "Maintaining Global Intermediary Identification Number"](#)
- [Section 2.5, "Maintaining Charge Transaction Codes"](#)

2.1 **Bank Parameters Maintenance**

This section contains the following topics:

- [Section 2.1.1, "Defining Bank Level Parameters"](#)
- [Section 2.1.2, "Financial Preferences Tab"](#)
- [Section 2.1.3, "General Preferences Tab"](#)
- [Section 2.1.4, "FATCA Tab"](#)
- [Section 2.1.5, "Regulatory Limits"](#)
- [Section 2.1.6, "Preferences Button"](#)
- [Section 2.1.7, "Account Mask Button"](#)

2.1.1 **Defining Bank Level Parameters**

In the 'Bank Wide Parameters' screen, you maintain basic information about your bank such as its name, head office, account number structure, local currency and so on.

The details that you maintain in this screen will be made applicable to all branches of your bank. For instance, the account number structure that you define in this screen will be a common format for customer accounts in all branches of your bank.

Invoke the 'Bank Wide Parameters' screen by typing 'STDBNKPM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Bank Parameters Maintenance

Save

Bank Code * 000 Bank Name FLEXCUBE UNIVERSAL

Head Office Branch

Branch Code * 000 Branch Description CITY HEAD OFFICE

Financial Preferences | General Preferences | FATCA | Regulatory Limits

Bank Default Currency Codes

Local Currency * GBP	Currency Description	GB POUND
Discount Currency * GBP	Currency Description	GB POUND
Head Office Currency * GBP	Currency Description	GB POUND
Reporting Currency * GBP	Currency Description	GB POUND

Control Accounts For Real Entries

Currency Mismatch Control Account	
Value Date Mismatch Control Account	

Control Accounts For Contingent Entries

Currency Mismatch Control Account	
Value Date Mismatch Control Account	

Preferences | Account Mask | Field Properties

Maker	Date Time:	Mod No	97	Record Status	Open
Checker	Date Time:			Authorization Status	

Cancel

You can maintain the following details in this screen:

Bank Code

Specify the bank code maintained in the Bank Core Parameters Maintenance (STDCRBK) screen. Click 'Unlock' to modify the values in this screen.

Name

You can also specify the detailed name of the bank. This name will always be displayed whenever the bank code is used.

Specifying Details of Head Office Branch

After specifying a code to identify your bank, you should specify details of the head office of your bank.

Code

From the list of the branches you have already maintained of your bank, designate one as your Head Office

Description

The description of the branch designated as Head Office is displayed.

2.1.2 Financial Preferences Tab

In this screen, you can maintain information regarding default currency for the branch, specify if balancing entries must be automatically generated in case of mismatches, define routing mask, clearing bank code etc.

Specifying Default Currency Codes

You can indicate currency preferences for your bank. You can specify preferences to indicate the default currencies for the following purposes:

- **Local** — The currency that you indicate as the local currency will be taken as the local currency for all branches of your bank and the default currency for all transactions input into Oracle FLEXCUBE. The income and expense balances of your bank will also be maintained in this currency
- **Discount** — If the discount rate for a particular currency is not maintained the discount rate of the specified discount currency will be picked up for discounting profits on forward foreign exchange contracts
- **Head Office** — The default currency for the Head Office
- **Reporting** — The default currency in which all financial reporting should be done

You will not have an option to modify the default currencies that you specify after the Bank Parameters record has been stored and authorized.

Auto Generate Currency and Value Date Mismatch Entries

You can specify that balancing entries must be generated automatically by Oracle FLEXCUBE, in the case of currency or value date mismatches in accounting entries due to transactions that are not balanced with respect to currency or value dates, for each branch (single entity) of your bank.

To specify the automatic generation of such balancing entries for currency mismatches, select the options 'Auto Generate Currency Mismatch Entries' and for generation of balancing entries to correct value date mismatches, select 'Auto Generate Value Date Mismatch Entries' in the Bank Wide Parameters screen.

If indicated in the Bank Wide Parameters, balancing entries will be automatically generated for any event if a mismatch of currency or value date entries (or both) is involved in any module of Oracle FLEXCUBE, with the exception of manually entered journal entries.

Specifying Control Accounts for Auto Balancing Entries (Real and Contingent)

If you specify that such automatic balancing entries must be generated, you can also specify the control accounts into which the entries must be booked.

There are two sets of accounts that you can maintain in the Bank-Wide Parameters screen, one for mismatches arising out of entries to real accounts and another for mismatches arising out of entries to contingent accounts. The relevant Control accounts must therefore be of Real or Contingent nature (as defined in the GL – Chart of Accounts). Such balancing entries will be automatically generated if a mismatch of currency or value date entries (or both) is involved in any module of Oracle FLEXCUBE, except Journal Entry.

In your Chart of Accounts, you must ensure that the following conditions are not indicated for the control accounts that you have specified for the currency mismatch and value date mismatch entries:

- **Position accounting:** Even if position accounting is set to "Yes" for the control account, the system will not pass any position accounting entries, since position accounting is done only for the main set of entries and not for the auto-balancing entries.
- **Account revaluation:** Account revaluation must be set for the control accounts since the effect of revaluing these balances would be offset the effect of revaluing the original GLs. (the GLs into which the main entries were posted).
- **Direct posting:** If you post a manual entry to one of the Control Accounts and the Position Entry Flag for the Control Account is set to 'Yes', then the system will do position accounting for that entry. Hence, for the GLs set-up as Control Accounts, the "Direct Posting" flag in the Chart of Accounts maintenance must be turned OFF.

Note

Additionally, it is also recommended that these Control Account GL's that you have specified in the Bank Wide Parameters screen for the mismatch entries are not used as part of Role to Head Mapping in any of the products. If maintained, the system would pass mismatch adjustment entries into the same GLs in which the main entries have been passed. There is no system-enforced validation of this and this aspect needs to be taken care of during Product set-up.

Generating Automatic Balancing Entries

In the case of transactions entered in any of the front-end modules of Oracle FLEXCUBE, the accounting process checks the entries at each business event, and automatically generates the balancing entries in case of a mismatch in currency or value date entries (or both).

Manually entered journal entries

In the case of manually entered journal entries, a journal batch that has been opened must be closed before it is authorized. During closure, the accounting process checks to see that the batch is balanced with respect to currency and value date entries. If a mismatch is detected, the accounting process raises an override to this effect. Depending upon how the override is configured, for your bank, the user who has opened the batch could adopt either of the following courses of action:

- If the override is configured to be an error, the system will not allow the user to close the batch without balancing the mismatches.
- If the override is configured to be a warning (either 'Override' or 'Ignore'), the user can save the batch with the mismatches. No balancing entries are automatically generated by the system for the mismatch.

Uploaded journal entries

In the case of uploaded journal entries, a journal batch that has mismatched entries is not rejected, but an override is raised by the accounting process. Depending upon how the override is configured, for your bank, the accounting process takes either of the following paths:

- If the override is configured to be an error, then the batch is rejected, and must be uploaded again with the corrected entries.
- If the override is configured to be a warning, the accounting process automatically generates the balancing entries for the currency or value date mismatches, for the batch, and posts them to the requisite control accounts specified in the Bank Parameters.

In each case, the transaction reference for the balancing entries is the same as that of the original accounting entry, in which the mismatch occurred, and the other details of the balancing entries are, by default, the corresponding values in the original entries.

The mismatch balancing entries are generated in the following order or preference:

- Currency mismatch balancing entries
- Value Date mismatch balancing entries

In the case of mismatches in accounting entries due to inter-branch transactions, the inter-branch balancing entries are generated before any balancing entries for currency mismatches, and then, finally, the value date mismatches.

Routing Mask

A mask defines the manner in which a Routing Number is generated for your bank. It is on the basis of the routing number that Oracle FLEXCUBE processes clearing transactions.

The following is a typical mask format: 'BBBbbbSSS', wherein, 'BBB' indicates the bank code, 'bbb' indicates the branch, and 'SSS' indicates the sector to which the branch belongs. On the basis of the routing number, clearing transactions are routed to the appropriate branch of your bank.

Clearing Bank Code

Specify the code by which your bank is identified in the Clearing Network you participate in. This has to be the same as that specified for your bank in the Clearing Bank Code Maintenance screen.

2.1.3 General Preferences Tab

In this screen, you can define format masks (for general ledger, CIF), choose if batch numbers should be auto-generated by the system, specify the details for cheque numbering etc.

The screenshot shows the 'Bank Wide Parameters' window with the 'General Preferences' tab selected. The window is divided into several sections:

- Bank Code:** 000
- Bank Name:** FLEXCUBE UNIVERSAL I
- Head Office Branch:** Branch Code * 000, Branch Description: FLEXCUBE UNIVERSAL I
- Financial Preferences:** General Preferences (selected), FATCA
- Format Mask:** Cif Mask: nnnnnn, General Ledger Mask: nnnnnnnnn
- Year End Profit and Loss:** General Ledger * 221000002, Transaction Code * YET
- Spread:** Spread Application: Both Legs, Spoof Files Purge Days: 90, Inter Pay Lead Days: 3
- Cheque Numbering Details:** Scheme: User Input, Cheque Number Mask: NNNN
- Checksum Algorithm:** Cheques Number Unique for Branch, Lodgement Numbers Unique For Branch
- TRS Details:** Sort Code, Account Number, Suspense Account, Payment And Collection Product Category

At the bottom, there is a status bar with fields for Maker, Checker, Date Time, Mod No, Record Status, Authorization Status, and an Exit button.

Defining Format Masks

A format mask is a structure that you can define for various elements that need to be entered in Oracle FLEXCUBE. You can define format masks for the following elements:

- General Ledgers
- Customer Identification File codes
- Customer account numbers

Once defined, you can modify the structure of a format mask only if no Customer or General Ledger Account has been opened using the mask. Customer Account mask is defined from the 'Account Mask' Button.

For more details on defining customer account mask, refer the section titled 'Specifying Account Generation Parameters at Bank Level'.

CIF Mask

You can maintain a mask for generation of identification numbers (CIF Number) for customers of your bank. During customer information maintenance, the system will automatically generate the CIF numbers based on the mask you define here and the customer number range maintained at the branch level.

A CIF mask consists of a maximum of 9 digits. The CIF mask could have only numbers or could be alpha numeric or could also have the branch code as a part of it.

For instance, you can maintain the CIF Mask as 'bbbnnnnnn' where 'bbb' represents a three-digit branch code and 'nnnnnn' represents a 6-digit number.

GL Mask

You can indicate a mask for the general ledgers that are maintained for your bank. The mask that you define here will be enforced whenever a General Ledger is created in the Chart of Accounts screen.

A GL mask can consist of a maximum of nine alphanumeric characters. It can be built using a combination of numbers and letters to indicate for instance, the category of the GL - asset, liability etc., the GLs hierarchical position and so on.

Each element used to define the mask would represent a single character. To represent an alphabet of the English language, indicate "a". To represent a number, indicate "n". The last character would be a D or d, which indicates a check digit generated by the system. For a numeric check digit define it as 'd'; for an alphanumeric check digit define it as 'D'.

You may use any of the following punctuation in the GL mask:

- dash (-)
- comma (,)
- asterisk (*)
- Full Stop (.)
- Forward slash (/)

For example, You wish to create a two level GL structure for your bank. You could define the first two characters of the GL to represent the category asset, liability etc., aa; the next two characters, nn, to represent the first level GL; and the next three characters, nnn, to represent the second level GL. A GL based on the given structure would read as AS01001 where AS represents the GL category - asset; 01 represents the first level GL; 001 represents the second level GL.

For creating this structure you would define your GL mask as - aannnnn'd/D'.

If you want to define your second level GL with a 4 digit numeric code instead of 3; other parameters remaining the same your mask would read as aannnnnn 'd'/'D'.

Indicating Year-end Profit & Loss

General Ledger

At the end of any financial year the balances in the income and expense accounts are posted by Oracle FLEXCUBE into a separate year-end account for the purpose of consolidation of balances and turnovers. This account is called the Year End profit and loss General Ledger Account.

You also specify year-end profit and loss GL for each GL account you maintain in the 'Chart of Accounts' screen. The year-end account specified at the bank level is the default year end profit and loss GL for all GL accounts maintained in the 'Chart of Accounts - GL' screen. If you

do not specify the account to which year end balances of a particular GL should be posted, it will be posted to the bank's year-end profit and loss account.

You can select a GL code from the option list of all assets, liabilities, income and expense GLs maintained in the chart of accounts screen.

Transaction Code

Indicate the transaction code that should be used to post the balances in the income and expense accounts to the year-end GL account.

You can select a transaction code from the list of transaction codes maintained in the 'Transaction Code Maintenance' screen.

Spread

Capture the following details.

Spread Application

Indicate the transaction legs for which the spread should be applicable. Choose the appropriate option from the following available in the adjoining drop-down list:

- Single Leg
- Both Legs

Spool File Purge Days

Specify the duration for which spool files should be stored in the spool file directory.

Interpay Lead Days

Specify the inter-pay lead days required for fetching billing records for inter-pay files for automatic billing of clients..

Auto Batch

Each time you post journal and multi offset entries, you need to open a batch. You can specify that the batch numbers of the journal entry batches opened in your bank should be generated automatically by enabling the Auto Batch option.

Consequently, the system automatically generates batch numbers while posting journal and multi offset entries.

Islamic Accounts

Profit Variation Limit for Accounts/Deposits

Specify the variance limit for the profit rate. By default, the value will be zero.

Mudarabah Fund Share Holder Balance Type

Select the balance type for Mudarabah fund share holder from the drop-down list.

2.1.4 FATCA Tab

In this screen, you can maintain the details regarding the banks' own FATCA classification. You mainly need to maintain the details in the following screen to identify:

- If FATCA is applicable to the bank
- The banks' own FATCA classification
- The banks' IRS issued EIN as well as its issue and expiry date

You can maintain these details by clicking the 'FATCA' tab. The screen appears as shown below:

Bank Parameters Maintenance

Save

Bank Code * 000 Bank Name FLEXCUBE UNIVERSAL

Head Office Branch

Branch Code * 000 Branch Description CITY HEAD OFFICE

Financial Preferences | General Preferences | **FATCA** | Regulatory Limits

☐ FATCA Applicable

Banks FATCA Classification

FATCA Classification

Employer Identification No. (EIN)

Issue Date/Date of Agreement YYYY-MM-DD

Expiry Date/Date of Re-validation YYYY-MM-DD

GIIN

Remarks

Grandfathered Obligation Cut off YYYY-MM-DD

Responsible Officer Details

Name

Designation

Address Line1

Address Line2

Address Line3

Address Line4

Telephone

Email ID

Preferences | Account Mask | Field Properties

Maker Date Time: Mod No 97 Record Status Open

Checker Date Time: Authorization Status

Cancel

FATCA Applicable

Check this box to indicate that the FATCA rules are applicable to the bank.

Banks FATCA Classification

FATCA Classification

Specify the bank's own FATCA classification. The adjoining option list displays the all the allowed classifications maintained for customer type bank using the 'Customer Type-Wise FATCA Parameters' screen.

Employer Identification No. (EIN)

Specify the employer identification number (EIN) issued to the bank by IRS.

Note

All the statuses do not require employer identification number (EIN).

Issue Date/Date of Agreement

Specify the date on which the employer identification number (EIN) was issued by IRS; or the date on which the bank entered into an agreement with IRS.

Expiry Date/Date of Revalidation

Some classification requires revalidation of employer identification number (EIN) periodically. Specify the date on which the EIN is to be revalidated.

GIIN

Specify the global Intermediary Identification number issued to the bank by the IRS.

Remarks

Provide any remarks, comments or observations regarding the Bank's FATCA Classification.

Grandfathered Obligation Cut off Date

Specify the cut off date for grandfathered obligations. The system will identify the grandfathered obligations based on the cut-off date. this date will be maintained at the bank parameter level.

Responsible Officer Details**Name**

Specify the name of the officer responsible for FATCA compliance.

Designation

Specify the designation of the officer responsible for FATCA compliance.

Address Line 1

Specify the address of the officer responsible for FATCA compliance.

Address Line 2

Specify the address of the officer responsible for FATCA compliance.

Address Line 3

Specify the address of the officer responsible for FATCA compliance.

Address Line 4

Specify the address of the officer responsible for FATCA compliance.

Telephone

Specify the telephone number of the officer responsible for FATCA compliance.

Email ID

Specify the e-mail ID of the officer responsible for FATCA compliance.

Next Balance Check Date

Specify the next balance check date.

Next Balance Check Frequency in Days

Specify the next balance check frequency in days.

The system will perform the following validations while saving the bank's own FATCA classification:

- If 'FATCA Applicable' field is checked then the system will capture the bank's own FATCA classification, GIIN number, Responsible officer name, designation, address line 1, telephone number and e-mail ID.

The GIIN entered should be validated against the list of GIINs provided by IRS. If the GIIN captured is not present in the list of GIIN, the system will display an override message. If you accept the override, then the record will be saved. If you cancel the override message, then the system will not save the record and 'FATCA Applicable' field will be unchecked.

2.1.5 Regulatory Limits

You can maintain the regulatory details by clicking the 'Regulatory Limits' tab. The screen appears as shown below:

The screenshot shows the 'Bank Parameters Maintenance' window. At the top, there is a 'Save' button. Below it, the 'Bank Code' is set to '000' and the 'Bank Name' is 'FLEXCUBE UNIVERSAL'. Under the 'Head Office Branch' section, the 'Branch Code' is '000' and the 'Branch Description' is 'CITY HEAD OFFICE'. The 'Regulatory Limits' tab is selected, showing 'Currency' as 'GBP' and 'Amount' as '1000'. At the bottom, there are tabs for 'Preferences', 'Account Mask', and 'Field Properties'. The 'Preferences' tab is active, displaying fields for 'Maker', 'Checker', 'Date Time', 'Mod No' (97), 'Record Status' (Open), and 'Authorization Status'. A 'Cancel' button is located at the bottom right.

Currency

Specify the currency for which you are defining the regulatory limits. The adjoining option list displays all valid currencies maintained in the system. You can select the appropriate one.

Amount

Specify the amount limit. This includes the limit for all cash transactions across all branches in the bank.

2.1.6 Preferences Button

In the Bank-Wide Preferences screen, you can specify the following:

- The route of inter-branch accounting — through HO, through RO or directly between branches
- Exchange rate preferences — to be maintained for the bank as a whole or at each branch
- Preference relating to update of GL balances — on-line or at the End of day
- Preference relating to Position Accounting
- Interface details

Click the 'Preferences' button to invoke the 'Preferences' screen.

The screenshot shows the 'Preferences' window with the following details:

- Interface Details:** Journal Account (text field), Width (text field).
- Inter Branch Scheme:** Inter Branch Entity (dropdown: General Ledger), Inter Branch Account Schedule (dropdown: Direct).
- Fund Inter Branch Scheme:** Inter Branch Account Schedule (dropdown: Normal), Inter Branch Entity (dropdown).
- Preferences:** A list of checkboxes for various system settings.
- Maintenance of Customer:** Bank Local (dropdown).
- Nodewise CIF Mask Maintenance:** (text field).

Interface Details

Specify the following details:

Journal Account

Specify Journal Account of the Interface details

Width

Specify width of the interface.

Inter Branch Scheme

Indicate the following details.

Inter Branch Account Schedule

You can indicate the route through which accounting entries for inter-branch transactions should be settled. You can select one of the following routes from the option list that is available:

- Choose 'Through HO' to indicate that inter-branch transactions should be settled through the Head Office
- If you specify 'Through RO' the accounting entries would be routed through the regional office. If two branches involved in a transaction do not report to a common regional office, the accounting entry would be routed through the HO
- If you specify 'Direct', each branch would have a direct accounting relationship with every other branch

The receivable and payable accounts between the branches, referred to as 'due from' and 'due to' accounts, are maintained in the 'Inter-branch parameters' screen.

For example, suppose the University Savings Bank has the following set up for its head office and branches in Headington, Oxford:

Roosevelt Avenue Branch, is the HO with Branch Code 000

Foxlake Drive Branch (Branch Code 001)

Mountainwood Road branch (Branch Code 002)

You have indicated that inter-branch transactions should be routed through the Head Office. Ms. Tanya Agnihotri has an account in Branch 002. She makes a cash withdrawal from Branch 001. This being an inter-branch transaction, Branch 001 will have to recover the money from Branch 002.

In this example the following movement of funds is involved:

- At Branch 001, the cash account is credited for the transaction amount and due from Head Office account debited.
- At Branch 000, the due from Branch 002 is debited and the due to Branch 001 is credited.
- At Branch 002, the Customer Account is debited and the due to Head Office account credited

Inter Branch Entity

Oracle FLEXCUBE allows you to post accounting entries related to inter-branch transactions to either of the following:

- Customer Accounts
- General Ledgers
- Both

If you select Customer Accounts as an inter-branch entity, you can specify the currency and the actual customer accounts involved in an inter-branch transaction between two branches of your bank. If the inter-branch entity is specified as 'General Ledgers', you need to specify the internal accounts that would be involved in a transaction between two different branches of your bank. If you select 'Both' option, it indicates that inter branch accounting entries could be posted for both GL and Customer accounts.

Fund Inter Branch Scheme

Indicate the following details.

Inter Branch Account Schedule

You can indicate the route through which accounting entries for inter-branch fund transactions should be settled. You can select one of the following routes from the option list that is available:

- Choose 'Normal' to indicate the inter-branch routing defined for corporate transactions will be applicable to the inter-branch fund transactions as well.
- Choose 'Through HO' to indicate inter-branch transactions should be settled through the Head Office.
- If you specify 'Through RO' the accounting entries would be routed through the regional office. If two branches involved in a transaction do not report to a common regional office, the accounting entry would be routed through the HO.
- If you specify 'Through RO and HO', the accounting entries would be routed through the Regional Office of the first branch, then the Head Office. From the Head Office, the entries would be routed through the Regional Office of the second branch.
- If you specify 'Direct', each branch would have a direct accounting relationship with every other branch.

The receivable and payable accounts between the branches, referred to as **due from** and **due to accounts**, are maintained in the '**Inter-branch parameters**' screen.

Inter Branch entity

Oracle FLEXCUBE allows you to post accounting entries related to inter-branch fund transactions to a General Ledger that you have specified.

If you choose '**Normal**' as the inter-branch routing, and you have not selected the option 'Allow Corporate Access' in the Branch Parameters screen, the Inter Branch transfer options you have chosen will be used.

If you have selected the option 'Allow Corporate Access' in the Branch Parameters screen and the branch is a fund branch, the entity will be defaulted as General Ledger. The GL will be based on the maintenance you have carried out in the Fund Inter Branch Accounts Maintenance screen, for the fund id. The same is explained in the chapter **Accounts for Inter-branch transactions**.

Online GL Updates

The update of GL balances can take place either on-line or during End of Day. For an on-line update select this checkbox.

Re-generate unused CIF ID

Check this box to indicate that the unused CIF ID needs to be re-generated automatically.

Note

Unused sequence number's of CIF is tracked for re-use only in the following scenarios:

- If the user cancels without saving new customer maintenance.
 - If the user deletes a new customer before authorizing it.
 - Unused customer account is regenerated on next day post cancelling or deleting.
-

Re-generate unused CASA no

Check this box to indicate that the unused CASA number needs to be re-generated automatically.

Note

Unused sequence number's of CASA is tracked for re-use only in the following scenarios:

- If the user cancels without saving a new CASA maintenance.
 - If the user deletes a new CASA before authorizing it.
 - The sequence numbers marked during delete operation is re-used in ascending order. The sequence numbers marked during cancel operation is reused only from next working day to prevent concurrency issues.
-

Auto- Generate CIF Numbers

This indicates whether or not the CIF should be generated automatically. Check this box to indicate the CIF number needs to be generated automatically.

Note

Unused sequence number's of CIF is tracked for re-use only if the CIF is generated automatically.

Re-Generate unused Multicurrency Account No

Check this box to indicate that the unused Multicurrency account number needs to be re-generated automatically.

Copy Exchange Rates to Branches

Exchange rates are maintained for a currency pair and are used to calculate the equivalent of one currency against the other. These exchange rates can be maintained in each branch or at the Head office. You can indicate your preference.

If you check against the option 'Copy to Branches' the exchange rates maintained at the Head Office will be made applicable to all branches of the bank. Leave it unchecked to indicate that exchange rates should be maintained at each branch.

Note

Propagation of rates happens only when the country code is same as uploaded country code.

Position Accounting Required

You can retrieve the position of a foreign currency, any time, by opting for position accounting in your bank. When you opt for position accounting, you maintain a Position GL and a Position Equivalent GL for every foreign currency maintained in your bank. The Position GL reflects the current position of the currency. If you have selected Position Accounting Required checkbox, then you have to maintain the Position GL and Position Equivalent GL using CYDPOSSL screen.

If you opt for position accounting while defining Bank-Wide Parameters, you have to maintain Position GLs and Position Equivalent GLs for every foreign currency that your bank deals in. When maintaining GLs for your bank, you can opt to link the different currencies, associated with the GL to either of the following:

- The Position GLs that you have specified for the currency (Your specifications in the Currency Definition screen will default here)
- Position GLs of your choice

Daily MIS Refinancing

As part of setting up the bank level preferences you can indicate whether MIS refinancing processing is required on a daily basis for the particular branch of your bank.

If you indicate that MIS refinancing should be done on a daily basis, refinance processing will be done on a daily basis for the following modules:

- Loans and Deposits
- Money Market

Note

You can indicate the rate type that is to be used for individual LD, and MM transactions while processing the contract.

Propagate Floating Rates to Branches

You have to indicate whether the floating rates maintained at the head-office of your bank should be propagated across all the branches of your bank.

Check the box positioned next to this field to indicate that floating rates need to be propagated across branches. Consequently, each time you maintain a floating rate for a particular rate code and currency combination at your bank, a corresponding floating rate record will be created and sent to all the branches of your bank.

Limits History Required

You can indicate whether date-wise limits history needs to be maintained for the Bank. If you choose to enable this option, the limits history is maintained at the following levels:

- Liability level history for storing liability records
- Limit level history for storing Lines records
- Line level history for storing Line Utilization records

Conditions for collating Limits History data:

- There is no retrospective effect on limits history.
 - Back-valued contracts and account transactions do not result in any adjustment to the previous records in the history. Such transactions are inserted with the current EOD date. Similarly any future-dated contracts and account transactions are also inserted with the current EOD dates.
 - In cases where the main line is changed to a sub line, the utilization is transferred from the old main line to the new main line and the effect cascades to the ultimate parent line. But existing records are not changed or updated.
 - Existing data will not reflect the change in the liability number for a customer.
- Revaluation has no effect on the limits history data
- Limits history is not maintained country-wise

The data is archived during the EOD processing. The history data is not updated for holidays.

Note

If there is no change for a liability/limit/line, data is not archived for that day.

Note

This option can be enabled or disabled at any point of time. Limits history will be recorded with effect from the day the option is enabled. Disabling the option will however not automatically purge history data.

You have the option of querying Liability history and drilling down to Limits Line history and further drilling down to Contract-wise Utilization history. Clean risk data is displayed only as of the date of query and history for the same is not maintained.

Branch wise Limits

This option indicates whether or not the limits tracking must be done at the branch level. If this box is checked, you will be allowed to view/change only the lines created from that branch for a given liability.

To illustrate, if you open any credit line facility in branch BR1, then in the Limit Restriction screen, the only branch available will be BR1.

Checking this option will also allow you to View details of line utilization at the branch level in the Limits Query screen.

For a total utilization of a global customer maintained in HO, you would have to generate a report of the limit utilization for each instance.

Pairwise Positioning Required

You have to select this option to indicate whether pair wise positioning entries need to be stored/handed off or not. If selected, the system will store position creating pair entries separately for handoff to other external systems.

When processing accounting entries, the system will check whether you have opted for pair wise positioning. If you opt for this option, the system will check for the following conditions in all the accounting entries that are posted:

- The set of entries posted are balanced i.e. total LCY debit is equal to total LCY credit
- At least one pair of accounting entry is in FCY
- Both the currencies are not the same

If the above conditions hold true, the system will store the entries along with the following information:

- Dr. Account: indicates the debit leg's account GL
- Cr. Account: indicates credit leg's account GL
- Event Code: is the event of the transaction
- Dr CCY/Bought Currency
- Dr. Amount/Bought Amount
- Cr. CCY/Sold Currency
- Cr. Amount/Sold Amount
- Dr Booking Date/Cr Booking Date
- Dr Value Date/ Cr Value Date
- Dr Transaction Code/Cr Transaction Code
- Exchange Rate
- Hand Off Flag

Note

While passing pair wise position entries, the main component will be passed with TRF_AMT tag and the equivalent entry will be passed with the AMT_EQUIV tag.

In case of accruals/revaluation also, if position entries are created, the corresponding entries will be stored separately for hand off.

Note

Pair-wise Positioning Required will decide whether position creating pair entries need to be stored by the accounting processor separately for handing off to other system.

Propagate CIF to other Nodes

You need to indicate whether or not the CIF number maintained in HO has to be propagated to other branches present in different instances. Check this box to indicate the CIF number has to be propagated to other Nodes/instances.

Propagate Customer Addresses to Nodes

You need to indicate whether or not the customer addresses maintained in HO has to be propagated to other branches present in different instances. Check this box to indicate the Customer addresses has to be propagated to other Nodes/instances.

Propagate Bank Instruction Codes Details to Nodes

This indicates whether or not the BIC data maintained in HO has to be propagated to other branches present in different instances. Check this box to propagate BIC details.

Mudarabah Fund Shareholder Balance Type

Specify whether the system should consider the month-end balance or the monthly average balance of the GL to compute the shareholders' investment in the linked *Mudarabah* fund. Choose from the following options available in the drop-down list:

- Monthly Average Balance
- Month End Balance

The option specified here will be common to all the shareholder GLs identified under the *Mudarabah* fund and once *Mudarabah* fund shareholder balance type is input and authorized, it will not be allowed to modify later.

Staff Account Restriction Required


Check this option to apply staff account restriction at the bank level.

Auto Account Closure

Check this box to enable Account Auto Closure functionality.

If you select 'Node' from the option list, you will need to maintain CIF masks at the Node level in the 'Node-wise CIF Mask Maintenance' screen. This would ensure that the branches maintained in different nodes/instances have different CIF masks.

Click 'Nodewise CIF mask Maintenance' button to access this screen. The screen appears as shown below:



You can specify the following details here:

Nodes

This indicates the node/instance for which the CIF mask is required. Select a node from the option list provided.

Customer Identification File Mask

This indicates the CIF mask for the corresponding instance/node. Select a CIF mask from the option list provided.

Autogenerate Customer Identification File Number

This indicates whether or not the CIF should be generated automatically. Check this box to indicate the CIF number needs to be generated automatically.

Allow Inventory Tracking

You can use this check box to allow/disallow inventory management and tracking. To use inventory management module, check this box.


Note

If inventory tracking is allowed then 'Cheque Numbering Scheme' should be left blank/null.

For more details on Inventory Tracking, refer the Instruments Inventory Tracking User Manual.

2.1.7 Account Mask Button

Account numbers in your bank are generated in the format of the account mask that you specify through the 'Account Parameters' sub-screen of the Bank-wide Parameters screen. Click 'Account Mask' button in the Bank-wide Parameters screen. Account Parameters screen is displayed. The screen appears as shown below:



Note

Since account level parameters are defined at the bank-level, by default these parameters will be defaulted to all the branches of your bank. However, individual branches of your bank will be allowed to change these specifications.

Specifying Customer Account Mask

Account numbers can either be generated automatically or you can choose to allocate them manually. In Oracle FLEXCUBE you have the option of maintaining three types of account masks.

They are as follows:

- **Alphanumeric** – this type of an account mask is a combination of alphabets and numbers where you can build the mask with components such as the Branch Code, the Account Class, the Currency Code, a check digit, etc
- **Numeric** - is a numeric type of account mask where the checksum algorithm associated with the account mask is either Modulo 11, Modulo 11 with weights or Modulo 97.
- **Pure Numeric** – is a numeric type of account mask, which does not have a checksum algorithm, associated with it. If you are maintaining a pure numeric mask you have to identify the start and end account number which is to be associated with it.

Alphanumeric customer account masks

The alphanumeric customer account mask can have a maximum of twenty alphanumeric characters. It can comprise of one or more of the following elements in combination:

- **Account Class** — Use “ACCLASS” to indicate that the account class to which the account belongs should be part of the mask.
- **CIF Number** — You can incorporate the nine-character CIF code assigned to the customer into the mask. To do so indicate ‘CIF Number’ in the mask.
- **Currency** — To add the currency of the customer account, use ‘CCY’
- **To indicate an alphabet or number** — Each element used to define the mask would represent a single character. To represent an alphabet of the English language, indicate “a”. To represent a number, indicate “n”.
- **Punctuation Marks** — When defining the customer account mask you have the option of separating the elements. To do this, you may use the following punctuation marks:
 - Dash (-)
 - Comma (,)
 - Asterisk (*)
 - Full stop (.)
 - Forward slash (/)

For Check Digit - The last character in the customer account mask should always be a ‘D’ or ‘d’. This indicates the check digit, which is generated by the system. When specified in the mask, the check digit component is generated using either of the following methods:

- Modulo 11
- Modulo 97
- Modulo 11 with Weights
- User Defined Algorithm

If you choose Modulo 97, all components of the account mask (for example, the Branch Code, the Account Class, the CIF ID, etc.) should be numeric. For example, if you enter ‘bbb’ in the account mask field (indicating that the branch code should be part of the account number), and choose the Modulo 97 option, ensure that the branch code is a numeric value, such as ‘000’, ‘123’, etc.

Note

The maximum length of twenty characters for the customer account mask is inclusive of the check digit

All customer accounts that are entered in any branch of your bank will compulsorily have to conform to the mask.

For example, you want the following elements to be part of the customer account mask:

The currency of the account

The nature of the account (savings, current etc.) and

The Customer Id

Given the above criteria the customer account mask would be:

ACCLASSCCYCIFNUMBERn'D'

This corresponds to:

LLLLL\$\$\$CCCCCCCnD

All customer accounts entered in any branch of your bank would now comprise of these elements, in the order defined in the mask.

A customer with CIF number 10005 has opened his first USD savings account with your bank, and the Account class for savings accounts is INDSB. His account number would read:

INDSB-USD-10005-1'D'

Similarly, the second GBP current account of a corporate customer with CIF Number 20005, would read

CUCOR-GBP-20005-2'D'

'CUCOR' being the account class representing current accounts of corporate customers.

Account mask generation using Alternate branch code

Alternate branch code will be represented as literal 'r' in the account mask. Following validations will be performed during account mask generations.

- The system will generate the unique serial number if:
 - Alternate Branch code alone is there in the account mask
 - Alternate Branch code is in combination with other literal like account code, currency type etc. in the account mask
- The serial number generated for the alternate branch code will be unique when two separate branches have the same alternate branch code.
- The system displays an error if the length of literal 'r' in the account mask used and the alternate branch code are not consistent. The system will not allow the account number generation.
- Modification to the alternate branch code will affect only the new account number. generation. It doesn't have any effect on the existing account number.
- The serial number generated should be unique for a particular criteria (alternate branch code/ customer/ currency/account class etc.) irrespective of the length of the corresponding literal maintained in the mask.

Characters Supported for Various Fields in Account Mask:

Field	Mask character	Max length supported
Account class code	L	6
Account code	T	4
Currency code	\$	3
Currency type	Z	3
Customer number	C	9
Branch code	b	3
Alternate Branch code	r	5
Serial Number	S	-
Numeric value(user to input)	n	-
Alphabet value(user to input)	a	-
UDF	U	-

Note

- Account mask should not have both the branch code and the alternate Branch code in the same mask
 - You must specify the mask character in the same case as mentioned above.
-

Field	Case 1	Case 2	Case3	Case4
CIF number	015005624	015005624	015005624	015005624
Currency code	GBP	GBP	GBP	YUV
Currency type	O	O	O	YA1
Account class	SAVINV	CACIN	123456	SAVINV
Account code	SA12	SA12	8909	SA12
Branch code	014	015	015	015

Mask maintained	Booked against	Chk sum Algorithm	Generated Account Number
LLLLLL\$\$\$CCCC CCCCSSd	Case 1	Modulo 11	SAVINVG- BP15005624019
LLLL\$\$\$TTCCCC CCCCSSd	Case 1	Modulo 11	SAVIGBP- SA15005624028
LLLLLL\$\$\$ZZCCC CCCnnd	Case 2	Modulo 11	CACINGB- PO005624997
nnnnnnnD	Case 1	Modulo 11	09888994
bbb- bLLLZZZZCCCC nnd	Case 4	Modulo 11	015SAVYA105624 074
LLLLLL\$\$\$CCCC CCCSSDD	Case 1 / 2	Modulo 97	Error. Will not be able to generate the check digit. The control digits value must be numeric for Mod- ulo 97.
LLLLLT- TTTTCCCCSSD D	Case 3	Modulo 97	123456890900562 40150

Customer Account Number Containing a UDF Value

While defining a customer account if you include 'U' in the account mask, it indicates that the customer account numbers will have the value of a user-defined field.

The number of U's will depend on the length of the UDF value that has to be included in the customer account number. For example, if you want to include 3 characters from a UDF, the account mask should consist of UUU (in addition to other parameters which you want to include in the customer account numbers).

Note

- A user-defined field can be part of the customer account mask only if the customer account number generation is not automatic.
 - Since a customer account number in Oracle FLEXCUBE can accommodate only up to 20 characters you have to ensure that the account mask you have defined does not exceed this number.
-

Numeric Account Masks with Modulo 11 and Modulo 97 as Checksum Algorithms

A numeric type of mask can have a maximum of twenty numeric characters, inclusive of the checksum algorithm.

If you associate Modulo 11, as the checksum algorithm, a single character D will be appended to the numeric mask. Let us assume that you have an account mask with five numeric values – 'nnnnn' and associated Modulo 11 as the checksum algorithm. The system automatically

appends 'D' to the numeric mask. The generated account numbers will have the following format – nnnnnD.

If the Account mask is Alphanumeric, and check sum digit is needed as per Modulo 11, then the check digit- 'd' has to be manually specified in the mask. For example, if you need an account mask as 'bbbCCCCCSCS', then considering Modulo 11 check sum digit, you need to input the mask as 'bbbCCCCCSCSd'.

Similarly, if you associate Modulo 97, with an account mask of five numeric values, the system appends a double-digit value of DD to the mask. The generated accounts will have the following format – nnnnnDD

Note

As system automatically appends DD in case of Modulo 97, if you input the customer mask with 'DD', system will display the error message as 'Cannot have D denoting Alphanumeric Characters'.

if you input 'dd' in the mask, then system displays the error message as 'Cannot have d denoting Alphanumeric Characters in account mask while using mod97 Checksum algorithm'.

System automatically appends DD always at the end of the Mask.

Algorithm	Contents of the mask	Check sum digit	Check digit character	Remarks
Modulo 11	Alphanumeric	User to input	d	Check digit should be specified manually in the mask
Modulo 11	Numeric	Auto append	D	System appends the check digit automatically, however, the mask characters should be 'n' for example, nnnnD
Modulo 97	Alphanumeric	Auto append	DD	If the values for the mask are alphanumeric, then check digit will not be generated
Modulo 97	Numeric	Auto append	DD	-
wing format – nnnnnDD.				

Numeric Account Masks with 'Modulo 11 with Weights' as Checksum Algorithm

The account mask with 'Modulo 11 with Weights' algorithm can have a maximum of 13 digits. It comprises of the following elements:

- Branch Code (3 digits) – Indicates the branch at which the customer account is maintained.
- Account Code (1 digit) – This will indicate the account code of the account class to which the customer account belongs. During account number generation (in the Customer Account Maintenance screen), you need to select the account class from the option-list provided. The system will then convert it to the account code maintained for that account class. The account code thus becomes a part of the customer account number.
- Currency Type (1 digit) – This will represent the currency type of the account currency. As explained for account code, you will select a 3-digit currency code during account generation. The system will convert it to the currency type maintained for that currency. The currency type will then form a part of the account mask.
- CIF Number – You can also include the CIF number of the customer as part of the account mask. The CIF number is automatically generated by the system when you capture customer details in the Customer Information Maintenance screen. During customer account maintenance, you can select the CIF number from the option list provided.

Sequence Number (1 digit) – The sequence number is automatically generated by the system for a combination of account code + currency type + customer. This means that, for this combination, you can maintain nine accounts. To maintain the 10th account for the same combination, the system will use the 'Dummy Customer No. Range' maintained at the branch level'.

Refer the section titled 'Creating Branches' of this document for more details on dummy number range.

- Control Number (1 digit) - This is the 13th digit of the account number. This number is also automatically generated by the system based on the 'Modulo 11 with Weights' algorithm.

For the above combination, the customer account mask would be:

'bbbTZCCCCCSd'

Where,

- bbb – is the branch code
- T – indicates the account code
- Z – is the currency type
- CCCCCC – is the CIF number of the customer
- S – is the sequence number for a combination of account code, currency type and customer
- d – is the control number generated by 'Modulo 11 with Weights' algorithm

The following example illustrates the manner in which the system calculates the 13th digit for a customer account number using the 'Modulo 11 with Weights' algorithm.

Assume that the account number of a customer is '000-4-1-123456-1'. As per this algorithm, the value of each position (1 to 12) is multiplied with the weight for each position (the weights are provided by your bank). Further, the sum of the product obtained is divided by 11. The remainder of the division will determine the value of the 13th digit.

The position-wise weight and account number and the product (of weight and number) is as follows:

Position	1	2	3	4	5	6	7	8	9	10	11	12
Weight (W)	2	4	8	5	10	9	7	3	6	2	3	5
Acct. No (N)	0	0	0	1	2	3	4	5	6	4	1	1
Product (W * N)	0	0	0	5	20	27	28	15	36	8	3	5

Sum of the product = 147.

Divide the value 147 by 11 to obtain the remainder

Remainder = $(147/11) = 4$

As per this algorithm, if the remainder is 10, then the control number will be zero. If it is any value other than 10, the remainder itself will be taken as the control number.

Therefore, the 13th digit = 4.

The customer account number will now read as '000-4-1-123456-1-4'

Numeric Account Masks with User Defined Algorithms as Checksum Algorithm

If the check digit component within a Customer Account Number is to be generated using a method of your choice you must identify the following:

- The User Defined Algorithm for the Customer Account Number – this identifies the name of the user-defined algorithm for check digit generation of account numbers.
- The User Defined Algorithm for Consumer Number – this stores the name of the user-defined algorithm for validating consumer numbers.

While capturing Customer Account numbers, the System checks for your specification for the checksum algorithm. If you have selected User Defined, the check digit is generated using the specified user-defined algorithm.

- Unused sequence numbers of CASA cannot be tracked for re-use if the sequence number is generated by user defined algorithm

Since these parameters are maintained for your bank, they are defaulted to the branches of your bank. You will not be allowed to change these for a specific branch of your bank.

Auto Generate Account

Enabling this box will generate customer account automatically. The customer account mask for this should contain only Numeric or combination of Numeric and Branch code.

Multicurrency Account Mask

Specify the multi currency account mask for supporting MCA generation.

Multicurrency Account Algorithm

Specify the multicurrency account algorithm value.

Multicurrency Checksum Algorithm

Select the multicurrency checksum algorithm value from the given list.

Start Multicurrency Account Number

Specify the multicurrency start account number creation.

End Multicurrency Account Number

Specify the multicurrency end account number creation.

Auto generate Multicurrency Account Number

Check this box to auto generate multi currency account. The customer account mask for this should contain only Numeric or combination of Numeric and Branch code.

Unused sequence numbers of CASA can be tracked for re-use only if the customer account mask contains numeric mask.

- If the account mask contains any of the following characters, the lost account number is re-used only if the same customer opens another account with the same branch code, account class, currency & sequence number combination:
- C(Customer number)
- b(Branch)
- T(Account class)
- Z(Currency)
- S(Single digit sequence number)
- SS(Double digit sequence number)
- Unused customer account number is reused in the same day, except in the following scenarios:
 - Session termination for the current user
 - Multiple windows opened for the same Function ID by the current user.

Pure Numeric Masks

A numeric account mask, which does not have a checksum algorithm associated with it, is called a pure numeric mask. Since it does not have a checksum algorithm associated with it you will have to specify the start and end account numbers and enable the auto-generated option.

The start account number forms the basis on which customer accounts numbers are to be generated. Similarly, you will not be allowed to maintain account numbers beyond the end account number.

Let us assume, that you are have maintained the following details in the Account Parameters screen at your bank:

Customer Account Mask	nnnnn
Start Account Number	1
End Account Number	50000
Cust Account Auto Generate	Yes

While generating a new account number the system will automatically generate 00001 corresponding to nnnnn. The next account will be – 00002.

Note

'n' is allowed in the account mask, only if auto account number generation is selected at branch level.

Including Value of a UDF as Part of Customer Account Number

If your bank has not opted for automatic generation of account numbers, you can specify a structure for customer account numbers. The structure can be a combination of CIF number, account class, value of a user defined field, currency, branch code, alphabets/numeric and a check digit which is automatically generated by the system.

For example, an account mask is CCCCCCLLbbbUUU\$\$\$ad.

This implies that a customer account number will contain:

CIF Id – represented by C

Account Class represented by L

Branch Code represented by b

Values of a user defined field represented by U

Any user-input alphabet represented by a (enter 'n' if you want to include a numeric)

Currency Code represented by \$\$\$

A check digit (which is automatically generated by the system) represented by 'd'

Note

The number of C's in the account mask should match with the CIF mask that you have specified. For instance, if the CIF mask is aaaannn (7characters), the account mask should consist 7 C's to include the CIF Id in the customer account number.

The value of a user-defined field can be used to include an additional parameter (for example: the code of the country to which the customer belongs) in the customer account number.

The steps involved for including the value of a user-defined field in a customer account number are as follows:

1. Include 'U' in the customer account mask to indicate that the customer account number should contain the value of a UDF
2. Create a new user defined field
3. Link it to the Function Id STDCIF
4. Specify the value of the user defined field at the time of creating a customer
5. Specify the UDF whose value has to be included in the customer account number to the Oracle FLEXCUBE implementer. The implementer will indicate this at the back end.

Maintaining Ten Digit Masks with Running Sequence Numbers

You can maintain a 10-digit mask of any combination, wherein the last two digits will necessarily be a running sequence number. This number will be automatically generated by the system. For instance, if you want to maintain a mask for the customer number and currency combination followed by the two digit running number, you will have to maintain the mask as CCCCC\$\$\$\$\$. Here, CCCCC stands for the customer number, \$\$\$ stands for the

currency of the account and SS stands for the running number. The system will generate the last two-digit number in a continuous sequence irrespective of the combination that you specify in the mask.

For example, let us assume that you want the customer account number to be a combination of the customer number and the account currency followed by the serial number. To achieve this, you have to specify the mask as CCCCC\$SSS. Based on this mask, for a customer with CIF ID 40207 with account in USD, the account number will be 40207USD01. If the same customer has another account in GBP, the next account number would be 40207GBP02. That is, there will not be any holes in the system generated running number.

2.2 Confirmation/Affirmation Type Maintenance

This section contains the following topics:

- [Section 2.2.1, "Invoking Confirmation/ Affirmation Type Maintenance"](#)
- [Section 2.2.2, "Viewing Confirmation/ Affirmation Type Summary Details"](#)

2.2.1 Invoking Confirmation/ Affirmation Type Maintenance

Manual confirmations received by FAX/telephone/Hard-copy etc. (Affirmation) need to be registered for a deal. You can maintain different Confirmation/Affirmation Types using 'Confirmation/Affirmation Type Maintenance' screen. You can invoke this screen by typing 'STDCNTYP' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Confirmation/Affirmation Type Maintenance

New

Type *

Description

☐ Confirmation

☐ Affirmation

☐ Consider for contract confirmation

Maker Date Time: Mod No Record Status

Checker Date Time: Authorization Status

Exit

You can specify the following details:

Type

Specify the confirmation or affirmation type.

Type Description

Specify the description for the selected type.

Confirmation/Affirmation

Select the type of contract. The options are as follows:

- Confirmation
- Affirmation


Consider for Contract Confirmation

Check this box for affirmation type of contract.

If this field is checked for an affirmation type and an affirmation is done for the contract with this affirmation type, then the contract will be considered as 'Confirmed'.

2.2.2 Viewing Confirmation/ Affirmation Type Summary Details

You can view confirmation or affirmation type details using 'Confirmation/ Affirmation Type Summary' screen. You can invoke this screen by typing 'STSCNTYP' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



In the above screen, you can base your queries on any or all of the following parameters and fetch records:

- Authorization Status
- Type
- Confirm/Affirm

Select any or all of the above parameters for a query and click 'Search' button. The following records are displayed:

- Type
- Description
- Confirm/ Affirm
- Confirm for Confirmation

2.3 Branch Restriction Maintenance

This section contains the following topics:

- [Section 2.3.1, "Placing User Restrictions on Data Entry Batches"](#)

- [Section 2.3.2, "Fields Button"](#)

2.3.1 Placing User Restrictions on Data Entry Batches

You can restrict the usage of batches to specific user by placing bank-wide User level batch restrictions. If you enable this option as a Bank Parameter, you need to allocate the batch number range for each user through the 'Batch Restriction Maintenance' screen.

The restriction on the usage of batch numbers is made applicable on data entry transactions. The user will be allowed to enter only those batches reserved for the user profile. As a result, each time a user specifies a batch number; it will be validated against the 'Allocated Batch Number Range'.

This feature is applicable only when batch generation is manual. Therefore, if you enable this option, you must ensure that the Auto Generate option has not been enabled. In a scenario where the User Restriction for Batch Number field is enabled and Auto Batch option has also been enabled, the system displays an error message as "Not a Valid Batch Number For the User".

In case you choose to auto generate batch numbers, the System will not perform the batch restriction validation.

You can invoke the 'Batch Restrictions Maintenance' screen by typing 'STDBRRES' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'User Batch Restriction' application window. It features a 'New' button in the top left corner. The main form area includes several input fields: 'User ID *', 'User Name', 'Branch Code *', 'Branch Name', 'Module Code *', and 'Module Description'. Below these fields is the 'Allocated Batch Number Range' section, which contains a 'Go' button and a table with columns for 'Start Number *' and 'End Number'. At the bottom of the window, there is a 'Fields' section with a table containing columns: 'Maker', 'Checker', 'Date Time:', 'Mod No', 'Record Status', 'Authorization Status', and an 'Exit' button.

Specify the following details in this screen:

- The User Profile for which the restrictions are being maintained. A list of all the User Profiles with access rights to the DE module is displayed in the option list. You can select the appropriate.
- The branch of your bank for which the restrictions will be made applicable. You can either choose a specific branch or make the restriction applicable to 'All' the branches of your bank.

- The module for which you are maintaining the Allocated Batch Number Range. This can be DE.
- The batch number range, which is indicated in terms of Start and End numbers. The range that you specify is allocated to the user. For distinct numbers, the start number and end number of the range will be the same.

Note

While processing DE transactions, the batch number specified by the user is validated against the allotted range. If the validation fails, an error message is displayed.

These validations are made applicable even during the Batch Upload operations for the following functions:

6. Journal Online – Single Entry
7. Multi-offset Entry
8. Teller Transaction Input

SSO Enabled

To enable Single Sign On (SSO) for your installation check the SSO Enabled check box. This enables restricted login from external systems into Oracle FLEXCUBE.

General Ledger Purge Days

You can specify here the maximum number of working days, the average GL balance computation for which is to be retained in the System.

Specifying Cheque Numbering Details

Scheme

In Oracle FLEXCUBE, cheque numbers can be generated automatically or can be manually entered. If you indicate manually, you can draw up numbering conventions and assign numbers to the cheques that are issued.

Cheque Number Mask

Specify the mask of a cheque number to be used by the bank. You can define numeric cheque mask as a series of N.

While defining an alpha numeric cheque mask, the alphanumeric character should always precede the numeric characters. For example: AANNNN, A being alpha numeric character and N being numeric character. Numeric characters should always follow the alpha numeric characters.


If cheque numbering scheme is 'Automatic' and checksum algorithm is selected, the 'Cheque mask' can be defined as only numeric. The cheque mask can contain only 'N' or can start with a 'T' followed by 'N'. If the cheque mask contains a 'T' in the first position, it indicates that the cheque is of type EURO or COMMERCIAL. If the mask contains only 'N', then the cheque is only numeric and cannot be EURO / COMMERCIAL. An appropriate error message is displayed if cheque numbering scheme is 'Automatic' and cheque number mask defined contains anything other than 'N' or 'T' in the first position.

If the cheque numbering scheme is 'Automatic' and checksum algorithm is selected at bank parameter, the cheque mask cannot be defined as alpha-numeric. The system validates if the cheque mask is alphanumeric and inventory is enabled at bank parameter. The system displays an appropriate error message as 'Alpha-numeric Cheque number is not supported as Inventory tracking is enabled'.

Checksum Algorithm

If you choose the automatic generation option you can indicate the algorithm based on which the cheque digit should be generated. A cheque number consists of three components:

- A check digit
- A cheque type
- A running serial number



You have the option to choose the algorithm to be used to arrive at the check digit. Currently Oracle FLEXCUBE supports only the Modulo-7 algorithm. Based on this algorithm the check type and serial number is divided by seven, and the remainder is taken to be the check digit. If the remainder is zero, then the check digit is set to seven.

The cheque type indicates whether the cheque is a Euro or Commercial cheque. The numeral 1 before a cheque serial indicates a Euro cheque and 2 indicates a Commercial cheque.

The cheque serial number is generated sequentially starting from 0001. This running serial number is assigned taking into account the last check number issued for the account.

Cheque Numbers Unique For Branch

For cheque numbers that are automatically generated, you can choose to make cheque numbers unique across the branches of your bank.

If you indicate that serial numbers need not be unique, you can have the same cheque number assigned to cheque leaves of different accounts within a branch. In effect cheque numbers remain unique to an account.

Lodgment Numbers Unique for Branch

You can indicate whether lodgment leaves must have unique numbers in a branch, or must be unique for individual accounts.

For example, in the Bank Wide Parameters, you have specified that lodgment book numbers must be unique for the branch. This means that lodgment numbers need to be unique across all accounts of that branch. For instance, if a book is maintained with the Start Number as 1, and containing 25 leaves, you cannot start another book in respect of any other account, with these numbers.

If you have specified that lodgment book numbers must be unique to accounts in the branch, and a book is maintained with the Start Number as 1, and containing 25 leaves, you cannot start another book in respect of the same account, with these numbers. However, you can start a book with the same numbers in respect of another account in the branch.

Specifying TRS Details

You can maintain the following details that will be used by the system to raise direct debit for Tax Relief at Source (TRS) rebate availed by customers on mortgage loans. The direct debit is raised during the End of Day (EOD) process after the LD batch processes.

Sort Code

Specify the destination bank code for which the bank raises direct debits for TRS claims.

Account Number

The destination account for which the bank raises direct debits for TRS claims.

Suspense Account

Specify the account that would be debited with the TRS amount, to credit customer account.

Viewing Trade License Details**Expiry Advice Generation Days**

If the trade license is set to expire on a particular date, the number displayed here denotes the number of days before that date when an advice is generated and sent to the customer informing about the impending expiration.

Specifying Mandatory Limit Tracking For Customer Type

You can maintain limit tracking as a mandatory option based on the customer type.

Corporate

Check this box if it is mandatory to link customer of Corporate type to credit line.

Bank

Check this box if it is mandatory to link customer of Bank type to credit line.

Individual

Check this box if it is mandatory to link customer of Individual type to credit line.

If a contract is saved without selecting the limit line for customers checked for mandatory limit tracking, then the system displays the error message as "Limit tracking is mandatory for this customer <Customer CIF>".

Note

- By default the customer type is selected as 'Individual'. However you can modify it.
 - At the customer maintenance level, system defaults 'Track Limits' option based on the option set here.
-

Specifying Cheque Discounting Details**Cheque Return Count for Drawer Blacklisting**


The system displays the number of cheque returns for a drawer. During the cheque return processing, the system check the number of cheque returns against this maintenance and marks the drawer as 'Blacklisted' drawer.

Specifying Passbook Details**Minimum Number of Digits for Passbook**

Specify the minimum number of digits for creating passbook number. The system defaults the minimum value 10. However you can modify it.

2.3.2 Fields Button

You can associate values to all the User Defined fields created and attached to the Bank Parameters Screen. You can view the list of User Defined fields associated by clicking the 'Fields' button. The screen appears as shown below:



Field Name *	Value	Value Description
--------------	-------	-------------------

You can enter the value for the UDFs listed here in the 'Value' column.

For more details on how to create user Defined fields, refer chapter 'Creating custom fields in Oracle FLEXCUBE' in the User Defined Fields User Manual under Modularity.

2.4 Maintaining Global Intermediary Identification Number

Global Intermediary Identification Number (GIIN) is the number by which IRS will identify financial institutions. GIIN will be issued by IRS to all banks that registers with them. It is the only way any bank can verify the participation status of a Foreign Financial Institution (FFI). GIIN list will be published by IRS every month. All participating and deemed compliant foreign financial institutions will have to apply to IRS and obtain GIIN. Other participating banks, USWA's etc.. will use GIIN to identify a banks participation status.

You can maintain GIIN details using 'Global Intermediary Identification Number (GIIN) Maintenance' screen, invoked from the Application Browser. You can invoke this screen by

typing 'STDGIINM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a software window titled "Global Intermediary Identification Number(GIIN)". Inside the window, there is a "New" button at the top left. Below it, there are six input fields arranged vertically: "Global Intermediary Identification Number(GIIN)", "Financial Institution Name", "Financial Institution Country", "Bank Code", "Branch Code", and "BIC Code". At the bottom of the window, there is a light blue bar containing several labels: "Maker", "Checker", "Date Time:", "Date Time:", "Mod No", "Record Status", "Authorization Status", and an "Exit" button.

You can specify the following details;

Global Intermediary Identification Number (GIIN)

Specify the GIIN code. you can also select the valid GIIN code from the adjoining option list.

Financial Institution Name

Specify the financial institute which has been assigned in the GIIN.

Financial Institution Country

Specify the country name where the financial institute is present

Bank Code

Specify the bank code details. You can also select the valid bank code from the adjoining option list.

Branch Code

Specify the branch code. You can also select the valid branch code from the adjoining option list.

BIC Code

Specify the BIC code. You can also select the valid BIC code from the adjoining option list.

2.5 Maintaining Charge Transaction Codes

This screen allows to define transaction codes used to levy charges and to link these transaction codes with Fee Type/Fee heading/Fee Sub Headings for different languages.

The first level of description is called Fee Heading. When you add further specific description to the Fee Heading you add a Fee Sub Heading. You can add upto three sub heading to describe the fee. The following table is an example of the headings and sub headings:

Fee Heading	Fee Sub Heading1	Fee Sub Heading2	Fee Sub Heading2
General account services	Maintaining the account		
Payments (excluding cards)	Credit transfer to another account in the country	Branch	Sepa Credit Transfer Charge
Other services	Providing a copy of an old statement		

When no heading is defined for a Transaction Code, it is tracked as Other Charges in the statement. Any transaction code maintained here is considered as charge in FLEXCUBE and will be used to report fees in the Statement of fees.

These headings are maintained for every Language.

You can maintain the details using 'Charge Transaction Code Heading Maintenance' screen. You can invoke this screen by typing 'STDTRNCH' in the field at the top right corner of the application tool bar and clicking the adjoining arrow button.

You can specify the following details:

Transaction Code

Select the transaction code from the list of values.

Description

Enter the description of the selected transaction code.

Language Code

Select the language code from the list of values.

Fee Heading

Enter the fee heading.

Fee Subheading1, Fee Subheading2, and Fee Subheading3

Enter the sub headings one, two, and three respectively.

3. Ramadan Maintenance

Zakat is a charge which is applied on the balance in an account if the balance is above a certain threshold amount. This charge is applicable only to savings accounts and Term Deposits (TD). It cannot be levied on current accounts.

The minimum threshold amount above which *Zakat* will be payable is decided every year before *Ramadan*. In addition, the percentage to be applied on the capital amount for calculation of *Zakat* is also decided.

This charge is levied on the savings accounts and TD accounts at *Ramadan*. For savings accounts, *Zakat* is computed on the balance as on the first day of *Ramadan* for all active accounts. The applicable amount is then deducted from the accounts.

In the case of TD accounts, *Zakat* is computed whenever there is a redemption of the principal. It is computed on the redeemed principal amount, provided the first day of *Ramadan* (for any one year of the TD tenor) falls between the profit start date of the deposit and the maturity date.

For computation and collection of *Zakat* you need to capture the first day of Ramadan every year.

This chapter contains the following sections:

- [Section 3.1, "Maintaining Ramadan Day"](#)

3.1 Maintaining Ramadan Day

You can capture the first day of *Ramadan* for a given year in the 'Ramadan Day Maintenance' screen. This is a bank-level maintenance that needs to be done at your Head Office. To invoke the 'Ramadan Day Maintenance' screen, type 'CSDRAMDN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a software window titled "Ramadan Day Maintenance". At the top, there is a toolbar with "New" and "Enter Query" buttons. Below the toolbar, there are two input fields: "Year*" and "First Day of Ramadan". The "Year*" field has a small calendar icon to its left, and the "First Day of Ramadan" field has a date picker icon to its right. At the bottom of the window, there is a status bar with three columns: "Input By" with a "Date Time" label, "Authorized By" with a "Date Time" label, and "Modification Number". To the right of these columns are two checkboxes labeled "Authorized" and "Open".

Here you can specify the following details:

Year

Specify the year for which you are capturing the first day of *Ramadan*. Note that you cannot maintain multiple records for the same year.

First Day of Ramadan

Specify the date on which *Ramadan* starts in the specified year. Note that the date should be valid as per the *Ramadan* calendar.

Refer the chapters titled 'Defining the attributes specific to an Interest or Charge product' and 'Daily Processing of Interest and Charges' in the Interest and Charges User Manual for details on Zakat computation and application.

4. Dealer Maintenance

This chapter contains the following section:

- [Section 4.1, "Defining Dealer"](#)

4.1 Defining Dealer

At the time of entering the details of a foreign exchange, money market, or securities deal, you will be required to enter details of the dealer who has struck the deal.

The dealers at your bank, who are associated with the buying and selling of foreign exchange, money or securities in the treasury, should each be assigned an identification number (ID number). The dealer list is maintained for the bank through the 'Dealer Maintenance' screen. Invoke this screen by typing 'STDDLRT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Fields			
Maker	Date Time:	Mod No	
Checker	Date Time:		

The following parameters need to be maintained to define a dealer ID:

Dealer Id

Enter a unique code to identify the dealer. The identification code can have a maximum of six alphanumeric characters.

The dealer will be identified by this code for all transactions entered in Oracle FLEXCUBE. You can also retrieve dealer-wise information on the treasury deals entered into by your bank.

Dealer Name

You can also enter a detailed name of the dealer. The name of the dealer will be displayed whenever the dealer Id is used.

5. Branch Parameters

This chapter contains the following sections:

- [Section 5.1, "Branch Parameter Maintenance"](#)
- [Section 5.2, "Maintaining Tax Cycle"](#)
- [Section 5.3.1, "Maintaining Role to Head Mapping at Branch Level"](#)

5.1 **Branch Parameter Maintenance**

This section contains the following topics:

- [Section 5.1.1, "Creating Branches"](#)
- [Section 5.1.2, "System Features"](#)
- [Section 5.1.3, "Creating Reporting Structure"](#)
- [Section 5.1.4, "Maintaining Branch Parameters"](#)
- [Section 5.1.5, "General Details Tab"](#)
- [Section 5.1.6, "Account Financial Details Tab"](#)
- [Section 5.1.7, "Duplication Check Details Tab"](#)
- [Section 5.1.8, "International Bank Account Number Details Tab"](#)
- [Section 5.1.9, "SWIFT Address Button"](#)
- [Section 5.1.10, "Account Mask Button"](#)
- [Section 5.1.11, "CIF Range Button"](#)
- [Section 5.1.12, "Global Interdict Functions Button"](#)
- [Section 5.1.13, "Preferences Button"](#)
- [Section 5.1.14, "Fields Button"](#)
- [Section 5.1.15, "Tax Button"](#)
- [Section 5.1.16, "Branch Currency Button"](#)
- [Section 5.1.17, "Account Statement Handoff"](#)
- [Section 5.1.18, "Account Statement Generation"](#)

5.1.1 **Creating Branches**

In the 'Branch Parameters' screen you create the various branches of your bank, define their reporting hierarchy, and maintain parameters such as their names, their address of location, SWIFT, TELEX, and HOST addresses.


In this screen you can do the following:

- Create the Regional Offices and branches of your bank by assigning each a unique branch code
- Maintain the address of location of each of the branches and also their SWIFT, TELEX and HOST addresses
- Specify the Suspense GL for posting all those accounting entries for which no GL has been specified or the specified GL has been closed
- Define preferences, such as - the retention duration, a CIF number for walk-in customers and the GL for netting FX contracts
- Maintain customer number range for generation of CIF numbers for customers of your bank.

The HO creates the branches at the bank level. All subsequent modifications on the table are done from the respective branches.

5.1.2 System Features

Oracle FLEXCUBE supports a three level reporting structure.



At the top stands the Head Office followed by the Regional Offices. At the lowest level are the branches. There can be any number of branches, but the number of regional offices is restricted to six. The system validates to check that the number of parent branches is not more than six. If the number of parent branches is more than six, system will give an error and restrict the number to six.

The branches report to the RO; and the ROs in turn report to the HO. Within this three level structure you can also have a branch reporting independently to the Head office (as branch, BR7 in the diagram).

It is also possible to have a two level reporting structure with only the HO and the branches, where each individual branch reports directly to the HO.

5.1.3 Creating Reporting Structure

The order in which you create the HO, the ROs and the branches should follow the hierarchy. Hence, the first branch to be created should be the HO, followed by the ROs, and then the branches.


The Head Office of your bank is created during installation. You only have to create the Regional Offices and the various branches. During installation, the system automatically populates this screen with the branch code and name of your Head Office that you have specified to the implementer. The 'Parent branch' and the Regional Office fields' also default to this branch code.

To create an RO, invoke a new screen. Then, enter the code and name of the RO against 'Branch Code' and 'Name' respectively. You do not need to specify the 'Regional office' because the HO Code is the default for the field. (All ROs report to the HO).

Then create all the branches. If a branch reports to an RO, to specify that RO is the branch's 'Regional Office', select the code you want from the option list provided for this field.

But before designating, you should authorize all the RO records you have created; the system will not allow you to use any unauthorized record.

(Diagrammatic Representation)



5.1.4 Maintaining Branch Parameters

In Oracle FLEXCUBE, the Head Office and the Regional Offices are defined as branches. You can maintain the details of the Head Office, regional offices and branches in the 'Branch Parameters Maintenance' screen. Invoke this screen by typing 'STDBRANC' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You can specify the following details here:

Branch Code

Specify the branch code maintained in 'Branch Core Parameter Maintenance' screen (STDCRBRN). Click 'P' Populate to default the values maintained in Branch Core Parameter Maintenance screen. You can modify these values.

Branch Name

This is the name of the office or branch, the code of which is input. Enter the name using a maximum of 35 characters, alphanumeric.

Alternate Branch Code

Specify the alternate name of the branch code. This field is an optional field. Alternate Branch Code would be maintained as a part of account mask maintenance. The alternate branch code will be used for the generation of CASA and TD account numbers (including Islamic CASA and TD).

The alternate branch code will not be unique. Two separate branches may have the same alternate branch code. It will have a literal 'r' to represent that in the account mask.

Following validation will be done when the account mask has literal 'r':

- Alternate Branch code field should be mandatorily maintained in the branch maintenance.
- Account mask can have maximum of five 'r'. If the account mask has five 'r' then the length of the data in the Alternate Branch code field should also be five characters long..
- If Alternate Branch code is maintained but account mask is not maintained at the branch level then the account mask maintained at the bank parameter will be considered for the above two validations.
- Account mask should not have both the branch code and the alternate Branch code in the same mask.

If Alternate Branch Code is not consistent, the system displays an error message "The Alternate Branch Code value is not consistent with the mask maintained".

Branch Available

The system displays the Branch Available status. If the status is 'Yes', it indicates that the branch can accept transactions for the day and if the status is 'No', then it indicates that the transactions will be accepted but it will be in effect only from the next business day.

Accordingly accounting entries will be passed checking the following, for tanking branch transactions:

- The Branch Available Status
- The Branch date and host date i.e. entries will be tanked if branch date is ahead of host date

When the Branch Available status is 'NO' or if branch date is ahead of host date, then the transactions will be tanked. These transactions will be untanked by the BOD program which runs post date change i.e. POSTDTCH.

Note

If you want to check whether the transaction is tanked or not, you should login to host and refer to the corresponding query function.

For more information on 'Querying the Transactions' refer Retail Teller, Clearing and Utility Payment Chapters under Oracle FLEXCUBE host module.

5.1.5 General Details Tab

You can maintain the branch details regarding the local currency, the parent branch, regional office of the branch, address details including telex, BIC etc.

Local Currency

Specify the currency of operation for your branch and the default currency for all transactions of your branch. The income and expense balances of your branch will also be maintained in this currency.

ARC Branch Group

Select the ARC branch group from the adjoining option list. All the ARC branch groups maintained in the ARC Branch Group Maintenance screen is displayed in this list.

Parent Branch

Parent Branch is to define an alternate reporting line, other than the three level HO-RO-Branch structure. The 'Parent' for all the branches you create is the HO code (default). To specify the Parent, other than the HO, select from the options displayed. The name of the parent branch is displayed alongside.

Regional Office

This is the branch code of the Head Office or Regional Office to which the branch (whose code is input eg. Branch Code) reports.

For a Head Office or a Regional office, this code should be the Head Office branch code, which is also the default for this field. For the branches, specify that branch as the RO, to which the branch reports. Select from the list of options displayed.

Country Code

Specify the country code in which the branch operates. Alternatively, you can select the country code from the option list. The list displays all the country codes maintained in the system. This is a mandatory field.

Customer Identity
Specify the customer's identity.

GL Class

Specify the GL Class. The adjoining option list displays a list of all the valid GL class codes and their description. You can choose the appropriate one.

Note

You can also select 'ALL' as an option. This indicates that all the GL codes are allowed for this branch.

City

Specify the city for which you have maintained tax exemption in the 'City Code Maintenance' screen. The adjoining option list displays the relevant cities. You can choose the appropriate one.

Specifying ATM Details

Specify the following details

ATM Branch

Specify the ATM branch.

Institution Identification

Your bank may have a branch or multiple branches for different countries. You have to capture the identification code that uniquely identifies your bank branch in the ATM transactions interchange environment. Specify a code to identify the institution. This institution ID will help identify whether a particular transaction has been sent from an external network or whether it has originated from your bank branch.

Inter Branch Transaction Code

You can specify the Transaction Code through which accounting entries for inter-branch transactions should be settled.

Customer Transfer

Check this option to indicate that transfer transaction should be permitted through the ATM

Specifying Address Details

For each branch of your bank you maintain the following parameters:

Branch Address

Input the address of location of the branch. Each line can have a maximum of 35 characters.

BIC

Input the SWIFT address for a branch using 8 or 11 characters, alphanumeric

Telex

Specify the branch's TELEX address, using a maximum of 14 characters, alphanumeric

Host Name

Against 'HOST' enter the name of the Host server for this branch, in not more than 35 characters, alphanumeric

Time Level

In this field is displayed the system time level status, represented by a number between 0 and 9

In Oracle FLEXCUBE, user access to the system can be controlled by assigning each user and the system, a time level. Both the system and the users are set to different time levels. Only those users who have a time level equal to or greater than the system time level can log into the system.

A control clerk, during the EOC process, does the change in time level status

Fund Branch

Even though the fund and the bank are in the same database, the fund is treated as a different legal entity and as such the books of the fund are maintained separately from those of the bank. Funds are created in a separate branch and any transaction initiated in the fund branch belongs to a fund. Check this box to indicate that the branch you are maintaining is a fund branch. Since the fund is a different legal entity, it should not be possible to initiate inter-branch accounting entries from the fund branch.

Any settlement with an external entity is routed through the normal settlements interface. In order to facilitate this, all the account fields in the system accept only the accounts in the transaction branch, if the branch happens to be a fund branch.

Allow Corporate Access

Select this option to specify that the fund subscription/redemption operations in the fund branch can access the accounts of corporate branch.

Note

- You will not be allowed to change this field once the branch record has been authorized.
 - This field will be enabled only if the branch is a fund branch.
-

External Value

Specify the name of the branch as maintained in an external system. This value can be used to interface with the external system.

EOC Status

Under EOC status one of the following alphabets will be displayed which stand for the following:

B - Beginning of financial input; indicates system transactions in progress

I -- Indicates that user transactions are in progress

T-- End of user transaction input; indicates system transactions in progress

F -- End of financial input; system transactions also completed

E -- End of Day, Branch awaiting date change

The values are updated by EOC process.

Specifying Time Zone Offset

For branches with different time zones, you can define the offset time that is to be displayed in maker/checker stamp and all the reports generated for the branch.

The offset time is specified in terms of hours and minutes, and the time will be added/subtracted from the Server Time maintained for the bank.

Hours

Specify the number of hours to be offset from Server Time to arrive at the local branch time.

This is the number of hours by which the branch leads or lags behind the Server Time

Minutes

Indicate the additional minutes by which the branch leads or lags behind the Server Time

Note

The reference of time is always the System Time (Server Time)

Ahead

The system calculates the local time of the Branch by adding/subtracting the Server Time and the Time Zone Offset time. When you maintain the offset time for the time zone, you need to specify whether the system should add or subtract the offset time from the Time Zone Offset.

Checking the Ahead box indicates that the offset time is added to the Server Time. Consequently, if the box is unchecked, the offset time is subtracted from the Server Time.

Additionally, the system validates the cutoff time depending on the time you specify here. The validation is based on following 3 parameters:

- Cutoff Time maintained for the currency in Currency Definition Screen
- Cutoff Offset Time maintained for the Branch in Branch Parameters Screen
- Time Zone Offset maintained for Branch in Branch Parameters Screen

GMT Time Zone

Hours

Specify the GMT hours of the Branch in hours. The format to be used is HH format.

Minutes

Specify the GMT minutes of the Branch in minutes. The format to be used is MM format.

GMT Ahead

Check this box if the given hour and minutes are ahead of GMT.

Indicating Cutoff Offset Time

When defining a currency, you can indicate a cut-off time for the currency. If your bank operates in branches located in different time zones, the cut-off time maintained for the bank will not be applicable across branches.

Therefore, you can set up an offset time for your branch based on the cut-off time set for the bank. You can specify an offset time for your branch in the Branch Parameters screen.

Hours & Minutes

The offset time is expressed in hours and minutes. The time you specify here is added or subtracted from the cut-off time maintained for the bank. This depends on the time difference between your branch and the Head Office.

Indicating Local Payments

Clearing Branch

Select the clearing branch from the adjoining option list.

Transaction Code for Consolidation Across Products

Select the transaction code for consolidation from the adjoining option list.

5.1.6 Account Financial Details Tab

You can specify the details regarding suspense GLs, Financial cycle, preference for floating rate, message generation (103+) for the branch in this screen. The screen appears as shown below:

Branch Parameters Maintenance

New

Branch Code * OSD
Branch Name * Bank Futura -Branch OSD

Alternate Branch Code 000
Branch Available Status

General Details | **Account Financial Details** | Duplication Check Details | International Bank Account Number Details

Suspense General Ledger

Real Local Currency	Description
261100005	Real Suspense General Ledger
Cont Local Currency * 640000002	Contingent Suspense General I
Real Foreign Currency 999900000	FGL - Year end Profit and Loss
Cont Foreign Currency 640000002	Contingent Suspense General I
ATM 171300006	ATM Suspense GL

Financial Cycle

Current Cycle FY2014
Current Period M01

Referral Cut Off Time

Hours
Minutes

Tax Cycle Closure Check Required

Tax Cycle Closure Check Required

Amount Block Processing

Transaction Code for Amount Block Release 000

Revaluation / Position Transfer Details

Transfer Type Reval
Transfer Branch 002
Position Asset GL
Position Liability GL
Transaction Code

Euro Redenomination General Ledger

Conversion General Ledger 261100005
Description Real Suspense General Ledger

Job Status
Auto Authorization

Preferences | SWIFT Address | Account Mask | CIF Range | Global Interdict Functions | Tax | Branch Currency | Fields

Maker RAVI01
Date Time: 2014-01-01 06:34:28
Mod No 1
Record Status Open
Checker RAVI01
Date Time: 2014-01-01 06:34:28
Authorization Status Authorized

Exit

Specifying Suspense GL

The accounting entries generated by different modules of Oracle FLEXCUBE will be passed into the specified 'Suspense GL' account if:

- The GL into which the entries are to be passed is not defined, or
- If the GL has been closed

Suspense GLs are of two types:

Real Suspense GL (Local and Foreign Currency)

The accounting entries that belong to asset, liability, income or expense GL categories will be passed to the 'Real suspense GL'. To indicate the real suspense GL for a branch, click option list and select a GL code from the option list.

Contingent Suspense GL (Local and Foreign Currency)

The accounting entries that belong to contingent asset or contingent liability GL categories will be posted to a 'Contingent Suspense GL'.

To indicate the contingent suspense GL for a branch, click option list and select a GL code from the option list.

Tax Cycle Closure Check Required

This check box is used when back valued transactions are posted to an account or to a contract that belongs to the branch.

If the check box is checked, then the following checks are done for every back valued transaction that are posted to an account or a contract that belongs to the branch:

- Identification of the tax cycle in which the back value date occurs.
- Check if the outstanding tax for that tax cycle has been paid to the tax authorities.

Certain back valued transactions may not be allowed if tax has been paid to the authorities.

If the check box is not checked, no such verification is done.

Note

To indicate that Tax has been paid and closed for a cycle, please refer section 5.2 of this User Manual.

Specifying Euro Redenomination GL

To facilitate the currency conversion process, you have to maintain a common Conversion GL and a Transaction Code.

The conversion GL that you specify in this screen will be identified as the common suspense GL for all balance conversions while re-denominating the currency of an account either for specific customers or for generic conversions.

In addition to the conversion GL you have to indicate a Transaction Code, which identifies conversion, related entries.

Indicating Payment Messages

Generate 103+

The 'Generate MT 103 + option' can generate outgoing MT 103 messages in the MT 103 + format.

Branch Code for Clearing

Indicate the code that identifies your branch in the Clearing Network. The code you specify for your branch should be the same as that defined in the Clearing Bank Code Maintenance screen.

Clearing Through Branch

If clearing transactions involving your branch are routed through another branch, specify the Oracle FLEXCUBE branch code of that branch in this field.

On the basis of the Routing Number Mask defined for your bank, and your specifications in this screen, Oracle FLEXCUBE automatically generates the Routing Number for clearing transactions involving your branch in the Routing Number field.

Loan Direct Debit Generation Days

Loan DD Generation days specifies the number of days before the schedule payment date, when a Direct Debit Contract is generated for the schedule due. This is applicable only for Loan Contracts in the local currency.

In order to facilitate the processing of loan repayments by customers who have their current or settlement accounts in some other bank of the clearing network you can initiate Direct Debits to these accounts. When a payment is due on a loan, a direct debit is generated 'Loan DD Generation Days' before the payment date.

As a result in Oracle FLEXCUBE the following entries will be passed:

Dr/Cr	GL
Dr	Clearing suspense
Cr	Dummy Settlement Account

During liquidation which is performed on the schedule date the entries passed are as follows:

Dr/Cr	GL
Dr	Dummy Settlement Account
Cr	Loan Asset GL / Interest Income GL

Processing Amount Block

Oracle FLEXCUBE passes the accounting entries for releasing an amount block through the 'Transaction Code for Amount Block Release' field. The system will check whether any amount block of type CASA for a branch is in open status. If an account is in open status, the system will group the amount blocks into primary account and primary account branch. Then, the system will remove the amount block from the cover account and debit the blocked amount of the cover account to the primary account.

Transaction Code for Amount Block Release

Specify the transaction code for the release of amount block. The adjoining option list displays all valid transaction codes maintained in the system. You can choose the appropriate one.

Indicating Financial Cycle

Current Cycle

This is the code for the current financial year as defined by you in the 'Period Code' screen.

Current Period

Each financial year is divided into accounting periods called 'Period Codes' defined in the 'Period Code Maintenance' Screen (for details refer 'period Code screen'). The current accounting period of the financial year is displayed in this field.

Specifying Referral Cut-off Time

Referral refers to the process of handling customer transactions that force the accounts involved in such transaction to exceed the overdraft limit. Examples of typical transactions, which force an account to move into overdraft, are Standing Instructions or Clearing transactions. If an account is marked for referral, the details of transactions resulting in the account moving into Overdraft will be sent to the referral queue.

Hours & Minutes

In branch parameter, you have to specify the referral cut-off time for accepting / rejecting transactions in the referral queue.

In case a transaction is rejected from the referral queue after the cut-off time then system displays the override message as “Rejected after cut off time”.

Note

Transactions are accepted into the Referral Queue even after cut-off time if account goes into overdraft.

Auto Authorisation

Oracle FLEXCUBE enables you to allow certain users (of your choice, depending on your requirements at your installation) to automatically authorize transactions.

To indicate applicability of automatic authorization for users of the branch, you must enable the Auto Authorization option in the Branch Parameters screen. When you do, you can then allow automatic authorization rights to the appropriate users at the branch.

For more details about automatic authorization, refer the Security Management System and Procedures user manuals.

Deferred Statement Status

This is a display field. This field indicates whether or not the Branch is ready for Deferred Statement Generation. ‘Y’ indicates the Branch is ready for deferred statement generation.

For further details on Referrals refer to the Processing Referrals in Oracle FLEXCUBE chapter of the Core Entities manual.

Install

Select the appropriate value from the drop-down list to indicate whether Oracle FLEXCUBE installation is complete or incomplete.

Proceed Without Maintaining Floating Rate

Check this option to indicate that floating rates should be propagated across all branches,

Sector code

Specify the Sector Code of your branch, as specified in the Clearing Bank Code Maintenance screen.

Routing No

On the basis of the Routing Number Mask defined for your bank, and your specifications in this screen for clearing and sector, Oracle FLEXCUBE automatically generates the Routing Number for clearing transactions involving your branch in the Routing Number field.

Specifying Revaluation/Position Transfer Details

You can transfer the currency positions from the individual branches to the designated branch during EOD. The system transfers the position from the existing branch to the treasury branch. When the position is negative in the given GL, then the system will choose the Offset account as Position asset GL and when the position is positive in the given GL, then the system will choose the Offset account as Position liability GL. Sequence of the EOD between the designated branch and all other branches are operationally controlled.

You can maintain the following revaluation/position transfer details:

Transfer Type

Select the transfer type from the drop-down list. Following are the options available in the drop-down list:

- Position
- Reval

Note

- If the Transfer Type field is left blank then neither the position transfer nor revaluation transfer to the designated branch will be done.
 - For position transfer, the 'Inter Branch in Local Currency' check box in the Transaction Code maintenance screen, should be checked to avoid creating position due to IB posting.
-

Transfer Branch

The system will identify the branch to which the revaluation/position transfer should be done.

During account/GL revaluation process, the system considers this branch and the GL to pass one leg of the revaluation profit and loss entries. The other leg of the entries will be passed based on the revaluation profit/loss GL and the account branch. The account branch in this case is the 'Revaluation Into' branch maintained as part of branch parameters maintenance.

Position Asset GL

Specify the GL to which the notional asset needs to be transferred..

Position Liability GL

Specify the GL to which the notional liability needs to be transferred.

Transaction Code

Specify the transaction code used to pass the accounting for position transfer.

While saving, the system will validate the difference between negotiated rate input by the user and the base rate maintained against the tolerance limit at the product level. If the difference is not within the tolerance limit, then the system will display an error message.

Specifying Suspense Batch Entry Details

Specify the following details:

Suspense Entry Required

Check this box to indicate that automatic suspense entries can be posted for a branch. If a mismatch occurs between real entries or contingent entries during the batch, then the system will post the balancing entries and will continue the EOD without interruption, if you check the 'Suspense Entry Required' option and specify the Suspense Batch Entry details. You can correct those entries manually at later stages.

If you leave this box unchecked and if a mismatch occurs in Real or contingent entries then the EOD is stopped and the error is thrown. You have to correct the entries.

Suspense Transaction Code

Specify the transaction code against which the suspense entries are posted or /reversed.

Suspense Batch Number

Specify the batch number against which the suspense entries are posted or reversed.

Reverse Suspense Entry Days

Specify the days till which the system can sustain the mismatch entries once the batch is run for the same. You can specify a value within a range of 1 to 9999.

If the 'Reverse Suspense Entry Days' is greater than the EOD suspense entry date and if reversal action is not performed for the suspense entry then the EOD is stopped and system displays an error message.

Maximum Real Suspense Amount

Specify the maximum amount that the system can consider to post suspense entry for an EOD for real entry.

Maximum Cont Suspense Amount

Specify the maximum amount that the system can consider to post suspense entry for an EOD for contingent entry.

5.1.7 Duplication Check Details Tab

You can maintain the number of days for which the duplication check should be done for a transaction in 'Duplication Check Details' tab. A transaction is compared with all previous transactions entered during the number of days maintained here, for any possible duplication.

The duplicate check is done starting from booking date till the booking date minus the number of days for duplicate check. This duplication check is carried out based on the combination of the preferences maintained at the SI product respectively.

Note

Duplicate transaction check is applicable only for SI transactions.

Branch Parameters Maintenance

New

Branch Code * OSD Branch Name * Bank Futura - Branch OSD

Alternate Branch Code 000 Branch Available Status

General Details Account Financial Details **Duplication Check Details** International Bank Account Number Details

Duplication Check Details

Module Duplication Check Required Duplication Days

Module	Duplication Check Required	Duplication Days
PC	<input checked="" type="checkbox"/>	1

Preferences | SWIFT Address | Account Mask | CIF Range | Global Interdict Functions | Tax | Branch Currency | Fields

Maker RAV001 Date Time: 2014-01-01 06:34:28 Mod No 1 Record Status Open
 Checker RAV001 Date Time: 2014-01-01 06:34:28 Authorization Status Authorized

Exit

You can specify the following details here:

Module

Specify the module for which you wish to maintain duplicate check days or select the module from the option list provided.

Duplication Check Required

Check this box to indicate that duplication check is required for the transactions related to the module selected.

Note

- However, despite checking this box if the duplication check criteria are not specified in the following screens the system will not perform duplication checks for all the respective contracts under this branch.
 - Standing Instruction Product Definition
-

Duplication Days

Specify the number of days for which the duplication checks for transactions need to be carried out. Calendar days are considered for duplication check.

Note

You need to specify a value here if 'Duplicate Check Required' option is selected. You cannot specify a negative value.

5.1.8 International Bank Account Number Details Tab

International Bank Account Number (IBAN) allows you to identify bank accounts across national borders. The IBAN consist of 34 alphanumeric characters out of which first two letters are the country code, next two characters being check digits followed by a country specific Basic Bank Account Number (BBAN). You can maintain IBAN and BBAN details in the 'International Bank Account Number Details' tab.

Branch Parameters Maintenance

New

Branch Code * OSD

Branch Name * Bank Futura -Branch OSD

Alternate Branch Code 000

Branch Available Status

General Details | Account Financial Details | Duplication Check Details | **International Bank Account Number Details**

IBAN Country Code GB

IBAN Check Digit Algorithm MOD 97

BBAN Format Mask

BBAN Data Type

BBAN Check Digit Algorithm MOD 97

User Defined Algorithm

BBAN Bank Code

BBAN Branch Code

Preferences | SWIFT Address | Account Mask | CIF Range | Global Interdict Functions | Tax | Branch Currency | Fields

Maker RAVI01 Date Time: 2014-01-01 06:34:28 Mod No 1 Record Status Open

Checker RAVI01 Date Time: 2014-01-01 06:34:28 Authorization Status Authorized

Exit

You can capture the following details:

IBAN Country Code

The system defaults the country code of the branch. The maximum allowed characters for IBAN country code is two. IBAN Country Code is mandatory.

IBAN Check Digit Algorithm

The system defaults MOD97 as IBAN check digit algorithm.

BBAN Format Mask

Specify the BBAN format mask. The maximum characters allowed for BBAN Format Mask is 30. The following mask characters are allowed in BBAN format

Mask Character	BBAN Parameter	BBAN Generation Details
b	BBAN Bank Code	The value is based on branch parameters maintained in IBAN details
s	BBAN Branch Code	Branch code as maintained in IBAN details
z	Account Number	This will be defaulted as Account number
l	Alternate Account Number	This will be defaulted as Alternate Account number.
d	BBAN check digit	Based on BBAN check digit maintenance in IBAN details.
t	Account Type	This will be replaced with the IBAN account type maintained at account class level.
h	Number of account holders	The number of account holders at the time of BBAN generation is defaulted here. The maximum allowed length of 'h' for a BBAN mask is 1.
i	National Identifier	This will be the National ID of the account customer as maintained in STDCIF based on customer type.

The mask characters will be repeated based on the length of each parameter in BBAN format.

The value for 'h' is derived as 1 if the account has a single account holder. The value of 'h' will vary between 2-9 depending on the number of joint account holders. If the total account holders are higher than 9, then the value of 'h' will be between A-Z. If the joint account holders along with the primary holder number are beyond 35, the system displays an error message upon IBAN generation.

The system displays an error message if:

- the account number is part of the BBAN mask and the length of the account mask maintained for the branch is greater than the corresponding BBAN mask account number length
- while generating IBAN the length of IBAN account type for the account class and account type (i) maintained in BBAN mask are not the same.
- characters other than b, s, z, l, d, h, i, t are used in BBAN mask
- there is a space between the characters in BBAN Mask

If the length of the account number or alternate account number is less than the BBAN mask account number length, then the account number will be prefixed with zeroes while generating the IBAN.

BBAN Data Type

Specify the data type of BBAN mask characters. BBAN Data Type is mandatory if BBAN format mask is maintained. BBAN Data Type can have only a (alphabet), n (number) and c (alphanumeric) as input.

BBAN Check Digit Algorithm

Select the algorithm to use for the generation from the drop-down list. The options available are:

- MOD 97
- MOD 10
- MOD 11
- MOD 11 with Weights
- User Defined

User Defined Algorithm

Select the user defined algorithm from the option list if the BBAN check digit algorithm is maintained as 'User Defined'.

BBAN Bank Code

Specify the BBAN bank code, which is used for IBAN generation. This field is mandatory if bank code is part of BBAN mask.

If the bank code is part of BBAN Mask and the value is not maintained in the branch IBAN details, then the system displays an override message.

BBAN Branch Code

Specify the BBAN branch code, which is used for IBAN generation. This field is mandatory if branch code is part of BBAN mask.

If the branch code is part of BBAN Mask and the value is not maintained in the IBAN details, the system displays an override message.

5.1.9 SWIFT Address Button

Click the 'SWIFT Address' in the Branch Parameters screen to invoke 'Additional SWIFT Address' screen.

The screen appears as shown below:

Branch Parameters Additional SWIFT Address

Branch Branch Name

SWIFT Addresses

SWIFT Address	Description

1 Of 1 Go

Ok Exit

You can specify the SWIFT addresses related to the branch in this screen.

5.1.10 Account Mask Button

Customer Account Masks can be defined at the Branch Level or at the Bank Level

Click the 'Account Mask' in the Branch Parameters screen to invoke 'Account Parameters' screen.

The screen is as shown below:

Account Parameters

Customer Account Mask

Checksum Algorithm

User Defined Algorithm

Customer Account

Consumer Number

Start Account Number

End Account Number

☐ Auto Generate Account

☐ Loan Account Auto Generate

Multi Currency

Multicurrency Account Mask

Multicurrency Checksum Algorithm

Multi Currency Account Algorithm

Start Multicurrency Account Number

End Multicurrency Account Number

☐ Auto Generate Multicurrency Account

Auto Account Creation

Start Account Number

End Account Number

Fund Subscription

Start Account Number

Ok Exit

For further details please refer the Section 'Specifying Account Generation Parameters at Bank Level' under 'Defining Bank Level Parameters'.

Fund Subscription

You may wish the system to automatically create deposit accounts for customers at the time of fund subscription. These system-created deposit accounts are for use as settlement accounts.

Here, you need to specify the range of numbers available for such auto created accounts by mentioning a start and an end number.

If you wish to retain the facility of auto creation of current accounts at loan initiation, you will have to ensure that the account number mask does not have any user input character.

Note

- The range of numbers specified for the creation of current accounts should not overlap with the range specified for the creation of deposit (or contra deposit) account.
 - Fund account number ranges are enabled only in the fund branch.
-

Multi Currency

Multicurrency Account Mask

Specify the multi currency account mask for supporting MCA generation.

Multicurrency Account Algorithm

Specify the multicurrency account algorithm value.

Multicurrency Checksum Algorithm

Select the multicurrency checksum algorithm value from the given list.

Start Multicurrency Account Number

Specify the multicurrency start account number creation.

End Multicurrency Account Number

Specify the multicurrency end account number creation.


Auto generate Multicurrency Account Number

Check this box to auto generate multi currency account.

5.1.11 CIF Range Button

You can specify a number range based on which the customers of your bank will be assigned CIF numbers for identification. Since the number range is maintained at the branch level, you can specify different number ranges for different branches of your bank.

To maintain the number range, click the 'CIF Range' in the Branch Parameters screen. The 'Customer Number Range' screen is displayed:



Specify the following in this screen:

Start Customer No.

This number is the basis on which the system generates the CIF numbers for customers of your branch.

The CIF number generation is determined by the following details:

- The CIF mask maintained in the Bank-Wide Parameters screen. Assume that the mask is 'bbbnnnnnn' (where 'bbb' represents a 3-digit branch code and 'nnnnnn' is a 6-digit number).
- The start customer no – assume that this number is 100

While generating CIF numbers, the system will automatically assign the number '000000100' to the first customer of your branch, assuming that the branch code is 000. This conforms to the CIF mask maintained for the bank. The next customer will be '000000101' and so on.

If the option 'Auto Generate CIF Numbers' is checked in the 'Bank Parameter Preferences' screen and the start CIF is zero or null, the new customer number will be generated for the branch as per the current running sequence number of the Head Office.

End Customer No

Just as you specify a Start Customer Number, you have to indicate the End Customer Number also. You will not be allowed to maintain customers beyond this range.

Let us assume that the 'End Customer No.' is 99999. As per the mask and the end number, the last customer CIF number that is generated at your branch will be '000099999'.

Start Dummy Customer Number & End Dummy Customer Number

You should also maintain a dummy customer number range in this screen. When maintaining a dummy range, you should ensure that dummy CIFs and the actual range do not overlap with one another.

The dummy CIF range will be used for account number generation. As explained earlier, the account number can be generated based on the following account mask:

'bbbTZCCCCCSd'

Where,

- bbb – is the branch code
- T – indicates the account code
- Z – is the currency type
- CCCCCC – is the CIF number of the customer
- S – is the sequence number for a combination of account code, currency type and customer
- d – is the control number generated by 'Modulo 11 with Weights' algorithm (explained earlier)

To recall, the sequence number that is automatically generated by the system is for an account code + currency type + customer combination. The sequence number is a single digit number (from 1 to 9). This means that, for the same combination, you will be allowed to maintain only nine accounts. To eliminate this limitation and to allow maintenance of more than nine accounts for the same combination, the dummy customer number range will be utilized. This is explained with the help of an example.

For example, Assume that you have maintained the following CIF range for your branch:

Number Type	Number
Start CIF No.	100000
End CIF No.	198999
Start Dummy No.	199000
End Dummy No.	199999

Ms. Jennifer approaches your bank to open a savings account in your branch (branch code is '000'). Further, the CIF and account number masks maintained for the branch are 'bbbnnnnn' and 'bbbTZCCCCCSd' respectively.

As per the CIF mask, Ms. Jennifer is assigned the CIF number: 000123456. According to the account number mask, the 6th to 12th digits will be the last six digits of the CIF number, which is '123456'.

The account number of the first savings account, in USD opened for Ms. Jennifer is: 000411234561 (we will consider only 12-digits for this example since the 13th digit is auto generated by the system based on Modulo 11 with Weights algorithm).

The components of the account number **000-4-1-123456-1** are as follows:

- 000 – is the branch code
- 4 – is the account code
- 1 – is the currency type
- 123456 – is the CIF number for Ms. Jennifer
- 1 – is the sequence number for the combination of account code, currency type and customer i.e. the number '4-1-123456' will be common for the first 9 accounts maintained for the same combination.

Now, Jennifer decides to open another account for the same combination. In this case, the sequence number gets incremented to 2 and the account will be assigned the number: **000-4-1-123456-2**.

This will go on till the 9th account for the same combination. The 9th account number would be **000-4-1-123456-9**.

If the customer decides to maintain the 10th account for the same combination, the sequence number will restart since it has reached the maximum allowed level. This would result in duplication of account numbers. To eliminate this, the system will now use the dummy CIF range to number the accounts.

Therefore, the 10th account number will be: **000-4-1-199000-1**. This sequence will continue for subsequent accounts maintained for the same combination.

Note

You can view all the dummy CIF numbers linked to a customer in the 'Customer Accounts – Allocated Dummy CIF' screen.

5.1.12 Global Interdict Functions Button

Click 'GI Functions' button in the Branch Parameters Maintenance screen to invoke 'Branch Global Interdict Functions' screen. Using this screen, you can integrate with Global Interdict System for online verification of transactions before authorisation in order to comply with 'Office of Foreign Assets Control' (OFAC) regulations in US.

Branch Parameters Global Interdict Functions

Branch Description

Global Interdict Functions

1 Of 1

Function Id *
<input type="checkbox"/>

Ok Exit

5.1.13 Preferences Button

To specify your preferences, click 'Preferences' button from the 'Branch-Wide Parameters' screen. The 'Preferences' screen is displayed.

Branch Parameters Preferences

Netting Suspense General Ledger

Walk In Customer

Internal Swap Customer

Clearing Account

Offset Clearing Account

Weekly Holiday 1

Weekly Holiday 2

Clearing Bank Code

MIS Group For Currency

Interdict Validation Required

Interdict Timeout Interval

Status Processing Basis

Provisioning Frequency

Uncollected Funds Basis

Minor Age Limit (Yrs)

Notification Days

Cheque Stale Days

Limit Expiry Advice Notification Days

Back Value Details

Back Valued Check Required

Back Value Days

Description

Profit and Loss Adjustment

Track Previous Year Profit And Loss Adjustment

Revaluation Split Details

Revaluation Split Required

Suspense Product Maintenance

Debit Product

Description

Credit Product

Description

Cheque Number Mask

Cheque Number Mask

FGL Integration

FGL Handoff Required

ELCM Integration

ELCM Replication

LDAP DN Template

LDAP DN Template

LCY Message Preferences

Ok Exit

In this screen you define the following preferences:

- The netting suspense GL into which settlement entries for netted FX Contracts should be posted
- The CIF Number against which all Walk in customers should be identified
-
- The duration for which spool files should be stored in the spool file directory
- The directory into which the files should be spooled
- MIS codes for posting of automatic balancing entries

These details can be maintained by the respective branches. For a branch you maintain the following, in the 'Preferences' screen:

Netting Suspense GL

All settlement accounting entries relating to a netted FX contract, is passed into the specified 'Netting suspense GL'. The net amount of the settlement is transferred through the Nostro accounts. For instance, let us take the following two outstanding contracts entered into by bank A; both settling on January 10, 1998:

- Bought from bank B 1 Million USD in exchange for 35 Million INR
- Sold to bank B 1/2 million USD in exchange for 18 million INR

The above contracts can be settled in either of the two ways given below, on the settlement date:

- Settle both contracts separately
- Net the settlements of the two contracts

If your bank has a netting agreement with the counterparty, the settlement entries are posted to this 'Netting suspense GL' and the net amounts are settled through the nostros.

Walk in Customer

For your branch you can create a walk in customer ID against which you track all those customers who do not hold a regular account with your bank but have approached the bank for a transaction, say, for encashment of traveler's checks or for manager's checks.

Internal Swap Customer

You need to specify an internal swap customer for processing internal swaps. The names of all the customers of your bank will be displayed in the option-list provided. This will be a unique customer meant for processing internal swaps.

Clearing Account

Specify the default GL account to be used for clearing transactions at the branch.

Offset Clearing Account

Specify the default offset GL account to be used for clearing transactions at the branch.

Weekly Holiday 1 & 2

Using this option you can indicate the holiday in a week for your branch. You can select the day for holiday from dropdown list. If you want to set only one holiday in a week for your branch, select the day for Weekly Holiday 1 and leave Weekly Holiday 2 Blank. If you want to opt for two holidays in a week, select the days for Weekly Holiday 1 & Weekly Holiday 2.

Clearing Bank Code

Specify the code by which your bank is identified in the Clearing Network you participate in. This has to be the same as that specified for your bank in the Clearing Bank Code Maintenance screen.

MIS Group for Currency (Mismatch Entries)

If the posting of automatic balancing entries due to currency and value date mismatches has been specified for your bank, you can specify the MIS codes or groups to be used for posting the balancing entries.

Interdict Validation Required

For your branch you need to indicate whether Interdict Validation is required for all Customers, Customer Accounts, Standing Instructions, Foreign Exchange, Letter of Credit and DD transaction processed within your branch.

The options available are:

- Yes – the details of CIFs and Customer Accounts, captured in the specific branch of your bank will be sent to the GI system as and when they are captured in Oracle FLEXCUBE.
- No – the details maintained in the specific branch will not be sent to the GI system for online verification.

Interdict Timeout Interval

If you indicate that the details should be sent to the GI system, you will also have to specify the interdict timeout interval period. If the response time from the GI system takes longer than

the time that you specify in this field, the transaction will be timed out since the processing time exceeds the time stipulated in this field.

If you enable this preference, you will have to identify the Code or ID of the function in Oracle FLEXCUBE for which such a validation should be performed by clicking on the 'GI' button in the Branch Parameters screen.

Status Processing Basis

In the Branch Parameters, you can indicate the basis upon which status processing must be done at the branch, for customer accounts as well as loan contracts.

Status processing can be done either at an individual contract / account level, or at a Group / CIF level.

If you opt for Group / CIF -level processing, it is done in two stages:

- The worst status among all contracts and accounts under a specific customer group or CIF is arrived at
- All accounts and contracts involving the customer group or CIF are then moved to the worst status that was arrived at

If you opt for status processing at individual contract / account level, the status of each contract or account would be assigned according to the status processing parameters that are operative for the contract or account.

If 'Status Processing' is at Individual Contract Level, then you can change the status and trigger the status change event along with accounting entry posting. However if the 'Status Processing' is at CIF/Group level individual module (LC, CI, MO, CA, IA and BC) batches will be updating common storage with the derived status of each contract and CIF/Group level status will be triggered by the common status change batch. The common status change batch will call the individual module function for status change processing.

For details about loan status processing and provisioning, consult the Loans user manual and the Core Entities user manual.

Provisioning Frequency

Provision processing depends upon status processing for accounts and contracts. The provisioning batch process executes after the status processing batch. If status processing is indicated to be processed at group / CIF level, you can indicate the frequency at which the provisioning batch is to be executed for your branch. The frequency options available are daily and monthly.

For details about loan status processing and provisioning, consult the Loans user manual and the Core Entities user manual.

(Withdrawable) Uncollected Funds Basis

You can define how the System enforces the allowable amount of uncollected funds (on an account) that can be withdrawn within a business day.

For each customer account, you designate a limit on the amount of uncollected funds that can be withdrawn (the Uncollected Funds Limit). You can also indicate whether, for a given business day, the System should consider the uncollected funds that are allowed to be withdrawn as:

- The funds scheduled to be released on the current date (today), OR,
- The total uncollected funds available against the account subject to the Uncollected Funds Limit

You can specify your preference by choosing any of the following options:

- **Uncollected Funds :** If you select this option, an amount up to or less than the uncollected funds limit defined for the account, is allowed to be withdrawn, on a given business day.
- **Uncollected Funds Available Same Day:** If you select this option, the funds allowed to be withdrawn against uncollected funds on a given business day are the funds scheduled to be released on the current date (today).

Deferred Statement Generation

Check this option to stop the automatic account statement generation at end of day.

If this option is checked, then the account statement generation will be deferred to whenever you initiate action for executing Batch Operations for statement generation. You can do this through the Branch Statement Status Change screen.

Enterprise GL

Check this option if this branch needs to have an enterprise GL hand-off. Once checked the system will identify the said branch for creating an ASCII hand-off file containing the relevant accounting entries to be sent to the external enterprise GL.

Minor Age Limit (Yrs)

Specify the minor age limit. This varies from nation to nation. However If user does not maintain the age limit, the system will automatically defaults it as 18 years during save.

Notification Days

Specify the intimation days to send advice prior to the customer turns major based on DOB.

Cheque Stale Days

Specify the cheque stale days. Here you can identify the number of days for which stale validation is done.

Limit Expiry Advice Notification Days

Specify the limit expiry advice notification days. The system will send advice to the customer these many days before the limit expiry date.

The limit expiry advice generated by the system provides information on the limit details. Multiple lines can be attached to a customer with different expiry dates. Advice sent to the customer contains the details of the line which is about to expire.

Central Bank Dormancy Days

You can define a period in the branch level in which a dormant account will become Central Bank Dormant. Apart from regular financial transaction, the customer can do the following non-financial transactions (through the STDNONFA screen) in between the dormant and Central Bank Dormant status to activate their dormant account:

- Cheque book request
- Passbook request
- Ad-hoc statement request
- ATM transactions for cheque book request, balance enquiry, mini statement, and ad-hoc statement

If the customer activates a single account, then by default all dormant accounts for the customer will be activated, based on the 'Dormancy Activation Level' you chose in the 'Branch Parameters Preferences' screen. You can define the non-financial transactions for the branch from the STDNONFA screen.

You can check the status of the customer's account from form the 'Auxiliary' tab of the STDCUSAC screen. For dormant accounts, the status 'Dormant' will be checked and for central bank dormant the 'Central Bank Dormant' check box will be checked. The 'Dormant' and 'Central Bank Dormant' check boxes are read-only fields.

Dormancy Activation Level

Select the condition which activates a dormant account, when there is a transaction in that account of the customer. The drop-down displays the following levels:

- Account: Only the account in which the transaction happens is activated.
- Branch: All the accounts of the customer in the current branch is activated.
- Across Branches: All the accounts of the customer in the current branch is activated, though the transaction happens in a different branch.

Note

This activation is only for 'Dormant' accounts and not 'Central Bank Dormant' accounts.

Specifying Back-Valued Details

For your branch you can specify the maximum period up to which back valued posting can be processed. This restriction can be made applicable by specifying the following preferences:

Back Value Check Required

It is used to indicate whether all back-valued transactions should be validated against a specific period.

Back Value Days

If you enable the Back Value Check Required option, you must indicate the number of calendar days up to which back-valued transactions can be allowed. During transaction processing you will be allowed to post back-valued transactions up to the specified date in the past (no check will be done). Further, if the option is checked but you have not maintained the 'Back Value Days' (maintained as NULL), the system will interpret it to be 'Zero' days allowed (for back valued transactions).

The restriction for the maximum period up to which back-valued posting can be allowed, will be made on transactions processed in following modules:

- Data Entry
- Retail Teller
- Utility Payments
- Foreign Exchange
- Money Market
- Expense Processing
- Loans and Deposits

While saving transactions pertaining to any of these modules the System validates the Value Date of the contract to check whether it adheres to the restriction. You will be intimated with an override if the Value Date is earlier than the specified period. This restriction is made applicable on all uploads as well.

Refer the Contract Processing chapter of the individual modules for additional information.

Indicating Profit and Loss Adjustment

Track Previous Year Profit and Loss Adjustment

You can collect data pertaining to the unrealized income booked for each contract during the year by triggering the Year-end batch process. But, you will be allowed to trigger the batch process for splitting the unrealized profit and loss for the previous year and the current year only if you have specified this (Track PY PnL Adjustment) as a preferred option for your branch.

If you set this preference, the data pertaining to the unrealized income is collected at contract level for the following modules:

- Securities - Unrealized Interest, Discount and Premium accrued for the year.
- Derivatives - unrealized income
- Bills and Collections - unrealized income
- Letters of Credit - unrealized income
- Money Markets - unrealized income

Indicating Revaluation Split Details

Revaluation Split Required

You can choose to break-up revaluation profit/loss into:

- Trading P&L – P&L due to revaluation of foreign currency transactions during the day
- Revaluation P&L – P&L due to revaluation of opening balances (balances without current day's turnover)

If you enable this preference, all GLs which are marked for revaluation split will have their revaluation profit/loss broken up into trading and revaluation P & L for entries posted from this branch.

For further details on Split Revaluation refer the GL user manual.

Specifying Suspense Product Maintenance

When a branch goes offline, user posts the transactions allowed in offline mode. Once the branch and host are online, branch starts posting these transactions as force post. If the force post fails, then the host needs to post these transactions as a suspense product in the branch.

Debit Product

Specify a valid debit product you need to maintain as Suspense Product. The adjoining option list displays all the valid debit products maintained in the system. You can select the appropriate one.

Description

The system displays the description based on the selected debit product

Credit Product

Specify a valid credit product you need to maintain as Suspense Product. The adjoining option list displays all the valid credit products maintained in the system. You can select the appropriate one.

Description

The system displays the description based on the selected credit product.

Indicating Cheque Number Mask

Cheque Number Mask

The system displays the cheque number mask maintained at bank parameter level.

The 'Cheque Number Mask' defined at branch parameter level cannot be changed once maintained and authorized.

If the cheque book is issued to non base branch accounts, the system populates or validates the cheque numbers based on the cheque mask of the account branch.

Indicating ELCM Integration

Check this box to indicate that the branch details will be replicated to ELCM system. System will select this option by default, but you can unselect it. System will not allow unselecting this option once it is selected.

LDAP DN Template

The LDAP DN template needs to be maintained here for each branch. This is used in Oracle FLEXCUBE user maintenance form to populate corresponding LDAP user-id automatically from the template.

5.1.13.1 LCY Message Preference Button

Click the 'LCY Msg Pref' button in the Preferences screen to invoke the 'LCY Message Preference' screen.

The screen is as shown below:

Branch

The system displays the branch details.

Description

The system displays the description.

Module

Specify the module details.

Module Description

Specify the description of the module.

Local Currency Message Type


Select the local currency message type from the drop-down list. Following are the options available in the drop-down list:

- Suppress LCY
- Generate LCY Message Thru SWIFT

5.1.14 Fields Button

You can associate values to all the User Defined fields created and attached to the Branch Parameters Screen. You can view the list of User Defined fields associated by clicking the 'Fields' button.

The screen appears as shown below:



The screenshot shows a window titled "User Defined Fields". Inside, there is a "Details" section with a table. The table has three columns: "Field Name", "Value", and "LBL_FIELD_VAL_DES". The "Field Name" column has a checkbox in the first row. The "Value" column has a text input field in the first row. The "LBL_FIELD_VAL_DES" column has a dropdown menu in the first row. There are also buttons for adding (+), deleting (-), and refreshing (circular arrow) records. A scrollbar is visible at the bottom of the table area.


Field Name	Value	LBL_FIELD_VAL_DES
<input type="checkbox"/>		

You can enter the value for the UDFs listed here in the 'Value' column.

For more details on how to create user Defined fields, refer chapter 'Creating custom fields in Oracle FLEXCUBE' in the User Defined Fields User Manual under Modularity.

5.1.15 Tax Button

To maintain Tax parameters at the branch level, click the 'Tax' button in the Branch Parameters Details screen. The screen appears as shown below:



Tax Cycle

This is the current tax cycle for the branch. This is a display field. Whenever the tax cycle changes, the field is updated during the date change authorization for that day.

Consolidated Tax Certificate Required

Check this option to indicate Consolidated Tax Certificate is required for all the transactions done in the Tax Cycle. This option works in conjunction with a similar option in the Customer Information Maintenance and the Tax Category Maintenance screen.

The Consolidated Tax Certificate would be generated at the frequency specified at the branch level. Apart from this, the certificate would also be generated at the end of the Tax Cycle. The consolidated tax certificate would always display all the transactions pertaining to the current Tax Cycle.

Individual Tax Certificate Required

Check this option to indicate Individual Tax Certificate is required for individual transactions under the selected tax category. This option works in conjunction with a similar option in the Customer Information Maintenance and the Tax Category Maintenance screen.

Tax Certificate Frequency

This field is enabled only if the Consolidated Tax Certificate option is checked.

You need to specify the frequency with which the tax certificate should be generated. This would be a combination of the Tax Certificate Frequency and the Tax Certificate Day. It could be any of the following:

- Monthly - This indicates that the tax certificate would be generated every month. The day of the month on which the Tax Certificate would be generated is defined in the Tax Certificate Day field.
- Quarterly (Q) – This indicates that the tax certificate is generated once in three months. The end-month for the first quarter is defined in the Tax Certificate Day field. The

Certificate would be generated on the last working day of the month defined in the Tax Certificate Day field. Subsequent end-months would be derived by the system.

- Half Yearly (H) – This indicates that the Tax Certificate would be generated once in six months. The end-month for the first half-year period is defined in the Tax Certificate Day field. The Certificate would be generated on the last working day of the month defined in the Tax Certificate day field. Subsequent end-months would be derived by the system.
- Yearly (Y) – This indicates that the tax certificate would be generated once a year. The month in which the certificate needs to be generated is defined in the Tax Certificate Day field. The Certificate would be generated on the last working day of the month defined in the Tax Certificate Day field.


Frequency Value

Select the appropriate month for tax certificate generation, from the adjoining drop-down list.

For more details on how to maintain tax cycles, refer section 'Maintaining Tax Cycles' in the chapter.

5.1.16 Branch Currency Button

You can maintain a list of currencies in which clearing transactions can be processed under a branch. In order to achieve this, you need to invoke the 'Clearing Currency' screen by clicking the 'Branch Currency' button in the 'Branch Parameters – Detail View' screen.



Here you can capture the following details:

Branch Code

The branch code gets defaulted from the 'Branch Parameters – Detail View' screen. A brief description of the branch is displayed alongside.

Currency Code

Specify the currency in which you wish to allow clearing transactions under this branch. You can specify multiple currencies for a branch. Click on the adjoining option list and select the appropriate code from the list of currencies maintained in the system.

Currency Description

A description of the chosen currency code is displayed here

5.1.17 Account Statement Handoff

The account statement handoff will consider the movements on accounts based on the Statement Date and not the Transaction Date. The Statement Status Change will itself run the Account Statement handoff for the previous working date before marking the Branch Statement Status as ready.

5.1.18 Account Statement Generation

Accounting entries with Statement Date lying between From Date and To Date populated in the handoff records will be picked up for Account Statement Generation processing.

5.2 Maintaining Tax Cycle

You can maintain tax cycle at the bank level through the 'Tax Cycle Maintenance' screen. Invoke this screen by typing 'STDTCYCL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

The screenshot shows the 'Tax Cycle Maintenance' application window. It has a standard Windows-style title bar. Below the title bar is a search bar with the text 'Enter Query'. The main area contains several input fields: 'Tax Cycle *', 'Description', 'Start Date *', and 'End Date *'. There is also a checkbox labeled 'Tax Paid and Cycle Closed'. At the bottom of the window, there is a 'Fields' section with input fields for 'Input By', 'Authorized By', and 'Modification Number', each with a 'Date Time' field. There are also checkboxes for 'Authorized' and 'Open'. An 'Exit' button is located in the bottom right corner.

Tax Cycle

You need to define the tax cycle, which will be uniquely identified in the system

Start and End dates for tax cycle

You need to indicate the start and end date of the tax cycle you are defining, using the adjoining calendar.

Tax Paid and Cycle Closed

Check this box to close the tax cycle. It will not have any bearing on the existing tax calculation. Once the tax cycle is closed, it will not be allowed to be opened again.

Updating Tax Cycle

The Current Tax Cycle would be updated as and when the tax cycle changes. This would be done during authorization of date change function on the first day of the new Tax Cycle.

5.3 Branch Level Role to Head Mapping

This section contains the following topics:

- [Section 5.3.1, "Maintaining Role to Head Mapping at Branch Level"](#)
- [Section 5.3.2, "Viewing Accounting Role to Head Mapping Details"](#)

5.3.1 Maintaining Role to Head Mapping at Branch Level

You can maintain different General Ledgers for different branches for the accounting roles defined in the system. If you have maintained Role to Head mapping for a product at the branch level, the system uses these accounting heads instead of the heads maintained at the product level.

You can maintain Role to Head mapping for a combination of branch, product and status in 'Branch Level Role to Head Mapping' screen. You can invoke this screen by typing 'CSDACRHM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Branch Level Role to Head

New

Branch *
Branch Name
Product Code *
Product Description
Status *

Role To Head Mapping Details

1 Of 1
Go

Accounting Role *	Accounting Head *
-------------------	-------------------

Fields

Maker	Date Time:	Mod No	Record Status
Checker	Date Time:		Authorization Status

Exit

You can specify the following details in this screen:

Branch Code

The branch code of the current branch gets defaulted here.

Branch Name

The name of the current branch corresponding to the branch code gets displayed here.

Product Code

Specify the product code for which you wish to maintain role to head mapping or select the product code from the option list provided.

Status

Specify the status code for which you wish to maintain role to head mapping or select the status code from the option list provided.

Accounting Role

Select the accounting role to be used for role to head mapping, from the option list provided.

Accounting Head

Select the GL accounting head to be used for role to head mapping, from the option list provided.

You can add more rows to accounting role and heads by clicking the 'plus' icon provided. You can also delete a row from this table by selecting the required row and clicking the 'minus' icon.

Note

The accounting roles and heads maintained here will override the default role head mapping maintained for the product.

5.3.2 Viewing Accounting Role to Head Mapping Details

You can view the details related to accounting roles and heads for a branch in 'Branch Level Role to Head Mapping Summary' screen. You can invoke this screen by typing 'CSSACRHM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a web application window titled 'LBL_BRRNTH'. At the top, there is a search bar with 'Search', 'Advanced Search', and 'Reset' buttons. Below the search bar, there are three dropdown menus: 'Authorization Status', 'Branch', and 'Status'. To the right of these are two more dropdown menus: 'Record Status' and 'Product Code'. Below the dropdowns, there is a table with the following columns: 'Authorization Status', 'Record Status', 'Branch', 'Product Code', and 'Status'. The table shows 1 record out of 1, with a 'Go' button and a '0' in a dropdown. An 'Exit' button is located at the bottom right of the window.

The following details get displayed in this screen:

- Authorization status
- Record status
- Branch code
- Product code
- Status

6. Account Branch Transfer

You may get request from the customers for change of account branch. Oracle FLEXCUBE allows you to transfer a customer account from one branch of the bank to another. You can also transfer the all accounts that belong to an account class to a different branch at once. This chapter explains the required maintenances and the methods to process account branch transfer.

This chapter contains the following sections:

- [Section 6.1, "Maintaining Branch Transfer Parameters"](#)
- [Section 6.2, "Customer Account Branch Transfer"](#)
- [Section 6.3, "Transferring Account Class Branch"](#)
- [Section 6.4, "Processing Account Branch Transfer Batch"](#)

6.1 Maintaining Branch Transfer Parameters

In order to facilitate this, you need to maintain the branch transfer parameters using 'Branch Transfer Parameters Maintenance' screen. To invoke this screen, type 'CSDACTRP' in the field at the top right corner of the Application toolbar and click the adjoining arrow button.

Branch Transfer Parameter Maintenance Screen

New

Branch Code * 000

Transaction Code * TFR

Transfer Bridge GL * 261100005

Process Mode Sequential

No of Parallel Jobs

Commitment Frequency 100

Fields

Maker VALLABH1 Date Time: 2014-01-01 18:19:12 Mod No 1 Record Status Open

Checker VALLABH2 Date Time: 2014-01-01 18:28:34 Authorization Authorized Status

Exit

Specify the following details:

Transaction Code

Specify a unique transaction code. The system will use this transaction code to post the accounting entries while processing the account balance transfer from one branch to another.

Note

Ensure that the options 'Account Activity', 'Cheque Mandatory', 'IC Transaction Count', 'IC Turnover Inclusion' and 'IC Penalty' are not checked on 'Transaction Code Maintenance' screen.

Transfer Bridge GL

Specify the bridge GL to be used while moving the account balance from one branch to another.

Process Mode

Specify the mode of processing the account transfer. The drop-down list displays the following options:

- Sequential – If you choose this, the system will process the transfer in a sequential order
- Job – If you choose this, the system will process the transfer as job

Choose the appropriate one.

Number of Parallel Jobs

Specify the number of parallel jobs. This is the maximum number of jobs that may be submitted for processing at the same time.

Commitment Frequency

Specify the commitment frequency. While processing the transfer batch, the system will perform commits based on the frequency set here.

6.2 Customer Account Branch Transfer

This section contains the following topics:

- [Section 6.2.1, "Transferring Customer Account Branch"](#)
- [Section 6.2.2, "Viewing Account Branch Transfer Details"](#)

6.2.1 Transferring Customer Account Branch

Using Oracle FLEXCUBE, you can transfer a customer account from one branch of the bank to another. The account branch transfer is processed using 'Account Transfer' screen. To

invoke this screen, type 'CSDACCTR' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

Bank Transfer

New

Transfer ID * 116ZTRF140900002

Current Branch * 116

Current Branch Name 116 BRANCH

Transfer Date * 2014-04-01

Target Branch * DC1

Target Branch Name

Regenerate IBAN

Account Number	Account Description	Customer Number	Customer Name
CACCR660002225116			

Fields

Maker SURENDRA1	Date Time: 2014-03-31 18:16:52	Mod No 1	Record Status Open
Checker SURENDRA1	Date Time: 2014-03-31 18:16:52	Authorization Authorized	Status

Exit

Specify the following details:

Transfer ID

The system generates a unique transfer ID. This will be used as a unique identifier of the account transfer.

Current Branch

Specify the current branch of the account. On processing the transfer, the system will move the account from this branch to the target branch.

Current Branch Name

The system displays the name of the current branch.

Target Branch

Specify the target branch code. The option list displays all valid branch codes maintained in the system. Choose the appropriate one.

On processing the transfer, the system will move the account from the current branch to the branch selected here.

Target Branch Name

Based on the branch code selected, the system displays the name of the target branch.

Regenerate IBAN

Check this box to regenerate IBAN upon branch transfer.

If you select the 'Regenerate IBAN' check box, the system performs the following actions:

- On saving branch transfer record, the system checks whether BBAN Format Mask and related values are available for IBAN regeneration.
- During branch transfer of accounts with IBAN, the system regenerates IBAN based on the IBAN/BBAN parameters of the new branch.

If you do not select the 'Regenerate IBAN' check box, the system performs the following actions:

- On saving branch transfer record, the system validates whether the BBAN Format Mask and data type are same for the current and destination branch.
- During branch transfer of CASA accounts, the system retains the original IBAN field value.

Transfer Date

Specify the effective date of the account branch transfer. Click the date button to choose a date from the calendar.

The transfer date must be a date in the future. You cannot process the transfer on the current date or a past date.

Account Details

You need to specify the following account details:

Account Number

Specify the account number that you need to transfer. The option list displays all valid account numbers at the selected branch. Choose the appropriate one.

To view the joint holder's details of an account and the mode of operation maintained at the account level, place the cursor on the Account Number field and press Ctrl+J. The system displays the 'Joint Holder' screen.

For more information on the 'Joint Holder' screen refer to the section 'Joint Holder Maintenance' in this User Manual.

Account Description

Based on the account selected, the system displays the description.

Customer Number

Based on the account selected, the system displays the customer number.

Customer Name

Based on the customer number selected, the system displays the name of the customer.

Once you have captured the details, save the record. The system will process the account transfer on the transfer date.

6.2.2 Viewing Account Branch Transfer Details

You can search and view the details of account branch transfer using 'Branch Transfer Log' screen. To invoke this screen, type 'CSDACLOG' in the field at the top right corner of the Application toolbar and click the adjoining arrow button.

Branch Transfer Log

Transfer Reference Number _____ Source Branch _____
Account Number _____ Target Branch _____
Transfer Date _____ Status _____
Customer No _____ Account Class _____

Error Details

1 Of 1 Go

Error Code	Error Message
------------	---------------

Exit

You can search for the account transfer details based on one or more of the following parameters:

- Transfer ID
- Account number
- Transfer date
- Customer number
- Source/current branch
- Target branch
- Status of the transfer record (Success/Error)
- Account class

Once you have set the search parameters, click search button. The system displays the account transfers that match the search criteria. Double-click a record to view the details.

To view the joint holder's details of an account and the mode of operation maintained at the account level, place the cursor on the Account Number field and press Ctrl+J. The system displays the 'Joint Holder' screen.

For more information on the 'Joint Holder' screen refer to the section 'Joint Holder Maintenance' in this User Manual.

Note

The system will not process the account transfer in the following circumstances:

- The account is a Nostro type account
 - Local currency of the current branch and the target branch are different, in case of individual account transfer
 - Minor age limit is different for the current branch and target branch
-

Note

- Staff restriction, account class restriction and branch restriction are applicable while maintaining details of individual account transfer.
 - You can mark for rerun the accounts with status 'Error' by clicking 'Resubmit' button. Such accounts are processed during EOD operations on the next day.
-

6.3 Transferring Account Class Branch

You can transfer all accounts that belong to an account class, from one branch to another, using 'Account Branch Class Transfer' screen. To invoke this screen, type 'CSDACLTR' at the top right corner of the Application toolbar and click the adjoining arrow button.

Account Class Branch Transfer

New

Transfer ID *

Account Class *

Account Class Description

Current Branch Code *

Current Branch Name

Target Branch *

Target Branch Name

Transfer Date *

Regenerate IBAN

Fields

Maker	Date Time:	Mod No	Record Status
Checker	Date Time:	Authorization Status	

Exit

Specify the following details:

Transfer ID

The system generates a unique transfer ID. This will be used as a unique identifier of the account class transfer.

Current Branch Code

Specify the current branch of the account class. On processing the transfer, the system will move the accounts that belong to the selected account class from the current branch to the target branch.

Current Branch Name

The system displays the name of the current branch.

Target Branch Code

Specify the target branch code. The option list displays all valid branch codes maintained in the system. Choose the appropriate one.

On processing the transfer, the system will move the accounts that belong to the selected account class from the current branch to the target branch selected here.

Target Branch Name

Based on the branch code selected, the system displays the name of the target branch.

Transfer Date

Specify the effective date of the account branch transfer. Click the date button to choose a date from the calendar.

The transfer date must be a date in the future. You cannot process the transfer on the current date or a past date.

Regenerate IBAN

Check this box to regenerate IBAN upon branch transfer.

If you select the 'Regenerate IBAN' check box, the system performs the following actions:

- On saving branch transfer record, the system checks whether BBAN Format Mask and related values are available for IBAN regeneration.
- During branch transfer of accounts with IBAN, the system regenerates IBAN based on the IBAN/BBAN parameters of the new branch.

If you do not select the 'Regenerate IBAN' check box, the system performs the following actions:

- On saving branch transfer record, the system validates whether the BBAN Format Mask and data type are same for the current and destination branch.
- During branch transfer of CASA accounts, the system retains the original IBAN field value.

Account Class

Specify the account class that you need to transfer. The option list displays all valid account classes maintained in the system. Choose the appropriate one.

Account Class Description

Based on the account class selected, the system displays the account description.

Once you have captured the details, save the record. The system will process the account transfer on the transfer date.

6.4 Processing Account Branch Transfer Batch

During Beginning of Day Operations, the system will check the accounts whose transfer date is the current system date. These accounts are processed by the account branch transfer batch (ACDTRBT), which is triggered as part of BoD operations.

The system verifies the balances of the accounts to be processed. There can be two cases as follows:

- Negative balance – If the account balance is negative, then the system will debit the transfer GL and credit the account to make the balance zero.
- Positive balance – If the account balance is positive, then the system will debit the account and credit the transfer GL to make the balance zero.

Further, the system updates the remaining necessary account information. The new branch code is updated in messages, statements and all branch related information specific to the account.

Note

The system will not process the account transfer in the following circumstances:

- The target branch is not allowed for the account class
 - The account has uncollected, unauthorized or tanked balance
 - The account status is 'Frozen', 'Deceased', 'No Debit' or 'No Credit'
 - The account is a Nostro type account
-

Once the details are updated, the system transfers the balance back to the account from the transfer GL.

Auto deposits linked to the account is handled as follows:

- Auto deposit maturing on the transfer date – The system does not transfer the auto deposits that mature on the date of transfer.
- Auto deposit maturing in the future – The system transfers the auto deposits that mature on a future date.

In case of a customer portfolio transfer or a bank merger, the accounts will be transferred to the corresponding branch. For further details on customer portfolio transfer and bank merger, refer to the sections 'Transferring Customer Portfolio' and 'Merging of Branches' in chapter 'Branch Transfer of Loans' of Retail Lending user manual.

7. Web Service Maintenance

Oracle FLEXCUBE supports a generic functionality to call external web services. The operations done on the screens have the information of web services. The request processed during the operations is analyzed and the web service is enabled. This chapter takes you through the WebService Maintenance, WebService Mapping and other details regarding WebService.

This chapter contains the following sections:

- [Section 7.1, "Maintaining Web Service"](#)
- [Section 7.2, "Mapping of Web Service"](#)
- [Section 7.3, "Web Service Details"](#)
- [Section 7.4, "WebService Maintenance"](#)

7.1 Maintaining Web Service

You can maintain Web service through WebService Maintenance screen. You can invoke this screen by typing 'CSDEXTWS' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Webservice Maintenance' application window. It features a 'New' button at the top left. The main form area is divided into two columns of input fields. The left column includes 'WebService Code *', 'WebService Description', 'WebService User *', and 'WebService Password *'. The right column includes 'WebService Server IP *', 'WebService Server Port *', and 'WebService Server URI *'. The bottom of the window has a light blue bar containing fields for 'Maker', 'Date Time:', 'Mod No', 'Record Status', 'Checker', 'Date Time:', 'Authorization Status', and an 'Exit' button.

Specify the following here:

WebService Code

The unique code for the web service s defaulted here.

WebService Description

The description of the web service is displayed here.

WebService User

The system displays the user of the web service.

WebService Password

The system displays the password with which the web service is invoked.

WebService Server IP

The system defaults the IP address of the server where web service is installed.

WebService Server Port

The system displays the port of the server where web service is installed.

WebService Server URI

The system defaults the URI of the server where web service is installed.

7.2 Mapping of Web Service

WebService mapping is attached to the transaction screens for which web service call is required. You can invoke this screen by typing 'CSCEXWSO' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

WebService Code	Calling Sequence Number	Calling Stage	Status	Details
-----------------	-------------------------	---------------	--------	---------

WebService Code

Select the unique web service code from the adjoining option list.

Call Sequence Number

The unique sequence number for the web service is displayed here.

Calling Stage

Select the stage at which web service should be called from the drop-down list.

Status

The system defaults the status of the web service.

7.3 Web Service Details

Web Service details is attached to the maintenance screens for which web service call is required. You can invoke this screen by typing 'CSCEXWSM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a window titled "Webservice Details". At the top, there is a "Key Id" label followed by a text input field. Below this is a table with a header row containing "WebService Code", "Calling Sequence Number", "Calling Stage", "Status", and "Details". The table body is currently empty. To the left of the table, there is a checkbox and a "Go" button. At the bottom right of the window, there are "Ok" and "Exit" buttons.

WebService Code

Select the unique web service code from the adjoining option list.

Call Sequence Number

The system displays the unique sequence number for the web service.

Calling Stage

Select the stage in which the web service should be called from the drop down list.

Status

Select the status of the web service from the drop down list.

Note

- When any operation is done in the screen and call to back end is made, the request built during this process will have the information of web services to be called. The web service call will be made based on the status of each web service which will be updated in the backend.
 - The details of an external web service is taken from the maintenance screen based on the web service code mentioned in the call form. Each web service should be deployed in the URL mentioned in the maintenance before processing the request.
 - A flag will be set to find whether the request contains the web service information and the same will be used for parsing the request in the application server. Call to the web service is based on the request format that particular web service accepts. The request to the web service should be in that format and it can be written in the handler class provided.
-


Sending request to back end involves two cases:

- If in the request, option to call the web service is pre, then the web service will be called and the response from the web service will be appended in the request before sending it to the back end.

- If in the request, option to call the web service is post, then the request will sent to back end first and the response from the back end will be sent to the web service. The response from the web Service Call will be appended in the request and sent to the backend again.

7.4 WebService Maintenance

Web Service Maintenance is attached to the maintenance screens for which web service call is required. You can invoke this screen by typing 'CSDEXWSD' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



WebService Code

The system displays the unique code of the web service

Call Sequence Number

The system displays the unique sequence number of the web service

Calling Stage

Select the stage in which the web service should be called.

Status

The system defaults the status of the web service.

Key ID

The system defaults the ID for which the web service is called.

Request

The system displays the request of the web service.

Response

The system displays the response of the web service.

8. Accounts for Inter-Branch Transactions

This chapter contains the following sections:

- [Section 8.1, "Defining Accounts for Inter-Branch Transactions"](#)
- [Section 8.2, "Defining Accounts for Inter-Branch Fund Transactions"](#)
- [Section 8.3, "Defining Accounts for Inter-Branch Currency Transactions"](#)
- [Section 8.4, "Querying on Netting Batch"](#)

8.1 Defining Accounts for Inter-Branch Transactions

A transaction that takes place in a branch of your bank may involve accounts that are maintained in another branch. For example, a customer has an account in the Head Office branch and approaches another branch of the bank for a cash withdrawal.

For each combination of branches that may be involved in an inter-branch transaction, you can define the currency and the respective customer accounts to which the related accounting entries will be posted.

The accounting entries for such inter-branch transactions can be routed in one of the following ways:

- **Directly** - where each branch will have a direct accounting relationship with all other branches
- **Through a Regional Office** -- where two branches involved in a transaction will interact through a common RO
- **Through the Head Office** -- where the two branches involved in the inter-branch transaction will interact only through the HO.

This route for all transactions is defined in the 'Bank parameters' screen. In the 'Inter-branch Parameters Maintenance' screen you define the internal accounts for pairs of branches that would be involved in any inter-branch accounting.

Invoke this screen by typing 'ACDIBMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen appears as shown below:

In this screen you maintain the following for each combination of branches that may be involved in an inter-branch transaction:


- Branch Code of both the branches that are involved in the transaction
- For each of the branches, whether inter-branch entries must be posted in transaction currency or settlement account currency
- GL accounts of Branch 1
 - Due to Branch 1
 - Due from Branch 1
- GL accounts of Branch 2
 - Due to Branch 2
 - Due from Branch 2

8.1.1 System Features

The system generates a set of pairs of branches for which internal accounts should be maintained. The pairs generated depend upon on two factors:

- The reporting structure for the branches as created in the 'Branch parameters' screen and
- The route defined for inter-branch transactions in the 'Bank-wide parameters -- Preferences' screen,

For example, the following represents the reporting structure of your bank:



If you have defined a direct inter-branch accounting route then you need to maintain an accounting relationship for each possible combination of

- Branch and branch
- Branch and RO
- RO and HO
- Branch and HO

For the above mentioned reporting structure the system will offer the following pairs of branch combinations to be maintained:

1. BR1- BR2
2. BR1- RO1
3. BR2- RO2
4. RO1- HO
5. RO2- HO
6. BR1 - RO2
7. BR2 - RO1
8. BR1 – HO
9. BR2 – HO
10. RO1 - RO2

If you have defined 'through RO' inter-branch accounting route then you need to maintain an accounting relationship for each possible combination of

- Branch and RO/HO
- RO and RO

In the branch and RO pair, the RO should be that RO to which this branch reports. For the above mentioned reporting structure the system will offer the following branch pairs to be maintained:

1. BR1 - RO1
2. BR2 - RO2
3. RO1 – HO
4. RO2 – HO
5. RO1 - RO2

If you have defined 'through HO' inter-branch accounting route then you need to maintain an accounting relationship for each possible combination of,

- Branches and HO
- ROs and HO

For the above mentioned reporting structure the system will offer the following branch pairs to be maintained:

1. HO - RO1
2. HO - RO2
3. HO - BR1
4. HO - BR2

The system has an in-built auto escalation path for inter-branch accounting transaction which escalates from Direct to Through RO to Through HO.

For example, in the 'Bank preferences' screen you have defined a 'direct' inter-branch accounting relationship. But in the 'Inter-branch Accounts' maintenance screen (where all inter-branch accounts are maintained), you have not maintained an accounting relationship between two branches -- 000 and 002. Then, in case of an inter-branch accounting transaction between 000 and 002, the system will first look for a 'direct relationship' since that has not been maintained it will look for a relationship through RO i.e., if the two branches have a common RO; if that too does not exist then 'through HO' the transaction would take place.

Specifying General Ledger Details

Specify the GL accounts which are involved in the inter-branch transaction, in the respective branches

To maintain GL accounts for the branch pair specified, the following parameters should be maintained:

Inter Bank Currency

For each branch, you have the option of specifying whether the inter-branch entries must be posted in the transaction currency or the settlement account currency.

For the booking branch, if the Inter-branch Transaction Currency option specified is Transaction Currency, inter-branch entries are posted in the transaction currency only if:

- The local currency of both branches involved in the transaction is the same
- One of the accounts in the entries belongs to the booking branch

Due To Branch 2

This field identifies the GL account maintained in Branch 2 into which the credit entry is passed.

To specify the GL account, select the appropriate account from the picklist of all the accounts maintained at Branch 2.

Due From Branch 2

This field identifies the GL account maintained in Branch 2 into which a debit entry will be passed.

Due to Branch 1

This identifies the GL account maintained at Branch 1 into which a credit entry will be passed.

Due From Branch 1

This account identifies the GL account maintained at Branch 1 into which a debit entry will be passed.

System uses the GL accounts specified in this screen and determines the settlement route for a transaction between two different branches of your bank.

8.2 Defining Accounts for Inter-Branch Fund Transactions

A fund transaction that takes place in a branch of your bank may involve accounts that are maintained in another branch.

As mentioned earlier, if you have selected the option 'Allow Corporate Access' in the Branch Parameters screen and the branch is a fund branch, the IB Entity will be defaulted as General Ledger. The GL that will be used will be based on the maintenance in the Fund Inter Branch Accounts Maintenance screen, for the fund id.

To invoke this screen, type 'IADIBMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

For a fund id, specify all the details necessary to define the Inter branch GL that will be used. The option list against the field Fund ID includes all the valid funds maintained in the system.

For an explanation on each of the other fields, refer to the previous section.

8.3 Defining Accounts for Inter-Branch Currency Transactions

Inter-Branch Currency Wise Parameter Maintenance (CADIBMNT) allows you to define the routing of accounting entries that take place between two branches when the debit and the credit entries are posted to accounts that belong to different branches.

This maintenance allows you to set up the inter-branch parameters by following Branch, Currency, Module and Product wise hierarchy. Inter-Branch accounts to be debited and credited in case of a cross-branch transaction can be defined in three different ways.

1. You can have a unique inter-branch entry definition for every Product belonging to a specific Module, per Currency,
2. A common definition of inter-branch entry for all Products under a Module, per Currency, or
3. An inter-branch entry definition common across an entire Branch, per currency.

System passes inter-branch entries based on the currency wise inter branch parameters, The preference will be given to the following order:

- Transaction module and transaction code
- Transaction module and all products
- All modules and all products

To invoke this screen, type 'CADIBMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Specify the following details in this screen:

Branch Code1

Specify the branch 1 code. Alternatively, you can also select the valid branch code from the adjoining option list.

Branch Code2

The system displays branch 2 code based on the branch code 1 selected.

Branch Name

The system displays the branch name based on the branch code selected.

Currency Code

Specify the currency code. Alternatively, you can select the currency code from the option list. The list displays all valid codes maintained in the system.

Currency Description

The system displays the currency description based on the currency code selected.

Module Code

Specify the module for which the currency wise inter-branch parameter to be maintained. Select '*' to maintain currency wise inter branch parameter for all modules.

Product Code

Specify the product code. Alternatively, you can select the product code from the adjoining list. Product code will fetch all the valid products for selected module. Currency wise Inter branch parameter can be maintained for all product by selecting '*' from the list values. You can select product code as '*', only if module code selected as '*'.

Specifying Account Details

Due To Branch 2

This field identifies the account maintained in Branch 2 into which the credit entry is passed.

To specify the account, select the appropriate account from the pick list of all the customer accounts maintained at Branch 2.

Due From Branch 2

This field identifies the account maintained in Branch 2 into which a debit entry will be passed.

Due to Branch 1

This identifies the account maintained at Branch 1 into which a credit entry will be passed.

Due From Branch 1

This identifies the account maintained at Branch 1 into which a debit entry will be passed.

System uses the accounts specified in this screen and determines the settlement route for a transaction between two different branches of your bank.

Note

When considering both ACDIBMNT and CADIBMNT screens, preference should be given to CADIBMNT screen.

8.4 Querying on Netting Batch

You can view all netted and non-netted transactions of the netting process from the 'Netting Batch Query' screen. You can invoke this screen by typing 'STDNETQY' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Netting Batch Query

Enter Query

Group Code _____

Account Number _____

Date _____

Netting Batch Details

1 Of 1

Netting Reference Number	Date	Branch	Account	Module	Event
--------------------------	------	--------	---------	--------	-------

Exit

You can query on the basis of one or more of the following parameters:

- Netting Group Code
- Account Number
- Date

To view the joint holder's details of an account and the mode of operation maintained at the account level, place the cursor on the Account Number field and press Ctrl+J. The system displays the 'Joint Holder' screen.

For more information on the 'Joint Holder' screen refer to the section 'Joint Holder Maintenance' in this User Manual.

On searching, the system displays the following details:

- Netting Reference Number
- Date
- Branch Code
- Account
- Module
- Event
- Reference Number
- Transaction Code
- Amount Tag
- Debit/Credit Transaction
- Account Currency
- Foreign Currency Amount
- Local Currency Amount

9. Error Queue Definition and Accounting Referral Queue

This chapter contains the following section:

- [Section 9.1, "Maintaining Error Queue"](#)
- [Section 9.2, "Viewing Accounting Referral Queue"](#)

9.1 Maintaining Error Queue

The 'Error Queue Access Control Definition' screen enables you to define access levels required to authorize the transactions for BANCONTROL or any other required queue. You can post or reject the transaction based on the decision taken by the user in the 'Referral Queue' screen.

The levels of authorization should decide on the number of approvers required to approve a transaction for a BANCONTROL/DORMANT Queue.

You can access this 'Error Queue Access Control Definition' screen by typing 'STDEQACD' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button. The screen appears as shown below.:

Error Code *	Description	Level of Authorization	Queue Name *	Level1
--------------	-------------	------------------------	--------------	--------

Specify the following details.

Branch Code

Specify the branch code or type *.* for all branches. Alternatively, you can select the branch code from the option list. The list displays all valid branch codes maintained in the system.

Branch Description

The system automatically displays the branch description upon the selection of the branch code.

Source Code

Specify the source code of the transaction. Alternatively, you can select the source code from the option list. The list displays all valid source codes maintained in the system.

Follow Sequence

Check this box to indicate that the sequence of levels should be followed for authorization.

System displays the following details pertaining to the fetched records:

- Error Code
- Description
- Level of Authorization
- Queue Name
- Level1
- Level2
- Level3
- Level4

Error Code

Specify the Error Code for which the record has to be populated into referral queue. Alternatively, you can select the error code from the list.

Description

This field displays the details of the error message.

Level of Authorization

Specify the levels of approval required in the referral queue.

Queue Name

Specify the name of referral queue record.

Level 1

Specify the role of the first level user who can approve the record. Alternatively, you can select the role from the list.

Level 2

Specify the role of the second level user who can approve the record. Alternatively, you can select the role from the list.

Level 3

Specify the role of the third level user who can approve the record. Alternatively, you can select the role from the list.

Level 4

Specify the role of the fourth level user who can approve the record. Alternatively, you can select the role from the list.

This section contains the following subsection:

- [Section 9.1.1, "Error Code List"](#)

9.1.1 Error Code List

Below table lists the error codes and their corresponding error messages

Error Code	Error Message
AC-OVD01	Available Amount for Account \$1 after this Entry is \$2, Total Available Amount is \$3

AC-OVD02	Available Amount for Account \$1 after this Entry is \$2, Total Available Amount is \$3
AC-OVD05	Available Balance \$2 for \$1 is lesser than the Min balance \$3 for the Account Class
AC-OVD09	The Debit Interest Due for Account \$1 is \$2. Continue?
AC-OVD50	Account \$1 set for closure do you wish to still process?
AC-OVD52	Account \$1 is bancontrol
AC-OVDLM	Available Amount for Account \$1 after this Entry is \$2, Total Available Amount is \$3
AC-OVNT1	Available Amount for Account \$1 after this Entry is \$2, Total Available Amount is \$3
AC-OVNT2	Available Amount for Account \$1 after this Entry is \$2, Total Available Amount is \$3
AC-PROD1	\$1 transaction is not allowed for account \$2 for product \$3
AC-TRN1	\$1 Transaction is not allowed for account \$2 for Transaction code \$3
AC-VAC05	Account \$1 Dormant
AC-VAC06	Account \$1 Closed Posting to deferred
AC-VAC11	The Account Opening Date \$1 Of The Account \$2 Is Greater Than The Value Date \$3 Of The Transaction.
AC-VAC15	Customer is Frozen
AC-VAC17	Customer Whereabouts are unknown.
AC-VAC18	Customer is deceased
ST-FUS-001	Transaction results in utilization of Daylight OD Limit
ST-FUS-002	Transaction results in utilization of Account OD Limit
ST-FUS-003	Transaction results in utilization of Sweep Eligible Balance
ST-FUS-004	Transaction results in utilization of AUF Limit
ST-FUS-005	Transaction results in utilization of TOD Limit
ST-FUS-006	Transaction results in overline utilization
ST-FUS-03	Account Class Transfer Initiated for Account \$1 in Debit Balance
ST-FUS-037	Both 'Default Deposit Rate' and 'Rate Code/Value' are given for Term Deposits.
ST-FUS-04	Customer Aggregation Initiated for Account \$1 in Debit Balance
ST-FUS-07	The Automatic Overdraft facility is applicable only to Individual type customers

ST-FUS-08	The Automatic Overdraft facility is allowed only for local currency accounts
ST-FUS-12	Entered rate outside acceptable range for interest rate
ST-LM113	Line \$1 - Amount exceeds line limit. Limit = \$3 \$2. Utilization = \$4 \$2. Overdraft = \$5 \$2 %Overdraft = \$6

Supported modules for Error Queue are LC,BC,SI,DE and FX.

Initial funding has to be handled operationally in STDCIF,STDCUSAC,STDCASAC & IADCUSAC screens, since accounting entries are posting while authorization.

9.2 Viewing Accounting Referral Queue

You can view the summary of accounting referral records in the 'Accounting Referral Queue' screen. This screen displays the status of the records maintained such as authorized, unauthorized or rejected. Records will be displayed for a given source depending on the error queue (BANCONTROL/DORMANT) selected.

The records will be displayed based on the logged-in users role. If you do not have the required role then the records will not be displayed. If there are multiple errors for an account, then all those entries should be populated in this screen for authorization or rejection.

You can invoke this screen by typing 'STDTRFQ' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button..

In the above screen, you can base your queries on any or all of the following parameters and fetch records:

- Branch
- Queue Name
- EA/ECA Block/Contract Reference
- Source Code

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Queue Name
- EA/ECA Block/Contract Reference
- Branch Code
- Account Number

- Module Code
- Error Code
- Override Details
- Pending Authorization
- Completed Authorization
- Remarks
- Override Auth Status
- Maker ID
- Status
- Authorization Details

You can click Confirm button to authorize a single record. And you can click Authorize All button to authorize all records.

10. Product Restrictions Maintenance

Oracle FLEXCUBE allows you to maintain branch, currency, customer category and customer restrictions while defining a product. From the head office of your bank, you may want to establish certain controls or standardize operations across the branches of your bank. For instance, you may want to restrict the products you offer to selected branches, currencies, customer categories and customer. You can achieve these controls by maintaining restriction lists when creating a product. When you create a product, you can specify the branches of your bank that can offer it and the currencies and customer categories that are allowed or disallowed for it.

These product restrictions can be maintained for all product definition screens except Salary Credit module:

This chapter contains following section:

- [Section 10.1, "Product Restriction"](#)

10.1 Product Restriction

This section contains the following topics:

- [Section 10.1.1, "Maintaining Product Restrictions"](#)
- [Section 10.1.2, "Viewing Product Restrictions"](#)

10.1.1 Maintaining Product Restrictions

You can maintain branch, currency, customer category and customer restrictions for a product in the 'Product Restriction' screen. You can invoke this screen by typing 'CSDPRDRS' in the top right corner of the Application toolbar and clicking the adjoining arrow button.

The screenshot shows the 'Product Restrictions' application window. It includes a 'New' button and an 'Enter Query' field. The main form has a 'Product Code *' field, a 'Product Description' field, and two tabs: 'Branch Restriction' (active) and 'Customer Restriction'. Under 'Branch Restriction', there is a 'Branch List' dropdown set to 'Disallowed', a 'Class Code' field, and a 'Description' field. Under 'Customer Restriction', there is a 'Currency Restrictions' dropdown set to 'Disallowed' and a 'Default From Class' button. Below the form are two data grids. The first grid has columns 'Branch Code' and 'Branch Name'. The second grid has columns 'Currency Code' and 'Currency Name'. At the bottom, there is a 'Change Log' section with columns for 'Maker', 'Checker', 'Date Time', 'Mod No', 'Record Status', and 'Authorization Status'. An 'Exit' button is located in the bottom right corner.

Specify the following details in this screen:

Product Code

Specify the product code. Alternatively, you can select the product code from the option list. The list displays all valid product codes maintained in the system.

Product Description

The system displays the product description based on the product code selected.

10.1.1.1 Branch Restriction Tab

Branch Restriction List

The system displays the branch list as Allowed or Disallowed based on the maintenance in the corresponding Product definition screen.

Class Code

Specify the class code. Alternatively, you can select the class code from the option list. The list displays all valid options based on the restrictions maintained.

Description

The system displays the description.

Branch Code

Specify the branch code. Alternatively, you can select the branch code from the option list. The list displays all valid branch codes maintained in the system.

Branch Name

The system displays the branch name based on the branch code selected.

Currency Restrictions List

The system displays the currency restrictions as Allowed or Disallowed based on the maintenance in the corresponding Product definition screen.

Currency Code

Specify the currency code. Alternatively, you can select the currency code from the option list. The list displays all valid codes maintained in the system.

Currency Name

The system displays the currency name based on the currency code selected.

10.1.1.2 Customer Restriction Tab

Categories Restriction List

The system displays the categories list based on the maintenance in the corresponding product screen.

Class Code

Specify the class code. Alternatively, you can select the class code from the option list. The list displays all valid options based on the restrictions maintained.

Description

The system displays the description.

Code

Specify the code. Alternatively, you can select the code from the option list. The list displays all valid options maintained in the system.

Description

The system displays the description based on the code selected.

Customer ID

Specify the customer ID. Alternatively, you can select the customer ID from the option list. The list displays all valid customer IDs maintained in the system.

Customer Name

The system displays the customer name.

Restriction Type

You can select the restriction type as 'Allowed' or 'Disallowed'.

If a customer category restriction is maintained as 'Disallowed' and if one of the customer in that disallowed customer category has restriction type maintained as 'Allowed', then the system considers individual customer's restriction type for further processing. This is applicable vice-versa also.

Click 'Change Log' button to view the details of values that are modified.

10.1.2 Viewing Product Restrictions

You can view the product restriction details from Product restriction Summary screen. You can invoke this screen by typing 'CSSPRDRS' at the top right corner of the Application toolbar and clicking the adjoining arrow button.

Product Restrictions Summary

Search Advanced Search Reset Clear All

Case Sensitive

Authorization Status Record Status

Product Code

Records per page 15 1 Of 1 Go Lock Columns 0

Authorization Status	Record Status	Product Code
----------------------	---------------	--------------

Exit

You can query on records based on any one or all of the following criteria:

- Authorization Status
- Record Status
- Product Code

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Product Code

11. Restriction Maintenance at Customer Level

Oracle FLEXCUBE provides a utility to maintain customer level restrictions which can be utilized for transactions like cash withdrawals, non-resident local currency credit restrictions and so on. This can be achieved by maintaining restriction codes and linking these restriction codes to a customer or customer category. The system also provides the facility to track the utilized and unutilized restriction amount for a customer. Additionally, a fee can be charged for branch transactions that exceed the utilized restriction amount.

These restrictions at a customer level can be maintained for the following modules in the Oracle FLEXCUBE Universal Banking system:

- Utility Bill Payments
- Standing Instructions
- Retail Teller
- ATM or Point of Sale Transactions
- Term Deposits
- Loans
- Accounting Entries Upload
- Interest to CASA

For more information on how the utilized restriction amount is tracked in each of these modules, refer to the section 'Restriction Utilization Tracking'

This chapter contains the following sections:

- [Section 11.1, "Restriction Code Maintenance"](#)
- [Section 11.2, "Restriction Code- Customer/Customer Category Linkage"](#)
- [Section 11.3, "Customer Restriction Inquiry"](#)
- [Section 11.4, "Restriction Utilization Tracking"](#)

11.1 Restriction Code Maintenance

This section contains the following topics:

- [Section 11.1.1, "Maintaining Restriction Codes"](#)
- [Section 11.1.2, "Viewing Restriction Codes"](#)

11.1.1 Maintaining Restriction Codes

In the 'Restriction Code Maintenance' screen, you can maintain restriction codes. These restriction codes can be linked to a customer or customer category.

For more information on attaching restriction codes to a customer or customer category, refer to the section on 'Restriction Code- Customer Linkage' in this module.

You can invoke the 'Restriction Code Maintenance' screen by typing STDRSTMT in the field at the top right corner of the application tool bar and clicking the adjoining arrow button.

You can perform the following operations in this screen:

- Input
- Delete (before Authorization)
- Modification: Status can be changed from active to inactive
- Close
- Reopen
- Authorization

Specify the following details:

Restriction Code

Specify a restriction code for customer level tracking.

Restriction Code Description

Specify a description for the earlier specified restriction code.

Restriction Period

Select a restriction period from the drop down list. The list of values displayed is as follows:

- Daily
- Monthly
- Quarterly
- Half Annually
- Annually

Track All Currency

Check this box if you intend to track the restriction amount against a default currency. On checking this field, the transaction amount is converted into the default currency and tracked against the default amount for those currencies for which the restriction amount is not explicitly maintained. In case the restriction amount is maintained for a specific currency, then

the transaction amount in that currency is tracked against the respective restriction amount. Provision to maintain the restriction amount is provided in the 'Restriction Code - Customer Linkage' screen.

Default Restriction Currency

This field is applicable when the field 'Track All Currency' is selected. Select the default currency against which the limit needs to be tracked, from the adjoining option list. If the 'Track All Currency' field is selected, then this field needs to be mandatorily updated.

Exchange Rate Type

Select the exchange rate type to be considered for cross currency transactions from the adjoining option list.

If 'Track All Currency' is checked, then 'Default Restriction Currency' and 'Exchange Rate Type' should be mandatorily updated.

Note

If the restriction amount is maintained in the transaction currency, then the transaction amount is tracked in that currency. However, if the restriction amount is not maintained in the transaction currency, then the transaction amount is converted to the default currency using the exchange rate type value.

Adhoc Period Days

Number of Days

Specify the number of days for which the transaction limit is applicable.

Day Basis

Select the day basis from the drop-down list. The list displays the following values:

- **Calendar:** If you select this option, maintained limit is applicable for selected number of calendar days. For instance, if you are transacting on 22 Jan 2015 and number of days as 15, then the set limit is for a period of 15 calendar days from 08 Jan 2015 to 22 Jan 2015.
- **Working:** If you select this option, maintained limit is applicable for selected number of customer home branch working days. Sunday is weekly holiday in Customer home branch. For instance, if you are transacting on 22 Jan 2015 and number of days as 15, which means set limit is for a period of 15 days from 6 Jan 2015 to 22 Jan 2015.

Sequence

Enter the sequence number. This field indicates the sequence in which the restriction needs to be tracked. Sequence No. 1 is given the highest precedence.

Type

Select the Product Type from the drop down list. The available values are:

- Group
- Category

Note

For all modules, product type should be selected as 'Group' except for Loans. For loans, the product type should be selected as 'Category'.

Product Group/Product Category

Select the Product Group or Product Category (for loans) to be maintained for restriction tracking, from the adjoining option list. The list of values displayed for Product Groups are obtained from the Product Group Maintenance (STDPRGRP) screen. For loans, you can maintain product categories in the 'Product Category' (CLDPRCMT) screen.

For more information on the Product Category screen, refer to the section 'Maintaining Product Categories' in the 'Retail Lending' module.

Debit Leg

Select the currency of the debit leg of the transaction that needs to be considered for tracking, from the drop down list. The list of values is as follows:

- LCY = Branch Currency
- FCY= Any currency other than branch currency

Credit Leg

Select the currency of the credit leg of the transaction that needs to be considered for tracking, from the drop down list. The list of values is as follows:

- All = All Currency
- LCY = Branch Currency
- All FCY = Any currency other than branch currency
- SameFCY = Debit Leg Currency

Tracking Leg

Select the leg of the transaction that needs to be tracked, from the drop down list. The list of values provided are as follows:

- Debit
- Credit

Status

Select the status of each record from the drop down list. The list of values provided are as follows:

- Active
- Inactive

11.1.2 Viewing Restriction Codes

You can view the summary details of the Restriction Codes maintained in the 'Restriction Code Summary' screen. To invoke this screen, type 'STSRSTMT' in the field at the top right corner of the application tool bar and click the adjoining arrow button.

The screenshot shows the 'Restriction Code Summary' application window. At the top, there are tabs for 'Search', 'Advanced Search', and 'Reset'. Below these are search filters: 'Authorization Status' (a dropdown menu), 'Restriction Code' (a text input field with a magnifying glass icon), 'Record Status' (a dropdown menu), and 'Restriction Period' (a dropdown menu). Below the filters is a pagination bar showing 'Records per page 15', '1 Of 1', and a 'Go' button. The main area is a table with the following columns: 'Authorization Status', 'Record Status', 'Restriction Code', 'Restriction Description', 'Restriction Period', 'Track All Currency', 'Exchange Rate Type', and 'Default Restriction Currency'. The table is currently empty. At the bottom right of the window is an 'Exit' button.

You can search for a record based on the following parameters:

- Authorization Status
- Restriction Code
- Record Status
- Restriction Period

On updating the above mentioned details, click the search button and the following details are populated:

- Authorization Status
- Record Status
- Restriction Code
- Restriction Description
- Restriction Period
- Track All Currency

11.2 Restriction Code- Customer/Customer Category Linkage

In the 'Customer Restriction Linkage' screen you can link a restriction code to a customer or a customer category. You can invoke this screen by typing "STDCSRST" in the field at the top right corner of the application tool bar and clicking the adjoining arrow button.

Customer Restriction Linkage

New

Customer * Category
Number

Customer Category/Customer No * CG1012393

Category Description/Customer Name JIMBLASH

1 Of 1 Go

Restriction Code *	Restriction Description	Track For *	Restriction Currency *	Restriction Amount *
--------------------	-------------------------	-------------	------------------------	----------------------

Maker SAURA_MAK Date Time: 2014-01-01 10:42:55 Mod No 1 Record Status Open
Checker SAURA_AUTH Date Time: 2014-01-01 10:43:32 Authorization Authorized Status Exit

Specify the following details in this screen:

Customer

Select number or category to define the restriction linkage to a customer or customer category.

Customer Category/Customer Number

Specify the Customer Category or Customer Number to which the restriction code is to be linked.

Category Description/ Customer Name

Specify the category description or customer name to which the restriction details are linked.

Restriction Code.

Select the relevant restriction code for restriction tracking, from the adjoining option list. All values as maintained in the 'Restriction Code Maintenance' screen, are populated in this field.

Restriction Description

Specify a description for the selected Restriction Code.

Track For

Select the type of customer for whom the restriction needs to be tracked, from the drop down list. The list of values provided is as follows:

- Foreign National: If the country code of the 'Address of Correspondence' is different from the branch country code, then this customer is classified as a Foreign National.
- Native: If the country code of the 'Address of Correspondence' is the same as the branch country code, then this customer is classified as a Native.

- Both: In this case, restrictions can be tracked for both the foreign national and a native customer.

Restriction Amount

Specify a restriction amount in this field.

Restriction Currency

Specify a restriction currency in this field.

11.3 Customer Restriction Inquiry

In the 'Customer Limit Inquiry' screen you can inquire the restriction details (utilized or unutilized) for a customer. You can invoke this screen by typing STDRSINQ in the field at the top right corner of the application tool bar and clicking the adjoining arrow button.

Specify the following details:

Customer

Select Number or Category to define restriction linkage to customer or customer category.

Customer Category/ Customer Number

Specify the customer or customer category as attached to a customer.

Category Description / Customer Name Restriction Period

The category description or the customer name based on the selection made in the 'Customer Category/Customer Number field, is displayed in this field.

Start Date

Specify the Start Date of the inquiry.

End Date

Specify the End Date of the inquiry.

Restriction Code

Select the restriction code. Alternatively, you can select the restriction code from the option list. The list displays all valid restriction code maintained in the system.

If you have selected 'Restriction Period' as Adhoc, then you should select Restriction Code and End Date. Then the system will show the utilization based on the restriction code maintenance. From date will be derived by the system based on the restriction code maintenance i.e. number of days and calendar days/business days.

Note

Restriction code will be applicable only for Ad-hoc. End date will be enabled and start date will be disabled for Ad-hoc enquiry.

Customer Number

The Customer ID is defaulted in this field.

Restriction Code

The Restriction Code defined for customer level tracking is displayed in this field.

Restriction Description

The description of the relevant restriction code is displayed in this field.

Restriction Period

The restriction period is defaulted in this field. One of the following values are displayed in this field:

- Daily
- Monthly
- Quarterly
- Semi Annually
- Annual

Restriction Amount

The restriction amount is defaulted in this field.

Restriction Currency

The restriction currency is defaulted in this field.

Start Date

The start date of the inquiry is defaulted in this field.

End Date

The end date of the inquiry is defaulted in this field.

Utilized Amount

The Utilized Restriction Amount is defaulted in this field.

Click the Transaction Details button to view the following details of the transaction:

The screenshot shows a window titled 'Transaction Details'. At the top, there are two rows of fields: 'Customer No' (00008143) and 'Restriction Code' (SSK3) on the left; 'Customer Name' (LC CUSTOMER1) and 'Restriction Description' (ssk1 daily) on the right. Below this is a table with two rows of data. The first row is selected with a checkbox. The table has columns for Contract Reference, Module, Product Group/Product Category, Transaction Amount, and Transaction curr. At the bottom right of the window is an 'Exit' button.

Contract Reference	Module	Product Group/Product Category	Transaction Amount	Transaction curr
<input checked="" type="checkbox"/> 504IU01131540011	BC	CDDEP	200	GBP
<input type="checkbox"/> 504IU01131540012	BC	CDDEP	300	GBP

In this screen the following details are displayed:

- Contract Reference Number
- Module
- Product Group or Product Category
- Transaction Amount
- Transaction currency
- Transaction Date
- Exchange Rate Type
- Tracking Leg
- Dr. Account Number
- Credit Account Number
- Restriction Currency
- Restriction Amount

Note

In case there are multiple (dr/cr) accounts involved in a transaction then under 'Customer Limit Inquiry – Transaction Details' screen, only one of the account will be displayed. However, for utilization amount consideration the amount as applicable for the customer will be considered.

11.4 Restriction Utilization Tracking

The system provides the facility to track the utilized and unutilized restriction amount for a customer. The restriction amount is tracked on a cumulative basis and across channels, for the restriction period maintained based on the transaction date. The restrictions are tracked against the sole owner or against the primary holder (in case of joint accounts). These restrictions can be maintained and tracked for different modules of the FLEXCUBE Universal Banking system. The scope of restriction utilization tracking in each module is detailed below:

Term Deposits

In Term Deposits, a CASA account is tracked for restriction amount utilization, when it is debited or credited while funding or due to redemption of a TD account. For multiple modes of payments (e.g. TD funding), the individual record (credit or debit amount) is tracked against the customer (primary holder) of the impacted CASA account. TD top-up facility is also considered for restriction utilization tracking.

For TD, a configurable override ST-CUS-099 is provided. When the error code is configured as an error and if the utilization amount breaches the restriction, then the transaction stops. When the error code is configured as an override the transaction proceeds even when the restriction amount is breached.

Interest to CASA

CASA account interest liquidation (not just settlement account for TD but all CASA accounts) is also tracked for restriction utilization. For CASA IC, a configurable override ST-CUS-099 is provided. When the error code is configured as an error and if the utilization amount breaches the restriction, then the transaction stops. When the error code is configured as an override the transaction proceeds even when the restriction amount is breached.

Retail Teller and Utility Payment

In the Retail Teller and Utility Payment module, if any transaction amount exceeds the maintained restriction amount (transaction amount + utilized amount > restriction amount), an override is provided which can be configured in the 'Error Code Maintenance' (CSDOVDME) screen. *For more information on this maintenance, refer to the section 'Specifying Override Type' in this module.*

In the Utility Payments module, the restriction amount is checked as on the execution date before the transaction is processed.

Standing Instructions

In the Standing Instructions module, if any transaction amount exceeds the maintained restriction amount (transaction amount + utilized amount > restriction amount), then the SI fails. The restriction amount is checked as on the execution date, before the transaction is processed.

Accounting Entries Upload

A file upload facility has been provided from the external channels to the FCUBS system. With this facility you can upload files to debit or credit transactions of specific customer accounts. The Generic Interface (GI) facility is utilized for this purpose. *For more information on this utility, refer to the section 'Processing File Upload Facility from Channels' in the CASA module.*

While uploading the accounting entries, the restriction amount is verified for multiple entries as a single transaction and not as individual entries. A Unique Reference number is used to identify a set of transaction entries. The first serial number of the Unique Reference number is considered to obtain the debit/credit indicator. The contra pair with the contra debit/credit indicator is identified using the amount tag field. Restriction amount utilization is tracked, if either of the two legs (debit/credit) is posted to a CASA account. If both the legs of the transaction are posted to a GL account, then restriction amount will not be tracked.

If the contra leg is not available, then customer limit is not tracked. If a verified transaction entry breaches the restriction amount, then either of the two scenarios can take place:

- the transaction fails and subsequent measures to handle this failure is applied

- the transaction continues by breaching the restriction amount. For this an override is provided which can be configured in the 'Error Code Maintenance' (CSDOVDME) screen. *For more information on this maintenance, refer to the section 'Specifying Override Type' in this module.*

Loans

In the Loans module, restriction utilization is tracked for a customer's CASA account when it is debited or credited during loan repayment or disbursement. Restriction amount utilization is tracked during disbursement, increase in principal and during loan repayment (including scheduled and unscheduled payment, prepayment, pre/part closure).

For disbursement, the principal amount is considered for tracking the restriction utilization amount. For loan repayment, principal (includes principal and profit for Islamic accounts) and interest components (all interest component along with penal interest) are considered for tracking the restriction utilization amount. In case of increase in principal, only the incremental increase in principal is considered for restriction utilization tracking.

If the utilized restriction amount for a customer exceeds the transaction amount, then the repayment or disbursement transaction is stopped for a channel based transaction, while a configurable override is provided for transactions performed by a bank user. For multiple modes of payment or disbursement, the individual record (credit/debit amount) is tracked against the respective customer (primary holder) of the impacted CASA account. The restriction amount utilization is tracked as on the Book Date of the event.

Note

Charges are not considered while tracking the utilized restriction amount.

The following are also included as part of the scope for restriction amount tracking:

Events such as renegotiation, split rollover and consolidated rollover

Mortgages, Lease and Islamic Loans

ATM/POS

For ATM/POS transactions, the restrictions are tracked once the amount block is in place. On release of the amount block for ATM/POS transactions, the utilized restriction amount is reduced by that amount. When the settlement file is uploaded, the restriction is tracked for the transaction amount. If an ATM transaction follows the direct debit flow of a transaction rather than amount block, then the restriction utilization is tracked for the transaction amount.

12. Sanction Check Maintenance

Oracle FLEXCUBE allows to identify individuals who are blacklisted or prohibited from certain financial transactions. Sanction check enables banks to comply with Government's regulatory requirements by checking multiple sanction check systems against the published data. Based on the result banks can freeze on assets, restrict transactions etc.

This chapter contains the following sections:

- [Section 12.1, "Sanction Check System Maintenance"](#)
- [Section 12.2, "Sanction Check Branch Parameters"](#)
- [Section 12.3, "Sanction Check Queue"](#)
- [Section 12.4, "Sanction Check Request Process"](#)

12.1 Sanction Check System Maintenance

This section contains the following topics:

- [Section 12.1.1, "Maintaining Sanction Check System Details"](#)
- [Section 12.1.2, "Status Mapping"](#)
- [Section 12.1.3, "Viewing Sanction Check System Details"](#)

12.1.1 Maintaining Sanction Check System Details

You can maintain sanction check systems for the modules in 'Sanction Check System Maintenance' screen from head office branch. You can also maintain details of the request queue and response queue for the sanction check using the queue related fields. Request queue is used for posting the request from FCUBS and response queue is used for fetching the response from the external system. Validations to check the accuracy of details provided in the queue has to be operationally controlled.

To invoke 'Sanction Check System Maintenance' screen type 'CSDSNCKM' in the field at the top right corner of the Application tool bar and click the adjoining arrow button. The screen appears as shown below:

Maker	Date Time:	Mod No	Record Status
Checker	Date Time:		Authorization Status

In this screen you can maintain the following:

Sanction Checks System

Specify the external system for the sanction check.

Description

Give a brief description about the external system for sanction check.

Click 'Populate Status' to populate the factory shipped statuses for the selected sanction check system.

Communication Method

Communication Method

Select the communication method from the drop-down list. The list displays the following values:

- Synchronous - In synchronous method, system posts the request to request queue and waits for the response for a specified period. If the response is available within the time out seconds then it is processed and the response is updated in FCUBS. If the response is not available within the time out seconds then the response status is updated as 'Time out' and the system continues with other processing.
- Asynchronous - In asynchronous case, system posts the request and does not wait for the response. A listener monitors the response queue and processes the response and updates the response back to FCUBS.

Timeout in Seconds

Specify the timeout in seconds for synchronous processing.

Preferences

Inqueue JNDI Name

Specify the JNDI name for the request queue.

Outqueue JNDI Name

Specify the JNDI name for the response queue.

Initial Context Factory Class

Specify the initial context factory class for queue setup.

Context Provider URL

Specify the context provider URL for queue set up.

Queue Factory JNDI

Specify the queue factory JNDI for queue set up.

Queue Authentication

Queue Authentication Required

Check this box if queue authentication is required for request and response queues.

User ID

Specify the user ID for queue authentication.

Password

Specify the password for queue authentication.

12.1.2 Status Mapping

Status Details

SC Status Code

Specify the status applicable for the sanction check.

SC Status Description

Give a brief description about sanction check approval status.

Final or Interim Status

Indicate whether the status is an interim status for sanctions checks or the final status of sanctions checks.

Final Status Type

If the 'Final or Interim Status' is 'Final', indicate whether the status type is 'Accept' or 'Reject'.

12.1.3 Viewing Sanction Check System Details

You can view the sanction check system maintenance details in Sanction Check System Summary screen. To invoke this screen type 'CSSSNCKM' in the top right corner of the Application toolbar and click adjoining arrow button.

The screenshot displays the 'CSSSNCKM_Desc' application window. At the top, there is a search bar with options for 'Search', 'Advanced Search', 'Reset', and 'Clear All'. Below this, a 'Case Sensitive' checkbox is present. The main search area includes two dropdown menus: 'Authorization Status' and 'Record Status'. Below these are two text input fields labeled 'Sanctions Checks System' and 'Description', each with a magnifying glass icon. A 'Records per page' dropdown is set to '15', and a '1 Of 1' page indicator is shown. A 'Go' button and a 'Lock Columns' dropdown (set to '0') are also visible. The data table below has four columns: 'Authorization Status', 'Record Status', 'Sanctions Checks System', and 'Description'. The table is currently empty, showing only the header row. A vertical scrollbar is on the right side of the table. At the bottom right corner of the window, there is an 'Exit' button.

You can query on records based on any one or all of the following criteria:

- Authorization Status
- Record Status
- Sanction Checks System
- Description

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Sanction Checks System
- Description

Double click on a record to invoke the detailed screen for that record.

12.2 Sanction Check Branch Parameters

This section contains the following topic

- [Section 12.2.1, "Maintaining Sanction Check Branch Parameters"](#)

12.2.1 Maintaining Sanction Check Branch Parameters

You can maintain sanction check branch parameters in 'Sanction Check Branch Parameters Maintenance' screen. To invoke this screen type 'CSDSCPRM' in the top right corner of the Application toolbar and click the adjoining arrow button.

Sanction Check Branch Parameter Maintenance

Save

Branch Code * 000

☐ Sanction Check Required

Sanction Checks System

Retry Days

Branch Name FLEXCUBE UNIVERSAL B/

Description

Maker
Checker

Date Time:
Date Time:

Mod No

Record Status
Authorization
Status

Cancel

You can maintain the following details in this screen:

Branch Code

Specify the branch code. Alternatively, you can select the branch code from the option list. The list displays all valid options.

Branch Name

The system displays the name of the branch.

Sanction Check Required

Check this box to indicate that sanction checks validation for the transactions of particular customer should be done with external system.

If 'Sanction Check Required' flag is selected then it is mandatory to provide 'Sanction Check System'.

Sanction Check System

Specify the external system for the sanction check. Alternatively, you can select the sanction check system from the option list. The list displays all active and authorised sanction check systems maintained in the system.

Description

The system displays the description for the selected sanction check system.

Retry Days

Specify the retry days to identify the days after which re-screening can be allowed for sanction check. By default the value for retry days will be zero, which means sanction check request

will be sent on every modification of the transaction without checking previous sanction check date.

12.3 Sanction Check Queue

This section contains following topics:

- [Section 12.3.1, "Viewing Sanction Check Queue Details"](#)
- [Section 12.3.2, "Viewing Status Change Details"](#)
- [Section 12.3.3, "Viewing Sanction Check Status Change History"](#)
- [Section 12.3.4, "Authorizing Sanction Check Status Change"](#)

12.3.1 Viewing Sanction Check Queue Details

You can view the details of entities and transactions eligible for external sanction check in 'Sanction Check Queue' screen. The entity will not continue with further processing until the response is received from external system or manually approved/rejected in this queue. You can invoke this screen by typing 'CSSSNCQU' at the top right corner of the Application toolbar and clicking the adjoining arrow button.

Sanction Check Queue

Search Advanced Search Reset Clear All

Sanction Reference Request Date Alternate Contract Ref No Entity Location Queue Auth Status Branch Code Entity Type Sanction System Code Customer Number Media Sanction Current Status Module Reference Number Event Code Account Number First Check Number Sanction Response Status

Records per page: 15 1 Of 1 Lock Columns: 0

Sanction Reference	Branch Code	Module	Request Date	Entity Type	Reference Number	Alternate Contract Ref No	Sanction System Code	Event Code	Entity	Customer Number
--------------------	-------------	--------	--------------	-------------	------------------	---------------------------	----------------------	------------	--------	-----------------

Status Change | Authorize

Exit

You can query on records based on any one or all of the following criteria:

- Sanction Reference
- Request Date
- Alternate Contract Ref No
- Entity
- Location
- Queue Auth Status
- Branch Code
- Entity Type
- Sanction System Code
- Customer Number
- Media
- Sanction Current Status
- Module
- Reference Number
- Event Code
- Account Number

- First Check Number
- Sanction Response Status

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Sanction Reference
- Branch Code
- Module
- Request Date
- Entity Type
- Reference Number
- Alternate Contract Ref No
- Sanction System Code
- Event Code
- Entity
- Customer Number
- Account Number
- Location
- Media
- First Check Number
- Queue Auth Status
- Sanction Current Status
- Sanction Response Status

12.3.2 Viewing Status Change Details

Click 'Status Change' button from Sanction Check Queue' screen to view the Status Change sub-screen.

Sanction Reference Number 000SNCK173560004

Branch Code 000

Sanction Current Status * P

Remarks

Sanction Previous Status

Sanction Response Status

Sanction Response Date YYYYMMDD

Description SC Pending

Description

Description

Party Type	Name	Address	Country Code	BIC	Sanction Check
<input checked="" type="checkbox"/> CUST_PRIM	Steven,Steven,STE,STEDL	FLAT NO 12,sh apartments,	IN,IN		
<input type="checkbox"/> CUST_PERS	Steven,Richard,	FLAT NO 12,sh apartments,			
<input type="checkbox"/> CUST_PROF		***			

Status Change History

Ok Exit

You can view the following details of each record from this screen. You can also modify the existing sanctions checks status to other sanctions checks status.

Sanction Check Reference Number

The system displays the sanction reference number.

Branch Code

The system displays the branch code.

Sanction Current Status

When a request is sent the value for this field will be updated as 'Pending'. You can change this status using the sanction check queue screen. When the sanction check response status gets updated through external system, the value for this field also gets updated as that of response status.

Description

The system displays the description of the 'Sanction Current Status'.

Remarks

Specify remarks, if any.

Sanction Previous Status

The system displays the value of the previous status of the request

Description

The system displays the status of the 'Sanction Previous Status'.

Sanction Response Status

The external system displays the sanction response status. On update of this field the current status also gets updated. If the current status is updated manually, the system does not update the response status.

Description

The system displays the description of sanction response status.

Sanction Response Date

The system displays the sanction response date.

Click 'OK' to change the status of the record. Authorization status of the record is decided based on the auto auth flag maintained at branch level. If auto auth is enabled at branch, User ID and Function ID levels, then the record will be auto authorized. Else the checker has to authorize using the Authorize sub-screen.

Once a user changes the status of a record, the same user can change the status of the same record any number of times. The system does not allow another user to do the status change before authorization.

You can view the following details of each record:

- Party Type
- Name
- Address
- Country Code
- BIC
- Member ID
- DOB
- Fax
- Phone Number

- Mobile Number
- National ID
- Passport Number
- SSN
- Tax ID
- E mail

12.3.3 Viewing Sanction Check Status Change History

Click 'Status Change History' button from 'View Status Change' sub screen to invoke 'Sanction Check Status Change History' screen.

You can view the history of status change done on the request in this screen:

- Sanction Reference Number
- Branch Code
- From Status
- Status Description
- To Status
- Status Description
- Maker ID
- Maker Date and Time
- Maker Remarks
- Authorizer ID
- Auth Date and Time
- Auth Remarks

12.3.4 Authorizing Sanction Check Status Change

Click 'Authorize' button from 'Sanction Check Queue' screen to invoke 'Sanction Check Status Change Authorize' screen. You can authorize the status change action performed in the queue using this screen. You can view the following details in this screen:

- Sanction Reference Number
- Branch Code
- Sanction Current Status

- Description
- Sanction Previous Status
- Description
- Maker ID
- Date Time
- Maker Remarks
- Auth Remarks

12.4 **Sanction Check Request Process**

The system allows you to perform sanction check on the following entities:

- Customer
- Customer address
- Customer Account- Conventional and Islamic
- Customer account address
- Term deposit/recurring deposit - Conventional and Islamic
- Cheque Book Maintenance
- Financial Inclusion Customer Account
- Origination for Corporate Customer Creation process flow, Term Deposit Creation process flow, Current and Savings Account process flow, Retail Lending process flow, Islamic Corporate Financing process flows and Islamic Retail Financing process flows

Sanction check request is sent only if the flag 'Sanction Check Required' is checked from the branch level. Sanction check is done during New, Modify and Reopen operations.

The system displays the sanction check status as 'Not required' by default. On sending the request for sanction check, the status is updated as 'Pending'. Modification and authorization are not allowed on the record when it is in 'Pending' status. The sanction check request is placed in the sanction check queue and this request is sent to external system. The response from external system is updated in the sanction check queue by the external system against the sanction check reference number.

The final status can be either 'Approved' or 'Rejected'. When the sanction check status is 'Rejected', a configurable error is displayed during authorization of the entity.

The system allows you to change the status manually from the Sanction Check Queue Maintenance screen under below conditions:

- From any Interim Status to any other Interim Status
- From any Interim Status to any other Final Status

You can process sanction check request for a new customer, existing customer and reopening of an existing customer based on the maintenance at customer level.

This section contains the following topics:

- [Section 12.4.1, "Processing Sanction Check Request for a New Entity"](#)
- [Section 12.4.2, "Processing Sanction Check Request for an Existing Entity"](#)
- [Section 12.4.3, "Processing Sanction Check Request for Reopen of an Existing Entity"](#)
- [Section 12.4.4, "Sanction Check Notification to External System"](#)
- [Section 12.4.5, "Periodic Sanction Check Request"](#)

12.4.1 Processing Sanction Check Request for a New Entity

The following table describes various statuses and allowed actions for different statuses for a new entity

Status\Action	Modify	Authorize	Delete
Pending	No	No	Yes
Approved	Yes	Yes	Yes
Rejected	Yes	Configurable error message displayed which can be maintained as an override message also.	Yes

For a tanked record:

- If there are multiple unauthorized modifications, then during authorization system considers the sanction check status of the final modification. You cannot authorize a sanction check approved modification which is not latest.
- You can reject the tanked records irrespective of the sanction check status.

12.4.2 Processing Sanction Check Request for an Existing Entity

The following table describes various statuses and allowed actions for different statuses for an existing entity:

Status\Action	Modify	Authorize	Delete (Tanking allowed)
Pending	No	No	Yes
Approved	Yes	Yes	Yes
Rejected	Yes	A configurable error is displayed	Yes

When a customer is copied, sanction check status will not be copied to the new customer. For the new customer the status will have the default value 'Not Required'.

For existing records, sanction check will be sent only if the party details are changed. In case of modification, sanction check request is sent only if some relevant fields are changed.

12.4.3 Processing Sanction Check Request for Reopen of an Existing Entity

If an existing entity is reopened, then sanction check request is send. In case of reopen, system sends sanction check request based on the branch level flag.

12.4.4 Sanction Check Notification to External System

You can send sanction check request to the external system and receive response on it. A scheduler job picks the sanction check queue data source through which you can fetch all the records for which the sanction check current status is 'Pending' and response status is 'Null'.

For each of this record, system generates a sanction check request and posts it to the request queue.

Response from the external queue can be in synchronous or asynchronous mode.

- In Synchronous mode, system sends the request to the request queue and waits for the response. Once the response is received, system updates the internal sanction check queue screen. The waiting time for the response is based on the value that is maintained at 'Sanction Check System Maintenance' screen.
- In Asynchronous mode, system sends the request to the sanction check queue and does not wait. A MDB bean listens to the response queue for the response and processes the same.

12.4.5 Periodic Sanction Check Request

Oracle FLEXCUBE allows you to send periodic sanction check request through generic interface architecture. The periodic sanction check request will be send for the following entities:

- Customer
- Customer Account - Conventional and Islamic
- Term Deposit creation (Conventional and Islamic)
- Customer Account Address
- Customer Address

If the 'Sanction Check Required' flag is checked, then periodic sanction check should be done for each of the above entities. You can maintain frequency of execution in Generic Interface Definition screen (GIDIFTDF). Based on the specified frequency, during EOD system generates flat file with data for each of the entities. These files are placed in the path mentioned in Interface Definition screen.

13. Currency Maintenance

This chapter contains the following sections:

- [Section 13.1, "Handling Euro"](#)
- [Section 13.2, "Maintaining Sequence Generation Format"](#)
- [Section 13.3, "Maintaining Corporate Deposits Currency Limits"](#)

13.1 Handling Euro

This section contains the following topics:

- [Section 13.1.1, "Maintaining Euro Related Information"](#)

13.1.1 Maintaining Euro Related Information

On 1 January 1999, eleven countries that are part of the European Union embarked on the first phase of economic integration, called the 'Economic and Monetary Union' (EMU). In Oracle FLEXCUBE, the eleven countries participating in the first phase of the EMU are referred to as 'In' countries and the respective national currencies as 'In' currencies. All other countries are referred to as 'Out' countries.

The first phase of the EMU, referred to as the 'transition period', ushered in a new, single European currency: the **Euro (EUR)**. During this phase, the National Currency Denominations of 'In' countries would co-exist with the Euro. That is, transactions involving an 'In' currency would, typically, be routed through the Euro during this phase. At the end of the transition period, in mid 2002, however, the national currencies of the participating countries would cease to exist as valid legal tenders. The Euro would be the only legal tender in 'In' countries.

In Oracle FLEXCUBE, you can handle the Euro and the attendant implications for your bank, by capturing additional currency and settlements related information. This chapter details how this information is to be captured, and its implications.

In Oracle FLEXCUBE, the details that you need to maintain in order to handle the EMU include:

- Maintaining Euro as a valid currency
- Indicating if a currency is 'In', 'Out', 'Euro', or 'Euro Closed'
- Maintaining Currency Redenomination details
- A common conversion GL and a transaction code to identify the redenomination entry
- Maintaining a 'Tolerance Limit' for a currency (to check against ERI information)
- Capturing additional settlement details (Euro related information for the MT 100 and MT 202 SWIFT messages)

You can maintain currency related information in the Currency and the Currency Pair Definition screens. 'Settlement' details can be captured in the Settlement Instruction Details screen.

13.1.1.1 Maintaining Currency Details

Your specifications for a currency in the Currency Definition screen determine the manner in which transactions in the currency are handled in Oracle FLEXCUBE.

Currency Type

When maintaining a currency in the Currency Definition screen, you have to specify the 'type' of the currency. You can do this in the 'Euro Type' field. Choose the appropriate option from the following:

- The Euro itself
- An 'In' currency
- An 'Out' currency
- 'Euro Closed'

National currencies of 'In' countries are referred to as 'In' currencies. When maintaining other currencies, you have to choose the 'Out Ccy' option under Euro Type.

When the transition period ends, the national currencies of the participating countries would cease to exist as valid legal tenders. The Euro would be the only legal tender in the participating countries. Consequently, the Euro changes made to Oracle FLEXCUBE will no longer be required.

You can turn off the changes at the end of the transition period by:

- Closing all 'In' currencies, and
- Choosing the 'Euro Closed' option (for the Euro)

The screenshot shows the 'Currency Definition' window with a 'New' record. The form includes the following fields:

- Maintenance Country *
- Currency Code *
- Currency Name
- Currency Type
- ISO Numeric Currency Code
- Currency Country
- Decimals
- Interest Method (30-Euro/360)
- Spot days
- Foreign Exchange Netting Days
- Settlement Message Days
- Position GL
- Position Equivalent GL
- Tolerance Limit
- Index Base Currency

On the right side, there are additional fields: Maintenance Country Name and Alternate Currency Code.

The bottom status bar shows: PC | Currency Country Mapping | Fields. Below this is a table with the following columns: Maker, Date Time, Mod No, Record Status, Checker, Date Time, Authorization Status. An 'Exit' button is located in the bottom right corner.

Tolerance Limit

When you are maintaining an 'In' Currency, or the Euro, in the Currency Definition screen, you can define a 'Tolerance Limit' for it. The limit is expressed as a percentage.

The Implication:

During the transition period, settlements of components in 'In' currencies can be made either in the same currency or in the Euro (EUR) depending on the settlement account(s) maintained. (Similarly, components in Euro can either be settled in EUR or in an 'In' currency.) In the settlement messages that are generated (MT 100, MT202), the settlement amount would be reported in the Settlement Account Currency. However, you can opt to additionally furnish the value of the component in Euro Related Information (ERI) currency. You have to

manually specify the settlement amount value, in the ERI currency, in the Settlement Message Details screen.

When generating the message towards settlement (MT100, MT202), the system ensures that the value you specify as the ERI Amount conforms to the Tolerance Limit defined for the ERI Currency (in the Currency Definition screen). That is, the system computes the ERI equivalent of the settling amount using the pegged rates, and compares the same against the ERI amount input by the user. If the difference is within the tolerance limits defined for the ERI currency, the user specified amount is used.

If the user specified ERI amount breaches the Tolerance Limit defined for the ERI currency, the system calculates and reports the ERI Amount on the basis of the exchange rate defined for the settlement currency vis-à-vis the ERI currency.

The following example illustrates the application of the Tolerance Limit.

Note

The system validates the ERI amount only when generating the settlement messages. It does not validate the ERI amount at the time of input (in the Settlement Message Details screen).

Currency pairs

In the Currency Pair Definition screen, you can specify a 'Through Currency'. When maintaining a pair involving an 'In' currency ('In' – 'Out' and 'In' – 'In'), you can only specify the Euro as the 'Through Currency'.

Note

You cannot maintain a 'Through Currency' for a pair constituted by an 'In' currency and the Euro.

13.1.1.2 Maintaining Conversion GLs

To facilitate the currency conversion process, two additional parameters need to be maintained in the 'Branch Parameters' screen. You have to maintain a common Conversion GL and a Transaction Code that identifies redenomination entries.

The screen is as shown below:

Indicating Euro Redenomination General Ledger

Conversion GL

The conversion GL that you specify will be identified as the common Suspense GL for all balance conversions while re-denominating the currency of an account either for specific customers or for generic conversions.

Transaction Code

In addition to the conversion GL, you have to indicate a Transaction Code, which identifies conversion related entries.

13.1.1.3 Implications of Currency Redenomination

In the IC Product Accounting Role Definition screen

For the purpose of currency conversion, an accounting role called 'Acquired' is available.

End of day processes

Maintaining a Conversion GL and Transaction Code simplifies the End of day process. Basically two important things happen when the End of day processes are run. Firstly interest is liquidated to the Acquired Interest GL and secondly all balances will be reduced to zero.

When you run the Beginning of day processes the next day the change in the currency conversion will be in place. In addition balances will get restored.

Change in field values due to conversion

The change in currency re-denomination impacts amount based fields pertaining to Accounts, Collaterals, Credit Lines and Customer Limits. The change in the value of these fields is reflected when you run the beginning of day processes.

The amount-based fields, which are affected by the change in currency denomination, will be updated with the equivalent value in the new currency

Accounts

The following fields will reflect the new values:

- Temporary Over Draft limit
- Sub-limit
- Uncollected Funds limit
- Offline limit
- Account Currency

These fields can be found in the Customer Accounts Maintenance screen.

Collateral

In the Limits Maintenance Collaterals screen the following fields will be updated:

- Collateral Currency
- Collateral Value
- Limit Contribution
- Issuer Exposure Amount

Credit Lines

In the Limits screen of the Limits Maintenance module the following fields will reflect the new values:

- Credit Line Currency
- Tenor limits
- Tenor utilization
- All Related Amounts

Customer Limits

In the Customer Maintenance screen of the Core Services module the following fields will be updated at BOD.

- Limit Currency
- Liability Risk Limit
- Customer Risk Limit

Note

Once the conversion process is complete the advices generated for your customer will carry the following information:

- The Old Value
- The New Value
- And the Exchange Rate used for the conversion

As a consequence of currency re-denomination you will not be able to pass entries where the value date falls before the currency conversion date.

13.1.1.4 Specifying Preferred ERI Currency for Counterparty

For a counterparty and currency (combination), you can maintain a preferred ERI currency. You can state this preference in the 'Settlement Instructions' screen.

The Implication

During the transition period, settlements of components in 'In' currencies can be made either in the same currency or in the Euro (EUR) depending on the settlement account(s) maintained. (Similarly, components in Euro can either be settled in EUR or in an 'In' currency.) In the settlement messages that are generated (MT 100, MT202), the settlement amount would be reported in the Settlement Account Currency. However, you can opt to additionally furnish the value of the component in Euro Related Information (ERI) currency. You can maintain this ERI currency (for a counterparty and currency combination) in the 'Settlement Instructions Maintenance' screen.

In the SWIFT messages that are generated towards settlement of a component (involving the counterparty and the currency), the component value will be expressed in this (ERI) currency, by default. Invoke this screen by typing 'ISDINSTN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

Settlement Instructions Maintenance

New

Counterparty * 000054
Counterparty Name 000054
Counterparty CF
Currency * ALL
Branch * ALL

Module * AL
Product Code * ALL
Sequence Number 0
Relations
Settlement Instruction Description DEFAULT

Pay

Branch AT1
Currency GBP
Account CORE_M
Description 000054 - AT10000540018
Payment By Messages

Receive

Branch AT1
Currency GBP
Account 2016-01-01 00:06:10
Description 000054 - AT10000540018
Payment By Messages

Cover Required
Cover By
Charges Details
Ourselves
Beneficiary
Shared

Pay Parties Pay Parties Receiver Parties Cover Parties Clear Details Cover Details Other Details

Intermediary Reimbursement Institution

Intermediary

Country

Country

Intermediary

Fields

Maker CORE_M
Checker 3
Date Time: 2016-01-01 00:06:10
Mod No
Record Status
Authorization Status
Exit

13.1.1.5 Specifying Settlement Message Details

SWIFT messages (MT 100/MT202) generated towards settlement can furnish the value of the settlement amount in both the settlement account currency, and an 'ERI' currency. If you opt to furnish the ERI value of the amount, you have to enter the following in the 'Settlement Details' screen:

- The ERI currency
- The ERI Amount

The screen appears as shown below on clicking 'Settlements' button in the contract screen:

The system defaults to the ERI currency specified for the customer and currency combination. You can change the default ERI currency. The ERI amount that you specify will be validated against the Tolerance Limit specified for the ERI currency.

13.1.1.6 Settlements of Foreign Exchange Deals

Oracle FLEXCUBE allows cross currency settlements of foreign exchange deals that involve an 'In' currency. You can settle the 'In' currency leg in another 'In' currency or in 'Euro'.

13.1.1.7 Reports and Advices

The following reports furnish the equivalent Euro values of amounts in an 'In' currency. The 'locked in' exchange rates defined for the Euro against the 'In' currency will be used for currency conversions.

The reports with this feature are the:

- Currency Position report
- Cash Flow report
- FX Maturity report

Note

These reports will not furnish the 'In' currency and equivalent Euro values when you close the 'In' currencies, and choose the 'Euro Closed' option (for the Euro) in the Currency Definition screen.

All advices that provide 'In' currency details will also provide the equivalent Euro values

Account Statements

Statements provided for accounts in an 'In' currency provide the Euro equivalent values of the following:

- The opening balance
- The closing balance

- Every transaction

13.1.2 Maintaining Limits Type

You can maintain various static types and their values through the 'Static Type Maintenance' screen. You can invoke this screen by typing 'CODTYPES' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

Fields	
Maker	Date Time:
Checker	Date Time:
	Mod No
	Record Status
	Authorization Status

Type

Specify the limit type for which you want to maintain values

Description

Specify the description for the limit type you are maintaining

Values

The values for the limit type that you are maintaining can be listed here. To add a value to the list of values, click on the 'Add' icon, and type the value. To remove a value from the list of values, check the box against that value and click on the 'Delete' icon.

Value

Specify the list of supported values. For example, MAIL, COURIER, BRANCH and so on.

Code

Specify the codes for the list of value. For example, CO, ML and so on.

13.1.3 Maintaining Transaction Limits

This section explains in detail about maintaining transaction limits, level of authorisations required for the transaction amounts and minimum user authorisation limit required for a transaction.

Oracle FLEXCUBE offers you a facility, whereby, each time a particular transaction processed in the system exceeds a certain limit; an override will be generated by the system.

You can maintain transactional limits for a module and product combination through the 'Product Transactional Limits Maintenance' screen. Invoke this screen by typing

'CSDPLMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen appears as shown below:

Product Transaction Limits Maintenance

New

Module Identification * BC LBL_SOURCE_CODE * FLEXCUBE

Module Description Bills and Collections Transaction Limit Currency * GBP

Product Code * ISLP Customer Type * All

Product Description INCOMING CLEAN SIGHT Customer Group * ALL

Role Based Authorization

Follow Sequence

Product Transaction Limit Details

1 Of 1 Go

Transaction Limit *	Level of Authorization	Minimum Authorization Limit	Cumulative
20000	2	20000	

Fields

Maker YAMUNA5 Date Time: 2014-01-01 10:47:01 Mod No 1 Record Status Open

Checker YAMUNA3 Date Time: 2014-01-01 10:47:34 Authorization Authorized Status

Exit

Module Identification

Each module in Oracle FLEXCUBE is identified by a code. First, you have to identify the module for which the currency-wise transactional limit is to be maintained. A list of all the modules operational at your bank will be displayed in the option list. You can choose the appropriate module code.

Module Description

The description associated with the module will be defaulted in the adjacent field.

Product Code

Each module contains a number of products within it. After you identify the module, indicate the product within the module for which you would like to maintain a currency-wise transactional limit. You can select the appropriate product code from the option list.

In the Product Transactional Limits screen, you can maintain the limits for:

- A specific module and a specific product
- A specific module and all products (select 'ZALL' as the Product Code)
- All modules (Select 'AL' as the Module Code) and all products

Product Description

The description associated with the module will be defaulted in the adjacent field.

Source Code

Specify the source code based on which you need to maintain the product transactional limits. The adjoining option list displays all valid source codes. The transaction limit amount maintained for the selected source code is used to validate transaction limit while authorizing the contract.

If the source code is available in Oracle FLEXCUBE, then the system enables all the fields available under 'Product Transaction Limit Details' multi grid.

If the source code external, then the system enables only 'Transaction Limit' available under 'Product Transaction Limit Details' multi grid.

Note

You cannot select a source code more than once.

Transaction Limit Currency

The transaction limit currency is the currency in which you would like to maintain the amount limit.

Customer Type

Select the type of customer for whom you are maintaining the transaction limits from the adjoining drop-down list. The following are the options available:

- Corporate
- Individual
- Bank
- All

Customer Group

Specify the customer group to which the authorization matrix is applicable. Alternatively, you can select the customer group from the option list. The list displays all the customer group maintained in the system.

Role Based Authorization

Check this box to authorize the transaction based on the roles defined in 'Authorization Role Mapping' section.

If you select this check box, it is mandatory to define authorization rules in the 'Authorization Role Mapping' section.

Follow Sequence

Check this box to follow a sequence during various levels of multiple authorization of a transaction. This field is enabled if the 'Role Based Authorization' is checked.

Product Transaction Limit Details

Specify the following transaction limit details:

Transaction Limit

Specify a transaction limit. Each time you process a transaction, the system checks the transaction amount involved in the contract against the limit specified here. If the contract currency is different from the transaction limit currency, then the system converts the contract amount using the standard mid rate to the transaction limit currency and check against the transaction limit amount maintained for the product

The system displays an appropriate message indicating the levels of authorization if the transaction amount booked is in excess of the maintained transaction limit.

Level Of Authorization

Specify the levels of authorization to be involved in the authorizing a particular transaction amount.

Note

The level of authorization should be greater than one. If the number of authorization levels are greater than five, the system displays an error message.

Minimum Authorization Limit

This option is enabled only if the 'Cumulative' option is checked. Specify the minimum authorization limit required for a transaction. The authorization limit cannot be greater than the transaction limit. This amount is used to validate authorizer limit while authorizing the contract.

Cumulative

Check this option to indicate that multiple authorisers are allowed to authorise a transaction. The authorisers must have equal or greater than the minimum authorization limit maintained in this screen. The system displays an appropriate error message if the authoriser tries to authorise a transaction having transaction amount greater than the minimum authorising limit.

This field is not applicable if you check the 'Role Based Authorization' check box,

Authorization Role Mapping**Authorization Rule**

The system displays the authorization rule maintained in the system. The list displays the following values:

- Primary - To authorize the transaction level.
- Alternate - To authorize the transaction for the respective level in addition to the users attached to the role in Primary rule.

Level 1

Specify the user role eligible to authorize the transaction in the first level.

Level 2

Specify the user role eligible to authorize the transaction in the second level.

Level 3

Specify the user role eligible to authorize the transaction in the third level.

Level 4

Specify the user role eligible to authorize the transaction in the fourth level.

Note

For Primary rule, you should specify the role for at least one level.

13.1.3.1 Validating Transaction Amount during Contract Processing

While saving a contract, the system will check the transaction amount against the cut-off amount maintained for the module and product currency involved in the transaction. If both the transaction currency and the limits currency are same, the comparison will be done directly. If different currencies are involved, the system will first convert the transaction amount into the cutoff amount currency using the STANDARD mid rate and then perform the validations.

To perform the check, the System will look for the limits maintained, in the following order:

1. The System looks for the limits maintained for a specific module and specific product combination

2. If the first option is not available, it checks the limits maintained for a specific module + ZALP (all products) combination
3. It checks the maintenance for AL (all modules) + ZALP (all products) combination

If the third option is also not available, the system displays an error message

When a transaction exceeds the amount limit, the system displays an override message while saving the transaction

13.2 Maintaining Sequence Generation Format

Every contract in Oracle FLEXCUBE is identified by a unique Contract Reference Number that is generated internally by the system. You are not allowed to modify this number. In addition, a contract is also identified by a unique User Reference Number. By default, the Contract Reference Number will be taken as the User Reference Number. But you have the option to change the User Ref Number.

Oracle FLEXCUBE also provides you the facility to generate the user reference number in a specific format.

To maintain a specific format, you need to identify the various components that would be part of the user reference number including details such as the length, order, value etc. of each component.

You can maintain a unique format through the 'Sequence Generation Input' screen. You can invoke this screen by typing 'CSDSQGEN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen appears as shown below:

You can maintain the following details of the sequence format:

Sequence Code

Each sequence format is identified by a unique sequence code. You can devise a code comprising a maximum of 20 alphanumeric characters.

Branch Code and Module Code

You can maintain the format for a specific branch and module combination. Select the branch code and the module code from the option-list. All authorized and active records will be displayed in the list.

Alternatively, you can maintain a sequence format that will be applicable to all the branches (ALL) and all the modules (AL) available in your bank.

Reset Frequency

You need to specify the frequency at which the system will drop and recreate the sequence numbers once again. At the reset frequency that you specify, all sequence numbers of the sequence format will be dropped and recreated again during the End of Day processing.

The options available are:

- None
- Daily
- Monthly
- Yearly

For example, let us assume that the running number in the sequence format is 4 characters long (starting from 0001) and the reset frequency is Monthly. Further, let us assume that the sequence number of the last contract processed on the last day of the month is 0199. At EOD of the last day of the month, the sequence numbers generated till date will be dropped and the system will begin regeneration starting from 0001 once again for all subsequent contracts.

Range

You can specify a range of sequential reference numbers. If you specify such a range, then no additional details need be specified. If you do not specify a range, you can specify additional details specific to each component of the sequence format.

In addition to the above details, you should also maintain details specific to each component of the sequence format. The details are as follows:

Component Order

Each component is assigned an order number based on which they would appear in the user reference number. The component order is automatically generated by the system and is non-editable.

Component

Each component in the sequence format is identified as one of the following:

- An Oracle FLEXCUBE Component – If your sequence format uses an Oracle FLEXCUBE column directly, you can specify it as an Oracle FLEXCUBE Component. For instance, you may want to include the product group associated with the product code involved in a contract, as a component in sequence number generation. To achieve this, you will use the Oracle FLEXCUBE column `PRODUCT_GROUP` (available in the table `CSTM_PRODUCT`) as an Oracle FLEXCUBE Component.
- A User Component – You may want the first two characters of your bank's name to be part of all the user reference numbers generated at your bank. You can define it as a user component. In addition, if you want to use the manipulated value of an Oracle FLEXCUBE Column in the sequence format, you can specify it as a User Component. For eg, you may want to include ONLY the first four characters of the product group in

the sequence number. In this case, the component would be defined as a User Component.

- A Separator – To separate the various components from one another, you can use the component known as the separator. Eg: a back slash, a hyphen etc.
- A Running Number – Each contract is identified by a unique sequence number. It is mandatory to maintain a running number as a component in the sequence format. If not included, you will not be allowed to save the details of the format. A running number is internally generated by the system.

Component Type

You need to identify the type of each component in the sequence format. A component can be constant through out or change for every contract processed at your bank. You can associate a component with one of the following types:

- Static – To include any hard coded component in the sequence format, you will specify the type to be static. For instance, you may want the first two characters of your bank's name to be part of all the user reference numbers generated at your bank. The component type would be static in this case.
- Dynamic – You will specify the component to be of the dynamic type if its value is picked up from the Oracle FLEXCUBE table. Eg: Product Group. A running number would always be dynamic in nature.

Use in Sequence Generation

You need to indicate whether the component being defined should be used in sequence generation or not. Specify 'YES' or 'NO' as per your choice.

You can also choose to display the reference number in the advices that are generated for a contract.

Component Length

You can also specify the length of each component in the sequence format. The component value is dependent on the component length maintained. For instance, if you specify 2 as the component length, the value should comprise of only two characters.

Component Value

As stated earlier, the component value is dependent on the component length. Based on the length, you can specify a value comprising of as many characters as specified in the Component Length field. However, this field is used only if the value of the component is required to be constant (static type) in all the user reference numbers generated at your bank. If the component value is changing constantly (Dynamic type) for every contract, the system will automatically pick up the value from the DB table based on the SQL query that you maintain for the purpose.

Component Column and Component Table

If your component is of the dynamic type, you will need to mention the name of the Oracle FLEXCUBE column from where the system will pick up the component value. Further, if you wish to include a manipulated column value in sequence generation, you will need to include 'SUBSTR' as well in the column name. For eg, to include only the first four characters of the product group associated with the product code involved in a contract, you will specify the following in the Component Column field:

SUBSTR (PRODUCT_GROUP, 1, 4)

You need to mention the table name also, if the component type is dynamic. The following table names are available in the option-list provided.

- DUAL
- STTM_BANK

- STTM_BRANCH
- CSTM_PRODUCT

For our example, the table name would be CSTM_PRODUCT.

Component Where Clause

The condition or the 'where clause' of the SQL code is specified here. In the example discussed above, the system will pick up the appropriate product group depending on the product code involved in the contract being processed. You can specify the following where clause as an extension of the SQL statement specified earlier:

WHERE PRODUCT_CODE = SUBSTR (P_CRN, 4, 4);

Click add icon to define each subsequent component in the format. Use the navigating icons to move between the various components of a sequence format.

13.3 Maintaining Corporate Deposits Currency Limits

You can invoke the 'Corporate Deposits Currency Limits Maintenance' screen by typing 'CSDXCCLM' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The 'Corporate Deposits Currency Limits Maintenance' screen is shown below:

You can specify the following here:

Start Date

You need to specify the period for which the limit maintenance is applicable. Select the start date of the period here.

End Date

You need to specify the period for which the limit maintenance is applicable. Select the end date of the period here.

Type

Select the type of fund flow to which the limit should be applied.

Customer Number

Specify the CIF of the customer for whom the currency limit should be applied. You can select the appropriate CIF from the option list.

Currency

Specify the currency code for which the limit should be applied. You can select the appropriate currency code from the option list.

Limit Amount

Specify the limit amount. The customer will be allowed to transact using the selected currency for a maximum of this limit amount.

Amount Utilized

The system displays the amount that has already been utilized by the customer.

Once you have captured the details, save the maintenance.

Currency Maintenance explained in this chapter are specific to Oracle FCUBS. For more details on Currency, Currency Pair and Currency Rates Maintenance refer Common Core - Core Entities and Services User Guide.

14. Currency Denomination

In the Data Entry module, you can specify a break up of a transaction amount for Teller transactions by denomination. The system also maintains a break-up of the till balances by denomination.

This chapter contains the following sections:

- [Section 14.1, "Currency Denomination Maintenance"](#)
- [Section 14.2, "Maintaining Denomination-wise Variance"](#)

14.1 Currency Denomination Maintenance

This section contains the following topics:

- [Section 14.1.1, "Maintaining Currency Denomination Details"](#)
- [Section 14.1.2, "Operations Allowed in the Currency Denomination Screen"](#)

14.1.1 Maintaining Currency Denomination Details

In the 'Currency Denomination' screen, you can maintain the standard currency denominations for each currency that your bank deals with. You can invoke this screen by typing 'CSDDEMAN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot displays the 'Denomination Details' window. At the top, there's a 'New' button and an 'Enter Query' section. The 'Enter Query' section includes fields for 'Denomination Type' (set to 'Cash'), 'Currency Code' (set to 'AED'), 'Currency Description' (set to 'UAE Dirham'), 'Issuer Code' (set to '0000'), and 'Issuer Description' (set to 'Bank Futura'). Below this is a 'Denomination Details' table with columns: Denomination Id, Denomination Description, Denomination Value, Sequence Number, and Type. The table lists six denominations: AED1 (ONE AED, Value 1, Note), AED2 (TEN AED, Value 10, Note), AED3 (HUNDRED AED, Value 100, Note), AED4 (THOUSAND AED, Value 1000, Note), AED5 (POINT ZERO ONE, Value .01, Coin), and AED6 (POINT ONE, Value .1, Coin). At the bottom, there's a status bar with fields for 'Maker' (LAKSHMI_MAK), 'Checker' (LAKSHMI_AUTH), 'Date Time' (2014-01-01 13:36:44 and 2014-01-01 13:37:15), 'Mod No' (2), 'Record Status' (Open), and 'Authorization' (Authorized Status). An 'Exit' button is located in the bottom right corner.

Denomination Id	Denomination Description	Denomination Value	Sequence Number	Type
AED1	ONE AED	1	1	Note
AED2	TEN AED	10	2	Note
AED3	HUNDRED AED	100	3	Note
AED4	THOUSAND AED	1000	4	Note
AED5	POINT ZERO ONE	.01	5	Coin
AED6	POINT ONE	.1	6	Coin

To maintain the denominations of a currency, you need to specify the following:

- The code of the currency for which you are defining denominations
- A unique code to identify each denomination of the currency. For example, you can assign D1, D10, D50 for USD 1, 10, 50.
- A description of the denomination unit
- The denomination type coin or note
-

- The value of the denomination in relation to one unit of the currency. It could be a fraction for coins

For example, for the currency USD you can maintain the denominations as follows:

CURRENCY CODE	DENM CODE	DESCRIPTION	VALUE	NOTE / COIN
USD	D100	100 dollars	100.00	NOTE
USD	D50	50 dollars	50.00	NOTE
USD	D20	20 dollars	20.00	NOTE
USD	D10	10 dollars	10.00	NOTE
USD	D5	5 dollars	5.00	NOTE
USD	D1N	1 dollar Note	1.00	NOTE
USD	D1C	1 dollar Coin	1.00	COIN
USD	C25	25 cents	0.25	COIN
USD	C10	10 cents	0.10	COIN
USD	C5	5 cents	0.05	COIN
USD	C1	1 cent	0.01	COIN

Denomination type Millionaire certificate is used to facilitate MC/LMC (Millionaire Certificate) transactions. You can have only one denomination with denomination type as 'Notes' and the currency code should be the LCY code of each country..

14.1.2 Operations Allowed in the Currency Denomination Screen

Following standard maintenance operations are possible in the 'Currency Denomination' screen:

- Add
- Modify
- Delete
- Authorize
- Close
- Re-open
- Inquiry
- Logs all maintenances in the Audit Trail.

14.2 Maintaining Denomination-wise Variance

You may need to apply different exchange rates to the same currency based on the denomination. You can maintain the variance in the exchange rate to be applied on the buy and sell leg of currency transactions using 'Denomination Wise Currency Variance

Maintenance' screen. To invoke this screen, type 'CSDDEVAR' in the field at the top right corner of the application toolbar and click the adjoining arrow button.

Specify the following details:

Currency 1

Specify the currency pair for which the denomination-wise exchange rate variance should be applied.

The option list displays all valid currency pairs maintained in the system. You can select the appropriate currency code from the option list.

Based on the currency pair selected, the system displays the currency 2, which is the second currency of the currency pair.

Description of Currency 1

The system displays the description of the first currency.

Currency 2

The system displays the currency code of the second currency, for on the currency pair selected in the field 'Currency 1'.

Description of Currency 2

The system displays the description of the second currency.

Denomination Variance for Currency 1

Rate Type

Specify the rate type for which the denomination based variance should be applied. The option list displays all valid rate types maintained in the system. You can select the appropriate one.

Denomination

Specify the denomination for which the variance should be applied. This should be the denomination of the currency selected in the field 'Currency 1'. The option list displays all valid denominations maintained in the system. Select the appropriate one.

Buy Variance

Specify the buy variance that should be applied for the selected denomination and currency pair. This variance will be applied to the second currency when one unit of the first currency is bought against the second currency.

The buy variance must be specified in terms of points. It can be a positive or negative value.

Sell Variance

Specify the sell variance that should be applied for the selected denomination and currency pair. This variance will be applied to the second currency when one unit of the first currency is sold against the second currency.

The sell variance must be specified in terms of points. It can be a positive or negative value.

Note

In order to enable denomination based variance for a function ID, you must set the required parameter to 'Yes' in 'CSTM_BRANCH_LOC_PARAMS and FBTB_PARAMS'. You can set this parameter to 'Yes' for the following transactions:

- Purchase of foreign currency against CASA account (8207)
 - Sale of foreign currency against CASA account (8206)
 - Purchase of foreign currency by walk-in customer (8004)
 - Sale of foreign currency to walk-in customer (8203)
-

15. Maintaining Limits for Cross Currency Transactions

This chapter contains the following sections:

- [Section 15.1, "Specifying Limits for Cross Currency Transactions"](#)

15.1 Specifying Limits for Cross Currency Transactions

Typically, the exchange rates applicable for cross currency or teller transactions is defaulted by the system depending upon the preference indicated in the product preferences, for the product involving the transaction.

In your bank, for high-value cross currency transactions, you may want the user to manually enter the exchange rate involved, rather than let the system automatically pick up a default rate during transaction input.

You can define such a preference to be applicable to cross currency transactions involving:

- A currency pair
- A specific product, or all products
- A specific module, or all modules
- A specific branch, or all branches
- A specific rate code

The transaction amount limit, above which the exchange rate must be entered, for a high value transaction, could be defined in terms of currency pair where the currency of the transaction is currency1 in the CCY pair defined in the maintenance.

To ensure that users manually enter exchange rates for high-value cross currency transactions in Oracle FLEXCUBE, you must specify the limit amounts that must be validated for each transaction in terms of currency pair, product, module, and branch combination. You can use the 'Product Limits Maintenance' screen to specify the limits.

When you have specified these limits, the system automatically validates the amount with each transaction for the currency pair, product, module and branch combination, and accordingly, if the limits are exceeded, enforces the manual entry of exchange rates.

In case, the limit between ccy1 and ccy2 is given in ccy2, the system will automatically convert the transaction amount to an amount in ccy2 using standard mid rate and check against the limit amount whether or not manual entry of exchange rates is required. You can invoke the 'Product Limits Maintenance' screen, by typing 'CSDPXMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen appears as shown below:

Branch Code

You must specify the branch for which the limit amount will be applicable. You can specify that the limits must be applicable for all branches.

Module Code

You must specify the module for which the limit amount will be applicable. You can indicate that these limits must be applicable for the Data Entry (DE) module.

Product Code

You must specify the product, transactions involving which the limit amount will be applicable. You can specify that the limits must be applicable for all products.

Currency 1

You need to specify the currency1 applicable for defining the Transaction Amount limit, beyond which the system will not default the Auto Exchange Rate.

All valid currencies defined in the Currency Pair Maintenance will appear for selection. This currency is always the transaction currency of the contract.

Currency2

You need to specify the currency2 applicable for defining the Transaction Amount limit, beyond which the system will not default the Auto Exchange Rate.

All valid currencies defined in the Currency Pair Maintenance will appear for selection. The Currency2 should be part of a Currency Pair Maintenance in which the Currency1 defined here is the first currency. Currency 2 can be specified as ALL.

Specifying Limit Details

Rate Code

You need to specify the Rate Type (code) for the Exchange Rate Limit

Limit Currency

You need to specify the currency in which the Limit Amount should be expressed. All valid currencies defined in the system will be applicable for selection. There will be a validation for the limit currency as either Currency1 or Currency2.

Limit Amount

You need to specify the maximum amount up to which the system should default the Exchange Rate or perform the Rate Variance validation.

16. Limit Revaluation

This chapter contains the following topic:

- [Section 16.1, "Limits Revaluation Input"](#)

16.1 Limits Revaluation Input

This section contains the following topics:

- [Section 16.1.1, "Maintaining Limits Revaluation Details"](#)
- [Section 16.1.2, "Viewing Limit Revaluation Details"](#)

16.1.1 Maintaining Limits Revaluation Details

You can post revaluation entries from the Limits system using Limits Revaluation Input screen. You can invoke this screen by typing 'STDLMRVL' in the field in the top right hand corner of the application toolbar and clicking on the adjoining arrow button.

Limits Revaluation Input

New Enter Query

Reference Number
Transaction Branch
Module
Event Code *
Event Sequence Number
Source Code

Related Reference *
Transaction currency
Transaction Amount
Transaction Date YYYY-MM-DD
Value Date YYYY-MM-DD
Force Process No

1 Of 1 Go

☐ Serial Number Liability Number * Linkage Type * Linkage Reference No * Transaction Limit Currency Transaction Amount * Remarks

Input By Date Time Status
Checker Date Time Authorization Status Exit

Specify the following details here:

Reference Number

Specify the reference number of revaluation request.

Transaction Branch

Specify the transaction branch.

Module

Specify the module of the transaction.

Event Code

Specify the event code used for the revaluation.

Event Sequence Number

Specify the event sequence number.

Source code

Specify the source code of the system.

Related Reference

Specify the related reference number.

Transaction currency

Specify the transaction currency.

Transaction Amount

Specify the consolidated amount for the revaluation request.

Transaction Date

Specify the booking date of the transaction.

Value Date

Specify the value date.

Force Process

Select the force process to force post the entry.

Serial Number

Specify the serial number.

Liability number

Specify the liability number of the facility.

Linkage Type

Specify the linkage type.

Linkage Reference Number

Specify the limit reference number. Specify Line code + Line serial number for local facility.

Transaction Limit Currency

Specify the limit currency.

Transaction Amount

Specify the limit adjustment amount.

Remarks

Specify remarks if any for the revaluation.

Note

- Only new request can be initiated from this screen or through this service. Reversal of wrong adjustment entries should be operationally handled by posting another adjustment entry.
 - Limit system will initiate the revaluation web service only for the local facility.
-

16.1.2 Viewing Limit Revaluation Details

You can view the limit revaluation details in the 'Limits Revaluation Summary' screen. You can invoke this screen by typing 'STSLMRVL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Limits Revaluation Summary

Search Advanced Search Reset Clear All

Case Sensitive

Authorization Status Transaction Status

Reference Number Related Reference

Records per page 15 1 Of 1 Go Lock Columns 0

Authorization Status	Transaction Status	Event	Event Sequence Number	Reference Number	Related Reference	Source Code
----------------------	--------------------	-------	-----------------------	------------------	-------------------	-------------

Exit

In the above screen, you can base your queries on any or all of the following parameters and fetch the required records:

- Authorization Status
- Reference Number
- Transaction Status
- Related Reference

Select any or all of the above parameters for a query and click 'Search' button. The records meeting the selected criteria will be displayed.

17. Maintaining Currency Spread for Customer

This chapter contains the following section:

- [Section 17.1, "Currency Spread Maintenance"](#)

17.1 Currency Spread Maintenance

This section contains the following topics:

- [Section 17.1.1, "Maintaining Customer Spread Details"](#)
- [Section 17.1.2, "Maintaining Currency Margins for Customer"](#)

17.1.1 Maintaining Customer Spread Details

For a customer and currency pair, you can maintain tenor-wise spread details in the 'Customer Currency Spread Maintenance' screen.

You can invoke this screen by typing 'CYDCUSPR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Tenor *	Buy Spread	Sale Spread

In this screen, for a customer and currency pair, you can maintain buy and sell spreads for different tenors.

You need to maintain customer spreads in each branch. Transactions initiated in a branch will pick up the spread(s) maintained for that branch.

Note

- Loans and Deposit contracts have tenor = 0 (zero). Therefore, you need to maintain Customer Spreads for zero tenor also.
 - The tenor is specified in days
-

17.1.1.1 Specifying Spread Details

When processing an FX deal involving a customer (for whom you have maintained spread details), the system picks up the customer spread corresponding to the tenor of the deal and

builds it into the exchange rate. If spread details are unavailable for a specific tenor, the system picks up the spread defined for the nearest lower tenor.

For example, assume for a customer and currency pair you maintain spread details for the following tenors: '3', '5', and '10' days. When processing a deal with a tenor of '4' days (involving the customer and the currency pair), the system picks up the spread details defined for a tenor of three days. This is because spread details for a '4' day tenor is unavailable for the customer and currency pair.

Note

You can also maintain customer spreads for the wildcard entry – ALL. If spread details for a specific counterparty (for the currency pair) are unavailable, the System looks for the customer spread maintained for the wildcard ALL entry. If even that is not available, then the customer spread defaults to zero.

17.1.1.2 **Computing Buy and Sell Spreads**

Using percentage system -- suppose the bank wants to make a profit of 5% over and above the mid rate quoted. Suppose the dealing currencies are USD and AUD. 1USD = 1.4166 AUD for Standard rate type. (Mid rate being 1.4166). Now to arrive at the spread the bank will use the following formula:

$$\text{Spread} = 5 / 100 \times \text{Mid rate} (1.4166) = 0.07083$$

Using the points system -- suppose the point quoted by the bank is 708.3. The points multiplier in this case would be 0.0001 (depends on the decimal points that the mid rate extends to. Usually it is 4 decimal places).

$$\text{Spread} = \text{Points} (708.3) \times \text{Points Multiplier} (0.0001)$$

Now coming to the buy and sale rate computing, there are two ways of computing the buy and sale rates -- Direct and Indirect. Depending upon the quotation method you have specified in the Currency pair screen, the system computes the spreads.

In the **Direct** method, the buy and sell rates are calculated as follows:

$$\text{Buy Rate} = \text{Mid-Rate} - \text{Buy Spread}$$

$$\text{Sell Rate} = \text{Mid-Rate} + \text{Sell Spread}$$

For cross currency contracts, the rate for the currency pair is:

$$1 \text{ unit of Ccy 1} = \text{Rate} \times 1 \text{ unit of Ccy 2}$$

In the **Indirect** method, the buy and sell rates are calculated as follows:

$$\text{Buy Rate} = \text{Mid-Rate} + \text{Buy Spread}$$

$$\text{Sell Rate} = \text{Mid-Rate} - \text{Sell Spread}$$

For cross currency contracts, the rate for the currency pair is:

$$1 \text{ unit of Ccy 2} = \text{Rate} \times 1 \text{ unit of Ccy 2}$$

The method of spread definition – percentage or points – that you have maintained for the currency pair is displayed on this screen.

17.1.2 Maintaining Currency Margins for Customer

For each customer of your bank you can define buy and sell margins for a specific currency. This spread is applied to floating interest components that involve the customer and currency combination.

You can define buy and sell margins for a customer in the Customer Spread Maintenance screen invoked from the Application Browser. You can invoke this screen by typing 'CFDCUMRG' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The margin that you define will be appropriately picked up and applied to arrive at the final rate that is applied to floating components of contracts that involve the customer - currency combination.

The buy and sell margins that you define are for a customer and currency combination. You can select the customer and currency combination from the option lists available.

For the selected currency – customer combination, you can define amount slabs and specify a Borrow and Lend margin for each slab. To add a slab to the list click add icon and enter the slab details. To remove a slab from the list, highlight it and click delete icon.

Whenever you enter a contract in Oracle FLEXCUBE that involves the customer and currency combination, the appropriate spread is applied to arrive at the floating rate to be charged. The slab is selected based on the contract amount and depending on the nature of the contract, the Borrow or Lend spread is applied.

The screenshot shows the 'Customer Spread Maintenance' window. At the top, there are buttons for 'New' and 'Enter Query'. Below these are input fields for 'Customer*' and 'Currency*', each with a selection icon. To the right, there are radio buttons for 'Borrow/Lend', with 'Borrow' selected. Below this is a table titled 'Customer Spread Maintenance' with two columns: 'Amount Slab' and 'Spread'. The table has a scroll bar on the right. At the bottom of the window, there is a 'Fields' section with the following fields: 'Input By Date Time', 'Authorized By Date Time', 'Modification Number', and two checkboxes labeled 'Authorized' and 'Open'.

17.1.2.1 Making Margin Applicable to All Customers

For a given currency, you can define borrow and sell margins to be applied to All customers. At the customer field choose ALL. However, if you have maintained currency margins for a specific customer and currency combination, it takes precedence over the margin defined for all customers.

Currency margins can be maintained for customers across branches. In effect, a branch can maintain margins for a customer belonging to another branch. These margins are propagated across branches of your bank.

18. Cluster Deposits

A cluster deposit involves the input of a deposit as a multiple of specific units of a certain currency. All operations concerning the principal, like drawing up payment schedules for the principal, change in principal, etc., have to be in multiples of the cluster size specified for the deposit. For example, you want to make a deposit in clusters of USD 10. In such a case you cannot make a deposit of say, USD 1234. It has to be either USD 1230 or USD 1240, since it has to be a multiple of the cluster USD 10.

This chapter contains the following section:

- [Section 18.1, "Cluster Deposit Maintenance"](#)

18.1 Cluster Deposit Maintenance

This section contains the following topics:

- [Section 18.1.1, "Invoking the Deposit Cluster Maintenance Screen"](#)
- [Section 18.1.2, "Viewing Corporate Deposits Cluster Details"](#)

18.1.1 Invoking the Deposit Cluster Maintenance Screen

You can define and maintain clusters through the 'Deposits Cluster Maintenance' screen. You can invoke the 'Deposits Cluster Maintenance' screen by typing 'LDDCLUST' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Cluster Definition

New Enter Query

Cluster Id *
Description *

Cluster Details

Currency *	Min booking amount *	Booking Unit *	Withdrawal Unit *

Fields

Input By Date Time Authorized By Date Time Modification Number

Authorized Open

In this screen, define the following details:

Cluster Identification

Specify a Cluster ID to uniquely identify a cluster. This ID is used to associate a cluster with a product or a specific deposit.

Description

Enter a description for each cluster that you define. This will be displayed when you specify the cluster while defining a product or a contract.

Specifying Cluster Details

Currency

Specify a particular currency for each cluster that you define.

Min Booking Amount

Specify the minimum amount for which you need to book a deposit.

Booking Unit

Specify unit for booking a deposit in the cluster. The deposit amount would be a multiple of the booking unit.

Withdrawal Unit

Specify unit for partial withdrawal of amount from a deposit. The partial withdrawal amount before maturity would be a multiple of the withdrawal unit.

18.1.2 Viewing Corporate Deposits Cluster Details

You can view all the deposits cluster details using 'Deposits Cluster Summary' screen. You can invoke the 'Deposits Cluster Summary' screen by typing 'LDSCLUST' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Summary

Advanced Search Reset

Authorization Status Record Status

Cluster Id Description

Records per page: 15 First Previous 1 Of 1 Next Last Go

Authorization Status	Record Status	Cluster Id	Description
----------------------	---------------	------------	-------------

Authoriza... Record St... Exit

In this screen, specify the following details. Based on any of the below details, you can query the cluster details.

Authorization Status

This field indicates whether the cluster created is authorized or not.

Cluster Identification

Cluster ID is a unique identification of a cluster. This ID is used to associate a cluster with a product or a specific deposit.

Record Status

The record status can be either open or closed. A open record can only be used to associate with the product.

Description

The description is defined at the time of creating a cluster. While defining a product or a contract, It is displayed when you specify the cluster ID.

19. Period Code Maintenance

Banks, like all business houses compute their profits and losses and assess their financial position at the end of each financial year, which typically extends to 12 months -- from January to December or from March to April. However, this could be changed, depending upon the Bank's policies and regulatory requirements.

For interim reporting needs, the financial year is further divided into accounting periods, the duration of which is again determined by the bank's accounting requirements. For example, your bank's Board of Directors meets once a month therefore, you would divide the financial cycle into monthly periods.

The financial year and the accounting periods are referred to in the Oracle FLEXCUBE system as the 'Financial Cycle' and the 'Financial Periods' respectively and are maintained at the bank level by your Head Office branch.

At the end of each financial period and financial cycle you can generate profit and loss statement and a balance sheet. The system also offers you the flexibility of keeping a financial period/financial cycle open, allowing you to post adjustments to it and obtain a revised profit or loss statement/balance sheet. You can maintain these details in the 'Period Code Maintenance' screen.

This chapter contains the following section:

- [Section 19.1, "Period Code Maintenance"](#)

19.1 Period Code Maintenance

This section contains the following topics:

- [Section 19.1.1, "Maintaining Period Code"](#)
- [Section 19.1.2, "System Functions"](#)

19.1.1 Maintaining Period Code

You can invoke this screen by typing 'STDPRCDE' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen appears as shown below:

In this screen you define the following:

- The financial cycle of your bank giving the start date and end date of each financial year
- The period group - financial periods into which each financial cycle is to be divided

The following are the features of the Period Code screen

Financial Cycle

For each financial cycle you maintain the following parameters:

Cycle

This is a code for the financial cycle. It acts as an identifier for the cycle. For example, while posting adjustments into a previous financial cycle -- you would identify the year through this code.

Input the code using a maximum of 9 characters, alphanumeric.

For example, the financial cycle extends from 1st April to 31st March in India. A bank here could define its code for the year 1996-97 as FY 1996-97.

Description

This describes the financial cycle. Enter description using a maximum of 35 characters, alphanumeric. Taking the above example, you could enter Financial Year - 1996-97.

Start Date

This is the first day of this Financial Cycle

End Date

This is the last day of this Financial Cycle

Period Group

The financial cycle defined above, can be divided into different accounting periods. To define individual accounting periods click on the first row under period code. A period called 'FIN' is

created by the system. This is an open ended period coinciding with the last day of the financial cycle (for details refer to the section 'System Functions').

You can maintain the following parameters for each accounting period within a financial cycle:

Period Code

This code identifies the accounting period. Enter a code using a maximum of 3 characters, alphanumeric. For example, if your period length is a quarter you can enter - Q1 for the first period; Q2 for the second; Q3 for the third and so on. If your period length is a bimonthly you can enter BM1, BM2. If your period length coincides with a month you can input M1, M2.

Start Date

This is the first day of the corresponding period

End Date

This is the last date of the corresponding period. 'End date' of a period should always end on a month end. Please note:

- The period codes could be of varying lengths but no gaps should be left between periods
- The duration of two periods should not overlap
- You can modify the period code of the current or a future period; however, a past period cannot be modified even if it has not been closed
- All details maintained in the 'Period Code Screen' will automatically apply to any new branch opened by you in the Branch Parameters Screen
- The current financial cycle code and the current period code are displayed in the 'Branch Parameters Screen'

Period Code Status

After authorisation, you can view whether a financial period is open or it has been closed. Each branch can view the status of a period in every other branch. Click the period whose status you want to view.

Branch

Displays the codes of the different branches of your bank

Status

Displays the corresponding status of the period code highlighted. 'O' - indicates open status; 'C' - indicates closed status

Note

The current financial cycle code and the current period code are displayed in the 'Branch Parameters Screen'

All details maintained in the 'Period Code Screen' will automatically apply to any new branch if incorporated to your bank post maintenance of this screen. The status of all periods in the new branch will be open.

19.1.2 System Functions

The system offers you the flexibility of posting transactions into a previous accounting period which has passed its due end date. For example, let's assume your bank's financial cycle extends from 1st January to 31st December; the first period starts on 1-01-96 ends on 31-03-96. Even beyond 31-03-96 you can keep the period open to be able to post for example,

expense bills you expect to receive in April. After you have posted all adjustments, you can close the period.

Even after you have closed the last accounting period of a year, the system offers you the flexibility of posting adjustments to the financial year.

For each financial year the system generates an open status period called FIN. Its start and end dates coincide with the last date of the financial cycle. Into this one day period you can post the accumulated profits and loss for the financial cycle, general reserves, and statutory reserves for the current year after paying off the dividends. After this one day period is closed the status of the financial cycle in the made by field 'status' is displayed as closed. With this the financial year stands closed and no adjustments can be posted to it.

Closure of a period/financial cycle can be invoked through the General Ledger/ Core Services module. The branches of the bank should close this period/financial cycle.

20. Status Code Maintenance

Loans and bills, which are past their due maturity date of installment re-payment, but remain unpaid, are defaulted contracts. In the Oracle FLEXCUBE system these defaulted contracts can be assigned to different statuses, based on the number of days for which the contract is outstanding.

Each status can be assigned a code. For instance, you can define a status code PDO to represent 'past due obligation', and specify a period of 15 days after which an outstanding contract should be marked as 'PDO'. If they are due for more than 60 days, you could assign a 'doubtful' status; 'sub-standard' if due for 6 months, and so on. Contracts for which no installments are due, or which are regularly paid on their due dates are assigned the status 'Active' by the system. According to the number of days of default defined for each status, a loan would be moved from 'Active' to PDO status, then to doubtful and finally to sub-standard status.

Similarly, you can define status codes for current and savings accounts also. Current and Savings accounts that have not generated any interest over a specific period or have remained inactive with interest overdue may be identified as 'NPAs' (Non-Performing Asset). In Oracle FLEXCUBE, you can assign these accounts different status codes and define status criteria based on which the status movement will occur.

Refer the 'Core Entities' user manual for details on associating status codes with a customer account class /account.

This chapter contains the following sections:

- [Section 20.1, "Status Codes Maintenance"](#)
- [Section 20.2, "Maintaining Dormancy Parameter Details"](#)
- [Section 20.3, "Maintaining Central Bank Dormancy Details"](#)

20.1 Status Codes Maintenance

This section contains the following topics:

- [Section 20.1.1, "Invoking Status Maintenance Screen"](#)
- [Section 20.1.2, "Maintaining Status Codes for OD Account"](#)

20.1.1 Invoking Status Maintenance Screen

You can invoke this screen by typing 'STDSTSCD' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Fields			
Maker	ADMINUSER3	Date Time:	2014-01-01 12:48:31
Checker	ADMINUSER3	Date Time:	2014-01-01 12:48:31
Mod No	1	Record Status	Open
		Authorization	Authorized
		Status	Status

In this screen you can maintain the following to user defined status of a loan or bill/account status:

- A unique code for the status
- A brief description for the status
- A sequence number for the status
- The type of status – Indicate whether the status codes are maintained for an 'Account' or for a 'Contract', or for 'Both'

The type of status you choose depends on the status processing basis for your branch, which is defined in the Branch Parameters Preferences maintenance. If status processing basis is at individual account / contract level, you can choose the applicable status types as 'Account' or 'Contract'. The status codes that have been maintained of type 'Account' are available for association in the Account maintenance and those maintained with type 'Contract' can be associated with contracts.

If status processing basis is at Group / CIF level, you can only maintain status codes of type 'Both' (that is, applicable for both accounts and contracts). In such a case, you must associate the statuses at both the Account maintenance as well as for contracts.

Note

- It is mandatory to maintain the status code 'NORM' (Normal) with the sequence number as '0', for all the status types. The sequence number must not be repeated for a status type.
 - The sequence number associated with the status will be used for determining the hierarchy of statuses, i.e., higher the number, worst the status and this will be unique for the status codes.
-

Maintaining Status Codes for Contracts

The following parameters need to be maintained for defining a status code:

Status Code

This is the code, which identifies the status to which the contract belongs.

For example, assign a code using a maximum of 3 characters, alphanumeric. For example, if your contract has past its due obligation status you can input code PD1. PD representing post due obligation. The number 1 stands for stage 1 of the post due obligation status

Status Description

This is the description of the status, Enter a description using a maximum of 35 SWIFT characters.

For example, taking the above example, you can input here - Past Due Obligation 1 for Loan if you are maintaining status codes for Loans.

Link to

This represents the category of the product - asset or liability to which the contract status is applicable.

For example, if you are maintaining status codes for loans or any money market placements, click on 'assets type of product'. If you are maintaining status codes for deposits, click on 'liability type of products'.

Effective days from Maturity

This indicates the number of days after the due date when this status becomes applicable to the contract. You can specify any number of days from 0-999.

The effective days defined here is defaulted to the product level in the Bills and Loans modules. You have the option of redefining the number of days at the product level.

20.1.2 Maintaining Status Codes for OD Account

Oracle FLEXCUBE provides a facility to maintain status codes for Charge-off and Write-off status of the OD account. These status codes are maintained in 'Status Code Maintenance' screen and the details of the same are as follows:

Status Code	Description	Status Sequence	Status Type
CROF	Status code for Charge-off of OD accounts.	Should be less than SUSP status sequence	Account
SUSP/WOFF	Status code for suspended status of OD accounts.	Should be greater than CROF status sequence	Account

20.2 Maintaining Dormancy Parameter Details

You can maintain the dormant statuses for the customer account in the 'Dormancy Parameter Maintenance' screen. To invoke this screen, type 'STDSTDOR' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

Transaction Branch

Select the appropriate branch from the list of branches available in the option list. This screen will be available only for those users who has 'Multi Branch Operational' check box enabled at 'User Maintenance' Screen.

While clicking 'Ok' button, the system validates the access rights of the selected branch and function for the user. If you don't have appropriate rights on the selected branch and function, the system would raise an error message. If you select a valid branch, the system updates the same as transaction branch and the transaction would be posted for this branch.

Note

The system performs the action level access rights validation only on 'Save' operation.

After selecting the Transaction Branch, you can enter the remaining details in the 'Dormancy Parameter Maintenance' screen.

Change Log				
Maker	Date Time:	Mod No	Record Status	Exit
Checker	Date Time:		Authorization Status	

You need to specify the following details:

Branch Code

Specify the branch code.

Customer A/C

Specify the customer account for which you are maintaining the dormant status. The adjoining option list displays all the customer account numbers that are maintained in the selected transaction branch. You can choose the appropriate one.

Debit

Check this box to indicate that no debits should be posted to the selected customer account.

Credit

Check this box to indicate that no credits should be posted to the selected customer account.

Frozen

Check this box to indicate that the customer account is frozen due to some unavoidable reason.

Dormant

Check this box to indicate that the account is in dormant status which means not used for along time.

Central Bank Dormant

This is checked if the account has become Central Bank Dormant. Users can update the status from here.

Dormant Param

Indicates the parameters for re-activating the dormant account. You can select one of the following options:

- Debit
- Credit
- Any

Remarks

Specify the remarks, if any.

20.3 Maintaining Central Bank Dormancy Details

You can maintain the non financial activities for dormancy in the 'Non Financial Activity For Dormancy Maintenance' screen. To invoke this screen, type 'STDNONFA' in the field at the top right corner of the application tool bar and click the adjoining arrow button.

Non Financial Activity For Dormancy Maintenance

New Enter Query

Branch Code *

1 Of 1 Go

Activity Code	Activity Description	Consider for Account Activation
---------------	----------------------	---------------------------------

Maker Date Time: Mod No Record Status
Checker Date Time: Authorization Status

Ok Exit

Specify the following details:

Branch Code

Select or the branch code from the option list. You can also enter the branch code manually.

Activity Code

Select the activity code to be considered for activation of accounts from central bank dormancy.

Activity Description

The description of the activity. Following table shows the codes and respective description:

Activity Code	Activity Description
CHQR	Cheque book request
PSRQ	Passbook request
STMT	Ad-hoc statement request
SWTH	Switch Transactions

Consider for Account Activation

Check the box if you want the activity to change the dormancy condition of the account

For dormant account, if any activity is checked then on the checked non-financial transaction, the Dormant account activates the and Dormancy Date is changed to Current Date+ Dormancy Days+1. The dormancy date is changed in the account level.

For dormant accounts if no activity is checked, but still there are the specified non-financial transactions the Dormancy Date is changed to Current Date+ Dormancy Days+1. The dormancy date is changed at the account level. But the account remains dormant.

21. Transaction Code

In the 'Transaction Codes Maintenance' screen you define transaction codes to representing various types of transactions, for example, transfer charges, incoming mail transfer, incoming telex transfer, reserve, incoming clearing transfer etc. All similar transactions can be grouped under a common transaction code with a description. This description will be printed on the account statements, reports and advices generated.

For a transaction type you also maintain other related processing details which will be applicable to all transactions posted under a common code. The details, such as, availability of funds for liability checking, SWIFT code for the transaction type, preferences regarding charges to be levied on turnovers, payment to be made through cheques etc. are available.

This chapter contains the following sections:

- [Section 21.1, "Transaction Code Maintenance"](#)

21.1 Transaction Code Maintenance

This section contains the following topic:

- [Section 21.1.1, "Invoking Transaction Code Screen"](#)
- [Section 21.1.2, "Transactions Tax Button"](#)

21.1.1 Invoking Transaction Code Screen

You can invoke 'Transaction Code Maintenance' screen by typing 'STDTRNCD' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Transaction Code Maintenance

New Enter Query

Transaction Details

Transaction Code *
Description *
Swift Code

MIS Head
External Code

Availability Information

☐ Immediate
☐ On Value Date
☐ After Days with New Value Date
☐ After X days
Days

Overdraft Tracking

Component type for transaction Principal

Debit/Credit Override Preferences

Debit Override Tracking Both

Preferences

☐ Cheque Mandatory
☒ Interests and Charges Transaction Count
☒ Interests and Charges Turnover Inclusion
☒ Consider for Account Activity
☒ Interest and Charges Balance Inclusion
☐ Available Balance Check Required
☒ Interests and Charges Penalty Inclusions
☒ Inter Branch in Local Currency
☐ Acumen Transaction Code
☐ Exempt Advance Interest
☐ Exempt Processing

Anti Money Laundering Monitoring

☐ Anti Money Laundering Required
Product Category
Statement Day Basis Current Working Day
Intra Day Release
Salary Credit

Fields | Transaction Tax

Maker	Date Time	Mod No	Record Status
Checker	Date Time		Authorization Status

Exit

In this screen you maintain the following for a transaction:

- A code representing the transaction type
- Description of the transaction type
- The interval after which funds should be made available after the transaction
- Preferences regarding charges to be levied or not on number of transaction counts and total turnover amounts
- Preference stating whether a transactions booked under this code should cause an account marked as 'dormant' by the system to be re-instated to 'active'
- Preference whether payment for a transactions posted under this code should be made through cheque
- Preference indicating whether payment for a transaction booked under this code should be considered for Escrow transfer processing

Maintaining Transaction Details

The following parameters need to be maintained for a transaction type:

Transaction Code

This is the code you assign to a transaction type. This code identifies the type of transaction.

Enter 3 characters, Alphanumeric. For example, for all transfer charges transaction you can give the code as TCT; for incoming telex transfer you can input - ITT. In case, you want to assign numeric codes only, then for ease of operation similar transaction types should be grouped into a range. For example, you can set a range for all Money Market transactions say, A1-A30; a different range for Bills and Collections B1-B30 and so on.

Description

This is the description of the transaction type

Enter the description using a maximum of 35 characters, alphanumeric. For example, for TCT code you can enter 'Transfer Charges Transaction'.

SWIFT Code

This is the SWIFT code to which this transaction code is linked. It is used for posting transaction details on SWIFT format.

Select from the option list. It will display a list of SWIFT formatted codes representing transaction types. The following list is displayed:

SWIFT CODES	TRANSACTION TYPE
BOE	Bill of Exchange
BRF	Brokerage fee
CHG	Charges and other Expenses
CHK	Cheques
CLR	Cash Letter/Cheque Remittance
COL	Collections
COM	Commission

DCR	Documentary Credit (for Principal Amount)
DIV	Dividends - Warrants
EQA	Equivalent Amount
ECK	Euro checks
FEX	Foreign Exchange
INT	Interest
LBX	Lock Box
LDP	Loan Deposit
MSC	Miscellaneous
RTI	Returned Item
SEC	Securities
STO	Standing Order
TCK	Travelers Cheques
TRF	Transfer
VDA	Value Date Adjustment

The codes COL -Collections, DCR - Documentary Credit and SCC- Securities are used when entering a principal amount.

MIS Head

Each Transaction Code that is created can be linked to an MIS Head. An MIS Head indicates the manner in which the type of entry should be considered for profitability reporting purposes.

Indicating Availability Information

This states the different time intervals after which funds will be available for withdrawal in case of all transactions posted under this transaction code.

The system defaults to immediate, which means that funds will be immediately available for withdrawal (the immediate option on the screen). Example: Teller Transaction. For all Clearing transactions you have the option to specify as to when will funds be made available for withdrawal. Click the desired option.

Click 'On Value Date' option if you want funds to be available on the date the transaction became effective. Example: A loan or a deposit

Incase you want to specify the number of days after which funds should be available for withdrawal, click on the option After Days. Enter the number in the box. It could be any two digit positive integer from 1 to 99. This option will make funds available for all transactions posted under this code, on the specified date from the value date. Example: Demand Draft

When you click the last option that is, After Days with New Value Date and enter the number of days in the box; then the original value date of the contract will take a new value date. This new value date = old value date + the number of days input by the user in the box against the option. Example: Future dated funds transfer.

The difference between the third and fourth option being that in the latter case the old value date changes; while in the former the value date does not change.

Intra-day Release

If you want uncollected funds on a transaction posted using the transaction code, to be manually released intra-day (that is, within the day), select the Intraday Release option. The Intraday Funds Batch, when manually executed during the day, picks up those transactions that are due for release on or before the system date, which have been posted with the transaction code (with the Intraday Release option enabled), for release of uncollected funds.

The Intraday Release option cannot be enabled if the Availability specified for the transaction code is Immediate.

You can use the ACUNCOLB (Intraday Funds Release) batch process to perform the intra-day release of uncollected funds in respect of transactions posted using a transaction code for which the Intraday Release option has been enabled.

For details about invoking the batch process, refer the Current and Savings Account user manual.

Tracking Overdraft

Component type for transaction

Select the component type for transaction from the drop-down list. The options available are:

- Principal - Select 'Principal', if a transaction type is not an interest or charge
- Interest - Select 'Interest', if a transaction code is used for debiting interest for an overdraft account.
- Charge - Select 'Charge', if a transaction code is used for debiting charge for an overdraft account.

The component type for the transaction code is mandatory for maintaining transaction code and cannot be modified after the first authorization.

Debit/Credit Override Preferences

Debit Override Tracking

Select the debit override tracking to validate debit override status from the drop-down list. The options available are:

- Both - Selecting 'Both' will display an override message for online transaction and fails during batch transactions
- Online - Selecting 'Online' will display an override message for online transaction and ignore during batch transactions
- Batch - Selecting 'Batch' will ignore the tracking during online transaction and fails during batch transaction.

The system defaults 'Both' as debit override tracking value.

Credit Override Tracking

Select the credit override tracking to validate credit override status from the drop-down list. The options available are:

- Both - Selecting 'Both' will display an override message for online transaction and fails during batch transactions
- Online - Selecting 'Online' will display an override message for online transaction and ignore during batch transactions

- Batch - Selecting 'Batch' will ignore the tracking during online transaction and fails during batch transaction.

The system defaults 'Both' as credit override tracking value.

Processing Debit and Credit Override Transactions

If a customer account is marked as Debit/Credit Override for all the Debit/Credit transactions to the account then the system does the following:

- If a debit/credit transaction to the account is performed through FCUBS user interface, the system checks the configuration for Debit/Credit Override Tracking at 'Transaction Code Maintenance' (STDTRNCD) screen. If the tracking is 'Online' or 'Both', then the system displays an override message as "Account 'CASA#' is in "Debit/Credit Override" status". If the tracking is enabled for batch transactions alone, then online transactions will go without any additional overrides.
- The user can either accept the override and go ahead with the debit/credit transaction or reject the override. The transaction gets dismissed if the override is rejected. If the override is accepted it is logged along with the transaction details.
- For all FCUBS transactions, the override will only get displayed during posting of accounting entries to the account.
- For the transactions where accounting entries are posted online, the system displays the override on the transaction screen itself.
- During bulk transaction processing in and Clearing transactions, where the accounting entries are deferred, the transactions moves to a debit/credit exception queue. From the queue these overrides can be accepted or rejected by the user.

Automatic Batch Process

During the automatic batch process, the transactions from batch will fail if 'Debit/Credit Override Tracking' is selected as 'Both' or 'Batch' at transaction code level. If the debit and credit override tracking is enabled for Online transactions, then the automatic batch process can be run.

Transaction from Interfaces

All the transactions initiated from an external interface will be stopped for the customer accounts whose status is marked as 'Debit Override' and 'Credit Override' status. This validation is applicable to all debit/credit transactions to the account and system will not consider the exceptions maintained at transaction code level.

If there are any debit or credit to account through accounting data entry upload or any generic interface upload, the system treats it as a request from the interface and rejects it based on Debit Override or Credit Override status. These transactions from external interfaces are handled through error code conversion functionality in Override maintenance (CSDOVDME) screen.

You can maintain the error code conversion based on the channel names. The new error codes can be 'Error/Override/Ignore' type. The conversion should be supported on the basis of 'Function ID' or a combination of 'Function ID and Source Code'. The error code maintained in conversion sub-screen should be unique for a combination of Parent error code, Branch Code, Source Code and Function ID.

Specifying Preferences

This field indicates your preferences regarding transactions booked against this transaction code. The preferences marked relate to the following:

Interest and Charges Transaction Count

Every debit or credit entry is passed under a transaction code. If for a transaction code you have checked 'I&C transaction count' then all entries made under that code would be picked up by the system as chargeable transaction counts which would be used by the I&C system to compute charges.

Therefore, you should take care not to check for all bank induced transactions like - service charges, interest payment, calculation, brokerage and charges, etc.

For example, your bank has a policy of limiting savings withdrawals without additional charges to only 8 in a month. Beyond which all withdrawals would be charged. For the ninth and onward withdrawals in the month from any account the system will maintain a count for computing charges. However, care should be taken to exclude all bank-induced transactions from the count.

Interest and Charges Turnover inclusion

Every debit or credit entry is passed under a transaction code. If for a transaction code you have checked 'I&C turnover inclusion' then the debit turnover/ credit turnover balance under that code would be picked up by the system as chargeable depending upon the option specified in the I&C module. Therefore you should take care not to check for all bank induced transactions like - service charges, interest payment, calculation, brokerage and charges, etc.

Interest and Charges Balance Inclusion

Check this box to indicate that the transactions posted under this code should be considered for the purpose of computation of Remuneration (Interest). By default this option is checked. Uncheck this box for such loan transactions or any other transactions for which you wish to exclude computation of remuneration (interest).

Note

Once the transaction code is authorized, you cannot change your preference.

Consider for Turnover Limit

Check this box to indicate that all transactions posted under this code should be considered as part of the turnover limit processing.

Consider for Cover Sweeps

Only if you check this box, the system will consider the debit transactions for sweep from cover accounts/auto linked TD/linked term deposits. .

If a particular transaction should not be considered for sweep, then the related transaction codes should be maintained with 'Consider for cover sweeps' as unchecked.

The above field is applicable only for clearing and teller modules. Oracle FLEXCUBE repays loan from multiple accounts. In Oracle FLEXCUBE, the loan account is the primary account and all the other accounts linked to it are cover accounts. While paying the settlement if the primary account has insufficient amount, the system will check the cover accounts for the remaining amount according to the preference.

Consider for Account activity

If you check the field 'Consider for A/C activity' for a transaction code, then any debit or credit posted under this code would reinstate the status of an account from dormant to active and accounting activity shall be considered.

Cheque Mandatory

If for a transaction code you check 'Cheque Mandatory' then, for all transactions posted under this code, transaction will take place through cheque. For example: Incoming Clearing transfer.

Cheque Mandatory should be checked only for SB cheque withdrawals and Cash Account Cheque withdrawals.

Available Balance Check Required

Select this option if you want the system to check for the availability of funds before posting a debit entry to a customer account. The system will check for the available balance in all customer accounts associated with the Transaction Code for which the option is enabled. If the available balance check fails i.e. if the system detects insufficient funds in the customer account, it will display a warning message.

Consider for Maximum Balance

Select this option if you want to use all the credit transaction codes for funding CATS accounts. You should not check this box for transaction codes that are used in interest liquidation accounting to CAT accounts.

Note

However, the system will check for the available balance only if you have selected the 'Available Balance Check required' option for both the transaction code associated with the accounting entry and the Customer Account Class to which the customer's account that is being debited, belongs. The check will not be performed if the option is not selected in both places.

Interest and Charges Penalty Inclusion

In the transaction code that you use for debit entries to time deposit accounts, you must indicate the computation of penalties on debit entries due to withdrawals from the account before the maturity date. You must select the IC Penalty Inclusion check box to indicate this.

Inter Branch in Local Currency

This indicates whether inter branch entries passed with this transaction code should be in Local currency. If this option is checked, the inter branch transactions would be passed in local currency. This way, the Treasury would be able to track its profit and the branch's profit by passing a single consolidated entry (Position transfer from one branch to the Treasury branch) at the treasury rate.

Note

- This option is applicable only if the local currency of the different branches is the same. This option is applicable only for Fcy1- Fcy1 transactions. For other transactions, namely, Fcy1-Fcy2, Lcy-Fcy, Fcy-Lcy, IB entries would be based on IB Parameters Maintenance.
 - For position transfer, the 'Inter Branch in Local Currency' check box in the Transaction Code maintenance screen should be checked to avoid creating position due to IB posting.
-

Acumen Transaction Code

You need to check this option in order to eliminate the deals/transactions uploaded from the Acumen in the Hand-off of transactions affecting FCY Position to Acumen from Oracle FLEXCUBE.

Note

This is applicable where Oracle FLEXCUBE interfaces with Acumen. Acumen is an Integrated Turn-key solution for Treasury, Derivatives and Capital Markets Covering Front, Risk Control, Middle Office from Login SA.

Exempt Advance Interest

Check this box to indicate that all the postings with this transaction code should not be considered for penalty interest calculation.

Escrow Processing

Check this box to indicate that all the payments related to this transaction code should be considered for Escrow sweeps. If this box is checked and the credit account (Project account) is Escrow enabled then the system will automatically compute predefined percentage of transaction amount and places an amount block on the credit account (Project account).

Note

Escrow processing is possible only if the trust account and escrow account are of the same currency and are with-in Oracle FLEXCUBE.

Available Balance update through PPC

Check this box to update the available balance on the project through PPC.

Salary Credit

Select the type of salary credit from the adjoining drop-down list. This list displays the following values:

- Normal Salary
- Bulk Salary

By default, the system selects null value.

Note

- The value 'Bulk Salary' can be selected only if the 'Availability Information' is 'Immediate'.
 - This applies when you use the option 'Bulk Salary' along with a transaction code. When a credit is made to an account through salary upload table along with a bulk salary enabled transaction code, the system blocks the entire credit amount on that account with effect from the date of upload. This block remains active for the period maintained in CSTB_PARAM against the parameter 'BULKSALARY_BLOCK_DAYS'. The number of days for expiry is mentioned terms of calendar days. The system does not allow manual operations on the amount block for these accounts.
-

Statement Day Basis

You need to specify when the transaction associated with the selected Transaction Code should appear in the account statement. The available options are:

- Current Working Day

- Previous Working Day

21.1.1.1 Accounting Entry Processing to Calculate Statement Date

The accounting entry processing will be enhanced to calculate the Statement Date based on the Transaction Code Maintenance and the Statement Status at the Branch level. The following illustration explains the calculation of Statement Date.

Assume two Transaction Codes TXN1 and TXN2 have been defined with Statement Date Basis as Current Working Day and Previous Working day respectively. The Statement Date would be derived as follows:

For a transaction C1 posted on say 25th Jan, 2004 with TXN1, the Statement Date would be derived as 25th Jan, 2004 irrespective of the Branch Statement Status.

For a transaction C2 posted on 25th Jan, 2004 with TXN2, the Statement Date would be derived as the Previous Working Day of 25th Jan, 2004 if the Branch Statement Status is set to 'N' specifying that the Branch is not yet ready for periodic statements processing.

For a transaction C3 posted on 25th Jan, 2004 with TXN2, the Statement Date would be derived as 25th Jan, 2004 if the Branch Statement Status is set to 'Y' specifying that the Branch is ready for periodic statements processing.

The Statement Date would be stored as part of the archived data also

The Statement Date would be recomputed during the reversal entry in the same logic

Monitoring Anti Money Laundering

Anti Money Laundering Required

Check this box to indicate that AML monitoring is required for all accounting entries linked to the particular transaction code. Leave it unchecked to indicate otherwise.

Product Category

If you indicate that AML tracking is required for all transactions linked to the particular transaction code you have to identify the product category for which AML tracking is necessary.

21.1.2 Transactions Tax Button

You can maintain details to calculate GMF tax in this screen.

Tax Scheme

Specify the tax scheme to be used for calculating GMF tax. A specific tax rule is attached to a tax scheme for tax calculation. The adjoining option list displays the tax schemes available. You can choose the appropriate one.

Tax Borne By

Select the account that will bear the tax from the adjoining drop-down list. The list displays the following values:

- Bank Account
- Customer Account

Tax Applicability

Select the type of transactions for which the tax is applicable from the adjoining drop-down list. The list displays the following values:

- Both Transaction
- Debit Transaction
- Credit Transaction

Account Type

Select the type of account for which the tax is applicable from the adjoining drop-down list. The list displays the following values:

- ALL
- General Ledger
- Savings Account
- Current Account
- Term Deposit

Where the transaction pertains to a GL, the system computes the tax only if the the GL is an internal leaf GLs.

22. Transaction Tax

Oracle FLEXCUBE allows you to maintain GMF Tax preferences at the branch level using 'Transaction Tax Maintenance' screen. This chapter contains the following sections:

- [Section 22.1, "Transaction Tax Maintenance"](#)

22.1 Transaction Tax Maintenance

This section contains the following topic:

- [Section 22.1.1, "Invoking Transaction Tax Maintenance Screen"](#)
- [Section 22.1.2, "Viewing Transaction Tax Details"](#)

22.1.1 Invoking Transaction Tax Maintenance Screen

You can invoke the Transaction Tax Maintenance' screen by typing 'STDTRNTX' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Transaction tax maintenance

New Enter Query

Branch Code *
Currency Code *

Tax Details

Tax Class
Tax Type Debit transaction tax
General Ledger Code
Description

Tax Scheme *
Effective Date
Nonpensioner monthly limit
Pensioner monthly limit

Maker
Checker
Date Time
Date Time
Mod No
Record Status
Authorization
Exit

Specify the following details:

Branch Code

Specify the branch code. The adjoining option list displays the valid branches in the system. You can choose the appropriate one.

You can specify 'ALL' whenever a particular maintenance is applicable to all branches in the bank.

Currency Code

Specify the currency code. The adjoining option list displays the valid currencies in the system. You can choose the appropriate one.

You can specify 'ALL' whenever a particular maintenance is applicable to all currencies in the bank.

Tax Scheme

Specify the tax scheme to be used to define the rule for Tax Calculation. The adjoining option list displays the valid tax schemes in the system. You can choose the appropriate one.

Tax Details

Tax Class

Specify the tax class to be used to define accounting entry. The adjoining option list displays the valid tax classes in the system. You can choose the appropriate one.

Tax Type

Select the tax type from the adjoining drop-down list. The list displays the following values:

- Debit Transaction Tax
- Value Added Tax

General Ledger Code

Specify the GL to be used when the tax scheme is 'Borne by the Bank Account'. The adjoining option list displays the valid GL codes in the system. You can choose the appropriate one.

Description

The system displays the description of the GL specified.

Effective Date

Specify the date from which the tax is effective.

Nonpensioner monthly limit

Specify the monthly limit for non-pensioners.

Pensioner monthly limit

Specify the limit for pensioners.

22.1.2 Viewing Transaction Tax Details

You can view the transaction tax maintenance details in the 'Transaction Tax Summary' screen. To invoke this screen type 'STSTRNTX' in the top right corner of the Application toolbar and click adjoining arrow button.

Transaction tax summary

Search Advanced Search Reset Clear All

Use Sensitive

Authorization Status Record Status

Branch Code Currency Code

Tax Scheme Tax Class

General Ledger Code

Records per page: 15 1 Of 1 Lock Columns: 0

Authorization Status	Record Status	Branch Code	Currency Code	Tax Scheme	Tax Class	General Ledger Code
----------------------	---------------	-------------	---------------	------------	-----------	---------------------

Exit

You can query on records based on any one or all of the following criteria:

- Authorization Status
- Record Status
- Branch Code
- Currency Code
- Tax Scheme
- Tax Class
- General Ledger Code

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Branch Code
- Currency Code
- Tax Scheme
- Tax Class
- General Ledger Code

Double click on a record to invoke the detailed screen for that record.

23. City Code

Oracle FLEXCUBE facilitates the maintenance of cities for which GMF tax is exempt. This chapter contains the following sections:

- [Section 23.1, "City Code Maintenance"](#)

23.1 City Code Maintenance

This section contains the following topics:

- [Section 23.1.1, "Invoking the City Code Maintenance Screen"](#)
- [Section 23.1.2, "Viewing City Code Details"](#)

23.1.1 Invoking the City Code Maintenance Screen

You can invoke this screen by typing 'STDCTMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

City Code Maintenance

New Enter Query

City * _____ State Code _____

Description _____ Description _____

Administrative Statistical Code _____ Corporation Center Code _____

City Compensation Code _____ Group Code _____

Transaction Tax Exemption Details

1 Of 1 Go

Tax Scheme	Tax Exempted	Exemption Percent
------------	--------------	-------------------

Maker Date Time: Mod No Record Status

Checker Date Time: Authorization Status

Ok Exit

Specify the following details:

City

Specify the city for which you are maintaining GMF exemption details.

Description

Specify an appropriate description for the city.

Administrative Statistical Code

Specify the administrative statistical code for the city. The adjoining option list displays the valid administrative statistical codes in the system. You can choose the appropriate one.

City Compensation Code

Specify the city compensation code for the city. The adjoining option list displays the valid city compensation codes in the system. You can choose the appropriate one.

State Code

Specify the state code for the city.

Description

Specify an appropriate description for the state.

Corporation Center Code

Specify the corporation center code for the city. The adjoining option list displays the valid corporation center codes in the system. You can choose the appropriate one.

Group Code

Specify the group code for the city. The adjoining option list displays the valid group codes in the system. You can choose the appropriate one.

Transaction Tax Exemption Details

Tax Scheme

Specify the tax scheme that is to be exempted from GMF tax. The adjoining option list displays the valid tax schemes in the system. You can choose the appropriate one.

Tax Exempted

Check this box to indicate that GMF tax is exempted for the specific city.

Exemption Percentage

Specify the percentage of tax that is exempted. This is applicable only if the box 'Tax Exempted' is checked.

23.1.2 Viewing City Code Details

You can view the summary of city codes maintained in the system in the 'City Code Summary' screen. To invoke this screen, type 'STSC TMNT' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.

City Code Summary

Search Advanced Search Reset Clear All

Case Sensitive

Authorization Status Record Status

City Description

Group Code

Records per page: 15 1 Of 1 Go Lock Columns: 0

Authorization Status	Record Status	City	Description	Group Code
----------------------	---------------	------	-------------	------------

Exit

You can query on records based on any one or all of the following criteria:

- Authorization Status

- Record Status
- City
- Description
- Group Code

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- City
- Description
- Group Code

Double-click a record to view it in detail.

24. Employment Details

In Oracle FLEXCUBE, you can maintain the employment details in the 'Employment Details' screen. This chapter contains the following sections:

- [Section 24.1, "Employment Detail"](#)

24.1 Employment Detail

This section contains the following topics:

- [Section 24.1.1, "Invoking the Employment Details Screen"](#)
- [Section 24.1.2, "Viewing Employment Details"](#)

24.1.1 Invoking the Employment Details Screen

You can invoke this screen by typing 'STDCSEMP' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Employment Details' window. The title bar says 'Employment Details'. Below it is a menu bar with 'New' and 'Enter Query'. The main content area has three input fields: 'Employment *' (with a red asterisk), 'Description', and 'Maximum Account Allowed For Exemption'. At the bottom, there is a status bar with fields for 'Maker', 'Checker', 'Date Time', 'Mod No', 'Record Status', 'Authorization Status', and an 'Exit' button.

Specify the following details:

Employment

Specify the employment type. The adjoining option list displays the employment types in the system. You can choose the appropriate one.

Description

The system displays the description for the employment specified.

Maximum Account Allowed For Exemption

Specify the maximum number of accounts for employment that would be exempted at account level.

24.1.2 Viewing Employment Details

You can view the summary of employment maintained in the system in the 'Employment Summary' screen. To invoke this screen, type 'STSCSEMP' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.

Employment Summary

Search Advanced Search Reset Clear All

Case Sensitive

Authorization Status Employment Record Status Description

Records per page: 15 1 Of 1 Go Lock Columns: 0

Authorization Status	Record Status	Employment	Description	Maximum Account Allowed For Exemption
----------------------	---------------	------------	-------------	---------------------------------------

Exit

- You can query on records based on any one or all of the following criteria:
- Authorization Status
- Employment
- Record Status
- Description

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Employment
- Description
- Maximum Account Allowed For Exemption

Double-click a record to view it in detail.

25. Employment Detail Maintenance

You can maintain the different types of employment in the system. This chapter contains the following sections:

- [Section 25.1, "Employment Detail Maintenance"](#)

25.1 Employment Detail Maintenance

This section contains the following topics:

- [Section 25.1.1, "Invoking the Employment Detail Maintenance Screen"](#)
- [Section 25.1.2, "Viewing Employment Type Details"](#)

25.1.1 Invoking the Employment Detail Maintenance Screen

You can invoke this screen by typing 'STDEMPMT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Maker	Date Time:	Mod No	Record Status	Authorization Status	Exit
Checker	Date Time:				

Specify the following details:

Employment

Select the employment type from the adjoining drop-down list. The list displays the following values:

- Full time Temporary
- Unemployed
- Full time Permanent
- Self Employed
- Part Time
- Retired Pensioned
- Retired Non Pensioned

- Other

Description

Specify an appropriate description for the employment type selected.

25.1.2 Viewing Employment Type Details

You can view the summary of employment types maintained in the system in the 'Employment Detail Summary' screen. To invoke this screen, type 'STSEMPMT' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.

You can query on records based on any one or all of the following criteria:

- Authorization Status
- Employment
- Record Status
- Description

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Employment
- Description

Double-click a record to view it in detail.

26. Account Revaluation Maintenance

Account revaluation is a process by which the LCY equivalent of balances in the FCY accounts is marked to market.

In all foreign currency accounts, the FCY current balance is displayed along with the LCY equivalent of the current balance. The LCY equivalent current balance is the aggregate of the LCY equivalent of the various transactions that have been posted to the account.

In the 'Chart of Accounts - GL Details' screen you specify whether a GL should be revalued or not.

This chapter contains the following section:

- [Section 26.1, "Account Revaluation Setup"](#)

26.1 Account Revaluation Setup

This section contains the following topic:

- [Section 26.1.1, "Maintaining Account Revaluation"](#)

26.1.1 Maintaining Account Revaluation

In the 'Account Revaluation Maintenance' screen, you specify parameters for account revaluation such as rate type, the GL to which the profit or loss from revaluation should be

posted, etc. You can invoke this screen by typing 'RVDXSETP' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

In this screen you can maintain the following parameters to define the revaluation parameters for a GL account:

- The general ledger accounts to which the profit or loss on revaluation is to be posted
- The account to which the revaluation profit is to be debited or loss credited
- The rate type to be used to revalue the GL
- The transaction code for posting the revaluation entries
- The rate type to be used for accounting entry-based revaluation of profit and loss GLs
- The transaction code that would be used to post revaluation entries due to accounting entry-based revaluation of profit and loss GLs

General Ledger Code

This is the code of the GL account for which you are specifying revaluation parameters.

Transaction Code

This is the transaction code under which the accounting entries would be posted to the defined revalued GL account

Rate type

This is the rate type to be used for revaluation of this GL

Profit General Ledger

If the result of revaluation is a profit, the profit amount is credited to this profit GL. If, for a GL, you have opted for revaluation split, then Revaluation Profit (as opposed to Trading Profit) is posted into this GL.

Revaluation split segregates revaluation profit / loss into:

- Trading Profit / Loss – Profit / Loss due to revaluation of FCY entries posted into the GL during the current day.
- Revaluation Profit / Loss – Profit / Loss due to revaluation of opening FCY balances (excludes current day's turnover).

Loss General Ledger

If the result of revaluation is a loss, the loss amount is debited to this loss GL. If, for a GL, you have opted for revaluation split, then Revaluation Loss (as opposed to Trading Loss) is posted into this GL.

Revalue into

This GL account is debited if the result of revaluation is a profit; and credited if the result of revaluation is a loss

This would typically be the GL code being revalued. For all non-contingent GLs belonging to the asset or liability categories, the system defaults to the GL being revalued.

If you wish to specify a different account for posting these entries specify by selecting from the list of maintained GLs. A list of all GLs would be displayed. Select.

Trading Profit Account/Trading Loss Account

This indicates the GL for posting profit/loss due to trading revaluation (Trading Profit / Loss) if you have indicated that revaluation split is required for a GL.

Netting of offset entries

A check against this indicates whether the offset entries for all accounts linked to the GL code need to be netted or not. If checked, a single consolidated entry would be passed (one for profit and one for loss).

Note

Netting of offset entries is applicable only for normal account revaluation and not for accounting entry-based revaluation of Income/Expense GLs.

Accounting entry-based revaluation of Income / Expense GLs

Income/expense GLs that are marked for entry-based revaluation are picked up by the EOD revaluation batch process, which executes before the account revaluation batch process on a given business day.

In the Account Revaluation Maintenance, you must specify the following parameters that would be used by the batch revaluation process, for revaluing FCY entries in Income/Expense GLs:

- Rate type
- Transaction code for posting entry-based revaluation entries

You can maintain these parameters for specific Income/Expense GLs. If you wish to maintain these parameters for all Income/Expense GLs, you can specify the 'STDPNL' option in the GL Code field. The 'STDPNL' option signifies that the entry-based parameters being maintained are applicable for all Income/Expense GLs.

When the revaluation batch revalues an Income/Expense GL, it uses the rate type and transaction code maintained for the GL in the Account Revaluation screen. If no maintenance exists for the specific GL, the parameters maintained for the 'STDPNL' GL Code option are used.

27. Maintaining Branch Holidays

For a year, you need to define your weekly holidays and your calendar year annual holidays. This is done in the 'Local Holiday Calendar' screen.

The system uses the information maintained in this screen to do the following:

- To check that the 'value date' of no Data Entry transaction falls on a holiday
- To check that the start date / maturing date and schedule date of a loans and deposit contract does not fall on a holiday
- To effect a date change on the system -- today's date and the next working date

For any schedule / contract maturing at a future date, say, 5 years hence, you can input a future date, only if the calendar for that year has been maintained. It is not necessary to maintain the list of all annual holidays, for future, you can merely define all regular weekly holidays.

This screen is maintained for each branch, of your bank, from the respective branches; thus making it possible to have a different set of holidays for different branches of the bank.

This chapter contains the following section:

- [Section 27.1, "Branch Holiday Maintenance"](#)

27.1 Branch Holiday Maintenance

This section contains the following topics:

- [Section 27.1.1, "Designating Unexpected Holidays for Branch"](#)

27.1.1 Designating Unexpected Holidays for Branch

The holiday calendar for your branch is maintained in the Branch Holiday Calendar screen.

In addition to the holiday calendar, you may need to designate certain days as holidays unexpectedly, without forewarning. Alternatively, you may also need to roll back a previously defined holiday date or set of dates. You can do this using the 'Unexpected Branch Holiday Maintenance' screen. You can invoke this screen by typing 'CGDUEHOL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

In this screen, for the current branch, you can maintain a range of dates, every date within which will be designated as holidays for the branch. You can also provide a reason for the designation. Every unexpected holiday you designate must be authorized for it to be effective.

Note

It is possible to maintain next working day as a holiday and next holiday as a working day using this screen.

27.1.1.1 **Reversing Designated Holiday**

In the Unexpected Holiday Maintenance screen, you can also reverse a designated holiday before the actual date. Specify the holiday date in the Holiday Date field, and check the Reverse box field alongside it.

When you designate unexpected holidays, any bank or customer value dates for any transactions, that coincided with the holiday are rolled forward. Any accounting entries passed are reversed and fresh entries are passed to reflect the new value date.

Note

For the release of uncollected funds, the original transaction date is considered for availability calculations

27.1.1.2 **Propagating Local Holidays**

Oracle FLEXCUBE facilitates propagation of holiday details maintained in the head branch to all other active branches. This propagation is based on the value maintained for the CSTB parameter 'PROPOGATION_OF_LOH'.

The system defaults the value as 'N' for 'PROPOGATION_OF_LOH', indicating that no propagation is allowed for local holidays; however, you can set the value as 'Y' if you need to allow propagation of holidays.

If the 'PROPOGATION_OF_LOH' value is maintained as 'Y', then the system will enable propagation of holiday maintenance from Head branch to other active branches under the following condition:

- Holiday details are authorized.
- Holiday details are not maintained for the year for the active branches
- Only when the new holiday details are maintained and authorized for the first time. Propagation of holiday maintenance at HO will be allowed for Un-authorized branch also, subsequent modification after first authorization, if year is not maintained for the branch.
- When a new branch is created and authorized for the first time
- Un-authorized branch with modifications after first authorization and no holiday details maintained for the year
- For the branches which are restricted

Propagated records will have the Maker ID and Checker ID details of the HO.

Propagation of Holidays during Modify Operation

After maintaining 'PROPOGATION_OF_LOH' flag as 'Y', if propagation of holidays during modify operation is required, then the parameter 'PROPOGATION_OF_LOH_ON_MODIFY' should also be set as 'Y' in CSTB_PARAM.

In this scenario when both parameters are set as 'Y', the propagation of holidays will also happen during modification of head office record and the calendar for all branches will be overwritten by the Head Office calendar.

28. Holiday File Upload

This chapter contains the following sections:

- [Section 28.1, "Uploading Holiday File"](#)

28.1 Uploading Holiday File

SWIFT provides a country-wise holiday file that can be uploaded into Oracle FLEXCUBE. For all countries where 'EUR' is not the local currency, the respective holidays can be uploaded into the currency holidays tables. For European countries, where 'EUR' is the currency, you can upload the TARGET holidays. Oracle FLEXCUBE allows you to upload these currency holidays through the 'BIC/BICPLUS – Upload' screen. You can invoke this screen by typing 'ISDBICPU' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Bank Identifier Code Upload

Save

Source Code *

File Name *

File Path *

Intraday Sequence Number

Submit Parameters Submit Batch

Cancel

Here you need to choose the source code as 'CCH' from the drop-down list. For further details about this screen, refer the section titled 'Uploading the BIC/BICPLUS files into Oracle FLEXCUBE' in the 'Common Core - Core Entities and Services User Manual'.

The holiday file gets uploaded with two records:

- HF Record – wherein 'EUR' is not the local currency
- HS Record - wherein 'EUR' is the local currency

For more details on the file formats of these records, refer the chapter titled 'Annexure – B – File Formats'.

29. Maintaining Clearing Holidays

You need to maintain a yearly list of holidays of your Clearing House. This is defined in the 'Clearing House Holiday Calendar' screen.

This chapter contains the following section:

- [Section 29.1, "Clearing House Holiday Maintenance"](#)

29.1 Clearing House Holiday Maintenance

This section contains the following topics:

- [Section 29.1.1, "Maintaining Clearing House Holidays"](#)
- [Section 29.1.2, "Steps to Define Clearing House Holidays"](#)
- [Section 29.1.3, "Defining Clearing House Holidays"](#)
- [Section 29.1.4, "Designating Unexpected Holidays for Clearing House"](#)

29.1.1 Maintaining Clearing House Holidays

This set of holidays is maintained at the bank level, by the Head Office. You can invoke this screen by typing 'STDCGHOL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Clearing House Holiday Maintenance' application window. It includes a toolbar with 'New' and 'Enter Query' buttons. The main area displays a 3x3 grid of calendar views for the months of the year. Each calendar has a header with day abbreviations (S, M, T, W, Th, F, Sa). Below the grid, there are input fields for 'Clearing House *' and 'Year *', and a 'Populate' button. At the bottom, there is a 'Holiday Details' section with a list box and a 'Fields' section with checkboxes for 'Input By Date Time', 'Authorized By Date Time', 'Modification Number', 'Authorized', and 'Open'.

In this screen, you maintain a list of holidays of the Clearing House with which your bank is associated with.

29.1.2 Steps to Define Clearing House Holidays

To define Clearing House holidays for a year, (for instance, for 2000) you have to do the following:

Building the calendar for the year

Step 1

Click new icon.

Step 2

Enter the year — 2000 or move to the year 2000 using the arrows.

Step 3

To build the calendar for the year, 2000 click the 'Refresh' button. This button is called the 'refresh / build up' button because it builds the calendar for you. Please note:

- Your clearing house can be identified with the name -- SYS, given to it by the Oracle FLEXCUBE system. This is displayed in the field 'Clearing House'
- Saturdays and Sundays are marked as weekly holidays for the Clearing House. This is the default setting of the system
- For identification, the working days are marked in black and the holidays in red
- All unauthorised records appear against a blue background. On authorisation of that record the background disappears

29.1.3 Defining Clearing House Holidays

To define an additional holiday, click the particular date which you need to be considered as holiday. The system will mark that date as a holiday. The system will change the color of the date to red.

If you click a date that is already marked as a holiday, the system will clear the holiday and treat that date as a working day. The color of the date text is changed to black, indicating that it is no more a holiday.

29.1.4 Designating Unexpected Holidays for Clearing House

The holiday calendar for your clearing house is maintained in the Clearing House Holiday Calendar screen

In addition to the holiday calendar, you may need to designate certain days as holidays unexpectedly, without forewarning. Alternatively, you may also need to roll back a previously defined holiday date or set of dates. You can do this using the 'Unexpected Clearing House Holiday Maintenance' screen.

You can invoke this screen by typing 'CGDCGHOL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

In this screen, for a clearing house, you can maintain a range of dates, every date within which will be designated as holidays for the clearing house. You can also provide a reason for the designation.

Every unexpected holiday you designate must be authorized for it to be effective

29.1.4.1 **Reversing Designated Holiday**

In the Unexpected Holiday Maintenance screen, you can also reverse a designated holiday before the actual date. Specify the holiday date in the Holiday Date field, and check the Reverse box field alongside it.

When you designate unexpected holidays, any bank or customer value dates for clearing transactions, that coincided with the holiday are rolled forward. Any accounting entries passed are reversed and fresh entries are passed to reflect the new value date.

Note

For the release of uncollected funds, the original transaction date is considered for availability calculations.

30. Document Maintenance

Before opening an account, the customers are expected to furnish the documents to the bank.

The following sections in this chapter discusses about the type of document to be submitted and the document checklist to be maintained.

This chapter contains the following sections:

- [Section 30.1, "Document Type Maintenance"](#)
- [Section 30.2, "Document Checklist Maintenance"](#)

30.1 Document Type Maintenance

This section contains the following topics:

- [Section 30.1.1, "Maintaining Document Type"](#)
- [Section 30.1.2, "Viewing Document Type Details"](#)

30.1.1 Maintaining Document Type

You can maintain the various document types in the 'Document Type Maintenance' screen. To invoke this screen, type 'CSDDOCTY' in the field at the top right corner of the Application toolbar and click the adjoining arrow button.

Document Maintenance

New

Document Category *

Document Description

Document Type

1 Of 1 Go

Document Type *	Document Type Description
-----------------	---------------------------

Maker ADMINUSER3 Date Time: 2014-01-01 08:51:09 Mod No 2 Record Status Closed

Checker ADMINUSER3 Date Time: 2014-01-01 08:51:09 Authorization Authorized Status

Ok Exit

Specify the following details:

Document Category

Specify the document category. The adjoining option list displays all the document categories that are maintained in the system. You can select the appropriate one.

Document Type

Specify the type of document.

Document Description

Specify a brief description for the document.


Note

The system generates a notification on authorization of any modification, addition or deletion of document details in this screen.

30.1.2 Viewing Document Type Details

You can view the document type details in the 'Document Type Summary' screen. To invoke this screen, type 'CSSDOCTY' in the field at the top right corner of the Application toolbar and click the adjoining arrow button.

The screen is as shown below:



You can query on records based on any one or all of the following criteria:

- Authorization Status
- Record Status
- Document Type
- Document Category
- Document Description

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Document Type
- Document Category
- Document Description

30.2 Document Checklist Maintenance

This section contains the following topics:

- [Section 30.2.1, "Maintaining Document Checklist Details "](#)

- [Section 30.2.2, "Viewing Document Type Details"](#)

30.2.1 Maintaining Document Checklist Details

You can maintain the various document checklist details in the 'Document Checklist Maintenance' screen. To invoke this screen, type 'CSDDOCHK' in the field at the top right corner of the Application toolbar and click the adjoining arrow button.

The screenshot shows the 'Document Reference' application window with a 'New' form. The form includes the following fields and values:

- Process Code ***: BASE
- Stage ***: ACDABLQY
- Document Details**:
 - Navigation: 1 Of 1, Go, +, -, ...
 - Document Category ***: CAPACITY
 - Type ***: 3 months salary slip
 - Mandatory**: Mandatory (dropdown menu)

The bottom status bar contains the following information:

Maker: SHUBHAM01	Date Time: 2014-01-04 11:33:41	Mod No: 1	Record Status: Open
Checker: SHUBHAM01	Date Time: 2014-01-04 11:33:41	Authorization: Authorized	Status: Status

An 'Exit' button is located in the bottom right corner of the status bar.

Specify the following details:

Process Code

Specify the process code. The adjoining option list displays the process codes that are maintained in the system. You can select the appropriate one.

Stage

Specify the stage in which you need to maintain the checklist details.

Document Category

Specify the document category. The adjoining option list displays all the document categories that are maintained in the system. You can select the appropriate one.

Document Type

Specify the type of document.

Mandatory

Indicates whether the document is needed for checklist.

30.2.2 Viewing Document Type Details

You can view the document type details in the 'Document Checklist Summary' screen. To invoke this screen, type 'CSSDOCHK' in the field at the top right corner of the Application toolbar and click the adjoining arrow button.

The screenshot shows a web application window titled 'Summary'. At the top, there are three tabs: 'Search', 'Advanced Search', and 'Reset'. Below the tabs, there are two search criteria fields: 'Authorization Status' and 'Record Status', each with a dropdown arrow. To the right of these fields is a 'Process Code' input field with a magnifying glass icon. Below the search fields, there is a 'Records per page' dropdown set to '15', a '1 Of 1' indicator, and a 'Go' button. The main area of the window is a table with four columns: 'Authorization Status', 'Record Status', 'Process Code', and 'Stage'. The table is currently empty. At the bottom right of the window, there is an 'Exit' button.

You can query on records based on any one or all of the following criteria:

- Authorization Status
- Record Status
- Process Code
- Stage

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Process Code
- Stage

31. Configuring Overrides

The system displays messages in respect of errors that occur when you execute operations during a work session, in any module. These error messages are also displayed in respect of automatic or batch processes, such as end of day processes.

Depending upon your requirements at your installation, you might require some of the errors to be ignored, and others to result in an override being sought from the user for the operation to proceed. For still others, you might require an online authorization for the operation to proceed. Accordingly, the implementers at your installation configure the sensitivity of such errors. Subsequently, you might also need to configure errors to suit your requirements.

This chapter contains the following sections:

- [Section 31.1, "Types of Overrides"](#)
- [Section 31.2, "Override Maintenance"](#)

31.1 Types of Overrides

In Oracle FLEXCUBE, you can assign a level of sensitivity to each override that arises or occurs during system operation. This level of sensitivity that you assign to an override indicates the action that will result when that specific override occurs. Accordingly, you can assign any of the following sensitivity levels to an override:

Ignore

This would mean that no override message would be displayed and the exception would be ignored

Override

This sensitivity indicates that an override message should be displayed, seeking confirmation from the user. If the user confirms or accepts the override, processing of the transaction would proceed; if not, the exception would have to be corrected before transaction processing can proceed.

For such overrides, you can assign an additional parameter to indicate whether an online authorization is required if the override is accepted. If you have assigned online authorization to be required, then, for transactions involving such overrides, an online authorization is requested as a mandatory procedure. The online authorization limit specified for the authorizer would be checked during authorization, in addition to the time level of the authorizer, which should be greater than the user who is input the transaction.

For such overrides, if you have specified that no online authorization is required, the user can accept the override, and it will not require any online authorization.

Error

This would indicate that, when an exception occurs, an override message would be displayed, and the transaction cannot be processed further, that is, it would stop being processed until the exception is corrected.

Online Authorization

This would indicate that an override message would be displayed, seeking confirmation from the user. However, in this case, online authorization would be required as a mandatory procedure, if the override were accepted.

Dual Authorization

This would indicate that an override message would be displayed, seeking confirmation from the user. However, in this case, online authorization would be required as a mandatory procedure, if the override were accepted. Also, at least two authorizers would be needed to authorize the transaction.

Override Types for Batch Functions

For exceptions occurring during execution of automatic or batch processes, you can assign the Ignore, Override or Error sensitivities.

31.2 Override Maintenance

This section contains the following topics:

- [Section 31.2.1, "Maintaining Overrides"](#)
- [Section 31.2.2, "Maintaining Error Messages"](#)

31.2.1 Maintaining Overrides

In the 'Overrides Maintenance' screen, all the error messages that would appear in each module, with their respective error codes, are displayed. The functions, with respect to which the error messages could be encountered, are also displayed. You can invoke this screen by typing 'CSDOVDME' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Maker	Date Time:	Mod No	Record Status
Checker	Date Time:		Authorization Status

In the Type field, you can specify, for each error message, the appropriate sensitivity level – Ignore, Override, Error, Online Authorization or Dual Authorization.

For error messages in respect of automatic or batch functions, you can specify the appropriate level in the Batch Type field – Ignore, Override or Error.

For certain overrides, (to which you have assigned the level Override, Online Authorization or Dual Authorization), you can indicate whether the authorizer must also confirm the override, by checking the Confirm box.

You can configure an override to be displayed at the Contract and Maintenance level, if the default interest rate is modified at the Product level for Term Deposit and Retail Loan. The system displays overrides during subsequent modifications of interest rate. You can also configure overrides for Dual Authorization to be displayed at Contract and Maintenance level.

Note

You can make changes to configurable overrides in the Error Codes Maintenance screen only after consulting the support team at your installation.

31.2.2 Maintaining Error Messages

According to the requirements of your bank, you can configure the system to display an error message if you have not opted for batch balancing at the time of opening a batch.

This is indicated in the 'Overrides Maintenance' screen before opening a batch.

You can invoke the 'Overrides Maintenance' screen by typing 'CSDOVDME' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Fields							
Maker		Date Time:		Mod No		Record Status	
Checker		Date Time:				Authorization Status	

According to your instructions in the 'Overrides Maintenance' screen, Oracle FLEXCUBE will either:

- Display an error message if balancing is not allowed at the time of opening a batch (system will allow you to enter the details of the journal entry only if the option 'Balancing' is checked)
- Display an override message reminding that the batch that has been opened will not be balanced (even if the option 'Balancing' is unchecked, system will display an override and allows you to proceed further and enter the journal entry details)
- Ignore your selection for the option 'Balancing'. System will not display an error message or override irrespective of your selection for the option 'Balancing' and you can proceed to enter the details of the journal entry in the 'Journal Entry' screen.

According to the requirements of your bank, indicate your option (Error, Override, or Ignore) for the error code DEBATBAL-1.

Depending on your selection in the 'Overrides Maintenance' screen for the error code DEBATBAL-1, system will either display an error message or an override message or will just ignore your selection for the option 'Balancing'.

In the 'Overrides Maintenance' screen, if you have indicated the 'Type' as 'Error' and if you don't opt for 'Balancing', system will display an error message as "The batch is not balanced".

and 'Balancing' is automatically checked. In other words, it is mandatory to opt for balancing. This is to ensure that all batches that are opened to post entries are balanced.

If you have indicated the Type as 'Override' and you haven't checked the option 'Balancing' system will display an override message as "The batch is not balanced. Do you want to proceed? Yes/No".

You can proceed to enter the details of the journal transaction if you select 'Yes'.

If you have opted for 'Ignore' in the 'Error Codes Maintenance' screen, irrespective of whether you opt for balancing of batches or not, system will allow you enter the details of the journal transaction in the 'Journal Entry' screen (system will not display an error message or an override).

31.3 Maintaining Conversion Overrides

In the 'Overrides Conversion Maintenance' screen, you can maintain the conversion error codes for the override error code. You can invoke this screen by typing 'CSDOVCNV' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Overrides Conversion Maintenance

New Enter Query

Error Code * Description

Override

1 Of 1 Go

Branch Code	Function Id	New Error Code *	Source Code
-------------	-------------	------------------	-------------

Maker Date Time: Mod No Record Status
Checker Date Time: Authorization Status Exit

You can enter the following details:

Error Code

Specify the error code. Alternatively you can select the code from the list.

Description

The error code description will be displayed based on the error code created in the 'Overrides Maintenance' screen.

Branch Code

Specify the branch code. Alternatively, you can select the code from the list. If ALL is specified, in all the branches the conversion will be done. However if it is maintained for a specific branch, only in that branch the conversion will be done.

Function Id

Specify function Id for which the override should be treated as error. Alternatively, you can select the Function Id from the list.

Source Code

Specify the source code. Alternatively, you can select the source code from the option list. The list displays all valid source codes maintained in the system.

New Error Code

You can map an already existing error code as the conversion error code or you can define the same. Specify the new error code.

You are not allowed to maintain/map conversion error codes for the error code which is a conversion error-code.

Note

- If you encounter overrides while processing, the system will check if any conversion error code mapped for the override for the combination of branch and function Id. If available then the system will raise the mapped error code instead of the original error code.
 - The system will allow you to map conversion codes only for the error codes with type as 'Override'.
 - If a modifiable error code is changed from 'Override' to 'Error', then the system will delete all the conversion error codes maintained for the same.
 - Configuration of till related overrides and overrides maintained in 'Function Workflow Definition Detail' (STDWFDEF) screen as information message is not supported.
-

32. Other Maintenances

In order to improve the performance of the system during online or batch processes, you can install some features on need basis on the system. This chapter explains the process of installing features.

This chapter contains the following sections:

- [Section 32.1, "Feature ID Maintenance"](#)
- [Section 32.2, "Feature Maintenance"](#)
- [Section 32.3, "Category Maintenance"](#)
- [Section 32.4, "Exposure Type Maintenance"](#)
- [Section 32.5, "Group Maintenance"](#)
- [Section 32.6, "Haircut Maintenance"](#)
- [Section 32.7, "Location Maintenance"](#)
- [Section 32.8, "Static Type Maintenance"](#)
- [Section 32.9, "Unique Identifier Maintenance"](#)
- [Section 32.10, "Replication Mode Maintenance"](#)
- [Section 32.11, "Local Collateral Maintenance"](#)
- [Section 32.12, "Customer Limit Details"](#)
- [Section 32.13, "Product UDF Mapping"](#)
- [Section 32.14, "GL Mask Maintenance for Multitenant Deployment"](#)

32.1 Feature ID Maintenance

This section contains the following topics:

- [Section 32.1.1, "Maintaining Feature ID"](#)
- [Section 32.1.2, "Fields Button"](#)
- [Section 32.1.3, "Viewing Feature ID Summary"](#)

32.1.1 Maintaining Feature ID

You can maintain required features using the 'Feature ID Maintenance' screen. You can invoke this screen by typing 'CSDFEMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Feature Id

New

Enter Query

Branch Code * AT1

Branch Description FLEXCUBE UNIVER

Feature Id * ACCOPENADV

Installed

Fields

Maker PAYM_C	Date Time: 2014-01-01 01:27:04	Mod No 1	Recorder
Checker PAYM_C	Date Time: 2014-01-01 01:27:04		Auth

You can specify the following details:

Branch Code

Specify the branch where the feature needs to be installed. The adjoining option list displays all valid branch codes maintained in the system. You can select the appropriate one.

Branch Name

The branch name is displayed here based on the chosen branch code.

Feature Id

Specify the feature that should be installed in the branch. You can also choose any of the following values from the adjoining option list:

Feature Id	Description	Mode - Online/Batch
ACCRESTR	Account Restriction feature which need to be enabled for replace amounts in overrides with wild char (*)	Online
ACSTHAND	Account Statement Handoff during EOD	Batch
APY	Movement of Annual Percentage Yield to history	Batch
CCYPOS	CCY position entries updation during EOD	Batch
CUSTMIS	building of Customer MIS details Transaction/Composite/Fund	Online

DDRECLOG	During Demand Draft creation - update of record log and field log	Online
DEFERLIQ	IC Deferred Liquidation	Batch
DORMUPD	Dormancy update during EOD	Batch
DRINTDUE	Dr. Interest Due	Batch
FCTDSTATS	Financial cycle wise account statistics update	Batch
GLCUSTSTATS	Period/Financial cycle wise customer GLs statistics update	Batch
GLFCTDSTATS	Financial cycle wise GL statistics update	Batch
GLPTDSTATS	Period wise GL statistics	Batch
ICINTSTMT	IC Interest Statement generation	Batch
ICRATECHG	Rate change Advice	Batch
IRASTMT	IRA Statement generation during EOD	Batch
LDSTMT	Loan Statements generation during EOD	Batch
LINKSTMTAC	Update of Previous Statement Date and No during statement generation	Batch
PRODTXNREST	Product and Transaction code restrictions applicability	Batch
PTDSTATS	Period wise account statistics update	Batch
RAC	Account entry serial number derivation logic when multiple FCUBS instances exists	Online/Batch
REGCC	Regulatory CC update for customer account during EOD	Batch
TRACKACCRINT	Tracking of Accrued interest	Batch
USREGCHGS	US Regulatory changes	Batch
VDBALINIC	VD balance update. This is equivalent to flag at bank parameters level	Online
PARTCHKPAY	Partial cheque payment feature	Online

Installed

Check this box to indicate that the feature should be installed in the branch.

Click save icon in the Application tool bar to save the changes.

32.1.2 Fields Button

All User Defined Fields (UDFs) linked to the function ID 'CSDFEMNT' are displayed in the 'User Defined Fields' screen. Invoke this screen by clicking 'Fields' button on the 'Feature ID Maintenance' screen.

The screen is as shown below:

Field Name *	Value	Value Description
--------------	-------	-------------------

Here you can specify values for each UDF.

Refer the User Manual titled 'User Defined Field' for details about defining UDFs.

32.1.3 Viewing Feature ID Summary

You can view summary of all feature IDs installed across branches, using the 'Feature ID Summary' screen. To invoke this screen, type 'CSSFEMNT' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

The screen is as shown below:

You can query on records based on any one or all of the following criteria:

- Authorization Status
- Record Status
- Branch Code
- Feature ID
- Installed

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Branch Code
- Feature ID
- Installed

Double click on a record to invoke the detailed screen for that record.

32.2 Feature Maintenance

This section contains the below topic:

- [Section 32.2.1, "Maintaining Feature"](#)

- [Section 32.2.2, "Fields Button"](#)

32.2.1 Maintaining Feature

You can maintain required features using the 'Feature Maintenance' screen. You can invoke this screen by typing 'CSDFTRMN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Feature Maintenance' application window. At the top, there's a title bar with standard window controls. Below it, a 'New' button is on the left, and an 'Enter Query' text field is on the right. Under the 'Enter Query' field, there's a label 'Feature *' and a checkbox labeled 'Applicable'. The bottom of the window features a 'Fields' section with a table. The table has five columns: 'Maker', 'Date Time', 'Mod No', 'Record Status', and 'Authorization Status'. An 'Exit' button is located to the right of the table.

Maker	Date Time	Mod No	Record Status	Authorization Status
Checker	Date Time:			

Specify the following details:

Feature

Specify the feature that you need to query.

Applicable

The system defaults this check box when you execute the query with the feature name.

32.2.2 Fields Button

All User Defined Fields (UDFs) linked to the function ID 'CSDFTRMN' are displayed in the 'User Defined Fields' screen. Invoke this screen by clicking 'Fields' button on the 'Feature Maintenance' screen.

For more information on UDF refer to the 'User Defined Field' User manual

32.3 Category Maintenance

You can maintain categories using the 'Category Maintenance' screen. You can invoke this screen by typing 'CODCATGY' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The 'Category Maintenance' screen is shown below:

Category Maintenance

New

Category *

Description

Fields

Maker	Date Time:	Mod No	Record Status
Checker	Date Time:		Authorization Status

Exit

You can specify the following here:

Category Name

Specify the category name.

Description

Enter a brief description of the category.

After entering the details, click the 'Save' button.

32.4 Exposure Type Maintenance

You can maintain exposure types using the 'Exposure Type Maintenance' screen. You can invoke this screen by typing 'CODEXPTY' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The 'Exposure Type Maintenance' screen is shown below:

Exposure Type Maintenance

New

Exposure Code *

Description

Fields

Maker
Checker

Date Time:
Date Time:

Mod No

Record Status
Authorization
Status

Exit

You can specify the following here:

Exposure Name

Specify the exposure name.

Description

Enter a brief description for the exposure.

After entering the details, click the 'Save' button.

32.5 Group Maintenance

You can invoke the 'Group Maintenance' screen by typing 'CODGROUP' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The 'Group Maintenance' screen is shown below:

Static Types Maintenance

New

Type *

Type Name *

Type Value

Fields

Maker	Date Time:	Mod No	Record Status
Checker	Date Time:		Authorization Status

Exit

You can specify the following here:

Type Name

Specify the type name.

Type Value

Specify the type value.

After entering the details, click the 'Save' button.

32.6 Haircut Maintenance

You can invoke the 'Haircut Maintenance' screen by typing 'CODHCUTT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The 'Haircut Maintenance' screen is shown below:

Fields			
Maker	Date Time:	Mod No	Record Status
Checker	Date Time:	Authorization Status	

You can specify the following here:

HairCut Name

Specify the haircut name.

Description

Enter a brief description for the haircut.

After entering the details, click the 'Save' button.

32.7 Location Maintenance

You can maintain the location details using the 'Location Maintenance' screen. You can invoke this screen by typing 'CODLOCCD' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The 'Location Maintenance' screen is shown below:

Fields					
Maker	Date Time:	Mod No	Record Status		
Checker	Date Time:		Authorization Status		

You can specify the following here:

Location Code

Specify the location code.

Description

Enter a brief description for the location.

After entering the details, click the 'Save' button.

32.8 Static Type Maintenance

You can maintain different type of channels in the 'Static Type Maintenance' screen. You can invoke the 'Static Type Maintenance' screen by typing 'CODTYPES' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The 'Static Type Maintenance' screen is shown below:

Static Types Maintenance

New

Type *

Type Name *

Type Value

Fields

Maker	Date Time:	Mod No	Record Status
Checker	Date Time:		Authorization Status

Exit

You can specify the following here:

Type

Specify the static type.

Type Name

Specify the type name.

Type Value

Specify the type value.

After entering the details, click the 'Save' button.

32.9 Unique Identifier Maintenance

You can maintain the unique identifier details in the 'Unique Identifier Maintenance' screen. You can invoke this screen by typing 'CODUIDN' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The 'Unique Identifier Maintenance' screen is shown below:

Fields			
Maker	Date Time:	Mod No	Record Status
Checker	Date Time:	Authorization Status	

You can specify the following here:

Unique ID Name

Specify the Unique ID name.

Description

Enter a brief description for the Unique ID.

After entering the details, click the 'Save' button.

32.10 Replication Mode Maintenance

You can invoke the 'Replication Mode Maintenance' screen by typing 'CODELREP' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The 'Replication Mode Maintenance' screen is shown below:

Replication Mode Maintenance

New

LBL_SOURCE_CODE*

Replication Type: Synchronous

Replication URL

Replication Queue

Remarks

Maker	Date Time:	Mod No	Record Status
Checker	Date Time:	Authorization Status	Exit

Click the Enter Query button to enter the following query criteria.

Source Code

Specify the source code for which you are maintaining the replication mode. Select the appropriate one from the option list

Replication Type

Select the replication type. Select one of the following:

- Synchronous
- Asynchronous

Replication URL

Specify the replication URL.

Replication Queue

Specify the replication queue.

Remarks

Enter the remarks, if any.

32.11 Local Collateral Maintenance

You can maintain local collateral details in 'Local Collateral Maintenance' screen. You can invoke this screen by typing 'STDCOLAT' in the top right corner of the Application toolbar and clicking the adjoining arrow button.

Local Collateral Maintenance

New Enter Query

Collateral Code *

Collateral Description

Collateral Currency

Collateral Value

Start Date YYYYMM-DD

End Date YYYYMM-DD

Branch Code

Customer No *

Liability No *

Taken Over

PPC Collateral

Collateral Type

Source Code

Available Amount 0

Utilized Amount 0

Blocked Amount 0

Linkage

Maker Date Time: Mod No Record Status

Checker Date Time: Authorization Status

Exit

You can specify the following details in this screen:

Collateral Code

Specify the collateral code.

Collateral Description

Give a brief description of the collateral here.

Collateral Currency

Specify the currency in which the Collateral has to be maintained. Once authorized you cannot change this entry.

Collateral Value

The collateral value depends on whether the security is Market Value based or Non-Market Value based.

If it is market value based then the collateral value is calculated as shown in the following examples.

Example

Input in case of a nominal quoted security:

Nominal Amount	Price Code	Market Price	Collateral Value [(Market price/100) * Nominal Amount]
10,00,000	BOM1	65	(65/100) * 10,00,000=650000
5,00,000	BOM2	70	(70/100) * 5,00,000= 350000
7,00,000	BOM3	80	(80/100) * 7,00,000= 560000

Input in case of a unit quoted security:

Number of Units	Price Code	Market Price	Collateral Value (Number of Units x Market price)
65	BOM1	120	7800
70	BOM2	130	9100
40	CAL1	95	3800

If it is Non-Market Value based then the user has to enter the collateral value manually.

When there is a linkage available for Bank Guarantee/ Standby LC and the linkage currency is different from the Local Collateral Currency, the Collateral Value will be derived based on the Account Contribution in linkages with the Collateral Currency.

Example

Linkage Currency	Contract Contribution (in Linkages)	Collateral Currency	Collateral Value
GBP	5000	USD	3000

Start Date and End Date

Specify the tenor of the collateral using the Start Date and End Date fields. The collateral is considered effective only during this period.

Branch Code

The system displays the branch code.

Customer No

Specify the customer number. Alternatively, you can select the customer number from the option list. The list displays all valid values.

Liability No

Collaterals issued have to be linked to a liability. Specify the liability Number for which the collateral is linked.

Taken Over

Taken Over collateral is checked if the collateral linked to CI/CL account is taken over.

PPC Collateral

Check this box to link the collateral to project finance.

Collateral Type

Indicate the type of collateral - Property, Vehicle, Marketable Securities, Plant & Machinery, Term Deposit & Transaction Account, Precious Metal, Bank Guarantee, Miscellaneous, and Policy.

Source Code

Specify the source code. Alternatively, you can select the source code from the option list. The list displays all valid values.

Available Amount

The system defaults the available amount for the collateral, on save of the collateral record.

Utilized Amount

The system displays the utilized amount.

Block Amount

When the collateral is linked to the collateral pool, the system computes and displays the amount to be blocked. The blocked amount is computed based on the linked percentage or linked amount specified when a collateral is linked to a Collateral Pool.

32.11.1 Linkage tab

Click the Linkage tab at the bottom of the page to view the Linkage page.

Local Collateral Maintenance

Linkage

Linkage

1 Of 1

Go

Account Type	Contract Reference *	Branch	Currency	Account Balance	Contract Contrib
Bank Guarantee					

Bank Guarantee

Standby LC

Ok Cancel

You link the Bank Guarantee or the Stand-By LC from the Linkage tab. •

If collateral type is 'Bank Guarantee', then there should be one linkage of Bank Guarantee or Standby LC.

Enter the details for the following fields:

Account Type

The type of account. It is either Bank Guarantee or Stand-by LC.

Contract Reference

The list which shows the active reference number for the selected account type.

A collateral can be linked either with a single Bank Guarantee or Stand By LC's, but not both or more than one.

Branch

The branch of the selected account. It is populated from the option list of the contract reference,

Currency

The currency of the collateral. It is populated from the option list of the contract reference,

Account Balance

The account balance. It is populated from the option list of the contract reference,

Contract Contribution

Contract Contribution of linked reference is a mandatory field and the value should be same as the collateral value. This amount cannot exceed the 'Account Balance'. value

The SDE BANK_GUARANTEE_AMT returns the value of linked amount in case if the linked collateral is of type 'Bank Guarantee'. Based on the rule and formula. the same amount is used for provisioning computation. The BANK_GUARANTEE_AMT will be zero if the linked Bank Guarantee or Standby LC has expired during provisioning computation.

32.12 Customer Limit Details

You can query the liability details, local facility and local collateral details of a customer using 'Customer Limit Details' screen. You can invoke this screen by typing 'STDLMBAL' in the top right corner of the Application toolbar and clicking the adjoining arrow button.

The screenshot shows the 'Customer Limit Details' application window. It features a search section with fields for 'Customer No *', 'Customer Name', and 'Branch Code'. Below this, there are sections for 'Liability Details' (with 'Liability Currency' and 'Liability Number' fields) and 'Facility Details' (with a table for facility information). The 'Facility Details' table has columns: Limit Reference, Availability, Facility Type, Line Currency, Effective Line Amount, Utilized Amount, and Available Amount. Below the facility table is a section for 'Collateral Details' with a table for collateral information. The 'Collateral Details' table has columns: Collateral Code, Collateral Currency, Collateral Description, Collateral Contribution, Collateral Value, Utilized Amount, and Available Amount. An 'Exit' button is located at the bottom right of the window.

You can view the following details in this screen based on the customer number selected:

Customer No.

Specify the customer number. Alternatively, you can select the customer number from the option list. The list displays all valid customer numbers maintained in the system.

Click 'Execute Query' to view the following liability, local facility and local collateral details.

- Customer Name
- Branch Code
- Liability Details
- Liability Currency
- Liability Number
- Facility Details
- Limit Reference
- Availability
- Facility Type
- Line Currency

- Effective Line Amount
- Utilized Amount
- Available Amount
- Blocked Amount
- Revolving Amount
- Matured Util
- Start Date
- Expiry Date
- Collateral Code
- Collateral Currency
- Collateral Description
- Collateral Contribution
- Collateral Value
- Utilized Amount
- Available Amount
- Blocked Amount
- Start Date
- End Date

32.13 Product UDF Mapping

You can maintain all User Defined Fields (UDFs) linked to the product code in the 'Product UDF Mapping' screen. You can invoke this screen by typing 'CSDPDUDF' in the top right corner of the Application toolbar and clicking the adjoining arrow button.

The screenshot shows the 'Product UDF Mapping' application window. At the top, there's a title bar and a menu bar with 'New' and 'Enter Query'. Below the menu bar, there are two input fields: 'Product Code *' and 'Product Description'. A 'Fields' section is present, which includes a table with columns 'Field Number' and 'Field Name'. The table is currently empty. At the bottom of the window, there is a 'Change Log' section with fields for 'Maker', 'Checker', 'Date Time', 'Mod No', 'Record Status', and 'Authorization Status'. An 'Exit' button is located in the bottom right corner.

Product Code


Specify the product code for product UDF mapping. Alternatively, you can select the product code from the list.

Field Name

Specify the field name. Alternatively, you can select the field name from the list.

32.14 GL Mask Maintenance for Multitenant Deployment

You can define structure for the General Ledgers in the Chart of accounts in the 'Multi Tenant Parameter' screen. The maintenance should be used for GL mask maintenance in a multi tenant deployment. Otherwise the mask maintained in bank parameter will be taken. You can invoke the 'Multi Tenant Parameter' screen by typing 'CSDMULPM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



General Ledger Mask

This is the structure for the General Ledgers in the Chart of accounts . It can comprise of a maximum of 9 characters. It can be built using a combination of numbers and letters to indicate for instance, category of the GL - asset, liability etc., GLs hierarchical position and so on.

To define the structure, use n for numbers and a for alphabets. The last character would be a D or d, which indicates a check digit generated by the system. For a numeric check digit define it as d ; for an alphanumeric check digit define it as D.

You may use the following punctuations in the GL mask:

- Dash (-)
- Comma (,)
- Asterisk (*)
- Full Stop (.)
- Forward slash (/)

Example

You wish to create a two level GL structure for your bank. You could define the first two characters of the GL to represent the category asset, liability etc., aa; the next two characters, nn, to represent the first level GL; and the next three characters, nnn, to represent the second level GL. A GL based on the given structure would read as AS01001 where AS represents the GL category - asset; 01 represents the first level GL; 001 represents the second level GL.

For creating this structure you would define your GL mask as - aannnnn d/D . If you want to define your second level GL with a 4 digit numeric code instead of 3; other parameters remaining the same your mask would read as aannnnnn d / D.

32.14.1 Viewing Multi Tenant Parameter Summary

You can view the GL mask details using 'Multi Tenant Parameter Summary' screen. You can invoke this screen by typing 'CSSMULPM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Multi Tenant Parameter Summary

Search Advanced Search Reset Clear All

Case Sensitive

Authorization Status Record Status

General Ledger Mask

Records per page 15 1 Of 1 Go Lock Columns 0

Authorization Status	Record Status	General Ledger Mask
----------------------	---------------	---------------------

Exit

This summary screen can be used to search GL mask details for any of the following criteria:

- Authorization Status
- Record Status
- General Ledger Mask

For each record fetched by the system based on your query criteria, the following details are displayed:

- Authorization Status
- Record Status
- General Ledger Mask

33. Support 24x7

Oracle FLEXCUBE is available on a 24x7 basis for two broad channels Web service & Web Branch. During EOD batch process, transactions are tanked and then get processed after the batch is completed.

This document details about the 24x7 support feature in FCUBS.

This chapter contains the following topics:

- [Section 33.1, "Gateway Messaging"](#)
- [Section 33.2, "Web Branch"](#)
- [Section 33.3, "Batch Processing "](#)
- [Section 33.4, "Processing Different Categories During EOD"](#)

33.1 Gateway Messaging

Oracle FLEXCUBE processes the following channel transactions, 24x7:

- FLEXCUBE UBS - Gateway - Web service
 - Customer (New, Modify, Close)
 - Customer Account (New, Modify, Close)
 - Consumer Loans

All new requests for maintenance functions or online functions when the branch available status is 'No' are accepted at the Gateway messaging layer. The Gateway messaging layer does not route the transaction requests during the Date Change Window.

33.2 Web Branch

Oracle FLEXCUBE processes the following channel transactions, 24x7:

- FLEXCUBE UBS - Retail Web Branch UI
 - Retail Teller
 - Instruments
 - Clearing
 - Utility Payments
 - Retail Loan

33.3 Batch Processing

Every day while processing a channel transaction, system checks for the branch availability status. The system displays the Branch Available status. If the status is 'Yes', it indicates that the branch can accept transactions for the day and if the status is 'No', then it indicates that the transactions will be accepted but it will be in effect only from the next business day.

Accordingly accounting entries will be passed checking the following, for tanking branch transactions:

- The Branch Available Status
- The Branch date and host date i.e. entries will be tanked if branch date is ahead of host date

When the Branch Available status is 'NO' or if branch date is ahead of host date, then the transactions will be tanked. These transactions will be untanked by the BOD program which runs post date change i.e. POSTDTCH.

The branch available status can be changed from Yes to No in two ways.

- Auto
 - At the start of EOTI if the branch available status is not 'No'.
 - At the start of ICEOD if the branch available status is not 'No'.
 - At the start of EOFI if the branch available status is not 'No'.
 - Drop of End of Transaction Input
 - System Date Change
- Manual
 - Manual – Scheduling and Execution as EOD batch.

IC EOD Process

The account resolution during IC EOD process excludes accounts that are with account creation status as Tanked.

Drop - End of Transaction Input (EOTI)

If the branch is not available during the Drop End Of Transaction Input, system automatically resets the Branch available status to 'Yes'. Also all the tanked transactions and accounting entries are released.

All transactions that are tanked would be released with tanked status as No and advices and payment messages if suppressed would be generated.

For the process that started when the branch available status was Yes, then the Status change to 'No' cannot be changed till the completion of the process. This is applicable for DE Batch upload process.

33.4 Processing Different Categories During EOD

During EOD batch process, the categories like maintenance and financial transaction process are explained below.

33.4.0.1 Processing Maintenance

The maintenance process includes:

- New Customer Creation
- Customer Amendment
- Customer Closure
- New Account Creation
- Account Amendment
- Account Closure

Creating Customers

While creating customer if the branch available status is no, then the creation date gets set to next branch working date. The customer details report requests are accepted and the processing of the same starts only during the next branch available status. The report would include the customer creation date also.

Creating Customer Accounts

The customer account creation requests are processed with the tanked status as 'Yes' if the branch is not available for transaction and these accounts are not considered for Interest & Charges calculation process

After the branch is available after the date change process, tanked status gets changed to 'No' and initiation entries of term deposit that are tanked are released with transaction date moved to next working date.

Processing TD Account Creation

The Term Deposit creation requests are processed with the tanked status as 'Yes' if the branch is not available for transaction. If the customer account is displaying as tanked, it indicates that the customer account creation request was processed when the branch available status is No or when branch date was ahead of host date.

The process when the TD account creation is received when the branch is unavailable or when branch date is ahead of host date is as follows:

- The TD account creation would be accepted with transaction status as Tanked.
- The initiation accounting entries will be posted as tanked entries.

The Term Deposit accounts that are in tanked status will not be considered for Interest & Charges calculation process.

After the branch available status is changed to 'Yes' then:

- The TD account tanked status will set to No.
- The Initiation entries of term deposit that are tanked would be released with transaction date moved to next working date.

Processing TD Account Redemption

The Term Deposit Redemption Transactions are processed partially if the branch is not available for transaction or when branch date is ahead of host date. Partial Redemption of the account is processed even after branch available status is 'No' or branch date is ahead of host date

- For TD redemption by Transfer to Savings, TD redemption by Transfer to GL, the RT Transaction done for moving the available funds will get tanked.
- For TD redemption By Bankers Cheque, the Instrument Transaction done for Issuing the BC will get tanked.

After the branch available status is changed to 'Yes' then:

- The transaction status of the TD Redemption Transaction will be changed to Active.

The tanked accounting entries if any would be un-tanked by the batch process.

Processing Account Closure

The Close out Withdrawal Transaction is not allowed if the branch is not available for transaction or when branch date is ahead of host date.

33.4.0.2 Processing transactions:

The transaction process includes:

- Retail Loan
- Retail Teller
- Instruments

- Standing Instructions
- Clearing
- Utility Payments

Processing Retail Teller Transactions

The retail teller transactions are processed with the tanked status as 'Yes' if the branch is not available for transaction. During the RT transaction query, the transaction can be viewed as tanked, if the RT transaction is tanked and that the request was processed when the branch available status is No or when branch date was ahead of host date.

The process when the RT transaction is received when the branch is unavailable or when branch date is ahead of host date is as follows:

- The RT transaction would be accepted with transaction status as Tanked.
- The accounting entries would be posted with tanked status.
- Message and advices of an RT transaction are suppressed.

After the branch available status is changed to 'Yes' then

- The transaction status of the RT transaction will be changed to Active.
- The tanked accounting entries if any would be un-tanked by the batch process for releasing the tanked accounting entries.
- The messages and the advices associated with the RT transaction that were suppressed are also generated.
- The transaction date of the RT transaction will remain unchanged during the process of un-tanking.

Processing Clearing Transactions

The clearing transactions are processed with the tanked status as 'Yes' if the branch is not available for transaction. During the clearing transaction query, the transaction can be viewed as tanked, if the CG transaction is tanked and that the request was processed when the branch available status is No or when branch date was ahead of host date.

The process when the clearing transaction is received when the branch is unavailable or when branch date is ahead of host date is as follows:

- The Clearing transaction would be accepted with transaction status as Tanked.
- The accounting entries would be posted with tanked status.

After the branch available status is changed to 'Yes' then:

- The transaction status of the Clearing transaction will be changed to Active.
- The tanked accounting entries if any would be un-tanked by the batch process for releasing the tanked accounting entries.

Processing Instrument Transactions

The instrument transactions are processed with the tanked status as 'Yes' if the branch is not available for transaction. During the DD transaction query, the transaction can be viewed as tanked, if the DD transaction is tanked and that the request was processed when the branch available status is No or when branch date was ahead of host date.

The process when the instrument transaction is received when the branch is unavailable or when branch date is ahead of host date is as follows:

- The instrument transaction would be accepted with transaction status as Tanked.
- The accounting entries would be posted with tanked status.

After the branch available status is changed to 'Yes' then:

- The transaction status of the Instrument transaction will be changed to Active.
- The tanked accounting entries if any would be un-tanked by the batch process for releasing the tanked accounting entries.

Processing Standing Instructions

The standing instructions are processed with the tanked status as 'Yes' if the branch is not available for transaction. During the standing instruction query, the instruction can be viewed as tanked, if it is tanked and that the request processed when the branch available status is 'No' or when branch date was ahead of host date.

When the instruction is received while the branch is unavailable, then the process is as follows:

- The instruction is accepted with transaction status as 'Tanked'.
- Accounting entries are posted with the status 'Tanked'.

Once the branch status is 'Available', then the following process is applicable:

- The transaction status of the instruction is changed to 'Un-tanked'
- A batch process releases the tanked accounting entries
- For all instructions whose booking date is the same as the Application date, the 'Date Change BOD Batch' of that date updates the status to 'Un-tanked'.
- The transaction date of the instruction remains the same after un-tanking.

Processing Utility Payment Transactions

The utility payment transactions are processed with the tanked status as 'Yes' if the branch is not available for transaction. During the UP transaction Query, the transaction can be viewed as tanked, if the UP transaction is tanked and that the request was processed when the branch available status is No or when branch date was ahead of host date.

The process when the utility transaction is received when the branch is unavailable or when branch date is ahead of host date is as follows:

- The UP transaction would be accepted with transaction status as Tanked.
- The accounting entries would be posted with tanked status.

After the branch available status is changed to 'Yes' then:

- The transaction status of the UP transaction will be changed to Active.
- The tanked accounting entries if any would be un-tanked by the batch process for releasing the tanked accounting entries.

The different categories which get processed during the End of the Day batch run are explained in the table below:

Maintenance/ Transactions	Branch Status – Not Available	Branch Status – Available (After date change)
------------------------------	----------------------------------	---

Customer/Account Creation	<p>The process is tanked till the branch available status is yes.</p> <p>Initiation accounting entries will be posted as tanked entries.</p>	<p>TD account status is changed from tanked to un-tanked.</p> <p>Initiation accounting entries are un-tanked and released with transaction date moved to next working date.</p>
TD Account Redemption	Processed partially	Transaction status is un-tanked and accounting entries if any would be un-tanked
Account Closure	Not Allowed	Processed normally
Retail Teller Transactions	Transaction/Accounting entries would be posted with tanked status.	Transaction/Accounting entries are un-tanked and processed.
Clearing Transactions	Transaction/Accounting entries would be posted with tanked status.	Transaction/Accounting entries are un-tanked and processed.
Instrument Transactions	Transaction/Accounting entries would be posted with tanked status.	Transaction/Accounting entries are un-tanked and processed.
Utility Payment Transactions	Transaction/Accounting entries would be posted with tanked status.	Transaction/Accounting entries are un-tanked and processed.

34. Purging Data

Purging is a process by which you remove unwanted data from the system. For example, you may find the interest rates that you have maintained for a financial cycle useless a couple of years later. You would want to remove such data from the system. You can achieve this by 'purging' the data of the system.

There are three types of purging data:

- Module Purging
- Entity Purging (User Defined)
- Subsystem Purging

This chapter contains the following sections:

- [Section 34.1, "Data Purging"](#)
- [Section 34.2, "Purge Parameter Configuration"](#)
- [Section 34.3, "Processing Ad-hoc Purge"](#)
- [Section 34.4, "Inquiring Purge Log"](#)

34.1 Data Purging

This section contains the following topics:

- [Section 34.1.1, "Module Purging"](#)
- [Section 34.1.2, "Maintaining Purge Details"](#)
- [Section 34.1.3, "Entity Purging"](#)
- [Section 34.1.4, "Defining Subsystem Purging"](#)

34.1.1 Module Purging

The purge function of Oracle FLEXCUBE allows you to purge:

- Contracts and transactions that you have entered into,
- Data relating to transactions (such as, interest rates)
- Limits history (Liability, Lines and Line Utilization history)
- GL Average Balance and Customer Account statistics

You can purge the contracts (or transactions) that you have entered into in the following modules of Oracle FLEXCUBE:

- Foreign Exchange
- Money Market
- Loans
- Deposits
- Data Entry
- Standing Instructions
- Letters of Credit
- Bills and Collections

You can purge data from the following modules:

- Accounting

- Currency
- General Ledger
- Interest and Charges
- Messaging
- MIS
- Reconciliation
- Receivable Liquidation

You can also purge data relating to transactions. For example, you can purge the currency rates that you have maintained, the messages in the messaging system of Oracle FLEXCUBE, the User Data Elements that you used to compute interest, interest statement details, user information maintained in the Security Management System of Oracle FLEXCUBE, customer information, and so on.

The system will automatically purge data according to the parameters that you define in the Purge Details Maintenance screen.

34.1.2 **Maintaining Purge Details**

In the 'Purge Details Maintenance' screen, you can define the parameters for purging data from the system. For instance, you may want to purge the contracts entered into in the previous financial cycle. Or, you may want to retain exchange rates in the system for a specific period. These are examples of parameters that you can define in the Purge Details Maintenance screen. You can invoke this screen by typing 'CSDPURGE' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Input By Date Time	Authorized By Date Time	Modification Number	Authorized	Open
			<input type="checkbox"/>	<input type="checkbox"/>

Specifying Module

In the Purge Details Maintenance screen you must first specify the module for which you are defining parameters. All parameters that you define subsequently will only apply to the module that you specify.

You can enter a description of the module for which you are maintaining purge details.

Note

For purging limits history which is Liability, Lines, and Lines Utilization history, you must specify LM as the module code. Limits history data is purged for the current branch only.

Specifying Nature of Data to be Purged

You can opt to purge contracts (of the module you specified) along the following criteria. You may either choose to purge any of the following:

- Liquidated contracts
- Closed (applicable only to the BC and LC modules)
- Reversed contracts

When you run the purge process, only those contracts that are in the status that you specified will be purged. That is, only contracts (in the module you specified) that are liquidated, closed, and/or reversed, depending on your specification, will be purged from the system.

Similarly, if you want to purge

- Exchange rates (from the Currency module), you should choose the 'None' option.
- Data from the Reconciliation module, you should choose any of the following options, depending on the data that you want to purge. The options available are:
 - System Date Relative
 - Match Relative
 - Closed Match
 - Closed External Statement

Retention Period

The retention period, as the term suggests, is the period for which data is stored in the system. For each module in Oracle FLEXCUBE, you can specify the retention period.

When you run the purge process on any given day, only the data that is beyond the retention period that you specified will be purged. The following example illustrates this concept.

For example,

The requirement: You would like to retain foreign exchange contracts that were liquidated 60 days prior to the running of the purge process, in the system. (That is, if the current system date is 30 June 1999 and you do not wish to purge the foreign exchange contracts that were liquidated between 1 May 1999 and 30 June 1999).

Solution: In the Retention Period field enter '60' (note this value is expressed in days), and in the 'Status' field choose the 'Liquidated' option.

Result: If this setup is authorised, and you run the purge process on 30 June 1999, the current system date, all foreign exchange contracts that you liquidated prior to 1 May 1999 will be purged. Contracts that were liquidated on or after 1 May 1999 will not be purged.

34.1.3 Entity Purging

In entity purging, you can archive or purge the data from the main tables and its child tables. You can also configure the purge type and the frequency of data purging.

There are 3 parts in an entity purging:

Purge Parameter Definition

The purge parameter definition is achieved through ODT. The ODT generates the purge source files which is then deployed in Oracle FLEXCUBE.

The ODT is used for the following:

- Maintaining the list of entities that need to be purged.
- Maintaining the purge behaviour.
- Maintaining the mode of purge.
- Maintaining the purge frequency.
- Maintaining the archive table suffix if the purge behaviour is to archive the data.
- Maintaining the filter criteria to determine what data to purge.
- Defining subsystem purging
- Purging bulk option for multi tables entity

You can capture the above parameters to define the entity and purge preferences.

Purge Parameter Configuration

Once the ODT generated scripts are deployed in Oracle FLEXCUBE, they can be re-configured in the purge parameter configuration.

Purge Execution

You can execute the purge in two modes:

- Batch Mode - In the batch mode you have to maintain the purge entity batch CSBPURGE. The AEOD batch process starts the purge process in which all the entities that are scheduled for purge on that day gets purged.
- Ad-hoc Mode - This mode supports purging of a single entity at any time.

You can define entities for purging in any module. However, pre-defined entities are available for the following modules:

- Accounting
- Bills and Collections
- Letters of Credit
- SWITCH

34.1.4 Defining Subsystem Purging

Subsystem purging is a method to define tables pertaining to subsystems purge entities. After defining subsystem purge entities, other module purge entities can include the defined subsystem purge entities as part of their purge definitions and link it to any main contract entity. Subsystem purging reduces duplication of effort or possible errors during definition of purge entity.

Note

You cannot execute subsystem purge entity independent of any parent purge entity.

Following are the subsystems defined as part of subsystem purging:

- MIS

- Tax
- Settlement
- Interest
- Charge
- Fees

You can also purge bulk operations for multi table using SQL bulk operators for archival or purge.

34.2 Purge Parameter Configuration

This section contains the following topics:

- [Section 34.2.1, "Configuring Purge Parameters"](#)
- [Section 34.2.2, "Branch Restrictions Button"](#)
- [Section 34.2.3, "Viewing Purge Parameter Configuration Details"](#)

34.2.1 Configuring Purge Parameters

You can configure the parameters for purging the data through 'Purge Parameter Configuration Maintenance' screen. You can query and modify entities in this screen. However new operation is not allowed. To invoke this screen type 'STDPMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The following details are captured in this screen:

Entity Id

Select the entity Id from the adjoining option list.

Purge Frequency

Select the frequency of purge from the adjoining drop-down list. The available options are:

- Ad-hoc - If the frequency is selected as Adhoc, then this particular entity will not be picked up for purging in the batch purge. This entity can be purged only by the Adhoc Purge option.
- Daily - The purge routine for the entity having daily frequency will run daily
- Weekly - The purge routine for the entity having weekly frequency will run every week. The day of the week will be determined based on the purge start date. If the purge start day is a Monday, then the purge routine runs on every Monday. If you want to change the day of the week, then 'Next Purge Date' needs to be updated.
- Monthly - The purge routine for the entity having monthly frequency will run every month. It is advised that the purge routines are not configured during the month-ends, as Purge Anniversary dates so as to reduce the processing load on the month-ends
- Quarterly - The purge routine for the entity having quarterly frequency will run every quarter.
- Half-Yearly - The purge routine for the entity having half-yearly frequency will run every 6 months.
- Yearly - The purge routine for the entity having yearly frequency will run every year.

Last Purge Date

The system displays the date on which the entity is purged.

Next Purge Date

Specify the next date for purging the entity. The system populates this date if purge frequency is not ad-hoc.

The next purge date is left blank initially. The system picks up for automatic purging of data and updates the subsequent dates only if the next purge date is provided.

Commit Frequency

Specify the commit frequency while purging the data. The default value for commit frequency is 100.

For example,

If the value is 100 (which is default), then the purge routine will commit after every 100 records.

Query

The system displays the full query for the entity.

Filter Details

Filter Name

The system displays the name of the purge filter criteria.

Column Data Type

The system displays the data type for the filter.

LHS

The system displays the LHS of the filter expression.

Operator

The system displays the operator for the filter.

RHS

The system displays the RHS or the value for the expression based on which data is purged. However RHS can be modified.

34.2.2 **Branch Restrictions Button**

Click on 'Branch Restrictions' to allow or disallow entities across branches.

Entity Id

Branch Restriction ☒ Allowed ☐ Disallowed

1 Of 1 Go

☐ Branch Code

Ok Exit

Entity Id

The system displays the entity ID.

Branch Restriction

Indicate whether the branch restriction is 'Allowed' or 'Disallowed'.

Branch Code

The system displays the branch code. However, you can add the branch codes here.

You should configure the branch restrictions as part of first time entity configurations.

34.2.3 **Viewing Purge Parameter Configuration Details**

You can view the purge parameter configuration details maintained in the 'Purge Parameter Configuration' screen using the 'Purge Parameter Configuration Summary' screen. You can

invoke this screen by typing 'STSPGMNT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

In the above screen, you can base your queries on any or all of the following parameters and fetch records:

- Authorization Status
- Entity Id
- Record Status

Select any or all of the above parameters for a query and click 'Search' button. The system displays the records meeting the selected criteria:

- Authorization Status
- Record Status
- Entity Id
- Description

34.3 Processing Ad-hoc Purge

You can process ad-hoc purge through 'Ad-hoc Purge Process' screen. An entity configured as automatic can also be started from this screen. However, this would not change the regular frequency cycle of the entity. The next purge date is not effected or changed if started from

this screen. To invoke this screen type 'AEDPGOP' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Entity Id

Select the entity ID from the adjoining option list.

Purge Frequency

The system displays the purge frequency.

Number of Threads

The system displays the number of parallel streams in which the purge should be run. However, you can modify it. The purge batch process is split into specified numbers and executed in separate threads.

Description

The system displays description on the entity ID.

Next Purge Date

The system displays the next purge date.

Last Purge Date

The system displays the last purge date.

Query

The system displays the query for the entity.

The system displays the following details:

- Filter Name - Name of the purge filter criteria
- Column Data Type - Data type of the filter
- LHS - LHS of the filter expression
- Operator - The operator for filter
- RHS - RHS or the value for the expression based on which data is purged. However, you can modify this.

Note

- Only 'Execution Filter' conditions are displayed in the Filter Condition Multi Entry Block.
 - 'Business Filter' conditions will not be displayed.
-

34.4 Inquiring Purge Log

You can inquire the purge history through the Purge Log Inquiry screen. To invoke this screen type 'AEDPGLOG' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Entity Id _____

From Date _____

To Date _____

1 Of 1

Entity Id	Run ID	Date	Start Time	End Time	Status
-----------	--------	------	------------	----------	--------

Exit

Entity Id

Select the entity Id from the adjoining option list.

From Date

Specify the date from when the log should be enquired.

To Date

Specify the date till when the log should be enquired.

The system displays the following details:

- Entity ID
- Run ID
- Date
- Start Time
- End Time
- Status
- Error
- Number of Records
- Query

35. Tanking of Maintenance Records

The maintenance records that are created or modified in the system can be tanked till they get authorized, so that it is possible to undo the modifications, if needed, before the records are authorized. The maintenance log also will store the changes till they get authorized. The new or the modified records are written to the static tables only after authorization.

This chapter contains the following section:

- [Section 35.1, "Tanking Records"](#)

35.1 Tanking Records

This sections contains the following topics:

- [Section 35.1.1, "Tanking New and Modified Maintenance Records"](#)
- [Section 35.1.2, "Tanking New Records"](#)
- [Section 35.1.3, "Tanking Modified Records"](#)
- [Section 35.1.4, "Closing a Record"](#)
- [Section 35.1.5, "Re-opening a Record"](#)
- [Section 35.1.6, "Authorizing a Record"](#)
- [Section 35.1.7, "Deleting a Record "](#)
- [Section 35.1.8, "Viewing Summary of Records"](#)
- [Section 35.1.9, "Modifying Tanking Preferences"](#)

35.1.1 Tanking New and Modified Maintenance Records

You can enable tanking of the creation and modification of maintenance records by selecting the 'Tanking Required' option provided at the function Id level. You need to enable the 'Tanking Required' option in RAD tool as well.

You can enable 'Tanking Required' option for individual function Ids in 'Function Description Maintenance' screen. You can invoke this screen by typing 'SMDFNDSC' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

To enable tanking of maintenance records for a function Id you need to select the function Id in this screen and then select the 'Tanking Required' checkbox.

For more details on this screen, refer Security Management System user manual.

Note

Tanking of records has been enabled only for the following function Ids:

- STDCIF
 - STDCUSAC
-

35.1.2 Tanking New Records

During the creation of a new record, if 'Tanking Required' option is enabled, the system tanks the details of the newly created record till the record gets authorized. Any query on this data retrieves this stored information.

35.1.3 Tanking Modified Records

All modifications to unauthorized records get tanked and the modified data gets written to actual tables only after authorization. In this case, the record remains in 'Authorized' status in the actual table and the unauthorized modifications will be kept pending for un-tanking. The most recent modifications will be shown in both summary and detailed screens with the Authorization status as 'Unauthorized'.

35.1.4 Closing a Record

You can close a record only if it is in 'Authorized' state, without any unauthorized modifications pending for un-tanking. Closure is possible only for records that are in 'Open' status. When

you close a record, the system tanks this and the record gets actually closed only after the closure gets authorized.

35.1.5 Re-opening a Record

You can re-open a record only if it has been closed and the closure is authorized. Re-opening of a record gets tanked till it gets authorized and the actual re-opening happens after the authorization.

35.1.6 Authorizing a Record

All unauthorized modifications get displayed when you click 'Authorize' menu option. You can select a modification number and the records get authorized till that modification. These records are un-tanked and their status gets updated as 'Authorized'. You can authorize the modifications partially, if required.

35.1.7 Deleting a Record

All unauthorized records will be available for deletion. You can select a modification number and system deletes all unauthorized modifications from the selected modification number. If the modifications getting deleted are made by a user other than the current user, the system displays an error message.

35.1.8 Viewing Summary of Records

All summary screens display data retrieved from both the summary data source and the table that contains the unauthorized tanked records.

35.1.9 Modifying Tanking Preferences

You can modify the tanking preferences specified for a function Id, if required. This modification is possible only if all records related to that function Id are in 'Authorized' status.

36. External Deal Maintenance

This chapter contains the following section:

- [Section 36.1, "Maintaining External Deal Linkage"](#)

36.1 Maintaining External Deal Linkage

You can capture the details of a deal booked in an external system using 'External Deal' maintenance screen. You can invoke this screen by typing 'STDEXLIN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

External Deal Linkage Detail

New

FLEXCUBE Reference *

Account Number

External Deal Reference

Deal Currency

Deal Amount

Exchange Rate

Deal Booking Date

Deal Expiry Date

Account Currency

Equivalent Amount

Remarks

Maker

Checker

Date Time:

Date Time:

Mod No

Record Status

Authorization Status

Exit

You can specify the following details in this screen:

FLEXCUBE Reference Number

This reference number is automatically generated by the system.

Account Number

Select the account number associated with the external deal from the option list which displays all valid account numbers in the system.

To view the joint holder's details of an account and the mode of operation maintained at the account level, place the cursor on the Account Number field and press Ctrl+J. The system displays the 'Joint Holder' screen.

For more information on the 'Joint Holder' screen refer to the section 'Joint Holder Maintenance' in this User Manual.

External Deal Reference Number

Specify a unique identification number for the external deal.

Deal Currency

Specify the currency in which the external deal was carried out or select the deal currency from the option list provided.

Account Currency

The account currency gets defaulted once you select the account number.

Deal Amount

Specify the amount associated with the external deal in terms of deal currency.

Equivalent Amount

The deal amount in terms of the account currency gets displayed here.

Equivalent Amount = Deal Amount * Exchange Rate

Exchange Rate

Specify the exchange rate to convert the deal currency in terms of the account currency.

Remarks

Specify any remarks associated with the external deal, if required.

Deal Booking Date

Specify the booking date of the external deal or select the deal booking date by clicking the 'Calendar' icon.

Deal Expiry Date

Specify the expiry date of the external deal or select the deal expiry date by clicking the 'Calendar' icon.

After specifying the above details you can save the record. An amount block equivalent to the deal amount is automatically created once these details are authorized.

Note

You can not modify a record in this screen, after it has been authorized.

For more details related to amount block maintenance, refer the chapter 'Maintaining Amount Blocks' in Current and Savings Account User Manual.

37. Multilevel Authorization of Contract

This chapter contains the following sections:

- [Section 37.1, "Invoke Multilevel Authorization Detailed screen"](#)

37.1 Invoke Multilevel Authorization Detailed screen

Some contracts may require multiple levels of authorization. The levels of authorizations are defined in the 'Product Transaction Limits' screen. You can use the 'Multilevel Authorization Detailed' screen for authorizing a contract n-1 times. However, you can do final authorization only in the contract screen.

You can invoke the 'Multilevel Authorization Detailed' screen by typing 'OVDAUDEF' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button. The screen is displayed below:

The screenshot shows the 'Multilevel Authorization Detailed' application window. It includes a search bar at the top with the text 'Enter Query'. Below the search bar are input fields for 'Module *', 'Product Code', 'Branch' (with 'T03' entered), and 'EA/ECA Block/Contract Reference'. A 'Go' button is next to the search bar. Below these fields is a table with columns: 'Contract Reference', 'Transaction currency', 'Transaction Amount', 'Counterparty', 'Product Code', 'Override Details', 'Error Code', and 'Pe'. The table is currently empty. At the bottom of the window are buttons for 'Confirm', 'Authorize All', 'Role Details', and 'Exit'.

Specify the following:

Branch

Specify the initiating branch code to authorize the records initiated through this branch. Alternatively, you can select the branch code from the option list. The list displays all the branch code maintained in the system.

Product Code

Specify the product code to filter the records for authorization. Alternatively, you can select the product code from the option list. The list displays all the product code maintained in the system.

Module

Select a module from the adjoining option list. The list displays all the modules maintained in the system which require multilevel authorizations.

EA/ECA Block/Contract Reference

Specify the contract reference number requiring multiple authorizations. Alternatively, you can select the contract reference number from the option list. The list displays the following values with all the valid contracts of the selected module requiring multilevel authorizations:

Branch – To query the record based on input branch

- Maker ID – To query the record based on Maker ID

- Product Code – To query the record based on product code used in the transaction record submitted. For example, CLDACCNT

With multi branch access, you can navigate to the respective transaction from the authorization queue by selecting a record and clicking 'View Contract Details' button from the same branch you are logged in.

Note

You can view the records for authorization for a combination of 'Branch and Module' or 'Branch, Module and Contract Reference'. To authorize a record, you should select the record and click the 'Accept' button.

Note

You can see the details of the contract only for internal transactions", when the 'Detail' button is pressed.

Multilevel Authorization Detail

The following details of the selected contract are displayed:

- Contract reference number
- Error code
- Override details
- Override authorization status
- Completed Levels of Authorization
- Pending levels of authorization
- Remarks
- Counter Party
- Product Code
- Transaction amount
- Transaction currency
- Maker ID
- Status of the authorization. The system displays the error details in case of authorization failure.

37.1.1 Authorize All Button

If you have the authorization limit as that of the contract amount, then click 'Authorize All' button to authorize all the levels of a contract displayed in this screen. Click 'Confirm' button to authorize/reject the records available in the grid individually.

Click the 'Authorizer All' button to view the details of all the authorizers involved in authorizing a contract. The system displays the following screen:

The system displays the following authorizer details:

- Authorizer ID
- Authorizer limit
- Contract Currency

37.1.2 Role Details Button

Click the 'Role Details' button to view the 'Multi Level Authorization Details' screen. The system displays the transaction and authorization role details as maintained in the 'Multi Authorization Role Details' screen.

You can view the roles for each level as per primary and alternate rule in successive rows. By default, the system selects the role as per the lowest level in the primary rule. During authorization, you can edit the role by clicking the check box against respective role based on

the roles mapped and authorize the transaction. You can also reject a transaction before authorization. To reject a transaction, select the transaction and click 'Reject' button.

To view the transaction details, click 'View' button. You can navigate to the respective transaction from the authorization queue by double-clicking on a record. This is applicable for authorizers with multi branch access to navigate from the same branch they are logged in.

Note

If you have Multi Branch Access, you can view and authorize pending records from other branch by querying on records of the respective branch. You can filter the records for authorization belonging to a specific branch and authorize the transaction

For more information on Mutli Level Authorization, refer to the section 'Multi Authorization Role Details Button' in the chapter 'Transaction Work flow' in Savings User Manual.

While Authorization of the Contract

- The level of authorization is decreased each time a contract is authorised successfully.
- On successful authorization, authorizer's authorization limit accumulates
- The system restricts authorization when the last level of authorization is pending if:
 - The authorization limit of the authorizer is less than the difference in contract value and the sum of authorization limit of the authorizers involved in the authorization process
 - The authorization limit of the authorizer is less than the minimum authorization limit

After Authorization of the Contract

- Creator of a contract cannot authorise an override
- An authorizer can authorize a contract at the contract screen when there is no authorization limit for the transaction amount and where the authorizers limit is equal or greater than the contract amount.
- An appropriate error will be displayed if the authorizer tries to approve a contract whose authorization limit is less than the minimum authorization limit maintained in the 'Product Transaction Limit Maintenance' screen.
- The contract amount is considered as authorizer's authorization limit during validation if:
 - The authorizer with no limit maintenance is authorizing the contract.
 - Contract will be listed even after the completion of n-1 level of authorization when the sum of authorization limit of the authorizer involved is less than the contract amount.
 - The system restricts authorization and displays an appropriate error message if the level of authorization is equal to or greater than n-1 and if the authorisation limit of the user is greater than or equal to contract value minus sum of authorisation limit of users involved in authorization

Refer the 'Maintaining Transaction Limits' section in this User Manual for more details on transaction limit maintenance.

38. Annexure A - File Formats

As mentioned earlier, SWIFT provides a country-wise holiday list that can be uploaded into Oracle FLEXCUE using the 'CCH' source code. This file consists of the 'HF' and 'HS' records. HF and HS are the tag identifiers through which the currency code can be obtained.

This chapter contains the following section:

- [Section 38.1, "Upload File Formats"](#)

38.1 Upload File Formats

HF – Non-European countries

As mentioned before, the HF record comprises the holiday details for countries where 'EUR' is not the local currency. The currency code is obtained from the country code present in this record. The holiday record is then uploaded into the Oracle FLEXCUBE holiday upload table.

The HF record has the following format:

Position	Description	Length	Type	Mandatory	Data
1	Tag Identifier	2	VAR-CHAR2	Y	'HF'
3	Modification Flag	1	VAR-CHAR2	Y	'A' addition 'M' modification 'D' deletion 'U' unchanged
4	Country Code	2	VAR-CHAR2	Y	ISO Country Code
6	Country Name	35	VAR-CHAR2	Y	Country Name (first part)
41	Country Name	35	VAR-CHAR2	N	Country Name (second part)
76	Date	8	VAR-CHAR2	Y	Date of a Holiday
84	Holiday type	1	VAR-CHAR2	Y	Code indicating type of Holiday (see below)

85	Special holi-day info.	320	VAR-CHAR2	N	Restrictions applicable if a holiday is not applicable country-wide, or is not a full day
----	------------------------	-----	-----------	---	---

HS – For European countries

The HS record comprises the Target holiday details for countries where 'EUR' is the local currency. The holiday record is uploaded into the Oracle FLEXCUBE holiday upload table.

The HS record has the following format:

Position	Description	Length	Type	Mandatory	Data
1	Tag Identifier	2	VARCHAR2	Y	'HS'
3	Modification Flag	1	VARCHAR2	Y	'A' addition 'M' modification 'D' deletion 'U' unchanged
4	Service Code	3	VARCHAR2	Y	Value Added Service Code
7	Date	8	VARCHAR2	Y	Date of a Holiday
15	Holiday type	1	VARCHAR2	Y	Code indicating type of holiday(see below)
16	Special holi-day info	320	VARCHAR2	N	Restrictions applicable if a holiday is not applicable country-wide, or is not a full day

39. Anti-Money Laundering

This chapter contains the following sections:

- [Section 39.1, "Anti-Money Laundering Reporting"](#)
- [Section 39.2, "Monitoring AML Accounting"](#)

39.1 Anti-Money Laundering Reporting

This section contains the following topics:

- [Section 39.1.1, "Guarding Against Money Laundering"](#)
- [Section 39.1.2, "Creating Product Categories in Oracle FLEXCUBE"](#)
- [Section 39.1.3, "Maintaining Limit Codes"](#)
- [Section 39.1.4, "Maintaining Anti Money Laundering Customer Groups"](#)
- [Section 39.1.5, "Linking Product Category with Customer Group"](#)

39.1.1 Guarding Against Money Laundering

In Oracle FLEXCUBE you can guard against Money Laundering by using the anti-money laundering option wherein you will be required to maintain certain basic information as a safeguard against Money Laundering activities that customers may indulge in.

The information that you need to maintain includes the maintenance of:

- Product Categories
- Limit Codes
- Customer Groups

39.1.2 Creating Product Categories in Oracle FLEXCUBE

You have to create product categories in Oracle FLEXCUBE, for the purpose of grouping common transactions. A product is a specific service that you offer your customers. Each transaction that you process in Oracle FLEXCUBE should be linked to a product. By maintaining amount limits at the product level, each time you link a transaction with a product the system verifies the amount limit maintained for the product. If the transaction amount exceeds the amount maintained at the product level the system intimates you with an override.

You can invoke the 'AML Product Categories Maintenance' screen by typing 'CSDAMLPC' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Product Category

You should identify each product category with an identification code by giving it a unique name.

Description

With each product category you have to associate a brief description. This description is meant for information purposes and will not be used for any processing.

Limit Currency

You have to identify the currency in which limits have to be tracked for transactions associated with the product category.

A list of all the currencies maintained in Oracle FLEXCUBE is available in the option list positioned next to this field. You can select the appropriate.

Product Type

Transactions grouped under a product can either be cash based or non-cash based. Therefore, you would have created products catering to cash based and non-cash based transactions.

While creating a product category, you have to indicate whether the products grouped under the respective category cater to cash based or non-cash based transactions. You can select the appropriate option.

Exchange Rate Code and Rate Type

The rate associated with this rate code will be used to derive the exchange rate when the currency of the transaction is different from the limit currency of the product category.

Similarly, you have to select the Rate Type that is to be associated with the rate code. The options available are as follows:

- Mid

- Buy
- Sell

The rate code along with the rate type will determine the exchange rate that is to be used.

Debit/Credit Indicator

As part of Anti-Money Laundering you can indicate the manner in which the system should track the Debit and Credit turnover limits for any of the limit types, for the product category. The options available are:

- Both (Aggregate Together) – absolute values of debits and credits will be aggregated together
- Both (Aggregate Separately) – debits and credits will be aggregated separately
- Debits alone or Credits alone

Limit Code and Limit Amount

At the product category level, you can specify the limit amount that should be associated with each limit code for a limit type.

A list of all the limit codes maintained for the specific limit type (Online, Individual, Daily turnover Batch, Daily turnover Online and Monthly turnover), in the Limit Codes Maintenance screen, will be displayed in the option list positioned next to this field. You can select the appropriate limit code and specify the limit amount that is to be linked with the code.

Note

For a particular product category you can choose to maintain Limit Code and Amount combinations for all of any of the five Limit types. They are:

- The Online transaction limit
- Individual limits
- Daily turnover limits
- Monthly turnover limits
- Online daily turnover limits

The transaction limits that you specify will be tracked online on a daily basis, whenever you process a transaction involving the product category. However, individual, daily and monthly turnover limits will be tracked only when the after the End of Day processes have been run successfully.

39.1.3 Maintaining Limit Codes

Before you begin the maintenance of product category records, you should necessarily maintain limit codes through the Limit Code Maintenance screen. While linking a limit amount with a limit code in the product category screen, only valid limit codes that you have maintained through this screen will be made available for mapping.

You can invoke this screen by typing 'CSDAMLLM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Limit Code

You can maintain limit codes for the various types of limit types like online tracking limits, individual tracking limits, daily turnover limits and monthly turnover limits.

You have to specify a unique name to identify each Limit Code that you would like to define. Subsequently, you can assign a brief description with each limit code that you define.

Limit Type

Since you can maintain separate limit codes for each limit type, you have to associate a limit code with each limit type. The options available are:

- Online Limit – tracks the limits of all online transaction that exceed limits
- Individual Transaction – during the batch processed executed at EOD the limit maintained for this type is used to tack all individual transactions that exceed the limit
- Online Daily Turnover –all transactions processed during the day are considered for an online tracking and an online reporting is done when the specified limit exceeds
- Monthly Turnover – all transactions processed during the month that have exceeded the specified limit will be reported
- Daily Turnover – during the batch processes executed at EOD all transactions for the business day that have exceed the limit will be reported

You can select the appropriate type from the list.

39.1.4 Maintaining Anti Money Laundering Customer Groups

Since you need to define transaction online, individual, daily and monthly limits for each customer, each product category that you maintain should be linked with a customer. To facilitate this linking, you are required to maintain AML Customer Groups. You have to link one of the limit codes of the respective type attached to the product category to the customer group

You can define product categories applicable to customer groups through the 'AML Customer Group Maintenance' screen. You can invoke this screen by typing 'CSDAMLCG' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

AML Customer Group Maintenance

New Enter Query

Customer Group * Next Review Date

Description *

Risk Profile ☒ High ☐ Low

Tracking ☒ Customer Group ☐ Customer

Product Details

Product Category *	Description	Online Limit Code	Individual Limit Code	Daily Limit Code

Fields

Input By Date Time Authorized By Date Time Modification Number

☐ Authorized ☐ Open

Customer Group

This is the AML group to which the particular customer belongs. You can select from the available option list and identify the AML group to which the customer belongs.

Note

In the CIF maintenance screen when you capture the customer code of a customer, the same will be defaulted in the AML Customer Group field since the system recognizes each customer code as a customer group. You can either choose to categorize the customer under the same group or choose another customer group.

You can capture a brief description that should be associated with every AML group

Next Review Date

While maintaining customer group and product category records you can specify the next date on which you would like to review the limits maintained for the various limit types.

Tracking

You have to specify whether the AML tracking is required for a customer or for all customers within a group. The system performs a group level tracking if you select Customer group. Conversely if you select Customer, the AML reporting, online tracking and data collection is done only at the customer level.

Note

If you fail to indicate your preference specifically the system will perform a customer group level tracking by default

Risk Profile

You can identify the risk profile of the customer group by selecting any one of the following options:

- High – indicating that the limits for the customer group need to be tracked regardless of the amount involved since the customer group is meant for high-risk customers.
- Low – indicating that the customer group is meant for low risk customers therefore amount limits need not be tracked if the amount involved falls within the limit amount.

You can select the required specification.

39.1.5 Linking Product Category with Customer Group

You have the option of selecting and linking as many limit codes as required for each limit type from the product categories maintained in the system. After you select the product category that is to be linked to the customer group, you have to identify the limit code associated with the limit type and in turn link it with the customer group.

Given below is a sample of the Customer Group maintenance record:

The Main details of the record are as follows:

Customer Group	AMLCUS01
Description	AMLCUSTOMER GROUP 1
Next Review Date	10-FEB-2003
Risk Profile	High

The Product Category linkage details are as follows:

Product Category	Description	Online Limit Code	Individual Limit Code	Daily Limit Code	Monthly Limit Code	Online Daily Turnover
PDT01	Product 1	LIM31	LIM01	LIM11	LIM21	LIM41
PDT02	Product 2	LIM36	LIM06	LIM16	LIM26	LIM46

Note

- Consequently, while processing transactions for all customers linked to the Customer Group AMLCUS01, the system does an online verification of transaction limits based on the amount limits maintained for the limit code LIM31 (linked to the product category PDT01) and LIM36 (linked to the product category PDT02) respectively.
 - It is mandatory for you to maintain a generic Customer Group called ALL for the customers of your bank. When product categories have not been linked to a specific customer or a customer group, the system picks up the limits maintained at the generic level for AML tracking purposes. Also, any new product category created and associated to the transaction code should be mandatorily associated with the ALL group.
-

39.2 Monitoring AML Accounting

For AML reporting purposes, while maintaining a transaction code you need to indicate whether AML monitoring is required for all accounting entries linked to the transaction code.

You can invoke this screen by typing 'STDTRNCD' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

The screenshot displays the 'Transaction Code Maintenance' window. At the top, there are buttons for 'New' and 'Enter Query'. The main area is divided into several sections:

- Transaction Details:** Includes fields for 'Transaction Code *', 'Description *', and 'Swift Code'.
- MIS Head:** A field for 'MIS Head' and 'External Code'.
- Availability Information:** Radio buttons for 'Immediate', 'On Value Date', 'After Days with New Value Date', and 'After X days', followed by a 'Days' input field.
- Overdraft Tracking:** A dropdown for 'Component type for transaction' set to 'Principal'.
- Debit/Credit Override Preferences:** A dropdown for 'Debit Override Tracking' set to 'Both'.
- Anti Money Laundering Monitoring:** Includes a checkbox for 'Anti Money Laundering Required', a dropdown for 'Product Category', a dropdown for 'Statement Day Basis' set to 'Current Working Day', a dropdown for 'Intra Day Release', and a dropdown for 'Salary Credit'.
- Credit Override Tracking:** A dropdown set to 'Both'.
- Preferences:** A list of checkboxes including 'Cheque Mandatory', 'Interests and Charges Transaction Count', 'Interests and Charges Turnover Inclusion', 'Consider for Account Activity', 'Interest and Charges Balance Inclusion', 'Available Balance Check Required', 'Interests and Charges Penalty Inclusions', 'Inter Branch in Local Currency', 'Acumen Transaction Code', 'Exempt Advance Interest', and 'Exempt Deposits'.

At the bottom, there is a 'Fields' section with a 'Transaction Tax' tab. Below this is a table with columns: 'Maker', 'Checker', 'Date Time:', 'Mod No', 'Record Status', and 'Authorization Status'. An 'Exit' button is located at the bottom right.

If you indicate that AML tracking is required for transactions linked to the transaction code you have to identify the product category with which the transaction code is to be linked.

Consequently, the system does a check for every accounting entry passed during online processing. The system checks the transaction amount of the entry with the transaction online limit maintained for the specific customer group (of the customer to whose account the entry has been posted) and the product category (for the transaction code of the entry). If the system finds that the limit amount has been exceeded an override message informing you of the same will be displayed.

During the End of Day (EOD) processing, the system identifies all accounting entries posted during the day, which have been marked for AML monitoring, and verifies the individual amount limit for the customer group and product category combination and stores this data in the system. You will be able to view this data when you generate an AML report using Business Objects.

As part of the EOD processes the system also updates the daily turnover limits for the particular customer group and product category combination. Monthly turnovers are updated for the Customer Number, Product Category and Currency combination.

40. Developer and Developer Project Maintenance

In Oracle FLEXCUBE, you can maintain details of the real-estate developer and developer projects. You can link the developers to loan accounts.

This chapter contains the following sections:

- [Section 40.1, "Developer Maintenance"](#)
- [Section 40.2, "Developer Project Maintenance"](#)

40.1 Developer Maintenance

This section contains the following topics:

- [Section 40.1.1, "Maintaining Developer Details"](#)
- [Section 40.1.2, "Project Button"](#)
- [Section 40.1.3, "Fields Button"](#)
- [Section 40.1.4, "Viewing Developer Maintenance Summary"](#)

40.1.1 Maintaining Developer Details

You can maintain contact and project details of the developer in the 'Developer Maintenance' screen. You can invoke this screen by typing 'CSDDEVDT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Developer Maintenance

New

Developer Code * SAC

Developer Name

Address ASDASD

Telephone

ASD

Email Id

ASDASD

Fax

ASDASD

Mobile

Zip 507125

Website

Country AE

Country Name UNITED ARAB EMIRATE

Project | Fields

Maker SANDEEPC Date Time: 2014-01-03 13:17:36 Mod No 1 Record Status Open

Checker SANDEEPM Date Time: 2014-01-03 13:21:33 Authorization Authorized Status

Exit

Here, you can specify the following details:

Developer Code

Specify the unique code of the developer.

Address

Specify the address of the developer.

Zip

Specify the ZIP code of the developer.

Country

Specify the code of the country to which the developer belongs. The adjoining option list displays all valid country codes maintained in the system. You can choose the appropriate one.

Country Name

The system displays the corresponding country name based on the specified code of the country.

Developer Name

Specify the name of the developer.

Telephone

Specify the telephone number of the developer.

Email ID

Specify the Email ID of the developer.

Fax

Specify the fax number that should be linked with the specified developer.

Mobile


Specify the mobile number of the developer.

Website

Specify the URL of the website linked to the developer.

40.1.2 Project Button

You can view the details of the projects linked to the developer by clicking 'Project' button in the 'Developer Maintenance' screen.




The screenshot shows a window titled "Projects Details" with a standard Windows-style title bar (minimize, maximize, close buttons). Inside the window, there is a table with two columns: "Project Name" and "Project Description". The table is currently empty. Above the table, there is a navigation bar with a "Go" button and a "1 Of 1" indicator. At the bottom right of the window, there are "Ok" and "Exit" buttons.

Here you can view the project names and descriptions that are linked to the specified developer.

40.1.3 Fields Button

You can view the UDF details by clicking 'Fields' button in the 'Developer Maintenance' screen.




The screenshot shows a window titled "User Defined Fields". Inside, there's a section labeled "UDF Details". At the top of this section, there are navigation arrows, a "1 Of 1" indicator, and a "Go" button. Below this is a table with three columns: "Field Name *", "Value", and "Value Description". The table is currently empty. At the bottom right of the window, there are "Ok" and "Exit" buttons.

Here you can view the field names and its value.

40.1.4 Viewing Developer Maintenance Summary

You can view the summary of developer maintenance in the 'Developer Maintenance Summary' screen. You can invoke this screen by typing 'CSSDEVDT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



The screenshot shows a window titled "Summary". It has a search bar at the top with "Search", "Advanced Search", and "Reset" options. Below the search bar, there are dropdown menus for "Authorization Status" and "Record Status". A "Developer Code" field is also present. Below these, there's a "Records per page" dropdown set to "15" and a "1 Of 1" indicator. A "Go" button is next to a field containing "0". Below this is a table with columns: "Authorization Status", "Record Status", "Developer Code", "Website", "Address", "Developer Name", "Country", "Email Id", and "Zip". The table contains many rows of data. At the bottom right, there is an "Exit" button.

In this screen, you can query based on any combination of the following fields:

- Authorization Status
- Developer Code
- Record Status

After specifying the parameters for the query, click 'Search' button. The system displays all the records matching the parameters specified. You can view the following details:

- Authorization Status

- Record Status
- Developer Code
- Website
- Address
- Developer Name
- Country
- Email ID
- Zip

40.2 Developer Project Maintenance

This section contains the following topics:

- [Section 40.2.1, "Maintaining Developer Project Details"](#)
- [Section 40.2.2, "Fields Button"](#)
- [Section 40.2.3, "Viewing Developer Project Maintenance Summary "](#)

40.2.1 Maintaining Developer Project Details

You can maintain the details of real estate development projects in the 'Developer Project Maintenance' screen. You can invoke this screen by typing 'CSDDEVPR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Developer Project Maintenance' application window. The window title is 'Developer Project Maintenance'. There is a 'New' button at the top left. The main form area contains the following fields:

- Project Name *** (text field)
- Developer Code *** (text field)
- Project Description** (text field)
- Address** (text field)
- Status** (text field)

Below the main form is a section titled 'Unit Details'. It contains a table with the following columns:

Unit Id	Unit Holder Name

At the bottom of the window is a 'Fields' section. It contains a table with the following columns:

Maker	Date Time:	Mod No	Record Status
Checker	Date Time:		Authorization Status

An 'Exit' button is located at the bottom right of the 'Fields' section.

Here you can specify the following details:

Project Name

Specify the name of the project.

Project Description

Specify a brief description about the project.

Address

Specify the address of the project location.

Status

Specify the status of the project.

Developer Code

Specify the unique code of the developer. The adjoining option list displays all valid codes maintained in the system. You can choose the appropriate one.

Unit Details

Specify the following details.

Unit ID

Specify the unit ID of the developer project.

Unit Holder Name

Specify the name of the unit holder of the developer project.

40.2.2 Fields Button

You can view the UDF details by clicking 'Fields' button in the 'Developer Project Maintenance' screen.

The screenshot shows a window titled "User Defined Fields". Inside, there is a tab labeled "UDF Details". Above the table, there are navigation buttons (back, forward, first, last) and a "Go" button. The table has three columns: "Field Name", "Value", and "Value Description". The table is currently empty. At the bottom right of the window, there are "Ok" and "Exit" buttons.

Here you can specify values for the UDF.

40.2.3 Viewing Developer Project Maintenance Summary

You can view the summary of developer project maintenance in the 'Developer Project Maintenance Summary' screen. You can invoke this screen by typing 'CSSDEVPR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Summary

Search Advanced Search Reset

Authorization Status Record Status

Developer Code Project Name

Records per page: 15 1 Of 1 Go 0

Authorization Status	Record Status	Developer Code	Project Name	Project Description	Address	Status
----------------------	---------------	----------------	--------------	---------------------	---------	--------

Exit

In this screen, you can query based on any combination of the following fields:

- Authorization Status
- Developer Code
- Record Status
- Project Name

After specifying the parameters for the query, click 'Search' button. The system displays all the records matching the parameters specified. You can view the following details:

- Authorization Status
- Record Status
- Developer Code
- Project Name
- Project Description
- Address
- Status

41. Project Financing

Project financing is the financing of long-term infrastructure and industrial projects involving a number of equity investors and a group of banks.

Project financing is a credit facility sanctioned to the contractors who execute large infrastructure projects, residential complexes, commercial complexes, etc. These contractors are awarded the contracts (projects) based on a BID system. Once the project is awarded to a contractor, he approaches the bank seeking for finance.


The contractor can avail financing from the bank against PPC (Project Progress Certificate/ Project Payment Certificate) or Invoice or TD or a clean line. PPCs are one type of backing against which OD is provided. The contractor can be a single entity or a joint venture (JV). In case of a joint venture, the share of the overdraft for each contractor will depend on their share in the joint venture.

This chapter contains the following sections:

- [Section 41.1, "Processing Finance for Project"](#)
- [Section 41.2, "Project Details Maintenance"](#)
- [Section 41.3, "Maintaining PPC"](#)
- [Section 41.4, "Maintaining PPC Liquidation"](#)
- [Section 41.5, "Dashboard Details"](#)
- [Section 41.6, "Querying Accounting Entries"](#)
- [Section 41.7, "Error and Error Codes for Project Financing"](#)

41.1 Processing Finance for Project

The process of project financing is as follows:



- Joint Venture Parties Details (In case of Joint Venture Limit Tracking)
 - PPC Limits Details
 - Non-PPC Limits Details
6. Link the Non-PPC lines defined in project to the project account using Limits tab
 7. The customer will utilize this clean limit line until he furnishes a PPC against part or full completion of a milestone.
 8. On receiving the PPC, the bank does the following:
 - Captures the PPC details
 - If it is a joint venture then the system will default the joint venture details to this screen based on the details captured in the project maintenance venture details screen.
 - If 'Auto Line Creation for PPC' field is unchecked,
 - You should manually create the line whenever a PPC is received.
 - The line currency can be other than project currency also, but the PPC CCY should be either project currency or line currency.
 - You should manually enter the limit line details in the project maintenance screen limits tab, if the project lines are created manually and in the PPC maintenance screen Joint Venture tab if PPC lines are created manually. If joint venture party limits tracking is not required, then the system will attach one line for the project customer with 100% tracking.
 - The system will also update the project ID and the PPC ID in the 'Facility Maintenance' screen, once the linkage between a line and a PPC/ Project is established manually during PPC maintenance
 - If 'Auto Line Creation for PPC' field is checked,
 - On authorizing the PPC, the system will create the limit lines for each of the PPC for liability ID of the project customer
 - You should allocate the limit to the project line equal to the lendable value of the respective PPC
 - You should allocate the limit to an individual customer limit lines based on the share each has in the joint venture if 'JV Limit Tracking Required' is checked
 - On authorizing the PPC, the system will automatically create line commitment contracts during the EOD. The rates used in the commitment are taken from project maintenance.
 - For each PPC authorized and if 'Limits tracking through Commitment' is checked, then the system will create the following line commitment contracts:
 - Project line commitment contract, regardless of whether there is a joint venture or not
 - Customer line commitment contract for each customer only in case of joint venture
 9. The bank will view the details of a project and the status of its collaterals from a Dashboard screen
 10. You should manually mark the PPC as CLOSED, if the payment against it has been received
 11. You should manually close the project account, if the system receives the payment towards all the PPC's and all the PPC's are marked as CLOSED
 12. When multiple lines are available and system has to utilize the lines, the priority will be determined based on the lowest interest rate + spread defined in the linkages screen.
 13. Using the PPC liquidation screen, you can choose the payment of the loan or credit to the project account. This transaction will be logged under the PPC.

14. PPC liquidation will be allowed even without the 'Entry No.', say, in case the contractor did not receive money due to contractual terms elapse etc. The system will display an override message when such an input is made.
15. Partial liquidation of PPC is allowed and they will be tracked. In case 'Entry No' is provided, loan payment will be considered only to the extent of PRINCIPAL payment and other component payments will not be considered.
16. Project closure activities include:
 - Liquidating PPCs
 - Marking PPCs as closed
 - All PPCs should be liquidated before they are closed
 - Closing all lines associated with the project
 - Manually created lines can be closed using the close button in the facility screen
 - Auto created lines (created by system) will be auto closed on the event of complete repayment and complete PPC liquidation
 - Manually closing project account
 - All lines associated with the project account should be closed
 - All PPCs should be closed
 - Manually closing project
 - All lines associated with the project should be closed
 - Commitment contracts will be auto closed on commitment maturity date through CL batch (Event: CLOC). Closure of commitment contracts before closure of project will have to be operationally controlled.

41.2 Project Details Maintenance

This section contains the following topics:

- [Section 41.2.1, "Maintaining Project Financing Transaction"](#)
- [Section 41.2.2, "Main Tab"](#)
- [Section 41.2.3, "Milestones Tab"](#)
- [Section 41.2.4, "Venture Details Tab"](#)
- [Section 41.2.5, "PPC Limits Tab"](#)
- [Section 41.2.6, "Non PPC Limits Tab"](#)

41.2.1 Maintaining Project Financing Transaction

Oracle FLEXCUBE allows you to maintain the project finance transaction in a bank with the details of the project undertaken with the contract. You can maintain these details using 'Project Detail and Maintenance' screen. To invoke this screen, type 'STDPJMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

Specifying the Project Details

Customer Number

Specify the customer number.

Project ID

Specify the project identification number.

Project Name

Specify the name of the project.

Project Account Branch

Specify the project account branch details.

Project Account

Specify the project account details.

Liability ID

Specify the liability ID.

Project Value

Specify the value of the project.

Remarks

Specify remarks, if any.

Ratio Change Allowed

Check this box if the joint venture ratio change is allowed during the course of the project.

This field is enabled only for new loans under the project financing.

JV Limit Tracking Required

Check this box if joint venture limit tracking is required.

Branch Code

The system displays the branch code.

Currency

Specify the currency details.

Number of PPCs

Specify the number of PPCs in the project.

Default PPC Clearance Days

Specify the default PPC duration for the payment.

Start Date

Specify the start date of the project.

End Date

Specify the end date of the project.

Sponsor Retention Margin (%)

Specify the retention margin for the sponsor while paying the PPC.

Bank Margin (%)

Specify the margin retained by the bank for the PPC..

Auto Line Creation for PPC

If you check this box, then the system will automatically create the credit lines while authorizing the PPC. Else, you need to manually create the line and link them in the PPC screen.

By default, this field will be checked.

Limit Track Required through Commitment

If you check this box, then the system will create the commitment contracts for every automatic line creation.

41.2.2 Main Tab

You can specify the main details of the project such as sponsor details and consultant details to validate the PPC and to recommend the sponsor for the payment.

The screenshot shows the 'Project Details and Maintenance' window with the 'New' form. The 'Main' tab is selected, showing various input fields for project details. The fields are organized into two columns. The left column includes 'Customer Number *', 'Project ID *', 'Project Name *', 'Project Account Branch *', 'Project Account *', 'Liability No *', 'Project Value *', and 'Remarks'. The right column includes 'Branch Code', 'Currency *', 'Number Of PPCs *', 'Default PPC Clearance Days *', 'Start Date *', 'End Date *', 'Sponsor Retention Margin (%)', and 'Bank Margin (%)'. Below these fields are three checkboxes: 'Ratio Change Allowed', 'JV Limit Tracking Required', and 'Auto Line Creation for PPC'. The bottom section of the form has two tabs: 'Sponsor' and 'Consultant'. The 'Sponsor' tab is active, showing a table with columns 'Sponsor ID', 'Sponsor Name *', and 'Sponsor Address L'. The 'Consultant' tab is also visible, showing a table with columns 'Consultant ID', 'Consultant Name *', and 'Consultant Address'. At the bottom of the window, there is a 'UDF' section with fields for 'Maker', 'Checker', 'Date Time:', 'Mod No', 'Record Status', 'Authorization Status', and an 'Exit' button.

Maintaining Sponsor Details

Sponsor ID

Specify the sponsor identification details of the project. If the sponsor is the customer of the bank, then you can specify the CIF identification details.

Sponsor Name

Specify the name of the sponsor.

The system will display the sponsor name, if you had specified the CIF ID in the 'Sponsor ID' field.

Sponsor Address

Specify the address of the sponsor.

The system will display the sponsor address, if you had specified the CIF ID in the 'Sponsor ID' field.

Maintaining Consultant Details

Consultant ID

Specify the consultant identification details of the project. If the sponsor is the customer of the bank, then you can specify the CIF identification details.

Consultant Name

Specify the name of the consultant.

The system will display the consultant name, if you had specified the CIF ID in the 'Consultant ID' field.

Consultant Address

Specify the address of the consultant.

The system will display the consultant address, if you had specified the CIF ID in the 'Consultant ID' field.

If the sponsor or consultant is not a customer of the bank, then the system will display only the name and address of the sponsor or the consultant.

41.2.3 Milestones Tab

You can specify the records of the various milestones in the project and percentage of completion with respect to the project.

The screenshot shows a software window titled "Project Details and Maintenance" with a "New" button. The "Project Details" section contains various input fields: Customer Number *, Project ID *, Project Name *, Project Account Branch *, Project Account *, Liability No *, Project Value *, Branch Code, Currency *, Number Of PPCs *, Default PPC Clearance Days *, Start Date *, End Date *, Sponsor Retention Margin (%), Bank Margin (%), Remarks, Ratio Change Allowed, JV Limit Tracking Required, Auto Line Creation for PPC, and Limit Track Required through Commitment. Below this is a tabbed interface with "Main", "Milestones", "Venture Details", "PPC Limits", and "Non PPC Limits". The "Milestones" tab is active, showing a table with columns: Milestone No *, Description *, Percentage Completion *, Start Date *, and End Date *. The table is currently empty. At the bottom, there is a "UDF" section with fields for Maker, Checker, Date Time, Mod No, Record Status, Authorization Status, and an "Exit" button.

Milestone No

Specify the milestone number.

Description

Specify the description of the milestone.

Percentage Completion

Specify the percentage of completion with respect to the milestone.

Start Date

Specify the start date of the milestone.

End Date

Specify the end date of the milestone.

41.2.4 Venture Details Tab

You can maintain the details of the joint venture. You can also change the joint venture ratios during the course of the project, but these ratios are effective only for future loans. Each loan created for the project can store the ratios at the loan level which is defaulted based on the application ratio at the time of loan creation. All limits tracking for joint venture parties will be based on this ratio.

The system will create the limit lines for each of the project venture parties when joint venture limit tracking is required at the project level. The line ID maintained at the limits is used to create the limits automatically. Each time the PPC is created, the system will create a new limit line using the same line for each of the liability of each joint venture. Different joint venture parties will have the same commitment product which can have different interest rate.

The screen is as shown below:

Project Details and Maintenance

New

Project Details

Customer Number *
Project ID *
Project Name *
Project Account Branch *
Project Account *
Liability No *
Project Value *
Remarks

Branch Code
Currency *
Number Of PPCs *
Default PPC Clearance Days *
Start Date *
End Date *
Sponsor Retention Margin (%)
Bank Margin (%)

Ratio Change Allowed
JV Limit Tracking Required
Auto Line Creation for PPC
Limit Track Required through Commitment

Main | Milestones | **Venture Details** | PPC Limits | Non PPC Limits

Default

1 Of 1
Go
Effective Date *

UDF

Maker	Date Time:	Mod No	Record Status
Checker	Date Time:	Authorization Status	Exit

Effective Date

Specify the effective date of the joint venture. For each effective date, the system maintains the ratio among the joint venture partners. The sum of ratios for each effective date must be equal to 100.

Party ID

The system displays the joint venture details of the project.

Party Name

The system will display the party name.

Liability ID

Specify the liability ID.

Ratio

Specify the percentage share of the joint venture party. The sum of all the ratios must be equal to 100.

Default Interest Rate

Specify the default interest rate that is used for the external component in the commitment product. The system will default this value to PPC.

Margin

Specify the margin applicable on the interest rate.

41.2.5 PPC Limits Tab

You can create the clean limit (ToD) manually using the line ID for the amount. You should then link this limit to the project account. The system creates the joint venture lines on authorization of the PPC maintenance with joint venture tracking required.

In case of manual line creation, the system will create the lines in project currency. Whenever there is a cross currency, the system will use a standard mid rate to convert from limit currency to project currency to track utilization. The LCY difference that may arise due to exchange rate differences will be handled by the ELCM CCY revaluation EOD batch.

You can view the limits detail such as line ID to create the project limits. There are two types, namely, PPC Limits and Non PPC Limits.

The screenshot for PPC Limits is as follows:

Project Details and Maintenance

New

Project Details

Customer Number *
Project ID *
Project Name *
Project Account Branch *
Project Account *
Liability No *
Project Value *
Remarks
Ratio Change Allowed
JV Limit Tracking Required

Branch Code
Currency *
Number Of PPCs *
Default PPC Clearance Days *
Start Date *
End Date *
Sponsor Retention Margin (%)
Bank Margin (%)
Auto Line Creation for PPC
Limit Track Required through Commitment

Main | Milestones | Venture Details | **PPC Limits** | Non PPC Limits

1 Of 1

Limit Type *	Limit Description	Credit Line *	Serial No *	Rate *	Margin *
--------------	-------------------	---------------	-------------	--------	----------

UDF

Maker
Checker
Date Time:
Date Time:
Mod No
Record Status
Authorization Status
Exit

Limit Type

Specify the type of limit.

Limit Description

The system displays the limit description.

Credit Line

Specify the credit line.

Serial No

The system displays the serial number for the limit created.

Commitment Product

Specify the commitment product details used when the respective limit line is created.

Rate

Specify the rate.

Margin

Specify the margin.

41.2.6 Non PPC Limits Tab

The screenshot for Non PPC Limits is as follows:

The screenshot shows the 'Non PPC Limits' tab in the 'Project Details and Maintenance' window. The window has a title bar with a close button. Below the title bar is a 'New' button. The main area is divided into two sections: 'Project Details' and 'Joint Venture Line Details'.

Project Details

Customer Number *
Project ID *
Project Name *
Project Account Branch *
Project Account *
Liability No *
Project Value *
Remarks
Ratio Change Allowed
JV Limit Tracking Required

Branch Code
Currency *
Number Of PPCs *
Default PPC Clearance Days *
Start Date *
End Date *
Sponsor Retention Margin (%)
Bank Margin (%)
Auto Line Creation for PPC
Limit Track Required through Commitment

Main | Milestones | Venture Details | PPC Limits | **Non PPC Limits**

Joint Venture Line Details

1 Of 1
Go

Limit Type *	Limit Description	Customer No *	Liability No *	Line Code *
--------------	-------------------	---------------	----------------	-------------

UDF

Maker
Checker

Date Time:
Date Time:

Mod No

Record Status
Authorization Status

Exit

Maintaining Joint Venture Line Details

Limit Type

Specify the type of limit.

Limit Description

The system displays the limit description.

Customer No

Specify the customer number.

Liability No

Specify the liability number.

Line Code

Specify the line code.

Line Serial

The system displays the serial number for the limit created.

Currency

The system displays the line currency details.

Rate

Specify the rate.

Margin

Specify the margin.

JV Line

This box will be checked by default.

Maintaining Party Line Details**Customer No**

Specify the customer number.

Liability No

Specify the liability number.

Line Code

Specify the line code.

Line Serial

The system displays the serial number for the limit created.

Currency

The system displays the line currency details.

41.3 Maintaining PPC

Oracle FLEXCUBE allows the executor to maintain the PPC during the course of the project, i.e. during the course of the project, once the executor completes the milestone should inform the sponsor. The sponsor in turn, will inspect and confirms the completion of the milestone. The executor is then allowed to raise the PPC with start date and the expiry date. The system calculates the expiry date based on the default PPC clearance days. However, the sponsor can change the expiry date. The system will accept the PPC in any currency. If there is a cross currency, then the system uses a standard mid rate for converting from limit currency to project currency.

You can maintain the PPC using 'PPC Maintenance' screen. To invoke this screen, type 'STDPPCMN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Specifying PPC Maintenance Details

Project ID

Specify the project ID.

PPC ID

The system displays the PPC ID.

PPC Description

Specify the description of the PPC.

Start Date

Specify the PPC start date.

End Date

Specify the PPC end date.

Milestone No

Specify the milestone sequence number.

Currency

Specify the currency of the PPC.

PPC Amount

Specify the amount of the PPC. If the sum of the PPC amounts for all the PPCs presented for the specific milestone is greater than the milestone percentage calculated amount an error message is displayed.

The system will create the automatic limit lines for the lendable amount arrived at after applying the sponsor retention margin and the bank margin.

Sponsor Retention Margin

The system displays the margin retained by the sponsor for this PPC. However, you can amend this field while creating the PPC.

Sponsor Amount

The system displays the sponsor amount after applying the sponsor retention margin.

Bank Margin

The system displays the margin retained by the bank for this PPC. However, you can amend this field while creating the PPC.

Lendable amount

The system displays the lendable amount after applying the bank margin.

Amount Paid

The system displays the amount that has been paid against this PPC.

Remarks

Specify remarks, if any.

Specifying Joint Venture Details

In case of manual line linkage, you need to operationally ensure the following points:

- Synchronization of Line End date and PPC end date
- Limit lines should have amounts equivalent to that of PPC lendable amount. In case line currency is different from PPC currency, lines should be created for the equivalent of PPC lendable amount by applying the rate conversion. If there is any mismatch in the amounts, while linking the manual lines, the system will display an override message

Party ID

The system defaults the party ID from the project maintenance.

Ratio

The system defaults the joint venture share ratio from the project maintenance.

Credit Line

The system defaults the line ID. The system uses this limit line for tracking the exposure of specific joint venture party.

If joint venture limit tracking is not required at project level, the system will not create the lines. In case auto creation of lines is not chosen, then you need to manually create limit lines and link them in this screen.

Serial Number

Specify the line serial of the credit line.

Currency

The system displays the line currency.

After specifying the PPC amount, click on 'CALC' button. The will calculate the sponsor margin and the bank margin and arrive at the sponsor amount and the lendable amount respectively.

41.4 Maintaining PPC Liquidation

You can maintain the liquidation details in the PPC screen, where in you can choose the payment of the loan or credit to the project account. This transaction is logged in the PPC. To invoke the PPC Liquidation screen, type 'STDPPCLQ' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot displays the 'PPC Liquidation' application window. At the top, there is a 'New' button. Below it, the 'PPC Liquidation' form contains several input fields: 'Project ID *', 'Branch Code *', 'Loan/Account Number *', 'Entry Number', 'Currency', 'Amount', 'PPC ID *', 'PPC Description', and 'Serial No'. The bottom section of the window is labeled 'UDF' and contains a table with the following columns: 'Maker', 'Date Time:', 'Mod No', 'Record Status', 'Checker', 'Date Time:', 'Authorization Status', and an 'Exit' button.

Project ID

Specify the project ID.

Project Name

The system displays the name of the project ID selected.

PPC ID

Specify the PPC ID.

PPC Description

The system displays the description for the PPC ID selected.

Loan/Account Number

Specify the loan or the account number.

Entry Number

Specify the entry number. If you have not specified the entry number, then the system will display an override message.

Amount

The system displays the amount for liquidation. However, you can amend this field.

Branch Code

Specify the branch code.

Currency

The system displays the currency details.

41.5 Dashboard Details

This section contains the following topics:

- [Section 41.5.1, "Viewing Dashboard Details"](#)
- [Section 41.5.2, "PPC Details Tab"](#)
- [Section 41.5.3, "Limit Details Tab"](#)
- [Section 41.5.4, "Commitment Details Tab"](#)
- [Section 41.5.5, "Loan Details Tab"](#)
- [Section 41.5.6, "Querying Dashboard Details"](#)

41.5.1 Viewing Dashboard Details

Oracle FLEXCUBE allows you to view the details of the PPC available in the project such as joint venture ratios, balance in the project account, the project lines and their limits for each project line, etc. You can view these details using 'Dashboard Details' screen. To invoke this screen, type 'STDPJDSH' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

Dashboard Detail

Enter Query

Project ID _____ Customer ID _____ Account No _____
Project Name _____ Customer Name _____ Account CCY _____
Project Amount _____ Available Balance _____ Current Balance _____
Project Utilization _____ Currency _____

PPC Details | Limit Details | Commitment Details | Loan Details

1 Of 1

Collateral Type	Sequence	Collateral Description	Amount	Currency	Out Standing	Status
-----------------	----------	------------------------	--------	----------	--------------	--------

1 Of 1

Party ID	% Share	Currency	Limit	Available
----------	---------	----------	-------	-----------

Exit

You can view the following details:

- Project ID
- Project Name
- Customer ID
- Customer Name
- Available Balance
- Account Number
- Account Currency

- Project Limit
- Project Utilization
- Current Balance

41.5.2 PPC Details Tab

You can view the PPC details by clicking on the 'PPC Details' tab in the 'Dashboard Details' screen.

The screen is as shown below:

Dashboard Detail

Enter Query

Project ID _____ Customer ID _____ Account No _____
 Project Name _____ Customer Name _____ Account CCY _____
 Project Amount _____ Available Balance _____ Current Balance _____
 Project Utilization _____ Currency _____

PPC Details | Limit Details | Commitment Details | Loan Details

Collateral Type	Sequence	Collateral Description	Amount	Currency	Out Standing	Status

Party ID	% Share	Currency	Limit	Available

Exit

You can view the following details:

- Collateral Details
 - Collateral Type
 - Sequence
 - Collateral Description
 - Amount
 - Outstanding
 - Status
- Venture Details
 - Party ID
 - % Share
 - Limit CCY
 - Limit
 - Available

41.5.3 Limit Details Tab

You can view the limit details by clicking on the 'Limit Details' tab in the 'Dashboard Details' screen.

The screen is as shown below:

Dashboard Detail

Enter Query

Project ID _____ Customer ID _____ Account No _____
Project Name _____ Customer Name _____ Account CCY _____
Project Amount _____ Available Balance _____ Current Balance _____
Project Utilization _____ Currency _____

PPC Details **Limit Details** Commitment Details Loan Details

1 Of 1 Go

<input type="checkbox"/>	Credit Line	Line Serial	Currency	Limit	Utilized	Paid
--------------------------	-------------	-------------	----------	-------	----------	------

1 Of 1 Go

<input type="checkbox"/>	Party ID	% Share	Credit Line	Line Serial	Currency	Limit	Utilized	Paid
--------------------------	----------	---------	-------------	-------------	----------	-------	----------	------

Exit

You can view the following details:

- Project Line Details
 - Line ID
 - Line Serial
 - Limit
 - Utilized
 - Paid
- Customer Line Details
 - Party ID
 - % Share
 - Line ID
 - Line Serial
 - Limit
 - Utilized
 - Paid

41.5.4 Commitment Details Tab

You can view the commitment details by clicking on the 'Commitment Details' tab in the 'Dashboard Details' screen.

The screen is as shown below:

The screenshot shows a web application window titled "Dashboard Detail". At the top, there is a search bar labeled "Enter Query". Below it, there are several input fields for search criteria: Project ID, Project Name, Project Amount, Project Utilization, Customer ID, Customer Name, Available Balance, Currency, Account No, Account CCY, and Current Balance. Below these fields, there are four tabs: "PPC Details", "Limit Details", "Commitment Details", and "Loan Details". The "Commitment Details" tab is currently selected. Below the tabs, there is a table with the following columns: "Contract Reference", "Currency", "Amount", "Outstanding Amount", and "Maturity Date". The table is currently empty. At the bottom right of the window, there is an "Exit" button.

You can view the following details:

- Contract Reference
- Currency
- Amount
- Outstanding Amount
- Maturity Date

41.5.5 Loan Details Tab

You can view the loan details by clicking on the 'Loan Details' tab in the 'Dashboard Details' screen.

The screen is as shown below:

This screenshot is identical to the previous one, but the "Loan Details" tab is now selected. The table below the tabs is still empty, showing the same column headers: "Contract Reference", "Currency", "Amount", "Outstanding Amount", and "Maturity Date".

You can view the following details:

- Contract Reference
- Currency
- Amount
- Outstanding Amount
- Maturity Date

41.5.6 Querying Dashboard Details

Oracle FLEXCUBE allows you to query the dashboard details based on the Project ID, Project Name, Customer ID, Customer Name, Account Number. You can view these details using 'Dashboard Summary' screen. To invoke this screen, type 'STSPJDSH' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

Dashboard Summary

Search Advanced Search Reset

Project ID(3) Project Name(3)
Customer ID(3) Customer Name(3)
Account No Account CCY
Project Amount

Records per page 15 1 Of 1 0

Project ID	Project Name	Customer ID	Customer Name	Account No	Account CCY	Project Amount
------------	--------------	-------------	---------------	------------	-------------	----------------

Exit

You can query the record based on the following details:

- Project ID
- Customer ID
- Account Number
- Project Limit
- Project Name
- Customer Name
- Account Currency

You can double-click on a specific record to view the detailed screen.

41.6 Querying Accounting Entries

Oracle FLEXCUBE allows you to view the accounting entry serial number which can be used in PPC liquidation screen for marking a specific credit entry for query. You can view these details using 'Customer Account Transaction Query' screen. To invoke this screen type 'ACDTRNQQY' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button

The screen is as shown below:

Customer Account Transaction Query

Query Criteria

Contract Reference _____ Debit/Credit
Account Number _____ Transaction Currency _____
Transaction Code _____ Module _____
Event Code _____ Transaction Date _____
Value Date _____ Related Account _____
Related Reference Number _____ To Date _____
From Date _____
Last N number of transactions _____

Account Details

Branch _____
Currency _____
Starting Balance _____
Debit Credit Balance _____
Account Number _____

Transaction Details

1 Of 1

<input type="checkbox"/>	Contract Reference	Entry Serial Number	Module Code	Transaction Code	Transaction Code Description	Transaction Date
--------------------------	--------------------	---------------------	-------------	------------------	------------------------------	------------------

You can query the record based on the following details:

- Contract Reference
- Account Number
- Debit/Credit
- Transaction Code
- Currency
- Event Code
- Module Code
- Value Date
- Transaction Date
- Related Reference
- Related Account
- From Date
- Last N Number of Transactions
- To Date

To view the joint holder's details of an account and the mode of operation maintained at the account level, place the cursor on the Account Number field and press Ctrl+J. The system displays the 'Joint Holder' screen.

For more information on the 'Joint Holder' screen refer to the section 'Joint Holder Maintenance' in this User Manual.

Clicking on the 'Query' button, the system displays the transaction details. You can double-click on a specific record to view the detailed screen.

Note

- You can query for a specific number of previous records by entering the value in 'Last N Number of Transactions'. By default, it is set as 100.
 - When you click 'Query' button, the system validates whether Last N.number of transactions is greater than the menu level MAX_RES_ROWS of the function ID 'ACDTRNQY'. If it is found greater than that, then the system displays a configurable message 'Last N number of transactions is greater than the allowed maximum transactions to be retrieved'.
 - If you do not enter the last N number of transaction and click the 'Query' button, and the number of transactions to be retrieved is greater than the menu level MAX_RES_ROWS for the function ID 'ACDTRNQY', then the system will retrieve only the first MAX_RES_ROWS number of transaction and display an information message 'Displaying only first[MAX_RES_ROWS] transactions'.
 - The starting balance and running balance fields of the Customer Account Transaction Query (ACDTRNQY) are not be applicable if you try to retrieve the Last N transaction.
-

41.7 Error and Error Codes for Project Financing

Validation	Error Code	Description
System should not allow entering PPCs if the total # of PPC's already entered exceeds the # allowed	ST-PPC-001	Max limit for number of PPCs exhausted.
Whenever there is a change in the # of PPC's, the system should validate whether the change is an increase or decrease. It should only allow an increase in the # of PPC's	ST-CON003	Decreasing number of PPCs not allowed
At the project maintenance, whenever there is a change in the project amount, the system should validate and only allow an increase in the project amount and not allow a decrease	ST-CON005	Decrease of project amount not allowed
In case of a JV, the total of the % share of individual customers should be 100%	ST-PROJ-009	Total share should be 100%
In case of a JV, each customer should have a separate Liability ID it is operational control. At the project maintenance, each project should have unique Line ID for PPC lines.	ST-PROJ-028	Liability ID already in use
The milestone start date and end date should be validated against that of the project	ST-PROJ-004	The milestone start date/ end date should be equal to or within the range of project start and end date
The project status when changed to CLOSED should be allowed only when all PPC's associated with the respective project are in CLOSED status	ST-PROJ-024	OPEN PPC's exist. Project status cannot be closed
In case of auto created lines, system should not allow amendment on these lines	ST-CON012	Amendment of auto-created lines not allowed
The number of milestones cannot exceed the number of PPCs	ST-PROJ-027	Number of milestones cannot be greater than the number of PPCs
The sum of the milestone percentage completion should be 100	ST-PROJ-010	The sum of milestone completion should be 100

PPC end date is different from PPC start date + PPC clearance days. Configurable override	ST-PROJ-031	PPC End Date is different from Project Start Date + PPC Clearance days.
---	-------------	---

42. Reports

This chapter contains the following sections:

- [Section 42.1, "Deleted Transaction Listing Report"](#)
- [Section 42.2, "Accounting Journal Report"](#)
- [Section 42.3, "Cash Flow Report"](#)
- [Section 42.4, "Future Dated Account Balance Report"](#)
- [Section 42.5, "Current Rates Report"](#)
- [Section 42.6, "Rate History Report"](#)
- [Section 42.7, "Customer Account Opening Confirmation Report"](#)
- [Section 42.8, "Account Closing Confirmation Report"](#)
- [Section 42.9, "Activity Journal Report"](#)
- [Section 42.10, "Core Exception Report"](#)
- [Section 42.11, "Uncollected Funds Report"](#)
- [Section 42.12, "Account Revaluation Report"](#)
- [Section 42.13, "Accounts Movement Report"](#)
- [Section 42.14, "Customer Details Report"](#)
- [Section 42.15, "Customer Accounts Report"](#)
- [Section 42.16, "Document Check List Report"](#)
- [Section 42.17, "Memo Revaluation Report"](#)
- [Section 42.18, "Black Listed During Contract Booking Report"](#)
- [Section 42.19, "Black List Report During File Upload Report"](#)
- [Section 42.20, "Cheque Book Issued Report"](#)
- [Section 42.21, "Demand Draft Issued Report"](#)
- [Section 42.22, "PDC Input Report"](#)
- [Section 42.23, "Temporary Overdraft Report"](#)
- [Section 42.24, "Daily Sales Report"](#)
- [Section 42.25, "Customer Restriction Utilization Report"](#)

42.1 Deleted Transaction Listing Report

This section contains the following topics:

- [Section 42.1.1, "Generating List of Deleted Transactions Report"](#)
- [Section 42.1.2, "Contents of Report"](#)

42.1.1 Generating List of Deleted Transactions Report

This report lists out the deleted transaction details pertaining to each product under each module pertaining to every user. You can invoke this screen by typing 'ACRDLTXN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Deleted Transactions Listing' window. It features a title bar with standard window controls. The main area is divided into several sections for data entry: 'Module' with radio buttons for 'Single' and 'All'; 'Products' with radio buttons for 'Single' and 'All'; 'User' with radio buttons for 'Single' and 'All'; 'Batch' with 'From' and 'To' text boxes; 'Transactions' with radio buttons for 'All', 'This Branch', 'Posted to Other Branch', and 'This Branch acted as Bridge', and a 'Print Copies' checkbox; 'Report Format' with a dropdown menu set to 'PDF'; 'Report Output' with a dropdown menu set to 'View'; 'Printer At' with a dropdown menu set to 'Client'; and a 'Printer' text box. At the bottom right, there are 'Ok' and 'Exit' buttons.

Specify the following details.

Module

Indicate whether the reports should be generated for a single module or for all modules.

If you choose 'Single', you need to specify the module for which the report needs to be generated. The option list provided displays all valid module codes maintained in the system. You can select the appropriate one.

Transactions

Indicate the type of transactions that should be covered in the report. The following options are available:

- All
- This branch
- Posted to Other Branch
- This branch acted as bridge

Products

Indicate whether the reports should be generated for a single product or for all products.

If you choose 'Single', you need to specify the product code for which the report needs to be generated. The option list provided displays all valid product codes maintained in the system. You can select the appropriate one.

User

Indicate whether the reports should be generated for a transactions entered by all users or a single user.

If you choose 'Single', you need to specify the user ID based on which the report needs to be generated. The option list provided displays all valid user IDs maintained in the system. You can select the appropriate one.

From

Specify the batch from which the transactions need to be considered for report generation.

To

Specify the batch until which transactions need to be considered for report generation.

Print Copies

Check this box to indicate that the report needs to be printed.

Click 'OK' to generate the report.

42.1.2 **Contents of Report**

The contents of this report are discussed under the following heads:

Header

The Header carries the title of the report, information on the branch code, branch date, the ID of the user who generated the report, the date and time at which it was generated, the modules covered in the report, the product codes covered in the report, batch information, transactions covered in the report and printing preference.

Body of the Report

This report is sorted module-wise. For every module the following details are displayed.

- Module
- Product
- User ID

The following transaction details are displayed.

Field Name	Field Description
Reference Number	This is the reference number of the deleted transaction
Account Branch	This is the branch where the account resides.
Account Number	This is the account number.
Currency	This is the currency of the transaction.
Debit/Credit	This indicates the nature of the transaction – debit or credit.
Transaction Code	This is the transaction code.
Status	This is the status of the transaction
Value Date	Indicates the value date of the transaction

Account description	This is the account description.
Fcy Amount	This is the transaction amount in foreign currency.
Transaction Description	This is the description of the transaction code
Exchange Rate	This is the exchange rate
LCY Amount	This is the Amount in Local currency
Narrative	This is the narrative text associated with the transaction.
Instrument Number	This is the instrument number linked to the transaction.
Auth ID	This is the authorization ID
Total Debits	Total amount debited under the respective user, product and module
Total Credits	Total amount credited under the respective user, product and module
User ID	This is the user ID of the user who entered the transaction.
Grand Total Debits	This is the grand total amount of all the debit transaction grouped by transaction code and user.
Grand Total Credits	This is the grand total amount of all the credit transaction grouped by transaction code and user.

42.2 **Accounting Journal Report**

This section contains the following topics:

- [Section 42.2.1, "Generating Accounting Journal Report"](#)
- [Section 42.2.2, "Contents of Report"](#)

42.2.1 Generating Accounting Journal Report

This report gives details of every journal entry transaction. You can invoke this screen by typing 'ACRJRNAL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Deleted Transactions Listing' window. It features a title bar with a minus, maximize, and close button. The main area is divided into several sections for data entry and selection. On the left, there are sections for 'Module', 'Products', 'User', and 'Batch'. 'Module' has radio buttons for 'Single' and 'All'. 'Products' has radio buttons for 'Single' and 'All'. 'User' has radio buttons for 'Single' and 'All'. 'Batch' has 'From' and 'To' text boxes. In the center, there is a 'Transactions' section with radio buttons for 'All', 'This Branch', 'Posted to Other Branch', and 'This Branch acted as Bridge'. To the right of 'Transactions' is a 'Report Date' text box with a red asterisk. Below 'Batch' are 'Report Format' (a dropdown menu showing 'PDF') and 'Report Output' (a dropdown menu showing 'View'). To the right of these are 'Printer At' (a dropdown menu showing 'Client') and 'Printer' (a text box). At the bottom right, there are 'Ok' and 'Exit' buttons.

Specify the following details:

Module

Indicate whether the reports should be generated for a single module or for all modules.

If you choose 'Single', you need to specify the module for which the report needs to be generated. The option list provided displays all valid module codes maintained in the system. You can select the appropriate one.

Transactions

Indicate the type of transactions that should be covered in the report. The following options are available:

- All
- This branch
- Posted to Other Branch
- This branch acted as bridge

Products

Indicate whether the reports should be generated for a single product or for all products.

If you choose 'Single', you need to specify the product code for which the report needs to be generated. The option list provided displays all valid product codes maintained in the system. You can select the appropriate one.

User

Indicate whether the reports should be generated for a transactions entered by all users or a single user.

If you choose 'Single', you need to specify the user ID based on which the report needs to be generated. The option list provided displays all valid user IDs maintained in the system. You can select the appropriate one.

From

Specify the batch from which the transactions need to be considered for report generation.

To

Specify the batch until which transactions need to be considered for report generation.

Print Copies

Check this box to indicate that the report needs to be printed.

Position Entries

Check this box to indicate that the report needs to cover position accounting entries.

Report Date

Specify the date as on which the report needs to be generated.

Click 'OK' to generate the report.

42.2.2 Contents of Report

The contents of this report are discussed under the following heads:

Header

The Header carries the title of the report, information on the branch code, branch date, the ID of the user who generated the report, the date and time at which it was generated, the modules covered in the report, the product codes covered in the report, batch information, transactions covered in the report and printing preference.

Body of the report

The report is sorted by modules. Under every module, it lists out product-wise transaction details.

The following transaction details are displayed.

Field Name	Field Description
Product	This is the product code of the transaction.
User Id	This is the user ID of the user who entered the transaction.
Reference No	This is the transaction reference number.
Account Branch	This is the account branch.
Account Number	This is the account number.
Currency	This is the currency of the transaction.
Dr/Cr	This is the nature of the transaction – either debit or credit.
Transaction Code	This is the transaction code while posting the journal entry.
Module	This is the module code of the report

Description	This is the description of the transaction code.
Status	Status of the transaction.
Value Date	This is the value date of the transaction.
Account Description	This is the description of the account.
Event	This is the event triggered on the transaction.
Fcy Amount	This is the transaction amount in a foreign currency
Exchange Rate	This is the exchange rate used if the transaction is in any other currency.
Lcy Amount	This is the transaction amount in local currency.
Auth ID	This is the user ID of the user who authorized the transaction.
Total Debits	Total amount debited under the respective user, product and module
Total Credits	Total amount credited under the respective user, product and module
Grand Total Debits	This is the grand total amount of all the debit transaction grouped by transaction code and user.
Grand Total Credits	This is the grand total amount of all the credit transaction grouped by transaction code and user.

42.3 Cash Flow Report

This section contains the following topic:

- [Section 42.3.1, "Generating Cash Flow Report"](#)
- [Section 42.3.2, "Contents of Report"](#)
- [Section 42.3.3, "Cash Flow \(Summary\) Report"](#)

42.3.1 Generating Cash Flow Report

The 'Cash flow report' gives details of the cash flow by accounts or by account class. The report contains details of the Account Number or Account Class, and the list of Accounts or Account Classes. You can invoke this screen by typing 'ACRPCASH' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

Cash Flow Report

Report Name

Report Type ☒ Summary ☐ Detail

Include Call-Notice Contracts ☐ Notice Contracts ☐ Call Contracts

Select Account Class/Account ☒ Account Class ☐ Account

☒ All Records ☐ Specific Records

Account Class

Account

1 Of 1 Go + -

1 Of 1 Go + -

Ok Exit

Specify the following details.

Report Name

Specify the name of the report. The option list provided displays all valid reports maintained in the system. You can select the appropriate one.

Report Type

Indicate whether the report should be a detailed report or a summary report.

Notice Contracts

Check this box to indicate that notice contracts should be covered in the report.

Call Contracts

Check this box to indicate that call contracts should be covered in the report.

Select Account Class/Account

Indicate whether the reports should be generated based on account class or account.

All/Specific Records

Indicate whether the reports should be generated for all records in an account class/account or for specific records.

Account Class

If you have indicated 'Account Class' as the basis for report generation, specify the account classes that should be considered. Click add icon to add rows. You can select a valid account class from the adjoining option list.

Account

If you have indicated 'Account' as the basis for report generation, specify the accounts that should be considered. Click add icon to add rows. You can select a valid account from the adjoining option list.

Click 'OK' to generate the report.

42.3.2 **Contents of Report**

The contents of the cash flow report are discussed under the following heads:

Header

The Header carries the title of the report, information on the branch code, the ID of the user who generated the report, the module, page number and the date and time at which it was generated.

Body of the Report

The report is sorted on the currency of the cash flow.

Field Name	Field Description
Interval	Indicates the interval of cash flow
Amount In	This is the amount debited into the particular account for the particular period.
Account	This is the account number
Account Class	This indicates the account class
Amount Out	This is the amount credited from the account during the specified period.
Net Flow	Indicates the net flow
Currency	Indicates the currency of the transaction

42.3.3 **Cash Flow (Summary) Report**

The Cash Flow summary report summarizes the details of cash flow for particular Accounts or Account Classes.

Header

The Header carries the title of the report, information on the branch code, the ID of the user who generated the report and the date and time at which it was generated.

Body of the Report

The report is sorted on the currency of the cash flow for different account classes and their accounts. The following details are displayed.

Field Name	Field Description
Amount In	This is the amount debited into the particular account for the specific period
Amount Out	This is the amount credited from the account during the specified period

Net Flow	This is the net amount available in the account for the specified period
----------	--

42.4 Future Dated Account Balance Report

This section contains the following topics:

- [Section 42.4.1, "Generating Future Dated Contracts Report"](#)
- [Section 42.4.2, "Contents of the Report"](#)

42.4.1 Generating Future Dated Contracts Report

This report gives balances of future dated transactions. You can invoke the screen by typing 'ACRPFVBL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You can specify the following parameters:

Select Account Class/Account

Select account criteria for generating the report from the following options:

- Account Class
- Account

Report Preferences

Select report preference criteria for generating the report from the following options:

- All Records
- Specific Records

Account Class

Specify valid account classes for which you need to generate the report from the adjoining option list, if you have selected 'Account Class'.

Account

Specify valid account classes for which you need to generate the report from the adjoining option list, if you have selected 'Account'.

42.4.2 Contents of the Report

Header

The Header carries the title of the report, information on the branch code, branch date, the ID of the user who generated the report, the date and time at which it was generated and the modules covered in the report.

Body of the Report

The following details are displayed.

Field Name	Field Description
Date	This gives the date for which a future dated transaction is booked for the account.
Reference Number	This is the reference number of the future dated transaction
Inflow	This is the inflow amount.
Outflow	This is the outflow amount.
Balance	This is the available balance.
Currency	This is the currency of the account
Customer	This is the name of the customer.
Account	This is the account number of the customer.
Account Class	This is the account class.
Opening	This is the opening balance of the account.


42.5 Current Rates Report

This section contains the following topics:

- [Section 42.5.1, "Generating Currency Rate Report"](#)
- [Section 42.5.2, "Contents of Report"](#)

42.5.1 Generating Currency Rate Report

This report gives details on rates for currency pairs. You can invoke the screen by typing 'CYRTCURR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



Specify the following details.

Selection

Indicate whether the report should be generated for all currency pairs or for a given currency pair.

Currency 1

If you have chosen, 'Selected Currency Pair', then specify the first currency that forms a pair. The adjoining option list displays all valid currency codes maintained in the system. You can select the appropriate one.

Currency 2

If you have chosen, 'Selected Currency Pair', then specify the second currency that forms the pair. The adjoining option list displays all valid currency codes maintained in the system. You can select the appropriate one.

Click 'OK' to generate the report.

42.5.2 Contents of Report

Header

The Header carries the title of the report, information on the branch code, the ID of the user who generated the report, the date and time at which it was generated, the module covered in the report and reporting options.

Body of the report

The report is sorted by currency pairs. The following details are displayed.

Field Name	Field Description
------------	-------------------

Currency Pair	This gives the currency pairs for which rate report has been generated.
Quotation	This indicates the quotation type – either direct or indirect.
No. of Units	This indicates the number of units of one currency being quoted against the other.
Rate Type	This is the rate type.
Mid Rate	This is the mid rate used for conversion.
Buy Rate	This is the buy rate used for conversion.
Sale Rate	This is the sell rate used for conversion.

42.6 Rate History Report

This section contains the following topics:

- [Section 42.6.1, "Generating Currency Rate History Report"](#)
- [Section 42.6.2, "Contents of the Report"](#)

42.6.1 Generating Currency Rate History Report

This report gives details on history of rates for currency pairs. You can invoke the screen by typing 'CYRTHIST' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

42.6.2 Contents of the Report

Header

The Header carries the title of the report, information on the branch code, branch date, the ID of the user who generated the report, the date and time at which it was generated, the module covered in the report, reporting options, currency pair, from date and to date .

Body of the report

The report is sorted by currency pairs. The following details are displayed.

Field Name	Field Description
Currency Pair	This gives the currency pairs for which rate report has been generated.
Quotation	This indicates the quotation type – either direct or indirect.
No of Units	This indicates the number of units of one currency being quoted against the other.
Rate Type	This is the rate type.
Date	The effective date of the rates applied.
Mid Rate	This is the mid rate used for conversion.
Buy Rate	This is the buy rate used for conversion.
Sale Rate	This is the sell rate used for conversion.

42.7 Customer Account Opening Confirmation Report

This section contains the following topics:

- [Section 42.7.1, "Generating Customer Account Opening Confirmation Report"](#)
- [Section 42.7.2, "Contents of the Report"](#)

42.7.1 Generating Customer Account Opening Confirmation Report

You can generate a report for the customer, confirming that his / her account with the bank has been successfully opened. This report contains the following details:

- Customer number
- Client account number
- Matter
- Account details

You can generate the Customer Account Opening Confirmation report for one customer or all the customers at once, as of a specific date. To generate the report, invoke 'Customer Account Opening Confirmation' screen.

You can invoke this screen by typing the code 'CSRACCO' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.

The screen is as shown below:

Customer Account Opening Confirmation

Customer Type ☒ All Customers ☐ Single

Customer Number

Date

Report Format

Report Output

Printer At

Printer

Ok Exit

Customer Type

You can generate customer account opening confirmation report for one or all the customers. Indicate your choice here. If you select 'Single Customer', you have to specify the customer number in the space provided.

Customer Number

If you wish to generate a report specific to one customer, specify the customer number. The option list displays all valid customer numbers maintained in the system. Select the appropriate one.

Date

Specify the date as of which you want to generate the report.

Once you have set the preferences, click 'OK' button. The system displays the print option screen, where you can set your preferences as to viewing and printing the report.

42.7.2 Contents of the Report

The contents of the report are discussed under the following heads:

Header

The Header carries the title of the report, information on the branch code, the date and time, the branch date, the user id, the module name and the page number of the report.

Body of the Report

Field Name	Field Description
Customer Name	Indicates the name of the customer
Customer Number	Indicates the customer number
First Nominee	Indicates the name of the first nominee
Second Nominee	Indicates the name of the second nominee
Address	Indicates the contact address for the customer whose cheque has been rejected.
Client Account Number	Indicates the Account Number of the client

42.8 Account Closing Confirmation Report


This section contains the following topics:

- [Section 42.8.1, "Generating Account Closing Confirmation Report"](#)
- [Section 42.8.2, "Contents of Report"](#)

42.8.1 Generating Account Closing Confirmation Report

This report gives details about closing confirmation of an account in 'Account Closing Confirmation' screen. To invoke this screen, type 'CSRPACCC' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:



42.8.2 Contents of Report

The contents of account closing confirmation have been discussed under the following heads:

Header

The Header carries the title of the report, information on the branch code, the ID of the user who generated the report, the date and time at which it was generated, the modules covered in the report and customer number of the account holder for whom the report is being generated.

Body

You can find the following details in the body of the report:

Field Name	Field Description
Client Number	The account number of the client

42.9 Activity Journal Report

This section contains the following topics:

- [Section 42.9.1, "Generating Activity Journal Report"](#)
- [Section 42.9.2, "Contents of Report"](#)

42.9.1 Generating Activity Journal Report

This report gives details about activity journal in 'Core Activity Journal' screen. To invoke this screen, type 'CSRPACTJ' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Core Activity Journal

From Date _____ To Date _____

Report For _____

Type ☒ All Modules ☐ Selected Modules

Report

1 Of 1 + -

Module

Report Format Report Output

Printer At Printer _____

From Date

Specify the start date of the report date range. The system will include the details of the record from this date.

To Date

Specify the end date of the report date range. The system will include the details of the record until this date.

Report For

Specify whether you want to generate the report for all the modules or selected modules alone. If you select 'Selected Modules', you need to specify the modules below.

Module

If you need to generate the report for selected modules, you need to indicate the modules here. Use the add button to add more modules.

42.9.2 Contents of Report

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

Header

The Header carries the title of the report, information on the branch code, the ID of the user who generated the report, the date and time at which it was generated and the modules covered in the report.

Body

You can find the following details in the body of the report:

Field Name	Field Description
Module	The module for which the report is being generated
Product Type	The type of product for which the report is being generated
Contract Ref No	The reference number of the contract being reported
Counter Party No	The CIF ID of the customer involved
Counter Party Name	This is the name of the customer involved
User Def. Status	The status if the user defined elements
Event Date	The date on which the event took place
Seq. No	The sequence number of the event
Event Description	The description of the event
Contract Status	The status of the contract i.e., active, closed etc.
Maker ID	The identification number of the maker
Checker ID	the identification number of the checker
Reversed Seq. No.	The reversed sequence number

42.10 Core Exception Report

This section contains the following topics:

- [Section 42.10.1, "Generating Core Exception Report"](#)
- [Section 42.10.2, "Contents of Report"](#)

42.10.1 Generating Core Exception Report

This report gives details about core exception in 'Core Exception' screen. To invoke this screen, type 'CSRPEXCP' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

From Date

Specify the start date of the report date range. The system will include the details of the record from this date.

To Date

Specify the end date of the report date range. The system will include the details of the record until this date.

Report For

Specify whether you want to generate the report for all the modules or selected modules alone. If you select 'Selected Modules', you need to specify the modules below.

Selected List

If you need to generate the report for selected modules, you need to indicate the modules here. Use the add button to add more modules.

42.10.2 Contents of Report

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

Header

The Header carries the title of the report, information on the branch code, the branch date, the ID of the user who generated the report, the date and time at which it was generated and the modules covered in the report.

Body

You can find the following details in the body of the report:

Field Name	Field Description
Module	The module for which the report is being generated

Contract Ref No	The reference number of the contract being reported
Counter Party	The name of the counter party
Counter Party Name	The name of the counter party involved
Event Description	The description of the event
Exception	The description about the exception

42.11 Uncollected Funds Report

This section contains the following topics:

- [Section 42.11.1, "Generating Uncollected Funds Report"](#)
- [Section 42.11.2, "Contents of Report"](#)

42.11.1 Generating Uncollected Funds Report

This report provides details of uncollected funds based on release date of the fund'. You can invoke this screen by typing 'ACRUNCOL' in the field at the top right corner of the application tool bar and clicking the adjoining arrow button.

Specify the following details.

Accounts

Select the account for which the report is to be generated. The options are:

- All - System fetches all the accounts which has uncollected funds.
- One - If this option is selected, system fetches the report for a particular account, which is selected in the option list.

Date option

Select the date for which report has to be generated:

- Present Date: System fetches the uncollected fund which are available in the current date

- Between dates: If between dates is selected then From date and to date is mandatory. System fetches the Uncollected fund details which are available in between dates.

From Date

Specify the From date.

To Date

Specify the To date.

42.11.2 Contents of Report

Header

The Header carries the title of the Report, information on the branch code, the branch date, the user ID, the module name, the date and time at which the report was generated and the page number of the report.

Body of the report

The details of the uncollected funds that would be displayed in the report are as follows:

Field Name	Field Description
Account	This is the account for which transaction details is being reported
Available Date	This indicates the available date
Transaction Reference	This is the reference number of the transaction for which account has uncollected balance
Amount	This is the uncollected amount in the account
Total Amount	This is the total uncollected amount in the account

42.12 Account Revaluation Report

This section contains the following topics:

- [Section 42.12.1, "Generating Account Revaluation Report"](#)
- [Section 42.12.2, "Contents of Report"](#)

42.12.1 Generating Account Revaluation Report

This report gives details of the memo revaluation funds. You can invoke this screen by typing 'ACRREVAL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

LBL_ACCT_REVAL_REPT

☒ Memo
☐ Normal

Branch Date _____

Report Format PDF
Report Output View

Printer At Client
Printer _____

Ok Exit

Memo or Normal

Specify the type of account revaluation report.

42.12.2 Contents of Report

Header

The Header carries the title of the Report, information on the branch code, the branch date, the user ID, the module name, the date and time at which the report was generated and the page number of the report.

Body of the report

The details of the uncollected funds that would be displayed in the report are as follows:

Field Name	Field Description
Currency	This is the currency for which transaction details is being reported
Revaluation Rate	This is the revaluation rate
Account	This is the account for which transaction details is being reported
Description	This is the description provided
Account Revalued	This is the revalued account
Account Balance	This indicated the account balance

LCY Equivalent (before revaluation)	This indicates the amount equivalent to local currency before revaluation
LCY Equivalent (after revaluation)	This indicates the amount equivalent to local currency after revaluation
Profit/ Loss	This is the profit or loss incurred
Profit/ Loss Amount	This is the profit or loss amount
P&L Account	This is the profit or loss account
Currency	This is the currency for which transaction details is being reported
Rate	This is the revaluation rate
Category	This is the GL category

42.13 Accounts Movement Report

This section contains the following topics:

- [Section 42.13.1, "Generating Accounts Movement Report"](#)
- [Section 42.13.2, "Contents of Report"](#)

42.13.1 Generating Accounts Movement Report

This report gives details of the movement of the accounts for that particular day. You can invoke this screen by typing 'ACRPMOVE' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

From Date

Specify the From Date from the option list.

To Date

Specify the To Date from the option list.

Account Number

Specify the account number from the option list.

Value Dated

Select if the report is value dated.

Booking Dated

Select if the report is booking dated.

Currency

Specify the currency from the option list.

Account Selection

Specify the type of account selection.

42.13.2 Contents of Report

Header

The Header carries the title of the Report, information on the branch code, the branch date, the user ID, the module name, the date and time at which the report was generated and the page number of the report.

Body of the report

The details of the uncollected funds that would be displayed in the report are as follows:

Field Name	Field Description
Account Number	This is the account number
Account Description	This is the brief description for the account
Account Currency	This is the currency of the account
Opening Balance	This is the opening balance of the account
FCY Amount	This is the opening balance of account in FCY
LCY Amount	This is the opening balance of account in LCY
Transaction Date	This is the transaction date
Transaction Description	This is a brief description of the transaction
Transaction Reference Number	This is the reference number of the transaction posted to account
Value Date	This is the value date of transaction
FCY Amount	This is the amount of transaction in Foreign Currency
Rate	This is the exchange rate for FCY and LCY

LCY Amount	This is the amount of transaction in Local Currency
Current Balance	This is the current balance in the account

42.14 Customer Details Report

This section contains the following topics:

- [Section 42.14.1, "Generating Customer Details Report"](#)
- [Section 42.14.2, "Contents of Report"](#)

42.14.1 Generating Customer Details Report

This report gives details of the customer and you can generate this report using the 'Customer Details' screen.

You can invoke this screen by typing 'STRCIF' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

42.14.2 Contents of Report

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

Header

The Header carries the branch, information on the branch date, the user ID, the module name, the date and time at which the report was generated and the page number of the report.

Body of the report

The details of the customer information details that would be displayed in the report are as follows

:

Field Name	Description
Customer Information	
Customer	Customer Identification Number of the customer
Customer Name	Customer name
Address lines	Displays the address of the customer.
Country	The country the customer belongs to.
Nationality	The nationality of the customer.
Type	Type of the customer (individual or Corporate or Bank).
Unique ID Name	Displays the customer's unique id name.
Unique ID Value	Displays the customer's unique id value.
Creation Date	Displays the date of customer's number creation.
Input By	The Login ID of the user that created the customer record.
Input Date and Time	The date the customer record was created.
Auth By	The Login ID of the user that has authorized the record.
Auth Date and Time	The date of the authorization.
Mod Number	Displays the number of times the record was modified.
Auth Stat	Displays the current status of the customer record.
Record	Displays the record status.
Exposure Country	Displays the exposure country details.
Frozen	Displays the frozen status of the customer's account.
Local Branch	Displays the customer's local branch details.
Whereabouts Unknown	Gives the customer's details regarding the whereabouts.
Deceased	Indicates whether the customer is fit or deceased.

Short Name	Customer's abbreviated name.
Liability	This is the customer Liability ID number for which credit facility granted to the customer.
Language	Language.
Category	Category of the customer of the bank.
Professional Details	
Designation	Indicates Designation
Employer	Indicates Employer
Status	Indicates Status
Tenure	Indicates Tenure
Address	Indicates Address
Email	Indicates Email
Fax	Indicates Fax
Phone	Indicates Phone
Telex	Indicates Telex
Home Value	Indicates Home Value
Insurance	Indicates Insurance
Loans	Indicates Loans
Expenses	Indicates Expenses
Income	Indicates Income
Previous Designation	Indicates Previous Designation
Previous Employer	Indicates Previous Employer
Rent	Indicates Rent
Ret Age	Indicates Ret Age
Credit Cards	Indicates Credit Cards

IE Currency	Indicates IE Currency
Salary	Indicates Salary
Corporate Details	
National Id	Indicates National Id
Name	Indicates Name
Currency Of Amounts	Indicates Currency Of Amounts
Incorporation Country	Indicates Incorporation Country
Incorporation Date	Indicates Incorporation Date
Net worth	Indicates Net worth
Capital	Indicates Capital
Registered Address	Indicates Registered Address
Address 2	Indicates Address 2
Address 3	Indicates Address 3
Country	Indicates Country
Business	Indicates Business
Director Name	Indicates Director Name
Personal Details	
Prefix	Indicates Prefix
First Named	Indicates First Named
Middle Name	Indicates Middle Name
Last Name	Indicates Last Name
Date Of Birth	Indicates Date Of Birth
Sex	Indicates Sex
Domicile	Indicates Domicile

Line 2	Indicates Line 2
Line 3	Indicates Line 3
Domicile Cntry	Indicates Domicile Cntry
Minor	Indicates Minor
Legal Guard.	Indicates Legal Guard.
Passport Number	Indicates Passport Number
Issue Date	Indicates Issue Date
Expiry Date	Indicates Expiry Date
Permanent Address	Indicates Permanent Address
Address	Indicates Address
Country	Indicates Country
National Id	Indicates National Id
Phone	Indicates Phone
Telex	Indicates Telex
Email	Indicates Email
Fax	Indicates Fax
Domestic Details	Indicates Domestic Details
Accommodation	Indicates Accommodation
Dependent Child	Indicates Dependent Child
Dependent Other	Indicates Dependent Other
Education	Indicates Education
Marital Status	Indicates Marital Status
Spouse	Indicates Spouse
Spouse Employment Status	Indicates Spouse Employment Status

42.15 Customer Accounts Report


This section contains the following topics:

- [Section 42.15.1, "Generating Customer Accounts Report"](#)
- [Section 42.15.2, "Contents of Report"](#)

42.15.1 Generating Customer Accounts Report

This report gives details of the customer account and you can generate this report using the 'Customer Accounts' screen.

You can invoke this screen by typing 'STRCUSAC' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



42.15.2 Contents of Report

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

Header

The Header carries the branch, information on the branch date, the user ID, the module name, the date and time at which the report was generated and the page number of the report.

Body of the report

The details of the customer accounts details that would be displayed in the report are as follows:

Field Name	Field Description
Account Number	Details about customer account Number
Account Class	Details about account class
Account Description	Account Description

Opening Date	The opening date of the account.
Dormant	The account status as dormant
Frozen	Account status as frozen.
No Credits	Gives no credit status of the account number.
No Debits	Gives no debit status of the account number.
Stop Payments	Gives the accounts stop pay status.
Statement Cycle	Gives the account statement cycle.
Statement Day	Gives the account statement day.
Statement Type	Gives account statement type.
Alternate Account Number	Gives an alternative account number.
Branch Code	Gives the branch code.
Currency	Currency
Customer Number	Gives customer number.
Nominee1	Gives the first nominee details
Nominee2	Gives the second nominee details
Account Type	Gives the account type.
Dr GL	Gives all debit balances within a specific account class
Cr GL	Gives all credit balances within a specific account class.
Dr HO Line	In this, all accounts belonging to account class will report, if they move to the status being defined.
Cr HO Line	In this, all accounts belonging to account class will report, if they move to the status being defined.
Dr CB Line	This is a GL to which all debit accounts belonging to an account class should report to.
Cr CB Line	This is a GL to which all credit accounts belonging to an account class should report to.
ATM Facility	Availability of ATM facility.

Cheque Book Facility	Availability of cheque book facility.
Passbook Facility	Availability of passbook facility.
Previous Statement Date	Gives the date of the previous statement.
Previous Statement Balance	Gives the balance of the previous statement.
Previous Statement Number	Gives the number of the previous statement
TOD Limit	The temporary overdraft limit facility granted to the customer account
Sublimit	It the overdraft facility maximum permitted to this account associated and tracked against the line id maintained for the liability.
Limit Currency	Displays the currency code of the limit
TOD Limit Start Date	The start date for the temporary overdraft facility
TOD Limit End Date	The end date for the temporary overdraft facility.
Uncollected Funds Limit	The funds hit the account which are debited / credited to the account with effect from the mentioned value days
Line ID	The line code is associated with the liability ID against which the overdraft facility is being tracked.
Tanked Status	It is the status of the transaction that hit the account in a specific branch once the branch is marked for EOTI.
Account Balance	Gives the total account balance
Maker ID	The identification number of the maker
Maker Date Stamp	This is the date on which the contract was uploaded.
Checker ID	This is the Login ID of the user who authorized the product.
Checker Date Stamp	This is the date on which the product was authorized.
Mod Number	Displays the number of times the record was modified.
Record Stat	Displays the current status of the external account record.
Authorization Status	Displays the current authorization status of the record.
Joint Holder Code	Displays joint holder CIF ID

Joint Holder Description	Displays description of the joint holder
Joint Holder	Displays linked entities of the joint holder

42.16 Document Check List Report

This section contains the following topics:

- [Section 42.16.1, "Generating Document Check List Report"](#)
- [Section 42.16.2, "Contents of the Report"](#)

42.16.1 Generating Document Check List Report

This report gives you the details of the customer account whose documents are pending for submission, expired, or about to expire.

You can invoke this screen by typing 'STRDOCL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Branch Code

Specify the branch code

Document Status

Specify the status of the document submitted by the customer from the adjoining option list. You can select one of the following:

- Pending
- About to Expire
- Expired

Note

- If you select the document status as 'About to Expire', then the 'From Date' should be greater than the current date.
 - If you select the document status as 'Expired', then the 'To Date' should be less than the current date.
-

From Date

Specify the date from which details should be made available in the report. The system will include all customers whose date is equal to or greater than this date.

To Date

Specify the date till which details should be made available in the report. The system will include all customers whose date is equal to or lesser than this date.

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location

Printer

Select printer using which you wish to print the report from the adjoining option list.

42.16.2 Contents of the Report

Header

The Header carries the title of the report, information on the branch code, the ID of the user who generated the report, the date and time at which it was generated and the modules covered in the report.

Body of the Report

Field Name	Field Description
Branch Code	Current branch code
Customer Number	Customer identification number
Customer Name	Customer name
Customer Account Number	Customer account number
Document Type	Type of document
Expiry Date	Expiry date of the document
Expected Date of Submission	Expected date of document submission
Actual Submission Date	Actual document submission date

42.17 Memo Revaluation Report

This section contains the following topics:

- [Section 42.17.1, "Generating Memo Revaluation Report"](#)
- [Section 42.17.2, "Contents of Report"](#)

42.17.1 Generating Memo Revaluation Report

You can invoke this screen by typing 'ACRMREVL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a window titled "Memo Revaluation Report". At the top, there are two groups of controls. On the left, "Report Format" is set to "PDF" and "Report Output" has a "View" button. On the right, "Printer At" is set to "Client" and there is a "Printer" label followed by a blank text field. The main area of the window is empty. At the bottom right, there are "Ok" and "Exit" buttons.

42.17.2 Contents of Report

Header

The Header carries the title of the Report, information on the branch code, the branch date, the user ID, the module name, the date and time at which the report was generated and the page number of the report.

Body of the Report

Field Name	Field Description
Currency	This is the currency for which transaction details is being reported
Revaluation Rate	This is the revaluation rate
Account	This is the account for which transaction details is being reported
Description	This is the description provided
Account Revalued	This is the revalued account
Account Balance	This indicated the account balance
Lcy Equivalent (before reval)	This indicates the local currency before revaluation
Lcy Equivalent (after reval)	This indicates the local currency after revaluation
Profit/ Loss	This is the profit or loss incurred
Profit/ Loss Amount	This is the profit or loss amount
P&L Account	This is the profit or loss account
Currency	This is the currency for which transaction details is being reported
Rate	This is the revaluation rate
Category	This is the category

42.18 Black Listed During Contract Booking Report

This section contains the following topics:

- [Section 42.18.1, "Generating Black Listed During Contract Booking Report"](#)
- [Section 42.18.2, "Contents of the Report"](#)

42.18.1 Generating Black Listed During Contract Booking Report

You can invoke 'Black Listed During Contract Booking Report' screen by typing 'CSRPBLCB' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screen is as shown below:



The screenshot shows a window titled "Black Listed During Contract Booking". Inside the window, there are several input fields and dropdown menus. At the top left, there is a "Date" field. Below it, there are two rows: "Report Format" with a dropdown menu showing "PDF", and "Report Output" with a dropdown menu showing "View". To the right of these, there are two more rows: "Printer At" with a dropdown menu showing "Client", and "Printer" with an empty text field. At the bottom right of the window, there are two buttons: "Ok" and "Exit".

Date

Specify the date when the contract was black listed from the adjoining calendar.

42.18.2 Contents of the Report

The contents of the report are discussed under the following heads:

Header

The header carries the Report Name, Branch, Branch Date, User Id, Module, Run Date and Time.

Body of the Report

Field Name	Field Description
Reference Number	Indicates the reference number
Customer Number	Indicates the customer number
Customer Name	This indicates the name of the customer
Nationality	Indicates the nationality of the customer
Unique ID Name	Indicates the unique identification name
RM Code	Indicates the relationship manager code
RM Name	Indicates the name of relationship manager

42.19 Black List Report During File Upload Report

This section contains the following topics:

- [Section 42.19.1, "Generating Black List Report During File Upload Report"](#)
- [Section 42.19.2, "Contents of the Report"](#)

42.19.1 Generating Black List Report During File Upload Report

You can invoke 'Black List Report During File Upload' screen by typing 'CSRPBLUP' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screen is as shown below:

Black List Report During File Upload

Report Format: PDF
Report Output: View

Printer At: Client
Printer: _____

Ok Exit

42.19.2 Contents of the Report

The contents of the report are discussed under the following heads:

Header

The header carries the Report Name, Branch, Branch Date, User Id, Module, Run Date and Time.

Body of the Report

Field Name	Field Description
Customer Number	Indicates the customer number
Customer Name	This indicates the name of the customer
Nationality	Indicates the nationality of the customer
Unique ID Name	Indicates the unique identification name
Unique ID Value	Indicates the unique identification value
RM Code	Indicates the relationship manager code
RM Name	Indicates the name of relationship manager

42.20 Cheque Book Issued Report

This section contains the following topics:

- [Section 42.20.1, "Generating Cheque Book Issued Report"](#)
- [Section 42.20.2, "Contents of the Report"](#)

42.20.1 Generating Cheque Book Issued Report

You can invoke 'Cheque Book Issued Report' screen by typing 'CSRPCHB' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screen is as shown below:

Cheque Book Issued Report

☒ All Branches
☐ Single Branch

Branch _____

Date Range

From Date * _____

To Date * _____

Report Format PDF ▾

Report Output View ▾

Printer At Client ▾

Printer _____

Ok Exit

Branch Code

You can generate this report for all the branches or a single branch alone. You can indicate the branch for which the report is being generated using the following options:

- All – If you choose this, the system will generate the report for all the branches.
- Single – If you choose this, you need to specify the branch code for which the report should be generated. The option list displays all valid branch codes maintained in the system. Choose the appropriate one.

Date Range

From Date

Specify a valid date from when you wish to generate the report from the adjoining calendar.

To Date

Specify a valid date till when you wish to generate the report from the adjoining calendar.

42.20.2 Contents of the Report

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

Header

The header carries the Report Name, Branch, Branch Date, User Id, Module, Run Date and Time.

Body of the Report

Field Name	Field Description
Date of Issue	Indicates the date of issue
Issuing Channel	Indicates the Issuing Channel
Account Number	Indicates the account number
Account Currency	Indicates the account currency
Account Name	Indicates the account name
Serial Number	Indicates the serial number
Maker ID	Indicates the maker ID
Checker ID	Indicates the checker ID

42.21 Demand Draft Issued Report

This section contains the following topics:

- [Section 42.21.1, "Generating Demand Draft Issued Report"](#)
- [Section 42.21.2, "Contents of the Report"](#)

42.21.1 Generating Demand Draft Issued Report

You can invoke 'Demand Draft Issued Report' screen by typing 'CSRPDDRP' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screen is as shown below:

Demand Draft Issued Report

☒ All Branches
☐ Single Branch

Branch

Report Format: PDF
Report Output: View

Printer At: Client
Printer:

Ok Exit

Branch Code

You can generate this report for all the branches or a single branch alone. You can indicate the branch for which the report is being generated using the following options:

- All – If you choose this, the system will generate the report for all the branches.

- Single – If you choose this, you need to specify the branch code for which the report should be generated. The option list displays all valid branch codes maintained in the system. Choose the appropriate one.

42.21.2 Contents of the Report

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

Header

The header carries the Report Name, Branch, Branch Date, User Id, Module, Run Date and Time.

Body of the Report

Field Name	Field Description
Account Number	Indicates the account number
Account Name	This indicates the name of the account
Currency	Indicates the currency of the account
Amount	Indicates the amount
Instrument Number	Indicates the instrument number
Description	Indicates the description of the demand draft
Cheque Number	Indicates the Cheque Number
Drawn On	Indicates the date when the DD was drawn
Input On	Indicates the date when the data was provided
Reference Number	Indicates the reference number
Maker ID	Indicates the identification of the maker of the record
Maker Date Stamp	Indicates the date when the record was created
Checker ID	Indicates the identification of the checker who authorized the record
Checker Date Stamp	Indicates the date on which the record was authorized

42.22 PDC Input Report


This section contains the following topics:

- [Section 42.22.1, "Generating PDC Input Report"](#)
- [Section 42.22.2, "Contents of the Report"](#)

42.22.1 Generating PDC Input Report

You can invoke 'PDC Input Report' screen by typing 'CSRPPDC' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screen is as shown below:



PDC Input Report

Report Format PDF

Report Output View

Printer At Client

Printer

Ok Exit

42.22.2 Contents of the Report

The contents of the report are discussed under the following heads:

Header

The header carries the Report Name, Branch, Branch Date, User Id, Module, Run Date and Time.

Body of the Report

Field Name	Field Description
Account Number	Indicates the account number
Account Name	This indicates the name of the account
Currency	Indicates the currency of the account
Amount	Indicates the amount
Instrument Number	Indicates the instrument number
Bank Name	Indicates the name of the bank
Clearing Date	Indicates the date of clearing
Value Date	Indicates the value date of the demand draft
Maker ID	Indicates the identification of the maker of the record
Maker Date Stamp	Indicates the date when the record was created
Reference Number	Indicates the reference number

42.23 Temporary Overdraft Report

This section contains the following topics:

- [Section 42.23.1, "Generating Temporary Overdraft Report"](#)
- [Section 42.23.2, "Contents of the Report"](#)

42.23.1 Generating Temporary Overdraft Report

You can invoke 'Temporary Overdraft Report' screen by typing 'CSRTEMOD' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screen is as shown below:

Temporary Overdraft Report

Branch Details

☒ All
☐ Single

Branch Code

Report Format PDF

Report Output View

Customer

Customer Type

☐ Bank
☐ Corporate
☐ Individual
☒ All

Printer At Client

Printer

Ok Exit

Branch Code

You can generate this report for all the branches or a single branch alone. You can indicate the branch for which the report is being generated using the following options:

- All – If you choose this, the system will generate the report for all the branches.
- Single – If you choose this, you need to specify the branch code for which the report should be generated. The option list displays all valid branch codes maintained in the system. Choose the appropriate one.

Customer Type

Select the type of customer from the following options provided:

- Bank
- Corporate
- Individual
- All

42.23.2 Contents of the Report

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

Header

The header carries the Report Name, Branch, Branch Date, User Id, Module, Run Date and Time.

Body of the Report

Field Name	Field Description
Customer Account Number	Indicates the customer account number
Customer Name	This indicates the name of the customer
Customer Type	Indicates the type of customer
Account Description	Displays the description for the account
Branch	Indicates the branch of the account
Customer Number	Indicates the customer number
Account Class	Indicates the account class of the customer
Customer Category	Indicates the category to which customer belong to
MIS Code	Indicates the MIS code
Currency	Indicates the currency of the account
Holding Amount	Indicates the holding amount
LCY Opening Balance	Indicates the opening balance in local currency
ACY Opening Balance	Indicates the opening balance of the account currency
ACY Available Balance	Indicates the available balance of the account currency
ACY Current Balance	Indicates the current balance of the account currency
Temp OD Since	Indicates the date when the temp OD was started
Overdraft Since	Indicates the date when the overdraft was started
Temp OD Debits Today	Indicates the day's temp OD debits
Temp OD Credits Today	Indicates the day's temp OD credits


42.24 Daily Sales Report

This section contains the following topics:

- [Section 42.24.1, "Generating Daily Sales Report"](#)
- [Section 42.24.2, "Contents of the Report"](#)

42.24.1 **Generating Daily Sales Report**

You can invoke the screen by typing the code 'CORDSLRP' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.



You can specify the following parameters here:

Branch Code

Specify the branch code from the adjoining option list.

From Date

Specify a valid date from when you wish to generate the report from the adjoining calendar.

To Date

Specify a valid date till when you wish to generate the report from the adjoining calendar.

42.24.2 **Contents of the Report**

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

Header

The following details are displayed in the header section:

Field Name	Field Description
Branch	Indicates Branch Code and Branch Name
Branch Date	Indicates Current Date of the Branch
User ID	Indicates User ID
Date & Time	Indicates the Date and Time when the report was generated

Module	Indicates module for which report is generated.
--------	---

Body of the Report

The following details are displayed as body of the generated report:

Field Name	Field Description
Module	Indicates the module code
Outstanding Amount	Indicates the outstanding amount
Product Code	Indicates the product code
Customer ID	Indicates the customer ID
Customer Name	Indicates the name of the customer
Product Description	Indicates the product description
Account Number	Indicates Customer Account number
Booking Date	Indicates the date of booking
Branch Name	Indicates Branch Name
RM Code	Indicates the relationship manager code
DS Code	Indicates the DS code


42.25 Customer Restriction Utilization Report

This section contains the following topics:

- [Section 42.25.1, "Generating Customer Restriction Utilization Report"](#)
- [Section 42.25.2, "Contents of the Report"](#)

42.25.1 Generating Customer Restriction Utilization Report

In this report, details of customer restrictions for a particular period is generated. You can invoke this screen by typing 'CSRRSTRP' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



To generate the report, enter the following details:

Customer Number

Select the customer number from the adjoining option list. All customer numbers as maintained in the system are displayed.

Restriction Code

Select the restriction code from the adjoining option list. The restriction code as maintained in the 'Restriction Code Maintenance' screen is displayed.

Start Date

Specify the start date for which the data needs to be generated.

End Date

Specify the end date for which the data needs to generated.

42.25.2 Contents of the Report

The following details of the report are displayed:

Field Name	Field Description
Customer Number	Indicates the customer number.
Customer Name	Indicates the name of the customer.
Account Number	Indicates the account number of the customer.
Transaction Date	Indicates the date of the transaction.
Transaction Reference Number	Indicates the reference number of the transaction.
Transaction Currency	Indicates the currency of the transaction.

Transaction Amount	Indicates the transaction amount.
Transaction Currency	Indicates the currency of the transaction amount.
Restriction Code	Indicates the Restriction Code for the transaction.
Restriction Description	Indicates the description of the transaction.
Restriction Period	Indicates the restriction period
Restriction Amount	Indicates the restriction amount
Restriction Currency	Indicates the restriction currency
Start Date	Indicates the Start Date of the Report
End Date	Indicates the End Date of the Report
Utilized Limit	Indicates the utilized restriction amount.

42.26 Integrating Oracle Business Intelligence Enterprise Edition

Oracle Business Intelligence Enterprise Edition (OBIEE) can be integrated with the Oracle FLEXCUBE LCM application. This will enable you to invoke all OBIEE reports or dashboards from the LCM dashboard menu screen. To integrate OBIEE with the application refer to the following steps:

When the user logs into the application, the OBIEE report/dashboard is displayed in the LCM dashboard menu screen.

1. Create a report or dashboard in OBIEE and name this report or dashboard using the function ID naming convention followed in Oracle FLEXCUBE.
2. Create a new function ID in the
3. 'Function Description Maintenance' screen (SMDFNDSC). The function ID created in this screen should be the same as the OBIEE report or dashboard name. For more information on creating a new function ID, refer to the section 'Maintaining Function Descriptions' in this User Manual.
4. Create a role for this function ID in the 'Role Maintenance' screen (SMDROLDF) and add the function to this role. For more information on creating a role refer to the section 'Defining a User Role' in this User Manual.
5. Add a user to this role in the 'User Maintenance' screen (SMDUSRDF). For more information on adding the user to a role, refer to the section 'Defining and Maintaining System Users' in this user manual.

In the following screen shot the 'Show Dashboard' and 'Alerts on Home' is displayed as Y which indicates the Alerts and Dashboard have been added to the home screen. These values are defaulted from the User Settings in the home screen

The screenshot shows the 'User Maintenance' application window. The 'User Details' section includes fields for User ID (35718C), Name (Default Admin User2), User Reference, Language (ENG), Home Branch (001), Customer Number, LDAP DN, Time Level (9), Amount Format, Date Format, Supervisor Id, Show Dashboards (Y), and Alerts On Home (Y). The 'User Password' section includes Password (masked), Password Changed On (2015-07-07), Force Password Change (unchecked), User Email, Start Date (2014-10-21), End Date, Screensaver Interval (in seconds), and External Alerts (unchecked). The 'Invalid Logins' section shows Cumulative (3) and Successive (1). The bottom status bar displays 'Restricted Password', 'Roles', 'Functions', 'User Branches Restrictions', 'Disallowed Functions', 'Maker 294/90C', 'Checker 294/90C', 'Date Time: 2015-01-06 12:24:53', 'Med No: 5', 'Record Status Open', and 'Authorization Status: Authorized'.

When the user logs into the application, the OBIEE report/dashboard is displayed in the ELCM dashboard menu screen.

43. Function ID Glossary

C

CADIBMNT	8-6
CGDUEHOL	27-1
CODCATGY	32-6
CODELREP	32-13
CODEXPTY	32-7
CODGROUP	32-8
CODHCUTT	32-9
CODLOCCD	32-10
CODTYPES	32-11
CODUIDN	32-12
CSCEXWSM	7-3
CSCEXWSO	7-2
CSDACCTR	6-3
CSDACLOG	6-5
CSDACLTR	6-6
CSDACTRP	6-1
CSDDOCHK	30-3
CSDDOCTY	30-1
CSDEXTWS	7-1
CSDEXWSD	7-4
CSDFTRMN	32-6
CSDMULPM	32-20
CSDOVCNV	31-4
CSDOVDME	31-2, 31-3
CSDPRDRS	10-1
CSDSCPRM	12-4
CSDSNCKM	12-1
CSDXCCLM	13-15
CSSDOCHK	30-4
CSSDOCTY	30-2
CSSMULPM	32-21
CSSPRDRS	10-3
CSSSNCKM	12-3
CSSSNCQU	12-5

I

ISDBICPU	28-1
----------------	------

L

LDDCLUST	18-1
LDSClust	18-2

O

OVDAUDEF	37-1
----------------	------

R

RVDXSETP	26-2
----------------	------

S

SMDFNDSC	42-51
SMDROLDf	42-51
SMDUSRDF	42-51
STDCGHOL	29-2
STDCOLAT	32-15
STDCSEMP	24-1
STDCSRST	11-6
STDCTMNT	23-1
STDDLrMT	4-1
STDEMPMT	25-1
STDEQACD	9-1
STDGIINM	2-35
STDLMBAL	32-18
STDLMRVL	16-1
STDNONFA	20-5
STDPRCDE	19-1
STDRSINQ I	11-7
STDRSTMT	11-1
STDTRFQ	9-4
STDTRNCD	21-1
STDTRNCH	2-36
STDTRNTX	22-1
STSCSEMP	24-2
STSCTMNT	23-2
STSEMPMT	25-2
STSLMRVL	16-3
STSRSTMT	11-5
STSTRNTX	22-2