

Retek® Merchandising System™ 10.1.6

Installation Guide



The software described in this documentation is furnished under a license agreement, is the confidential information of Retek Inc., and may be used only in accordance with the terms of the agreement.

No part of this documentation may be reproduced or transmitted in any form or by any means without the express written permission of Retek Inc., Retek on the Mall, 950 Nicollet Mall, Minneapolis, MN 55403, and the copyright notice may not be removed without the consent of Retek Inc.

Information in this documentation is subject to change without notice.

Retek provides product documentation in a read-only-format to ensure content integrity. Retek Customer Support cannot support documentation that has been changed without Retek authorization.

Corporate Headquarters:

Retek Inc.

Retek on the Mall

950 Nicollet Mall

Minneapolis, MN 55403

888.61.RETEK (toll free US)

+1 612 587 5000

European Headquarters:

Retek

110 Wigmore Street

London

W1U 3RW

United Kingdom

Switchboard:

+44 (0)20 7563 4600

Sales Enquiries:

+44 (0)20 7563 46 46

Fax: +44 (0)20 7563 46 10

Retek® Merchandising System™ is a trademark of Retek Inc.

Retek and the Retek logo are registered trademarks of Retek Inc.

This unpublished work is protected by confidentiality agreement, and by trade secret, copyright, and other laws. In the event of publication, the following notice shall apply:

©2003 Retek Inc. All rights reserved.

All other product names mentioned are trademarks or registered trademarks of their respective owners and should be treated as such.

Printed in the United States of America.

Customer Support

Customer Support hours

Customer Support is available 7x24x365 via e-mail, phone, and Web access.

Depending on the Support option chosen by a particular client (Standard, Plus, or Premium), the times that certain services are delivered may be restricted. Severity 1 (Critical) issues are addressed on a 7x24 basis and receive continuous attention until resolved, for all clients on active maintenance. Retek customers on active maintenance agreements may contact a global Customer Support representative in accordance with contract terms in one of the following ways.

Contact Method	Contact Information
E-mail	support@retek.com
Internet (ROCS)	rocs.retek.com Retek's secure client Web site to update and view issues
Phone	1 612 587 5800
Toll free alternatives are also available in various regions of the world:	
Australia	1 800 555 923 (AU-Telstra) or 1 800 000 562 (AU-Optus)
France	0800 90 91 66
United Kingdom	0800 917 2863
United States	1 800 61 RETEK or 800 617 3835
Mail	Retek Customer Support Retek on the Mall 950 Nicollet Mall Minneapolis, MN 55403

When contacting Customer Support, please provide:

- Product version and program/module name.
- Functional and technical description of the problem (include business impact).
- Detailed step by step instructions to recreate.
- Exact error message received.
- Screen shots of each step you take.

Contents

Chapter 1 – Database server installation instructions 1

Mount CD-ROM on the Database Server	1
Update XML DDL	2
Update DDL	2
Update control tables.....	2
Update packages, stored procedures and functions.....	3
Recompile libraries and batch programs	3

Chapter 2 – Application Server installation instructions 5

UNIX Application Server installation instructions	5
---	---

Chapter 1 – Database server installation instructions

Before you apply the RMS 10.1.6 patch:

- Make a backup of all your objects and database schema.
- Check that RMS 10.1.5 is installed.
- Review the enclosed RMS 10.1.6 Patch Release Notes (rms-1016-rn.pdf).
- Review each of the enclosed SIR documents.

Before copying over any files:

- Note whether customizations have been made to the module. If so, then the customizations must be reapplied over the new version of the module (or the fix may need to be applied to the custom version of the code).
- Copy the original files to a different directory before copying over them in case they need to be referred to at a later date.

Note: These instructions refer to rmsdev10 as the Oracle owning schema.

Mount CD-ROM on the Database Server

- 1 Mount the CD-ROM on your Database Server.
- 2 Copy the rms1016dbpatch.tar.Z file from the CD /dbserverunix directory to a newly created staging directory on your UNIX server.
- 3 Log in to UNIX.
- 4 Change directories to the staging directory.

Note: The tar file must have a .Z extension.

- 5 If the tar file has a “z” in lowercase, change it by typing:

```
mv rms1016dbpatch.tar.z rms1016dbpatch.tar.Z
```

- 6 Uncompress the tar file by entering:

```
uncompress rms1016dbpatch.tar.Z
```

- 7 Untar the tar file by entering:

```
tar xvf rms1016dbpatch.tar
```

Update XML DDL

Note: This script will attempt to drop tables that may not exist in the database. This is done to insure that the correct table is being created.

- 1 Log in to UNIX as the retek user.
- 2 Change directories to <staging area>/xml.
- 3 Review and understand the scripts before running them.
- 4 If you have customized any objects, make modifications.
- 5 Log in to SQLPLUS as the rmsdev10 user.
- 6 Enter the following command:
`SQL> @patch1016xml.sql`
- 7 View the spool file patch1016xml.log when finished to verify that no errors were found.

Update DDL

Note: This script will attempt to drop a number of objects that may not exist in the database. This is done to insure that the correct object is being created.

- 1 Change directories to <staging area>/dbcs.
- 2 Review and understand the scripts before running them.
- 3 If you have customized any objects, make modifications.
- 4 Log in to SQLPLUS as the rmsdev10 user.
- 5 Enter the following command:
`SQL> @patch1016dbcs.sql`
- 6 View the spool file patch1016dbcs.log when finished to verify that no errors were found.

Update control tables

- 1 On the server, change directories to <staging area>/sqlplus.
- 2 Log in to SQLPLUS as rmsdev10.
- 3 Enter the following command to update control tables:
`SQL> @patch1016ctl.sql`
- 4 View the spool file patch1016ctl.log when finished to verify that no errors were found.

Update packages, stored procedures and functions

- 1 On the server, change directories to <staging area>/db_objects.
- 2 Log in to SQLPLUS as rmsdev10.
- 3 Enter the following command to update packages, procedures, and functions:
SQL> @patch1016rms.sql
- 4 Exit SQLPlus.
- 5 View the spool file patch1016rms.log when finished to verify that no errors were found.

Recompile libraries and batch programs

Note: If you are using Oracle Financials please refer to Appendix A.

After the packages/procedures have been successfully compiled:

- 1 Copy the batch library from <staging area>/batch/lib/src into the appropriate directories.
- 2 Copy the base RMS C programs from <staging area>/batch/proc/src into the appropriate directories.
- 3 Compile the batch library and base RMS C programs as directed in the RMS 10.1 install guide.
- 4 Because of an addition to the make command you need to run the following command from <INSTALL_DIR>/rms/oracle/proc/src directory
`make -f rms.mk PRODUCT_PROCFLAGS=dynamic=ansi ditinsrt`

Chapter 2 – Application Server installation instructions

Note: If you have modified any forms, reports, or toolset libraries, make a backup copy so that you can reapply any custom modifications.

UNIX Application Server installation instructions

- 1 Mount the CD-ROM on your UNIX Application Server.
- 2 Change directories to /appserverunix.
- 3 Copy the rms1016apppatch.tar.Z file from the CD /appserverunix directory to a newly created staging directory on your UNIX Application server.
- 4 Log in to UNIX.
- 5 Change directories to the staging directory.

Note: The tar file must have a .Z extension.

- 6 If the tar file has a Z in lowercase, change it by typing:
`mv rms1016apppatch.tar.z rms1016apppatch.tar.Z`
- 7 Uncompress the tar file by entering:
`uncompress rms1016apppatch.tar.Z`
- 8 Untar the tar file by entering:
`tar xvf rms1016apppatch.tar`
- 9 Make sure your UNIX environment is set up properly to compile Oracle Forms (see the RMS 10.1 installation guide for more information).
- 10 Copy the RMS reference forms source code (*.fmb) located on UNIX in the <staging area>/toolset/src to your UNIX Web forms src directory.
- 11 In the toolset src directory, compile the RMS reference forms (*.fmb) as outlined in the RMS 10.1 installation guide, Appendix B.
- 12 Move all compiled reference forms in the toolset src directory to the bin directory.
- 13 Copy the RMS forms source code (*.fmb and .mmb) located on UNIX in the <staging area>/forms/src to your UNIX Web forms src directory.
- 14 In the Web forms src directory, compile the RMS forms (*.fmb) as outlined in the RMS 10.1 installation guide, Appendix B.
- 15 In the Web forms src directory, compile RMS menus (*.mmb) as outlined in the RMS 10.1 installation guide, Appendix B.

- 16 Move all compiled forms and menus (*.fmx and *.mmx) in the Web forms src directory to the bin directory.
- 17 Copy the report source codes (*.rdf) located on UNIX in the <staging area>/reports/src to your UNIX Web reports src directory.
- 18 In the Web reports src directory, compile the RMS reports (*.rdf) as outlined in the RMS 10.1 installation guide, Appendix B.
- 19 Move compiled objects (*.rep) to the bin directory.
- 20 The RMS forms server process and reports server process should be reloaded after the RMS 10.1.6 executables have been copied to the appropriate directories on the Windows webserver.