

Intermediary  
Version-11.0  
9NT1316-ORACLE FCUBSV.UM 11.0.0.0.0.0  
[January] [2010]  
Oracle Part Number E51573-01



---

## Document Control

Author: Documentation Team	Group: UBPG	
Created on: December 15, 2009	Revision No: Final	
Updated by: Documentation Team	Reviewed by: Development/Testing teams	Approved by: Software Quality Assurance Team
Updated on: January 04, 2010	Reviewed on: January 04, 2010	Approved on: January 04, 2010

## Table of Content0073

<b>1. ABOUT THIS MANUAL.....</b>	<b>1-1</b>
1.1 INTRODUCTION.....	1-1
1.1.1 Audience.....	1-1
1.1.2 Organization.....	1-1
1.1.3 Related Documents.....	1-2
1.1.4 Glossary of Icons.....	1-2
<b>2. INTERMEDIARY - AN OVERVIEW.....</b>	<b>2-1</b>
2.1 INTRODUCTION.....	2-1
<b>3. GENERAL MAINTENANCE.....</b>	<b>3-1</b>
3.1 INTRODUCTION.....	3-1
3.2 CAPTURING BRANCH PARAMETERS.....	3-1
3.2.1 Actions Allowed.....	3-2
3.3 VIEWING BRANCH PARAMETERS SUMMARY.....	3-2
3.4 CAPTURING INTERMEDIARY SDE DETAILS.....	3-3
3.4.1 Actions Allowed.....	3-5
3.5 VIEWING SDE SUMMARY DETAILS.....	3-5
3.6 DEFINING AN INTERMEDIARY RULE.....	3-6
3.6.1 Capturing Rule Formula.....	3-8
3.6.2 Actions Allowed.....	3-10
3.7 VIEWING RULE SUMMARY DETAILS.....	3-10
3.8 MAINTAINING INTERMEDIARY GROUP.....	3-11
3.8.1 Actions Allowed.....	3-11
3.9 VIEWING GROUP SUMMARY DETAILS.....	3-12
3.10 MAINTAINING INTERMEDIARY HIERARCHY DETAILS.....	3-13
3.10.1 Intermediary Tab.....	3-14
3.10.2 Settlement and Statement Tab.....	3-17
3.10.3 Products Tab.....	3-19
3.10.4 Capturing Events.....	3-20
3.10.5 Maintaining MIS Details.....	3-22
3.10.6 Viewing UDE Values.....	3-23
3.10.7 Actions Allowed.....	3-24
3.11 VIEWING INTERMEDIARY SUMMARY DETAILS.....	3-24
3.12 SPECIFYING EXTERNAL UDE VALUES.....	3-25
3.12.1 Actions Allowed.....	3-27
3.13 VIEWING EXTERNAL UDE SUMMARY.....	3-27
<b>4. SETTING UP A PRODUCT.....</b>	<b>4-1</b>
4.1 INTRODUCTION.....	4-1
4.2 MAINTAINING AN INTERMEDIARY PRODUCT.....	4-1
4.2.1 Specifying Accounting Roles.....	4-2
4.2.2 Specifying Events.....	4-3
4.2.3 Specifying Product Preferences.....	4-6
4.2.4 Specifying Branch and Currency Restrictions.....	4-8
4.2.5 Specifying Module Product Restrictions.....	4-9
4.2.6 Specifying MIS Details.....	4-11
4.2.7 Actions Allowed.....	4-11
4.3 VIEWING PRODUCT SUMMARY.....	4-12
4.4 SPECIFYING UDE VALUES.....	4-13

4.4.1	<i>Actions Allowed</i> .....	4-13
4.5	VIEWING UDE SUMMARY DETAILS .....	4-14
<b>5.</b>	<b>OPERATIONS</b> .....	<b>5-1</b>
5.1	INTRODUCTION .....	5-1
5.2	COMMISSION PROCESSING.....	5-1
5.2.1	<i>Settlement of Commission Between Intermediaries</i> .....	5-2
5.3	VIEWING INTERMEDIARY SYSTEM DATA ELEMENTS.....	5-3
5.3.1	<i>Actions Allowed</i> .....	5-4
5.4	VIEWING SDE SUMMARY.....	5-4
5.5	VIEWING CALCULATED COMMISSION .....	5-5
5.5.1	<i>Actions Allowed</i> .....	5-7
5.6	VIEWING COMMISSION CALCULATION SUMMARY .....	5-7
5.7	LIQUIDATING INTERMEDIARY COMMISSION MANUALLY .....	5-8
5.7.1	<i>Actions Allowed</i> .....	5-10
5.8	VIEWING MANUAL LIQUIDATION SUMMARY .....	5-11
<b>6.</b>	<b>ANNEXURE A – ACCOUNTING ENTRIES AND ADVICES</b> .....	<b>6-1</b>
6.1	INTRODUCTION .....	6-1
6.2	EVENTS .....	6-1
6.3	ACCOUNTING ROLES .....	6-1
6.4	AMOUNT TAGS .....	6-1
6.5	ACCOUNTING ENTRIES AND ADVICES .....	6-2
6.5.1	<i>Payment</i> .....	6-2
6.5.2	<i>Collection</i> .....	6-2
6.6	ADVICE FORMAT .....	6-3
6.6.1	<i>INTER_CR_ADV</i> .....	6-3
6.6.2	<i>INTER_DR_ADV</i> .....	6-4
6.6.3	<i>INTER_STMT</i> .....	6-4

---

# 1. About this Manual

## 1.1 Introduction

This manual is designed to help acquaint you with the Intermediary module of Oracle FLEXCUBE.

In addition to this User Manual, you can find answers to specific features and procedures, in the Online Help. It can be invoked by choosing Help Contents from the Help Menu of the software. You can further obtain information about to a particular field by placing the cursor on the relevant field and striking the <F1> key on the keyboard.

### 1.1.1 Audience

This manual is intended for the following User/User Roles:

Role	Function
Back office data entry clerk	Input functions for contracts
Back office managers/officers	Authorization functions
Product Managers	Product definition and authorization
End of Day operators	Processing during End of Day/ Beginning of Day
Financial Controller / Product Managers	Generation of reports

### 1.1.2 Organization

This manual is organized into the following chapters:

<b>Chapter 1</b>	<i>About this Manual</i> gives information on the intended audience. It also lists the various chapters covered in this User Manual.
<b>Chapter 2</b>	<i>Intermediary - An Overview</i> gives a snapshot of the features that the module provides.
<b>Chapter 3</b>	<i>Generic Maintenances</i> discusses the details that need to be maintained in order to process transactions requiring intermediary services.
<b>Chapter 4</b>	<i>Setting up a Product</i> chapter talks about defining the attributes specific to setting up an intermediary product.
<b>Chapter 5</b>	<i>Operations</i> talks about commission calculation for intermediaries.
<b>Chapter 6</b>	<i>Annexure A – Accounting Entries and Advices</i> explains the types of accounting entries and advices generated for every event.

### 1.1.3 Related Documents

You may need to refer to any or all of the User Manuals while working on the Intermediary module:

- Core
- Procedures
- Settlements
- Interest
- User Defined
- Retail Lending
- Leasing
- Mortgages

### 1.1.4 Glossary of Icons

This User Manual may refer to all or some of the following icons.

Icons	Function
	New
	Copy
	Save
	Delete
	Unlock
	Print
	Close
	Re-open
	Reverse
	Template
	Roll-over
	Hold
	Authorize

<b>Icons</b>	<b>Function</b>
	Liquidate
	Exit
	Sign-off
	Help
	Add row
	Delete row

*Refer the Procedures User Manual for further details about the icons.*

---

## 2. Intermediary - An Overview

### 2.1 Introduction

An intermediary is a third party who offers intermediation services between two trading parties. From a software application perspective, an intermediary acts as a middleware between the bank and the customer. The bank may also contract an intermediary to market its funds, thereby attracting the customers. Intermediaries can avail the commission from the bank on every successful loan created through them. An intermediary can be a single entity or a group. The banks can follow hierarchical structure to group multiple intermediaries. In case of multiple intermediaries, the commission earned should be shared with all intermediaries who are part of the same hierarchical structure up to the specified levels.

This manual explains the processing of intermediaries in Oracle FLEXCUBE. Using the Intermediary Service that Oracle FLEXCUBE provides, you can:

- Capture and maintain the Intermediary hierarchy structure
- Maintain commission plans and commission calculation for main loans and third party products such as insurances, warranty contracts, etc
- Pay commission to the intermediaries as the loan is disbursed
- Maintain charge backs in case of early pay-offs and defaults
- Generate Intermediary statements
- Capture and maintain periodic billing and accounting

You can process intermediaries in Oracle FLEXCUBE in the following manner:

- Maintain Intermediary details
- Maintain intermediary rules
- Maintain branch and currency restrictions
- Capture Intermediary account details

## 3. General Maintenance

### 3.1 Introduction

You need to maintain the following details in order to process transactions using intermediary services:

- Branch Parameters
- Intermediary System Data Element (SDE) Details
- Intermediary Rules
- Intermediary Group
- Intermediary Hierarchy
- External UDE Values

### 3.2 Capturing Branch Parameters

You can maintain branch-level parameters for all transaction involving the intermediary module, using the 'Intermediary Branch Parameters Maintenance' screen. You can invoke this screen by typing 'INDBRMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a web-based form for maintaining branch parameters. The form includes a dropdown for 'Branch Code \*', a text input for 'Branch Name', radio buttons for 'Process Till' (with 'System Date' selected), a checkbox for 'Intermediary Daily Computation', and a dropdown for 'Product Category for PC Upload'. The bottom of the screen features a dark blue navigation bar with fields for 'Maker', 'Checker', 'Date Time:', 'Mod No', 'Authorized', 'Open', and a 'Cancel' button.

Specify the following details.

#### **Branch Code**

Specify the branch code for which you are maintaining parameters. The adjoining option list displays all valid branch codes maintained in the system. You can select the appropriate one.

#### **Branch Name**

The system displays the branch name associated with the branch code.

## **Process Till**

This specification determines the day on which automatic events such as accrual, liquidation etc. falling due on a holiday, should be processed. Indicate your preference by selecting the appropriate option. The available options here are:

- System Date - If you select this option, events will be scheduled as per the date irrespective of whether it is a holiday or not.
- Next Working Day -1 - If you select this option, events scheduled for a holiday will be processed on the last working day before the holiday.

## **Intermediary Daily Computation**

Check this box to indicate that SDE calculation should happen daily for every intermediary.

## **Product Category for PC upload**

Specify the product category to be used for Payments and Collections (PC) transaction upload. The adjoining option list displays all product categories maintained under the PC module. You can choose the appropriate one.

### **3.2.1 Actions Allowed**


You can perform the following actions on a record:

- New
- Delete
- Unlock
- Save
- Auth (Authorise)
- Reverse
- Execute
- Query

*Refer the Procedures User Manual for details about each action.*

### **3.3 Viewing Branch Parameters Summary**

You can view parameters maintained for every branch, using the 'Intermediary Branch Parameters Summary' screen. You can invoke this screen by typing 'INSBRMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



You can query on records based on any or all of the following criteria:

- Authorization Status
- Record Status
- Branch Code
- Process Till

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Branch Code
- Process Till


### 3.4 Capturing Intermediary SDE Details

The following System Data Elements (SDEs) are available in the system.

Element	Description	Calculation method
LOAN_COUNT	This SDE returns the total number of loans created by a particular Intermediary	Periodic
LOAN_DISBURSED_AMT	This SDE returns the sum of amount	Periodic

Element	Description	Calculation method
	disbursed of all loans created by a particular Intermediary.	
LOAN_OVERDUE_AMT	This SDE returns the sum of all overdue amount i.e. sum of all overdue components i.e. PRINCIPAL, INTEREST etc. of all the loans created by a particular Intermediary.	As of date
LOAN_OVERDUE_PRINC	This SDE returns the sum of the overdue principal amount i.e. sum of PRINCIPAL of all the loans created by a particular Intermediary.	As of date
LOAN_OUTSTAND_PRINC	This SDE returns the sum of outstanding principal of all the loans created by a particular Intermediary.	As of date
LOAN_PREPAID_AMT	This SDE returns the sum of amount paid as pre-payment on all loans created by a particular Intermediary.	Periodic
LOAN_BOOKED_AMT	This SDE returns the sum of amount booked on all loans created by a particular Intermediary.	Periodic
LOAN_COLLECTED_AMT	This SDE returns the sum of amount collected by the Intermediary for the current cycle of liquidation. This is the actual amount collected and it excludes the amount paid and reversed in the current liquidation cycle.	Periodic
LOAN_COLL_REV_AMT	This SDE returns the sum of reversed amount, which was collected by the Intermediary for the previous cycle but was reversed in the current liquidation cycle.	Periodic

You can view details of each one of them in the 'Intermediary SDE Maintenance' screen. You can invoke this screen by typing 'INDSDEMT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



Here you can view the following details.

### **Element**

The system displays a unique identification code for the System Data Element (SDE).

### **Description**

The system displays a brief description for the System Data Element.

### **Calculation Method**

The system displays the method that should be used for calculation purposes from the adjoining drop-down list. The options available are:

- Periodic - These SDEs will always aggregate data for an intermediary between the last settlement date and the next settlement date. The computation of all such SDEs will be based on the booking date.
- As of date - These SDEs will be the aggregated data as of that point in time.

## **3.4.1 Actions Allowed**


You can perform the following actions on a record:

- Query

*Refer the Procedures User Manual for details about each action.*

## **3.5 Viewing SDE Summary Details**

You can view all SDEs maintained for intermediaries in the 'Intermediary SDE Maintenance Summary' screen. You can invoke this screen by typing 'INSSDEMT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



You can query based on the SDE ID.

Click 'Search' button. The system identifies all records matching the criteria specified and displays the following details for each of them:

- Element
- Description
- Calculation Method

### **3.6 Defining an Intermediary Rule**

An Intermediary Rule identifies the method to calculate commission payable to the Intermediary and Pre-Payment/Late Payment penalty charge to be recovered from the Intermediary. You can maintain such rules in the 'Intermediary Rule Maintenance' screen. You can invoke this screen by typing 'INDRLMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Specify the following details.

### **Rule ID**

Specify a unique rule identification code for the Intermediary rule you are creating.

### **Rule Description**

Give a brief description for the rule ID.

### **Currency**

Specify the currency in which the aggregation of total amount should be considered in the rule. The adjoining option list displays all valid currencies maintained in the system. You can choose the appropriate one.

### **Exchange Rate Type**

Specify the rate type to be used for cross currency transactions. The adjoining option list displays all valid exchange rate types maintained in the system. You can choose the appropriate one.

### **Rule Type**

Select the type of rule from the adjoining drop-down list. The options available here are:

- Payment
- Collection

This value determines the accounting set-up that needs to be done for the intermediary product.

*Refer the chapter titled 'Setting up A Product' in this User Manual for details about product set-up.*

### **SDE Details**

You can specify the following details for SDEs.

#### **SDE ID**

Specify the System Data Elements ID to be included in the rule. The adjoining option list displays all valid SDE IDs available in the system. You can choose the appropriate one.

You can maintain multiple SDEs.

#### **UDE ID**

Specify the User Data Element ID to be included in the rule.

#### **UDE Type**

Select the type of the UDE from the adjoining drop-down list. The following options are available:

- Amount
- Rate
- Number

#### **UDE Basis**

Select the UDE basis from the adjoining drop-down list. The following options are available:

- Internal
- External

#### **UDE Currency**


Specify the UDE currency. The adjoining option list displays all valid currency codes maintained in the system. You can choose the appropriate one.

Note that you can specify the currency only if UDE type is 'Amount' and basis is 'External'.

You can maintain multiple UDEs.

### **3.6.1 Capturing Rule Formula**

You can specify the formula for the rule using the 'Formula' screen. You can invoke this screen by clicking 'Formula' button in the 'Intermediary Rule Maintenance' screen.



Specify the following details.

### Line

Assign a unique sequence number/formula number for each condition. The conditions are evaluated based on this number.


### Condition

Specify the condition for the rule.

### Result

Specify the result of the condition being satisfied.

To define a condition, click on 'Condition' in the screen above. The following screen is displayed:



In this screen, you can use the elements, operators, and logical operators to build a condition.

Although you can define multiple expressions for a component, if a given condition is satisfied, subsequent conditions are not evaluated. Thus, depending on the condition of the expression that is satisfied, the corresponding formula result is picked up for component value computation. Therefore, you have the flexibility to define a computation logic for each component of the product.

### 3.6.2 Actions Allowed


You can perform the following actions on a record:

- New
- Delete
- Unlock
- Save
- Auth (Authorise)
- Reverse
- Execute
- Query

*Refer the Procedures User Manual for details about each action.*

### 3.7 Viewing Rule Summary Details

You can view details of all intermediary rules maintained in the system, using the 'Intermediary Rule Maintenance Summary' screen. You can invoke this screen by typing 'INSRLMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



You can query based on the following criteria:


- Authorization Status
- Record Status
- Rule ID

Click 'Search' button. The system identifies all records matching the criteria specified and displays the following details for each of them:

- Authorization Status
- Record Status
- Rule ID
- Rule Description
- Rule Type

## 3.8 **Maintaining Intermediary Group**

You can associate a set of intermediaries to a group and link the group to transactions. You can maintain such intermediary groups using the 'Intermediary Group Maintenance' screen. You can invoke this screen by typing 'INDGRPMT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



The screenshot shows a web browser window titled "Intermediary Group Maintenance -- Webpage Dialog". The main content area contains two input fields: "Group Code \*" and "Group Description". The "Group Code \*" field has a red asterisk indicating it is a required field. The "Group Description" field is empty. At the bottom of the window, there is a dark blue footer area with several fields: "Maker", "Checker", "Date Time:", "Mod No", "Authorized", "Open", and a "Cancel" button. The "Authorized" and "Open" fields have small square icons next to them.

You can specify the following details:

### **Group Code**

Specify a unique code to identify the group that you want to maintain.

### **Description**

Specify a brief description for the group code.

### 3.8.1 **Actions Allowed**

You can perform the following actions on a record:


- New

- Delete
- Unlock
- Save
- Auth (Authorise)
- Reverse
- Execute
- Query

Refer the Procedures User Manual for details about each action.

### 3.9 Viewing Group Summary Details

You can view all the details of intermediary groups in the 'Intermediary Group Maintenance Summary' screen. You can invoke this screen by typing 'INSGRPMT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



You can query based on the following criteria:

- Authorization Status
- Record Status
- Group Code

Click 'Search' button. The system identifies all records matching the criteria specified and displays the following details for each of them:

- Authorization Status

- Record Status
- Group Code

### 3.10 Maintaining Intermediary Hierarchy Details

You can maintain intermediaries in Oracle FLEXCUBE. You can also create a hierarchy of intermediaries and specify commission processing share for each one in the hierarchy.

You can maintain such hierarchy details through the 'Intermediary Maintenance' screen. You can then link the intermediary to a loan. You can invoke this screen by typing 'INDINMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You should specify the following details in the above screen.

#### **Intermediary Code**

The system generates a unique numeric intermediary code for every intermediary as per the following mask:

NNNNNNNNN

Where,

NNNNNNNNN - Running sequence number

#### **Intermediary Name**

Specify the name of the Intermediary associated with the bank.

You can specify additional details for the intermediary in the following tabs:

- Intermediary
- Settlement and Statement
- Products

### **3.10.1 Intermediary Tab**

The system displays this tab by default when you invoke this screen.

#### **Intermediary Details**

You can specify the following details.

##### **Primary Contact**

Specify the name of the person to be contacted from the intermediary.

##### **Type**

Indicate whether the intermediary is internal or external to your bank by selecting the one of the options from the adjoining drop-down list:

- Internal
- External

##### **Branch Code**

This field indicates the Home Branch of the intermediary. This value is defaulted based on the current logged-in branch.

##### **Effective Date**

The system displays the current system date.

##### **Intermediary Category**

Specify whether the Intermediary is a single entity or group of intermediaries. The options available here are:

- Individual
- Group

##### **Group Code**

If you have selected the category as 'Group', then you have to specify the group code to which the intermediary should belong. The adjoining option list displays all valid intermediary group codes maintained in the system. You can choose the appropriate one.

##### **Parent Intermediary Code**

In order to build a hierarchy of intermediaries, you need to specify the parent intermediary code. The adjoining option list displays all valid intermediary codes maintained in the system. You can choose the appropriate one.

The system will allow only intermediaries with the same home branch to be linked as parent intermediary.

**Parent Intermediary Name**

Based on the parent intermediary code, the system displays the corresponding intermediary name.

**Intermediary Customer Number**

Specify the customer number of the intermediary. You can choose the appropriate customer number from the adjoining option list. This list displays all valid and open accounts maintained in the system.

**Address**

Specify the address of the intermediary.

The system retrieves the address based on the customer number (CIF). However, you can change it.

**ZIP**

Specify the ZIP code of the address.

The system retrieves the ZIP code based on the customer number (CIF). However, you can change it.

**Country**

Specify the country in which intermediary resides. The adjoining option list displays all valid country codes maintained in the system. You can choose the appropriate one.

The system retrieves the country based on the customer number (CIF). However, you can change it.

**Collection Agent**

Check this box to indicate that the Intermediary can act as a collection agent.

**Root Intermediary**

Indicate whether the intermediary is at the root of the hierarchy or not by selecting one of the following options:

- Yes
- No

**Liquidation Mode**

Select the mode of liquidation for settlement of intermediary transactions from the adjoining drop-down list. The options available are:

- Automatic
- Manual

**Minimum Amount for Liquidation**

Specify the minimum amount required for primary commission liquidation. While processing transactions for the intermediary, if the calculated amount is less than the amount maintained here, it will not consider the amount for liquidation.

### **Intermediary Status**

Indicate the status of the intermediary by choosing one of the following options from the adjoining drop-down list:

- Active
- Inactive

### **Cascade Child**

Check this box to indicate that status of the parent should be applied to the child intermediaries. Once checked, if you change the status of a parent intermediary from active to inactive, the system will make all child intermediaries inactive. However, you can also leave the box unchecked. In such case, the status of parent intermediary will not be applied to the child intermediaries. During hierarchy commission distribution, the system will stop processing on encountering the first inactive record.

### **Level Number**

The system updates the level of the intermediary in the hierarchy on saving the record.

### **Cascade Till**

Indicate the level until which the system should process hierarchy commission by choosing one of the following values from the adjoining drop-down list:

- Immediate - If you select this option, commission hierarchy will be processed only up to immediate parent.
- Root - If you select this option, commission hierarchy will be processed up to the root intermediary till the minimum hierarchy commission amount is reached.

### **Telephone**

Specify the telephone number of the intermediary.

The system retrieves the telephone number based on the customer number (CIF). However, you can change it.

### **Mobile**

Specify the mobile number of the intermediary.

The system retrieves the mobile number based on the customer number (CIF). However, you can change it.

### **Fax**

Specify the facsimile (fax) number of the intermediary.

The system retrieves the fax number based on the customer number (CIF). However, you can change it.

### **E-Mail ID**

Specify the e-mail ID of the intermediary.

The system retrieves the e-mail ID based on the customer number (CIF). However, you can change it.

### 3.10.2 Settlement and Statement Tab

Click 'Settlement and Statement' tab to capture details about settlement processing.

The screenshot displays a web application window titled "Intermediary Maintenance -- Webpage Dialog". At the top, there are fields for "Intermediary Code" (00000161) and "Intermediary Name". Below this, there are three tabs: "Intermediary", "Settlement and Statement" (which is selected), and "Products". The "Settlement and Statement" tab is divided into two main sections: "Settlement Details" and "Statement Details".

**Settlement Details:**

- Settlement Currency \* (with a selection icon)
- Settlement Mode (dropdown menu)

**Statement Details:**

- Statement Frequency (dropdown menu)
- Statement Frequency Unit (text field)
- Statement Start Month (dropdown menu)
- Statement Start Date (text field)
- Last Statement Date (text field)
- Next Statement Date (text field)

**CASA:**

- Settlement Branch \* (with a selection icon)
- Settlement Account \* (with a selection icon)

**External Account Details:**

- External Account Name (text field)
- External Account Number (text field)
- External Bank Code (with a selection icon)

At the bottom of the window, there are navigation tabs: "Events", "MIS", and "UDE Values". A dark blue footer contains fields for "Maker", "Checker", "Date Time", "Mod No", "Authorized", "Open", and an "Exit" button.

You can specify the following details.

#### **Settlement Details**

Specify the following details for settlement processing.

##### **Settlement Currency**

Specify the currency to be used for settlement processing. The adjoining option list displays all valid currency codes maintained in the system. You can select the appropriate one.

##### **Settlement Mode**

Indicate the settlement mode by choosing one of the following values from the adjoining drop-down list:

- CASA
- External

If you choose 'CASA', you will have to specify the settlement account under 'CASA' section. If you choose 'External', you will have to specify the settlement account for CASA as well as external account details under the 'External Account' section.

## **Statement Details**

Specify the following details for statement generation.

### **Statement Frequency**

Select the frequency at which statement should be generated for the intermediary, from the adjoining drop-down list. The following values are available:

- Daily
- Weekly
- Monthly
- Yearly

### **Statement Frequency Unit**

Specify a numeric value to denote the unit of statement frequency. For example, if the frequency is daily and the unit is specified as '3', it will imply that statements should be generated every 3 days.

### **Statement Start Month**

From the adjoining drop-down list, select the month from which statement generation should begin if you have chosen the frequency as 'Monthly' or 'Yearly'.

### **Statement Start Date**

Specify the date from which the statement generation should begin based on the given frequency, using the adjoining calendar.

### **Last Statement Date**

The system displays the date of last statement generation.

### **Next Statement Date**

Based on the statement generation parameters, the system arrives at the next statement date and displays it here.

## **CASA**

If settlement needs to be done using an internal account (CASA), you need to specify the following details.

### **Settlement Branch**

Specify the branch code where the settlement needs to be done. The adjoining option list displays all valid branch codes maintained in the system. You can select the appropriate one.

### **Settlement Account**

Specify the account from which settlement needs to be done. The adjoining option list displays all valid accounts available for the CIF. You can select the appropriate one.

Input to this field is mandatory for both CASA and External modes of settlement.

## **External Account**

If settlement needs to be done using an external account, you need to specify the following details.

### **External Account Name**

Specify the name of the external account.

### **External Account Number**

Specify the external account number.

### **External Bank Code**

Specify the bank code to which the external account belongs. The adjoining option list displays all valid bank codes maintained in the system. You can select the appropriate one.

## **3.10.3 Products Tab**

Click 'Products' tab to capture details about products under which the intermediary can transact.

The screenshot shows a web application window titled "Intermediary Maintenance -- Webpage Dialog". At the top, there are input fields for "Intermediary Code" (with the value "000000161") and "Intermediary Name". Below these are three tabs: "Intermediary", "Settlement and Statement", and "Products", with "Products" being the active tab. The main area is divided into two sections: "Product Details" and "UDE Details".

**Product Details Table:**

<input checked="" type="checkbox"/>	Product Code	Product Description	Last Settlement Date	Last Processing Date	Next Processing Date	Hierarchy	Commission Perc
<input checked="" type="checkbox"/>	<input type="text"/>						

**UDE Details Table:**

<input checked="" type="checkbox"/>	Rule ID	UDE ID	UDE Value
<input checked="" type="checkbox"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>

At the bottom of the window, there are tabs for "Events", "MIS", and "UDE Values". A dark blue footer contains fields for "Maker", "Checker", "Date Time", "Mod No", "Authorized", "Open", and an "Exit" button.

Specify the following details:

### **Product Code**

Specify the intermediary product in which the intermediary can transact. The adjoining option list displays all open and authorized intermediary products maintained in the system. You can choose the appropriate one.

You can link multiple products to the intermediary.

**Product Description**

The system displays a brief description of the product.

**Last Settlement Date**

The system displays the last settlement date for the product.

**Last Processing Date**

The system displays the last processing date for the product.

**Next Processing Date**

The system displays the next settlement date for the product based on the settlement frequency.

**Hierarchy Commission Percentage**

Specify the commission that the intermediary should get in terms of a percentage of the transaction amount.

**Minimum Hierarchy Commission**

Specify the minimum amount that should be granted as commission.

**UDE Details**

The system displays all rules linked to the product. You can specify the UDE values for them.

**Rule ID**

The system displays the rules that are linked to the product.

**UDE ID**


The system displays the UDE ID associated with the rule.

**UDE Value**

Specify the value for the UDE IDs.

**3.10.4 Capturing Events**


Click 'Events' button in the 'Intermediary Maintenance' screen and invoke the 'Events' screen.



Here you can view the following details:

- Event Number
- Event Code
- Event Date


Click 'Messages' button and invoke the 'Messages' screen to view the messages generated for the intermediary.



Here you can view the following details:

- Event Number
- Message Type
- Party ID
- Suppress
- Priority

Click 'Accounting Entries' button and invoke the 'Accounting Entries' screen to view accounting entries posted for transactions of the intermediary.




Here you can view the following details:

- Branch Code
- Account Number
- D/C
- Local Currency
- Local Ccy Amount
- Exchange Rate
- Foreign Ccy Amount
- Date
- Value date
- Amount Tag
- Code

### **3.10.5 Maintaining MIS Details**


Click 'MIS' button in the 'Intermediary Maintenance' screen and invoke the 'Management Information System' screen.



Refer the User Manual on MIS for further details.

### 3.10.6 Viewing UDE Values

Click 'UDE Values' button in the 'Intermediary Maintenance' screen to invoke the 'UDE Values' screen. You can view values for all UDEs applicable to the Intermediary in this screen. Note that you will be able to invoke this screen only in the Query mode. In all other cases, this button will be disabled.



Here you can view the following details:

- Rule ID
- UDE ID
- UDE Value

### 3.10.7 Actions Allowed

You can perform the following actions on a record:

- New
- Delete
- Unlock
- Save
- Auth (Authorise)
- Reverse
- Execute
- Query

*Refer the Procedures User Manual for details about each action.*

### 3.11 Viewing Intermediary Summary Details

You can view details of all intermediaries in the 'Intermediary Maintenance Summary' screen. You can invoke this screen by typing 'INSINMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a web application window titled "Intermediary Maintenance Summary -- Webpage Dialog". The interface includes a search section with several dropdown menus and text input fields for filtering records. Below the search section is a table with the following columns: Authorization Status, Record Status, Intermediary Code, Intermediary Name, Intermediary Status, Parent Intermediary Code, and Primary Contact. The table is currently empty. At the bottom right of the window, there is an "Exit" button.

You can query on records based on any or all of the following criteria:

- Authorization Status
- Record Status
- Intermediary Code
- Intermediary Name

- Intermediary Status
- Parent Intermediary Code
- Primary Contact
- Intermediary Category

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Intermediary Code
- Intermediary Name
- Intermediary Status
- Parent Intermediary Code
- Primary Contact
- Intermediary Category

### 3.12 Specifying External UDE Values

You may need to capture data from external systems for computation of intermediary commission. You can capture such data in the 'External UDE Values Maintenance' screen. You can invoke this screen by typing 'INDUDEM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'External UDE Values Maintenance' web application. At the top, there are search fields for 'Intermediary Code' and 'UDE Effective Date'. Below this is a 'Product Details' section with a table containing 'Product Code' and 'Product Description' columns. Underneath is the 'UDE Details' section, which includes a table with columns for 'Rule ID', 'UDE ID', 'UDE Currency', 'UDE Type', and 'UDE Value'. The bottom of the window features a status bar with fields for 'Maker', 'Checker', 'Date Time', and 'Mod No', along with checkboxes for 'Authorized' and 'Open', and a 'Cancel' button.

Specify the following details.

### **Intermediary Code**

Specify the intermediary code for which you want to capture external UDE values. The adjoining option list displays all valid intermediary codes maintained in the system. You can choose the appropriate one.

### **UDE Effective Date**

Specify the date from which the UDE should be effective.

### **Product Details**

You can link products to the intermediary code.

### **Product Code**

Specify the intermediary product code for which you want to capture external UDE values. The adjoining option list displays all valid intermediary product codes maintained in the system. You can choose the appropriate one.

### **Product Description**

The system displays a brief description of the product.

### **UDE Details**

The system displays all rules linked to the specified product code.

### **Rule ID**

The system displays all rules linked to the product.

### **UDE ID**

Specify the external UDE ID that you want to attach to the rule. The adjoining option list displays all valid UDEs maintained in the system. You can select the appropriate one.

### **UDE Currency**

The system displays the UDE currency based on the UDE ID. However you can change it. The adjoining option list displays all valid currency codes maintained in the system. You can choose the appropriate one.

### **UDE Type**

The system displays the UDE type based on the UDE ID. However you can change it. Select the type of the UDE from the adjoining drop-down list. The options available here are:

- Number
- Rate
- Amount

## UDE Value

Specify the external UDE value. At the time of processing, the system checks the UDE value for the corresponding product maintained in this screen for the maximum effective date falling between the last liquidation date and the calculation date. If no value is maintained in this screen, the UDE value will be considered as '0'.

### 3.12.1 Actions Allowed

You can perform the following actions on a record:

- New
- Delete
- Unlock
- Save
- Auth (Authorise)
- Reverse
- Execute
- Query

*Refer the Procedures User Manual for details about each action.*

### 3.13 Viewing External UDE Summary

You can view details of all external UDEs through 'External UDE Value Maintenance Summary' screen. You can invoke this screen by typing 'INSUDEM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot displays a web application window titled "External UDE Values Maintenance Summary -- Webpage Dialog". The interface features a search and filter section at the top with dropdown menus for "Authorization Status", "Record Status", "Intermediary Code", and "UDE Effective Date". Below these are buttons for "Search", "Advanced Search", "Refresh", and "Reset". A table below the search section has columns for "Authorization Status", "Record Status", "Intermediary Code", and "UDE Effective Date". The table is currently empty. At the bottom right of the window, there is an "Exit" button.

You can query on records based on any or all of the following criteria:

- Authorization Status
- Record Status
- Intermediary Code
- UDE Effective Date

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Intermediary Code
- UDE Effective Date

---

## 4. Setting up a Product

### 4.1 Introduction

You can maintain a product and define specific attributes like rules for processing intermediary commission and also define settlement frequency for the same. This product in turn can be linked to an intermediary.

### 4.2 Maintaining an Intermediary Product

You can maintain a product and link it to lending transactions requiring an intermediary. You can maintain an intermediary product using the 'Intermediary Product' screen. You can invoke this screen by typing 'INDPRMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a web-based dialog box titled "Intermediary Product -- Webpage Dialog". The main content area is labeled "Product Details" and contains several input fields: "Intermediary Product Code \*" (a required text field), "Product Description" (a text area), "Start Date" (a date picker), "End Date" (a date picker), and "Remarks" (a text area). Below the main content area is a navigation bar with tabs for "Accounting Roles", "Events", "Preferences", "Restrictions", "Module Product", and "MIS". At the bottom of the dialog, there is a dark blue footer area containing fields for "Maker", "Checker", "Date Time:", "Date Time:", "Mod No", "Authorized" (checkbox), "Open" (checkbox), and a "Cancel" button.

You can specify the following details:

#### **Intermediary Product Code**

Specify a unique code to identify the intermediary product.

#### **Product Description**

Specify a brief description for the intermediary product.

**Start Date**

Specify the date from which this product will be available, using the adjoining calendar.

**End Date**

Specify the date until which this product will be available, using the adjoining calendar.

**Remarks**


You can enter some information about the product which is internal to the bank. This will not be printed on any correspondence with the intermediary.

You can maintain additional details for the product by clicking the following buttons on the screen.

<b>Buttons</b>	<b>Description</b>
Accounting Roles	Click this button to define the accounting role to accounting head mapping.
Events	Click this button to select the events for the product and then maintain event-wise accounting entries and advices.
Preferences	Click this button to define preferences like tenor, Prepayment option etc.
Restrictions	Click this button to maintain the list of allowed/ disallowed branches and currencies for the product.
Module Product	Click this button to maintain the list of allowed/ disallowed customers/customer categories.
MIS	Click this button to capture MIS related parameters.

**4.2.1 Specifying Accounting Roles**


Click 'Accounting Roles' button to maintain accounting roles for the product.



*Refer the chapter titled 'Product Definition' in the Products User Manual under Modularity for details about role definition.*

#### **4.2.2 Specifying Events**


Click 'Events' button and invoke the 'Events' screen to maintain events for the product.



Here you can specify events that should occur in the lifecycle of transactions linked to the product.


#### **4.2.2.1 Specifying Accounting Entries**

Click 'Accounting Entries' button in the 'Events' screen and invoke the 'Accounting Entries' screen to maintain event-wise accounting entries.



#### 4.2.2.2 Specifying Advices

Click 'Advices' button in the 'Product Event Accounting Entries Maintenance' screen and invoke the 'Advices' screen to maintain event-wise advices.



All suggested accounting entries are listed in the chapter titled 'Annexure A – Accounting entries and Advices' of this User Manual.

*Refer the chapter titled 'Product Definition' in the Products User Manual under Modularity for details about events, accounting entries and advices.*

### 4.2.3 **Specifying Product Preferences**

Click 'Preferences' button and invoke the Intermediary Product 'Preferences' screen to maintain generic attributes of the product.

Settlement Details		Charge Details	
Settlement Frequency *	<input type="text"/>	Charge Back Unit *	<input type="text"/>
Settlement Frequency Unit *	<input type="text"/>	Charge Back Period *	<input type="text"/>
Settlement Start Month	<input type="text"/>		
Settlement Start Date	<input type="text"/>		

Rule Details	
Rule ID	Rule Description
<input checked="" type="checkbox"/>	

Specify the following details:

#### **Settlement Details**

You can capture the following settlement details.

#### **Settlement Frequency**

Select the frequency for settlement of payment from the adjoining drop-down list. The options available here are:

- Daily
- Weekly
- Monthly
- Yearly

### **Settlement Frequency Unit**

Specify a numeric value to denote the unit of settlement frequency. For example, if the frequency is daily and the unit is specified as '3', it will imply that payments should be scheduled every 3 days.

### **Settlement Start Month**

Select the month from which settlement should begin if you have chosen the frequency as 'Monthly' or 'Yearly'.

### **Settlement Start Date**

Specify the date from which the settlement should begin based on the given frequency, using the adjoining calendar.

### **Charge Back Unit**

Select the unit for calculation of pre-payment penalty period from the adjoining drop-down list. The options available here are:

- Daily
- Weekly
- Monthly
- Yearly

If the requirement is to consider all pre-payments, the penalty period can be maintained as null and penalty unit should be left blank. In this case, the system will consider all pre-payments.

### **Charge Back Period**

Specify the period within which if prepayment is done a loan, then pre-payment penalty should be charged from the Intermediary. This indicates the duration from the date of the first loan disbursement. During this period, if any pre-payment is done, then pre-payment charges will be levied on the Intermediary.

#### **Example**

Assume that you have maintained the 'Charge Back Period' as 6 months and 'Unit' is monthly. This product is linked to a loan with first loan disbursement date is January 01, 2009. If prepayment on the same is within 6 months from the first disbursement (i.e. before July 01, 2009, prepayment penalty charge will be levied on the intermediary..

### **Rule Details**

You can link rules to the product.

#### **Rule ID**

Specify the rule that should be linked to the product. The adjoining option list displays all intermediary rules maintained in the system. You can select the appropriate one.

#### **Rule Description**

Based on the rule ID, the system displays a brief description of the rule.

## 4.2.4 Specifying Branch and Currency Restrictions

You can maintain a list of branches and currencies that should be allowed or disallowed for all transactions under the product. You can specify such restrictions using the 'Branch and Currency Restrictions' screen. You can invoke this screen by clicking 'Restrictions' button in the 'Intermediary Product' screen.

The screenshot shows a web-based dialog box titled "Branch and Currency Restrictions -- Webpage Dialog". It contains the following elements:

- Product Code: [ ]
- Product Description: [ ]
- Branch To be Considered for Computation:  Allowed,  Disallowed
- Currency To be Considered for Computation:  Allowed,  Disallowed
- Branch Restrictions table:

Branch Code	Branch Description
<input checked="" type="checkbox"/>	[ ]
- Currency Restrictions table:

Currency Code	Currency Description
<input checked="" type="checkbox"/>	[ ]
- Buttons: Ok, Cancel

Specify the following details.

### Product Code and Description

The system displays the product code and description.

### Branch To Be Considered for Computation

Indicate whether you want to create a list of allowed branches or disallowed branches by selecting one of the following options:

- Allowed
- Disallowed

### Currency To Be Considered for Computation

Indicate whether you want to create a list of allowed currencies or disallowed currencies by selecting one of the following options:

- Allowed
- Disallowed

### **Branch Restriction**

Depending on whether you have opted to create an 'Allowed' or 'Disallowed' list, you can specify the branches to be included in the list.

#### **Branch Code**

Specify the branch code that should be included in the 'Allowed' or 'Disallowed' list. The adjoining option list displays all valid branch codes maintained in the system. You can select the appropriate one.

#### **Branch Description**

Based on the branch code, the system displays a brief description of the branch.

You can maintain multiple branches in the list.

### **Currency Restrictions**

Depending on whether you have opted to create an 'Allowed' or 'Disallowed' list, you can specify the currencies to be included in the list.

#### **Currency Code**

Specify the currency code that should be included in the 'Allowed' or 'Disallowed' list. The adjoining option list displays all valid currency codes maintained in the system. You can select the appropriate one.

#### **Currency Description**

Based on the currency code, the system displays a brief description of the currency.

You can maintain multiple currencies in the list.

## **4.2.5 Specifying Module Product Restrictions**

Click 'Module Product' button in the 'Intermediary Product' screen and invoke the 'Module Products Restriction' screen. You can maintain a list of products (from other modules) that should be allowed or disallowed for all transactions under this product.

Product Code

Product Description

Loans To be Considered for Computation  Allowed  Disallowed

1 of 1

Product Code	Product Description
<input checked="" type="checkbox"/>	

Ok Cancel

Specify the following details.

### **Product Code and Description**

The system displays the product code and description.

### **Loans To Be Considered for Computation**

Indicate whether you want to create a list of allowed loans or disallowed loans by selecting one of the following options:

- Allowed
- Disallowed

### **Module Products Restrictions**

Depending on whether you have opted to create an 'Allowed' or 'Disallowed' list, you can specify the loan products to be included in the list.

#### **Product Code**

Specify the product code that should be included in the 'Allowed' or 'Disallowed' list. The adjoining option list displays all valid product codes maintained in the system for the following modules:

- Retail Lending
- Mortgages
- Leasing

You can select the appropriate one.

## Product Description

Based on the product code, the system displays a brief description of the product.

You can maintain multiple products in the list.

### 4.2.6 Specifying MIS Details

Click 'MIS' button to maintain MIS details.

The screenshot shows a web-based dialog titled "MIS Details -- Webpage Dialog". It contains the following elements:

- Product Code:** A text input field.
- MIS Group:** A dropdown menu.
- Pool Code:** A dropdown menu.
- Default From MIS Group:** A button.
- Cost Code:** A label followed by four dropdown menus.
- MIS Classes Table:** A table with columns "MIS Class" and "MIS CODE". It contains three rows:

MIS Class	MIS CODE
<input checked="" type="checkbox"/> COS_CENTR	<input type="text"/>
<input type="checkbox"/> LOAN_TERM	<input type="text"/>
<input type="checkbox"/> LOAN_TYPE	<input type="text"/>
- Navigation:** "Go to Page" and "1 of 1" indicators.
- Buttons:** "Ok" and "Cancel" buttons at the bottom right.

Refer the Management Information System User Manual under Modularity for further details.

### 4.2.7 Actions Allowed

You can perform the following actions on a record:

- New
- Delete
- Unlock
- Save
- Auth (Authorise)
- Reverse
- Execute
- Query



## 4.4 Specifying UDE Values

As you can recall, you can link rules to a product. A rule consists of System Data Elements and the User Data Elements. You can maintain the values for the UDEs defined for the rule in the 'Internal UDE Value Maintenance' screen. You can invoke this screen by typing 'INDIUDVM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Rule ID *	UDE ID *	UDE Value
<input checked="" type="checkbox"/>	<input type="text"/>	

Specify the following details:

### **Product Code**

Specify the Intermediary product code for which you want to maintain UDE values.

### **Rule ID**

The system displays all intermediary rules linked to the product.

### **UDE ID**

The system displays the UDE ID linked to the rule.

### **UDE Value**

Specify the value for the applicable UDE IDs.

### 4.4.1 Actions Allowed

You can perform the following actions on a record:

- New

- Delete
- Unlock
- Save
- Auth (Authorise)
- Reverse
- Execute
- Query

Refer the Procedures User Manual for details about each action.

## 4.5 Viewing UDE Summary Details

You can view summary details of all UDE values in the 'UDE Values Summary' screen. You can invoke this screen by typing 'INSIUDVM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You can query on records based on any or all of the following criteria:

- Authorization Status
- Record Status
- Product Code

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Product Code

---

## 5. Operations

### 5.1 Introduction

You can process commission payment/charge collection at defined frequency level for every intermediary based on the transactions. You can also pay commission/collect charge to/from the intermediary at a pre-defined frequency specified for every intermediary product. Hierarchy distribution of the commission is done based on the hierarchy percentage maintained at intermediary product level.

After settlement is done, the system generates an intermediary statement based on the product maintenance displaying details of computation and the settlement amount.

This chapter explains the processing for computing commission.

### 5.2 Commission Processing

As part of the End of Day (EOD) processing, the system computes System Data Elements (SDEs) for the Intermediaries across products. Calculation of SDEs is done for intermediaries based on the branch-level parameter 'Daily SDE Computation'. If the branch parameter is checked, the system will do daily computation of SDEs for all intermediaries irrespective of whether the settlement is due on application date or not. If it is not checked, the system will compute SDEs only if settlement processing is due on the said date.

#### Example

Assume a transaction with the following details:

- SDE - LOAN\_DISBURSED\_AMT
- Batch Processing Date - 01 February, 2009
- Last Settlement Date for the intermediary product - 01 January, 2009

The batch will calculate the total amount disbursed for the intermediary between last settlement date, i.e 01 January, 2009 and processing date i.e. 01 February, 2009. This amount will be used for computation of the SDE and then logged into a data store for processing.

Subsequent to SDE calculation, the system does the following:

- Calculation of amount for all the rules for the product (say INP1)
  - Assume the following figure is calculated rule-wise:
    - RUL1: 200 (Commission)
    - RUL2: 100 (Charge/Penalty)
- Netting the amount across all the rules
  - For above scenario, the accounting should be as under
    - RUL1

Accounting Role	Amount Tag	Debit/Credit
Expense	200	Dr
Intermediary	200	Cr

→ RUL2

Accounting Role	Amount Tag	Debit/Credit
Intermediary	100	Dr
Income	100	Cr

In the above scenario, netting will be done as under:

Accounting Role	Amount Tag	Debit/Credit
Expense	200	Dr
Income	100	Cr
Intermediary	100	Cr


- Processing settlement with the intermediary based on netted amount
  - The system posts settlement entries as per the netted. The settlement with the intermediary is based on the intermediary set-up. If CASA is the settlement mode maintained for the intermediary, settlement will happen using the CASA maintained. If External Account is the settlement mode maintained, then settlement will happen using a PC transaction.

The system performs the following validations:

- For every product-intermediary combination, a liquidation reference number is generated. The sequence is based on the product code. The entries are passed when the INLQ event defined at the product level is triggered.
- If the settlement mode of the intermediary is CASA, settlement will be processed with the CASA (both debit/credit). The corresponding debit/credit advice will get generated for the intermediary based on the product set-up and the netted amount. If the netted amount to the intermediary is a credit, credit advice will get generated. If the netted amount is a debit, debit advice will get generated.
- If the settlement mode of the intermediary is 'External Account', the system will check for the following:
  - If the transaction is a credit to the intermediary, settlement will get processed using a PC transaction based on the maintenance at intermediary level and the category maintained at the intermediary branch level.
  - If the transaction is a debit to the intermediary, settlement will get processed using the settlement account/branch maintained for the intermediary.

### **5.2.1 Settlement of Commission Between Intermediaries**


Oracle FLEXCUBE supports commission settlement between intermediaries in a hierarchical way. The system computes the hierarchy amount payable to the parent intermediary for each intermediary based on the intermediary maintenance. The following diagram illustrates the hierarchical structure that can be maintained for intermediaries.



The computation happens till the level specified at the intermediary level. If the level is immediate, calculation will happen only till the immediate parent level; otherwise it will happen till the root level. This computation will happen product-wise for the intermediary.

### 5.3 Viewing Intermediary System Data Elements

For a given product, you can view all SDE values for the current liquidation cycle, through the 'Intermediary SDE View' screen. You can invoke this screen by typing 'INDSDVAL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



Here you can capture the following details.

## Product Code

Specify the product for which you want to view SDEs. The adjoining option list displays all valid Intermediary products maintained in the system. You can select the appropriate one.

## Intermediary Code

Specify the Intermediary code for which you want to view SDEs. The adjoining option list displays all valid Intermediary codes maintained in the system. You can select the appropriate one.

### 5.3.1 Actions Allowed

You can perform the following action on a record:

- Query

*Refer the Procedures User Manual for details about each action.*

## 5.4 Viewing SDE Summary

You can view a summary of all SDEs for different product-intermediary combinations, through the 'Intermediary SDE View Summary' screen. You can invoke this screen by typing 'INSSDVAL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a web application window titled "Intermediary SDE View Summary -- Webpage Dialog". At the top, there are three input fields: "Product Code", "Intermediary Code", and "Rule ID", each with a search icon to its right. Below these fields are buttons for "Search", "Advanced Search", "Refresh", and "Reset". A "Records per page" dropdown is set to "15", and there is a "Lock" button. The main area is a table with three columns: "Product Code", "Intermediary Code", and "Rule ID". The table is currently empty. At the bottom right of the window, there is an "Exit" button.

You can query based on all or any of the following criteria:

- Product Code

- Intermediary Code

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Product Code
- Intermediary Code
- SDE
- SDE Value

## 5.5 Viewing Calculated Commission

You can view all the accounts considered for commission/charge calculation across intermediary products for a given execution date, using the 'Intermediary Calculation View' screen. You can invoke this screen by typing 'INDIVIEW' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Specify the following details.

### **Product Code**

Specify the intermediary product code for which you want to view commission calculation.

### **Intermediary Code**

Specify the intermediary code for which you want to view commission calculation.

**Branch Code**

Specify the branch code under which transactions should be considered for commission calculation view.

**Reference Number**

Specify the contract reference number for which you want to view commission calculation.

**Event Code**

Specify the event code for which you want to view commission calculation.

**Execution Date**

Specify the date of automatic transaction execution based on which you want to view commission calculation.

**Rule ID**

Specify the intermediary rule based on which you want to view commission calculation.

**Manual Execution Date**

Specify the date of manual transaction execution based on which you want to view commission calculation.

**Amount**

Specify the transaction amount based on which you want to view commission calculation.

**Currency**

Specify the transaction currency based on which you want to view commission calculation.

**SDE ID**

Specify the SDE ID based on which you want to view commission calculation.

**SDE Value**

Specify the SDE value based on which you want to view commission calculation.

**Settlement Branch**

Specify the settlement branch code based on which you want to view commission calculation.

**Settlement Account**

Specify the settlement account based on which you want to view commission calculation.

**Hierarchy Commission Processed**

Indicate the hierarchy commission processing status by choosing one of the following options from the adjoining drop-down list:

- Yes
- No

Click Single View icon. This screen displays the following details of accounts considered for commission calculation:

- Reference Number
- Branch Code
- Customer ID
- Book Date
- Module Code

### 5.5.1 Actions Allowed

You can perform the following action on a record:

- Query

*Refer the Procedures User Manual for details about each action.*

## 5.6 Viewing Commission Calculation Summary

You can view summary of all commission calculation through the 'Intermediary Calculation View Summary' screen. You can invoke this screen by typing 'INSIVIEW' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a web application window titled "Intermediary Calculation View Summary -- Webpage Dialog". It contains several input fields for filtering data: Product Code, Branch Code, Event Code, Rule ID, Intermediary Code, Reference Number, and Execution Date. Below these fields are buttons for "Search", "Advanced Search", "Refresh", and "Reset". A table below the search area has columns for Product Code, Intermediary Code, Branch Code, Reference Number, Event Code, Execution Date, Rule ID, and Hierarchy Commission Processed. The table is currently empty. At the bottom right of the window, there is an "Exit" button.

You can query on records based on any or all of the following criteria:

- Product Code
- Branch Code
- Event Code
- Rule ID
- Intermediary Code
- Reference Number
- Execution Date

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Product Code
- Branch Code
- Event Code
- Rule ID
- Intermediary Code
- Reference Number
- Execution Date
- Rule ID
- Hierarchy Commission Processed
- Amount
- Currency
- SDE ID
- SDE Value
- Settlement Branch
- Settlement Account

## **5.7 Liquidating Intermediary Commission Manually**

As mentioned before, commission calculation and liquidation can be automated as part of the EOD batch. However, you can also manually liquidate commission or charge for the failed settlements in the batch, through the 'Intermediary Manual Liquidation' screen. You can invoke this screen by typing 'INDMPMCL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a web application dialog titled "Intermediary Manual Liquidation -- Webpage Dialog". It features several input fields and a table:

- Product Code \***: Input field with a dropdown arrow.
- Rule ID \***: Input field with a dropdown arrow.
- Intermediary Code \***: Input field with a dropdown arrow.
- Branch Code**: Input field.
- Reference Number**: Input field.
- Event Code \***: Input field with the value "INLQ".
- Execution Date \***: Input field with a calendar icon.
- Amount**: Input field.
- Currency**: Input field.
- SDE ID**: Input field.
- SDE Value**: Input field.
- Settlement Branch**: Input field.
- Settlement Account**: Input field.
- Manual Execution Date**: Input field.

Below the input fields is a table titled "Account Details" with a "Go to Page" button and a "1 of 1" indicator. The table has the following columns:

<input type="checkbox"/>	Reference Number	Branch Code	Customer ID	Book Date	Module Code

At the bottom of the dialog, there is a footer area with the following fields: "Input By", "Auth By", "Status", "Authorized" (with a checkbox), and a "Cancel" button.

Specify the following details.

### Product Code

Specify the intermediary product code for which you want to liquidate commission. The adjoining option list displays all valid product codes maintained in the system. You can select the appropriate one.

### Rule ID

Specify the intermediary rule based on which you want to liquidate commission. The adjoining option list displays all valid rule IDs maintained in the system. You can select the appropriate one.

### Intermediary Code

Specify the intermediary code for which you want to liquidate commission. The adjoining option list displays all valid intermediary codes maintained in the system. You can select the appropriate one.

### Branch Code

The system displays the current logged-in branch code.

### Reference Number

Specify the contract reference number for which you want to view liquidate commission. The adjoining option list displays all transactions linked to the intermediary. You can select the appropriate one.

**Event Code**

Specify the event code for which you want to liquidate commission.

**Execution Date**

Specify the date of automatic transaction execution based on which you want to liquidate commission, using the adjoining calendar.

**Amount**

Specify the commission amount that you want to liquidate.

**Currency**

Specify the currency based on which you want to liquidate commission.

**SDE ID**

Specify the SDE ID based on which you want to liquidate commission.

**SDE Value**

Specify the SDE value based on which you want to liquidate commission.

**Settlement Branch**

Specify the settlement branch code based on which you want to liquidate commission.

**Settlement Account**

Specify the settlement account based on which you want to liquidate commission.

**Manual Execution Date**

Specify the date of manual transaction execution based on which you want to liquidate commission, using the adjoining calendar.

Click Single View icon. This screen displays the following details of accounts considered for commission liquidation:

- Reference Number
- Branch Code
- Customer ID
- Book Date
- Module Code

**5.7.1 Actions Allowed**

You can perform the following actions on a record:

- New
- Delete
- Unlock
- Save

- Auth (Authorise)
- Reverse
- Execute
- Query

Refer the Procedures User Manual for details about each action.

## 5.8 Viewing Manual Liquidation Summary

You can view summary of all manual liquidations through the 'Intermediary Manual Liquidation Summary' screen. You can invoke this screen by typing 'INSMPMCL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a web application window titled "Intermediary Manual Liquidation Summary -- Webpage Dialog". The interface includes a search area with a search bar and buttons for "Search", "Advanced Search", "Refresh", and "Reset". Below the search area is a table with the following columns: "Authorized", "Product Code", "Branch Code", "Intermediary Code", "Rule ID", "Event Code", "Execution Date", and "Reference Number". The table is currently empty. At the bottom right of the window, there is an "Exit" button.

You can query based on all or any of the following criteria:

- Authorized
- Branch Code
- Rule ID
- Execution Date
- Product Code
- Intermediary Code
- Event Code
- Reference Number

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorized
- Product Code
- Branch Code
- Intermediary Code
- Rule ID
- Event Code
- Execution Date
- Reference Number

---

## 6. Annexure A – Accounting Entries and Advices

### 6.1 Introduction

This section contains details of the suggested accounting entries that can be set up for the Intermediary module of Oracle FLEXCUBE. The details of the suggested accounting entries are given event-wise.

### 6.2 Events

You can link the following events to an Intermediary product.

Event Code	Event Description
INLQ	Intermediary Liquidation
INHL	Intermediary Hierarchy Liquidation
IMST	Intermediary Statement

### 6.3 Accounting Roles

The following accounting roles are available in the module.

Accounting Role	Role Description
EXPENSE	Expense GL
REC_INTER	Receiving Intermediary
PAY_INTER	Paying Intermediary
INCOME	Income GL

### 6.4 Amount Tags

The following amount tags are available in the module.

Amount Tag	Tag Description
<RULEID>_INTERPAY_AMT	Amount paid to the Intermediary
INTERHIE_AMT	Amount for hierarchy-wise settlement

## 6.5 Accounting Entries and Advices

You can set up accounting entries for the following types of products:

- Payment
- Collection

### 6.5.1 Payment

For a product linked to payment type of rule, you can maintain the following accounting entries.

#### 6.5.1.1 Accounting Entries

##### INLQ – Intermediary Liquidation

Dr/Cr Indicator	Accounting Role	Amount Tag
Dr	EXPENSE	<RULEID>_INTERPAY_AMT
Cr	REC_INTER	<RULEID>_INTERPAY_AMT

#### 6.5.1.2 Advices

You can link the following advices to the events.

Event	Message Name	Description
INLQ	IN_INTER_CR	Credit Advice
INLQ	IN_INTER_DR	Debit Advice
IMST	IN_INTER_STMT	Intermediary Statement

The advices will address the primary intermediary.

### 6.5.2 Collection

For a product linked to collection type of rule, you can maintain the following accounting entries.

#### 6.5.2.1 Accounting Entries

##### INLQ – Intermediary Liquidation

Dr/Cr Indicator	Accounting Role	Amount Tag
Dr	PAY_INTER	<RULEID>_INTERPAY_AMT
Cr	INCOME	<RULEID>_INTERPAY_AMT
Cr	REC_INTER	<RULEID>_INTERPAY_AMT
Dr	EXPENSE	<RULEID>_INTERPAY_AMT

### **INHL – Intermediary Hierarchy Liquidation**

<b>Dr/Cr Indicator</b>	<b>Accounting Role</b>	<b>Amount Tag</b>
Dr	PAY_INTER	INTERHIE_AMT
Cr	REC_INTER	INTERHIE_AMT

Rule ID will be replaced with actual Rule ID while processing the entries.

#### **6.5.2.2 Advices**

You can link the following advices to the events.

<b>Event</b>	<b>Message Name</b>	<b>Description</b>
INLQ	IN_INTER_CR	Credit Advice
INLQ	IN_INTER_DR	Debit Advice
IMST	IN_INTER_STMT	Intermediary Statement

The advices will address the primary intermediary.

If settlement mode for intermediary is CASA for both debit and credit, the settlement details will be picked up from the settlement account maintenance for the intermediary.

If settlement mode for intermediary is 'External Account', the credits will be handled using the external account by triggering a PC transaction. Debits to intermediary will be handled using the settlement account details maintained for the intermediary.

## **6.6 Advice Format**

You can maintain the following advice formats using the 'Advice Format' screen:

- INTER\_CR\_ADV (for credit advice)
- INTER\_DR\_ADV (for debit advice)
- INTER\_STMT (for intermediary statement)

### **6.6.1 INTER CR ADV**

You can capture the following details in this format:

- Date
- Intermediary Code
- Intermediary Name
- Address
- Intermediary Customer Id
- Value Date
- Amount
- Currency

- Credit Account

### **6.6.2 INTER DR ADV**

You can capture the following details in this format:

- Date
- Intermediary Code
- Intermediary Name
- Address
- Intermediary Customer Id
- Value Date
- Amount
- Currency
- Debit Account

### **6.6.3 INTER STMT**

You can capture the following details in this format:

- Date
- Statement Period
- Intermediary Code
- Intermediary Name
- Address
- Intermediary Customer id
- Transaction Date
- Transaction Details
- Amount
- Currency
- Debit/Credit
- Settlement account



Intermediary  
[January] [2010]  
Version 11.0

Oracle Corporation  
World Headquarters  
500 Oracle Parkway  
Redwood Shores, CA 94065  
U.S.A.

Worldwide Inquiries:  
Phone: +1.650.506.7000  
Fax: +1.650.506.7200  
[www.oracle.com/ financial\\_services/](http://www.oracle.com/financial_services/)

Copyright © [2010] Oracle Financial Services Software Limited. All rights reserved.

No part of this work may be reproduced, stored in a retrieval system, adopted or transmitted in any form or by any means, electronic, mechanical, photographic, graphic, optic recording or otherwise, translated in any language or computer language, without the prior written permission of Oracle Financial Services Software Limited.

Due care has been taken to make this document and accompanying software package as accurate as possible. However, Oracle Financial Services Software Limited makes no representation or warranties with respect to the contents hereof and shall not be responsible for any loss or damage caused to the user by the direct or indirect use of this document and the accompanying Software System. Furthermore, Oracle Financial Services Software Limited reserves the right to alter, modify or otherwise change in any manner the content hereof, without obligation of Oracle Financial Services Software Limited to notify any person of such revision or changes.

All company and product names are trademarks of the respective companies with which they are associated.