

Gateway Documentation - ELCoreService
Oracle FLEXCUBE Universal Banking
Release FCELCM_1.1.13_FCUBS12_0_87_1.0
[August] [2014]



Table Of Contents

1. BACKGROUND	1
2. ELCoreService	2
2.1. CustomerReopen	2
2.1.1. CO-CustomerReopen-Res-Full-MSG.xsd	2
2.1.2. CO-CustomerReopen-Res-PK-MSG.xsd	22
2.1.3. CO-CustomerReopen-Req-Full-MSG.xsd	30
2.1.4. CO-CustomerReopen-Req-IO-MSG.xsd	48
2.2. CCYPairModify	55
2.2.1. CO-CCYRatesModify-Req-Full-MSG.xsd	55
2.2.2. CO-CCYRatesModify-Req-IO-MSG.xsd	67
2.2.3. CO-CCYRatesModify-Res-Full-MSG.xsd	78
2.2.4. CO-CCYRatesModify-Res-PK-MSG.xsd	92
2.3. CCYPairNew	101
2.3.1. CO-CCYRatesNew-Req-Full-MSG.xsd	101
2.3.2. CO-CCYRatesNew-Req-IO-MSG.xsd	113
2.3.3. CO-CCYRatesNew-Res-Full-MSG.xsd	125
2.3.4. CO-CCYRatesNew-Res-PK-MSG.xsd	139
2.4. CCYPairQuery	148
2.4.1. CO-CCYRatesQuery-Req-IO-MSG.xsd	148
2.4.2. CO-CCYRatesQuery-Res-Full-MSG.xsd	155
2.5. CCYPairReopen	169
2.5.1. CO-CCYRatesReopen-Req-Full-MSG.xsd	169
2.5.2. CO-CCYRatesReopen-Req-IO-MSG.xsd	181
2.5.3. CO-CCYRatesReopen-Res-Full-MSG.xsd	188
2.5.4. CO-CCYRatesReopen-Res-PK-MSG.xsd	202
2.6. CCYRatesAuth	211
2.6.1. CO-CurrencyPairAuth-Req-Full-MSG.xsd	211
2.6.2. CO-CurrencyPairAuth-Req-IO-MSG.xsd	223
2.6.3. CO-CurrencyPairAuth-Res-Full-MSG.xsd	230
2.6.4. CO-CurrencyPairAuth-Res-PK-MSG.xsd	244
2.7. CCYRatesClose	252
2.7.1. CO-CurrencyPairClose-Req-Full-MSG.xsd	252
2.7.2. CO-CurrencyPairClose-Req-IO-MSG.xsd	264
2.7.3. CO-CurrencyPairClose-Res-Full-MSG.xsd	271
2.7.4. CO-CurrencyPairClose-Res-PK-MSG.xsd	285
2.8. CCYRatesDelete	293
2.8.1. CO-CurrencyPairDelete-Req-Full-MSG.xsd	293
2.8.2. CO-CurrencyPairDelete-Req-IO-MSG.xsd	305
2.8.3. CO-CurrencyPairDelete-Res-Full-MSG.xsd	312
2.8.4. CO-CurrencyPairDelete-Res-PK-MSG.xsd	326
2.9. CustomerAuthorize	334
2.9.1. CO-CustomerAuthorize-Req-Full-MSG.xsd	334
2.9.2. CO-CustomerAuthorize-Req-IO-MSG.xsd	352
2.9.3. CO-CustomerAuthorize-Res-Full-MSG.xsd	359
2.9.4. CO-CustomerAuthorize-Res-PK-MSG.xsd	379
2.10. CustomerClose	387
2.10.1. CO-CustomerClose-Req-Full-MSG.xsd	387
2.10.2. CO-CustomerClose-Req-IO-MSG.xsd	405
2.10.3. CO-CustomerClose-Res-Full-MSG.xsd	412
2.10.4. CO-CustomerClose-Res-PK-MSG.xsd	432
2.11. CustomerCreate	440
2.11.1. CO-CustomerCreate-Req-Full-MSG.xsd	440
2.11.2. CO-CustomerCreate-Req-IO-MSG.xsd	458
2.11.3. CO-CustomerCreate-Res-Full-MSG.xsd	476

2.11.4. CO-CustomerCreate-Res-PK-MSG.xsd	496
2.12. CustomerDelete	504
2.12.1. CO-CustomerDelete-Req-Full-MSG.xsd	504
2.12.2. CO-CustomerDelete-Req-IO-MSG.xsd	522
2.12.3. CO-CustomerDelete-Res-Full-MSG.xsd	529
2.12.4. CO-CustomerDelete-Res-PK-MSG.xsd	549
2.13. CustomerModify	557
2.13.1. CO-CustomerModify-Req-Full-MSG.xsd	557
2.13.2. CO-CustomerModify-Req-IO-MSG.xsd	575
2.13.3. CO-CustomerModify-Res-Full-MSG.xsd	593
2.13.4. CO-CustomerModify-Res-PK-MSG.xsd	613
2.14. CustomerQuery	621
2.14.1. CO-CustomerQuery-Req-IO-MSG.xsd	621
2.14.2. CO-CustomerQuery-Res-Full-MSG.xsd	628
2.15. CCYPairAuth	648
2.15.1. CO-CCYRatesAuth-Req-Full-MSG.xsd	648
2.15.2. CO-CCYRatesAuth-Req-IO-MSG.xsd	660
2.15.3. CO-CCYRatesAuth-Res-Full-MSG.xsd	667
2.15.4. CO-CCYRatesAuth-Res-PK-MSG.xsd	682
2.16. CCYPairClose	691
2.16.1. CO-CCYRatesClose-Req-Full-MSG.xsd	691
2.16.2. CO-CCYRatesClose-Req-IO-MSG.xsd	703
2.16.3. CO-CCYRatesClose-Res-Full-MSG.xsd	710
2.16.4. CO-CCYRatesClose-Res-PK-MSG.xsd	724
2.17. CCYPairDelete	733
2.17.1. CO-CCYRatesDelete-Req-Full-MSG.xsd	733
2.17.2. CO-CCYRatesDelete-Req-IO-MSG.xsd	745
2.17.3. CO-CCYRatesDelete-Res-Full-MSG.xsd	752
2.17.4. CO-CCYRatesDelete-Res-PK-MSG.xsd	767

1.BACKGROUND

Integration of different applications and solutions is a key area in today's systems. A variety of specialized applications deployed on disparate platforms and using different infrastructure need to be able to communicate and integrate seamlessly with FLEXCUBE UBS in order to exchange data. The FLEXCUBE UBS Integration Gateway (referred to as Gateway) will cater to these integration needs.

The integration needs supported by the Gateway can be broadly categorized from the perspective of the Gateway as follows:

1. Inbound application integration – used when any external system needs to add, modify or query information within FLEXCUBE UBS

2. Outbound application integration– used when any external system needs to be notified of the various events that occur within FLEXCUBE UBS

The following sections provide detailed XSD documentation of all operations available in ELCoreService of EL-Module

2.ELCoreService

ELCoreServiceELCoreService

2.1.CustomerReopen

Reopen Customer

2.1.1.CO-CustomerReopen-Res-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

Customer-Full

CUSTOMERNO

CUSTOMERTYPE

CUSTOMERNAME1

ADDRESSLINE1

ADDRESSLINE3

ADDRESSLINE2

ADDRESSLINE4

COUNTRY

SHORTNAME

NATIONALITY

LANGUAGE

EXPOSURECOUNTRY

LOCALBRANCH

UNIQUEIDNAME
 UNIQUEIDVALUE
 FROZEN
 DECEASED
 CUSTOMERCATEGORY
 SSN
 LOCCODE
 FULLNAME
 GROUPCODE
 FAXNUMBER
 CRMCUSTOMER
 CREDITRATING
 REVISIONDATE
 SHORTNAME2
 UNADVISED
 ISSUERCUSTOMER
 TREASURYCUSTOMER
 SOURCE
 USERREFNO
 MAKERID
 MAKERDTSTAMP
 CHECKERID
 CHECKERDTSTAMP
 MODNO
 AUTHSTAT
 RECSTAT
 ONCEAUTH
 UDFDETAILS
 FUNCTIONID
 FIELD_NAME
 DATATYPE
 FIELD_VALUE
 VAL_TYPE
 FCUBS_ERROR_RESP
 ERROR
 ECODE
 EDESC
 FCUBS_WARNING_RESP
 WARNING
 WCODE
 WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER

Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description
Name	CORRELID
Datatype	String

Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

SERVICE

Attribute	Description
------------------	--------------------

Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	

Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description				
Name	MSGSTAT				
Datatype	String				
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>enumeration</td><td>SUCCESS,WARNING,FAILURE</td></tr></tbody></table>	Restrictions	Description	enumeration	SUCCESS,WARNING,FAILURE
	Restrictions	Description			
enumeration	SUCCESS,WARNING,FAILURE				

[TOP](#)

ADDL

Attribute	Description				
Name	ADDL				
Datatype					
Description	This node is to be used for Additional information about a message.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				

[TOP](#)

PARAM

Attribute	Description						
Name	PARAM						
Datatype							
Description	This is the parent node for each parameter in the additional node.						
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>maxOccurs</td><td>unbounded</td></tr><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	maxOccurs	unbounded	minOccurs	0
	Attribute	Description					
	maxOccurs	unbounded					
minOccurs	0						

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

Customer-Full

Attribute	Description
Name	Customer-Full
Datatype	
Description	

[TOP](#)

CUSTOMERNO

Attribute	Description	
Name	CUSTOMERNO	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	9

[TOP](#)

CUSTOMERTYPE

Attribute	Description	
Name	CUSTOMERTYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	B,C,I

[TOP](#)

CUSTOMERNAME1

Attribute	Description	
Name	CUSTOMERNAME1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

ADDRESSLINE1

Attribute	Description				
Name	ADDRESSLINE1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>1</td></tr></tbody></table>	Attribute	Description	minOccurs	1
	Attribute	Description			
minOccurs	1				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>105</td></tr></tbody></table>	Restrictions	Description	maxLength	105
	Restrictions	Description			
maxLength	105				

[TOP](#)

ADDRESSLINE3

Attribute	Description				
Name	ADDRESSLINE3				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>105</td></tr></tbody></table>	Restrictions	Description	maxLength	105
	Restrictions	Description			
maxLength	105				

[TOP](#)

ADDRESSLINE2

Attribute	Description				
Name	ADDRESSLINE2				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>105</td></tr></tbody></table>	Restrictions	Description	maxLength	105
	Restrictions	Description			
maxLength	105				

[TOP](#)

ADDRESSLINE4

Attribute	Description				
Name	ADDRESSLINE4				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>105</td></tr></tbody></table>	Restrictions	Description	maxLength	105
	Restrictions	Description			
maxLength	105				

[TOP](#)

COUNTRY

Attribute	Description
-----------	-------------

Name	COUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

SHORTNAME

Attribute	Description	
Name	SHORTNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

NATIONALITY

Attribute	Description	
Name	NATIONALITY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LANGUAGE

Attribute	Description	
Name	LANGUAGE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

EXPOSURECOUNTRY

Attribute	Description	
Name	EXPOSURECOUNTRY	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LOCALBRANCH

Attribute	Description	
Name	LOCALBRANCH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

UNIQUEIDNAME

Attribute	Description	
Name	UNIQUEIDNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

UNIQUEIDVALUE

Attribute	Description	
Name	UNIQUEIDVALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

FROZEN

Attribute	Description	
Name	FROZEN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

DECEASED

Attribute	Description	
Name	DECEASED	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CUSTOMERCATEGORY

Attribute	Description	
Name	CUSTOMERCATEGORY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

SSN

Attribute	Description	
Name	SSN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	11

[TOP](#)

LOCCODE

Attribute	Description	
Name	LOCCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

FULLNAME

Attribute	Description	
Name	FULLNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

GROUPCODE

Attribute	Description	
Name	GROUPCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

FAXNUMBER

Attribute	Description	
Name	FAXNUMBER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

CRMCUSTOMER

Attribute	Description	
Name	CRMCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CREDITRATING

Attribute	Description	
Name	CREDITRATING	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

REVISIONDATE

Attribute	Description	
Name	REVISIONDATE	
Datatype	Date	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SHORTNAME2

Attribute	Description	
Name	SHORTNAME2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

UNADVISED

Attribute	Description	
Name	UNADVISED	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ISSUERCUSTOMER

Attribute	Description	
Name	ISSUERCUSTOMER	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

TREASURYCUSTOMER

Attribute	Description	
Name	TREASURYCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERREFNO

Attribute	Description	
Name	USERREFNO	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	50

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description
Name	FUNCTIONID
Datatype	String

Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description	
Name	ERROR	
Datatype		
Description	This indicates the type of error encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

ECODE

Attribute	Description	
Name	ECODE	
Datatype	String	
Description	This indicates the code for the error encountered.	

[TOP](#)

EDESC

Attribute	Description	
Name	EDESC	
Datatype	String	
Description	This indicates the description of the error encountered.	

[TOP](#)

FCUBS_WARNING_RESP

Attribute	Description	
Name	FCUBS_WARNING_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

WARNING

Attribute	Description	
Name	WARNING	
Datatype		
Description	Indicates the warning encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

[TOP](#)

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

[TOP](#)

2.1.2.CO-CustomerReopen-Res-PK-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

Customer-PK

CUSTOMERNO

MODNO

FCUBS_ERROR_RESP

ERROR

ECODE

EDESC

FCUBS_WARNING_RESP

WARNING

WCODE

WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description
-----------	-------------

Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description				
Name	MULTITRIPID				
Datatype	String				
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

FUNCTIONID

Attribute	Description						
Name	FUNCTIONID						
Datatype	String						
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.						
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0		
	Attribute	Description					
minOccurs	0						
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>8</td></tr><tr><td>pattern</td><td>[A-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	maxLength	8	pattern	[A-Z_0-9]*
	Restrictions	Description					
	maxLength	8					
pattern	[A-Z_0-9]*						

[TOP](#)

ACTION

Attribute	Description				
Name	ACTION				
Datatype	String				
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

MSGSTAT

Attribute	Description				
Name	MSGSTAT				
Datatype	String				
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				

Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

Customer-PK

Attribute	Description
Name	Customer-PK

Datatype	
Description	

[TOP](#)

CUSTOMERNO

Attribute	Description	
Name	CUSTOMERNO	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	9

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description	
Name	ERROR	
Datatype		
Description	This indicates the type of error encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

ECODE

Attribute	Description	
Name	ECODE	
Datatype	String	
Description	This indicates the code for the error encountered.	

[TOP](#)**EDESC**

Attribute	Description
Name	EDESC
Datatype	String
Description	This indicates the description of the error encountered.

[TOP](#)**FCUBS_WARNING_RESP**

Attribute	Description						
Name	FCUBS_WARNING_RESP						
Datatype							
Description							
Attributes	<table border="1"> <thead> <tr> <th>Attribute</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>maxOccurs</td> <td>unbounded</td> </tr> <tr> <td>minOccurs</td> <td>0</td> </tr> </tbody> </table>	Attribute	Description	maxOccurs	unbounded	minOccurs	0
Attribute	Description						
maxOccurs	unbounded						
minOccurs	0						

[TOP](#)**WARNING**

Attribute	Description				
Name	WARNING				
Datatype					
Description	Indicates the warning encountered.				
Attributes	<table border="1"> <thead> <tr> <th>Attribute</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>maxOccurs</td> <td>unbounded</td> </tr> </tbody> </table>	Attribute	Description	maxOccurs	unbounded
Attribute	Description				
maxOccurs	unbounded				

[TOP](#)**WCODE**

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

[TOP](#)**WDESC**

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

[TOP](#)

2.1.3.CO-CustomerReopen-Req-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

Customer-Full

CUSTOMERNO

CUSTOMERTYPE

CUSTOMERNAME1

ADDRESSLINE1

ADDRESSLINE3

ADDRESSLINE2

ADDRESSLINE4

COUNTRY

SHORTNAME

NATIONALITY

LANGUAGE

EXPOSURECOUNTRY

LOCALBRANCH

UNIQUEIDNAME

UNIQUEIDVALUE

FROZEN

DECEASED

CUSTOMERCATEGORY

SSN

LOCCODE
 FULLNAME
 GROUPCODE
 FAXNUMBER
 CRMCUSTOMER
 CREDITRATING
 REVISIONDATE
 SHORTNAME2
 UNADVISED
 ISSUERCUSTOMER
 TREASURYCUSTOMER
 SOURCE
 USERREFNO
 MAKERID
 MAKERDTSTAMP
 CHECKERID
 CHECKERDTSTAMP
 MODNO
 AUTHSTAT
 RECSTAT
 ONCEAUTH
 UDFDETAILS
 FUNCTIONID
 FIELD_NAME
 DATATYPE
 FIELD_VALUE
 VAL_TYPE

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description
Name	USERID
Datatype	String

Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	

Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	

Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description	
Name	VALUE	
Datatype	String	
Description	The value of the additional parameter comes here.	

[TOP](#)

FCUBS_BODY

Attribute	Description	
Name	FCUBS_BODY	
Datatype		
Description		

[TOP](#)

Customer-Full

Attribute	Description	
Name	Customer-Full	
Datatype		
Description		

[TOP](#)

CUSTOMERNO

Attribute	Description				
Name	CUSTOMERNO				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>1</td></tr></tbody></table>	Attribute	Description	minOccurs	1
	Attribute	Description			
minOccurs	1				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>9</td></tr></tbody></table>	Restrictions	Description	maxLength	9
	Restrictions	Description			
maxLength	9				

[TOP](#)

CUSTOMERTYPE

Attribute	Description				
Name	CUSTOMERTYPE				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>enumeration</td><td>B,C,I</td></tr></tbody></table>	Restrictions	Description	enumeration	B,C,I
	Restrictions	Description			
enumeration	B,C,I				

[TOP](#)

CUSTOMERNAME1

Attribute	Description				
Name	CUSTOMERNAME1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>105</td></tr></tbody></table>	Restrictions	Description	maxLength	105
	Restrictions	Description			
maxLength	105				

[TOP](#)

ADDRESSLINE1

Attribute	Description				
Name	ADDRESSLINE1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>1</td></tr></tbody></table>	Attribute	Description	minOccurs	1
	Attribute	Description			
minOccurs	1				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>105</td></tr></tbody></table>	Restrictions	Description	maxLength	105
	Restrictions	Description			
maxLength	105				

[TOP](#)

ADDRESSLINE3

Attribute	Description
-----------	-------------

Name	ADDRESSLINE3	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

ADDRESSLINE2

Attribute	Description	
Name	ADDRESSLINE2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

ADDRESSLINE4

Attribute	Description	
Name	ADDRESSLINE4	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

COUNTRY

Attribute	Description	
Name	COUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

SHORTNAME

Attribute	Description	
Name	SHORTNAME	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

NATIONALITY

Attribute	Description	
Name	NATIONALITY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LANGUAGE

Attribute	Description	
Name	LANGUAGE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

EXPOSURECOUNTRY

Attribute	Description	
Name	EXPOSURECOUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LOCALBRANCH

Attribute	Description	
Name	LOCALBRANCH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

UNIQUEIDNAME

Attribute	Description	
Name	UNIQUEIDNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

UNIQUEIDVALUE

Attribute	Description	
Name	UNIQUEIDVALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

FROZEN

Attribute	Description	
Name	FROZEN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

DECEASED

Attribute	Description	
Name	DECEASED	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

CUSTOMERCATEGORY

Attribute	Description	
Name	CUSTOMERCATEGORY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	10

SSN

Attribute	Description	
Name	SSN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	11

LOCCODE

Attribute	Description	
Name	LOCCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

FULLNAME

Attribute	Description	
Name	FULLNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

GROUPCODE

Attribute	Description	
Name	GROUPCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

FAXNUMBER

Attribute	Description	
Name	FAXNUMBER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

CRMCUSTOMER

Attribute	Description	
Name	CRMCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CREDITRATING

Attribute	Description	
Name	CREDITRATING	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

REVISIONDATE

Attribute	Description
Name	REVISIONDATE

Datatype	Date	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SHORTNAME2

Attribute	Description	
Name	SHORTNAME2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

UNADVISED

Attribute	Description	
Name	UNADVISED	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ISSUERCUSTOMER

Attribute	Description	
Name	ISSUERCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

TREASURYCUSTOMER

Attribute	Description	
Name	TREASURYCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERREFNO

Attribute	Description	
Name	USERREFNO	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	50

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

RECSTAT

Attribute	Description
Name	RECSTAT

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		

Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

2.1.4.CO-CustomerReopen-Req-IO-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

Customer-IO

CUSTOMERNO

MODNO

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description
Name	UBSCOMP
Datatype	String
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.
Restrictions	Restrictions
	enumeration
	Description
	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description
Name	MSGID
Datatype	String
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.
Attributes	Attribute
	minOccurs
	0
nillable	
true	
Restrictions	Restrictions
	pattern
	Description
	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description
Name	CORRELID
Datatype	String
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.
Attributes	Attribute
	minOccurs
	0
nillable	
true	
Restrictions	Restrictions
	pattern
	Description
	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description
Name	USERID
Datatype	String

Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	

Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	

Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description	
Name	VALUE	
Datatype	String	
Description	The value of the additional parameter comes here.	

[TOP](#)

FCUBS_BODY

Attribute	Description	
Name	FCUBS_BODY	
Datatype		
Description		

[TOP](#)

Customer-IO

Attribute	Description	
Name	Customer-IO	
Datatype		
Description		

[TOP](#)

CUSTOMERNO

Attribute	Description	
Name	CUSTOMERNO	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	9

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

2.2.CCYPairModify

CCYPairModify

2.2.1.CO-CCYRatesModify-Req-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

RatesMaster-Full

BRANCHCODE

CCY1

CCY2

MAKERID

MAKERDTSTAMP

CHECKERID

CHECKERDTSTAMP

MODNO

AUTHSTAT

RECSTAT

ONCEAUTH

Rates

RATETYPE

MIDRATE

BUYSPREAD

SALESPREAD

[BUYRATE](#)
[SALERATE](#)
[UDFDETAILS](#)
[FUNCTIONID](#)
[FIELD_NAME](#)
[DATATYPE](#)
[FIELD_VALUE](#)
[VAL_TYPE](#)

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description
Name	MSGID
Datatype	String
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.

Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description
------------------	--------------------

Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

NAME

Attribute	Description
Name	NAME

Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

RatesMaster-Full

Attribute	Description
Name	RatesMaster-Full
Datatype	
Description	

[TOP](#)

BRANCHCODE

Attribute	Description				
Name	BRANCHCODE				
Datatype	String				
Description					
Attributes	<table border="1"> <thead> <tr> <th>Attribute</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>minOccurs</td> <td>0</td> </tr> </tbody> </table>	Attribute	Description	minOccurs	0
Attribute	Description				
minOccurs	0				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>maxLength</td> <td>3</td> </tr> </tbody> </table>	Restrictions	Description	maxLength	3
Restrictions	Description				
maxLength	3				

[TOP](#)

CCY1

Attribute	Description				
Name	CCY1				
Datatype	String				
Description					
Attributes	<table border="1"> <thead> <tr> <th>Attribute</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>minOccurs</td> <td>1</td> </tr> </tbody> </table>	Attribute	Description	minOccurs	1
Attribute	Description				
minOccurs	1				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>maxLength</td> <td>3</td> </tr> </tbody> </table>	Restrictions	Description	maxLength	3
Restrictions	Description				
maxLength	3				

[TOP](#)

CCY2

Attribute	Description				
Name	CCY2				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

MAKERID

Attribute	Description				
Name	MAKERID				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>12</td></tr></tbody></table>	Restrictions	Description	maxLength	12
	Restrictions	Description			
maxLength	12				

[TOP](#)

MAKERDTSTAMP

Attribute	Description				
Name	MAKERDTSTAMP				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>25</td></tr></tbody></table>	Restrictions	Description	maxLength	25
	Restrictions	Description			
maxLength	25				

[TOP](#)

CHECKERID

Attribute	Description				
Name	CHECKERID				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>12</td></tr></tbody></table>	Restrictions	Description	maxLength	12
	Restrictions	Description			
maxLength	12				

[TOP](#)

CHECKERDTSTAMP

Attribute	Description
-----------	-------------

Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

Rates

Attribute	Description	
Name	Rates	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

RATETYPE

Attribute	Description	
Name	RATETYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8

[TOP](#)

MIDRATE

Attribute	Description	
Name	MIDRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYSPREAD

Attribute	Description	
Name	BUYSPREAD	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALESPREAD

Attribute	Description	
Name	SALESPREAD	
Datatype	Number	

Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYRATE

Attribute	Description	
Name	BUYRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALERATE

Attribute	Description	
Name	SALERATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

2.2.2.CO-CCYRatesModify-Req-IO-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

RatesMaster-IO

BRANCHCODE

CCY1

CCY2

MODNO

Rates

RATETYPE

MIDRATE

BUYSPREAD

SALESPREAD

BUYRATE

SALERATE

UDFDETAILS

FUNCTIONID

FIELD_NAME

DATATYPE

FIELD_VALUE

VAL_TYPE

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description
Name	CORRELID
Datatype	String

Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

SERVICE

Attribute	Description
------------------	--------------------

Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	

Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description				
Name	MSGSTAT				
Datatype	String				
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>enumeration</td><td>SUCCESS,WARNING,FAILURE</td></tr></tbody></table>	Restrictions	Description	enumeration	SUCCESS,WARNING,FAILURE
	Restrictions	Description			
enumeration	SUCCESS,WARNING,FAILURE				

[TOP](#)

ADDL

Attribute	Description				
Name	ADDL				
Datatype					
Description	This node is to be used for Additional information about a message.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				

[TOP](#)

PARAM

Attribute	Description						
Name	PARAM						
Datatype							
Description	This is the parent node for each parameter in the additional node.						
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>maxOccurs</td><td>unbounded</td></tr><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	maxOccurs	unbounded	minOccurs	0
	Attribute	Description					
	maxOccurs	unbounded					
minOccurs	0						

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

RatesMaster-IO

Attribute	Description
Name	RatesMaster-IO
Datatype	
Description	

[TOP](#)

BRANCHCODE

Attribute	Description	
Name	BRANCHCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY1

Attribute	Description	
Name	CCY1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY2

Attribute	Description	
Name	CCY2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	totalDigits	22

[TOP](#)

Rates

Attribute	Description	
Name	Rates	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

RATETYPE

Attribute	Description	
Name	RATETYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8

[TOP](#)

MIDRATE

Attribute	Description	
Name	MIDRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYSPREAD

Attribute	Description	
Name	BUYSPREAD	
Datatype	Number	
Description		

Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALESPREAD

Attribute	Description	
Name	SALESPREAD	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYRATE

Attribute	Description	
Name	BUYRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALERATE

Attribute	Description	
Name	SALERATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	

Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

2.2.3.CO-CCYRatesModify-Res-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

RatesMaster-Full

BRANCHCODE

CCY1

CCY2

MAKERID

MAKERDTSTAMP

CHECKERID

CHECKERDTSTAMP

MODNO

AUTHSTAT

RECSTAT

ONCEAUTH

Rates

RATETYPE

MIDRATE

BUYSPREAD

SALESPREAD

BUYRATE

SALERATE

UDFDETAILS

FUNCTIONID
 FIELD_NAME
 DATATYPE
 FIELD_VALUE
 VAL_TYPE
 FCUBS_ERROR_RESP
 ERROR
 ECODE
 EDESC
 FCUBS_WARNING_RESP
 WARNING
 WCODE
 WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description				
Name	SOURCE				
Datatype	String				
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>pattern</td> <td>[a-zA-Z_0-9]*</td> </tr> </tbody> </table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

UBSCOMP

Attribute	Description				
Name	UBSCOMP				
Datatype	String				
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>enumeration</td> <td>FCUBS,FCIS</td> </tr> </tbody> </table>	Restrictions	Description	enumeration	FCUBS,FCIS
	Restrictions	Description			
enumeration	FCUBS,FCIS				

[TOP](#)

MSGID

Attribute	Description
Name	MSGID

Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

MULTIRIPID

Attribute	Description	
Name	MULTIRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTIRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

RatesMaster-Full

Attribute	Description
Name	RatesMaster-Full
Datatype	
Description	

[TOP](#)

BRANCHCODE

Attribute	Description				
Name	BRANCHCODE				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
Attribute	Description				
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
Restrictions	Description				
maxLength	3				

[TOP](#)

CCY1

Attribute	Description				
Name	CCY1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>1</td></tr></tbody></table>	Attribute	Description	minOccurs	1
Attribute	Description				
minOccurs	1				

Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY2

Attribute	Description	
Name	CCY2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

Rates

Attribute	Description	
Name	Rates	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

RATETYPE

Attribute	Description	
Name	RATETYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8

[TOP](#)

MIDRATE

Attribute	Description	
Name	MIDRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYSPREAD

Attribute	Description	
Name	BUYSPREAD	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALESPREAD

Attribute	Description	
Name	SALESPREAD	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYRATE

Attribute	Description	
Name	BUYRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALERATE

Attribute	Description	
Name	SALERATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

FCUBS_ERROR_RESP

Attribute		Description
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute		Description
Name	ERROR	
Datatype		
Description	This indicates the type of error encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

ECODE

Attribute		Description
Name	ECODE	
Datatype	String	
Description	This indicates the code for the error encountered.	

[TOP](#)

EDESC

Attribute		Description
Name	EDESC	
Datatype	String	
Description	This indicates the description of the error encountered.	

[TOP](#)

FCUBS_WARNING_RESP

Attribute		Description
Name	FCUBS_WARNING_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

WARNING

Attribute	Description
-----------	-------------

Name	WARNING	
Datatype		
Description	Indicates the warning encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

[TOP](#)

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

[TOP](#)

2.2.4.CO-CCYRatesModify-Res-PK-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

RatesMaster-PK

BRANCHCODE

CCY1

CCY2

FCUBS_ERROR_RESP

ERROR

ECODE

EDESC

FCUBS_WARNING_RESP

WARNING

WCODE

WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

RatesMaster-PK

Attribute	Description
Name	RatesMaster-PK

Datatype	
Description	

[TOP](#)

BRANCHCODE

Attribute	Description	
Name	BRANCHCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY1

Attribute	Description	
Name	CCY1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY2

Attribute	Description	
Name	CCY2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description				
Name	ERROR				
Datatype					
Description	This indicates the type of error encountered.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>maxOccurs</td><td>unbounded</td></tr></tbody></table>	Attribute	Description	maxOccurs	unbounded
	Attribute	Description			
maxOccurs	unbounded				

[TOP](#)

ECODE

Attribute	Description
Name	ECODE
Datatype	String
Description	This indicates the code for the error encountered.

[TOP](#)

EDESC

Attribute	Description
Name	EDESC
Datatype	String
Description	This indicates the description of the error encountered.

[TOP](#)

FCUBS_WARNING_RESP

Attribute	Description						
Name	FCUBS_WARNING_RESP						
Datatype							
Description							
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>maxOccurs</td><td>unbounded</td></tr><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	maxOccurs	unbounded	minOccurs	0
	Attribute	Description					
	maxOccurs	unbounded					
minOccurs	0						

[TOP](#)

WARNING

Attribute	Description				
Name	WARNING				
Datatype					
Description	Indicates the warning encountered.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>maxOccurs</td><td>unbounded</td></tr></tbody></table>	Attribute	Description	maxOccurs	unbounded
	Attribute	Description			
maxOccurs	unbounded				

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

2.3.CCYPairNew

CCYPairNew

2.3.1.CO-CCYRatesNew-Req-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

RatesMaster-Full

BRANCHCODE

CCY1

CCY2

MAKERID

MAKERDTSTAMP

CHECKERID

CHECKERDTSTAMP

MODNO

AUTHSTAT

RECSTAT

ONCEAUTH

Rates

RATETYPE

MIDRATE

BUYSPREAD

SALESPREAD

[BUYRATE](#)
[SALERATE](#)
[UDFDETAILS](#)
[FUNCTIONID](#)
[FIELD_NAME](#)
[DATATYPE](#)
[FIELD_VALUE](#)
[VAL_TYPE](#)

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description
Name	MSGID
Datatype	String
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.

Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description
------------------	--------------------

Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description						
Name	SOURCE_USERID						
Datatype	String						
Description	This is the user id in the Source system who is performing the action.						
Attributes	<table border="1"> <thead> <tr> <th>Attribute</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>minOccurs</td> <td>0</td> </tr> <tr> <td>nullable</td> <td>true</td> </tr> </tbody> </table>	Attribute	Description	minOccurs	0	nullable	true
Attribute	Description						
minOccurs	0						
nullable	true						

[TOP](#)

DESTINATION

Attribute	Description				
Name	DESTINATION				
Datatype	String				
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.				
Attributes	<table border="1"> <thead> <tr> <th>Attribute</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>minOccurs</td> <td>0</td> </tr> </tbody> </table>	Attribute	Description	minOccurs	0
Attribute	Description				
minOccurs	0				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>pattern</td> <td>[a-zA-Z_0-9]*</td> </tr> </tbody> </table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
Restrictions	Description				
pattern	[a-zA-Z_0-9]*				

[TOP](#)

MULTIRIPID

Attribute	Description				
Name	MULTIRIPID				
Datatype	String				
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTIRIPID from the earlier received response if the source system accepts the overrides.				
Attributes	<table border="1"> <thead> <tr> <th>Attribute</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>minOccurs</td> <td>0</td> </tr> </tbody> </table>	Attribute	Description	minOccurs	0
Attribute	Description				
minOccurs	0				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>pattern</td> <td>[a-zA-Z_0-9]*</td> </tr> </tbody> </table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
Restrictions	Description				
pattern	[a-zA-Z_0-9]*				

[TOP](#)

FUNCTIONID

Attribute	Description						
Name	FUNCTIONID						
Datatype	String						
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.						
Attributes	<table border="1"> <thead> <tr> <th>Attribute</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>minOccurs</td> <td>0</td> </tr> </tbody> </table>	Attribute	Description	minOccurs	0		
Attribute	Description						
minOccurs	0						
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>maxLength</td> <td>8</td> </tr> <tr> <td>pattern</td> <td>[A-Z_0-9]*</td> </tr> </tbody> </table>	Restrictions	Description	maxLength	8	pattern	[A-Z_0-9]*
Restrictions	Description						
maxLength	8						
pattern	[A-Z_0-9]*						

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

NAME

Attribute	Description
Name	NAME

Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

RatesMaster-Full

Attribute	Description
Name	RatesMaster-Full
Datatype	
Description	

[TOP](#)

BRANCHCODE

Attribute	Description				
Name	BRANCHCODE				
Datatype	String				
Description					
Attributes	<table border="1"> <thead> <tr> <th>Attribute</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>minOccurs</td> <td>0</td> </tr> </tbody> </table>	Attribute	Description	minOccurs	0
Attribute	Description				
minOccurs	0				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>maxLength</td> <td>3</td> </tr> </tbody> </table>	Restrictions	Description	maxLength	3
Restrictions	Description				
maxLength	3				

[TOP](#)

CCY1

Attribute	Description				
Name	CCY1				
Datatype	String				
Description					
Attributes	<table border="1"> <thead> <tr> <th>Attribute</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>minOccurs</td> <td>1</td> </tr> </tbody> </table>	Attribute	Description	minOccurs	1
Attribute	Description				
minOccurs	1				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>maxLength</td> <td>3</td> </tr> </tbody> </table>	Restrictions	Description	maxLength	3
Restrictions	Description				
maxLength	3				

[TOP](#)

CCY2

Attribute	Description				
Name	CCY2				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

MAKERID

Attribute	Description				
Name	MAKERID				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>12</td></tr></tbody></table>	Restrictions	Description	maxLength	12
	Restrictions	Description			
maxLength	12				

[TOP](#)

MAKERDTSTAMP

Attribute	Description				
Name	MAKERDTSTAMP				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>25</td></tr></tbody></table>	Restrictions	Description	maxLength	25
	Restrictions	Description			
maxLength	25				

[TOP](#)

CHECKERID

Attribute	Description				
Name	CHECKERID				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>12</td></tr></tbody></table>	Restrictions	Description	maxLength	12
	Restrictions	Description			
maxLength	12				

[TOP](#)

CHECKERDTSTAMP

Attribute	Description
-----------	-------------

Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

Rates

Attribute	Description	
Name	Rates	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

RATETYPE

Attribute	Description	
Name	RATETYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8

[TOP](#)

MIDRATE

Attribute	Description	
Name	MIDRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYSPREAD

Attribute	Description	
Name	BUYSPREAD	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALESPREAD

Attribute	Description	
Name	SALESPREAD	
Datatype	Number	

Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYRATE

Attribute	Description	
Name	BUYRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALERATE

Attribute	Description	
Name	SALERATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

2.3.2.CO-CCYRatesNew-Req-IO-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

RatesMaster-IO

BRANCHCODE

CCY1

CCY2

MAKERID

MAKERDTSTAMP

CHECKERID

CHECKERDTSTAMP

MODNO

AUTHSTAT

RECSTAT

ONCEAUTH

Rates

RATETYPE

MIDRATE

BUYSPREAD

SALESPREAD

BUYRATE

SALERATE

UDFDETAILS

[FUNCTIONID](#)
[FIELD_NAME](#)
[DATATYPE](#)
[FIELD_VALUE](#)
[VAL_TYPE](#)

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	

Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	

Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	

Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description
------------------	--------------------

Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

RatesMaster-IO

Attribute	Description
Name	RatesMaster-IO
Datatype	
Description	

[TOP](#)

BRANCHCODE

Attribute	Description	
Name	BRANCHCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY1

Attribute	Description	
Name	CCY1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY2

Attribute	Description	
Name	CCY2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

Rates

Attribute	Description
Name	Rates

Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

RATETYPE

Attribute	Description	
Name	RATETYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8

[TOP](#)

MIDRATE

Attribute	Description	
Name	MIDRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYSPREAD

Attribute	Description	
Name	BUYSPREAD	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALESPREAD

Attribute	Description	
Name	SALESPREAD	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYRATE

Attribute	Description
------------------	--------------------

Name	BUYRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALERATE

Attribute	Description	
Name	SALERATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

2.3.3.CO-CCYRatesNew-Res-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

RatesMaster-Full

BRANCHCODE

CCY1

CCY2

MAKERID

MAKERDTSTAMP

CHECKERID

CHECKERDTSTAMP

MODNO

AUTHSTAT

RECSTAT

ONCEAUTH

Rates

RATETYPE

MIDRATE

BUYSPREAD

SALESPREAD

BUYRATE

SALERATE

UDFDETAILS

FUNCTIONID
 FIELD_NAME
 DATATYPE
 FIELD_VALUE
 VAL_TYPE
 FCUBS_ERROR_RESP
 ERROR
 ECODE
 EDESC
 FCUBS_WARNING_RESP
 WARNING
 WCODE
 WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description				
Name	SOURCE				
Datatype	String				
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>pattern</td> <td>[a-zA-Z_0-9]*</td> </tr> </tbody> </table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

UBSCOMP

Attribute	Description				
Name	UBSCOMP				
Datatype	String				
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>enumeration</td> <td>FCUBS,FCIS</td> </tr> </tbody> </table>	Restrictions	Description	enumeration	FCUBS,FCIS
	Restrictions	Description			
enumeration	FCUBS,FCIS				

[TOP](#)

MSGID

Attribute	Description
Name	MSGID

Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

SOURCE_USERID

Attribute		Description
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

DESTINATION

Attribute		Description
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

MULTITRIPID

Attribute		Description
Name	MULTITRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

FUNCTIONID

Attribute		Description
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

RatesMaster-Full

Attribute	Description
Name	RatesMaster-Full
Datatype	
Description	

[TOP](#)

BRANCHCODE

Attribute	Description				
Name	BRANCHCODE				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
Attribute	Description				
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
Restrictions	Description				
maxLength	3				

[TOP](#)

CCY1

Attribute	Description				
Name	CCY1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>1</td></tr></tbody></table>	Attribute	Description	minOccurs	1
Attribute	Description				
minOccurs	1				

Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY2

Attribute	Description	
Name	CCY2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

Rates

Attribute	Description	
Name	Rates	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

RATETYPE

Attribute	Description	
Name	RATETYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8

[TOP](#)

MIDRATE

Attribute	Description	
Name	MIDRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYSPREAD

Attribute	Description	
Name	BUYSPREAD	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALESPREAD

Attribute	Description	
Name	SALESPREAD	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYRATE

Attribute	Description	
Name	BUYRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALERATE

Attribute	Description	
Name	SALERATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)**FCUBS_ERROR_RESP**

Attribute		Description
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)**ERROR**

Attribute		Description
Name	ERROR	
Datatype		
Description	This indicates the type of error encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)**ECODE**

Attribute		Description
Name	ECODE	
Datatype	String	
Description	This indicates the code for the error encountered.	

[TOP](#)**EDESC**

Attribute		Description
Name	EDESC	
Datatype	String	
Description	This indicates the description of the error encountered.	

[TOP](#)**FCUBS_WARNING_RESP**

Attribute		Description
Name	FCUBS_WARNING_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)**WARNING**

Attribute	Description
-----------	-------------

Name	WARNING	
Datatype		
Description	Indicates the warning encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

[TOP](#)

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

[TOP](#)

2.3.4.CO-CCYRatesNew-Res-PK-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

RatesMaster-PK

BRANCHCODE

CCY1

CCY2

FCUBS_ERROR_RESP

ERROR

ECODE

EDESC

FCUBS_WARNING_RESP

WARNING

WCODE

WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

RatesMaster-PK

Attribute	Description
Name	RatesMaster-PK

Datatype	
Description	

[TOP](#)

BRANCHCODE

Attribute	Description	
Name	BRANCHCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY1

Attribute	Description	
Name	CCY1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY2

Attribute	Description	
Name	CCY2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description				
Name	ERROR				
Datatype					
Description	This indicates the type of error encountered.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>maxOccurs</td><td>unbounded</td></tr></tbody></table>	Attribute	Description	maxOccurs	unbounded
	Attribute	Description			
maxOccurs	unbounded				

[TOP](#)

ECODE

Attribute	Description
Name	ECODE
Datatype	String
Description	This indicates the code for the error encountered.

[TOP](#)

EDESC

Attribute	Description
Name	EDESC
Datatype	String
Description	This indicates the description of the error encountered.

[TOP](#)

FCUBS_WARNING_RESP

Attribute	Description						
Name	FCUBS_WARNING_RESP						
Datatype							
Description							
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>maxOccurs</td><td>unbounded</td></tr><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	maxOccurs	unbounded	minOccurs	0
	Attribute	Description					
	maxOccurs	unbounded					
minOccurs	0						

[TOP](#)

WARNING

Attribute	Description				
Name	WARNING				
Datatype					
Description	Indicates the warning encountered.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>maxOccurs</td><td>unbounded</td></tr></tbody></table>	Attribute	Description	maxOccurs	unbounded
	Attribute	Description			
maxOccurs	unbounded				

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

2.4.CCYPairQuery

CCYPairQuery

2.4.1.CO-CCYRatesQuery-Req-IO-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

RatesMaster-IO

BRANCHCODE

CCY1

CCY2

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description
Name	SOURCE
Datatype	String
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".

Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description
Name	OPERATION

Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTIRIPID

Attribute	Description
Name	MULTIRIPID

Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description	
Name	VALUE	
Datatype	String	
Description	The value of the additional parameter comes here.	

[TOP](#)

FCUBS_BODY

Attribute	Description	
Name	FCUBS_BODY	
Datatype		
Description		

[TOP](#)

RatesMaster-IO

Attribute	Description	
Name	RatesMaster-IO	
Datatype		
Description		

[TOP](#)

BRANCHCODE

Attribute	Description				
Name	BRANCHCODE				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

CCY1

Attribute	Description				
Name	CCY1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

CCY2

Attribute	Description				
Name	CCY2				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

2.4.2.CO-CCYRatesQuery-Res-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

RatesMaster-Full

BRANCHCODE

CCY1

CCY2

MAKERID

MAKERDTSTAMP

CHECKERID

CHECKERDTSTAMP

MODNO

AUTHSTAT

RECSTAT

ONCEAUTH

Rates

RATETYPE

MIDRATE

BUYSPREAD

SALESPREAD

BUYRATE

SALERATE

UDFDETAILS

FUNCTIONID
 FIELD_NAME
 DATATYPE
 FIELD_VALUE
 VAL_TYPE
 FCUBS_ERROR_RESP
 ERROR
 ECODE
 EDESC
 FCUBS_WARNING_RESP
 WARNING
 WCODE
 WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description				
Name	SOURCE				
Datatype	String				
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>pattern</td> <td>[a-zA-Z_0-9]*</td> </tr> </tbody> </table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

UBSCOMP

Attribute	Description				
Name	UBSCOMP				
Datatype	String				
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>enumeration</td> <td>FCUBS,FCIS</td> </tr> </tbody> </table>	Restrictions	Description	enumeration	FCUBS,FCIS
	Restrictions	Description			
enumeration	FCUBS,FCIS				

[TOP](#)

MSGID

Attribute	Description
Name	MSGID

Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

SOURCE_USERID

Attribute		Description
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	
	minOccurs	0
	nullable	true

DESTINATION

Attribute		Description
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	
	minOccurs	0
Restrictions	Restrictions	
	pattern	[a-zA-Z_0-9]*

MULTIRIPID

Attribute		Description
Name	MULTIRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTIRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	
	minOccurs	0
Restrictions	Restrictions	
	pattern	[a-zA-Z_0-9]*

FUNCTIONID

Attribute		Description
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

RatesMaster-Full

Attribute	Description
Name	RatesMaster-Full
Datatype	
Description	

[TOP](#)

BRANCHCODE

Attribute	Description				
Name	BRANCHCODE				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
Attribute	Description				
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
Restrictions	Description				
maxLength	3				

[TOP](#)

CCY1

Attribute	Description				
Name	CCY1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>1</td></tr></tbody></table>	Attribute	Description	minOccurs	1
Attribute	Description				
minOccurs	1				

Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY2

Attribute	Description	
Name	CCY2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

Rates

Attribute	Description	
Name	Rates	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

RATETYPE

Attribute	Description	
Name	RATETYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8

[TOP](#)

MIDRATE

Attribute	Description	
Name	MIDRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYSPREAD

Attribute	Description	
Name	BUYSPREAD	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALESPREAD

Attribute	Description	
Name	SALESPREAD	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYRATE

Attribute	Description	
Name	BUYRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALERATE

Attribute	Description	
Name	SALERATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)**FCUBS_ERROR_RESP**

Attribute		Description
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)**ERROR**

Attribute		Description
Name	ERROR	
Datatype		
Description	This indicates the type of error encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)**ECODE**

Attribute		Description
Name	ECODE	
Datatype	String	
Description	This indicates the code for the error encountered.	

[TOP](#)**EDESC**

Attribute		Description
Name	EDESC	
Datatype	String	
Description	This indicates the description of the error encountered.	

[TOP](#)**FCUBS_WARNING_RESP**

Attribute		Description
Name	FCUBS_WARNING_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)**WARNING**

Attribute	Description
-----------	-------------

Name	WARNING	
Datatype		
Description	Indicates the warning encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

[TOP](#)

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

[TOP](#)

2.5.CCYPairReopen

CCYPairReopen

2.5.1.CO-CCYRatesReopen-Req-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

RatesMaster-Full

BRANCHCODE

CCY1

CCY2

MAKERID

MAKERDTSTAMP

CHECKERID

CHECKERDTSTAMP

MODNO

AUTHSTAT

RECSTAT

ONCEAUTH

Rates

RATETYPE

MIDRATE

BUYSPREAD

SALESPREAD

[BUYRATE](#)
[SALERATE](#)
[UDFDETAILS](#)
[FUNCTIONID](#)
[FIELD_NAME](#)
[DATATYPE](#)
[FIELD_VALUE](#)
[VAL_TYPE](#)

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description
Name	MSGID
Datatype	String
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.

Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description
------------------	--------------------

Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTIRIPID

Attribute	Description	
Name	MULTIRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTIRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

NAME

Attribute	Description
Name	NAME

Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

RatesMaster-Full

Attribute	Description
Name	RatesMaster-Full
Datatype	
Description	

[TOP](#)

BRANCHCODE

Attribute	Description				
Name	BRANCHCODE				
Datatype	String				
Description					
Attributes	<table border="1"> <thead> <tr> <th>Attribute</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>minOccurs</td> <td>0</td> </tr> </tbody> </table>	Attribute	Description	minOccurs	0
Attribute	Description				
minOccurs	0				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>maxLength</td> <td>3</td> </tr> </tbody> </table>	Restrictions	Description	maxLength	3
Restrictions	Description				
maxLength	3				

[TOP](#)

CCY1

Attribute	Description				
Name	CCY1				
Datatype	String				
Description					
Attributes	<table border="1"> <thead> <tr> <th>Attribute</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>minOccurs</td> <td>1</td> </tr> </tbody> </table>	Attribute	Description	minOccurs	1
Attribute	Description				
minOccurs	1				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>maxLength</td> <td>3</td> </tr> </tbody> </table>	Restrictions	Description	maxLength	3
Restrictions	Description				
maxLength	3				

[TOP](#)

CCY2

Attribute	Description				
Name	CCY2				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

MAKERID

Attribute	Description				
Name	MAKERID				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>12</td></tr></tbody></table>	Restrictions	Description	maxLength	12
	Restrictions	Description			
maxLength	12				

[TOP](#)

MAKERDTSTAMP

Attribute	Description				
Name	MAKERDTSTAMP				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>25</td></tr></tbody></table>	Restrictions	Description	maxLength	25
	Restrictions	Description			
maxLength	25				

[TOP](#)

CHECKERID

Attribute	Description				
Name	CHECKERID				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>12</td></tr></tbody></table>	Restrictions	Description	maxLength	12
	Restrictions	Description			
maxLength	12				

[TOP](#)

CHECKERDTSTAMP

Attribute	Description
-----------	-------------

Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

Rates

Attribute	Description	
Name	Rates	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

RATETYPE

Attribute	Description	
Name	RATETYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8

[TOP](#)

MIDRATE

Attribute	Description	
Name	MIDRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYSPREAD

Attribute	Description	
Name	BUYSPREAD	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALESPREAD

Attribute	Description	
Name	SALESPREAD	
Datatype	Number	

Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYRATE

Attribute	Description	
Name	BUYRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALERATE

Attribute	Description	
Name	SALERATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

2.5.2.CO-CCYRatesReopen-Req-IO-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

RatesMaster-IO

BRANCHCODE

CCY1

CCY2

MODNO

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

USERID

Attribute	Description
Name	USERID
Datatype	String

Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	

Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	

Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

RatesMaster-IO

Attribute	Description
Name	RatesMaster-IO
Datatype	
Description	

[TOP](#)

BRANCHCODE

Attribute	Description				
Name	BRANCHCODE				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

CCY1

Attribute	Description				
Name	CCY1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

CCY2

Attribute	Description				
Name	CCY2				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

MODNO

Attribute	Description				
Name	MODNO				
Datatype	Number				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>totalDigits</td><td>22</td></tr></tbody></table>	Restrictions	Description	totalDigits	22
	Restrictions	Description			
totalDigits	22				

[TOP](#)

2.5.3.CO-CCYRatesReopen-Res-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

RatesMaster-Full

BRANCHCODE

CCY1

CCY2

MAKERID

MAKERDTSTAMP

CHECKERID

CHECKERDTSTAMP

MODNO

AUTHSTAT

RECSTAT

ONCEAUTH

Rates

RATETYPE

MIDRATE

BUYSPREAD

SALESPREAD

BUYRATE

SALERATE

UDFDETAILS

FUNCTIONID
 FIELD_NAME
 DATATYPE
 FIELD_VALUE
 VAL_TYPE
 FCUBS_ERROR_RESP
 ERROR
 ECODE
 EDESC
 FCUBS_WARNING_RESP
 WARNING
 WCODE
 WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description				
Name	SOURCE				
Datatype	String				
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>pattern</td> <td>[a-zA-Z_0-9]*</td> </tr> </tbody> </table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

UBSCOMP

Attribute	Description				
Name	UBSCOMP				
Datatype	String				
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>enumeration</td> <td>FCUBS,FCIS</td> </tr> </tbody> </table>	Restrictions	Description	enumeration	FCUBS,FCIS
	Restrictions	Description			
enumeration	FCUBS,FCIS				

[TOP](#)

MSGID

Attribute	Description
Name	MSGID

Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

MULTIRIPID

Attribute	Description	
Name	MULTIRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTIRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

RatesMaster-Full

Attribute	Description
Name	RatesMaster-Full
Datatype	
Description	

[TOP](#)

BRANCHCODE

Attribute	Description				
Name	BRANCHCODE				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
Attribute	Description				
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
Restrictions	Description				
maxLength	3				

[TOP](#)

CCY1

Attribute	Description				
Name	CCY1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>1</td></tr></tbody></table>	Attribute	Description	minOccurs	1
Attribute	Description				
minOccurs	1				

Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY2

Attribute	Description	
Name	CCY2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

ONCEAUTH

Attribute	Description
Name	ONCEAUTH

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

Rates

Attribute	Description	
Name	Rates	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

RATETYPE

Attribute	Description	
Name	RATETYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8

[TOP](#)

MIDRATE

Attribute	Description	
Name	MIDRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYSPREAD

Attribute	Description	
Name	BUYSPREAD	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALESPREAD

Attribute	Description	
Name	SALESPREAD	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYRATE

Attribute	Description	
Name	BUYRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALERATE

Attribute	Description	
Name	SALERATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)**FCUBS_ERROR_RESP**

Attribute		Description
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)**ERROR**

Attribute		Description
Name	ERROR	
Datatype		
Description	This indicates the type of error encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)**ECODE**

Attribute		Description
Name	ECODE	
Datatype	String	
Description	This indicates the code for the error encountered.	

[TOP](#)**EDESC**

Attribute		Description
Name	EDESC	
Datatype	String	
Description	This indicates the description of the error encountered.	

[TOP](#)**FCUBS_WARNING_RESP**

Attribute		Description
Name	FCUBS_WARNING_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)**WARNING**

Attribute	Description
-----------	-------------

Name	WARNING	
Datatype		
Description	Indicates the warning encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

[TOP](#)

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

[TOP](#)

2.5.4.CO-CCYRatesReopen-Res-PK-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

RatesMaster-PK

BRANCHCODE

CCY1

CCY2

FCUBS_ERROR_RESP

ERROR

ECODE

EDESC

FCUBS_WARNING_RESP

WARNING

WCODE

WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

RatesMaster-PK

Attribute	Description
Name	RatesMaster-PK

Datatype	
Description	

[TOP](#)

BRANCHCODE

Attribute	Description	
Name	BRANCHCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY1

Attribute	Description	
Name	CCY1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY2

Attribute	Description	
Name	CCY2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description				
Name	ERROR				
Datatype					
Description	This indicates the type of error encountered.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>maxOccurs</td><td>unbounded</td></tr></tbody></table>	Attribute	Description	maxOccurs	unbounded
	Attribute	Description			
maxOccurs	unbounded				

[TOP](#)

ECODE

Attribute	Description
Name	ECODE
Datatype	String
Description	This indicates the code for the error encountered.

[TOP](#)

EDESC

Attribute	Description
Name	EDESC
Datatype	String
Description	This indicates the description of the error encountered.

[TOP](#)

FCUBS_WARNING_RESP

Attribute	Description						
Name	FCUBS_WARNING_RESP						
Datatype							
Description							
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>maxOccurs</td><td>unbounded</td></tr><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	maxOccurs	unbounded	minOccurs	0
	Attribute	Description					
	maxOccurs	unbounded					
minOccurs	0						

[TOP](#)

WARNING

Attribute	Description				
Name	WARNING				
Datatype					
Description	Indicates the warning encountered.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>maxOccurs</td><td>unbounded</td></tr></tbody></table>	Attribute	Description	maxOccurs	unbounded
	Attribute	Description			
maxOccurs	unbounded				

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

2.6.CCYRatesAuth

Authorisation Of Currency Rates

2.6.1.CO-CurrencyPairAuth-Req-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

CcyPairDefn-Full

CCY1

CCY2

THROUGHCCY

QUOTATION

NOOFUNITS

SPREADDEFN

POINTSMULTIPLIER

MAKERID

MAKERDTSTAMP

CHECKERID

CHECKERDTSTAMP

MODNO

AUTHSTAT

RECSTAT

ONCEAUTH

CpairChkThruCcy

[CHKTHRUCCY](#)
[UDFDETAILS](#)
[FUNCTIONID](#)
[FIELD_NAME](#)
[DATATYPE](#)
[FIELD_VALUE](#)
[VAL_TYPE](#)

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description				
Name	SOURCE				
Datatype	String				
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>pattern</td> <td>[a-zA-Z_0-9]*</td> </tr> </tbody> </table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

UBSCOMP

Attribute	Description				
Name	UBSCOMP				
Datatype	String				
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>enumeration</td> <td>FCUBS,FCIS</td> </tr> </tbody> </table>	Restrictions	Description	enumeration	FCUBS,FCIS
	Restrictions	Description			
enumeration	FCUBS,FCIS				

[TOP](#)

MSGID

Attribute	Description						
Name	MSGID						
Datatype	String						
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.						
Attributes	<table border="1"> <thead> <tr> <th>Attribute</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>minOccurs</td> <td>0</td> </tr> <tr> <td>nillable</td> <td>true</td> </tr> </tbody> </table>	Attribute	Description	minOccurs	0	nillable	true
	Attribute	Description					
	minOccurs	0					
nillable	true						

Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	

Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description
Name	SOURCE_USERID
Datatype	String

Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description
Name	ACTION

Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

CcyPairDefn-Full

Attribute	Description
Name	CcyPairDefn-Full
Datatype	
Description	

[TOP](#)

CCY1

Attribute	Description	
Name	CCY1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY2

Attribute	Description	
Name	CCY2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

THROUGHCCY

Attribute	Description
Name	THROUGHCCY
Datatype	String
Description	

Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

QUOTATION

Attribute	Description	
Name	QUOTATION	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	D,I

[TOP](#)

NOOFUNITS

Attribute	Description	
Name	NOOFUNITS	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SPREADDEFN

Attribute	Description	
Name	SPREADDEFN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	%,.

[TOP](#)

POINTSMULTIPLIER

Attribute	Description	
Name	POINTSMULTIPLIER	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

MODNO

Attribute	Description
Name	MODNO

Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CpairChkThruCcy

Attribute	Description	
Name	CpairChkThruCcy	
Datatype		
Description		
Attributes	Attribute	Description
	minOccurs	0

CHKTHRUCCY

Attribute	Description	
Name	CHKTHRUCCY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

2.6.2.CO-CurrencyPairAuth-Req-IO-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

CcyPairDefn-IO

CCY1

CCY2

MODNO

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

USERID

Attribute	Description	
Name	USERID	
Datatype	String	

Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	

Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	

Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description	
Name	VALUE	
Datatype	String	
Description	The value of the additional parameter comes here.	

[TOP](#)

FCUBS_BODY

Attribute	Description	
Name	FCUBS_BODY	
Datatype		
Description		

[TOP](#)

CcyPairDefn-IO

Attribute	Description	
Name	CcyPairDefn-IO	
Datatype		
Description		

[TOP](#)

CCY1

Attribute	Description				
Name	CCY1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

CCY2

Attribute	Description				
Name	CCY2				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

MODNO

Attribute	Description				
Name	MODNO				
Datatype	Number				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>totalDigits</td><td>22</td></tr></tbody></table>	Restrictions	Description	totalDigits	22
	Restrictions	Description			
totalDigits	22				

[TOP](#)

2.6.3.CO-CurrencyPairAuth-Res-Full-MSG.xsd

FCUBS_HEADER
SOURCE
UBSCOMP
MSGID
CORRELID
USERID
BRANCH
MODULEID
SERVICE
OPERATION
SOURCE_OPERATION
SOURCE_USERID
DESTINATION
MULTITRIPID
FUNCTIONID
ACTION
MSGSTAT
ADDL
PARAM
NAME
VALUE
FCUBS_BODY
CcyPairDefn-Full
CCY1
CCY2
THROUGHCCY
QUOTATION
NOOFUNITS
SPREADDEFN
POINTSMULTIPLIER
MAKERID
MAKERDTSTAMP
CHECKERID
CHECKERDTSTAMP
MODNO
AUTHSTAT
RECSTAT
ONCEAUTH
CpairChkThruCcy
CHKTHRUCCY
UDFDETAILS
FUNCTIONID

FIELD_NAME
 DATATYPE
 FIELD_VALUE
 VAL_TYPE
 FCUBS_ERROR_RESP
 ERROR
 ECODE
 EDESC
 FCUBS_WARNING_RESP
 WARNING
 WCODE
 WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description
Name	MSGID
Datatype	String

Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description						
Name	MODULEID						
Datatype	String						
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.						
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr><tr><td>nullable</td><td>true</td></tr></tbody></table>	Attribute	Description	minOccurs	0	nullable	true
	Attribute	Description					
	minOccurs	0					
nullable	true						

[TOP](#)

SERVICE

Attribute	Description				
Name	SERVICE				
Datatype	String				
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>nullable</td><td>true</td></tr></tbody></table>	Attribute	Description	nullable	true
	Attribute	Description			
nullable	true				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

OPERATION

Attribute	Description				
Name	OPERATION				
Datatype	String				
Description	This is the operation of the service which is being invoked. This field is case-sensitive.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>nullable</td><td>true</td></tr></tbody></table>	Attribute	Description	nullable	true
	Attribute	Description			
nullable	true				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

SOURCE_OPERATION

Attribute	Description						
Name	SOURCE_OPERATION						
Datatype	String						
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.						
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr><tr><td>nullable</td><td>true</td></tr></tbody></table>	Attribute	Description	minOccurs	0	nullable	true
	Attribute	Description					
	minOccurs	0					
nullable	true						
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*		
	Restrictions	Description					
pattern	[a-zA-Z_0-9]*						

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

CcyPairDefn-Full

Attribute	Description
Name	CcyPairDefn-Full
Datatype	
Description	

[TOP](#)

CCY1

Attribute	Description				
Name	CCY1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>1</td></tr></tbody></table>	Attribute	Description	minOccurs	1
	Attribute	Description			
minOccurs	1				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

CCY2

Attribute	Description				
Name	CCY2				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				

Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

THROUGHCCY

Attribute	Description	
Name	THROUGHCCY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

QUOTATION

Attribute	Description	
Name	QUOTATION	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	D,I

[TOP](#)

NOOFUNITS

Attribute	Description	
Name	NOOFUNITS	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SPREADDEFN

Attribute	Description	
Name	SPREADDEFN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	%,.

[TOP](#)

POINTSMULTIPLIER

Attribute	Description	
Name	POINTSMULTIPLIER	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CpairChkThruCcy

Attribute	Description	
Name	CpairChkThruCcy	
Datatype		
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

CHKTHRUCCY

Attribute	Description	
Name	CHKTHRUCCY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description
-----------	-------------

Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		

Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description	
Name	ERROR	
Datatype		
Description	This indicates the type of error encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ECODE

Attribute	Description
Name	ECODE
Datatype	String
Description	This indicates the code for the error encountered.

[TOP](#)

EDESC

Attribute	Description
Name	EDESC
Datatype	String
Description	This indicates the description of the error encountered.

[TOP](#)

FCUBS_WARNING_RESP

Attribute	Description	
Name	FCUBS_WARNING_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

WARNING

Attribute	Description	
Name	WARNING	
Datatype		
Description	Indicates the warning encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

[TOP](#)

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

[TOP](#)

2.6.4.CO-CurrencyPairAuth-Res-PK-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

CcyPairDefn-PK

CCY1

CCY2

FCUBS_ERROR_RESP

ERROR

ECODE

EDESC

FCUBS_WARNING_RESP

WARNING

WCODE

WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description
-----------	-------------

Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description				
Name	MULTITRIPID				
Datatype	String				
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

FUNCTIONID

Attribute	Description						
Name	FUNCTIONID						
Datatype	String						
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.						
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0		
	Attribute	Description					
minOccurs	0						
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>8</td></tr><tr><td>pattern</td><td>[A-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	maxLength	8	pattern	[A-Z_0-9]*
	Restrictions	Description					
	maxLength	8					
pattern	[A-Z_0-9]*						

[TOP](#)

ACTION

Attribute	Description				
Name	ACTION				
Datatype	String				
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

MSGSTAT

Attribute	Description				
Name	MSGSTAT				
Datatype	String				
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				

Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

CcyPairDefn-PK

Attribute	Description
Name	CcyPairDefn-PK

Datatype	
Description	

[TOP](#)

CCY1

Attribute	Description	
Name	CCY1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY2

Attribute	Description	
Name	CCY2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description	
Name	ERROR	
Datatype		
Description	This indicates the type of error encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

ECODE

Attribute	Description
-----------	-------------

Name	ECODE
Datatype	String
Description	This indicates the code for the error encountered.

[TOP](#)

EDESC

Attribute	Description
Name	EDESC
Datatype	String
Description	This indicates the description of the error encountered.

[TOP](#)

FCUBS_WARNING_RESP

Attribute	Description	
Name	FCUBS_WARNING_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

WARNING

Attribute	Description	
Name	WARNING	
Datatype		
Description	Indicates the warning encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

[TOP](#)

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

[TOP](#)

2.7.CCYRatesClose

Closure Of Currency Rates

2.7.1.CO-CurrencyPairClose-Req-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

CcyPairDefn-Full

CCY1

CCY2

THROUGHCCY

QUOTATION

NOOFUNITS

SPREADDEFN

POINTSMULTIPLIER

MAKERID

MAKERDTSTAMP

CHECKERID

CHECKERDTSTAMP

MODNO

AUTHSTAT

RECSTAT

ONCEAUTH

CpairChkThruCcy

[CHKTHRUCCY](#)
[UDFDETAILS](#)
[FUNCTIONID](#)
[FIELD_NAME](#)
[DATATYPE](#)
[FIELD_VALUE](#)
[VAL_TYPE](#)

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description				
Name	SOURCE				
Datatype	String				
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>pattern</td> <td>[a-zA-Z_0-9]*</td> </tr> </tbody> </table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

UBSCOMP

Attribute	Description				
Name	UBSCOMP				
Datatype	String				
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>enumeration</td> <td>FCUBS,FCIS</td> </tr> </tbody> </table>	Restrictions	Description	enumeration	FCUBS,FCIS
	Restrictions	Description			
enumeration	FCUBS,FCIS				

[TOP](#)

MSGID

Attribute	Description						
Name	MSGID						
Datatype	String						
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.						
Attributes	<table border="1"> <thead> <tr> <th>Attribute</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>minOccurs</td> <td>0</td> </tr> <tr> <td>nillable</td> <td>true</td> </tr> </tbody> </table>	Attribute	Description	minOccurs	0	nillable	true
	Attribute	Description					
	minOccurs	0					
nillable	true						

Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	

Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description
Name	SOURCE_USERID
Datatype	String

Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description
Name	ACTION

Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

CcyPairDefn-Full

Attribute	Description
Name	CcyPairDefn-Full
Datatype	
Description	

[TOP](#)

CCY1

Attribute	Description	
Name	CCY1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY2

Attribute	Description	
Name	CCY2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

THROUGHCCY

Attribute	Description
Name	THROUGHCCY
Datatype	String
Description	

Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

QUOTATION

Attribute	Description	
Name	QUOTATION	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	D,I

[TOP](#)

NOOFUNITS

Attribute	Description	
Name	NOOFUNITS	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SPREADDEFN

Attribute	Description	
Name	SPREADDEFN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	%,.

[TOP](#)

POINTSMULTIPLIER

Attribute	Description	
Name	POINTSMULTIPLIER	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

MODNO

Attribute	Description
Name	MODNO

Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CpairChkThruCcy

Attribute	Description	
Name	CpairChkThruCcy	
Datatype		
Description		
Attributes	Attribute	Description
	minOccurs	0

CHKTHRUCCY

Attribute	Description	
Name	CHKTHRUCCY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

2.7.2.CO-CurrencyPairClose-Req-IO-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

CcyPairDefn-IO

CCY1

CCY2

MODNO

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

USERID

Attribute	Description	
Name	USERID	
Datatype	String	

Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	

Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	

Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description	
Name	VALUE	
Datatype	String	
Description	The value of the additional parameter comes here.	

[TOP](#)

FCUBS_BODY

Attribute	Description	
Name	FCUBS_BODY	
Datatype		
Description		

[TOP](#)

CcyPairDefn-IO

Attribute	Description	
Name	CcyPairDefn-IO	
Datatype		
Description		

[TOP](#)

CCY1

Attribute	Description				
Name	CCY1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

CCY2

Attribute	Description				
Name	CCY2				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

MODNO

Attribute	Description				
Name	MODNO				
Datatype	Number				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>totalDigits</td><td>22</td></tr></tbody></table>	Restrictions	Description	totalDigits	22
	Restrictions	Description			
totalDigits	22				

[TOP](#)

2.7.3.CO-CurrencyPairClose-Res-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

CcyPairDefn-Full

CCY1

CCY2

THROUGHCCY

QUOTATION

NOOFUNITS

SPREADDEFN

POINTSMULTIPLIER

MAKERID

MAKERDTSTAMP

CHECKERID

CHECKERDTSTAMP

MODNO

AUTHSTAT

RECSTAT

ONCEAUTH

CpairChkThruCcy

CHKTHRUCCY

UDFDETAILS

FUNCTIONID

FIELD_NAME
 DATATYPE
 FIELD_VALUE
 VAL_TYPE
 FCUBS_ERROR_RESP
 ERROR
 ECODE
 EDESC
 FCUBS_WARNING_RESP
 WARNING
 WCODE
 WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description
Name	MSGID
Datatype	String

Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description						
Name	MODULEID						
Datatype	String						
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.						
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr><tr><td>nullable</td><td>true</td></tr></tbody></table>	Attribute	Description	minOccurs	0	nullable	true
	Attribute	Description					
	minOccurs	0					
nullable	true						

[TOP](#)

SERVICE

Attribute	Description				
Name	SERVICE				
Datatype	String				
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>nullable</td><td>true</td></tr></tbody></table>	Attribute	Description	nullable	true
	Attribute	Description			
nullable	true				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

OPERATION

Attribute	Description				
Name	OPERATION				
Datatype	String				
Description	This is the operation of the service which is being invoked. This field is case-sensitive.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>nullable</td><td>true</td></tr></tbody></table>	Attribute	Description	nullable	true
	Attribute	Description			
nullable	true				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

SOURCE_OPERATION

Attribute	Description						
Name	SOURCE_OPERATION						
Datatype	String						
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.						
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr><tr><td>nullable</td><td>true</td></tr></tbody></table>	Attribute	Description	minOccurs	0	nullable	true
	Attribute	Description					
	minOccurs	0					
nullable	true						
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*		
	Restrictions	Description					
pattern	[a-zA-Z_0-9]*						

SOURCE_USERID

Attribute		Description
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	
	minOccurs	0
	nullable	true

DESTINATION

Attribute		Description
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	
	minOccurs	0
Restrictions	Restrictions	
	pattern	[a-zA-Z_0-9]*

MULTIRIPID

Attribute		Description
Name	MULTIRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTIRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	
	minOccurs	0
Restrictions	Restrictions	
	pattern	[a-zA-Z_0-9]*

FUNCTIONID

Attribute		Description
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

CcyPairDefn-Full

Attribute	Description
Name	CcyPairDefn-Full
Datatype	
Description	

[TOP](#)

CCY1

Attribute	Description				
Name	CCY1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>1</td></tr></tbody></table>	Attribute	Description	minOccurs	1
	Attribute	Description			
minOccurs	1				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

CCY2

Attribute	Description				
Name	CCY2				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				

Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

THROUGHCCY

Attribute	Description	
Name	THROUGHCCY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

QUOTATION

Attribute	Description	
Name	QUOTATION	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	D,I

[TOP](#)

NOOFUNITS

Attribute	Description	
Name	NOOFUNITS	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SPREADDEFN

Attribute	Description	
Name	SPREADDEFN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	%,.

[TOP](#)

POINTSMULTIPLIER

Attribute	Description	
Name	POINTSMULTIPLIER	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CpairChkThruCcy

Attribute	Description	
Name	CpairChkThruCcy	
Datatype		
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

CHKTHRUCCY

Attribute	Description	
Name	CHKTHRUCCY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description
-----------	-------------

Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		

Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description	
Name	ERROR	
Datatype		
Description	This indicates the type of error encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ECODE

Attribute	Description
Name	ECODE
Datatype	String
Description	This indicates the code for the error encountered.

[TOP](#)

EDESC

Attribute	Description
Name	EDESC
Datatype	String
Description	This indicates the description of the error encountered.

[TOP](#)

FCUBS_WARNING_RESP

Attribute	Description	
Name	FCUBS_WARNING_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

WARNING

Attribute	Description	
Name	WARNING	
Datatype		
Description	Indicates the warning encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

[TOP](#)

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

[TOP](#)

2.7.4.CO-CurrencyPairClose-Res-PK-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

CcyPairDefn-PK

CCY1

CCY2

FCUBS_ERROR_RESP

ERROR

ECODE

EDESC

FCUBS_WARNING_RESP

WARNING

WCODE

WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description
-----------	-------------

Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description				
Name	MULTITRIPID				
Datatype	String				
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

FUNCTIONID

Attribute	Description						
Name	FUNCTIONID						
Datatype	String						
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.						
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0		
	Attribute	Description					
minOccurs	0						
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>8</td></tr><tr><td>pattern</td><td>[A-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	maxLength	8	pattern	[A-Z_0-9]*
	Restrictions	Description					
	maxLength	8					
pattern	[A-Z_0-9]*						

[TOP](#)

ACTION

Attribute	Description				
Name	ACTION				
Datatype	String				
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

MSGSTAT

Attribute	Description				
Name	MSGSTAT				
Datatype	String				
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				

Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description	
Name	VALUE	
Datatype	String	
Description	The value of the additional parameter comes here.	

[TOP](#)

FCUBS_BODY

Attribute	Description	
Name	FCUBS_BODY	
Datatype		
Description		

[TOP](#)

CcyPairDefn-PK

Attribute	Description	
Name	CcyPairDefn-PK	

Datatype	
Description	

[TOP](#)

CCY1

Attribute	Description	
Name	CCY1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY2

Attribute	Description	
Name	CCY2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description	
Name	ERROR	
Datatype		
Description	This indicates the type of error encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

ECODE

Attribute	Description
-----------	-------------

Name	ECODE
Datatype	String
Description	This indicates the code for the error encountered.

[TOP](#)

EDESC

Attribute	Description
Name	EDESC
Datatype	String
Description	This indicates the description of the error encountered.

[TOP](#)

FCUBS_WARNING_RESP

Attribute	Description	
Name	FCUBS_WARNING_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

WARNING

Attribute	Description	
Name	WARNING	
Datatype		
Description	Indicates the warning encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

[TOP](#)

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

[TOP](#)

2.8.CCYRatesDelete

Deletion Of Currency Rates

2.8.1.CO-CurrencyPairDelete-Req-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

CcyPairDefn-Full

CCY1

CCY2

THROUGHCCY

QUOTATION

NOOFUNITS

SPREADDEFN

POINTSMULTIPLIER

MAKERID

MAKERDTSTAMP

CHECKERID

CHECKERDTSTAMP

MODNO

AUTHSTAT

RECSTAT

ONCEAUTH

CpairChkThruCcy

[CHKTHRUCCY](#)
[UDFDETAILS](#)
[FUNCTIONID](#)
[FIELD_NAME](#)
[DATATYPE](#)
[FIELD_VALUE](#)
[VAL_TYPE](#)

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description				
Name	SOURCE				
Datatype	String				
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>pattern</td> <td>[a-zA-Z_0-9]*</td> </tr> </tbody> </table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

UBSCOMP

Attribute	Description				
Name	UBSCOMP				
Datatype	String				
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>enumeration</td> <td>FCUBS,FCIS</td> </tr> </tbody> </table>	Restrictions	Description	enumeration	FCUBS,FCIS
	Restrictions	Description			
enumeration	FCUBS,FCIS				

[TOP](#)

MSGID

Attribute	Description						
Name	MSGID						
Datatype	String						
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.						
Attributes	<table border="1"> <thead> <tr> <th>Attribute</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>minOccurs</td> <td>0</td> </tr> <tr> <td>nillable</td> <td>true</td> </tr> </tbody> </table>	Attribute	Description	minOccurs	0	nillable	true
	Attribute	Description					
	minOccurs	0					
nillable	true						

Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	

Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description
Name	SOURCE_USERID
Datatype	String

Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description
Name	ACTION

Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

CcyPairDefn-Full

Attribute	Description
Name	CcyPairDefn-Full
Datatype	
Description	

[TOP](#)

CCY1

Attribute	Description	
Name	CCY1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY2

Attribute	Description	
Name	CCY2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

THROUGHCCY

Attribute	Description
Name	THROUGHCCY
Datatype	String
Description	

Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

QUOTATION

Attribute	Description	
Name	QUOTATION	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	D,I

[TOP](#)

NOOFUNITS

Attribute	Description	
Name	NOOFUNITS	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SPREADDEFN

Attribute	Description	
Name	SPREADDEFN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	%,.

[TOP](#)

POINTSMULTIPLIER

Attribute	Description	
Name	POINTSMULTIPLIER	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

MODNO

Attribute	Description
Name	MODNO

Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CpairChkThruCcy

Attribute	Description	
Name	CpairChkThruCcy	
Datatype		
Description		
Attributes	Attribute	Description
	minOccurs	0

CHKTHRUCCY

Attribute	Description	
Name	CHKTHRUCCY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

2.8.2.CO-CurrencyPairDelete-Req-IO-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

CcyPairDefn-IO

CCY1

CCY2

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description
Name	USERID
Datatype	String

Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	

Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	

Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

CcyPairDefn-IO

Attribute	Description
Name	CcyPairDefn-IO
Datatype	
Description	

[TOP](#)

CCY1

Attribute	Description				
Name	CCY1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

CCY2

Attribute	Description				
Name	CCY2				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

2.8.3.CO-CurrencyPairDelete-Res-Full-MSG.xsd

FCUBS_HEADER
SOURCE
UBSCOMP
MSGID
CORRELID
USERID
BRANCH
MODULEID
SERVICE
OPERATION
SOURCE_OPERATION
SOURCE_USERID
DESTINATION
MULTITRIPID
FUNCTIONID
ACTION
MSGSTAT
ADDL
PARAM
NAME
VALUE
FCUBS_BODY
CcyPairDefn-Full
CCY1
CCY2
THROUGHCCY
QUOTATION
NOOFUNITS
SPREADDEFN
POINTSMULTIPLIER
MAKERID
MAKERDTSTAMP
CHECKERID
CHECKERDTSTAMP
MODNO
AUTHSTAT
RECSTAT
ONCEAUTH
CpairChkThruCcy
CHKTHRUCCY
UDFDETAILS
FUNCTIONID

FIELD_NAME
 DATATYPE
 FIELD_VALUE
 VAL_TYPE
 FCUBS_ERROR_RESP
 ERROR
 ECODE
 EDESC
 FCUBS_WARNING_RESP
 WARNING
 WCODE
 WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description
Name	MSGID
Datatype	String

Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description						
Name	MODULEID						
Datatype	String						
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.						
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr><tr><td>nullable</td><td>true</td></tr></tbody></table>	Attribute	Description	minOccurs	0	nullable	true
	Attribute	Description					
	minOccurs	0					
nullable	true						

[TOP](#)

SERVICE

Attribute	Description				
Name	SERVICE				
Datatype	String				
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>nullable</td><td>true</td></tr></tbody></table>	Attribute	Description	nullable	true
	Attribute	Description			
nullable	true				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

OPERATION

Attribute	Description				
Name	OPERATION				
Datatype	String				
Description	This is the operation of the service which is being invoked. This field is case-sensitive.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>nullable</td><td>true</td></tr></tbody></table>	Attribute	Description	nullable	true
	Attribute	Description			
nullable	true				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

SOURCE_OPERATION

Attribute	Description						
Name	SOURCE_OPERATION						
Datatype	String						
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.						
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr><tr><td>nullable</td><td>true</td></tr></tbody></table>	Attribute	Description	minOccurs	0	nullable	true
	Attribute	Description					
	minOccurs	0					
nullable	true						
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*		
	Restrictions	Description					
pattern	[a-zA-Z_0-9]*						

SOURCE_USERID

Attribute		Description
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

DESTINATION

Attribute		Description
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
	Restrictions	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

MULTIRIPID

Attribute		Description
Name	MULTIRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTIRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
	Restrictions	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

FUNCTIONID

Attribute		Description
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

CcyPairDefn-Full

Attribute	Description
Name	CcyPairDefn-Full
Datatype	
Description	

[TOP](#)

CCY1

Attribute	Description				
Name	CCY1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>1</td></tr></tbody></table>	Attribute	Description	minOccurs	1
	Attribute	Description			
minOccurs	1				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

CCY2

Attribute	Description				
Name	CCY2				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				

Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

THROUGHCCY

Attribute	Description	
Name	THROUGHCCY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

QUOTATION

Attribute	Description	
Name	QUOTATION	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	D,I

[TOP](#)

NOOFUNITS

Attribute	Description	
Name	NOOFUNITS	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SPREADDEFN

Attribute	Description	
Name	SPREADDEFN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	%,.

[TOP](#)

POINTSMULTIPLIER

Attribute	Description	
Name	POINTSMULTIPLIER	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CpairChkThruCcy

Attribute	Description	
Name	CpairChkThruCcy	
Datatype		
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

CHKTHRUCCY

Attribute	Description	
Name	CHKTHRUCCY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description
-----------	-------------

Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		

Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description	
Name	ERROR	
Datatype		
Description	This indicates the type of error encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ECODE

Attribute	Description
Name	ECODE
Datatype	String
Description	This indicates the code for the error encountered.

[TOP](#)

EDESC

Attribute	Description
Name	EDESC
Datatype	String
Description	This indicates the description of the error encountered.

[TOP](#)

FCUBS_WARNING_RESP

Attribute	Description	
Name	FCUBS_WARNING_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

WARNING

Attribute	Description	
Name	WARNING	
Datatype		
Description	Indicates the warning encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

[TOP](#)

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

[TOP](#)

2.8.4.CO-CurrencyPairDelete-Res-PK-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

CcyPairDefn-PK

CCY1

CCY2

FCUBS_ERROR_RESP

ERROR

ECODE

EDESC

FCUBS_WARNING_RESP

WARNING

WCODE

WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description
------------------	--------------------

Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description				
Name	MULTITRIPID				
Datatype	String				
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

FUNCTIONID

Attribute	Description						
Name	FUNCTIONID						
Datatype	String						
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.						
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0		
	Attribute	Description					
minOccurs	0						
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>8</td></tr><tr><td>pattern</td><td>[A-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	maxLength	8	pattern	[A-Z_0-9]*
	Restrictions	Description					
	maxLength	8					
pattern	[A-Z_0-9]*						

[TOP](#)

ACTION

Attribute	Description				
Name	ACTION				
Datatype	String				
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

MSGSTAT

Attribute	Description				
Name	MSGSTAT				
Datatype	String				
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				

Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

CcyPairDefn-PK

Attribute	Description
Name	CcyPairDefn-PK

Datatype	
Description	

[TOP](#)

CCY1

Attribute	Description	
Name	CCY1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY2

Attribute	Description	
Name	CCY2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description	
Name	ERROR	
Datatype		
Description	This indicates the type of error encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

ECODE

Attribute	Description
-----------	-------------

Name	ECODE
Datatype	String
Description	This indicates the code for the error encountered.

[TOP](#)

EDESC

Attribute	Description
Name	EDESC
Datatype	String
Description	This indicates the description of the error encountered.

[TOP](#)

FCUBS_WARNING_RESP

Attribute	Description	
Name	FCUBS_WARNING_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

WARNING

Attribute	Description	
Name	WARNING	
Datatype		
Description	Indicates the warning encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

[TOP](#)

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

[TOP](#)

2.9.CustomerAuthorize

Authorisation Of Customer

2.9.1.CO-CustomerAuthorize-Req-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

Customer-Full

CUSTOMERNO

CUSTOMERTYPE

CUSTOMERNAME1

ADDRESSLINE1

ADDRESSLINE3

ADDRESSLINE2

ADDRESSLINE4

COUNTRY

SHORTNAME

NATIONALITY

LANGUAGE

EXPOSURECOUNTRY

LOCALBRANCH

UNIQUEIDNAME

UNIQUEIDVALUE

FROZEN

DECEASED
 CUSTOMERCATEGORY
 SSN
 LOCCODE
 FULLNAME
 GROUPCODE
 FAXNUMBER
 CRMCUSTOMER
 CREDITRATING
 REVISIONDATE
 SHORTNAME2
 UNADVISED
 ISSUERCUSTOMER
 TREASURYCUSTOMER
 SOURCE
 USERREFNO
 MAKERID
 MAKERDTSTAMP
 CHECKERID
 CHECKERDTSTAMP
 MODNO
 AUTHSTAT
 RECSTAT
 ONCEAUTH
 UDFDETAILS
 FUNCTIONID
 FIELD_NAME
 DATATYPE
 FIELD_VALUE
 VAL_TYPE

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description
Name	SOURCE
Datatype	String
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".

Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description
Name	OPERATION

Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTIRIPID

Attribute	Description
Name	MULTIRIPID

Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description	
Name	VALUE	
Datatype	String	
Description	The value of the additional parameter comes here.	

[TOP](#)

FCUBS_BODY

Attribute	Description	
Name	FCUBS_BODY	
Datatype		
Description		

[TOP](#)

Customer-Full

Attribute	Description	
Name	Customer-Full	
Datatype		
Description		

[TOP](#)

CUSTOMERNO

Attribute	Description				
Name	CUSTOMERNO				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>1</td></tr></tbody></table>	Attribute	Description	minOccurs	1
	Attribute	Description			
minOccurs	1				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>9</td></tr></tbody></table>	Restrictions	Description	maxLength	9
	Restrictions	Description			
maxLength	9				

[TOP](#)

CUSTOMERTYPE

Attribute	Description				
Name	CUSTOMERTYPE				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>enumeration</td><td>B,C,I</td></tr></tbody></table>	Restrictions	Description	enumeration	B,C,I
	Restrictions	Description			
enumeration	B,C,I				

[TOP](#)

CUSTOMERNAME1

Attribute	Description				
Name	CUSTOMERNAME1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>105</td></tr></tbody></table>	Restrictions	Description	maxLength	105
	Restrictions	Description			
maxLength	105				

[TOP](#)

ADDRESSLINE1

Attribute	Description				
Name	ADDRESSLINE1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>1</td></tr></tbody></table>	Attribute	Description	minOccurs	1
	Attribute	Description			
minOccurs	1				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>105</td></tr></tbody></table>	Restrictions	Description	maxLength	105
	Restrictions	Description			
maxLength	105				

[TOP](#)

ADDRESSLINE3

Attribute	Description
-----------	-------------

Name	ADDRESSLINE3	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

ADDRESSLINE2

Attribute	Description	
Name	ADDRESSLINE2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

ADDRESSLINE4

Attribute	Description	
Name	ADDRESSLINE4	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

COUNTRY

Attribute	Description	
Name	COUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

SHORTNAME

Attribute	Description	
Name	SHORTNAME	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

NATIONALITY

Attribute	Description	
Name	NATIONALITY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LANGUAGE

Attribute	Description	
Name	LANGUAGE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

EXPOSURECOUNTRY

Attribute	Description	
Name	EXPOSURECOUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LOCALBRANCH

Attribute	Description	
Name	LOCALBRANCH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

UNIQUEIDNAME

Attribute	Description	
Name	UNIQUEIDNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

UNIQUEIDVALUE

Attribute	Description	
Name	UNIQUEIDVALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

FROZEN

Attribute	Description	
Name	FROZEN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

DECEASED

Attribute	Description	
Name	DECEASED	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

CUSTOMERCATEGORY

Attribute	Description	
Name	CUSTOMERCATEGORY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	10

SSN

Attribute	Description	
Name	SSN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	11

LOCCODE

Attribute	Description	
Name	LOCCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

FULLNAME

Attribute	Description	
Name	FULLNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

GROUPCODE

Attribute	Description	
Name	GROUPCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

FAXNUMBER

Attribute	Description	
Name	FAXNUMBER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

CRMCUSTOMER

Attribute	Description	
Name	CRMCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CREDITRATING

Attribute	Description	
Name	CREDITRATING	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

REVISIONDATE

Attribute	Description
Name	REVISIONDATE

Datatype	Date	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SHORTNAME2

Attribute	Description	
Name	SHORTNAME2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

UNADVISED

Attribute	Description	
Name	UNADVISED	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ISSUERCUSTOMER

Attribute	Description	
Name	ISSUERCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

TREASURYCUSTOMER

Attribute	Description	
Name	TREASURYCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERREFNO

Attribute	Description	
Name	USERREFNO	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	50

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

RECSTAT

Attribute	Description	
Name	RECSTAT	

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description
Name	FIELD_NAME
Datatype	String
Description	

Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

2.9.2.CO-CustomerAuthorize-Req-IO-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

Customer-IO

CUSTOMERNO

MODNO

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description
Name	USERID
Datatype	String

Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	

Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	

Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description	
Name	VALUE	
Datatype	String	
Description	The value of the additional parameter comes here.	

[TOP](#)

FCUBS_BODY

Attribute	Description	
Name	FCUBS_BODY	
Datatype		
Description		

[TOP](#)

Customer-IO

Attribute	Description	
Name	Customer-IO	
Datatype		
Description		

[TOP](#)

CUSTOMERNO

Attribute	Description				
Name	CUSTOMERNO				
Datatype	String				
Description					
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>9</td></tr></tbody></table>	Restrictions	Description	maxLength	9
	Restrictions	Description			
maxLength	9				

[TOP](#)

MODNO

Attribute	Description				
Name	MODNO				
Datatype	Number				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				

[TOP](#)

2.9.3.CO-CustomerAuthorize-Res-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

Customer-Full

CUSTOMERNO

CUSTOMERTYPE

CUSTOMERNAME1

ADDRESSLINE1

ADDRESSLINE3

ADDRESSLINE2

ADDRESSLINE4

COUNTRY

SHORTNAME

NATIONALITY

LANGUAGE

EXPOSURECOUNTRY

LOCALBRANCH

UNIQUEIDNAME

UNIQUEIDVALUE

FROZEN

DECEASED

CUSTOMERCATEGORY

SSN

LOCCODE
 FULLNAME
 GROUPCODE
 FAXNUMBER
 CRMCUSTOMER
 CREDITRATING
 REVISIONDATE
 SHORTNAME2
 UNADVISED
 ISSUERCUSTOMER
 TREASURYCUSTOMER
 SOURCE
 USERREFNO
 MAKERID
 MAKERDTSTAMP
 CHECKERID
 CHECKERDTSTAMP
 MODNO
 AUTHSTAT
 RECSTAT
 ONCEAUTH
 UDFDETAILS
 FUNCTIONID
 FIELD_NAME
 DATATYPE
 FIELD_VALUE
 VAL_TYPE
 FCUBS_ERROR_RESP
 ERROR
 ECODE
 EDESC
 FCUBS_WARNING_RESP
 WARNING
 WCODE
 WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description
-----------	-------------

Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description				
Name	MULTITRIPID				
Datatype	String				
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

FUNCTIONID

Attribute	Description						
Name	FUNCTIONID						
Datatype	String						
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.						
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0		
	Attribute	Description					
minOccurs	0						
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>8</td></tr><tr><td>pattern</td><td>[A-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	maxLength	8	pattern	[A-Z_0-9]*
	Restrictions	Description					
	maxLength	8					
pattern	[A-Z_0-9]*						

[TOP](#)

ACTION

Attribute	Description				
Name	ACTION				
Datatype	String				
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

MSGSTAT

Attribute	Description				
Name	MSGSTAT				
Datatype	String				
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				

Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description	
Name	VALUE	
Datatype	String	
Description	The value of the additional parameter comes here.	

[TOP](#)

FCUBS_BODY

Attribute	Description	
Name	FCUBS_BODY	
Datatype		
Description		

[TOP](#)

Customer-Full

Attribute	Description	
Name	Customer-Full	

Datatype	
Description	

[TOP](#)

CUSTOMERNO

Attribute	Description	
Name	CUSTOMERNO	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	9

[TOP](#)

CUSTOMERTYPE

Attribute	Description	
Name	CUSTOMERTYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	B,C,I

[TOP](#)

CUSTOMERNAME1

Attribute	Description	
Name	CUSTOMERNAME1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

ADDRESSLINE1

Attribute	Description	
Name	ADDRESSLINE1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	105

ADDRESSLINE3

Attribute	Description	
Name	ADDRESSLINE3	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

ADDRESSLINE2

Attribute	Description	
Name	ADDRESSLINE2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

ADDRESSLINE4

Attribute	Description	
Name	ADDRESSLINE4	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

COUNTRY

Attribute	Description	
Name	COUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

SHORTNAME

Attribute	Description	
Name	SHORTNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

NATIONALITY

Attribute	Description	
Name	NATIONALITY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LANGUAGE

Attribute	Description	
Name	LANGUAGE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

EXPOSURECOUNTRY

Attribute	Description	
Name	EXPOSURECOUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LOCALBRANCH

Attribute	Description
Name	LOCALBRANCH

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

UNIQUEIDNAME

Attribute	Description	
Name	UNIQUEIDNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

UNIQUEIDVALUE

Attribute	Description	
Name	UNIQUEIDVALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

FROZEN

Attribute	Description	
Name	FROZEN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

DECEASED

Attribute	Description	
Name	DECEASED	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CUSTOMERCATEGORY

Attribute	Description	
Name	CUSTOMERCATEGORY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

SSN

Attribute	Description	
Name	SSN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	11

[TOP](#)

LOCCODE

Attribute	Description	
Name	LOCCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

FULLNAME

Attribute	Description	
Name	FULLNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

GROUPCODE

Attribute	Description	
Name	GROUPCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

FAXNUMBER

Attribute	Description	
Name	FAXNUMBER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

CRMCUSTOMER

Attribute	Description	
Name	CRMCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CREDITRATING

Attribute	Description	
Name	CREDITRATING	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

REVISIONDATE

Attribute	Description	
Name	REVISIONDATE	
Datatype	Date	
Description		
Attributes	Attribute	Description
	minOccurs	0

SHORTNAME2

Attribute	Description	
Name	SHORTNAME2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

UNADVISED

Attribute	Description	
Name	UNADVISED	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

ISSUERCUSTOMER

Attribute	Description	
Name	ISSUERCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

TREASURYCUSTOMER

Attribute	Description
Name	TREASURYCUSTOMER

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERREFNO

Attribute	Description	
Name	USERREFNO	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	50

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description	
Name	ERROR	
Datatype		
Description	This indicates the type of error encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

ECODE

Attribute	Description	
Name	ECODE	
Datatype	String	
Description	This indicates the code for the error encountered.	

[TOP](#)

EDESC

Attribute	Description	
Name	EDESC	
Datatype	String	
Description	This indicates the description of the error encountered.	

[TOP](#)

FCUBS_WARNING_RESP

Attribute	Description	
Name	FCUBS_WARNING_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

WARNING

Attribute	Description	
Name	WARNING	
Datatype		
Description	Indicates the warning encountered.	

Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

[TOP](#)

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

[TOP](#)

2.9.4.CO-CustomerAuthorize-Res-PK-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

Customer-PK

CUSTOMERNO

MODNO

FCUBS_ERROR_RESP

ERROR

ECODE

EDESC

FCUBS_WARNING_RESP

WARNING

WCODE

WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description
-----------	-------------

Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description				
Name	MULTITRIPID				
Datatype	String				
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

FUNCTIONID

Attribute	Description						
Name	FUNCTIONID						
Datatype	String						
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.						
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0		
	Attribute	Description					
minOccurs	0						
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>8</td></tr><tr><td>pattern</td><td>[A-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	maxLength	8	pattern	[A-Z_0-9]*
	Restrictions	Description					
	maxLength	8					
pattern	[A-Z_0-9]*						

[TOP](#)

ACTION

Attribute	Description				
Name	ACTION				
Datatype	String				
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

MSGSTAT

Attribute	Description				
Name	MSGSTAT				
Datatype	String				
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				

Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

Customer-PK

Attribute	Description
Name	Customer-PK

Datatype	
Description	

[TOP](#)

CUSTOMERNO

Attribute	Description	
Name	CUSTOMERNO	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	9

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description	
Name	ERROR	
Datatype		
Description	This indicates the type of error encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

ECODE

Attribute	Description	
Name	ECODE	
Datatype	String	
Description	This indicates the code for the error encountered.	

[TOP](#)**EDESC**

Attribute	Description
Name	EDESC
Datatype	String
Description	This indicates the description of the error encountered.

[TOP](#)**FCUBS_WARNING_RESP**

Attribute	Description	
Name	FCUBS_WARNING_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)**WARNING**

Attribute	Description	
Name	WARNING	
Datatype		
Description	Indicates the warning encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)**WCODE**

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

[TOP](#)**WDESC**

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

[TOP](#)

2.10.CustomerClose

Closure Of Customer

2.10.1.CO-CustomerClose-Req-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

Customer-Full

CUSTOMERNO

CUSTOMERTYPE

CUSTOMERNAME1

ADDRESSLINE1

ADDRESSLINE3

ADDRESSLINE2

ADDRESSLINE4

COUNTRY

SHORTNAME

NATIONALITY

LANGUAGE

EXPOSURECOUNTRY

LOCALBRANCH

UNIQUEIDNAME

UNIQUEIDVALUE

FROZEN

DECEASED
 CUSTOMERCATEGORY
 SSN
 LOCCODE
 FULLNAME
 GROUPCODE
 FAXNUMBER
 CRMCUSTOMER
 CREDITRATING
 REVISIONDATE
 SHORTNAME2
 UNADVISED
 ISSUERCUSTOMER
 TREASURYCUSTOMER
 SOURCE
 USERREFNO
 MAKERID
 MAKERDTSTAMP
 CHECKERID
 CHECKERDTSTAMP
 MODNO
 AUTHSTAT
 RECSTAT
 ONCEAUTH
 UDFDETAILS
 FUNCTIONID
 FIELD_NAME
 DATATYPE
 FIELD_VALUE
 VAL_TYPE

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description
Name	SOURCE
Datatype	String
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".

Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description
Name	OPERATION

Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTIRIPID

Attribute	Description
Name	MULTIRIPID

Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description	
Name	VALUE	
Datatype	String	
Description	The value of the additional parameter comes here.	

[TOP](#)

FCUBS_BODY

Attribute	Description	
Name	FCUBS_BODY	
Datatype		
Description		

[TOP](#)

Customer-Full

Attribute	Description	
Name	Customer-Full	
Datatype		
Description		

[TOP](#)

CUSTOMERNO

Attribute	Description				
Name	CUSTOMERNO				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>1</td></tr></tbody></table>	Attribute	Description	minOccurs	1
	Attribute	Description			
minOccurs	1				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>9</td></tr></tbody></table>	Restrictions	Description	maxLength	9
	Restrictions	Description			
maxLength	9				

[TOP](#)

CUSTOMERTYPE

Attribute	Description				
Name	CUSTOMERTYPE				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>enumeration</td><td>B,C,I</td></tr></tbody></table>	Restrictions	Description	enumeration	B,C,I
	Restrictions	Description			
enumeration	B,C,I				

[TOP](#)

CUSTOMERNAME1

Attribute	Description				
Name	CUSTOMERNAME1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>105</td></tr></tbody></table>	Restrictions	Description	maxLength	105
	Restrictions	Description			
maxLength	105				

[TOP](#)

ADDRESSLINE1

Attribute	Description				
Name	ADDRESSLINE1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>1</td></tr></tbody></table>	Attribute	Description	minOccurs	1
	Attribute	Description			
minOccurs	1				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>105</td></tr></tbody></table>	Restrictions	Description	maxLength	105
	Restrictions	Description			
maxLength	105				

[TOP](#)

ADDRESSLINE3

Attribute	Description
-----------	-------------

Name	ADDRESSLINE3	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

ADDRESSLINE2

Attribute	Description	
Name	ADDRESSLINE2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

ADDRESSLINE4

Attribute	Description	
Name	ADDRESSLINE4	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

COUNTRY

Attribute	Description	
Name	COUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

SHORTNAME

Attribute	Description	
Name	SHORTNAME	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

NATIONALITY

Attribute	Description	
Name	NATIONALITY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LANGUAGE

Attribute	Description	
Name	LANGUAGE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

EXPOSURECOUNTRY

Attribute	Description	
Name	EXPOSURECOUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LOCALBRANCH

Attribute	Description	
Name	LOCALBRANCH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

UNIQUEIDNAME

Attribute	Description	
Name	UNIQUEIDNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

UNIQUEIDVALUE

Attribute	Description	
Name	UNIQUEIDVALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

FROZEN

Attribute	Description	
Name	FROZEN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

DECEASED

Attribute	Description	
Name	DECEASED	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

CUSTOMERCATEGORY

Attribute	Description	
Name	CUSTOMERCATEGORY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	10

SSN

Attribute	Description	
Name	SSN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	11

LOCCODE

Attribute	Description	
Name	LOCCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

FULLNAME

Attribute	Description	
Name	FULLNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

GROUPCODE

Attribute	Description	
Name	GROUPCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

FAXNUMBER

Attribute	Description	
Name	FAXNUMBER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

CRMCUSTOMER

Attribute	Description	
Name	CRMCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CREDITRATING

Attribute	Description	
Name	CREDITRATING	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

REVISIONDATE

Attribute	Description
Name	REVISIONDATE

Datatype	Date	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SHORTNAME2

Attribute	Description	
Name	SHORTNAME2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

UNADVISED

Attribute	Description	
Name	UNADVISED	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ISSUERCUSTOMER

Attribute	Description	
Name	ISSUERCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

TREASURYCUSTOMER

Attribute	Description	
Name	TREASURYCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERREFNO

Attribute	Description	
Name	USERREFNO	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	50

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

RECSTAT

Attribute	Description
Name	RECSTAT

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		

Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

2.10.2.CO-CustomerClose-Req-IO-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

Customer-IO

CUSTOMERNO

MODNO

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description
Name	USERID
Datatype	String

Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	

Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	

Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description	
Name	VALUE	
Datatype	String	
Description	The value of the additional parameter comes here.	

[TOP](#)

FCUBS_BODY

Attribute	Description	
Name	FCUBS_BODY	
Datatype		
Description		

[TOP](#)

Customer-IO

Attribute	Description	
Name	Customer-IO	
Datatype		
Description		

[TOP](#)

CUSTOMERNO

Attribute	Description	
Name	CUSTOMERNO	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	9

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

2.10.3.CO-CustomerClose-Res-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

Customer-Full

CUSTOMERNO

CUSTOMERTYPE

CUSTOMERNAME1

ADDRESSLINE1

ADDRESSLINE3

ADDRESSLINE2

ADDRESSLINE4

COUNTRY

SHORTNAME

NATIONALITY

LANGUAGE

EXPOSURECOUNTRY

LOCALBRANCH

UNIQUEIDNAME

UNIQUEIDVALUE

FROZEN

DECEASED

CUSTOMERCATEGORY

SSN

LOCCODE
 FULLNAME
 GROUPCODE
 FAXNUMBER
 CRMCUSTOMER
 CREDITRATING
 REVISIONDATE
 SHORTNAME2
 UNADVISED
 ISSUERCUSTOMER
 TREASURYCUSTOMER
 SOURCE
 USERREFNO
 MAKERID
 MAKERDTSTAMP
 CHECKERID
 CHECKERDTSTAMP
 MODNO
 AUTHSTAT
 RECSTAT
 ONCEAUTH
 UDFDETAILS
 FUNCTIONID
 FIELD_NAME
 DATATYPE
 FIELD_VALUE
 VAL_TYPE
 FCUBS_ERROR_RESP
 ERROR
 ECODE
 EDESC
 FCUBS_WARNING_RESP
 WARNING
 WCODE
 WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description
-----------	-------------

Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description				
Name	MULTITRIPID				
Datatype	String				
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

FUNCTIONID

Attribute	Description						
Name	FUNCTIONID						
Datatype	String						
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.						
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0		
	Attribute	Description					
minOccurs	0						
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>8</td></tr><tr><td>pattern</td><td>[A-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	maxLength	8	pattern	[A-Z_0-9]*
	Restrictions	Description					
	maxLength	8					
pattern	[A-Z_0-9]*						

[TOP](#)

ACTION

Attribute	Description				
Name	ACTION				
Datatype	String				
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

MSGSTAT

Attribute	Description				
Name	MSGSTAT				
Datatype	String				
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				

Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

Customer-Full

Attribute	Description
Name	Customer-Full

Datatype	
Description	

[TOP](#)

CUSTOMERNO

Attribute	Description	
Name	CUSTOMERNO	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	9

[TOP](#)

CUSTOMERTYPE

Attribute	Description	
Name	CUSTOMERTYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	B,C,I

[TOP](#)

CUSTOMERNAME1

Attribute	Description	
Name	CUSTOMERNAME1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

ADDRESSLINE1

Attribute	Description	
Name	ADDRESSLINE1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	105

ADDRESSLINE3

Attribute	Description	
Name	ADDRESSLINE3	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

ADDRESSLINE2

Attribute	Description	
Name	ADDRESSLINE2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

ADDRESSLINE4

Attribute	Description	
Name	ADDRESSLINE4	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

COUNTRY

Attribute	Description	
Name	COUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

SHORTNAME

Attribute	Description	
Name	SHORTNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

NATIONALITY

Attribute	Description	
Name	NATIONALITY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LANGUAGE

Attribute	Description	
Name	LANGUAGE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

EXPOSURECOUNTRY

Attribute	Description	
Name	EXPOSURECOUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LOCALBRANCH

Attribute	Description
Name	LOCALBRANCH

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

UNIQUEIDNAME

Attribute	Description	
Name	UNIQUEIDNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

UNIQUEIDVALUE

Attribute	Description	
Name	UNIQUEIDVALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

FROZEN

Attribute	Description	
Name	FROZEN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

DECEASED

Attribute	Description	
Name	DECEASED	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CUSTOMERCATEGORY

Attribute	Description	
Name	CUSTOMERCATEGORY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

SSN

Attribute	Description	
Name	SSN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	11

[TOP](#)

LOCCODE

Attribute	Description	
Name	LOCCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

FULLNAME

Attribute	Description	
Name	FULLNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

GROUPCODE

Attribute	Description	
Name	GROUPCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

FAXNUMBER

Attribute	Description	
Name	FAXNUMBER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

CRMCUSTOMER

Attribute	Description	
Name	CRMCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CREDITRATING

Attribute	Description	
Name	CREDITRATING	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

REVISIONDATE

Attribute	Description	
Name	REVISIONDATE	
Datatype	Date	
Description		
Attributes	Attribute	Description
	minOccurs	0

SHORTNAME2

Attribute	Description	
Name	SHORTNAME2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

UNADVISED

Attribute	Description	
Name	UNADVISED	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

ISSUERCUSTOMER

Attribute	Description	
Name	ISSUERCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

TREASURYCUSTOMER

Attribute	Description
Name	TREASURYCUSTOMER

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERREFNO

Attribute	Description	
Name	USERREFNO	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	50

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description	
Name	ERROR	
Datatype		
Description	This indicates the type of error encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

ECODE

Attribute	Description	
Name	ECODE	
Datatype	String	
Description	This indicates the code for the error encountered.	

[TOP](#)

EDESC

Attribute	Description	
Name	EDESC	
Datatype	String	
Description	This indicates the description of the error encountered.	

[TOP](#)

FCUBS_WARNING_RESP

Attribute	Description	
Name	FCUBS_WARNING_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

WARNING

Attribute	Description	
Name	WARNING	
Datatype		
Description	Indicates the warning encountered.	

Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

[TOP](#)

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

[TOP](#)

2.10.4.CO-CustomerClose-Res-PK-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

Customer-PK

CUSTOMERNO

MODNO

FCUBS_ERROR_RESP

ERROR

ECODE

EDESC

FCUBS_WARNING_RESP

WARNING

WCODE

WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description
-----------	-------------

Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description				
Name	MULTITRIPID				
Datatype	String				
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

FUNCTIONID

Attribute	Description						
Name	FUNCTIONID						
Datatype	String						
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.						
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0		
	Attribute	Description					
minOccurs	0						
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>8</td></tr><tr><td>pattern</td><td>[A-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	maxLength	8	pattern	[A-Z_0-9]*
	Restrictions	Description					
	maxLength	8					
pattern	[A-Z_0-9]*						

[TOP](#)

ACTION

Attribute	Description				
Name	ACTION				
Datatype	String				
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

MSGSTAT

Attribute	Description				
Name	MSGSTAT				
Datatype	String				
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				

Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

Customer-PK

Attribute	Description
Name	Customer-PK

Datatype	
Description	

[TOP](#)

CUSTOMERNO

Attribute	Description	
Name	CUSTOMERNO	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	9

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description	
Name	ERROR	
Datatype		
Description	This indicates the type of error encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

ECODE

Attribute	Description	
Name	ECODE	
Datatype	String	
Description	This indicates the code for the error encountered.	

[TOP](#)

EDESC

Attribute	Description
Name	EDESC
Datatype	String
Description	This indicates the description of the error encountered.

[TOP](#)

FCUBS_WARNING_RESP

Attribute	Description	
Name	FCUBS_WARNING_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

WARNING

Attribute	Description	
Name	WARNING	
Datatype		
Description	Indicates the warning encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

[TOP](#)

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

[TOP](#)

2.11.CustomerCreate

Creation Of new Customer

2.11.1.CO-CustomerCreate-Req-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

Customer-Full

CUSTOMERNO

CUSTOMERTYPE

CUSTOMERNAME1

ADDRESSLINE1

ADDRESSLINE3

ADDRESSLINE2

ADDRESSLINE4

COUNTRY

SHORTNAME

NATIONALITY

LANGUAGE

EXPOSURECOUNTRY

LOCALBRANCH

UNIQUEIDNAME

UNIQUEIDVALUE

FROZEN

DECEASED
 CUSTOMERCATEGORY
 SSN
 LOCCODE
 FULLNAME
 GROUPCODE
 FAXNUMBER
 CRMCUSTOMER
 CREDITRATING
 REVISIONDATE
 SHORTNAME2
 UNADVISED
 ISSUERCUSTOMER
 TREASURYCUSTOMER
 SOURCE
 USERREFNO
 MAKERID
 MAKERDTSTAMP
 CHECKERID
 CHECKERDTSTAMP
 MODNO
 AUTHSTAT
 RECSTAT
 ONCEAUTH
 UDFDETAILS
 FUNCTIONID
 FIELD_NAME
 DATATYPE
 FIELD_VALUE
 VAL_TYPE

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description
Name	SOURCE
Datatype	String
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".

Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description
Name	OPERATION

Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTIRIPID

Attribute	Description
Name	MULTIRIPID

Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description	
Name	VALUE	
Datatype	String	
Description	The value of the additional parameter comes here.	

[TOP](#)

FCUBS_BODY

Attribute	Description	
Name	FCUBS_BODY	
Datatype		
Description		

[TOP](#)

Customer-Full

Attribute	Description	
Name	Customer-Full	
Datatype		
Description		

[TOP](#)

CUSTOMERNO

Attribute	Description				
Name	CUSTOMERNO				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>1</td></tr></tbody></table>	Attribute	Description	minOccurs	1
	Attribute	Description			
minOccurs	1				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>9</td></tr></tbody></table>	Restrictions	Description	maxLength	9
	Restrictions	Description			
maxLength	9				

[TOP](#)

CUSTOMERTYPE

Attribute	Description				
Name	CUSTOMERTYPE				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>enumeration</td><td>B,C,I</td></tr></tbody></table>	Restrictions	Description	enumeration	B,C,I
	Restrictions	Description			
enumeration	B,C,I				

[TOP](#)

CUSTOMERNAME1

Attribute	Description				
Name	CUSTOMERNAME1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>105</td></tr></tbody></table>	Restrictions	Description	maxLength	105
	Restrictions	Description			
maxLength	105				

[TOP](#)

ADDRESSLINE1

Attribute	Description				
Name	ADDRESSLINE1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>1</td></tr></tbody></table>	Attribute	Description	minOccurs	1
	Attribute	Description			
minOccurs	1				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>105</td></tr></tbody></table>	Restrictions	Description	maxLength	105
	Restrictions	Description			
maxLength	105				

[TOP](#)

ADDRESSLINE3

Attribute	Description
-----------	-------------

Name	ADDRESSLINE3	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

ADDRESSLINE2

Attribute	Description	
Name	ADDRESSLINE2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

ADDRESSLINE4

Attribute	Description	
Name	ADDRESSLINE4	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

COUNTRY

Attribute	Description	
Name	COUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

SHORTNAME

Attribute	Description	
Name	SHORTNAME	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

NATIONALITY

Attribute	Description	
Name	NATIONALITY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LANGUAGE

Attribute	Description	
Name	LANGUAGE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

EXPOSURECOUNTRY

Attribute	Description	
Name	EXPOSURECOUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LOCALBRANCH

Attribute	Description	
Name	LOCALBRANCH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

UNIQUEIDNAME

Attribute	Description	
Name	UNIQUEIDNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

UNIQUEIDVALUE

Attribute	Description	
Name	UNIQUEIDVALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

FROZEN

Attribute	Description	
Name	FROZEN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

DECEASED

Attribute	Description	
Name	DECEASED	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

CUSTOMERCATEGORY

Attribute	Description	
Name	CUSTOMERCATEGORY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	10

SSN

Attribute	Description	
Name	SSN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	11

LOCCODE

Attribute	Description	
Name	LOCCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

FULLNAME

Attribute	Description	
Name	FULLNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

GROUPCODE

Attribute	Description	
Name	GROUPCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

FAXNUMBER

Attribute	Description	
Name	FAXNUMBER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

CRMCUSTOMER

Attribute	Description	
Name	CRMCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CREDITRATING

Attribute	Description	
Name	CREDITRATING	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

REVISIONDATE

Attribute	Description
Name	REVISIONDATE

Datatype	Date	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SHORTNAME2

Attribute	Description	
Name	SHORTNAME2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

UNADVISED

Attribute	Description	
Name	UNADVISED	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ISSUERCUSTOMER

Attribute	Description	
Name	ISSUERCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

TREASURYCUSTOMER

Attribute	Description	
Name	TREASURYCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERREFNO

Attribute	Description	
Name	USERREFNO	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	50

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

RECSTAT

Attribute	Description	
Name	RECSTAT	

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		

Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

2.11.2.CO-CustomerCreate-Req-IO-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

Customer-IO

CUSTOMERNO

CUSTOMERTYPE

CUSTOMERNAME1

ADDRESSLINE1

ADDRESSLINE3

ADDRESSLINE2

ADDRESSLINE4

COUNTRY

SHORTNAME

NATIONALITY

LANGUAGE

EXPOSURECOUNTRY

LOCALBRANCH

UNIQUEIDNAME

UNIQUEIDVALUE

FROZEN

DECEASED

CUSTOMERCATEGORY

SSN

LOCCODE
 FULLNAME
 GROUPCODE
 FAXNUMBER
 CRMCUSTOMER
 CREDITRATING
 REVISIONDATE
 SHORTNAME2
 UNADVISED
 ISSUERCUSTOMER
 TREASURYCUSTOMER
 SOURCE
 USERREFNO
 MAKERID
 MAKERDTSTAMP
 CHECKERID
 CHECKERDTSTAMP
 MODNO
 AUTHSTAT
 RECSTAT
 ONCEAUTH
 UDFDETAILS
 FUNCTIONID
 FIELD_NAME
 DATATYPE
 FIELD_VALUE
 VAL_TYPE

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description
Name	USERID
Datatype	String

Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	

Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	

Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description	
Name	VALUE	
Datatype	String	
Description	The value of the additional parameter comes here.	

[TOP](#)

FCUBS_BODY

Attribute	Description	
Name	FCUBS_BODY	
Datatype		
Description		

[TOP](#)

Customer-IO

Attribute	Description	
Name	Customer-IO	
Datatype		
Description		

[TOP](#)

CUSTOMERNO

Attribute	Description				
Name	CUSTOMERNO				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>1</td></tr></tbody></table>	Attribute	Description	minOccurs	1
	Attribute	Description			
minOccurs	1				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>9</td></tr></tbody></table>	Restrictions	Description	maxLength	9
	Restrictions	Description			
maxLength	9				

[TOP](#)

CUSTOMERTYPE

Attribute	Description				
Name	CUSTOMERTYPE				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>enumeration</td><td>B,C,I</td></tr></tbody></table>	Restrictions	Description	enumeration	B,C,I
	Restrictions	Description			
enumeration	B,C,I				

[TOP](#)

CUSTOMERNAME1

Attribute	Description				
Name	CUSTOMERNAME1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>105</td></tr></tbody></table>	Restrictions	Description	maxLength	105
	Restrictions	Description			
maxLength	105				

[TOP](#)

ADDRESSLINE1

Attribute	Description				
Name	ADDRESSLINE1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>1</td></tr></tbody></table>	Attribute	Description	minOccurs	1
	Attribute	Description			
minOccurs	1				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>105</td></tr></tbody></table>	Restrictions	Description	maxLength	105
	Restrictions	Description			
maxLength	105				

[TOP](#)

ADDRESSLINE3

Attribute	Description
-----------	-------------

Name	ADDRESSLINE3	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

ADDRESSLINE2

Attribute	Description	
Name	ADDRESSLINE2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

ADDRESSLINE4

Attribute	Description	
Name	ADDRESSLINE4	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

COUNTRY

Attribute	Description	
Name	COUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

SHORTNAME

Attribute	Description	
Name	SHORTNAME	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

NATIONALITY

Attribute	Description	
Name	NATIONALITY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LANGUAGE

Attribute	Description	
Name	LANGUAGE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

EXPOSURECOUNTRY

Attribute	Description	
Name	EXPOSURECOUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LOCALBRANCH

Attribute	Description	
Name	LOCALBRANCH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

UNIQUEIDNAME

Attribute	Description	
Name	UNIQUEIDNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

UNIQUEIDVALUE

Attribute	Description	
Name	UNIQUEIDVALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

FROZEN

Attribute	Description	
Name	FROZEN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

DECEASED

Attribute	Description	
Name	DECEASED	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

CUSTOMERCATEGORY

Attribute	Description	
Name	CUSTOMERCATEGORY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	10

SSN

Attribute	Description	
Name	SSN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	11

LOCCODE

Attribute	Description	
Name	LOCCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

FULLNAME

Attribute	Description	
Name	FULLNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

GROUPCODE

Attribute	Description	
Name	GROUPCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

FAXNUMBER

Attribute	Description	
Name	FAXNUMBER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

CRMCUSTOMER

Attribute	Description	
Name	CRMCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CREDITRATING

Attribute	Description	
Name	CREDITRATING	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

REVISIONDATE

Attribute	Description
Name	REVISIONDATE

Datatype	Date	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SHORTNAME2

Attribute	Description	
Name	SHORTNAME2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

UNADVISED

Attribute	Description	
Name	UNADVISED	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ISSUERCUSTOMER

Attribute	Description	
Name	ISSUERCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

TREASURYCUSTOMER

Attribute	Description	
Name	TREASURYCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERREFNO

Attribute	Description	
Name	USERREFNO	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	50

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

RECSTAT

Attribute	Description
Name	RECSTAT

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		

Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

2.11.3.CO-CustomerCreate-Res-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

Customer-Full

CUSTOMERNO

CUSTOMERTYPE

CUSTOMERNAME1

ADDRESSLINE1

ADDRESSLINE3

ADDRESSLINE2

ADDRESSLINE4

COUNTRY

SHORTNAME

NATIONALITY

LANGUAGE

EXPOSURECOUNTRY

LOCALBRANCH

UNIQUEIDNAME

UNIQUEIDVALUE

FROZEN

DECEASED

CUSTOMERCATEGORY

SSN

LOCCODE
 FULLNAME
 GROUPCODE
 FAXNUMBER
 CRMCUSTOMER
 CREDITRATING
 REVISIONDATE
 SHORTNAME2
 UNADVISED
 ISSUERCUSTOMER
 TREASURYCUSTOMER
 SOURCE
 USERREFNO
 MAKERID
 MAKERDTSTAMP
 CHECKERID
 CHECKERDTSTAMP
 MODNO
 AUTHSTAT
 RECSTAT
 ONCEAUTH
 UDFDETAILS
 FUNCTIONID
 FIELD_NAME
 DATATYPE
 FIELD_VALUE
 VAL_TYPE
 FCUBS_ERROR_RESP
 ERROR
 ECODE
 EDESC
 FCUBS_WARNING_RESP
 WARNING
 WCODE
 WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description
-----------	-------------

Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description				
Name	MULTITRIPID				
Datatype	String				
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

FUNCTIONID

Attribute	Description						
Name	FUNCTIONID						
Datatype	String						
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.						
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0		
	Attribute	Description					
minOccurs	0						
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>8</td></tr><tr><td>pattern</td><td>[A-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	maxLength	8	pattern	[A-Z_0-9]*
	Restrictions	Description					
	maxLength	8					
pattern	[A-Z_0-9]*						

[TOP](#)

ACTION

Attribute	Description				
Name	ACTION				
Datatype	String				
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

MSGSTAT

Attribute	Description				
Name	MSGSTAT				
Datatype	String				
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				

Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

Customer-Full

Attribute	Description
Name	Customer-Full

Datatype	
Description	

[TOP](#)

CUSTOMERNO

Attribute	Description	
Name	CUSTOMERNO	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	9

[TOP](#)

CUSTOMERTYPE

Attribute	Description	
Name	CUSTOMERTYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	B,C,I

[TOP](#)

CUSTOMERNAME1

Attribute	Description	
Name	CUSTOMERNAME1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

ADDRESSLINE1

Attribute	Description	
Name	ADDRESSLINE1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	105

ADDRESSLINE3

Attribute	Description	
Name	ADDRESSLINE3	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

ADDRESSLINE2

Attribute	Description	
Name	ADDRESSLINE2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

ADDRESSLINE4

Attribute	Description	
Name	ADDRESSLINE4	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

COUNTRY

Attribute	Description	
Name	COUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

SHORTNAME

Attribute	Description	
Name	SHORTNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

NATIONALITY

Attribute	Description	
Name	NATIONALITY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LANGUAGE

Attribute	Description	
Name	LANGUAGE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

EXPOSURECOUNTRY

Attribute	Description	
Name	EXPOSURECOUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LOCALBRANCH

Attribute	Description
Name	LOCALBRANCH

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

UNIQUEIDNAME

Attribute	Description	
Name	UNIQUEIDNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

UNIQUEIDVALUE

Attribute	Description	
Name	UNIQUEIDVALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

FROZEN

Attribute	Description	
Name	FROZEN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

DECEASED

Attribute	Description	
Name	DECEASED	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CUSTOMERCATEGORY

Attribute	Description	
Name	CUSTOMERCATEGORY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

SSN

Attribute	Description	
Name	SSN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	11

[TOP](#)

LOCCODE

Attribute	Description	
Name	LOCCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

FULLNAME

Attribute	Description	
Name	FULLNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

GROUPCODE

Attribute	Description	
Name	GROUPCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

FAXNUMBER

Attribute	Description	
Name	FAXNUMBER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

CRMCUSTOMER

Attribute	Description	
Name	CRMCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CREDITRATING

Attribute	Description	
Name	CREDITRATING	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

REVISIONDATE

Attribute	Description	
Name	REVISIONDATE	
Datatype	Date	
Description		
Attributes	Attribute	Description
	minOccurs	0

SHORTNAME2

Attribute	Description	
Name	SHORTNAME2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

UNADVISED

Attribute	Description	
Name	UNADVISED	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

ISSUERCUSTOMER

Attribute	Description	
Name	ISSUERCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

TREASURYCUSTOMER

Attribute	Description
Name	TREASURYCUSTOMER

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERREFNO

Attribute	Description	
Name	USERREFNO	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	50

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description	
Name	ERROR	
Datatype		
Description	This indicates the type of error encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

ECODE

Attribute	Description	
Name	ECODE	
Datatype	String	
Description	This indicates the code for the error encountered.	

[TOP](#)

EDESC

Attribute	Description	
Name	EDESC	
Datatype	String	
Description	This indicates the description of the error encountered.	

[TOP](#)

FCUBS_WARNING_RESP

Attribute	Description	
Name	FCUBS_WARNING_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

WARNING

Attribute	Description	
Name	WARNING	
Datatype		
Description	Indicates the warning encountered.	

Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

[TOP](#)

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

[TOP](#)

2.11.4.CO-CustomerCreate-Res-PK-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

Customer-PK

CUSTOMERNO

MODNO

FCUBS_ERROR_RESP

ERROR

ECODE

EDESC

FCUBS_WARNING_RESP

WARNING

WCODE

WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description
-----------	-------------

Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description				
Name	MULTITRIPID				
Datatype	String				
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

FUNCTIONID

Attribute	Description						
Name	FUNCTIONID						
Datatype	String						
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.						
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0		
	Attribute	Description					
minOccurs	0						
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>8</td></tr><tr><td>pattern</td><td>[A-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	maxLength	8	pattern	[A-Z_0-9]*
	Restrictions	Description					
	maxLength	8					
pattern	[A-Z_0-9]*						

[TOP](#)

ACTION

Attribute	Description				
Name	ACTION				
Datatype	String				
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

MSGSTAT

Attribute	Description				
Name	MSGSTAT				
Datatype	String				
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				

Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

Customer-PK

Attribute	Description
Name	Customer-PK

Datatype	
Description	

[TOP](#)

CUSTOMERNO

Attribute	Description	
Name	CUSTOMERNO	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	9

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description	
Name	ERROR	
Datatype		
Description	This indicates the type of error encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

ECODE

Attribute	Description	
Name	ECODE	
Datatype	String	
Description	This indicates the code for the error encountered.	

[TOP](#)**EDESC**

Attribute	Description
Name	EDESC
Datatype	String
Description	This indicates the description of the error encountered.

[TOP](#)**FCUBS_WARNING_RESP**

Attribute	Description						
Name	FCUBS_WARNING_RESP						
Datatype							
Description							
Attributes	<table border="1"> <thead> <tr> <th>Attribute</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>maxOccurs</td> <td>unbounded</td> </tr> <tr> <td>minOccurs</td> <td>0</td> </tr> </tbody> </table>	Attribute	Description	maxOccurs	unbounded	minOccurs	0
	Attribute	Description					
	maxOccurs	unbounded					
minOccurs	0						

[TOP](#)**WARNING**

Attribute	Description				
Name	WARNING				
Datatype					
Description	Indicates the warning encountered.				
Attributes	<table border="1"> <thead> <tr> <th>Attribute</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>maxOccurs</td> <td>unbounded</td> </tr> </tbody> </table>	Attribute	Description	maxOccurs	unbounded
	Attribute	Description			
maxOccurs	unbounded				

[TOP](#)**WCODE**

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

[TOP](#)**WDESC**

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

[TOP](#)

2.12.CustomerDelete

Deletion Of Customer

2.12.1.CO-CustomerDelete-Req-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

Customer-Full

CUSTOMERNO

CUSTOMERTYPE

CUSTOMERNAME1

ADDRESSLINE1

ADDRESSLINE3

ADDRESSLINE2

ADDRESSLINE4

COUNTRY

SHORTNAME

NATIONALITY

LANGUAGE

EXPOSURECOUNTRY

LOCALBRANCH

UNIQUEIDNAME

UNIQUEIDVALUE

FROZEN

DECEASED
 CUSTOMERCATEGORY
 SSN
 LOCCODE
 FULLNAME
 GROUPCODE
 FAXNUMBER
 CRMCUSTOMER
 CREDITRATING
 REVISIONDATE
 SHORTNAME2
 UNADVISED
 ISSUERCUSTOMER
 TREASURYCUSTOMER
 SOURCE
 USERREFNO
 MAKERID
 MAKERDTSTAMP
 CHECKERID
 CHECKERDTSTAMP
 MODNO
 AUTHSTAT
 RECSTAT
 ONCEAUTH
 UDFDETAILS
 FUNCTIONID
 FIELD_NAME
 DATATYPE
 FIELD_VALUE
 VAL_TYPE

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description
Name	SOURCE
Datatype	String
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".

Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description
Name	OPERATION

Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTIRIPID

Attribute	Description
Name	MULTIRIPID

Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description	
Name	VALUE	
Datatype	String	
Description	The value of the additional parameter comes here.	

[TOP](#)

FCUBS_BODY

Attribute	Description	
Name	FCUBS_BODY	
Datatype		
Description		

[TOP](#)

Customer-Full

Attribute	Description	
Name	Customer-Full	
Datatype		
Description		

[TOP](#)

CUSTOMERNO

Attribute	Description				
Name	CUSTOMERNO				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>1</td></tr></tbody></table>	Attribute	Description	minOccurs	1
	Attribute	Description			
minOccurs	1				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>9</td></tr></tbody></table>	Restrictions	Description	maxLength	9
	Restrictions	Description			
maxLength	9				

[TOP](#)

CUSTOMERTYPE

Attribute	Description				
Name	CUSTOMERTYPE				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>enumeration</td><td>B,C,I</td></tr></tbody></table>	Restrictions	Description	enumeration	B,C,I
	Restrictions	Description			
enumeration	B,C,I				

[TOP](#)

CUSTOMERNAME1

Attribute	Description				
Name	CUSTOMERNAME1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>105</td></tr></tbody></table>	Restrictions	Description	maxLength	105
	Restrictions	Description			
maxLength	105				

[TOP](#)

ADDRESSLINE1

Attribute	Description				
Name	ADDRESSLINE1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>1</td></tr></tbody></table>	Attribute	Description	minOccurs	1
	Attribute	Description			
minOccurs	1				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>105</td></tr></tbody></table>	Restrictions	Description	maxLength	105
	Restrictions	Description			
maxLength	105				

[TOP](#)

ADDRESSLINE3

Attribute	Description
-----------	-------------

Name	ADDRESSLINE3	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

ADDRESSLINE2

Attribute	Description	
Name	ADDRESSLINE2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

ADDRESSLINE4

Attribute	Description	
Name	ADDRESSLINE4	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

COUNTRY

Attribute	Description	
Name	COUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

SHORTNAME

Attribute	Description	
Name	SHORTNAME	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

NATIONALITY

Attribute	Description	
Name	NATIONALITY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LANGUAGE

Attribute	Description	
Name	LANGUAGE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

EXPOSURECOUNTRY

Attribute	Description	
Name	EXPOSURECOUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LOCALBRANCH

Attribute	Description	
Name	LOCALBRANCH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

UNIQUEIDNAME

Attribute	Description	
Name	UNIQUEIDNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

UNIQUEIDVALUE

Attribute	Description	
Name	UNIQUEIDVALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

FROZEN

Attribute	Description	
Name	FROZEN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

DECEASED

Attribute	Description	
Name	DECEASED	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

CUSTOMERCATEGORY

Attribute	Description	
Name	CUSTOMERCATEGORY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	10

SSN

Attribute	Description	
Name	SSN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	11

LOCCODE

Attribute	Description	
Name	LOCCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

FULLNAME

Attribute	Description	
Name	FULLNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

GROUPCODE

Attribute	Description	
Name	GROUPCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

FAXNUMBER

Attribute	Description	
Name	FAXNUMBER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

CRMCUSTOMER

Attribute	Description	
Name	CRMCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CREDITRATING

Attribute	Description	
Name	CREDITRATING	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

REVISIONDATE

Attribute	Description
Name	REVISIONDATE

Datatype	Date	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SHORTNAME2

Attribute	Description	
Name	SHORTNAME2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

UNADVISED

Attribute	Description	
Name	UNADVISED	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ISSUERCUSTOMER

Attribute	Description	
Name	ISSUERCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

TREASURYCUSTOMER

Attribute	Description	
Name	TREASURYCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERREFNO

Attribute	Description	
Name	USERREFNO	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	50

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

RECSTAT

Attribute	Description
Name	RECSTAT

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		

Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

2.12.2.CO-CustomerDelete-Req-IO-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

Customer-IO

CUSTOMERNO

MODNO

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description
Name	USERID
Datatype	String

Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	

Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	

Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description	
Name	VALUE	
Datatype	String	
Description	The value of the additional parameter comes here.	

[TOP](#)

FCUBS_BODY

Attribute	Description	
Name	FCUBS_BODY	
Datatype		
Description		

[TOP](#)

Customer-IO

Attribute	Description	
Name	Customer-IO	
Datatype		
Description		

[TOP](#)

CUSTOMERNO

Attribute	Description				
Name	CUSTOMERNO				
Datatype	String				
Description					
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>9</td></tr></tbody></table>	Restrictions	Description	maxLength	9
	Restrictions	Description			
maxLength	9				

[TOP](#)

MODNO

Attribute	Description				
Name	MODNO				
Datatype	Number				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				

[TOP](#)

2.12.3.CO-CustomerDelete-Res-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

Customer-Full

CUSTOMERNO

CUSTOMERTYPE

CUSTOMERNAME1

ADDRESSLINE1

ADDRESSLINE3

ADDRESSLINE2

ADDRESSLINE4

COUNTRY

SHORTNAME

NATIONALITY

LANGUAGE

EXPOSURECOUNTRY

LOCALBRANCH

UNIQUEIDNAME

UNIQUEIDVALUE

FROZEN

DECEASED

CUSTOMERCATEGORY

SSN

LOCCODE
 FULLNAME
 GROUPCODE
 FAXNUMBER
 CRMCUSTOMER
 CREDITRATING
 REVISIONDATE
 SHORTNAME2
 UNADVISED
 ISSUERCUSTOMER
 TREASURYCUSTOMER
 SOURCE
 USERREFNO
 MAKERID
 MAKERDTSTAMP
 CHECKERID
 CHECKERDTSTAMP
 MODNO
 AUTHSTAT
 RECSTAT
 ONCEAUTH
 UDFDETAILS
 FUNCTIONID
 FIELD_NAME
 DATATYPE
 FIELD_VALUE
 VAL_TYPE
 FCUBS_ERROR_RESP
 ERROR
 ECODE
 EDESC
 FCUBS_WARNING_RESP
 WARNING
 WCODE
 WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description
-----------	-------------

Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description				
Name	MULTITRIPID				
Datatype	String				
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

FUNCTIONID

Attribute	Description						
Name	FUNCTIONID						
Datatype	String						
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.						
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0		
	Attribute	Description					
minOccurs	0						
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>8</td></tr><tr><td>pattern</td><td>[A-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	maxLength	8	pattern	[A-Z_0-9]*
	Restrictions	Description					
	maxLength	8					
pattern	[A-Z_0-9]*						

[TOP](#)

ACTION

Attribute	Description				
Name	ACTION				
Datatype	String				
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

MSGSTAT

Attribute	Description				
Name	MSGSTAT				
Datatype	String				
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				

Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

Customer-Full

Attribute	Description
Name	Customer-Full

Datatype	
Description	

[TOP](#)

CUSTOMERNO

Attribute	Description	
Name	CUSTOMERNO	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	9

[TOP](#)

CUSTOMERTYPE

Attribute	Description	
Name	CUSTOMERTYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	B,C,I

[TOP](#)

CUSTOMERNAME1

Attribute	Description	
Name	CUSTOMERNAME1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

ADDRESSLINE1

Attribute	Description	
Name	ADDRESSLINE1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	105

ADDRESSLINE3

Attribute	Description	
Name	ADDRESSLINE3	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

ADDRESSLINE2

Attribute	Description	
Name	ADDRESSLINE2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

ADDRESSLINE4

Attribute	Description	
Name	ADDRESSLINE4	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

COUNTRY

Attribute	Description	
Name	COUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

SHORTNAME

Attribute	Description	
Name	SHORTNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

NATIONALITY

Attribute	Description	
Name	NATIONALITY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LANGUAGE

Attribute	Description	
Name	LANGUAGE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

EXPOSURECOUNTRY

Attribute	Description	
Name	EXPOSURECOUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LOCALBRANCH

Attribute	Description
Name	LOCALBRANCH

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

UNIQUEIDNAME

Attribute	Description	
Name	UNIQUEIDNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

UNIQUEIDVALUE

Attribute	Description	
Name	UNIQUEIDVALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

FROZEN

Attribute	Description	
Name	FROZEN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

DECEASED

Attribute	Description	
Name	DECEASED	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CUSTOMERCATEGORY

Attribute	Description	
Name	CUSTOMERCATEGORY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

SSN

Attribute	Description	
Name	SSN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	11

[TOP](#)

LOCCODE

Attribute	Description	
Name	LOCCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

FULLNAME

Attribute	Description	
Name	FULLNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

GROUPCODE

Attribute	Description	
Name	GROUPCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

FAXNUMBER

Attribute	Description	
Name	FAXNUMBER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

CRMCUSTOMER

Attribute	Description	
Name	CRMCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CREDITRATING

Attribute	Description	
Name	CREDITRATING	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)**REVISIONDATE**

Attribute	Description	
Name	REVISIONDATE	
Datatype	Date	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)**SHORTNAME2**

Attribute	Description	
Name	SHORTNAME2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)**UNADVISED**

Attribute	Description	
Name	UNADVISED	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)**ISSUERCUSTOMER**

Attribute	Description	
Name	ISSUERCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)**TREASURYCUSTOMER**

Attribute	Description
Name	TREASURYCUSTOMER

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERREFNO

Attribute	Description	
Name	USERREFNO	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	50

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description	
Name	ERROR	
Datatype		
Description	This indicates the type of error encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

ECODE

Attribute	Description	
Name	ECODE	
Datatype	String	
Description	This indicates the code for the error encountered.	

[TOP](#)

EDESC

Attribute	Description	
Name	EDESC	
Datatype	String	
Description	This indicates the description of the error encountered.	

[TOP](#)

FCUBS_WARNING_RESP

Attribute	Description	
Name	FCUBS_WARNING_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

WARNING

Attribute	Description	
Name	WARNING	
Datatype		
Description	Indicates the warning encountered.	

Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

[TOP](#)

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

[TOP](#)

2.12.4.CO-CustomerDelete-Res-PK-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

Customer-PK

CUSTOMERNO

MODNO

FCUBS_ERROR_RESP

ERROR

ECODE

EDESC

FCUBS_WARNING_RESP

WARNING

WCODE

WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description
-----------	-------------

Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description				
Name	MULTITRIPID				
Datatype	String				
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

FUNCTIONID

Attribute	Description						
Name	FUNCTIONID						
Datatype	String						
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.						
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0		
	Attribute	Description					
minOccurs	0						
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>8</td></tr><tr><td>pattern</td><td>[A-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	maxLength	8	pattern	[A-Z_0-9]*
	Restrictions	Description					
	maxLength	8					
pattern	[A-Z_0-9]*						

[TOP](#)

ACTION

Attribute	Description				
Name	ACTION				
Datatype	String				
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

MSGSTAT

Attribute	Description				
Name	MSGSTAT				
Datatype	String				
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				

Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description	
Name	VALUE	
Datatype	String	
Description	The value of the additional parameter comes here.	

[TOP](#)

FCUBS_BODY

Attribute	Description	
Name	FCUBS_BODY	
Datatype		
Description		

[TOP](#)

Customer-PK

Attribute	Description	
Name	Customer-PK	

Datatype	
Description	

[TOP](#)

CUSTOMERNO

Attribute	Description	
Name	CUSTOMERNO	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	9

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description	
Name	ERROR	
Datatype		
Description	This indicates the type of error encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

ECODE

Attribute	Description	
Name	ECODE	
Datatype	String	
Description	This indicates the code for the error encountered.	

[TOP](#)

EDESC

Attribute	Description
Name	EDESC
Datatype	String
Description	This indicates the description of the error encountered.

[TOP](#)

FCUBS_WARNING_RESP

Attribute	Description	
Name	FCUBS_WARNING_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

WARNING

Attribute	Description	
Name	WARNING	
Datatype		
Description	Indicates the warning encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

[TOP](#)

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

[TOP](#)

2.13.CustomerModify

Modify Customer

2.13.1.CO-CustomerModify-Req-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

Customer-Full

CUSTOMERNO

CUSTOMERTYPE

CUSTOMERNAME1

ADDRESSLINE1

ADDRESSLINE3

ADDRESSLINE2

ADDRESSLINE4

COUNTRY

SHORTNAME

NATIONALITY

LANGUAGE

EXPOSURECOUNTRY

LOCALBRANCH

UNIQUEIDNAME

UNIQUEIDVALUE

FROZEN

DECEASED
 CUSTOMERCATEGORY
 SSN
 LOCCODE
 FULLNAME
 GROUPCODE
 FAXNUMBER
 CRMCUSTOMER
 CREDITRATING
 REVISIONDATE
 SHORTNAME2
 UNADVISED
 ISSUERCUSTOMER
 TREASURYCUSTOMER
 SOURCE
 USERREFNO
 MAKERID
 MAKERDTSTAMP
 CHECKERID
 CHECKERDTSTAMP
 MODNO
 AUTHSTAT
 RECSTAT
 ONCEAUTH
 UDFDETAILS
 FUNCTIONID
 FIELD_NAME
 DATATYPE
 FIELD_VALUE
 VAL_TYPE

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description
Name	SOURCE
Datatype	String
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".

Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description
Name	OPERATION

Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description
Name	MULTITRIPID

Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description	
Name	VALUE	
Datatype	String	
Description	The value of the additional parameter comes here.	

[TOP](#)

FCUBS_BODY

Attribute	Description	
Name	FCUBS_BODY	
Datatype		
Description		

[TOP](#)

Customer-Full

Attribute	Description	
Name	Customer-Full	
Datatype		
Description		

[TOP](#)

CUSTOMERNO

Attribute	Description				
Name	CUSTOMERNO				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>1</td></tr></tbody></table>	Attribute	Description	minOccurs	1
	Attribute	Description			
minOccurs	1				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>9</td></tr></tbody></table>	Restrictions	Description	maxLength	9
	Restrictions	Description			
maxLength	9				

[TOP](#)

CUSTOMERTYPE

Attribute	Description				
Name	CUSTOMERTYPE				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>enumeration</td><td>B,C,I</td></tr></tbody></table>	Restrictions	Description	enumeration	B,C,I
	Restrictions	Description			
enumeration	B,C,I				

[TOP](#)

CUSTOMERNAME1

Attribute	Description				
Name	CUSTOMERNAME1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>105</td></tr></tbody></table>	Restrictions	Description	maxLength	105
	Restrictions	Description			
maxLength	105				

[TOP](#)

ADDRESSLINE1

Attribute	Description				
Name	ADDRESSLINE1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>1</td></tr></tbody></table>	Attribute	Description	minOccurs	1
	Attribute	Description			
minOccurs	1				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>105</td></tr></tbody></table>	Restrictions	Description	maxLength	105
	Restrictions	Description			
maxLength	105				

[TOP](#)

ADDRESSLINE3

Attribute	Description
-----------	-------------

Name	ADDRESSLINE3	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

ADDRESSLINE2

Attribute	Description	
Name	ADDRESSLINE2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

ADDRESSLINE4

Attribute	Description	
Name	ADDRESSLINE4	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

COUNTRY

Attribute	Description	
Name	COUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

SHORTNAME

Attribute	Description	
Name	SHORTNAME	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

NATIONALITY

Attribute	Description	
Name	NATIONALITY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LANGUAGE

Attribute	Description	
Name	LANGUAGE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

EXPOSURECOUNTRY

Attribute	Description	
Name	EXPOSURECOUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LOCALBRANCH

Attribute	Description	
Name	LOCALBRANCH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

UNIQUEIDNAME

Attribute	Description	
Name	UNIQUEIDNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

UNIQUEIDVALUE

Attribute	Description	
Name	UNIQUEIDVALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

FROZEN

Attribute	Description	
Name	FROZEN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

DECEASED

Attribute	Description	
Name	DECEASED	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

CUSTOMERCATEGORY

Attribute	Description	
Name	CUSTOMERCATEGORY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	10

SSN

Attribute	Description	
Name	SSN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	11

LOCCODE

Attribute	Description	
Name	LOCCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

FULLNAME

Attribute	Description	
Name	FULLNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

GROUPCODE

Attribute	Description	
Name	GROUPCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

FAXNUMBER

Attribute	Description	
Name	FAXNUMBER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

CRMCUSTOMER

Attribute	Description	
Name	CRMCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CREDITRATING

Attribute	Description	
Name	CREDITRATING	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

REVISIONDATE

Attribute	Description
Name	REVISIONDATE

Datatype	Date	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SHORTNAME2

Attribute	Description	
Name	SHORTNAME2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

UNADVISED

Attribute	Description	
Name	UNADVISED	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ISSUERCUSTOMER

Attribute	Description	
Name	ISSUERCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

TREASURYCUSTOMER

Attribute	Description	
Name	TREASURYCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERREFNO

Attribute	Description	
Name	USERREFNO	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	50

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

RECSTAT

Attribute	Description
Name	RECSTAT

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		

Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

2.13.2.CO-CustomerModify-Req-IO-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

Customer-IO

CUSTOMERNO

CUSTOMERTYPE

CUSTOMERNAME1

ADDRESSLINE1

ADDRESSLINE3

ADDRESSLINE2

ADDRESSLINE4

COUNTRY

SHORTNAME

NATIONALITY

LANGUAGE

EXPOSURECOUNTRY

LOCALBRANCH

UNIQUEIDNAME

UNIQUEIDVALUE

FROZEN

DECEASED

CUSTOMERCATEGORY

SSN

LOCCODE
 FULLNAME
 GROUPCODE
 FAXNUMBER
 CRMCUSTOMER
 CREDITRATING
 REVISIONDATE
 SHORTNAME2
 UNADVISED
 ISSUERCUSTOMER
 TREASURYCUSTOMER
 SOURCE
 USERREFNO
 MAKERID
 MAKERDTSTAMP
 CHECKERID
 CHECKERDTSTAMP
 MODNO
 AUTHSTAT
 RECSTAT
 ONCEAUTH
 UDFDETAILS
 FUNCTIONID
 FIELD_NAME
 DATATYPE
 FIELD_VALUE
 VAL_TYPE

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description
Name	USERID
Datatype	String

Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	

Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	

Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description	
Name	VALUE	
Datatype	String	
Description	The value of the additional parameter comes here.	

[TOP](#)

FCUBS_BODY

Attribute	Description	
Name	FCUBS_BODY	
Datatype		
Description		

[TOP](#)

Customer-IO

Attribute	Description	
Name	Customer-IO	
Datatype		
Description		

[TOP](#)

CUSTOMERNO

Attribute	Description				
Name	CUSTOMERNO				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>1</td></tr></tbody></table>	Attribute	Description	minOccurs	1
	Attribute	Description			
minOccurs	1				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>9</td></tr></tbody></table>	Restrictions	Description	maxLength	9
	Restrictions	Description			
maxLength	9				

[TOP](#)

CUSTOMERTYPE

Attribute	Description				
Name	CUSTOMERTYPE				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>enumeration</td><td>B,C,I</td></tr></tbody></table>	Restrictions	Description	enumeration	B,C,I
	Restrictions	Description			
enumeration	B,C,I				

[TOP](#)

CUSTOMERNAME1

Attribute	Description				
Name	CUSTOMERNAME1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>105</td></tr></tbody></table>	Restrictions	Description	maxLength	105
	Restrictions	Description			
maxLength	105				

[TOP](#)

ADDRESSLINE1

Attribute	Description				
Name	ADDRESSLINE1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>1</td></tr></tbody></table>	Attribute	Description	minOccurs	1
	Attribute	Description			
minOccurs	1				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>105</td></tr></tbody></table>	Restrictions	Description	maxLength	105
	Restrictions	Description			
maxLength	105				

[TOP](#)

ADDRESSLINE3

Attribute	Description
-----------	-------------

Name	ADDRESSLINE3	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

ADDRESSLINE2

Attribute	Description	
Name	ADDRESSLINE2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

ADDRESSLINE4

Attribute	Description	
Name	ADDRESSLINE4	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

COUNTRY

Attribute	Description	
Name	COUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

SHORTNAME

Attribute	Description	
Name	SHORTNAME	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

NATIONALITY

Attribute	Description	
Name	NATIONALITY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LANGUAGE

Attribute	Description	
Name	LANGUAGE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

EXPOSURECOUNTRY

Attribute	Description	
Name	EXPOSURECOUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LOCALBRANCH

Attribute	Description	
Name	LOCALBRANCH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

UNIQUEIDNAME

Attribute	Description	
Name	UNIQUEIDNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

UNIQUEIDVALUE

Attribute	Description	
Name	UNIQUEIDVALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

FROZEN

Attribute	Description	
Name	FROZEN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

DECEASED

Attribute	Description	
Name	DECEASED	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

CUSTOMERCATEGORY

Attribute	Description	
Name	CUSTOMERCATEGORY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	10

SSN

Attribute	Description	
Name	SSN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	11

LOCCODE

Attribute	Description	
Name	LOCCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

FULLNAME

Attribute	Description	
Name	FULLNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

GROUPCODE

Attribute	Description	
Name	GROUPCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

FAXNUMBER

Attribute	Description	
Name	FAXNUMBER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

CRMCUSTOMER

Attribute	Description	
Name	CRMCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CREDITRATING

Attribute	Description	
Name	CREDITRATING	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

REVISIONDATE

Attribute	Description
Name	REVISIONDATE

Datatype	Date	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SHORTNAME2

Attribute	Description	
Name	SHORTNAME2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

UNADVISED

Attribute	Description	
Name	UNADVISED	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ISSUERCUSTOMER

Attribute	Description	
Name	ISSUERCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

TREASURYCUSTOMER

Attribute	Description	
Name	TREASURYCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERREFNO

Attribute	Description	
Name	USERREFNO	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	50

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

RECSTAT

Attribute	Description	
Name	RECSTAT	

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		

Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

2.13.3.CO-CustomerModify-Res-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

Customer-Full

CUSTOMERNO

CUSTOMERTYPE

CUSTOMERNAME1

ADDRESSLINE1

ADDRESSLINE3

ADDRESSLINE2

ADDRESSLINE4

COUNTRY

SHORTNAME

NATIONALITY

LANGUAGE

EXPOSURECOUNTRY

LOCALBRANCH

UNIQUEIDNAME

UNIQUEIDVALUE

FROZEN

DECEASED

CUSTOMERCATEGORY

SSN

LOCCODE
 FULLNAME
 GROUPCODE
 FAXNUMBER
 CRMCUSTOMER
 CREDITRATING
 REVISIONDATE
 SHORTNAME2
 UNADVISED
 ISSUERCUSTOMER
 TREASURYCUSTOMER
 SOURCE
 USERREFNO
 MAKERID
 MAKERDTSTAMP
 CHECKERID
 CHECKERDTSTAMP
 MODNO
 AUTHSTAT
 RECSTAT
 ONCEAUTH
 UDFDETAILS
 FUNCTIONID
 FIELD_NAME
 DATATYPE
 FIELD_VALUE
 VAL_TYPE
 FCUBS_ERROR_RESP
 ERROR
 ECODE
 EDESC
 FCUBS_WARNING_RESP
 WARNING
 WCODE
 WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description
-----------	-------------

Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description				
Name	MULTITRIPID				
Datatype	String				
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

FUNCTIONID

Attribute	Description						
Name	FUNCTIONID						
Datatype	String						
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.						
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0		
	Attribute	Description					
minOccurs	0						
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>8</td></tr><tr><td>pattern</td><td>[A-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	maxLength	8	pattern	[A-Z_0-9]*
	Restrictions	Description					
	maxLength	8					
pattern	[A-Z_0-9]*						

[TOP](#)

ACTION

Attribute	Description				
Name	ACTION				
Datatype	String				
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

MSGSTAT

Attribute	Description				
Name	MSGSTAT				
Datatype	String				
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				

Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

Customer-Full

Attribute	Description
Name	Customer-Full

Datatype	
Description	

[TOP](#)

CUSTOMERNO

Attribute	Description	
Name	CUSTOMERNO	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	9

[TOP](#)

CUSTOMERTYPE

Attribute	Description	
Name	CUSTOMERTYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	B,C,I

[TOP](#)

CUSTOMERNAME1

Attribute	Description	
Name	CUSTOMERNAME1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

ADDRESSLINE1

Attribute	Description	
Name	ADDRESSLINE1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	105

ADDRESSLINE3

Attribute	Description	
Name	ADDRESSLINE3	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

ADDRESSLINE2

Attribute	Description	
Name	ADDRESSLINE2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

ADDRESSLINE4

Attribute	Description	
Name	ADDRESSLINE4	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

COUNTRY

Attribute	Description	
Name	COUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

SHORTNAME

Attribute	Description	
Name	SHORTNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

NATIONALITY

Attribute	Description	
Name	NATIONALITY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LANGUAGE

Attribute	Description	
Name	LANGUAGE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

EXPOSURECOUNTRY

Attribute	Description	
Name	EXPOSURECOUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LOCALBRANCH

Attribute	Description
Name	LOCALBRANCH

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

UNIQUEIDNAME

Attribute	Description	
Name	UNIQUEIDNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

UNIQUEIDVALUE

Attribute	Description	
Name	UNIQUEIDVALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

FROZEN

Attribute	Description	
Name	FROZEN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

DECEASED

Attribute	Description	
Name	DECEASED	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CUSTOMERCATEGORY

Attribute	Description	
Name	CUSTOMERCATEGORY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

SSN

Attribute	Description	
Name	SSN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	11

[TOP](#)

LOCCODE

Attribute	Description	
Name	LOCCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

FULLNAME

Attribute	Description	
Name	FULLNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

GROUPCODE

Attribute	Description	
Name	GROUPCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

FAXNUMBER

Attribute	Description	
Name	FAXNUMBER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

CRMCUSTOMER

Attribute	Description	
Name	CRMCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CREDITRATING

Attribute	Description	
Name	CREDITRATING	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

REVISIONDATE

Attribute	Description	
Name	REVISIONDATE	
Datatype	Date	
Description		
Attributes	Attribute	Description
	minOccurs	0

SHORTNAME2

Attribute	Description	
Name	SHORTNAME2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

UNADVISED

Attribute	Description	
Name	UNADVISED	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

ISSUERCUSTOMER

Attribute	Description	
Name	ISSUERCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

TREASURYCUSTOMER

Attribute	Description
Name	TREASURYCUSTOMER

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERREFNO

Attribute	Description	
Name	USERREFNO	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	50

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description	
Name	ERROR	
Datatype		
Description	This indicates the type of error encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

ECODE

Attribute	Description	
Name	ECODE	
Datatype	String	
Description	This indicates the code for the error encountered.	

[TOP](#)

EDESC

Attribute	Description	
Name	EDESC	
Datatype	String	
Description	This indicates the description of the error encountered.	

[TOP](#)

FCUBS_WARNING_RESP

Attribute	Description	
Name	FCUBS_WARNING_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

WARNING

Attribute	Description	
Name	WARNING	
Datatype		
Description	Indicates the warning encountered.	

Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

[TOP](#)

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

[TOP](#)

2.13.4.CO-CustomerModify-Res-PK-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

Customer-PK

CUSTOMERNO

MODNO

FCUBS_ERROR_RESP

ERROR

ECODE

EDESC

FCUBS_WARNING_RESP

WARNING

WCODE

WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description
-----------	-------------

Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description				
Name	MULTITRIPID				
Datatype	String				
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

FUNCTIONID

Attribute	Description						
Name	FUNCTIONID						
Datatype	String						
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.						
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0		
	Attribute	Description					
minOccurs	0						
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>8</td></tr><tr><td>pattern</td><td>[A-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	maxLength	8	pattern	[A-Z_0-9]*
	Restrictions	Description					
	maxLength	8					
pattern	[A-Z_0-9]*						

[TOP](#)

ACTION

Attribute	Description				
Name	ACTION				
Datatype	String				
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>pattern</td><td>[a-zA-Z_0-9]*</td></tr></tbody></table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

MSGSTAT

Attribute	Description				
Name	MSGSTAT				
Datatype	String				
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				

Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

Customer-PK

Attribute	Description
Name	Customer-PK

Datatype	
Description	

[TOP](#)

CUSTOMERNO

Attribute	Description	
Name	CUSTOMERNO	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	9

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description	
Name	ERROR	
Datatype		
Description	This indicates the type of error encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

ECODE

Attribute	Description	
Name	ECODE	
Datatype	String	
Description	This indicates the code for the error encountered.	

[TOP](#)

EDESC

Attribute	Description
Name	EDESC
Datatype	String
Description	This indicates the description of the error encountered.

[TOP](#)

FCUBS_WARNING_RESP

Attribute	Description						
Name	FCUBS_WARNING_RESP						
Datatype							
Description							
Attributes	<table border="1"> <thead> <tr> <th>Attribute</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>maxOccurs</td> <td>unbounded</td> </tr> <tr> <td>minOccurs</td> <td>0</td> </tr> </tbody> </table>	Attribute	Description	maxOccurs	unbounded	minOccurs	0
Attribute	Description						
maxOccurs	unbounded						
minOccurs	0						

[TOP](#)

WARNING

Attribute	Description				
Name	WARNING				
Datatype					
Description	Indicates the warning encountered.				
Attributes	<table border="1"> <thead> <tr> <th>Attribute</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>maxOccurs</td> <td>unbounded</td> </tr> </tbody> </table>	Attribute	Description	maxOccurs	unbounded
Attribute	Description				
maxOccurs	unbounded				

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

[TOP](#)

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

[TOP](#)

2.14.CustomerQuery

Query Of Customer

2.14.1.CO-CustomerQuery-Req-IO-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

Customer-IO

CUSTOMERNO

MODNO

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description
Name	SOURCE
Datatype	String
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".

Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description
Name	OPERATION

Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description
Name	MULTITRIPID

Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description	
Name	VALUE	
Datatype	String	
Description	The value of the additional parameter comes here.	

[TOP](#)

FCUBS_BODY

Attribute	Description	
Name	FCUBS_BODY	
Datatype		
Description		

[TOP](#)

Customer-IO

Attribute	Description	
Name	Customer-IO	
Datatype		
Description		

[TOP](#)

CUSTOMERNO

Attribute	Description				
Name	CUSTOMERNO				
Datatype	String				
Description					
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>9</td></tr></tbody></table>	Restrictions	Description	maxLength	9
	Restrictions	Description			
maxLength	9				

[TOP](#)

MODNO

Attribute	Description				
Name	MODNO				
Datatype	Number				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				

[TOP](#)

2.14.2.CO-CustomerQuery-Res-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

Customer-Full

CUSTOMERNO

CUSTOMERTYPE

CUSTOMERNAME1

ADDRESSLINE1

ADDRESSLINE3

ADDRESSLINE2

ADDRESSLINE4

COUNTRY

SHORTNAME

NATIONALITY

LANGUAGE

EXPOSURECOUNTRY

LOCALBRANCH

UNIQUEIDNAME

UNIQUEIDVALUE

FROZEN

DECEASED

CUSTOMERCATEGORY

SSN

LOCCODE
 FULLNAME
 GROUPCODE
 FAXNUMBER
 CRMCUSTOMER
 CREDITRATING
 REVISIONDATE
 SHORTNAME2
 UNADVISED
 ISSUERCUSTOMER
 TREASURYCUSTOMER
 SOURCE
 USERREFNO
 MAKERID
 MAKERDTSTAMP
 CHECKERID
 CHECKERDTSTAMP
 MODNO
 AUTHSTAT
 RECSTAT
 ONCEAUTH
 UDFDETAILS
 FUNCTIONID
 FIELD_NAME
 DATATYPE
 FIELD_VALUE
 VAL_TYPE
 FCUBS_ERROR_RESP
 ERROR
 ECODE
 EDESC
 FCUBS_WARNING_RESP
 WARNING
 WCODE
 WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description
-----------	-------------

Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description	
Name	VALUE	
Datatype	String	
Description	The value of the additional parameter comes here.	

[TOP](#)

FCUBS_BODY

Attribute	Description	
Name	FCUBS_BODY	
Datatype		
Description		

[TOP](#)

Customer-Full

Attribute	Description	
Name	Customer-Full	

Datatype	
Description	

[TOP](#)

CUSTOMERNO

Attribute	Description	
Name	CUSTOMERNO	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	9

[TOP](#)

CUSTOMERTYPE

Attribute	Description	
Name	CUSTOMERTYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	B,C,I

[TOP](#)

CUSTOMERNAME1

Attribute	Description	
Name	CUSTOMERNAME1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

ADDRESSLINE1

Attribute	Description	
Name	ADDRESSLINE1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	105

ADDRESSLINE3

Attribute	Description	
Name	ADDRESSLINE3	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

ADDRESSLINE2

Attribute	Description	
Name	ADDRESSLINE2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

ADDRESSLINE4

Attribute	Description	
Name	ADDRESSLINE4	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

COUNTRY

Attribute	Description	
Name	COUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

SHORTNAME

Attribute	Description	
Name	SHORTNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

NATIONALITY

Attribute	Description	
Name	NATIONALITY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LANGUAGE

Attribute	Description	
Name	LANGUAGE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

EXPOSURECOUNTRY

Attribute	Description	
Name	EXPOSURECOUNTRY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

LOCALBRANCH

Attribute	Description
Name	LOCALBRANCH

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

UNIQUEIDNAME

Attribute	Description	
Name	UNIQUEIDNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

UNIQUEIDVALUE

Attribute	Description	
Name	UNIQUEIDVALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)

FROZEN

Attribute	Description	
Name	FROZEN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

DECEASED

Attribute	Description	
Name	DECEASED	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CUSTOMERCATEGORY

Attribute	Description	
Name	CUSTOMERCATEGORY	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	1
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

SSN

Attribute	Description	
Name	SSN	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	11

[TOP](#)

LOCCODE

Attribute	Description	
Name	LOCCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

FULLNAME

Attribute	Description	
Name	FULLNAME	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

GROUPCODE

Attribute	Description	
Name	GROUPCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)

FAXNUMBER

Attribute	Description	
Name	FAXNUMBER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	105

[TOP](#)

CRMCUSTOMER

Attribute	Description	
Name	CRMCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

CREDITRATING

Attribute	Description	
Name	CREDITRATING	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	10

[TOP](#)**REVISIONDATE**

Attribute	Description	
Name	REVISIONDATE	
Datatype	Date	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)**SHORTNAME2**

Attribute	Description	
Name	SHORTNAME2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	20

[TOP](#)**UNADVISED**

Attribute	Description	
Name	UNADVISED	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)**ISSUERCUSTOMER**

Attribute	Description	
Name	ISSUERCUSTOMER	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)**TREASURYCUSTOMER**

Attribute	Description
Name	TREASURYCUSTOMER

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERREFNO

Attribute	Description	
Name	USERREFNO	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	50

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description	
Name	ERROR	
Datatype		
Description	This indicates the type of error encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

ECODE

Attribute	Description	
Name	ECODE	
Datatype	String	
Description	This indicates the code for the error encountered.	

[TOP](#)

EDESC

Attribute	Description	
Name	EDESC	
Datatype	String	
Description	This indicates the description of the error encountered.	

[TOP](#)

FCUBS_WARNING_RESP

Attribute	Description	
Name	FCUBS_WARNING_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

WARNING

Attribute	Description	
Name	WARNING	
Datatype		
Description	Indicates the warning encountered.	

Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

[TOP](#)

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

[TOP](#)

2.15.CCYPairAuth

CCYPairAuth

2.15.1.CO-CCYRatesAuth-Req-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

RatesMaster-Full

BRANCHCODE

CCY1

CCY2

MAKERID

MAKERDTSTAMP

CHECKERID

CHECKERDTSTAMP

MODNO

AUTHSTAT

RECSTAT

ONCEAUTH

Rates

RATETYPE

MIDRATE

BUYSPREAD

SALESPREAD

[BUYRATE](#)
[SALERATE](#)
[UDFDETAILS](#)
[FUNCTIONID](#)
[FIELD_NAME](#)
[DATATYPE](#)
[FIELD_VALUE](#)
[VAL_TYPE](#)

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description
Name	MSGID
Datatype	String
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.

Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description
------------------	--------------------

Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTIRIPID

Attribute	Description	
Name	MULTIRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTIRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

NAME

Attribute	Description
Name	NAME

Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

RatesMaster-Full

Attribute	Description
Name	RatesMaster-Full
Datatype	
Description	

[TOP](#)

BRANCHCODE

Attribute	Description				
Name	BRANCHCODE				
Datatype	String				
Description					
Attributes	<table border="1"> <thead> <tr> <th>Attribute</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>minOccurs</td> <td>0</td> </tr> </tbody> </table>	Attribute	Description	minOccurs	0
Attribute	Description				
minOccurs	0				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>maxLength</td> <td>3</td> </tr> </tbody> </table>	Restrictions	Description	maxLength	3
Restrictions	Description				
maxLength	3				

[TOP](#)

CCY1

Attribute	Description				
Name	CCY1				
Datatype	String				
Description					
Attributes	<table border="1"> <thead> <tr> <th>Attribute</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>minOccurs</td> <td>1</td> </tr> </tbody> </table>	Attribute	Description	minOccurs	1
Attribute	Description				
minOccurs	1				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>maxLength</td> <td>3</td> </tr> </tbody> </table>	Restrictions	Description	maxLength	3
Restrictions	Description				
maxLength	3				

[TOP](#)

CCY2

Attribute	Description				
Name	CCY2				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

MAKERID

Attribute	Description				
Name	MAKERID				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>12</td></tr></tbody></table>	Restrictions	Description	maxLength	12
	Restrictions	Description			
maxLength	12				

[TOP](#)

MAKERDTSTAMP

Attribute	Description				
Name	MAKERDTSTAMP				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>25</td></tr></tbody></table>	Restrictions	Description	maxLength	25
	Restrictions	Description			
maxLength	25				

[TOP](#)

CHECKERID

Attribute	Description				
Name	CHECKERID				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>12</td></tr></tbody></table>	Restrictions	Description	maxLength	12
	Restrictions	Description			
maxLength	12				

[TOP](#)

CHECKERDTSTAMP

Attribute	Description
-----------	-------------

Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

Rates

Attribute	Description	
Name	Rates	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

RATETYPE

Attribute	Description	
Name	RATETYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8

[TOP](#)

MIDRATE

Attribute	Description	
Name	MIDRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYSPREAD

Attribute	Description	
Name	BUYSPREAD	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALESPREAD

Attribute	Description	
Name	SALESPREAD	
Datatype	Number	

Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYRATE

Attribute	Description	
Name	BUYRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALERATE

Attribute	Description	
Name	SALERATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

2.15.2.CO-CCYRatesAuth-Req-IO-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

RatesMaster-IO

BRANCHCODE

CCY1

CCY2

MODNO

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

USERID

Attribute	Description	
Name	USERID	
Datatype	String	

Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	

Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	

Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description	
Name	VALUE	
Datatype	String	
Description	The value of the additional parameter comes here.	

[TOP](#)

FCUBS_BODY

Attribute	Description	
Name	FCUBS_BODY	
Datatype		
Description		

[TOP](#)

RatesMaster-IO

Attribute	Description	
Name	RatesMaster-IO	
Datatype		
Description		

[TOP](#)

BRANCHCODE

Attribute	Description				
Name	BRANCHCODE				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

CCY1

Attribute	Description				
Name	CCY1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

CCY2

Attribute	Description				
Name	CCY2				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

MODNO

Attribute	Description				
Name	MODNO				
Datatype	Number				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>totalDigits</td><td>22</td></tr></tbody></table>	Restrictions	Description	totalDigits	22
	Restrictions	Description			
totalDigits	22				

[TOP](#)

2.15.3.CO-CCYRatesAuth-Res-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

CHOICE

RatesMaster-IO

BRANCHCODE

CCY1

CCY2

MODNO

RatesMaster-Full

BRANCHCODE

CCY1

CCY2

MAKERID

MAKERDTSTAMP

CHECKERID

CHECKERDTSTAMP

MODNO

AUTHSTAT

RECSTAT

ONCEAUTH

Rates

RATETYPE

MIDRATE
 BUYSREAD
 SALESPREAD
 BUYRATE
 SALERATE
 UDFDETAILS
 FUNCTIONID
 FIELD_NAME
 DATATYPE
 FIELD_VALUE
 VAL_TYPE
 FCUBS_ERROR_RESP
 ERROR
 ECODE
 EDESC
 FCUBS_WARNING_RESP
 WARNING
 WCODE
 WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description				
Name	SOURCE				
Datatype	String				
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>pattern</td> <td>[a-zA-Z_0-9]*</td> </tr> </tbody> </table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
Restrictions	Description				
pattern	[a-zA-Z_0-9]*				

[TOP](#)

UBSCOMP

Attribute	Description
Name	UBSCOMP
Datatype	String
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.

Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description
-----------	-------------

Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	

Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description
Name	FUNCTIONID

Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	

Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

CHOICE

Attribute	Description
Name	CHOICE
Datatype	
Description	

[TOP](#)

RatesMaster-IO

Attribute	Description
Name	RatesMaster-IO
Datatype	
Description	

[TOP](#)

BRANCHCODE

Attribute	Description	
Name	BRANCHCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY1

Attribute	Description	
Name	CCY1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY2

Attribute	Description	
Name	CCY2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	totalDigits	22

[TOP](#)

RatesMaster-Full

Attribute	Description
Name	RatesMaster-Full
Datatype	
Description	

[TOP](#)

BRANCHCODE

Attribute	Description
Name	BRANCHCODE

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY1

Attribute	Description	
Name	CCY1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY2

Attribute	Description	
Name	CCY2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	totalDigits	22

[TOP](#)

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

Rates

Attribute	Description	
Name	Rates	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

RATETYPE

Attribute	Description	
Name	RATETYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8

[TOP](#)

MIDRATE

Attribute	Description	
Name	MIDRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYSPREAD

Attribute	Description	
Name	BUYSPREAD	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALESPREAD

Attribute	Description	
Name	SALESPREAD	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYRATE

Attribute	Description	
Name	BUYRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALERATE

Attribute	Description	
Name	SALERATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description
Name	FIELD_VALUE

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description	
Name	ERROR	
Datatype		
Description	This indicates the type of error encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

ECODE

Attribute	Description	
Name	ECODE	
Datatype	String	
Description	This indicates the code for the error encountered.	

[TOP](#)

EDESC

Attribute	Description
Name	EDESC
Datatype	String
Description	This indicates the description of the error encountered.

[TOP](#)

FCUBS_WARNING_RESP

Attribute	Description						
Name	FCUBS_WARNING_RESP						
Datatype							
Description							
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>maxOccurs</td><td>unbounded</td></tr><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	maxOccurs	unbounded	minOccurs	0
Attribute	Description						
maxOccurs	unbounded						
minOccurs	0						

[TOP](#)

WARNING

Attribute	Description				
Name	WARNING				
Datatype					
Description	Indicates the warning encountered.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>maxOccurs</td><td>unbounded</td></tr></tbody></table>	Attribute	Description	maxOccurs	unbounded
Attribute	Description				
maxOccurs	unbounded				

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

[TOP](#)

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

[TOP](#)

2.15.4.CO-CCYRatesAuth-Res-PK-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

RatesMaster-PK

BRANCHCODE

CCY1

CCY2

FCUBS_ERROR_RESP

ERROR

ECODE

EDESC

FCUBS_WARNING_RESP

WARNING

WCODE

WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

RatesMaster-PK

Attribute	Description
Name	RatesMaster-PK

Datatype	
Description	

[TOP](#)

BRANCHCODE

Attribute	Description	
Name	BRANCHCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY1

Attribute	Description	
Name	CCY1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY2

Attribute	Description	
Name	CCY2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description				
Name	ERROR				
Datatype					
Description	This indicates the type of error encountered.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>maxOccurs</td><td>unbounded</td></tr></tbody></table>	Attribute	Description	maxOccurs	unbounded
	Attribute	Description			
maxOccurs	unbounded				

[TOP](#)

ECODE

Attribute	Description
Name	ECODE
Datatype	String
Description	This indicates the code for the error encountered.

[TOP](#)

EDESC

Attribute	Description
Name	EDESC
Datatype	String
Description	This indicates the description of the error encountered.

[TOP](#)

FCUBS_WARNING_RESP

Attribute	Description						
Name	FCUBS_WARNING_RESP						
Datatype							
Description							
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>maxOccurs</td><td>unbounded</td></tr><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	maxOccurs	unbounded	minOccurs	0
	Attribute	Description					
	maxOccurs	unbounded					
minOccurs	0						

[TOP](#)

WARNING

Attribute	Description				
Name	WARNING				
Datatype					
Description	Indicates the warning encountered.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>maxOccurs</td><td>unbounded</td></tr></tbody></table>	Attribute	Description	maxOccurs	unbounded
	Attribute	Description			
maxOccurs	unbounded				

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

2.16.CCYPairClose

CCYPairClose

2.16.1.CO-CCYRatesClose-Req-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

RatesMaster-Full

BRANCHCODE

CCY1

CCY2

MAKERID

MAKERDTSTAMP

CHECKERID

CHECKERDTSTAMP

MODNO

AUTHSTAT

RECSTAT

ONCEAUTH

Rates

RATETYPE

MIDRATE

BUYSPREAD

SALESPREAD

[BUYRATE](#)
[SALERATE](#)
[UDFDETAILS](#)
[FUNCTIONID](#)
[FIELD_NAME](#)
[DATATYPE](#)
[FIELD_VALUE](#)
[VAL_TYPE](#)

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description
Name	MSGID
Datatype	String
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.

Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description
------------------	--------------------

Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
	Restrictions	Description
Restrictions	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
	Restrictions	Description
Restrictions	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTIRIPID

Attribute	Description	
Name	MULTIRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTIRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

NAME

Attribute	Description
Name	NAME

Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

RatesMaster-Full

Attribute	Description
Name	RatesMaster-Full
Datatype	
Description	

[TOP](#)

BRANCHCODE

Attribute	Description				
Name	BRANCHCODE				
Datatype	String				
Description					
Attributes	<table border="1"> <thead> <tr> <th>Attribute</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>minOccurs</td> <td>0</td> </tr> </tbody> </table>	Attribute	Description	minOccurs	0
Attribute	Description				
minOccurs	0				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>maxLength</td> <td>3</td> </tr> </tbody> </table>	Restrictions	Description	maxLength	3
Restrictions	Description				
maxLength	3				

[TOP](#)

CCY1

Attribute	Description				
Name	CCY1				
Datatype	String				
Description					
Attributes	<table border="1"> <thead> <tr> <th>Attribute</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>minOccurs</td> <td>1</td> </tr> </tbody> </table>	Attribute	Description	minOccurs	1
Attribute	Description				
minOccurs	1				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>maxLength</td> <td>3</td> </tr> </tbody> </table>	Restrictions	Description	maxLength	3
Restrictions	Description				
maxLength	3				

[TOP](#)

CCY2

Attribute	Description				
Name	CCY2				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

MAKERID

Attribute	Description				
Name	MAKERID				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>12</td></tr></tbody></table>	Restrictions	Description	maxLength	12
	Restrictions	Description			
maxLength	12				

[TOP](#)

MAKERDTSTAMP

Attribute	Description				
Name	MAKERDTSTAMP				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>25</td></tr></tbody></table>	Restrictions	Description	maxLength	25
	Restrictions	Description			
maxLength	25				

[TOP](#)

CHECKERID

Attribute	Description				
Name	CHECKERID				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>12</td></tr></tbody></table>	Restrictions	Description	maxLength	12
	Restrictions	Description			
maxLength	12				

[TOP](#)

CHECKERDTSTAMP

Attribute	Description
-----------	-------------

Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

Rates

Attribute	Description	
Name	Rates	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

RATETYPE

Attribute	Description	
Name	RATETYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8

[TOP](#)

MIDRATE

Attribute	Description	
Name	MIDRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYSPREAD

Attribute	Description	
Name	BUYSPREAD	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALESPREAD

Attribute	Description	
Name	SALESPREAD	
Datatype	Number	

Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYRATE

Attribute	Description	
Name	BUYRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALERATE

Attribute	Description	
Name	SALERATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

2.16.2.CO-CCYRatesClose-Req-IO-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

RatesMaster-IO

BRANCHCODE

CCY1

CCY2

MODNO

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

USERID

Attribute	Description
Name	USERID
Datatype	String

Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	

Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	

Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description	
Name	VALUE	
Datatype	String	
Description	The value of the additional parameter comes here.	

[TOP](#)

FCUBS_BODY

Attribute	Description	
Name	FCUBS_BODY	
Datatype		
Description		

[TOP](#)

RatesMaster-IO

Attribute	Description	
Name	RatesMaster-IO	
Datatype		
Description		

[TOP](#)

BRANCHCODE

Attribute	Description				
Name	BRANCHCODE				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

CCY1

Attribute	Description				
Name	CCY1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

CCY2

Attribute	Description				
Name	CCY2				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

MODNO

Attribute	Description				
Name	MODNO				
Datatype	Number				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>totalDigits</td><td>22</td></tr></tbody></table>	Restrictions	Description	totalDigits	22
	Restrictions	Description			
totalDigits	22				

[TOP](#)

2.16.3.CO-CCYRatesClose-Res-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

RatesMaster-Full

BRANCHCODE

CCY1

CCY2

MAKERID

MAKERDTSTAMP

CHECKERID

CHECKERDTSTAMP

MODNO

AUTHSTAT

RECSTAT

ONCEAUTH

Rates

RATETYPE

MIDRATE

BUYSPREAD

SALESPREAD

BUYRATE

SALERATE

UDFDETAILS

FUNCTIONID
 FIELD_NAME
 DATATYPE
 FIELD_VALUE
 VAL_TYPE
 FCUBS_ERROR_RESP
 ERROR
 ECODE
 EDESC
 FCUBS_WARNING_RESP
 WARNING
 WCODE
 WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description				
Name	SOURCE				
Datatype	String				
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>pattern</td> <td>[a-zA-Z_0-9]*</td> </tr> </tbody> </table>	Restrictions	Description	pattern	[a-zA-Z_0-9]*
	Restrictions	Description			
pattern	[a-zA-Z_0-9]*				

[TOP](#)

UBSCOMP

Attribute	Description				
Name	UBSCOMP				
Datatype	String				
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>enumeration</td> <td>FCUBS,FCIS</td> </tr> </tbody> </table>	Restrictions	Description	enumeration	FCUBS,FCIS
	Restrictions	Description			
enumeration	FCUBS,FCIS				

[TOP](#)

MSGID

Attribute	Description
Name	MSGID

Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

SOURCE_USERID

Attribute		Description
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	
	minOccurs	0
	nullable	true

DESTINATION

Attribute		Description
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	
	minOccurs	0
Restrictions	Restrictions	
	pattern	[a-zA-Z_0-9]*

MULTITRIPID

Attribute		Description
Name	MULTITRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	
	minOccurs	0
Restrictions	Restrictions	
	pattern	[a-zA-Z_0-9]*

FUNCTIONID

Attribute		Description
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

RatesMaster-Full

Attribute	Description
Name	RatesMaster-Full
Datatype	
Description	

[TOP](#)

BRANCHCODE

Attribute	Description				
Name	BRANCHCODE				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

CCY1

Attribute	Description				
Name	CCY1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>1</td></tr></tbody></table>	Attribute	Description	minOccurs	1
	Attribute	Description			
minOccurs	1				

Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY2

Attribute	Description	
Name	CCY2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

ONCEAUTH

Attribute	Description
Name	ONCEAUTH

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

Rates

Attribute	Description	
Name	Rates	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

RATETYPE

Attribute	Description	
Name	RATETYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8

[TOP](#)

MIDRATE

Attribute	Description	
Name	MIDRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYSPREAD

Attribute	Description	
Name	BUYSPREAD	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALESPREAD

Attribute	Description	
Name	SALESPREAD	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYRATE

Attribute	Description	
Name	BUYRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALERATE

Attribute	Description	
Name	SALERATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)**FCUBS_ERROR_RESP**

Attribute		Description
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)**ERROR**

Attribute		Description
Name	ERROR	
Datatype		
Description	This indicates the type of error encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)**ECODE**

Attribute		Description
Name	ECODE	
Datatype	String	
Description	This indicates the code for the error encountered.	

[TOP](#)**EDESC**

Attribute		Description
Name	EDESC	
Datatype	String	
Description	This indicates the description of the error encountered.	

[TOP](#)**FCUBS_WARNING_RESP**

Attribute		Description
Name	FCUBS_WARNING_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)**WARNING**

Attribute	Description
-----------	-------------

Name	WARNING	
Datatype		
Description	Indicates the warning encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

[TOP](#)

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

[TOP](#)

2.16.4.CO-CCYRatesClose-Res-PK-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

RatesMaster-PK

BRANCHCODE

CCY1

CCY2

FCUBS_ERROR_RESP

ERROR

ECODE

EDESC

FCUBS_WARNING_RESP

WARNING

WCODE

WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	nillable	true
	pattern	[a-zA-Z_0-9]*

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	nillable	true

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

RatesMaster-PK

Attribute	Description
Name	RatesMaster-PK

Datatype	
Description	

[TOP](#)

BRANCHCODE

Attribute	Description	
Name	BRANCHCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY1

Attribute	Description	
Name	CCY1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY2

Attribute	Description	
Name	CCY2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description				
Name	ERROR				
Datatype					
Description	This indicates the type of error encountered.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>maxOccurs</td><td>unbounded</td></tr></tbody></table>	Attribute	Description	maxOccurs	unbounded
	Attribute	Description			
maxOccurs	unbounded				

[TOP](#)

ECODE

Attribute	Description
Name	ECODE
Datatype	String
Description	This indicates the code for the error encountered.

[TOP](#)

EDESC

Attribute	Description
Name	EDESC
Datatype	String
Description	This indicates the description of the error encountered.

[TOP](#)

FCUBS_WARNING_RESP

Attribute	Description						
Name	FCUBS_WARNING_RESP						
Datatype							
Description							
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>maxOccurs</td><td>unbounded</td></tr><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	maxOccurs	unbounded	minOccurs	0
	Attribute	Description					
	maxOccurs	unbounded					
minOccurs	0						

[TOP](#)

WARNING

Attribute	Description				
Name	WARNING				
Datatype					
Description	Indicates the warning encountered.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>maxOccurs</td><td>unbounded</td></tr></tbody></table>	Attribute	Description	maxOccurs	unbounded
	Attribute	Description			
maxOccurs	unbounded				

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

2.17.CCYPairDelete

CCYPairDelete

2.17.1.CO-CCYRatesDelete-Req-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

RatesMaster-Full

BRANCHCODE

CCY1

CCY2

MAKERID

MAKERDTSTAMP

CHECKERID

CHECKERDTSTAMP

MODNO

AUTHSTAT

RECSTAT

ONCEAUTH

Rates

RATETYPE

MIDRATE

BUYSPREAD

SALESPREAD

[BUYRATE](#)
[SALERATE](#)
[UDFDETAILS](#)
[FUNCTIONID](#)
[FIELD_NAME](#)
[DATATYPE](#)
[FIELD_VALUE](#)
[VAL_TYPE](#)

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description
Name	MSGID
Datatype	String
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.

Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description
------------------	--------------------

Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTIRIPID

Attribute	Description	
Name	MULTIRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTIRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

NAME

Attribute	Description
Name	NAME

Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

RatesMaster-Full

Attribute	Description
Name	RatesMaster-Full
Datatype	
Description	

[TOP](#)

BRANCHCODE

Attribute	Description				
Name	BRANCHCODE				
Datatype	String				
Description					
Attributes	<table border="1"> <thead> <tr> <th>Attribute</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>minOccurs</td> <td>0</td> </tr> </tbody> </table>	Attribute	Description	minOccurs	0
Attribute	Description				
minOccurs	0				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>maxLength</td> <td>3</td> </tr> </tbody> </table>	Restrictions	Description	maxLength	3
Restrictions	Description				
maxLength	3				

[TOP](#)

CCY1

Attribute	Description				
Name	CCY1				
Datatype	String				
Description					
Attributes	<table border="1"> <thead> <tr> <th>Attribute</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>minOccurs</td> <td>1</td> </tr> </tbody> </table>	Attribute	Description	minOccurs	1
Attribute	Description				
minOccurs	1				
Restrictions	<table border="1"> <thead> <tr> <th>Restrictions</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>maxLength</td> <td>3</td> </tr> </tbody> </table>	Restrictions	Description	maxLength	3
Restrictions	Description				
maxLength	3				

[TOP](#)

CCY2

Attribute	Description				
Name	CCY2				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

MAKERID

Attribute	Description				
Name	MAKERID				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>12</td></tr></tbody></table>	Restrictions	Description	maxLength	12
	Restrictions	Description			
maxLength	12				

[TOP](#)

MAKERDTSTAMP

Attribute	Description				
Name	MAKERDTSTAMP				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>25</td></tr></tbody></table>	Restrictions	Description	maxLength	25
	Restrictions	Description			
maxLength	25				

[TOP](#)

CHECKERID

Attribute	Description				
Name	CHECKERID				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>12</td></tr></tbody></table>	Restrictions	Description	maxLength	12
	Restrictions	Description			
maxLength	12				

[TOP](#)

CHECKERDTSTAMP

Attribute	Description
-----------	-------------

Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

Rates

Attribute	Description	
Name	Rates	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

RATETYPE

Attribute	Description	
Name	RATETYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8

[TOP](#)

MIDRATE

Attribute	Description	
Name	MIDRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYSPREAD

Attribute	Description	
Name	BUYSPREAD	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALESPREAD

Attribute	Description	
Name	SALESPREAD	
Datatype	Number	

Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYRATE

Attribute	Description	
Name	BUYRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALERATE

Attribute	Description	
Name	SALERATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

2.17.2.CO-CCYRatesDelete-Req-IO-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

RatesMaster-IO

BRANCHCODE

CCY1

CCY2

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

USERID

Attribute	Description	
Name	USERID	
Datatype	String	

Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	

Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	

Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description	
Name	NAME	
Datatype	String	
Description	The name of the additional parameter comes here.	

[TOP](#)

VALUE

Attribute	Description	
Name	VALUE	
Datatype	String	
Description	The value of the additional parameter comes here.	

[TOP](#)

FCUBS_BODY

Attribute	Description	
Name	FCUBS_BODY	
Datatype		
Description		

[TOP](#)

RatesMaster-IO

Attribute	Description	
Name	RatesMaster-IO	
Datatype		
Description		

[TOP](#)

BRANCHCODE

Attribute	Description				
Name	BRANCHCODE				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

CCY1

Attribute	Description				
Name	CCY1				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

CCY2

Attribute	Description				
Name	CCY2				
Datatype	String				
Description					
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	minOccurs	0
	Attribute	Description			
minOccurs	0				
Restrictions	<table border="1"><thead><tr><th>Restrictions</th><th>Description</th></tr></thead><tbody><tr><td>maxLength</td><td>3</td></tr></tbody></table>	Restrictions	Description	maxLength	3
	Restrictions	Description			
maxLength	3				

[TOP](#)

2.17.3.CO-CCYRatesDelete-Res-Full-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

CHOICE

RatesMaster-IO

BRANCHCODE

CCY1

CCY2

RatesMaster-Full

BRANCHCODE

CCY1

CCY2

MAKERID

MAKERDTSTAMP

CHECKERID

CHECKERDTSTAMP

MODNO

AUTHSTAT

RECSTAT

ONCEAUTH

Rates

RATETYPE

MIDRATE

BUYSREAD
 SALESPREAD
 BUYRATE
 SALERATE
 UDFDETAILS
 FUNCTIONID
 FIELD_NAME
 DATATYPE
 FIELD_VALUE
 VAL_TYPE
 FCUBS_ERROR_RESP
 ERROR
 ECODE
 EDESC
 FCUBS_WARNING_RESP
 WARNING
 WCODE
 WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	

Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nullable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nullable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	

Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MULTIRIPID

Attribute	Description	
Name	MULTIRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTIRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	

Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	

Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

CHOICE

Attribute	Description
Name	CHOICE
Datatype	
Description	

[TOP](#)

RatesMaster-IO

Attribute	Description
Name	RatesMaster-IO
Datatype	
Description	

[TOP](#)

BRANCHCODE

Attribute	Description	
Name	BRANCHCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY1

Attribute	Description	
Name	CCY1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY2

Attribute	Description	
Name	CCY2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

RatesMaster-Full

Attribute	Description
Name	RatesMaster-Full
Datatype	
Description	

[TOP](#)

BRANCHCODE

Attribute	Description	
Name	BRANCHCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY1

Attribute	Description
Name	CCY1

Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY2

Attribute	Description	
Name	CCY2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

MAKERID

Attribute	Description	
Name	MAKERID	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

MAKERDTSTAMP

Attribute	Description	
Name	MAKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

CHECKERID

Attribute	Description	
Name	CHECKERID	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	12

[TOP](#)

CHECKERDTSTAMP

Attribute	Description	
Name	CHECKERDTSTAMP	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	25

[TOP](#)

MODNO

Attribute	Description	
Name	MODNO	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

AUTHSTAT

Attribute	Description	
Name	AUTHSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

[TOP](#)

RECSTAT

Attribute	Description	
Name	RECSTAT	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

ONCEAUTH

Attribute	Description	
Name	ONCEAUTH	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	1

Rates

Attribute	Description	
Name	Rates	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

RATETYPE

Attribute	Description	
Name	RATETYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8

MIDRATE

Attribute	Description	
Name	MIDRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

BUYSREAD

Attribute	Description	
Name	BUYSREAD	
Datatype	Number	

Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALESPREAD

Attribute	Description	
Name	SALESPREAD	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

BUYRATE

Attribute	Description	
Name	BUYRATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

SALERATE

Attribute	Description	
Name	SALERATE	
Datatype	Number	
Description		
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

UDFDETAILS

Attribute	Description	
Name	UDFDETAILS	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	

Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

[TOP](#)

FIELD_NAME

Attribute	Description	
Name	FIELD_NAME	
Datatype	String	
Description		
Restrictions	Restrictions	Description
	maxLength	105
	minLength	1

[TOP](#)

DATATYPE

Attribute	Description	
Name	DATATYPE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	15

[TOP](#)

FIELD_VALUE

Attribute	Description	
Name	FIELD_VALUE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	255
	minLength	0

[TOP](#)

VAL_TYPE

Attribute	Description	
Name	VAL_TYPE	
Datatype	String	
Description		

Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	2
	minLength	0

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description	
Name	ERROR	
Datatype		
Description	This indicates the type of error encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

ECODE

Attribute	Description	
Name	ECODE	
Datatype	String	
Description	This indicates the code for the error encountered.	

[TOP](#)

EDESC

Attribute	Description	
Name	EDESC	
Datatype	String	
Description	This indicates the description of the error encountered.	

[TOP](#)

FCUBS_WARNING_RESP

Attribute	Description	
Name	FCUBS_WARNING_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

WARNING

Attribute	Description	
Name	WARNING	
Datatype		
Description	Indicates the warning encountered.	
Attributes	Attribute	Description
	maxOccurs	unbounded

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

[TOP](#)

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered

[TOP](#)

2.17.4.CO-CCYRatesDelete-Res-PK-MSG.xsd

FCUBS_HEADER

SOURCE

UBSCOMP

MSGID

CORRELID

USERID

BRANCH

MODULEID

SERVICE

OPERATION

SOURCE_OPERATION

SOURCE_USERID

DESTINATION

MULTITRIPID

FUNCTIONID

ACTION

MSGSTAT

ADDL

PARAM

NAME

VALUE

FCUBS_BODY

RatesMaster-PK

BRANCHCODE

CCY1

CCY2

FCUBS_ERROR_RESP

ERROR

ECODE

EDESC

FCUBS_WARNING_RESP

WARNING

WCODE

WDESC

FCUBS_HEADER

Attribute	Description
Name	FCUBS_HEADER
Datatype	
Description	

[TOP](#)

SOURCE

Attribute	Description	
Name	SOURCE	
Datatype	String	
Description	This is the code for the system which has sourced this message. For request messages, this field has to contain the source code for the partner system as maintained within FLEXCUBE UBS. In case of response messages this field will contain "FLEXCUBE".	
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

UBSCOMP

Attribute	Description	
Name	UBSCOMP	
Datatype	String	
Description	This is the component of FLEXCUBE for which this message is meant. Gateway supports both FLEXCUBE UBS and FLEXCUBE Investor Services. If the message is for FLEXCUBE UBS then this field should contain "FCUBS" and "FCIS" if meant for FLEXCUBE Investor Services. This field is case-sensitive.	
Restrictions	Restrictions	Description
	enumeration	FCUBS,FCIS

[TOP](#)

MSGID

Attribute	Description	
Name	MSGID	
Datatype	String	
Description	This is the "unique" message ID for this message. In inbound messages, if this field is present then Gateway would perform technical duplicate recognition using this field. For all messages going out from Gateway, Gateway will populate a unique message ID in this field.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

CORRELID

Attribute	Description	
Name	CORRELID	
Datatype	String	
Description	This is the correlation ID for the message. Gateway supports 2 correlation patterns, namely "Message ID to Correlation ID" (M2C) and "Correlation ID to Correlation ID" (C2C). While using asynchronous means of communication (like a JMS queue), the partner system can correlate the response received from Gateway to the request message sent by it using this field. If the correlation pattern is M2C then this field will contain the MSGID of the request message. If the correlation pattern is C2C then this field will contain the CORRELID of the request message.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

[TOP](#)

USERID

Attribute	Description	
Name	USERID	
Datatype	String	
Description	This is the user id which will be used within FLEXCUBE to record the transaction. This needs to be a valid user id as maintained within FLEXCUBE.	
Restrictions	Restrictions	Description
	maxLength	12
	pattern	[A-Z_0-9]*

[TOP](#)

BRANCH

Attribute	Description	
Name	BRANCH	
Datatype	String	
Description	This is the Branch of FLEXCUBE where the transaction would be recorded. This needs to be a valid Branch code as maintained in FLEXCUBE.	
Restrictions	Restrictions	Description
	length	3
	pattern	[a-zA-Z_0-9]{3}

[TOP](#)

MODULEID

Attribute	Description	
Name	MODULEID	
Datatype	String	
Description	This field is applicable only if messages are being sent to FCIS using Gateway. This is the module id of FCIS where the transaction will be recorded.	
Attributes	Attribute	Description
	minOccurs	0
	nillable	true

[TOP](#)

SERVICE

Attribute	Description	
Name	SERVICE	
Datatype	String	
Description	This field should contain the code of the Service of FLEXCUBE which is being requested. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

OPERATION

Attribute	Description	
Name	OPERATION	
Datatype	String	
Description	This is the operation of the service which is being invoked. This field is case-sensitive.	
Attributes	Attribute	Description
	nillable	true
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

SOURCE_OPERATION

Attribute	Description	
Name	SOURCE_OPERATION	
Datatype	String	
Description	This is the code for the operation being invoked in the Source system. The code of Source Operation being sent needs to be maintained as a valid Source Operation for the Source within FLEXCUBE.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

SOURCE_USERID

Attribute	Description	
Name	SOURCE_USERID	
Datatype	String	
Description	This is the user id in the Source system who is performing the action.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

DESTINATION

Attribute	Description	
Name	DESTINATION	
Datatype	String	
Description	This the system for which this message is destined. In case of request messages to FLEXCUBE, it should be "FLEXCUBE". In case of response, the SOURCE from the request message is reproduced here.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

MULTITRIPID

Attribute	Description	
Name	MULTITRIPID	
Datatype	String	
Description	In response messages, this is the ID sent by FLEXCUBE in case any overrides are encountered. In request messages, the source system is expected to reproduce the MULTITRIPID from the earlier received response if the source system accepts the overrides.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

FUNCTIONID

Attribute	Description	
Name	FUNCTIONID	
Datatype	String	
Description	This is the function in FLEXCUBE which is being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	8
	pattern	[A-Z_0-9]*

ACTION

Attribute	Description	
Name	ACTION	
Datatype	String	
Description	This is the action on the function being invoked. For integration scenarios this need not be sent. This is used by FLEXCUBE native user interface.	
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	pattern	[a-zA-Z_0-9]*

MSGSTAT

Attribute	Description	
Name	MSGSTAT	
Datatype	String	
Description	In response messages, FLEXCUBE will indicate the status of the request in this field. The various values are "SUCCESS", "WARNING" and "FAILURE".	
Attributes	Attribute	Description
	minOccurs	0

Restrictions	Restrictions	Description
	enumeration	SUCCESS,WARNING,FAILURE

[TOP](#)

ADDL

Attribute	Description	
Name	ADDL	
Datatype		
Description	This node is to be used for Additional information about a message.	
Attributes	Attribute	Description
	minOccurs	0

[TOP](#)

PARAM

Attribute	Description	
Name	PARAM	
Datatype		
Description	This is the parent node for each parameter in the additional node.	
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

NAME

Attribute	Description
Name	NAME
Datatype	String
Description	The name of the additional parameter comes here.

[TOP](#)

VALUE

Attribute	Description
Name	VALUE
Datatype	String
Description	The value of the additional parameter comes here.

[TOP](#)

FCUBS_BODY

Attribute	Description
Name	FCUBS_BODY
Datatype	
Description	

[TOP](#)

RatesMaster-PK

Attribute	Description
Name	RatesMaster-PK

Datatype	
Description	

[TOP](#)

BRANCHCODE

Attribute	Description	
Name	BRANCHCODE	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY1

Attribute	Description	
Name	CCY1	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

CCY2

Attribute	Description	
Name	CCY2	
Datatype	String	
Description		
Attributes	Attribute	Description
	minOccurs	0
Restrictions	Restrictions	Description
	maxLength	3

[TOP](#)

FCUBS_ERROR_RESP

Attribute	Description	
Name	FCUBS_ERROR_RESP	
Datatype		
Description		
Attributes	Attribute	Description
	maxOccurs	unbounded
	minOccurs	0

[TOP](#)

ERROR

Attribute	Description				
Name	ERROR				
Datatype					
Description	This indicates the type of error encountered.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>maxOccurs</td><td>unbounded</td></tr></tbody></table>	Attribute	Description	maxOccurs	unbounded
	Attribute	Description			
maxOccurs	unbounded				

[TOP](#)

ECODE

Attribute	Description
Name	ECODE
Datatype	String
Description	This indicates the code for the error encountered.

[TOP](#)

EDESC

Attribute	Description
Name	EDESC
Datatype	String
Description	This indicates the description of the error encountered.

[TOP](#)

FCUBS_WARNING_RESP

Attribute	Description						
Name	FCUBS_WARNING_RESP						
Datatype							
Description							
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>maxOccurs</td><td>unbounded</td></tr><tr><td>minOccurs</td><td>0</td></tr></tbody></table>	Attribute	Description	maxOccurs	unbounded	minOccurs	0
	Attribute	Description					
	maxOccurs	unbounded					
minOccurs	0						

[TOP](#)

WARNING

Attribute	Description				
Name	WARNING				
Datatype					
Description	Indicates the warning encountered.				
Attributes	<table border="1"><thead><tr><th>Attribute</th><th>Description</th></tr></thead><tbody><tr><td>maxOccurs</td><td>unbounded</td></tr></tbody></table>	Attribute	Description	maxOccurs	unbounded
	Attribute	Description			
maxOccurs	unbounded				

[TOP](#)

WCODE

Attribute	Description
Name	WCODE
Datatype	String
Description	This indicates the code for the warning encountered.

WDESC

Attribute	Description
Name	WDESC
Datatype	String
Description	This indicates the description of the warning encountered



ELCoreService
[August] [2014]

Oracle Financial Services software Limited
Oracle Park
Off Western Express Highway
Goregaon (East)
Mumbai, Maharashtra 400 063
India

Worldwide Inquiries:
Phone: +91 22 6718 3000
Fax: +91 22 6718 3001
www.oracle.com/financialservices/

Copyright © [2007], [2014], Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are commercial computer software pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any

kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.