

Branch Upload Interface details:

Template:

BRANCHSETUP~ BANK_ID ~ BRANCH_NAME ~ TIME_ZONE~ DOMESTIC_SWEEP~ DOMESTIC_POOL~
 LOCAL_CURRENCY~CROSS_BORDER_SWEEP~ CROSS_BORDER_POOL~ LINE1~ LINE2~ LINE3~
 COUNTRY_ID~ REGION~BIC_CODE~LOCAL_CLEARING_CODE~BRANCH_ID~MAKER_ID~ BRANCHSETUP ~
 BRANCHPARAM ~ BRANCH_ID ~PARAM_NAME~PARAM_VALUE~ BRANCHPARAM

Sample:

BRANCHSETUP~B045~CITI Singapore~UTC+13:00~1~1~USD~1~1~WEST~addLine2~addLine3~addLine4~KIR~Phoenix
 Islands~GHUSD5~5647HND~BR45~SYSTEM~BRANCHSETUP~BRANCHPARAM~BR45~FGD~15~BRANCHPARAM~BRANCHPARAM~BR45~LKSJH~15~BRANCHPARAM
 BRANCHSETUP~B046~BANCO SANTANDER Mexico~UTC+14:00~1~1~USD~1~1~EAST~Mambalam~addLine3~addLine4~KIR~Line
 Islands~GWERS~HNDFGHD~BR46~SYSTEM~BRANCHSETUP~BRANCHPARAM~BR46~LKMB~10~BRANCHPARAM

Attribute name	Type	Size	Remarks
BRANCHSETUP			START TAG(Not repeatable)
BANK_ID	STRING	3	
BRANCH_NAME	STRING	300	
TIME_ZONE	STRING	30	
DOMESTIC_SWEEP	STRING	1	0 – Disabled/ 1 - Enabled
DOMESTIC_POOL	STRING	1	0 – Disabled/ 1 - Enabled
LOCAL_CURRENCY	STRING	10	
CROSS_BORDER_SWEEP	STRING	1	0 – Disabled/ 1 - Enabled
CROSS_BORDER_POOL	STRING	1	0 – Disabled/ 1 - Enabled
LINE1	STRING	300	
LINE2	STRING	300	
LINE3	STRING	300	
LINE4	STRING	300	
COUNTRY_ID	STRING	100	
REGION	STRING	100	
BIC_CODE	STRING	15	

LOCAL_CLEARING_CODE	STRING	50	
BRANCH_ID	STRING	5	
MAKER_ID	STRING	12	
BRANCHSETUP			END TAG
BRANCHPARAM			START TAG(Repeatable)
BRANCH_ID	STRING	5	Same as above
PARAM_NAME	STRING	255	
PARAM_VALUE	STRING	255	