

Millionaire Certificate User Guide

Oracle FLEXCUBE Universal Banking

Release 14.0.0.0.0

Part No. E88855-01

December 2017

Millionaire Certificate User Guide
Oracle Financial Services Software Limited

Oracle Park

Off Western Express Highway
Goregaon (East)
Mumbai, Maharashtra 400 063
India

Worldwide Inquiries:

Phone: +91 22 6718 3000

Fax: +91 22 6718 3001

<https://www.oracle.com/industries/financial-services/index.html>

Copyright © 2007, 2017, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are “commercial computer software” pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Contents

1. Preface	1-1
1.1 Introduction.....	1-1
1.2 Audience.....	1-1
1.3 Documentation Accessibility	1-1
1.4 Organization	1-1
1.5 Glossary of Icons.....	1-2
1.6 Related Documents	1-2
2. Overview - Millionaire Certificates	2-1
2.1 Millionaire Certificate	2-1
2.2 Lien Millionaire Certificates.....	2-2
2.3 Draw Procedure.....	2-2
2.4 Scope of the Module.....	2-2
2.5 MB Module Functions & Features	2-3
2.5.1 Flexible Parameters Definition.....	2-3
2.5.2 MC/LMC Customers	2-3
2.5.3 Instrument Numbering.....	2-3
3. Maintenances	3-1
3.1 Pay-In Parameter Maintenance.....	3-1
3.1.1 Maintaining Pay-in Parameter Details	3-1
3.1.2 Viewing Pay-in Parameter Details Summary.....	3-2
3.2 Monthly Provision Maintenance.....	3-3
3.2.1 Maintaining Monthly Provision Details.....	3-3
3.2.2 Viewing Monthly Provision Details Summary	3-5
3.3 Draw Parameter Definition	3-5
3.3.1 Maintaining Draw Parameter Details	3-6
3.3.2 Viewing Draw Parameter Summary	3-7
3.4 Processing EOD Batch	3-8
4. Defining Product Attributes	4-1
4.1 Millionaire Certificate Product Definition.....	4-1
4.1.1 Capturing Millionaire Certificate Product Details	4-1
4.1.2 Specifying Preferences for a Product.....	4-3
4.1.3 Specifying Charges (ICCF) for a Product.....	4-4
4.1.4 Viewing Product Definition Details Summary	4-5
5. Processing MB Contract	5-1
5.1 Millionaire Certificate Contract Details.....	5-1
5.1.1 Capturing Millionaire Certificate Contract Details	5-1
5.1.2 Denomination Details	5-4
5.1.3 Customer Details	5-4
5.1.4 Certificate Details	5-6
5.1.5 Viewing Millionaire Certificate Contract Summary.....	5-7
5.1.6 Querying Customer Balance	5-8
5.1.7 Mapping Customer Reference to CIF.....	5-9
6. Payment	6-1

6.1	Millionaire Certificate Payment Input	6-1
6.1.1	<i>Millionaire Certificate Payment Details</i>	<i>6-1</i>
7.	Accounting Entries and Advices	7-1
7.1	MB Events	7-1
7.2	Accounting Entries	7-1
7.2.1	<i>MC Issuance – Cash/Cheque/Credit Card/Account transfer</i>	<i>7-2</i>
7.2.2	<i>MC Re-issuance</i>	<i>7-2</i>
7.2.3	<i>MC Issuance to winners</i>	<i>7-2</i>
7.2.4	<i>MC Liquidation/Encashment.....</i>	<i>7-2</i>
7.2.5	<i>MC Monthly Provisioning.....</i>	<i>7-3</i>
7.2.6	<i>MC Reversal.....</i>	<i>7-3</i>
7.2.7	<i>LMC Issuance.....</i>	<i>7-3</i>
7.2.8	<i>LMC Manual Roll-over.....</i>	<i>7-3</i>
7.2.9	<i>LMC Cancellation</i>	<i>7-3</i>
7.2.10	<i>LMC Monthly Amortization</i>	<i>7-4</i>
7.2.11	<i>LMC Reversal.....</i>	<i>7-4</i>
7.3	Advices	7-5
7.4	Notification.....	7-5
8.	Function ID Glossary	8-1

1. Preface

1.1 Introduction

Millionaire Certificate (MC) is a savings and investment opportunity which offers a maximum returns of 1000 times the investment value and at the same time the customer's certificates are completely capital guaranteed and en-cashable at any point in time.

Oracle FLEXCUBE Millionaire Certificate module (MB) module helps you to facilitate MC/LMC transactions. This module provide features to issue, redeem, partially redeem, cancel and mark as lost or reissue certificates. Certificates can be bought by cash or cheque or credit card. Certificates can also be bought on lien by paying the interest amount.

1.2 Audience

This manual is intended for the following User/User Roles:

Role	Function
Back Office Trade Finance Department Clerks	Contract Input functions except Authorization.
Back Office Trade Finance Department Officers	Contract Authorization, maintenance of static data specific to this module.
Front end Trade Finance Product Managers	Product definition functions excluding authorization. Query functions.
End of Day Operators	End and beginning of day related processing functions
Bank's Financial Controller/Trade Finance Department Manager	Branch level processing related setup for this module and Authorization of the same.
MIS Department Officers	Query/Report functions.

1.3 Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

1.4 Organization

This Manual is organized into the following chapters:

Chapter	Description
Chapter 1	<i>About this Manual</i> gives information on the intended audience. It also lists the various chapters covered in this User Manual.

Chapter 2	<i>Overview - Millionaire Certificates</i> gives you an overview of the MB module of Oracle FLEXCUBE.
Chapter 3	<i>Maintenances</i> chapter elaborates on the required maintenance for enabling and using the Millionaire Certificates (MB) module of Oracle FLEXCUBE.
Chapter 4	<i>Defining Product Attributes</i> explains about defining the basic information such as associated accounting roles, events, branches/customers restrictions, charges, product preferences, MIS & UDF and so on specific to setting up MB product.
Chapter 5	<i>Processing MB Contract</i> details about Capturing and processing Contract details related to MB
Chapter 6	<i>Payment</i> elaborates upon the operations which can be performed using the function present as part of the Millionaire Certificate (MB) module of Oracle FLEXCUBE.
Chapter 7	<i>Accounting Entries and Advices</i> list the suggested accounting roles and events related to the MB module of Oracle FLEXCUBE.
Chapter 8	<i>Function ID Glossary</i> has alphabetical listing of Function/Screen ID's used in the module with page references for quick navigation.

1.5 Glossary of Icons

This User Manual may refer to all or some of the following icons.

Icons	Function
	Exit
	Add row
	Delete row
	Option List

1.6 Related Documents

You may need to refer to any or all of the User Manuals while working on the MB module:

- Core Entities
- Inventory
- ELCM
- Procedures
- Products
- User Defined Fields

2. Overview - Millionaire Certificates

This chapter gives you an overview of the Millionaire Certificate (MC) module of Oracle FLEXCUBE. There are two types of certificates issued by the bank:

- Millionaire Certificate (MC)
- Lien Millionaire Certificates (LMC)

This chapter contains the following sections:

- [Section 2.1, "Millionaire Certificate"](#)
- [Section 2.2, "Lien Millionaire Certificates"](#)
- [Section 2.3, "Draw Procedure"](#)
- [Section 2.4, "Scope of the Module"](#)
- [Section 2.5, "MB Module Functions & Features"](#)

2.1 Millionaire Certificate

Millionaire Certificate (MC) is a savings and investment opportunity which offers a good returns on your investment and certificates are completely capital guaranteed and en-cashable at any point of time. The subscription to MC is in multiple of thousands only.

To subscribe to MC, you should hold a Valid Visa (Transit/ Visit/Business/Residential) and a Passport. MC can be bought from any of the branches of the bank or through any channels like their associated exchanges and gets processed from the bank. The non-residential clients would be able to redeem it through a Power of Attorney issued with proper documentation.

Customers of the bank can get certificates attached to their account if the MCs have been purchased under the CIF # of the account as well. Non customers of the bank can purchase the MC and later associates with the Customer or CIF if he becomes customer and declares the same to the bank.

Inventory module is used to track the movement of the instruments between central vault and branches and tracks the status of each instrument by serial number.

The MB module provides you with the following features:

- MC is open ended and don't have any maturity date and can be withdrawn at any point in time across the counter. But any encashment within X number of days from the date of purchase shall be subject to a nominal pre-encashment fee of 2.5% of total certificate value.
- Certificates are Non-Interest bearing, non-negotiable and non-pledgeable to any third party. Customers can walk into any Bank branch and en-cash their certificates. Withdrawal of MC can be cash or transfer to customer account with the bank.
- Minimum investment allowed as certificates is issued in respective LCY equivalents.
- One time fee is charged per transaction irrespective of number of certificates issued.
- Draw is conducted on a daily/weekly/bimonthly/monthly/quarterly basis with minimum savings condition.
- Secured over draft facility is there to meet the immediate financial needs while remaining in the running for a million dirham draw. You can avail the facility of a secured over draft against their Millionaire certificates – up to 90% of MC value at the rate of 8.5%
- MC can be purchased on-line by account holders of your bank and non-account holders. All credit card holders are accepted to purchase MC (customers & non customers). For

other bank credit card customers, there is an additional MC issuance charge of 1.5% on the (transaction amount + normal issuance fee).

- In case of lost certificates, the bank reprints the MC and may charge a new issuance fee.
- After winning the draw, MM certificates equivalent to the winning amount would be issued to the winner without any cash payments. Winner has an option to redeem the certificates.

2.2 Lien Millionaire Certificates

Lien Millionaire Certificates (LMC) is another product offered by the bank. All features are like the Millionaire Certificates but for the below mentioned features:

- While purchasing the MC you have an option to pay the interest (Currently 6% per year per certificate) and get add-on notional MC. Notional certificates are eligible to participate in the draw.
- The number of MC you can buy on lien is dependent on the number of MC you hold.
- The subscription transaction fee (MC) is waived-off if the customer opts for the Lien.
- Liened MC can be renewed every year by paying the same interest. If the renewal is not done then the notional certificate will be active up to grace period end defined at product preference and after grace period end Notional certificate is dropped automatically.
- The bank has an option to Reverse the MC/LMC with an option to refund the interest when:
 - Reversal of MC contract is allowed only if it has not undergone liquidation/re-issuance and it should not be linked to any LMC contracts.
 - Reversal of LMC contract is allowed only if it has not undergone cancellation/rollover/reissuance/monthly interest amortization.
- If a customer liquidates the MC, then proportionate of LMC should be dropped accordingly as per eligibility matrix. Interest rate charged is not refundable and unearned interest is transferred to earned GL.

2.3 Draw Procedure

A member from the Economic Panel would be part of the draw. This is generally conducted in a Mall or a Beach or an open place where public gathering generally happens. The Lottery happens through a throw of dice corresponding to the Units place, hundreds place etc... considering the total number of reference active deposits in consideration.

Currently the Bank is getting the sequence/reference no. through the lot and then contacting the customer support centre to ensure that the deposit is active. Oracle FLEXCUBE provides the reference number and the corresponding certificate number immediately instead of using the manual process.

2.4 Scope of the Module

The MB module comprises the following high-level functions:

- Product Definition
- Contract Input
- Pay-in Parameter Maintenance
- Monthly Provision Maintenance
- Draw Parameter Maintenance
- 'Factory shipped' report is only for a single report for draw data.

- 'Advices' is only to provide advice field tags.

2.5 MB Module Functions & Features

The following sections give you a brief overview of the MB module's various functions and features and contains the following topics:

- [Section 2.5.1, "Flexible Parameters Definition"](#)
- [Section 2.5.2, "MC/LMC Customers"](#)
- [Section 2.5.3, "Instrument Numbering"](#)

2.5.1 Flexible Parameters Definition

Parameters Definition for millionaire certificate product, associated charges, accounting entries and preferences are completely user defined and flexible.

Certificate issuance, encashment, cancellation (including partial cancellation) and re-issuance are handled as different stages/events of a contract.

Inventory module is used to track the flow of inventory from head office to various branches. It also tracks the status of the instrument.

MC contracts can be used as collateral to a liability in the collateral maintenance screen, in the ELCM module. MC contract is then blocked to the extent of collateralized amount.

2.5.2 MC/LMC Customers

All customers of MC/LMC (including customers/credit card holders of your bank and walk-in customers/credit card holders) are CIF in Oracle FLEXCUBE. Each type of MC customers are created with different charge groups to facilitate differential charging, if any.

For new walk-in customers, during MC issuance you can record the basic details of the customer in 'Customer details' section of MC contract issuance screen. These details are stored against the customer reference number and would not create a CIF in the system. The system generated customer reference number would then be mapped against the standard walk-in CIF defined in the branch parameters.

Upon fresh/first time purchase of MC by CIF, system dynamically generates the customer reference number and associates it to the CIF. This reference number would be a ten digit number - branch code followed by running sequence number.

System would not validate the MC customers based on customer nationality/visa details/age.

2.5.3 Instrument Numbering

MC/LMC would involve the following two numbers:

- Certificate number – a ten digit number with branch code followed by running sequence number.
- Control/key/serial number - unique number printed on the stationary/instrument and would be used to authenticate the issued certificates.

3. Maintenances

As part of enabling and using the Millionaire Certificates (MB) module of Oracle FLEXCUBE, there are several maintenances to be performed. These maintenances have been elaborated upon in the sections given below.

Note

Unless specified otherwise, all maintenances specified below allow all standard maintenance functions – Add, Modify, Delete, Authorize, Close, Re-open, and Inquiry. The maintenance functions also log all maintenances in the Audit Trail.

The common maintenance related to Millionaire Certificate transactions are maintained in the following screens:

- Function ID 'CSDDEMAN' under the heading 'Maintaining Currency Denomination Details' in CS module
- Function ID 'IVDSTKCD' under the heading 'Stock Catalog Definition' in Instruments Inventory Tracking (IV) module.
- Function ID 'IVDTXNAS' under the heading 'Adjust Inventory Balance' in Instruments Inventory Tracking (IV) module.

This chapter contains the following sections:

- [Section 3.1, "Pay-In Parameter Maintenance"](#)
- [Section 3.2, "Monthly Provision Maintenance"](#)
- [Section 3.3, "Draw Parameter Definition"](#)
- [Section 3.4, "Processing EOD Batch "](#)

3.1 Pay-In Parameter Maintenance

This section contains the following topics:

- [Section 3.1.1, "Maintaining Pay-in Parameter Details"](#)
- [Section 3.1.2, "Viewing Pay-in Parameter Details Summary"](#)

3.1.1 Maintaining Pay-in Parameter Details

You can maintain the general ledger code for each product, branch and pay-in-option (viz. by cash, cheque and credit card) in the 'Pay-in parameter Maintenance' screen from the head office level.

To invoke the 'Pay-in parameter Maintenance' screen, enter MBDMBPAY' in the field at the top right corner of the Application Toolbar and then click the adjoining arrow button.

The screenshot shows the 'Pay-In Parameter Maintenance' application window. It features a 'New' button at the top left. The main form area includes the following fields:

- Product Code ***: A text input field.
- Product Description**: A text input field.
- Branch Code ***: A text input field.
- General Ledger Code ***: A text input field.
- Pay In ***: A dropdown menu currently showing 'Cash'.

At the bottom of the window, there is a table with the following structure:

Maker	Date Time:	Mod No	Record Status
Checker	Date Time:		Authorization Status

An 'Exit' button is located in the bottom right corner of the window.

You can maintain the following details here.

Product Code

Specify the MC product code for which you are maintaining the details.

The description for the specified product gets displayed in the adjacent field.

Branch Code

Specify the branch code where the product MC product is issued.

Pay-in Option

Select a valid paying option from the drop-down list. The values are:

- Cash
- Cheque
- Credit card.

General ledger code

Specify the GL code for the selected pay-in option.

MC issuance through cheque and credit card is a deposit in teller module to the specified GL codes. MC issuance through cash would impact the till in teller module and update the specified cash GL. During MC issuance, based on the pay-in option, these GL codes would be used for further processing.

3.1.2 Viewing Pay-in Parameter Details Summary

You can view the summary of monthly provision details through the 'Pay-in Parameter Summary' screen.

To invoke the 'Pay-in Parameter Summary' screen, enter 'MBSMBPAY' in the field at the top right corner of the Application Toolbar and then click the adjoining arrow button.

You can query the contract records with the following details

- Authorization Status
- Record Status
- Product Code
- Branch Code
- Pay in

Click 'search' button to view the records with the specified values.

3.2 Monthly Provision Maintenance

This section contains the following topics:

- [Section 3.2.1, "Maintaining Monthly Provision Details"](#)
- [Section 3.2.2, "Viewing Monthly Provision Details Summary"](#)

3.2.1 Maintaining Monthly Provision Details

You can maintain monthly provision for MC / LMC in the 'Monthly Provision Maintenance' screen from the head office level.

For a product, provision is allowed only once in a calendar month and if it is done for 'ALL' products, then provisioning for individual products is not allowed. Similarly, If provisioning is done for specific product then system would not allow provisioning for 'ALL' products in the given calendar month.

To invoke the 'Monthly Provision Maintenance' screen, enter 'MBDMPROV' in the field at the top right corner of the Application Toolbar and then click the adjoining arrow button.

The screenshot shows a software window titled "Monthly Provision Maintenance". Inside, there's a "New" button at the top left. Below it, the form has five input fields arranged in two columns. The left column contains "Product Code *" (with a red asterisk), "Provision Currency", and "Provision Amount *" (with a red asterisk). The right column contains "Product Description" and "Provision Date". At the bottom of the window, there's a light blue bar containing a table with the following columns: "Maker", "Date Time:", "Mod No", "Record Status", "Checker", "Date Time:", "Authorization Status", and an "Exit" button on the far right.

You can maintain the following details here.

Product Code

Select a valid MC/LMC product code for provisioning from the list of values maintained. You can specify 'ALL' products also for provisioning.

The description for the specified product gets displayed in the adjacent field. Provision date gets defaulted as the system date.

Provision Amount

Specify the amount for provision. The currency gets displayed in the adjacent field.

After the provision is authorized you cannot modify the record. System compute the branch provision share for all the branches holding active MC/LMC as on provision date and post provision accounting entries for all these branches.

Branch provision amount is computed by apportioning the 'Provision amount', based on the number of MC/LMC in books of branch under consideration with that of total number of MC/LMC in books of all branches. System would use contract originating branch as the basis to group MC/LMC for a given branch.

Branch Provision Share = (Provision amount * Total MC/LMC in books of branch "A" / Total MC/LMC Deposits in all branches).

Upon computing branch provision amount, system would trigger the 'PROV' event to pass the inter-branch accounting entries as mentioned below:

In Books of Branch "A":

Debit– Expense GL<Branch Provision Share>

Credit – Head Office Account in books of branch "A" <Branch Provision Share>

In Books of Head Office:

Debit – Branch “A” Account in Head Office books <Branch Provision Share>


Credit – MM Provision GL (Liability GL) <Branch Provision Share>

The date of provision gets defaulted.

3.2.2 Viewing Monthly Provision Details Summary

You can view the summary of monthly provision details through the 'Monthly Provision - Summary' screen.

To invoke the 'Monthly Provision - Summary' screen, enter 'MBSMPROV' in the field at the top right corner of the Application Toolbar and then click the adjoining arrow button.



You can query the contract records with the following details

- Authorization Status
- Record Status
- Product Code
- Provision Date
- Provision Currency
- Provision Amount

Click 'search' button to view the records with the specified values.

3.3 Draw Parameter Definition

This section contains the following topics:

- [Section 3.3.1, "Maintaining Draw Parameter Details"](#)
- [Section 3.3.2, "Viewing Draw Parameter Summary"](#)

3.3.1 Maintaining Draw Parameter Details

You can maintain the data file extraction details in the 'Draw parameter Maintenance' screen from the head office level.

To invoke the 'Draw parameter Maintenance' screen, enter 'MBDDRMNT' in the field at the top right corner of the Application Toolbar and then click the adjoining arrow button.

The screenshot shows the 'Draw Parameter Definition' window. It includes input fields for 'Draw Reference Number', 'Cutoff Date *', and 'Min No of MC *' (0). Below these are three sections: 'Product List', 'Branch List', and 'Certificate List'. Each section has a 'Product Restriction' (Allowed/Disallowed), 'Branch Restriction' (Allowed/Disallowed), and 'Certificate Restriction' (Allowed/Disallowed) with radio buttons. Each list has a table with columns for 'Product Code', 'Product Description', 'Branch Code', 'Branch Description', 'Certificate Number', and 'Product Code'. At the bottom, there is a status bar with fields for 'Maker', 'Checker', 'Date Time', 'Mod No', 'Record Status', 'Authorization Status', and an 'Exit' button.

You can maintain the following details here.

A unique draw reference number gets displayed here.

Cut-off date

Specify the cut-off date for the draw. All active certificates with value date lesser than the specified cut-off date are eligible to participate in the draw.

Min. No. of MC

Specify the Minimum number of MC. If the number of MC held by the customer (including all mapped to customer reference number) is less than this specified quantity then the customer is not eligible to participate in the draw.

Product Restrictions

Indicate the restriction for the product during the draw. You can select one of the following options:

- Disallowed
- Allowed

Product

You can specify the list of MC/LMC products to be included in the restriction for the draw.

Product Code

Specify the product to be included in the restriction for the draw. The product description gets displayed.

Branch Restrictions

Indicate the restriction for the branch during the draw. You can select one of the following options:

- Disallowed

- Allowed

Branch

You can specify the list of branch to be included in the restriction for the draw. System would use contract originating branch as the basis to tag MC/LMC to a given branch.

Branch Code

Specify the branch to be included in the restriction for the draw. The branch description gets displayed.

Certificate Restrictions

Indicate the restriction for the certificate numbers during the draw. You can select one of the following options:

- Disallowed
- Allowed

Exclude Certificate Number

You can specify the list of certificate numbers to be included in the restriction for the draw.

Certificate No

Specify the certificate number to be included in the restriction for the draw.

After the authorization, system would extract the eligible certificate details based on the data provided.

Note

Only active MC/LMC will be considered for the draw. All certificates that have been re-deemed or cancelled will not be eligible for the draw.

An OBIEE report gets displayed with draw data based on this maintenance. Report accepts 'Draw reference number' as the input parameter and displays sequence number, certificate number and customer reference number for all certificates eligible for the draw.

3.3.2 Viewing Draw Parameter Summary

You can view the summary of monthly provision details through the 'Draw Parameter Summary' screen.

To invoke the Monthly Provision - Summary' screen, enter 'MBSDRMNT' in the field at the top right corner of the Application Toolbar and then click the adjoining arrow button.

You can query the contract records with the following details

- Authorization Status
- Record Status
- Draw Reference Number
- Cutoff Date
- Min No of MC

Click 'search' button to view the records with the specified values.

3.4 Processing EOD Batch

During the End of Transaction Input, to amortize the interest received in advance on LMC, an EOD batch (MBBEODFN) is run on a monthly basis. The lien amount is amortized over the period of one year based on the following formula.

Monthly amortization amount = Total interest amount/(No of Days in Year – No Of days passed by) * No. of days in a month.

In the month when LMC is issued, the no. of days for the above calculations is from date of issuance till month end and in the last month i.e. 12th month, the total unamortized amount would be amortized.

System triggers the 'LMCA' event to post accounting entries for monthly amortization amount.

On the maturity date of LMC, this EOD batch marks the LMC status as 'Pending renewal'. LMC with 'Pending Renewal' status are not eligible to participate in the draw. If the LMC contract is not renewed before the grace period then this EOD batch would 'Close' the LMC contract.

4. Defining Product Attributes

In this chapter, we shall discuss the manner in which you can define attributes specific to a MB Product.

In the product definition, you can specify basic information, associated accounting roles, events, branches/customers restrictions, charges, product preferences, MIS & UDF. Separate products are created for millionaire certificate and lien millionaire certificate.

This chapter contains the following section:

- [Section 4.1, "Millionaire Certificate Product Definition"](#)

4.1 Millionaire Certificate Product Definition

This section contains the following topics:

- [Section 4.1.1, "Capturing Millionaire Certificate Product Details"](#)
- [Section 4.1.2, "Specifying Preferences for a Product"](#)
- [Section 4.1.3, "Specifying Charges \(ICCF\) for a Product"](#)
- [Section 4.1.4, "Viewing Product Definition Details Summary"](#)

4.1.1 Capturing Millionaire Certificate Product Details

You can maintain the MB product definition in the 'Millionaire Certificate Product Definition' screen. To invoke the screen, type 'MBDPRMNT' in the field at the top right corner of the Application Toolbar and then click the adjoining arrow button.

Millionaire Certificate Product Definition

New

Product Code _____

Product Description _____

Product Type ☒ Millionaire Certificate
☐ Lien Millionaire Certificate

Start Date _____

End Date _____

Remarks _____

Accounting Role | Events | Branch & Currency | Customer | MIS | Preferences | Charges

Maker Date Time: Mod No Record Status
Checker Date Time: Authorization Status

Exit

You can specify all attributes related to MB product here.

The buttons on this screen are explained below:

Buttons	Description
Accounting Roles	Click this button to define the accounting role to accounting head mapping.
Events	Click this button to select the events for the product and then maintain event-wise accounting entries and advices.
Branch	Click this button to maintain the list of allowed/ disallowed branches for the product.
Customer	Click this button to maintain the list of allowed/ disallowed customers/customer categories.
Preferences	Click this button to define preferences of the product.
Charges	Click this button to define charge components, rules, events and other associated details.
Fields	Click this button to provide values for the UDFs associated with the screen.

For any product you create in Oracle FLEXCUBE, you can define generic attributes, such as branch, currency, and customer restrictions, interest details, tax details, etc., by clicking on the appropriate icon in the horizontal array of icons in this screen.

Product Code

Specify the code you assign to a product which is used to identify the product throughout the module. The code should contain four characters. You can follow your own convention for devising the code; but at least one of the characters should be a letter of the English alphabet.

Since the code that you define is used to identify the product, it should be unique across the modules of Oracle FLEXCUBE. For instance, if you have assigned the code 'MC01' to a particular product in this module, you cannot use it as a code in any other module.

Description

Specify a brief description of the product, which will be associated with the product for information retrieval purposes.

Product Type

Indicate the type of product from the options given below:

- Millionaire Certificate
- Lien Millionaire Certificate

Start/End Date

A product can be set up for use over a specific period, by defining a start and an end date. The Issue Date of an MC involving a product should be:

- The same as or later than the Start Date.
- The same as or earlier than the End Date.

The start and end dates of a product come in handy when you are defining a product for a scheme, which is open for a specific period.

Remarks

You can enter information about the product, intended for the internal reference of your bank. The remarks are displayed when the details of the MC are displayed or printed, but not printed on any correspondence with the customer.

4.1.2 Specifying Preferences for a Product

Click 'Preference' button from 'Millionaire Certificate Product Definition' screen to invoke the preference screen.

The screenshot shows a 'Preferences' window with the following fields and sections:

- Product Code
- Product Description
- Stock Code *
- KYC Limit *
- Renewal Grace Period
- Product Currency *
- Certificate Value *
- Certificate Number Mask *
- LMC Eligibility Ratio section with a table containing one row:

LMC Start Number *	LMC End Number *	LMC Eligibility Ratio *
☐		
- LMC Price section with a table containing one row:

LMC Start Number *	LMC End Number *	Issuance Price *
☐		
- Bottom right buttons: Ok, Exit

You can specify the following values here:

Product code and the description for the code get displayed here.

Stock Code

Specify the stock code of pre-printed MC stationary/inventory. It should be a valid code in inventory module.

Certificate Value displays the value of the associated MC product. The denomination value associated with the selected stock code would be defaulted.

Renewal Grace Period

Specify the grace period for LMC renewal/manual rollover. Grace period would be specified as number of calendar days.

You can renew the LMC only after the maturity date.

If the LMC contract is not renewed before the grace period then EOD batch would 'Close' the LMC contract.

If LMC contract is renewed (Event: ROLL) before the grace period then system would increase the maturity value of the contract by a year.

LMC contracts in grace period, which are yet to be renewed, are not eligible to participate in the draw.

Certificate Number Mask

Specify the mask for certificate numbers.

Typical 'Certificate Number Mask' would be 'bbbnnnnnnn', where 'bbb' would represent the branch code and 'n' would represent the numeric character.

Product currency

Specify the currency associated with the product/certificate value/issuance price for LMC. Currency code should be the LCY code.

KYC Verification Limit

Specify the limit for KYC verification. After the MC issuance to customers, if the cumulative value of MC held by the customer (including the current contract and by considering all the mapped customer reference number) exceeds this limit then system validates the KYC compliance of the CIF.

LMC Eligibility Ratio

Specify the following details to calculate LMC eligibility ratio for a given range of MC held by the customers.

Based on the number of MC held by the customers, system computes the maximum number of LMC that can be held by the customer. Any decimal/fractional output will be truncated in deriving the maximum eligible LMC.

LMC Price

Specify the following details to maintain the issuance price for a given range of LMC issued to the customers.

4.1.3 Specifying Charges (ICCF) for a Product

Click 'Charge' button on 'Millionaire Certificate Product Definition' screen to define the charge components, rules, events and other associated details.

The screenshot shows the 'Charge Details' window with the following sections and fields:

- Product Code** and **Product Description** (text boxes)
- Component Details** section with a '1 Of 1' indicator and buttons: **Stop Association**, **Propagation Required**, and **Default From Class**.
- Charge Type** (dropdown), **Debit/Credit** (dropdown), **Add/Subtract** (dropdown), and **SWIFT Qualifier** (text box).
- Third Party Type** (text box) with sub-options: **Net Consideration** and **Advice Charge**.
- Event Details** section with two columns:
 - Event For Association** (text box) and **Description** (text box)
 - Event For Application** (text box) and **Description** (text box)
 - Event For Liquidation** (text box) and **Description** (text box)
 - Basis Amount Tag** (text box) and **Description** (text box)
- Rule Details** section with **Settlement Currency** (text box), **Rule** (text box), and **Description** (text box). Buttons on the right: **Default Waiver**, **Capitalize**, **Collect LC Advising Charges in Bills**, and **Collect LC Charges in Bills**.
- Other Details** section with buttons: **Allow Rule Amendment**, **Amend After Association**, **Allow Amount Amendment**, **Amend After Application**, **Consider as Discount**, and **Annual Required**. A **Discount Basis** dropdown is also present.
- Ok** and **Exit** buttons at the bottom right.

Issuance charge is a flat amount based charge associated to appropriate events. It could also be a percentage of total amounts of certificates issued.

Pre-encashment charge is a 'tenor basis' charge with 2.5% charge for 0-90 days and 0% thereafter. The tenor of the open-ended MC contract (with maturity date as null) would be computed as (Application date – Value date).

Charge currency code should be the LCY code.

Note

Any changes in product parameters would be applied for prospective contracts/events only.

For further information on the generic attributes that you can define for a product, please refer the following Oracle FLEXCUBE User Manuals under Modularity:

- *Product Definition*
- *User Defined Fields*
- *Settlements*

Millionaire Certificate Product Definition' screen allows all standard maintenance functions – Add, Modify, Delete, Authorize, Close, Re-open, and Inquiry. It also log all maintenances in the Audit Trail.

4.1.4 Viewing Product Definition Details Summary

You can view the summary of monthly provision details through the 'Product Definition Summary' screen.

To invoke the 'Product Definition Summary' screen, enter 'MBSPRMNT' in the field at the top right corner of the Application Toolbar and then click the adjoining arrow button.

The screenshot shows a web application window titled 'Summary'. At the top, there are tabs for 'Search', 'Advanced Search', and 'Reset'. Below these, there are two dropdown menus for 'Authorization Status' and 'Record Status', and a text input field for 'Product Code'. To the right of these, there are two more dropdown menus for 'Record Status' and 'Product Type'. Below the search filters, there is a pagination bar showing 'Records per page: 15', '1 Of 1', and a 'Go' button. The main area of the screen is a table with the following columns: 'Authorization Status', 'Record Status', 'Product Code', 'Product Type', 'KYC Limit', 'Certificate Value', 'Stock Code', 'Product Currency', 'Start Date', and 'End Date'. The table is currently empty. At the bottom right corner, there is an 'Exit' button.

You can query the contract records with the following details

- Authorization Status
- Record Status
- Product code

- Product Type

Click 'search' button to view the records with the specified values.

5. Processing MB Contract

An MC/LMC contract is an instruction wherein a customer requests the bank to issue a Millionaire Certificate. Certificate issuance, encashment, lost, partial re-issue, cancellation and re-issuance are handled as different stages or events of a contract.

This chapter contains the following section:

- [Section 5.1, "Millionaire Certificate Contract Details"](#)

5.1 Millionaire Certificate Contract Details

This section contains the following topics:

- [Section 5.1.1, "Capturing Millionaire Certificate Contract Details"](#)
- [Section 5.1.2, "Denomination Details"](#)
- [Section 5.1.3, "Customer Details"](#)
- [Section 5.1.4, "Certificate Details"](#)
- [Section 5.1.5, "Viewing Millionaire Certificate Contract Summary"](#)
- [Section 5.1.6, "Querying Customer Balance "](#)
- [Section 5.1.7, "Mapping Customer Reference to CIF"](#)

5.1.1 Capturing Millionaire Certificate Contract Details

You can input MC/LMC contract in the 'Millionaire Certificate Contract Input' screen.

For walk-in customers, during MC issuance you can record the basic details of the customer in 'Customer details' section of MC contract issuance screen. These details are stored against the customer reference number without creating a CIF in the system. The system generated customer reference number is then be mapped against the standard walk-in CIF defined in the branch parameters.

To invoke the 'Millionaire Certificate Contract Input' screen, enter 'MBDTRONL' in the field at the top right corner of the Application Toolbar and then click the adjoining arrow button.

Millionaire Certificate Contract Input

New

Version Number: 1 Of 1

Contract Details

Product Code *
Transaction Type * Normal Issue
No of Certificates *
Charge Group

Product Description
Customer No *
Pay-In Option * Cash
Default

Other Details

Contract Reference *
User Reference *
Currency *
Value Date *
Certificate Amount *
Customer Reference *
Control Number *

Source Code * FLEXCUBE
Source Reference *
Issuance Price *
Book Date
Maturity Date
Account No, GL Code *
Original Purchase Date *
Remarks

Navigation: Certificate Details | Denomination Details | Customer Details | Events | Charges | MIS | Fields

Input By: Checker
Date Time: Date Time
Status: Authorization Status
Exit

The system generated contract reference number gets displayed in the screen. You can specify the following details here.

Product Code

Specify the millionaire certificate product to be used in the contract. The product description gets displayed in the adjacent field.

Customer No

Specify the CIF number of the customer. Customer Reference Number mapped to the selected customer gets displayed.

For new walk-in customers, you have to select the standard walk-in-customer id as maintained in the branch parameters. Additional details of new walk-in-customers should be recorded in the customer details section.

Transaction Type

Specify the type of transaction from the drop-down options. Transaction types are associated to a specific event for differential charging and accounting. The options are:

- Normal Issue (Event : INIT) For normal issuance of MC to customers.
- Replacement Issue (Event : RIMC) In case of lost certificates, an indemnity may be taken from customer and the bank reprints the MC certificates with new system generated certificate numbers. Old control number would be marked as lost and system would force the user to enter new control number.

Note

This option is available only on contract amendment.

- Issue to winners (Event : WIMC) - For issuance of MC to winners. "Pay-in option" has to be "Other GL" – enabling user to specify the debit GL (eg. HO account in CPC books or MM provision GL or other expense GL).
- Lien Issue (Event : INIT) For issue of notional/lien MC.
- Lien Rollover (Event : ROLL) For renewing the lien.

Note

This option would be available only on contract amendment.

User Reference

Specify the user reference number.

Source Code

Specify the source of the contract.

Source Reference

Specify the source reference of the contract.

Value Date

Specify the value date of the contract. Only MC issuance can be back dated. Future dated contract is not supported.

The application date gets displayed as the booking date of the contract.

For LMC issuance, maturity date is computed as (value date + one year). Upon rollover of LMC, maturity date gets incremented by a year.

Note

For MC contract maturity date would be blank/null

No of Certificates

Specify the number of certificates participating in the specified transaction type.

The MC certificate value or LMC issuance price gets displayed as Issuance Price.

While saving, the issuance price for MC/LMC is defaulted by the system. LMC issuance price is derived based on the number of liened certificates requested in the contract and LMC pricing maintained in product definition.

Control Number

Specify the control number of pre-printed stationary/instrument which should be a valid stock number as maintained through 'Adjust Inventory Balance' - 'MC - Branch to User'.

For contracts initiated from FCDB source, system would not allow to track control number.

The computed contract value based on the number of certificates and issuance price gets displayed in the Amount.

Pay-in option

Select the pay option from the drop-down list. The options are:

- Cash - cash GL of the current branch gets impacted.
- Cheque
- Account transfer - system allows only LCY accounts to be selected.
- Credit card
- Other GL.

Account No/GL code

Specify the GL code from which the contract value should be debited. If the GL code is not selected then while saving system would default the relevant GL code from pay-in parameter maintenance.

- For pay-in-option as account transfer, specify the customer account number (linked to the selected CIF). System would support only LCY accounts.
- For pay-in-option as 'Other GL', specify the GL code from which the contract value should be debited. This option is allowed only if the 'Transaction Type' is selected as 'Issue to Winners'.

The original purchase, purchase/issue date of the certificates gets displayed.

Remarks

Specify any additional remarks or information for the contract.

Charge Group

While selecting the CIF, system defaults the associated charge group. You can modify the charge group of the contract.

5.1.2 Denomination Details

For cash payment, you can maintain denomination details. You should operationally maintain appropriate denomination details for the amount settled across counter, which system does not validate.

The screenshot shows a software window titled "Denomination Details". It features a toolbar at the top with a "Go" button and a "1 Of 1" indicator. Below the toolbar is a table with the following columns: "Denomination Code", "Denomination Value", "Units", and "Total Amount". The table is currently empty. Below the table, there are two input fields labeled "Currency" and "Total Amount". At the bottom right of the window, there are "Ok" and "Exit" buttons.

Denomination Code

Specify the denomination code for the currency.

Denomination Value

Specify the value of the denomination.

Units


Specify the units of the denomination.

Currency and the total amount get displayed here.

5.1.3 Customer Details

For new walk-in customers, during MC issuance you can record the basic details of the customer in this section. These details are stored against the customer reference number and

would not create a CIF in the system. The system generated customer reference number should then be mapped against the standard walk-in CIF defined in the branch parameters.



You can maintain the following details of a walk-in customer here. Branch code gets displayed.

Customer Name

Specify the customer name.

Customer Short Name

Specify a short name for the customer.

Party type

Select the party type of the customer from the following drop-down options:

- Individual
- Corporate
- Bank

Address for Correspondence

You can provide the customer address in the following fields:

- Address 1
- Address 2
- Address 3
- Address 4

Geographic

You can provide the geographic information of the customer here.

Country Code

Specify the country code of the customer.

Nationality

Specify the nationality of the customer.

Language

Specify the language of the customer for communication.

Unique Identifier

You can provide the unique identifier details of the customer here.

Name

Specify the name of the unique identifier details of the customer.

Value

Specify the value of the identifier details of the customer.

KYC Status

Select the status of KYC checking of the customer from the following drop-down options:

- Yet to Verify
- Verified

Charge Group

Specify the charge group of the customer.

Passport Details

You can provide the passport details of the customer here.

Passport Number

Specify the passport number of the customer.


Issue Date

Specify the issue date of the customer passport.

Expiry Date

Specify the expiry date of the customer passport.

5.1.4 Certificate Details



The screenshot shows a window titled "Certificate Details". Inside, there is a table with the following columns: Control Number, Certificate Start no, Certificate End No, No of Certificates, Certificate Amount, and Currency. The table is currently empty. At the bottom right of the window, there are "Ok" and "Exit" buttons.

When you save the contract and system performs the following:

- Upon MC issuance to customers, if the cumulative value of MC held by the customer (including the current contract and by considering all the mapped customer reference number) exceeds the KYC limit then system would validate the KYC compliance of the CIF. If the CIF is not KYC compliant then system raises an error.

- Contracts initiated from FCDB source can only be viewed in the system. Customer can do further lifecycle in FCDB only. System would not allow any operations/processing on FCDB contracts through Oracle FLEXCUBE source.
- You can operate contracts initiated through other branches. For account transfer, system would post accounting entry to the branch in which the account is held.
- Reversal of MC contracts is allowed only if it has not undergone liquidation/reissuance and it should not be linked to any LMC contracts.
- Reversal of LMC contracts is allowed only if it has not undergone cancellation/rollover/reissuance/monthly interest amortization. In such reversals the accounting entries are reversed to refund the interest collected.
- During the reversal of MC contract, REVR entry gets fired and it reverses the INIT accounting entry.

5.1.5 Viewing Millionaire Certificate Contract Summary

You can view the summary of millionaire certificate contracts through the 'Millionaire Certificate Contract Summary' screen.

To invoke the 'Millionaire Certificate Contract Summary' screen, enter 'MBSTRONL' in the field at the top right corner of the Application Toolbar and then click the adjoining arrow button.

You can query the contract records with the following details

- Contract Reference
- Product Code
- Currency
- Contract Status
- Source Code
- Source Reference
- Authorization Status

Click 'search' button to view the records with the specified values.

5.1.6 Querying Customer Balance

You can query the MC and LMC holding balance of a customer in the 'Customer Balance Inquiry' screen.

To invoke the 'Customer Balance Inquiry' screen, enter 'MBDCUBAL' in the field at the top right corner of the Application Toolbar and then click the adjoining arrow button.

Customer Balance Inquiry

New

Enter Query

Customer No *
Control No

Customer Reference No ALL
Certificate No

Query

Balance Details

1 Of 1

Go

☐ Customer Reference No Product Code Contract Reference Control No Certificate Start No Certificate End No

No of MC Held

No of LMC Held

Exit

System would display the MC/LMC holding details of the given customer number and customer reference number.

Customer No

Specify the customer number/CIF to query the balance of that customer.

Customer Reference Number

Specify a valid reference number mapped to the selected customer number. You can select 'ALL' to view the consolidated holdings of the customer (across all customer reference number mapped to the CIF).

Control No

Specify the control number to query the balance.

Certificate Number

Specify the MC certificate number of the customer to query the balance.

Click 'Query' button to view the balance details as per the selected criteria. You can view the following details:

- Customer Reference No
- Record Code
- Contract Reference No
- Control No
- Certificate Start No
- Certificate End No
- Quantity
- Total Certificate Value

- Status

Number of MC held and Number of LMC held by the customer gets displayed.

5.1.7 **Mapping Customer Reference to CIF**

You can map a single or multiple customer reference number to a CIF with one of the customer reference number to be selected as default. Customer reference mapping can be done through 'Customer Reference Mapping' screen.

To invoke the 'Customer Balance Inquiry' screen, enter 'MBDCMAP' in the field at the top right corner of the Application Toolbar and then click the adjoining arrow button.

You can map customer reference number or multiple customer reference numbers to a CIF with one of the customer reference number to be selected as default here.

Customer No

Select the customer number or CIF for mapping the customer reference number.

Customer Reference Details

Customer Reference No

Select the customer reference number to map the selected customer number/CIF. The customer reference numbers which are yet to be mapped to a customer number are listed in the LOV.

You cannot map a customer reference number already mapped to one CIF to other CIF.

Default

Specify the default customer reference number of the selected customer. One of the mapped customer reference numbers has to be selected as the default reference number for the CIF.

6. Payment

This chapter elaborates upon the operations which can be performed using the function present as part of the Millionaire Certificate (MB) module of Oracle FLEXCUBE. These operations have been elaborated upon in the sections given below.

This chapter contains the following section:

- [Section 6.1, "Millionaire Certificate Payment Input"](#)

6.1 Millionaire Certificate Payment Input

This section contains the following topic:

- [Section 6.1.1, "Millionaire Certificate Payment Details"](#)

6.1.1 Millionaire Certificate Payment Details

You can liquidate or cancel the Millionaire Certificates or Lien Millionaire Certificates using the 'Millionaire Certificate Payment Input' screen. System allows you to perform partial liquidation for MC contracts also using the same screen.

To invoke the 'Millionaire Certificate Payment Input' screen, enter 'MBDTRPAY' in the field at the top right corner of the Application Toolbar and then click the adjoining arrow button.

Millionaire Certificate Payment Input

New

Version Number Of

Contract Details

Product Code *

Transaction Type * Liquidate

Active Certificates *

Contract Reference *

No of Certificate to Liquidate

Other Details

User Reference *

Currency *

Value Date *

Customer Reference

Control Number

Liquidated Certificate Amount

Charge Group

Product Description

Customer No *

Pay-in Option * Cash

Source Code * FLEXCUBE

Source Reference *

Issuance Price *

Book Date

Maturity Date

Account No/ GL Code *

LMC Control No

Certificate Details | Denomination Details | Charges | Fields

Input By Date Time Status

Checker Date Time Authorization Status

Exit

The following details are displayed here:

- Product Code
- Product Description
- Customer No
- Customer Reference Number
- Transaction Type as liquidate

Contract Reference No

Specify the contract reference number.

User Reference

Specify the user reference number.

Source Code

Specify the source of the contract.

Source Reference

Specify the source reference of the contract.

The following details are displayed:

- Value Date - system defaults the application date to value date.
- Book Date - book date of the contract
- Maturity Date - maturity date of the contract.
- Issuance Price - MC certificate value or LMC issuance price.

No of Certificates

Specify the number of certificates participating in the specified transaction type.

The computed contract value based on the number of certificates and issuance price gets displayed as amount.

Control Number

Specify the control number of pre-printed stationary/instrument which should be a valid stock number as maintained through 'Adjust Inventory Balance' - 'MC - Branch to User'.

System would accept this control number value only for partial liquidation of MC contract. The details of remaining active MC are printed on the instrument with the specified control number.

In case of complete liquidation of MC contract or cancellation of LMC contract, control number value has to be left blank/null.

For contracts initiated from FCDB source, system would not allow to track control number.

LMC Control Number

Specify the control number of pre-printed stationary/instrument which is a valid stock number as maintained through 'Adjust Inventory Balance' - 'MC - Branch to User'.

If the Liquidation of MC causes reduction in the eligibility of the LMC for that customer reference number, then auto liquidation of LMCs held by the customer is done. Hence this control number is used for the partially liquidated LMCs.

Pay-in option

Specify the pay option from the following drop down list:

- Cash
- Account Transfer

Account No/GL code

Upon selection of pay-in-option as cash, you should select the GL code (as maintained in pay-in parameters) from which the contract value would be debited. If the GL code is not selected then upon save system would default the relevant GL code from pay-in parameter maintenance.

For pay-in-option as account transfer, you should specify the customer account number (linked to the selected CIF). System would allow only LCY accounts to be selected.

Remarks

Specify any additional remarks for the Payment.

Charge Group

System defaults the charge group associated with the CIF to be used for the contract. You can modify the charge group of the contract.

Denomination Details

For cash payment, you can maintain denomination details. You should operationally maintain appropriate denomination details for the amount settled across counter which is not validated by the system.

7. Accounting Entries and Advices

This Annexure contains details of the suggested accounting roles and events related to the MB module of Oracle FLEXCUBE. The annexure lists details of the suggested accounting entries, event-wise. Supporting Advices and Notifications are also listed in this chapter in the following sections:

- [Section 7.1, "MB Events"](#)
- [Section 7.2, "Accounting Entries "](#)
- [Section 7.3, "Advices"](#)
- [Section 7.4, "Notification"](#)

7.1 MB Events

The following is an exhaustive list of events that are part of millionaire certificate product maintenance. In the subsequent paragraphs we shall examine the accounting entries for each of the events listed below.

Event Code	Event Description
BOOK	MC/LMC Book
INIT	MC/LMC Issuance
RIMC	MC/LMC Re-issuance
WIMC	MC Issuance to winners
LIQD	MC/LMC Liquidation
ROLL	LMC rollover
LMCA	LMC Monthly amortization
PROV	MC Monthly provision
CLOS	LMC Closure
REVR	Reversal

7.2 Accounting Entries

No accounting entries are maintained for BOOK and CLOS events. The accounting entries are maintained for other events as mentioned below:

7.2.1 MC Issuance – Cash/Cheque/Credit Card/Account transfer

Event	Accounting Role	Dr/Cr Ind	Amount tag	Amount tag Description
INIT	MC_CUST_AC_GL	Dr	CERT_AMT	Certificate value * No. of certificates
INIT	MC_CUST_AC_GL	Dr	<Charge-Class>_AMT	Issuance charge
INIT	MC_LIAB_GL	Cr	CERT_AMT	Certificate value * No. of certificates
INIT	<Charge-Class>_INC	Cr	<Charge-Class>_AMT	Issuance charge

7.2.2 MC Re-issuance

Event	Accounting Role	Dr/Cr Ind	Amount tag	Amount tag Description
RIMC	MC_CUST_AC_GL	Dr	<Charge-Class>_AMT	Re-Issuance charge
RIMC	<Charge-Class>_GL	Cr	<Charge-Class>_AMT	

7.2.3 MC Issuance to winners

Event	Accounting Role	Dr/Cr Ind	Amount tag	Amount tag Description
WIMC	HO_AC_CPC	Dr	CERT_AMT	Certificate value * No. of certificates
WIMC	MC_LIAB_GL	Cr	CERT_AMT	

7.2.4 MC Liquidation/Encashment

Event	Accounting Role	Dr/Cr Ind	Amount tag	Amount tag Description
LIQD	MC_LIAB_GL	Dr	CERT_AMT	Certificate value * No. of certificates
LIQD	MC_CUST_AC_GL	Cr	CERT_AMT	
LIQD	MC_CUST_AC_GL	Dr	<Charge-Class>_AMT	Pre-encashment fee
LIQD	MC_INCOME_GL	Cr	<Charge-Class>_AMT	

7.2.5 MC Monthly Provisioning

Event	Accounting Role	Dr/Cr Ind	Amount tag	Amount tag Description
PROV	MC_EXP_GL	Dr	PROV_AMT	Monthly provision amount. This would trigger an interbranch accounting entry (Debit the local branch and credit the HO).
PROV	MC_PROV_GL	Cr	PROV_AMT	

7.2.6 MC Reversal

Event	Accounting Role	Dr/Cr Ind	Amount tag	Amount tag Description
REVR	MC_CUST_AC_G L	Dr	CERT_AMT	Certificate value * No. of certificates (Negative amount)
REVR	MC_LIAB_GL	Cr	CERT_AMT	Certificate value * No. of certificates (Negative amount)

7.2.7 LMC Issuance

Event	Accounting Role	Dr/Cr Ind	Amount tag	Amount tag Description
INIT	LMC_ASSET_GL	Dr	CERT_AMT	Certificate value *
INIT	LMC_LIAB_GL	Cr	CERT_AMT	No. of certificates
INIT	MC_CUST_AC_GL	Dr	INT_AMT	Issuance price *
INIT	LMC_AD-V_INT_GL	Cr	INT_AMT	No. of LMC issued

7.2.8 LMC Manual Roll-over

Event	Accounting Role	Dr/Cr Ind	Amount tag	Amount tag Description
ROLL	MC_CUST_AC_GL	Dr	INT_AMT	Issuance price * No. of LMC issued
ROLL	LMC_AD-V_INT_GL	Cr	INT_AMT	

7.2.9 LMC Cancellation

Event	Accounting Role	Dr/Cr Ind	Amount tag	Amount tag Description
LIQD	LMC_LIAB_GL	Dr	CERT_AMT	Certificate value * No. of certificates

LIQD	LMC_ASSET_GL	Cr	CERT_AMT	
LIQD	LMC_ADV_INT_GL	Dr	UNAMOR-TIZED_INT_AMT	Unamortized interest amount
LIQD	LMC_INT_IN-COME_GL	Cr	UNAMOR-TIZED_INT_AMT	

7.2.10 LMC Monthly Amortization

Event	Accounting Role	Dr/Cr Ind	Amount tag	Amount tag Description
LMCA	LMC_ADV_INT_GL	Dr	AMOR-TIZE_INT_AMT	Amortized interest amount
LMCA	LMC_INT_IN-COME_GL	Cr	AMOR-TIZE_INT_AMT	

7.2.11 LMC Reversal

Event	Accounting Role	Dr/Cr Ind	Amount tag	Amount tag Description
REVR	LMC_ASSET_GL	Dr	CERT_AMT	Certificate value * (Negative Amount)
REVR	LMC_LIAB_GL	Cr	CERT_AMT	No. of certificates (Negative Amount)
REVR	MC_CUST_AC_GL	Dr	INT_AMT	Issuance price * (Negative Amount)
REVR	LMC_ADV_INT_GL	Cr	INT_AMT	No. of LMC issued (Negative Amount)

7.3 Advices

System supports the below mentioned advices.

Event	Advice Name	Advice Description	Supported Field Tags	Field Tag Description
INIT/ RIMC/ WIMC MB_ISSUE Millionaire Certificate Issuance			_CUST-NAME1_	Customer Name
			BRANCH-NAME	Branch Name
			_BOOK_DATE_	Booking Date
			_VALUE_DATE_	Value Date
			_ORIGINAL_PURCHASE_DATE_	Original Purchase Date
			_CERT_START_NUM_	Certificate Start Number
			_CERT_END_NUM_	Certificate End Number
			_NUM_CERT_	Number of Certificates
			_CERT_AMT_	Certificate Amount
			_CONTROL_NUM_	Control Number
			_CONTRACT_REF_NO_	Contract Reference Number

7.4 Notification

System supports gateway notification for the below mentioned events:

Event Code	Event Description
INIT	MC/LMC Issuance
RIMC	MC/LMC Re-issuance
WIMC	MC Issuance to winners
LIQD	MC/LMC Liquidation
ROLL	LMC rollover

8. Function ID Glossary

M		MBDTRONL 5-1
MBDCMAP 5-9		MBDTRPAY 6-1
MBDCUBAL 5-8		MBSDRMNT 3-8
MBDDRMNT 3-6		MBSMBPAY 3-3
MBDMBPAY 3-2		MBSMPROV 3-5
MBDMPROV 3-4		MBSPRMNT 4-5
MBDPRMNT 4-1		MBSTRONL 5-7