

Fixed Assets User Guide

Oracle FLEXCUBE Universal Banking

Release 14.4.0.0.0

Part No. F20443-01

MAY 2020

Fixed Assets User Guide
Oracle Financial Services Software Limited
Oracle Park

Off Western Express Highway
Goregaon (East)
Mumbai, Maharashtra 400 063
India

Worldwide Inquiries:

Phone: +91 22 6718 3000

Fax: +91 22 6718 3001

<https://www.oracle.com/industries/financial-services/index.html>

Copyright © 2007, 2020, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Contents

1. Preface	1-1
1.1 Introduction.....	1-1
1.2 Audience.....	1-1
1.3 Documentation Accessibility.....	1-1
1.4 Abbreviations.....	1-2
1.5 Organization	1-2
1.6 Glossary of Icons.....	1-3
2. Fixed Assets - An Overview	2-1
2.1 Introduction.....	2-1
2.2 Features of the Module.....	2-2
3. Maintenances for Fixed Asset Module	3-1
3.1 Asset Category Details	3-1
3.1.1 <i>Invoking Assets Category Maintenance Screen</i>	3-1
3.1.2 <i>Fields Button</i>	3-3
3.2 Codes for Asset Locations.....	3-3
3.2.1 <i>Invoking Location Code Maintenance Screen</i>	3-3
3.3 Branch Parameters Set-up for the Product	3-4
3.3.1 <i>Invoking Branch Parameters - Fixed Assets Screen</i>	3-4
3.4 Location Restrictions Classes	3-6
3.4.1 <i>Invoking Fixed Assets Location Restriction Class Maintenance Screen</i>	3-6
3.5 Asset Category Restriction Classes	3-7
3.5.1 <i>Invoking Asset Category Restriction Class Maintenance Screen</i>	3-8
3.6 Asset Rules Definition	3-9
3.6.1 <i>Invoking the Rule Definition – Fixed Assets Screen</i>	3-9
3.7 Asset Category and Location Rule Mapping	3-10
3.7.1 <i>Invoking the Asset Category Rule Mapping screen</i>	3-10
4. Defining a Product	4-1
4.1 Product Definition	4-1
4.1.1 <i>Invoking the Fixed Asset Product Maintenance Screen</i>	4-1
4.1.2 <i>Preference Button</i>	4-3
4.1.3 <i>Category Restrictions Button</i>	4-5
4.1.4 <i>Instrument Restrictions</i>	4-7
5. Processing Fixed Assets	5-1
5.1 Fixed Asset Details.....	5-1
5.1.1 <i>Invoking the Fixed Asset Capture Screen</i>	5-1
5.1.2 <i>Asset Details Tab</i>	5-2
5.1.3 <i>Depreciation Details Tab</i>	5-4
5.1.4 <i>Linkage Details Button</i>	5-6
5.1.5 <i>Asset Details Button</i>	5-7
5.1.6 <i>Ad hoc-Schedule Button</i>	5-8
5.2 Asset Transfer Details	5-9
5.2.1 <i>Invoking the Asset Transfer Details Screen</i>	5-9
5.2.2 <i>Asset Transfer Process</i>	5-11
5.3 Asset Sale Details	5-12

5.3.1	<i>Invoking Asset Sale Detail Button</i>	5-13
5.4	Asset Write Off Details	5-13
5.4.1	<i>Invoking the Asset Write Off Screen</i>	5-14
5.5	Authorizing Fixed Asset Contracts	5-14
5.5.1	<i>Invoking the Fixed Assets Authorization Screen</i>	5-14
5.6	Contract Reassign to another User	5-16
5.6.1	<i>Invoking the Fixed Assets Contract Reassign Screen</i>	5-16
5.7	Drill Down Query	5-17
6.	Annexure A - Accounting Entries and Advices	6-1
6.1	FA Events	6-1
6.2	Amount Tags	6-1
6.3	Accounting Roles.....	6-3
6.4	Event-wise Accounting Entries and Advices	6-3
7.	Glossary	7-1
7.1	Important Terms	7-1
8.	Function ID Glossary	8-1

1. Preface

1.1 Introduction

This user manual is designed to help you quickly get acquainted with the Fixed Assets (FA) module of Oracle FLEXCUBE.

The manual gives you an overview of the Fixed Assets module, and takes you through the various steps involved in setting up and maintaining a fixed asset.

You can obtain information specific to a particular field by placing the cursor on the relevant field, and striking <F1> on the keyboard.

1.2 Audience

This manual is intended for the following User/User Roles:

Role	Function
Back office clerk	Input functions for contracts
Back office managers/ officers	Authorization functions
Product Managers	Product definition and authorization
End of Day operators	Processing during End of Day/ Beginning of Day
Financial Controller/ Product Managers	Generation of reports

1.3 Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

1.4 Abbreviations

Abbreviation	Description
Oracle FLEX-CUBE	Oracle FLEXCUBE
FA	Fixed Assets
BOD	Beginning of Day
EOD	End of Day
PO	Purchase Order
MIS	Management Information System
SLM	Straight Line Method
WDV	Written Down Value method

1.5 Organization

This manual is organized into the following chapters:

Chapter	Description
Chapter 1	<i>About this Manual</i> gives information on the intended audience. It also lists the various chapters covered in this User Manual.
Chapter 2	<i>Fixed Assets - An Overview</i> is a snapshot of the features that the module provides.
Chapter 3	<i>Maintenances for Fixed Assets Module</i> details the maintenances required for fixed assets.
Chapter 4	<i>Defining a Product</i> details the procedure to set up FA products.
Chapter 5	<i>Processing Fixed Assets</i> discusses the processing of the fixed asset.
Chapter 6	<i>Annexure A - Accounting Entries and Advices</i> contains an event-wise list of suggested accounting entries and advices.
Chapter 7	<i>Glossary</i> defines the important terms list in the module.
Chapter 8	<i>Function ID Glossary</i> has alphabetical listing of Function/Screen ID's used in the module with page references for quick navigation.

1.6 Glossary of Icons

This User Manual may refer to all or some of the following icons:

Icons	Function
	Exit
	Add row
	Delete row
	Option List

2. Fixed Assets - An Overview

2.1 Introduction

The Fixed Assets module is a complete front-end module of Oracle FLEXCUBE that captures and tracks the characteristics of the fixed asset of your bank. Using this module you can clearly identify the various applicable events and manage all the activities during the assets useful lifecycle.

Fixed asset, also known as property, plant, and equipment (PP&E), is a term used in accountancy for assets and property which cannot easily be converted into cash. This can be compared with current assets such as cash or bank accounts, which are described as liquid assets. In most cases, only tangible assets are referred to as fixed.

Fixed assets normally include items such as land and buildings, motor vehicles, furniture, office equipment, computers, fixtures and fittings, and plant and machinery. These often receive favorable tax treatment (depreciation allowance) over short-term assets.

Fixed Assets are items of property, plant and equipment engaged by a business entity in the generation and expansion of revenue. According to International Accounting Standard (IAS) 16, Fixed Assets are assets whose future economic benefit is probable to flow into the entity, whose cost can be measured reliably.

It is pertinent to note that the cost of a fixed asset is its purchase price, including import duties and other deductible trade discounts and rebates. In addition, cost attributable to bringing and installing the asset in its needed location and the initial estimate of dismantling and removing the item if they are eventually no longer needed on the location.

Depreciation is simply put to be the expense generated by the use of an asset. It is the wear and tear of an asset or diminution in the historical value owing to usage. Further to this, it is the cost of the asset less any salvage value over its estimated useful life. It is an expense because it is matched against the revenue generated through the use of the same asset. Depreciation is usually spread over the economic useful life of an asset because it is regarded as the cost of an asset absorbed over its useful life. Invariably the depreciation expense is charged against the revenue generated through the use of the asset. The method of depreciation to be adopted is best left for the management to decide in consideration to the peculiarity of the business, prevailing economic condition of the assets and existing accounting guideline and principles as implied in the organizational policies.

The primary objective of a business entity is to make profit and increase the wealth of its owners. In the attainment of this objective it is required that the management will exercise due care and diligence in applying the basic accounting concept of "Matching Concept". Matching concept is simply matching the expenses of a period against the revenues of the same period.

The use of assets in the generation of revenue is usually more than a year- that is long term. It is therefore obligatory that in order to accurately determine the net income or profit for a period depreciation is charged on the total value of asset that contributed to the revenue for the period in consideration and charge against the same revenue of the same period. This is essential in the prudent reporting of the net revenue for the entity in the period.

The product definition function, the mainstay of Oracle FLEXCUBE's design, enables you to create products for specific fixed asset that you set up. The module gives you the *flexibility* to define components (charge), restrictions (branch), preferences, events and accounting entries into 'Classes'. When defining a product, you merely need to associate it with the different classes that you have built.

This chapter contains the following sections:

- [Section 2.2, "Features of the Module"](#)

2.2 Features of the Module

Definition of Classes

In Oracle FLEXCUBE, a 'Class' embodies a generic set of attributes. A class could represent:

- a set of *restrictions* (branch, locations, asset category)
- a set of events and the corresponding accounting roles and heads
- a *component* (charge)

As part of your one-time set up, you can define several sets of classes of a particular type. In Oracle FLEXCUBE, therefore, you do not have to specify restrictions, preferences, and components every time you create a product. You only need to associate the different set of classes that you have already maintained.

This feature eliminates redundancy, and saves processing time.

Note

The process to create a class is discussed in the Procedures User Manual of Oracle FLEXCUBE.

Creating Products

When setting up the module, you can define the various parameters for the assets. For each product, you can also define 'attributes', or in other words, the terms and conditions. When a user at the bank actually processes a fixed asset, it can be associated with a product. The asset acquires the terms *defined for the product that it involves*. (However, you can allow a user to change the inherited attributes of an asset for specific transactions.)

Processing Depreciation

The depreciation charge processing will be done as part of the End of Day and Beginning of Day processing. This will process all the assets for depreciation depending on frequency of the depreciation that you specify in the 'Asset Category – Rule mapping maintenance' screen.

The Depreciation rate can be maintained in Oracle FLEXCUBE for a combination of asset category and the location where the asset is placed. Separate rates can be maintained for computing depreciation for tax and book purpose.

3. Maintenances for Fixed Asset Module

You need to maintain certain details before you start entering the details of the assets.

Therefore, you need to maintain the following information as part of processing fixed assets:

- Asset category maintenance
- Locations maintenance
- Branch Parameters
- Class(es) for locations restrictions
- Class(es) for category restrictions
- Asset category restrictions
- Rule definition

This chapter enumerates the maintenance of the above mentioned parameters used by the Fixed Assets module in Oracle FLEXCUBE:

This chapter contains the following sections:

- [Section 3.1, "Asset Category Details"](#)
- [Section 3.2, "Codes for Asset Locations"](#)
- [Section 3.3, "Branch Parameters Set-up for the Product"](#)
- [Section 3.4, "Location Restrictions Classes"](#)
- [Section 3.5, "Asset Category Restriction Classes"](#)
- [Section 3.6, "Asset Rules Definition"](#)
- [Section 3.7, "Asset Category and Location Rule Mapping"](#)

3.1 Asset Category Details

This section contains the following topics:

- [Section 3.1.1, "Invoking Assets Category Maintenance Screen"](#)
- [Section 3.1.2, "Fields Button"](#)

3.1.1 Invoking Assets Category Maintenance Screen

In the 'Asset Category Maintenance' screen, you can group all the assets that are similar under one category. This will be useful for charging a common depreciation rate, generating MIS reports etc. You can also define the useful life for different categories of assets.

You can invoke this screen by typing 'FADACAT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows the 'Asset Category Maintenance' application window. At the top, there is a toolbar with 'New' and 'Enter Query' buttons. The main content area contains the following fields and options:

- Category Code * (text input)
- Category Description * (text input)
- Main Category (dropdown menu)
- Useful Life * (text input)
- Useful Life Unit: Year, Month
- Calculation Depreciation On: Capitalization Amount, Capitalization Amount - Residual Value

At the bottom, there is a 'Fields' section with the following details:

- Input By: Date Time
- Authorized By: Date Time
- Modification Number: Authorized, Open

Specify the following:

Category Code

You have to specify the unique code to identify the category for the asset. You will not be able to modify the category code once it is authorized.

Note

You can restrict usage of any asset category by disallowing the category in Asset category restriction screen, accessed through the product maintenance screen.

Category Description

You have to capture a brief description about the asset category that you are defining. For example you could create a category called Land and categorize all immovable assets under this category. You could assign a description called Lands and Buildings to this category.

Main Category

You can choose the main category code for the asset from the drop down list. For example for an asset like car, you can have Vehicle as your main category. This is meant for information purposes only.

Useful Life

Mention the useful life of the asset in this field. If you select the Year as your useful life unit in the next field then you have to mention the number of years the asset will be active.

If your preference is Month then mention the number of months for which the asset is useful.

The significance of capturing this information is that if the depreciation is adhoc, the rates captured at the contract level should cover the useful life of the asset. Also, the sum of the depreciation rates should add up to hundred percent for the useful life period. However, if the depreciation is rule based, this will have no effect on the depreciation calculation.

Useful Life Unit

This is where you can mention the unit for measuring the useful life of an asset. The useful life unit can be Year or Month and this will determine the useful life mentioned in the previous field.

Calculation Depreciation On


Here you can mention whether you want to calculate the depreciation on the capitalization amount or on capitalization amount minus the residual value. You can indicate your preference by clicking against the option.

Note

Residual Value is the scrap value of the asset which can be realized when the asset is sold after its useful life is complete. Residual value is often determined on the basis of judgment. Hence, Oracle FLEXCUBE allows you to change the Residual Value of the asset during its existence.

3.1.2 Fields Button

You can associate values to all the User Defined fields created and attached to the 'Asset Category Maintenance' screen. You can view the list of User Defined fields associated to this screen by clicking 'Fields' button on the 'Asset Category Maintenance' screen.



You can enter the value for the UDFs listed here in the 'Value' column.

For more details on how to create user Defined fields, refer chapter 'Creating custom fields in Oracle FLEXCUBE' in the User Defined Fields User Manual under Modularity.

3.2 Codes for Asset Locations

This section contains the following topics:

- [Section 3.2.1, "Invoking Location Code Maintenance Screen"](#)

3.2.1 Invoking Location Code Maintenance Screen

Through the 'Location Code Maintenance' screen, you can assign a unique location code to identify different locations where the asset physically exists.

You can invoke this screen by typing 'FADLOCN' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Fields		
Input By Date Time	Authorized By Date Time	Modification Number
		<input type="checkbox"/> Authorized
		<input type="checkbox"/> Open

Specify the following:

Location Code

You have to capture a code to identify the particular location. You will not be able to modify it once it is authorized. You can pick this code from the Asset Capture screen and the system will default the description for the location.

Note

You can restrict usage of any location by disallowing the location in Locations Restriction screen, accessed through the 'Product Maintenance' screen.

Description

In this field, you can specify any general information of the location such as the name of the city, pin code etc.

3.3 Branch Parameters Set-up for the Product

This section contains the following topics:

- [Section 3.3.1, "Invoking Branch Parameters - Fixed Assets Screen"](#)

3.3.1 Invoking Branch Parameters - Fixed Assets Screen

You can define parameters at the branch level for functions such as depreciation period, residual value for writing off an asset, the cut off date for an asset to be included for depreciation for the particular period, etc.

You can invoke the 'Branch Parameters – Fixed Assets' screen by typing 'FADBRMNT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Specify the following:

Branch Code and Branch Description

Select the code for the branch, for which you want to define the parameters, from the option list. Once you select the branch code, the description of the branch is defaulted in the next field.

Process Depreciation Till

Here you have to mention the date on which the depreciation has to be processed. It can be either the System date or the Next Working Day – 1.

If you select the System date, the depreciation will be processed only till the day on which EOD is run. If your choice is Next Working Day – 1, then the depreciation will be processed till the last day before the next working day when the batch process is run during EOD. This is applicable only for working days within a month. For instance, if Today's Date is 10th June and the Next Working Date is 15th June, the system will pass accounting entries for contracts falling due up to 14th June during the EOD processes executed on 10th June. But, if Today's Date were 28th June and the Next Working Date happens to be 3rd July, the processing will be done only upto the 30th of June since it is the month end. The system will post the accounting entries for the first and second of July during the BOD process executed on the 3rd of July.

Note

This is with the assumption that the Accounting Period is Monthly. If it were to be Quarterly, the processing will be done till the end of the period which is the corresponding quarter.

3.3.1.1 Depreciation Parameters

Specify the following:

Depreciation Period

The calculation of depreciation for the year is based on the depreciation period, considering the cutoff period and date. You can choose the period from the option list positioned next to this field. The choices are:

- Monthly
- Quarterly
- Half-yearly
- Yearly

Cut Off Date and Cut Off Period

You need to mention the cut off date and cut off month for calculating the depreciation for the asset. If the asset is acquired before the mentioned cutoff date and cut off month, the depreciation is calculated for the full period.

If the depreciation period chosen in the previous field is Quarterly, Half Yearly or Yearly, you have to specify the cut off date and cut off month.

If the depreciation frequency chosen in the previous field is Monthly, then you need to mention only the cut off date.

The depreciation is calculated from the next period if the asset is acquired after the cut off period.

Amortize over full Period

Specify if you want to amortize over the full period by checking the box. When an asset is acquired after the specified cut off date and month, the depreciation will be calculated from the next period and it will amortize the depreciation over the period of acquisition also.

If you leave this box unchecked, then the amortization will be done from the next period.

3.4 Location Restrictions Classes

This section contains the following topics:

- [Section 3.4.1, "Invoking Fixed Assets Location Restriction Class Maintenance Screen"](#)

3.4.1 Invoking Fixed Assets Location Restriction Class Maintenance Screen

You can define restrictions for certain locations that can be defaulted at the product level.

You can invoke the 'Fixed Assets Location Restriction Class Maintenance' screen by typing 'FADLOCCL' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows the 'Fixed Assets Location Restriction Class Maintenance' application window. The window title is 'Fixed Assets Location Restriction Class Maintenance'. The interface includes a top toolbar with 'New' and 'Enter Query' buttons. The main form area contains the following elements:

- Class Code ***: A text input field.
- Description ***: A text input field.
- Module**: A dropdown menu set to 'FA', with a sub-menu showing 'Fixed Assets'.
- Restriction Type**: Radio buttons for 'Allowed' (selected) and 'Disallowed'.
- Location Restriction**: A table with columns 'Code' and 'Description'. The table is currently empty.
- Fields**: A section at the bottom with labels for 'Input By Date Time', 'Authorized By Date Time', and 'Modification Number'. There are checkboxes for 'Authorized' and 'Open'.

Specify the following:

Class Code and Description

You can identify a Location Restriction class that you build with a unique ten character Class Code and a brief description.

You can follow your own convention for devising the code. The description that you specify is for information purposes only and will not be printed on any customer correspondence.

Restriction Type

You can specify Location restrictions either in the form of an 'Allowed' type, or in the form of a 'Disallowed' type.

When you associate a restriction class with a product, those locations that do not figure in the list cannot offer the service. If you have maintained a disallowed type for a class, locations that do not figure in it can offer the service.

Location Restriction

Specify the following:

Code and Description

You can select location code from option list based on the 'Restriction Type' selected for a class.

3.5 Asset Category Restriction Classes

This section contains the following topics:

- [Section 3.5.1, "Invoking Asset Category Restriction Class Maintenance Screen"](#)

3.5.1 Invoking Asset Category Restriction Class Maintenance Screen

An asset category restriction class identifies a unique list of allowed or disallowed categories. At your head office, you can associate a product that you propose to offer with any Asset Category Restriction Class that you have maintained. The asset category restrictions defined for the class will apply to the service.

Note

Any product that your bank offers is available to all asset categories, by default, unless you specifically restrict its availability.

You will be able to define Asset category restriction classes through the 'Asset Category Restriction Class Maintenance' screen. You can invoke this screen by typing 'FADCATCL' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button. The asset category restriction classes that you define and authorize in this screen are the ones which can be used while creating the Fixed Assets products.

The screenshot shows the 'Fixed Assets Category Restriction Class Maintenance' application window. The title bar includes a diamond icon and the text 'Fixed Assets Category Restriction Class Maintenance'. Below the title bar is a toolbar with 'New' and 'Enter Query' buttons. The main content area contains several input fields: 'Class Code *', 'Description *', 'Module' (with 'FA' entered), and 'Fixed Assets'. Below these is a 'Restriction Type' section with two radio buttons: 'Allowed' and 'Disallowed' (which is selected). A 'Restricted Categories' table is present, with columns for 'Code *' and 'Description'. At the bottom of the window, there is a 'Fields' section with checkboxes for 'Input By Date Time', 'Authorized By Date Time', 'Modification Number', 'Authorized', and 'Open'.

An Asset Category Restriction Class, is identified by a unique Code and a Description.

The asset category classes that you maintain have to be specific to a module in Oracle FLEXCUBE. This is because, a class maintained for one module would be unsuitable for another.

Class Code and Description

You can identify a Category Restriction class that you build with a unique ten character Class Code and a brief description.

Restriction Type

You can specify Category restrictions either in the form of an 'Allowed' type, or in the form of a 'Disallowed' type.

When you associate a restriction class with a product, those categories that do not figure in the list cannot offer the service. If you have maintained a disallowed type for a class, categories that do not figure in it can offer the service.

Restricted Categories

Specify the following:

Code and Description

You can select location code from option list based on the 'Restriction Type' selected for a class.

3.6 Asset Rules Definition

This section contains the following topics:

- [Section 3.6.1, "Invoking the Rule Definition – Fixed Assets Screen"](#)

3.6.1 Invoking the Rule Definition – Fixed Assets Screen

For every asset and category combination, you can maintain different rates for depreciation. You can record the depreciation rates for the asset category and the location combination.

You can invoke the 'Rule Definition – Fixed Assets' screen by typing 'FADRULDF' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Specify the following:

Rule Code and Description

Give a unique code to identify the rule you are going to define. This code cannot be modified later. You can give a brief description for the code in the description field.

Rate

You have to specify rate for calculating the depreciation for the asset. This rate can be specified for time period in case the asset is dependent on capitalization. In this case, different rates can be maintained for the first year only. The Rate over Periods has to be entered in DD-MON format.

If you have selected Independent of capitalization as your rate type, then the rate will be set for the whole useful period of the asset.

Note

The depreciation rate has to be mentioned in percentage.

Rate Type

If you want to have a different depreciation rates for different periods of acquisition in the first year of the asset life then chose Dependent on capitalization. In contradiction to this, you can choose Independent of capitalization to keep a single rate type through out the life of the asset.

Rate over periods

Specify the following:

Start Date and End Date

If the rule type is dependent on capitalization, and if the effective depreciation date falls between the Start and End date, the rates that you specify in this section of the screen will be considered for computing depreciation. Else, the value that you have specified in the Rate field will be considered.

Note

This is applicable for the first year only.

3.7 Asset Category and Location Rule Mapping

This section contains the following topics:

- [Section 3.7.1, "Invoking the Asset Category Rule Mapping screen"](#)

3.7.1 Invoking the Asset Category Rule Mapping screen

Through the asset category – location rule mapping screen, you can map predefined depreciation rules to a combination of asset category and location. You can also define various depreciation parameters such as depreciation method for book and tax purposes, frequency of depreciation, depreciation rate type etc.

You can invoke the 'Asset Category Rule Mapping' screen by typing 'FADRULMP' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Specify the following:

Asset Category

Choose the category code for the asset, from the list available. Once you choose the asset category code, the description for the category will be displayed in the next field.

Location Code

You can select the location code for the asset from the given option list.

Depreciation Type

You have to mention the type of depreciation required for the asset. The two options available are Rule based and Ad-hoc.

If you select Rule based type of depreciation, then a fixed percentage is depreciated every year.

If you chose ad-hoc as the depreciation type then you have to maintain depreciation rates in the Depreciation Maintenance screen at the Asset Capture level. In such a scenario, the fields for rule are not applicable.

Depreciation Parameters Book and Tax

Specify the following:

Method

Here you have to indicate if you want SLM (Straight Line Method) or WDV (Written Down Value Method) as your depreciation method. Choose the method of depreciation by clicking on the appropriate option.

This data is maintained for both book of accounts and tax purposes.

Frequency

You need to mention the start date and the start month to determine when the first cycle of the depreciation accounting entries are to be posted.

Select the frequency for calculating of depreciation from the option list. This data is recorded for both book of accounts and tax purposes.

Frequency Start Date

Mention the start date to determine when the first cycle of the depreciation accounting entries are to be posted.

This data is recorded for both book of accounts and tax purpose.

Frequency Start Month

Mention the start month to determine when the first cycle of the depreciation accounting entries are to be posted.

This data is recorded for both book of accounts and tax purpose.

Rule

Select the rule to be used for depreciation from the option list. This data is recorded for both book of accounts and tax purpose.

Refer the section on Depreciation Maintenance for details on maintaining depreciation percentage for each period.

4. Defining a Product

In this chapter, we shall discuss the manner in which you can define attributes specific to a Fixed Assets (FA) product.

This chapter contains the following sections:

- [Section 4.1, "Product Definition"](#)

4.1 Product Definition

This section contains the following topics:

- [Section 4.1.1, "Invoking the Fixed Asset Product Maintenance Screen"](#)
- [Section 4.1.2, "Preference Button"](#)
- [Section 4.1.3, "Category Restrictions Button"](#)
- [Section 4.1.4, "Instrument Restrictions"](#)

4.1.1 Invoking the Fixed Asset Product Maintenance Screen

You can access the Fixed Asset 'Product Maintenance' screen, by typing 'FADPRMNT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button. In this screen, you can enter basic information relating to a FA product such as the Product Code, Product type, the Description, etc.

The screenshot shows the 'Fixed Assets Product Definition' window. It features a 'New' button at the top left. The main area contains a form with the following fields:

- Product Code *
- Product Description *
- Product Type
- Description
- Slogan
- Product Group
- Product Group Description
- Start Date
- End Date
- Remarks
- Exchange Rate Variance (%)
- Override Limit * (value 3)
- Stop Limit * (value 100)
- Rate Code * (dropdown menu)
- Rate Type Preferred *

At the bottom of the window, there is a navigation bar with the following buttons: Accounting Roles, Events, Branch & Currency, MIS, Preferences, Category Restrictions, Instrument Restrictions, Charges, and Fields. Below this bar is a status bar with the following fields: Maker, Checker, Date Time, Mod No, Record Status, Authorization Status, and an Exit button.

For any product data you create in Oracle FLEXCUBE, you can define generic attributes, such as branch, location, and category, etc., by clicking on the appropriate button in the horizontal array of buttons in this screen.

You can define the attributes specific to a FA product in the 'FA Product Definition' Main screen and the 'FA Product Preferences' screen. In these screens, you can specify the product type and set the product preferences respectively.

For further information on the generic attributes that you can define for a product, please refer the following Oracle FLEXCUBE User Manuals under Modularity:

- Product Definition
- Charges
- User Defined Fields

Product Code

You can associate every FA contract that you maintain in Oracle FLEXCUBE with a Product that you have maintained in this screen.

When you associate a contract with a product, it acquires the attributes defined for the product. This means, you do not have to define the attributes of the contract/transaction/deal, all over again, when maintaining it.

Identify the product that you are creating with a unique Product Code. This code should be unique across all the modules of Oracle FLEXCUBE.

Product Description

In this field, briefly describe the product that you are maintaining. The description that you enter here will help you identify the product all through the module.

Product Type

An important detail in defining a product is to specify the type of product you are creating. The product type identifies the basic nature of a product. This helps to classify the product.

Slogan

You can enter a slogan for the product that you are creating. In this field, enter a slogan that suitably announces the product to your customers.

Product Group

Grouping products, according to the common features they share, helps you organize information relating to the services you provide. Product Groups also help you retrieve information easily.

In this field, you can invoke a list of the product groups that you have maintained in your bank. Choose the product group to which the product that you are creating belongs.

Start Date

When you create a product, you must specify a date from which it can be offered. Enter this date in the Start Date field.

End Date

You can choose to specify the date up to, which a product is open. Enter this date in this field. You cannot enter a date that is earlier than the current system date.

Note

You cannot offer a product beyond the specified end date. If you do not specify an end date for a product, you can offer it for an indefinite period.

Remarks

If you would like to enter any remarks relating to the product, do so in this field. This information is for your reference.

Exchange Rate Variance (in %)

For a special customer, or in special cases, you may want to use an exchange rate (a special rate) that is greater than the exchange rate maintained for a currency pair. The variance is referred to as the Exchange Rate Variance.

When creating a product, you can express an Exchange Rate Variance Limit in terms of a percentage. This variance limit would apply to all FA contracts associated with the product.

Override Limit

In this field, you can enter an Override limit. The implication of your entry in this field is discussed below.

If the variance between the default rate and the rate input varies by a percentage that is between the 'Override Limit' and the 'Rate Stop Limit' (that you specify in the Stop Limit field), you can save the transaction by providing an 'Override'.

Stop Limit

For a special customer, or in special cases, you may want to use an exchange rate (a special rate) that is greater than the exchange rate maintained for a currency pair. The variance is referred to as the Exchange Rate Variance.

When creating a product, you can express an Exchange Rate Variance Limit in terms of a percentage. This variance limit would apply to all FA contracts associated with the product.

In this field, you can enter the Stop Limit. The implication of your entry in this field is discussed below.

Rate Code

If the Charge Currency is different from the Contract Currency the rate associated with the Rate Code will be picked up.

Select the appropriate from the drop-down list.

Rate Type Preferred

If the Charge Currency is different from the Contract Currency the rate associated with the Rate Code will be picked up.

Select the appropriate rate type from the drop-down list.

4.1.2 Preference Button

The attributes specific to an asset are defined in the Preferences screen.

You can invoke 'Fixed Asset Product - Preferences' screen from the 'Product Maintenance' screen by clicking 'Preferences' button.

Fixed Assets Product Preferences

Product Code

Description

Purchase Order Required Yes No

Depreciation Processing Required For Book Yes No

Depreciation Processing Required For Tax Yes No

Rekey Required Yes No

Asset Cost

Capitalization Date

Depreciation Effective Date

Ok Exit

Specify the following:

Product Code

This is the code for the product that you are defining here. The code is defaulted from the 'Product Definition' screen.

Product Description

This is the description of the product that is being defined. This is defaulted from the product definition screen.

Purchase Order Required

You have to indicate whether a purchase order is required or not for procuring a new FA. Choose 'Yes' if you need the PO (Purchase Order) or choose 'No' to indicate otherwise.

Note

If your preference for PO is 'Yes' then you will have to link an XP (Expense Processing) contract in the FA Capture screen for the asset. FA and XP modules are closely linked to each other. Payments for the asset purchased are done through XP module, and the XP contract reference number would be internally linked to FA module for the purpose of capitalizing the asset and calculating depreciation.

Depreciation Processing Required for TAX and BOOK

You have to mention if you want the depreciation process to be carried out for the asset. Choose your preference by clicking on YES or NO accordingly.

If you choose No then the depreciation will not be charged for the assets which come under this product.

This data is maintained for both books of account as well as tax purposes.

Note

Accounting entries will be passed only for book type of depreciation.

Rekey Required

Indicate if you require any parameters to be keyed in, at the time of authorization, for the asset.

Rekey Parameters

All operations on a FA contract have to be authorized by a user other than the one who carried out the operation. Authorization is a cross checking mechanism to ensure that the entries made by a user are correct. All operations on a FA contract except placing it on hold, should be authorized before the beginning of the End of Day operations.

You have the option of specifying whether certain important details of the FA contract need to be rekeyed, at the time of authorization. If you enable this option you should also specify the field that will have to be rekeyed at the time of contract authorization. You can specify any one of the following rekey fields:

- Asset Cost
- Capitalization Date
- Depreciation Effective Date

When you invoke a FA contract for authorization, the complete details of the contract will be displayed only after the values to the rekey fields are entered. Suppose you choose not to define any rekey fields the details of the contract will be displayed immediately once the authorizer calls the FA contract for authorization. The re-key option also serves as a means of ensuring the accuracy of inputs.

4.1.3 Category Restrictions Button


You can define specific restrictions for an asset at the product level. They are:

- Asset category restrictions
- Locations restrictions

You have already categorized assets that share similar attributes in the Asset Category Maintenance screen. The categorization of assets is useful for charging a common depreciation rate, generating MIS reports etc. You can also define the useful life for different categories of assets.

While creating an FA product, you may want to establish certain controls by restricting the usage of the product to select asset categories only. You can achieve this control by maintaining restriction lists when creating a product.

Click 'Category Restrictions' button to display the 'Asset Category Restriction' screen.



You can choose to specify Asset Category Restrictions either by:

- Associating the product with a Asset Category Restriction class
- By defining these restrictions specifically for the product

Product Code

This is the code for the product that you are defining here. The code is defaulted from the 'Product Definition' screen.

Product Description

This is the description of the product that is being defined. This is defaulted from the product definition screen.

Class Code

This is the unique identifier for the class. You can default the asset category restrictions from the previous defined class by clicking on the 'Default From Class' button.

Class Description

A brief description of the class code is displayed here.

For more details refer section titled 'Maintaining Location Restrictions Classes' in the chapter 'Maintenance for Fixed Asset'.

Restriction Type

You have categorized assets that share similarities under one category through the Asset Category Maintenance screen.

You can specify asset category restrictions for a fixed asset product either in the form of an 'Allowed' list, or in the form of a 'Disallowed' list. Choose the appropriate option to indicate the List Type that you would like to maintain.

You cannot deal in asset categories, which do not figure in an 'Allowed' list. Alternatively, if you maintain a 'Disallowed' list, you can deal in asset categories that do not figure in the list.

Fixed Assets Category Restrictions

Specify the following:

Category Code

You have to specify the unique code to identify the category for the asset. You will not be able to modify the category code.

Description

Enter any information regarding the asset category. This information can be the type of the category and the assets it will hold under this category etc.

If you would like to *associate a restrictions class* to a product that you are defining, choose the 'Default From Class' button in the 'Fixed Assets Category Restriction' screen. A list of the restrictions classes that you have defined specifically for the Fixed Assets module will be displayed. Choose a suitable Restrictions class.

Alternatively, you can choose to define asset category restrictions *specifically* for the product. In this case, you would choose not to associate restriction classes with the product. You would define restrictions for the product by:

- Specifying the List type – wherein you restrict the usage of an asset category (or asset categories as the case may be) to the product by maintaining an Allowed or Disallowed list.
- Move a Category to the Allowed/Disallowed column depending on the list type that you choose to maintain

4.1.4 Instrument Restrictions

Through the Location Code maintenance you have assigned unique location codes to identify different locations where the asset physically exists. Using the 'Fixed Assets Location Restrictions' screen you can restrict the usage of a product to specific locations. Click 'Instrument Restrictions' button to invoke the 'Fixed Assets Product Location Details' screen.

The screenshot shows a software window titled "Fixed Assets Product Location Details". It features several input fields for "Product Code", "Product Description", "Class Code", and "Class Description". A "Default From Class" button is positioned next to the "Class Description" field. Below these fields, there are radio buttons for "Restriction Type", with "Disallowed" selected. A "Locations" section contains a table with columns "Location Code" and "Location Description". The table is currently empty. At the bottom right, there are "Ok" and "Exit" buttons.

The details of all the locations that you have maintained will be displayed here. You can choose to specify the Location Restrictions either by associating the product with a Location Restriction class or by defining these restrictions specifically for the product.

Product Code

This is the code for the product that you are defining here. The code is defaulted from the 'Product Definition' screen.

Product Description

This is the description of the product that is being defined. This is defaulted from the product definition screen.

Class Code

Enter a unique identifier for the class. Also give a brief description of the class in the free format text field positioned next to the class code.

Restriction Type

You can specify asset location restrictions for a fixed asset product either in the form of an 'Allowed' list, or in the form of a 'Disallowed' list. Choose the appropriate option to indicate the List Type that you would like to maintain.

You cannot deal in asset locations, which do not figure in an 'Allowed' list. Alternatively, if you maintain a 'Disallowed' list, you can deal in asset locations that do not figure in the list.

Locations

Specify the following:

Location Code

This is the code for the particular location. You can pick this code from the Asset Capture screen and the system will default the description for the location. This description can be modified.

Description

In this field, you can specify the general information of the location such as the name of the city, pin code etc.

5. Processing Fixed Assets

In Fixed assets module of Oracle FLEXCUBE you can capture static details such as Asset Code, Asset Cost, Date of Acquisition, Date of capitalization, Location, Asset category code etc. You cannot change the FA product associated with the contract during the entire life cycle of the asset.

Fixed Assets purchase/acquisition online processing function enables you to perform the following functions:

- Amendment/ change in FA details
- Copy existing FA details for recording details of new FA
- Delete/Undo of a FA record from one user to another
- Recording of individual items for an Asset
- Recording of FA-XP contract linkages
- Any other fields may be captured using UDF

This chapter explains the processing of purchase or acquisition of an FA.

This chapter contains the following sections:

- [Section 5.1, "Fixed Asset Details"](#)
- [Section 5.2, "Asset Transfer Details"](#)
- [Section 5.3, "Asset Sale Details"](#)
- [Section 5.4, "Asset Write Off Details"](#)
- [Section 5.5, "Authorizing Fixed Asset Contracts "](#)
- [Section 5.6, "Contract Reassign to another User"](#)
- [Section 5.7, "Drill Down Query"](#)

5.1 Fixed Asset Details

This section contains the following topics:

- [Section 5.1.1, "Invoking the Fixed Asset Capture Screen"](#)
- [Section 5.1.2, "Asset Details Tab"](#)
- [Section 5.1.3, "Depreciation Details Tab"](#)
- [Section 5.1.4, "Linkage Details Button"](#)
- [Section 5.1.5, "Asset Details Button"](#)
- [Section 5.1.6, "Ad hoc-Schedule Button"](#)

5.1.1 Invoking the Fixed Asset Capture Screen

You can capture the various details of the asset such as asset code, asset cost, date of acquisition, date of capitalization, location, asset category code etc. Through this screen you can associate the asset to a product code and the all the restrictions maintained at the Product level will be enforced while you record the new asset. You are not allowed to change the product associated with the asset during the life cycle of the asset once you have associated the product to the asset.

You can invoke the 'Fixed Assets Asset Capture' screen by typing 'FADTRONL' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The Asset capture screen consists of the following screens:

- FA Main details
- FA Items
- Depreciation details
- FA-XP contract linkage
- FA depreciation view

Each of the above mentioned screens and the data captured in each screen are explained in detail in this chapter.

Specify the following details:

Product Code

Choose a product code from the option list. All the preferences defined at the product level will be defaulted. Once you specify the product code, the system will create the reference number in the next field for the asset.

Contract Reference Number

The system automatically creates the reference number for the asset.

The reference number generated is a combination of branch code, product code, the Julian date of transaction input and a running serial number.

Product Description

Once you have selected the product code, the product description is displayed.

User Reference Number

You can enter any reference number for a FA contract that you process. The FA contract will be identified through this number in addition to the Contract Reference Number generated by the system. Two FA contracts cannot have the same User Reference Number. By default, the Contract Reference Number generated by the system will be taken as the User Reference Number. You can use this number, to retrieve information relating to an FA contract.

5.1.2 Asset Details Tab

Capture the following details:

Category

You can link the asset to an existing asset category that is not restricted for the branch. Choose the category of the asset from the option list.

Location

Identify the location at which the asset is currently stationed. The option list will display the list of locations based on the restrictions maintained at the product definition screen.

Location Description

On selecting the location, the description of the location is displayed.

Asset Currency

This is the local currency of the branch. You will not be allowed to modify this data.

Asset Cost

Enter the value of the asset in this field.

Asset Description

In this field, you can enter the description of the asset stating whether the asset is an office building or computers etc.

Status

Here you have to mention the status of the asset your branch is holding. The available options are:

- Capitalized
- Work in progress

Booking Date

The system date is defaulted as the booking date of the asset. You will not be allowed to modify this date.

Acquisition Date

Mention the date on which the asset is acquired in the date/month/year format.

Acquired Depreciation

You can specify the acquired depreciation in case of the asset being transferred from a previous branch. The system arrives at the accumulated depreciation based on the acquired depreciation that you specify as well as the depreciation calculated. The acquired depreciation is considered to track depreciation on books and not for tax purposes.

You will not be allowed to specify the acquired depreciation once you save and authorize a contract.

Residual Value

The Residual Value is taken into account for the purpose of computing the depreciation of the asset. However, you must ensure to enable the Asset Cost – Residual Value option in the Asset Category screen.

Note

The total depreciation for the asset will not exceed the residual value.

Original Reference Number

This field is updated only during Fixed Asset Transfers. Transferred asset is automatically created in the branch/location on Save of transfer. This field displays the original reference number of the asset in the old branch/location. You cannot modify this number.

All other details of the transferred asset will remain the same as before except for a few conditions.

Please refer the section Asset Transfer Process for more details.

Capitalization Date

If you have selected the status of the asset as Capitalized then you have to specify the date on which the asset was capitalized.

Effective Depreciation Date

In this field, you have to mention the date from which the depreciation should be charged for the asset. The capitalization date will be taken as the default date if you do not mention the date. You can choose to change this but this date cannot be less than the capitalization date. Also this date cannot be a future date.

Useful Life

Specify the following:

Useful Life

This is the unit to measure the useful life of asset (months/years). The data is defaulted from asset category maintenance. You can choose to change this unit.

Useful Life Units

This is the useful life of the asset. The data is defaulted from asset category maintenance however you can choose to change this.

Depreciation Suspension

Specify the following:

Suspend Depreciation

By choosing this preference you can stop the depreciation calculation for an asset. If there is a negotiation for sale or change in Residual Value for the asset, then choose this option to suspend the depreciation. Otherwise you can leave it unchecked.

Suspension Date

If you choose to suspend the depreciation then the system takes the application date as the suspension date. You will not be allowed to modify this date.

5.1.3 Depreciation Details Tab

You can view the depreciation charged for the asset from this screen.

Depreciation view screen displays the depreciation details of the asset recorded for book and tax purposes.

The screenshot shows the 'Fixed Assets Asset Capture' application window. The 'Depreciation Details' tab is active. The form includes fields for 'Product Code', 'Product Description', 'Contract Reference', 'User Reference', 'Source Reference', 'Version Number', and 'Source Code'. Below these are sections for 'Depreciation Book' and 'Depreciation Tax', each containing fields for 'Year To Days Depreciation', 'Accumulated Depreciation', 'Year Open Written Down Value', and 'Current Written Down Value'. A navigation bar at the bottom contains tabs for 'Events', 'Asset Details', 'Ad hoc Schedule', 'Linkage Details', 'Settlements', 'Advices', 'Charges', 'MIS', and 'Fields'. A status bar at the very bottom shows 'Input By', 'Auth By', 'Date Time', and 'Authorization Status'.

Specify the following:

Asset Reference Number

The system will generate the asset reference number based on the branch, product, Julian date and a running sequence of 4 bytes.

You cannot change this reference number.

Depreciation Book and Tax

Capture the following details:

Year To Days Depreciation

This field displays the depreciation charged on an asset from the start of the current financial year till the last depreciation date. This data is recorded for book and tax purpose.

No modification is allowed in this field.

Accumulated Depreciation

This field displays the depreciation charged on an asset for account book and tax purpose. The depreciation is calculated from the effective date of depreciation till the system date.

No modification is allowed in this field.

Year open Written Down Value

The field displays the value of the asset that was written down at the beginning of the financial year for book and tax purpose.

No modification is allowed in this field.

Current Written Down Value

This field displays the value of the asset that was written down on the system date for book and tax purpose.

No modification is allowed in this field.

5.1.4 Linkage Details Button

When an asset is purchased against a purchase order, you can link the asset to the contracts in Expense Processing module.

To access this screen, click 'Linkage Details' button in the Asset Capture Online' screen under Asset Capture, Fixed Assets from the Application Browser.

The screenshot shows a software window titled "Linkage Details". At the top, there are two text input fields: "Asset Reference" and "Asset Description". Below these is a table with a header row containing "Expense Processing Contract Reference", "Vendor Code", "Contract Amount", and "Linked Amount". The table body is currently empty. At the bottom of the window, there is a "Total Linked Amount" input field and two buttons labeled "Ok" and "Exit".

This screen enables you to add or delete a record.

Asset Reference Number

The reference number of the asset is defaulted from the asset capture screen. You will not be able to change this number.

Specifying the Expense Block

Expense Processing Contract Reference Number

Here you have to mention the reference number of the contract in the XP module. You can pick the reference number from the option list available or you can mention the number which will be validated against the XP contract.

Vendor Code

Once you choose the XP contract, the code for the vendor will be defaulted automatically.

Contract Amount

Once you choose the XP contract, the contract amount will be defaulted automatically in this field.

Note

The XP contract amount is displayed in asset currency.

Linked Amount

You have to specify the amount of the XP contract that has been used for the purchase of the asset.

Make sure that the sum of the linked amounts for all the linked contracts is less than or equal to the actual cost of the asset.

5.1.5 Asset Details Button

This screen is used to record individual item details under a single asset code in cases where many similar assets are grouped under one category.

To access this screen, click 'Asset Details' button in the 'Asset Capture Online' screen under Asset Capture, Fixed Assets from the Application Browser.

The screenshot shows the 'Asset Details' application window. At the top, there are two input fields: 'Asset Reference' and 'Description'. Below these is a table titled 'Asset Items'. The table has a header row with the following columns: 'Item Number *', 'Description', 'Item Cost', 'Expected Delivery Date', 'Delivered', 'Inspected', and 'Remarks'. Above the table, there is a 'Go' button and a status indicator '1 Of 1'. Below the table, there is a 'Total Item Cost' field. At the bottom right of the window, there are 'Ok' and 'Exit' buttons.

In this screen you are allowed to add or delete a asset from the asset group.

Asset Reference Number

The reference number of the asset is defaulted from the asset capture screen. You will not be able to change this number.

Asset Item Block

Item Number

You need to enter a unique number for the asset to identify the particular asset.

Description

You can record the general information regarding the asset in the Description field.

Item Cost

You need to specify the cost of the individual item.

Note

Take care that the sum of all item costs does not exceed the asset cost.

Expected Delivery Date

Mention the date on which the item is scheduled for delivery.

Note

Ensure that the delivery date is not less than the capitalization date.

Delivered

Check the box if the delivery of the asset has been carried out. Keep the box unchecked to indicate that the asset has not been delivered.

Inspected

If the asset has been inspected then check the box. Leave it unchecked to indicate that the asset has not undergone inspection.

Note

You will also be able to perform queries about assets delivered but not inspected and assets inspected but not capitalized, based on the Delivery Date and Status.

Remarks

In this field you can enter general remarks for the asset for future reference.

5.1.6 Ad hoc-Schedule Button

You will be able to define different rates for depreciation. This is exclusively done for adhoc type of depreciation.

To access this screen, click 'Adhoc Schedule' button in the 'Asset Capture Online'.

Schedule For Book		Schedule For Tax	
Year	Rate	Year	Rate
<input type="checkbox"/>		<input type="checkbox"/>	

Asset Reference Number

The reference number of the asset and its description is defaulted from the contract input screen. You will not be able to modify this number.

Specifying the Schedule For Book and Tax

Year

You have to maintain the depreciation schedule for the asset if you have chosen Ad-hoc as the depreciation type in the 'Asset Category location rule mapping' screen.

If the useful life is in months, then also, the adhoc depreciation schedule needs to be recorded in terms of years.

The sum of the depreciation rate across the useful life of the asset should be add up to 100. Additionally, you have to ensure that you have maintained depreciation rates for all the years of Useful Life.

Rate

You need to maintain the depreciation rate for the asset across the useful life of the asset.

Note

The depreciation rate will always be in percentage terms per annum.

5.2 Asset Transfer Details

This section contains the following topics:

- [Section 5.2.1, "Invoking the Asset Transfer Details Screen"](#)
- [Section 5.2.2, "Asset Transfer Process"](#)

5.2.1 Invoking the Asset Transfer Details Screen

Through the Transfer of Fixed Asset screens you can transfer a Fixed Asset to a different branch/ location. All the necessary details such as date of sale/transfer/write off, sale price, transfer details etc is captured through these screens.

You can invoke the 'Asset Transfer' screen by typing 'FADTRTFR' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows the Oracle 'Transfer' application window. At the top, there is a search bar with 'Enter Query' and a 'Reference Number *' field. The main content area is split into two columns: 'Asset Details' and 'Transaction detail'. 'Asset Details' includes fields for Asset Description, Asset Cost, Asset Currency, Category, Location, and Accumulated Depreciation. 'Transaction detail' includes Transfer Amount *, Value Date *, Officer In Charge *, and Remarks *. Below these are 'Transfer Details' with fields for New Branch, New Location, and New Reference. At the bottom, there is a navigation bar with links for Events, Settlements, Advice, Charges, MIS, and Fields. A status bar at the very bottom shows Input By, Authorized By, Status, Date Time, Authorization Status, and an Exit button.

The process of transfer is automated and the transferred asset is automatically created in the branch/location on Save of transfer.

Transfer value of the asset will be the current book value of the asset itself and cannot be modified. Book Value is arrived at by subtracting the accumulated depreciation from the asset cost.

Note

At least one of the two (new location and branch) must be different than current location and branch of the asset. Oracle FLEXCUBE will display an error message if this condition is not met.

The reference number of the asset is defaulted from the contract input screen. You will not be able to modify this number. To move to the next asset or previous asset, use the Up and Down arrow keys in the keyboard.

Asset Details

Click 'New' button in the toolbar to make a new entry for sale/write off.

Depending on the reference number you choose, the details for the asset will be defaulted in the following fields:

- Asset Description - the general information regarding the asset in this free format text field
- Asset Cost - the cost of the individual item
- Category – the code of the category under which the asset is placed
- Location – the location code where the asset is currently stationed
- Accumulated Depreciation – the accumulated depreciation from previous branch in case of transfer

Transaction Details

Specify the following details:

Transfer Amount

This is the net sale value of the asset. This field is mandatory if the asset is being sold.

For a Write off, this value will be the current book value and is not modifiable.

Value Date

This is the date on which the asset is sold or written off.

In case of a Sale, the default date will be the system date and you can choose to change this date.

For a Writeoff, this date will always be the system date and you will not be allowed to modify this date.

Officer Incharge

For both Sale and Write off, you have to mention the name of the officer in charge of the sale or transfer of the asset. This data is recorded for general information purpose.

Remarks

You can enter general remarks for the asset in this free format text field for information purposes.

Note

Any sale/transfer/write off has to be authorized before the end of day.

Transfer Details

Specify the following details:

New Branch

This is the branch where the asset is to be transferred. This field is mandatory for asset transfer. Select the branch from the option list.

New Location

This is the location to which the asset is to be transferred. This field is mandatory for asset transfer. Select the branch from the option list.

New Reference

This is the asset reference number of the asset created in the new branch/location and you will not be allowed to modify the number.

This number is automatically generated by the system when you save the asset transfer.

5.2.2 Asset Transfer Process

The following conditions are mandatory for asset transfer –

- The category - location rule mapping for the new location should be rule based
- If only the branch is being changed and not the location, the existing category – location depreciation type can be ad hoc. In this case ad hoc schedules will be copied from the old asset to the new asset.
- If the location is being changed, then the new category – location combination should have depreciation type as rule based. Old category – location combination can have ad hoc depreciation. Transfer is possible only if the new category location rule mapping has the same rule type as the old category.

Example,

Assume category='a'; location='x';'y' ; rule='r1'(ad hoc);'r2'(rule based).

Mapping is a-x-r1 and a-y-r2. branch's are b1, b2. asset 0001 has category='a'; location='x'.

Asset cannot be transferred from b1-b2-y; b1-b1-y.

- In branch parameters, depreciation period, cut off date and cut off period fields should have the same value in both the old and the new branches
- If the asset is being transferred to a new branch, the new branch should have exactly the same definition of financial year and financial periods. If not, it might result in erroneous depreciation calculation.

While doing an asset transfer, system will check the preferences maintained at the branch parameters level to complete or reverse depreciation for the period in which the asset is being transferred to a new branch/location.

- If the asset is being transferred after the cut off date, then depreciation will be completed for the current period in the transferor branch. Further depreciation will happen in the transferee branch for rest of the depreciation period in the current financial year.

- If the asset is being transferred on or before the cut off date, any depreciation which might have happened in the current period will be reversed out for the transferor branch. Further depreciation from the current period onwards will happen in the transferor branch according to the category –location rule maintenance for the new location (in case the location has changed).

The original reference number for the transferred asset will be the original reference number of the asset in the old branch/location.

All other details of the asset will be the same as they were before transfer except for the following:

- Acquired depreciation – This will be updated with the total depreciation amount (Accumulated depreciation) for the asset in the previous branch/location.
- Ad hoc Schedules – The new asset created will not have ad hoc depreciation schedules if the asset is transferred to a new location as the new category – location combination must allow for rule based depreciation. If the location is the same, then the original ad hoc schedules will be replicated to the new asset.
- Asset Acquisition date will be the transfer date
- In case a capitalized asset is transferred, capitalization date will be the transfer date else it will not be updated (if asset is transferred in WIP stage).
- In case a capitalized asset is transferred, effective depreciation date will be the transfer date else it will not be updated (if asset is transferred in WIP stage).

The new asset created will be automatically authorized once the transfer of the asset is authorized. Till such time, the new asset cannot be modified independently. After authorization of the transfer, the new asset created will be independent of the original transferred asset.

On deletion of the transfer, the new asset created will also be deleted.

Refer the examples in the accounting entry process in the Appendix manual for the above two scenarios.

5.3 Asset Sale Details

This section contains the following topics:

- [Section 5.3.1, "Invoking Asset Sale Detail Button"](#)

5.3.1 Invoking Asset Sale Detail Button

You can specify the asset sale details in the 'Fixed Assets Sale Details' screen. You can invoke this screen by typing 'FADTRSLE' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows a window titled "Sale" with a standard Windows-style title bar. The main content area is divided into three sections:

- Reference Number ***: A text input field at the top left.
- Asset Details**: A section containing six text input fields: Asset Description, Asset Cost, Asset Currency, Category, Location, and Accumulated Depreciation.
- Transaction detail**: A section containing four text input fields: Sale Value *, Value Date *, Officer In Charge *, and Remarks *.
- Transfer Details**: A section containing two text input fields: New Branch and New Location.

At the bottom of the window, there is a navigation bar with the following items: Events | Settlements | Advice | Charges | MIS | Fields. Below this is a status bar with three columns: "Input By" (with a sub-field "Date Time"), "Authorized By" (with a sub-field "Date Time"), and "Status" (with a sub-field "Authorization Status"). An "Exit" button is located in the bottom right corner of the status bar.

For more details on the screen refer section 'Specifying the Asset Transfer Details' in this chapter.

5.4 Asset Write Off Details

This section contains the following topics:

- [Section 5.4.1, "Invoking the Asset Write Off Screen"](#)

5.4.1 Invoking the Asset Write Off Screen

You can specify the asset write off details in the 'Asset Write Off' screen. You can invoke this screen by typing 'FADTRWRF' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Input By	Authorized By	Status
Date Time	Date Time	Authorization Status

Write Off value, value date, details of the officer authorizing the write off and internal remarks are captured through this screen.

For more details on the screen refer section 'Specifying the Asset Transfer Details' in this chapter.

5.5 Authorizing Fixed Asset Contracts

This section contains the following topics:

- [Section 5.5.1, "Invoking the Fixed Assets Authorization Screen"](#)

5.5.1 Invoking the Fixed Assets Authorization Screen

You can use the 'Fixed Assets Authorize Contract' screen to authorize asset capture, sale, write-off and transfer operations performed on any fixed asset contract.

You can invoke this screen by typing 'FADTRAUT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button. The screen is displayed below:

Specify the following details:

Contract Reference

Specify the contract number which you are authorizing.

Event Date

Current system date is displayed here.

Event Code

A code for this authorizing event is displayed here.

Maker

On selecting the contract number, the Maker ID is displayed.

Rekey Fields

Rekey the following details for authorizing a contract.

- Asset Currency
- Asset Cost
- Capitalization Date
- Effective Depreciation Date

Change Log Details

If there are any values changed in the contract, then the following details are displayed here:

- Field Description
- Old Value
- New Value

Overrides

The following override details of the contract for all operations is displayed here:

- Confirmed
- Remarks
- Authorized By
- Authorized Date
- Status
- Remarks

5.6 Contract Reassign to another User

This section contains the following topics:

- [Section 5.6.1, "Invoking the Fixed Assets Contract Reassign Screen"](#)

5.6.1 Invoking the Fixed Assets Contract Reassign Screen

A contract can be deleted only by the user who entered it. If a contract has to be deleted and the user who input the same is not available to do it, you can reassign the contract to another user so that the other user can delete it. Typically, this situation may arise during EOD operations, when a contract that is not authorized has to be deleted and the user who input it has left office for the day.

You can invoke the 'Fixed Assets Contract Reassign' screen by typing 'FADTREAS' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Input By	Date Time	Status
Checker	Date Time	Authorization Status

To reassign a contract to another user, the following steps are required:

Product Code

1. Indicate the product associated with the contract. You can select a product code from the option list, which contains a list of the authorized products that you have created.

Contract Reference

2. Indicate the contract reference number of the fixed asset you wish to reassign, to another user. You can select a reference number from the option list, which contains a list of all the active fixed asset contracts.

New User Identity

3. Select the User ID of the user to whom you are assigning the contract.

Note

This user to whom you reassign a contract should have access rights to enter fixed asset contracts.

Your User ID will be defaulted from the login screen. Select 'Save' from the Actions menu in the Application toolbar or click save icon to save the specifications you have made. Click 'Exit' or 'Cancel' button if you do not want to save the details that you entered.

5.7 Drill Down Query

You can define the total capitalized amount for each category code through 'Drill Down Query' screen. In order to define capitalized amount, you have to select status to Capitalized and provide Capitalization date in the FADTRONL screen.

You can invoke the 'Drill Down Query' screen by typing 'FADQDRIL' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Category Code	Category Description	Main Category	Capitalized Amount
---------------	----------------------	---------------	--------------------

You can specify the following details:

Product Code

Specify the fixed asset product code.

Product Description

The system displays the product description.

Total Capitalized Amount

The system displays the capitalized amount.

General Ledger Code

The system displays the general ledger code for the product.

General Ledger Description

The system displays the GL description.

Product Categories**Category Code**

The system displays the category code maintained for each product.

Category Description

The system display the sum of asset cost of each category for the product.

Main Category

The system displays any main category maintained.

Capitalized Amount

The system displays capitalized amount for each category.

6. Annexure A - Accounting Entries and Advices

This section contains details of the suggested accounting entries that can be set up, for the FA module of Oracle FLEXCUBE. The details of the suggested accounting entries are listed event-wise.

This chapter contains the following sections:

- [Section 6.1, "FA Events"](#)
- [Section 6.2, "Amount Tags"](#)
- [Section 6.3, "Accounting Roles"](#)
- [Section 6.4, "Event-wise Accounting Entries and Advices"](#)

6.1 FA Events

The following is an exhaustive list of events that can take place during the lifecycle of an FA contract. In the subsequent paragraphs we shall examine the accounting entries and advices for each of the events listed below.

SI No	Event Code	Event Description	Remarks
1	BOOK	Booking an FA contract (Mandatory)	All Types
2	CAPT	Capitalization of an asset	All Types
3	DEPR	Depreciation Processing for Booking	All Types
4	AMND	Amendment of a contract	All Types
5	SALE	Sale of an asset	All Types
6	WRTO	FA Write off	All Types
7	DPTX	Depreciation for Tax purposes (no accounting entries are passed for this event)	All Types
8	REVC	Reversal of a contract	All Types.
9	TSFR	Transfer of Asset	

6.2 Amount Tags

The amount tags listed below are hard-coded in Oracle FLEXCUBE.

Amount Tag	Description
FA_CAPT_AMT	Asset Cost Capitalized

FA_DEPR_ACC	Accumulated depreciation
FA_DEPR_ADD	Additional depreciation to be charged
FA_DEPR_RED	Reduction in depreciation amount already charged
FA_SALE_AMT	Net Sale Value
FA_SALE_LOS	Loss on account of sale (Book Value-Sale Value)
FA_SALE_PFT	Profit on account of Sale
FA_WR-TO_AMT	Amount Written Off (Book Value)
FA_TSFR_AMT	Transfer Amount (Asset Amount – Accumulated Depreciation)

In addition to these you can define amount tags as per your requirements for charges that will be attached to the product.

Amount Tags and their usage during various events

Listed below are the various Events along with the Amount Tags that would be used during the respective events.

Event	Amount Tag	Explanation of the Amount Tags
BOOK	FA_CAP-T_AMT	Asset Cost
DEPR	FA_-DEPR_ADD	Additional depreciation to be charged on account of increase in depreciation rate or change in depreciation method or change in capitalization date
DEPR	FA_-DEPR_RED	Reduction in cumulative depreciation on account of reduction in rate, change in capitalization date or change in depreciation method
CAPT	FA_CAP-T_AMT	Asset Cost capitalized
SALE	FA_-SALE_AMT	Net Sale Value
SALE	FA_-SALE_LOS	Loss on Account of Sale (Book Value-Net Sale Value)
SALE	FA_-SALE_PFT	Profit on Account of Sale (Net Sale Value-Book Value)
SALE	FA_-DEPR_ACC	Accumulated depreciation
WRO	FA_WR-TO_AMT	Amount Written off (Book Value)
WRO	FA_CAP-T_AMT	Asset Cost capitalized

WRT O	FA_- DEPR_ACC	Accumulated depreciation
TSF R	FA_- DEPR_ACC	Accumulated depreciation
TSF R	FA_TS- FR_AMT	Transfer Amount (Asset Amount – Accumulated Depreciation)

6.3 Accounting Roles

In this section we have provided a list of sample accounting roles that can be used for all types of products in the FA module:

Accounting Role	Description	Role Type
FAASSETACC	Asset Account	Asset
FAWIPACC	Work-In-Progress Account	Liability
FACUSTACC	Customer Account	Customer
FADEPREXP	Depreciation Account	Expense
FAACCDEPRLIB	Accumulated depreciation Acct	Liability
FASALEEXP	Loss on Sale Account	Expense
FASALEINC	Profit on Sale Account	Income
FAWRTOEXP	Asset Written Off Account	Expense
FATSFRACC	Transfer Account	Asset

6.4 Event-wise Accounting Entries and Advices

In the subsequent sections we have defined suggested accounting entries and advices for each of the events in the life-cycle of an FA contract.

BOOK: Booking

Accounting Entries

Condition	Accounting Role	Amount Tag	Dr./Cr. Indicator
No PO required	FAWIPACC	FA_ASST_AMT	Dr
for Purchase	FACUSTACC	FA_ASST_AMT	Cr

CAPT: Capitalization of Asset

Accounting Entries

Condition	Accounting Role	Amount Tag	Dr./Cr. Indicator
None	FAASSETACC	FA_CAPT_AMT	Dr
	FAWIPACC	FA_CAPT_AMT	Cr

DEPR: Depreciation processing

Condition	Accounting Role	Amount Tag	Dr./Cr.
Increase in depreciation	FADEPREXP	FA_DEPR_ADD	Dr
	FAACCDEPRLIB	FA_DEPR_ADD	Cr
Decrease in depreciation	FAACCDEPRLIB	FA_DEPR_RED	Dr
	FADEPREXP	FA_DEPR_RED	Cr
If Acquired depreciation is entered	FAWIPACC	FA_DEPR_ACQ	Dr
	FAACCDEPRLIB	FA_DEPR_ACQ	Cr

AMND: Amendment of the contract

No Accounting Entries need to be captured at this stage since all the adjustments to be done will be taken care of by the depreciation processing event.

SALE: Sale of Asset

Condition	Accounting Role	Amount Tag	Dr./Cr.
Loss on Sale	FAACCDEPRLIB	FA_DEPR_ACC	Dr
Loss on Sale	FACUSTACC	FA_SALE_AMT	Dr
Loss on Sale	FASALEEXP	FA_SALE_LOS	Dr
Loss on Sale	FAASSETACC	FA_CAPT_AMT	Cr
Profit on Sale	FAACCDEPRLIB	FA_- DEPR_ACC	Dr
Profit on Sale	FACUSTACC	FA_SALE_AMT	Dr
Profit on Sale	FAASSETACC	FA_CAPT_AMT	Cr
Profit on Sale	FAASSETACC	FA_SALE_PFT	Dr
Profit on Sale	FASALEINC	FA_SALE_PFT	Cr

In Oracle FLEXCUBE, all Credit and Debit entries have to be paired up. So the entries will be as follows:

Condition	Accounting Role	Amount Tag	Dr./Cr.
Loss on Sale	FACUSTACC	FA_SALE_AMT	Dr
Loss on Sale	FAASSETACC	FA_SALE_AMT	Cr
Loss on Sale	FAACCDEPRLIB	FA_DEPR_ACC	Dr
Loss on Sale	FAASSETACC	FA_DEPR_ACC	Cr
Loss on Sale	FASALEEXP	FA_SALE_LOS	Dr
Loss on Sale	FAASSETACC	FA_SALE_LOS	Cr
Profit on Sale	FACUSTACC	FA_SALE_AMT	Dr
Profit on Sale	FAASSETACC	FA_SALE_AMT	Cr
Profit on Sale	FAACCDEPRLIB	FA_DEPR_ACC	Dr
Profit on Sale	FAASSETACC	FA_DEPR_ACC	Cr
Profit on Sale	FAASSETACC	FA_SALE_PFT	Dr
Profit on Sale	FASALEINC	FA_SALE_PFT	Cr

Advices

A Payment message would be generated for the customer to whom the asset is sold.

WRTO: FA Write off

Condition	Accounting Role	Amount Tag	Dr./Cr.
None	FAACCDEPRLIB	FA_DEPR_ACC	Dr.
	FAWRTOEXP	FA_WRTO_AMT	Dr
	FAASSETACC	FA_CAPT_AMT	Cr

Since all debit and credit entries have to be paired up in Oracle FLEXCUBE, the entries will be reflected as follows:

Condition	Accounting Role	Amount Tag	Dr./Cr.
None	FAWRTOEXP	FA_CAPT_AMT	Dr
	FAASSETACC	FA_CAPT_AMT	Cr
	FAACCDEPRLIB	FA_DEPR_ACC	Dr
	FAWRTOEXP	FA_DEPR_ACC	Cr

TSFR: Transfer of asset from one branch/location to another

The Transfer event is automated and the transferred asset will be automatically created in the branch/location on save of transfer.

This event will be triggered when the asset is transferred from one branch/ location to another.

The Accounting entry setup for the asset in Transferor and Transferee branch will be as described below.

1) Asset still in WIP stage

Transferor branch – Event TSFR

DR/CR	Accounting Role	Description	Amount Tag	Description
DR	FATSFACC	Transfer Account (Transferee Branch)	FA_ASST_AMT	Original Asset cost
CR	FAWIPACC	Work in Progress Account (Transferor Branch)	FA_ASST_AMT	Original Asset cost

Transferee Branch – Event BOOK

DR/CR	Accounting Role	Description	Amount Tag	Description
DR	FAWIPACC	Work in Progress Account (Transferee Branch)	FA_ASST_AMT	Original Asset cost
CR	FACUSTACC	Customer Account	FA_ASST_AMT	Original Asset cost

DR	FAWIPACC	Work in Progress Account (Transferee Branch)	FA_TSFR_AMT	Original Asset cost
CR	FATSFRACT	Transfer Account (Transferor Branch)	FA_TSFR_AMT	Original Asset cost

Only the second set of entries will be passed in case of an asset transfer.

2) Capitalized Asset

Transferor branch – Event TSFR

DR/CR	Accounting Role	Description	Amount Tag	Description
DR	FATSFRACT	Transfer Account (Transferee Branch)	FA_CAPT_AMT	Original Asset cost
CR	FASSTACC	Asset Account (Transferor Branch)	FA_CAPT_AMT	Original Asset cost
DR	FAACCDEPRLIB	Accumulated depreciation Account	FA_-DEPR_ACC	Accumulated Dep.
CR	FATSFRACT	Transfer Account (Transferee Branch)	FA_-DEPR_ACC	Accumulated Dep.

Transferor Branch – Event DEPR (Along with TSFR)

DR/CR	Accounting Role	Description	Amount Tag	Description
DR	FADEPREXP	Dep. Expense	FA_DEPR_ADD	Depreciation Addition
CR	FAACCDEPRLIB	Accumulated depreciation Account	FA_DEPR_ADD	Depreciation Addition
DR	FAACCDEPRLIB	Accumulated depreciation Account	FA_DEPR_RED	Depreciation Reduction
CR	FADEPREXP	Dep. Expense	FA_DEPR_RED	Depreciation Reduction

Transferee Branch – Event BOOK

DR/CR	Accounting Role	Description	Amount Tag	Description
DR	FAWIPACC	Work in Progress Account (Transferee Branch)	FA_ASST_AMT	Original Asset cost
CR	FACUSTACC	Customer Account	FA_ASST_AMT	Original Asset cost

DR	FAWIPACC	Work in Progress Account (Transferee Branch)	FA_TSFR_AMT	Original Asset cost – Acquired Depreciation
CR	FATSFACC	Transfer Account (Transferor Branch)	FA_TSFR_AMT	Original Asset cost - Acquired Depreciation

Only the second set of entries will be passed in case of an asset transfer.

Transferee Branch – Event DEPR (Along with BOOK)

DR/CR	Accounting Role	Description	Amount Tag	Description
DR	FAWIPACC	Work in Progress Account (Transferee Branch)	FA_DEPR_ACQ	Acquired Depreciation
CR	FAAC-CDEPRLIB	Accumulated depreciation Account	FA_DEPR_ACQ	Acquired Depreciation

Capitalization entries will be passed as usual for the new asset.

Examples

Formula for calculating depreciation to be passed / reversed:

Depreciation already done for current period =

YTD depreciation – (Depreciation per period * No. of previous periods)

Depreciation to be reversed (If Dep. Effective date <= Cut Off date) =

Depreciation already done for the current period

Depreciation to be passed (If Dep. Effective date > Cut Off date) =

Depreciation per period - Depreciation already done for current period

The above formula will be valid for WDV method of depreciation also since the depreciation process considers the Written Down Value of the asset only as of the beginning of the current financial year.

Consider the following parameters –

Financial Year - 01-Jan-2008 to 31-Dec-2008

Depreciation period- Quarterly

Cut off Month- 1

Cut off Date- 20

Depreciation effective date - 17-Apr-2008

Transfer Date- 25-Aug-2008

Asset Cost- 12000

Depreciation rate- 10%

Now according to the above parameters,

If asset is acquired in current year, we need to find out the period when depreciation started.

Depreciation Start period = 2 (2nd quarter of the year)

Transfer is happening in the 3rd Period, So No of previous periods = 3-2 =1

Total depreciation for the year= $12000 * 10 / 100 = 1200$

Actual depreciation for the year = $1200 * \text{Applicable periods} / \text{No of periods in a year}$

= $1200 * 3/4$

= 900

Depreciation per period= $900 / 3$

= 300

Let us assume that when the transfer is happening on 25-Aug-2008 YTD depreciation is 475. Since transfer is happening after the cut off date (10-Jul-2008) for the 3rd period, we need to complete depreciation for this period. According to the above formula –

Depreciation already done for current period= $475 - [(300 * (2-1))]$

= 175

Extra depreciation to be passed= $300-175$

= 125

This is the amount for which depreciation entry is passed on transfer.

Let us now assume that the cut off date is 27-Aug-2008. Since transfer is happening before the cut off date, we need to reverse the depreciation for this period

Depreciation already done for current period = $475 - [(300 * (2-1))]$

= 175

Depreciation to be reversed= 175

1) Asset transferred before Cut off date

Consider the following parameters for a fixed asset –

Asset Cost – 12000

Acquisition Date – 10-Nov-2007

Capitalization date– 17-Jan-2008

Effective depreciation date– 17-Jan-2008 (Defaulted to Capitalization date)

Depreciation Period – Quarterly

Cut off date– 20

Cut off period– 1

Depreciation Frequency – Monthly

Frequency start date– 15

Depreciation Rate–10% Per Annum

Fin year start date- 01-Jan-2008

Fin year end date- 31-Dec-2008

According to the above parameters, the cut off date for depreciation is 20-Jan-2008. Any asset having effective depreciation date on or before 20-Jan-2008 will be depreciated for 4 periods in the first year. Any asset having effective depreciation date after 20-Jan-2008 will be depreciated only for the next 3 periods in the first year. Since our asset has effective depreciation date as 17-Jan-2008 which is before the cut off date, it will be depreciated for the full year. Since we are considering the case where transfer is done in the first year itself, accumulated depreciation will always be the same as YTD depreciation.

Depreciation on 15-feb-2008

Total depreciation for the year =

$[(\text{Asset cost} * \text{rate}) * \text{Applicable dep. Periods}] / \text{No of depreciation periods in the year}$

$= [(12000 * .10) * 4] / 4$

=1200

Total depreciation runs in the year=12 (Monthly frequency)

Future Depreciation runs left =10 (march Onwards)

Future depreciation=1200*10/12

=1000

Depreciation to be passed this time=1200-1000

=200

Depreciation accounting entries (DEPR event) on 15-feb-2008

Accounting entries passed on 15-Feb-2008

DR/CR	Accounting Role	Description	Amount Tag	Description
DR	FADEPREXP	Dep. Expense	FA_DEPR_ADD	200
CR	FAACCDEPRLIB	Accumulated Dep.	FA_DEPR_ADD	200

Accounting entries passed on 15-Mar-2008

DR/CR	Accounting Role	Description	Amount Tag	Description
DR	FADEPREXP	Dep. Expense	FA_DEPR_ADD	100
CR	FAACCDEPRLIB	Accumulated Dep.	FA_DEPR_ADD	100

Accounting entries passed on 15-Apr-2008

DR/CR	Accounting Role	Description	Amount Tag	Description
DR	FADEPREXP	Dep. Expense	FA_DEPR_ADD	100
CR	FAACCDEPRLIB	Accumulated Dep.	FA_DEPR_ADD	100

Now let us assume that the asset is transferred to another branch/location on 17-Apr-2008.

Cut off date for asset transfer will be taken from branch parameters. For this case it will be 20-Apr-2008.

Since the asset is transferred before the cut off date, any depreciation done for the asset in the 2nd depreciation period will be reverted back on transfer from the transferor branch.

YTD depreciation = 200+100+100

= 400

Depreciation already done for current period =

YTD depreciation - Depreciation for all previous periods

= 400 - 300

= 100

Acquired depreciation for the asset in new branch/location =

Accumulated Dep.- Dep. for current period

= 400-100

= 300

Accumulated Depreciation also now becomes 300.

Accounting entries passed in the transferor branch –

Event – TSFR

DR/CR	Accounting Role	Description	Amount Tag	Description
DR	FATSFRACT	Transfer Account (Transferee Branch)	FA_ASST_AMT	12000
CR	FASSTACC	Asset Account (Transferor Branch)	FA_ASST_AMT	12000
DR	FAAC-CDEPRLIB	Accumulated depreciation Account	FA_DEPR_ACC	300
CR	FATSFRACT	Transfer Account (Transferee Branch)	FA_DEPR_ACC	300

Event – DEPR (Triggered along with TSFR)

DR/CR	Accounting Role	Description	Amount Tag	Description
DR	FAACCDEPRLIB	Accumulated Dep.	FA_DEPR_RED	100
CR	FADEPREXP	Dep. Expense	FA_DEPR_RED	100

Accounting entries passed in the transferee branch –

Event BOOK

DR/CR	Accounting Role	Description	Amount Tag	Description
-------	-----------------	-------------	------------	-------------

DR	FAWI-PACC	Work in Progress Account (Transferee Branch)	FA_TS-FR_AMT	11700
CR	FATS-FRACC	Transfer Account (Transferor Branch)	FA_TS-FR_AMT	11700

Event DEPR (Triggered along with BOOK)

DR/CR	Accounting Role	Description	Amount Tag	Description
DR	FAWIPACC	Work in Progress Account (Transferee Branch)	FA_-DEPR_ACQ	300
CR	FAAC-CDEPRLIB	Accumulated depreciation Account	FA_-DEPR_ACQ	300

From here onwards, the depreciation of the asset will be done in the new branch/location with the rule defined for the new category – location combination.

2) Asset transferred after Cut off date

Assume that everything remains the same as the previous asset but the asset is transferred on 10-May-2008 i.e after the cut off date. In this case, the system will depreciate the asset for the current period fully on transfer and depreciation in the new branch/location will start from the next period onwards only. Since we are considering the case where transfer is done in the first year itself, accumulated depreciation will always be the same as YTD depreciation.

YTD depreciation (after depreciation on 15-Apr) = 200+100+100

= 400

Total depreciation for current period = Dep. for the year/No of dep. Periods = 900/3

=300

Depreciation already done for current period

= YTD depreciation - Depreciation for all previous periods

= 400 -100

= 100

Remaining dep. For current period = 300-100 = 200

Acquired depreciation for the asset in new branch/location

= Accumulated Depreciation

= Current Accumulated Dep.+ Remaining Dep. for current period

= 400+200

= 600

Accounting entries passed in the transferor branch –

Event – TSFR

DR/ CR	Accounting Role	Description	Amount Tag	Amount
DR	FATSFRACT	Transfer Account (Transferee Branch)	FA_ASST_AMT	12000
CR	FASSTACC	Asset Account (Transferor Branch)	FA_ASST_AMT	12000
DR	FAAC-CDEPRLIB	Accumulated depreciation Account	FA_DEPR_ACC	600
CR	FATSFRACT	Transfer Account (Transferee Branch)	FA_DEPR_ACC	600

Event – DEPR (Triggered along with TSFR)

DR/CR	Accounting Role	Description	Amount Tag	Amount
DR	FADEPREXP	Dep. Expense	FA_DEPR_ADD	200
CR	FAACCDEPRLIB	Accumulated Dep.	FA_DEPR_ADD	200

Accounting entries passed in the transferee branch –

Event BOOK

DR/CR	Accounting Role	Description	Amount Tag	Amount
DR	FAWIPACC	Work in Progress Account (Transferee Branch)	FA_TSFR_AMT	11400
CR	FATS-FRACC	Transfer Account (Transferor Branch)	FA_TSFR_AMT	11400

Event DEPR (Triggered along with BOOK)

DR/ CR	Accounting Role	Description	Amount Tag	Amount
-------------------	----------------------------	--------------------	-------------------	---------------

DR	FAWIPACC	Work in Progress Account (Transferee Branch)	FA_- DEPR_ACQ	600
CR	FAAC- CDEPRLIB	Accumulated depreciation Account	FA_- DEPR_ACQ	600

From here onwards, the depreciation of the asset will be done in the new branch/location with the rule defined for the new category – location combination.

The following details the possible advices and the stage at which the advices are generated for the Accounting entries:

Advice Code	Advice Description	Receiver
PAYMENT_MESSAGE	Payment Message	Counter-party

This advice is generated on Book Event (If PO required is 'N' at product level) and on Sale Event.

On transfer of an asset, a transfer advice called FA_TRANSFER will be generated. Following details will be available in the transfer advice –

- Original asset reference
- Transferor Branch
- Transferee Branch
- Accumulated depreciation
- Asset Cost
- Current Book Value
- Date of Transfer

The receiver of the advice will be the Walk in Customer for the Transferor Branch.

This chapter contains the following section:

- [Section 7.1, "Important Terms"](#)

7.1 Important Terms

The following terms are used in this module.

Ad Hoc Depreciation rates

Depreciation rates that do not default from the Product but are defined at the contract level at the time of input of the asset.

Book Value

This indicates the value at which an asset is carried on a balance sheet. In other words, the cost of an asset minus accumulated depreciation.

Capitalisation

When a business purchases assets like furniture, machinery, equipment, etc. they get posted to the balance sheet as "fixed assets". For financial statement purposes, these assets have "lives" and usually last for years. For this reason, they are not expensed. Instead they are capitalized (shown as assets on the balance sheet) and depreciated. Each year the company records depreciation on these assets to show that it is using them over time.

Depreciation

Depreciation is the reduction in the value of an asset due to usage, passage of time, wear and tear, technological outdating or obsolescence, depletion or other such factors.

Purchase Order

A purchase order (PO) is a commercial document issued by a buyer to a seller, indicating the type, quantities and agreed prices for products or services the seller will provide to the buyer. Sending a PO to a supplier constitutes a legal offer to buy products or services.

Rate over Period

For calculating depreciation for the first year the company can mention a depreciation rate that is different from the depreciation rule that has been specified. This is mentioned as a part of the Rule definition.

Residual Value

Residual Value is the scrap value of the asset which can be realized when the asset is sold after its useful life is complete.

SLM

The simplest and most commonly used, straight line depreciation is calculated by taking the purchase or acquisition price of an asset subtracted by the salvage value divided by the total productive years the asset can be reasonably expected to benefit the company [called "useful life" in accounting jargon].

Purchase price of asset – approximate salvage value

Estimated useful life of asset

Under straight line method, a fixed percentage is applied on the original cost of the asset, thereby ensuring that the depreciation per annum over the useful life is constant.

Transfer Value

This indicates the value of the asset when transferred from one branch to another.

Useful Life

This indicates the life of the asset. i.e. the period for which the asset would be useful for the organization.

WDV

Under written down value method, a fixed percentage is applied on the written down value (original cost less depreciation charged till the end of the previous year) of the asset. This results in higher depreciation in the earlier years and lesser depreciation in the later years.

Normally the depreciation rate under written down value is higher than the rate under straight line method. This ensures creation of depreciation provision over the useful life of the asset.

WIP

Work that has not been completed but has already incurred a capital investment from the company. This is usually recorded as an asset on the balance sheet. Work in progress indicates any good that is not considered to be a final product, but must still be accounted for because funds have been invested toward its production.

Write Off

This indicates a reduction in the value of an asset or earnings by the amount of an expense or loss.

8. Function ID Glossary

F

FADACAT3-2
FADBRMNT3-5
FADCATCL3-8
FADLOCCL3-7
FADLOCN3-4
FADPRMNT4-1
FADQDRIL5-17

FADRULDF3-9
FADRULMP3-11
FADTRAUT5-14
FADTREAS5-16
FADTRONL5-1, 5-17
FADTRSLE5-13
FADTRTFR5-9
FADTRWRF5-14