Oracle® Hospitality Cruise Shipboard Property Management System
OHC Tools User Guide

Release 20.1

F33513-01

September 2020

ORACLE®

Oracle Hospitality Cruise Shipboard Property Management System OHC Tools User Guide, Release 20.1

F33513-01

Contents

Preface

1   OHC Tools Functionality

Preface

The OHC Tools is a program that manages data security in Oracle Hospitality Cruise Shipboard Management System (SPMS) such as securing credit card data with an encryption key, changing of database password, export/import database with secure password and others.

Audience

This document is intended for project managers, application specialists and users of Oracle Hospitality Cruise Shipboard Property Management System.

Customer Support

To contact Oracle Customer Support, access My Oracle Support at the following URL:

https://support.oracle.com

When contacting Customer Support, please provide the following:

- Product version and program/module name
- Functional and technical description of the problem (include business impact)
- Detailed step-by-step instructions to re-create
- Exact error message received
- Screenshots of each step you take

Documentation

Oracle Hospitality product documentation is available on the Oracle Help Center at http://docs.oracle.com/en/industries/hospitality/.

Revision History

Table 1   Revision History

Date	Description of Change
September 2020	Initial Publication

1

OHC Tools Functionality

The OHC Tools is an application that manages the data security, credit card data encryption, database password change, and has an added database import/export functionality.

Figure 1-1   Functions in OHC Tools Home Tab

Figure 1-2   Functions in OHC Tools Import/Export Tab

Change Database Encryption Key

The Change Database Encryption Key allows you to secure and protect important data such as credit card information and user passwords stored in their database using an encryption method compliance to PA-DSS policy.

Creating an Encryption Passphrase

1. Login to Tools application and select **Change Database Encryption Key** from the ribbon bar.

2. In the Encryption Key Manager window, enter the **Passphrase1** and **Passphrase 2, Old Password, New Password,** and **Confirm New Password**.

3. Click **Apply** to proceed. The system prompts *'Please ensure there is no application is currently running in order to prevent data corruption later'*.

4. If Transparent Data Encryption (TDE) is used, the system performs a database backup, allowing you to restore at a later stage. This requires a password for the DMP file. If an error were to occur during the backup, you will be prompt to enter the same password and they must be identical.

Figure 1-3   DMP Password

5. Click **OK** to continue and program prompts a request to stop the running application, if any.

6. When the change encryption key begins, program performs a backup process on tables that need to be re-encrypted.

7. If corrupted data is found during the encryption process, the system continues the process and prompts a warning at the end of the process before generating an error log.

Figure 1-4   Encryption Failed Warning

8. At the error prompt, choose **Yes** to continue replacing the encryption key or **No** to roll back the process by restoring the backup.

9. The Passphrase is saved in OHCSecurity.par and is valid for one year from the date of encryption.

Verify Encrypted Database Data

The **Verify Database Encrypted Data** function verifies the encrypted data and confirm that encryption can be change before performing the Change Encryption Key.

1. At the Tools application, select **Verify Database Encrypted Data** from the ribbon bar.

2. At the Verify Encrypted Data window, click **Verify**.

3. The Verify Database Encryption Data verifies data in User login credentials, Parameter, Reservation, POS Information, (PGP Key), Credit Card Registration, Transfer and Authorization

4. If the verification returns a failed message, possibility due to invalid data, correct the error, and repeat the process.

Figure 1-5 Verify Encrypted Database

5. Click **Close** when the process finishes.

Change Password

The Change Password function changes the database password, including the MICROS, SMTP and VOIP password and prevents you from changing the passwords directly from external database tools.

You are not allow to change the Ship's DB password when QCI Sync application is running and must have Database privilege granted before you are allowed to proceed.

Figure 1-6   Password Manager Window

1. In Tools window, select **Change Password** from the ribbon bar.

2. In Password Manger window, enter the system **User, System Password, Database User,** and **Database Password** and password must fulfil the password specification.

3. Click **Apply** to update the database password and save the encrypted password to OHCSecurity.par.

4. Repeat the steps above to change the password for MICROS, SMTP and VOIP.

Upload PGP Key

The Upload PGP Key function is used to upload the Public Key (.pkr) and Private Key (.skr), a key pair for function that requires a Pretty Good Privacy (PGP) Key. For example, Payroll, Credit Card, DGS Resonline and Data Import handling. You can only generate a key pair using a third party tools such as PortablePGP and FileAssurity OpenPGP. See *PA-DSS 3.2 Implementation Guide* for more information.

For Credit Card process, the Ship sends the public key to the credit card provider and in return receives a public key from the provider.

Figure 1-7   PGP Key Uploader

1. In the Tools window, select **Upload PGP Key** from the ribbon bar

2. In the PGP Key Uploader window Credit Card tab, click the **Browse** button next to **Public Key** and select a .pkr file to upload. To upload a Private Key, click the **Browse** button next to Private Key to select a .skr file.

3. Enter the **Key Passphrase** if the key is generate with specific passphrase.

4. Click **Upload** to upload the keys. The system prompts '*Key upload is done successfully*' when upload completes and stores both the encrypted keys in `TYP_PGP` table.

5. For DGS Credit Card handling, a key version is required.

> ✎ **Note:**
>
> The PGP Key has an expiry date and you must generate a new PGP Key and re-upload to the database once you receive a reminder. The program does not allow reuse of the same PGP Key.

Copy System Account

The Copy System Account function copies the System Account from one database to another database.

1. In the Tools window, select **Copy System Account** from the ribbon bar.

2. In Copy System account window, select the source database from the Server drop-down list and then enter the **User password**.

3. At the end of the ribbon bar, click **Connect** under the **Copy System Account** group. The System Accounts shall populate if the connection is successful.

Figure 1-8   Copy System Account

4. Check the **Delete All Destination System Account** to add or remove the account in destination database. This is only possible when no posting exists in the account during copy process.

5. Click **Copy** to complete the process.

Change Log Trigger

The following function creates a Database Trigger that logs changes made to selected fields. Values from the selected fields are stored the log in Payroll Audit Trail table.

1. In the Tools window, select **Change Log Trigger** from the ribbon bar.

2. In Create Change Log Trigger window, check the table on the left pane and then navigate to **Monitor Column** on the right pane.

3. In the **Monitor Column**, check the required change fields to log into Payroll Audit Trail table and then navigate to **Acc ID Column** tab.

4. In **Acc ID Column** tab, check the field to write into Payroll Contract Account ID.

5. Click **Create Change Log Trigger** at the ribbon bar to create the trigger.

6. Repeat the above steps to add more table field.

Delete Log Trigger

This function creates a Database Trigger that logs data deletion activities of the selected fields. Values deleted from the selected fields will be logged into Audit Trail Deletion table.

1. In OHC Tools, select **Delete Log Trigger** from the ribbon bar.

2. From the Create Deletion Log Trigger window, navigate to the **Description** column

3. Listed under the Description column, select all the fields so that their changes will be logged into the SDR table

4. Navigate to the **Acc ID** column tab.

5. In Acc ID Column tab, select the fields that will be written into the SDR_ACC_ID

6. Click **Create Deletion Log Trigger** on the ribbon bar to create the database trigger.

7. The system will prompt a total of number of database triggers that tracks fields deleted and also track fields created/upload. Click **OK** button to continue.

8. Repeat the steps above to add more table fields.

Insert Log Trigger

This function creates a Database Trigger that logs data insertion activities of the selected fields. Values added from the selected fields will be logged into Audit Trail Insertion table.

1. In the Tools window, select **Insertion Log Trigger** from the ribbon bar.

2. In Create Insertion Log Trigger window, select the table on left pane by checking the check box and then navigate to **Description Column** on the right pane.

3. In the **Description Column**, select the fields log into the Audit Trail Insertion table.

4. Navigate to **Acc ID Column** tab, and select the field to write into Audit Trail Insertion Account ID.

5. Click **Create Insertion Log Trigger** at the ribbon bar.

6. The system will prompt a total of number of database triggers that tracks fields deleted and also track fields created/upload. Click **OK** to continue.

7. Repeat the above steps to add more table field.

Serial Port Reader

The Serial Port Reader is a tool to test the reader connection with the barcode or card reader COM port.

Figure 1-9   Serial Port Reader Setting

1. Connect the device to the PC and click **Serial Port Reader** at the ribbon bar.

2. In Serial Port reader window, select the **Com Port, Parity, Baud Rate, Data Bit, Stop Bit**.

3. Check the **Show Result as Hex** checkbox to show the read result in Hexadecimal format.

4. Click **Connect**. The connection indicator turns to green if the device is successfully connected.

5. Press the any button on the device to start reading a barcode. The result shown in the text field.

6. Click **Clear All Text** to clear the field.

Credit Card Token Handling

This function fixes the credit card data before transferring from a non-token authorization to token handling. This special tool is used to ensure all existing Credit Card Authorization (CCA) and Credit Card Settlement (CCT) records are process before changing the credit card format to SERVEBASE Tokenization handling.

1. In the Tools window, select **Credit Card Token Handling** from the ribbon bar.

2. At the Credit Card Token Handling prompt 'By doing this, you are agreeing to use credit card tokenization handling', select **Yes** to agree or **No** to return to the main menu.

3. In Oracle Hospitality Cruise SPMS Credit Card Tokenization window, click the **Process** and select **Yes** to implement the credit card handling.

4. When **Yes** is clicked, verification of credit card will commence based on following criteria:

   a. Parameter 'Not Specified', 'CC Transfer Format' is not 'SERVEBASE'.

   b. No outstanding status for CCA record, where status is = 0

   c. No outstanding status for CCT record, where status is =0

5. If the above criteria are not met, the change token handling will not proceed and following message will show *'There are some authorizations still pending'*.

6. Check and correct the CCA and CCT record and the repeat the above steps when ready.

7. When the **Process** completes successfully, the system prompts a message *'Credit card token handling is implemented'*. The parameter 'Not Specified', 'CC Transfer Format' is updated to SERVEBASE and all credit card records are Deactivated.

Manual activation is not allowed and the system prompts 'Settlement or reversal had done for this card, please get credit card again'.

Verify Embarkation Data

This function validates and lists all VARCHAR2, CHAR fields that has ASCII value of more than 127. For example: €, ‡, Œ, Ž, ¢, ©, ®. The verification validates the reservation fields used in Advanced Quick Check In application such as `CAB`, `RES`, `CRD`, `SEC`, `SIG`, `USR`, `UXP`, `VIS_BLOB`, `VIS_TEXT`.

1. In the Tools window, select **Verify Embarkation Data** from the ribbon bar.

2. In Verify Embarkation Data window, check the relevant options and **Include Check In** if you want to include check ins.

3. Click **Verify Data** to proceed with verification. Below is the sample results shown in the verification window.

   • The Non-ASCII code size less than 18 characters will have status as *OK*.

   • The Non-ASCII code size that are more than 18 will have status shown as *Not OK* and listed with '*There is potential x problem(s) found, please review the log file VERIFYDATA_yyymmdd.txt'*.

Figure 1-10   Verify Embarkation Data

Export Database

The Export Database function enables you to export some data table from the database. The export function only exports table, data, index and trigger and does not export the view or sequence.

1. In the Tools Import/Export tab, select **Export Database** from the ribbon bar.

2. In the Export Database window, enter the 16 digits **Encryption Key** for the dump file.

3. Select the table to export individually or click **Select All** at the ribbon bar for all tables.

4. Click **Backup** at the ribbon bar to compress and encrypt the data table. The system prompts 'File had been backup to `'C:\<FilePath>\<Filename>'` when the export is ready.

   If TDE applies, the backup file will be stored as `DATA_PUMP_DIR` in the Oracle Database directory instead. You will be prompt to enter the **DMP Password** and **Filename**.

5. Click **OK** to confirm and close the window.

Import Database

The Import Database function only imports data table of the dump file exported using the Export Database function.

Figure 1-11   Import Database

1. In Tools Import/Export tab, select **Import Database** from the ribbon bar.

2. In the Import Database window, enter **Encryption Key** of the dump file. The encryption key must match the key entered during database export in Tools application, Export Database function.

3. Click the **Select Dump File** at the ribbon bar and browse the file to import.

4. If the Encryption Key does not match, you are prompt with message, *'Padding is invalid and cannot be removed. This could mean the encryption key is wrong.'*

   If TDE applies, you will be prompt to enter the DMP file name and password mentioned in step 4 of Export Database. If the destination database is on another server, copy the DMP file from the source database server to the destination server first before proceeding to step 5.

5. List of tables populates on the window once the dump file decompresses and decrypted successfully. This does not apply if TDE is used. Select the table to import.

   Table that does not exists in dump file are marked with comment *'table does not exist in dump file'* in the comment column. The system will drop and re-import all existing table during this process.

6. Click **Import Database** at the ribbon bar. You will be prompt to close all application before continuing.

7. Click **Yes** to stop the running instance and proceed with import. During the import routine, the system drops the database tables and re-import all existing tables.

8. Once import completes, system prompts *'Import Database Completed, the log file will be show.'*

9. Close the prompt to exit the application.

Export Safety Setup

This function exports all the Safety setup from one ship to another. We recommend that you to use this tool with the new Muster List, In Port Manning and Safety Drill setup.

Figure 1-12   Export Safety Setup

1. In the Tools Import/Export tab, select **Export Safety Setup** from the ribbon bar.

2. In Export Safety Setup window, check the desire the Safety setup and then click **Export** to export. Files are exported to `C:\Users\Public\Documents\Oracle Hospitality Cruise\SafetySetup_v8.xxx_yyymmdd.xml.'`

Import Safety Setup

This function is similar to the Import Database function with the exception that it *only* import Safety Setup that are export from Export Safety Setup in Tools application.

1. At the Tools Import/Export tab, select **Import Safety Setup** from the ribbon bar.

2. At the Import Safety Setup window, click **SELECT FILE** to browse the XML file from Public Document folder.

Figure 1-13   Import Safety Setup

3. Check **Overwrite all the existing data without interlink** if you wish to overwrite existing data without interlink. The system does not overwrite data that has an inter link to other tables and prompt the following message if inter link data is found *'System notified that there are some inter link table. System not going to overwrite existing data. Import Failed.'*

   Completed course and certificate (COU) are not import into database if the record is found in Require Course and Certificate (REQ), Require Substitution Courses (RQS), and Require Course and Certificate for each operation position (RER). The same applies to Muster List setup.

4. Click **Import** and select **Yes** when prompt *'There are existing data in either of this table (xxx,xxx). Are you sure want to overwrite?'*.

5. At the message prompt *'Import of Safety Setup Completed.'*, click **Close** to exit.

Export Package Template

This function duplicates the package plan template from one ship to another.

1. At the Tools Import/Export tab, select **Export Package Template** from the ribbon bar.

2. At the Export Package Template setup, select the **Package Plan Template** to export.

3. Click **Export** and browse the location to save the XML file.

4. Click **OK** when message prompt *'Export of Package Template Completed.'*

Import Package Template

This function imports the package plan template exported from Export Package Template function in Tools application.

1. At the Tools Import/Export tab, select **Import Package Template** from the ribbon bar.

2. At Import Package Template window, click **Select File** to browse the XML file.

3. Check mark the template you wish to import from the **Selected** column.

4. Click **Import** to be begin import.

5. At the message prompt 'Some of the template already exists in the DB, do you want to overwrite it?', click **Yes** to continue, and then **OK** to close the window.

Import Barcode for Simphony

This function imports menu item barcode into Simphony database and it requires a connection to Simphony System setup in **Administration, System Setup, Parameter 'PROMO', 'Micros Server Name = 'hostname of Simphony database / Simphony'**, and a username. The database password entered is using the Change Password function in MICROS Password in Tools application.

When importing the barcode and the system prompt a message *'The Micros DB is not Simphony or the DB is offline.'*. This is due to the parameter **'Simphony', 'Micros Simphony Property Number'** that is use to copy the DB is invalid.

1. At the Tools Import/Export tab, select **Import Barcode for Simphony** from the ribbon bar and select the revenue center under the **Locations** section.

2. Click **Load from CSV file**. Sample in the CSV file format are:

    • Field 1 = menu item object number

    • Field 2 = menu item name (for reference only)

    • Field 3 = barcode

3. You can select to import from **Parent, Property ID** or in **Revenue Center**.

4. When importing from Parent group, the Child group will follow. However, changes made to the Child group does not affect the Parent record. All new records will not have any status shown in the status column.

5. Click **Import** to proceed and the system prompt a message *'x record(s) imported, x record (s) failed to imported'* when the import completes. The program only import valid item and non-duplicate item.