Claim Lodged Under Guarantee Issued User Guide Oracle Banking Trade Finance Process Management

Release 14.5.2.0.0

Part No. F45916-01

August 2021



Oracle Banking Trade Finance Process Management - Claim Lodged Under Guarantee Issued User Guide Oracle Financial Services Software Limited

Oracle Park
Off Western Express Highway
Goregaon (East)
Mumbai, Maharashtra 400 063
India
Worldwide Inquiries:
Phone: +91 22 6718 3000
Fax: +91 22 6718 3001

www.oracle.com/financialservices/

Copyright © 2018-2021, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Contents

Oracle Banking Trade Finance Process Management	1
Overview	1
Benefits	1
Key Features	1
Claim Lodged Under Guarantee Issued	
Common Initiation Stage	2
Registration	3
Application Details	5
Guarantee Details	6
Miscellaneous	8
Scrutiny	g
Main Details	12
Claim Details	18
Document Details	22
Additional Fields	24
Advices	26
Additional Details	30
Summary	37
Data Enrichment	40
Main Details	42
Claim Details	42
Document Details	42
Additional Fields	43
Advices	44
Additional Details	44
Preview Message	
Settlement Details	
Summary	
Multi Level Approval	
Re-Key Authorization	50
Reference and Feedback	54
References	54
Documentation Accessibility	54
Feedback and Support	54



Oracle Banking Trade Finance Process Management

Welcome to the Oracle Banking Trade Finance Process Management (OBTFPM) User Guide. This guide provides an overview on the OBTFPM application and takes you through the various steps involved in creating and processing Trade Finance transactions.

This document will take you through following activities in OBTFPM:

- To create and handle Trade Finance transaction.
- Help users to conveniently create and process Trade Finance transaction.

Overview

OBTFPM is a trade finance middle office platform, which enables bank to streamline the trade finance operations. OBTFPM enables the customers to send request for new trade finance transaction either by visiting the branch (offline channels) or through SWIFT/Trade Portal/other external systems (online channels).

Benefits

OBTFPM helps banks to manage Trade Finance operations across the globe in different currencies. OBTFPM allows you to:

- Handle all Trade Finance transactions in a single platform.
- Provides support for limit verification and limit earmarking.
- · Provide amount block support for customer account.
- Provides acknowledgement to customers.
- Enables the user to upload related documents during transaction.
- Enables to Integrate with back end applications for tracking limits, creating limit earmarks, amount blocks, checking KYC, AML and Sanction checks status.
- Create, track and close exceptions for the above checks.
- Enables to use customer specific templates for fast and easy processing of trade transactions that reoccur periodically.

Key Features

- Stand-alone system that can be paired with any back end application.
- Minimum changes required to integrate with bank's existing core systems.
- Faster time to market.
- Capable to interface with corporate ERP and SWIFT to Corporate.
- Highly configurable based on bank specific needs.
- Flexibility in modifying processes.



Claim Lodged Under Guarantee Issued

As part of Lodge Claim - Guarantee Issued process, the applicant can lodge a claim against the Guarantee/SBLC issued.

The various scenarios to lodge the complaint against the guarantee issued:

- · Claim received from beneficiary directly at Issuing Bank
- Claim received from the Counter Issuing Bank (CIB) at Counter Counter Issuing Bank (enable SWIFT STP)
- Claim received from LIB at CIB (enable SWIFT STP)
- Claim received from advising bank/ATB at ISB (enable SWIFT STP)
- Claim received from beneficiary bank through a swift message at ISB (enable SWIFT STP)
- Claim received at the LIB to be claimed with CIB-Enable SWIFT STP
- Claim received from LIB at CIB to be claimed from CCIB- Enable SWIFT STP

In the subsequent sections, let's look at the details for Lodge Claim - Guarantee Issuance process:


This section contains the following topics:

Common Initiation Stage	Registration
Data Enrichment	Scrutiny
Multi Level Approval	

Common Initiation Stage

The user can initiate the new claim under Guarantee Issued request from the common Initiate Task screen.

- 1. Using the entitled login credentials, login to the OBTFPM application.
- 2. Click Trade Finance > Initiate Task.





Provide the details based on the description in the following table:

Field	Description
Process Name	Select the process name to initiate the task.
Branch	Select the branch.

Action Buttons

Use action buttons based on the description in the following table:

Field	Description
Proceed	Task will get initiated to next logical stage.
Clear	The user can clear the contents update and can input values again.

Registration


During the Registration stage, the user can register a claim request against the Guarantee/SBLC issued.


The user can capture the basic details of the application, check the signature of the applicant and upload the related documents of the applicant.

1. Using the entitled login credentials for registration stage, login to the OBTFPM application.











3. Click Trade Finance> Bank Guarantee Issuance > Lodge Claim - Guarantee Issued.



The Registration stage has two sections Application Details and Guarantee Details. Let's look at the registration screens below:

Application Details



Provide the Application Details based on the description in the following table:


Field	Description	Sample Values
Undertaking Number	User can enter the undertaking number. The user can also search the undertaking number through LOV search.	
Customer ID/ Name	Read only field.	001345
	System defaults the Customer ID/ Name from Guarantee/ SBLC Issuance.	
Branch	Customer's home branch will be displayed.	203-Bank
	Read only field.	Futura -Branch FZ1
	System defaults the home branch from Guarantee/ SBLC Issuance.	
Claim Serial Number	Read only field.	
	System defaults the claim serial number from Guarantee/ SBLC Issuance. This should be the latest claim number available in back-end system +1.	
Process Reference	Unique sequence number for the transaction.	203GTEISS000
Number	This is auto generated by the system based on process name and branch code.	001134
Priority	Priority maintained will be populated as either 'Low or Medium or High'. If priority is not maintained for a customer, 'Medium' priority will be defaulted.	High



Field	Description	Sample Values
Submission Mode	Select the submission mode of Guarantee Issuance request. By default the submission mode will have the value as 'Desk'.	Desk
	Desk- Request received through Desk	
	Fax - Request received through Fax	
	Email - Request received through Email	
Claim Lodgement Date	By default, the application will display branch's current date. Read only field.	04/13/2018
	Note Future date and back date selection is not allowed.	
Beneficiary Reference Number	User can enter the 'Beneficiary Reference number' if available.	

Guarantee Details

Registration user can provide Guarantee details in this section. Alternately, guarantee details can be provided by Scrutiny user.



Provide the Guarantee Details based on the description in the following table:

Field	Description	Sample Values
Guarantee Type	Read only field. System defaults the value from Guarantee/ SBLC Issuance.	ADVP




Field	Description	Sample Values
Date of Issue	Read only field.	04/13/18
	System defaults the value from Guarantee/ SBLC Issuance.	
Purpose of message	Read only field.	
	System defaults the purpose of message from Guarantee/ SBLC Issuance.	
Expiry Type	This field indicates whether undertaking has specified expiry date or is open-ended.	
	System defaults the expiry type from Guarantee/ SBLC Issuance.	
Date Of Expiry	Expiry date of the Guarantee Issuance.	09/30/18
	System defaults the expiry date from Guarantee/ SBLC Issuance.	
Claim Date	System defaults the claim date from Guarantee/ SBLC Issuance.	04/13/2018
Claim Expiry Date	System defaults the claim expiry date from Guarantee/ SBLC Issuance.	04/13/2018
Outstanding Currency/ Amount	System defaults the outstanding currency and amount from Guarantee/ SBLC Issuance.	
Applicable Rules	Rules for Guarantee. Read only field.	URDG -
	System defaults the value from Guarantee/ SBLC Issuance.	Uniform rules for demand guarantees
Applicant Bank	Read only field.	001345 Nestle
	System defaults the applicant bank details from Guarantee/ SBLC Issuance.	
Applicant	Read only field.	001345 Nestle
	System defaults the applicant from Guarantee/SBLC Issuance.	
Beneficiary	Read only field.	001345 Nestle
	System defaults the beneficiary from Guarantee/ SBLC Issuance. User can modify the beneficiary if required.	
Advising Bank	Read only field.	001343 - Bank
	System defaults the advising bank if available.	Of America
Advising Through Bank	Read only field.	Advising Bank
	System defaults the advising through bank if available.	Reference



Field	Description	Sample Values
Counter Guarantee Issuing Bank	Read only field. System defaults the counter guarantee issuing through bank if available.	
Local Guarantee Issuing Bank	Read only field. System defaults the local guarantee issuing bank if available.	
Presenting Bank	User can select the presenting bank reference if available. Note Currently this field is not available in OBTF.	

Miscellaneous



Provide the Miscellaneous Details based on the description in the following table:

Field	Description	Sample Values
Documents	Upload the claim documents.	
	Application will display the mandatory and optional documents.	
Remarks	Provide any additional information regarding the Claim Guarantee Issuance. This information can be viewed by other users processing the request.	
	Content from Remarks Field should be handed off to Remarks field in Backend application.	
View Guarantee/SBLC	User can view the the latest Guarantee/Standby LC details.	
Guarantee/SBLC Events	User can view all the previous events under the Guarantee/Standby LC.	



Field	Description	Sample Values
Submit	On Submit, system will trigger acknowledgment to the customer and give confirmation message for successful submission. Task will get moved to next logical stage of Guarantee Issuance. If mandatory fields have not been captured, system will display an error message until the mandatory fields data are provided.	
Save & Close	Save the information provided and holds the task in you queue for working later. This option will not submit the request.	
Cancel	Cancels the Guarantee Issuance Registration stage input.	
Hold	The details provided will be registered and status will be on hold. This option is used, if there are any pending information yet to be received from applicant.	
Checklist	Make sure that the details in the checklist are completed and acknowledge. If mandatory checklist items are not marked, system will display an error on submit. 1. Signatures on Claim verified 2. Documents are verified and uploaded	


Scrutiny

On successful completion of Registration of a Guarantee issuance request, the request moves to scrutiny stage. At this stage the gathered information during Registration stage and claim request are scrutinized. As part of scrutiny, the bank user can update the various claim fields. The user should also be able to input the transaction details.


Do the following steps to acquire a task currently at Scrutiny stage:



1. Using the entitled login credentials for scrutiny stage, login to the OBTFPM application.




2. On login, user must be able to view the dashboard screen with widgets as mapped to the user.







3. Click Trade Finance> Tasks> Free Tasks.



Select the appropriate task and click Acquire & Edit to edit the task or click Acquire to edit the task from My Tasks.



5. The acquired task will be available in **My Tasks** tab. Click **Edit** to provide input for data enrichment stage.



The Scrutiny stage has five sections as follows:

- Main Details
- Claim Details
- Document Details
- Additional Fields



- Advices
- Additional Details
- Settlement Details
- Summary

Let's look at the details for scrutiny stage. User can enter/update the following fields as part of claim under Guarantee/SBLC - Scrutiny Stage. Some of the fields that are already having value from registration/online channels may not be editable.

In case of requests received through SWIFT MT765, the task will be created in Scrutiny stage directly and the fields will be populated based on the incoming request.


Main Details

Main details section has three sub section as follows:

- Application Details
- Guarantee Details

Application Details

All fields displayed under Application details section, would be read only except for the **Priority**. Refer to Application Details in the Registration stage for more information of the fields.



In case of SWIFT MT 765, the system displays the following fields.

Field	Description	Sample Values
Undertaking Number	In case of SWIFT MT 765, Read Only. System to populate the undertaking number from the incoming SWIFT MT 765, Tag 21 Related Reference.	
Customer ID/ Name	Read only field. System defaults the Customer ID/ Name from the underlying Guarantee/ SBLC Issuance.	001345




Field	Description	Sample Values
Branch	Read only field. System defaults the branch code as applicable.	203-Bank Futura -Branch FZ1
Claim Serial Number	Read only field. System defaults the claim serial number from Guarantee/ SBLC Issuance. This should be the latest claim number available in back-end system +1.	
Process Reference Number	Unique sequence number for the transaction. This is auto generated by the system based on process name and branch code.	203GTEISS000 001134
Priority	Priority maintained will be populated as either 'Low or Medium or High'. If priority is not maintained for a customer, 'Medium' priority will be defaulted.	High
Submission Mode	In case of SWIFT MT 765 system defaults the submission mode as 'SWIFT'.	
Claim Lodgement Date	By default, the application will display branch's current date. Read only field. Note Future date and back date selection is not allowed.	04/13/2018
Beneficiary Reference Number	In case of SWIFT MT 765, System populates Tag 23 - Beneficiary Reference Number from the Incoming MT 765.	

Guarantee Details

The fields listed under this section are same as the fields listed under the Guarantee Details section in Registration. Refer to Guarantee Details for more information of the fields. During registration, if user has not captured input, then user can capture the details in this section.





In case of SWIFT MT 765, the system displays the following fields.



Field	Description	Sample Values
Guarantee Type	Read only field.	ADVP
	System defaults the value from Guarantee/ SBLC Issuance.	
Date of Issue	Read only field.	04/13/18
	System defaults the value from Guarantee/ SBLC Issuance.	
Purpose of message	Read only field.	
	System defaults the purpose of message from Guarantee/ SBLC Issuance.	
Expiry Type	Read only field.	
	System defaults the expiry type as in Guarantee/ SBLC Issuance.	
Date Of Expiry	Read only field. System defaults the expiry date as in Guarantee/ SBLC Issuance.	09/30/18
Claim Date	Read only field. System defaults the claim date as in Guarantee/ SBLC Issuance.	04/13/2018
Claim Expiry Date	Read only field. System defaults the claim expiry date as in Guarantee/ SBLC Issuance.	04/13/2018
Outstanding Currency/ Amount	Read only field. System defaults the outstanding currency and amount from Guarantee/ SBLC Issuance.	
Applicable Rules	Read only field.	URDG -
	System defaults the value from Guarantee/ SBLC Issuance.	Uniform rules for demand guarantees
Applicant Bank	Read only field.	001345 Nestle
	System defaults the applicant bank details from Guarantee/ SBLC Issuance.	
Applicant	Read only field.	001345 Nestle
	System defaults the applicant from Guarantee/ SBLC Issuance.	
Beneficiary	System defaults the beneficiary as in Guarantee/ SBLC Issuance.	001345 Nestle
Advising Bank	Read only field.	001343 - Bank
	System defaults the advising bank if available in issuance.	Of America
Advising Through Bank	Read only field.	
	System defaults the advising through bank if available in issuance.	



Field	Description	Sample Values
Counter Guarantee Issuing Bank	Read only field. System defaults the counter guarantee issuing through bank if available in issuance.	
Local Guarantee Issuing Bank	Read only field. System defaults the local guarantee issuing bank if available in issuance.	
Presenting Bank	System defaults the presenting bank if available in issuance.	

Action Buttons

Use action buttons based on the description in the following table:


Field	Description	Sample Values
Reject	On click of Reject, user must select a reject reason from a list displayed by the system and the task may be terminated or moved to Reject Approval Stage.	
	Reject Codes:	
	 R1- Documents missing 	
	 R2- Signature Missing 	
	R3- Input Error	
	R4- Insufficient Balance/Limits	
	R5 - Others.	
	Select a Reject code and give a reject description.	
	This reject reason will be available in the remarks window throughout the process.	
Refer	On click of Refer, user will be able to refer the task back to the Data Enrichment user. User must select a Refer Reason from the values displayed by the system.	
	Refer Codes:	
	R1- Documents missing	
	R2- Signature Missing	
	R3- Input Error	
	R4- Insufficient Balance/Limits	
	R5 - Others.	
Hold	The details provided will be on hold.	
	This option is used, if there are any pending information yet to be received from applicant.	
Cancel	Cancel the Guarantee Issuance scrutiny stage inputs.	



Field	Description	Sample Values
Save & Close	Save the information provided and holds the task in you queue for working later. This option will not submit the request	
Next	On click of Next, system should validate if all the mandatory fields have been captured. Necessary error and override messages to be displayed. On successful validation, system moves the task to the next data segment.	
Documents	Click the Documents icon to View/Upload the required documents.	
	Application will display the mandatory and optional documents.	
	Note Not applicable for STP of SWIFT MT 765.	
Remarks	Click the Remarks icon to view the remarks captured as part of Registration stage and also can input Remarks, which can be seen by other users.	
Overrides	Click to view the overrides accepted by the user.	
Incoming Message	Clicking this button allows the user to see the message in case of STP of incoming MT 765.	
View Undertaking	Clicking this button allows the user to view the underlying Guarantee/SBLC from the back office system.	



Claim Details



Provide the Claim details based on the description in the following table:

Field	Description	Sample Values
Claim Received From	User can select the option from whom the claim has been received from the drop-down list.	
	The values are:	
	Beneficiary	
	Local Issuing Bank	
	Counter Issuing Bank	
	Advising Bank	
	Presenting Bank	
	In case of STP of Incoming MT 765, system should default the value based on the sender details available in MT 765.	
Claiming Bank Reference	The user can enter the claiming bank reference details, if the claimed is not received from Beneficiary.	
	User can enter the Transaction Reference number from MT 765. In case of STP of incoming MT 765, system to populate the details from incoming MT 765.	
	If the claim is received from the beneficiary, this field will not be editable.	
Claim To	User can select the party to which the claim has to be sent from the drop-down list.	
	The values are:	
	Applicant	
	Counter	
	Issuing Bank	
	I	I



Field	Description	Sample Values
Date of Demand	User can enter the date on which the demand is issued by the beneficiary.	
	In case of STP of Incoming MT 765, the System to populate the value in tag 31L, Date of Demand from incoming MT 765.	
Demand Type	This field specifies the type of demand.	
	The values are:	
	PAEX- Pay or extend	
	PAYM- Pay only.	
	In case of STP of Incoming MT 765, the demand type is defaulted from the incoming MT 765 message.	
	In case of Non-Online, User can input the value as per claim.	
Claim Currency/ Amount	User can select the currency for claim and enter the claim amount.	
New Expiry Date	User can enter the new expiry date, if Demand Type field is 'PAEX -Pay or extend'.	
	This field is disabled if the Demand Type is 'PAYM- Pay only'.	
	In case of STP of Incoming MT 765, the new expiry date is defaulted from the incoming MT 765 message.	
	In case of Non-Online, User can input the value as per claim.	
	System validates that the New Expiry Date is not earlier than the Expiry Date or not earlier than Branch Date	
Demand Statement	This field specifies the narrative text that constitutes the demand.	
	The codes can be:	
	 COMP: Complete demand, no other documentation to accompany or follow this message. 	
	 INCP: Incomplete demand, supporting documentation to be presented separately. 	
	In case of STP of Incoming MT 765, this field is defaulted from the incoming MT 765 message. In case of Non-Online, User can input the value as per claim.	



Field	Description	Sample Values
Presentation Completion Details	The user can enter the presentation of completion details, if demand statement is provided. This field specifies information about the presentation documentation. If the presentation is incomplete, this must specify how the presentation will be completed	
	In case of STP of Incoming MT 765, this field is defaulted from the incoming MT 765 message.	
	In case of Non-Online, User can input the value as per claim.	
Additional Amount Information	The user can enter the details on additional amount in this field.	
	In case of STP of Incoming MT 765, this field is defaulted from the incoming MT 765 message.	
	In case of Non-Online, User can input the value as per claim	
Intermediary	The user can enter the Intermediary bank details. This field specifies the financial institution through which the amount claimed must pass to reach the account with institution.	
	In case of STP of Incoming MT 765, this field is defaulted from the incoming MT 765 message.	
	In case of Non-Online, User can input the value as per claim.	
Account with Institution	The user can enter the details of Account with Institution.	
	This field specifies the financial institution at which the amount claimed is to be settled.	
	In case of STP of Incoming MT 765, this field is defaulted from the incoming message.	
	In case of Non-Online, User can input the value as per claim	
File Identification	The user can enter the File identification.	
	This field identifies the type of delivery channel and associated file name or reference.	
	In case of STP of Incoming MT 765, this field is defaulted from the incoming MT 765 message.	
	Non-Online – Not Applicable	
Sender to Receiver Information	The user can enter the Sender to receiver information from the incoming message in this field.	
	In case of STP of Incoming MT 765, this field is defaulted from the incoming MT 765 message.	
	Non-Online – Not Applicable.	



Action Buttons

Use action buttons based on the description in the following table:


Field	Description	Sample Values
Reject	On click of Reject, user must select a reject reason from a list displayed by the system and the task may be terminated or moved to Reject Approval Stage.	
	Reject Codes:	
	R1- Documents missing	
	R2- Signature Missing	
	R3- Input Error	
	R4- Insufficient Balance/Limits	
	R5 - Others.	
	Select a Reject code and give a reject description.	
	This reject reason will be available in the remarks window throughout the process.	
Refer	On click of Refer, user will be able to refer the task back to the Data Enrichment user. User must select a Refer Reason from the values displayed by the system.	
	Refer Codes:	
	 R1- Documents missing 	
	 R2- Signature Missing 	
	R3- Input Error	
	R4- Insufficient Balance/Limits	
	R5 - Others.	
Hold	The details provided will be on hold.	
	This option is used, if there are any pending information yet to be received from applicant.	
Cancel	Cancel the Guarantee Issuance scrutiny stage inputs.	
Save & Close	Save the information provided and holds the task in you queue for working later. This option will not submit the request	
Next	On click of Next, system should validate if all the mandatory fields have been captured. Necessary error and override messages to be displayed. On successful validation, system moves the task to the next data segment.	



Field	Description	Sample Values
Documents	Click the Documents icon to View/Upload the required documents.	
	Application will display the mandatory and optional documents.	
	Note Not applicable for STP of SWIFT MT 765.	
Remarks	Click the Remarks icon to view the remarks captured as part of Registration stage and also can input Remarks, which can be seen by other users.	
Overrides	Click to view the overrides accepted by the user.	
Incoming Message	Clicking this button allows the user to see the message in case of STP of incoming MT 765.	
View Undertaking	Clicking this button allows the user to view the underlying Guarantee/SBLC from the back office system.	

Document Details

In Document Details, the user can to view the Documents required for a claim and verify if the Claim Documents are submitted as per documents required. The user, can scrutinize the claim request and input data as required.



Provide the Document details based on the description in the following table:

In case of STP of Incoming MT 765, values should be handled as done in Offline process for Guarantee Claim.



Field	Description	Sample Values
Code	User can enter the document code.	
Name	System defaults the document name based on the document code.	
Сору	Copy of the document.	
Original	Original claim document.	
Description	User can enter the description of the document if any.	
Documents Received	User can enter the details of document received.	

Action Buttons

Use action buttons based on the description in the following table:

Field	Description	Sample Values
Reject	On click of Reject, user must select a reject reason from a list displayed by the system and the task may be terminated or moved to Reject Approval Stage.	
	Reject Codes:	
	R1- Documents missingR2- Signature MissingR3- Input Error	
	 R4- Insufficient Balance/Limits R5 - Others. 	
	Select a Reject code and give a reject description.	
	This reject reason will be available in the remarks window throughout the process.	
Refer	On click of Refer, user will be able to refer the task back to the Data Enrichment user. User must select a Refer Reason from the values displayed by the system.	
	Refer Codes:	
	 R1- Documents missing R2- Signature Missing R3- Input Error R4- Insufficient Balance/Limits 	
	R5 - Others.	




Field	Description	Sample Values
Hold	The details provided will be on hold. This option is used, if there are any pending information yet to be received from applicant.	
Cancel	Cancel the Guarantee Issuance scrutiny stage inputs.	
Save & Close	Save the information provided and holds the task in you queue for working later. This option will not submit the request	
Next	On click of Next, system should validate if all the mandatory fields have been captured. Necessary error and override messages to be displayed. On successful validation, system moves the task to the next data segment.	
Documents	Click the Documents icon to View/Upload the required documents. Application will display the mandatory and optional documents. Note Not applicable for STP of SWIFT MT 765.	
Remarks	Click the Remarks icon to view the remarks captured as part of Registration stage and also can input Remarks, which can be seen by other users.	
Overrides	Click to view the overrides accepted by the user.	
Incoming Message	Clicking this button allows the user to see the message in case of STP of incoming MT 765.	
View Undertaking	Clicking this button allows the user to view the underlying Guarantee/SBLC from the back office system.	

Additional Fields

This stage displays the additional fields based on the User defined fields maintained in the system.



In case of STP of Incoming MT 765, values should be handled as done in Offline process for Guarantee Claim.



Action Buttons

Use action buttons based on the description in the following table:

Field	Description	Sample Values
Reject	On click of Reject, user must select a Reject Reason from a list displayed by the system.	
	Reject Codes:	
	R1- Documents missing	
	 R2- Signature Missing 	
	R3- Input Error	
	R4- Insufficient Balance/Limits	
	R5 - Others.	
	Select a Reject code and give a Reject Description.	
	This reject reason will be available in the remarks window throughout the process.	
Refer	On click of Refer, user will be able to refer the task back to the Data Enrichment user. User must select a Refer Reason from the values displayed by the system.	
	Refer Codes:	
	R1- Documents missing	
	 R2- Signature Missing 	
	R3- Input Error	
	R4- Insufficient Balance/Limits	
	R5 - Others.	




Field	Description	Sample Values
Hold	The details provided will be on hold. This option is used, if there are any pending information yet to be received from applicant.	
Cancel	Cancel the Guarantee Advise Amendment inputs.	
Next	On click of Next, system should validate if all the mandatory fields have been captured. Necessary error and override messages to be displayed. On successful validation, system moves the task to the next data segment.	
Save & Close	Save the information provided and holds the task in you queue for working later. This option will not submit the request	
Documents	Click the Documents icon to View/Upload the required documents. Application will display the mandatory and optional documents. Note Not applicable for STP of SWIFT MT 765.	
Remarks	Click the Remarks icon to view the remarks captured as part of Registration stage and also can input Remarks, which can be seen by other users.	
Overrides	Click to view the overrides accepted by the user.	
Incoming Message	Clicking this button allows the user to see the message in case of STP of incoming MT 765.	
View Undertaking	Clicking this button allows the user to view the underlying Guarantee/SBLC from the back office system.	

Advices


This section defaults the advices maintained for the product based on the advices maintained at the Product level.

In case of STP of Incoming MT 765, values should be handled as done in Offline process for Guarantee Claim.





The user can also suppress the Advice, if required.



Field	Description	Sample Values
Suppress Advice	Toggle on : Switch on the toggle if advice is suppressed.	
	Toggle off : Switch off the toggle if suppress advice is not required for the amendments	
Advice Name	User can select the instruction code as a part of free text.	
Medium	The medium of advices is defaulted from the system. User can update if required.	
Advice Party	Value be defaulted from Guarantee /SBLC Issuance. User can update if required.	
Party ID	Value be defaulted from Guarantee /SBLC Issuance. User can update if required.	



Field	Description	Sample Values
Party Name	Read only field.	
	Value be defaulted from Guarantee /SBLC Issuance.	
Free Format Text		
FTT Code	User can select the FFT code as a part of free text.	
FFT Description	FFT description is populated based on the FFT code selected.	
+	Click plus icon to add new FFT code.	
-	Click minus icon to remove any existing FFT code.	
Instruction Details		
Instruction Code	User can select the instruction code as a part of free text.	
Instruction Description	Instruction description is populated based on the FFT code selected.	
+	Click plus icon to add new instruction code.	
-	Click minus icon to remove any existing instruction code.	



Action Buttons

Use action buttons based on the description in the following table:

Field	Description	Sample Values
Reject	On click of Reject, user must select a Reject Reason from a list displayed by the system. Reject Codes: R1- Documents missing R2- Signature Missing R3- Input Error R4- Insufficient Balance/Limits R5 - Others. Select a Reject code and give a Reject Description. This reject reason will be available in the remarks window throughout the process.	
Refer	On click of Refer, user will be able to refer the task back to the Data Enrichment user. User must select a Refer Reason from the values displayed by the system. Refer Codes: R1- Documents missing R2- Signature Missing R3- Input Error R4- Insufficient Balance/Limits R5 - Others.	
Hold	The details provided will be on hold. This option is used, if there are any pending information yet to be received from applicant.	
Cancel	Cancel the Guarantee Advice Scrutiny inputs.	
Next	Task will get moved to next logical stage of Guarantee Amendment Advise. If mandatory fields have not been captured, system will display an error message until the mandatory fields data are provided.	
Save & Close	Save the information provided and holds the task in you queue for working later. This option will not submit the request	
Back	On clicking the Back, system should move the task to the previous segment.	



Field	Description	Sample Values
Documents	Click the Documents icon to View/Upload the required documents.	
	Application will display the mandatory and optional documents.	
	Note Not applicable for STP of SWIFT MT 765.	
Remarks	Click the Remarks icon to view the remarks captured as part of Registration stage and also can input Remarks, which can be seen by other users.	
Overrides	Click to view the overrides accepted by the user.	
Incoming Message	Clicking this button allows the user to see the message in case of STP of incoming MT 765.	
View Undertaking	Clicking this button allows the user to view the underlying Guarantee/SBLC from the back office system.	


Additional Details

As a part of Additional details section, Guarantee /Standby claim may have impact on the Limits & Collaterals.

If any of the fields in the financial section of the pop up screen is checked then the limits and collaterals screen will be enabled.

In case of STP of Incoming MT 765, values should be handled as done in Offline process for Guarantee Claim.







Limits & Collateral

Provide the Limit Details based on the description in the following table:







Field	Description	Sample Values
Edit Link	Click edit link to edit any existing Limit Details.	
Plus Icon	Click plus icon to add new Limit Details.	
Minus Icon	Click minus icon to remove any existing Limit Details.	
Limit Details	Customer ID: Applicant's/Applicant Bank customer ID will get defaulted.	
Line ID	User can choose from the various lines available and mapped under the customer id gets listed in the drop down. LINE ID-DESCRIPTION will be available for selection along with Line ID. When you click on 'verify', the system will return value if the limit check was successful or Limit not Available. If limit check fails, the outstanding limit after the transaction value will be shown in the limit outstanding amount.	




Field	Description	Sample Values
Contribution	System will default this to 100% and user can modify. System will display an alert message, if modified.	
	Once contribution % is provided, system will default the amount.	
	System to validate that if Limit Contribution% plus Collateral% is equal to 100. If the total percentage is not equal to 100 application will display an alert message.	
Contribution Currency	The guarantee currency will be defaulted in this field.	
Contribution Amount	Contribution amount will default based on the contribution %.	
Limit Currency	Limit Currency will be defaulted in this field.	
Limit Available Amount	This field will display the value of available limit, i.e., limit available without any earmark. The Limit Available Amount must be greater than the Contribution Amount.	
Limit Check Response	Response can be 'Success' or 'Limit not Available'.	
Response Message	Detailed Response message.	
Expiry Date	This field displays the date up to which the Line is valid	

Provide the collateral details based on the description provided in the following table:







Field	Description	Sample Values
Edit Link	Click edit link to edit any existing Limit Details.	
Plus Icon	Click plus icon to add new Collateral Details.	
Minus Icon	Click minus icon to remove any existing Collateral Details.	
Collateral Type	Cash Collateral (CASA) will be the default value available as collateral type. User can select either Cash Collateral or Deposits.	
Collateral %	User must enter the percentage of collateral to be linked to this transaction. If the value is more than 100% system will display an alert message.	




Field	Description	Sample Values
Currency	The guarantee currency will get defaulted in this field.	
Contribution Amount	Collateral contribution amount will get defaulted in this field.	
Settlement Account	Select the settlement account for the collateral.	
Settlement Account Branch	Settlement Account Branch will be auto- populated based on the Settlement Account selection.	
Settlement Account Currency	Select the Settlement Account Currency.	
Account Available Amount	Account Available Amount will be auto-populated based on the Settlement Account selection.	
Response	Response can be 'Success' or 'Amount not Available'.	
Response Message	Detailed Response message.	

Charge Details

Click on **Default Charges** button to the default commission, charges and tax if any will get populated.

If default charges are available under the product, they should be defaulted here with values. If customer or customer group specific charges are maintained, then the same will be defaulted from back end system.



Provide the Charge Details based on the description provided in the following table:

Field	Description	Sample Values
Component	Charge Component type.	
Currency	Defaults the currency in which the charges have to be collected.	
Amount	An amount that is maintained under the product code gets defaulted in this field. User can edit the value, if required.	



Field	Description	Sample Values
Modified Amount	User can enter a new amount in 'Modified amount' field. This will be the new charge for the modified component.	
Billing	If charges are handled by separate billing engine, then by selecting billing the details to be available for billing engine for further processing.	
	On simulation of charges/commission from Back Office, if any of the Charges/Commission component for the customer is 'Billing' enabled, 'Billing' toggle for that component should be automatically checked in OBTFPM.	
	The user can not select/de-select the check box if it is de-selected by default.	
	This field is disabled, if 'Defer' toggle is enabled.	
Defer	If charges have to be deferred and collected at any future step, this check box has to be selected.	
	On simulation of charges/commission from Back Office, if any of the Charges/Commission component for the customer is AR-AP tracking enabled, 'Defer' toggle for that component should be automatically checked in OBTFPM.	
	The user can select/de-select the check box. On de-selection the user has to click on 'Recalculate' charges button for re-simulation.	
Waive	If charges have to be waived, this check box has to be selected.	
	Based on the customer maintenance, the charges should be marked for Billing or for Defer.	
	This field is disabled, if 'Defer' toggle is enabled.	
Charge Party	Charge party will be applicant by default. You can change the value to beneficiary	
Settlement Account	Details of the settlement account.	

Commission Details

Provide the Commission Details based on the description provided in the following table:



Field	Description	Sample Values
Component	Select the commission component	




Field	Description	Sample Values
Rate	Defaults from product. User can change the rate, if required.	
Currency	Defaults the currency in which the commission needs to be collected	
Amount	An amount that is maintained under the product code defaults in this field. User can modify the value, if required.	
Modified Amount	User can enter a new amount in 'Modified amount' field. This will be the new charge for the modified component.	
Billing	If charges/commission is handled by separate billing engine, then by selecting billing the details to be available for billing engine for further processing.	
Defer	Select the check box, if charges/commissions has to be deferred and collected at any future step.	
Waive	Select the check box to waive charges/ commission.	
	Based on the customer maintenance, the charges/commission can be marked for Billing or Defer.	
Charge Party	Charge party will be 'Applicant' by Default. You can change the value to Beneficiary.	
Settlement Account	Details of the Settlement Account.	

Tax Details

The tax component defaults if maintained in the product level. Tax detail cannot be updated by you and any change in Tax amount on account of modification of charges/ commission will be available on click of Re-Calculate button or on hand off to back-end system.

Following Tax Details will be displayed:



Field	Description	Sample Values
Component	Tax Component type.	
Currency	The tax currency is the same as the commission.	
Amount	The tax amount defaults based on the percentage of commission maintained. User can edit the tax amount, if required.	



Field	Description	Sample Values
Settlement Account	Details of the settlement account.	

Field	Description	Sample Values
Save & Close	Save the information provided and holds the task in you queue for working later. This option will not submit the request	
Cancel	Cancel the Scrutiny Stage Inputs.	
Hold	The details provided will be registered and status will be on hold. This option is used, if there are any pending information yet to be received from applicant.	
Reject	On click of Reject, user must select a reject reason from a list displayed by the system. Reject Codes: R1- Documents missing R2- Signature Missing R3- Input Error R4- Insufficient Balance/Limits R5 - Others. Select a Reject code and give a reject description. This reject reason will be available in the remarks window throughout the process.	
Next	On click of Next, system should validate if all the mandatory fields have been captured. Necessary error and override messages to be displayed. On successful validation, system moves the task to the next data segment.	
Documents	Click the Documents icon to View/Upload the required documents. Application will display the mandatory and optional documents. Note Not applicable for STP of SWIFT MT 765.	




Field	Description	Sample Values
Remarks	Click the Remarks icon to view the remarks captured as part of Registration stage and also can input Remarks, which can be seen by other users.	
Overrides	Click to view the overrides accepted by the user.	
Incoming Message	Clicking this button allows the user to see the message in case of STP of incoming MT 765.	
View Undertaking	Clicking this button allows the user to view the underlying Guarantee/SBLC from the back office system.	

Summary

User can review the summary screen for Guarantee /Standby Claim request.

Log in to Oracle Banking Trade Finance Process Management (OBTFPM) system, user can see the summary tiles. The tiles must display a list of important fields with values. The tiles where fields have been amended is highlighted in different color, User must be also able to drill down from summary tiles into respective data segments.



Tiles Displayed in Summary

- Main Details User can view the application details and Guarantee/ Standby details. User can modify the details if required.
- Party Details User can view the party details like beneficiary, advising bank etc.
- Claim Details User can view the claim details.
- Documents Details- User can view the Document details.
- Additional Fields User can view the additional fields.
- Commission, tax and Charges User can view the details provided for charges. User can modify the details if required.



Field	Description	Sample Values
Submit	Task will get moved to next logical stage of Guarantee Claim.	
	If mandatory fields have not been captured, system will display an error message until the mandatory fields data are provided.	
Reject	On click of Reject, user must select a Reject Reason from a list displayed by the system.	
	Reject Codes:	
	R1- Documents missing	
	R2- Signature Missing	
	R3- Input Error	
	R4- Insufficient Balance/Limits	
	R5 - Others.	
	Select a Reject code and give a Reject Description.	
	This reject reason will be available in the remarks window throughout the process.	
Refer	On click of Refer, user will be able to refer the task back to the Data Enrichment user. User must select a Refer Reason from the values displayed by the system.	
	Refer Codes:	
	R1- Documents missing	
	R2- Signature Missing	
	R3- Input Error	
	R4- Insufficient Balance/Limits	
	R5 - Others.	
Hold	The details provided will be on hold.	
	This option is used, if there are any pending information yet to be received from applicant.	
Cancel	Cancel the Guarantee Advice Scrutiny inputs.	
Save & Close	Save the information provided and holds the task in you queue for working later. This option will not submit the request	
Back	On clicking the Back, system should move the task to the previous segment.	



Field	Description	Sample Values
Documents	Click the Documents icon to View/Upload the required documents.	
	Application will display the mandatory and optional documents.	
	Note Not applicable for STP of SWIFT MT 765.	
Remarks	Click the Remarks icon to view the remarks captured as part of Registration stage and also can input Remarks, which can be seen by other users.	
Overrides	Click to view the overrides accepted by the user.	
Incoming Message	Clicking this button allows the user to see the message in case of STP of incoming MT 765.	
View Undertaking	Clicking this button allows the user to view the underlying Guarantee/SBLC from the back office system.	

Data Enrichment


As part of Data Enrichment, user can enter/update the various fields of the claim request. The user can also input the transaction details.

In case of requests received through SWIFT MT765, the task will be created in DE stage directly and the fields will be populated based on the incoming request.


Do the following steps to acquire a task which completed the Registration and Scrutiny and currently at Data enrichment stage:




1. Using the entitled login credentials for scrutiny stage, login to the OBTFPM application.



2. On login, user must be able to view the dashboard screen with widgets as mapped to the user.




3. Click Trade Finance> Tasks> Free Tasks.



4. Select the appropriate task and click **Acquire & Edit** to edit the task or click **Acquire** to edit the task from **My Tasks**.



5. The acquired task will be available in My Tasks tab. Click Edit to scrutinize the registered task.



The Data Enrichment stage has three sections as follows:

- Main Details
- Claim Details
- Document Details
- Additional Fields



- Advices
- Additional Details
- Settlement Details
- Summary

Main Details


Refer to Main Details.

Claim Details

Refer to Claim Details.

Document Details

As a part of Data Enrichment the user can capture the documents under acclaim and user must be able to input the details if required.




System defaults the document details ilf documents to be submitted were provided in the Guarantee Issuance, else the user can capture the documents submitted under the claim.

Refer to Document Details



Additional Fields

This stage displays the additional fields based on the User defined fields maintained in the system.



Refer to Additional Fields.

Advices

This section defaults the advices maintained for the product based on the advices maintained at the Product level.



Refer to Advices.


Additional Details

Refer to Additional Details.



Preview Message

Based on details captured in the previous screen, the preview message simulated from the back office and the user can view the message.




Field	Description	Sample Values	
Preview SWIFT Message	Preview SWIFT Message		
Currency	The tax currency is the same as the commission.		
Language	Select the language for the SWIFT message.		
Message Type	Select the message type.		
Preview Advice	Display a preview of the draft message.		
Preview Mail Device			
Language	Select the language for the advice message.		
Advice Type	Select the advice type.		
Message Type	Display a preview of the advice.		
Following fields will have values on receipt of customer response.			
Customer Response	User can enter the response received from customer. If the response is received online, the response is auto populated in this field by the system		
Customer Remarks	Remarks from the customer for the draft		
Response Date	Customer Response received date.		
Default Email list	Default email address of the customer.		
Add Recipients	Enables to add more recipients for the customer response.		



Field	Description	Sample Values
Refer	On click of Refer, user will be able to refer the task back to the Data Enrichment user. User must select a Refer Reason from the values displayed by the system. Refer Codes: R1- Documents missing R2- Signature Missing R3- Input Error R4- Insufficient Balance/Limits R5 - Others.	
Hold	The details provided will be on hold. This option is used, if there are any pending information yet to be received from applicant.	
Cancel	Cancel the Guarantee Advice Scrutiny inputs.	
Next	Task will get moved to next logical stage of Guarantee Amendment Advise. If mandatory fields have not been captured, system will display an error message until the mandatory fields data are provided.	
Save & Close	Save the information provided and holds the task in you queue for working later. This option will not submit the request	
Back	On clicking the Back, system should move the task to the previous segment.	



Settlement Details



Current Event	The user can select the check box to populate the settlement details of the current event associated with the task. On De-selecting the check box, the system list all the accounts under the settlement details irrespective of the current event.	
Component	Components gets defaulted based on the product selected.	
Currency	Application displays the default currency for the component.	
Debit/Credit	Application displays the debit/credit indicators for the components.	
Account	Application Displays the account details for the components.	
Account Description	Application displays the description of the selected account.	
Account Currency	Application defaults the currency for all the items based on the account number.	
Netting Indicator	Application displays the applicable netting indicator.	
Current Event	System displays the current event as Y or N.	




Field	Description	Sample Values
Reject	On click of Reject, user must select a Reject Reason from a list displayed by the system. Reject Codes: R1- Documents missing R2- Signature Missing R3- Input Error R4- Insufficient Balance/Limits R5 - Others. Select a Reject code and give a Reject Description. This reject reason will be available in the remarks window throughout the process.	
Refer	On click of Refer, user will be able to refer the task back to the Data Enrichment user. User must select a Refer Reason from the values displayed by the system. Refer Codes: R1- Documents missing R2- Signature Missing R3- Input Error R4- Insufficient Balance/Limits R5 - Others.	
Hold	The details provided will be on hold. This option is used, if there are any pending information yet to be received from applicant.	
Cancel	Cancel the Guarantee Advice Scrutiny inputs.	
Next	Task will get moved to next logical stage of Guarantee Amendment Advise. If mandatory fields have not been captured, system will display an error message until the mandatory fields data are provided.	
Save & Close	Save the information provided and holds the task in you queue for working later. This option will not submit the request	
Back	On clicking the Back, system should move the task to the previous segment.	
Incoming Message	Clicking this button allows the user should be able to see the message in case of STP of incoming MT 767.	



Summary

User can review the summary of details updated in Data Enrichment stage for claim logged under Guarantee / SBLC Issued request.

Log in to Oracle Banking Trade Finance Process Management (OBTFPM) system to see the Summary tiles. The tiles must display a list of important fields with values.



Tiles Displayed in Summary

- Main Details User can view the application details and Guarantee/ Standby details. User can modify the details if required.
- Party Details User can view the party details like beneficiary, advising bank etc.
- Claim Details User can view the claim details.
- Documents Details- User can view the Document details.
- Additional Fields User can view the additional fields.
- Limits and Collaterals User can view the limits and collateral details. User can modify the details if required.
- Commission, tax and Charges User can view the details provided for charges. User can modify the details if required.
- Preview Messages User can drill down to view the message preview, legal verification and customer draft confirmation details. The message preview screen has the Legal Verification details.
- Settlement Details User can view the settlement details.
- Compliance User can view compliance details. The status must be verified for KYC and to be initiated for AML and Sanction Checks.



Field	Description	Sample Values
Reject	On click of Reject, user must select a Reject Reason from a list displayed by the system. Reject Codes: R1- Documents missing R2- Signature Missing R3- Input Error R4- Insufficient Balance/Limits R5 - Others. Select a Reject code and give a Reject Description. This reject reason will be available in the remarks window throughout the process.	
Refer	On click of Refer, user will be able to refer the task back to the Data Enrichment user. User must select a Refer Reason from the values displayed by the system. Refer Codes: R1- Documents missing R2- Signature Missing R3- Input Error R4- Insufficient Balance/Limits R5 - Others.	
Hold	The details provided will be on hold. This option is used, if there are any pending information yet to be received from applicant.	
Cancel	Cancel the Guarantee Advice Scrutiny inputs.	
Next	Task will get moved to next logical stage of Guarantee Amendment Advise. If mandatory fields have not been captured, system will display an error message until the mandatory fields data are provided.	
Save & Close	Save the information provided and holds the task in you queue for working later. This option will not submit the request	
Incoming Message	Clicking this button allows the user should be able to see the message in case of STP of incoming MT 767.	



Multi Level Approval

This stage allows the approver user to approve a Claim Lodged under Guarantee Issued Transaction.

Log in into OBTFPM application and open the task to see the summary tiles. The tiles should display a list of important fields with values. User must be able to drill down from summary Tiles into respective data segments to verify the details of all fields under the data segment.

In case of MT 765, Approval stage processing is same as in Offline Processing for Guarantee Claim.


Re-Key Authorization

The application will request approver for few critical field values as an authorization step. If the values captured match with the values available in the screen, system will allow user to open the transaction screens for further verification. If the re-key values are different from the values captured, then application will display an error message.

Open the task and re-key some of the critical field values from the request in the Re-key screen. Some of the fields below will dynamically be available for re-key.:


- Applicant Name
- Beneficiary Name
- Undertaking Currency
- Undertaking
- Amount
- Expiry Date

Re-key is applicable to the first approver in case of multiple approvers. All approvers will however be able see the summary tiles and the details in the screen by drill down from tiles.





Summary



Tiles Displayed in Summary

- Main Details User can view the application details and Guarantee/ Standby details. User can modify the details if required.
- Party Details User can view the party details like beneficiary, advising bank etc.
- Claim Details User can view the claim details.
- Documents Details- User can view the Document details.
- Additional Fields User can view the additional fields.
- Limits and Collaterals User can view the limits and collateral details. User can modify the details if required.
- Commission, tax and Charges User can view the details provided for charges. User can modify the details if required.
- Preview Messages User can drill down to view the message preview, legal verification and customer draft confirmation details. The message preview screen has the Legal Verification details.
- Settlement Details User can view the settlement details.
- Compliance User can view compliance details. The status must be verified for KYC and to be initiated for AML and Sanction Checks.
- Accounting Entries User can view the accounting entries.



Field	Description	Sample Values
Reject	On click of Reject, user must select a reject reason from a list displayed by the system. Reject Codes: R1- Documents missing R2- Signature Missing R3- Input Error R4- Insufficient Balance/Limits R5 - Others. Select a Reject code and give a reject description. This reject reason will be available in the remarks	
Hold	window throughout the process. The details provided will be registered and status	
Tiold	will be on hold. This option is used, if there are any pending information yet to be received from applicant.	
Refer	User will be able to refer the task back to the Data Enrichment user. User must select a Refer Reason from the values displayed by the system. Refer Codes: • R1- Documents missing • R2- Signature Missing • R3- Input Error • R4- Insufficient Balance- Limits • R5 - Others	
Cancel	Cancel the Guarantee Issuance approval.	
Approve	On approve, application must validate for all mandatory field values, and task must move to the next logical stage. If there are more approvers, task will move to the next approver for approval. If there are no more approvers, the transaction is handed off to the back end system for posting.	



Index

A	
Additional Details	20
Action Buttons	27
Limits & Collateral	
Additional Fields	
Action Buttons	
Advices	
Action Buttons Application Details	
В	
Benefits	1
C	
Charge Details	25
Commission	26
Commission Details	26
Common Initiation Stage	2
Action Buttons	3
D	
Data Enrichment	9
Data Enrichment - Summary	
Action Buttons	29
K	
Key Features	1
L	
Limit and Collateral	21
Collateral Details	24
Limits Details	22
M	
Main Details	12
Action Buttons	13
Application Details	
Guarantee Details	
Miscellaneous	
Multi	
Multi Level Approval	
Action ButtonsSummary	
Out 1111101 \$	🔾 1

0	
Overview	1
P	
Preview	19
Action Buttons	19
R	
Registration	9 5
Miscellaneous	8
Т	
Tax Details	27



Reference and Feedback

References

For more information on any related features, you can refer to the following documents:

- Getting Started User Guide
- Common Core User Guide

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

Feedback and Support

Oracle welcomes customers' comments and suggestions on the quality and usefulness of the document. Your feedback is important to us. If you have a query that is not covered in this user guide or if you still need assistance, please contact documentation team.

