

Cross Schema Scripts Utility
Oracle FLEXCUBE Investor Servicing

Release 14.5.2.0.0
[November] [2021]



Table of Contents

- 1. CROSS SCHEMA SCRIPTS UTILITY 1-1
 - 1.1 INTRODUCTION 1-1
 - 1.2 SETTING UP CROSS SCHEMA ENTRIES..... 1-1

1. Cross Schema Scripts Utility

1.1 Introduction


This chapter explains the steps to execute cross schema scripts using Oracle FLEXCUBE Investor Servicing Installer.

Fund Handoff and Dividend Handoff require grant to populate Fund Information and Dividend Information from AMC to Distributor Schema. To enable Internal Handoff feature, below steps to be followed to provide grants from Distributor LOB to AMC LOB Schema.

1.2 Setting up Cross Schema Entries

In order to execute cross schema scripts, follow the steps given below.

Start Oracle FLEXCUBE Investor Servicing Installer.



The screenshot shows the Oracle FLEXCUBE Investor Servicing installer window. The title bar is red with the text "Oracle FLEXCUBE Investor Servicing" and the Oracle logo. The main content area is titled "Prerequisites" and contains the instruction "Please specify the JDK and Oracle Home path." Below this, there are four fields for configuration:

Field Name	Value	Icon
JDK Path	c:/Software/Java/jdk1.8.0_91	Folder icon
Oracle Home	c:/Software/Oracle12c/product12.1.0/dbhome_1	Folder icon
Application Server Home	c:/Software/Weblogic12211/wlserver	Folder icon
Application Server Location	Local	Dropdown arrow

At the bottom of the window, there are four buttons: "Log", "Back", "Next", and "Exit".

Specify the following details:

JDK Path

Specify the location of the JDK. You can use the directory button to browse to the JDK location.

Oracle Home


Specify the location of the Oracle Home installation. You can use the directory button to browse to the location.

Application Server Home


Specify the location of the application server.

Note: In case any of the selected directories is incorrect, the Installer will display an appropriate error message. In that case, you need to correct the directory path and proceed.

Click 'Next'. The following screen is displayed.



Select 'Cross Schema Grants' and click 'Next'. The following screen is displayed.



Enter the FCHOME folder path. Click Next.

The following screen is displayed.

Oracle FLEXCUBE Universal Installer

Oracle FLEXCUBE Investor Servicing ORACLE

Cross Schema Grants Schema Details

Schema Type **SMS**

Name	Value
Username	installer
Password	••••••••
Service Name	testdb
IP Address	10.10.10.10
Port	1521
TNS Connect Descriptor	testdb.world

No of parallel process

Test Connection

Log Back Next Exit

Oracle FLEXCUBE Universal Installer

Oracle FLEXCUBE Investor Servicing ORACLE

Cross Schema Grants Schema Details

Schema Type **LOB** CTX Index Tablespace

Name	Value
Username	installer
Password	••••••••
Service Name	testdb
IP Address	10.10.10.10
Port	1521
TNS Connect Descriptor	testdb.world

No of parallel process

Test Connection

Log Back Next Exit

Specify the following schema details. This is the Schema on which scripts of other schema are to be executed.

Schema Type

Specify schema type from the drop down. If LOB or PENSION type is selected then CTX Index Tablespace must be entered

CTX Index Tablespace

Specify the name of CTX index tablespace.

User Name

Specify the user name to access the schema.

Password

Enter the schema password.

Service Name

Provide service name of Database.

TNS Connect Descriptor

Specify a valid connect string that contains the details for database connectivity.

IP Address

Specify the IP address of the system where the database schema is installed.

Port

Specify the port number.

Number of Parallel Process:

Specify number of parallel process for recompilation.

Once you have entered the details, you can test the database schema connection using 'Test Connection' button.

Note:

- If the connection is established, the installer displays a message 'Connection Successful'.
- If there is an error in establishing the connection, the system displays the message 'Invalid DB Credentials'.
- If the TNS entry is not proper, the installer displays the message 'TNS entries are not proper'.

After testing the connection successfully, click 'Next'. The following screen is displayed.

Oracle FLEXCUBE Universal Installer

Oracle FLEXCUBE Investor Servicing ORACLE

Destination Schema Details
Provide the Schema Names of the Destinations

Schema Type: REPORTS (+)

Schema Name: [] (-)

Destination Temp Directory: D:\DESTTEMPDIR (Folder icon)

S.No	Schema Type	Schema Name
------	-------------	-------------

Log Back Next Exit

Specify the following details:

Schema Type

The target Schema pointing to which scripts are to be executed in the current schema.

Schema Name

Name of the Destination schema

Destination Temp Directory

Destination directory. Any valid name can be given.


Once the details are updated, click on + button. This will insert the details in the multi entry table.

Continue to change the Schema Type to include all other target schema as applicable. Add the details and click on +.

Above process need to be done for all the below combinations.

From	Destination Schema			
	LOB	SMS	SP	
REPORTS	LOB	SMS	SP	
SMS	LOB	SP	REPORTS	PENSION
SP	LOB	SMS	REPORTS	PENSION
LOB	SMS	SP	REPORTS	
PENSION	SMS	SP		

Once done, click next .The following screen is displayed.



Click Copy to copy the cross schema scripts to the Destination folder.

Click Execute to execute the cross schema scripts in the current folder.

Once done, click next .The following screen is displayed:

The screenshot shows the Oracle FLEXCUBE Investor Servicing Database Installation screen. The title bar is red with the text "Oracle FLEXCUBE Investor Servicing" and the Oracle logo. Below the title bar, the text "Database Installation" is displayed. Underneath, it says "Current screen Displays the number of invalids in the DB." A progress bar shows 0%. A table lists object types, their invalid counts, and total counts. At the bottom, there are buttons for "Invalids List", "Recompile", "Log", "Back", "Next", and "Exit".

Object Type	Invalid Count	Total Count
FUNCTION	0	82
PROCEDURE	0	655
VIEW	0	341
TRIGGER	0	3
PACKAGE	0	1723
PACKAGE BODY	0	1728

Click 'Invalid List' button to view 'InvalidList.txt' created in the destination directory under the folder 'DBScripts'.

You can use the 'Recompile' button to do a cyclic recompilation. This will reduce the invalid objects count. The Installer allows you to use 'Recompile' button multiple times, in order to reduce the invalid objects count.



Cross Schema Scripts Utility
Version 14.5.2.0.0
[November] [2021]

Oracle Financial Services Software Limited
Oracle Park
Off Western Express Highway
Goregaon (East)
Mumbai, Maharashtra 400 063
India

Worldwide Inquiries:
Phone: +91 22 6718 3000
Fax: +91 22 6718 3001
www.oracle.com/financialservices/

Copyright © [2007], [2021], Oracle and/or its affiliates.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.