

US Fedwire User Guide

Oracle Banking Payments

Release 14.5.3.0.0

Part No. F51810-01

October 2022

US Fedwire User Guide
Oracle Financial Services Software Limited

Oracle Park

Off Western Express Highway
Goregaon (East
Mumbai, Maharashtra 400 063
India

Worldwide Inquiries:

Phone: +91 22 6718 3000

Fax: +91 22 6718 3001

www.oracle.com/financialservices/

Copyright © 2017, 2022, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are “commercial computer software” pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Contents

1.	About this Manual	1-1
1.1	Introduction.....	1-1
1.2	Audience.....	1-1
1.3	Documentation Accessibility.....	1-1
1.4	Organization	1-1
1.5	Glossary of Icons.....	1-2
2.	Fedwire Maintenances	2-1
2.1	Fedwire Network.....	2-2
2.1.1	<i>Fedwire Network Preferences Detailed</i>	<i>2-2</i>
2.1.2	<i>Fedwire Network Currency Preferences Detailed</i>	<i>2-5</i>
2.2	Fedwire Directory	2-8
2.2.1	<i>Fedwire Directory Maintenances</i>	<i>2-8</i>
2.2.2	<i>Fedwire Directory Upload</i>	<i>2-10</i>
2.3	Fedwire Connectivity	2-11
2.3.1	<i>Outgoing Fedwire Connectivity Details.....</i>	<i>2-11</i>
2.3.2	<i>Incoming Fedwire Connectivity Details.....</i>	<i>2-12</i>
2.3.3	<i>Fedwire Connector Start/Stop</i>	<i>2-14</i>
3.	Fedwire Transactions	3-1
3.1	Fedwire Outbound Transactions	3-1
3.1.1	<i>Outbound Fedwire Transaction Input</i>	<i>3-1</i>
3.1.2	<i>Outbound Fedwire View</i>	<i>3-20</i>
3.1.3	<i>Fedwire Reversal Request Detailed.....</i>	<i>3-31</i>
3.1.4	<i>Fedwire Reversal Response Detailed</i>	<i>3-36</i>
3.1.5	<i>Fedwire Service Message Detailed</i>	<i>3-40</i>
3.2	Fedwire Inbound Transactions	3-44
3.2.1	<i>Inbound Fedwire Transaction Input.....</i>	<i>3-44</i>
3.2.2	<i>Inbound Fedwire View</i>	<i>3-56</i>
3.2.3	<i>Fedwire Reversal Request Queue Summary</i>	<i>3-68</i>
3.3	Fedwire Browser.....	3-71
3.3.1	<i>Fedwire Outbound Browser Summary</i>	<i>3-71</i>
3.3.2	<i>Fedwire Inbound Message Browser Summary.....</i>	<i>3-72</i>
3.3.3	<i>Fedwire Incoming Service Message View.....</i>	<i>3-76</i>
3.3.4	<i>Fedwire Broadcasts & Statements Browser Summary.....</i>	<i>3-80</i>
3.4	Fedwire Non-Financial Service Request	3-81
3.4.1	<i>Fedwire Service Request Generation.....</i>	<i>3-82</i>
3.4.2	<i>Fedwire Service Request Generation Summary</i>	<i>3-84</i>
4.	Fedwire Drawdowns	4-1
4.1	Fedwire Drawdowns	4-1
4.1.1	<i>Fedwire Drawdown Authorization Agreement</i>	<i>4-1</i>
4.1.2	<i>Fedwire Drawdown Request Detailed</i>	<i>4-4</i>
4.1.3	<i>Fedwire Drawdown View</i>	<i>4-11</i>
4.1.4	<i>Fedwire Drawdown Request Manual Match.....</i>	<i>4-15</i>
4.1.5	<i>Fedwire Drawdown Approval Queue.....</i>	<i>4-17</i>
5.	Fedwire Processing	5-1
5.1	ACK/NAK Processing	5-1
5.1.1	<i>Positive Response Processing</i>	<i>5-1</i>

5.1.2	<i>Negative Response Processing</i>	5-2
5.2	Fedwire Inbound Reversal Request Processing	5-2
5.3	Fedwire Reversal Queue - Accept User action processing	5-3
6.	Fedwire gpi Processing	6-1
6.1	Outbound Fedwire Payments - gpi Processing	6-1
6.1.1	<i>SWIFT STP Changes</i>	6-1
6.1.2	<i>Outbound gCCT Processing</i>	6-1
6.1.3	<i>Outbound gCOV Processing</i>	6-3
6.1.4	<i>Outbound gpi Confirmations</i>	6-4
6.1.5	<i>Inbound gpi Confirmations</i>	6-5
6.2	Inbound Fedwire Payments - gpi Processing	6-5
6.2.1	<i>Inbound gCCT & gCOV Processing</i>	6-5
6.2.2	<i>Outbound gpi Confirmations</i>	6-6
6.2.3	<i>Inbound gpi Confirmations</i>	6-8
7.	Function ID Glossary	7-1

1. About this Manual

1.1 Introduction

This manual is designed to help you to quickly get familiar with the Oracle Banking Payments. It takes you through the various stages in processing Fedwire Payments.

You can further obtain information specific to a particular field by placing the cursor on the relevant field and striking <F1> on the keyboard.

1.2 Audience

This manual is intended for the following User/User Roles:

Role	Function
Payment Department Operators	Payments Transaction Input functions except Authorization
Back Office Payment Department Operators	Payments Related Maintenances/Payment Transaction Input functions except Authorization
Payment Department Officers	Payments Maintenance/ Transaction Authorization
Bank's Financial Controller/ Payment Department Manager	Host level processing related setup and Dashboard/ Query functions

1.3 Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

1.4 Organization

This manual is organized into the following chapters:

Chapter	Description
Chapter 1	<i>About this Manual</i> gives information on the intended audience. It also lists the various chapters covered in this User Manual.
Chapter 2	<i>Fedwire Maintenances</i> provides information to get familiar with various maintenance required for Fedwire Network, Directory, and Connectivity.
Chapter 3	<i>Fedwire Transactions</i> provides information on initiation and processing of outgoing and incoming Fedwire payments.
Chapter 4	<i>Fedwire Drawdowns</i> provides information on B2B transactions.
Chapter 5	<i>Fedwire Processing</i> provides information on various message processing for Fedwire payments.

Chapter	Description
Chapter 6	<i>Fedwire gpi Processing</i> provides information on processing of inbound and outbound Fedwire payments.
Chapter 7	<i>Function ID Glossary</i> has alphabetical listing of Function/Screen ID's used in the module with page references for quick navigation.

1.5 Glossary of Icons

This User Manual may refer to all or some of the following icons:

Icons	Function
	Exit
	Add row
	Delete row
	Option List

2. Fedwire Maintenances

Fedwire Funds Service is a real-time, gross settlement (RTGS) payment system of USA. It processes each RTGS payment initiated by the Fedwire Member bank on an individual basis and settles it immediately upon receipt. Settlement of funds is immediate, final and irrevocable, as in a RTGS system in any other country.

Highlights of Fedwire Payments Module

- Manual Payment Initiation
- Receipt of individual payment requests from bank channels
- Receipt of Bulk file for outward payments
- Fedwire network rules validation
- Derivation of Type Code and Sub-type Code in case of outgoing payment
- Support for input of exhaustive Payment related information for 'CTP' payments
- Sanctions check by interfacing with an external Sanctions screening system
- External Credit Approval Check
- Accounting
- Fedwire Message generation
- Multiple Network Cutoff times
- Fedwire business day spanning 2 calendar days
- Sending and receiving Service messages
- Incoming SWIFT to Fedwire Pass-through Transaction Processing
- Incoming Fedwire to SWIFT Pass-through Transaction Processing
- Support for Swift gpi

2.1 Fedwire Network

2.1.1 Fedwire Network Preferences Detailed

You can capture Network Preferences for Fedwire Network in this maintenance screen.

You can invoke the “Fedwire Network Preferences Detailed” screen by typing ‘PWDNWPRF’ in the field at the top right corner of the application toolbar and clicking the adjoining arrow button. Click New button on the Application toolbar.

The screenshot shows the 'Fedwire Network Preferences Detailed' screen. It features a title bar with 'New' and 'Enter Query' buttons. The main area contains several sections for data entry: 'Network Code *', 'Host Code *', 'Transaction Type *' (with a dropdown menu showing 'Outgoing'), 'Network Description', 'Network Type Description', 'Exchange Rate Preference', 'FX Rate Type', 'External Exchange Rate Applicable' (checkbox), 'Split Accounting Preferences', 'Early Nostro/Vostro Entry Posting' (dropdown), 'Cutoff', 'Funds Transfer CutOff Hours', 'Funds Transfer CutOff Minutes', 'Foreign Transfer CutOff Hours', 'Foreign Transfer CutOff Minutes', 'Settlement Transfer CutOff Hours', 'Settlement Transfer CutOff Minutes', 'Service Start Time', 'Process on Network Start Day' (checkbox), 'Beneficiary Name Match Required' (checkbox), 'Beneficiary Validation Currency', 'Beneficiary Validation Amount', 'Value Dating Preferences', 'Branch Holiday Check' (checkbox), and 'Debit value date basis for outbound payments' (dropdown). The bottom status bar includes fields for 'Maker', 'Checker', 'Date Time:', 'Mod No', 'Record Status', 'Authorization Status', and an 'Exit' button.

Specify the following fields:

Network Code

Specify a network code of the Fedwire network.

Network Description

System defaults the description on the Fedwire network selected.

Network Type Description

System defaults the Network Type Description on the Network code selected.

Host Code

Displays the Host code assigned to of the branch selected by the logged in user.

Transaction Type

Specify if the Fedwire Network preferences are being specified for transaction type is Outgoing or Incoming transaction type.

Exchange Rate Preference

FX Rate Type

Specify the FX Rate Type from the list of values.

External Exchange Rate Applicable

Check this box to indicate that fetching External Exchange Rate is applicable.

Split Accounting Preferences

Early Nostro/Vostro Entry Posting

You can select the values from either Yes or No.

Cutoff

Funds Transfer CutOff Hours

Specify the Cutoff hours for Funds Transfer of Type code 10.

Funds Transfer CutOff Minutes

Specify the Cutoff Minutes for Funds Transfer of Type code 10.

Foreign Transfer CutOff Hours

Specify the Cutoff hours for Foreign Transfers to foreign central banks and international organizations i.e. fund transfers of Type code 15.

Foreign Transfer CutOff Minutes

Specify the Cutoff Minutes for Foreign Transfers to foreign central banks and international organizations.

Settlement Transfer CutOff Hours

Specify the Cutoff hours for Settlement Transfers between Direct Fedwire members i.e. fund transfers of Type code 16.

Settlement Transfer CutOff Minutes

Specify the Cutoff Minutes for Settlement Transfers between Direct Fedwire members.

Service Start Time

Process on Network Start Day

You can check this box to specify the Process on Next Start Day.

Beneficiary Name Match Required

For inbound payments beneficiary name match is done based on this flag. The preference created here can be applied if the Host Code, Network code, Currency and Payment Method fields inputted during inbound payment processing is exactly matched.

Beneficiary Validation Currency

Specify the Currency.

Beneficiary Validation Amount

Specify the Amount in specified currency.

2.1.1.1 Viewing Fedwire Network Preferences Summary

You can view the summary in “Fedwire Network Preferences Summary” screen. You can invoke the Fedwire Network Preferences Summary screen by typing ‘PWSNWPRF’ in the field at the top right corner of the Application toolbar and clicking on the adjoining arrow button.

Fedwire Network Preferences Summary

Search Advanced Search Reset Clear All

Case Sensitive

Authorization Status [v] Record Status [v]

Network Code [v] Host Code [v]

Transaction Type [v]

Records per page 15 1 Of 1 Go Lock Columns 0

Authorization Status	Record Status	Network Code	Host Code	Transaction Type
----------------------	---------------	--------------	-----------	------------------

Exit

You can search for the records using one or more of the following parameters:

- Authorization Status
- Record Status
- Network Code
- Host Code
- Transaction Type

Once you have specified the search parameters, click ‘Search’ button. The system displays the records that match the search criteria. You can view the following details:

- Authorization Status
- Record Status
- Network Code
- Host Code
- Transaction Type

Double click a record or select a record and click on ‘Details’ button to view the detailed maintenance screen.

2.1.2 Fedwire Network Currency Preferences Detailed

You can capture Network Currency Preferences for Fedwire Network.

You can invoke the “Fedwire Network Currency Preferences Detailed” screen by typing ‘PWNDNCPRF’ in the field at the top right corner of the application toolbar and clicking the adjoining arrow button. Click New button on the Application toolbar.

The screenshot shows the 'Fedwire Network Currency Preferences Detailed' application window. It features a toolbar at the top with 'New' and 'Enter Query' buttons. The main form area is organized into several sections with input fields and dropdown menus. The 'Network Code' and 'Host Code' fields are marked with a red asterisk, indicating they are required. The 'Transaction Type' field is a dropdown menu currently set to 'Incoming'. The 'Transfer Currency' field is also marked with a red asterisk. The 'Limit Details' section includes 'Minimum Amount' and 'Maximum Amount' fields. The 'Pricing Details' section includes five fields for various pricing codes. The 'Accounting Codes' section includes 'Debit Liquidation' and 'Credit Liquidation' fields. The 'Small FX Limit' section includes 'Small FX Limit Currency' and 'Small FX Limit Amount' fields. The 'Return Accounting' section includes a 'Payment Return GL' field. The 'Network Account Details' section includes a 'Network Account' field. At the bottom of the window, there is a status bar with fields for 'Maker', 'Checker', 'Date Time', 'Mod No', 'Record Status', 'Authorization Status', and an 'Exit' button.

Specify the following fields:

Network Code

Select the network code of the logged in user from the available list of values for the Host.

Network Description

This field is auto-populated based on the network code selected.

Network Type Description

System defaults the Network Type Description on the Network code selected.

Host Code

Displays the Host code assigned to of the branch selected by the logged in user.

Transaction Type

Select the type of transaction for which the Fedwire Network preferences are being specified. The options are:

- Incoming
- Outgoing

Transfer Currency

Select the required currency from the list of available currencies for the Fedwire network.

Limit Details

Minimum Amount

Specify the minimum amount for a Fedwire payment.

Maximum Amount

Specify the maximum amount for a Fedwire payment.

Pricing Details

Transaction Pricing Code

Select the Pricing code from the list of available Pricing codes.

Drawdown Request Pricing Code

Select the drawdown pricing code from the list of available Pricing codes.

Drawdown Payment Pricing Code

Select the Payment pricing code from the list of available Pricing codes.

Reversal Payment Pricing Code

Select the Reversal Payment pricing code from the list of available Pricing codes.

Reversal Request Pricing Code

Select the Reversal request pricing code from the list of available Pricing codes.

Accounting Codes

Debit Liquidation

Specify the template for Debit Liquidation from the list of available accounting templates. You can select the template from the option list. The list displays all the accounting templates maintained in the system.

Credit Liquidation

Specify the template for Credit Liquidation.

Small FX Limit

Small FX Limit Currency

Select the required currency from the list of available currencies for specifying the Small FX Limit.

Small FX Limit Amount

Specify the amount for the Small FX Limit.

Return Accounting

Payment Return GL

Specify the payment return GL, which of picked up, when return of transaction happens.

Network Account Details

Network Account

Specify the Network Account specific to Fedwire.

2.1.2.1 Viewing Fedwire Network Currency Preferences Summary

You can view the summary in “Fedwire Network Currency Preferences” screen. You can invoke the Fedwire Network Currency Preferences screen by typing ‘PWSNCPRF’ in the field at the top right corner of the Application toolbar and clicking on the adjoining arrow button.

The screenshot displays the 'Fedwire Network Currency Preferences Summary' application window. At the top, there is a search bar with buttons for 'Search', 'Advanced Search', 'Reset', and 'Clear All'. Below the search bar, there are several filter fields: 'Case Sensitive' (a checkbox), 'Authorization Status' (a dropdown menu), 'Record Status' (a dropdown menu), 'Network Code' (a text input field with a magnifying glass icon), 'Transaction Type' (a dropdown menu), and 'Transfer Currency' (a text input field with a magnifying glass icon). Below these filters, there is a table with columns for 'Authorization Status', 'Record Status', 'Network Code', 'Host Code', 'Transaction Type', and 'Transfer Currency'. The table is currently empty. At the bottom right of the window, there is an 'Exit' button.

You can search for the records using one or more of the following parameters:

- Authorization Status
- Record Status
- Network Code
- Transaction Type
- Transfer Currency

Once you have specified the search parameters, click ‘Search’ button. The system displays the records that match the search criteria. You can view the following details in here:

- Authorization Status
- Record Status
- Network Code
- Host Code
- Transaction Type
- Transfer Currency

Double click a record or select a record and click on ‘Details’ button to view the detailed maintenance screen. You can also export the details of selected records to a file using ‘Export’ button.

2.2 Fedwire Directory

2.2.1 Fedwire Directory Maintenances

Fedwire Directory Maintenance can be used to maintain details of all types of Direct Fedwire participants. All the participants defined in this directory who are direct participants, can send/receive to/from messages directly to Fedwire and settle payments on their Master account.

You can manually create new records through this maintenance screen or can upload the details through 'Fedwire Directory Upload' screen. Records created manually and the records uploaded can be viewed here.

You can invoke "Fedwire Directory Maintenance" screen by typing 'PMDFWDIR' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button. Click New button on the Application toolbar.

Maker	Date Time	Mod No	Record Status
Checker	Date Time		Authorization Status

Exit

You can specify the following details:

Routing Number

Specify the routing number. It is a unique number and is mandatory. This is the 9 digit number of the Fedwire participant,

Participant Name

Specify the name of the Fedwire Participant.

Telegraphic Name

Specify the short name of the Fedwire participant. This is an optional field with length of 18 characters.

State

Select the State from the list of values displayed. It is the 2 character code of the US state, where the Fedwire participant is located.

City

Specify the name of the City.

Funds Transfer Status

Select the Funds Transfer Status from the LOV displayed. This status indicates if the Fedwire Payment can be received by the participant and settled by Fedwire Clearing. The options are:

- Yes - Eligible
- No - Ineligible

Funds Settlement-only Status

Select the Funds Settlement Status from the LOV available. This is an optional field and indicates if the settlement of payment is supported for the participant. The options are:

- Blank
- Settlement Only

Note

You can select the value in this field, only when the 'Funds Transfer Status' field has value of 'Yes- Eligible'.

Date of Last revision

Select the Last Revision date. This indicates the date, when the record was last updated in YYYYMMDD format Invoking Fedwire Directory Upload screen.

2.2.1.1 Fedwire Directory Summary

You can search for records in the Fedwire Directory Summary Screen. You can invoke 'Fedwire Directory Summary' screen by typing 'PMSFWDIR' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows the 'Fedwire Directory Summary' application window. At the top, there is a search bar with 'Search', 'Advanced Search', 'Reset', and 'Clear All' buttons. Below the search bar, there are two dropdown menus: 'Authorization Status' and 'Record Status'. A 'Routing Number' field with a magnifying glass icon is also present. The main area displays a table with columns: 'Authorization Status', 'Record Status', 'Routing Number', 'Participant Name', 'Telegraphic Name', 'Funds Transfer Status', and 'Funds Settlement-only status'. The table is currently empty. At the bottom right, there is an 'Exit' button.

You can search using one or more of the following parameters:

- Authorization Status
- Record Status
- Routing Number


Once you have specified the search parameters, click 'Search' button. The system displays the records that match the search criteria.

Double click a record or select a record and click on 'Details' button to view the detailed maintenance screen.

2.2.2 **Fedwire Directory Upload**

A facility is available for manual upload of Fedwire Directory using fixed length text file. The name of this screen is "Fedwire Directory Upload".

You can invoke "Fedwire Directory Upload" screen by typing 'PMDFWUPD' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button. Click New button on the Application toolbar.



You can specify the following fields:

File Name

Specify the File name of the Fedwire Directory text file.

File Path

Specify the DB server path where the Directory file is placed.

Upload Type

This field indicates if the file to be uploaded is a Full file containing all Fedwire participants or a Partial file containing records updated since a specific date in the past. This drop-down field contain two options – 'Full' and 'Partial'. Choose the required option:

- Full - All existing records in the Fedwire Directory table would be overwritten by the records in the uploaded file.
- Partial - Only specific existing records in the Fedwire Directory table are overwritten by the records in the uploaded file. The records to be updated are identified based on routing number.

Upload button

Click this button to initiate the process of picking up the file from the specified location, parsing it and inserting the records in the Fedwire Directory table.

2.3 Fedwire Connectivity

2.3.1 Outgoing Fedwire Connectivity Details

You can capture specific JMS queues for outbound messages of Fedwire Network.

Below is the list of message types, which falls under the outbound messages category:

- Outbound Messages
 - Fund transfer messages
 - SVC messages
 - Non SVC messages

You can invoke the 'Outgoing Fedwire Connectivity Details' screen by typing 'PWDFDOCN' in the field at the top right corner of the application toolbar and clicking the adjoining arrow button. Click New button on the Application toolbar.

Outgoing Fedwire Connectivity Details

New Enter Query

Connector Name * Host Description

Host Code *

Connector type

Outgoing Queue Details

Outgoing Queue Name

Outgoing Queue Profile

Maker Date Time: Mod No Record Status

Checker Date Time: Authorization Status Exit

You can specify the following fields:

Connector Name

Specify the Connector Name for which queue details to be mapped.

Host Code

System defaults the host code of transaction branch on click of 'New'.

Host Description

Displays the Description of the Host Code.

Connector type

Select the Connector type as given below:

- Auto
- Manual

Outgoing Queue Details

Outgoing Queue Name

Specify the JMS Queue name in which outbound messages gets dispatched.

Below messages are mapped to the Outgoing Queue:

- Outbound Funds Transfer and SVC messages FTI0811
- Account Balance Report FTIABAL
- End Point Grand Total Request FTI0041
- Detailed Summary of Transfer Messages request FTI0043
- Error code Description Request FTI0091
- Retrieval request FTI0051

Outgoing Queue Profile

Specify the JMS Queue Profile ID for Outbound Messages.

2.3.2 Incoming Fedwire Connectivity Details

You can capture specific JMS queues for inbound messages of FEDWIRE Network.

Below is the list of message types, which falls under the inbound messages category:

- Inbound Messages
 - Inbound fund transfer messages & normal SVC messages
 - Acknowledgements & service responses
 - Broadcasts
 - Statements

You can invoke the 'Incoming Fedwire Connectivity Details' screen by typing 'PWDFDICN' in the field at the top right corner of the application toolbar and clicking the adjoining arrow button. Click New button on the Application toolbar.

The screenshot shows a web application window titled "Incoming Fedwire Connectivity Details". At the top, there is a toolbar with "New" and "Enter Query" buttons. Below the toolbar, there are input fields for "Connector Name *" (with a red asterisk), "Host Code *" (with a red asterisk), and "Connector type" (a dropdown menu). To the right of these fields is a "Host Description" field. Below these fields is a section titled "Incoming Queue Details" which contains a list of input fields for various queue names and profiles: "AckNack Queue Name", "AckNack Queue Profile", "AckNack Listener Count", "Advices Queue Name", "Advices Queue Profile", "Advices Listener Count", "Broadcast Queue Name", "Broadcast Queue Profile", "Broadcast Listener Count", "Statement Queue Name", "Statement Queue Profile", and "Statement Listener Count". At the bottom of the window, there is a status bar with fields for "Maker", "Date Time:", "Mod No", "Record Status", "Checker", "Date Time:", "Authorization Status", and an "Exit" button.

You can specify the following fields:

Connector Name

Specify the Connector Name for which queue details to be mapped.

Host Code

System defaults the host code of transaction branch on click of 'New'.

Host Description

Displays the Description of the Host Code.

Connector type

Select the Connector type as given below:

- Auto
- Manual

Incoming Queue Details

AckNack Queue Name

Specify the JMS Queue name in which Ack/Nack messages FTFR12 gets received.

AckNack Queue Profile

Specify the JMS Queue Profile ID for Ack/Nack messages.

AckNack Listener Count

Specify the count of Listeners for Ack/Nack messages.

Advices Queue Name

Specify the JMS Queue name in which Funds transfer SVC messages and Response to the Non SVC messages gets received.

Below messages are mapped to the Advices Queue:

- Inbound Funds Transfer and SVC messages FTR811
- Response to Account Balance Report FTHBAL
- Response to End Point Grand Total Request FTR041
- Response to Detailed Summary of Transfer Messages request FTR043
- Response to Error code Description Request FTR091
- Response to Retrieval request FTR051

Advices Queue Profile

Specify the JMS Queue Profile ID for Advices.

Advices Listener Count

Specify the count of Listeners for Advices.

Broadcast Queue Name

Specify the JMS Queue name in which Broadcast messages gets received.

Message IDs applicable for broadcast are FT1000, FT1010, FT1090.

Broadcast Queue Profile

Specify the JMS Queue Profile ID for Broadcast Messages.

Broadcast Listener Count

Specify the count of Listeners for Broadcast Messages.

Statement Queue Name

Specify the JMS Queue name in which Statement messages gets received.

Message IDs applicable for Statement are FT1020.

Statement Queue Profile

Specify the JMS Queue Profile ID for Statement Messages.


Statement Listener Count

Specify the count of Listeners for Statement Messages.

2.3.3 Fedwire Connector Start/Stop

You can view the summary in “Fedwire Connector Start/Stop” screen. You can invoke the “Fedwire Connector Start/Stop” summary screen by typing ‘PWSFDCST’ in the field at the top right corner of the Application toolbar and clicking on the adjoining arrow button.

You can click Start/Stop button to start or stop specific JMS queues for inbound and outbound messages of Fedwire Network.



You can search for the records using one or more of the following parameters:

- Connector Name
- Host Code
- Direction

Once you have specified the search parameters, click ‘Search’ button. The system displays the records that match the search criteria. You can view the following details:

- Connector Name
- Host Code
- Direction
- Status

Double click a record or select a record and click on ‘Details’ button to view the detailed maintenance screen.

3. Fedwire Transactions

3.1 Fedwire Outbound Transactions

All outbound Fedwire transactions, reversal of the transactions can be done through these screens.

3.1.1 Outbound Fedwire Transaction Input

System supports Fedwire Outbound Payments for the below mentioned transfer type:

- Customer Transfer
- Bank Transfer

Outbound Fedwire payments can be manually booked from this screen in case the inward Fedwire message cannot be received or processed due to any reason. You can invoke 'Outbound Fedwire Transaction Input' screen by typing 'PWDOTONL' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button. Click New button on the Application toolbar.

You can specify the following fields:

Transaction Branch

The system defaults the transaction branch code with the user's logged in branch code.

Branch Name

The system defaults the Branch Name on clicking New button.

Host code

The system defaults the host code of transaction branch.

Host code Description

The system defaults the host code description-of transaction branch.

Source Code

The system derives the source code for the transaction depending on the source from where it is received. For manual transactions, source code is defaulted to MANL.

Source code Description

The system defaults the description of the source code.

Network Code

Specify the required Fedwire network code.

Network code Description

The system defaults the description of the Network code.

Transaction Reference Number

The system generates and displays a unique reference number for the transaction.

User Reference

The system defaults the User reference number same as the Transaction Reference Number. You can edit this value to provide own reference number.

Source Reference Number

The system displays the Source Reference Number provided by the channel or any other source for the transaction. You can input the value for manually booked transaction.

Transaction Type Code

Specify the required transaction type code.

Type

Select the type code of the payment from LOV. The values are:

- 10 (Customer Transfers)
- 15 (International Transfers)
- 16 (Settlement transfers between Fedwire members)

Sub Type

Select the sub type code from LOV. The values are:

- 00
- 02
- 08
- 32

Note

If you do not select any value, the system default the Sub-Type code value.

:3600:Business Function Code

Specify the desired Business Function Code from the available options. For e.g. CTR (Customer Transfer), BTR (Bank Transfer) etc.

Prefunded Payments

On checking 'Prefunded Payments', Debit Account Number gets defaulted, when the Prefunded GL is defined for that Source and Network.

Process on Network Start Day

Check this box to process this transaction on the Network start day as defined in network preferences.

3.1.1.1 Main Tab

Click 'Main' tab to capture the Outbound Fedwire details.

The screenshot shows the Oracle Remittance Information form, Main Tab. The form is divided into several sections: :5000:Originator, :5010:Originator Option F, :4400:Account Debited in DrawDown, :4100:Beneficiary FI, Payment Details, :3700:Charges, and :4200:Beneficiary. Each section contains various input fields for account numbers, identifiers, names, addresses, and payment details. The form also includes a navigation bar at the top with tabs: Main, Pricing, FI Information, Additional, Remittance Parties, and Remittance Information. At the bottom, there is a status bar with fields for Maker ID, Release Time, Checker ID, Checker Date Stamp, Authorization Status, and an Exit button.

Specify the following details:

:5000:Originator

Debit Account

Specify the debit account number of the Originating customer. Alternatively, you can select the debit account number from the option list. The list displays all open and active customer accounts.

Debit Currency & Debit Currency Name

System defaults the currency and currency name on selecting the debit account. But, if in case selected Debit Account is a GL account, then you can specify the Debit currency from the list of values.

Debit Amount

Specify the debit amount from customer account.

ID Code

Select the ID code from the drop down list corresponding to the type of originator identification and details that are desired to be input in the following fields. The options are:

- B - SWIFT Bank Identifier Code (BIC)
- C- CHIPS Participant
- D - Demand Deposit Account (DDA) Number

- F - Fed Routing Number
- T - SWIFT BIC or Bank Entity Identifier (BEI) and account number
- U - CHIPS Identifier
- 1 - Passport Number
- 2 - Tax Identification Number
- 3 - Driver's License Number
- 4 - Alien Registration Number
- 5 - Corporate Identification
- 9 - Other Identification

Identifier

Specify the identifier details as per the selected ID Code.

Name

The system displays the Originator's name based on the selected Debit account.

Address

Specify the address details of the originator.

Address 1

Specify the additional address details of the originator.

SSI Label

Select the SSI label from the list of values.

Payment Details

Booking Date

Specify the booking date of the payment.

Instruction Date

Specify the Instruction Date of the outgoing payment which can be current or future business date.

Value Date

Specify the Value date of the transaction.

Instructed Currency Indicator

Select any of the two options:

- Transfer Currency - If the Instructed currency option is 'Transfer Currency' then the Instructed amount provided will be considered as the Transfer Amount.
- Debit Currency - If the option is 'Debit Currency', then the Instructed Amount provided will be the Debit amount.

Instructed Currency

Specify the instructed currency.

Instructed Currency Name

Instructed Currency Name gets defaulted.

Instructed Amount

Specify the Instructed amount.

Transfer Currency

System displays the transfer currency of USD by default.

Transfer Currency Name

System displays the transfer currency name.

Transfer Amount

Specify the amount for the transfer.

3720:Exchange Rate

Exchange rate for converting the Transfer amount in USD to debit account currency is derived on clicking the Enrich button.

Enrich

Click this button for enrichment of the transaction that includes deriving exchange rate (if applicable), Value dates, Charges and mandatory field validation.

Note

When you click on Enrich action, below listed actions are done:

- Pricing account maintained in the Customer Preference maintenance screen (PMDFLPRF) is checked for the customer. If a valid maintenance (open & authorized) is found, then the Pricing account, Pricing account's currency and Pricing account's branch gets defaulted into Charge Account Number, Charge Account currency and Charge Account Branch respectively.
 - Charge account defaulting is done only if the Charge Account number is not provided by user at the time of clicking Enrich button.
-

:5010:Originator Option F**Party Identifier Format**

Select the Party Identifier Format. Options are Account Number / Unique Identifier.

Party Identifier

Select the Party Identifier from drop-down values.

Name &Line 1-3

Select the unique values from drop-down values.

Debit Value Date

The system displays the derived debit value date on clicking Enrich.

Credit Value Date

The system displays the credit value date on clicking Enrich.

Customer No

The system displays the customer number (of the customer maintained in the system) that is derived based on the selected debit account number of the originator.

Customer Service Model

The system displays the customer service model linked to the customer.

Remarks

Specify any remarks for the payment being booked.

Note

On Fedwire Outbound Transaction liquidation, Debit Advice is generated as per current advice framework, to the debtor, Advice tag '_REMARKS_' for Remark is available in the generated mail advice.

Receiver**Receiver ABA Number**

Select the ABA Number of Receiver DI (Depository Institution) from the list of all Fedwire members.

Receiver Short Name

Specify the Receiver DI's Short Name.

Country of Receiver DI Head Office

Select the Receiver details from list of values.

:3700:ChargesDetails of Charges

Select the details of charges from the drop down list. The options are:

- B (Beneficiary)
- S (Shared)

Senders Charges

Specify the sender's charges as <USD><Amount>. For e.g. USD10.25.

:4400:Account Debited in Drawdown**ID Code**

Select the ID code from the drop down corresponding to the type of identification of Beneficiary FI and details that are desired to be input in the following fields. The options are:

- B - SWIFT Bank Identifier Code (BIC)
- C - CHIPS Participant
- D - Demand Deposit Account (DDA) Number
- F - Fed Routing Number
- U - CHIPS Identifier

Identifier

Specify the Beneficiary FI identifier as per the selected ID Code.

Name

Specify the name of the beneficiary FI.

Address

Specify the address of the beneficiary FI.

:4100:Beneficiary FI**ID Code**

Select the ID code from the drop down corresponding to the type of identification of Beneficiary FI and details that are desired to be input in the following fields. The options are:

- B - SWIFT Bank Identifier Code (BIC)

- C - CHIPS Participant
- D - Demand Deposit Account (DDA) Number
- F - Fed Routing Number
- U - CHIPS Identifier

Identifier

Specify the Beneficiary FI identifier as per the selected ID Code.

Name

Specify the name of the beneficiary FI.

Address

Specify the address of the beneficiary FI.

:4200:Beneficiary

ID Code

Select the ID code from the drop down corresponding to the type of identification of Beneficiary and details that are desired to be input in the following fields. The options are:

- B - SWIFT Bank Identifier Code (BIC)
- C - CHIPS Participant
- D - Demand Deposit Account (DDA) Number
- F - Fed Routing Number
- T - SWIFT BIC or Bank Entity Identifier (BEI) and account number
- U- CHIPS Identifier
- 1 - Passport Number
- 2 - Tax Identification Number
- 3 - Driver's License Number
- 4 - Alien Registration Number
- 5 - Corporate Identification
- 9 - Other Identification

Identifier

Specify the identification details as per the selected ID Code.

Name

Specify the name of the beneficiary.

Address

Specify the address details of the Beneficiary.

3.1.1.2 Pricing Tab

This tab displays the pricing details of the charges computed by system based on the transaction attributes in the Main tab. These details are populated on clicking Enrich button in

the Main tab before saving the transaction, or as part of processing on saving the transaction without clicking Enrich.

The below mentioned attributes will be available in the Pricing tab:

Pricing Component

The system displays the Name of the pricing component applicable for the transaction for which charges are computed.

Pricing Currency

The system displays the Currency in which the charge amount is calculated for the Pricing component.

Amount

The system displays the charge amount calculated for each pricing component.

Waived

This field if checked indicates that the charge is waived for the pricing component.

Debit currency

The system displays the currency in which the charge amount is debited for the pricing component. This is the currency of the debit (originator) account.

Debit amount

The system displays the charge amount in debit currency to be debited. This amount is different from the calculated Pricing amount if the debit currency is different from the Pricing Currency. The Debit amount for charges is calculated by converting the Pricing amount in Pricing Currency to Debit currency using specified Exchange Rate type in Pricing Code maintenance.

Deferred

This field if checked indicates that the charges are not collected during transaction processing but their liquidation is deferred based on customer preferences. Applicable only for "S" (Shared) type of charges.

Borne By Bank

This field if checked indicates that the charges are borne by bank.

3.1.1.3 FI Information

Click 'FI Information' tab to specify the FI Information details.

The screenshot displays the 'FI Information' tab within a software application. The tab is highlighted in red. The interface is organized into several sections for entering FI details:

- :6100:Receiver FI Information**: Includes fields for 'Advice Code' (a dropdown menu) and 'Additional Information' (a text area).
- :6200:Intermediary FI Information**: Includes fields for 'Advice Code' (a dropdown menu) and 'Additional Information' (a text area).
- :6300:Beneficiary's FI Information**: Includes fields for 'Advice Code' (a dropdown menu) and 'Additional Information' (a text area).
- :6400:Beneficiary Information**: Includes fields for 'Advice Code' (a dropdown menu) and 'Additional Information' (a text area).
- :6420:Method of Payment to Beneficiary**: Includes fields for 'Method of payment' and 'Additional Information'.
- :6500:FI to FI Information**: Includes a text area for additional information.

The bottom of the screen features a light blue bar with the following fields: 'Maker ID', 'Release Time', 'Checker ID', 'Checker Date Stamp', 'Authorization Status', and an 'Exit' button.

Specify the following details:

:6100:Receiver FI Information

Specify the information for the Receiver FI in the lines provided.

:6110:Drawdown Debit Account Advice Information

Advice Code

Select the Advice Code for draw-downs from the drop down list. The options are LTR, PHN, TLX and WRE.

Additional Information

Specify additional information on the Advice.

:6200:Intermediary FI Information

Specify the information for the Intermediary FI in the lines provided.

:6210:Intermediary FI Advice Information

Advice Code

Select the appropriate value of the Intermediary FI Advice from the drop down list. The options are LTR, PHN, TLX and WRE.

Additional Information

Specify additional information on the Advice.

:6300:Beneficiary's FI Information

Specify the Beneficiary FI Information in the lines provided.

:6310:Beneficiary's FI Advice Information

Advice Code

Select the appropriate value of Advice code for the Beneficiary FI Advice from the drop down list. The options are LTR, PHN, TLX and WRE. After selecting the option, you may specify additional information in the lines provided.

Additional Information

Specify additional information on the Advice.

:6400:Beneficiary Information

Specify the information for the beneficiary in the lines provided.

:6410:Beneficiary Advice Information

Advice Code

Select the Advice Code for the Beneficiary Advice from the drop down list. The options are LTR, PHN, TLX and WRE.

Additional Information

Specify additional information on the Advice.

:6420:Method of Payment to Beneficiary

Method of payment

Specify the method of payment. 'CHECK' is the only valid option that can be input.

Additional Information

Specify additional information on the method of payment.

:6000:Originator to Beneficiary Information

Specify the Originator to Beneficiary details in the lines provided.

:6500:FI to FI Information

Specify the FI to FI Information in the lines provided.

3.1.1.4 Additional Tab

Click 'Additional' tab to capture the additional details.

Specify the following details:

Additional Details

:3320:Sender's Reference

Specify the Sender's Reference.

:3610:Local Instrument Code

Select the local Instrument Code from the drop down list. The available values are ANSI, COVS, GXML, IXML, NARR, PROP, RMTS, RRMT, S820, SWIF and UEDI.

Proprietary Code

Specify a Proprietary Code if the Local Instrument Code element selected is PROP.

:4320:Reference for Beneficiary

Specify the reference details for beneficiary.

Previous Message Identifier

This field list IMADs of all incoming transactions (CTR / BTR / CTP). You can select IMAD from LOV.

This field becomes mandatory, when the Sub Type value is 02 or 08 and when the BFC is CTR or BTP or CTP.

:4000:Intermediary FI

ID Code

Select the required ID Code from the drop down list. The available values are B, C, D, U and F.

Identifier

Specify the Identifier details of the Intermediary for the selected ID Code.

Name

Specify the name of the Intermediary.

Address 1 to 3

Specify the address of the Intermediary in the lines provided.

:5200:Instructing FI**ID Code**

Specify the required ID Code from the drop down list. The available values are B, C, D, U and F.

Identifier

Specify the Identifier details for the selected ID code.

Name

Specify the name of the Instructing FI.

Address 1 to 3

Specify the address of the Instructing FI in the lines provided.

:8250:Related Remittance Information**Remittance Identification**

Specify the Remittance Identification details.

Remittance Location Method

Specify the Remittance Location Method details.

Remittance Location Electronic Address

Specify the Remittance Location Electronic Address details.

Name

Specify the name as mentioned in the Remittance Information.

Address Type

Specify the Address Type which should be one of the following allowed values - ADDR, BIZZ, DLVY, HOME, MLTO and PBOX.

Department

Specify the associated department details.

Sub Department

Specify the associated sub department details.

Street Name

Specify the Street Name.

Building Number

Specify the Building Number.

Address

Specify the address.

:8200:Unstructured Addenda Information

Line 1-5

Specify the line details.

Addenda Length

The value gets defaulted.

3.1.1.5 Remittance Parties Tab

Click 'Remittance Parties' tab to capture the information on Remittance.

Main	Pricing	FI Information	Additional	Remittance Parties	Remittance Information
:8300:Remittance Originator					
:8350:Remittance Beneficiary					
:8300:Remittance Originator Identification Type			Name		
Identification Code			Identification Type		
Name			Identification Code		
Identification Number			Identification Number		
Identification Number Issuer			Identification Number Issuer		
Date of Birth YYYY-MM-DD			Date of Birth YYYY-MM-DD		
Place of Birth			Place of Birth		
Address Type			Address Type		
Department			Department		
Sub Department			Sub Department		
UDF MIS					
Maker Id		Checker ID		Authorization Status	
Release Time		Checker Date Stamp		Exit	

Specify the following details:

:8300:Remittance Originator

:8300:Remittance Originator Identification Type

Select the Originator Identification Type from the drop down.

Identification Code

Specify the Identification Code.

Name

Specify the name of the Remittance Originator.

Identification Number

Specify the Identification Number of the Originator.

Identification Number Issuer

Specify the Identification Number Issuer of the identification.

Date & Place Of Birth

Specify the Originator's date of birth and place of birth.

Address Type

Specify the address type, which should be one of the following allowed values - ADDR, BIZZ, DLVY, HOME, MLTO and PBOX.

Department

Specify the department.

Sub Department

Specify the sub department.

Street Name

Specify the street name.

Building Number

Specify the building number.

Post Code

Specify the Post Code.

Town Name

Specify the Town name.

Country Subdivision/ State

Specify the Country subdivision/State.

Country

Specify the Country.

Address

Specify the address details.

:8350:Remittance Beneficiary**Name**

Specify the name of the Beneficiary of the remittance.

Identification Type

Specify the Identification Type of the Beneficiary.

Identification Code

Specify the Identification Code of the Beneficiary as per the selected Identification type.

Identification Number

Specify the Identification Number of the beneficiary.

Identification Number Issuer

Specify the beneficiary's Identification Number Issuer.

Date & Place Of Birth

Specify the beneficiary's date of birth and place of birth.

Address Type

Select the address type from the drop down, which should be one of the following allowed values - ADDR, BIZZ, DLVY, HOME, MLTO and PBOX.

Department

Specify the department.

Address

Specify the address details.

Also you can specify the following details:

- Country of Residence
- Contact Name
- Contact Phone
- Contact Mobile Number
- Contact Fax Number
- Contact Electronic Address
- Contact Other Information

3.1.1.6 Remittance Information Tab

Click 'Remittance Information' tab to capture the information on Remittance.

The screenshot shows a software interface with a tabbed menu at the top: Main, Pricing, FI Information, Additional, and Remittance Information (highlighted in red). The main content area is divided into two columns and several sections:

- :8300:Remittance Originator**
 - :8300:Remittance Originator Identification Type (dropdown)
 - Identification Code
 - Name
 - Identification Number
 - Identification Number Issuer
 - Date & Place Of Birth
 - Address Type (dropdown)
 - Department
 - Address
- :8400:Primary Remittance Document Information**
 - Document Type Code (dropdown)
 - Proprietary Document Type Code
 - Document Identification Number
 - Issuer
- :8550:Amount of Negotiated Discount**
 - Discount Currency Code
 - Amount
- :8600:Adjustment Information**
 - Adjustment Reason Code (dropdown)
 - Credit Debit Indicator
 - Currency Code
 - Amount
 - Additional Information
- :8750:Remittance Free Text**
 - Text area for free text
- :8350:Remittance Beneficiary**
 - Name
 - Identification Type (dropdown)
 - Identification Code
 - Identification Number
 - Identification Number Issuer
 - Date & Place Of Birth
 - Address Type (dropdown)
 - Department
 - Address
- :8450:Actual Amount Paid**
 - Currency Code
 - Amount
- :8500:Gross Amount of Remittance Document**
 - Document Currency Code
 - Amount
- :8650:Date Of Remittance Document**
 - Date
- :8700:Secondary Remittance Document Information**
 - Document Type Code (dropdown)
 - Proprietary Document Type Code
 - Document Identification Number
 - Issuer

At the bottom, there is a status bar with fields for Maker ID, Release Time, Checker ID, Checker Date Stamp, Authorization Status, and an Exit button.

:8400:Primary Remittance Document Information

Document Type Code

Select the code to specify the document type from the drop down list.

Proprietary Document Type Code

Specify a Proprietary Document Type Code if the Document Type Code selected is PROP.

Document Identification Number

Specify the Document Identification Number.

Issuer

Specify the Issuer of the document.

:8450:Actual Amount Paid**Currency Code**

Specify the currency code of the actual amount remitted.

Amount

Specify the actual amount remitted.

:8500:Gross Amount of Remittance Document**Document Currency Code**

Specify the currency code of the gross amount remitted as mentioned in the Remittance Document.

Amount

Specify the gross amount remitted.

:8550:Amount of Negotiated Discount**Discount Currency Code**

Specify the currency code of the negotiated discount for the amount payable.

Amount

Specify the discounted amount.

:8600:Adjustment Information**Adjustment Reason Code**

Specify the adjustment reason code from the drop down.

Credit Debit Indicator

Specify if the adjustment is done for credit or debit.

Currency Code

Specify the currency code of the adjustment amount.

Amount

Specify the adjusted amount.

Additional Information

Specify any other related information.

:8700:Secondary Remittance Document Information**Document Type Code**

Select the code to specify the document type from the drop down list.

Proprietary Document Type Code

Specify a Proprietary Document Type Code if the Document Type Code selected is PROP.

Document Identification Number

Specify the Document Identification Number.

Issuer

Specify the Issuer of the Secondary Remittance Document document.

:8750 Remittance Free text

Specify any remarks on the remittance in the free text format in the lines provided.

3.1.1.7 Sequence B - Cover Details Tab

Click 'Sequence B - Cover Details' tab to capture the information on Remittance.

Outbound Fedwire View

Enter Query

Transaction Branch	Transaction Reference Number	Type
Host Code	User Reference	Sub Type Code
Source Code	Source Reference Number	:3600 Business Function Code
Network Code	Transaction Type Code	File Reference Number
gpi Agent	Incoming gpi	Payment Batch ID
UETR		Prefunded Payments

Main Pricing FI Information Additional Remittance Parties Remittance Information Exceptions Sequence B - Cover Details

Payment Details

Booking Date	:5000:Originator	:4200:Beneficiary
Original Instruction Date	Debit Account	ID Code
Instruction Date	ID Code	Identifier
Value Date	Identifier	Name
Transfer Currency	Name	Address
Transfer Currency Name	Address 1	
Transfer Amount	Address 2	
Debit Account Currency	Address 3	
Debit Currency Name	SSI Label	
Debit Amount		:4100:Beneficiary FI
Exchange Rate	Debit Value Date	ID Code
Instructed Currency Indicator	Credit Value Date	Identifier
Instructed Currency	Customer Number	Name
Instructed Currency Name	Customer Service Model	Address
Instructed Amount	Remarks	
FX Reference Number	:6000:Originator to Beneficiary Information	
Charge Account Number		:4400:Account Debited in DrawDown
Charge Account Branch		ID Code
Charge Account Currency		Identifier

Receiver

Receiver ABA Number	:5100:Originator FI
Receiver Short Name	Identifier
Country of Receiver DI Head Office	Line 1
	Line 2
	Line 3

:3700:Charges

Charges
Senders Charges

Transaction Status

Transaction Status
Debit Liquidation Status
Credit Liquidation Status
Dispatch Status
Cancellation Remarks
Reason Code

External System Status

Sanctions Check Status	Not Applicable
Sanctions Check Reference	
External Credit Approval Status	
External Credit Approval Reference	
External Exchange Rate Status	Not Applicable
External Rate Reference	
View Queue	

Pending Queue Details

Queue Code

Sanction Seizure

Sanction Seizure

View Queue Action | UDF | MIS | All Messages | Accounting Entries | View Repair Log | gpi Confirmations


Maker Id
Maker Date Stamp
Authorization Status

Checker ID
Checker Date Stamp

Exit

3.1.1.8 UDF Tab


Click on the 'UDF' button present in the bottom of the screen to invoke this screen.



You can specify user defined fields for each transaction.

3.1.1.9 MIS Tab

Click on the 'MIS' button present in the bottom of the screen, to invoke this screen.



You can specify the MIS details in this sub-screen.

3.1.1.10 Viewing Outbound Fedwire Transaction Summary

You can view the outbound fedwire transactions summary in this screen. You can invoke the “Outbound Fedwire Transaction Summary” screen by typing ‘PWSOTONL’ in the field at the top right corner of the Application toolbar and clicking on the adjoining arrow button.

Outbound Fedwire Transaction Summary

Search Advanced Search Reset Clear All

Case Sensitive

Transaction Reference Number Value Date YYYY-MM-DD

Network Code User Reference

Source Code Transaction Branch

Instruction Date YYYY-MM-DD Booking Date

Customer Number Customer Service Model

Receiver DI Authorization Status

Source Reference Number

Records per page 15 1 Of 1 Go Lock Columns 0

Transaction Reference Number	Value Date	Network Code	User Reference	Source Code	Transaction Branch	Instruction Date	Booking Date	Customer Number	Customer !
------------------------------	------------	--------------	----------------	-------------	--------------------	------------------	--------------	-----------------	------------

Exit

You can search for the records using one or more of the following parameters:

- Transaction reference no
- Value Date
- Network Code
- User Reference
- Source Code
- Transaction Branch
- Instruction Date
- Booking Date
- Customer Number
- Customer Service Model
- Receiver DI
- Authorization Status
- Source Reference Number

Once you have specified the search parameters, click ‘Search’ button. The system displays the records that match the search criteria.

Double click a record or select a record and click on ‘Details’ button to view the detailed maintenance screen.

3.1.2 Outbound Fedwire View

You can view the details of an outbound Fedwire transaction in this screen. You can invoke the 'Outbound Fedwire View' screen by typing 'PWDOVIEW' in the field at the top right corner of the Application toolbar and clicking on the adjoining arrow button.

- From this screen, click Enter Query. The Transaction Reference field gets enabled, for the user to specify the Reference Number.
- Along with the transaction details in the Main and Pricing tabs you can also view the Status details for the following:
 - Transaction Status
 - External System Status
 - Pending Queue Details
 - Sanction Seizure

View Queue

This button launches the corresponding Queue screen, where the transaction is currently held. The Queue screen will be launched in query mode, listing this transaction alone.

- Click Execute Query to populate the details of the transaction in the Outbound Fedwire View Detailed screen.

gpi Agent

This field is not editable and is disabled. This field has the drop-down values as -Yes/No.

Incoming gpi

This field is disabled. This is set to 'Y' for pass-through cases only when processing an inbound gpi message.

:6000:Originator to Beneficiary Information

In the mail-based Debit advice processing populates the values for this advice tag from the Outbound Fedwire transaction Tag {6000} - Originator to Beneficiary Information Line 1 to Line 4.

UETR

The UETR (Unique End-to-End Transaction Reference) is generated for the outbound transaction.

gpi/Universal Confirmation Status

Confirmation Status

Displays the following values:

- Ungenerated
- Generated

Confirmation Type

Displays the following values:

- Interim
- Credit
- Reject

For more details on Main, Pricing, Fi Information, Additional Details, Remittance Parties, Remittance Information, Sequence B - Cover Details tabs, refer to 'PWDOTONL' screen details above.

Note

- Outbound Fedwire transactions is also created via inbound pass-through SWIFT message upload.
 - Based on Network Rules defined, Fedwire network is derived and outbound Fedwire transaction is created and available for view in PWDOVIEW.
 - Outbound Fedwire is created as CTR, BTR, CTP based on the inbound pass-through SWIFT message type uploaded.
-

3.1.2.1 Exceptions Tab

Click on the 'Exceptions' tab to view the reversal details for the transaction. Following details can be viewed:

- Reversal Details
- Reversal request Details
- Reversal Payment details
- External System Status Reversal request

- External System Status Reversal payment

[Main](#) | [Pricing](#) | [FI Information](#) | [Additional](#) | [Remittance Parties](#) | [Remittance Information](#) | **Exceptions**

Reversal Details

Reversal request status

Reversal Request Details	Reversal Payment details
Reversal Reference	Reversal Payment Reference
Reversal Request Date YYYYMM-DD	Reversal Payment date YYYYMM-DD
Sub Type Code	BFC
Reversal Request Reason 1	Type Code
Reversal Request Reason 2	Sub Type Code
Reversal Request Reason 3	Returned Amount

[View Queue Action](#) | [UDF](#) | [MIS](#) | [All Messages](#) | [Accounting Entries](#) | [View Repair Log](#)

Maker Id	Checker ID
Maker Date Stamp	Checker Date Stamp
Authorization Status	Cancel

3.1.2.2 View Queue Action Log

You can view all the queue actions for the respective transaction initiated. You can invoke this screen by clicking the 'View Queue Action' button in View screen, where the Transaction Reference Number is auto populated and related details are displayed.

View Queue Action Log

Enter Query

Transaction Reference Number Network Code

Transaction Reference Number	Action	Remarks	Queue Code	Authorization Status	Maker Id	Maker Date Stamp
View Request Message View Response Message						

Following details are displayed:

- Transaction Reference Number
- Network Code
- Action
- Remarks
- Queue Code
- Authorization Status
- Maker ID
- Maker Date Stamp

- Checker ID
- Checker Date Stamp
- Queue Status
- Queue Reference No
- Primary External Status
- Secondary External Status
- External Reference Number

You can view the request sent and the corresponding response received for each row in Queue Action Log.

Also you can view the request sent to and the response received from external systems for the following:

- Sanction screening
- External credit approval
- External Account Check
- External FX fetch
- External price fetch
- Accounting system

3.1.2.3 UDF Tab

You can invoke this screen by clicking 'UDF' tab in the screen.

Field Label	Field Value
-------------	-------------

3.1.2.4 MIS Tab

You can invoke this screen by clicking 'MIS' tab in the screen.

MIS Details

Transaction Reference Number * MIS Group Default

Transaction MIS Composite MIS

Ok Exit

3.1.2.5 All Messages

Click the "All Messages" link in the View screen to invoke this sub-screen.

View Fedwire Message Detailed

Transaction Reference Number

1 Of 1 Go

Transaction Reference No	Message Reference Number	Network Code	IMAD	Direction	Receiver Id	Business Function Code	URC
--------------------------	--------------------------	--------------	------	-----------	-------------	------------------------	-----

Message Acknowledgement

Exit

The system displays the following details in a grid form containing one or multiple rows:

Transaction Reference No

Displays the transaction reference number.

Message Reference Number

Displays Message Reference Number.

Network Code

Displays Network Code.

IMAD

Displays IMAD.

Direction

Displays the Direction.

Receiver Id

Displays the Receiver Id.

Business Function Code

Displays Business Function Code.

URC

Displays URC.

Acknowledge

Acknowledgement button shows the ACK or NACK message received for selected FW out message sent.

3.1.2.6 Message Details

You can select a particular message in the All Messages summary sub-screen (explained above) and view the message details in this screen.

Displays the following details for the selected message:

Reference Number

Specify the transaction reference number.

DCN

The system displays DCN of the message.

ESN/Version Number

The system displays the version number of the message.

Receiver/Sender

The system displays receiver/sender of the message.

Message Type

The system displays system defined message type.

SWIFT Message Type

The system displays SWIFT message type.

Message

The system displays details of the actual message including BIC and Name and Address details of the Sender and Receiver as well as the fields and values populated in the message body.

Remarks

Specify a comments or remarks for the message.

Reject Reason

The system displays the reject reason code.

Message Trailers

The system displays the message trailers.

3.1.2.7 Accounting Entries

During payment transaction processing, the accounting entries whose for which hand -off status is pending are posted to a JMS Queue. Once these entries are posted in the queue, the status is updated as handed off.

If the Accounting system and the ECA system are not the same, an update is sent to the ECA system as well while doing the accounting handoff. Any amount block in the customer account done during External credit approval can be released on receiving accounting update.

Click the “Accounting Entries” tab in the view screen to invoke the screen.

The screenshot shows the 'Accounting Entries' screen. The top navigation bar has tabs for 'Main', 'Pricing', 'FI Information', 'Additional', 'Remittance Information', and 'Accounting Entries' (which is highlighted in red). Below the tabs is a toolbar with navigation icons and a 'Go' button. The main area is a table with columns: 'Netting', 'Offset Account', 'Offset Ac Branch', 'Offset Txn Code', 'Offset Amount Tag', and 'Offset Currency'. Below the table is a footer section with links: 'View Queue Action', 'UDF', 'MIS', and 'All Messages'. At the bottom, there are fields for 'Maker ID', 'Release Time', 'Authorization Status', 'Checker ID', and 'Checker Date Stamp', along with an 'Exit' button.

The system displays the following details in a grid form that contains accounting entries in multiple rows:

Reference Number

Displays the Transaction reference number.

Event Code

Displays the Accounting event code.

Account

The system displays the transaction account number that is debited or credited in the accounting entry.

Account Branch

The system displays the account branch.

TRN Code

The system populates the transaction code of the accounting entry from the Account Template maintenance.

Dr/Cr.

The system displays whether the accounting entry is 'debit' or 'credit' leg.

Amount Tag

The system displays the amount tag of the Amount being debited/credited.

Account Currency

The system displays the transaction account currency.

Transaction Amount

The system displays the transaction amount being debited/credited.

Netting

The system displays if Netting of accounting entries is required.

Offset Account

The system displays the Offset Account of the accounting entry for posting the offset debit/credit.

Offset Account Branch

The system displays the Offset Account Branch.

Offset TRN Code

The system displays the Offset Transaction Code from the Account Template maintenance.

Offset Amount Tag

The system displays the Offset Amount Tag of the Offset amount.

Offset Currency

The system displays the Offset Amount Currency.

Offset Amount

The system displays the Offset Amount being debited or credited.

Offset Netting

The system displays if the Offset Netting is required.

3.1.2.8 View Repair Log

You can view all the Repair actions for the respective transaction initiated. You can invoke this screen by clicking the 'View Repair Log' button in View screen, where the Transaction Reference Number is auto populated and related details are displayed:

Queue Reference No	Field Name	Old Value	Repaired Data	Error
--------------------	------------	-----------	---------------	-------

Following details are displayed:

- Queue Reference No
- Field Name
- Old Value
- Repaired Data
- Error

3.1.2.9 gpi Confirmations

You can view all the confirmation messages received from gpi Tracker and sent to gpi Tracker. You can invoke this screen by clicking the 'gpi Confirmations' button in View screen, where the Transaction Reference Number is auto populated and related details are displayed.

This screen has 'Tracker Confirmations', 'Our Confirmations' Tabs displaying gCCT/ gCOV confirmations received from and sent to the tracker.

gpi Confirmations

Transaction Reference Number

Tracker Confirmations Our Confirmations

gCCT Confirmations

Reference Number	Message Date and Time	Status Code	Reason Code	Status Originator BIC	Forwarded To BIC	Currency	Amount
------------------	-----------------------	-------------	-------------	-----------------------	------------------	----------	--------

Message

gCOV Confirmations

Reference Number	Message Date and Time	Status Code	Reason Code	Status Originator BIC	Forwarded To BIC	Currency	Amount
------------------	-----------------------	-------------	-------------	-----------------------	------------------	----------	--------

Message

Exit

gpi Confirmations

Transaction Reference Number

Tracker Confirmations Our Confirmations

gCCT Confirmations

Reference Number	Message Date and Time	Generation Mode	Tracker Interaction	Status Code	Reason Code	Status
------------------	-----------------------	-----------------	---------------------	-------------	-------------	--------

Message

API Response Status

gCOV Confirmations

Reference Number	Message Date and Time	Generation Mode	Tracker Interaction	Status Code	Reason Code	Status
------------------	-----------------------	-----------------	---------------------	-------------	-------------	--------

Message

API Response Status

Exit

Following are the details listed under 'Tracker Confirmations' and 'Our Confirmations' tab in the screen:

- **gCCT Confirmations:**

- Reference Number
- Message Date and Time (Only for Tracker Confirmations)
- Status Code
- Reason Code
- Status Originator BIC
- Forwarded To BIC
- Currency
- Amount
- Exchange Rate

- **gCOV Confirmations:**

- Reference Number
- Message Date and Time
- Status Code
- Reason Code
- Status Originator BIC
- Forwarded To BIC
- Currency
- Amount

Message Button

Click on 'Message' button, to view gCCT/gCOV confirmation message that received or generated and sent out.

API Response Status Button

Click on 'API Response Status' button, to view API Response Status screen for gCCT/gCOV confirmation message that was generated and sent out.

View API Response Status

Execute Query

DCN

Response Status

Response Code

Error

Cancel

The system displays the following details:

DCN

The system displays Document Number value of the API message.

Response Status

This field displays value as 'Success' or 'Failure'.

Response Code

This field displays HTTP Response code.

Error

This field displays HTTP Error message.

3.1.2.10 Outbound Fedwire View Summary

You can invoke the “Outbound Fedwire View Summary” screen by typing 'PWSOVIEW' in the field at the top right corner of the application toolbar and clicking on the adjoining arrow button.

Outbound Fedwire View Summary

Search Advanced Search Reset Clear All

Case Sensitive

Transaction Reference No
Transaction Status
Debit Liquidation Status
Transfer Currency
Source Reference Number
File Reference Number

Network Code
Authorization Status
Credit Liquidation Status
Instruction Date
3600 Business Function Code
gpi Enabled

Debit Account
Booking Date
Queue Code
Customer Number
Type
UETR

Records per page 15 1 Of 1

Transaction Reference No	User Reference	Network Code	Receiver ABA Number	Identifier	Debit Account	Transaction Status	Transfer Amount	Authorization Status	Exchange Rate	Booking Date	Debit Liquidation Status	Credit Liq
--------------------------	----------------	--------------	---------------------	------------	---------------	--------------------	-----------------	----------------------	---------------	--------------	--------------------------	------------

Reverse Generate Confirmation

Exit

You can search for the records using one or more of the following parameters:

- Transaction reference no
- Network Code
- Debit Account
- Transaction Status
- Authorization Status
- Booking Date
- Debit Liquidation Status
- Credit Liquidation Status
- Queue Code
- Transfer Currency
- Instruction Date

- Customer Number
- Transfer Type
- Source Reference Number
- gpi Enabled
- Type
- File Reference Number
- UETR

Once you have specified the search parameters, click 'Search' button. The system displays the records that match the search criteria.

Below actions are allowed in this Summary screen:

Action	Description
Reverse	When you click on the Reverse action button, Fedwire Transaction Reversal Request (PWDTRNRV) screen is opened.
Generate Confirmation	You can use this action for manually generating the Swift gpi/Universal Confirmation. This action is only allowed when below conditions are satisfied: • You have required role or user level queue action access right for the user action 'Generate Confirmation' • BFC of the Inbound message is 'CTR' (or) 'CTP' [CTP without Tag{3610} LOCAL INSTRUMENT value as 'COVS'] • UETR value is present Refer to Cross_Border User Guide section(4.1.8) for more details.

3.1.3 Fedwire Reversal Request Detailed

A new Transaction Input screen is created for initiating Request for Reversal of a Fedwire payment sent in the current or previous Fedwire business day.

You can view the details of a Fedwire Reversal Request Detailed in the "Fedwire Reversal Request Detailed" Screen. You can invoke the "Fedwire Reversal Request Detailed" screen by typing 'PWDOTREV' in the field at the top right corner of the Application toolbar and clicking on the adjoining arrow button.

The following tabs are available in this screen:

3.1.3.1 **Main Tab**

You can specify the Main details of the Fedwire Reversal Request like Reversal Details, Original Outgoing Transaction Details, Originator and Beneficiary details.

Specify the following fields:

Reversal Reference Number

This is populated when you click on New.

Reversal Request Date

Specify the Reversal Request Date.

BFC

This is defaulted and fixed to “CTP” Customer Transfer Plus, for the reversal request.

Original Outgoing Payment Preference

Select the Original Outgoing Payment Preference from the LOV.

Outgoing payment Date

After selecting the Original Outgoing Payment Preference, the Outgoing payment Date is populated by the system. The system indicates Input Cycle Date i.e. Fedwire business date of the selected outgoing payment.

Transaction Branch

This is populated when you click on New.

Source Code

This is populated when you click on New.

Host Code

This is populated when you click on New.

Network Code

This is populated when you click on New.

Reversal Details**Type Code**

This is populated after selecting the Original Outgoing Payment Preference. This is derived and populated to be same as that of the selected outgoing payment transaction being requested to be reversed.

Sub Type Code

This is populated after selecting the Original Outgoing Payment Preference. This would be derived and populated to be one of the following:

- “01” – If the selected payment transaction was sent in current Fedwire business day (Cycle date = current business day),
- “07” – If the payment transaction was sent in previous Fedwire business day

Reversal Request Reason 1 - 6

Specify the reason for Reversal Request in the lines specified. This is a mandatory text field containing multiple lines for user to input (free format) the reason for Reversal request and any relevant info.

Original Outgoing Transaction Details**Transfer Amount**

This is populated after selecting the Original Outgoing Payment Preference.

Transfer Currency

This is populated after selecting the Original Outgoing Payment Preference.

Receiver DI

This is populated after selecting the Original Outgoing Payment Preference. This is also the Receiver of the generated Reversal request.

IMAD

This is populated after selecting the Original Outgoing Payment Preference.

BFC

This is populated after selecting the Original Outgoing Payment Preference.

Type Code

This is populated after selecting the Original Outgoing Payment Preference.

:5000:Originator**Debit Account**

This is populated after selecting the Original Outgoing Payment Preference.

Debit Currency

This is populated after selecting the Original Outgoing Payment Preference.

Id Code

This is populated after selecting the Original Outgoing Payment Preference.

Beneficiary ID

This is populated after selecting the Original Outgoing Payment Preference.

Name

This is populated after selecting the Original Outgoing Payment Preference.

:5010:Originator Option F**Party Identifier**

If Originator in Option F {5010} is present, then this field is auto-populated.

Name

If Originator in Option F {5010} is present, then this field is auto-populated.

:4200:Beneficiary**ID Code**

Specify the ID code.

Beneficiary ID

Specify the Beneficiary Id.

Name

Specify the name.

3.1.3.2 Pricing Tab

Pricing related information of the Fedwire Reversal Request are available in this tab. This tab displays the pricing details of the charges computed by system based on the transaction attributes in the Main tab. These details are populated on clicking Enrich button in the Main tab before saving the transaction, or as part of processing on saving the transaction without clicking Enrich.

1 Of 1

Pricing Code	Component Name	Pricing Currency	Amount	Waived	Debtor Account Currency
--------------	----------------	------------------	--------	--------	-------------------------

Maker Id
Maker Date Stamp

Checker ID
Checker Date Stamp

Authorization Status

Cancel

The below mentioned attributes will be available in the Pricing tab:

Pricing Component

The system displays the Name of the pricing component applicable for the transaction for which charges are computed.

Pricing Currency

The system displays the Currency in which the charge amount is calculated for the Pricing component.

Amount

The system displays the charge amount calculated for each pricing component.

Waived

This field if checked indicates that the charge is waived for the pricing component.

Debtor Account Currency

The system displays the currency in which the charge amount is debited for the pricing component. This is the currency of the debit (originator) account.

Debit Amount

The system displays the charge amount in debit currency to be debited. This amount is different from the calculated Pricing amount if the debit currency is different from the Pricing Currency. The Debit amount for charges is calculated by converting the Pricing amount in Pricing Currency to Debit currency using specified Exchange Rate type in Pricing Code maintenance.

Accounting Code

The system indicates the Accounting Code.

Lcy Amount

The system indicates the Lcy Amount.

Exchange Rate

The system indicates the Exchange Rate.

3.1.3.3 Fedwire Reversal Request Summary

You can invoke the “Fedwire Reversal Request Summary” screen by typing ‘PWSOTREV’ in the field at the top right corner of the Application toolbar and clicking on the adjoining arrow button.

Fedwire Reversal Request Summary

Search Advanced Search Reset Clear All

Case Sensitive

Reversal Reference Number Reversal Request Date YYYY-MM-DD

Records per page 15 1 Of 1 Go Lock Columns 0

Reversal Reference Number	Reversal Request Date	BFC	Original Outgoing Payment Preference	Outgoing payment Date	Transaction Branch

Exit

You can search for the records using one or more of the following parameters:

- Reversal Reference Number
- Reversal Request Date

Once you have specified the search parameters, click 'Search' button. The system displays the records that match the search criteria.

Double click a record or select a record and click on 'Details' button to view the detailed maintenance screen.

3.1.4 Fedwire Reversal Response Detailed

All the Reversal requests that are successful, are made available in the Reversal response screen for Ops decision. Responses for the reversal requests initiated is given through this screen.

You can invoke 'Fedwire Reversal Response Detailed' screen by typing 'PWDREVRS' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button. Click New button on the Application toolbar.

The screenshot shows the 'Fedwire Reversal Response Detailed' application window. It features a search bar at the top with the text 'Enter Query'. Below this, there are several sections for data entry and display. The 'Reversal Response Details' section includes fields for 'Reversal Reference *', 'Reversal Request Date', 'Original Incoming Reference *', and 'Network Code'. The 'Incoming Reversal Request Details' section includes fields for 'Response Reference', 'Response Date', 'Transaction Branch', and 'Host Code'. The 'Original Incoming Transaction Details' section includes fields for 'Current Transaction Status', 'Transfer Amt', 'Receiver DI', 'IMAD', 'Business Function Code', and 'Type Code'. The 'Originator' section includes fields for 'Debit Account', 'Debit Currency', 'ID Code', 'Identifier', and 'Name'. The 'Beneficiary' section includes fields for 'ID Code', 'Identifier', and 'Name'. The 'FI to FI Information' section includes fields for 'Transfer Share', 'Sender DI', 'IMAD', ':1510.Type', 'Sub Type', and ':3320:Sender's Reference'. There are also buttons for 'Main', 'Pricing', 'Enrich', and 'Ok/Exit'.

You can specify the following details:

Reversal Reference

Select a reversal reference from the LOV. On selection of a record, this field would be populated with value of IMAD of the Reversal request message.

Note

This LOV would be filtered on all the matched and validated Reversal requests received and for which Reversal response transaction has not been created.

Reversal Request Date

Select the Reversal request date. This is the Cycle Date from OMAD of Reversal request message.

Original Incoming Reference Number

Incoming Reference number is auto populated with the IMAD of the matched incoming payment.

Network Code

System defaults the Network Code of the reversal reference specified.

Response Reference

System auto -generates the reference number for reversal response. This would not be sent in the outgoing payment message (if sent) but only used in system for internal tracking.

Response Date

System automatically generates the Response date. This is the date of authorization of response transaction.

Transaction Branch

System defaults the Branch code for the Reversal reference specified.

Host Code

System defaults the user's logged in branch.

Reversal Response Details**Reversal Response**

You can select the reversal responses from the drop-down values. Options are - Accept/ Reject. You can either accept/ reject the request.

Reject Reason

This field is mandatory and enabled only if the Reversal Response is 'Reject'.

Additional Comments

Specify the remarks, if any. Free text field to input Comments/Remarks about Accept or Reject response.

Enrich

Click on Enrich button on specifying all the mandatory details. System processes all the validations and charges on clicking Enrich.

Incoming Reversal Request Details

Following details are auto populated on specifying a valid Reversal Request Reference. All the details pertaining to that reference are displayed:

- Transfer Share
- Sender DI
- IMAD
- :1510:Type
- Sub Type
- :3320:Sender's Reference

Original Incoming Transaction Details

The following key details of the matched original incoming payment are auto-populated for information only, on selection of the Reversal Request Reference:

- Current Transaction Status
- Transfer Amount
- Receiver DI
- IMAD
- Business Function Code
- Type Code

:6100:Receiver FI Information

System auto populates the FI information details, on selecting the Reversal Request Reference, if these details are specified in the original transaction.

Originator

System auto populates the Originator details, on selecting the Reversal Request Reference, if tags{5000} or{5010} are specified in the original transaction. Following details are populated:

- Debit Account
- Debit Currency
- ID Code
- Identifier
- Name

Beneficiary

System auto populates the Beneficiary details, on selecting the Reversal Request Reference, if tags{4200} are specified in the original transaction. Following details are populated:

- ID Code
- Identifier
- Name

FI to FI Information

System auto populates the FI to FI information details, on selecting the Reversal Request Reference, if these details are specified in the original transaction.

3.1.4.1 Pricing Tab

Pricing related information of the Fedwire Reversal response are available in this tab. This tab displays the pricing details of the charges computed by system based on the transaction attributes in the Main tab. These details are populated on clicking Enrich button in the Main tab before saving the transaction, or as part of processing on saving the transaction without clicking Enrich.

Component Name	Pricing Currency	Amount	Waived	Debtor Account Currency	Lcy Amount	Deferred	Borne By Bank
----------------	------------------	--------	--------	-------------------------	------------	----------	---------------

The below mentioned attributes will be available in the Pricing tab:

Component Name

The system displays the Name of the pricing component applicable for the transaction for which charges are computed.

Pricing Currency

The system displays the Currency in which the charge amount is calculated for the Pricing component.

Amount

The system displays the charge amount calculated for each pricing component.

Waived

This field if checked indicates that the charge is waived for the pricing component.

Debtor Account Currency

The system displays the currency in which the charge amount is debited for the pricing component. This is the currency of the debit (originator) account.

LCY Amount

System displays the charge amount in local currency.

Deferred

If any fees/charges are deferred, then it is marked here.

Borne By Bank

If the charges is borne by bank or to be paid by customer is displayed here.

3.1.4.2 Fedwire Reversal Response Summary

You can search for reversal response records in this screen. You can invoke 'Fedwire Reversal Response Summary' screen by typing 'PWSREVRS' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Fedwire Reversal Response Summary

Search Advanced Search Reset Clear All

Case Sensitive

Reversal Reference Original Incoming Reference Number

Reversal Request Date Response Reference

Authorization Status

Records per page: 15 Go Lock Columns: 0

Reversal Reference	Original Incoming Reference Number	Reversal Request Date	Response Reference	Response Date	Host Code	Network Code	Transaction Branch	Reversa
--------------------	------------------------------------	-----------------------	--------------------	---------------	-----------	--------------	--------------------	---------

Exit

You can search using one or more of the following parameters:

- Reversal Reference
- Original Incoming Reference Number
- Reversal Request Date
- Response Reference
- Authorization Status

Once you have specified the search parameters, click 'Search' button. The system displays the records that match the search criteria.

Double click a record or select a record and clicking on 'Details' button to view the detailed maintenance screen.

3.1.5 Fedwire Service Message Detailed

You can initiate Fedwire Service Message. A Service Message sent using the Fedwire network is a non-value message used to communicate questions and information related to messages sent/received previously of certain Type and Sub-type codes.

This input screen allows you to initiate Service messages with reference to any Fedwire value and non-value message sent or received earlier.

You can view the details of a Fedwire Service Message Detailed in the "Fedwire Service Message Detailed" Screen. You can invoke the "Fedwire Service Message Detailed" screen

by typing 'PWDSVCME' in the field at the top right corner of the Application toolbar and clicking on the adjoining arrow button.

Specify the following fields:

Transaction Branch

This is auto-populated once you click on New button.

Reference Number

This is auto-populated once you click on New button.

Network Code

This is auto-populated once you click on New button. The value would be FEDWIRE.

Related Reference Number

You can input or search and select Reference number of an outgoing/incoming transaction of the selected Type code and Sub-type code combination. e.g. Reversal request of type code 10 sent earlier.

IMAD

In case of Incoming message, you can input or search and select IMAD of an incoming transaction of the selected Type code and Sub-type code combination. e.g. Reversal request of type code 16 received from another bank.

Host Code

This is auto-populated once you click on New button.

BFC

This is defaulted and fixed to "SVC" i.e. Service message.

Type Code

Select any of the Type Codes from the LOV.

Sub-Type Code

Select any of the Type Codes from the LOV.

Note

Sub-type code of '33' would not be allowed if Type code selected is '15'.

Receiver DI

ABA number of the Receiver of this Service message, which can be input or searched and selected from LOV.

Receiver DI Name

This is populated when you select the required Receiver DI.

Service Message Information**Line 1-12**

Specify the service message information in the lines.

Transaction Status**Transaction Status**

This displays the Transaction Status.

External System Status**Sanctions Check Status**

This displays the Sanctions Check Status.

Sanctions Check Reference

This displays the Sanctions Check Reference.

Pending Queue Details**Queue Code**

This displays the Queue Code.

Sanction Seizure**Sanction Seizure**

This displays the Sanction Seizure.

3.1.5.1 Fedwire Service Message Summary

You can invoke the “Fedwire Service Message Summary” screen by typing ‘PWSSVCME’ in the field at the top right corner of the Application toolbar and clicking on the adjoining arrow button.

Redwire Service Message Summary

Search Advanced Search Reset Clear All

Case Sensitive

Reference No			Related Reference Number		
Network Code			Transaction Branch		
Type Code			Sub-Type Code		
IMAD			Receiver DI		
Authorization Status					

Records per page ◀ 1 Of 1 ▶ Go Lock Columns

	Reference No	Related Reference Number	Network Code	Transaction Branch	Host Code	Type Code	Sub-Type Code	IMAD	Receiver
									
									
									
									
									
									
									
									

Exit

You can search for the records using one or more of the following parameters:

- Reference Number
- Network Code
- Type Code
- IMAD
- Authorization Status
- Related Reference Number
- Transaction Branch
- Sub-Type Code
- Receiver DI

Once you have specified the search parameters, click 'Search' button. The system displays the records that match the search criteria.

Double click a record or select a record and clicking on 'Details' button to view the detailed maintenance screen.

3.2 Fedwire Inbound Transactions

All inbound Fedwire transactions, reversal of the transactions can be done through these screens.

3.2.1 Inbound Fedwire Transaction Input

System supports Fedwire Incoming Payments for the below mentioned transfer type:

- Customer Transfer
- Bank Transfer

Inbound Fedwire payments can be manually booked from this screen in case the inward Fedwire message cannot be received or processed due to any reason. You can invoke “Inbound Fedwire Transaction Input” screen by typing ‘PWDITONL’ in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button. Click New button on the Application toolbar.

Inbound Fedwire Transaction Input

New Enter Query

Transaction Branch *
Branch Name
Host Code *
Host Code Description
Source Code * MANL
Source Code Description
Network Code *
Network Code Description

Transaction Reference Number *
Source Reference Number
OMAD
IMAD
:3600 Business Function Code
Message Duplication Code

Transaction Type Code
Type
Sub Type
Credit to GL

Main Pricing FI Information Additional Remittance Parties Remittance Information

:4200:Beneficiary
ID Code *
Beneficiary Identifier *
Beneficiary Currency
Credit Amount
Name
Address
Address 2
Address 3

:4100:Beneficiary FI
ID Code *
Identifier
Name
Address

Sender
Sender ABA Number
Sender Short Name

:3700:Charges
Details of Charges
Senders Charges

:4400:Account Debited in DrawDown
ID Code *
Identifier
Name
Address

Payment Details
Booking Date
Instruction Date *
Original Instruction Date
Activation Date
Transfer Currency * USD
Transfer Currency Name
Transfer Amount *

Debit Value Date
Credit Value Date
Customer Number
Customer Service Model
Remarks

:5000:Originator
ID Code *
Identifier
Name
Address

:5010:Originator Option F
Party Identifier Format
Party Identifier
Name
Line 2
Line 3

UDF MIS

Maker Id
Release Time

Checker ID
Checker Date Stamp

Authorization Status

Exit

You can specify the following fields:

Transaction Branch

The system defaults the transaction branch code with the user's logged in branch code.

Branch Name

The system defaults the Branch Name on clicking New button.

Host code

The system defaults the host code of transaction branch.

Host code Description

The system defaults the host code description-of transaction branch.

Source Code

The system derives the source code for the transaction depending on the source from where it is received. For manual transactions, source code is defaulted to MANL.

Source code Description

The system defaults the description of the source code.

Network Code

Specify the required Fedwire network code.

Network code Description

The system defaults the description of the Network code.

Transaction Reference Number

The system generates and displays a unique reference number for the transaction.

Source Reference Number

The system displays the Source Reference Number provided by the channel or any other source for the transaction. You can input the value for manually booked transaction.

OMAD

This field is data string in the OMAD tag in the received message, which primarily consists of Output Cycle Date (CCYYMMDD), unique Output Sequence Number (6 char) and Output Date (calendar date in MMDD format) fields.

OMAD is generated and appended by Fedwire in the cleared message sent to Receiving bank.

IMAD

This is the value of IMAD {1520} tag in the received message generated by the Sending bank, which primarily consists of Input Cycle Date (CCYYMMDD) and unique Input Sequence Number (6 char).

:3600:Business Function Code

Specify the desired Business Function Code from the available options. For e.g. CTR (Customer Transfer), BTR (Bank Transfer) etc.

Message Duplication Code

This field indicates if the message received is an original message sent by the Sending bank or a possible duplicate message as identified by Fedwire. This is a drop-down field allowing user to select one of the options given below:

- Original
- Duplicate

Transaction Type Code

Specify the required transaction type code.

Type

Specify the type code of the payment. The options are:

- 10 (Customer Transfers)
- 15 (International Transfers)
- 16 (Settlement transfers between Fedwire members)

Sub Type

The system defaults the Sub-type code to “00” and is non-editable.

Note

This is because only the sub-type code of “00” is currently supported for any of the type codes.

Credit to GL

This is a flag to indicate that the incoming Fedwire payment needs to be credited to a GL instead of a beneficiary customer account.

Note

This is applicable, where the actual incoming Fedwire message and the associated credit accounting would be processed by another bank system. Only Nostro accounting would be expected from Payments system that would involve crediting the amount of the incoming payment to a specified internal GL.

- System will verify whether 'Inbound Credit to GL' is checked in the Source maintenance. If it is not set for the source, error will be thrown on screen on save of transaction.
 - If 'Credit to GL' flag is checked for the source then the 'Intermediary Credit GL' maintained for the source in Source maintenance would be identified as the Beneficiary account.
-

3.2.1.1 Main Tab

Click 'Main' tab to capture the Inbound Fedwire details.

The screenshot shows the 'Main' tab of the Oracle Inbound Fedwire details form. The form is divided into several sections: Beneficiary, Payment Details, Sender, Originator, and Charges. The Beneficiary section includes fields for ID Code, Beneficiary Identifier, Beneficiary Currency, Credit Amount, Name, Address, Address 2, and Address 3. The Payment Details section includes fields for Booking Date, Instruction Date, Original Instruction Date, Activation Date, Transfer Currency, Transfer Currency Name, Transfer Amount, Debit Value Date, Credit Value Date, Customer Number, Customer Service Model, and Remarks. The Sender section includes fields for Sender ABA Number and Sender Short Name. The Originator section includes fields for ID Code, Identifier, Name, and Address. The Charges section includes fields for Details of Charges and Senders Charges. The form also includes a bottom section for UDF, MIS, Maker ID, Release Time, Checker ID, Checker Date Stamp, Authorization Status, and an Exit button.

Specify the following details:

:4200:Beneficiary ID Code

Select the ID code from the drop down list corresponding to the type of originator identification and details that are desired to be input in the following fields. The options are:

- B - SWIFT Bank Identifier Code (BIC)
- C- CHIPS Participant
- D - Demand Deposit Account (DDA) Number
- F - Fed Routing Number
- T - SWIFT BIC or Bank Entity Identifier (BEI) and account number
- U - CHIPS Identifier
- 1 - Passport Number
- 2 - Tax Identification Number
- 3 - Driver's License Number
- 4 - Alien Registration Number
- 5 - Corporate Identification
- 9 - Other Identification

Beneficiary Identifier

Specify the identifier details as per the selected ID Code.

Beneficiary Currency

Specify the Beneficiary Currency from the list of values, if Beneficiary Identifier selected is a GL account.

Credit Amount

Specify the credit amount to customer account.

Name

The system displays the Originator's name based on the selected Debit account.

Address

Specify the address details of the originator.

Address 2-3

Specify the additional address details of the originator.

Payment Details**Booking Date**

Specify the booking date of the payment.

Instruction Date

Specify the Instruction Date of the incoming payment which can be current or future business date.

Original Instruction Date

System defaults the Original Instruction Date.

Activation Date

System defaults the Activation Date on successful completion of transaction.

Transfer Currency

System displays the transfer currency of USD by default.

Transfer Currency Name

System displays the currency name.

Transfer Amount

Specify the amount for the transfer.

Enrich

Click this button for enrichment of the transaction that includes deriving exchange rate (if applicable), Value dates, Charges and mandatory field validation.

:4100:Beneficiary FI**ID Code**

Select the ID code from the drop down corresponding to the type of identification of Beneficiary FI and details that are desired to be input in the following fields The options are:

- B - SWIFT Bank Identifier Code (BIC)
- C - CHIPS Participant
- D - Demand Deposit Account (DDA) Number
- F - Fed Routing Number
- U - CHIPS Identifier

Identifier

Specify the Beneficiary FI identifier as per the selected ID Code.

Name

Specify the name of the beneficiary FI.

Address

Specify the address of the beneficiary FI.

Debit Value Date

The system displays the derived debit value date on clicking Enrich.

Credit Value Date

The system displays displays the credit value date on clicking Enrich.

Customer No

The system displays the customer number (of the customer maintained in the system) that is derived based on the selected debit account number of the originator.

Customer Service Model

The system displays the customer service model linked to the customer.

Remarks

Specify any remarks for the payment being booked.

Sender**Sender ABA Number**

Select the ABA Number of Sender DI (Depository Institution) from the list of all Fedwire members.

Sender Short Name

Specify the Sender's Short Name.

:3700:Charges

Details of Charges

Select the details of charges from the drop down list. The options are:

- B (Beneficiary)
- S (Shared)

Senders Charges

Specify the sender's charges as <USD><Amount>. For e.g. USD10.25.

:5000:Originator**ID Code**

Select the ID code from the drop down corresponding to the type of identification of Originator and details that are desired to be input in the following fields. The options are:

- B - SWIFT Bank Identifier Code (BIC)
- C - CHIPS Participant
- D - Demand Deposit Account (DDA) Number
- F - Fed Routing Number
- T - SWIFT BIC or Bank Entity Identifier (BEI) and account number
- U- CHIPS Identifier

- 1 - Passport Number
- 2 - Tax Identification Number
- 3 - Driver's License Number
- 4 - Alien Registration Number
- 5 - Corporate Identification
- 9 - Other Identification

Identifier

Specify the identification details as per the selected ID Code.

Name

Specify the name of the Originator.

Address

Specify the address details of the Originator.

:4400:Account Debited in Drawdown

ID Code

Select the ID code from the drop down corresponding to the type of identification of Beneficiary FI and details that are desired to be input in the following fields The options are:

- B - SWIFT Bank Identifier Code (BIC)
- C - CHIPS Participant
- D - Demand Deposit Account (DDA) Number
- F - Fed Routing Number
- U - CHIPS Identifier
- 1 - Passport Number
- 2 - Tax Identification Number
- 3 - Driver's License Number
- 4 - Alien Registration Number
- 5 - Corporate Identification
- 9 - Other Identification

Identifier

Specify the Beneficiary FI identifier as per the selected ID Code.

Name

Specify the name of the beneficiary FI.

Address

Specify the address of the beneficiary FI.

:5010:Originator Option F

Party Identifier Format

Select the Party Identifier Format. Options are Account Number / Unique Identifier.

Party Identifier

Select the Party Identifier from drop-down values.

Name & Line 1- 3

Select the unique values from drop-down values.

3.2.1.2 Pricing Tab

This tab displays the pricing details of the charges computed by system based on the transaction attributes in the Main tab. These details are populated on clicking Enrich button in the Main tab before saving the transaction, or as part of processing on saving the transaction without clicking Enrich.

Pricing Component	Pricing Currency	Amount	Waived	Debit Currency	Debit Amount	Deferred	Borne By Bank
-------------------	------------------	--------	--------	----------------	--------------	----------	---------------

The below mentioned attributes will be available in the Pricing tab:

Pricing Component

The system displays the Name of the pricing component applicable for the transaction for which charges are computed.

Pricing Currency

The system displays the Currency in which the charge amount is calculated for the Pricing component.

Amount

The system displays the charge amount calculated for each pricing component.

Waived

This field if checked indicates that the charge is waived for the pricing component.

Debit currency

The system displays the currency in which the charge amount is debited for the pricing component. This is the currency of the debit (originator) account.

Debit amount

The system displays the charge amount in debit currency to be debited. This amount is different from the calculated Pricing amount if the debit currency is different from the Pricing Currency. The Debit amount for charges is calculated by converting the Pricing amount in Pricing Currency to Debit currency using specified Exchange Rate type in Pricing Code maintenance.

Deferred

This field if checked indicates that the charges are not collected during transaction processing but their liquidation is deferred based on customer preferences. Applicable only for “S” (Shared) type of charges.

Borne By Bank

This field if checked indicates that the charges are borne by bank.

3.2.1.3 FI Information

Click 'FI Information' tab to specify the FI Information details. For more details on fields, refer

The screenshot displays the 'FI Information' tab within a software application. The interface features a top navigation bar with tabs: 'Main', 'Pricing', 'FI Information' (highlighted in red), 'Additional', and 'Remittance Information'. The main content area is divided into several sections for data entry:

- :6100:Receiver FI Information**: Includes a text field for 'Receiver FI Information' and a section for 'Additional Information' with multiple lines.
- :6110:Drawdown Debit Account Advice Information**: Includes a dropdown for 'Advice Code' and a section for 'Additional Information' with multiple lines.
- :6300:Beneficiary's FI Information**: Includes a text field for 'Beneficiary's FI Information' and a section for 'Additional Information' with multiple lines.
- :6310:Beneficiary's FI Advice Information**: Includes a dropdown for 'Advice Code' and a section for 'Additional Information' with multiple lines.
- :6400:Beneficiary Information**: Includes a text field for 'Beneficiary Information' and a section for 'Additional Information' with multiple lines.
- :6410:Beneficiary Advice Information**: Includes a dropdown for 'Advice Code' and a section for 'Additional Information' with multiple lines.
- :6420:Method of Payment to Beneficiary**: Includes a text field for 'Method of payment' and a section for 'Additional Information' with multiple lines.
- :6500:FI to FI Information**: Includes a text field for 'FI to FI Information' and a section for 'Additional Information' with multiple lines.

At the bottom of the form, there is a status bar with the following fields: 'Maker ID', 'Release Time', 'Checker ID', 'Checker Date Stamp', 'Authorization Status', and an 'Exit' button.

to section 2.2.1.3.

3.2.1.4 Additional Tab

Click 'Additional' tab to capture the additional details. For more details on the fields, refer to section 2.2.1.4.

The screenshot shows the 'Additional' tab selected in a remittance form. The form is divided into several sections:

- Additional Details:** Includes fields for :3320:Sender's Reference, :3610:Local Instrument Code (with a dropdown), Proprietary Code, and :4320:Reference for Beneficiary.
- :5200:Instructing FI:** Includes fields for ID Code, Identifier, Name, Address, Address 2, and Address 3.
- :8250:Related Remittance Information:** Includes fields for Remittance Identification, Remittance Location Method, Remittance Location Electronic Address, Name, Address Type, Department, Sub Department, Street Name, Building Number, and Address.
- :4000:Intermediary FI:** Includes fields for ID Code (with a dropdown), Identifier, Name, Address, Address 2, and Address 3.
- :6000:Originator to Beneficiary Information:** Includes fields for Identifier, Name, Address, Address 2, and Address 3.

At the bottom of the form, there are fields for Maker ID, Release Time, Checker ID, Checker Date Stamp, and Authorization Status. An 'Exit' button is located in the bottom right corner.

3.2.1.5 Remittance Parties

Click 'Remittance Parties' tab to capture the information on Remittance Parties. For more details on the fields, refer to section 2.2.1.5.

The screenshot shows the 'Remittance Parties' tab selected in a remittance form. The form is divided into two main sections:

- :8300:Remittance Originator:** Includes fields for :8300:Remittance Originator (with a dropdown), Identification Type (with a dropdown), Identification Code, Name, Identification Number, Identification Number Issuer, Date of Birth (YYYY-MM-DD), Place of Birth, Address Type (with a dropdown), Department, and Sub Department.
- :8350:Remittance Beneficiary:** Includes fields for Name, Identification Type (with a dropdown), Identification Code, Identification Number, Identification Number Issuer, Date of Birth (YYYY-MM-DD), Place of Birth, Address Type (with a dropdown), Department, and Sub Department.

At the bottom of the form, there are fields for Maker ID, Release Time, Checker ID, Checker Date Stamp, and Authorization Status. An 'Exit' button is located in the bottom right corner.

3.2.1.6 Remittance Information Tab

Click 'Remittance Information' tab to capture the information on Remittance. For more details on the fields, refer to section 2.2.1.6.

The screenshot shows the 'Remittance Information' tab selected in the top navigation bar. The main content area is divided into two columns. The left column contains fields for ':8400:Primary Remittance Document Information', including 'Document Type Code' (a dropdown menu), 'Proprietary Document Type Code', 'Document Identification Number', 'Issuer', and 'Sequence Number'. The right column contains fields for ':8450:Actual Amount Paid' (with 'Currency Code' and 'Amount' sub-fields), ':8500:Gross Amount of Remittance Document' (with 'Document Currency Code' and 'Amount' sub-fields), and ':8650:Date Of Remittance Document' (with a 'YYYY-MM-DD' date picker). Below these columns is a section for ':8550:Amount of Negotiated Discount' with a 'UDF | MIS' label. At the bottom, there is a light blue footer bar with fields for 'Maker Id', 'Release Time', 'Checker ID', 'Checker Date Stamp', and 'Authorization Status', along with an 'Exit' button.

3.2.1.7 Accounting Entries Tab

You can invoke this screen by clicking 'Accounting Entries' tab in the PWDITONL screen.

The screenshot shows the 'Accounting Entries' tab selected. At the top, there is a header bar with the title 'Accounting Entries' and a search bar labeled 'Enter Query'. Below the search bar is a field for 'Transaction Reference Number'. The main area is a table titled 'Accounting Entries'. The table has a header row with columns: 'Event Code', 'Transaction Date', 'Value Date', 'Account', 'Account Branch', 'TRN Code', 'Dr/Cr', 'Amount Tag', and 'Account Currency'. Below the header, there is a large empty space for the table content. At the bottom, there is a light blue footer bar with the text 'Accounting Details' and an 'Exit' button.

By default, the following attributes of the **Accounting Entries** tab are displayed:

- Event Code
- Transaction Date
- Value Date
- Account
- Account Branch
- TRN Code

- Dr/Cr.
- Amount Tag
- Account Currency
- Transaction Amount
- Netting
- Offset Account
- Offset Account Branch
- Offset TRN Code
- Offset Amount Tag
- Offset Currency
- Offset Amount
- Offset Netting
- Handoff Status

Note

In the Outbound Cross Border Transaction Processing, posting the Debit Liquidation (DRLQ) entry immediately after resolving Processing Dates [After Repair field validations and after resolving Accounts & Dates] for Cross Border pass-through payments.

3.2.1.8 Viewing Inbound Fedwire Transaction Summary

You can view the summary in “Inbound Fedwire Transaction Summary” screen. You can invoke the “Inbound Fedwire Transaction Summary” screen by typing ‘PWSITONL’ in the field at the top right corner of the Application toolbar and clicking on the adjoining arrow button.

You can search for the records using one or more of the following parameters:

- Transaction reference no
- Value Date
- Network Code
- User Reference
- Source Code
- Transaction Branch
- Instruction Date
- Booking Date
- Customer No
- Customer Service Model
- Receiver ABA Number
- Authorization Status

Once you have specified the search parameters, click 'Search' button. The system displays the records that match the search criteria.

Double click a record or select a record and clicking on 'Details' button to view the detailed maintenance screen.

3.2.2 Inbound Fedwire View

You can view the details of an Incoming Fedwire transaction in the "Inbound Fedwire View" Screen You can invoke the "Inbound Fedwire View" screen by typing 'PWDIVIEW' in the field at the top right corner of the Application toolbar and clicking on the adjoining arrow button.

The screenshot displays the 'Inbound Fedwire View' application window. It features a top toolbar with a search field containing 'PWDIVIEW' and an arrow button. The main interface is divided into several sections:

- Header Section:** Includes fields for Transaction Reference Number, Source Reference Number, Transaction Type Code, Sub Type Code, and FX Reference Number. It also has a 'Credit to GL' button.
- Search Parameters:** A section on the left with fields for Transaction Branch, Branch Name, Host Code, Host Code Description, Source Code, Source Code Description, Network Code, and Network Code Description.
- Transaction Details:** A central area with multiple tabs (Main, Pricing, FI Information, Additional, Remittance Parties, Exceptions, Cover Payment Info). The 'Main' tab is active, showing fields for ID Code, Identifier, Name, Address, and various transaction status indicators.
- Payment Details:** A section on the right with fields for Booking Date, Instruction Date, Original Instruction Date, Authentication Date, Transfer Currency, Transfer Amount, Exchange Rate, Credit Account, Credit Amount, Debit Value Date, Credit Value Date, Customer Number, and Remarks.
- Sender Information:** Fields for Sender ABA Number, Sender Short Name, and Sender Charges.
- Originator Information:** Fields for Originator ID Code, Identifier, Name, Address, and Party Identifier.
- External System Status:** Fields for Sanctions Check Status, Sanctions Check Reference, External Account Check Status, External Account Check Reference, External Exchange Rate Status, and External Rate Reference.
- Queue and Confirmation:** Fields for Queue Code, Queue ID, Confirmation Status, and Confirmation Type.

The bottom of the screen contains a status bar with fields for Maker ID, Release Time, Authorization Status, Checker ID, and Checker Date Stamp, along with an 'Exit' button.

- From this screen, click Enter Query. The Transaction Reference field gets enabled, for the user to specify the Reference Number.
- Along with the transaction details in the Main and Pricing tabs you can also view the Status details for the following:
 - Transaction Status
 - External System Status
 - Pending Queue Details
 - Sanction Seizure

View Queue

This button launches the corresponding Queue screen, where the transaction is currently held. The Queue screen will be launched in query mode, listing this transaction alone.

- Click Execute Query to populate the details of the transaction in the Inbound Fedwire View Detailed screen.

gpi Enabled

This field is not editable and is disabled. This field has the drop-down values as - Yes/No.

Incoming gpi

This field is disabled. This is set to 'Y' for pass-through cases only when processing an inbound gpi message.

:6000:Originator to Beneficiary Information

In the mail-based Debit advice processing populates the values for this advice tag from the Outbound Fedwire transaction Tag {6000} - Originator to Beneficiary Information Line 1 to Line 4.

UETR

The UETR (Unique End-to-End Transaction Reference) is generated for the outbound transaction.

gpi/Universal Confirmation Status

Confirmation Status

Displays the following values:

- Ungenerated
- Generated

Confirmation Type

Displays the following values:

- Interim
- Credit
- Reject

For more details on Main, Pricing, Fi Information, Additional Details, Remittance Parties, Remittance Information tabs refer to 'PWDITONL' screen details above.

3.2.2.1 Exceptions Tab

Click on the 'Exceptions' tab to view the reversal details for the transaction. Following details can be viewed:

- Reversal Details
- Reversal request Details
- Reversal Payment details
- External System Status Reversal request
- External System Status Reversal payment


3.2.2.2 View Queue Action Log

You can view all the queue actions for the respective transaction initiated. You can invoke this screen by clicking the 'View Queue Action' button in View screen, where the Transaction Reference Number is auto populated and related details are displayed.

For more details on the fields and screen, refer to section 2.2.2.2.

3.2.2.3 UDF Tab


You can invoke this screen by clicking 'UDF' tab in the screen.



The screenshot shows a window titled 'Fields' with a close button (X) in the top right corner. Below the title bar, there is a navigation bar with a back arrow, '1 Of 1', a forward arrow, and a 'Go' button. The main area contains a table with two columns: 'Field Label' and 'Field Value'. The table is currently empty. At the bottom right, there are 'Ok' and 'Exit' buttons.

3.2.2.4 MIS Tab

You can invoke this screen by clicking 'MIS' tab in the screen.



The screenshot shows a window titled 'MIS Details' with a close button (X) in the top right corner. Below the title bar, there is a 'Transaction Reference Number *' field and a 'MIS Group' dropdown menu with a 'Default' button. The main area is divided into two sections: 'Transaction MIS' and 'Composite MIS'. Each section contains a table with multiple rows and columns for data entry. At the bottom right, there are 'Ok' and 'Exit' buttons.

3.2.2.5 All Messages

Click the “All Messages” link in the View screen to invoke this sub-screen.

	DCN	Message Type	SWIFT Message Type	Direction	Value Date	Message Status	Test Status
☐	*						

The system displays the following details in a grid form containing one or multiple rows:

Transaction Reference

Displays the transaction reference number.

DCN

Displays the unique DCN number assigned by the system to each generated message.

Message Type

Displays the system defined message type e.g. Cust_Transfer, Cover etc.

SWIFT Message Type

Specify the SWIFT message type of the generated message e.g. MT103, MT202COV etc.

Direction

Displays if the message is outgoing or incoming.

Media

Displays the message generation date.

Message Status

The system displays the message status. e.g. Hand-off, Repair etc.

Test Status

The system displays the Test status of the message, which would generally be “Not Applicable”.

Authorization Status

The system displays the authorization status. i.e. Authorized or Unauthorized. For incoming messages which fall into Repair or a user defined queue, this status may be “Unauthorized” if the message has been manually repaired and awaiting authorization.

Acknowledgment Status

The system displays whether Acknowledgement from SWIFT (ACK/NAK) is required or not for the outgoing SWIFT message. This value is displayed based on the message level configuration.

Media

The system displays the media of the message which is "SWIFT".

Receiver/Sender

Displays the Customer ID of the Receiver of an outgoing SWIFT message or of the Sender of an incoming SWIFT message.

Receiver Name

Displays the name of the receiver or sender.

PDE Flag

Displays if PDE trailer is included in the incoming or outgoing message.

3.2.2.6 Message Details

You can select a particular message in the All Messages summary sub-screen (explained above) and view the message details in this screen.

Displays the following details for the selected message.

Reference Number

Specify the transaction reference number.

DCN

The system displays DCN of the message.

ESN/Version Number

The system displays the version number of the message.

Receiver/Sender

The system displays receiver/sender of the message.

Message Type

The system displays system defined message type.

SWIFT Message Type

The system displays SWIFT message type.

Message

The system displays details of the actual message including BIC and Name and Address details of the Sender and Receiver as well as the fields and values populated in the message body.

Remarks

Specify a comments or remarks for the message.

Reject Reason

The system displays the reject reason code.

Message Trailers

The system displays the message trailers.

3.2.2.7 Accounting Entries

During payment transaction processing, the accounting entries whose for which hand -off status is pending are posted to a JMS Queue. Once these entries are posted in the queue, the status is updated as handed off.

If the Accounting system and the ECA system are not the same, an update is sent to the ECA system as well while doing the accounting handoff. Any amount block in the customer account done during External credit approval can be released on receiving accounting update.

Click the “Accounting Entries” tab in the view screen to invoke the screen.

Main Pricing FI Information Additional Remittance Information **Accounting Entries**

1 Of 1 Go

Netting	Offset Account	Offset Ac Branch	Offset Txn Code	Offset Amount Tag	Offset Currency
---------	----------------	------------------	-----------------	-------------------	-----------------

View Queue Action | UDF | MIS | All Messages

Maker ID Checker ID
Release Time Checker Date Stamp
Authorization Status

Exit

The system displays the following details in a grid form that contains accounting entries in multiple rows:

Reference Number

Displays the Transaction reference number.

Event Code

Displays the Accounting event code.

Account

The system displays the transaction account number that is debited or credited in the accounting entry.

Account Branch

The system displays the account branch.

TRN Code

The system populates the transaction code of the accounting entry from the Account Template maintenance.

Dr/Cr.

The system displays whether the accounting entry is 'debit' or 'credit' leg.

Amount Tag

The system displays the amount tag of the Amount being debited/credited.

Account Currency

The system displays the transaction account currency.

Transaction Amount

The system displays the transaction amount being debited/credited.

Netting

The system displays if Netting of accounting entries is required.

Offset Account

The system displays the Offset Account of the accounting entry for posting the offset debit/credit.

Offset Account Branch

The system displays the Offset Account Branch.

Offset TRN Code

The system displays the Offset Transaction Code from the Account Template maintenance.

Offset Amount Tag

The system displays the Offset Amount Tag of the Offset amount.

Offset Currency

The system displays the Offset Amount Currency.

Offset Amount

The system displays the Offset Amount being debited or credited.

Offset Netting

The system displays if the Offset Netting is required.

3.2.2.8 View Repair Log

You can view all the Repair actions for the respective transaction initiated. You can invoke this screen by clicking the 'View Repair Log' button in View screen, where the Transaction Reference Number is auto populated and related details are displayed.

Queue Reference No	Field Name	Old Value	Repaired Data	Error
--------------------	------------	-----------	---------------	-------

Following details are displayed:

- Queue Reference No
- Field Name
- Old Value
- Repaired Data
- Error

3.2.2.9 gpi Confirmations

You can view all the confirmation messages received from gpi Tracker and sent to gpi Tracker. You can invoke this screen by clicking the 'gpi Confirmations' button in View screen, where the Transaction Reference Number is auto populated and related details are displayed.

The screenshot shows the 'gpi Confirmations' window. At the top, there is a 'Transaction Reference Number' field. Below it, there are two tabs: 'Tracker Confirmations' (selected) and 'Our Confirmations'. The 'Tracker Confirmations' section displays a table with columns: Reference Number, Message Date and Time, Status Code, Reason Code, Status Originator BIC, Forwarded To BIC, Currency, and Amount. Below the table is a 'Message' button. The 'gCCT Confirmations' section also displays a table with the same columns. Below the table is a 'Message' button. At the bottom right, there is an 'Exit' button.

The screenshot shows the 'gpi Confirmations' window with the 'Our Confirmations' tab selected. The 'Transaction Reference Number' field is populated. The 'Tracker Confirmations' section displays a table with columns: Reference Number, Message Date and Time, Generation Mode, Tracker Interaction, Status Code, Reason Code, and Status. Below the table is a 'Message' button and an 'API Response Status' button. The 'gCCT Confirmations' section also displays a table with the same columns. Below the table is a 'Message' button and an 'API Response Status' button. At the bottom right, there is an 'Exit' button.

This screen has 'Tracker Confirmations', 'Our Confirmations' Tabs displaying gCCT/gCOV confirmations received from and sent to the tracker.

Following are the details listed under 'Tracker Confirmations' and 'Our Confirmations' tab in the screen:


- **gCCT Confirmations:**
 - Reference Number
 - Message Date and Time (Only for Tracker Confirmations)
 - Status Code
 - Reason Code
 - Status Originator BIC
 - Forwarded To BIC
 - Currency
 - Amount
 - Exchange Rate
- **gCOV Confirmations:**
 - Reference Number
 - Message Date and Time
 - Status Code
 - Reason Code
 - Status Originator BIC
 - Forwarded To BIC
 - Currency
 - Amount

Message Button

Click on 'Message' button, to view gCCT/gCOV confirmation message that was received or generated and sent out.

API Response Status Button

Click on 'API Response Status' button, to view API Response Status screen for gCCT/gCOV confirmation message that was generated and sent out.



View API Response Status

Execute Query

DCN

Response Status

Response Code

Error

Cancel

The system displays the following details:

DCN

The system displays Document Number value of the API message.

Response Status

This field displays value as 'Success' or 'Failure'.

Response Code

This field displays HTTP Response code.

Error

This field displays HTTP Error message.

3.2.2.10 Inbound Fewdire View Summary

You can invoke the 'Inbound Fedwire View Summary' screen by typing 'PWSIVIEW' in the field at the top right corner of the application toolbar and clicking the adjoining arrow button.

The screenshot shows the 'Outbound Fedwire View Summary' application window. At the top, there is a search bar with 'PWSIVIEW' entered and an arrow button. Below the search bar, there are several search criteria fields organized into three columns. The first column includes Transaction Reference No, Transaction Status, Debit Liquidation Status, Transfer Currency, Source Reference Number, and File Reference Number. The second column includes Network Code, Authorization Status, Credit Liquidation Status, Instruction Date, :3600 Business Function Code, and gpi Enabled. The third column includes Debit Account, Booking Date, Queue Code, Customer Number, Type, and UETR. Below these fields, there is a table with columns: Transaction Reference No, User Reference, Network Code, Receiver ABA Number, Identifier, Debit Account, Transaction Status, Transfer Amount, Authorization Status, Exchange Rate, Booking Date, Debit Liquidation Status, and Credit Liquidation Status. The table is currently empty. At the bottom of the window, there are buttons for 'Reverse' and 'Generate Confirmation', and an 'Exit' button in the bottom right corner.

You can search for the records using one or more of the following parameters:

- Transaction reference no
- Network Code
- Originator F Account Number 5010
- Transaction Status
- Authorization Status
- Booking Date
- Debit Liquidation Status
- Credit Liquidation Status
- Queue Code
- Transfer Currency
- Instruction Date
- Customer Number
- Business Function Code
- Type
- OMAD
- UETR
- IMAD
- gpi Agent

Once you have specified the search parameters, click 'Search' button. The system displays the records that match the search criteria.

Below actions are allowed in this Summary screen:

Action	Description
Reverse	When you click on the Reverse action button, Fedwire Transaction Reversal Request (PWDTRNRV) screen is opened.
Generate Confirmation	You can use this action for manually generating the Swift gpi/Universal Confirmation. This action is only allowed when below conditions are satisfied: - You have required role or user level queue action access right for the user action 'Generate Confirmation' - BFC of the Inbound message is 'CTR' (or) 'CTP' [CTP without Tag{3610} LOCAL INSTRUMENT value as 'COVS'] - UETR value is present Refer to Cross_Border User Guide section(4.1.8) for more details.

3.2.3 Fedwire Reversal Request Queue Summary

You can invoke the 'Fedwire Reversal Request Queue Summary' screen by typing 'PQSFREVQ' in the field at the top right corner of the application toolbar and clicking the adjoining arrow button.

You can search for the records using one or more of the following parameters:

- Source Code
- Host Code
- Authorization Status
- Transaction Reference Number
- Queue Status
- Transaction Branch
- Queue Reference Number

- Network Code
- Customer Service Model
- Network Type Code

Once you have specified the search parameters, click 'Search' button. The system displays the records that match the search criteria.

Below actions are allowed in this Summary screen:

Action	Description
View Reversal Transaction	On clicking of 'View Reversal Transaction' action, the reversal request transaction screen 'PWDIREVW' gets launched displaying the reversal request transaction details.
View Queue Action	After clicking View Queue Action, existing Queue Action screen 'PQDQUACL' gets launched and displays all the user actions taken on the reversal request transaction from this screen.
Manual Match	This action is allowed if the reversal request match status is 'Unmatched'. A Manual Match sub screen is launched to capture the Inbound Fedwire Transaction Reference.
Accept	This action is allowed if the reversal request match status is 'Unmatched'. A Reversal Response sub screen is launched to capture the remarks.
Reject	This action is allowed if the reversal request match status is 'Unmatched'. The sub screen which gets launched for 'Accept' user action to capture the remarks. The user action field is populated as 'Reject'.
Authorize	This action is allowed only if the user has required role/user level access and if the user is different from maker. This action launches sub screens based on the last user action to capture the Authorizer's remarks and the authorization processing for the last user action gets triggered.
Delete	This action is allowed if the current user is the maker of that user action. Queue action log gets deleted. Authorization status is made blank. If last user action is Accept or Reject, the 'Queue status' field is marked as 'Pending'. If last user action is Manual Match, then the 'Queue Status' field is marked as 'Pending'.

3.2.3.1 **Inbound Fedwire Reversal Request Transaction View Detailed**

You can invoke the 'Inbound Fedwire Reversal Request Transaction View Detailed' screen 'PWDIREVW' by clicking 'View Reversal Transaction' action on the 'Fedwire Reversal Request Queue Summary' screen 'PQSFREVQ'.

The 'Inbound Fedwire Reversal Request Transaction View Detailed' screen displays the reversal request transaction details.

Inbound Fedwire Reversal Request Transaction View Detailed

Transaction Reference Number	Transaction Branch
Host Code	Branch Name
Description	Network Code
1310 Type Code	Network Description
Sub Type	
Business Function Code	
Name	

External System Status

Sanctions Check Status: Not Applicable

Sanctions Check Reference

Pending Queue Details

Queue Code: Sanction Check Queue

Sanction Seizure

Sanction Seizure

Transaction Status

Transaction Status: Unprocessed

Matched Status: Unmatched

Response Status

Reject Reason

View Queue Action

Maker Id

Release Time

Authorization Status: Authorized

Checker ID

Checker Date Stamp

3.3 Fedwire Browser

3.3.1 Fedwire Outbound Browser Summary

You can view all the outbound Fedwire messages sent through this screen. All the outbound messages of all the message status are displayed here.

You can invoke the 'Fedwire Outbound Browser Summary' screen by typing 'PWSOTBRW' in the field at the top right corner of the application toolbar and clicking the adjoining arrow button.

Fedwire Outgoing Browser Summary

Search Advanced Search Reset Clear All

Case Sensitive

Transaction Reference No IMAD

Transaction Branch Business Function Code

Receiver DI Handoff Date

Originator Account Type Code

Message Status Ack Nak Status

Message Generate Status

Records per page: 15 1 Of 1 Go Lock Columns: 0

Transaction Reference No	IMAD	Transaction Branch	Business Function Code	Receiver DI	Handoff Date	Handoff Time	Originator Account	Type Code	Message Status	Host Code
--------------------------	------	--------------------	------------------------	-------------	--------------	--------------	--------------------	-----------	----------------	-----------

View Message | View Acknowledgement | View Transaction

Exit

You can search using one or more of the following parameters:

- Transaction Reference No
 - Transaction Branch
 - Receiver DI
 - Originator Account
 - Message Status
 - Message Generate Status
 - IMAD
 - Business Function Code
 - Handoff Date
 - Type Code
 - Ack Nak Status
- You can view all the messages for the various Message status listed.

Once you have specified the search parameters, click 'Search' button. The system displays the records that match the search criteria.

Double click a record or select a record and click on 'Details' button to view the detailed maintenance screen.

3.3.1.1 View Message

Also you can view the outbound Fedwire message details by clicking the 'View Message' action button, present in the bottom of the screen.

Fedwire Outbound View Message

Message Reference Number 1930911217200000

Message FT0811.XFTB11 (1500)3037136734T (1510)1090(1520)20191105OBPAY/MNT000002(2000)000000000000(3100)11110001SCITI bank US* (3320)1922112049800000(3400)121140399SIL VLY BK SCLA(3500)13600(SVC)9000)Testing maximum length supported by this with multi-line

Exit

3.3.1.2 View Acknowledgement

Also you can view the ack message sent by clicking the 'View Acknowledgement' action button, present in the bottom of the screen.

View Ack Message Detailed

Transaction Reference No 1509414625600001 URC 72353280

Transaction Reference No	IMAD	Transaction Branch	Message Status	Originator Account	Receiver DI	URC	Network
1909414625600001	IMAD	NYC				72353280	FEDWIRE

Message

Exit

3.3.1.3 View Transaction

Also you can view the Outbound Fedwire View screen by clicking the 'View Transaction' action button, present in the bottom of the screen. Refer to Section 3.1.2, "Outbound Fedwire View".

3.3.2 Fedwire Inbound Message Browser Summary

You can view the uploaded inbound Fedwire messages and its related transactions, if any through this screen. All SVC messages, received by the system, are displayed here.

You can invoke the 'Fedwire Inbound Message Browser Summary' screen by typing 'PWSSVCBR' in the field at the top right corner of the application toolbar and clicking the adjoining arrow button.

You can search for records using one or more of the following parameters:

- Transaction Reference Number
- Message Reference Number
- Generated Reference
- IMAD
- OMAD
- Message Type
- Received Date
- Status
- Network Code
- Authorization Status


Once you have specified the search parameters, click 'Search' button. The system displays records that match the search criteria.

Select a record and click on View Message or View Transaction button to view the detailed transaction or uploaded inbound message.

3.3.2.1 **View Message**

You can view the uploaded inbound Fedwire message by clicking the 'View Message' action button, present in the bottom of the screen. The uploaded inbound message gets displayed.

You need to select a record and click on 'View Message' to view the message details.



3.3.2.2 View Transaction

You can view the Transaction, which is linked to an uploaded inbound Fedwire message by clicking the 'View Transaction' action button present in the bottom of the screen. The detailed Inbound FEDWIRE view screen gets displayed.

You need to select a record and click on 'View Transaction' to view the linked transaction in detailed view:

- Fedwire Incoming transaction view screen (PWDIVIEW) gets launched for Fedwire Incoming payment.
- Cross Border Outbound transaction view (PXDOVIEW) screen gets launched for the Fedwire pass-through payment.

Note

In case the Incoming Fedwire transaction is in Non-STP queue, the launched Fedwire Incoming transaction view screen (PWDIVIEW) do not shows any transaction data.

3.3.2.3 Retry

This action is allowed only if the message status is 'Failed', and authorization status is 'Blank'/'Authorized'.

The inbound Fedwire message upload processing gets triggered. The payment type is resolved first.

- If the payment type is resolved as Fedwire inbound, then an inbound Fedwire transaction is booked.
- If the payment type is resolved as Cross Border pass-through, then an outbound Cross Border transaction is booked.
- If the payment type resolution is failed again, the status field in Inbound Fedwire message browser is updated to 'Failed' and Error code/Error description is populated again.

Note

It is expected that user maintains the required D to A maintenance before retrying message upload.

3.3.2.4 Edit

This action is allowed only if the status is in 'Failed'.

Message Reference Number		2011115686000012	
IMAD		20200213B1Q8311C4715	
Sender		011100028	
Error Code		FW-VAL-101	
Error Description		Failed to resolve the paym	
Message Type		BTR	
View Details			
ID Code	D	Address	US
Identifier	FE9989111111701		
Name	LEKYA		
Edit Details			
Bank Identifier Code		BIC Code Description	
Remarks			
Remarks		Authorizer Remarks	
Maker	Date Time	Mod No	Record Status
Checker	Date Time		Authorization Status
			Ok Exit

3.3.2.5 Authorize

This action is allowed only if the user has required role/user level access and if the user is different from maker.

3.3.3 Fedwire Incoming Service Message View

Processing of Incoming Service Messages would involve linking them to underlying payment transactions and making them available to be viewed in the relevant View screen.

On receipt of incoming Service message, system would attempt to match it to an underlying outgoing/incoming payment transaction (including Drawdown or Reversal payment), Drawdown/Reversal request, Drawdown Refusal message or Service message.

- This would be done using the value present in {3500} Previous Message Identifier tag of the received Service message with the value of IMAD in any of the following:
 - 'Processed' outgoing payment transaction
 - Incoming payment transaction in any status
 - Outgoing Drawdown request transaction – whose message is generated
 - Incoming Drawdown request message
 - Outgoing Reversal Request transaction – whose message is generated
 - Incoming Reversal request message
 - Generated or received Drawdown Refusal message
 - Generated Service message
- Once the underlying transaction or message is identified, system would validate that the Sender DI of the Service message is either the Receiver DI or Sender DI of the identified underlying transaction or message.
- Thereafter, system would generate Sanctions request for the received Service message and send it to Sanctions system.
 - This would involve including the actual Service message in a message block in the Sanctions request and sending it to Sanctions system.
- On receiving an Approved response from Sanctions system, the incoming Service message would be linked to the matched Payment or Request transaction, and would be available to be viewed in the relevant View screen.
- If any status other than Approved is received from Sanctions system then system will move the incoming Service message to the existing Sanctions queue.

- You can take appropriate action on the message in the queue similar to the existing functionality for payment transactions.
- If Auto-cancellation has been configured for a Reject response from Sanctions then the incoming Service message would be auto-cancelled.

If the incoming Service message could not be matched to any payment/request transaction then it would be available to be viewed in a Fedwire Incoming Service Message View screen.

You can invoke the 'Fedwire Incoming Service Message View' screen by typing 'PWDISMVW' in the field at the top right corner of the application toolbar and clicking the adjoining arrow button.

Specify the 'DCN' and click on enter query button to view the details. System displays the following details on clicking Execute Query:

- IMAD - value of IMAD tag present in the incoming Service message
- OMAD - value of OMAD tag present in the incoming Service message
- Output Cycle Date - Cycle date in CCYYMMDD format that is part of the OMAD value
- Service Message - actual message would be displayed in this text area box
- Host Code
- Network Code
- DCN
- Transaction Status
- Pending Queue Details - Queue Code
- Sanction Seizure
- External System Status - Sanctions Check Status and Sanctions Check Reference

3.3.3.1 Fedwire Incoming Service Message View Summary

This screen enables you to query for incoming service messages that were not matched with any underlying transaction or message.

You can invoke the 'Fedwire Incoming Service Message View Summary' screen by typing 'PWSISMVW' in the field at the top right corner of the application toolbar and clicking the adjoining arrow button.

You can search using one or more of the following parameters:

- DCN
- IMAD
- Output Cycle Date
- Host Code
- OMAD
- Received Date

Once you have specified the search parameters, click 'Search' button. The system displays the records that match the search criteria.

Double click a record or select a record and click on 'Details' button to view the detailed maintenance screen.

Below actions are allowed:

Action	Function
View Reversal Transaction	When you click on 'View Reversal Transaction' action, the reversal request transaction screen 'PWDIREVW' gets launched displaying the reversal request transaction details.
Create Reversal Request	This action is allowed if the reversal request reference is blank. A new sub screen gets launched to capture the remarks and a provision to match with an existing inbound Fedwire transaction.

Action	Function
Authorize	This action launches the same sub screen that is launched for the 'Create Reversal Request' action to capture the authorizer remarks. Authorizer remarks are updated in the queue action log and checker id/date time is also updated.
Delete	This action is allowed if the current user is the maker of that user action. Queue action log gets deleted. Authorization status is made blank. Reversal Response reference is updated as blank.

Inbound Fedwire Reversal Request Transaction View Detailed

You can invoke the 'Inbound Fedwire Reversal Request Transaction View Detailed' screen 'PWDIREVW' by clicking 'View Reversal Transaction' action on the 'Fedwire Reversal Request Queue Summary' screen 'PQSFREVQ'.

The 'Inbound Fedwire Reversal Request Transaction View Detailed' screen displays the reversal request transaction details.

The screenshot displays the 'Inbound Fedwire Reversal Request Transaction View Detailed' screen. It features a header bar with the title. Below the header, the screen is organized into several sections with input fields and dropdown menus. The 'Transaction Reference Number' section includes fields for Host Code, Description, :1510 Type Code, Sub Type, Business Function Code, and Name. The 'Transaction Branch' section includes fields for Branch Name, Network Code, and Network Description. The 'External System Status' section includes a dropdown for Sanctions Check Status (set to 'Not Applicable'), a field for Sanctions Check Reference, and a field for Service Message. The 'Pending Queue Details' section includes a dropdown for Queue Code (set to 'Sanction Check Queue'). The 'Sanction Seizure' section includes a dropdown for Sanction Seizure. The 'Transaction Status' section includes dropdowns for Transaction Status (set to 'Unprocessed'), Matched Status (set to 'Unmatched'), Response Status, and Reject Reason. The 'View Queue Action' section includes fields for Maker Id, Release Time, Authorization Status (set to 'Authorized'), Checker ID, and Checker Date Stamp.

3.3.4 Fedwire Broadcasts & Statements Browser Summary

You can view the broadcasts messages & statements received from network in this screen.

You can invoke the 'Fedwire Broadcasts & Statements Browser Summary' screen by typing 'PWSBRBRW' in the field at the top right corner of the application toolbar and clicking the adjoining arrow button.

You can search using one or more of the following parameters:

- Message Type (Broadcast/ Statement)
- Message ID (Broadcast:FT1000/ FT1010/ FT1090/ Statement: FT1020)
- Received Date

You can view messages based on the gpi enabled.

Once you have specified the search parameters, click 'Search' button. The system displays the records that match the search criteria.

Select a record and click on 'View Message' button to view the message received from Network.

3.3.4.1 View Message

You can view the uploaded inbound Fedwire Broadcast and Statement messages received from network by clicking the 'View Message' action button, present in the bottom of the screen. The uploaded message gets displayed.

You need to select a record and click on 'View Message' to view the message details

3.4 **Fedwire Non-Financial Service Request**

Fedwire Non-Financial Service Request supports the following service request to Fedwire and the related responses:

- Account Balance Request(FTIABAL) - To obtain current account balance
- Endpoint (Lterm) Grant Totals Request(FTI0041) - To obtain their current summary of the day's traffic associated with a given End point (Lterm)
- Detailed summary of Transfer Messages Request(FTI0043) - To obtain the details of a range of sequence numbers for the incoming or outgoing messages associated with a given endpoint (LTerm)
- Error Code Description Request(FTI0091) - To obtain detailed information for an error code and guidelines for its resolution
- Retrieval Request(FTI0051) - To obtain a copy of one or more of outgoing or incoming Fedwire Fund Service messages

3.4.1 Fedwire Service Request Generation

You can generate a Service Request in Fedwire Service Request Generation Screen by typing 'PWDFWSVC' in the field at the top right corner of the Application toolbar and clicking on the adjoining arrow button.

Fedwire Service Request Generation Detailed

New Enter Query

Host Code * Host Description

Message Type * Message Description

Message Reference * URC

Message Date YYYYMMDD Endpoint ID

Account Settlement Details Detailed Summary or Retrievals

Inquiry ABA Traffic Type

Balance Type Self Balance Start Sequence

Stop Sequence

Error Code Details

Fedwire Error Code

Maker Date Time: Mod No Record Status

Checker Date Time: Authorization Status

Exit

Host Code

System defaults the host code of logged in branch.

Message Type

Input the message Type from option list. Applicable values are:

- FTIABAL - Account Balance Request
- FTI0041 - Endpoint (Lterm) Grant Totals Request
- FTI0043 - Detailed summary of Transfer Messages Request
- FTI0091 - Error Code Description Request
- FTI0051 - Retrieval Request Message Reference

System generates 16 digit Message Reference number for the request.

URC

System generates 8 length alphanumeric User Correlated Reference for each message.

Message Date

Specify the Message Date.

Endpoint ID

Select the Endpoint ID from the LOV.

The value maintained for the system parameter FEDWIRE_ENDPOINT_ID is populated in this field provided the message Type is selected as FTI0041, FTI0043 or FTI0051.

Inquiry ABA

Select the ABA number of the branch whose balance to be retrieved. LOV lists all valid ABA numbers applicable for the bank and Host Applicable for message type FTIABAL.Traffic Type.

Select the Traffic Type as either Message Sent or Message Received. Applicable for message type FTI0043, FTI0051. Balance Type.

Select the Balance Type as either Self Balance or Master Balance. Default value is Self Balance. Applicable for message type FTIABALStart sequence.

Input the Start sequence of Input (IMAD) or Output (OMAD). Applicable for message types FTI0043 and FTI0051.

Stop Sequence

Input the Stop sequence of Input (IMAD) or Output (OMAD). Applicable for message types FTI0043 and FTI0051.

System validate START-SEQ# & STOP-SEQ# as IMAD number if the traffic type selected is 'Message sent'. For traffic type 'Message Received', only OMAD numbers are allowed.

Fedwire Error Code

Mention the error code for sending Error Code Description Request Message. Applicable for message type FTI0091.

3.4.2 Fedwire Service Request Generation Summary

You can view the Fedwire Service Request and the corresponding response message by typing 'PWSFWSVC' in the field at the top right corner of the Application toolbar and clicking on the adjoining arrow button.

The screenshot shows a web application window titled "Fedwire Service Request Generation Summary". At the top, there are links for "Search", "Advanced Search", "Reset", and "Clear All". Below this is a "Case Sensitive" checkbox. The search criteria section includes: "Authorization Status" (a dropdown menu currently showing "Authorized"), "Message Reference" (a text input field), "Endpoint ID" (a text input field), "Record Status" (a dropdown menu), "Message Type" (a text input field), and "Handoff Date" (a date picker showing "YYYY-MM-DD"). Below the search criteria is a toolbar with "Records per page" (set to 15), navigation buttons, "1 Of 1", a "Go" button, and "Lock Columns" (set to 0). The main area is a table with the following columns: Authorization Status, Record Status, Message Reference, Message Type, Endpoint ID, Handoff Date, Handoff Time, Balance Type, Branch Code, Fedwire Error Code, Host Code, and Inq. The table is currently empty. At the bottom left, there are links for "View Message" and "View Response". At the bottom right, there is an "Exit" button.

You can search using one or more of the following parameters:


- Authorization Status
- Message Reference
- Endpoint ID
- Record Status
- Message Type
- Handoff Date

Once you have specified the search parameters, click 'Search' button. The system displays the records that match the search criteria.

Select a record and click on 'View Message' button to view the message received from Network.

3.4.2.1 View Message

You can view the uploaded messages received from network by clicking the 'View Message' action button, present in the bottom of the screen. The uploaded message gets displayed.



The screenshot shows a window titled "Fedwire Outbound View Message". It contains a form with the following fields:


- Message Reference Number: 193091029500000
- Message: FT00051 X788964890BPAYMNTS1 2110519

An "Exit" button is located at the bottom right of the window.

You need to select a record and click on 'View Message' to view the message details.

3.4.2.2 View Response

You can view the responses received from network by clicking the 'View Response' action button, present in the bottom of the screen. The uploaded message gets displayed.



The screenshot shows a window titled "View Response Detailed". It contains a form with the following fields:

- Execute Query
- Message Reference Number: _____
- URC: _____
- Generated Reference: _____
- Transaction Reference No: _____
- Message: _____

An "Exit" button is located at the bottom right of the window.

4. Fedwire Drawdowns

4.1 Fedwire Drawdowns

- Fedwire Drawdown requests and payments are also known as “Reverse Wires”.
- A Fedwire Drawdown or Reverse wire is typically a B2B transaction which involves the corporate bank account holder authorizing another party, such as a vendor, to withdraw funds from their account via a wire transfer. It is called a Reverse wire because it is initiated by the recipient of the funds, rather than the sender. The applicable Business Function Code (BFC) is “DRC” i.e. Customer or Corporate Drawdown Request.
- The payment for a Drawdown request, called Drawdown payment, is similar to any other Fedwire payment (say, like CTR or BTR BFC) and settled by Fedwire Funds Service in real time and sent to the beneficiary mentioned in the Drawdown request.
- The benefit to the payer of Drawdown payment is that once they have authorized their bank in writing to respond to future draw-down requests, no work is required on the payer’s part to execute a payment.
- Drawdown requests are of particular use where the payment is high-risk (or time critical), on a recurring basis, and for a variable amount. Typical scenarios for initiating Drawdown requests include high-volume, variable amount purchases of perishable inventory, and Payroll services.
- If the inbound Drawdown request matches with the agreement and all the validations are success then the Drawdown request gets automatically processed by booking an outbound Fedwire payment transaction with BFC as “DRW”, sub-type code as “32” and Type code as “10”. Previous message identifier of Outbound drawdown payment gets populated with IMAD of inbound Drawdown request.

This section contains the following sub-sections:

- Fedwire Drawdown Authorization Agreement Detailed
- Fedwire Drawdown Request Detailed
- Fedwire Drawdown Request Manual Match Detailed
- Fedwire Drawdown Approval Queue
- Fedwire Drawdown View

4.1.1 Fedwire Drawdown Authorization Agreement

This Maintenance captures the details of Drawdown Authorization Agreement between the Payer (Originator) of a Drawdown payment and their bank i.e. ODFI (same as Sender DI) of the Drawdown payment.

This agreement maintenance captures transaction attributes necessary for validating an incoming Drawdown request and for the ODFI to process the outgoing Drawdown payment.

You can invoke the “Fedwire Drawdown Authorization Agreement Detailed” screen by typing ‘PWDRAGMT’ in the field at the top right corner of the Application toolbar and clicking on the adjoining arrow button.

Specify the following fields:

Host Code

This is auto-populated once you click on New button.

Network Code

This is auto-populated once you click on New button.

Customer No

Select the Customer Number from the LOV.

Debtor Details

Debtor Account Number

Select the Account number of the customer to be used in Drawdown payment from the LOV.

Debit Account Currency

This is auto-populated once you select the Account Number.

Debit Account Branch

This is auto-populated once you select the Account Number.

Account Name

This is auto-populated once you select the Account Number.

:4200:Beneficiary

Id Code

This field indicates the ID code of the identifier of the Beneficiary. Select one of the options such as B, C, F, U, 1, 2, 3, 4, 5 or 9.

Beneficiary ID

Specify the identification of beneficiary as per the selected ID code option.

Name

Specify the name of the beneficiary.

Address

Specify the address of the beneficiary.

Beneficiary Account

Specify Account number of the beneficiary.

Authorization Details**Sequence Type**

This field indicates if only one or multiple Drawdown requests are expected. The drop down option is One Off.

Drawdown Amount Limit

Specify the maximum limit on the USD amount of any Drawdown request from the beneficiary.

Drawdown Amount Currency

This is auto-populated once you click on New button.

Effective Date

This is auto-populated once you click on New button. Specifies the date from which this Authorization would be effective. The date may be changed to a future date also.

Expiry Date

Specifies the End date of this authorization after which it would not be valid. This is an optional field. If not specified, then it means the Authorization agreement is perpetual.

Beneficiary FI Details**Beneficiary FI ABA Number**

Select the ABA number of the Beneficiary's bank which would also be the Receiver DI of the outgoing Drawdown payment message from the LOV.

Beneficiary FI Name

Specify the Beneficiary FI Name.

Beneficiary FI Address

Specify the Beneficiary FI Address details.

Beneficiary FI Phone Number

Specify the Beneficiary FI Phone Number.

Beneficiary FI Email Address

Specify the Beneficiary FI Email Address.

4.1.1.1 Fedwire Drawdown Authorization Agreement Summary

You can invoke the “Fedwire Drawdown Authorization Agreement Summary” screen by typing ‘PWSRAGMT’ in the field at the top right corner of the Application toolbar and clicking on the adjoining arrow button.

The screenshot displays the 'Fedwire Drawdown Authorization Agreement Summary' application window. At the top, there is a search bar with the 'Advanced Search' tab selected, alongside 'Search', 'Reset', and 'Clear All' buttons. Below the search bar, a 'Case Sensitive' checkbox is present. The main area contains several search criteria fields: 'Authorization Status' (a dropdown menu), 'Record Status' (a dropdown menu), 'Host Code', 'Fedwire Network Code', 'Customer No', and 'Debtor Account Number'. Each of these fields has a magnifying glass icon to its right. Below the search fields, there is a table with the following columns: 'Authorization Status', 'Record Status', 'Host Code', 'Fedwire Network Code', 'Customer No', 'Debtor Account Number', 'Debit Account Currency', 'Debtor Account Branch', and 'Account Name'. The table is currently empty. At the bottom right of the window, there is an 'Exit' button.

You can search for the records using one or more of the following parameters:

- Authorization Status
- Record Status
- Host Code
- Network Code
- Customer No
- Debtor Account Number

Once you have specified the search parameters, click ‘Search’ button. The system displays the records that match the search criteria.

Double click a record or select a record and click on ‘Details’ button to view the detailed maintenance screen.

4.1.2 Fedwire Drawdown Request Detailed

This screen allows only Corporate Drawdown requests to be initiated for receiving Fedwire payment from a corporate account maintained with another bank (who would be the receiver of Drawdown request).

You can invoke the “Fedwire Drawdown Request Detailed” screen by typing ‘PWDOTDRC’ in the field at the top right corner of the Application toolbar and clicking on the adjoining arrow button.

The screenshot shows the 'Fedwire Drawdown Request Detailed' window. It contains various input fields for transaction details, beneficiary information, payment details, and account debited information. The 'Main' tab is selected, showing 'FI Information' and 'Pricing' sub-tabs. The 'Transaction Branch' section includes fields for Host Code, Source Code (MANL), Network Code, :3600:Business Function Code (DRC), :1510:Type Code (10), and Sub Type Code (31). The 'Transaction Reference Number' section includes fields for User Reference Number, Source Reference Number, Template Id, and a 'Save as Template' button. The 'Main' section includes 'FI Information' and 'Pricing' sub-tabs. The ':4200:Beneficiary' section includes fields for Beneficiary Account, Beneficiary Account Currency, ID Code (D), Beneficiary ID, Name, Address, and an 'Enrich' button. The 'Payment Details' section includes fields for Booking Date, Instruction Date, Activation Date, Drawdown Request Currency (USD), Drawdown Request Amount, Customer Number, Customer Service Model, Remarks, and Message Date. The ':4400:Account Debited in DrawDown' section includes fields for ID Code (D) and Identifier. The 'Receiver' section includes fields for Receiver ABA Number and Receiver Short Name. The bottom section includes fields for Maker Id, Release Time, Checker ID, Checker Date Stamp, Authorization Status, and an 'Exit' button.

Specify the following fields:

Transaction Branch

The Transaction Branch code is populated on the click of New button.

Host Code

The Host Code is populated on the click of New button.

Source Code

The Source Code is populated on the click of New button. I fixed and defaulted to MANL.

Network Code

Specify the Network Code from the LOV.

:3600:Business Function Code

This is defaulted and fixed to "DRC" i.e. Customer or Corporate Drawdown Request.

:1510:Type Code

This is defaulted and fixed to "10" (Funds Transfer).

Sub Type Code

This is defaulted and fixed to "31" (Request for Credit (Drawdown)).

Transaction Reference No

The Transaction Reference Number is generated and populated.

User Reference Number

Specify the User Reference Number.

Source Reference Number

Specify the Source Reference Number.

Template Id

Specify the Template ID to identify this template if this Save as Template flag is selected.

Save as Template

Click this flag to indicate if this Drawdown request can be saved as a Template.

4.1.2.1 Main Tab

Click the New button in the Fedwire Drawdown Request Detailed screen. The fields in the Main Tab get enabled.

The screenshot shows the 'Main Tab' of the Fedwire Drawdown Request Detailed screen. The form is organized into three main sections: **:4200:Beneficiary**, **Payment Details**, and **Receiver**. The **:4200:Beneficiary** section includes fields for **Beneficiary Account ***, **Beneficiary Account Currency**, **Id Code** (a dropdown menu with 'D' selected), **Beneficiary ID**, **Name**, and **Address**. The **Payment Details** section includes **Booking Date**, **Instruction Date**, **Activation Date**, **Drawdown Request Currency** (set to USD), **Drawdown Request Amount ***, **Customer No**, **Customer Service Model**, **Remarks**, and **Message Date**. The **Receiver** section includes **Receiver ABA Number**, **Receiver Short Name**, and **:3200:Sender's Reference**. At the bottom of the form, there are fields for **Maker Id**, **Checker ID**, **Authorization Status**, **Release Time**, **Checker Date Stamp**, and an **Exit** button.

Specify the following fields:

:4200:Beneficiary

Beneficiary Account

Account number of the Beneficiary can be input or searched and selected from LOV that is filtered on all valid Normal accounts in the system.

Beneficiary Account Currency

Currency of the selected account is populated.

Id Code

This field indicates the ID code of the identifier of the Beneficiary that is included in the Fedwire Drawdown message. This field is defaulted and fixed to option "D" (Demand Deposit Account (DDA) Number).

Beneficiary ID

Specify the Beneficiary Id.

Name

This field is defaulted with the Account name of the Beneficiary account number, on Save.

Address

This field is defaulted with the address of the Customer of the selected Beneficiary account number on the click on Save button. Alternatively, you can input the address before saving the transaction.

Payment Details

Booking Date

This is defaulted as application server date.

Instruction Date

Specify the Instruction (Value) date of the payment, as instructed by the customer. This can be the current date or any date in the future. Back valued payments are not allowed.

Activation Date

Specify the date on which the transaction is processed. This date will be same as the Revised Instruction date.

Drawdown Request Currency

This is defaulted and fixed to USD.

Drawdown Request Amount

Specify the Drawdown amount requested. This amount is populated in tag {2000} of outgoing Drawdown request.

Customer No

The system indicates the customer number of the Beneficiary of the Drawdown request.

Customer Service Model

Specify the Service model derived for the customer.

Remarks

Specify remarks for the outgoing Drawdown request.

Message Date

This date is derived and populated as part of processing the transaction. This would be same as the Revised Instruction date.

:4400:Account Debited in DrawDown**ID Code**

This field indicates the ID code of the identifier of the Payer of the Drawdown payment. This field is defaulted and fixed to option "D" (Demand Deposit Account (DDA) Number).

Identifier

Specify the Payer's account number.

Name

Specify the account name of the Payer's account number.

Address

Specify the address of the Payer's account. 3 lines of Address details each containing up to 35 characters can be specified.

Receiver**Receiver ABA Number**

Specify the ABA number of the Receiver DI or search and select from the LOV filtered on ABA numbers from Fedwire directory maintenance.

Receiver Short Name

This is populated upon the selection of the ABA number from the 'Telegraphic Name' field of the Fedwire directory.

:3200:Sender's Reference

This field is populated with Transaction Reference number generated for this Drawdown request when it is manually initiated.

4.1.2.2 FI Information Tab

Click the FI Information Tab in the Fedwire Drawdown Request Detailed screen. The fields in the Main Tab get enabled.

The screenshot shows the 'FI Information' tab selected in the 'Main', 'FI Information', and 'Pricing' tabs. The form is divided into four main sections:

- :6100:Receiver FI Information**: A large text area for receiver information.
- :6110:Drawdown Debit Account Advice Information**: Includes an 'Advice Code' dropdown menu (set to 'LTR') and an 'Additional Information' text area.
- :6410:Beneficiary Advice Information**: Includes an 'Advice Code' dropdown menu (set to 'LTR') and an 'Additional Information' text area.
- :6500:FI to FI Information**: A text area for FI to FI information.

At the bottom, there is a light blue bar containing fields for 'Maker Id', 'Release Time', 'Checker ID', 'Checker Date Stamp', 'Authorization Status', and a 'Cancel' button.

Specify the following fields:

:6100:Receiver FI Information

This is a free format field that can be used to specify any information specifically meant for the Receiver of the Drawdown request. These details can be specified in 1 line of up to 30 characters, plus up to 5 lines of 33 characters each.

:6110:Drawdown Debit Account Advice Information

Advice Code

Select one of the values like LTR, PHN, TLX or WRE.

Additional Information

Specify any additional info about the Advice in 1 line of up to 26 characters, plus up to 5 lines of 33 characters each.

:6410:Beneficiary Advice Information

Advice Code

Select one of the values like LTR, PHN, TLX, HLD or WRE.

Additional Information

Specify any additional info about the Advice in 1 line of up to 26 characters, plus up to 5 lines of 33 characters each.

:6500:FI to FI Information

This is a free format field that can be used to input any additional info that could not be accommodated in {6100}.

4.1.2.3 Pricing Tab

This tab displays the pricing details of the charges computed by system based on the transaction attributes in the Main tab. These details are populated on clicking Enrich button in the Main tab before saving the transaction, or as part of processing on saving the transaction without clicking Enrich.

Pricing Code	Component Name	Pricing Currency	Amount	Waived	Debtor Account Currency
--------------	----------------	------------------	--------	--------	-------------------------

Maker Id

Release Time

Checker ID

Checker Date Stamp

Authorization Status

Exit

The below mentioned attributes will be available in the Pricing tab:

Pricing Code

The system displays the Pricing Code.

Component Name

The system displays the Name of the pricing component applicable for the transaction for which charges are computed.

Pricing Currency

The system displays the Currency in which the charge amount is calculated for the Pricing component.

Amount

The system displays the charge amount calculated for each pricing component.

Waived

This field if checked indicates that the charge is waived for the pricing component.

Debtor Account Currency

The system displays the Debtor Account Currency.

4.1.2.4 Fedwire Drawdown Request Summary

You can invoke the “Fedwire Drawdown Request Summary” screen by typing ‘PWSOTDRC’ in the field at the top right corner of the Application toolbar and clicking on the adjoining arrow button.

The screenshot shows the 'Fedwire Drawdown Request Summary' application window. At the top, there is a search bar with a magnifying glass icon and buttons for 'Search', 'Advanced Search', 'Reset', and 'Clear All'. Below the search bar, the text 'Case Sensitive' is displayed. The main area contains several input fields for search criteria: 'Transaction Reference No', 'Instruction Date' (with a date picker), 'Network Code', 'Customer No', 'Receiver ABA Number', 'Booking Date' (with a date picker), 'Activation Date' (with a date picker), 'User Reference Number', 'Customer Service Model', and 'Source Reference Number'. Each field has a small blue icon to its right. Below the input fields, there is a table with columns: 'Transaction Reference No', 'Booking Date', 'Instruction Date', 'Activation Date', 'Network Code', 'User Reference Number', 'Customer No', and 'Customer'. The table is currently empty. At the bottom right of the window, there is an 'Exit' button.

You can search for the records using one or more of the following parameters:

- Transaction Reference No
- Instruction Date
- Network Code
- Customer No
- Receiver ABA Number
- Booking Date
- Activation Date
- User Reference Number
- Customer Service Model
- Source Reference Number

Once you have specified the search parameters, click ‘Search’ button. The system displays the records that match the search criteria.

Double click a record or select a record and click on ‘Details’ button to view the detailed maintenance screen.

4.1.3 Fedwire Drawdown View

You can invoke the 'Fedwire Drawdown View' screen by typing 'PWDDDRVW' in the field at the top right corner of the application toolbar and clicking the adjoining arrow button. Click new button on the Application toolbar.

- From this screen, click Enter Query. The Transaction Reference field gets enabled which opens an LOV screen.
- Click the Fetch button and select the required value.
- Along with the transaction details in the Main and Pricing tabs you can also view the Status details for the following:
 - External System Status
 - Transaction Status

View Queue

This button launches the corresponding Queue screen, where the transaction is currently held. The Queue screen will be launched in query mode, listing this transaction alone.

- Click Execute Query to populate the details of the transaction in the Fedwire Drawdown View screen.

For more details on Main, Pricing tabs refer to 'PWDOTDRC' screen details above.

4.1.3.1 View Queue Action Log

You can view all the queue actions for the respective transaction initiated. You can invoke this screen by clicking the 'View Queue Action' button in View screen, where the Transaction Reference Number is auto populated and related details are displayed.

View Queue Action Log

Enter Query

Transaction Reference Number Network Code

1 Of 1 Go

Transaction Reference Number	Action	Remarks	Queue Code	Authorization Status	Maker Id	Maker Date Stamp
------------------------------	--------	---------	------------	----------------------	----------	------------------

View Request Message View Response Message

Exit

For more details on the fields and screen, refer to section 2.2.2.2

4.1.3.2 UDF Tab

You can invoke this screen by clicking 'UDF' tab in the screen.

Fields

Fields

1 Of 1 Go

Field Label	Field Value
-------------	-------------

Ok Exit

4.1.3.3 MIS Tab

You can invoke this screen by clicking 'MIS' tab in the screen.

MIS Details

Transaction Reference Number * MIS Group Default

Transaction MIS Composite MIS

Ok Exit

4.1.3.4 All Messages

Click the "All Messages" link in the View screen to invoke this sub-screen. For more details on fields, refer to section 2.2.7.5 and 2.2.7.6.

All Messages

Execute Query

Contract Reference

1 Of 1 Go

DCN *	Message Type	SWIFT Message Type	Direction	Value Date	Message Status	Test Statu

Message

Cancel

4.1.3.5 Accounting Entries

During payment transaction processing, the accounting entries whose for which hand -off status is pending are posted to a JMS Queue. Once these entries are posted in the queue, the status is updated as handed off.

If the Accounting system and the ECA system are not the same, an update is sent to the ECA system as well while doing the accounting handoff. Any amount block in the customer account done during External credit approval can be released on receiving accounting update.

Click the “Accounting Entries” tab in the view screen to invoke the screen. For details on the

fields refer to section 2.2.7.7.

4.1.3.6 Fedwire Drawdown View Summary

You can invoke the ‘Fedwire Drawdown View Summary’ screen by typing ‘PWSDDRVW’ in the field at the top right corner of the application toolbar and clicking the adjoining arrow button.

You can search using one or more of the following parameters:

- Transaction Reference Number
- Host Code
- Identifier
- Sender/Receiver Di ABA Number
- Sender Reference
- BFC
- Transaction Status

Once you have specified the search parameters, click 'Search' button. The system displays the records that match the search criteria.

Double click a record or select a record and click on 'Details' button to view the detailed maintenance screen.

4.1.4 **Fedwire Drawdown Request Manual Match**

If the system cannot match a Processed Drawdown payment to Drawdown request sent earlier then you can manually match both from a New Manual match screen, called "Fedwire Drawdown Request Manual Match".

You can view the details of a Fedwire Drawdown Request Manual Match Detailed in the "Fedwire Drawdown Request Manual Match Detailed" Screen. You can invoke the "Fedwire Drawdown Request Manual Match Detailed" screen by typing 'PWDDDMAT' in the field at the top right corner of the Application toolbar and clicking on the adjoining arrow button.

Fedwire Drawdown Request Manual Match Detailed

New Enter Query

Host Code *

Drawdown Request Reference *

Drawdown Payment Reference

Maker ID Checker ID Authorization Status

Maker Date Stamp Checker Date Stamp Exit

Specify the following fields:

Host Code

This is auto-populated once you click on New button.

Drawdown Request Reference

Select the Transaction Reference of Drawdown request. The LOV is filtered on transaction ref. numbers of only those Drawdown requests that are not linked with any Drawdown payment.

Drawdown Payment Reference

Select the Transaction Reference of Drawdown payment transaction. The LOV is filtered on transaction ref. numbers. of only those Drawdown payments that are not linked with any Drawdown requests.

4.1.4.1 Fedwire Drawdown Request Manual Match Summary

You can invoke the “Fedwire Drawdown Request Manual Match Summary” screen by typing ‘PWSDDMAT’ in the field at the top right corner of the Application toolbar and clicking on the adjoining arrow button.

The screenshot shows a web application window titled "Fedwire Drawdown Request Manual Match Summary". The interface includes a search bar with a "Search" button and options for "Advanced Search", "Reset", and "Clear All". Below the search bar, there are input fields for "Authorization Status" and "Drawdown Request Reference", with a "Case Sensitive" checkbox. A table with the following columns is displayed: "Authorization Status", "Host Code", "Drawdown Request Reference", and "Drawdown Payment Reference". The table is currently empty. At the bottom right of the window is an "Exit" button.

You can search for the records using one or more of the following parameters:

- Authorization Status
- Drawdown Request Reference

Once you have specified the search parameters, click 'Search' button. The system displays the records that match the search criteria.

Double click a record or select a record and click on 'Details' button to view the detailed maintenance screen.

4.1.5 Fedwire Drawdown Approval Queue

In case of failure of non-critical agreement validations, the Drawdown request is moved to a New exception queue called “Fedwire Drawdown Approval” queue for decision by Operational users.

You can invoke the ‘Fedwire Drawdown Approval Queue’ screen by typing ‘PQSFWDDQ’ in the field at the top right corner of the application toolbar and clicking the adjoining arrow button. Click New button on the Application toolbar.

The screenshot shows the 'Fedwire Drawdown Approval Queue' application window. At the top, there is a title bar with the window name and standard OS controls. Below the title bar is a search bar with buttons for 'Search', 'Advanced Search', 'Reset', and 'Clear All'. The main area is divided into two columns of search criteria, each with a magnifying glass icon. The left column includes 'Queue Reference Number', 'Input Cycle Date' (with a date picker), 'Transfer Currency', 'Sender Reference', 'Beneficiary Identifier', and 'Authorization Status' (a dropdown). The right column includes 'Sender DI ABA Number', 'IMAD', 'Amount Requested', 'Drawdown Debit Account', 'Transaction Branch', and 'Network Type Code'. Below the search criteria is a table with columns: 'Queue Reference Number', 'Sender DI ABA Number', 'Input Cycle Date', 'IMAD', 'Transfer Currency', 'Amount Requested', 'Sender Reference', and 'Drawdown D'. The table is currently empty. At the bottom of the window, there is a navigation bar with links: 'View Drawdown Request', 'Release', 'Reject', 'Authorization', and 'View Queue Action'. An 'Exit' button is located in the bottom right corner.

You can search using one or more of the following parameters:

- Queue Reference Number
- Input Cycle Date
- Amount Requested
- Drawdown Debit Account
- Transaction Branch
- Sender DI ABA Number
- IMAD
- Transfer Currency
- Sender Reference
- Beneficiary Identifier
- Authorization Status
- Network Type Code
- Network Code

Once you have specified the search parameters, click ‘Search’ button. The system displays the records that match the search criteria:

The following actions can be performed for transactions in Business Override queue:

Actions	Functions
View Drawdown Request	You can view the selected transaction details.
Release	The system processes the Drawdown request
Reject	The system generates the Drawdown Refusal message. While rejecting the Drawdown request, it is mandatory to input Remarks for specifying reason for rejection. This would be included in the generated Drawdown Refusal message. The Remarks text would be allowed up to 195 characters.
Authorization	You can manually move the transaction for processing on next working day.
View Queue Actions	Displays all queue activities performed for the selected transaction. This action allows you to view key details of the selected Drawdown request.
View Transaction	You can view the selected transaction details.

5. Fedwire Processing

5.1 ACK/NAK Processing

5.1.1 Positive Response Processing

For every Outbound message sent, Fedwire Fund Service sends the positive acknowledgement for accepted messages in FTFR12 message format.

The incoming positive response is in the following format:

Field Name	Field Name	Type	Description
URC	8	AN	User Response Correlation is same as in the corresponding outbound message
INPUT_CYCLE_DATE	4	N	MMDD format; cycle date of outbound message
INPUT_SOURCE	8	AN	End point ID of the bank
INPUT_SEQUENCE_NUMBER	6	N	Sequence Number provided for the outbound message
INPUT_DATE_N_TIME	8	N	Calendar date MMDD and time HHMM based on Eastern time when the message was received by Fedwire Fund Service
INPUT_FRB_APPLICATION_ID	4	AN	Fedwire service site which processed the message FT01,FT02 or FT03
MSG_STATUS_CD	1	N	2-Accepted with fund transfer accounting 7-Accepted without accounting (Example type/subtype code 1090)
MSG_DUPLICATION_CD	1	A	" " :Original message 'P' :Possible duplicate message This value will be same as the one for the outbound message sent
OUTPUT_CYCLE_DATE	4	N	The cycle date for FFS (MMDD)
OUTPUT_SOURCE	8	AN	Unique endpoint of the receiver (Bank)
OUTPUT_SEQUENCE_NUMBER	6	N	The sequence number generated by Fedwire service. It will be starting with 1 for every cycle and right justified with leading zeroes.

Field Name	Field Name	Type	Description
OUTPUT_DATE_N_TIME	8	N	Calendar date MMDD and time HHMM based on Eastern time on which the advice is generated
OUTPUT_FRB_APPLICATION_ID	4	AN	FT01,FT02 or FT03
INPUT_CYCLE_YEAR	4	N	The cycle & year (CCYY)when the message was sent
OUTPUT_CYCLE_YEAR	4	N	The cycle & year (CCYY)when the message was generated
FILLER	24	ANS	For future use (spaces)

On upload of acknowledgement, system matches the URC & input sequence number received with the URC & sequence number generated for the outbound message.

Network status gets marked as Accepted/Accepted without accounting based on MSG_STATUS_CD received in the acknowledgement.

5.1.2 **Negative Response Processing**

The negative acknowledgement is a Reject message from network which contain the copy of the original message with error tag {1130}.

- Error Category- Alphanumeric 1 (E-Data Error)
- F-Insufficient Balance X-Duplicate IMAD
- H-Accountability Error
- W-Cutoff hour timing error
- I-In process/Intercepted)
- Error code Alphanumeric 1
- Error Description Alphanumeric & special characters 0-35

On upload of a reject message, Network status of the message gets marked as rejected. You can get the number of messages accepted/rejected by the network in the dashboard.

Based on Network status, messages/Transactions can be fetched in the Outbound Fedwire message browser/Outbound Fedwire View summary screens The applicable values are 'ACK Received', 'ACK-without accounting' & 'NAK Received'.

5.2 **Fedwire Inbound Reversal Request Processing**

Reversal Transaction

Once the inbound message is identified as a reversal request message (using sub type code '01' or '07' for BFCs CTR/BTR/CTP & SVC], a reversal transaction gets created.

A new reversal reference number gets generated. Reversal Request date is populated with the current processing date. Host code and branch code are populated based on the Receiver ABA number.

Transaction Status is populated as 'Unprocessed'.

Match Criteria

The received reversal request is matched with an Inbound Fedwire transaction using Tag {3500} - Previous Message Identifier. Matching criteria is as below.

- {3500} Previous Message Identifier - IMAD of original incoming transaction

Below fields are also considered for matching:

- Sender DI ABA Number Sender DI of Original incoming transaction
- Type Code Type Code of Original incoming transaction
- Amount Transfer Amount of the Original incoming transaction
- Tag {4200} Beneficiary ID code/Identifier with original incoming transaction
- Tag {5000} Originator ID code/identifier with original incoming transaction

Match status is updated as 'Matched' if the original transaction is matched successfully. Otherwise, the match status is updated as 'Unmatched'.

A new record is logged into the Inbound Fedwire Reversal Request Match / Response Queue populating queue status as 'Pending'.

5.3 Fedwire Reversal Queue - Accept User action processing

Reversal response processing gets triggered upon 'Accept' user action.

- A new reference - Reversal Response reference gets generated.

ECA Processing

The transaction is sent for ECA with credit account as the account and with the original transaction amount as amount for blocking. The reference number sent in the ECA is the original transaction reference. The transaction is marked as 'Exception', Queue status is marked as 'ECA' till the response is received.

Once the response is received from ECA system, the reversal processing proceeds further.

If the response is successful, then:

- Accounting Handoff is prepared.
- Original incoming transaction credit account is the debit account of reversal transaction.

DRLQ

Account Template for Debit Liquidation code is picked from Fedwire Network Currency preference Detailed (PWNDNCPRF) for transaction type 'Outbound'.

CRLQ

Account Template for Credit Liquidation code is picked from Fedwire Network Currency preference Detailed (PWNDNCPRF) for transaction type 'Outbound'.

Message Generation

Reversal response message is generated with sub type code as '02' if sub type code of reversal request is '01' (or) with '08' if sub type code of original reversal request is '07'. If the sub type code of the reversal request is neither '01' nor '07', then the sub type code is populated as '02' if original inbound transaction activation date is today. Otherwise, the sub type code is populated as '08'.

BFC is populated with the original message BFC.

6. Fedwire gpi Processing

This section contains all the maintenances pertaining to gpi and required for gpi. Below are the existing gpi Maintenances which are applicable for the payment types - Fedwire.

Following are the required maintenances for gpi:

- SWIFT gpi Static Preferences (PXDGPISIT). Refer to *Cross_Border User Guide section(4.1.1)* for more details.
- SWIFT gpi Host Preferences (PXDGPIPF). Refer to *Cross_Border User Guide section(4.1.4.1)* for more details.
- SWIFT gpi Directory (PMDGPIDR). Refer to *Cross_Border User Guide section(4.1.5)* for more details.

For more details on the above maintenances refer to CrossBorder_Payments User Guide section(4.1).

Following points need to be considered during Fedwire gpi processing:

1. RMA/RMA+ Validation for Tracker should not be performed for exchange of gCCT/gCOV confirmations.
2. In Branch Core Parameters screen (STDCRBRN), default BIC value is gpi Participant ID(11-Character BIC) of the processing branch.

6.1 Outbound Fedwire Payments - gpi Processing

6.1.1 SWIFT STP Changes

Following changes are done to the Outbound Fedwire payment transaction creation processing from an Incoming SWIFT message:

- For Outbound Fedwire payment, UETR field populates with the Tag 121 of incoming SWIFT MT103/ MT202COV / MT205 COV messages.
- For the incoming SWIFT MT103 / MT202 COV / MT205 COV message whose Tag 111 value is '001', the 'Incoming gpi flag' gets automatically checked else unchecked.

6.1.2 Outbound gCCT Processing

gpi enabled Transaction:

When you select the Business Function Code as 'CTP', Local Instrument value [{3610}] as 'COVS', and Type & Subtype(combined) value as '1000' (Funds Transfer/Basic Funds Transfer) (or) '1600'(Settlement Transfer/Basic Funds Transfer), system performs below validation:

- Checks whether 'gpi Processing Enabled' is set to 'Y' at host level (PXDGPIPF).
- When the 'gpi Processing Enabled' flag is set to 'Y', then system checks Sender BIC (Processing branch BIC – Default BIC (11 Character) linked in Branch Core Parameters screen (STDCRBRN)) and Transfer Currency combination is present in SWIFT gpi Directory (PMDGPIDR).
- When 'Yes', then the transaction is set as 'gpi enabled' and is processed as a SWIFT gpi transaction.
- When 'No', then the 'gpi enabled' flag is set as 'No' and the transaction is processed as normal SWIFT transaction.

Fedwire message generation:

- At the transaction level, if the 'gpi Enabled' flag is 'Yes' and if the charging method is BEN or SHA, then the tags {3620} and {3700} populates as below

Tag	Tag Name	Element Name	Format	Population Logic
3620	Payment Notification	Element 01 – Notification Indicator	1 Character	Value '3' hardcoded gets populated
3620	Payment Notification	Element 03 – Contact Name	140 Characters	UETR value gets populated
3700	Charges	Senders Charges	15 Characters	Sender Charges information received in the Inbound SWIFT message gets populated. If there are no sender charges applicable, then populate this field with a value "USD0,00"

System populates the tags {3620} and {3700} values as below when the charging method is OUR

Tag	Tag Name	Element Name	Format	Population Logic
3620	Payment Notification	Element 01 – Notification Indicator	1 Character	Value '4' hardcoded gets populated
3620	Payment Notification	Element 03 – Contact Name	140 Characters	UETR value gets populated
3620	Payment Notification	Element 06 – Contact Fax Number	35 Characters	Charges information if applicable for the transaction gets populated

Tag {3700} should not get populated when charging method is OUR

Note

For 'gpi Enabled' Outbound Fedwire transactions, Network cutoff time validation logic remains same as existing.

6.1.3 **Outbound gCOV Processing**

gpi enabled Transaction:

When you select the Business Function Code as 'CTP', Local Instrument value {{3610}} as 'COVS', and Type & Subtype(combined) value as '1000' (or) '1600', system performs below validation:

- Checks whether 'gpi Processing Enabled' is set to 'Y' at host level (PXDGPIPF)
- When the 'gpi Processing Enabled' flag is set to 'Y', then system checks Sender BIC (Processing branch BIC – Default BIC (11 Character) linked in Branch Core Parameters screen (STDCRBRN)) and Transfer Currency combination is present in SWIFT gpi Directory (PMDGPIDR)
- When 'Yes', then the transaction is set as 'gpi enabled' and is processed as a SWIFT gpi transaction.
- When 'No', then the 'gpi enabled' flag is set as 'No' and the transaction is processed as normal SWIFT transaction.

Fedwire message generation:

At the transaction level, if the 'gpi Enabled' flag is 'Yes', then the tag {3620} populates as below:

§Tag {3620} Element 01 Payment Notification Indicator populates with a value '3'

§Tag{3620} Element 03 Contact Name populates with UETR value

Tag	Tag Name	Element Name	Format	Population logic
3620	Payment Notification	Element 01- Notification Indicator	1 Character	Value '4' hardcoded gets populated
3620	Payment Notification	Element 03- Contact Name	140 Characters	UETR value gets populated

Note

For 'gpi Enabled' Outbound Fedwire transactions, Network cutoff time validation logic remains same as existing.

6.1.4 Outbound gpi Confirmations

For the Outbound Pass-through Fedwire gpi payments, if the transaction level 'gpi Enabled' flag set to 'Yes' then system generates SWIFT gpi Confirmations (MT199 for gCCT/MT299 for gCOV) and populates the Confirmation messages fields as listed below:

- Receiver field value gets updated with the value of Tracker BIC maintained in the gpi Host preferences maintenance (PXDGPIPF)
- Field 111 of Block 3 populates with '001' (Service type identifier for gCCT/gCOV)
- Field 121 of Block 3 will be populated with UETR of the transaction
- Field 20 populates with the Fedwire Transaction Reference
- Field 21 populates with Field 20 of MT103 for gCCT confirmation and with Field 20 of MT202 COV/MT205 COV for gCOV confirmation message
- Following details gets populated for Field 79 of the gCCT/gCOV confirmation messages:
 - Line 1 populates with date & time along with UTC offset
 - Line 2 populates with confirmation statuses code and reason code depending on the transaction processing status [Refer table]

Processing status	Message generated	Status Code / Reason Code	Date & Time details	Payment Processing Status [PXDGPIST]	In Progress Codes [PXDGPIST]
Payment Processed & forwarded as a gpi message to a gpi agent	On successful receipt of ACK message for outbound Fedwire message	ACSP/G000	Message generation Date & time	NA	NA
Outbound payment Processed & forwarded as a gpi message to a non-gpi agent	On successful receipt of ACK message for outbound Fedwire message	ACSP/G001	Message generation Date & time	NA	NA
Pending by EOD in process exceptions queues(including Warehouse queue)	By EOD, transaction is pending in any exception queue	ACSP/G002	Message generation Date & time	IN PROGRESS	PENDING CREDIT

Cancelled	On successful cancellation action	RJCT	Message generation Date & time	REJECTED	NA
Sanctions Seized	On Sanctions Seizure	RJCT	Message generation Date & time	REJECTED	NA

- Line 3 populates with Branch default BIC followed by Intermediary FI BIC if available (or) by Beneficiary FI BIC.
- Line 4 populates with settlement amount [Final amount deducting charges if any].
- For gCCT confirmation message:
 - Line 5 : EXCH, Original Currency, Transfer Currency & Exchange Rate should not be populated
 - Charge deduction : If there is no charge then system populates Zero charge amount else charge amount details gets populated

Note

- System will not perform RMA/RMA+ validation on the Tracker BIC.
 - At EOD, confirmation message should get generated by the auto job 'PQDPRQUE'.
-

6.1.5 Inbound gpi Confirmations

- System links the Incoming gpi confirmation messages (gCCT/gCOV) with the original Outbound Fedwire transaction. From Block 3, Matching criteria happens as follows
 - 121: UETR of Outbound Fedwire Transaction = 121: UETR of gpi confirmation
- Once the match is successful, system parses the message and the same should be stored to display the confirmations at the Outbound transaction view screen (PWDOVIEW)

6.2 Inbound Fedwire Payments - gpi Processing

6.2.1 Inbound gCCT & gCOV Processing

Following changes are done to the Inbound Fedwire payment transaction creation processing from an Inbound Fedwire message to populate gpi related fields.

Incoming gpi:

This field updates to 'Y' once the below conditions met.

In Customer Transfer (or) Cover Transfer message , Tag {3600} value is 'CTP' / Tag {3610} is not present (or) Tag {3610} is present and value is 'COVS' in Tag {3620} Payment notification , the Element 01 Notification Indicator contains either a value either '3' or '4'.

UETR Population:

The Tag {3620} 'Payment notification - Element 03' receives the UETR value and populates the same in the Inbound Fedwire transaction UETR field.

The above populated value gets converted to lower case.

gpi Enabled flag:

The 'gpi Enabled' field sets to 'Y' once the below conditions are satisfied for the Inbound Customer Transfer ('CTP') or Cover Transfer ('CTP COVS') Fedwire payment.

Host level 'gpi Processing Enabled' flag value is 'Y' (PXDGPIPF).

SWIFT gpi Directory (PMDGPIDR) has the maintenance of Processing Branch BIC (Default BIC: 11 Character which is linked in Branch Core Parameters screen (STDCRBRN)) and Transfer Currency values.

The Tag {3620} 'Payment notification – Element 01' related 'Notification Indicator' field contains either a value '3' or '4'.

The 'gpi Enabled' field sets to 'Confirm' once the below conditions are satisfied for the Inbound Customer Transfer ('CTP') or Cover Transfer ('CTP COVS') Fedwire payment.

Host level 'gpi Processing Enabled' flag value is 'Y' (PXDGPIPF).

SWIFT gpi Directory (PMDGPIDR) has the Processing Branch BIC (Default BIC : 11 Character – linked in Branch Core Parameters screen (STDCRBRN) value should be gpi Customer which is not the gpi Agent for the Transfer Currency.

The Tag {3620} 'Payment notification – Element 01' related 'Notification Indicator' field should have either a value '3' or '4'.

6.2.2 Outbound gpi Confirmations

For the Inbound Fedwire gpi payments, if the transaction level 'gpi Enabled' flag set to 'Yes' then system generates SWIFT gpi Confirmations (MT199 for gCCT/MT299 for gCOV) and populates the Confirmation messages fields as listed below:

- Receiver field value gets updated with the value of Tracker BIC maintained in the gpi Host preferences maintenance (PXDGPIPF)
- Field 111 of Block 3 populates with '001' (Service type identifier for gCCT/gCOV)
- Field 121 of Block 3 will be populated with UETR of the transaction
- Field 20 populates with the Fedwire Transaction Reference
- If the Inbound Fedwire message has Sender's reference value then only the system populates the Field 21 with the Sender's Reference value received in Tag {3320} else Field 21 should not get populated

Following details gets populated for Field 79 of the gCCT/gCOV confirmation messages:

- Line 1 populates with date & time [Refer table below] along with UTC offset
- Line 2 populates with confirmation statuses code and reason code depending on the transaction processing status [Refer table]

Processing status	Message generated	Status Code / Reason Code	Date & Time details	Payment Processing Status [PXDGPIS]	In Progress Codes [PXDGPIS]
Processed & credited to beneficiary's account	On accounting completion	ACSC	Credit value date & current time	PROCESSED	NA
Pending by EOD in process exceptions queues (including Warehouse queue)	By EOD, transaction is pending in any exception queue	ACSP/G002	Message generation Date & time	IN PROGRESS	PENDING CREDIT
Cancelled from any exception queue	On successful cancellation action	RJCT	Message generation Date & time	REJECTED	NA
Sanctions Seized	On Sanctions Seizure	RJCT	Message generation Date & time	REJECTED	NA

- Line 3 populates with Branch default BIC.
- Line 4 populates with settlement amount [Final amount deducting charges if any].
- For gCCT confirmation message:
 - Line 5 : EXCH, Original Currency, Transfer Currency & Exchange Rate should not be populated
 - Charge deduction : If there is no charge then system populates Zero charge amount else charge amount details gets populated

Note

- System will not perform RMA/RMA+ validation on the Tracker BIC.
 - At EOD, confirmation message should get generated by the auto job 'PQDPRQUE'.
-

6.2.3 Inbound gpi Confirmations

- System links the Incoming gpi confirmation messages (gCOV) with the Inbound Fedwire transaction when it can't find any matching Outbound Fedwire transaction. From Block 3, Matching criteria happens as follows
 - 121: UETR of Inbound Fedwire Transaction = 121: UETR of gpi confirmation

Once the match is successful, system parses the message and the same should be stored to display the confirmations at the Inbound transaction view screen (PWDIVIEW).

7. Function ID Glossary

P

PMDFWDIR	2-8	PWDRAGMT	4-2
PMDFWUPD	2-10	PWDREVRS	3-36
PMSFWDIR	2-9	PWDSVCME	3-41
PQSFREVQ	3-68, 3-70, 3-79	PWSBRBRW	3-80
PQSFWDDQ	4-17	PWSDDMAT	4-16
PWDDDMAT	4-15	PWSDDRvw	4-14
PWDDDRVW	4-11	PWSFDCST	2-14
PWDFDICN	2-12	PWSFWSVC	3-84
PWDFDOCN	2-11	PWSISMVW	3-78
PWDIREVW	3-69, 3-70, 3-78, 3-79	PWSITONL	3-55
PWDISMVW	3-77	PWSIVIEW	3-67
PWDITONL	3-44	PWSNCPRF	2-7
PWDIVIEW	3-56	PWSNWPRF	2-4
PWDNCPRF	2-5	PWSOTDRC	4-10
PWDNWPRF	2-2	PWSOTONL	3-19
PWDOTDRC	4-4, 4-11	PWSOTREV	3-35
PWDOTONL	3-1	PWSRAGMT	4-4
PWDOTREV	3-31	PWSREVRS	3-40
PWDOVIEW	3-20	PWSSVCBR	3-73
		PWSSVCME	3-43