

**Oracle FLEXCUBE Universal Banking
Integration Guide**

Oracle Banking Origination

Release 14.5.4.0.0

Part Number F54319-01

February 2022

Oracle FLEXCUBE Universal Banking Integration Guide

Oracle Financial Services Software Limited

Oracle Park

Off Western Express Highway

Goregaon (East)

Mumbai, Maharashtra 400 063

India

Worldwide Inquiries:

Phone: +91 22 6718 3000

Fax: +91 22 6718 3001

<https://www.oracle.com/industries/financial-services/index.html>

Copyright © 2021, 2022 Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are “commercial computer software” pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited. The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Contents

1	About this manual	1
1.1	Purpose	1
1.2	Audience	1
1.3	List of Topics	1
2	Integration Guide	2
2.1	Introduction.....	2
2.2	Prerequisite	2
2.3	Maintenance for Oracle FLEXCUBE Universal Banking	2
2.4	Maintenance for Oracle Banking Origination	5

1 About this manual

1.1 Purpose

This guide is to help with Integration of Oracle Banking Origination Product with Oracle FLEXCUBE Universal Banking acting as the backend Product Processor.

1.2 Audience

This guide is primarily intended for the following user/user roles:

Table 1: Audience

Role	Function
Implementation and IT Staff	Implementation and maintenance of the software

1.3 List of Topics

Table 2: Topics

Topics	Description
Integration Guide	This topic helps you to integrate Oracle Banking Origination with Oracle FLEXCUBE Universal Banking.

2 Integration Guide

2.1 Introduction

You can integrate Oracle Banking Origination with Oracle FLEXCUBE Universal Banking acting as the backend Product Processor through Oracle Banking Routing Hub. This document briefs you about the specific steps needed for integration of these two products and specific maintenances.

2.2 Prerequisite


Specify **User Id** and **Password**, and login to **Oracle FLEXCUBE Universal Banking Home** screen.

2.3 Maintenance for Oracle FLEXCUBE Universal Banking

Gateway setup should be done in Oracle FLEXCUBE Universal Banking for particular source system (Oracle Banking Origination) by doing maintenance in the below mentioned screens.


1. CODSORCE – Upload Source Maintenance

Figure 1: Upload Source Maintenance



2. CODUPLDM – Upload Source Preferences Maintenance – For modules CL and ST

Figure 2: Upload Source Preferences Maintenance



3. GWDETSYS – External System Maintenance

Figure 3: External System Maintenance

The screenshot displays the 'External System Maintenance' window. It includes a 'Save' button at the top left. The 'External System' section shows 'RPM' as the system name and 'RPM_EXTERNAL_SYSTEM' as the description. The 'Correlation Pattern' is set to 'Message ID'. The 'Message Exchange Pattern' section shows 'Request Message' and 'Response Message' both set to 'Full Screen', with a checkbox for 'XSD Validation Required' checked. The 'Queue' section shows 'Default Response Queue' and 'Dead Letter Queue' fields. The 'External System Queues' section shows a table with two columns: 'In Queue' and 'Response Queue'. The table contains two rows: 'MDB_QUEUE' and 'MDB_QUEUE_RESPONS'.

4. GWDETFUN – External System Functions – for below function and actions.

Table 4: Function IDs

Function ID	Action
STGCUSAC	NEW
STGCUSTD	NEW
STQTDSIM	VIEW
CLGACCNT	NEW
CLGSIMNT	VIEW
CLQPRMNT	VIEW
CLVPRMNT	VIEW
STQACLIC	VIEW
STQACUVL	VIEW
STVACCLS	VIEW
STGCRLIB	NEW
STQLMBAL	VIEW
STGCOLAT	NEW
STGCRLIK	NEW

Figure 4: External System Functions

The screenshot shows the 'External System Functions' window. It contains a form with the following fields: External System (RPM), Function (STGCUSAC), Action (NEW), Service Name (FCUSSAccService), and Operation Code (CreateCustAcc). A description field shows 'RPM EXTERNAL SYSTEM'. A checkbox for 'Bulk SMS Check' is present. An 'Information Message' dialog box is displayed in the center, stating 'Record Successfully Saved and Authorized'. The bottom status bar shows 'Maker ANILG2', 'Checker ANILG2', 'Date Time: 2020-03-26 13:13:39', 'Mod No 1', 'Record Status Open', and 'Authorization Status Authorized'. Buttons for 'New', 'Copy', 'Close', 'Print', 'Enter Query', and 'Exit' are visible.

5. SMDROLD – Role Definition – The function ids in above Table 4 needs to be added to the correct role. This role needs to be mapped with Oracle FLEXCUBE Universal Banking user which is configured in the PLATO PROPERTIES table of Oracle Banking Origination.

Figure 5: Role Maintenance

The screenshot shows the 'Role Maintenance' window. It contains a form with the following fields: Role Id (ALLROLES), Role Description (all roles), and a checkbox for 'Centralisation Role'. The bottom status bar shows 'Maker PRANAV2', 'Checker PRANAV2', 'Date Time: 2000-07-03 12:14:47', 'Mod No 25', 'Record Status Open', and 'Authorization Authorized Status'. Buttons for 'New', 'Copy', 'Close', 'Unlock', 'Print', 'Enter Query', and 'Exit' are visible.


2.4 Maintenance for Oracle Banking Origination

Maintain Oracle Banking Routing Hub configuration in common core for Oracle FLEXCUBE Universal Banking.

1. From **Home screen**, click **Core Maintenance**. Under **Core Maintenance**, click **Routing Hub**.
2. Under **Routing Hub**, click **Service Consumers**.


→ The **Service Consumers** screen is displayed.

Figure 6: Service Consumers



3. Click **Import** and upload the RPM_ORIGINATION_Consumer.json file provided in the release and click **Extract**.

Figure 7: Success



4. Select **FCUBS** and click **Import**.

Figure 8: Confirmation





Figure 9: RPM Origination



5. Click **RPM_ORIGINATION**.
6. Under **RPM_ORIGINATION**, click **FCUBS**.

Figure 10: RPM Origination






Figure 11: RPM Origination

7. Click **Edit**.
8. Change the host and port as per the Oracle FLEXCUBE Universal Banking installation and save it.

Figure 12: Edit Implementation

9. Repeat the same for all the FCUBS Service Providers

The below consumer services will be imported.

Consumer Service	Description
Collateral_Creation	Usage: Create Local Collateral Service: FCUBSCoreService Operation: CreateLocalCollateral
Liability_Creation	Usage: Create Liability Service: FCUBSCoreentitiesService Operation: CreateLiability

Customer_Liability_Linkage	Usage: Create Customer Liability Service: FCUBSCoreentitiesService Operation: CreateCustomerLiab
CASA_Account_Creation	Usage: Create CASA Account Service: FCUBSAccService Operation: CreateCustAcc
Loan_Simulation	Usage: Perform Loan Account Simulation Service: FCUBSCLService Operation: CreateAccountSim
TD_Simulation	Usage: Perform Term Deposit Account Simulation Service: FCUBSAccService Operation: QueryTDCustAccSim
Get_Liability_Interest_Details	Usage: Fetch Liability Interest and Charge Details Service: FCUBSSTService Operation: QueryAccClasUde
Get_Liability_Product_Details	Usage: Fetch Liability Product Details Service: FCUBSSTService Operation: QueryAccClasQuery
Get_Loan_Product_Details	Usage: Fetch Loan Product Details Service: FCUBSCLService Operation: QueryProduct

List_All_Loan_Products	Usage: List Loan Products Service: FCUBSCLService Operation: SummaryQueryProduct
List_All_Liability_Products	Usage: List Liability Products Service: FCUBSSTService Operation: SummaryQueryAccClasMaint
TD_Account_Creation	Usage: Create Term Deposit Account Creation Service: FCUBSAccService Operation: CreateTDCustAcc
Loan_Account_Creation	Usage: Create Loan Account Creation Service: FCUBSCLService Operation: CreateAccount
Get_Customer_Liability_Details	Usage: Fetch Customer Limit Details Service: FCUBSSTService Operation: QuerySTCustLimitDet
Get_Liability_Details	Usage: Fetch Liability Details Service: FCUBSCoreentitiesService Operation: QueryLiability
fetchTDAccount	Usage: Fetch TD accounts which are tagged as “Collateral Linkage”, for a particular customer number. This will be used for attaching TD accounts as collaterals in Oracle Banking Origination screens Service: fcubs-co-mo-lov-service

	Note: Make sure that the above service is deployed in FCUBS. Also make sure that the following INC which is released as part of FCUBS is present in CSTB_LOV_INFO table. 20211112_1735420 82_36_CSZB_LOV_INI
--	---

NOTE: Refer PDF attachments for downloading the file.