

User Defined Events User Guide

Oracle FLEXCUBE Universal Banking

Release 14.7.4.0.0

Part No. F98075-01

June 2024

User Defined Events User Guide
Oracle Financial Services Software Limited
Oracle Park

Off Western Express Highway
Goregaon (East)
Mumbai, Maharashtra 400 063
India

Worldwide Inquiries:

Phone: +91 22 6718 3000

Fax: +91 22 6718 3001

<https://www.oracle.com/industries/financial-services/index.html>

Copyright © 2007, 2024, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are “commercial computer software” pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Contents

1. Preface	1-1
1.1 Introduction.....	1-1
1.2 Documentation Accessibility.....	1-1
1.3 Organization	1-1
1.4 Glossary of Icons.....	1-1
1.5 Related Documents.....	1-1
2. User Defined Events	2-1
2.1 Introduction.....	2-1
2.2 Event Details	2-1
2.2.1 <i>Invoking User Defined Events Screen</i>	2-1
2.2.2 <i>Default Button</i>	2-4
2.2.3 <i>Value Date Derivation Button</i>	2-5
2.2.4 <i>Event Processing Button</i>	2-6
2.2.5 <i>Calculating the Commission on the Highest Outstanding Balance</i>	2-6
2.2.6 <i>Viewing Event Details</i>	2-7
2.3 Accounting Roles and Heads	2-11
2.3.1 <i>Invoking Accounting Roles and Heads Screen</i>	2-12
2.3.2 <i>Amount Tag Tab</i>	2-12
2.3.3 <i>Accounting Roles Tab</i>	2-16
2.4 User Defined Events.....	2-17
2.4.1 <i>Triggering User Defined Events Automatically</i>	2-17
3. Function ID Glossary	3-1

1. Preface

1.1 Introduction

This manual is intended as a guide to help you define User Defined events in FLEXCUBE. Besides this User Manual, you can find answers to specific features and procedures in the Online Help, which can be invoked, by choosing 'Help Contents' from the *Help* Menu of the software. You can further obtain information specific to a particular field by placing the cursor on the relevant field and striking <F1> on the keyboard.

1.2 Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.





1.3 Organization

This manual is organized as follows:

Chapter	Description
Chapter 1	<i>About this Manual</i> gives information on the intended audience. It also lists the various chapters covered in this User Manual.
Chapter 2	<i>Building User Defined Events</i> explains how to define events in Oracle FLEXCUBE either for your own convenience or to suit the requirements of your bank.
Chapter 3	Function ID Glossary has alphabetical listing of Function/Screen ID's used in the module with page references for quick navigation.

1.4 Glossary of Icons

This User Manual may refer to all or some of the following icons.

Icons	Function
	Exit
	Add row
	Delete row
	Option List

1.5 Related Documents

For further information on procedures discussed in the manual, refer to the Oracle FLEXCUBE manuals on:

- Core Services

- Common Procedures

2. User Defined Events

2.1 Introduction

A contract that you process in Oracle FLEXCUBE goes through different stages during its life cycle. These stages are defined as Events. Every new module that you maintain has to be associated with a set of events, which will be triggered at appropriate stages during the lifecycle of the contract.

Apart from the factory shipped events, you can create your own events as per the requirements of the bank.

This chapter contains the following sections:

- [Section 2.2, "Event Details"](#)
- [Section 2.3, "Accounting Roles and Heads"](#)
- [Section 2.4, "User Defined Events"](#)

2.2 Event Details

This section contains the following topics:

- [Section 2.2.1, "Invoking User Defined Events Screen"](#)
- [Section 2.2.2, "Default Button"](#)
- [Section 2.2.3, "Value Date Derivation Button"](#)
- [Section 2.2.4, "Event Processing Button"](#)
- [Section 2.2.5, "Calculating the Commission on the Highest Outstanding Balance"](#)
- [Section 2.2.6, "Viewing Event Details"](#)

2.2.1 Invoking User Defined Events Screen

You can define the events through the 'User defined Events' screen. You can invoke this screen by typing 'UDDEVMNT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

You can define events for a new module and also for existing modules in this screen.

User Defined Events J L X

New Enter Query

Report Module *	<input type="text"/>
Event Code *	<input type="text"/>
Event Description	<input type="text"/>

Accounting Entries Definition	No	Association	
Advice Definition	No	Allow Charge	No
UDE Advice Definition	No	Allow Transaction Tax	No

Application		Liquidation	
Allow Charge	No	Allow Charge	No
Allow Transaction Tax	No	Allow Transaction Tax	No

Fields Default Audit Exit

User defined events will be linked to a product and is triggered in the life cycle of a contract, which is processed under that product.

Report Module

Specify the module for which you want to set up a user-defined event. The adjoining option list contains all the module codes available in the system. Select the appropriate one.

Event Code

Specify the event code that you want to set up for the module.

Event Description

Give a brief description of the event that you are defining. The description that you enter is for information purposes.

Accounting Entries Definition

Specify the accounting entries definition. You have the following options:

- Yes
- No

Advice Definition

Specify the advice entries definition. You have the following options:

- Yes
- No

UDE Advices Definition

Specify the UDE advice definition. You have the following options:

- Yes
- No

Association

Indicate your preferences.

Allow Charge

Specify the association allow charge. You have the following options:

- Yes
- No

Allow Transaction Tax

Specify the association allow transaction tax. You have the following options:

- Yes
- No

Application

Indicate your preferences. These fields will not be applicable if you have specified any one of the following in the 'Report Module' field:

- CL
- CI
- LE
- MO

Allow Charge

Specify the application allow charge. You have the following options:

- Yes
- No

Allow Transaction Tax

Specify the application allow transaction tax. You have the following options:

- Yes
- No

Liquidation

Indicate your preferences. These fields will not be applicable if you have specified any one of the following in the 'Report Module' field:

- CL
- CI
- LE
- MO

Allow Charge

Specify the liquidation allow charge. You have the following options:

- Yes
- No

Allow Transaction Tax

Specify the liquidation allow transaction tax. You have the following options:

- Yes

- No

2.2.2 Default Button

Click 'Default' button in the 'User Defined Events' screen to define the triggering parameters for the configured event.

The screenshot shows the 'Event Trigger' configuration window. It includes the following elements:

- Module Code**: A text input field with an asterisk indicating it is required.
- Event Code**: A text input field with an asterisk indicating it is required.
- Event Trigger**: Two radio button options: 'Automatic' and 'Manual'.
- Value Date Derivation**: A checkbox that is currently unchecked.
- Event Processing**: A checkbox that is currently unchecked.
- Execution Query**: A large, empty text area for entering a query.
- Bottom Bar**: Contains buttons for 'Value Date Derivation', 'Event Processing', 'Ok', and 'Exit'.

In this screen you can enter the following details below:

Module Code

The system displays the module code here.

Event Code

The system displays the event code here.

Event Trigger

The event, which you are defining, can be triggered in either of the following ways:

- Automatic – This means that the event should be triggered automatically during EOD.
- Manual - This means that the event should be triggered manually from the 'User Defined Event' triggering screen.

Value Date Derivation

Check this box to indicate that the value date derivation is defined for a particular event.

Event Processing

Check this box to indicate the event processing is defined for a particular event.

Execution Query

Enter the query condition to select the list of accounts for the execution of the event during EOD. Input to this field will be mandatory if you choose 'Automatic' triggering of the event.

2.2.3 Value Date Derivation Button

Click 'Value Date Derivation' button on the 'Event Trigger' screen and invoke the 'Derivation Rule' screen to specify the value date derivation logic.

The screenshot shows a web-based form titled "Derivation Rule". The form is divided into two main sections. The top section, titled "Value Date Derivation Rule", contains three input fields: "Module Code *", "Event Code *", and "Value Date Derivation Rule". There is a "Default" button next to the "Event Code" field. The bottom section, titled "Error", contains two buttons: "X" and "E". At the bottom right of the screen are "Ok" and "Exit" buttons.

In this screen you can enter the following details:

Module Code

The system displays module code here.

Event Code

The system displays event code here.

Value Date Derivation Rule


Enter description about the value date derivation rule. You need to assign a value to 'L_VAL_DT'. For instance, 'L_VAL_DT:=global.application_date'.

Error

Click 'X' button to execute the code. The derivation code will be validated by the system. If any checks fail, you must alter the statement so that the validation can be made successfully. Click 'E' button to view the errors.

2.2.4 Event Processing Button

Click 'Event Processing' button on the 'Event Trigger' screen and invoke the 'Derivation Rule' screen to assign values for processing of the event.



In this screen you can enter the following details:

Module Code

The system displays module code here.

Event Code

The system displays event code here.

Errors

Click 'X' button to execute the code. The derivation code will be validated by the system. If any checks fail, you must alter the statement so that the validation can be made successfully. Click 'E' button to view the errors.

2.2.5 Calculating the Commission on the Highest Outstanding Balance

System uses UDE to calculate the commission on the highest outstanding balance of the loan and the mortgage Accounts.

You can define a UDE Highest Debit Balance Commission Event (HDBC) for computation of commission with following parameters:

- Event Trigger can be either Auto or Manual
- Apply Charge should be Yes
- Execution Query should be all accounts which satisfy the following criteria:
 - Account Status is Active
 - Outstanding Principal is greater than 0.00
- Value Date derivation rule to return the date as month-end
- This event is available at Loan and Mortgage product level.

2.2.6 Viewing Event Details

You can view the event details maintained in the 'User Defined Events' screen under 'Events' screen of a contract screen. You can invoke the 'Events' screen by typing 'CSDEVENT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Reference Number

Specify the reference number.

The system displays the following details:

- Event Number
- Event code
- Description
- Event Date
- Authorization Status
- Maker Id
- Checker Id

2.2.6.1 Viewing Accounting Entries

You can view the accounting entries maintained for an event in the 'Accounting Entries' screen by selecting an event and clicking on 'Accounting Entries' button in the 'Events'

screen. To invoke the screen type 'CSDACENT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Reference Number

Specify the transaction reference number

See Position Entries

Check this box to view currency position of the entries.

Event

Specify the event.

Event Number

The system displays the event number.

The following details are displayed in the Accounting Entries:

- Event
- Branch
- Account
- Account Description
- Dr/Cr
- Amount Tag
- Account Ccy
- Foreign Currency Amount
- Rate
- Local Currency Amount
- Date
- Value Date
- Txn Code

The following details are displayed in the Accounting Under Process:

- Event
- Branch

- Account
- Dr/Cr
- Amount Tag
- Account Ccy
- Foreign Currency Amount
- Rate
- Local Currency Amount
- Date
- Value Date
- Txn Code

Override Details

Click on 'Overrides' button to view the override details of the accounting entries.

Accounting Entries

⌵ ⌴ X

Reference Number *

See Position Entries

Event Number *

Event *

Accounting Entries
Overrides

Overrides

⌵ ⌴ ≡

<input type="checkbox"/> Overrides ⌵	Override Status ⌵	Authorized By ⌵	Auth Date Stamp ⌵
No data to display.			

Page (0 of 0 items) | < < 1 > >

2.2.6.2 Viewing Messages

You can view the messages by selecting an event and clicking on 'Messages' button in the 'Events' screen. To invoke the screen type 'CSDMSGVW' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows the Oracle 'Message' screen. At the top, there is a search bar with 'Enter Query' and three input fields: 'Contract Reference *', 'Event Sequence Number *', and 'Event'. Below these is a table titled 'Messages' with columns: 'Message Type', 'SWIFT Message Type', 'Sub Message Type', 'SWIFT Sub Message Type', 'Test Status', 'Medium', and 'Message Status'. The table is currently empty, displaying 'No data to display.' and a pagination control showing 'Page 1 (0 of 0 items)'. A 'Print' button is located below the table. At the bottom of the screen, there are 'Message Details' and 'Exit' buttons.

The system displays the following details:

- Contract Reference
- ESN
- Event
- Message Type
- SWIFT Message Type
- Medium
- Message Status
- Authorization Status
- Receiver
- Receiver Name
- DCN

Message Details

You can view the details of a message by selecting a message from the 'Message' screen and clicking on 'Message Details' button.

The screenshot displays the 'Message Details' interface. At the top, there is a title bar with the word 'Message' and window control icons. Below the title bar is a search bar labeled 'Enter Query'. The main area contains several search filters: 'Reference Number', 'DCN *', 'Event Sequence Number or Version Number', 'Receiver or Sender', 'Message Type', 'SWIFT Message Type', 'Sub Message Type', and 'SWIFT Sub Message Type'. Each filter has a corresponding input field. Below the filters is a large area labeled 'Message' which is currently empty. In the top right corner of this area, there is a pagination indicator '1 Of 1' with navigation arrows. At the bottom right corner of the entire screen, there is an 'Exit' button.

2.3 Accounting Roles and Heads

This section contains the following topics:

- [Section 2.3.1, "Invoking Accounting Roles and Heads Screen"](#)
- [Section 2.3.2, "Amount Tag Tab"](#)
- [Section 2.3.3, "Accounting Roles Tab"](#)

2.3.1 Invoking Accounting Roles and Heads Screen

You can define the amount tags for accounting roles through the 'Accounting Role and Head Maintenance' screen. You can invoke this screen by typing 'UDDRLTAG' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Accounting Role & Head Maintenance

New Enter Query

Module Code *

Description

Amount Tag Accounting Roles

Amount Tag Details

<input type="checkbox"/>	Amount Tag	Description	Charge	Accounting	Transaction Tax	Local Currency	Local Currency Equivalent Tag	Derivation
No data to display.								

Page 1 (0 of 0 items) |< < 1 > >|

Audit Exit

You can specify the following parameters for the module:

- Amount Tag
- Accounting Roles

2.3.2 Amount Tag Tab

This tab is displayed by default when you invoke the screen.

Amount Tag

Specify the amount tag.

Description

Enter the brief description for amount tag.

Charge

Indicate whether the amount tag pertains to a charge or not by choosing one of the following options:

- Yes
- No

Accounting

Indicate whether accounting entries are required or not by choosing one of the following options:

- Yes
- No

Transaction Tax

Indicate whether transaction tax is applicable or not by choosing one of the following options:

- Yes
- No

Local Currency


Indicate the local currency preference by choosing one of the following options:

- Average
- Equivalent

Local Currency Eq. Tag

Specify the amount tag for the local currency equivalent amount.

Click 'Derivation' button and invoke the 'Derivation Rule Details' screen to derive the amount and currency for the amount tag.



Here you can specify derivation logic for the following:

- Amount Rule
- Currency Rule

Module Code

The system displays module code here.

Amount Tag

The system displays the amount tag here.

Amount Rule Derivation

You can specify the following details.

Amount Rule Type

Check this box if the amount has to be derived based on a specified condition. The amount for a particular tag can be derived based on a condition.

Derivation Amount Rule

If you have checked against the option 'Amount Rule Type', the system will derive the amount for the amount tag that is being defined. You can use the following as variables while creating the derivation rule:

- Account Level UDF
- SDE

You can use any of the following SDEs:

- CUSTOMER_CATEGORY - Category of the customer of the loan
- CUSTOMER_ID - Customer ID
- LOAN_STATUS - Status
- ACCOUNT_CCY - Loan account's currency
- TODAY - Today
- NEXT_WORKDAY - Date of next workday
- PAYMENT_VALUE_DATE - Payment value date
- LAST_PAYMENT_DATE - Last payment date for the customer
- DAYS_FOR_NEXT_PMNT - Days for next payment
- AMOUNT_DISBURSED - Current disbursement amount
- COMMITMENT_UTILIZED - Utilized part of commitment
- EMI_AMOUNT - EMI AMOUNT
- NET_PRINCIPAL - Non-funded amount for which the loan is applied
- TOTAL_DUE_AMOUNT - Sum of all the Outstanding Balances for the Customer
- LAST_PAYMENT_AMOUNT - Last Payment Amount for the Customer
- CURRENT_PAYMENT_AMOUNT - Current Amount which is Due
- PAID_INTEREST_AMOUNT - Total Interest Amount Paid
- INTEREST_ACCRUED_AMOUNT - Sum of all the Accrued Amounts for Interest
- AMOUNT_NOT_DISBURSED - Amount Not Disbursed
- COMMITMENT_UNUTILIZED - Unutilized part of commitment
- TOTAL_PRINCIPAL - Amount for which the loan is applied
- TENOR - Duration for which the loan is applied
- LOAN_PRINCIPAL - Principal
- PRINCIPAL - Amount disbursed
- PRINCIPAL_OUTSTAND - Principal amount outstanding
- OVERDUE_MONTHS - OverDue Months
- TOTAL_OVERDUE_AMOUNT - Total Overdue amount for all components
- INS_TENOR - INSTALLMENT TENOR
- NO_OF_RPMNT_SCHS - Number of Non-Moratorium repayment schedules
- MORA_OUTSTANDING - Moratorium Outstanding Amount
- COMPOUND_VALUE - Amount Compounded

- TOTAL_MORA_AMOUNT - Total Moratorium Amount
- _OVR_DAYS - <Component> overdue days
- _EXPECTED - <Component> expected amount
- _OUTSTAND - <Component> outstanding amount
- _CCY - <Component> currency
- _OVERDUE - <Component> overdue amount
- _FN_NO_REPAY_SCH - <Component> number of schedules for a component if periodic
- _NET_PRINCIPAL - <Component> amount financed
- PROJECTED_AMOUNT - Projected Amount
- UIDB_DIFFERENTIAL - UIDB Differential
- BALLOON_AMOUNT - Balloon Amount
- RESIDUAL_AMOUNT - Residual Amount
- CAPITAL_AMOUNT - Capital Amount
- CLOSURE_AMOUNT - Closure Amount
- NET_MORTGAGE - Net Mortgage Amount

Assume that you have an account-level UDF called 'OSCHGRATE'.

The derivation rule using the SDEs and UDF may be given as under.

DECLARE

l_osprin_amt number;

rate number;

BEGIN

l_osprin_amt:=(@SDE_VAL#PRINCIPAL_OUTSTAND);

rate:=(@UDF_UD#OSCHGRATE);

l_amount:=rate * l_osprin_amt;

END

Amount Rule Error Description

Enter a brief description about amount rule error that should be displayed in case the derivation fails.

Currency Rule Derivation

The currency can either be derived from the existing account currency or can be maintained as a UDF field in the account or it can be hard-coded in the 'Currency Rule Definition' screen.

Currency Rule Type

Check this box if the currency for a particular amount tag has to be derived based on the derivation rule.

Derivation Currency Rule

Specify the rule based on which the system should derive the currency for the amount tag. You need to assign a value to 'L_CCY'. For instance, the rule may be given as under.

```

BEGIN

SELECT currency

INTO   l_ccy

FROM   cltb_account_master

WHERE  account_number = p_acc_no

AND    branch_code=p_branch;

END;

```

Currency Rule Error Description

Enter a brief description about currency rule error that should be displayed in case the derivation fails.

2.3.3 Accounting Roles Tab

Click 'Accounting Roles' tab in the 'Accounting Role and Head Maintenance' screen.

The screenshot shows the 'Accounting Role & Head Maintenance' application window. At the top, there are 'New' and 'Enter Query' buttons. Below is a search area with 'Module Code' and 'Description' fields. A tab bar at the bottom of the search area shows 'Amount Tag' and 'Accounting Roles'. The 'Accounting Roles' tab is active, displaying the 'Account Rule Details' section. This section contains a table with columns for 'Role Code', 'Description', and 'Role Type'. The table is currently empty, showing 'No data to display.' Below the table is a page navigation bar indicating 'Page 1 (0 of 0 items)' with navigation arrows. At the bottom right of the window, there are 'Audit' and 'Exit' buttons.

In this screen you can enter the following details:

Role Code

Specify the role code.

Description

Enter a brief description about role code.

Role Type

Select the role type from the adjoining drop-down list. The following values are available:

- Asset
- Liability
- Income

- Expense
- C Asset
- C Liability
- Customer

2.4 User Defined Events

This section contains the following topics:

- [Section 2.4.1, "Triggering User Defined Events Automatically"](#)

2.4.1 Triggering User Defined Events Automatically

You can add the user defined event batch to the mandatory programs to be run for the module, using the 'Mandatory Batch Program Maintenance' screen. You can invoke this screen by typing 'EIDMANPR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Mandatory Batch Program Maintenance

New Enter Query

Branch * 000 Function * [Search]

Module * [Search] Sequence Number []

Description []

End of Cycle Group

Txn Input

End of Txn Input

End of Fin Input

End of Day

Beginning of Day

End of Previous Day

Error Handling

Stop Automatic End of Day and Run Emergency Program

Continue with Automatic End of Day

Frequency Daily Number Of Days []

Holiday Rule Do Not Execute Run Date []

Execution Layer Database Application Job Code [Search]

Description []

Fields Audit Exit

Module

Choose the module code from the adjoining option list.

Function Identification

Specify 'UDBATEVT' as the batch that needs to be run. You can also select this value from the adjoining option list.

End Of Cycle Group

Select the option 'End Of Transaction Input'.

Predecessors

You need to add the following batches as predecessors to the 'UDBATEVT' batch:

- CL batch (CLBATCH)
- Islamic CL batch (CIDBATCH)
- Leasing batch (LEDBATCH)
- Mortgage batch (MODBATCH)

For further details about this screen, refer the chapter 'Setting- up Mandatory Programs for EOD' in the AEOD User Manual.

This batch fetches the list of user defined events of the following modules for which the event triggering is set as 'Automatic':

- CL
- Islamic Financing
- Mortgages
- Leasing

It fetches valid accounts associated with the event by the executing the query defined for the event in the 'Event Trigger' screen. The settlement account and branch are defaulted from the settlement details maintained for the account. If these details are not maintained, they will be defaulted from the settlement details maintained for the 'Principal' component.

The system triggers the derivation rule maintained for the event to arrive at the value date of the event. The system then posts accounting entries to the respective GLs using the value date derived. The system also derives the amount and currency for each amount tag of the accounting entries defined for the event. The system allows you to link only payment advice 'CR_ADV, DR_ADV' to the user defined event. So if linked to an account, this advice will be generated.

3. Function ID Glossary

C

CSDACENT2-8
CSDEVENT2-7
CSDMSGVW2-10

E

EIDMANPR 2-17

U

UDDEVMNT 2-1
UDDRLTAG 2-12