Guarantee SBLC Advised - Claim Update User Guide Oracle Banking Trade Finance Process Management

Release 14.7.5.0.0

Part No. G15303-01

September 2024



Oracle Banking Trade Finance Process Management - Guarantee SBLC Advised Claim Update User Guide Oracle Financial Services Software Limited

Oracle Park
Off Western Express Highway
Goregaon (East)
Mumbai, Maharashtra 400 063
India
Worldwide Inquiries:
Phone: +91 22 6718 3000
Fax: +91 22 6718 3001

www.oracle.com/financialservices/

Copyright © 2018- 2024, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Contents

1.	Pre	face		1-1
	1.1	Introdu	uction	1-1
	1.2	Audier	nce	1-1
	1.3	Docum	nentation Accessibility	1-1
	1.4	Organization		
	1.5	Relate	d Documents	1-1
	1.6	Divers	ity and Inclusion	1-1
	1.7	Conve	ntions	1-2
	1.8	Screer	nshot Disclaimer	1-2
	1.9	Glossary of Icons		1-2
2.	Ora	cle Ba	nking Trade Finance Process Management	2-1
	2.1	Overvi	ew	2-1
	2.2	Benefi	ts	2-1
	2.3	Key Features		2-1
3.	Gua	Guarantee SBLC Advised - Claim Update		
	3.1	Common Initiation Stage		3-1
	3.2	Regist	ration	3-2
		3.2.1	Application Details	3-4
		3.2.2	Guarantee Details	3-6
		3.2.3	Miscellaneous	3-8
		3.2.4	Document Linkage	3-9
		3.2.5	Bi-Directional Flow for Offline Transactions Initiated from OBTFPM	3-13
	3.3	Data E	Enrichment	3-14
		3.3.1	Main Details	3-17
		3.3.2	Claim Details	3-20
		3.3.3	Document Details	3-26
		3.3.4	Additional Fields	3-30
		3.3.5	Advices	3-33
		3.3.6	Additional Details	3-37
		3.3.7	Settlement Details	3-50
		3.3.8	Summary	3-54
	3.4	Multi L	evel Approval	3-58
		3.4.1	Re-Key Authorization	3-58

1. Preface

1.1 Introduction

This user manual is designed to help you quickly get acquainted with Guarantee SBLC Advised Claim Update process in Oracle Banking Trade Finance Process Management.

1.2 Audience

This manual is intended for the following User/User Roles:

- Oracle Implementers
- Customer Service Representatives (CSRs)
- Oracle user

1.3 **Documentation Accessibility**

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info or visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs if you are hearing impaired.

1.4 Organization

This manual is organized into the following chapters:

- Preface gives information on the intended audience, structure, and related documents for this User Manual.
- The subsequent chapters provide an overview to the module.

1.5 Related Documents

- Getting Started User Guide
- Common Core User Guide

1.6 **Diversity and Inclusion**

Oracle is fully committed to diversity and inclusion. Oracle respects and values having a diverse workforce that increases thought leadership and innovation. As part of our initiative to build a more inclusive culture that positively impacts our employees, customers, and partners, we are working to remove insensitive terms from our products and documentation. We are also mindful of the necessity to maintain compatibility with our customers' existing technologies and the need to ensure continuity of service as Oracle's offerings and industry standards evolve. Because of these technical constraints, our effort to remove insensitive terms is ongoing and will take time and external cooperation.

1.7 Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text.
italic	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

1.8 Screenshot Disclaimer

Personal information used in the interface or documents is dummy and does not exist in the real world. It is only for reference purposes.

1.9 Glossary of Icons

This User Manual may refer to all or some of the following icons.

Icons	Function
×	Exit
+	Add row
_	Delete row
Q	Option List

2. Oracle Banking Trade Finance Process Management

Welcome to the Oracle Banking Trade Finance Process Management (OBTFPM) User Guide. This guide provides an overview on the OBTFPM application and takes you through the various steps involved in creating and processing Trade Finance transactions.

This document will take you through following activities in OBTFPM:

- To create and handle Trade Finance transaction.
- Help users to conveniently create and process Trade Finance transaction

2.1 Overview

OBTFPM is a Trade Finance middle office platform, which enables bank to streamline the Trade Finance operations. OBTFPM enables the customers to send request for new Trade Finance transaction either by visiting the branch (offline channels) or through SWIFT/Trade Portal/other external systems (online channels).

2.2 Benefits

OBTFPM helps banks to manage Trade Finance operations across the globe in different currencies. OBTFPM allows you to:

- Handle all Trade Finance transactions in a single platform.
- Provides support for limit verification and limit earmarking.
- Provide amount block support for customer account.
- Provides acknowledgement to customers.
- Enables the user to upload related documents during transaction.
- Enables to Integrate with back end applications for tracking limits, creating limit earmarks, amount blocks, checking KYC, AML and Sanction checks status.
- Create, track and close exceptions for the above checks.
- Enables to use customer specific templates for fast and easy processing of trade transactions that reoccur periodically.

2.3 Key Features

- Stand-alone system that can be paired with any back end application.
- Minimum changes required to integrate with bank's existing core systems.
- Faster time to market.
- Capable to interface with corporate ERP and SWIFT to Corporate.
- Highly configurable based on bank specific needs.
- Flexibility in modifying processes.



3. Guarantee SBLC Advised - Claim Update

As part of update a claim lodged under a Guarantee/SBLC Advised process, the applicant can register an update to a claim against the Guarantee/SBLC advised.

In the subsequent sections, let's look at the details for update a claim lodged under Guarantee/SBLC Advised process:


This section contains the following topics:

3.1 Common Initiation Stage	3.2 Registration
3.3 Data Enrichment	3.4 Multi Level Approval

3.1 Common Initiation Stage

The user can initiate the new update a claim update under a Guarantee/SBLC request from the common Initiate Task screen.

- 1. Using the entitled login credentials, login to the OBTFPM application.
- 2. Click Trade Finance > Initiate Task.



Provide the details based on the description in the following table:

Field	Description	
Process Name	Select the process name to initiate the task.	
Branch	Select the branch.	

3.1.0.1 Action Buttons

Use action buttons based on the description in the following table:

Field	Description	
Proceed	Task will get initiated to next logical stage.	
Clear	The user can clear the contents update and can input values again.	

3.2 Registration

During the Registration stage, the user can register an update to the claim lodged under a Guarantee/SBLC Advised.

In this stage the user can initiate an update to the Guarantee/ SBLC Claim Lodged. The user can capture the basic details of the application, check the signature of the applicant and upload the related documents of the applicant.


The OBTFPM user can process MT798 with sub messages MT726-MT759 message received through SWIFT. The OBTFPM verifies the field 21 and 26E (of the MT759 and identifies the Original Contract Reference Number and Amendment Number and invokes the process. The user can cancel the previously received MT798 referenced message which is under process.

The OBTFPM user can process incoming MT798(up to a maximum of 8 messages) with sub messages MT788-MT799 message received through SWIFT and enables the user to cancel the previously received MT798 referenced message which is under process.

1. Using the entitled login credentials for registration stage, login to the OBTFPM application.



2. On login, user must be able to view the dashboard screen with widgets as mapped to the user.




3. Click Trade Finance> Bank Guarantee Advise > Guarantee SBLC Advised - Claim Update.



The Registration stage has two sections Application Details and Guarantee Details. Let's look at the registration screens below:

Application Details 3.2.1



The request is received at the Branch/ Front office or Processing centre. The user should be able to input the following details.


Provide the Application Details based on the description in the following table:

Field	Description	Sample Values
Guarantee/SBLC Number	User can enter the undertaking number. The user can also search the undertaking number through LOV search.	
	System displays all the claims lodged under the Guarantee/ SBLC and user can select the claim for which update is required.	
Guarantee Advised by Us	Read only field.	
	System defaults the value from Guarantee/ SBLC Advise.	
Claim Serial Number	Read only field.	
	System defaults the claim serial number from Guarantee/ SBLC Advised to which update has to be done.	
Beneficiary ID/ Name	Read only field.	001345
	System defaults the Beneficiary ID/ Name from Guarantee/ SBLC Advise.	
Branch	Customer's home branch will be displayed.	203-Bank
	Read only field.	Futura -Branch FZ1
	System defaults the branch name from Guarantee/ SBLC Advise.	

Field	Description	Sample Values
Process Reference Number	Read only field. Unique sequence number for the transaction. This is auto generated by the system based on process name and branch code.	203GTEISS000 001134
Priority	Priority maintained will be populated as either 'Low or Medium or High'. If priority is not maintained for a customer, 'Medium' priority will be defaulted.	High
	The user can change the priority.	
Submission Mode	Select the submission mode of Guarantee Advised Claim Update request. By default the submission mode will have the value as 'Desk'.	Desk
	Desk- Request received through Desk	
	Fax - Request received through Fax	
	Email - Request received through Email	
Claim Update Date	Read only field.	04/13/2018
	NoteBy default, the application will display branch's current date for the claim lodgment date.	
	Future date and back date selection is not allowed.	
Beneficiary Reference Number	User can enter the Beneficiary Reference Number, if available.	
Issuing Bank	Read only field. System defaults the Issuing Bank (applicable for CTB,LTB).	
Issuing Bank Reference Number	Read only field. System defaults the Issuing Bank Reference (applicable for CTB,LTB)	203GTEISS000 001134
Version	Read only field. System defaults the version number.	
User Reference Number		PK2GUI121144
Oser Mererence Number	Read only field. System defaults the user reference number from Guarantee/ SBLC claim	0001

3.2.2 **Guarantee Details**

Registration user can provide Guarantee details in this section. Alternately, guarantee details can be provided by Data Enrichment user.




Provide the Guarantee Details based on the description in the following table:

Field	Description	Sample Values
Guarantee Type	Read only field.	ADVP
	System defaults the value from Guarantee/ Standby Advised.	
Date of Issue	Read only field.	04/13/18
	System defaults the value from Guarantee/ Standby Advised.	
Purpose of message	Read only field.	
	System defaults the purpose of message from Guarantee/ Standby Advised.	
Expiry Type	This field indicates whether undertaking has specified expiry date or is open-ended.	
	Read only field. System defaults the expiry type from Guarantee/ Standby Advised.	
Date Of Expiry	Expiry date of the Guarantee Advise.	09/30/18
	Read only field. System defaults the expiry date from Guarantee/ Standby Advised.	
Claim Date	Read only field. System defaults the claim date from Guarantee/ Standby Advised.	04/13/2018
Claim Expiry Date	Read only field. System defaults the claim expiry date from Guarantee/ Standby Advised.	04/13/2018
Outstanding Currency/	Read only field.	
Amount	System defaults the outstanding currency and amount from Guarantee/ SBLC Advised.	
Applicable Rules	Rules for Guarantee. Read only field.	URDG - Uni-
	System defaults the value from Guarantee/ Standby Advised.	form rules for demand guar- antees

Field	Description	Sample Values
Applicant Bank	Read only field.	001345 Nestle
	System defaults the applicant bank details from Guarantee/ Standby Advised.	
Applicant	Read only field.	001345 Nestle
	System defaults the applicant from Guarantee/ Standby Advised.	
Beneficiary	Read only field.	001345 Nestle
	System defaults the beneficiary from Guarantee/ Standby Advised.	
Advising Bank	Read only field.	001343 - Bank Of America
	System defaults the advising bank from Guarantee/ Standby Advised.	
Advising Through Bank	Read only field.	Advising Bank Reference
	System defaults the advising through bank from Guarantee/ Standby Advised.	
Counter Guarantee Issu-	Read only field.	
ing Bank	System defaults the counter guarantee issuing through bank from Guarantee/ Standby Advised.	
Local Guarantee Issuing	Read only field.	
Bank	System defaults the local guarantee issuing bank from Guarantee/ Standby Advised.	
Accountee	Read only field.	
	System defaults the accountee name if available.	

3.2.3 Miscellaneous



Provide the Miscellaneous Details based on the description in the following table:

Field	Description	Sample Values
Signatures	Click the Signature button to verify the signature of the customer/ bank if required.	
	The user can view the Customer Number and Name of the signatory, Signature image and the applicable operation instructions if any available in the back-office system.	
	If more than one signature is available, system should display all the signatures.	
Documents	User can upload the claim documents.	
	Application will display the mandatory and optional documents.	
Remarks	User can enter the additional information that can be viewed by other users in other stages of the process.	
	Content from Remarks Field should be handed off to Remarks field in Backend application.	

Field	Description	Sample Values
Customer Instruction	Click to view/ input the following	
	 Standard Instructions – In this section, the system will populate the details of Standard Instructions maintained for the customer. User will not be able to edit this. 	
	Transaction Level Instructions – In this section, OBTFPM user can input any Customer Instructions received as part of transaction processing. This section will be enabled only for customer initiated transactions.	
View Guarantee/SBLC	User can view all the latest Guarantee/Standby LC details.	
Guarantee/SBLC Events	User can view all the previous events under the Guarantee/Standby LC.	
Hold	The details provided will be registered and status will be on hold.	
	This option is used, if there are any pending information yet to be received from applicant.	
Cancel	Cancels the Guarantee Advised Claim Update Registration stage input.	
Save & Close	Save the information provided and holds the task in you queue for working later. This option will not submit the request.	
Submit	On Submit, system will trigger acknowledgment to the customer and give confirmation message for successful submission. Task will get moved to next logical stage of Guarantee/ SBLC Claim update. If mandatory fields have not been captured, sys-	
	tem will display an error message until the man- datory fields data are provided.	
Checklist	Make sure that the details in the checklist are completed and acknowledge. If mandatory checklist items are not marked, system will display an error on submit.	
	Mandatory claim Documents receivedSignatures on Claim verified	

3.2.4 **Document Linkage**

The user can link an existing uploaded document in any of the process stages.


In OBTFPM, system should display Document Ids available in the DMS system. In DMS system, the documents can be Uploaded and stored for future access. Every document stored in DMS will have a unique document id along with other Metadata. The uploaded




Document image in the DMS should be available/queried in the Process flow stage screens to link with the task by using the Document ID.

System displays the Documents ids which is not linked with any of the task. Mid office should allow either upload the document or link the document during task processing. The Mid office should allow to Link the same Document in multiple tasks.

- 1. Navigate to the Registration screen.
- 2. On the header of **Registration** screen, click **Documents** button. The Document pop-up screen appears.




3. Click the Add Additional Documents button/ link. The **Document** screen appears.



Field	Description	Sample Values
Document Type	Select the Document type from list.	
	Indicates the document type from metadata.	
Document Code	Select the Document Code from list.	
	Indicates the document Code from metadata.	
Document Title	Specify the document title.	
Document Description	Specify the document description.	
Remarks	Specify the remarks.	
Document Expiry Date	Select the document expiry date.	
Link Document	The link to link the existing uploaded documents from DMS to the workflow task.	

4. Select the document to be uploaded or linked and click the **Link Document** link. The link Document pop up appears.

The value selected in Document Type and Document code of Document screen are defaulted in the Link Document Search screen.



Close

5. Click **Fetch** to retrieve the details from DMS. System Displays all the documents available for the given Document Type and Document Code for the Customer.

Field	Description	Sample Values
Customer ID	This field displays the transaction Customer ID.	
Document ID	Specify the document Id.	
Document Type	Select the document type from list.	
Document Code	Select the document code from list.	
Search Result		
Link Document	The link to link the existing uploaded documents from DMS to the workflow task.	
Document ID	This field displays the document Code from meta data.	
Customer ID	This field displays the transaction Customer ID.	
Document Type	This field displays the document type from meta data.	
Document Code	This field displays the document code from meta data.	
Upload Date	The field displays the upload date of the document.	
Reference Number	The field displays the reference number of the document.	

Link Document Customer Id * Document Id 032204 Document Code * Document Type * Documentary Collection Insurance Policy Link Document **Upload Date** Document Id Customer Id **Document Type Document Code** Reference Number Link 1559 032204 HGJH **INSURANCE** Mar 9, 2023 032IDCB000017631 2649 INSURANCE 032ILCC000021179 Link 032204 testing Mar 29, 2023 4143 032204 INSURANCE May 8, 2023 03211/CU000032029 Link

INSURANCE

INSURANCE

May 8, 2023

May 10, 2023

032ILCU000032042

032IDCB000033105

6. Click **Link** to link the particular document required for the current transaction.

Post linking the document, the user can View, Edit and Download the document.

7. Click Edit icon to edit the documents. The Edit Document screen appears.

Link

Page

4145


4305

1 of 2 (1-5 of 7 items)

032204

032204

< 1 2 >



3.2.5 Bi-Directional Flow for Offline Transactions Initiated from OBTFPM

This topic provides the systematic instructions to initiate the Bi-Directional Flow for Offline Transactions Initiated from OBTFPM.

Offline Transactions means those transactions which are not initiated by OBDX, but are initiated directly by the bank user in OBTFPM upon request received from the customer.

Pre- Conditions:

- Customer Maintenance details are replicated from OBTF to OBTFPM.
- Task is initiated in OBTFPM, Customer ID is captured/populated and Process Reference Number is generated.
- 1. Customer Maintenance details are replicated from OBTF to OBTFPM.
- 2. In OBTFPM, user clicks Request Clarification, the system checks if the request is initiated from OBDX by validating the value available in the submission mode field is "Online".
- 3. In case submission mode is "Online", the user can enter the clarification details in "Clarification Required" placeholder. In case submission mode is not "Online", the system will validates if the counterparty is a OBDX customer by checking the flag "Trade Finance Portal" in the Customer Maintenance table replicated from OBTF. In this case, the user can submit clarification.
- 4. In case submission mode is not "Online", and if the "Trade Finance Portal" flag is set to 'No' in Customer Maintenance Table, the system should display the error message that 'The customer is not subscribed to Trade Finance Portal'. Once the request is submitted, the Request Clarification functionality would be applicable to offline initiated transactions also.

3.3 Data Enrichment

On successful completion of Registration of a Guarantee SBLC Advised - Claim update request, the request moves to Data Enrichment stage. At this stage the bank user can update the various claim fields. The user can input the transaction details.


At this stage the gathered information during Registration stage and claim update request are scrutinized and enter the data as required.

Note


For expired line of limits, the task moves to "Limit Exception" stage under Free Tasks, on 'Submit' of DE Stage with the reason for exception as "Limit Expired".

Do the following steps to acquire a task currently at Data Enrichment stage:


1. Using the entitled login credentials for scrutiny stage, login to the OBTFPM application.




2. On login, user must be able to view the dashboard screen with widgets as mapped to the user.




3. Click Trade Finance> Tasks> Free Tasks.



4. Select the appropriate task and click **Acquire & Edit** to edit the task or click **Acquire** to edit the task from **My Tasks**.



The acquired task will be available in My Tasks tab. Click Edit to provide input for data enrichment stage.



The Data Enrichment stage has five sections as follows:

- Main Details
- Claim Details
- Document Details
- Additional Fields

- Advices
- Additional Details
- Settlement Details
- Summary

Let's look at the details for Data Enrichment stage. User can enter/update the following fields as part of Guarantee/SBLC claim update - Data Enrichment Stage. Some of the fields that are already having value from registration/ online channels may not be editable.

In case of requests received through SWIFT MT765, the task will be created in DE stage directly and the fields will be populated based on the incoming request.


3.3.1 Main Details

Main details section has three sub section as follows:

- Application Details
- Guarantee Details


3.3.1.1 Application Details

All fields displayed under Application details section, would be read only except for the **Priority**. Refer to 3.2.1 Application Details in the Registration stage for more information of the fields.



3.3.1.2 **Guarantee Details**

The fields listed under this section are same as the fields listed under the 3.2.2 Guarantee Details section in 3.2 Registration. Refer to 3.2.2 Guarantee Details for more information of the fields.



3.3.1.3 Action Buttons

Use action buttons based on the description in the following table:

Field	Description	Sample Values
Clarification Details	Clicking the button opens a detailed screen, user can see the clarification details in the window and the status will be Clarification Requested.	
Documents	Click the Documents icon to View/Upload the required documents. Application will display the mandatory and optional documents.	
	The user can view and input/view application details simultaneously.	
	When a user clicks on the uploaded document, Document window get opened and on clicking the view icon of the uploaded document, Application screen should get split into two. The one side of the document allows to view and on the other side allows to input/view the details in the application.	
Remarks	Click the Remarks icon to view the remarks captured as part of Registration stage and also can input Remarks, which can be seen by other users.	
Overrides	Click to view overrides, if any.	


Field	Description	Sample Values
Customer Instruction	Click to view/ input the following	
	Standard Instructions – In this section, the system will populate the details of Standard Instructions maintained for the customer. User will not be able to edit this.	
	Transaction Level Instructions – In this section, OBTFPM user can input any Customer Instructions received as part of transaction processing. This section will be enabled only for customer initiated transactions.	
Incoming Message	Clicking this button allows the user should be able to see the message in case of STP of incoming MT 767.	
	In case of MT798-MT726-MT759 request, user can view MT798 message(726-759) in this place-holder in Header of the task.	
	In case of MT798_MT788-MT799 request, user can view MT798 message (788-799) in this place-holder in Header of the process-task.	
View Undertaking	Clicking this button allows the user should to view the undertaking details.	
Signatures	Click the Signature button to verify the signature of the customer/ bank if required.	
	The user can view the Customer Number and Name of the signatory, Signature image and the applicable operation instructions if any available in the back-office system.	
	If more than one signature is required, system should display all the signatures.	
Request Clarification	User should be able to submit the request for clarification to the "Trade Finance Portal" User for the transactions initiated offline.	

Field	Description	Sample Values
Reject	On click of Reject, user must select a reject reason from a list displayed by the system and the task may be terminated or moved to Reject Approval Stage.	
	Reject Codes:	
	 R1- Documents missing 	
	 R2- Signature Missing 	
	R3- Input Error	
	R4- Insufficient Balance/Limits	
	R5 - Others.	
	Select a Reject code and give a reject description.	
	This reject reason will be available in the remarks window throughout the process.	
Refer	On click of Refer, user will be able to refer the task back to the Data Enrichment user. User must select a Refer Reason from the values displayed by the system. Refer Codes:	
	R1- Documents missing	
	R2- Signature Missing	
	R3- Input Error	
	 R4- Insufficient Balance/Limits 	
	R5 - Others.	
Hold	The details provided will be on hold. This option is used, if there are any pending information yet to be received from applicant.	
Cancel	Cancel the Guarantee/ SBLC Advised - Claim update DE stage inputs.	
Save & Close	Save the information provided and holds the task in you queue for working later. This entire will not submit the request	
	This option will not submit the request	
Next	On click of Next, system should validate if all the mandatory fields have been captured. Necessary error and override messages to be displayed. On successful validation, system moves the task to the next data segment.	

3.3.2 Claim Details

As part of DE, the bank user can update the various claim fields under guarantee advised. The user can also be able to input the transaction details.

The user can scrutinize the claim update request and input data as required.



Provide the Claim details based on the description in the following table:

Field	Description	Sample Values
Claiming Bank	Read only field.	
	The Claiming Party from whom the claim under the Bank Guarantee issued is received while lodging the Guarantee Claim.	
Claiming Bank Name &	Read only field.	
Address	Displays the claiming bank details.	
Claiming Bank Reference	Read only field.	
	This field displays the claiming bank reference number.	
Date of Demand	Read Only field.	
	System defaults value from Guarantee /SBLC Advise claim.	
Demand Indicator	Read Only field.	
	System defaults value from Guarantee /SBLC claim.	
Demand Type	Read Only field.	
	System defaults value from Guarantee /SBLC Advise claim.	
Claim Currency/ Amount	Read Only field.	
	System defaults currency for claim and the claim amount from Guarantee /SBLC claim.	

Field	Description	Sample Values
New Expiry Date	System defaults value from Guarantee /SBLC Advise claim.	
	If the applicant has accepted the extension in expiry date, then the new expiry date should be updated in the Guarantee Amend module in OBTF. Any additional commission for the extension to be calculated from the Amendment module	
New Expiry Date-Local Undertaking	Specify or select the date for new expiry date of local undertaking.	
Demand Statement		
	Specify or click Search icon to search and select the narrative text that constitutes the demand	
Presentation Completion Details	Specify or click Search icon to search and select the presentation of completion details. This field specifies information about the presentation documentation. If the presentation is incomplete, this must specify how the presentation will be completed.	
Additional Amount Information	Specify or click Search icon to search and select the details on additional amount in this field.	
Intermediary	Read Only field.	
	System defaults value from Guarantee /SBLC Advise claim.	
Account with Institution	Read Only field.	
	System defaults value from Guarantee /SBLC Advise claim.	
File Identification	Read Only field.	
	System defaults value from Guarantee /SBLC claim.	
Sender to Receiver Infor-	Read Only field.	
mation	System defaults value from Guarantee /SBLC claim.	

3.3.2.1 Claim Update Details

Provide the Claim Update details based on the description in the following table:

Field	Description	Sample Values
Guarantor Response	The user can select the guarantor response.	
	This values are:	
	Accept Extension	
	Reject Extension	
	Invalid Claim	
Status	Read Only field.	
	System with default status based on the user acceptance or rejection of the extension request.	
	If the applicant has accepted the extension, the status of the claim update should be Extension – Accepted and handoff from OBTFPM should be provided to the Guarantee Amendment function id in OBTF.	
	If the applicant has rejected the extension, the status of the claim update should be Extension – Rejected and handoff from OBTFPM should be provided to the Guarantee Claim Update function id in OBTF.	
	If the applicant has provided the legal injunction, the status of the claim update should be Injunction and handoff from OBTFPM should be provided to the Guarantee Claim Update function id in OBTF.	
	If the bank has found discrepancy in the claim, user selects Invalid Claim. The status should be Rejected and handoff from OBTFPM should be provided to the Guarantee Claim Update function id in OBTF.	
Legal Injunction	User can update the claim status if there is any legal injunction in processing the claim.	
	Toggle On: If Legal injunction toggle is set to 'Yes' all other subsequent fields will be ready only. User cannot update any other field.	
Reason for Refusal	User can enter the reason for refusal.	
	This field appears if you select Reject Claim option in Guarantor Response field.	
Disposal of Documents	User can enter the mode in which the documents have to be disposed in case of rejection of claim.	
Sender to Receiver Information	Specify the details of sender to receiver Information.	

3.3.2.2 <u>Action Buttons</u>

Use action buttons based on the description in the following table:

Field	Description	Sample Values
Clarification Details	Clicking the button opens a detailed screen, user can see the clarification details in the window and the status will be Clarification Requested.	
Documents	Click the Documents icon to View/Upload the required documents.	
	Application will display the mandatory and optional documents.	
	The user can view and input/view application details simultaneously.	
	When a user clicks on the uploaded document, Document window get opened and on clicking the view icon of the uploaded document, Application screen should get split into two. The one side of the document allows to view and on the other side allows to input/view the details in the application.	
Remarks	Click the Remarks icon to view the remarks captured as part of Registration stage and also can input Remarks, which can be seen by other users.	
Overrides	Click to view overrides, if any.	
Customer Instruction	Click to view/ input the following	
	 Standard Instructions – In this section, the system will populate the details of Standard Instructions maintained for the customer. User will not be able to edit this. 	
	 Transaction Level Instructions – In this section, OBTFPM user can input any Customer Instructions received as part of transaction processing. This section will be enabled only for customer initiated transactions. 	
Incoming Message	Clicking this button allows the user should be able to see the message in case of STP of incoming MT 767.	
	In case of MT798-MT726-MT759 request, user can view MT798 message(726-759) in this placeholder in Header of the task.	
	In case of MT798_MT788-MT799 request, user can view MT798 message (788-799) in this placeholder in Header of the process-task.	


Field	Description	Sample Values
View Undertaking	Clicking this button allows the user should to view the undertaking details.	
Signatures	Click the Signature button to verify the signature of the customer/ bank if required.	
	The user can view the Customer Number and Name of the signatory, Signature image and the applicable operation instructions if any available in the back-office system.	
	If more than one signature is required, system should display all the signatures.	
Request Clarification	User should be able to submit the request for clarification to the "Trade Finance Portal" User for the transactions initiated offline.	
Reject	On click of Reject, user must select a reject reason from a list displayed by the system and the task may be terminated or moved to Reject Approval Stage.	
	Reject Codes:	
	 R1- Documents missing 	
	 R2- Signature Missing 	
	R3- Input Error	
	R4- Insufficient Balance/LimitsR5 - Others.	
	Select a Reject code and give a reject description.	
	This reject reason will be available in the remarks window throughout the process.	
Refer	On click of Refer, user will be able to refer the task back to the Data Enrichment user. User must select a Refer Reason from the values displayed by the system.	
	Refer Codes:	
	 R1- Documents missing 	
	 R2- Signature Missing 	
	R3- Input Error	
	R4- Insufficient Balance/LimitsR5 - Others.	
Hold	The details provided will be on hold.	
	This option is used, if there are any pending information yet to be received from applicant.	
Cancel	On click of Cancel the user can cancel the task window and return to the dashboard. The data input will not be saved.	

Field	Description	Sample Values
Save & Close	Save the information provided and holds the task in 'My Tasks' for working later. This option will not submit the request	
Back	On clicking Back, system should move the task to the previous segment.	
Next	On click of Next, system should validate if all the mandatory fields have been captured. Necessary error and override messages to be displayed. On successful validation, system moves the task to the next data segment.	

3.3.3 <u>Document Details</u>

In Document Details, the user can to view the Documents required for a claim and verify if the Claim Documents are submitted as per documents required. The user, can scrutinize the claim request and input data as required.

The user can capture documents as part of claim under Guarantee/SBLC Advised - DE Stage.



If documents to be submitted were provided in the Guarantee Advised they will be defaulted, else the user can capture the documents submitted under the claim in this section.

Provide the Document details based on the description in the following table:

Field	Description	Sample Values
Code	User can enter the document code.	
Document Description	System defaults the document name based on the document code.	
Сору	Copy of the document.	

Field	Description	Sample Values
Original	Original claim document.	
Documents Received	System displays whether original document is received or not.	
Action	Click Edit icon to edit the document details. Click Delete icon to delete the document details.	

3.3.3.1 Additional Conditions

Field	Description	Sample Values
FFT Code	FFT code is auto-populated,	
FFT Description	System defaults the FFT description based on the FFT code.	
Action	Click Edit icon to edit the FFT details. Click Delete icon to delete the FFT details.	

3.3.3.2 Action Buttons

Use action buttons based on the description in the following table:


Field	Description	Sample Values
Clarification Details	Clicking the button opens a detailed screen, user can see the clarification details in the window and the status will be Clarification Requested.	
Documents	Click the Documents icon to View/Upload the required documents.	
	Application will display the mandatory and optional documents.	
	The user can view and input/view application details simultaneously.	
	When a user clicks on the uploaded document, Document window get opened and on clicking the view icon of the uploaded document, Application screen should get split into two. The one side of the document allows to view and on the other side allows to input/view the details in the application.	
Remarks	Click the Remarks icon to view the remarks captured as part of Registration stage and also can input Remarks, which can be seen by other users.	
Overrides	Click to view overrides, if any.	

Field	Description	Sample Values
Customer Instruction	Standard Instructions – In this section, the system will populate the details of Standard Instructions maintained for the customer. User will not be able to edit this. Transaction Level Instructions – In this section, OBTFPM user can input any Customer Instructions received as part of transaction processing. This section will be enabled only for customer initiated transactions.	
Incoming Message	Clicking this button allows the user should be able to see the message in case of STP of incoming MT 767.	
	In case of MT798-MT726-MT759 request, user can view MT798 message(726-759) in this placeholder in Header of the task.	
	In case of MT798_MT788-MT799 request, user can view MT798 message (788-799) in this place-holder in Header of the process-task.	
View Undertaking	Clicking this button allows the user should to view the undertaking details.	
Signatures	Click the Signature button to verify the signature of the customer/ bank if required.	
	The user can view the Customer Number and Name of the signatory, Signature image and the applicable operation instructions if any available in the back-office system.	
	If more than one signature is required, system should display all the signatures.	
Request Clarification	User should be able to submit the request for clarification to the "Trade Finance Portal" User for the transactions initiated offline.	

Field	Description	Sample Values
Reject	On click of Reject, user must select a reject reason from a list displayed by the system and the task may be terminated or moved to Reject Approval Stage.	
	Reject Codes:	
	R1- Documents missing	
	R2- Signature Missing	
	R3- Input Error	
	R4- Insufficient Balance/Limits	
	R5 - Others.	
	Select a Reject code and give a reject description.	
	This reject reason will be available in the remarks window throughout the process.	
Refer	On click of Refer, user will be able to refer the task back to the Data Enrichment user. User must select a Refer Reason from the values displayed by the system.	
	Refer Codes:	
	R1- Documents missing	
	R2- Signature Missing	
	R3- Input Error	
	R4- Insufficient Balance/LimitsR5 - Others.	
Hold	The details provided will be on hold.	
	This option is used, if there are any pending information yet to be received from applicant.	
Cancel	On click of Cancel the user can cancel the task window and return to the dashboard. The data input will not be saved.	
Save & Close	Save the information provided and holds the task in 'My Tasks' for working later.	
	This option will not submit the request	
Back	On clicking Back, system should move the task to the previous segment.	
Next	On click of Next, system should validate if all the mandatory fields have been captured. Necessary error and override messages to be displayed. On successful validation, system moves the task to the next data segment.	

3.3.4 Additional Fields

3.3.4.1 This stage displays the additional fields based on the User defined fields maintained in the system.



3.3.4.2 Action Buttons

Use action buttons based on the description in the following table:


Field	Description	Sample Values
Clarification Details	Clicking the button opens a detailed screen, user can see the clarification details in the window and the status will be Clarification Requested.	
Documents	Click the Documents icon to View/Upload the required documents.	
	Application will display the mandatory and optional documents.	
	The user can view and input/view application details simultaneously.	
	When a user clicks on the uploaded document, Document window get opened and on clicking the view icon of the uploaded document, Application screen should get split into two. The one side of the document allows to view and on the other side allows to input/view the details in the application.	
Remarks	Click the Remarks icon to view the remarks captured as part of Registration stage and also can input Remarks, which can be seen by other users.	
Overrides	Click to view overrides, if any.	

Field	Description	Sample Values
Customer Instruction	Click to view/ input the following	
	Standard Instructions – In this section, the system will populate the details of Standard Instructions maintained for the customer. User will not be able to edit this.	
	 Transaction Level Instructions – In this section, OBTFPM user can input any Customer Instructions received as part of transaction processing. This section will be enabled only for customer initiated transactions. 	
Incoming Message	Clicking this button allows the user should be able to see the message in case of STP of incoming MT 767.	
	In case of MT798-MT726-MT759 request, user can view MT798 message(726-759) in this place-holder in Header of the task.	
	In case of MT798_MT788-MT799 request, user can view MT798 message (788-799) in this place-holder in Header of the process-task.	
View Undertaking	Clicking this button allows the user should to view the undertaking details.	
Signatures	Click the Signature button to verify the signature of the customer/ bank if required.	
	The user can view the Customer Number and Name of the signatory, Signature image and the applicable operation instructions if any available in the back-office system.	
	If more than one signature is required, system should display all the signatures.	
Request Clarification	User should be able to submit the request for clarification to the "Trade Finance Portal" User for the transactions initiated offline.	


Field	Description	Sample Values
Reject	On click of Reject, user must select a reject reason from a list displayed by the system and the task may be terminated or moved to Reject Approval Stage.	
	Reject Codes:	
	R1- Documents missing	
	R2- Signature Missing	
	R3- Input Error	
	R4- Insufficient Balance/Limits	
	R5 - Others.	
	Select a Reject code and give a reject description.	
	This reject reason will be available in the remarks window throughout the process.	
Refer	On click of Refer, user will be able to refer the task back to the Data Enrichment user. User must select a Refer Reason from the values displayed by the system.	
	Refer Codes:	
	R1- Documents missing	
	R2- Signature Missing	
	R3- Input Error	
	R4- Insufficient Balance/LimitsR5 - Others.	
Hold	The details provided will be on hold.	
	This option is used, if there are any pending information yet to be received from applicant.	
Cancel	On click of Cancel the user can cancel the task window and return to the dashboard. The data input will not be saved.	
Save & Close	Save the information provided and holds the task in 'My Tasks' for working later.	
	This option will not submit the request	
Back	On clicking Back, system should move the task to the previous segment.	
Next	On click of Next, system should validate if all the mandatory fields have been captured. Necessary error and override messages to be displayed. On successful validation, system moves the task to the next data segment.	

3.3.5 Advices

This section defaults the advices maintained for the product based on the advices maintained at the Product level.



The user can also suppress the Advice, if required.



3.3.5.1

Field	Description	Sample Values
Suppress Advice	Toggle on : Switch on the toggle if advice is suppressed.	
	Toggle off : Switch off the toggle if suppress advice is not required for the amendments	
Advice Name	Read only field.	
	Displays the advise name.	
Medium	The medium of advices is defaulted from the system. User can update if required.	
Advice Party	Read only field.	
	Value be defaulted from Guarantee /SBLC advise.	
Party ID	Read only field.	
	Value be defaulted from Guarantee /SBLC advise.	
Party Name	Read only field.	
	Value be defaulted from Guarantee /SBLC advise.	
Free Format Text		
+	Click plus icon to add new FFT code.	
FTT Code	User can select the FFT code as a part of free text.	
FFT Description	FFT description is populated based on the FFT code selected.	
D)	Click edit icon to edit any existing FFT code.	
Action	Click Edit icon to edit the FFT details.	
	Click Delete icon to delete the FFT details.	
Instruction Details		
+	Click plus icon to add new instruction code.	
Instruction Code	User can select the instruction code as a part of free text.	

Field	Description	Sample Values
Instruction Description	Instruction description is populated based on the Instruction code selected.	
	Click edit icon to edit any existing Instruction code.	
Action	Click Edit icon to edit the instruction details. Click Delete icon to delete the instruction details.	

3.3.5.2 Action Buttons

Field	Description	Sample Values
Clarification Details	Clicking the button opens a detailed screen, user can see the clarification details in the window and the status will be Clarification Requested.	
Documents	Click the Documents icon to View/Upload the required documents.	
	Application will display the mandatory and optional documents.	
	The user can view and input/view application details simultaneously.	
	When a user clicks on the uploaded document, Document window get opened and on clicking the view icon of the uploaded document, Application screen should get split into two. The one side of the document allows to view and on the other side allows to input/view the details in the application.	
Remarks	Click the Remarks icon to view the remarks captured as part of Registration stage and also can input Remarks, which can be seen by other users.	
Overrides	Click to view overrides, if any.	
Customer Instruction	Click to view/ input the following	
	 Standard Instructions – In this section, the system will populate the details of Standard Instructions maintained for the customer. User will not be able to edit this. Transaction Level Instructions – In this section, OBTFPM user can input any Customer Instructions received as part of transaction processing. This section will be enabled only for customer initiated transactions. 	


Field	Description	Sample Values
Incoming Message	Clicking this button allows the user should be able to see the message in case of STP of incoming MT 767.	
	In case of MT798-MT726-MT759 request, user can view MT798 message(726-759) in this place-holder in Header of the task.	
	In case of MT798_MT788-MT799 request, user can view MT798 message (788-799) in this place-holder in Header of the process-task.	
View Undertaking	Clicking this button allows the user should to view the undertaking details.	
Signatures	Click the Signature button to verify the signature of the customer/ bank if required.	
	The user can view the Customer Number and Name of the signatory, Signature image and the applicable operation instructions if any available in the back-office system.	
	If more than one signature is required, system should display all the signatures.	
Request Clarification	User should be able to submit the request for clarification to the "Trade Finance Portal" User for the transactions initiated offline.	
Reject	On click of Reject, user must select a reject reason from a list displayed by the system and the task may be terminated or moved to Reject Approval Stage.	
	Reject Codes:	
	 R1- Documents missing 	
	 R2- Signature Missing 	
	R3- Input Error	
	R4- Insufficient Balance/LimitsR5 - Others.	
	Select a Reject code and give a reject description.	
	This reject reason will be available in the remarks window throughout the process.	

Field	Description	Sample Values
Refer	On click of Refer, user will be able to refer the task back to the Data Enrichment user. User must select a Refer Reason from the values displayed by the system.	
	Refer Codes:	
	R1- Documents missing	
	R2- Signature Missing	
	R3- Input Error	
	R4- Insufficient Balance/Limits	
	R5 - Others.	
Hold	The details provided will be on hold.	
	This option is used, if there are any pending information yet to be received from applicant.	
Cancel	On click of Cancel the user can cancel the task window and return to the dashboard. The data input will not be saved.	
Save & Close	Save the information provided and holds the task in 'My Tasks' for working later. This option will not submit the request	
Back	On clicking Back, system should move the task to the previous segment.	
Next	On click of Next, system should validate if all the mandatory fields have been captured. Necessary error and override messages to be displayed. On successful validation, system moves the task to the next data segment.	

3.3.6 Additional Details

As a part of Additional details section, Guarantee /Standby claim may have impact on Charges.


If any of the fields in the financial section of the pop up screen is checked then the limits and collaterals screen will be enabled.



3.3.6.1 Commission, Charges and Taxes Details

Click on **Default Charges** button to the default commission, charges and tax if any, will get populated.

If default charges are available under the product, they should be defaulted here with values. If customer or customer group specific charges are maintained, then the same will be defaulted from back end system.



3.3.6.2 <u>Commission Details</u>

Provide the Commission Details based on the description provided in the following table:

Field	Description	Sample Values
Event	Read only field. This field displays the event name.	
Event Description	Read only field. This field displays the description of the event.	
Component	Select the commission component	
Rate	Defaults from product. User can change the rate, if required.	
Modified Rate	From the default value, if the rate is changed or the amount is changed, the same gets updated in 'Modified' field.	
Currency	Defaults the currency in which the commission needs to be collected.	
Amount	An amount that is maintained under the product code defaults in this field. User can modify the value, if required.	
Modified	From the default value, if the rate is changed or the amount is changed, the same gets updated in 'Modified' field.	
Defer	Select the check box, if charges/commissions has to be deferred and collected at any future step.	
Waive	Select the check box to waive charges/commission.	
	Based on the customer maintenance, the charges/commission can be marked for Billing or Defer.	
Charge Party	Charge party will be 'Applicant' by Default. You can change the value to Beneficiary.	
Settlement Account	Details of the Settlement Account.	
Amendable	Displays if the field is amendable or not.	

3.3.6.3 Charge Details

Provide the Charge Details based on the description provided in the following table:

Field	Description	Sample Values
Tag Currency	Defaults the tag currency in which the charges have to be collected.	

Field	Description	Sample Values
Tag Amount	Tag amount that is maintained under the product code.	
Component	Charge Component type.	
Currency	Defaults the currency in which the charges have to be collected.	
Amount	An amount that is maintained under the product code gets defaulted in this field. User can edit the value, if required.	
Modified	From the default value, if the rate is changed or the amount is changed, the same gets updated in 'Modified' field.	
Billing	If charges are handled by separate billing engine, then by selecting billing the details to be available for billing engine for further processing.	
	On simulation of charges/commission from Back Office, if any of the Charges/Commission component for the customer is 'Billing' enabled, 'Billing' toggle for that component should be automatically checked in OBTFPM.	
	The user can not select/de-select the check box if it is de-selected by default.	
	This field is disabled, if 'Defer' toggle is enabled.	
Defer	If charges have to be deferred and collected at any future step, this check box has to be selected.	
	On simulation of charges/commission from Back Office, if any of the Charges/Commission component for the customer is AR-AP tracking enabled, 'Defer' toggle for that component should be automatically checked in OBTFPM.	
	The user can select/de-select the check box. On de-selection the user has to click on 'Recalculate' charges button for re-simulation.	
Waive	If charges have to be waived, this check box has to be selected.	
	Based on the customer maintenance, the charges should be marked for Billing or for Defer.	
	This field is disabled, if 'Defer' toggle is enabled.	
Charge Party	Charge party will be applicant by default. You can change the value to beneficiary	
Settlement Account	Details of the settlement account.	

3.3.6.4 Tax Details

The tax component defaults if maintained in the product level. Tax detail cannot be updated by you and any change in Tax amount on account of modification of charges/ commission will be available on click of Re-Calculate button or on hand off to back-end system.

Following Tax Details will be displayed:

Field	Description	Sample Values
Component	Tax Component type.	
Туре	Type of tax Component.	
Value Date	This field displays the value date of tax component.	
Currency	The tax currency is the same as the commission.	
Amount	The tax amount defaults based on the percentage of commission maintained. User can edit the tax amount, if required.	
Billing	If taxes are handled by separate billing engine, then by selecting billing the details to be available for billing engine for further processing. This field is disabled, if 'Defer' toggle is enabled.	
Defer	If taxes have to be deferred and collected at any future step, this option has to be enabled. The user can enable/disable the option the check box. On de-selection the user has to click on 'Recalculate' charges button for re-simulation.	
Settlement Account	Details of the settlement account.	

3.3.6.5 Tracers Details

The bank users can capture these tracer details for Claim Lodgment in Guarantee and should send the tracers to the customer till its Settled / Extended / Rejected / Injunction.




Field	Description	Sample Values
Tracer Code	Read only field.	
	Tracer code is defaulted by the system maintained in the Product level.	
Description	Read only field.	
	Description of the racer code is auto populated.	

Field	Description	Sample Values
Party Type	Specify the party type or click 'Search' to search and select the Receiver party type from the lookup.	
Required	Enable this option, if the respective tracer is required.	
Maximum Tracers	Specify the value for maximum number of tracers to be sent.	
	Maximum allowed is 99 exceeding the same system should prompt an error message for the same "Maximum number of numerals allowed is: 2" and should clear the field to enter the correct value by the user.	
	Maximum Tracers cannot be less than the "Number Sent", system needs to validate the same.	
Number Sent	Number Sent is defaulted by the System with the value, where the number of tracers sent so far. And it cannot be greater than the "Maximum Tracers".	
Start Days	Specify the number of days after which the tracer has to be sent from the Tracer Start date. It should be positive numeric value.	
Last Sent On	Read only field.	
	Tracer last sent date is defaulted by the system.	
Medium	Select the medium in which the Tracer has to be generated. It lists all the possible mediums maintained in the system.	
	The options are:	
	SWIFT MAIL	
Frequency	Specify the medium in which the Tracer has to be generated. It should be positive numeric value.	
	System should default the Frequency captured as part of the Contract here and should allow the user to modify the same.	

Field	Description	Sample Values
Template ID	Specify the party type or click 'Search' to search and select the template ID in which the tracer has to be generated from the lookup.	
	It is a lookup which lists all the possible templates maintained in the system.	
	Template ID is nothing but the data that goes in Tag 79 in MT799.	
	This template ID is applicable only for medium 'SWIFT'	
	Template lookup displays all the template ids applicable for the given Tracer Code.	
Action	Click the Edit icon to edit the tracer details.	

3.3.6.6 Preview Message

The bank user can view a preview of the message and advice simulated from back office which is based on the guarantee Claim captured in the previous screen.




The Preview section consists of following.

Field	Description	Sample Values
Preview SWIFT Message		
Language	Read only field.	
	English is set as default language for the preview	
Message Type	Select the message type.	
Message Status	Read only field.	
	Display the message status of draft message of guarantee details.	


Field	Description	Sample Values
Repair Reason	Read only field.	
	Display the message repair reason of draft message of guarantee details.	
Preview Message	Display a preview of the draft message.	
Preview Mail Device		
Language	Read only field.	
	English is set as default language for the preview	
Advice Type	Select the advice type.	
Message Status	Read only field.	
	Display the message status of advice message of guarantee details.	
Repair Reason	Read only field.	
	Display the message repair reason of advice message of guarantee details.	
Preview Message	Display a preview of the advice.	

3.3.6.7 FX Linkage

This section enables the user to link the existing FX contract(s) to the Guarantee/SBLC Claim Settlement. FX Linkage call should be triggered on DE-submit.







Provide the FX linkage detail based on the description in the following table:

Field	Description	Sample Values
Click + plus icon to add new	r FX linkage details.	
Below fields are displayed of	on the FX linkage pop-up screen, if the user clicks plu	ıs icon.
FX Reference Number	Select the FX contract reference number from the LOV.	
	On select and save and close, system defaults the available amount, bot currency, sold currency and rate.	
	Forward FX Linkage available for selection at guarantee would be as follows,	
	 Counterparty of the FX contract should be the counterparty of the Guarantee Claim. 	
	 Active Forward FX transactions authorized not marked for auto liquidation. 	
	Guarantee Claim currency should be Sold currency for claim settlement for Guarantees Issued.	
Currency	This field displays the FX BOT currency from the linked FX contract.	
Contract Amount	This field displays the FX BOT currency and Amount.	
	The user can change the currency.	

Field	Description	Sample Values
Available FX Contract Amount	This field displays the available FX contract amount.	
	The value is from the "Available Amount" in FXDLINKG screen in OBTR.	
	Available Amount BOT currency and Amount is displayed.	
Linkage Amount	This field displays the amount available for linkage.	
	The Linkage amount should default the LC Contract Currency and allowed to change the linkage amount alone.	
	The validation "Sum of Linked amount will not be greater than contract amount" or "Linkage amount will not be greater than the available amount for linkage" should be triggered on save of the FX linkage screen when trying to link the single FX or multiple FX.	
Rate	This field displays the exchange rate defaulted from the linked FX Contract.	
FX Amount in Local Currency	This field displays the FX amount in local currency.	
	The value is defaulted as FX BOT currency and Amount from FXDTRONL	
FX Expiry Date	This field displays the expiry date from the linked FX contract.	
FX Delivery Period - From	This field displays the date from which the contract is valid for utilization.	
FX Delivery Period - To	This field displays the date to which the contract is valid for utilization.	
Below fields appear in the F	X linkage grid along with the above fields.	I
Bought Currency	This field displays the currency from the linked FX contract.	
Sold Currency	This field displays the currency from the linked FX contract.	
Available Contract Amount	Available amount will be FX contract amount minus the linked amount. Available amount for linkage should be greater than Zero.	
Linked Amount	Sum of Linked amount will not be greater than LC contract amount.	
	Linked amount will not be greater than the available amount for linkage.	

Field	Description	Sample Values
Total Utilized amount	This field displays the total amount utilized against the corresponding linked FX. On query, both Utilized and Total Utilized amount holds the amount of latest version.	
	The value is Total Utilized Amount BOT currency and Amount for Import LC/Guarantee Issuance from FXDLINKG	
Average FX Rate	Multiple forward FX contract could be linked, and exchange rate of FX contract vary from each. Hence, effective exchange rate for bill would be arrived using weighted average method and it is utilized during purchase/negotiation/discount or liquidation of the bill. This will be populated in the Average FX Rate.	
Action	Click the Edit icon to modify the FX details. Click the Delete icon to delete the FX details.	


3.3.6.8 Action Buttons

Field	Description	Sample Values
Clarification Details	Clicking the button opens a detailed screen, user can see the clarification details in the window and the status will be Clarification Requested.	
Documents	Click the Documents icon to View/Upload the required documents.	
	Application will display the mandatory and optional documents.	
	The user can view and input/view application details simultaneously.	
	When a user clicks on the uploaded document, Document window get opened and on clicking the view icon of the uploaded document, Application screen should get split into two. The one side of the document allows to view and on the other side allows to input/view the details in the application.	
Remarks	Click the Remarks icon to view the remarks captured as part of Registration stage and also can input Remarks, which can be seen by other users.	
Overrides	Click to view overrides, if any.	

Field	Description	Sample Values
Customer Instruction	Click to view/ input the following	
	Standard Instructions – In this section, the system will populate the details of Standard Instructions maintained for the customer. User will not be able to edit this.	
	Transaction Level Instructions – In this section, OBTFPM user can input any Customer Instructions received as part of transaction processing. This section will be enabled only for customer initiated transactions.	
Incoming Message	Clicking this button allows the user should be able to see the message in case of STP of incoming MT 767.	
	In case of MT798-MT726-MT759 request, user can view MT798 message(726-759) in this place-holder in Header of the task.	
	In case of MT798_MT788-MT799 request, user can view MT798 message (788-799) in this place-holder in Header of the process-task.	
View Undertaking	Clicking this button allows the user should to view the undertaking details.	
Signatures	Click the Signature button to verify the signature of the customer/ bank if required.	
	The user can view the Customer Number and Name of the signatory, Signature image and the applicable operation instructions if any available in the back-office system.	
	If more than one signature is required, system should display all the signatures.	
Request Clarification	User should be able to submit the request for clarification to the "Trade Finance Portal" User for the transactions initiated offline.	

Field	Description	Sample Values
Reject	On click of Reject, user must select a reject reason from a list displayed by the system and the task may be terminated or moved to Reject Approval Stage.	
	Reject Codes:	
	R1- Documents missing	
	 R2- Signature Missing 	
	R3- Input Error	
	R4- Insufficient Balance/LimitsR5 - Others.	
	Select a Reject code and give a reject description.	
	This reject reason will be available in the remarks window throughout the process.	
Refer	On click of Refer, user will be able to refer the task back to the Data Enrichment user. User must select a Refer Reason from the values displayed by the system.	
	Refer Codes:	
	R1- Documents missing	
	R2- Signature Missing	
	R3- Input Error	
	R4- Insufficient Balance/LimitsR5 - Others.	
Hold	The details provided will be on hold. This option is used, if there are any pending information yet to be received from applicant.	
Cancel	On click of Cancel the user can cancel the task window and return to the dashboard. The data input will not be saved.	
Save & Close	Save the information provided and holds the task in 'My Tasks' for working later.	
	This option will not submit the request	
Back	On clicking Back, system should move the task to the previous segment.	
Next	On click of Next, system should validate if all the mandatory fields have been captured. Necessary error and override messages to be displayed. On successful validation, system moves the task to the next data segment.	

3.3.7 Settlement Details



Provide the settlement details based on the description in the following table:

Field	Description	Sample Values
Current Event	The user can select the check box to populate the settlement details of the current event associated with the task. On De-selecting the check box, the system list all the accounts under the settlement details irrespective of the current event.	
Component	System populates the components based on the product selected.	
Currency	System displays the currency for the component.	
Debit/Credit	System defaults the debit/credit indicators for the components	
Account	System defaults the value based on the product selected.	
Account Description	System displays the account description for the account chosen.	
Account Currency	System displays the account currency for all items based on account number	
Netting Indicator	System displays the netting indicator applicable.	
Current Event	System displays the current event as Y or N.	

On click of any component in the grid, the application displays Party Details, Payment Details and Remittance Information.

3.3.7.1 Party Details

Provide the party details based on the description in the following table:

Field	Description	Sample Values
Transfer Type	Select the transfer type from the drop list: Customer Transfer Bank Transfer for own account Direct Debit Advice Managers Check Customer Transfer with Cover Bank Transfer	
Charge Details	Select the charge details for the transactions: Beneficiary All Charges Remitter Our Charges Remitter All Charges	
Netting Indicator	Select the netting indicator for the component: • Yes • No	
Ordering Customer	Select the ordering customer from the LOV.	
Ordering Institution	Select the ordering institution from the LOV.	
Senders Correspondent	Select the senders correspondent from the LOV.	
Receivers Correspondent	Select the receivers correspondent from the LOV.	
Intermediary Institution	Select the intermediary institution from the LOV.	
Account with Institution	Select the account with institution from the LOV.	
Beneficiary Institution	Select the beneficiary institution from the LOV.	
Ultimate Beneficiary	Select the ultimate beneficiary from the LOV.	
Intermediary Reimburse- ment Institution	Select the intermediary reimbursement institution from the LOV.	

3.3.7.2 Payment Details

Provide the Payment Details based on the description in the following table:

Field	Description	Sample Values
Sender to Receiver 1	Provide the sender to receiver message.	
Sender to Receiver 2	Provide the sender to receiver message.	

Field	Description	Sample Values
Sender to Receiver 3	Provide the sender to receiver message.	
Sender to Receiver 4	Provide the sender to receiver message.	
Sender to Receiver 5	Provide the sender to receiver message.	
Sender to Receiver 6	Provide the sender to receiver message.	

3.3.7.3 Remittance Information

Provide the Payment Details based on the description in the following table:

Field	Description	Sample Values
Payment Detail 1	Provide the payment details.	
Payment Detail 2	Provide the payment details.	
Payment Detail 3	Provide the payment details.	
Payment Detail 4	Provide the payment details.	

3.3.7.4 Action Buttons

Field	Description	Sample Values
Clarification Details	Clicking the button opens a detailed screen, user can see the clarification details in the window and the status will be Clarification Requested.	
Documents	Click the Documents icon to View/Upload the required documents.	
	Application will display the mandatory and optional documents.	
	The user can view and input/view application details simultaneously.	
	When a user clicks on the uploaded document, Document window get opened and on clicking the view icon of the uploaded document, Application screen should get split into two. The one side of the document allows to view and on the other side allows to input/view the details in the application.	
Remarks	Click the Remarks icon to view the remarks captured as part of Registration stage and also can input Remarks, which can be seen by other users.	
Overrides	Click to view overrides, if any.	

Field	Description	Sample Values
Customer Instruction	Click to view/ input the following	
	Standard Instructions – In this section, the system will populate the details of Standard Instructions maintained for the customer. User will not be able to edit this.	
	 Transaction Level Instructions – In this section, OBTFPM user can input any Customer Instructions received as part of transaction processing. This section will be enabled only for customer initiated transactions. 	
Incoming Message	Clicking this button allows the user should be able to see the message in case of STP of incoming MT 767.	
	In case of MT798-MT726-MT759 request, user can view MT798 message(726-759) in this placeholder in Header of the task.	
	In case of MT798_MT788-MT799 request, user can view MT798 message (788-799) in this place-holder in Header of the process-task.	
View Undertaking	Clicking this button allows the user should to view the undertaking details.	
Signatures	Click the Signature button to verify the signature of the customer/ bank if required.	
	The user can view the Customer Number and Name of the signatory, Signature image and the applicable operation instructions if any available in the back-office system.	
	If more than one signature is required, system should display all the signatures.	
Request Clarification	User should be able to submit the request for clarification to the "Trade Finance Portal" User for the transactions initiated offline.	


Field	Description	Sample Values
Reject	On click of Reject, user must select a reject reason from a list displayed by the system and the task may be terminated or moved to Reject Approval Stage.	
	Reject Codes:	
	 R1- Documents missing 	
	 R2- Signature Missing 	
	R3- Input Error	
	 R4- Insufficient Balance/Limits 	
	R5 - Others.	
	Select a Reject code and give a reject description.	
	This reject reason will be available in the remarks window throughout the process.	
Refer	On click of Refer, user will be able to refer the task back to the Data Enrichment user. User must select a Refer Reason from the values displayed by the system.	
	Refer Codes:	
	 R1- Documents missing 	
	 R2- Signature Missing 	
	R3- Input Error	
	R4- Insufficient Balance/LimitsR5 - Others.	
Hold	The details provided will be on hold. This option is used, if there are any pending infor-	
	mation yet to be received from applicant.	
Cancel	On click of Cancel the user can cancel the task window and return to the dashboard. The data input will not be saved.	
Save & Close	Save the information provided and holds the task in 'My Tasks' for working later.	
	This option will not submit the request	
Back	On clicking Back, system should move the task to the previous segment.	
Next	On click of Next, system should validate if all the mandatory fields have been captured. Necessary error and override messages to be displayed. On successful validation, system moves the task to the next data segment.	

3.3.8 **Summary**

User can review the summary screen for Guarantee SBLC Advised Claim update request.



In this section the user can see the summary tiles. The tiles must display a list of important fields with values. The tiles where fields have been amended is highlighted in different color, User must be also able to drill down from summary tiles into respective data segments.



Tiles Displayed in Summary

- Main Details User can view the application details and Guarantee/ Standby details.
 User can modify the details if required.
- Claim Details User can view the claim details.
- Documents Details User can view the Document details.
- Advices User can view the advices details.
- Commission, Charges and taxes User can view the details provided for charges. User can modify the details if required.
- Preview Message User can drill down to view the message preview, legal verification and customer draft confirmation details. The message preview screen has the Legal Verification details.
- Settlement Details User should be able to view the settlement details.
- Party Details User can view the party details like beneficiary, advising bank etc.
- Tracer Details User can view the tracer details.
- Compliance The compliance tile has the KYC, Sanctions and AML
- Accounting Details User can see the accounting details.

Note

When the Value Date is different from the Transaction Date for one or more accounting entries, system displays an Alert Message "Value Date is different from Transaction Date for one or more Accounting entries.

FX Linkage - User can view theFX Linkage details.

3.3.8.1 <u>Action Buttons</u>

Field	Description	Sample Values
Clarification Details	Clicking the button opens a detailed screen, user can see the clarification details in the window and the status will be Clarification Requested.	
Documents	Click the Documents icon to View/Upload the required documents.	
	Application will display the mandatory and optional documents.	
	The user can view and input/view application details simultaneously.	
	When a user clicks on the uploaded document, Document window get opened and on clicking the view icon of the uploaded document, Application screen should get split into two. The one side of the document allows to view and on the other side allows to input/view the details in the application.	
Remarks	Click the Remarks icon to view the remarks captured as part of Registration stage and also can input Remarks, which can be seen by other users.	
Overrides	Click to view overrides, if any.	
Customer Instruction	Click to view/ input the following	
	 Standard Instructions – In this section, the system will populate the details of Standard Instructions maintained for the customer. User will not be able to edit this. 	
	 Transaction Level Instructions – In this section, OBTFPM user can input any Customer Instructions received as part of transaction processing. This section will be enabled only for customer initiated transactions. 	
Incoming Message	Clicking this button allows the user should be able to see the message in case of STP of incoming MT 767.	
	In case of MT798-MT726-MT759 request, user can view MT798 message(726-759) in this placeholder in Header of the task.	
	In case of MT798_MT788-MT799 request, user can view MT798 message (788-799) in this place-holder in Header of the process-task.	

Field	Description	Sample Values
View Undertaking	Clicking this button allows the user should to view the undertaking details.	
Signatures	Click the Signature button to verify the signature of the customer/ bank if required.	
	The user can view the Customer Number and Name of the signatory, Signature image and the applicable operation instructions if any available in the back-office system.	
	If more than one signature is required, system should display all the signatures.	
Request Clarification	User should be able to submit the request for clarification to the "Trade Finance Portal" User for the transactions initiated offline.	
Reject	On click of Reject, user must select a reject reason from a list displayed by the system and the task may be terminated or moved to Reject Approval Stage.	
	Reject Codes:	
	 R1- Documents missing 	
	 R2- Signature Missing 	
	R3- Input Error	
	R4- Insufficient Balance/Limits	
	R5 - Others.	
	Select a Reject code and give a reject description.	
	This reject reason will be available in the remarks window throughout the process.	
Refer	On click of Refer, user will be able to refer the task back to the Data Enrichment user. User must select a Refer Reason from the values displayed by the system.	
	Refer Codes:	
	R1- Documents missing	
	R2- Signature Missing	
	R3- Input Error R4- Input Fire and Balance (Limits)	
	R4- Insufficient Balance/LimitsR5 - Others.	
Hold	The details provided will be on hold.	
	This option is used, if there are any pending information yet to be received from applicant.	
Cancel	On click of Cancel the user can cancel the task window and return to the dashboard. The data input will not be saved.	

Field	Description	Sample Values
Save & Close	Save the information provided and holds the task in 'My Tasks' for working later. This option will not submit the request	
Back	On clicking Back, system should move the task to the previous segment.	

3.4 Multi Level Approval

This stage allows the approver user to approve a Guarantee SBLC Advised - Claim Update transaction.

Log in into OBTFPM application and open the task to see the summary tiles. The tiles should display a list of important fields with values. User must be able to drill down from summary Tiles into respective data segments to verify the details of all fields under the data segment.

Note

The user can simulate/recalculate charge details and during calling the handoff, if handoff is failed with error the OBTFM displays the Handoff failure error during the Approval of the task.

3.4.1 Re-Key Authorization


The application will request approver for few critical field values as an authorization step. If the values captured match with the values available in the screen, system will allow user to open the transaction screens for further verification. If the re-key values are different from the values captured, then application will display an error message.

Open the task and re-key some of the critical field values from the request in the Re-key screen. Some of the fields below will dynamically be available for re-key.:

- Claim Amount
- •
- Currency

•


Re-key is applicable to the first approver in case of multiple approvers. All approvers will however be able see the summary tiles and the details in the screen by drill down from tiles.



In Approval, the user can view a snapshot of the amendment made to this transaction. Corresponding to the field the current latest Guarantee value and the new amended value should be displayed.

6. On clicking next, user can see the summary

3.4.1.1 **Summary**



Tiles Displayed in Summary

- Main Details User can view the application details and Guarantee/ Standby details.
 User can modify the details if required.
- Claim Details User can view the party details like beneficiary, advising bank etc.
- Documents Details User can view the Document details.

- Advices User can view the advices details.
- Commission, Charges and taxes User can view the details provided for charges. User can modify the details if required.
- Preview Message User can drill down to view the message preview, legal verification and customer draft confirmation details. The message preview screen has the Legal Verification details.
- Settlement Details User should be able to view the settlement details.
- Party Details User can view the party details like beneficiary, advising bank etc.
- Compliance The compliance tile has the KYC, Sanctions and AML
- Accounting Details User can see the accounting details.

Note

When the Value Date is different from the Transaction Date for one or more accounting entries, system displays an Alert Message "Value Date is different from Transaction Date for one or more Accounting entries.

- Exception (Approval) User can view the Exception (Approval) details.
- Tracer Details User can view the tracer details.
- FX Linkage User can view theFX Linkage details.

3.4.1.2 Action Buttons

Field	Description	Sample Values
Documents	Click the Documents icon to View/Upload the required documents.	
	Application will display the mandatory and optional documents.	
	The user can view and input/view application details simultaneously.	
	When a user clicks on the uploaded document, Document window get opened and on clicking the view icon of the uploaded document, Application screen should get split into two. The one side of the document allows to view and on the other side allows to input/view the details in the application.	
Remarks	Click the Remarks icon to view the remarks captured as part of Registration stage and also can input Remarks, which can be seen by other users.	
Overrides	Click to view overrides, if any.	

Field	Description	Sample Values
Customer Instruction	Click to view/ input the following	
	 Standard Instructions – In this section, the system will populate the details of Standard Instructions maintained for the customer. User will not be able to edit this. 	
	Transaction Level Instructions – In this section, OBTFPM user can input any Customer Instructions received as part of transaction processing. This section will be enabled only for customer initiated transactions.	
Incoming Message	Clicking this button allows the user should be able to see the message in case of STP of incoming MT 767.	
	In case of MT798-MT726-MT759 request, user can view MT798 message(726-759) in this place-holder in Header of the task.	
	In case of MT798_MT788-MT799 request, user can view MT798 message (788-799) in this place-holder in Header of the process-task.	
View Undertaking	Clicking this button allows the user should to view the undertaking details.	
Signatures	Click the Signature button to verify the signature of the customer/ bank if required.	
	The user can view the Customer Number and Name of the signatory, Signature image and the applicable operation instructions if any available in the back-office system.	
	If more than one signature is required, system should display all the signatures.	
Reject	On click of Reject, user must select a reject reason from a list displayed by the system.	
	Reject Codes:	
	R1- Documents missing	
	R2- Signature MissingR3- Input Error	
	R4- Insufficient Balance/Limits	
	• R5 - Others.	
	Select a Reject code and give a reject description.	
	This reject reason will be available in the remarks window throughout the process.	

Field	Description	Sample Values
Hold	The details provided will be registered and status will be on hold. This option is used, if there are any pending information yet to be received from applicant.	
Refer	User will be able to refer the task back to the Data Enrichment user. User must select a Refer Reason from the values displayed by the system. Refer Codes: R1- Documents missing R2- Signature Missing R3- Input Error R4- Insufficient Balance- Limits R5 - Others	
Cancel	Cancel the Guarantee Issuance approval.	
Approve	On approve, application must validate for all mandatory field values, and task must move to the next logical stage. If there are more approvers, task will move to the next approver for approval. If there are no more approvers, the transaction is handed off to the back end system for posting.	

Index

A
Additional Details25
Action Buttons29
Additional Fields20
Action Buttons
Advices
Action Buttons
Application Details5
В
Benefits1
С
Charge Details25
Claim Details14
Action Buttons16
Commission Details
Common Initiation Stage2
Action Buttons2
D
Data Envishment
Data Enrichment
Document Details
Action buttons19
K
Key Features1
•
M
Main Details11
Action Buttons13
Application Details12
Guarantee Details12
Miscellaneous
Multi Level Approval
Action Buttons
Summary38 Multilevel Approval
Summary38
Outlinary
0
Overview1
P
Preview Message28

N.	
Registration	3
Re-Key Authorization	37
Т	
Tax Details	27

