

Relationship Manager User Guide

**Oracle Banking Retail and SME  
Lending Cloud Service**

**Release 14.8.2.0.0**

**Part No. G55841-01**

April 2026

Relationship Manager User Guide  
Oracle Banking Retail and SME Lending Cloud Services

Release 14.8.2.0.0

Copyright © 2021, 2026, Oracle and/or its affiliates.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, MySQL, and NetSuite are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners. Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

---

# Contents

<b>1. Preface .....</b>	<b>1-1</b>
1.1 Introduction.....	1-1
1.2 Audience.....	1-1
1.3 Documentation Accessibility.....	1-1
1.4 Critical Patches.....	1-1
1.5 Organization .....	1-1
1.6 Glossary of Icons.....	1-1
<b>2. Relationship Manager .....</b>	<b>2-1</b>
2.1 User Maintenance .....	2-1
2.1.1 <i>Invoking User Maintenance Screen</i> .....	2-1
2.1.2 <i>Roles Button</i> .....	2-3
2.2 RM Hierarchy Mapping.....	2-4
2.2.1 <i>Invoking RM Hierarchy Mapping Screen</i> .....	2-4
2.2.2 <i>Viewing RM Hierarchy Mapping Summary</i> .....	2-5
2.2.3 <i>Viewing RM Hierarchy Summary</i> .....	2-6
2.3 RM Mass Amendment.....	2-6
2.3.1 <i>Changing Relationship Managers in Bulk</i> .....	2-6
2.3.2 <i>Viewing RM Mass Amendment Summary</i> .....	2-8
<b>3. Function ID Glossary .....</b>	<b>3-1</b>

---

# 1. Preface

## 1.1 Introduction

This manual explains the features related to relationship manager in Oracle Banking Retail and SME Lending Cloud Service.

## 1.2 Audience

This manual is intended for the relationship managers in your bank.

## 1.3 Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

## 1.4 Critical Patches

Oracle advises customers to get all their security and vulnerability information from the Oracle Critical Patch Update Advisory, which is available at [Critical Patches, Security Alerts and Bulletins](#). All critical patches should be applied in a timely manner to ensure effective security, as strongly recommended by [Oracle Software Security Assurance](#).





## 1.5 Organization

This manual is organized into the following chapters:

Chapter	Description
Chapter 1	<i>About this Manual</i> gives information on the intended audience. It also lists the various chapters covered in this User Manual.
Chapter 2	<i>Relationship Manager</i> discusses the basic maintenances required to use the RM feature.
Chapter 3	<i>Function ID Glossary</i> has alphabetical listing of Function/Screen ID's used in the module with page references for quick navigation.

## 1.6 Glossary of Icons

This User Manual may refer to all or some of the following icons.

Icons	Function
	Exit
	Add row
	Delete row
	Option List



---

## 2. Relationship Manager

Relationship Managers (RM) are contact points at the bank for the customers. They handle initial customer contacts and ensure that the appropriate suite of products and solutions are offered to the customers. Relationship managers also develop an understanding of customers' day-to-day administrative and business activities and communicate the same to the front office and back office team.

Using Oracle Banking Retail and SME Lending Cloud Service, you can designate a customer or a group of customers to an RM. The RM will be responsible for helping the customers designated to him/her in need.

This chapter contains the following sections:

- [Section 2.1, "User Maintenance"](#)
- [Section 2.2, "RM Hierarchy Mapping"](#)
- [Section 2.3, "RM Mass Amendment"](#)
- [Section 2.3.1, "Changing Relationship Managers in Bulk"](#)

### 2.1 User Maintenance

This section contains the following topics:

- [Section 2.1.1, "Invoking User Maintenance Screen"](#)
- [Section 2.1.2, "Roles Button"](#)

#### 2.1.1 Invoking User Maintenance Screen

Invoking User Maintenance Screen User Profile defines the activities that a user can carry out on the system. In Oracle Banking Retail and SME Lending Cloud Service, you can define user profiles with their role as 'Relationship Manager'. This section explains the process of defining a user profile with RM role.

To invoke the 'User Maintenance' screen, type 'SMDUSRDF' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

For more information on maintaining user profiles in Oracle Banking Retail and SME Lending Cloud Service, refer to the section 'Defining a User Profile' in Security Management System user manual.

### User Identification

Specify the user ID. This ID identifies the user whose profile you are defining. In a user ID, you can use alphabets in upper or lower case, numbers 0 to 9 and \_ (underscore).

The number of characters in a User ID should be greater than or equal to six and less than 12.

### Name

Specify the name of the user.

### Supervisor Identification

Specify the ID of the supervisor of the user. The option list displays all valid supervisor identifications maintained in the system. Choose the appropriate one.

In case of relationship managers, you can also use this field to define the RM hierarchy. For defining RM hierarchy in this method, you need to select the RM user who is one level up in the hierarchical order as the supervisor.

If the user is the superior in the RM hierarchical order, you can specify his/her own user ID as supervisor ID. The supervisor ID option list also shows the user ID of the user being maintained. This means, you can define an RM user as his/her own supervisor.

---

### Note

The RM hierarchy defined in this method is considered only if the checkbox 'RM Hierarchy Setup Required' is not checked in 'Bank Parameters Maintenance' screen.

---

### Supervisor Name

Based on the supervisor ID selected, the system displays the name of the supervisor.

### Other RM Customer Access Restricted

You can restrict the users' access to the transactions of the customers who are assigned to a different relationship manager. Check this box to restrict the user from viewing, creating,

authorizing or amending the transactions of the customers assigned to a different relationship manager.

If you do not check this box, the user can view, create, authorize and amend the transactions of the customers assigned to other relationship managers.


The customers not assigned to the RM include the customers assigned to other relationship managers as well as those who are not assigned to any relationship manager.

This is applicable to the users created with their role as 'Relationship Manager'.

## 2.1.2 **Roles Button**

A user role is associated to a user for a specific Branch in Oracle Banking Retail and SME Lending Cloud Service. The User at such a branch directly inherits the values set at the Role level. You can also define a user as a relationship manager by assigning the RM role.

To attach the user profile you are defining to a role, you must use the 'Roles' screen. Click 'Roles' button on 'User Maintenance' screen.



The screenshot shows a web application window titled 'Roles'. Inside, there is a 'User Role Mapping' section with a table. The table has three columns: 'Branch Code', 'Role', and 'Role Description'. The table is currently empty, with the text 'No data to display.' below it. Below the table is a pagination control showing 'Page 1 (0 of 0 items)' and navigation arrows. At the bottom right of the window, there are 'Exit' and 'Save' buttons.

Specify the following details:

### **Branch Code**

Specify the branch code assigned to the user role. The option list displays all the valid branch codes maintained in the system. You can choose the appropriate one.

### **Role**

Specify the role assigned to the user for the selected branch. The option list displays all valid roles maintained in the system. Choose the appropriate one.

---

### **Note**

You can assign the role of Relationship Manager to a user by selecting 'RM-ROLE'.

---

### **Role Description**

Based on the role selected, the system displays the role description.

Click add icon to add a record under the 'Roles' list. Specify the above details to attach more roles to the user.

To delete a role attached to a user profile, check the box beside it and click delete icon.

## 2.2 RM Hierarchy Mapping

This section contains the following topics:

- [Section 2.2.1, "Invoking RM Hierarchy Mapping Screen"](#)
- [Section 2.2.2, "Viewing RM Hierarchy Mapping Summary"](#)
- [Section 2.2.3, "Viewing RM Hierarchy Summary"](#)

### 2.2.1 Invoking RM Hierarchy Mapping Screen

You can define the hierarchy for relationship managers at the bank. RM hierarchy can be defined in Oracle Banking Retail and SME Lending Cloud Service using two methods. One method is to select the RM user who is one level up in the hierarchical order as the supervisor of a RM user.

The other method is to define the hierarchical structure using 'RM Hierarchy Mapping' screen.

To invoke this screen, type 'STDRMHR' in the field at the top right corner of the Application toolbar and click the adjoining arrow button.

The screenshot shows the 'RM Hierarchy Mapping' application window. The title bar includes the text 'RM Hierarchy Mapping' and window control icons. Below the title bar is a toolbar with 'New' and 'Enter Query' buttons. The main content area is a light-colored panel containing four input fields arranged in a 2x2 grid. The top-left field is labeled 'RM ID \*' and has a search icon. The top-right field is labeled 'RM Name'. The bottom-left field is labeled 'Parent RM ID \*' and has a search icon. The bottom-right field is labeled 'Parent RM Name'. At the bottom right of the panel, there are two buttons: 'Audit' and 'Exit'.

Specify the following details to define the RM hierarchy.

#### **RM ID**

Specify the relationship manager ID. The option list displays all valid RM user IDs maintained in the system. Choose the appropriate one.

Using this screen, you will assign a parent RM user to this user.

#### **RM Name**

Based on the RM ID, the system displays the name of the relationship manager.

## Parent RM ID

Specify the parent RM ID. The option list displays all valid RM user IDs maintained in the system. Choose the appropriate one.

In the RM hierarchy, this RM user will be the parent user of the user selected above.

## Parent RM Name

Based on the parent RM ID, the system displays the name of the parent relationship manager.

This method allows you to define the parent RM for all relationship managers, thus defining a RM hierarchy.

The RM hierarchy defined in this method is enabled only if the checkbox 'RM Hierarchy Setup Required' is checked in 'Bank Parameters Maintenance' screen.

## 2.2.2 Viewing RM Hierarchy Mapping Summary

You can view a summary of relationship managers hierarchy mapping using 'RM Hierarchy Mapping Summary' screen. To invoke the screen, type 'STSRMHR' in the field at the top right corner of the Application toolbar and click the adjoining arrow button.

The screenshot shows the 'RM Hierarchy Mapping Summary' application window. At the top, there are search options: 'Search', 'Advanced Search', 'Reset', and 'Clear All'. A 'Records per page' dropdown is set to 15. Below this is a search filter section with a dropdown for 'Search (Case Sensitive)'. The main search area contains four input fields: 'Authorization Status', 'Record Status', 'RM ID', and 'Parent RM ID'. Below the search fields is a 'Search Results' section with a 'Lock Columns' dropdown set to 0. The results table has four columns: 'Authorization Status', 'Record Status', 'RM ID', and 'Parent RM ID'. The table is currently empty, displaying 'No data to display.' At the bottom, there is a pagination control showing 'Page 1 Of 1' and navigation arrows. An 'Exit' button is located at the bottom right corner.

You can search for RM hierarchy details based on one or more of the following parameters:

- Authorization status of the record
- Record status
- Relationship manager ID
- Parent relationship manager ID

Once you have set the search criteria, click 'Search' button. The system displays all RM hierarchy mapping records that match the search criteria. Double-click a record to view the detailed screen.

### 2.2.3 Viewing RM Hierarchy Summary

You can query for the hierarchy of relationship manager using 'RM Hierarchy Summary' screen. To invoke the screen, type 'STDRMHRV' in the field at the top right corner of the Application toolbar and click the adjoining arrow button.

RM Id	RM Name	Parent RM ID	Parent RM Name
No data to display.			

You can query for the hierarchy details of a relationship manager.

Specify the following details:

#### **RM ID**

Specify the ID of the relationship manager whose hierarchy details you need to find. Choose the appropriate one from the option list.

Based on the RM ID selected, the system displays the relationship manager hierarchy details.

## 2.3 RM Mass Amendment

This section contains the following topics:

- [Section 2.3.1, "Changing Relationship Managers in Bulk"](#)
- [Section 2.3.2, "Viewing RM Mass Amendment Summary"](#)

### 2.3.1 Changing Relationship Managers in Bulk

Oracle Banking Retail and SME Lending Cloud Service allows you to change the some or all customers associated with one relationship manager to a different relationship manager. You can change the relationship manager for a number of customers at once using 'RM Mass Amendment' screen. To invoke the screen, type 'STDRMAMD' in the field at the top right corner of the application toolbar and click the adjoining arrow button.

The screenshot shows a web interface titled "RM Mass Amendment". At the top left, there are "New" and "Enter Query" buttons. The main form area contains several input fields: "Reference Number", "From RM ID" (with a search icon), "To RM ID" (with a search icon), "Effective Date", "From RM Name", "To RM Name", and "Status" (which is pre-filled with "Not Started"). Below these fields are radio buttons for "Customer Restrictions": "Allowed Customers", "Restrictive Customers", and "All Customers" (which is selected). At the bottom of the form area, there is a "Customers" table with expand/collapse and refresh icons. At the very bottom right, there are "Audit" and "Exit" buttons.

Specify the following details:

### Reference Number

The system generates and displays the reference number of the RM mass amendment operation.

### From RM ID

Specify the ID of the relationship manager with whom the customers to be reassigned are associated with. The option list displays all valid RM IDs maintained in the system. Choose the appropriate one.

While processing the reassignment, the system assigns the selected customers associated with this RM to the RM specified in the field 'To RM ID'.

### From RM Name

Based on the RM ID, the system displays the name of the relationship manager.

### To RM ID

Specify the ID of the relationship manager to whom the customers will be reassigned. The option list displays all valid RM IDs maintained in the system. Choose the appropriate one.

While processing the reassignment, the system reassigns the selected customers to this RM.

### To RM Name

Based on the RM ID selected, the system displays the name of the relationship manager.

### Status

The system displays the status of the mass RM amendment. The status can be one of the following:

- Not Started – indicates that the mass amendment record has just been created
- Completed – indicates that the customer has been moved under the new RM without any error, after the mass amendment effective date
- Failed – indicates that the movement of customer from one RM to another RM has failed for any reason such as closure of CIF or closure of RM

### **Effective Date**

Specify the date from which the RM change will be effective. The system will process the request during the RM mass amendment batch on this date. The customers will be associated with the other RM from this date onwards.

### **Allowed Customers/Restrictive Customers/All Customers**

Specify the type of customers to whom the RM change is applicable. You can choose one of the following:

- Allowed Customers – if you select this, the system will change the RM of all customers selected under the 'Customers' grid
- Restrictive Customers – if you select this, the system will change the RM of all customers other than the restricted customers listed
- All Customers – if you select this, the system will change the RM of all customers under the RM

### **Customers**

Select the customers to whom the RM change is applicable. You need to specify the following details of the customer:

#### **Customer Number**

Specify the CIF of the customer who will be reassigned to a different RM. The option list displays all valid customer numbers assigned to the RM selected under 'From RM ID'. Choose the appropriate one.

#### **Customer Name**

Based on the customer number, the system displays the name of the customer.

You can add more customers to the list by clicking the add button. In case you need to remove a customer from this list, check the adjoining checkbox and click delete button.

Once you have specified the above details, save the record.

The system processes the amendment during RM Mass Amendment batch at end of transactions input (EOTI) stage. This batch will reassign the customers from the current RM to the new RM specified here.

Once the customers are reassigned, the system updates the status as 'Completed'. In case of any failure during the process, the system updates the status as 'Failed' and logs the failure reason.

## **2.3.2 Viewing RM Mass Amendment Summary**

You can view a summary of the RM mass amendments using 'RM Mass Amendment Summary' screen. To invoke this screen, type 'STSRMAMD' in the field at the top right corner of the Application toolbar and click the adjoining arrow button.

**RM Mass Amendment Summary**

Search Advanced Search Reset Clear All Records per page 15

Search (Case Sensitive)

Authorization Status [Dropdown] Record Status [Dropdown] Reference Number [Text] [Q]

From RM ID [Text] [Q] To RM ID [Text] [Q]

Search Results Lock Columns 0

<input type="checkbox"/>	Authorization Status	Record Status	Reference Number	From RM ID	To RM ID	Customer Restrictions	Effective Date	Status
No data to display.								

Page 1 Of 1 [K] [Left Arrow] [Right Arrow] [X]

Exit

You can search the RM mass amendment summary based on one or more of the following parameters:

- Authorization status of the amendment maintenance
- Record status
- Reference number
- RM ID from which the customers are reassigned (From RM ID)
- RM ID to which the customers are reassigned (To RM ID)

Once you have set the search criteria, click search button. The system displays the following details of the RM mass amendment records that match the criteria.

- Authorization status
- Record status
- Reference number
- From RM ID
- To RM ID
- Effective Date

Double-click a record to view the details.

---

### 3. Function ID Glossary

**S**

SMDUSRDF .....2-1

STDRMAMD .....2-6

STDRMHR ..... 2-4

STDRMHRV ..... 2-6

STSRMAMD ..... 2-8