

Oracle® Communications

Cloud Native Core Solution Upgrade Guide



Release 3.25.1.200.0

G36485-01

June 2025

ORACLE®

Oracle Communications Cloud Native Core Solution Upgrade Guide, Release 3.25.1.200.0

G36485-01

Copyright © 2022, 2025, Oracle and/or its affiliates.

Contents

1	Introduction	
1.1	Overview	1
1.1.1	Supported Upgrade Paths for CNC Components except CNE	2
1.2	References	2
2	Upgrade of Oracle CNC Solution deployed on Oracle CNE	
2.1	Overview	1
2.2	Planning Upgrade	2
2.2.1	General Guidelines	3
2.2.2	Preupgrade Checklist	3
2.2.2.1	Resource Requirement	4
2.2.2.2	Prerequisites	4
2.2.3	Upgrade Workflow	5
2.2.3.1	CNC NFs and Companion Components Upgrade	5
2.2.3.2	CNE Upgrade	6
2.3	Performing the Upgrade	7
2.4	Performing the Postupgrade Tasks	8
2.4.1	NF Postupgrade	8
2.4.2	CNE Postupgrade	8
2.5	Performing the Rollback	9
2.6	Performing the Postrollback Tasks	11
3	Upgrade of Oracle CNC Solution deployed on Non-Oracle CNE	
3.1	Overview	1
3.2	Planning Upgrade	2
3.2.1	General Guidelines	2
3.2.2	Preupgrade Checklist	2
3.2.2.1	Resource Requirement	2
3.2.2.2	Prerequisites	3
3.2.3	Upgrade Workflow	3
3.2.3.1	CNC NFs and Companion Components Upgrade	3

3.2.3.2	Compatibility Check of Target NF Component with Installed Non-Oracle cloud native environment	5
3.3	Performing the NF Upgrade	6
3.3.1	Non-Oracle Cloud Native Environment Upgrade	7
3.3.2	Compatibility Check of NF Component with Target Cloud Native Environment	8
3.4	Performing the Postupgrade Tasks	9
3.4.1	NF Postupgrade	9
3.4.2	Cloud Native Environment Postupgrade	9
3.5	Performing the Rollback	9
3.6	Performing the Postrollback Tasks	10

4 Upgrade of Oracle CNC Solution deployed on with OCI

4.1	Planning Upgrade	1
4.1.1	Guidelines	1
4.1.2	Preupgrade Checklist	1
4.1.2.1	Resource Requirement	1
4.1.2.2	Prerequisites	2
4.1.3	Upgrade Workflow	2
4.1.3.1	CNC NFs and Companion components Upgrade	3
4.1.4	Compatibility Check of Target NF Component with Installed OCI	4
4.2	Performing the NF Upgrade	5
4.2.1	Upgrade Workflow	6
4.2.2	Compatibility Check of CNC NF Component on Target OCI Environment	6
4.3	Performing the Postupgrade Tasks	8
4.3.1	NF Postupgrade	8
4.3.2	OCI Environment Postupgrade	8
4.4	Performing the Rollback	8
4.5	Performing the Postrollback Tasks	10

A Frequently Asked Questions (FAQs)

Preface

- [Documentation Accessibility](#)
- [Diversity and Inclusion](#)
- [Conventions](#)

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Access to Oracle Support

Oracle customer access to and use of Oracle support services will be pursuant to the terms and conditions specified in their Oracle order for the applicable services.

Diversity and Inclusion

Oracle is fully committed to diversity and inclusion. Oracle respects and values having a diverse workforce that increases thought leadership and innovation. As part of our initiative to build a more inclusive culture that positively impacts our employees, customers, and partners, we are working to remove insensitive terms from our products and documentation. We are also mindful of the necessity to maintain compatibility with our customers' existing technologies and the need to ensure continuity of service as Oracle's offerings and industry standards evolve. Because of these technical constraints, our effort to remove insensitive terms is ongoing and will take time and external cooperation.

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

My Oracle Support

My Oracle Support (<https://support.oracle.com>) is your initial point of contact for all product support and training needs. A representative at Customer Access Support can assist you with My Oracle Support registration.

Call the Customer Access Support main number at 1-800-223-1711 (toll-free in the US), or call the Oracle Support hotline for your local country from the list at <http://www.oracle.com/us/support/contact/index.html>. When calling, make the selections in the sequence shown below on the Support telephone menu:

- For Technical issues such as creating a new Service Request (SR), select **1**.
- For Non-technical issues such as registration or assistance with My Oracle Support, select **2**.
- For Hardware, Networking and Solaris Operating System Support, select **3**.

You are connected to a live agent who can assist you with My Oracle Support registration and opening a support ticket.

My Oracle Support is available 24 hours a day, 7 days a week, 365 days a year.

Acronyms and Terminologies

Table Acronyms and Terminologies

Term	Definition
BSF	Oracle Communications Cloud Native Core, Binding Support Function
CNC	Cloud Native Core
cnDBTier	Oracle Communications Cloud Native Core, Cloud Native Database Tier
CNE	Oracle Communications Cloud Native Environment
Policy	Oracle Communications Cloud Native Core, Converged Policy
NEF	Oracle Communications Cloud Native Core, Network Exposure Function
NF	Network Function
NRF	Oracle Communications Cloud Native Core, Network Repository Function
NSSF	Oracle Communications Cloud Native Core, Network Slice Selection Function
OCCM	Oracle Communications Cloud Native Core, Certification Management
OSO	Oracle Communications Cloud Native Core, Operation Services Overlay
PDB	Pod Distribution Budget
SCP	Oracle Communications Cloud Native Core, Service Communication Proxy
SEPP	Oracle Communications Cloud Native Core, Security Edge Protection Proxy
UDR	Oracle Communications Cloud Native Core, Unified Data Repository
Cloud Native Core (CNC) Network Functions (NFs)	This includes all Oracle NFs such as, Policy, BSF, NRF, UDR, SEPP, NSSF, SCP, NEF.
CNC Companion Components	This includes companion components such as CNCC, cnDBTier, OSO, OCCM.
Oracle CNC Solution	This includes Oracle CNC NFs and Companion components that are deployed on Oracle CNE, Non-Oracle CNE, or OCI.
CNC Components	This includes CNC NFs, CNC Companion Components, and Oracle CNE.

What's New in This Guide

This section introduces the documentation updates for release 3.25.1.2xx.0.

Release 3.25.1.200.0 - G36485-01, June 2025

Updated the source and target release versions for the upgrade and rollback in the [Planning Upgrade](#) and [Performing the Rollback](#) respectively in the [Upgrade of Oracle CNC Solution deployed on Oracle CNE](#) chapter.

1

Introduction

1.1 Overview

Oracle's Cloud Native Core (CNC) Network Functions (NFs) support deployment on Oracle Communications Cloud Native Environment (CNE), non-Oracle cloud native environment, and Oracle Cloud Infrastructure (OCI) environment. This document provides information on Cloud Native Core (CNC) guidelines required to upgrade and rollback Oracle CNC Solution in the following environment:

- CNC Solution deployed on CNE: For information on upgrade or rollback procedures, see [Upgrade of Oracle CNC Solution deployed on Oracle CNE](#).
- CNC Solution deployed on non-Oracle CNE: For information on upgrade or rollback procedures, see [Upgrade of Oracle CNC Solution deployed on Non-Oracle CNE](#).
- CNC Solution deployed on OCI: For information on upgrade or rollback procedures, see [Upgrade of Oracle CNC Solution deployed on with OCI](#).

Oracle CNC Solution includes:

- when deployed on Oracle CNE:
 - CNC NFs
 - CNC Companion Components
 - CNE
- when deployed on non-Oracle CNE:
 - CNC NFs
 - CNC Companion Components

CNC NF includes:

- Oracle Communications Cloud Native Core, Binding Support Function (BSF)
- Oracle Communications Cloud Native Core, Converged Policy (Policy)
- Oracle Communications Cloud Native Core, Service Communication Proxy (SCP)
- Oracle Communications Cloud Native Core, Security Edge Protection Proxy (SEPP)
- Oracle Communications Cloud Native Core, Network Exposure Function (NEF)
- Oracle Communications Cloud Native Core, Network Repository Function (NRF)
- Oracle Communications Cloud Native Core, Network Slice Selection Function (NSSF)
- Oracle Communications Cloud Native Core, Unified Data Repository (UDR)

CNC Companion components includes:

- Oracle Communications Cloud Native Configuration Console (CNC Console)
- Oracle Communications Cloud Native Core, cnDBTier (cnDBTier)
- Oracle Communications Operations Services Overlay (OSO)

- Oracle Communications Cloud Native Core, Certification Management (OCCM)

1.1.1 Supported Upgrade Paths for CNC Components except CNE

[Figure 1-1](#) outlines the supported upgrade paths for different CNC components except CNE. It is not recommended to skip intermediate versions, unless explicitly mentioned.

Figure 1-1 CNC Upgrade Paths for CNC components except CNE

Source Releases	Target Releases								
	24.3. x	25.1.1xx	25.1.2xx	25.2.1xx	25.2.2xx	26.1.1xx	26.1.2xx	26.2.1xx	26.2.2xx
24.2. x	Y	Y	NS*	NS	NS	NS	NS	NS	NS
24.3. x	NA	Y	Y	NS	NS	NS	NS	NS	NS
25.1.1xx	NA	NA	Y	NS	NS	NS	NS	NS	NS
25.1.2xx	NA	NA	NA	Y	Y	NS	NS	NS	NS
25.2.1xx	NA	NA	NA	NA	Y	NS	NS	NS	NS
25.2.2xx	NA	NA	NA	NA	NA	Y	Y	NS	NS
26.1.1xx	NA	NA	NA	NA	NA	NA	Y	NS	NS
26.1.2xx	NA	NA	NA	NA	NA	NA	NA	Y	Y
26.2.1xx	NA	NA	NA	NA	NA	NA	NA	NA	Y
26.2.2xx	NA	NA	NA	NA	NA	NA	NA	NA	NA

Legends: NS: Not Supported, NA: Not Applicable, Y: Yes, upgrade supported

Note

- * Policy, CNCC, UDR, SLF, and cnDBTier supports upgrade from **24.2.x** to **25.1.2xx** (this exception applies only to upgrade from 24.2.x to 25.1.2xx).
- This upgrade guideline is applicable to CNC components except CNE. For CNE upgrade guideline, see [Figure 2-4](#).
- This upgrade path is an example, and it does not show future release plans.
- If the source release is **A.B.1xx**, upgrades must follow an incremental sequence, for example,
 1. A.B.1xx
 2. A.B.2xx
 3. A.(B+1).1xx
 Skipping intermediate versions (such as A.B.2xx) is not supported.
- Upgrading from **A.B.2xx** to **A.(B+1).2xx** is allowed.
- Be sure to select intermediate versions to maintain compatibility throughout the upgrade.

1.2 References

The following references provide additional information on product operations, maintenance, and support:

- *Oracle Communications Cloud Native Core, Cloud Native Environment Installation, Upgrade, and Fault Recovery Guide.*
- *Oracle Communications Cloud Native Configuration Console Installation, Upgrade, and Fault Recovery Guide.*
- *Oracle Communications Cloud Native Core, cnDBTier Installation, Upgrade, and Fault Recovery Guide.*
- *Oracle Communications Cloud Native Core, Operations Services Overlay Installation and Upgrade Guide.*
- *Oracle Communications Cloud Native Core, Network Slice Selection Function Installation, Upgrade, and Fault Recovery Guide.*
- *Oracle Communications Cloud Native Core, Service Communication Proxy Installation, Upgrade, and Fault Recovery Guide.*
- *Oracle Communications Cloud Native Core, Policy Installation, Upgrade, and Fault Recovery Guide.*
- *Oracle Communications Cloud Native Core, Network Exposure Function Installation, Upgrade, and Fault Recovery Guide.*
- *Oracle Communications Cloud Native Core, Unified Data Repository Installation, Upgrade, and Fault Recovery Guide.*
- *Oracle Communications Cloud Native Core, Network Repository Function Installation, Upgrade, and Fault Recovery Guide.*
- *Oracle Communications Cloud Native Core, Security Edge Protection Proxy Installation, Upgrade, and Fault Recovery Guide.*
- *Oracle Communications Cloud Native Core, Binding Support Function Installation, Upgrade, and Fault Recovery Guide.*
- *Oracle Communications Cloud Native Core, Certification Management Installation, Upgrade, and Fault Recovery Guide.*
- *Oracle Communications Cloud Native Core, OCI Adaptor User Guide*
- *Oracle Communications, OCI Deployment Guide*

2

Upgrade of Oracle CNC Solution deployed on Oracle CNE

This chapter provides information about Oracle Cloud Native Core (CNC) Solution upgrade when deployed on Oracle Communications Cloud Native Environment (CNE).

2.1 Overview

This section provides an overview of upgrade procedures of CNC components. You must complete the preupgrade procedures described in each subsection to ensure that the system is ready for an upgrade.


You can upgrade each Cloud Native Core (CNC) Network Functions (NFs) and Companion components from the specified source release to the target release. Once the required network function is up and running, upgrade infrastructure, followed by CNE upgrade.

Note

The upgrade procedure for the infrastructure is not covered in this document. For more information about infrastructure upgrades, see the relevant infrastructure document.

If you are using CNC Solution on Oracle CNE, perform the upgrade procedure in the following sequence:


Figure 2-1 CNC Solution Upgrade Order on Oracle CNE



2.2 Planning Upgrade

The following flow diagram gives a high-level overview of the sequence to be followed for upgrading CNC Solution deployed on CNE.

Figure 2-2 Planning Upgrade of CNC Solution



The following table lists the supported upgrade sequence:

Table 2-1 Upgrade Sequence

Deployment Mode	Source Version	Target Version	Upgrade Sequence
Single Cluster or Multicluster	24.3.x, 25.1.1xx	25.1.200	1. Oracle CNC NFs and Companion components: a. CNC Console Upgrade b. OCCM Upgrade c. CNC NF Upgrade d. cnDBTier Upgrade 2. Infrastructure (if needed) 3. CNE

2.2.1 General Guidelines

Oracle recommends the following guidelines for upgrading CNC Solution deployed on CNE:

- Perform upgrade testing in sandbox or lab deployment before testing in production sites.
- Follow the upgrade sequence outlined in the [Figure 1-1](#) and [CNE Upgrade](#) sections.
- Upgrade all components to their target release, as per the compatibility matrix provided in *Oracle Communications Cloud Native Core Release Notes*.
- In a multisite deployment model, perform the upgrade of one site at a time. Follow the sequence mentioned in [upgrade sequence](#) to upgrade all the components in the specific site and then proceed to the next site.
Refer to cnDBTier and NF-specific installation, upgrade, and fault recovery guide for post upgrade steps to verify the health of cnDBTier services and NF components.
- It is recommended to perform an upgrade of CNC Console, OCCM, NF, and cnDBTier in a single maintenance window. If upgrade takes longer than a single maintenance window, individual components can be upgraded in multiple maintenance windows. Ensure that the upgrade order is followed as per the sequence mentioned in [upgrade sequence](#).
- Ensure that Console and NF versions are compatible with OCCM before upgrade.
- Perform infrastructure upgrade, if needed.
- You can perform a CNE upgrade in multiple maintenance windows. For more information about upgrading CNE, see *Oracle Communications Cloud Native Environment Installation, Upgrade, and Fault Recovery Guide*.
- If CNE is a shared cluster, upgrade all the instances of CNC Console, OCCM, NF, and cnDBTier before upgrading CNE.
- If multiple NFs share a cnDBTier, upgrade all the instances of CNC Console, OCCM, and NFs sharing that cnDBTier of the specific site, before upgrading the cnDBTier of the site.
- Rollback is the reverse order of upgrade.

2.2.2 Preupgrade Checklist

Go through the following checklist before performing an upgrade.

2.2.2.1 Resource Requirement

This section details about the resources required to upgrade CNE, CNC NFs and Companion components.

2.2.2.1.1 Cloud Native Environment

CNE automatically drains its worker nodes while performing the upgrade. When a worker node is drained, Kubernetes safely evicts all of the pods that were hosted on that worker node.

Note

NF, cnDBTier, and CNC Console support Pod Distribution Budget (PDB) to gracefully handle worker node draining. Thus, based on available resources, a CNE worker node upgrade will happen. Operator needs to ensure that enough resources are available after draining the worker node. For more information on CNE resource requirements, see *Oracle Communications Cloud Native Core, Cloud Native Environment Installation, Upgrade, and Fault Recovery Guide*.

2.2.2.1.2 CNC NFs and Companion Components

For CNC NFs and Companion components upgrade, reevaluate resource requirement before performing the upgrade. It is possible that CNC NFs and Companion components require additional resources due to changes in architecture or service model.

For more information on NF resource requirements, see NF-specific installation, upgrade, and fault recovery guides.

2.2.2.2 Prerequisites

Ensure that the following prerequisites are met before performing an upgrade:

- Verify that all required worker nodes are available for scheduling pods during upgrade. For example, taints applied on worker nodes (for any maintenance activity etc.). Make sure required number of worker nodes are available as per dimensioning before upgrade.
- Ensure that at least two worker nodes (that is, resource for largest worker node in cluster x 2) worth of total resources are free and available in CNE cluster.
- Monitor infrastructure related issue (for example, storage or hardware alarms from infrastructure) manually before CNE or Operating System upgrade.
- Take a backup of the following artifacts after installation of each of the CNC components:
 - custom values.yaml file
 - servicemesh-config-custom-values.yaml file
 - Updated helm charts
 - Secrets
 - Certificates
 - Keys used

- See CNC Console, OCCM, NF, cnDBTier, and CNE installation and upgrade guides for preupgrade task details before upgrading respective components.

2.2.3 Upgrade Workflow


The section provides details about the upgrade sequence.

See CNC NFs, Companion components, and CNE installation, upgrade, and fault recovery guides for details on upgrading the respective components. The infrastructure upgrade is performed (if needed) after CNC components upgrade and before CNE upgrade.

2.2.3.1 CNC NFs and Companion Components Upgrade

This section describes the upgrade workflow for CNC Components deployed on CNE.

Figure 2-3 CNC Components Upgrade deployed on CNE



The following procedure explains the upgrade work flow for CNC Components:

1. Check the supported upgrade path for each NF. To know the upgrade path, see *Oracle Communications Cloud Native Core Release Notes*. Check the upgrade sequence mentioned in the [Supported Upgrade Paths for CNC Components except CNE](#) section.

Note

For multisite deployment model, follow the procedure on each site.

2. Check if all the CNC components support incremental upgrades. If it is not supported, perform one of the following procedure:
 - a. perform multiple hop upgrades.
 - b. perform a fresh installation after site isolation.
 - c. contact [My Oracle Support](#).
3. Upgrade the CNC components based on the upgrade sequence mentioned in the [Planning Upgrade](#) section.

4. Run the Helm test command to check the upgrade status.
5. Once the Helm test is successful, then the upgrade is complete.
6. Perform the above upgrade steps in the production environment.

2.2.3.2 CNE Upgrade

Supported CNE Upgrade Paths

To ensure a smooth and supported upgrade process, follow the upgrade sequence outlined in [Figure 2-4](#) outlines the supported upgrade paths for CNE. It is not recommend to skip intermediate versions, unless explicitly mentioned.

Figure 2-4 Supported CNE Upgrade Paths


Source Releases	Target Releases								
	24.3. x	25.1.1xx	25.1.2xx	25.2.1xx	25.2.2xx	26.1.1xx	26.1.2xx	26.2.1xx	26.2.2xx
24.2. x	Y	NS	NS	NS	NS	NS	NS	NS	NS
24.3. x	NA	Y	NS	NS	NS	NS	NS	NS	NS
25.1.1xx	NA	NA	Y	NS	NS	NS	NS	NS	NS
25.1.2xx	NA	NA	NA	Y	NS	NS	NS	NS	NS
25.2.1xx	NA	NA	NA	NA	Y	NS	NS	NS	NS
25.2.2xx	NA	NA	NA	NA	NA	Y	NS	NS	NS
26.1.1xx	NA	NA	NA	NA	NA	NA	Y	NS	NS
26.1.2xx	NA	NA	NA	NA	NA	NA	NA	Y	NS
26.2.1xx	NA	NA	NA	NA	NA	NA	NA	NA	Y
26.2.2xx	NA	NA	NA	NA	NA	NA	NA	NA	NA

Legend: NS: Not Supported, NA: Not Applicable, Y: Yes, upgrade supported

CNE Upgrade Workflow

The following flow diagram explains the process for upgrading CNE:

Figure 2-5 CNE Upgrade Procedure



The following procedure explains the upgrade workflow for Oracle Communications Cloud Native Core, Cloud Native Environment (CNE):

1. Check the supported upgrade path for CNE. To know the upgrade path, see *Oracle Communications Cloud Native Core Release Notes*.
2. Check if CNE supports incremental upgrades. If it is not supported, contact [My Oracle Support](#).
3. Upgrade the components based on the upgrade sequence mentioned in the [Planning Upgrade](#) section.
4. Check and perform an application pod restart, if required.
For example: After upgrading the service mesh, restart the application pods of CNC Console, OCCM, NF, and cnDBTier even if they are running on the latest versions.
5. Run the Helm test command to check the upgrade status.
6. Once the Helm test is successful, the upgrade is complete.

2.3 Performing the Upgrade

See the following documents for detailed procedures to upgrade the respective components:

Table 2-2 CNC Network Functions Document Reference

CNC Network Functions	Document Reference
Oracle Communications Cloud Native Core, Binding Support Function (BSF)	<i>Oracle Communications Cloud Native Core, Binding Support Function Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Network Exposure Function (NEF)	<i>Oracle Communications Cloud Native Core, Network Exposure Function Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Network Repository Function (NRF)	<i>Oracle Communications Cloud Native Core, Network Repository Function Installation, Upgrade, and Fault Recovery Guide</i>

Table 2-2 (Cont.) CNC Network Functions Document Reference

CNC Network Functions	Document Reference
Oracle Communications Cloud Native Core, Network Slice Selection Function (NSSF)	<i>Oracle Communications Cloud Native Core, Network Slice Selection Function Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Converged Policy (Policy)	<i>Oracle Communications Cloud Native Core, Converged Policy Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Security Edge Protection Proxy (SEPP)	<i>Oracle Communications Cloud Native Core, Security Edge Protection Proxy Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Service Communication Proxy (SCP)	<i>Oracle Communications Cloud Native Core, Service Communication Proxy Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Unified Data Repository (UDR)	<i>Oracle Communications Cloud Native Core, Unified Data Repository Installation, Upgrade, and Fault Recovery Guide</i>

Table 2-3 CNC Companion Components Document Reference

CNC Companion Components	Document Reference
Oracle Communications Cloud Native Configuration Console (CNC Console)	<i>Oracle Communications Cloud Native Configuration Console Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, cnDBTier (cnDBTier)	<i>Oracle Communications Cloud Native Core, cnDBTier Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Certification Management (OCCM)	<i>Oracle Communications Cloud Native Core, Certification Management, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Operations Services Overlay (OSO)	<i>Oracle Communications Cloud Native Core, Operations Services Overlay Installation and Upgrade Guide</i>

2.4 Performing the Postupgrade Tasks

This section explains the postupgrade tasks.

2.4.1 NF Postupgrade

- Verify postupgrade of all the CNC NFs and Companion components by running the "helm test" to verify the deployment health and status.
- See CNC NFs and Companion components installation, upgrade, and fault recovery guides for postupgrade task details after upgrading the respective components.

2.4.2 CNE Postupgrade

For information on CNE postupgrade tasks, see *Oracle Communications Cloud Native Core, Cloud Native Environment Installation, Upgrade, and Fault Recovery Guide*.

2.5 Performing the Rollback


Note

Before rollback contact [My Oracle Support](#) to analyze the cause of failure and any possible workarounds.

This section helps you to decide the order of the rollback of the components that were upgraded successfully. For example, a rollback is triggered if the cnDBTier upgrade fails (or validation after an upgrade fails) for any reason, and this guide provides the information to perform the rollback of CNC Components in a given order.

The following diagram details the rollback sequence:

Figure 2-6 Rollback Sequence



The following table lists the supported rollback sequence:

Table 2-4 Rollback Sequence

Deployment Mode	Source Version	Target Version	Rollback Sequence
Single Cluster or Multicluster	25.1.200	24.3.x, 25.1.1xx	1. CNE roll back 2. Infrastructure roll back 3. CNC NFs and Companion components a. cnDBTier roll back b. NF roll back c. OCCM roll back d. CNC Console roll back

See the following documents for detailed procedures to roll back the respective components:

Table 2-5 CNC Network Functions Document Reference

CNC Network Functions	Document Reference
Oracle Communications Cloud Native Core, Binding Support Function (BSF)	<i>Oracle Communications Cloud Native Core, Binding Support Function Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Network Exposure Function (NEF)	<i>Oracle Communications Cloud Native Core, Network Exposure Function Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Network Repository Function (NRF)	<i>Oracle Communications Cloud Native Core, Network Repository Function Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Network Slice Selection Function (NSSF)	<i>Oracle Communications Cloud Native Core, Network Slice Selection Function Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Converged Policy (Policy)	<i>Oracle Communications Cloud Native Core, Converged Policy Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Security Edge Protection Proxy (SEPP)	<i>Oracle Communications Cloud Native Core, Security Edge Protection Proxy Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Service Communication Proxy (SCP)	<i>Oracle Communications Cloud Native Core, Service Communication Proxy Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Unified Data Repository (UDR)	<i>Oracle Communications Cloud Native Core, Unified Data Repository Installation, Upgrade, and Fault Recovery Guide</i>

Table 2-6 CNC Companion Components Document Reference

CNC Companion Components	Document Reference
Oracle Communications Cloud Native Configuration Console (CNC Console)	<i>Oracle Communications Cloud Native Configuration Console Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, cnDBTier (cnDBTier)	<i>Oracle Communications Cloud Native Core, cnDBTier Installation, Upgrade, and Fault Recovery Guide</i>

Table 2-6 (Cont.) CNC Companion Components Document Reference

CNC Companion Components	Document Reference
Oracle Communications Cloud Native Core, Certification Management (OCCM)	<i>Oracle Communications Cloud Native Core, Certification Management, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Operations Services Overlay (OSO)	<i>Oracle Communications Cloud Native Core, Operations Services Overlay Installation and Upgrade Guide</i>

2.6 Performing the Postrollback Tasks

Perform the following postrollback tasks:

- Verify the rollback of all the CNC NFs and Companion components by running the "helm test" to verify the deployment health and status.
- See CNC NFs and Companion components installation, upgrade, and fault recovery guides for postrollback task details after rolling back respective components.

3

Upgrade of Oracle CNC Solution deployed on Non-Oracle CNE

This chapter provides information about Oracle Cloud Native Core (CNC) Solution upgrade when deployed on Non-Oracle cloud native environment.

3.1 Overview

This section provides an overview of upgrade procedures of CNC components. You must complete the preupgrade procedures described in each subsection to ensure that the system is ready for an upgrade.


You can upgrade each Cloud Native Core (CNC) Network Functions (NFs) and Companion components from the specified source release to the target release. Once the required network function is up and running, upgrade non-Oracle cloud native environment or infrastructure.

① Note

The upgrade procedure for the infrastructure is not covered in this document. For more information about infrastructure upgrades, see the relevant infrastructure document.

If you are using Oracle CNC Solution on non-Oracle CNE, perform the upgrade procedure in the following sequence:

Figure 3-1 Oracle CNC Solution Upgrade Order on Non-Oracle CNE



See CNC NFs and Companion components installation, upgrade, and fault recovery guides for details on upgrading the respective components.

3.2 Planning Upgrade

This section explains the planning for upgrading CNC NFs and Companion components deployed on non-Oracle cloud native environment.

3.2.1 General Guidelines

Oracle recommends the following guidelines:

- Perform upgrade testing in sandbox or lab deployment before testing in production sites.
- Follow the upgrade sequence outlined in the [Figure 1-1](#) section.
- Upgrade all components to their target release, as per the compatibility matrix provided in the CNC release notes.
- In a multisite deployment model, perform the upgrade of one site at a time. Follow the sequence mentioned in [Figure 3-1](#) to upgrade all the components in the specific site and then proceed to the next site.
Refer to cnDBTier and NF-specific installation, upgrade, and fault recovery guide for post upgrade steps to verify the health of cnDBTier services and NF components.
- Perform an upgrade of CNC Console, OCCM, NF, and cnDBTier in a single maintenance window. If upgrade takes longer than a single maintenance window, individual components can be upgraded in multiple maintenance windows. Ensure that the upgrade order is followed as per the sequence mentioned in [Figure 3-1](#).
- Ensure that CNC Console and NF versions are compatible with OCCM before upgrade.
- If multiple NFs share a cnDBTier, upgrade all the instances of CNC Console, OCCM, and NFs sharing that cnDBTier of the specific site, before upgrading the cnDBTier of the site.
- Rollback is the reverse order of upgrade.

3.2.2 Preupgrade Checklist

Go through the following checklist before performing an upgrade.

3.2.2.1 Resource Requirement

This section details about the resources required to upgrade a non-Oracle cloud native environment, CNC NFs, and Companion components.

3.2.2.1.1 Cloud Native Environment

Ensure that the number of planned resources required for NF, CNC Console, and cnDBTier are available during the non-Oracle cloud native environment upgrade.

For more information on non-Oracle cloud native environment resource requirements, see the installation and upgrade guide provided by the non-Oracle cloud native environment vendor.

3.2.2.1.2 CNC NFs and Companion components

For CNC NFs and Companion components upgrade, reevaluate resource requirement before performing the upgrade. It is possible that CNC NFs or Companion components requires additional resources due to changes in architecture or service model.

For more information on CNC NFs and Companion components resource requirements, see NF-specific installation, upgrade, and fault recovery guides.

3.2.2.2 Prerequisites

Ensure that you have the following prerequisites before performing an upgrade:


- Keep the backup of the following artifacts from your recent successful installation handy:
 - custom values.yaml file
 - servicemesh-config-custom-values.yaml file, if any
 - Updated helm charts
 - Secrets
 - Certificates
 - Keys used
- See CNC Console, OCCM, NF, cnDBTier, and OSO guides for preupgrade task details before upgrading respective components.
- Refer to customer-specific non-Oracle cloud native environment Upgrade document for preupgrade tasks.

3.2.3 Upgrade Workflow

The following diagram details the upgrade sequence if you are using a non-Oracle CNE.

3.2.3.1 CNC NFs and Companion Components Upgrade

This section explains the upgrade workflow of CNC NFs and Companion Components deployed on Non-Oracle cloud native environment.

Figure 3-2 CNC NFs and Companion components Upgrade on Non-Oracle cloud native environment

The following procedure explains the upgrade workflow for CNC NFs and Companion Components:

1. Check the supported upgrade path for each CNC NFs and Companion Components. To know the upgrade path, see *Oracle Communications Cloud Native Core Release Notes*.

Note

It is recommended to upgrade in the similar supported upgrade path of the [Upgrade Workflow](#).

2. Check for the compatibility of the target CNC component. See [Compatibility check of target NF component with installed CNE](#) section for the procedure.
3. If the CNC components are not compatible, upgrade non-Oracle cloud native environment.
4. If all CNC components are compatible, upgrade the components based on the upgrade sequence mentioned in [Upgrade Workflow](#) section.
5. Run the Helm test command to check the upgrade status. In case of any failure, contact [My Oracle Support](#).
6. Once the Helm test is successful, then the upgrade is complete.
7. Perform the above upgrade steps in the production environment.

3.2.3.2 Compatibility Check of Target NF Component with Installed Non-Oracle cloud native environment

Follow the procedure to check the compatibility of target NF component with installed Non-Oracle cloud native environment:

1. Run the following command to get the list of resource versions for the installed non-Oracle cloud native environment release:

```
kubectl api-resources --sort-by='name' (or kubectl api-versions)
```

Sample output:

```
serviceaccounts          sa
v1                      true      ServiceAccount
serviceentries          se      networking.istio.io/
v1beta1                true      ServiceEntry
servicemonitors
monitoring.coreos.com/v1 true      ServiceMonitor
services               svc
v1                      true      Service
sidecars               networking.istio.io/
v1beta1                true      Sidecar ...
...
...
...
```

2. Run the following command to get the list of target CNC Console, OCCM, NF, cnDBTier, and OSO resources and their versions:

```
helm upgrade <helm release> <chart tarball> -f <ASM Custom File> -n <helm
release> --dry-run | egrep -i "^apiVersion:|^kind:" | sed 's/\r$//' | awk
'{ ORS = (NR%2 ? " , " : RS) } 1' | sort | uniq
```

For example:

```
helm upgrade ocp-f-lp occnp-23.2.0-od-20230210.tgz -f occnp-23.2.0-
nb-20230127-custom-values-pcf-ASM.yaml -n ocp-f-lp --dry-run | egrep -i
"^apiVersion:|^kind:" | sed 's/\r$//' | awk '{ ORS = (NR%2 ? " , " : RS) }
1' | sort | uniq
```

Sample output:

```
apiVersion: apps/v1, kind: Deployment
apiVersion: apps/v1, kind: StatefulSet
apiVersion: autoscaling/v1, kind: HorizontalPodAutoscaler
apiVersion: autoscaling/v2beta1, kind: HorizontalPodAutoscaler
apiVersion: autoscaling/v2beta2, kind: HorizontalPodAutoscaler
apiVersion: batch/v1, kind: Job
apiVersion: policy/v1beta1, kind: PodDisruptionBudget
```

```

apiVersion: rbac.authorization.k8s.io/v1beta1, kind: RoleBinding
apiVersion: rbac.authorization.k8s.io/v1, kind: Role
apiVersion: rbac.authorization.k8s.io/v1, kind: RoleBinding
apiVersion: v1, kind: ConfigMap
apiVersion: v1, kind: Service
apiVersion: v1, kind: ServiceAccount

```

3. Verify that installed non-Oracle cloud native environment has all Kubernetes resources and their versions required by CNC Console, OCCM, NF, cnDBTier, and OSO.

3.3 Performing the NF Upgrade

See the following documents for detailed procedures to upgrade the respective components:

Table 3-1 CNC Network Functions Document Reference

CNC Network Functions	Document Reference
Oracle Communications Cloud Native Core, Binding Support Function (BSF)	<i>Oracle Communications Cloud Native Core, Binding Support Function Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Network Exposure Function (NEF)	<i>Oracle Communications Cloud Native Core, Network Exposure Function Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Network Repository Function (NRF)	<i>Oracle Communications Cloud Native Core, Network Repository Function Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Network Slice Selection Function (NSSF)	<i>Oracle Communications Cloud Native Core, Network Slice Selection Function Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Converged Policy (Policy)	<i>Oracle Communications Cloud Native Core, Converged Policy Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Security Edge Protection Proxy (SEPP)	<i>Oracle Communications Cloud Native Core, Security Edge Protection Proxy Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Service Communication Proxy (SCP)	<i>Oracle Communications Cloud Native Core, Service Communication Proxy Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Unified Data Repository (UDR)	<i>Oracle Communications Cloud Native Core, Unified Data Repository Installation, Upgrade, and Fault Recovery Guide</i>

Table 3-2 CNC Companion Components Document Reference


CNC Companion Components	Document Reference
Oracle Communications Cloud Native Configuration Console (CNC Console)	<i>Oracle Communications Cloud Native Configuration Console Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, cnDBTier (cnDBTier)	<i>Oracle Communications Cloud Native Core, cnDBTier Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Certification Management (OCCM)	<i>Oracle Communications Cloud Native Core, Certification Management, Upgrade, and Fault Recovery Guide</i>

Table 3-2 (Cont.) CNC Companion Components Document Reference

CNC Companion Components	Document Reference
Oracle Communications Cloud Native Core, Operations Services Overlay (OSO)	<i>Oracle Communications Cloud Native Core, Operations Services Overlay Installation and Upgrade Guide</i>

3.3.1 Non-Oracle Cloud Native Environment Upgrade

Figure 3-3 Non-Oracle CNE Upgrade



The following procedure explains the upgrade workflow for non-Oracle cloud native environment:

1. Check for the compatibility of the target NF component. Refer to [Compatibility check of target NF component with installed CNE](#) section for compatibility check procedure.
2. Check for resource requirements detail for worker nodes upgrade in vendor-specific cloud native core documentation.
3. Upgrade cloud native core and restart the applications, if required.
4. Run the Helm test command to check the upgrade status.
5. Once the Helm test is successful, the upgrade is complete.
6. Perform the above steps in the production environment.

3.3.2 Compatibility Check of NF Component with Target Cloud Native Environment

Perform the following compatibility checks:

1. Run the following commands to get the list of deployed resources and their versions from a given CNC Console, OCCM, NF, cnDBTier and OSO release:

```
helm get manifest <helm release> -n <namespace> | egrep -i "^apiVersion:|
^kind:" | sed 's/\r$//' | awk '{ ORS = (NR%2 ? " , " : RS) } 1' | sort | uniq
```

Sample Output:

```
apiVersion: apps/v1, kind: Deployment
apiVersion: apps/v1, kind: StatefulSet
apiVersion: autoscaling/v1, kind: HorizontalPodAutoscaler
apiVersion: autoscaling/v2beta1, kind: HorizontalPodAutoscaler
apiVersion: autoscaling/v2beta2, kind: HorizontalPodAutoscaler
apiVersion: policy/v1beta1, kind: PodDisruptionBudget
apiVersion: rbac.authorization.k8s.io/v1beta1, kind: RoleBinding
apiVersion: rbac.authorization.k8s.io/v1, kind: Role
apiVersion: rbac.authorization.k8s.io/v1, kind: RoleBinding
apiVersion: v1, kind: ConfigMap
apiVersion: v1, kind: Service
apiVersion: v1, kind: ServiceAccount
```

2. Run the following command to get the list of resource versions for the target cloud native environment release:

Note

- See Kubernetes release documentation for supported resources and versions.
- Alternate approach: From any installed target cloud native environment release, run the following command to get a list of all supported api-versions:

```
kubectl api-resources --sort-by='name' (or kubectl api-versions)
```

Sample output:

serviceaccounts	sa		
v1		true	ServiceAccount
serviceentries	se		networking.istio.io/
v1beta1		true	ServiceEntry
servicemonitors			
monitoring.coreos.com/v1		true	ServiceMonitor
services	svc		
v1		true	Service

```

sidecars                                networking.istio.io/
v1beta1                                true      Sidecar ...
...
...
...

```

3. Manually ensure that all installed CNC Console, OCCM, NF, cnDBTier, and OSO resources and their versions are available in the target cloud native environment.

3.4 Performing the Postupgrade Tasks

This section explains the postupgrade tasks.

3.4.1 NF Postupgrade

- Verify postupgrade of all the CNC NFs and Companion components by running the "helm test" to verify the deployment health and status.
- See CNC NFs and Companion components installation, upgrade, and fault recovery guides for postupgrade task details after upgrading respective components.

3.4.2 Cloud Native Environment Postupgrade

- Re-validate the stability of all the components by running "helm test" provided by CNC Console, OCCM, NF, and cnDBTier to verify the deployment health and status.
- For procedures to perform any restart required by CNC Console, OCCM, NF, cnDBTier, or any other external component, see the component-specific guides or documents.

3.5 Performing the Rollback

Once a rollback is triggered for a component, this section of the guide helps you to decide the order of the rollback for other components that were upgraded successfully. For example, a rollback is triggered if the cnDBTier upgrade fails (or validation after an upgrade fails) for any reason, and this guide provides the information to perform the rollback of CNC NFs and CNC Console in a given order.

The following diagram details the rollback sequence:

Figure 3-4 Rollback Sequence with Non-Oracle CNE




Table 3-3 CNC Network Functions Document Reference

CNC Network Functions	Document Reference
Oracle Communications Cloud Native Core, Binding Support Function (BSF)	<i>Oracle Communications Cloud Native Core, Binding Support Function Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Network Exposure Function (NEF)	<i>Oracle Communications Cloud Native Core, Network Exposure Function Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Network Repository Function (NRF)	<i>Oracle Communications Cloud Native Core, Network Repository Function Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Network Slice Selection Function (NSSF)	<i>Oracle Communications Cloud Native Core, Network Slice Selection Function Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Converged Policy (Policy)	<i>Oracle Communications Cloud Native Core, Converged Policy Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Security Edge Protection Proxy (SEPP)	<i>Oracle Communications Cloud Native Core, Security Edge Protection Proxy Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Service Communication Proxy (SCP)	<i>Oracle Communications Cloud Native Core, Service Communication Proxy Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Unified Data Repository (UDR)	<i>Oracle Communications Cloud Native Core, Unified Data Repository Installation, Upgrade, and Fault Recovery Guide</i>

Table 3-4 CNC Companion Components Document Reference

CNC Companion Components	Document Reference
Oracle Communications Cloud Native Configuration Console (CNC Console)	<i>Oracle Communications Cloud Native Configuration Console Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, cnDBTier (cnDBTier)	<i>Oracle Communications Cloud Native Core, cnDBTier Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Certification Management (OCCM)	<i>Oracle Communications Cloud Native Core, Certification Management, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Operations Services Overlay (OSO)	<i>Oracle Communications Cloud Native Core, Operations Services Overlay Installation and Upgrade Guide</i>

3.6 Performing the Postrollback Tasks

Perform the following postrollback tasks:

- Verify the rollback of all the CNC NFs and Companion components by running the "helm test" to verify the deployment health and status.
- See CNC NFs and Companion components installation and upgrade guides for postrollback task details after rolling back respective components.

4

Upgrade of Oracle CNC Solution deployed on with OCI

This section provides an overview of how to perform an upgrade of Oracle CNC NFs and Companion components in Oracle Cloud Infrastructure (OCI) environment.

4.1 Planning Upgrade

This section explains the planning for upgrading CNC with OCI Environment (OKE).

4.1.1 Guidelines

Oracle recommends the following guidelines:

- Perform upgrade testing in sandbox or lab deployment before testing in production sites.
- Upgrade all components to their target release, as per the compatibility matrix provided in the CNC release notes.
- In a multisite deployment model, perform the upgrade of one site at a time. Follow the sequence mentioned in [upgrade sequence](#) to upgrade all the components in the specific site and then proceed to the next site.
Refer to cnDBTier and NF-specific installation, upgrade, and fault recovery guide for post upgrade steps to verify the health of cnDBTier services and NF components.
- Perform an upgrade of CNC Console, NF, and cnDBTier in a single maintenance window. If upgrade takes longer than a single maintenance window, individual components can be upgraded in multiple maintenance windows. Ensure that the upgrade order is followed as per the sequence mentioned in [upgrade sequence](#).
- If multiple NFs share a cnDBTier, upgrade all the instances of CNC Console and NFs sharing that cnDBTier of the specific site, before upgrading the cnDBTier of the site.
- Rollback is the reverse order of upgrade.

4.1.2 Preupgrade Checklist

Go through the following checklist before performing an upgrade.

4.1.2.1 Resource Requirement

This section details about the resources required to upgrade CNC NFs and Companion components deployed on OCI environment.

4.1.2.1.1 OCI

Ensure that the number of planned resources required for NF, CNC Console, and cnDBTier are available during the upgrade.

4.1.2.1.2 Network Functions

For CNC NFs and Companion components upgrade, reevaluate resource requirement before performing the upgrade. It is possible that CNC NFs and Companion components require additional resources due to changes in architecture or service model.

For more information on NF resource requirements, see NF-specific installation, upgrade, and fault recovery guides.

4.1.2.2 Prerequisites

Ensure that you have the following prerequisites before performing an upgrade:


- Keep the backup of the following artifacts from your recent successful installation handy:
 - custom values.yaml file
 - Updated helm charts
 - Secrets
 - Certificates
 - Keys used
- See CNC Console, NF, and cnDBTier guides for preupgrade task details before upgrading respective components.

4.1.3 Upgrade Workflow

The following diagram details the upgrade sequence if you are using OCI.

Note


OCI Adaptor doesn't support upgrade. Since OCI Adaptor requires reinstall, metrics scraping is impacted during that period.

Figure 4-1 CNC NFs and Companion components Upgrade Order on OCI Environment

See CNC NFs and Companion components installation, upgrade, and fault recovery guides for details on upgrading the respective components.

4.1.3.1 CNC NFs and Companion components Upgrade

This section explains the upgrade workflow of CNC NFs and Companion Components deployed on OCI environment.

Figure 4-2 CNC NFs and Companion components Upgrade on OCI Environment

The following procedure explains the upgrade workflow for Oracle NFs:

1. Check the supported upgrade path for each NF. To know the upgrade path, see *Oracle Communications Cloud Native Core Release Notes*.

Note

It is recommended to upgrade in the similar supported upgrade path of the [Upgrade Workflow](#).

2. Check for the compatibility of the target NF component. See [Compatibility check of target NF component with installed CNE](#) section for the procedure.
3. If the NFs are not compatible, upgrade non-Oracle cloud native environment.
4. If all NFs are compatible, upgrade the components based on the upgrade sequence mentioned in [Upgrade Workflow](#) section.
5. Run the Helm test command to check the upgrade status. In case of any failure, contact [My Oracle Support](#).
6. Once the Helm test is successful, then the upgrade is complete.
7. Perform the above upgrade steps in the production environment.

4.1.4 Compatibility Check of Target NF Component with Installed OCI

1. Run the following command to get the list of resource versions for the installed OCI:

```
kubectl api-versions
```

Sample output:

```
admissionregistration.k8s.io/v1 apiextensions.k8s.io/v1
apiregistration.k8s.io/v1 apps/v1
authentication.k8s.io/v1 authorization.k8s.io/v1
autoscaling/v1
autoscaling/v2 autoscaling/v2beta2
batch/v1 certificates.k8s.io/v1 coordination.k8s.io/v1
discovery.k8s.io/v1 events.k8s.io/v1
flowcontrol.apiserver.k8s.io/v1beta1
flowcontrol.apiserver.k8s.io/v1beta2 metrics.k8s.io/v1beta1
networking.k8s.io/v1 node.k8s.io/v1 policy/v1 rbac.authorization.k8s.io/v1
scheduling.k8s.io/v1 storage.k8s.io/v1 storage.k8s.io/v1beta1 v1
```

2. Run the following command to get the list of target CNC Console, NF, and cnDBTier resources and their versions:

```
helm upgrade <helm release> <chart tarball> -f <Custom File> -n <helm
release> --dry-run | egrep -i "^apiVersion:|^kind:" | sed 's/\r$//' | awk
'{ ORS = (NR%2 ? " , " : RS) } 1' | sort | uniq
```

For example:

```
helm upgrade ocudr ocudr-23.4.0.tgz -f ocudr_custom_values_23.4.0.yaml -n
ocudr --dry-run | egrep -i "^apiVersion:|^kind:" | sed 's/\r$//' | awk
'{ ORS = (NR%2 ? " , " : RS) } 1' | sort | uniq
```

Sample output:

```
apiVersion: apps/v1 # for versions before 1.9.0 use apps/v1beta2 ,
kind: Deployment apiVersion: apps/v1 # for versions before 1.9.0 use apps/
v1beta2,
kind: Deployment apiVersion: apps/v1,
kind: Deployment apiVersion: apps/v1,
kind: StatefulSet apiVersion: autoscaling/v2,
kind: HorizontalPodAutoscaler apiVersion: batch/v1,
kind: Job apiVersion: policy/v1,
kind: PodDisruptionBudget
apiVersion: rbac.authorization.k8s.io/v1,
kind: Role apiVersion: rbac.authorization.k8s.io/v1,
kind: RoleBinding apiVersion: v1,
kind: ConfigMap apiVersion: v1,
kind: Pod apiVersion: v1,
kind: Service apiVersion: v1,
kind: ServiceAccount
kind: Service, apiVersion: v1
```

3. Verify that installed OCI has all resources and their versions required by CNC Console, NF, and cnDBTier.

4.2 Performing the NF Upgrade

See the following documents for detailed procedures to upgrade the respective components:

Table 4-1 CNC Network Functions Document Reference

CNC Network Functions	Document Reference
Oracle Communications Cloud Native Core, Binding Support Function (BSF)	<i>Oracle Communications Cloud Native Core, Binding Support Function Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Network Exposure Function (NEF)	<i>Oracle Communications Cloud Native Core, Network Exposure Function Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Network Repository Function (NRF)	<i>Oracle Communications Cloud Native Core, Network Repository Function Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Network Slice Selection Function (NSSF)	<i>Oracle Communications Cloud Native Core, Network Slice Selection Function Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Converged Policy (Policy)	<i>Oracle Communications Cloud Native Core, Converged Policy Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Security Edge Protection Proxy (SEPP)	<i>Oracle Communications Cloud Native Core, Security Edge Protection Proxy Installation, Upgrade, and Fault Recovery Guide</i>

Table 4-1 (Cont.) CNC Network Functions Document Reference

CNC Network Functions	Document Reference
Oracle Communications Cloud Native Core, Service Communication Proxy (SCP)	<i>Oracle Communications Cloud Native Core, Service Communication Proxy Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Unified Data Repository (UDR)	<i>Oracle Communications Cloud Native Core, Unified Data Repository Installation, Upgrade, and Fault Recovery Guide</i>

Table 4-2 CNC Companion Components Document Reference

CNC Companion Components	Document Reference
Oracle Communications Cloud Native Configuration Console (CNC Console)	<i>Oracle Communications Cloud Native Configuration Console Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, cnDBTier (cnDBTier)	<i>Oracle Communications Cloud Native Core, cnDBTier Installation, Upgrade, and Fault Recovery Guide</i>

Table 4-3 OCI Components Document Reference

OCI Components	Document Reference
OCI Adaptor	• <i>Oracle Communications Cloud Native Core, OCI Adaptor User Guide</i> • <i>Oracle Communications Cloud Native Core, OCI Deployment Guide</i>

Note

OCI Adaptor doesn't support upgrade.

4.2.1 Upgrade Workflow

The following procedure explains the upgrade workflow for CNC components in OCI environment:

1. Check for the compatibility of the target NF component. Refer to [Compatibility check of target NF component with installed CNE](#) section for compatibility check procedure.
2. Upgrade cloud native core and restart the applications, if required.
3. Run the Helm test command to check the upgrade status.
4. Once the Helm test is successful, the upgrade is complete.
5. Perform the above steps in the production environment.

4.2.2 Compatibility Check of CNC NF Component on Target OCI Environment

Perform the following compatibility checks:

1. Run the following commands to get the list of deployed resources and their versions from a given CNC NFs and Companion components release:

```
helm get manifest ocudr -n ocudr | egrep -i "^apiVersion:|^kind:" | sed
's/\r$//' | awk '{ORS = (NR%2 ? " , " : RS) } 1' | sort | uniq
```

Sample output:

```
apiVersion: apps/v1      # for versions before 1.9.0 use apps/v1beta2 ,
kind: Deployment
apiVersion: apps/v1      # for versions before 1.9.0 use apps/v1beta2, kind:
Deployment
apiVersion: apps/v1, kind: Deployment
apiVersion: apps/v1, kind: StatefulSet
apiVersion: autoscaling/v2, kind: HorizontalPodAutoscaler
apiVersion: policy/v1, kind: PodDisruptionBudget
apiVersion: rbac.authorization.k8s.io/v1, kind: Role
apiVersion: rbac.authorization.k8s.io/v1, kind: RoleBinding
apiVersion: v1, kind: ConfigMap
apiVersion: v1, kind: Service
apiVersion: v1, kind: ServiceAccount
```

2. Run the following command to get the list of resource versions for the target cloud native environment release:

Note

- See OKE release documentation for supported resources and versions.
- Alternate approach: From any installed target cloud native environment release, run the following command to get a list of all supported api-versions:

```
kubectl api-versions
```

Sample output:

```
admissionregistration.k8s.io/v1 apiextensions.k8s.io/v1
apiregistration.k8s.io/v1 apps/v1
authentication.k8s.io/v1 authorization.k8s.io/v1
autoscaling/v1
autoscaling/v2 autoscaling/v2beta2
batch/v1 certificates.k8s.io/v1 coordination.k8s.io/v1
discovery.k8s.io/v1 events.k8s.io/v1
flowcontrol.apiserver.k8s.io/v1beta1
flowcontrol.apiserver.k8s.io/v1beta2 metrics.k8s.io/v1beta1
networking.k8s.io/v1 node.k8s.io/v1 policy/v1 rbac.authorization.k8s.io/v1
scheduling.k8s.io/v1 storage.k8s.io/v1 storage.k8s.io/v1beta1 v1
```

3. Manually ensure that all installed CNC NFs and Companion components resources and their versions are available in the target OCI environment.

4.3 Performing the Postupgrade Tasks

This section explains the postupgrade tasks.

4.3.1 NF Postupgrade

Perform the following NF postupgrade tasks:

- Verify postupgrade of all the components by running the "helm test" provided by CNC Console, NFs, and cnDBTier to verify the deployment health and status.
- See CNC Console, NFs, and cnDBTier installation, upgrade, and fault recovery guides for postupgrade task details after upgrading respective components.

4.3.2 OCI Environment Postupgrade

Perform the following postupgrade tasks:

- Re-validate the stability of all the components by running "helm test" provided by CNC Console, NF, and cnDBTier to verify the deployment health and status.
- For procedures to perform any restart required by CNC Console, NF, or cnDBTier, see the NF-specific installation, upgrade, and fault recovery guides.


4.4 Performing the Rollback

Once a rollback is triggered for a component, this section of the guide helps you to decide the order of the rollback for other components that were upgraded successfully. For example, a rollback is triggered if the cnDBTier upgrade fails (or validation after an upgrade fails) for any reason, and this guide provides the information to perform the rollback of CNC NFs and Companion components in a given order.

Note

OCI Adaptor doesn't support rollback.

The following diagram details the rollback sequence:

Figure 4-3 Performing the Rollback**Note**

OCI Adaptor rollback is not supported. The user must use OCI Resource Manager to remove the OCI Adaptors stack.

Table 4-4 CNC Network Functions Document Reference

CNC Network Functions	Document Reference
Oracle Communications Cloud Native Core, Binding Support Function (BSF)	<i>Oracle Communications Cloud Native Core, Binding Support Function Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Network Exposure Function (NEF)	<i>Oracle Communications Cloud Native Core, Network Exposure Function Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Network Repository Function (NRF)	<i>Oracle Communications Cloud Native Core, Network Repository Function Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Network Slice Selection Function (NSSF)	<i>Oracle Communications Cloud Native Core, Network Slice Selection Function Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Converged Policy (Policy)	<i>Oracle Communications Cloud Native Core, Converged Policy Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Security Edge Protection Proxy (SEPP)	<i>Oracle Communications Cloud Native Core, Security Edge Protection Proxy Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, Service Communication Proxy (SCP)	<i>Oracle Communications Cloud Native Core, Service Communication Proxy Installation, Upgrade, and Fault Recovery Guide</i>

Table 4-4 (Cont.) CNC Network Functions Document Reference

CNC Network Functions	Document Reference
Oracle Communications Cloud Native Core, Unified Data Repository (UDR)	<i>Oracle Communications Cloud Native Core, Unified Data Repository Installation, Upgrade, and Fault Recovery Guide</i>

Table 4-5 CNC Companion Components Document Reference

CNC Companion Components	Document Reference
Oracle Communications Cloud Native Configuration Console (CNC Console)	<i>Oracle Communications Cloud Native Configuration Console Installation, Upgrade, and Fault Recovery Guide</i>
Oracle Communications Cloud Native Core, cnDBTier (cnDBTier)	<i>Oracle Communications Cloud Native Core, cnDBTier Installation, Upgrade, and Fault Recovery Guide</i>

Table 4-6 OCI Components Document Reference

OCI Components	Document Reference
OCI Adaptor	<i>Oracle Communications Cloud Native Core, OCI Adaptor User Guide</i> <i>Oracle Communications Cloud Native Core, OCI Deployment Guide</i>

4.5 Performing the Postrollback Tasks

Perform the following postrollback tasks:

- Verify the rollback of all the CNC NFs and Companion components by running the "helm test" to verify the deployment health and status.
- See CNC NFs and Companion components installation, upgrade, and fault recovery guides for postrollback task details after rolling back respective components.

A

Frequently Asked Questions (FAQs)

This section lists the most commonly asked questions while upgrading a Network Function (NF).

What is the upgrade sequence for NFs and cnDBTier when there are multiple NFs in a network?

You can perform upgrade of an NF followed by cnDBTier in a site. This is the only recommended upgrade sequence. There's no fixed order of upgrade between multiple NFs.

For Example: NRF, SCP, or SEPP are deployed in the network, if the NFs are 3GPP compliant, upgrade sequence between NFs isn't dependent. If you upgrade NRF first, then follow the upgrade of cnDBTier connected to NRF. For more information about the upgrade sequence, see the [Overview](#) section.

What if during the upgrade of a site, the upgrade fails? What should be the upgrade sequence?

There's no change in the upgrade sequence. You can perform upgrade of an NF followed by cnDBTier. This is the only recommended upgrade sequence. In case the upgrade fails, perform fault recovery procedures for the site. For more information about the upgrade sequence, see the [Overview](#) section.

If it's a NF, then follow the fault recovery procedure provided in NF-specific *Installation, Upgrade, and Fault Recovery Guide*.

If it's the cnDBTier, then follow the fault recovery procedure provided in *Oracle Communications Cloud Native Core DBTier Installation, Upgrade, and Fault Recovery Guide*.

During the upgrade, if georeplication fails then what are recommended upgrade procedures to recover the sites?

In case the replication fails during upgrade or postupgrade, then resync the replication after upgrade completion using cnDBTier procedures. For more information about the resync, see *Oracle Communications Cloud Native Core DBTier Installation, Upgrade, and Fault Recovery Guide*. If the issue persists, contact [My Oracle Support](#).

What is the upgrade impact if the NF schema version changes when georeplication is enabled?

NF upgrade takes care of any schema changes automatically. If any NF requires an alternate update strategy due to non-backward compatibility issues, it will be documented in NF-specific *Installation, Upgrade, and Fault Recovery Guide*.

If I want all the NFs to be at the same version before upgrading cnDBTier, does this impact the upgrade strategy?

It isn't suggested upgrading a layer of same NFs across all sites, before moving to the next. There's a higher risk of rollback scenarios of all the sites, which can impact the service. The recommended upgrade sequence is provided in the [Overview](#) section.

For Example: In three-site georedundancy, if NRF, SCP, and cnDBTier are deployed, upgrade cnDBTier and the NFs in the specific site, instead of first upgrading cnDBTier across all the sites and then the NFs.

What should I do if I see an error while upgrading?

If you see any upgrade or rollback error, see NF-specific *Troubleshooting Guide*. In case the error persists, collect the log and report it to [My Oracle Support](#).

How do I verify if the upgrade is successful?

Perform verification tasks provided in NF-specific *Installation, Upgrade, and Fault Recovery Guide*. For more information about the upgrade, see the "Upgrade Tasks" section in the NF-specific *Installation, Upgrade, and Fault Recovery Guide*.

When I have a non-Oracle CNE, how do I check if the NFs are compatible or not?

Perform compatibility check between the NFs and non-Oracle CNE. For more information about the procedure, see [Compatibility Check of Target NF Component with Installed Non-Oracle cloud native environment](#).