Oracle[®] Hospitality Cruise Shipboard Property Management System Administration User Guide



Release 20.3 F59779-03 June 2023

ORACLE

Oracle Hospitality Cruise Shipboard Property Management System Administration User Guide, Release 20.3

F59779-03

Copyright © 1995, 2023, Oracle and/or its affiliates.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle[®], Java, and MySQL are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

Preface

Prerequisite, Supported Systems and Compatibility

1 Administration

2 System Setup

Harbour Setup	2-2
Setting Up a Harbour/Port	2-2
Removing a Harbour/Port	2-3
System Cruise Setup	2-3
Creating System Cruise	2-4
Adding Port Day to Cruise	2-4
Removing Port Day	2-4
Copying Cruise Day	2-5
Removing a Cruise	2-5
System Date Change	2-5
Performing System Date Change	2-5
System Cruise Change	2-6
Performing System Cruise Change	2-6
Database Parameters	2-7
Defining the Days to Leep Log Files	2-8
Airport Setup	2-9
Adding Airport Code Manually	2-9
Company Entity	2-9
Assigning Company ID	2-11
Time Zone Change	2-11
Batch Reports Printing Setup	2-11
Adding Report to Batch Printing	2-12
Copying Batch Details to Other Report	2-13



2-13
2-13
2-15
2-16
2-17
2-17
2-17

3 Financial Setup

Department Codes	3-1
Main Department	3-1
Adding a Main Department Code	3-2
Deleting a Main Department	3-2
Sub-Department	3-2
Adding a Debit Sub-Department	3-5
Adding a Credit Sub-Department	3-5
Deleting Sub-Department Code	3-5
Currencies	3-6
Adding Currency Rate	3-6
Merchant Details	3-6
Pre-Selection Groups	3-7
Stateroom Upgrade Setup	3-7
Discount Templates	3-7
Quick Posting Template	3-8
Import Credit Card Bin	3-8
Disallow Manual Posting Applications	3-8
Department Grouping	3-8
VAT Handling	3-8
VAT Tax Class	3-9
VAT Tax Rate	3-9
Activating a Tax Rate	3-10
VAT Tax Reminder	3-10

4 Itinerary Setup

Adding an Activity	4-1
Copying an Activity Setup	4-2
Add Package Price	4-3
Adding Team/Time Frame	4-3



5 Events

5-2
5-2
5-2
5-3

6 Vendors

Setting Up a Vendor	6-1
0	

7 Safety Setup

Safety Setup Type	7-1
Configuring Safety Codes in Standard Drill	7-5
Setting Up Muster Station	7-5
Setting Up Lifeboat/Liferaft	7-6
Setting Up Drill Definition	7-7
Setting Up Course and Certificates	7-7
Advance Safety Drill Mode	7-8
Setting Up Muster Station In Advance Drill Mode	7-9
Setting Up Lifeboat/Liferaft in Advance Drill Mode	7-10
Setting Up Safety Function in Advance Drill Mode	7-10
Setting Up Drill Type	7-11
Setting Up Drill Definition in Advance Drill Mode	7-11
Setting Up Drill Template in Advance Drill Mode	7-12
Setting Up Course and Certificates in Advance Drill Mode	7-13

8 Stateroom Setup

Adding, Editing and Copying A Stateroom	8-1
Editinga a Cabin	8-2
Copying a Cabin Code	8-2
Batch Check-In/Out	8-2
Feature/Amenity Item	8-3
Cabin Cleaning State Color	8-3
Deck Plan Designer	8-4
Editing a Deck Plan	8-5
Linking a Plan	8-5
Deck Plan Setup	8-5



4-3

Ving Card Crew Key Type	8-5
Common Access Area	8-6
Common Access Area Name	8-6
Common Access Area Definition	8-6

9 System Codes

Setting Up System Codes	9-2
Nationality Codes	9-2
Setting Up Nationality Groups	9-2
Setting Up Nationality Codes	9-3
Setting Up Document Types	9-3
Setting Up General Reason Code	9-4
Setting Up Comment Departments	9-4
Enabling/Disabling Log Entry	9-5

10 Package Plans

11 Maintenance Code Setup

Workers in Workgroup	11-2
Adding Task Code	11-2
Adding Items Code	11-3

12 Gift Card

13 POS Discount

14 Security Display Setup

15 Visa Type Setup

Multimedia File Maintenance 16

Board Card Printing Template	
Creating Board Card Printing Template	17-4
Removing Template	17-4
Security Alert Setup	
Beeper Setup	
Security	
Photo Setup	
Upload/Export Photos	21-1
Export Document	21-5

Export Document



Preface

Oracle Hospitality Cruise Shipboard Property Management System (SPMS) offers the ship side users access to the ship data. The Administration module is the backbone of the SPMS, where system codes are built according to the approved ship's operational guidelines and requirements. As each of these codes may link to other fields or require other codes to be setup first, it is advisable to study and understand the relationship of each requirement before you start coding. The System Administrator, Chief Purser, Accounting Purser, Crew Purser, Cruise Director, and Group Coordinator and Safety Officer are the key personnel responsible for configuring and maintaining these codes.

Audience

This document is for technical personnel, application specialists, and users of SPMS.

Customer Support

To contact Oracle Customer Support, access My Oracle Support at the following URL:

https://iccp.custhelp.com

When contacting Customer Support, please provide the following:

- Product version and program/module name
- Functional and technical description of the problem (include business impact)
- Detailed step-by-step instructions to re-create
- Exact error message received
- Screenshots of each step you take

Documentation

Oracle Hospitality product documentation is available on the Oracle Help Center at http://docs.oracle.com/en/industries/hospitality/.

Revision History

Table 1 Revision History

Date	Description of Change
September 2022	Initial publication.
January 2023	Updated the information in Performing System Date Change.
June 2023	Updated new customer portal.



Prerequisite, Supported Systems and Compatibility

This section describes the minimum requirements for the Administration module.

Prerequisites

OHC Administration.exe

Compatibility

SPMS version 20.3 or later. For customers operating on version 20.3 and below, database upgrade to the recommended or latest version is required.



1 Administration

The Administration Menu comprises of configuration input fields required by the ship's operations. Some of the codes depend on another set of code, and may result in some functions not working as desires if they are not properly set up. Consult Oracle Hospitality Cruise Support if you have any questions about configuring the codes.



2 System Setup

In Administration, System Setup Menu, you can set up configurations such as Port of call, System Cruise, System Date Change, System Cruise Change, and Database Parameters.

Administratio	n Reports	Security	About	Exit	
System Financia Itinerary Crew Se Safety S Stateroo System Package Maintee Gift Car POS Dis Security Manual Visa Typ Internet User De Multim Board C	Setup I Setup tup etup m Setup Codes Plans ance Setup d Setup	up on Setup ntenance	About	Exit System Date Change System Cruise Change System Cruise Setup System Cruise Setup Harbour Setup Harbour Setup (IATA) Company Entity Setup Timezone Change Setup Database Parameters Reports Batch Printing Setu Reports Setup Reset Tender Queue Numb Change Disembark Date Change Embark Date Labels Setup	
Signatu Upload Export F	tem Posting re Device Co Photos				

Figure 2-1 Administration Menu



Harbour Setup

The Harbour Setup function enables you to maintain the ship's port of embarkation and the local agent handling the port administration.

Setting Up a Harbour/Port

W Ha	arbo	our Setup	×
All Harbour		Harbour	
COBH Cobh	~	Description:	TLD Fort Lauderdale
COCH Cochin/India		Description: I	
COLO Colombo			US0388>, <fort lauderdale="">, <united< td=""></united<></fort>
COPE Copenhagen			TATES>, <florida>-USPEF-, -PT EVERGLADES-,-</florida>
COZU Cozumel			NITED STATES-
CRISTO Cristobal Panama			
DANANG Danang			
DARW Darwin			× .
		Courtes D	
DUBLI Dublin		Country	
DUBRO Dubrovnik		0	
EDEN Eden		Custom Info	
ELPOVE El Porvenir Panama		Enabled	
FREDER Frederiksted/St.Croix/USA Virgin Islands		,	
FREE Freeport/Bahamas			
FTLD Fort Lauderdale * Add New			
FUNCH Funchal X Remove		- Port Agent Info	
GENO Genova		-	
GOET Goeteburg		Company Name	
GRTURK Grand Turk/Turks&Caicos Islands		Contact Person	
GTGC George Town/Grand Cayman		Dhana Number	· · · · · · · · · · · · · · · · · · ·
GUSTAV Gustavia/St. Barthelemy		Phone Number:	
HAMB Hamburg		eMail Address:	
HAMI Hamilton/Bermuda			
HANGA Hanga Roa			
HEIL Heiligendamm			
HELL V Hell Ville			
HELS Helsinki			
HILO Hilo			
HOBART Hobart			
HOCHI Ho Chi Minh City			
HONGK Hong Kong			
HONO Honolulu	~		OK Cancel Apply

Figure 2-2 Harbour Setup

- **1.** From the **Administration Menu**, select **System Setup**, and then **Harbour Setup** under the sub-category.
- 2. In the left pane of the Harbour Setup window, right-click and select **Add New** to add a new code.
- 3. In the **Description** field, enter the short code and description of the harbour name.
- 4. In the Comment field, enter the ISO Port Codes using an angle bracket <> and comma as separator, if any. The system also inserts the standard ISO Port codes from APIS during installation/update in the Comment field.
- 5. Select the **Country**, if any, from the drop-down list.
- In the Port Agent Info section, enter the Port Agent information and click Apply to save the entry. The Enabled check box is selected by default. Deselect the check box to disable the code from the selection window.



Removing a Harbour/Port

- 1. From the Harbour Setup window, right-click the **Port code** and select **Remove**.
- 2. Click **OK** to save and close the window.

System Cruise Setup

Before the ship sets sail on its voyage, you must set up the start/end of the cruise in System Cruise Setup, detailing the start and end date, arrival/departure time at each port, and the base currency.

Figure 2-3 Cruise Setup

4	Cruise Setup)		- • •
All Cruises All Cruises 23/02/2015 HK/NV/BKK 03/02/2015 Hong Kong/Nietnam/Bang 31/01/2015 A 29/01/2015 Vietnam/Hong Kong/Maca * Add New Port/Day Remove Port/Day * Add Cruise Copy Cruise	Cruise Setup Setup Cruise Current Cruise Description: HK/V Start Date: 23/0 Island Date: Itinerary ID: Center Id: Currency: 9503 External Cruise ID: Safety Assembly Time: 2000	N/BKK 2/2015 3 USD US Dollar	Cruise Available	
Kemove Cruise	Cruise Statistics Cruise Day Embarkation Day-Hong Kong Island Tour Danang Ho Chi Minh City - Overnight Bangkok Debarkation - Bangkok	Guests Onboard C 0 0 0	Crew Onboard Children Onboard 0 0 0 0 0 0 0 0 0 0 0	ard First Gangway Time Last Gang
< >	<u> </u>		ок	Cancel Apply

Table 2-1 Cruise Setup Field Definition

Field Name	Description
Description	Short code of the cruise. Mainly use to identify the cruise.
Start Date	The start date of the cruise.
Island Date	Special coded description for General Ledger (GL) Interface.



Field Name	Description
Itinerary ID	An identifier for the voyage/cruise.
Center ID	Special coded description for GL.
Currency	Official on board currency. See Financial Setup, Currencies
External Cruise ID	Cruise ID from an external party.
Safety Assembly Time	Schedule Safety Assembly Time for the cruise.

 Table 2-1
 (Cont.) Cruise Setup Field Definition

Creating System Cruise

- 1. Select System Setup, then System Cruise Setup from the drop-down list.
- 2. In the Cruise Setup window, right-click the **All Cruises** pane and select **Add Cruise** to open a blank setup form.
- 3. Enter the Description, Start Date, Island Date, Itinerary and Currency.
- 4. Click Apply to save.

Adding Port Day to Cruise

- 1. At the All Cruises section of the Cruise Setup form, right-click on the Cruise Name and select Add New Port/Day.
- 2. At the Setup Cruise form, enter the **Date**, **Description**, **Port Comments**, **Weather** and select from the drop-down list the **Arrival Port**, **IPM Port Type**, **Arrival Country**, **Arrival Time** and **Departure Date/Time**.
- 3. Click Apply to save the form.
- 4. Repeat the above steps for additional port day.

Note:

You cannot alter the Port Day once the date is entered. You must first remove and re-enter the port day before adding the remaining port day.

Removing Port Day

- 1. In the All Cruises pane, right-click the **Port Date** you wish to remove.
- 2. Select the Remove Port/Day option.

Note:

The system validates all reservations against the port day before a port/day or cruise is removed. If there are linked reservations found, amend the booking before proceeding.



Copying Cruise Day

The Copy Cruise function copies the same cruise setup/itineraries into a future date. If the information is completely different, we recommend that you create the cruise from scratch and add the port day individually.

1. In the All Cruise section, select the Cruise Day, then right-click and select Copy Cruise.

Duplicate to	
Start Date	Description
I	
Add	Remove
18/2/2015	Bangkok/Vietnam/h

Figure 2-4 Duplicate Cruise

- 2. Insert the **Start Date** and **Description** in the Duplicate Cruise window, then click **Add**. The copy cruise is not allowed if a Start Date exists.
- 3. Click **OK** to confirm and populate the information in the All Cruises section.

Removing a Cruise

You can only remove a cruise when there are no reservation records attached to the cruise day. This option is dimmed when the system detects there is a link to a port day.

- In the All Cruises section, expand the Cruise Day container and select the port day to remove by right-clicking the date.
- 2. Repeat the above step until all of the port days for that cruise are removed.
- 3. Right-click on the Cruise Day and select Remove Cruise.
- 4. Click **OK** to exit and return to System Cruise setup.

System Date Change

The Night Auditor or appointed user from the Finance Department is responsible for performing the System Date Change nightly. Before you run the **System Date Change**, all revenue centers must be in balance, and this includes the Point-of-Sale (POS) System, Cashbook, and other processes deemed necessary by the ship operator.

Performing System Date Change

1. From the System Setup drop-down menu, select System Date Change.



Note: You are not allowed to proceed when the Cashier's sessions is still active.

 At the System Date Change prompt, confirm the New System Date by clicking OK.

Figure 2-5 System Date Change

System	Date C	hange	
Current System Date	e: 29/01/2	015	
New System Date:	30/01/2	015	Ŧ
	ок	Ca	ncel

- 3. You will receive a warning message when the expected disembarking guest/crew remain as check-in in the system. Select **Yes** to proceed or **No** to return to the previous menu and resolve all pending check outs.
- 4. When you select **Yes**, a progress window **Closing pay period** appears once the System Date Change commences. It only appears if the Payroll system is linked, and it changes all the pending reservation statuses for the date to *No-Show*.
- 5. Once the System Date Change completes, you will receive an window indicating the new system date. Click **OK** to close the prompt.

Note:

Cruise Statistics includes Guest Onboard, Visitor Onboard, Crew Onboard, and Children Onboard count will be displayed as well.

System Cruise Change

At the end of each cruise, all revenue centers and system accounts must be in balance and closed before you start a new cruise. This task is performed by the Chief Purser.

Performing System Cruise Change

Important:

The following process sets all accounts to **Closed**. All outstanding balances are carried forward to the next cruise. Proceed with caution.

1. Select System Cruise Change.



2. At the System Cruise Change prompt, click **OK** to confirm the New System Cruise.

Starting date: 29/01/2015 Base currency: 9503 US Dollar Vietnam/Hong Kong/Macau v System Cruise Starting date: 03/02/2015 Base currency: 9503 US Dollar		Race currency: 0503115 Dollar
	Vietnam/Hor	
Starting date: 03/02/2015 Base currency: 9503 US Dollar	New System Cruise	
Hong Kong/Vietnam/Bangkok		

Figure 2-6 System Cruise Change

- 3. You will receive an Open Balance Warning if an unbalanced System Account is detected. Select **Yes** to proceed or **No** to return to the previous menu and resolve all pending check outs.
- 4. Once the cruise change completes, the application returns to the Main menu.

Database Parameters

The application is deployed with a set of Database Parameters that controls the operability and functionality of the module. These system parameters are grouped by module, followed by their function. Please consult Oracle Hospitality Cruise Customer Support prior to changing any of these parameters to avoid adverse implications.



81a	Quick Search			
Advance QCI ^	Group/Name:			
Advance Visitor Imp	Group/ Name:			
Amenities				
CARICOM		1		
CMS			Search	Reset
Cashbook				<u></u>
Cashier	Parameter Details			
Commission on Payment	Enabled:	•		
Posting Requires Password	chableu:	1		
Show onboard currency as this dept	Version:	7.30		
Use Full Cashier	Access:	1		
Casino Casino	202 9229 2			
Comment Card	Value Data Type:	s - string		
Consolidation	Value:	0		
Canal Constant Consta	Description:	1 - Require Password on Posting, 0	- PW not Required	
DataImport	Description	1 - Require Password off Posulig, o	- FW NOL REQUILED	
Cebug				
Departments	Comments:			
Chining Dining				
E-Tix				
CONTRACT CONTRACTOR OF CONTRACT CONTRACTOR OF CONTRACT CONTRACTOR OF CONTRACT				
EONE .		1		
🙀 Exchange				
Excursions				
FCSEWMON				
FCTICKET				
FastPictureTaking				
Ferry Ferry				
Gangway				
General General				
General Ledger				
Hotel Bar Svc Chg				
HouseKeeping				
ingenico				
🙀 Install 🗸 🗸				

Figure 2-7 Database Parameter

- 1. From the System Setup menu, select Database Parameters.
- In the Database Parameters Setup window, click the plus (+) key to expand the group or navigate to the Quick Search section and search the parameter name in the Group/Name field and then click Search.
- **3.** Changing the value at the **Parameter Details** changes the behavior of the functions.
 - a. **Enabled:** By default, all parameters are set to Enabled. In order to disable a parameter, change the value to 0 (0 = Disabled/ 1 = Enabled).
 - b. Value: The acceptable value is defined in the description.

Defining the Days to Leep Log Files

You can to keep an activity log of certain functions, particularly the Interfaces. The number of days to keep is set up in Database Parameter:

- Group Interface, Days to keep Log File.
- Group Gangway, Gangway Log Days

Once defined, the system checks the log entries when the module starts and purges entries older than the days entered.



Airport Setup

The Airport Setup code is used in the Crew and Management Module, Flight Overview window. It allows you to arrange a passenger or crew arrival pickup or departure drop-off. You can also import an airport list instead of inserting the details manually, and this list must be saved in eXtensible Markup Language (XML) format (IATA_AIRPORT_List.XML) in the Oracle Hospitality Cruise folder.

- 1. From the System Setupmenu, select Airport Setup (IATA).
- 2. In the Airport (IATA) setup window, the import commences once it detects the IATA_AIRPORT_List.xml file.
- 3. Click **Yes** at the Admin prompt to confirm the data to import and then click **OK** when the import is successful.

Adding Airport Code Manually

- 1. In the Airport Setup (IATA) setup, All Airport section, right-click and select Add New.
- 2. Enter a **short code**and description in the Description field.
- 3. Enter a **comment** in the Comment field, if any.
- 4. Click Apply to save.

Company Entity

This function allows you to enter the company entity of the ship.

- 1. From the System Setup menu, select Company Entity Setup.
- 2. Right-click on the left pane of the form and select Add New.
- 3. Enter all the information in the **Entity Details** section and then click **Apply**.



	Company Entities Setup	2
DEM Demo Cruise	Entity Details Entity ID: 186000000117 Link to PAR 'WHO	AM
	Code: DEM	
* Add New Kemove		
? Set Who Am I		
r Set Who Am I	Enabled: True 🗨	
	FC ID: 186-117	
	Record ID: 16	
	Type: 1 - Vessel 💌	
	Address:	
	City & Country Code: US	
	Phone:	
	Fax:	
		_
	Email:	
	Print Order Report ID:	
	License:	_
	IDEA Enabled: False	
	,	
		_
	OK Cancel Apply	

Figure 2-8 Company Entities Setup

 Table 2-2
 Field Definition of Company Entities Setup

Field Name	Description
Entity ID	Company Entity ID, provided by SPMS.
Code	Company or Ship Code.
Name	Company or Ship name.
Enabled	Set to True.
Record ID	Defines the record ID representing an entity.
Туре	 Type of Entity 1 = Vessel/Ship 2 = Headquarter 3 = Warehouse
Address	Address of entity.
City & Country Code	Country of entity.
Phone	Phone.
Fax	Fax.
Email	Email address.
Print Order Report ID	Print Order Report ID used by Materials Management System (MM).
License	License Code provided by SPMS.



Field Name	Description
IDEA Enabled	Field use by MMS and is defaulted to False.

Table 2-2 (Cont.) Field Definition of Company Entities Setup

Assigning Company ID

- 1. At the left pane of Company Entity Setup window, right-click the entity name and select **Set Who Am I**.
- 2. At the confirmation prompt, select **Yes** to update information to Parameter **Who Am I** link.
- 3. Restart the application for change to take effect.

Time Zone Change

This function enables you to set the ship's clock forward or backward when the ship travels through different time zones, thus recording an accurate crew work hours. This function is only used in the Time & Attendance module.

- 1. From the System Setup option, select Timezone Change Setup.
- 2. At the Timezone Change Setup window, right-click on the left pane and select Add.
- 3. In the Details section, select the **Data** and **Time** from the drop-down list to specify when the time change should take place.
- 4. Enter the number of hours in the Change Hours field and a remark about the change.
- 5. Click Apply to save.

Batch Reports Printing Setup

The Batch Reports Printing enables you to set up a group of reports to print at a scheduled time. It requires the OHC Auto Report application to run at all times.

1. In the System Setup option, select **Reports Batch Printing Setup**.



Batch Re	ports	s Printing Setup	
Add New Delete Save Undo	te	Refresh Exit	d
Expand All	ſ	Batch Parameters	
Batch Printing Definition Crew Report Definition Cruise Balance Reports Definition Cruise Balance Ist Definition Definition Comparison Compar		Number 4 Name End of Day Reports Privilege No Privilege Require	•
3 - Activities Report - SPA		Always Valid	
		Valid From 25 January 2014 • 16:00:00	÷.
		Valid To 28 February 2014 - 22:00:00	•
	4	Repeat task every minute(s) Note: Use the value '0' (mins) for daily task. (If <valid to=""> date time value is used, this task will be run one time each day until it reach the <valid to=""> date time. Note: Use the value '-1' (mins) for daily task. (If <valid to=""> date time value is used, this task will be run one time each day on the <valid from=""> time until it reach the <valid to=""> date time. Note: Use the value '-2' (mins) for system cruise change batch reporting.</valid></valid></valid></valid></valid>	

Figure 2-9 Batch Reports Printing Setup

- 2. In the Batch Reports Printing Setup window ribbon bar, click the **Add New** button.
- 3. Complete all of the required fields and click Save.

Adding Report to Batch Printing

- 1. Select the **Report Group** from the Batch Printing tree.
- 2. In the Report Parameters tab, select an Action Type from the drop-down list.

Option	Description
1 – Skip	Option to skip the selection process.
2 – Report	Enable a search option and report selection from existing report database.
3 – External Program	The function calls an external program when running the Batch Report. Only external program defined in the General, External Program List parameter is allowed to be saved.
4 – Call Batch Printing	Enable in order to link and include existing report group in the current.

 Table 2-3
 Batch Report Printing Options

- 3. In the Report Name field, click Search to locate the report.
- 4. Select the day of the week from the **Schedule** drop-down field.
- Select the Output method from the drop-down list. If the selected methods is to save to file, enter the Export File name and path and Email Address for the files to be sent to the specific user.



6. Click **Save** at the ribbon bar to save.

Copying Batch Details to Other Report

- 1. Select the Report Group from the tree and then click the **Copy** button at the ribbon bar.
- 2. In the Report Group to copy to, click Add New and then Paste.
- 3. Click the **Save** button to save.

Deleting Batch Report Details

- **1.** Select the Report Group from the Batch Printing tree and then click **Delete** button at the ribbon bar.
- 2. At the confirmation prompt, click Yes to proceed.



This action deletes the record permanently. Please proceed with caution.

Reports Setup

The Report Setup function allows you to add customized Crystal reports to the existing System report set, or export the report template for use on another ship or for further customization.





1			
Current Reports List	Default Standard	Direct Printing Properties	
10c US Immigration		port (Load Variables Export to Crystal Up	load Report
1a Passenger - General		eport Template)	
10 Passenger - Manifests		d Exported from the database. Reports exported Selection Parameters into the Customs properties	
1d Passenger - Disembarking		n, dick the option above to automatically insert th	
1e Passengers - Transit	variables into the database.		
1f U.S. Immigration Lists		Report Details	
1g IMO Immigration Lists	Report ID:		
th Passenger Data Import Reports	Report File Name:		
Passenger Data Import Reports			
ssenger Complaints	Report Title:		
enger Reports for Naples	Report Access:		
General Manifest	Report Sort:		
	Report Group:		¥
Manifests	Report Comments:		
Embarking	Report Comments.		
niform and Items		Print Default	
ruise Balance	Printer Type:		v
New Cruise Balance		5	
open Balance	Number of Copies:	1	
Debit	Orientation:	Landscape	v
- Credit		201	
×	and the second	SQL	
l - Currency Exchange	Database SQL		
		6	
- Analysis		5048-0	
- Online Credit Card		Selection Formula	
er - General ons	Crystal Selection Formula:		
s	a providence of the states	7	
		•	
Drill			
Courses&Certificates	Formulas:		
General			
mental			
abin Plan			

 Table 2-4
 Setup Functions In Report

Figure	Description
1	Tools function that uploads report templates from a public folder.
2	List of report sets available, including those manually uploaded.
3	Search function that enables you to search for a report.
4	Report detail of the report. For example, Report ID, User Access, Report Group.
5	Default printer configuration.
6	Formula embedded in the Crystal Report template.
7	Selection criterion input required from the user prior to generating a report.



Adding New Report

- **1.** From the **System Setup** option, select **Reports Setup**.
- 2. In the User Customizable Report Setup, Current Report List pane, right-click and select **Add New Report** to enable the fields on the right pane.
- 3. Navigate to the right pane and select Upload New Report (Load Variables From the Report Template) or Upload Report.
- 4. Search for the .RPT file on your local drive if you are uploading a report template.
- 5. In the Report Details section, enter the following information:
 - a. Report ID: Unique ID of customized report.
 - **b. Report File Name:** Crystal Report file name, for example, pabxnationbreak.rpt.
 - c. Report Title: Report name to show in Current Report List.
 - d. Report Access: User Access Right to view/print report.
 - e. **Report Sort:** Sort order of the report within the assigned report group.
 - f. Report Group: Group this report belongs to. Select from the drop-down list.
 - g. Report Comments: Additional comments/Information pertaining to this report.



Default Standa	L L	Direct Printing P		1
	the Report	(Load Variables From t Template)	Export to Crystal	Upload Report
Reports can be Import with the Selection Para option above to autom	ameters into th	ne Customs properties	e. Reports exported by th of the report. When Impo s into the database.	e system, are embed orting them, click the
		Report De	tails	
Report ID:				
Report File Name:				
Report Title:				
Report Access:				
Report Sort:				
Report Group:				
Report Comments:				
		Print Defa	ult	
Printer Type:		Re	ports	
Number of Copies:		1		
Orientation:		La	ndscape	
		50L		
Database SQL				
		Selection Fo	rmula	
Crystal Selection Formu	la:			
Formulas:				

Figure 2-11 Default Standard for Report

- 6. In the Print Default section, select the **Printer Type**, **Number of Copies** and the **Print Orientation**.
- 7. Click Save to add the report to the list.
- 8. Click **OK** at the Save New Report prompt. The newly added report name appears at the bottom of the screen

Removing a Report

- 1. In the User Customizable Report Setup window, expand the **Current Report List** tree by clicking the plus (+) key.
- 2. Right-click the **report name** you wish to remove and then select **Remove Report**.
- 3. Click **Yes** when prompted.

Exporting a Report

- 1. In the User Customizable Report Setup window, expand the **Current Report List** tree.
- 2. Click the Export to Crystal button in the Default Standard tab.
- 3. Select the **location** to save the file and note that the file type is indicated as Crystal Report.

Change Debark/Embark Date

This function allows you to change the Debark or Embark Date when the need arises, for example, if passengers are not allowed to debark due to severe weather conditions.

- 1. From the System Setup option, select Change Debark Date or Change Embark Date.
- 2. Select the date from the **From/To Date** field and check the applicable passenger type and the status.
- 3. Select a **New Date** and check the **Reset Boardcards** check box if you need to issue new boardcard.
- 4. Click OK and then select Yes to proceed or No to abort.

Labels Setup

The system is pre-installed with a range of hard coded labels for use in various functions. You can modify the description of the labels to suit the ship's operation. Consult Oracle Hospitality Cruise Support if you wish to change the description of these labels.



3 Financial Setup

In the Financial Setup function, you can create and manage the Ship's accounting codes, ensuring the daily revenues/expenses are correctly mapped to the codes configured. A greater financial reporting can be achieved through a well thought out system of accounts. It is highly recommended for shore side accounting personnel to play a key role in creating/ developing the accounts and to revisit this setup from time to time. Configuration of these codes is under the responsibility of the System Administrator, Chief Purser, and Accounting Purser.

Department Codes

The Department Codes is where all debit and credit posting codes are stored, and codes entered are mapped to the Back Office Accounting System using the General Ledger (GL) ID. These codes are sub-divided into several codes within a Main Group.




Figure 3-1 Main/Sub-Department Setup

Main Department

The Main Department code is the higher level of grouping of the approved Chart of Account and in this instance, the revenue or cost centers. The Main Department Setup is comprised of two tabs: a Debit and Credit tab. In general, the Debit departments are the revenue centers and outlets, while the Credit department represents the payment methods accepted by the Ship. All codes are entered through **Administration, Financial Setup, Department Codes**.



Adding a Main Department Code

- **1.** From the **Administration, Financial Setup** menu, select the **Department Codes** option.
- 2. Select either a **debit** or a **credit** tab.
- 3. Click the New button located at the bottom of the screen.
- 4. Enter the **code**, **description**, and other required fields approved by your Financial Department and then click **OK** to save.

Field	Description
Code	Department code in numeric character.
Description	Description or name of the code.
Other Description	Alternative name or other description of the code, if any.
Sub-Department Code	Pre-defined Sub-Department code of Automatic Service Charge.
Percentage to distribute	Percentage value of Automatic Service Charge to distribute.
% for Team Server 1	Percentage of Service Charge to distribute by Team.
% for Team Server 2	Percentage of Service Charge to distribute by Team.
% for Pool Distribution	Percentage of Service Charge to distribute from Service Charge Pool.
External ID	Department Location ID.
Credit Limit	Overall Floor Limit Allowed.

Table 3-1 Main Department Code

Deleting a Main Department

- 1. From the Main Department Codes setup, select the **code** and then click the **Delete** button.
- 2. At the confirmation prompt, click **Yes** to proceed.

Note:

Once a code is used and has transactions linked, you are not allowed to delete it. You can hide the code using the **Hide** button.

Sub-Department

You can only add a Sub-Department when the the Main Department code is present. The information required in a debit sub-department code defers from the credit subdepartment code, although the process to create them is similar.



Field Name	Description
Type of Posting	System coded posting type: Posting Department (D) or Tax Department (DX).
Department Code	Department Code in numeric characters only.
Description	Description of the code.
Other Description	Additional description of the code, if any.
Department Grouping	Code use to group certain department codes for reporting purposes.
POS Revenue Center	Revenue Center code defined in POS System, use in Interface mapping.
POS Sales Itemizer no	Sales Itemizer number defined in POS system.
POS Sales Period	Sales Period defined in POS.
POS Revenue C.Desc	Revenue center description from POS System.
D.Code for Gratuities M.	Manual Service Charge Department Code.
D.Code for Gratuities A.	Auto Service Charge Department Code.
D.Code for Taxes	Department code for taxes, use in Interface mapping.
Gratuity Typ	Not in Use.
Gratuity/Service Tax Department	Not in Use.
PBX Call Type	Call charge type from PBX System, use in Interface mapping.
Max. Daily Limit	Maximum Daily Limit allowable for this code.
Service Charge Dept.	Service Charge Department for Casino postings.
Service Charge	Service Charge Value.
Max. Cruise Limit	Maximum Cruise Limit allowable for this code.
Req. Signature During Folio Payout	Define whether signature is required on folio payout.
Guest/Crew Discounts Dept.	Applicable discount department code.
Dept. Security Level	Defined User Security Access Level 1 – 9.
Eligible Department	Check box that determines the department is not eligible for refund.
Origin	General Ledger codes defined in Chart of Accounts.
VAT Tax Class	Classification of VAT Tax.
Casino Department	Determines whether the department code belongs to Casino.
Exclude from Revenue Overview	Revenue to be excluded from Revenue Overview function in Management.

 Table 3-2
 Debit Sub-Department Field Definitions



Field Name	Description
Payment Type	The payment type of this code. For example, Cash, Foreign Currency, Credit Card, Check, Cabin Charge, City Ledger.
Department Code	Department Code in numeric characters only.
Description	Description of the code.
Other Description	Additional description of the code, if any.
Department Grouping	Code used to group certain department codes for reporting purposes.
Credit Card Digits	Acceptable credit card digits associated with the type of credit card.
Credit Card ID	Short code of credit card type.
Credit Card Internal ID	Internal credit card ID preset by the system.
Credit Card Merchant ID	Card Merchant ID.
Foreign Currency Code	ISO Currency codes. Refer to Typ_Cur when the payment type=CF Foreign Currency.
Floor Limit	Maximum limit allowed in guest account for this card type.
Crew Floor Limit	Maximum limit allowed in Crew account for this card type.
Minimum Authorization Value	Minimum amount to obtain from card merchant.
Commission Department	Department code for chargeable commission.
Commission Rate	Percentage of applicable commission or value defined if 'Commission is fix value' is checked.
Daily Limit	Daily Posting limit.
Debit Card No Commission	Commission is exempted if checked.
Commission is fixed value	Applicable commission is value based instead of percentage.
Auto Balance (Interface)	Auto Balance function for cash/credit card posting via interface.
Rewards Card	Denotes Rewards Card if checked.
Gift Card	Denotes Gift card if checked.
POS Tender Type No.	Tender Media Number defined in POS System.
System Account No.	The Account Number defined in System Account.
Incentives Payout Group	Incentive payout group setup from Crew Incentive.
External Department ID	External Department ID for payment from 3rd party system.

 Table 3-3
 Credit Sub-Department Field Definitions



Field Name	Description
External Itemizer ID	External Itemizer ID from third–party system.
Allow Posting to Guest Cabin	Posting allowed by Micros POS System.
Allow Posting to Crew Cabin	Posting allowed by Micros POS System.
Allow Posting to Gift Card	Posting allowed by Micros POS System.
G.Ledger Id.	General Ledger codes in Chart of Accounts.
Eligible Department	If the check box is checked, the department is not eligible for refund.
Dept. Security Level	Defined User Security Access Level 1 – 9.
Req. Signature During Folio Payout	Define whether signature is required on folio payout.
Credit Card Disclaimer Note	Disclaimer note to print on invoice when payment is by credit card.
Department for routing	Payment Type allowed for routing.

Table 3-3	(Cont.) Credit Sub-Department Field Definitions
-----------	---

Adding a Debit Sub-Department

- **1.** From the **Main Department Setup** window, select the **Debit tab** and then the **Department Code**.
- 2. Click New to open the Debit Department Code Setup form.
- **3.** Enter the **code**, **description**, and other required fields approved by your Financial System.
- 4. Click OK to save.

Adding a Credit Sub-Department

- 1. From the Main Department Setup window, select the Credit tab and then the Department Code.
- 2. Click New to open the Payment Setup form.
- **3.** Enter the **code**, **description**, and other required fields approved by your Financial System.
- 4. Click OK to save.

Note:

No posting is allowed when a credit code does not have a floor limit assigned or the value is 0.00. The General, Check Buyer Limit, and Check Credit Limit parameters are used to validate and manage the credit limit during posting.

Deleting Sub-Department Code

1. From the Main Department Setup window, select the **Sub-Department** to delete.



- 2. Click the **Delete** button located at the bottom of the screen.
- 3. At the confirmation prompt, select **Yes** to delete the code.

Note:

It is not possible to delete a code that has a transaction linked to it. Once the code is deleted, is not reversible. If the code is no longer in use and deleting is not possible, use the **Hide/Show** function to disable them.

Currencies

The Currencies functionality enables you to input the currency rate used in the Currency Exchange module. You can also update the exchange rates from the Currency Exchange module. The feature uses the Currency Codes configured in Credit Sub-Department.

Adding Currency Rate

- 1. From the Financial Setup menu, select Currencies.
- 2. In the All Currencies section, right-click and select Add Rate.
- 3. Navigate to the Setup Exchange Rates section and select the currency code from Currency/Check drop-down list.
- 4. Enter the Valid From date, Minimum Denomination (Buy/Sell) and select the Rate Calculation method from the drop-down list.
- 5. Selecting the **Disable From** check box disables the currency from appearing in the Currency Exchange module from the date specified. Disabled currency is marked with an asterisk *.
- 6. Enter the **Available Notes**, if any. If you specify Available Notes, the system uses the Available Notes for calculation and ignore the Minimum Denomination setup.
- 7. Enter the Exchange Rates and Commission % or Min. Commission, then click OK to save.

Removing Currency Rate

You can remove currency rates by right-clicking the currency rate and selecting **Remove Rate**.

Merchant Details

For every credit card provider the Sship deals with, you must create a Merchant credential to facilitate the credit card authorization and handling. Such information is provided by the third-party service provider.

- 1. From the Financial Setup menu, select Credit Card Merchant Setup.
- 2. On the left pane of the setup screen, right-click and select Add New.
- 3. Select the Credit Card Type and Currency from the drop-down list.
- 4. Enter the Terminal ID, Bank ID, Decimal, IP Port, Merchant Login ID and Merchant Password.



- 5. Click **OK** to save.
- 6. Repeat the above steps for other credit card types accepted by the merchant.

Pre-Selection Groups

The Pre-Selection Groups allow you to categorize numerous department codes into a group, for use in Routing and Discount assignments.

- 1. From the Financial Setup menu, select the Department Groups Setup.
- 2. On the left pane of the setup screen, right-click and select Add Department Group.
- 3. In the **Department Groups** section, enter the **Description** of the group and the **Department Codes**.
- 4. Click OK to save.

Stateroom Upgrade Setup

In the Stateroom Upgrade Setup functionality, you can create a price table and manage the price differences to charge when a performing a cabin upgrade.

- 1. From the Financial Setup menu, select Stateroom Upgrade Setup.
- 2. In the Price Table of the Upgrades screen, click New.
- 3. In the Edit Upgrade Prices window, select a category from the Category Identifies.

Note:

The Cabin Categories only appear if they are set up in Stateroom setup. Sorting the category pricing from higher to lower is recommended.

- 4. Enter the Sorting, Price and Maximum Person allowed.
- 5. Click OK to save.

Discount Templates

The Discount Templates functionality enable you set up various discount type templates, for use in Discount, Routing and Package Handling.

- 1. From the **Financial Setup** menu, select **Discount Templates**.
- 2. On the left pane of the setup screen, right-click and select Add New.
- 3. Navigate to the Fidelio Department section and then click **Add**. This launches the Discounts window.
- 4. In the Discounts window, enter the **Percentage, number of count to apply** in the How Much section. When the Percentage check box is deselected, the discount becomes a value based discount. If the **Apply Count** field is blank, the discount is unlimited.
- 5. Select the applicable Department Code and then click OK to apply.



Quick Posting Template

This Quick Posting Template enables you to create a criteria filter to be used in the Quick Posting function of the Cashier Function, for example, a posting to a specific nationality.

- 1. From the Financial Setup menu, select **Quick Posting Templates**.
- 2. On the left panel of the setup screen, right-click and select Add New.
- 3. Enter the **short code** and **description** in the Description field and then insert the criteria in the **Comments** field.
- 4. Click OK to save.

Import Credit Card Bin

You can import a complete set of eligible Bank Identification Numbers (BIN) provided by the credit card provider by overriding the previously loaded BIN information during the reload process.

- 1. From the Financial Setup menu, select Import Credit Card Bin file.
- 2. At the bottom of the screen, select the BIN file to import.
- **3.** By default, all the check boxes are selected. Click **Import** to save the information into the BIN table.
- 4. Click Close to exit.

Disallow Manual Posting Applications

Use this function to prevent users from manually posting a transaction through the listed application when the posting is set to *No* in the guest account.

- **1.** From the Financial Setup menu, select **Disallow Manual Posting Applications**.
- 2. Right-click on the left pane and select Add New.
- 3. Enter a short code and the application name in the Description field.
- 4. Click Apply to save.

Department Grouping

This function allow you to categorize a department group for use as financial classification and in report grouping.

- 1. From the Financial Setup menu, select Department Grouping.
- 2. Right-click the left pane and select Add New.
- 3. Enter a **short code** and **description** in the Description Field and then click **OK** to save.

VAT Handling

Before you use VAT Handling, these VAT components must be in place.

• VAT Tax Class.



• VAT Tax Rate.

VAT Tax Class

The VAT Tax Class is a tax group classification, for example, a Regular Tax, Reduced Tax, and others.

- 1. From the Financial Setup menu, select VAT Tax Class.
- 2. On the left pane of the setup screen, right-click and select Add New.
- 3. Enter the **short code** and the **application name** in the Description Field and click **Apply** to save.

VAT Tax Rate

The VAT Tax Rate code is used to define the various tax rates applicable to each country or class, and the tax posting code.

VAT Tax Rate	Per Country Setup
Add New Delete Save Undo Copy	Paste Refresh Exit
Expand All	
 AO Angola AU Australia BJ Benin BM Bermuda BO Bolivia BG Bulgaria MY Malaysia FM Micronesia, Federated States of US United States T_VAT T_VAT VAT1 Tax 1 VAT2 Tax 2 	Country US United States
	Apply

Figure 3-2 VAT Tax Rate Per Country Setup

1. From the Financial Setup menu, select VAT Tax Rate.



- 2. Click Add New at the ribbon bar and then select the Country code from the dropdown list.
- 3. Click Save.
- 4. Expand the Country container and select the Tax Class.
- 5. Insert the **tax rate** in the VAT Tax Rate field and select the **Tax Department** code from the drop-down list.
- 6. Click **Save** to save the changes.

Activating a Tax Rate

This function enable you to apply the correct Tax Rate based on the cruise location and stores the information in **Parameter**, **"General"**, **"Current VAT Tax Country"**. A system restart is required on all posting modules for changes to take effect.

- 1. From the Financial Setup menu, select Activate Tax Rate.
- 2. Select the country tax to activate from the drop-down list and then click OK.
- 3. At the confirmation prompt, select Yes to activate.

VAT Tax Reminder

A reminder can be added to remind you when to activate the tax country on a specified date.

\$		N	AT Tax Sch	nedule Rer	ninder		
	New De	lete Save	Undo	Exit	New	Reco	oro
AT	Tax Sched	lule					
	VAT Tax	Activation Date	e/Time	4	Active Tax Count	σγ	
	22/04/20	16 11:41:52	Australi	a			
*			~				
ſ	8		Selec	t Date		×	
	21	April	2016			•	
	11	46:30)	▲ 0		ncel	

Figure 3-3 VAT Tax Reminder

- 1. From the Financial Setup menu, select VAT Tax Reminder.
- 2. Click Add New at the ribbon bar, and then select the Date and Time from the drop-down list.
- 3. From Active Tax Country, select the Country in which the tax is to be activated.
- 4. Click Save to save and exit.



4 Itinerary Setup

The Itinerary Setup enables you to plan the daily activities available for each voyage by Location, Events, Packages or through an Agent. The information entered here are appears as an information board in the Management, Itinerary Overview, and are entered through **Administration, Itinerary Setup**.

Adding an Activity

<u>6</u>	Activities Setup
All Activities	Setup Activity
	Event Details Type/Title: Active Programm Snorkelling View
29/01/2015 Vietnam/Hong Kong/Macau 31/01/2015 A 31/01/2015 Embarkation Day 15:00 High Tea 16:00 Indoor Games 16:00 Indoor Games 16:30 Pottery Class 16:30 Pottery Class 18:00 Pre-dinner Cocktail 19:30 Dinner 01/02/2015 Island Tour at Danang 01/02/2015 Island Tour at Danang	Description Language: EN English Title: Snorkelling Description: Snorkelling Time and Place Start DateTime: 01/02/2015 09:00 Duration Time: 60 minutes Deadline DateTime: Setup Time: 10 minutes Dates Accuracy: All Accurate Clean-up Time: 10 minutes
Snorkelling & Fishing Snorkelling & Fis	Location: Castaway Beach Edit Comments:
** Add Package/Price X Remove Package/Price	Reservations
 ★ Add Team/Time Frame ★ Remove Team/Time Frame 	Waiting List: No waiting list Booking Status: Enabled Booking Options: Booking Required Min/Max Available: 5 20
	Pricing
< >>	OK Cancel Apply

Figure 4-1 Activities Setup

Table 4-1 Field Description of Activities Setup

Field Name	Description
Type/Title	The type of activity and title.
Language	The language offered in this activity.
Title	Title of the activity.
Description	Brief description of the activity.
Start DateTime	Start date and time of the activity.



Field Name	Description
Duration Time	Duration of the activity.
Deadline DateTime	Booking deadline date/time.
Setup Time	Setup time required in minutes.
Dates Accuracy	Activity dates accuracy (1-All Accurate, 2-All Approximate, 3-Starting Approx., 4-Duration Approx.).
Clean-up Time	Clean up time in minutes
Location	Location of the activity
Comments	Comments for the activity
Waiting List	Waiting List is allowed/disallowed.
Booking Status	Activity booking status (Enable/Disable).
Booking Options	Activity booking options — Booking is required or not.
Min/Max Available	Minimum or Maximum number of bookings allowed.
Agent/Vendor	Agent/Vendor Name.
Adult Cost Price	Agent/Vendor Cost Price.
Child Cost Price	Agent/Vendor Cost Price.
Department	Agent/Vendor Posting Department.

Table 4-1 (Cont.) Field Description of Activities Setup

- **1.** From the **Itinerary Setup** menu, select **Activities**.
- 2. On the left pane, right-click on the selected **Cruise Day**.
- 3. Select Add Activity from option menu.
- 4. In the Setup Activity section, update all of the activities details.
- 5. Click the **More Details** button to insert the Meeting Date/Time, clothing requirements, and other information, and click **OK** to return to previous screen.
- 6. In the Reservation section, select the appropriate **booking options** from the dropdown list.
- 7. Enter the **pricing** and select the **Agent/Vendor** providing the service.
- 8. Click **OK** to save.

Copying an Activity Setup

An existing activity can be copied into the future cruise by day or by activity instead of re-creating every single activity.

- 1. From the Activites setup window, right-click on the **Cruise Day** and select **Copy Day/Activity**.
- 2. In the Duplicate whole day window, enter the date to copy to, and click Add.
- 3. Click **OK** to copy the activities.



Note:

To copy a single activity, select an Activity instead of by Cruise Day.

Add Package Price

The Add Package/Price is an additional information field for the activity is not meant for posting.

Adding Team/Time Frame

You can add the team member required to handle the activities by indicating the time and number of the member required.

- 1. In the Activities Setup window, right-click on the activities details and select Add Team/ Time Frame.
- 2. In the Team/Time Frame section, enter the number of the **team member** and select the time to reserve from and duration.
- 3. Click OK to save.

Removing an Activity

Activities that are no longer required or haves been added as duplicate can be easily removed by right-clicking on the **activity** and selecting **Remove Activity**. If the activity has a **Team/Time Frame** or **Packages/Price information**, you must remove these before removing the activity.



5 Events

The section describes the setup of an activity category, its location, and requirements.

W Even	ts Setup 📧
All Events Setup Event Details Number: Control Golf Language: Snorkelling Dining Description: High Tea Type:	EN English Dining Dining Main Dining Room Edit Dining Reservation (no ticket) 21 to 999 Age Restriction: Yes All Group: All Group:
	OK Cancel Apply

Figure 5-1 Event Setup Screen

 Table 5-1
 Event Setup Field Definition

Field Name	Description
Number	Order Number of the event.
Language	Language used in the event.
Title	Event Title.
Description	Short description of the event.
Location	Location of the event.
Туре	Type of event.
Ticket	Determine if the event is ticket based or not.
Comments	Additional comments of the event.
Age Range	Age Range, if any.
Age Restriction	Age Restriction, if any.



Field Name	Description
Family Status	Family Status of attendees, if any.
Marital Status	Marital Status, if any.
Gender	Target gender, if any.
Group	Group name for special event.

Table 5-1 (Cont.) Event Setup Field Definition

Adding an Event

- 1. From the Itinerary Setup drop-down menu, select Events.
- 2. In the All Events section, right-click and select Add Event Type.
- 3. Enter a short code and description in the **Description** field and then click **OK**.
- 4. Select the Event Type, then right-click and select Add Event.
- 5. In the Details section, enter the event number, title, and description of the event.
- 6. Select a Location, Type, and Ticket from the drop-down list.
- 7. In the **Demographics** section, enter the **Age Range** and select the **Family Status, Marital Status, Gender**, and **Age Restriction** from the drop-down list.
- 8. Click **OK** to save the entry.

Setting Up Event Location

The Location is used to describe the location where event/activity is held.

- 1. From the Itinerary Setup menu, select Locations.
- 2. In the All Locations section, right-click and select All Location.
- In the Setup Location Section, enter a code and description in the Title field, select the Deck from the drop-down list and attach a picture, if any.
- 4. Select the **Availability Status** and appropriate **prompt** to use for an overbooked location and click **OK** to save.
- 5. Select the Location, then right-click, and select Add Table/Seat.
- 6. In the Details section, enter the even number, title, and description.
- 7. Select a Location, Type and Ticket from the drop-down list.
- In the Demographics section, enter the Age Range and select the Family Status, Marital Status, Gender and Age Restriction from the down-down list.

Adding Event Table/Seat

- 1. In the Location Setup window, right-click on the location.
- 2. Click Add Table/Seats.
- **3.** Fill in all the fields.
- 4. Click OK to save.



Adding an Event Exception

- **1.** At the Location Setup window, right-click and select **Add Exception**.
- 2. Fill in the information and select the **Reason** from the drop-down list.
- 3. Click OK to save.
- 4. Locations that have an exception are marked with an Exclamation mark.



6 Vendors

The Vendors/Agents Setup is used for storing contact information of vendors/agents handling the events.

•	Agents/Vendors Setup	
All Agents	Agent Details Comments Agent Setup Salutation Salutation MR First_Name Image: Company	
	Street Zp/City State/Country Phone/Fax E-Mail Comments Handle ground travel and local tours, operating with 10no, 30 seater buses. Status V Enabled	
	Currency: (not applicable)	
	OK Cancel	Apply

Figure 6-1 Agents/Vendors Setup

Setting Up a Vendor

- 1. From the Agents/Vendors Setup window, right-click and select Add Agent.
- 2. Enter the **Agents details** and then navigate to the **Comments** tab to add the additional comments or document image.
- 3. In the Comments tab, click **Add Comment** to enter a new comment and the relevant details.
- 4. Navigate to the Document tab to upload, scan or export an image file.
- 5. Click Save.
- 6. Click **OK** to save the Agent details.



7 Safety Setup

The Safety Setup contains all the codes required in Standard Safety Drill and Advance Safety Drill modes. The setup varies depending on the mode defined in **Parameter group, Safety, Advance Safety Drill** (0=Standard Safety Drill / 1 = Advance Safety Drill).

Safety Setup Type

In the following figures, you will see the list of codes available to Standard Safety Drill and Advanced Safety Drill mode.

Below are the function codes available to Standard Safety Drill mode where **Parameter**, **Safety**, **Advance Safety Drill** are set to zero.



8		
Administration Reports Security	About	Exit
System Setup	•	1
Financial Setup	+	
Itinerary Setup	+	Standard Safety Drill Setup Codes
Crew Setup	•	Standard Safety Drin Setup Codes
Safety Setup	×	Muster Station
Stateroom Setup	×	Life Boat
System Codes	•	Gangway Locations
Package Plans	•	Safety Department
Maintenance Setup	•	Safety Group
Gift Card Setup	•	Safety Position
POS Discount	•	Safety Role
Security Display Setup		Safety Function
Manual Authorization		Safety Drill Type
Visa Types Setup		Drill Location
Internet Rates Setup		Drill Instructorship
User Definable Field Setup		Drill Definition
Multimedia File Maintenance		
Board Card Printing Template		Course Type
Security Alert Setup		Courses & Certificates
Beeper Setup		Accredited Training Centres
Micros Item Posting Restriction		
Signature Device Configurator		
Upload Photos		
Export Photos		
Export Documents		

Figure 7-1 Standard Safety Drill Setup Codes

Below are the function codes available to Advanced Safety Drill mode where **Parameter, Safety, Advance Safety Drill** are set to one.

8				
Administration System Setu Financial Se Itinerary Setu Crew Setup Safety Setu	etup tup	Security	About	Exit Advance Safety Drill Setup Codes Deck
Stateroom System Coo Package Pla Maintenand Gift Card Se POS Discou Security Dis Manual Au Visa Types Internet Rat User Defina Multimedia	des ans ce Setup int splay Setup thorization Setup tes Setup ible Field S	etup		Fire Zone Stair Well Muster Station Life Boat Gangway Locations Safety Department Safety Group Safety Group Safety Position Safety Role Safety Function Safety Reporting List Group
Board Card Security Ale Beeper Setu Micros Item Signature D Upload Pho Export Phot	ert Setup up n Posting F Device Con	Restriction		Safety Drill Type Drill Definition Drill Template Setup Absence Reason Excuse Request Reason Excuse Unapprove Reason Interview Comment Courses & Certificates Proficiency Level Accredited Training Centres

Figure 7-2 Advance Safety Drill Setup Codes

Table 7-1	Safety Setup Configuration Codes	
-----------	----------------------------------	--

Function Name	Definition
Deck Setup	Define the deck location in Muster Station Setup. Available in Advance Safety Drill.
Fire Zone Setup	Define the Fire Zone for the drill in Muster Station Setup. Available in Advance Safety Drill.



Function Name	Definition
Stair Well Setup	Define the stairwell location in Muster Station Setup. Available in Advance Safety Drill.
Muster Station Setup (definable label - TYP_LBL = SFTMST)	Define the assembly location.
Lifeboat Setup (definable label - TYP_LBL = SFTBOT)	Define the lifeboat or life raft capacity.
Gangway Locations	Define the location of gangway.
Safety Department (definable label - TYP_LBL = SFTDIV)	Define the department responsible for safety for each location.
Safety Group (definable label - TYP_LBL = SFTSGP)	Define the responsibilities and task of each safety group.
Safety Position (definable label - TYP_LBL = SFTCRW)	Define the position of the crew.
Safety Role (definable label - TYP_CLBL = SFTROL)	Define the role of the safety crew.
Safety Function (definable label – TYP_LBL = SFTFCT)	Define the role of crew in command of Survival Craft.
Safety Drill Type	Define the type of drills.
Drill Location	Define the location of the schedule drill. Available in Standard Safety Drill only.
Drill Instructorship	Define the instructor responsible for the scheduled drill. Available in Standard Safety Drill only.
Drill Definition	Definition of drills.
Drill Template Setup	Template for each drill type.
Absence Reason	Absent reason from attending safety drill. Available in Advance Safety Drill only.
Excuse Request Reason	Reason to be excused from attending safety drill. Available in Advance Safety Drill only.
Excuse Unapproved Reason	Reason for not approving the excuse request. Available in Advance Safety Drill only.
Interview Comment	A comment field used during interview as a predefined comment, or you can input using free text. Available in Advance Safety Drill only.
Course & Certificates	Type of Courses and Certification required for each drill type.
Proficiency Level	Proficiency level offered in Courses and Certification.
Accredited Training Centers	Reputable Safety training centers recognized by the ship.

Table 7-1	(Cont.) Safety Setup Configuration Codes
	(Cond) Carely Cetap Conngaration Codes



Configuring Safety Codes in Standard Drill

The majority of the setup windows are the same in Standard Safety Drill mode and below are the steps to configure the new codes for Gangway Locations, Safety Department, Safety Group, Safety Position, Safety Role, Safety Function, Safety Drill Type, Drill Location, Drill Instructorship, Course Type and Accredited Training Centers.

- **1.** From the Safety Setup menu, select the **code** to configure.
- 2. Right-click the blank space on the left and select Add New.
- 3. Enter a short code and the name, and further describe the code in the **Comments** field.
- 4. The Enabled field is selected by default. Deselect the box to disable the code.
- 5. Click Apply to save the code.
- 6. Right-click the **code** and select **Remove** to delete the code from the system.

Setting Up Muster Station

A Muster Station is a required field in the Safety Drill setup and must be set up before you configure any Safety Drill. The layout of the configuration screen differs, depending on the setup mode in the **Parameter group, Safety, Advance Safety Drill**.

- 1. From the Safety Setup menu, select Muster Station.
- 2. Right-click on the blank space and select Add Muster Station.
- 3. Enter a short code, field name, and the Capacity allowed.
- Select the Lifeboat Type from the drop-down list and insert an Emergency Phone No, if any.
- 5. Right-click the **code** and select **Copy Muster Station** to copy the information and add more codes.
- 6. In the Duplicate Muster Station window, enter the **Muster Station** and **description**.
- 7. Click **Apply** to save.

👰	Muster Station @	
All Muster Station @ MusterStation CP MusterStation A Musterstation B Musterstation C Musterstation D Musterstation E Musterstation F Musterstation G	Muster Station @ Setup Muster Station @ Details Description: A Musterstation A Capacity: 96 Person(s) Lifeboat Type: LB LifeBoat@1 Emergency Phone No: Last Drill:	
Musterstation H	OK Cancel Apply	

Figure 7-3 Muster Station Setup



Setting Up Lifeboat/Liferaft

A lifeboat/liferaft has a maximum capacity and does require a number of qualified crew to handle them in the event of an emergency.

2	Lifeboat / Liferaft Setu	р		×
Overview Setup All Lifeboat / Liferaft	Details Description: Type: Min Crew with CPSC Required: Max Capacity: Operators/Crew Assigned: Max Certified Capacity: Muster Station Ralf Crane Launch Sequence Remarks:	01 LB LifeBoat 2 313 14 0 0 Lifeboat Sta	Person(s) Person(s) Person(s) Person(s)	

Figure 7-4 Lifeboat/Liferaft Setup

Table 7-2 Lifeboat/Liferaft Setup Field Definition

Field Name	Description
Description	Short code and description of the lifeboat/ liferaft.
Туре	The type of lifeboat/liferaft. These codes are predefined and hard coded.
Min. Crew with CPSC Required	Minimum number of CPSC certified crew on lifeboat/liferaft.
Max Capacity	Maximum capacity allowed per lifeboat/ liferaft.
Operators/Crew Assigned	Number of crew assigned to this lifeboat/ raft.
Max Certified Capacity	Maximum certified capacity of the lifeboat/ raft.
Muster Station Raft Crane	Raft crane the lifeboat is assigned to in Muster Station.
Launch Sequence	Launch sequence of the lifeboat.
Remarks	Additional remarks of the lifeboat.

To set up the codes, repeat the steps in Setting Up Muster Station. You can also duplicate an existing Lifeboat code using the same steps.



Setting Up Drill Definition

The Drill Definition code setup is where you define the type of drills and attendance requirement and identify drills that are Course and Certificate related.

4	2					Drill Defini	tion Setup			- • •	3
	Ac	dd New	Modify Delet	e 🗋 D	uplicate		Save 🕜 Exit				
Ē	Drill Type Filt	er Safety Drill	Life Boat								
	Drill Definit								Required Operational Positions		
	Status	Code	Description	Туре	Once Every	Unit of Frequency	Required x Days After Embark	ation	Position	Comment	-
	Inactive	DR006	Drill - FIRE	SDR003 Safety Drill -					2		
	Active	DR007	Drill	SDR003 Safety Drill -	1	Month			2		
									2		4
Γ.	Location –			Instructor					2	<u> </u>	- 1
	Loc	cation	Comment		Name		Function				
U		~		4			×		- Assigned Manning Number @		
li									Position	Comment	5
									×		
ſ,	Schedule S										
	Drill	Date	Scheduled Count Excuse Pending Co	unt Excused Co	unt		Attended Count				
										~	

Figure 7-5 Drill Definition Setup

- 1. From the Safety Setup menu, select the **Drill Definition**.
- 2. To add a new drill, click Add New.
- 3. Select the Status from the drop-down list. and enter the Drill Code and description.
- 4. In the Drill Definition section, select the Drill Type from the drop-down list.
- 5. Enter the Unit of Frequency and Required x Days after embarkation.
- 6. Click Save to save the record.
- 7. Select the drill and click Modify.
- 8. Enter the Location, Instructor, Required Operational Positions and Assigned Manning Number.
- 9. At the Location and Instructor section, right-click and select Add New.
- **10.** Select the location from the drop-down list and enter the comment or function, if any.
- 11. At the Required Operational Positions section, right-click and select Add New.
- 12. Add a position individually or select Add All to select multiple positions or all.
- **13.** In the Assigned Manning Number section, repeat step 7 and select **Assigned Manning number**.

Setting Up Course and Certificates

The Courses and Certificates code allow you to define the type Courses and Certifications required for each drill type, and identify the certificates expiry during an Emergency # (E Number) change.



🗊 Admin	istration Reports Security About Ex	it					- 8 ×
Type: Related	All	•	Details Code: CMS Code: Name: Related to:	CPSC CPSC Certificates Safety	Proficiency Survival Craft		
Code	Description	Type ^	Instructor: Training Centre:				
CPSC	Certificates Proficiency Survival Craft	Certificate	Renewal Days: Grace Period:	All 0 Days 0 Days			
CRISIS	Crisis Managment Certificate	Course	Expire Upon Debarkation:	No Active			
CROWD	Crowd Managment Certificate	Course	Status: Priority:	No O			
ENV	Enviromental Training	Course	Minimum Required per Vessel: Comment:	Certificates	Proficiency Survival Craft		
F.AID	First Aid - Medical certificate	Medical Certi	Comment:				
1							
•		•	D	elete	Edit	New	Exit

Figure 7-6 Course and Certificates Setup Window

- 1. Select the Course and Certificates from the Safety Setup menu.
- 2. In the Course and Certificate window, click New.
- 3. In the Code and Name section, enter the **code**and the **name** of the course.
- 4. Select the Type and Related to from the drop-down list.
- 5. Enter the course description, instructor's name and the training center location.
- 6. Select the type of expiration section.
- 7. Enter the Minimum Required Per Vessel.
- 8. The Active check box is checked by default. Un-check if you wish to disable the course.
- 9. Check the **Priority** check box if the course is a priority.
- 10. Click OK to save the code.

Advance Safety Drill Mode

The Advance Safety Drill mode has more configuration codes in comparison to the Standard Safety Drill mode. Below are the additional codes.

- Deck Setup
- Fire Zone Setup
- Stair Well Setup
- Absence Reason
- Excuse Request Reason
- Excuse Unapprove Reason
- Interview Comment

These functions is enabled with Safety, Advance Safety Drill parameter set to one.

The majority of the screen layout and configuration of the codes are the same as Standard Safety Drill mode, with the exception of the below listed codes, which have



additional fields or functions. The steps to create these codes are described in the following topic.

- Muster Station
- Lifeboat/Liferft
- Safety Function
- Drill Type
- Drill Definition
- Drill Template Setup
- Courses & Certificates

See chapter Configuring Safety Codes in Standard Safety Drill on how to set up new Safety Drill codes

Setting Up Muster Station In Advance Drill Mode

The Muster Station is a required field in the Safety Drill setup, which you must set up before you configure any Safety Drill. The layout of the configuration screen differs from the Standard Safety Drill mode.

- 1. From the Safety Setup menu, select **Muster Station**.
- 2. Right-click on the blank space and select Add Muster Station.
- 3. Enter a short code, field name and the **Capacity** allowed.
- 4. Select the Lifeboat Type from the drop-down list
- 5. In the Location section, check the correct **Deck**, **Fire Zone**, **Stair Well** and **Side** of the ship for each muster station.
- 6. Right-click the **code** and select **Copy Muster Station** to copy the information and add more codes.
- 7. In the Duplicate Muster Station window, enter the **Muster Station** and **description**.
- 8. Click **Apply** to save.



<u>\$</u>		Muster	Station 🗾
All Muster Station		- Setup Muster S	tation
		Details	
	_	Description:	A Assembly Station A
Assembly Station A	^	Station Type:	Emergency And Muster Stati
Assembly Station A1			
Assembly Station A1 & A2		Capacity:	0 Person(s)
Assembly Station A2			
Assembly Station A3		Lifeboat Type:	(undefined)
Assembly Station A3 & A4			
Assembly Station A4		Last Drill:	
Assembly Station B			
Assembly Station B1		- Location	
Assembly Station B1 & B2			
Assembly Station B2		Deck:	Fire Zone:
Assembly Station B3		15 - 15	A 0 - 0
Assembly Station B3 & B4		16 - 16	1 - 1
Assembly Station B4		17 - 17	2 - 2
Assembly Station C		18 - 18	3 - 3
🌠 Assembly Station C1		2 - 2	4 - 4
Assembly Station C1 & C2		3 - 3	5 - 5
Assembly Station C2		₹ 4 - 4	6 - 6
Assembly Station C3		✓ 5 - 5	V 7-7
Assembly Station C3 & C4		Stair Well:	Side:
Assembly Station C4			
Assembly Station D		(undefined)	▼ MID - Middle Section ∧
🥵 Assembly Station D1			PSIDE - Port Side
Assembly Station D1 & D2			S-S
Assembly Station D2			
Assembly Station D3 & D4	~		OK Canada Laterty
<	>		OK Cancel Apply

Figure 7-7 Muster Station Setup

Setting Up Lifeboat/Liferaft in Advance Drill Mode

You can define the drills types required based on the rules set forth, and this rule apply to the Training Drills set up that haves the **Apply Training Rule** selected.

- 1. From the Safety Setup menu, select **Safety Drill Type**.
- 2. Right-click in the blank space and select Add Drill Type.
- 3. Enter the short code and description.
- 4. Check the **Apply Drill Rule** check box to enable the fields in Drill Rule.
- Select the drills required from the drop-down list, enter the number of days after embark, the number of Emergency Attendance (ES) and Muster Attendance (MS) per calendar month.
- 6. Select the Apply Training Rule check box if the rule applies to Training Drills.
- 7. Click Apply to save.

Setting Up Safety Function in Advance Drill Mode

The role of Crew in Command of the Survival Craft is setup here and is required in the Muster List and Drill Template Setup. The layout of the configuration window differs from Standard Safety Drill mode.

- 1. From the Safety Setup menu, select the Safety Function.
- 2. Right-click in the blank space and select Add.



- 3. Enter a short code, description and comments, if any.
- 4. Select the Commander/2nd Commander check box if needed.
- 5. Click **Apply** to save the code.

Setting Up Drill Type

The Safety drill type defines the type of drills required based on the rules set forth, and the rules is applicable to Training Drills if the **Apply Training Rule** is checked.

Figure 7-8 Drill Type Setup

S	Drill Type
All Drill Type	Setup Drill Type Description: BRAVO1 FIRE DRILL ✓ Enabled ✓ Apply Drill Rule Crewmembers must either attend first 2 • drill(s) after embark, or drills that are within first 5 • day(s) after embark, whichever that yields the most drills. Thereafter, crewmembers must attend to 1 • ES and 1 • MS per calendar month during drill(s) and must not be absent for 2 •
HELO - HELICOPTER EVACUATION I LEFILL - LIFEBOAT LOADING LRAFT - LIFERAFT LAUNCHING DRI MASS - MASS CASUALTY INCIDENT MES - MARINE EVACUATION SYSTE OSCAR - MAN OVERBOARD DRILL PAX - GUEST MUSTER DRILL	drill(s) in a row. If there is a training within 2 day(s) after embark, it is compulsory that crewmembers attend. OK Cancel Apply

- 1. From the Safety Setup, select the Safety Drill Type.
- 2. Right-click the All Drill Type section and select Add Drill Type.
- 3. Enter a code and description in the Description field.
- 4. Check the **Apply Drill Rule** to enable input of the rule.
- 5. Update all the fields in the Apply Drill Rule.
- 6. Check Apply Training Rule if the rule applies to Training.
- 7. Click **Apply** to save.

Setting Up Drill Definition in Advance Drill Mode

The Drill Definition code defines the type of drills, attendance requirements and identify whether drills are Course and Certificate related.





Status	Code	Description	Type	Attendance Requirement	Course And Certificate
ctive 💌	003	Fire Dril	BRAVO Bravo - Bravo - Bravo Drill		
Active	005	Confine Space Rescue Drill	BRAVO Bravo - Bravo - Bravo Drill	Emergency Station	
Active	006	Damage Control Drill	BRAVO Bravo - Bravo - Bravo Drill	Emergency Station	
Active	007	Oil Spill Drill	BRAVO Bravo - Bravo - Bravo Dril	Emergency Station	
Active	008	Chemical Spill Drill	BRAVO Bravo - Bravo - Bravo Drill	Emergency Station	
Active	014	Rescue from Confined Space Drill	BRAVO Bravo - Bravo - Bravo Drill	Emergency Station	

- **1.** From the Safety Setup menu, select the **Drill Definition**.
- 2. Click Add New to add a new drill.
- **3.** At the definition grid, update the following.
 - a. Status
 - b. Drill Code and Description
 - c. Type
 - d. Attendance Requirement
 - e. Course and Certificate
- 4. Click Save.

Setting Up Drill Template in Advance Drill Mode

A drill template is setup to assist you in generating a crew list under Proposed Crew section using the criteria defined when creating a drill.



\$	Drill Ten	nplate Setup	x
All Templates	Setup Drill Template		
ALPHA - ALPHA - ALPHA DRILL BRAVO - BRAVO - BRAVO DRILL General CHO - ECHO DRILL General Drill - CHARLIE - CHARLIE DRI General Drill - Port Boats Down General Muster Drill GosCAR - OSCAR - OSCAR DRILL K Add Template	Description: Template Category: Safety Department Safety Position Safety Group Safety Function	ALPHA ALPHA - ALPHA DRILL Rejection Template • 10 DECK • 1 MASTER • 1 Operational Comma • 003 As Circumstance I • Craft Type Craft Side	
Copy Template	Life Boat Safety Role	Z5 Z5 V (undefined) (undefined) VCO Overall Comma V	1
× Remove Template	Emergency Station:	Deck MFZ BRDSAF-Bridge/Safet Deck MFZ Stair Side Undefined) Deck MFZ	_
	Muster Station	Z5 -Z5 v (undefined) v (undefined) Stair Side (undefined) v (undefined) v	
	Safety Requirement:	 ✓ ALPHA - Alpha ✓ BRAVO - Bravo ✓ CHARLI - Charlie □ DELTA - Delta □ ECHO - Echo □ OSCAR - Oscar □ PAX - Pax 	
< >>		OK Cancel Reset Apply	

Figure 7-10 Drill Template Setup

- 1. Select **Drill Template** from the Safety Setup menu.
- 2. Right-click the blank space and select Add Template.
- **3.** In the Details section, enter a short code and description, and then select the applicable code in all the fields.
- 4. Click Apply to save the template.
- 5. Click **OK** to exit.
- 6. Click **Reset** to clear the selected information from the screen.

Setting Up Course and Certificates in Advance Drill Mode

The Courses and Certificates code allow you to define the type of courses and certifications required for each drill type and identify the certificates expiry during on Emergency # (E Number) change.



			Setup Sa	ety Courses & Certificates		
Type: Related to	Courses D: All		•	Details Code: CMS Code: Name: Related to: Instructor:	00A CERTIFICATE A CERTIFICATE A Safety	
Code	Description	Type	Related To ^	Training Centre: Proficiency Level:		
00A	CERTIFICATE A	Course	Safety	Renewal Days:	All 365 Days	
008	Certificate B	Course	Safety	Grace Period: Expire Upon Debarkation:	0 Days No	
00C	Certificate C	Course	Safety	Status: Priority:	Active No	
00D	Certificate D	Course	Safety	Re-qualifying Course: Minimum Required per Vessel:	No 0	
10COMM	COMMUNICATION COUNTS 2010	Course	Safety	Expire On E Number Change: Comment:	No	
10CULD	CULTURAL DIVERSITY 2010	Course	Safety	Master Cert:	HBST HOTEL BASIC SAFETY TRNG STCW	
10FAID	FIRST AID	Course	Safety			
10WPS	CREW WORK PLACE SAFETY 2010	Course	Safety			
10ZTOL	ZERO TOLERANCE 2010	Course	Safety			
•			•	Delete	Edit New	Exit

Figure 7-11 Course and Certificate Setup Advance Drill Mode

Figure 7-12 Edit Course/Certificate Window

4	Edit Course/Cert	ificate ×
Code & Name Code CMS Code Name Type Related to Master Cert	FIRST AID Course	Expiration Valid for specified number of days Days Valid: 1826 Grace Period (Days): Valid until crew Debark Expire On E # Change: No No Others
Description — Description Instructor Training Centre	Basic First Aid Course	Minimum Required Per Vessel: 0 Proficiency (undefined) Level: Re-qualifying Course
Active Priority	,	OK Cancel

- 1. Select the **Course and Certificates** from the Safety Setup menu.
- 2. In the Course and Certificate window, click New.
- 3. In the Code and Name section, enter the **code** and the **name** of the course.
- 4. Select the Type and Related to and Master Cert from the drop-down list.
- 5. In the Description section, enter the **course description, instructor's name** and the **training center** location.
- 6. In the Expiration section, Select the type of expiration.
- 7. Enter the Minimum Required Per Vessel, Proficiency and check the Requalifying Course, if required.



- 8. The Active check box is selected by default. Deselect if you wish to disable the course.
- 9. Select the **Priority** check box if the course is a priority.
- **10.** Click **OK** to save the code.



8 Stateroom Setup

The Stateroom Setup is a function used to define both the passenger and crew cabins. Before you begin coding the cabin, you must have the following:

- Cabin features codes
- Exact location of the cabin in Safety Plan
- Housekeeping sections

Cabin		Location	^	Cabin Description			Show Only			-
1012	Penthouse Grand Suite Cat.09	Penthouse Deck		Cabin No.: No. of Berth:	10000 1	Passenger	Decks	All	-	Edi
1013	Penthouse Grand Suite Cat.09	Penthouse Deck	-	Berth Setup: Location:	1 Penthouse Ded	L.	Category	All	•	Edi
1014	Penthouse Grand Suite Cat.09	Penthouse Deck		Category:	Suite Cat.01	ĸ	Sections	All	-	Ed
1015	SPA Suite Cat. 10	Penthouse Deck	-	Classification: Common Access Are:			Muster Station	All	-	Ed
1016	SPA Suite Cat. 10	Penthouse Deck		Resident Cabin:	No		Life Boat	All	•	Ed
1017	SPA Suite Cat. 10	Penthouse Deck	_	Status: Features:	AV ,C 1S,		Location	All	-]
1018	SPA Suite Cat. 10	Penthouse Deck	- 1	reatures.	,013,		Classification	All	-	Edi
1019		Penthouse Deck		Connected with:			Vertical Zone	All	-	Ed
	SPA Suite Cat. 10		_	Telephone Nos. HK Section:	[1] 10000 [2] Engine Oficer]		1		
102		Penthouse Deck		Remarks:	Chief Engineer		⊂ Al ⊂	Starboard C	Portside	
1020	SPA Suite Cat. 10	Penthouse Deck								
1021	SPA Suite Cat. 10	Penthouse Deck		Muster Station: Life Boat:	Musterstation Y	ſ	- Link Cabin			
1022	SPA Suite Cat. 10	Penthouse Deck	-	Starboard/Portside: Location:	Portside Not Define					
1023	SPA Suite Cat. 10	Penthouse Deck		Sort Priority:	10020					
1024	SPA Suite Cat. 10	Penthouse Deck	-	Vertical Zone:						
1025	SPA Suite Cat. 10	Penthouse Deck		With Special Need:	No					
1026	SPA Suite Cat. 10	Penthouse Deck	-							
	SPA Suite Cat. 10	Penthouse Deck		Cabin Inventory: Actu	ual Show Only					
1027	SPA Suite Cat. 10	Penthouse Deck		Guest: 8	01 801					
1027 1028			_	Crew: 3	87 387					
	SPA Suite Cat. 10	Penthouse Deck		Total: 11	88 1188					

Figure 8-1 Cabin Setup Window

Adding, Editing and Copying A Stateroom

- 1. From the Stateroom Setup menu, select Staterooms from the drop-down list.
- 2. In the Cabin Setup window, click New.
- 3. In the New Cabin form, enter the **Cabin number, No of Berth,** and **Berth Setup** and select the **Deck** from the drop-down list.
- 4. In the Feature section, select the **Type, Category, Features, Classification** and **Common Access Area**.
- 5. Select the **With Special Need Feature** if the cabin is equipped with special needs amenities.
- 6. Select the HK Section, Life Boat, Muster Station, Location and Vertical Zone in the Assignments section.



- 7. In the Crew Assignment section, select the Keeper, Assistant Keeper, Head Waiter, Waiter and Assistant Waiter.
- 8. Enter the Phone extension of the cabin in the Phone Numbers section.
- 9. If the cabin is linked to another cabin and has a common door, check the cabin number in the Link Cabin section.
- **10.** Click **OK** to save the cabin number.
- **11.** Repeat the same for the remaining cabin or use Copy Cabin to copy cabin of the same category and features.

Editinga a Cabin

- 1. Select the **Cabin number** from the Cabin Setup window.
- 2. Click Edit.
- 3. Click OK to save the changes.

Copying a Cabin Code

The Copy Cabin function enables you to copy the cabin of the same type, and category and has the same features.

- 1. In the Cabin Setup window, select the **cabin number** to copy.
- 2. In the Cabin Setup form, enter the new cabin number and the telephone number.
- 3. Click Add to List.
- 4. Continue to add the cabin number until you complete the list.
- 5. Click OK to save.

Batch Check-In/Out

The Batch Check-In/Out function allows you to send triggers by batch to enable/ disable the Telephone, ITV, or Dining System.

Figure 8-2 Batch Check In/Out Window

6	Bate	ch Check-in/out
PBX Communication		Filter
Send Check-in	Send Check-out	 Include All Check In Guest/Crew Include Check In Guest Only
Interactive TV		C Include Check In Crew Only
Send Check-in	Send Check-out	Include Guest/Crew with below disembarkation date Include Guest Only with below disembarkation date
Dining		C Include Crew Only with below disembarkation date
Send Check-in	Send Check-out	31/01/2015
		Close



Field Name	Description
Include All Check In Guest/Crew	Sends triggers for all check-in/out for all guest.
Include Check In Guest Only	Sends triggers for check in/out guest only.
Include Check In Crew Only	Sends triggers for check in/out crew only.
Include Guest/Crew with below disembarkation date	Sends triggers for check/out guest/crew with specified disembarkation date.
Include Guest Only with below disembarkation date	Sends triggers for check/out guest with specified disembarkation date.
Include Crew Only with below disembarkation date	Sends triggers for check/out crew with specified disembarkation date.

- 1. From the Stateroom Setup menu, select **Batch Check-In/Out**.
- 2. Select from the available filter and select a **Date**.
- 3. Select the **type of batch** to execute.
- 4. Click Close to exit.

Feature/Amenity Item

The Feature/Amenity Item is for you to set up the special request codes offered in Reservation.

- 1. Select Feature or Amenity Items from the Stateroom Setup menu.
- 2. Right-click on the blank space and select Add New.
- 3. Enter a code and description, and a comment if any.
- 4. Click OK to save.

Cabin Cleaning State Color

The Cleaning State Color allow you to define the cabin state according to its cleaning status if you choose not to use the system defaulted color. If you are defining your own cabin state color, you must update the color in the Deck Plan Setup.



Figure 8-3 Cleaning State Color Setup

All Cleaning State Color	Cleaning State Color		
Verified Failed Occupied Clean Occupied Dirty Occupied Dirty Service Suite PickUp Required Vacant Clean Vacant Dirty Vacant Dirty Service Suite Verified	Description: VC Color Backg	Vacant Clean	
		OK Cancel	Apply

- 1. Select the **Cleaning State Color** from the Stateroom Setup menu.
- 2. Select the Cleaning Status.
- 3. In the **Color** field, click to change the background color.
- 4. Click OK to save.

Deck Plan Designer

Using the Deck Plan Designer, you can create a deck plan by linking the cabin number to the plan This provides a layout view of the cabin in Management module.

New Plan Remarke Plan Save Plan As Delete Plan New Bernent	
Plan Name: Image: Colon Number: Image: Number of Bennet: 23 Load Picture Delta Picture Next Plan: v Search Calon Number: Sourch Zoom Best: Picture Delta Picture	
Restaurant	>

Figure 8-4 Deck Plan Setup

- 1. Select the **Deck Plan Designer** from the Stateroom Setup menu.
- 2. Click New Plan and insert the Plan name.
- 3. Click **Load Picture** to load the base plan from file.
- 4. Click **New Element** and then drag the element box to the desired location.
- 5. Select the **Cabin Number** from drop-down list, then click the element box to assign the cabin.
- 6. Repeat steps 4 and 5 until all cabin numbers for the deck are assigned.



7. Click Save Plan to save the changes.

Editing a Deck Plan

- 1. From the Deck Plan Designer window, right-click the **element** you wish to edit.
- 2. Select the **option** from the menu.
- 3. Click Save Plan to save the changes.

Linking a Plan

The system allows you to link a deck plan to the next plan, enabling you to navigate from one plan to another with a single click. To link a plan, you must have multiple plans saved in Deck Plan Designer

- 1. Select a **Plan Name** to edit.
- 2. Select the Next Plan from the drop-down list.
- 3. Click New Element and place the element near a staircase of the diagram.
- 4. Click Save Plan.

Deck Plan Setup

Deck Plan Setup enable you to define the cabin color by the cabin cleaning status. It is recommended that you use the same color scheme as the Cabin Cleaning State color.

- 1. Select Stateroom Setup, Deck Plan Setup from the Administration menu.
- 2. Click the Font Color or Back Color for the status and select the color from chart.
- 3. Select the **default plan** to appear in the Management module from the **Default Deck Plan**.

Note:

Checking the **Show Deck Plan by default** changes the cabin selection window from Classic View to Deck Plan View in the Management module.

Ving Card Crew Key Type

This feature is designed to enable you to create the crew key card by berth instead of cabin number and is based on the crew's embarkation/disembarkation.

- 1. In the Stateroom Setup, select Ving Card Crew Key Type.
- 2. Right-click on the left panel and select Add New.
- 3. Enter the Code, Description and Comment.
- 4. Click OK to save.



Common Access Area

This feature enables you to create the common area accessible by guest or crew, which you can encode into their keycard.

Common Access Area Name

- 1. Select Common Access Area Name from the drop-down list.
- 2. Right-click on the left panel and select Add New.
- 3. Enter a Code, Description and Comment.
- 4. Click OK to save.

Common Access Area Definition

This feature groups the common areas accessible by guests. The areas are linked in Cabin Setup or Guest Handling.

🧼 Common	Access Area Definition Setup
All Common Access Area Definition	Common Access Area Definition Description: 02 Teens only For Enabled Common Access Area
	✓ 01 Lower Pool Deck Side A 02 Lower Pool Deck Main 03 Lower Pool Deck Side C 04 05 06 07 08 Teen ✓ 09 Kid 10 11 12 24
N	OK Cancel Apply

Figure 8-5 Common Access Area Definition

- 1. Select Common Access Area Name Definition from the drop-down list.
- 2. Right-click on the left panel and select Add New.
- 3. Enter a Code, Description and Comment.
- 4. Check the respective common area for this code and click Apply.
- 5. Repeat the above until you have created all of the areas.
- 6. Click OK to save.



9 System Codes

The Systems Codes is an area where you would configure majority of the guest related codes. These codes is use to manage the guest preferences, requests and statistic tracking. These system codes are entered from **Administration**, **System Codes** and the setup is similar for most of the codes, with the exception for those marked with an asterisk (*).

Function Name	Description
Action Codes	A follow up code for services.
Amenity Codes	Amenities provided to guest.
VIP Codes	Use in defining the type of VIP categories.
Session Codes	Defines the session use in Cashbook module.
Handicap Codes	Defines the type of disability/accessibility required by guest.
Nationality Groups *	Defines group of nationality for use in Shore Denied list.
Accounts Categories	Defines the category of accounts group
Document Types *	Defines the acceptable type of legal documents.
Guest Categories	Defines the classification of guest types.
Dining Times	Defines the available dining time slots.
General Reason Codes *	Defines the reason codes use in various modules, for example, cabin change reason, voiding a transaction, and so on.
Marital Status Codes	Defines the guest/crew marital status.
Payroll Pension Plan Type	Defines the available pension plan offered to crew.
Nationality Codes *	Defines the nationality codes in ISO codes.
Fravel Insurance	Defines the Travel Insurance plan available.
Comment Types	Defines the type of comments received. For example, Service, pricing, food quality and others.
Comment Report Types	Defines the method comments were received
Comment Departments Involved *	Defines the department involves in handling the comments.
Resolution Types	Defines the resolution codes use in Comment
Comment Category	Defines the comment by category/group.
Chips Workstation	Defines the Chips & Pin workstation name.
Enable/Disable Log Entry	Defines the functions to enable/disable in the log entry, besides the default value.

Table 9-1 System Codes Field Definition



Function Name	Description
eOne Enable Contingency Mode Reason Code	Defines the reason use when enabling contingency mode.
eOne Disable Contingency Mode Reason Code	Defines the reason use when disabling contingency mode.
Nationality Flag	Defines the additional Nationality Flag for Crew.

Table 9-1 (Cont.) System Codes Field Definition

Setting Up System Codes

- 1. From the System Codes menu, select the **code** to set up.
- 2. In the Codes Setup window, right-click the blank space and select Add New.
- 3. Enter a Code, Description and Comment, if any.
- 4. Click **OK** to save.

Nationality Codes

Setting Up Nationality Groups

Wationality Group	Contraction in the second s				
	Nationality	Groups			
	defining. N	ify nationalities you wa ationalities listed must b n (e.gUS-,-UK-,-AU-)	e separa		
	Nationality	-US-,-VI-,-UM-			~
	Codes:				~
	Comments:	-US-,-VI-,-UM-			
		c	. 1	Cancel	Apply

Figure 9-1 Nationality Groups Setup

- **1**. From the System Codes menu, select the **Nationality Groups**.
- 2. In the Nationality Setup window, right-click the **blank space** at the left panel and select **Add Nationality Group**.
- 3. Enter the **description**, the **Nationality Codes** with a hyphen (-) before and after the code , and a **comma** (,) to separate the codes.
- 4. Enter a **Comment**, if any.



5. Click **Apply** to save.

Setting Up Nationality Codes

Figure 9-2	Nationality	Codes	Setup
------------	-------------	-------	-------


Il Nationality Codes	Nationality Codes					
PW Palau PY Paraguay	^	Description:	US	United State	25	
QA Qatar RE Reunion RO Romania RS Serbia		Comments:	-USA-,-840-			^
RU Russian Federation RW Rwanda SA Saudi Arabia SB Solomon Islands SC Seychelles		Default Language Other Desc	EN Englis	h		-
SD Sudan SE Sweden SG Singapore TH Thailand J Tajikistan	~	I Enabled		ок	Cancel	Apply

A set of standard ISO nationality code is pre-installed in the system. The steps to configure the Nationality Codes is the same as the above. You can define the language use for each nationality code by changing the default language.

Setting Up Document Types

A wide range of travel document types is accepted by the ship. in order to provide an electronic pre-arrival and departure manifest data on all passengers and crew to border security. These document types must be mapped in the Advanced Passenger Information System (APIS) code.





Dep Driver License Limit (MB):
D_TYPE> Mapping:
led OK Cancel Apply

- 1. Select the Document Types Setup from the System Codes menu.
- 2. Right-click the blank space on the left panel and select Add New.
- Enter the Doc.Type, Description and maximum file size allow in the File Size Limit (MB).
- 4. In the APIS<ID_TYPE> Mapping, enter the corresponding APIS Doc Type.
- 5. Click Apply to save.

Setting Up General Reason Code

The General Reason Codes is used when voiding a charge, changing a cabin, or make any changes that require a reason. These codes can be module specific or shared.

- 1. Select the General Reason Codes from the System Codes menu.
- 2. Right-click the **blank space** on the left panel and select **Add New**.
- 3. Enter the Code, Description, and the Comment.
- 4. Select the Module from the drop-down list if it is module specific.
- 5. Click Apply to save.

Setting Up Comment Departments

The Common Departments feature enable you to create and group various departments involved in handling a request or comment received.



All Comment Departments Involved	Comment De	partments In	volved		
	Description:	FB-BAR	Bar Service		
	Comments:				~
					~
	 198-Asst. 702-Asst. 284A-Ass 277-Asst. 	Info Hostess Refriger.Ted Shop Manage t.Waiter/Util. Waiter/Util.C r - Pizzamake oy Manager ecretary ender	n. er CDM DM		
			ок	Cancel	Apply

Figure 9-4 Comment Departments Involved

- 1. Select the **Comment Departments Involved** from the System Codes menu.
- 2. Right-click the **blank space** on the left panel and select **Add New**.
- 3. Enter the Code, Description and the Comment.
- 4. Click Apply to save.

Enabling/Disabling Log Entry

The Log Entry Setup lists the default log entry available in SPMS for use in reporting. These codes are enabled by default. You can disable this feature by selecting the feature from the list, deselecting the **Enable** check box, and clicking **OK** to save.



10 Package Plans

The Package Plan manages components purchased at a fixed package value. Package components are typically comprised of cabin charge, food and beverage, and/or tours or spa. These posting are generally routed from the Point of Sale (POS) system to SPMS through an interface.

For more details on Package Plan setup and usage, see Package Plan Handling.



11 Maintenance Code Setup

In the Maintenance Code feature, you can customized the locations, task codes, work order type used, workers within the workgroup, items used for repair and maintenance and the priority order for the task.

The steps to configure the codes below are the same while other codes such as Workers in Workgroup, Task Code, and Items require more steps.

- Location Codes: Define the location that requires maintenance work outside the cabins.
- Work Order Type: Define the type of maintenance work required.
- Priority: Define the work order priority.
- Location Usable Status: Define the location availability.

Setting Up Maintenance Codes

Figure 11-1 Maintenance Locations Setup

Waintenance Locations Setup				×
All Maintenance Locations	 Maintenance 	Locations		
****Unspecified Location	Description:	13PY00	ATRIUM, LOWER L	EVEL , DECK 3
	beschption		,,	
LOWER DINING RM, AFT PS, DECK 4	Comments:			A 1
ATRIUM , MID LEVEL MID CNTR, DECK 4				
ALTERNATIVE THEATRE, FUID OB DECK 4				
MAIN SHW LNGE, MID LVL I ⊁ Add New				
UPPER DINING RM, AFT SE X Remove				
SHOP MNGR OFFICE, SHOP TWD SD, DECK 3		1		×
TO OPEN DECK, FWD SB, DECK 5				
CONCIERGE, MID CNTR, DECK 7	Enabled			
		OK	Cancel	Apply

- **1.** From the Maintenance Setup menu, select the **Locations**.
- 2. Right-click the left pane and select Add New.
- 3. Enter a code, description, and comment.
- 4. Click **OK** to save

You can also use the Customized Location as a sub-category, to further define the location, for example, vending machine at bar area, open shower at Pool Deck.

- 1. From the Maintenance Setup menu, select the **Customized Locations**.
- 2. Right-click the left pane and select Add New.
- 3. Enter a code, description and comment.



- 4. Click Apply to save.
- 5. Right-click the newly created location and select Add Location or Add Category, depending on your requirement.
- 6. Enter a code, description and comment.
- 7. Check the Crew Supervision Assignment if that task requires supervision.
- 8. Click **OK** to save.

Workers in Workgroup

The Worker in Workgroup is a sub-category of Work Order Type, where workers are grouped according to their skills and expertise.

- 1. Select Workers in Workgroup from the Maintenance Setup menu.
- 2. Right-click and select Add Group.
- 3. Enter a code, description, and comments.
- 4. Click Apply to save.
- 5. Right-click on the newly created code and select Add Worker.
- 6. Select to Assign by Crew or Assign by Operation Position, then select the crew name or position from the Name field.
- 7. Enter a description and click Apply to save.
- 8. Click **OK** to close the window.

Adding Task Code

The Task Code is used to define the required task, crew involved, and task priority.

🥪 Main	ntenance Task Codes Setup 🗧	×)
All Maintenance Task Codes	- Maintenance Task Codes	
AC030 A/C - Too Noisy AL010 Alarm - Handicap:Check Cab AL020 Alarm - Handicap:Check Pub AL030 Alarm - Saunas BA010 Balcony - Bulkhead Damage, BA020 Balcony - Cleaning BA030 Balcony - Connecting Door C BA040 Balcony - Deck Damage/Dirt BA050 Balcony - Door Lock OOO BA060 Balcony - Door OOO	Description: BA070 Balcony - Furniture Damaged Comments:	
BA070 Balcony - Furniture Damage BA080 Balcony - Partition Rusty BA090 Balcony - Rail Varnish Dama BA100 Balcony - Railing Painted BA110 Paper Towel Holder - Loose, V	Priority: 1 Medium Fibre Enabled OK Cancel Apply	

Figure 11-2 Maintenance Task Codes

1. Select Maintenance Task Code Setup from the Maintenance Setup menu.



- 2. Right-click and select Add New.
- 3. Enter a code, description, and comments, and then select the Work Types, Work Group and Priority from the drop-down list.
- 4. Click Apply to save.

Adding Items Code

The Item codes is used to describe the items required for repair work. You can add a cost and inventory to the items.

Figure 11-3 Maintenance Item Setup

	Item Setup
All Items All Items TTEM1 ITEM 1 TTEM2 ITEM 2 PLUMB Plumbing PIPE * Add Item Type	Setup Item Type Item Type Description: PLUMB Plumbing Comments:
Remove Item Type Add Item	
Remove Item	OK Cancel Apply

- **1**. Select **Items** from the Maintenance Setup menu.
- 2. Right-click on the left pane and select Add Item Type.
- 3. Enter a code, description, and comments.
- 4. Click Apply to save.



Figure 11-4	Maintenance	Item	Туре
-------------	-------------	------	------

	Item Setup
All Items	Setup Item Details Item Code: Description: PIPE Average Price: 12 Stock On Hand: 296 OK Cancel

- 5. Right-click on the newly created **item code** and select **Add Item Type**.
- 6. Enter the Item Code, Description, Average Price, and Stock On Hand.
- 7. Click **OK** to save.

12 Gift Card

Gift card is used as a consumer incentive or integrated into a reward point program to increase the sales volumes. The Gift card can also be given and used as a pre-paid credit while on-board the ship.

For more details on Gift Card setup and usage, see *Gift Card Handling Guide*.



13 POS Discount

There are two methods of setting up the POS discount:

- A Basic Setup with discounts applicable to the MICROS discount itemizer level.
- An Advance Setup with discounts applicable to the MICROS major group, family group, and menu item level.

You can choose to set up with one or both methods to provide for different type of discounts. The POS Discount Handling guide provides more information on configuring the discounts, linking the MICROS Server, and usage.



14 Security Display Setup

In Security Display Setup, you can customize additional information for display in the Security WPF module. To use these customized fields, you must insert the precise data field names.

All Security Display Setup	Security Display Setup
P Passenger Display	Use this form to setup the types of information you want to display on FC Security per guest, crew & visitors account type. Example of setup: Hair Color : [uxp_h_hair], Eye Color : [uxp_h_eyes] Use comma ',' as the information separator, use square bracket [] to contain the database column
	Account Type C Crew Display
	User Defined Birthdate: [uxp_h_birthd], Position:
	×
	✓ Enabled
	OK Cancel Apply

Figure 14-1 Security Display Setup Window

- 1. Select the Security Display Setup from the Administration menu.
- 2. Right-click the space on the left panel and select Add New.
- 3. In the Account Type field, enter a **code** and **description**.
- 4. In the **User Defined** field, insert the name field, followed by the data field name using the square bracket []. Use a comma(,) to separate the field.
- 5. Click **Apply** to save.



15 Visa Type Setup

In the Visa Types Setup, you can create the type of travel visa recognized by the ship.

- **1.** Select the **Visa Type Setup** from the Administration menu.
- 2. Right-click the space on the left panel and select Add New.
- 3. Enter the Code, Description and Comment, if any
- 4. Click **OK** to save.



16 Multimedia File Maintenance

The system supports use of multimedia file such as .AVI or MP3 for promotion presentation, alerts or as a standard template use on signature device. You can also link a web page for ease of access.

🖏 - Multimedia File Mair	tenance					×
Excursions & Kiosk Multimedia File	Kiosk Picture File	Security Sound File	Signature Pad File	Report File	iCrew Sound File	Quick CheckIn File
Kiosk Flash 1 Picture		Kiosk Flash	3 Picture		Kosk Button 1 Picture Select Select Select Select	Remove
Select	Remove		Select	Remove	Kiosk Button 3 Picture	Remove
					Kiosk Button 4 Picture Select	Remove
Select	Remove				Close	

Figure 16-1 Multimedia File Setup

- 1. Select the Multimedia File Maintenance from the Administration menu.
- 2. Navigate to the tab where you wish to add the multimedia file or image.
- 3. Click Select and choose the file from the window explorer.
- 4. Click **OK** to save.
- 5. Click Play or Preview to view the file.

17 Board Card Printing Template

This feature allows you to set up predefined information to print on the board card.

VIP Description VIP Card Type (Prompt) Prompt C Yes C No	1	
Custom Report Template (Optional) With Picture PaxCardPic1 Select Shore Res ID Prompt C Predefine From 18 To 299 Cabin Prompt C Predefine From 18 To 299 Cabin Prompt C Predefine To Manifest Prompt C Predefine To Reservation Status C Prompt C Check-In C Prompt Reservation Date © Predefine Reservation Group Name (For Group Cards Only) © Prompt C Predefine From Name Prompt C Predefine From Prompt C Predefine From	ion Date 08/01/2016	Card Encoded Status

Figure 17-1 Board Card Batch Printing Template

Table 17-1 Board Card Batch Printing Template Field Definition

Field Name	Description
Description	Template Name.
Card Type	Type of card to print, for example: Guest, Crew, Group, Visitor, Gift Card or Prompt to define the criteria in Advance BCard Printing window.
Make a copy of existing card	Prints board card with the same account ID or new account ID.



Field Name	Description		
Custom Report Template	Prints board card using customized report template instead of System Default report. Report template must be available when setting up the Board Card Template setup.		
Shore Res ID	Prints board card by Shore Reservation ID.		
Age	Prints board card by age range.		
Cabin	Prints board card by cabin range.		
Manifest	Prints board card by manifest number range.		
Reservation Status	 Prints board card by reservation status: Checked-In Prompt Reservation Date — A user define date in Advance BCard printing window a time of printing. Pre-define Reservation Date— Prints according to date set in the template. 		
Group Name	Prints board card by Group Name and applicable to Card Type = Group		
Name	Print board card by name range.		
Nationality	 Prints board card for: All nationalities US Citizens only Non-US Citizens 		
Product / Pre-Product / Award Level	 Prints board card by Product: All (Field value is both null and not null) Only when specified (Field value is not null). Only when not specified (Field value is null) 		

 Table 17-1
 (Cont.) Board Card Batch Printing Template Field Definition



	General	User Define Filter(1-3)	User Define Filter(4-5)	Sorting
VIP VIP	User Define Filter 1			
	Description VIP Status			
	Field Name C			Validate Field
	Prompt C User De	fine	-	
		ave Blank for manually enter)	Validate SQL Query	
	SQL QUE Y TO TELEBEILE (LE	ave blank for manually entery	Valuate SQL QUELY	
	User Define Filter 2			
	Description			
	Field Name		States and States	Validate Field
	C Prompt @ User De	fine WITTH		
		ave Blank for manually enter)	Validate SQL Query	
	SQL QUBY IN TELEBRICE (LE	cave blank for manually entery	Valuate SQL QUELY	
	User Define Filter 3			
	Description			
	Field Name			Validate Field
	Prompt C User De	fine		-
		ave Blank for manually enter)	Validate SQL Query	
		are out to ha out oney	Taloble Side (and)	

Figure 17-2 Board Card Batch Printing Template-User Define Filter

 Table 17-2
 Board Card Batch Printing Template User Define Filter Field Definition

Field Name	Description
Description	Name of the Filter.
Field Name	Field name to filter. Reference to field name of System Data table.
SQL Query for reference	Additional Filter using SQL Command.

9		Board Car	d Batch Printing Te	mplate Setu	ıp		— ו
		General	User Define Fi	lter(1-3)	User Define Filter (4-5)		Sorting
3. 11	Sorting	Prompt - C Pr	redefine				1
	Sorting 1:	RES_CAB	-	Sorting 1 cust	om SQL		Validate SQL Query
	Sorting 2:	UXP_A_NAME	•	Sorting 2 cust	om SQL		Validate SQL Query
		,					
			Copy Pa	iste	OK Cancel	Apply	



Select one of the following two sort options:

- Prompt User when printing the board card.
- Pre-define by field using Custom SQL.

Creating Board Card Printing Template

- 1. Select Board Card Batch Printing Template from the Administration menu.
- 2. At the Board Card Batch Printing Template Setup window, right-click and select Add Template.
- 3. Enter the name of the template in the **Description** field and select the **Card Type** from the drop-down list.
- Check the applicable prompt button when generating the card or use the predefined option. If you choose to use the **Predefine** option, enter the value in the field next to it.
- 5. Click Apply to save the selection and navigate to the User Define Filter tab.
- 6. At the User Define Filter, enter or do the following:
 - a. The filter name in the **Description** field.
 - b. Field name (reference to System data table) or
 - c. Check the User Define radio button and insert a value.
- 7. Click the Validate Field to verify.
- 8. Use the **SQL Query** to filter the fields further by inserting the SQL Command and then click the **Validate SQL Query**.
- 9. Navigate to the Sorting tab and select the sorting type.
- **10.** Click **Apply** to save the filter.
- **11.** Click **OK** to save the template.

Removing Template

You can remove a template by right-clicking the **Template name** and selecting **Remove Template**.



18 Security Alert Setup

You can set up a security alert at a check point for when there is a security breach. This feature is configured only by the Implementation team. Please contact Oracle Hospitality Customer Support if you wish to use this feature.



19 Beeper Setup

The Beeper Setup feature enables you to configure the beeper number for use in the Child Location function. You can configure the beeper unit using the same steps as System Codes. See System Codes for more information.



20 Security

In this Security function, you can find information such as User Login, Statistic Count for the passengers on-board or at shore, and Port/Visa Requirement

Login

The Login Function enables you to log into and out of the current session using either a Function Key **(F8)** or by selecting the option from the Security menu.

User Logfile

The User Logfile records all transactions performed by users in date/time order. You can retrieve the information using the available fields such as By User, Type of Activities, Date, Time or Workstation. The transaction log is printable and exportable.

Gangway Logfile

The Gangway Logfile records all the gangway movement for all passengers going ashore or coming onboard. You can search the information by location, movement directions, type of passengers, date, time, cabin number, and name. Information is printable and exportable to a supported file format.

Count Onboard/Shoreside

The Count Onboard/Shoreside gives you a total passenger count of those who are onboard or ashore and by the type of passenger you select. This count can be reset by clicking the **Reset Security** button.

Note:

Do pay attention to the message prompt when resetting the status as the message in each prompt is different.



Guest/Crew Onboard

Cabin	Name	Nationality	^	Page Up Check-out Resident
			_	Show
				⊂ All
		12		
	The state of			 Only Guest
	Sector B	1		⊂ Only Resident
		1		ି Only Crew
				2
				 Only Visitors
				ି Only Check-Out onboard
	1-	1	~	52 S
Last Co	, - oming On-board on 13/01/2015 1	6:29:46	Y	

Figure 20-1 Current Guest/Crew Onboard Listing

The Guest/Crew Onboard lists all passengers onboard and display the last time-stamp of the last passenger who comes onboard.

- Clicking **Go Ashore** sets the selected passenger status from Onboard to Ashore.
- Clicking the Gangway Log opens the Gangway movement log.

Guest/Crew Shoreside

This function is the same as the Guest/Crew Onboard, and only displays passenger's who are Ashore.

Clicking Go Onboard sets the selected passenger status from Ashore to Onboard.

Port/Visa Requirement

This function restricts passengers who has travel restrictions on their travel documents from going ashore on port day. Once this is set up, when restricted passengers swipe their travel document at the Gangway, and you will receive a system prompt.



Date & Time F	rom 27/8/2015 00:0	0:15	Date & Time To	27/08/2015 23:00:00	
Remarks			Port	(not applicable)	-
- Conditions -	17		Apply To	Pax and Crew Pax Pax Crew	
Nationality	MY Malaysia] Visa Type	B2 Tourist Visa	.
	Add New	Delete	Save	Qlose	
lationality Vi		From 5 00:00:01 2	Until 8/08/2016 23:00:0	Remark	s
		Insert C	onfirm ?		×
				2 Tourist Visa not o 27/08/2015 23:00:00	
			[_

Figure 20-2 Port/Visa Requirement Window

- **1**. From the Security options, select **Port/Visa Requirement**.
- 2. Click Add New.
- 3. Enter the **Date/Time From/To** field and select the **Port** from the drop-down list.
- 4. Select the applicable passenger type.
- 5. In the Conditions Setup section, select the **Nationality** and **Visa Type** from the dropdown list.
- 6. Click Save.
- 7. At the Insert Confirmation prompt, select Yes to confirm, then click Close to exit.



21 Photo Setup

The Photo Setup allows you to configure the photos of the Guests, Crews, Visitors and Staffs. To access the functionality, go to the **Administration** menu and select from the following:

- Upload Photos
- Export Photos
- Export Documents

Upload/Export Photos

Upload Photos

The Upload Photos allows you to upload photos either by batch or individually using the following steps:



🍓 Upload Photos	×
This process will upload photos either by batch or upload below.	individually. Select the method to
Name Lists	Account Categories Guests Crew Visitors Account Status Expected Checked-In Checked-Out Scan
Batch Upload Select the file directory which contains files to uple File location: Delete files from the directory after upload	
Individual Upload Select the individual file to upload to the selected File location:	account above:
Delete file from the directory after upload Upload file format RES_ACC	Upload Qose

Figure 21-1 Upload Photos

- **1.** Click the **Administration** option from the main menu.
- 2. Select the **Photo Upload** option from the menu.
- 3. At the Upload Photos form, select the Account Categories and Account Status.
- 4. Click the **Scan** button to populate the names under the Name Lists section.
- 5. Browse the file location that contains the files to upload.
- 6. Select the **Upload file format** from the drop-down list.



Note:

If you are uploading the photos using the RES_ACC format, ensure the file name is the same as the guest booking number.

- 7. Check the Delete files from directory after upload and then click Upload.
- 8. Click **Close** to exit.

Batch Upload

For batch upload to work, you need to rename every single photos of the person with the folio number so that the system recognizes them. The photos will not update correctly if you name them wrongly. For example, picture name is "123456.jpg" for folio number 123456. Once you complete renaming the photos, you can proceed to upload using the following steps:

- **1**. Repeat the above steps.
- 2. At the Batch Upload section, browse and select the **folder path** where the photos are stored.
- 3. Click the **Upload** button and the photos upload with their unique ID, which is the reservation account number.

Individual Upload

Figure 21-2	Individual	Upload
-------------	------------	--------

Select the individu	al file to upload to the selected account above	ve:
File location:		
	Brow	se
Delete file from	n the directory after upload	

- 1. For Individual Upload, select the file path where the photo is stored.
- 2. Click the Upload button and you will see the photo on the bottom right corner.

Export Photos

This function allow you to export the photos by guest type and account status. You must have Security Access rights **#338** — **Export Photos in Single or Batch** to perform this function.



Figure 21-3	Export Photos
-------------	---------------

Export Photos					×
This process will exp Customize Expo Search for the file t	rt	selected file	e directory		
File location: C: V Name/Cabin: Select the following	ng categories	of photos to	o export		(<u>Browse</u>)
Guests Export File Name Save using u Save Using 0	nique id	C Sav		rew external id	I
 Account Status Expected 	Check	ed-In 🔽	Checkee	d-Out	
C All Date		ic Embarkati 9 /23/2011		ange o 9/23/201	1 🔹
					<u>S</u> can

- 1. Select the **Export Photo** option from the Administration menu.
- 2. At the **Export Photos, Customize Export** section, browse and select a destination location.
- 3. Select the categories to export by selecting the respective check boxes.
- 4. Select the Export File Name. You can select from:
 - Save using unique ID (The unique ID is the reservation account number).
 - Save using custom ID.
 - Save using crew external ID.
 - Save using crew internal ID.
- 5. Select the Account Status.
- 6. You can either select All Date or specify a date range.
- 7. Click Scan to begin.
- 8. A list of names will populate in the Name Lists section.
- Individually select the account you wish to export or click the Check All option to export all.
- **10.** Click **Export** to begin export.



Export Document

This feature enable you to export documents to a support file format. The steps to export the document is the same as Export Photos. See Upload/Export Photos for steps to export the document.

