Development Workbench – Getting Started
Oracle FLEXCUBE Universal Banking
Release 14.1.0.0.0
[May] [2018]

ORACLE

FINANCIAL SERVICES

Contents

1 Preface

This document describes helps developer to familiarize with ORACLE FLEXCUBE Development Workbench for Universal Banking.

1.1 Audience

This document is intended for FLEXCUBE Application developers/users that use Development Workbench to develop   various FLEXCUBE components.

To Use this manual, you need conceptual and working knowledge of the below:

Proficiency	*Resources*
FLEXCUBE Functional Architecture	Training programs from Oracle Financial Software Services.
FLEXCUBE Object Naming conventions	Development Overview Guide
Working knowledge of Web based applications	Self Acquired
Working knowledge of XML files	Self Acquired

1.2   Related Documents

01-Development_WorkBench_Installation.docx
02-Development_WorkBench _Administration.docx

2 Introduction

This document contains information about the following topics:

- Chapter 2 , "Introduction"
- Chapter 3 , "Explanation of Some Basic Icons"
- Chapter 4 , "Login"
- Chapter 5 , "Browser"
- Chapter 6 , "Windows"
- Chapter 7, "Launch FCUBS"
- Chapter 8 , "User Preferences"
- Chapter 9 , "Change Password"
- Chapter 10 , "Sign Out"
- Chapter 11 , "About"

3   Explanation of Some Basic Icons and Jargons

Icons	Function
	New Button used to add new User, Environment, Release etc
	Save button used to save the work done by user.
	Close button clears all the data in the screen and all buttons will be reset to initial position.
	Enter query button to retrieve existing data from the screen. Primary key field will be get enabled.
	Execute query button. This gets enabled on click of enter query button. On click of this button it will retrieve the required data and displays on the screen.
	Unlock button used to modify the existing record. On click of this , all fields except primary key fields gets enabled.
	List Of Values
	To add New labels or modify existing labels in FLEXCUBE schema
	Generate Files.
	Deploy Files.
	Release Files.

Radxml: Workbench saves all the activities carried out by the developer in an xml file   referred to as radxml

Rad/RadTool/ODT: These terms also refers to FLEXCUBE Development Workbench for Universal Banking

4   Client Browser Settings

➢ **Recommended Browsers:**

- Microsoft Internet Explorer 8.0
  The version of Microsoft Internet Explorer 8.0 should not be a Beta version,
  Partner Build or a Release Candidate. It should be the Final build of Microsoft
  Internet Explorer 8 or later. The minimum version of Microsoft Internet
  Explorer 8 should be **8.0.6001.18702**. This can be verified by visiting the
  'About Internet Explorer' dialog in the Help menu as shown below.

- Mozilla Firefox

- Google Chrome

> **Recommended Screen Resolution:**
>   1280*1024 pixels

4.1   IE Specific Settings

ActiveX Scripting has to be enabled to read and write files in Client Machine.
Therefore, if you have to generate the files in client machine (instead of
downloading as zip from server); certain settings has to be done in the browser.
Client Mode is supported only in Internet Explorer. Settings required in IE for
enabling writing to Client Machines is explained below

MSXML 6.0 :
                Microsoft Core XML Services (MSXML 6.0) needs to be
        installed in the system. It can be downloaded from,
        http://www.microsoft.com/en-us/download/details.aspx?id=3988

The following IE settings need to be done to launch the Workbench Login page
1) Go to Internet Explorer →Tools→Internet options
2) Click on Security tab, select Internet and click on Custom level button as shown below:

3) As security settings make all settings as enabled except **use Pop-up Blocker** as shown below
   Make sure following things are enabled
   - o .Allow previously unused active controls to run
   - o Allow script lets
   - o Automatic prompting for active control
   - o Binary and script behaviors.
   - o Only allow approved domains to use active control without prompting.
   - o Run active controls and plug-ins.
   - o Script active controls marked for saving.

Development Workbench - Getting Started

4) Repeat the same steps for Local Intranet by selecting the same as shown below :

Development Workbench - Getting Started

5) After all these settings are done, go to **Advanced** tab and check whether the checkbox 'Use JRE (Version) for <applet>(requires restart)' is checked or not. If its nnot checked, then it has to be checked as shown below.

Development Workbench - Getting Started

5   Login

Developers will be provided with Login credentials for Workbench which has to be used for accessing the Tool

   Initial login credentials, after installation, will be RADTOOL/RADTOOL. Using this credential; developer has to create release, environment and users. Refer *02-Development_WorkBench _Administration.docx* for further details.

Fig 4.1: ODT login Screen

On successful login Workbench landing page will be displayed as shown below. Browser will display the available options to user in tree view based on role.


Fig 4.2: The landing page

Development Workbench - Getting Started

Below options are available in landing page.

6   Browser

It is drop down tree menu. Based on role of the user, Workbench displays the options in tree.

- **Administration:** This is used to add releases, environments and users.
- **Function Generation:** This is used to design FLEXCUBE screens.
- **Screen Customizer:** This is used to design FLEXCUBE screens. Main Difference between function generation and screen customizer is in screen customizer user can just modify the screen lay out. No additions and deletions allowed.
- **Tracking Changes:** This module helps in tracking the changes done in a particular release. A Change Report can be generated OR the changes can be viewed
- **Notification Triggers:** This will be used to create notification triggers.
- **Notification:** This will be used to create notification xml.
- **Bulk Generation:** This option used to generate all output files for a set of radxmls at one time.
- **Excel Template Generation:** This option will be used to generate excel template out of radxml which can be used to upload data into FLEXCUBE.
- **Refresh:** This option will be used to upgrade Radxml from lower version to higher version and to update child RADxml with parent changes.
- **Web Services:** Artifacts required for creation of a Web service can be generated using this feature.
- **Block Detail Upload:** This option will be used to upload block detailed information into schema from a set of radxml at one time.
- **Test Case Definition:** This option will be used to define new test case and modify existing test cases.
- **Run Chart Definition:** This option will be used to define run charts for test cases.
- **Test Case Data Upload:** This option will be used to upload test case data for the defined test cases. Data has to be uploaded in the standard excel formats.
- **Create Request:** This option will be used to create request xml (compatible with FLEXCUBE) for a test case data set.
- **Test Case Execution:** This option is used to execute test case on FLEXCUBE environment
- **Run Chart Execution:** This option will be used to execute run chart on FLEXCUBE environment

- **Test Case Data Bulk Upload:** This option will be used to upload multiple test case data at one time.
- **Execution Report:** This option generates report for the executed test cases and run charts

7   Windows

It will display all opened windows in drop down menu. User can select the required window to show on top of the tool.


Fig 6.1: The Windows opened

8   Launch FCUBS

This will be used to launch FLEXCUBE link directly from Workbench. User has to maintain correct FLEXCUBE url while adding environment. Refer *02-Development_WorkBench_Administration.docx* details on environment creation.

Fig 7.1: Launch FCUBS Screen

9 User Preferences

This option will be used to set user preferences. By default user will be mapped to a release code and its corresponding environment.

If developer wants to change the working release or environment, he has to set it in this screen.

Language Code: Default Language of the environment can be changed if required

Save Mode: Default Save Mode of the user would be displayed here. This can be changed if required

Work Directory: Work Directory can be modified if the Save Mode.

Excel Format: Excel Format can be changed from the value defined at User Definition screen

XML Indentation: If the generated Xmls has to intended, this option can be checked. Note that XML indentation feature won't be available if Save Mode ids Client

Development Workbench - Getting Started

Fig 8.1: User Preferences Screen

After changing required fields click on **Set button** for changing the details

Fig 8.2: The screen to change preferences

Changes done in user preferences on release, environment or work directory will effect only to the current session. On sign out and re-login, default release details will be assigned again.
If developer wishes to change default settings for the user, same can be done by modifying the default options for the User in Administration section

10 Change Password

This option can be used to change User Password. Enter old password and new password and confirm password.

Development Workbench - Getting Started

Fig 9.1: Screen to change password

Click on change button. On successful change it will display message.

Fig 9.2: Message on password change

11 Sign Out

On click of sign out button user will logout from FLEXCUBE Development Workbench. All opened windows will get closed automatically. It will redirect to login page.

Development Workbench - Getting Started

12 About

On click of this, Development Workbench version information popup window will get displayed.

Fig 11.1: 'About' Screen that gives details of ODT

ORACLE®