

**Oracle FLEXCUBE  
ATM User Manual  
Release 5.0.0.0.0  
Part No E52077-01**

**ORACLE®**  
FINANCIAL SERVICES

**ORACLE®**

## Table of Contents (index)

<b>1. ATM .....</b>	<b>3</b>
1.1. ATM01 - ATM Bank Params Maintenance .....	4
1.2. ATM02 - ATM Acquirer POS Id Maintenance .....	10
1.3. ATM03 - ATM Cash Replenishment by Branch Vault.....	14
1.4. ATM04 - ATM Cash Replenishment by Third Party.....	18

## 1. ATM

ATM (Automated Teller machines) have become the most significant delivery channels after branch. Starting as a simple cash dispensing machine, now a days ATMs come with features where one can pay utility bill. Initiate fund transfer request, get statement of account, request for cheque books and several other services.

## 1.1. ATM01 - ATM Bank Params Maintenance

Using this option, you can define the bank parameters / GL accounts required for **Oracle FLEXCUBE**, which are necessary for maintaining ATM (Automated Teller Machine) transactions, which occur through various ATM channels across the network. The hold variance percentage and the hold period is also defined here.

The system places a Master Money Hold on the account when it grants authorization on an offline POS i.e. signature based POS transaction. The Hold has a certain validity period. The MasterMoney Hold will be removed by the system if the debit has a matching Authorization Code and is within the defined tolerance range. The debit will then be posted to the account. If either the Authorization Code and/or settlement amount for debit (not within the tolerance) does not match, the Hold is not removed. Such a Hold will expire on the expiry date.

### Definition Prerequisites

- BAM20 - Bank Codes Maintenance

### Other Prerequisites

- GL Codes have to be defined

### Modes Available

Add By Copy, Add, Modify, Delete, Cancel, Amend, Authorize, Inquiry. For more information on the procedures of every mode, refer to **Standard Maintenance Procedures**.

#### To add ATM bank parameters

1. Type the fast path **ATM01** and click **Go** or navigate through the menus to **Global Definitions > Channels > ATM Bank Params Maintenance**.
2. The system displays the **ATM Bank Params Maintenance** screen.

## ATM Bank Params Maintenance

ATM Bank Params Maintenance

Bank Code :

Institution Id :

Issuer Fee GL :

Forwarder Cash GL :

Forwarder Fee GL :

Debit Suspense GL :

Remittance Debit GL :

Settlement GL :

Remit Branch Code :

Allow Funds Transfer Across Customers :

Levy Issuer Fee Online :

Funds Appropriation Sequence :

Remarks:

**Record Details**

Input By	Authorized By	Last Mnt. Date	Last Mnt. Action	Authorized
<input type="checkbox"/> Add By Copy	<input type="radio"/> Add <input type="radio"/> Modify <input type="radio"/> Delete <input type="radio"/> Cancel <input type="radio"/> Amend <input type="radio"/> Authorize <input type="radio"/> Inquiry			<input type="checkbox"/>
<input type="button" value="UDF"/> <input type="button" value="Ok"/> <input type="button" value="Close"/> <input type="button" value="Clear"/>				

## Field Description

Field Name	Description
<b>Bank Code</b>	<p>[Mandatory, Numeric, Five]</p> <p>Type the code of the bank, for which global ATM definitions should be maintained.</p> <p>Each code uniquely identifies a different bank.</p>
<b>Institution Id</b>	<p>[Mandatory, Numeric, 11]</p> <p>Type the institution code.</p> <p>Each code uniquely identifies the bank in the network.</p> <p>Institution ID is allotted by the central bank of the country, or the body that governs payment systems in the country.</p>
<b>Issuer Fee GL</b>	<p>[Mandatory, Numeric, Nine]</p> <p>Type the issuer fee GL code.</p> <p>This GL account will be credited for fees on transactions done through the Bank's ATM network.</p>

Field Name	Description
<b>ATM Cash GL</b>	<p>[Mandatory, Numeric, Nine]</p> <p>Type the ATM cash GL code.</p> <p>This GL account will be credited or debited for cash transactions done through the Bank's ATM network by the bank customers.</p>
<b>Forwarder Cash GL</b>	<p>[Mandatory, Numeric, Nine]</p> <p>Type the forwarder cash GL code.</p>
<b>Acquirer Cash GL</b>	<p>[Mandatory, Numeric, Nine]</p> <p>Type the acquirer cash GL code.</p> <p>This GL account will be debited for the remote on-us transactions (transactions performed by the customers of other banks, through the Bank's ATM network).</p>
<b>Forwarder Fee GL</b>	<p>[Mandatory, Numeric, Nine]</p> <p>Type the forwarder fee GL code.</p> <p>This GL account will be credited for the transactions performed by other bank's customers through the ATM network, owned and managed by our bank in the capacity of a forwarder.</p>
<b>Acquirer Fee GL</b>	<p>[Mandatory, Numeric, Nine]</p> <p>Type the acquirer fee GL code.</p> <p>This GL account will be credited for fees on transactions done by banks, which act as Acquirer institutions.</p>
<b>Debit Suspense GL</b>	<p>[Mandatory, Numeric, Nine]</p> <p>Type the debit suspense GL code.</p> <p>This GL account will be debited in case of any suspense generated on account of ATM transactions. Entries in this GL should be manually reversed out after rectifying the cause of suspense. The entered GL account should be the Miscellaneous Debit implemented GL. Both the GLs should be of similar type either implemented GL or Normal GL.</p>
<b>Credit Suspense GL</b>	<p>[Mandatory, Numeric, Nine]</p> <p>Type the credit suspense GL code.</p> <p>This GL account will be credited in case of any suspense generated on account of ATM transactions. Entries in this GL should be manually reversed out after rectifying the cause of suspense. The entered GL account should be the Miscellaneous Credit implemented GL. Both the GLs should be of similar type either implemented GL or Normal GL.</p>

Field Name	Description
<b>Remittance Debit GL</b>	<p>[Mandatory, Numeric, Nine]</p> <p>Type the remittance debit GL code.</p> <p>The GL will be debited if the other bank account holder is allowed to give debit instructions for debiting an ATM bank customer. The reconciliation or accounting of the remittance debit GL has to be done operationally from the file hand off.</p>
<b>Remittance Credit GL</b>	<p>[Mandatory, Numeric, Nine]</p> <p>Type the remittance credit GL code.</p> <p>The GL will be credited if the ATM facilitates fund transfer option, and the customer of the bank does a fund transfer from his account to an external account.</p> <p>The reconciliation or accounting of the remittance credit GL has to be done operationally from the file hand off.</p>
<b>Settlement GL</b>	<p>[Mandatory, Numeric, Nine]</p> <p>Type the settlement GL code.</p> <p>This GL account will be debited or credited, in case of remote on us or off us transactions. The net balance in this GL will be claimed from, or paid to other banks in the network.</p>
<b>Remit Branch Code</b>	<p>[Optional, Alphanumeric, 12]</p> <p>Type the branch code for remittance.</p>
<b>Allow Funds Transfer Across Customers</b>	<p>[Optional, Check Box]</p> <p>Select the <b>Allows Funds Transfer Across Customers</b> check box if you want to allow the transactions involving funds transfer, across accounts belonging to different customers.</p>
<b>Levy Issuer Fee Online</b>	<p>[Optional, Check Box]</p> <p>Select the <b>Levy Issuer Fee Online</b> check box if you want to debit the issuer fees online simultaneously, along with the transaction.</p> <p>Issuer fees is normally passed on by the switch/ETBI on which the ATM / TBS runs. Issuer fees is included in the message that is passed on by the switch/ETBI, and gets debited online with the original transaction amount, provided this flag is checked.</p>

Field Name	Description
<b>Funds Appropriation Sequence</b>	<p>[Mandatory, Alphanumeric, Five]</p> <p>Type the funds appropriation sequence.</p> <p>This field denotes the sequence in which the transaction amount needs to be appropriated while debiting the account.</p> <p>The options are:</p> <ul style="list-style-type: none"><li>• S – Sweep-In</li><li>• O – Overdraft</li><li>• V – Overline</li><li>• A – Advance against unclear funds</li><li>• T – Temporary Overdraft</li></ul>

3. Click the **Add** button.
4. Enter the bank code and press the **<Tab>** key.
5. Enter the required information in the various fields.

## ATM Bank Params Maintenance

ATM Bank Params Maintenance\*

Bank Code :	335	Bank Code :	335										
Institution Id :	1111	Institution Id :	1111										
Issuer Fee GL :	100031800	ATM Cash GL :	100010101										
Forwarder Cash GL :	100010101	Acquirer Cash GL :	100010101										
Forwarder Fee GL :	100031800	Acquirer Fee GL :	100031800										
Debit Suspense GL :	100074000	Credit Suspense GL :	100074000										
Remittance Debit GL :	100074000	Remittance Credit GL :	100074000										
Settlement GL :	100074000												
Remit Branch Code :	HO												
<input checked="" type="checkbox"/> Allow Funds Transfer Across Customers : <input checked="" type="checkbox"/> Levy Issuer Fee Online : Funds Appropriation Sequence : BOSA													
<b>Remarks:</b> _____													
<b>Record Details</b> <table border="1"> <thead> <tr> <th>Input By</th> <th>Authorized By</th> <th>Last Mnt. Date</th> <th>Last Mnt. Action</th> <th>Authorized</th> </tr> </thead> <tbody> <tr> <td>THELSON</td> <td>SSUDEEP</td> <td>11/12/2009 14:06:38</td> <td>Authorize</td> <td><input checked="" type="checkbox"/></td> </tr> </tbody> </table>				Input By	Authorized By	Last Mnt. Date	Last Mnt. Action	Authorized	THELSON	SSUDEEP	11/12/2009 14:06:38	Authorize	<input checked="" type="checkbox"/>
Input By	Authorized By	Last Mnt. Date	Last Mnt. Action	Authorized									
THELSON	SSUDEEP	11/12/2009 14:06:38	Authorize	<input checked="" type="checkbox"/>									
<input type="checkbox"/> Add By Copy <input checked="" type="radio"/> Add <input type="radio"/> Modify <input type="radio"/> Delete <input type="radio"/> Cancel <input type="radio"/> Amend <input type="radio"/> Authorize <input type="radio"/> Inquiry													
<input type="button" value="UDF"/> <input type="button" value="Ok"/> <input type="button" value="Close"/> <input type="button" value="Clear"/>													

6. Click the **Ok** button.
7. The system displays the message "Record Added...Authorization Pending.." Click the **OK** button.
8. The ATM bank parameters are added once the record is authorized.

## 1.2. ATM02 - ATM Acquirer POS Id Maintenance

Using this option, you can maintain the various Switch IDs, the physical ATM terminals that connect to these switches, and the originating branch code for a particular ATM.

Each ATM is logically attached to a GL (ATM CASH GL) in some branch (originating branch) in **FLEXCUBE**. Every ATM in the ATM network of a Bank has two ATM IDs (Card Acceptor terminal ID and Card Acceptor ID code), which uniquely identify the ATM. The ATM Acquirer POS ID Xref maintenance, maintains the cross-reference between the ATM IDs, ATM CASH GL and the ATM branch. Also, every Forwarder (VISA/Master Card), which the bank interfaces with, has to be configured through this option.

### Definition Prerequisites

- BAM03 - Branch Master Maintenance

### Other Prerequisites

- GL Codes have to be defined

### Modes Available

Add, Modify, Delete, Cancel, Amend, Authorize, Inquiry. For more information on the procedures of every mode, refer to **Standard Maintenance Procedures**.

#### To add ATM acquirer POS ID

1. Type the fast path **ATM02** and click **Go** or navigate through the menus to **Global Definitions > Channels > ATM Acquirer POS Id Maintenance**.
2. The system displays the **ATM Acquirer POS Id Maintenance** screen.

## ATM Acquirer POS Id Maintenance

ATM Acquirer POS Id Maintenance

Acquirer Institution Id

Card Acceptor Identification Code

Forwarder Institution Id

Card Acceptor Terminal Id  ...

Originating Branch Code

ATM Cash GL

Deposit Cash GL

Acquirer Fee GL

Forwarder Fee GL

Incoming Remit GL

Outgoing Remit GL

Settlement GL

**Record Details**

Input By  Authorized By  Last Mnt. Date  Last Mnt. Action  Authorized

Add  Modify  Delete  Cancel  Amend  Authorize  Inquiry

## Field Description

Field Name	Description
<b>Acquirer Institution Id</b>	[Mandatory, Numeric, 11] Type the acquirer institution ID. The institution ID is allotted to the bank by the central bank or the governing body for non-branch channels like TBS, ATM and POS.
<b>Card Acceptor Identification Code</b>	[Mandatory, Alphanumeric, 15] Type the card acceptor identification code. This code identifies the ATM, which defines the point of the transaction in both local and interchange environment.
<b>Forwarder Institution Id</b>	[Mandatory, Alphanumeric, 11] Type the forwarder institution ID. The institution ID allotted to the bank by the central bank or the governing body for non-branch channels like TBS, ATM and POS who own and manage the ATM network.

Field Name	Description
<b>Card Acceptor Terminal Id</b>	[Display] This field displays the card terminal ID. Each unique code identifies a terminal at the card acceptor location.
<b>Originating Branch Code</b>	[Mandatory, Drop-Down] Select the branch code from the drop-down list. The originating branch code refers to the branch through which the ATM transactions would be routed to respective branches. In practical scenarios, where all ATM operations are centralized, the branch code would be unique. However, if there are multiple switches that accept ATM requests, all catered to by different branches, the respective branch code needs to be maintained.
<b>ATM Cash GL</b>	[Mandatory, Numeric, Nine] Type the ATM cash GL code. This GL account will be debited on performing on-us, remote on us, off us transactions.
<b>Deposit Cash GL</b>	[Mandatory, Numeric, Nine] Type the deposit cash GL code.
<b>Acquirer Fee GL</b>	[Mandatory, Numeric, Nine] Type the acquirer fee GL code which accepts the card for performing the transaction.
<b>Forwarder Fee GL</b>	[Mandatory, Numeric, Nine] Type the forwarder fee GL code which is responsible for forwarding the transaction from the acquirer to the issuer.
<b>Incoming Remit GL</b>	[Mandatory, Numeric, Nine] Type the incoming remit GL code.
<b>Outgoing Remit GL</b>	[Mandatory, Numeric, Nine] Type the outgoing remit GL code.
<b>Settlement GL</b>	[Mandatory, Numeric, Nine] Type the settlement GL code.

3. Click the **Add** button.
4. Enter the acquirer institution ID and press the **<Tab>** key.
5. Enter the appropriate information in the fields.
6. Select the appropriate branch code from the drop-down list.

## ATM Acquirer POS Id Maintenance

Acquirer Institution Id	0021
Card Acceptor Identification Code	52215
Forwarder Institution Id	L552
Card Acceptor Terminal Id	
Originating Branch Code	JubbankKAS
ATM Cash GL	212101100
Deposit Cash GL	250010900
Acquirer Fee GL	250171800
Forwarder Fee GL	250171100
Incoming Remit GL	250171200
Outgoing Remit GL	212109101
Settlement GL	330001008

Record Details

Input By	Authorized By	Last Mnt. Date	Last Mnt. Action	Authorized
<input checked="" type="checkbox"/> Add <input type="radio"/> Modify <input type="radio"/> Delete <input type="radio"/> Cancel <input type="radio"/> Amend <input type="radio"/> Authorize <input type="radio"/> Inquiry				
<input type="button" value="Ok"/> <input type="button" value="Close"/> <input type="button" value="Clear"/>				

7. Click the **Ok** button.
8. The system displays the message "Record Added...Authorization Pending...Click Ok to Continue". Click the **OK** button.
9. The ATM acquirer POS ID is added once the record is authorized.

**Note:** The same **Card Acceptor Identification Code** can have multiple **Card Acceptor Terminal Ids** linked to it.  
 Every combination of **Card Acceptor Identification Code** and **Card Acceptor Terminal Ids** is unique.

### 1.3. ATM03 - ATM Cash Replenishment by Branch Vault

This screen can be used to maintain the ATM TIL position in the branch when the actual cash is replenished in the ATM machine by Branch Vault. The screen 'ATM Cash Replenishment by Branch Vault' will be available to branch teller. Any transaction done through this screen will not be treated as a regular cash transaction done by Teller and Teller's TIL position will not be updated for any of the transactions that take place through this screen. The system will only update the TIL Position of the ATM terminal id on successful completion of a transaction through this screen.

#### Definition Prerequisites

- ATM02 - ATM Acquirer POS Id Maintenance
- TIL01-TIL ID Maintenance
- TIL02 - TIL Linkage Maintenance

#### Modes Available

Not Applicable

#### To maintain the ATM TIL position when Cash Replenishment is done by Third Party

1. Type the fast path **ATM03** and click **Go** or navigate through the menus to **Global Definitions > Channels > ATM Cash Replenishment by Third Party**.
2. The system displays the **ATM Cash Replenishment by Branch Vault** screen.

## ATM Cash Replenishment from Branch Vault

ATM Cash Replenishment from Branch Vault\*

Card Acceptor Terminal Id :	<input type="text"/>	...
TIL ID :	<input type="text"/>	
Currency :*	<input type="text"/>	
Total Required Cash :*	<input type="text"/>	
Narrative :	<input type="text" value="ATM Cash Replenishment from Branch Vault"/>	
<input type="button" value="Card"/> <input type="button" value="Change Pin"/> <input type="button" value="Cheque"/> <input type="button" value="Cost Rate"/> <input type="button" value="Handle FCY Change"/> <input type="button" value="Denomination"/> <input type="button" value="Instrument"/> <input type="button" value="Inventory"/> <input type="button" value="Pin Validation"/> <input type="button" value="Service Charge"/> <input type="button" value="Signature"/> <input type="button" value="Travellers Cheque"/>		
<input type="button" value="UDF"/> <input type="button" value="OK"/> <input type="button" value="Close"/> <input type="button" value="Clear"/>		

Field Name	Description
<b>Card Acceptor Terminal ID</b>	[Mandatory, Pick list, 16] Select Card Acceptor Terminal Id (ATM Terminal ID) from the pick list. This field will display the selected Card Acceptor Terminal ID defined in the branch.
<b>TIL ID</b>	[Display] The System will display the TIL Id. linked to the ATM terminal id.
<b>Currency</b>	[Mandatory, Drop-down] Select the Currency in which Cash will be replenished in the ATM Terminal.
<b>Total Required Cash</b>	[Mandatory, Text box] Enter transaction amount

Field Name	Description
<b>Narrative</b>	<p>[Mandatory, Alphanumeric, 120 ]</p> <p>Enter the transaction narrative in this field.</p> <p>3. Select the Card Acceptor Terminal ID using the pick list. 4. The system will display the TIL ID automatically. 5. Select the Currency in which you wish the cash to be replenished in the ATM terminal using the respective dropdown. 6. Enter the transaction amount in the respective field. 7. Write the descriptive Narration in the respective field.</p>

## ATM Cash Replenishment from Branch Vault

ATM Cash Replenishment from Branch Vault\*

Card Acceptor Terminal Id : 1213441 ...

TIL ID : 124

Currency : \* RMB

Total Required Cash : \* 10,000.00

Narrative : ATM Cash Replenishment from Branch Vault

Card | Change Pin | Cheque | Cost Rate | Handle FCY Change | Denomination | Instrument | Inventory | Pin Validation | Service Charge | Signature | Travellers Cheque

UDF | OK | Close | Clear

8. Click on **OK** button.
9. The system will ask for authorization with the following message "Authorization required .Do you want to continue ?
10. Click on **OK** button and Grant the permission to authorize the transaction.
11. On successful completion the system will display "**Transaction completed Successfully**" message on a Pop up.

## 1.4. ATM04 - ATM Cash Replenishment by Third Party

This screen can be used to maintain the ATM TIL position in the branch when the actual cash is replenished in the ATM machine by third party. The screen 'ATM Cash Replenishment by Third Party' will be available to all type of tellers. Any transaction done through this screen will not be treated as a regular cash transaction done by Teller and Teller's TIL position will not be updated for any of the transactions that take place through this screen. The system will only update the TIL Position of the ATM terminal id on successful completion of a transaction through this screen.

### Definition Prerequisites

- ATM02 - ATM Acquirer POS Id Maintenance
- TIL01-TIL ID Maintenance
- TIL02 - TIL Linkage Maintenance

### Modes Available

Not Applicable

### To maintain the ATM TIL position when Cash Replenishment is done by Third Party

1. Type the fast path **ATM04** and click **Go** or navigate through the menus to **Global Definitions > Channels > ATM Cash Replenishment by Third Party**.
2. The system displays the **ATM Cash Replenishment by Third Party** screen.

## ATM Cash Replenishment By Third Party

ATM Cash Replenishment By Third Party\*

Card Acceptor Terminal Id :	<input type="text"/>	...
TIL Id :	<input type="text"/>	
Currency :*	<input type="button" value="▼"/>	
Total Required Cash :*	<input type="text"/>	
GL Account :	<input type="text"/>	<input type="text"/>
CASA Account :	<input type="text"/>	<input type="text"/>
Narrative :*	<input type="text" value="ATM Cash Replenishment By Third Party"/>	

Card | Change Pin | Cheque | Cost Rate | FCY Change | Denomination | Instrument | Inventory | Pin Validation | Service Charge | Signature | Travellers Cheque

UDF | OK | Close | Clear

Field Name	Description
<b>Card Acceptor Terminal ID</b>	[Mandatory, Pick list, 16] Select Card Acceptor Terminal Id (ATM Terminal ID) from the pick list. This field will display the selected Card Acceptor Terminal ID defined in the branch.
<b>TIL ID</b>	[Display] The System will display the TIL Id. linked to the ATM terminal id.
<b>Currency</b>	[Mandatory, Drop-down] Select the Currency in which Cash will be replenished in the ATM Terminal.
<b>Total Required Cash</b>	[Mandatory, Text box] Enter transaction amount

Field Name	Description
<b>GL Account</b>	<p>[Conditional, Text box, 9]</p> <p>Enter GL Account For crediting Third Party GL. This field will be mandatory if the CASA account is not entered. You must enter either GL account or CASA account.</p> <p>This field will become disabled if the CASA account is entered.</p>
<b>CASA Account</b>	<p>[Conditional, Text box, 16 ]</p> <p>Enter CASA Account For crediting Third Party CASA account. This field will be mandatory if the GL account is not entered. User must enter either GL account or CASA account.</p> <p>This field will become disabled if the GL account is entered.</p>
<b>Narrative</b>	<p>[Mandatory, Alphanumeric, 120 ]</p> <p>Enter the transaction narrative in this field.</p> <ol style="list-style-type: none"> <li>3. Select the Card Acceptor Terminal ID using the pick list.</li> <li>4. The system will display the TIL ID automatically.</li> <li>5. Select the Currency in which you wish the cash to be replenished in the ATM terminal using the respective dropdown.</li> <li>6. Enter the transaction amount in the respective field.</li> <li>7. Enter the GL Account or CASA Account for crediting third party CASA or GL Account.</li> <li>8. Write the descriptive Narration in the respective field.</li> </ol>

## ATM Cash Replenishment By Third Party

ATM Cash Replenishment By Third Party\*

Card Acceptor Terminal Id :  ...

TIL Id :

Currency : \*

Total Required Cash : \*

GL Account :

CASA Account :

Narrative : \*

Card Change Pin Cheque Cost Rate FCY Change Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear

9. Click on **OK** button.
10. The system will ask for authorization with the following message "Authorization required .Do you want to continue ?".
11. Click on **OK** button and Grant the permission to authorize the transaction.
12. On successful completion the system will display "Transaction completed Successfully " message on a Pop up.



**ATM User Manual**

**May 2013**

**Version : 5.0.0.0.0**

**Oracle Corporation  
World Headquarters  
500 Oracle Parkway  
Redwood Shores, CA 94065  
U.S.A.**

**Worldwide Inquiries:**  
Phone: +1.650.506.7000  
Fax: +1.650.506.7200

[www.oracle.com/financial\\_services/](http://www.oracle.com/financial_services/)

**Copyright © 2013 Oracle and/or its affiliates. All rights reserved.**

**No part of this work may be reproduced, stored in a retrieval system, adopted or transmitted in any form or by any means, electronic, mechanical, photographic, graphic, optic recording or otherwise, translated in any language or computer language, without the prior written permission of Oracle Financial Services Software Limited.**

**Due care has been taken to make this document and accompanying software package as accurate as possible. However, Oracle Financial Services Software Limited makes no representation or warranties with respect to the contents hereof and shall not be responsible for any loss or damage caused to the user by the direct or indirect use of this document and the accompanying Software System. Furthermore, Oracle Financial Services Software Limited reserves the right to alter, modify or otherwise change in any manner the content hereof, without obligation of Oracle Financial Services Software Limited to notify any person of such revision or changes.**

**All company and product names are trademarks of the respective companies with which they are associated.**