

Intermediary User Guide

Oracle FLEXCUBE Universal Banking

Release 12.1.0.0.0

Part No. E64763-01

September 2015

Intermediary User Guide
September 2015
Oracle Financial Services Software Limited

Oracle Park

Off Western Express Highway
Goregaon (East)
Mumbai, Maharashtra 400 063
India

Worldwide Inquiries:

Phone: +91 22 6718 3000

Fax: +91 22 6718 3001

www.oracle.com/financialservices/

Copyright © 2007, 2015, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Contents

1. Preface	1-1
1.1 Introduction.....	1-1
1.2 Audience.....	1-1
1.3 Documentation Accessibility	1-1
1.4 Organization	1-1
1.5 Related Documents	1-2
1.6 Glossary of Icons.....	1-2
2. Intermediary - An Overview	2-1
2.1 Introduction.....	2-1
3. General Maintenance	3-1
3.1 Introduction.....	3-1
3.2 Branch Parameters.....	3-1
3.2.1 Capturing Branch Parameters	3-1
3.2.2 Actions Allowed	3-2
3.2.3 Viewing Branch Parameters Summary.....	3-3
3.3 Intermediary SDE Details	3-3
3.3.1 Capturing Intermediary SDE Details.....	3-4
3.3.2 Actions Allowed	3-6
3.3.3 Viewing SDE Summary Details	3-7
3.4 Intermediary Rule	3-7
3.4.1 Defining an Intermediary Rule	3-7
3.4.2 Capturing Rule Formula	3-10
3.4.3 Actions Allowed	3-11
3.4.4 Viewing Rule Summary Details	3-11
3.5 Intermediary Group.....	3-12
3.5.1 Maintaining Intermediary Group	3-12
3.5.2 Actions Allowed	3-12
3.5.3 Viewing Group Summary Details.....	3-13
3.6 Intermediary Hierarchy Details	3-13
3.6.1 Maintaining Intermediary Hierarchy Details.....	3-14
3.6.2 Intermediary Tab	3-15
3.6.3 Settlement and Statement Tab.....	3-18
3.6.4 Products Tab	3-20
3.6.5 Capturing Events.....	3-21
3.6.6 Maintaining MIS Details.....	3-24
3.6.7 Viewing UDE Values	3-24
3.6.8 Actions Allowed	3-25
3.6.9 Viewing Intermediary Summary Details.....	3-25
3.7 External UDE Values.....	3-26
3.7.1 Specifying External UDE Values	3-26
3.7.2 Actions Allowed	3-28
3.7.3 Viewing External UDE Summary	3-29
4. Setting up a Product	4-1
4.1 Introduction.....	4-1

4.2	Intermediary Product	4-1
4.2.1	Maintaining an Intermediary Product.....	4-1
4.2.2	Specifying Accounting Roles.....	4-3
4.2.3	Specifying Events	4-4
4.2.4	Specifying Product Preferences	4-6
4.2.5	Specifying Branch and Currency Restrictions	4-7
4.2.6	Specifying Module Product Restrictions	4-9
4.2.7	Specifying MIS Details.....	4-10
4.2.8	Actions Allowed	4-10
4.2.9	Viewing Product Summary	4-11
4.3	UDE Values	4-11
4.3.1	Specifying UDE Values	4-11
4.3.2	Actions Allowed	4-12
4.3.3	Viewing UDE Summary Details	4-13
5.	Operations	5-1
5.1	Introduction.....	5-1
5.2	Commission.....	5-1
5.2.1	Commission Processing	5-1
5.2.2	Settlement of Commission Between Intermediaries.....	5-3
5.2.3	Viewing Intermediary System Data Elements	5-3
5.2.4	Actions Allowed	5-4
5.2.5	Viewing SDE Summary	5-4
5.2.6	Viewing Calculated Commission	5-5
5.2.7	Actions Allowed	5-6
5.2.8	Viewing Commission Calculation Summary	5-7
5.3	Intermediary Commission.....	5-8
5.3.1	Liquidating Intermediary Commission Manually.....	5-8
5.3.2	Actions Allowed	5-9
5.3.3	Viewing Manual Liquidation Summary	5-10
6.	Annexure A – Accounting Entries and Advices	6-1
6.1	Introduction.....	6-1
6.2	Events.....	6-1
6.3	Accounting Roles.....	6-1
6.4	Amount Tags	6-1
6.5	Accounting Entries and Advices	6-2
6.5.1	Payment	6-2
6.5.2	Collection.....	6-2
6.6	Advice Format	6-3
6.6.1	INTER_CR_ADV	6-4
6.6.2	INTER_DR_ADV	6-4
6.6.3	INTER_STMT	6-4
7.	Function ID Glossary	7-1

1. Preface

1.1 Introduction

This manual is designed to help acquaint you with the Intermediary module of Oracle FLEXCUBE.

In addition to this User Manual, you can find answers to specific features and procedures, in the Online Help. It can be invoked by choosing Help Contents from the Help Menu of the software. You can further obtain information about to a particular field by placing the cursor on the relevant field and striking the <F1> key on the keyboard.

1.2 Audience

This manual is intended for the following User/User Roles:

Role	Function
Back office data entry clerk	Input functions for contracts
Back office managers/officers	Authorization functions
Product Managers	Product definition and authorization
End of Day operators	Processing during End of Day/ Beginning of Day
Financial Controller / Product Managers	Generation of reports

1.3 Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

1.4 Organization

This manual is organized into the following chapters:

Chapter	Description
Chapter 1	<i>About this Manual</i> gives information on the intended audience. It also lists the various chapters covered in this User Manual.
Chapter 2	<i>Intermediary - An Overview</i> gives a snapshot of the features that the module provides.
Chapter 3	<i>Generic Maintenance</i> discusses the details that need to be maintained in order to process transactions requiring intermediary services.
Chapter 4	<i>Setting up a Product</i> chapter talks about defining the attributes specific to setting up an intermediary product.
Chapter 5	<i>Operations</i> talks about commission calculation for intermediaries.

Chapter 6	<i>Annexure A – Accounting Entries and Advices</i> explains the types of accounting entries and advices generated for every event.
Chapter 7	<i>Function ID Glossary</i> has alphabetical listing of Function/Screen ID's used in the module with page references for quick navigation.

1.5 Related Documents

You may need to refer to any or all of the User Manuals while working on the Intermediary module:

- Core
- Procedures
- Settlements
- Interest
- User Defined
- Retail Lending
- Leasing
- Mortgages
- Islamic Financing

1.6 Glossary of Icons

This User Manual may refer to all or some of the following icons.

Icons	Function
	Exit
	Add row
	Delete row
	Option List

2. Intermediary - An Overview

2.1 Introduction

An intermediary is a third party who offers intermediation services between two trading parties. From a software application perspective, an intermediary acts as a middleware between the bank and the customer. The bank may also contract an intermediary to market its funds, thereby attracting the customers. Intermediaries can avail the commission from the bank on every successful loan created through them. An intermediary can be a single entity or a group. The banks can follow hierarchical structure to group multiple intermediaries. In case of multiple intermediaries, the commission earned should be shared with all intermediaries who are part of the same hierarchical structure up to the specified levels.

This manual explains the processing of intermediaries in Oracle FLEXCUBE. Using the Intermediary Service that Oracle FLEXCUBE provides, you can:

- Capture and maintain the Intermediary hierarchy structure
- Maintain commission plans and commission calculation for main loans and third party products such as insurances, warranty contracts, etc
- Pay commission to the intermediaries as the loan is disbursed
- Maintain charge backs in case of early pay-offs and defaults
- Generate Intermediary statements
- Capture and maintain periodic billing and accounting

You can process intermediaries in Oracle FLEXCUBE in the following manner:

- Maintain Intermediary details
- Maintain intermediary rules
- Maintain branch and currency restrictions
- Capture Intermediary account details

3. General Maintenance

3.1 Introduction

You need to maintain the following details in order to process transactions using intermediary services:

- Branch Parameters
- Intermediary System Data Element (SDE) Details
- Intermediary Rules
- Intermediary Group
- Intermediary Hierarchy
- External UDE Values

This chapter contains the following sections:

- [Section 3.2, "Branch Parameters"](#)
- [Section 3.3, "Intermediary SDE Details"](#)
- [Section 3.4, "Intermediary Rule"](#)
- [Section 3.5, "Intermediary Group"](#)
- [Section 3.6, "Intermediary Hierarchy Details"](#)
- [Section 3.7, "External UDE Values"](#)

3.2 Branch Parameters

This section contains the following topics:

- [Section 3.2.1, "Capturing Branch Parameters "](#)
- [Section 3.2.2, "Actions Allowed"](#)
- [Section 3.2.3, "Viewing Branch Parameters Summary"](#)

3.2.1 Capturing Branch Parameters

You can maintain branch-level parameters for all transaction involving the intermediary module, using the 'Intermediary Branch Parameters Maintenance' screen. You can invoke

this screen by typing 'INDBRMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Specify the following details.

Branch Code

Specify the branch code for which you are maintaining parameters. The adjoining option list displays all valid branch codes maintained in the system. You can select the appropriate one.

Branch Name

The system displays the branch name associated with the branch code.

Process Till

This specification determines the day on which automatic events such as accrual, liquidation etc. falling due on a holiday, should be processed. Indicate your preference by selecting the appropriate option. The available options here are:

- System Date - If you select this option, events will be scheduled as per the date irrespective of whether it is a holiday or not.
- Next Working Day -1 - If you select this option, events scheduled for a holiday will be processed on the last working day before the holiday.

Intermediary Daily Computation

Check this box to indicate that SDE calculation should happen daily for every intermediary.

Product Category for PC upload

Specify the product category to be used for Payments and Collections (PC) transaction upload. The adjoining option list displays all product categories maintained under the PC module. You can choose the appropriate one.

3.2.2 Actions Allowed

You can perform the following actions on a record:

- New
- Delete

- Unlock
- Save
- Auth (Authorise)
- Reverse
- Execute
- Query

Refer the Procedures User Manual for details about each action.

3.2.3 Viewing Branch Parameters Summary

You can view parameters maintained for every branch, using the 'Intermediary Branch Parameters Summary' screen. You can invoke this screen by typing 'INSBRMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You can query on records based on any or all of the following criteria:

- Authorization Status
- Record Status
- Branch Code
- Process Till

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Branch Code
- Process Till

3.3 Intermediary SDE Details

This section contains the following topics:

- [Section 3.3.1, "Capturing Intermediary SDE Details"](#)
- [Section 3.3.2, "Actions Allowed"](#)
- [Section 3.3.3, "Viewing SDE Summary Details"](#)


3.3.1 Capturing Intermediary SDE Details

The following System Data Elements (SDEs) are available in the system.

Element	Description	Calculation method
LOAN_COUNT	This SDE returns the total number of loans created by a particular Intermediary	Periodic
LOAN_DISBURSED_AMT	This SDE returns the sum of amount disbursed of all loans created by a particular Intermediary.	Periodic
LOAN_OVERDUE_AMT	This SDE returns the sum of all overdue amount i.e. sum of all overdue components i.e. PRINCIPAL, INTEREST etc. of all the loans created by a particular Intermediary.	As of date
LOAN_OVERDUE_PRINC	This SDE returns the sum of the overdue principal amount i.e. sum of PRINCIPAL of all the loans created by a particular Intermediary.	As of date
LOAN_OUTSTAND_PRINC	This SDE returns the sum of outstanding principal of all the loans created by a particular Intermediary.	As of date
LOAN_PREPAID_AMT	This SDE returns the sum of amount paid as pre-payment on all loans created by a particular Intermediary.	Periodic
LOAN_BOOKED_AMT	This SDE returns the sum of amount booked on all loans created by a particular Intermediary.	Periodic
LOAN_COLLECTED_AMT	This SDE returns the sum of amount collected by the Intermediary for the current cycle of liquidation. This is the actual amount collected and it excludes the amount paid and reversed in the current liquidation cycle.	Periodic
LOAN_COLL_REV_AMT	This SDE returns the sum of reversed amount, which was collected by the Intermediary for the previous cycle but was reversed in the current liquidation cycle.	Periodic
CASA_COUNT	This SDE returns the total number of CASA applications created by a particular intermediary for all the customers.	Periodic

CASA_MIN_BALANCE	The SDE returns the minimum balance required to be maintained for CASA applications created by a particular intermediary.	Periodic
ISLAMIC_CASA_MIN_BALANCE	The SDE returns the minimum balance required to be maintained for Islamic CASA applications created by a particular Intermediary.	Periodic
TD_COUNT	The SDE returns the count of Term deposit account referred by a particular Intermediary	Periodic
ISLAMIC_CASA_COUNT	The SDE returns the count of Islamic CASA account referred by a particular Intermediary.	As of date
ISLAMIC_TD_COUNT	The SDE returns the count of Islamic term deposit account referred by a particular intermediary	Periodic
TD_AMOUNT	The SDE returns the sum TD amount by a particular intermediary.	As of date
TD_PART_WITHDRAW	The SDE returns the sum of the amount withdrawn partially for TD by a particular intermediary	As of date
TD_ROLLOVER_AMOUNT	The SDE returns the sum of the rollover amount by a particular intermediary.	As of date
ISLAMIC_TD_AMOUNT	The SDE returns the sum of the Islamic TD amount by a particular Intermediary.	As of date
ISLAMIC_PART_WITHDRAW	The SDE returns the sum of the amount withdraw partially for Islamic TD by a particular intermediary.	As of date
ISLAMIC_TD_ROLLOVER_AMOUNT	The SDE returns the sum of the rollover amount by a particular Intermediary for Islamic TD	As of date

You can view details of each one of them in the 'Intermediary SDE Maintenance' screen. You can invoke this screen by typing 'INDSDEMT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



Here you can view the following details.

Element

The system displays a unique identification code for the System Data Element (SDE).

Description

The system displays a brief description for the System Data Element.

Calculation Method

The system displays the method that should be used for calculation purposes from the adjoining drop-down list. The options available are:

- Periodic - These SDEs will always aggregate data for an intermediary between the last settlement date and the next settlement date. The computation of all such SDEs will be based on the booking date.
- As of date - These SDEs will be the aggregated data as of that point in time.

3.3.2 Actions Allowed

You can perform the following actions on a record:

- Query

Refer the Procedures User Manual for details about each action.

3.3.3 Viewing SDE Summary Details

You can view all SDEs maintained for intermediaries in the 'Intermediary SDE Maintenance Summary' screen. You can invoke this screen by typing 'INSSDEMT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a web application window titled 'LBL_SDE_SUM'. At the top, there is a search bar with 'Advanced Search' and 'Reset' buttons. Below the search bar is a table with three columns: 'Element', 'Description', and 'Calculation Method'. The table is currently empty. To the left of the table, there is a 'Records per page' dropdown set to '15' and a '1 Of 1' indicator. At the bottom right of the window, there is an 'Exit' button.

You can query based on the SDE ID.

Click 'Search' button. The system identifies all records matching the criteria specified and displays the following details for each of them:

- Element
- Description
- Calculation Method

3.4 Intermediary Rule

This section contains the following topics:

- [Section 3.4.1, "Defining an Intermediary Rule"](#)
- [Section 3.4.2, "Capturing Rule Formula"](#)
- [Section 3.4.3, "Actions Allowed"](#)
- [Section 3.4.4, "Viewing Rule Summary Details"](#)

3.4.1 Defining an Intermediary Rule

An Intermediary Rule identifies the method to calculate commission payable to the Intermediary and Pre-Payment/Late Payment penalty charge to be recovered from the Intermediary. You can maintain such rules in the 'Intermediary Rule Maintenance' screen.

You can invoke this screen by typing 'INDRLMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Specify the following details.

Rule ID

Specify a unique rule identification code for the Intermediary rule you are creating.

Rule Description

Give a brief description for the rule ID.

Currency

Specify the currency in which the aggregation of total amount should be considered in the rule. The adjoining option list displays all valid currencies maintained in the system. You can choose the appropriate one.

Exchange Rate Type

Specify the rate type to be used for cross currency transactions. The adjoining option list displays all valid exchange rate types maintained in the system. You can choose the appropriate one.

Rule Type

Select the type of rule from the adjoining drop-down list. The options available here are:

- Payment
- Collection

This value determines the accounting set-up that needs to be done for the intermediary product.

Refer the chapter titled 'Setting up A Product' in this User Manual for details about product set-up.

SDE Details

You can specify the following details for SDEs.

SDE ID

Specify the System Data Elements ID to be included in the rule. The adjoining option list displays all valid SDE IDs available in the system. You can choose the appropriate one.

You can maintain multiple SDEs.

UDE ID

Specify the User Data Element ID to be included in the rule.

UDE Type

Select the type of the UDE from the adjoining drop-down list. The following options are available:

- Amount
- Rate
- Number

UDE Basis

Select the UDE basis from the adjoining drop-down list. The following options are available:

- Internal
- External

UDE Currency

Specify the UDE currency. The adjoining option list displays all valid currency codes maintained in the system. You can choose the appropriate one.

Note

You can specify the currency only if UDE type is 'Amount' and basis is 'External'.

You can maintain multiple UDEs.

3.4.2 Capturing Rule Formula

You can specify the formula for the rule using the 'Formula' screen. You can invoke this screen by clicking 'Formula' button in the 'Intermediary Rule Maintenance' screen.

The 'Formula' screen displays a table with the following columns: Line *, Condition, Result, and Condition. The first row contains a 'Condition' button in the last column. The screen also features a 'Go' button, a '1 Of 1' indicator, and 'Ok' and 'Exit' buttons at the bottom.

Specify the following details.

Line

Assign a unique sequence number/formula number for each condition. The conditions are evaluated based on this number.

Condition

Specify the condition for the rule.

Result

Specify the result of the condition being satisfied.

To define a condition, click on 'Condition' in the screen above. The following screen is displayed:

The 'Condition' screen displays several input fields and buttons. On the left, there are fields for 'Fields', 'Condition', 'Elements', 'Logical Operations', and 'Mathematical Operations'. On the right, there is an 'Operator' dropdown, a 'Value' field, and buttons for 'And', 'Or', 'Append', and 'Clear'. The screen also features 'Ok' and 'Exit' buttons at the bottom.

In this screen, you can use the elements, operators, and logical operators to build a condition.

Although you can define multiple expressions for a component, if a given condition is satisfied, subsequent conditions are not evaluated. Thus, depending on the condition of the expression that is satisfied, the corresponding formula result is picked up for component value computation. Therefore, you have the flexibility to define a computation logic for each component of the product.

3.4.3 Actions Allowed

You can perform the following actions on a record:

- New
- Delete
- Unlock
- Save
- Auth (Authorise)
- Reverse
- Execute
- Query

Refer the Procedures User Manual for details about each action.

3.4.4 Viewing Rule Summary Details

You can view details of all intermediary rules maintained in the system, using the 'Intermediary Rule Maintenance Summary' screen. You can invoke this screen by typing 'INSRLMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You can query based on the following criteria:

- Authorization Status
- Record Status
- Rule ID

Click 'Search' button. The system identifies all records matching the criteria specified and displays the following details for each of them:

- Authorization Status
- Record Status

- Rule ID
- Rule Description
- Rule Type

3.5 Intermediary Group

This section contains the following topics:

- [Section 3.5.1, "Maintaining Intermediary Group"](#)
- [Section 3.5.2, "Actions Allowed"](#)
- [Section 3.5.3, "Viewing Group Summary Details"](#)

3.5.1 Maintaining Intermediary Group

You can associate a set of intermediaries to a group and link the group to transactions. You can maintain such intermediary groups using the 'Intermediary Group Maintenance' screen. You can invoke this screen by typing 'INDGRPMT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a software window titled "Intermediary Group Maintenance". At the top, there is a menu bar with "New" and "Enter Query" options. Below the menu bar, there are two input fields: "Group Code *" (with a red asterisk indicating a required field) and "Group Description". The main body of the window is a large, empty white space. At the bottom, there is a dark blue footer area containing several labels: "Maker", "Checker", "Mod No", "Date Time:", "Record Status", and "Authorization Status". An "Exit" button is located in the bottom right corner of the footer area.

You can specify the following details:

Group Code

Specify a unique code to identify the group that you want to maintain.

Description

Specify a brief description for the group code.

3.5.2 Actions Allowed

You can perform the following actions on a record:

- New
- Delete
- Unlock

- Save
- Auth (Authorise)
- Reverse
- Execute
- Query

Refer the Procedures User Manual for details about each action.

3.5.3 Viewing Group Summary Details

You can view all the details of intermediary groups in the 'Intermediary Group Maintenance Summary' screen. You can invoke this screen by typing 'INSGRPMT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You can query based on the following criteria:

- Authorization Status
- Record Status
- Group Code

Click 'Search' button. The system identifies all records matching the criteria specified and displays the following details for each of them:

- Authorization Status
- Record Status
- Group Code

3.6 Intermediary Hierarchy Details

This section contains the following topics:

- [Section 3.6.1, "Maintaining Intermediary Hierarchy Details"](#)
- [Section 3.6.2, "Intermediary Tab"](#)
- [Section 3.6.3, "Settlement and Statement Tab"](#)
- [Section 3.6.4, "Products Tab"](#)
- [Section 3.6.5, "Capturing Events"](#)
- [Section 3.6.6, "Maintaining MIS Details"](#)

- [Section 3.6.7, "Viewing UDE Values"](#)
- [Section 3.6.8, "Actions Allowed"](#)
- [Section 3.6.9, "Viewing Intermediary Summary Details"](#)

3.6.1 **Maintaining Intermediary Hierarchy Details**

You can maintain intermediaries in Oracle FLEXCUBE. You can also create a hierarchy of intermediaries and specify commission processing share for each one in the hierarchy.

You can maintain such hierarchy details through the 'Intermediary Maintenance' screen. You can then link the intermediary to a loan. You can invoke this screen by typing 'INDINMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You should specify the following details in the above screen.

Intermediary Code

The system generates a unique numeric intermediary code for every intermediary as per the following mask:

NNNNNNNNNN

Where,

NNNNNNNNNN - Running sequence number

Intermediary Name

Specify the name of the Intermediary associated with the bank.

You can specify additional details for the intermediary in the following tabs:

- Intermediary
- Settlement and Statement
- Products

3.6.2 Intermediary Tab

The system displays this tab by default when you invoke this screen.

Intermediary Details

You can specify the following details.

Primary Contact

Specify the name of the person to be contacted from the intermediary.

Type

Indicate whether the intermediary is internal or external to your bank by selecting the one of the options from the adjoining drop-down list:

- Internal
- External

Branch Code

This field indicates the Home Branch of the intermediary. This value is defaulted based on the current logged-in branch.

Effective Date

The system displays the current system date.

Intermediary Category

Specify whether the Intermediary is a single entity or group of intermediaries. The options available here are:

- Individual
- Group

Group Code

If you have selected the category as 'Group', then you have to specify the group code to which the intermediary should belong. The adjoining option list displays all valid intermediary group codes maintained in the system. You can choose the appropriate one.

Parent Intermediary Code

In order to build a hierarchy of intermediaries, you need to specify the parent intermediary code. The adjoining option list displays all valid intermediary codes maintained in the system. You can choose the appropriate one.

The system will allow only intermediaries with the same home branch to be linked as parent intermediary.

Parent Intermediary Name

Based on the parent intermediary code, the system displays the corresponding intermediary name.

Intermediary Customer Number

Specify the customer number of the intermediary. You can choose the appropriate customer number from the adjoining option list. This list displays all valid and open accounts maintained in the system.

Address

Specify the address of the intermediary.

The system retrieves the address based on the customer number (CIF). However, you can change it.

ZIP

Specify the ZIP code of the address.

The system retrieves the ZIP code based on the customer number (CIF). However, you can change it.

Country

Specify the country in which intermediary resides. The adjoining option list displays all valid country codes maintained in the system. You can choose the appropriate one.

The system retrieves the country based on the customer number (CIF). However, you can change it.

Collection Agent

Check this box to indicate that the Intermediary can act as a collection agent.

Root Intermediary

Indicate whether the intermediary is at the root of the hierarchy or not by selecting one of the following options:

- Yes
- No

Liquidation Mode

Select the mode of liquidation for settlement of intermediary transactions from the adjoining drop-down list. The options available are:

- Automatic
- Manual

Minimum Amount for Liquidation

Specify the minimum amount required for primary commission liquidation. While processing transactions for the intermediary, if the calculated amount is less than the amount maintained here, it will not consider the amount for liquidation.

Intermediary Status

Indicate the status of the intermediary by choosing one of the following options from the adjoining drop-down list:

- Active
- Inactive

Cascade Child

Check this box to indicate that status of the parent should be applied to the child intermediaries. Once checked, if you change the status of a parent intermediary from active to inactive, the system will make all child intermediaries inactive. However, you can also leave the box unchecked. In such case, the status of parent intermediary will not be applied to the

child intermediaries. During hierarchy commission distribution, the system will stop processing on encountering the first inactive record.

Level Number

The system updates the level of the intermediary in the hierarchy on saving the record.

Cascade Till

Indicate the level until which the system should process hierarchy commission by choosing one of the following values from the adjoining drop-down list:

- Immediate - If you select this option, commission hierarchy will be processed only up to immediate parent.
- Root - If you select this option, commission hierarchy will be processed up to the root intermediary till the minimum hierarchy commission amount is reached.

Telephone

Specify the telephone number of the intermediary.

The system retrieves the telephone number based on the customer number (CIF). However, you can change it.

Mobile

Specify the mobile number of the intermediary.

The system retrieves the mobile number based on the customer number (CIF). However, you can change it.

Fax

Specify the facsimile (fax) number of the intermediary.

The system retrieves the fax number based on the customer number (CIF). However, you can change it.

E-Mail ID

Specify the e-mail ID of the intermediary.

The system retrieves the e-mail ID based on the customer number (CIF). However, you can change it.

3.6.3 Settlement and Statement Tab

Click 'Settlement and Statement' tab to capture details about settlement processing.

The screenshot shows the 'Intermediary Maintenance' window with the 'Settlement and Statement' tab selected. The window has a title bar with a diamond icon and standard window controls. Below the title bar are 'New' and 'Enter Query' buttons. The main area is divided into sections: 'Intermediary' (with fields for Intermediary Code and Intermediary Name), 'Settlement Details' (with fields for Settlement Currency, Settlement Mode, and Settlement Branch/Account), 'Statement Details' (with fields for Statement Frequency, Statement Frequency Unit, Statement Start Month, Statement Start Date, Last Statement Date, and Next Statement Date), 'Account' (with fields for Settlement Branch and Settlement Account), and 'External Account Details' (with fields for External Account Name, External Account Number, and External Bank Code). At the bottom, there are tabs for 'Events', 'MIS', and 'UDE Values'. The footer contains fields for Maker, Checker, Mod No, Date Time, Record Status, and Authorization Status, along with an 'Exit' button.

You can specify the following details.

Settlement Details

Specify the following details for settlement processing.

Settlement Currency

Specify the currency to be used for settlement processing. The adjoining option list displays all valid currency codes maintained in the system. You can select the appropriate one.

Settlement Mode

Indicate the settlement mode by choosing one of the following values from the adjoining drop-down list:

- CASA
- External

If you choose 'CASA', you will have to specify the settlement account under 'CASA' section. If you choose 'External', you will have to specify the settlement account for CASA as well as external account details under the 'External Account' section.

Statement Details

Specify the following details for statement generation.

Statement Frequency

Select the frequency at which statement should be generated for the intermediary, from the adjoining drop-down list. The following values are available:

- Daily
- Weekly
- Monthly
- Yearly

Statement Frequency Unit

Specify a numeric value to denote the unit of statement frequency. For example, if the frequency is daily and the unit is specified as '3', it will imply that statements should be generated every 3 days.

Statement Start Month

From the adjoining drop-down list, select the month from which statement generation should begin if you have chosen the frequency as 'Monthly' or 'Yearly'.

Statement Start Date

Specify the date from which the statement generation should begin based on the given frequency, using the adjoining calendar.

Last Statement Date

The system displays the date of last statement generation.

Next Statement Date

Based on the statement generation parameters, the system arrives at the next statement date and displays it here.

CASA

If settlement needs to be done using an internal account (CASA), you need to specify the following details.

Settlement Branch

Specify the branch code where the settlement needs to be done. The adjoining option list displays all valid branch codes maintained in the system. You can select the appropriate one.

Settlement Account

Specify the account from which settlement needs to be done. The adjoining option list displays all valid accounts available for the CIF. You can select the appropriate one.

Input to this field is mandatory for both CASA and External modes of settlement.

External Account

If settlement needs to be done using an external account, you need to specify the following details.

External Account Name

Specify the name of the external account.

External Account Number

Specify the external account number.

External Bank Code

Specify the bank code to which the external account belongs. The adjoining option list displays all valid bank codes maintained in the system. You can select the appropriate one.

3.6.4 Products Tab

Click 'Products' tab to capture details about products under which the intermediary can transact.

The screenshot shows the 'Intermediary Maintenance' window with the 'Products' tab selected. The window has a title bar with a diamond icon and standard window controls. Below the title bar are 'New' and 'Enter Query' buttons. There are input fields for 'Intermediary Code' and 'Intermediary Name'. The 'Products' tab is highlighted in the tab bar, which also includes 'Intermediary' and 'Settlement and Statement' tabs. Below the tabs, there are two main sections: 'Product Details' and 'UDE Details'. Each section has a table with columns and a 'Go' button. The 'Product Details' table has columns: Product Code, Product Description, Last Settlement Date, Last Processing Date, Next Processing Date, and Hierarch. The 'UDE Details' table has columns: Rule Id, User Defined Element Id, and UDE Value. At the bottom of the window, there is a status bar with labels for 'Events', 'MIS', and 'UDE Values'. Below this, there are labels for 'Maker', 'Checker', 'Mod No', 'Date Time:', 'Record Status', and 'Authorization Status'. An 'Exit' button is located in the bottom right corner.

Product Code	Product Description	Last Settlement Date	Last Processing Date	Next Processing Date	Hierarch

Rule Id	User Defined Element Id	UDE Value

Events | MIS | UDE Values

Maker
Checker
Mod No

Date Time:
Date Time:
Record Status
Authorization Status

Exit

Specify the following details:

Product Code

Specify the intermediary product in which the intermediary can transact. The adjoining option list displays all open and authorized intermediary products maintained in the system. You can choose the appropriate one.

You can link multiple products to the intermediary.

Product Description

The system displays a brief description of the product.

Last Settlement Date

The system displays the last settlement date for the product.

Last Processing Date

The system displays the last processing date for the product.

Next Processing Date

The system displays the next settlement date for the product based on the settlement frequency.

Hierarchy Commission Percentage

Specify the commission that the intermediary should get in terms of a percentage of the transaction amount.

Minimum Hierarchy Commission

Specify the minimum amount that should be granted as commission.

UDE Details

The system displays all rules linked to the product. You can specify the UDE values for them.

Rule ID

The system displays the rules that are linked to the product.

UDE ID

The system displays the UDE ID associated with the rule.

UDE Value

Specify the value for the UDE IDs.

3.6.5 Capturing Events


Click 'Events' button in the 'Intermediary Maintenance' screen and invoke the 'Events' screen.

The screenshot shows a software window titled "Events". Inside, there's a section labeled "Event Details" which contains a table. The table has three columns: "Event Number", "Event Code", and "Event Date". Below the column headers, there is a single row with three empty input fields. Above the table, there are navigation controls showing "1 Of 1" and a "Go" button. At the bottom of the window, there is a status bar with the text "Messages | Accounting Entries" and an "Exit" button.

Here you can view the following details:

- Event Number
- Event Code
- Event Date

Click 'Messages' button and invoke the 'Messages' screen to view the messages generated for the intermediary.



The screenshot shows a window titled 'Messages' with a sub-header 'Advice Details'. Below the header is a navigation bar with '1 Of 1' and a 'Go' button. A table with five columns is displayed: 'Event Number', 'Message Type', 'Party Id', 'Suppress', and 'Priority'. The table contains one row of data. An 'Exit' button is located at the bottom right of the window.

Event Number	Message Type	Party Id	Suppress	Priority

Here you can view the following details:

- Event Number
- Message Type
- Party ID
- Suppress
- Priority

Click 'Accounting Entries' button and invoke the 'Accounting Entries' screen to view accounting entries posted for transactions of the intermediary.

View Details

Reference Number* Event

☐ See Position Entries

Accounting Entries

Event	Branch	Account	Dr/Cr	Amount Tag	Currency	Foreign Currency Amount	Rate	Local Currency

Overrides

Overrides

Here you can view the following details:

- Branch Code
- Account Number
- D/C
- Local Currency
- Local Ccy Amount
- Exchange Rate
- Foreign Ccy Amount
- Date
- Value date
- Amount Tag
- Code

Maintaining MIS Details

Click 'MIS' button in the 'Intermediary Maintenance' screen and invoke the 'Management Information System' screen.

Management Information System

Branch

Account

MIS Group

Default MIS Group

☐ Link to Group

Rate Code

Calc Method

Rate Type

Spread

☒ Pool Code

☐ Account Level

Pool Code

Reference Rate

Transaction MIS Codes

Address 2

Cost Code

Composite MIS Codes

Address 3

Change Log

Transfer Log

Ok

Exit

Refer the User Manual on MIS for further details.

3.6.7 Viewing UDE Values

Click 'UDE Values' button in the 'Intermediary Maintenance' screen to invoke the 'UDE Values' screen. You can view values for all UDEs applicable to the Intermediary in this screen. Note that you will be able to invoke this screen only in the Query mode. In all other cases, this button will be disabled.

The screenshot shows a window titled "UDE Values". Inside, there is a section labeled "UDE Details" which contains a table. The table has three columns: "Rule Id", "User Defined Element Id", and "UDE Value". There is one row of data in the table. The "Rule Id" column contains the value "1". The "User Defined Element Id" and "UDE Value" columns are empty. The table is part of a larger interface that includes navigation controls at the top and an "Exit" button at the bottom right.

Rule Id	User Defined Element Id	UDE Value
1		

Here you can view the following details:

- Rule ID
- UDE ID
- UDE Value

3.6.8 Actions Allowed

You can perform the following actions on a record:

- New
- Delete
- Unlock
- Save
- Auth (Authorise)
- Reverse
- Execute
- Query

Refer the Procedures User Manual for details about each action.

3.6.9 Viewing Intermediary Summary Details

You can view details of all intermediaries in the 'Intermediary Maintenance Summary' screen. You can invoke this screen by typing 'INSINMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a web application window titled "Intermediary Maintenance Summary". At the top, there are "Advanced Search" and "Reset" buttons. Below this, there are two columns of search filters. The left column includes "Authorization Status", "Intermediary Code", "Intermediary Status", and "Primary Contact". The right column includes "Record Status", "Intermediary Name", "Parent Intermediary Code", and "Intermediary Category". Each filter has a corresponding input field with a dropdown arrow or a search icon. Below the filters, there is a table with columns: "Authorization Status", "Record Status", "Intermediary Code", "Intermediary Name", "Intermediary Status", and "Parent Intermediary Code". The table is currently empty. At the bottom right of the window, there is an "Exit" button.

You can query on records based on any or all of the following criteria:

- Authorization Status
- Record Status
- Intermediary Code
- Intermediary Name
- Intermediary Status
- Parent Intermediary Code

- Primary Contact
- Intermediary Category

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Intermediary Code
- Intermediary Name
- Intermediary Status
- Parent Intermediary Code
- Primary Contact
- Intermediary Category

3.7 External UDE Values

This section contains the following topics:

- [Section 3.7.1, "Specifying External UDE Values"](#)
- [Section 3.7.2, "Actions Allowed"](#)
- [Section 3.7.3, "Viewing External UDE Summary "](#)

3.7.1 Specifying External UDE Values

You may need to capture data from external systems for computation of intermediary commission. You can capture such data in the 'External UDE Values Maintenance' screen.

You can invoke this screen by typing 'INDUEMT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

External UDE Values Maintenance

New Enter Query

Intermediary Code

UDE Effective Date

Product Details

1 Of 1

Product Code	Product Description

UDE Details

1 Of 1

Rule Id	User Defined Element Id	UDE Currency	UDE Type	UDE Value

Maker Date Time:
Checker Date Time:
Mod No Record Status
Authorization Status

Exit

Specify the following details.

Intermediary Code

Specify the intermediary code for which you want to capture external UDE values. The adjoining option list displays all valid intermediary codes maintained in the system. You can choose the appropriate one.

UDE Effective Date

Specify the date from which the UDE should be effective.

Product Details

You can link products to the intermediary code.

Product Code

Specify the intermediary product code for which you want to capture external UDE values. The adjoining option list displays all valid intermediary product codes maintained in the system. You can choose the appropriate one.

Product Description

The system displays a brief description of the product.

UDE Details

The system displays all rules linked to the specified product code.

Rule ID

The system displays all rules linked to the product.

UDE ID

Specify the external UDE ID that you want to attach to the rule. The adjoining option list displays all valid UDEs maintained in the system. You can select the appropriate one.

UDE Currency

The system displays the UDE currency based on the UDE ID. However you can change it. The adjoining option list displays all valid currency codes maintained in the system. You can choose the appropriate one.

UDE Type

The system displays the UDE type based on the UDE ID. However you can change it. Select the type of the UDE from the adjoining drop-down list. The options available here are:

- Number
- Rate
- Amount

UDE Value

Specify the external UDE value. At the time of processing, the system checks the UDE value for the corresponding product maintained in this screen for the maximum effective date falling between the last liquidation date and the calculation date. If no value is maintained in this screen, the UDE value will be considered as '0'.

3.7.2 Actions Allowed

You can perform the following actions on a record:

- New
- Delete
- Unlock
- Save
- Auth (Authorise)
- Reverse
- Execute
- Query

Refer the Procedures User Manual for details about each action.

3.7.3 Viewing External UDE Summary

You can view details of all external UDEs through 'External UDE Value Maintenance Summary' screen. You can invoke this screen by typing 'INSUDEMT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

External UDE Values Maintenance Summary

Advanced Search Reset

Authorization Status Record Status

Intermediary Code UDE Effective Date

Records per page 15 1 Of 1 Go

☐	Authorization Status	Record Status	Intermediary Code	UDE Effective Date
☐				
☐				
☐				
☐				
☐				

Exit

You can query on records based on any or all of the following criteria:

- Authorization Status
- Record Status
- Intermediary Code
- UDE Effective Date

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Intermediary Code
- UDE Effective Date

4. Setting up a Product

4.1 Introduction

You can maintain a product and define specific attributes like rules for processing intermediary commission and also define settlement frequency for the same. This product in turn can be linked to an intermediary.

This chapter contains the following sections:

- [Section 4.2, "Intermediary Product"](#)
- [Section 4.3, "UDE Values"](#)

4.2 Intermediary Product

This section contains the following topics:

- [Section 4.2.1, "Maintaining an Intermediary Product"](#)
- [Section 4.2.2, "Specifying Accounting Roles"](#)
- [Section 4.2.3, "Specifying Events "](#)
- [Section 4.2.4, "Specifying Product Preferences"](#)
- [Section 4.2.5, "Specifying Branch and Currency Restrictions"](#)
- [Section 4.2.6, "Specifying Module Product Restrictions"](#)
- [Section 4.2.7, "Specifying MIS Details"](#)
- [Section 4.2.8, "Actions Allowed"](#)
- [Section 4.2.9, "Viewing Product Summary"](#)

4.2.1 Maintaining an Intermediary Product

You can maintain a product and link it to lending transactions requiring an intermediary. You can maintain an intermediary product using the 'Intermediary Product' screen. You can invoke

this screen by typing 'INDPRMNT ' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You can specify the following details:

Intermediary Product Code

Specify a unique code to identify the intermediary product.

Product Description

Specify a brief description for the intermediary product.

Start Date

Specify the date from which this product will be available, using the adjoining calendar.

End Date

Specify the date until which this product will be available, using the adjoining calendar.

Remarks

You can enter some information about the product which is internal to the bank. This will not be printed on any correspondence with the intermediary.

You can maintain additional details for the product by clicking the following buttons on the screen.

Buttons	Description
Accounting Roles	Click this button to define the accounting role to accounting head mapping.
Events	Click this button to select the events for the product and then maintain event-wise accounting entries and advices.
Preferences	Click this button to define preferences like tenor, Prepayment option etc.

Restrictions	Click this button to maintain the list of allowed/ disallowed branches and currencies for the product.
Module Product	Click this button to maintain the list of allowed/ disallowed customers/ customer categories.
MIS	Click this button to capture MIS related parameters.

4.2.2 Specifying Accounting Roles

Click 'Accounting Roles' button to maintain accounting roles for the product.

The screenshot shows the 'Accounting Roles' window. It includes input fields for 'Product Code', 'Product Description', 'Class Code', and 'Class Description'. A 'Default From Class' button is located to the right of the 'Class Details' section. Below this is a table titled 'Roles' with columns: 'Accounting Role', 'Role Description', 'Account Head', and 'GL Description'. The table currently shows one row with empty fields. Navigation controls for the table are visible above the first row. At the bottom right of the window are 'Ok' and 'Exit' buttons.

Refer the chapter titled 'Product Definition' in the Products User Manual under Modularity for details about role definition.

4.2.3 Specifying Events

Click 'Events' button and invoke the 'Events' screen to maintain events for the product.

The screenshot shows the 'Events' screen with the following components:

- Product Code** and **Product Description** input fields.
- Class Details** section containing **Class Code** and **Class Description** input fields.
- Event Details** section containing a table with columns **Event Code *** and **Description**.
- Default From Class** button.
- Accounting Entries | Advices** status bar.
- Ok** and **Exit** buttons.

Here you can specify events that should occur in the lifecycle of transactions linked to the product.

4.2.3.1 Specifying Accounting Entries

Click 'Accounting Entries' button in the 'Events' screen and invoke the 'Accounting Entries' screen to maintain event-wise accounting entries.

Accounting Entries

Event Code Event Description

Accounting Entries Details

1 Of 1

☐	Accounting Role *	Amount Tag *	Dr/Cr *	Transaction Code *	Netting	MIS Head	Profit GL
☐			Debit		No		

Ok Exit

4.2.3.2 Specifying Advices

Click 'Advices' button in the 'Product Event Accounting Entries Maintenance' screen and invoke the 'Advices' screen to maintain event-wise advices.

Advices

Event Code Description

Advices Details

1 Of 1

☐	Advice Name *	Description	Generation Time	Suppress	Priority	Charges
☐			Authorize	No	High	☐

Ok Exit

All suggested accounting entries are listed in the chapter titled 'Annexure A – Accounting entries and Advices' of this User Manual.

Refer to the 'Product Definition' User Manual under Modularity for details about events, accounting entries and advices.

4.2.4 Specifying Product Preferences

Click 'Preferences' button and invoke the Intermediary Product 'Preferences' screen to maintain generic attributes of the product.

The screenshot shows a 'Preferences' window with three main sections: Settlement Details, Charge Details, and Rule Details. The Settlement Details section includes fields for Settlement Frequency (dropdown), Settlement Frequency Unit (dropdown), Settlement Start Month (dropdown), and Settlement Start Date (text). The Charge Details section includes fields for Charge Back Unit (dropdown) and Charge Back Period (text). The Rule Details section shows a table with columns for Rule Id and Rule Description, and a 'Go' button. The window has 'Ok' and 'Exit' buttons at the bottom right.

Rule Id	Rule Description

Specify the following details:

Settlement Details

You can capture the following settlement details.

Settlement Frequency

Select the frequency for settlement of payment from the adjoining drop-down list. The options available here are:

- Daily
- Weekly
- Monthly
- Yearly

Settlement Frequency Unit

Specify a numeric value to denote the unit of settlement frequency. For example, if the frequency is daily and the unit is specified as '3', it will imply that payments should be scheduled every 3 days.

Settlement Start Month

Select the month from which settlement should begin if you have chosen the frequency as 'Monthly' or 'Yearly'.

Settlement Start Date

Specify the date from which the settlement should begin based on the given frequency, using the adjoining calendar.

Charge Back Unit

Select the unit for calculation of pre-payment penalty period from the adjoining drop-down list. The options available here are:

- Daily
- Weekly

- Monthly
- Yearly

If the requirement is to consider all pre-payments, the penalty period can be maintained as null and penalty unit should be left blank. In this case, the system will consider all pre-payments.

Charge Back Period

Specify the period within which if prepayment is done a loan, then pre-payment penalty should be charged from the Intermediary. This indicates the duration from the date of the first loan disbursement. During this period, if any pre-payment is done, then pre-payment charges will be levied on the Intermediary.

Rule Details

You can link rules to the product.

Rule ID

Specify the rule that should be linked to the product. The adjoining option list displays all intermediary rules maintained in the system. You can select the appropriate one.

Rule Description

Based on the rule ID, the system displays a brief description of the rule.

4.2.5 Specifying Branch and Currency Restrictions

You can maintain a list of branches and currencies that should be allowed or disallowed for all transactions under the product. You can specify such restrictions using the 'Branch and Currency Restrictions' screen. You can invoke this screen by clicking 'Restrictions' button in the 'Intermediary Product' screen.

The screenshot shows a software window titled "Branch and Currency Restrictions". At the top, there are input fields for "Product Code" and "Product Description". Below these, there are two sets of radio buttons: "Branch To be Considered for Computation" and "Currency To be Considered for Computation", each with "Allowed" and "Disallowed" options. The "Allowed" option is selected for both. Below the radio buttons are two tables. The "Branch Restrictions" table has columns "Branch Code" and "Branch Description". The "Currency Restrictions" table has columns "Currency Code" and "Currency Description". Both tables are currently empty. At the bottom right of the window are "Ok" and "Exit" buttons.

Specify the following details.

Product Code and Description

The system displays the product code and description.

Branch To Be Considered for Computation

Indicate whether you want to create a list of allowed branches or disallowed branches by selecting one of the following options:

- Allowed
- Disallowed

Currency To Be Considered for Computation

Indicate whether you want to create a list of allowed currencies or disallowed currencies by selecting one of the following options:

- Allowed
- Disallowed

Branch Restriction

Depending on whether you have opted to create an 'Allowed' or 'Disallowed' list, you can specify the branches to be included in the list.

Branch Code

Specify the branch code that should be included in the 'Allowed' or 'Disallowed' list. The adjoining option list displays all valid branch codes maintained in the system. You can select the appropriate one.

Branch Description

Based on the branch code, the system displays a brief description of the branch.

You can maintain multiple branches in the list.

Currency Restrictions

Depending on whether you have opted to create an 'Allowed' or 'Disallowed' list, you can specify the currencies to be included in the list.

Currency Code

Specify the currency code that should be included in the 'Allowed' or 'Disallowed' list. The adjoining option list displays all valid currency codes maintained in the system. You can select the appropriate one.

Currency Description

Based on the currency code, the system displays a brief description of the currency.

You can maintain multiple currencies in the list.

4.2.6 Specifying Module Product Restrictions

Click 'Module Product' button in the 'Intermediary Product' screen and invoke the 'Module Products Restriction' screen. You can maintain a list of products (from other modules) that should be allowed or disallowed for all transactions under this product.

The screenshot shows a software window titled "Module Products Restrictions". It contains the following elements:

- Product Code** and **Product Description** input fields.
- Loans To be Considered for Computation** section with two radio buttons: **Allowed** (selected) and **Disallowed**.
- A table titled **Module Products Restrictions** with two columns: **Product Code** and **Product Description**. The table currently has one row with empty input fields.
- Navigation controls above the table: "1 Of 1" and "Go" button.
- Ok** and **Exit** buttons at the bottom right.

Specify the following details.

Product Code and Description

The system displays the product code and description.

Loans To Be Considered for Computation

Indicate whether you want to create a list of allowed loans or disallowed loans by selecting one of the following options:

- Allowed
- Disallowed

Module Products Restrictions

Depending on whether you have opted to create an 'Allowed' or 'Disallowed' list, you can specify the loan products to be included in the list.

Product Code

Specify the product code that should be included in the 'Allowed' or 'Disallowed' list. The adjoining option list displays all valid product codes maintained in the system for the following modules:

- Retail Lending
- Mortgages
- Leasing

You can select the appropriate one.

Product Description

Based on the product code, the system displays a brief description of the product.

You can maintain multiple products in the list.

4.2.7 Specifying MIS Details

Click 'MIS' button to maintain MIS details.

The screenshot shows the 'MIS Details' window. At the top, there are input fields for 'Product Code', 'MIS Group', and 'Pool Code'. To the right of these is a button labeled 'Default From MIS Group'. Below these fields is a section titled 'MIS Classes' which contains a table with two columns: 'MIS Class' and 'MIS Code'. The table has a header row and one data row. To the right of the table is a section labeled '- Cost Code' with a vertical list of five input fields. At the bottom right of the window are 'Ok' and 'Exit' buttons.

Refer the Management Information System User Manual under Modularity for further details.

4.2.8 Actions Allowed

You can perform the following actions on a record:

- New
- Delete
- Unlock
- Save
- Auth (Authorise)
- Reverse
- Execute
- Query

Refer the Procedures User Manual for details about each action.

4.2.9 Viewing Product Summary

You can view summary details of all products using the 'Intermediary Product Summary' screen. You can invoke this screen by typing 'INSPRMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Intermediary Product Summary

Advanced Search Reset

Authorization Status Record Status

Intermediary Product Code Settlement Frequency

Charge Back Unit

Records per page 15 1 Of 1

	Authorization Status	Record Status	Intermediary Product Code	Settlement Frequency	Charge Back Unit
☐					
☐					
☐					
☐					
☐					
☐					

Exit

You can query on records based on any or all of the following criteria:

- Authorization Status
- Record Status
- Intermediary Product Code
- Settlement Frequency
- Charge Back Unit

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Intermediary Product Code
- Settlement Frequency
- Charge Back Unit

4.3 UDE Values

This section contains the following topics:

- [Section 4.3.1, "Specifying UDE Values"](#)
- [Section 4.3.2, "Actions Allowed"](#)
- [Section 4.3.3, "Viewing UDE Summary Details"](#)

4.3.1 Specifying UDE Values

As you can recall, you can link rules to a product. A rule consists of System Data Elements and the User Data Elements. You can maintain the values for the UDEs defined for the rule in the 'Internal UDE Value Maintenance' screen. You can invoke this screen by typing

'INDIUDVM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a web application window titled "Internal UDE Value Maintenance". At the top, there is a toolbar with a "New" button and an "Enter Query" button. Below the toolbar is a search field labeled "Product Code *". Underneath the search field is a pagination bar showing "1 Of 1" and a "Go" button. Below the pagination bar is a table with three columns: "Rule Id *", "User Defined Element Id *", and "UDE Value". The table has one row with empty input fields. At the bottom of the window is a dark blue footer area containing labels for "Maker", "Checker", "Mod No", "Date Time:", "Record Status", and "Authorization Status". There is also an "Exit" button in the bottom right corner.

Specify the following details:

Product Code

Specify the Intermediary product code for which you want to maintain UDE values.

Rule ID

The system displays all intermediary rules linked to the product.

UDE ID

The system displays the UDE ID linked to the rule.

UDE Value

Specify the value for the applicable UDE IDs.

4.3.2 Actions Allowed

You can perform the following actions on a record:

- New
- Delete
- Unlock
- Save
- Auth (Authorise)
- Reverse
- Execute
- Query

Refer the Procedures User Manual for details about each action.

4.3.3 Viewing UDE Summary Details

You can view summary details of all UDE values in the 'Internal UDE Value Maintenance Summary' screen. You can invoke this screen by typing 'INSIUDVM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Internal UDE Value Maintenance Summary

Advanced Search Reset

Authorization Status Record Status

Product Code

Records per page 15 1 Of 1

	Authorization Status	Record Status	Product Code
☐			
☐			
☐			
☐			
☐			
☐			
☐			

Exit

You can query on records based on any or all of the following criteria:

- Authorization Status
- Record Status
- Product Code

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Product Code

5. Operations

5.1 Introduction

You can process commission payment/charge collection at defined frequency level for every intermediary based on the transactions. You can also pay commission/collect charge to/from the intermediary at a pre-defined frequency specified for every intermediary product. Hierarchy distribution of the commission is done based on the hierarchy percentage maintained at intermediary product level.

After settlement is done, the system generates an intermediary statement based on the product maintenance displaying details of computation and the settlement amount.

This chapter explains the processing for computing commission.\

This chapter contains the following sections

- [Section 5.2, "Commission"](#)
- [Section 5.3, "Intermediary Commission"](#)

5.2 Commission

This section contains the following topics:

- [Section 5.2.1, "Commission Processing"](#)
- [Section 5.2.2, "Settlement of Commission Between Intermediaries"](#)
- [Section 5.2.3, "Viewing Intermediary System Data Elements"](#)
- [Section 5.2.4, "Actions Allowed"](#)
- [Section 5.2.5, "Viewing SDE Summary "](#)
- [Section 5.2.6, "Viewing Calculated Commission"](#)
- [Section 5.2.7, "Actions Allowed"](#)
- [Section 5.2.8, "Viewing Commission Calculation Summary"](#)

5.2.1 Commission Processing

As part of the End of Day (EOD) processing, the system computes System Data Elements (SDEs) for the Intermediaries across products. Calculation of SDEs is done for intermediaries based on the branch-level parameter 'Daily SDE Computation'. If the branch parameter is checked, the system will do daily computation of SDEs for all intermediaries irrespective of whether the settlement is due on application date or not. If it is not checked, the system will compute SDEs only if settlement processing is due on the said date.

Consider the following example:

Assume a transaction with the following details:

- SDE - LOAN_DISBURSED_AMT
- Batch Processing Date - 01 February, 2009
- Last Settlement Date for the intermediary product - 01 January, 2009

The batch will calculate the total amount disbursed for the intermediary between last settlement date, i.e 01 January, 2009 and processing date i.e. 01 February, 2009. This

amount will be used for computation of the SDE and then logged into a data store for processing.

Subsequent to SDE calculation, the system does the following:

- Calculation of amount for all the rules for the product (say INP1)
 - Assume the following figure is calculated rule-wise:
RUL1: 200 (Commission)
RUL2: 100 (Charge/Penalty)
- Netting the amount across all the rules
 - For above scenario, the accounting should be as under

RUL1

Accounting Role	Amount Tag	Debit/Credit
Expense	200	Dr
Intermediary	200	Cr

RUL2

Accounting Role	Amount Tag	Debit/Credit
Intermediary	100	Dr
Income	100	Cr

In the above scenario, netting will be done as under:

Accounting Role	Amount Tag	Debit/Credit
Expense	200	Dr
Income	100	Cr
Intermediary	100	Cr

- Processing settlement with the intermediary based on netted amount
 - The system posts settlement entries as per the netted. The settlement with the intermediary is based on the intermediary set-up. If CASA is the settlement mode maintained for the intermediary, settlement will happen using the CASA maintained. If External Account is the settlement mode maintained, then settlement will happen using a PC transaction.


The system performs the following validations:

- For every product-intermediary combination, a liquidation reference number is generated. The sequence is based on the product code. The entries are passed when the INLQ event defined at the product level is triggered.
- If the settlement mode of the intermediary is CASA, settlement will be processed with the CASA (both debit/credit). The corresponding debit/credit advice will get generated for the intermediary based on the product set-up and the netted amount. If the netted amount to the intermediary is a credit, credit advice will get generated. If the netted amount is a debit, debit advice will get generated.
- If the settlement mode of the intermediary is 'External Account', the system will check for the following:

- If the transaction is a credit to the intermediary, settlement will get processed using a PC transaction based on the maintenance at intermediary level and the category maintained at the intermediary branch level.
- If the transaction is a debit to the intermediary, settlement will get processed using the settlement account/branch maintained for the intermediary.

5.2.2 Settlement of Commission Between Intermediaries

Oracle FLEXCUBE supports commission settlement between intermediaries in a hierarchical way. The system computes the hierarchy amount payable to the parent intermediary for each intermediary based on the intermediary maintenance. The following diagram illustrates the hierarchical structure that can be maintained for intermediaries.



The computation happens till the level specified at the intermediary level. If the level is immediate, calculation will happen only till the immediate parent level; otherwise it will happen till the root level. This computation will happen product-wise for the intermediary.

5.2.3 Viewing Intermediary System Data Elements

For a given product, you can view all SDE values for the current liquidation cycle, through the 'Intermediary SDE View' screen. You can invoke this screen by typing 'INDSDVAL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Here you can capture the following details.

Product Code

Specify the product for which you want to view SDEs. The adjoining option list displays all valid Intermediary products maintained in the system. You can select the appropriate one.

Intermediary Code

Specify the Intermediary code for which you want to view SDEs. The adjoining option list displays all valid Intermediary codes maintained in the system. You can select the appropriate one.

5.2.4 Actions Allowed

You can perform the following action on a record:

- Query

Refer the Procedures User Manual for details about each action.

5.2.5 Viewing SDE Summary

You can view a summary of all SDEs for different product-intermediary combinations, through the 'Intermediary SDE View Summary' screen. You can invoke this screen by typing 'INSSDVAL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Intermediary SDE View Summary

Advanced Search Reset

Product Code Intermediary Code

Rule Id

Records per page 15 1 Of 1

	Product Code	Intermediary Code	Rule Id
☐			
☐			
☐			
☐			
☐			
☐			
☐			

Exit

You can query based on all or any of the following criteria:

- Product Code
- Intermediary Code

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Product Code
- Intermediary Code
- SDE
- SDE Value

5.2.6 Viewing Calculated Commission

You can view all the accounts considered for commission/charge calculation across intermediary products for a given execution date, using the 'Intermediary Calculation View' screen. You can invoke this screen by typing 'INDIVIEW' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Intermediary Calculation View

New Enter Query

Product Code *
Intermediary Code *
Branch Code *
Reference Number *
Event Code *
Execution Date *
Rule Id *
Manual Execution Date

Amount
Currency
SDE Id
SDE Value
Settlement Branch
Settlement Account
Hierarchy Commission Processed

1 Of 1 Go

Account Number *	Branch Code *	Customer	Book Date	Module Code

Exit

Specify the following details.

Product Code

Specify the intermediary product code for which you want to view commission calculation.

Intermediary Code

Specify the intermediary code for which you want to view commission calculation.

Branch Code

Specify the branch code under which transactions should be considered for commission calculation view.

Reference Number

Specify the contract reference number for which you want to view commission calculation.

Event Code

Specify the event code for which you want to view commission calculation.

Execution Date

Specify the date of automatic transaction execution based on which you want to view commission calculation.

Rule ID

Specify the intermediary rule based on which you want to view commission calculation.

Manual Execution Date

Specify the date of manual transaction execution based on which you want to view commission calculation.

Amount

Specify the transaction amount based on which you want to view commission calculation.

Currency

Specify the transaction currency based on which you want to view commission calculation.

SDE ID

Specify the SDE ID based on which you want to view commission calculation.

SDE Value

Specify the SDE value based on which you want to view commission calculation.

Settlement Branch

Specify the settlement branch code based on which you want to view commission calculation.

Settlement Account

Specify the settlement account based on which you want to view commission calculation.

Hierarchy Commission Processed

Indicate the hierarchy commission processing status by choosing one of the following options from the adjoining drop-down list:

- Yes
- No

Click Single View icon. This screen displays the following details of accounts considered for commission calculation:

- Reference Number
- Branch Code
- Customer ID
- Book Date
- Module Code

5.2.7 Actions Allowed

You can perform the following action on a record:

- Query

Refer the Procedures User Manual for details about each action.

5.2.8 Viewing Commission Calculation Summary

You can view summary of all commission calculation through the 'Intermediary Calculation View Summary' screen. You can invoke this screen by typing 'INSIVIEW' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Intermediary Calculation View Summary

Advanced Search Reset

Product Code Intermediary Code
Branch Code Reference Number
Event Code Execution Date
Rule Id

Records per page 15 1 Of 1 Go

☐	Product Code	Intermediary Code	Branch Code	Reference Number	Event Code	Execution Date	Rule Id	Hie
☐								
☐								
☐								
☐								
☐								
☐								

Exit

You can query on records based on any or all of the following criteria:

- Product Code
- Branch Code
- Event Code
- Rule ID
- Intermediary Code
- Reference Number
- Execution Date

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Product Code
- Branch Code
- Event Code
- Rule ID
- Intermediary Code
- Reference Number
- Execution Date
- Rule ID
- Hierarchy Commission Processed
- Amount
- Currency
- SDE ID
- SDE Value
- Settlement Branch

- Settlement Account

5.3 Intermediary Commission

This section contains the following topics:

- [Section 5.3.1, "Liquidating Intermediary Commission Manually"](#)
- [Section 5.3.2, "Actions Allowed"](#)
- [Section 5.3.3, "Viewing Manual Liquidation Summary"](#)

5.3.1 Liquidating Intermediary Commission Manually

As mentioned before, commission calculation and liquidation can be automated as part of the EOD batch. However, you can also manually liquidate commission or charge for the failed settlements in the batch, through the 'Intermediary Manual Liquidation' screen. You can invoke this screen by typing 'INDMPMCL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Specify the following details.

Product Code

Specify the intermediary product code for which you want to liquidate commission. The adjoining option list displays all valid product codes maintained in the system. You can select the appropriate one.

Rule ID

Specify the intermediary rule based on which you want to liquidate commission. The adjoining option list displays all valid rule IDs maintained in the system. You can select the appropriate one.

Intermediary Code

Specify the intermediary code for which you want to liquidate commission. The adjoining option list displays all valid intermediary codes maintained in the system. You can select the appropriate one.

Branch Code

The system displays the current logged-in branch code.

Reference Number

Specify the contract reference number for which you want to view liquidate commission. The adjoining option list displays all transactions linked to the intermediary. You can select the appropriate one.

Event Code

Specify the event code for which you want to liquidate commission.

Execution Date

Specify the date of automatic transaction execution based on which you want to liquidate commission, using the adjoining calendar.

Amount

Specify the commission amount that you want to liquidate.

Currency

Specify the currency based on which you want to liquidate commission.

SDE ID

Specify the SDE ID based on which you want to liquidate commission.

SDE Value

Specify the SDE value based on which you want to liquidate commission.

Settlement Branch

Specify the settlement branch code based on which you want to liquidate commission.

Settlement Account

Specify the settlement account based on which you want to liquidate commission.

Manual Execution Date

Specify the date of manual transaction execution based on which you want to liquidate commission, using the adjoining calendar.

Click Single View icon. This screen displays the following details of accounts considered for commission liquidation:

- Reference Number
- Branch Code
- Customer ID
- Book Date
- Module Code

5.3.2 Actions Allowed

You can perform the following actions on a record:

- New
- Delete
- Unlock
- Save
- Auth (Authorise)
- Reverse

- Execute
- Query

Refer the Procedures User Manual for details about each action.

5.3.3 Viewing Manual Liquidation Summary

You can view summary of all manual liquidations through the 'Intermediary Manual Liquidation Summary' screen. You can invoke this screen by typing 'INSMPMCL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You can query based on all or any of the following criteria:

- Authorized
- Branch Code
- Rule ID
- Execution Date
- Product Code
- Intermediary Code
- Event Code
- Reference Number

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorized
- Product Code
- Branch Code
- Intermediary Code
- Rule ID
- Event Code
- Execution Date
- Reference Number

6. Annexure A – Accounting Entries and Advices

6.1 Introduction

This section contains details of the suggested accounting entries that can be set up for the Intermediary module of Oracle FLEXCUBE. The details of the suggested accounting entries are given event-wise.

This chapter contains the following sections:

- [Section 6.2, "Events"](#)
- [Section 6.3, "Accounting Roles"](#)
- [Section 6.4, "Amount Tags"](#)
- [Section 6.5, "Accounting Entries and Advices"](#)
- [Section 6.6, "Advice Format"](#)

6.2 Events

You can link the following events to an Intermediary product.

Event Code	Event Description
INLQ	Intermediary Liquidation
INHL	Intermediary Hierarchy Liquidation
IMST	Intermediary Statement

6.3 Accounting Roles

The following accounting roles are available in the module.

Accounting Role	Role Description
EXPENSE	Expense GL
REC_INTER	Receiving Intermediary
PAY_INTER	Paying Intermediary
INCOME	Income GL

6.4 Amount Tags

The following amount tags are available in the module.

Amount Tag	Tag Description
<RULEID>_INTERPAY_AMT	Amount paid to the Intermediary
INTERHIE_AMT	Amount for hierarchy-wise settlement

6.5 Accounting Entries and Advices

You can set up accounting entries for the following types of products:

- Payment
- Collection

This section contains the following topics:

- [Section 6.5.1, "Payment"](#)
- [Section 6.5.2, "Collection"](#)

6.5.1 Payment

For a product linked to payment type of rule, you can maintain the following accounting entries.

6.5.1.1 Accounting Entries

INLQ – Intermediary Liquidation

Dr/Cr	Accounting Role	Amount Tag
Dr	EXPENSE	<RULEID>_INTERPAY_AMT
Cr	REC_INTER	<RULEID>_INTERPAY_AMT

6.5.1.2 Advices

You can link the following advices to the events.

Event	Message Name	Description
INLQ	IN_INTER_CR	Credit Advice
INLQ	IN_INTER_DR	Debit Advice
IMST	IN_INTER_STMT	Intermediary Statement

The advices will address the primary intermediary.

6.5.2 Collection

For a product linked to collection type of rule, you can maintain the following accounting entries.

6.5.2.1 Accounting Entries

INLQ – Intermediary Liquidation

Dr/Cr Indicator	Accounting Role	Amount Tag
Dr	PAY_INTER	<RULEID>_INTERPAY_AMT
Cr	INCOME	<RULEID>_INTERPAY_AMT
Cr	REC_INTER	<RULEID>_INTERPAY_AMT
Dr	EXPENSE	<RULEID>_INTERPAY_AMT

INHL – Intermediary Hierarchy Liquidation

Dr/Cr Indicator	Accounting Role	Amount Tag
Dr	PAY_INTER	INTERHIE_AMT
Cr	REC_INTER	INTERHIE_AMT

Rule ID will be replaced with actual Rule ID while processing the entries.

6.5.2.2 Advices

You can link the following advices to the events.

Event	Message Name	Description
INLQ	IN_INTER_CR	Credit Advice
INLQ	IN_INTER_DR	Debit Advice
IMST	IN_INTER_STMT	Intermediary Statement

The advices will address the primary intermediary.

If settlement mode for intermediary is CASA for both debit and credit, the settlement details will be picked up from the settlement account maintenance for the intermediary.

If settlement mode for intermediary is 'External Account', the credits will be handled using the external account by triggering a PC transaction. Debits to intermediary will be handled using the settlement account details maintained for the intermediary.

6.6 Advice Format

You can maintain the following advice formats using the 'Advice Format' screen:

- INTER_CR_ADV (for credit advice)
- INTER_DR_ADV (for debit advice)
- INTER_STMT (for intermediary statement)

This section contains the following topics:

- [Section 6.6.1, "INTER_CR_ADV "](#)
- [Section 6.6.2, "INTER_DR_ADV "](#)
- [Section 6.6.3, "INTER_STMT "](#)

6.6.1 INTER_CR_ADV

You can capture the following details in this format:

- Date
- Intermediary Code
- Intermediary Name
- Address
- Intermediary Customer Id
- Value Date
- Amount
- Currency
- Credit Account

6.6.2 INTER_DR_ADV

You can capture the following details in this format:

- Date
- Intermediary Code
- Intermediary Name
- Address
- Intermediary Customer Id
- Value Date
- Amount
- Currency
- Debit Account

6.6.3 INTER_STMT

You can capture the following details in this format:

- Date
- Statement Period
- Intermediary Code
- Intermediary Name
- Address
- Intermediary Customer id
- Transaction Date
- Transaction Details
- Amount
- Currency
- Debit/Credit
- Settlement account

7. Function ID Glossary

I

INDBRMNT	3-2	INDUDEMNT	3-27
INDGRPMT	3-12	INSBRMNT	3-3
INDINMNT	3-14	INSGRPMT	3-13
INDIUDVM	4-12	INSINMNT	3-25
INDIVIEW	5-5	INSIUDVM	4-13
INDMPMCL	5-8	INSIVIEW	5-7
INDPRMNT	4-2	INSMPMCL	5-10
INDRLMNT	3-8	INSPRMNT	4-11
INDSDEMNT	3-6	INSRLMNT	3-11
INDSDVAL	5-3	INSSDEMNT	3-7
		INSSDVAL	5-4
		INSUDEMNT	3-29