Open Development Tool Installation Oracle FLEXCUBE Universal Banking Release 12.1.0.0.0



Table of Contents

1.	OP	EN DEVELOPMENT TOOL INSTALLATION	1-1
		INTRODUCTION INSTALLING OPEN DEVELOPMENT TOOL	
2.	SET	TTING UP DATABASE FOR OPEN DEVELOPMENT TOOL	1-7
3.	OP	EN DEVELOPMENT TOOL (ODT) APPLICATION FULL DEPLOYMENT	1-1
4.	DE	VELOPMENT TOOL (ODT) APPLICATION FULL DEPLOYMENT	1-9



1. Open Development Tool Installation

1.1 Introduction

This document explains about the creation of .war file using ODT (Open Development Tool) and setting up database for ODT installation.

1.2 Installing Open Development Tool

To install ODT, follow the steps given below:

Soracle FLEXCUBE Universal Installer 12.0.2.0	
Oracle FLEXCUBE Universal Banking	ORACLE
Welcome To Oracle FLEXCUBE Select the option for installation P- T Oracle FLEXCUBE	
Orlader EbroopE Oniversal Banking Solution Orlader EbroopE Orlader Eb	
 Switch Interface for Gateway Installation 	
Log Back	Next Exit

- 2. Click 'Open Development Tool'.
- 3. Click 'Next'. The following screen is displayed.



Stracle FLEXCUBE Ur	iversal Installer	
Oracle FLEXC	UBE Universal Banking	ORACLE
Welcome To Oracl Choose Oracle FLE	e FLEXCUBE XCUBE Component for installation.	
Build Application Database Deploy Application		
Operating System	Linux	
Application Server	Weblogic 👻	
DataBase Server	Oracle	
Log	Ba	ck Next Exit

- 4. Select 'Build Application' as Oracle FLEXCUBE component for installation.
- 5. Specify the following details.

Operating System

Specify the operating system in which you are installing Oracle FLEXCUBE.

Application Server

Specify the application server on which you are installing Oracle FLEXCUBE.



Oracle FLEXCUBE Un	iversal Installer			
Oracle FLEXC	UBE Universal Banking	ORACLE		
Build Process Current screen provides an option to enter application jndi names and logger path				
ODT JNDI	jdbc/ODT12_2			
Logger Path	/ODT/logs			
PROVIDER_URL	t3://10.10.10.10:0101			
Log	Back	Next Exit		

7. Specify the following details.

ODT JNDI

Specify the JNDI for the ODT.

Logger Path

Specify the path where the logs have to be written.

Provider_URL

Specify the provider URL.



Solution of the second	ersal Installer	
Oracle FLEXCU	3E Universal Banking	ORACLE
Build Process Specify the source and c	destination directories, application name	
	Multiple Sources	
Source Directory	D:\INSTALLATIONDIRECTORY	
Destination Directory	D:\DESTTEMPDIR	
Application Name	RAD	
Log	Back	Next Exit

Source Directory

Specify the source directory. You can use the directory icon to browse to the source directory location. The source directory must contain src, ToolWeb folders. If the required folders are not present, then the error message is displayed.

Check the box 'Multiple Sources' to use multiple source directories.

Destination Directory

Specify the destination directory. You can use the directory icon to browse to the source directory location.

Application Name

Specify the desired name for the application. For example,: RAD.

9. Click 'Next. The following screen is displayed.

Multiple Sources

In case of Cluster/Patch releases, you can get the files from multiple source directories. If you check this box, the installer will not allow you to specify the source directory in this screen. On clicking 'Next', the following screen is displayed.



실 Oracle FLEX	CUBE Universal Installer		
Oracle F	LEXCUBE Universal Banking		ORACLE
Build Proces			
Current scree	en provides an option to enter mutilple source path		
SI No	Source Path	Sele	ect
1			▲
2			
3			=
4			
5			
6			
7			
8			
-		<u> </u>	
Log	Ba	ck 1	Next Exit

You can select all the source directories in this screen. The Installer will copy the sources from the multiple locations into the destination directory. You can have consolidated sources in the destination directory.

Source FLEXCUBE Universal Installer	
Oracle FLEXCUBE Universal Banking	ORACLE
Build Process Current screen displays the status of copying and building of the sources	
0%	
Copy Build Log Back	Next Exit

- 11. Click 'Copy' button to copy sources to the destination location.
- Click 'Build' button to build the war file in the destination location.
 The system displays the following screen when the copying is complete.



Source FLEXCUBE Universal Installer	
Oracle FLEXCUBE Universal Banking	ORACLE
Build Process	
Current screen displays the status of copying and building of the sources	
100%	
Copying from D:\ODT_SOURCES\FE Copying RAD Sources Copying src folder 70 java Files copied Copying ToolWeb folder 3 xml Files copied 1 xsd Files copied 63 JS Files copied 117 jsp Files copied	
Copy Build Log Back	Next Exit

13. The system displays the following screen when the building is complete.

Soracle FLEXCUBE Universal Installer	
Oracle FLEXCUBE Universal Banking	ORACLE
Build Process	
Current screen displays the status of copying and building of the sources	
100%	
Copying jars into D:\JUNK/201303271617/FCJRADTool/Build/War	^
Compilation started	
Sources compiled successfully	=
RAD.war File built successfully in the path D:JUNK/201303271617/FCJRADTool_Deploy	
	-
Copy Build	
Log Back	Next Exit



2. Setting up Database for Open Development Tool

To set up database for Open Development Tool (ODT), follow the steps given below:

14. Run 'FCUBSInstaller.bat' batch file to launch Oracle FLEXCUBE Universal Banking Solution Installer.

15. Click 'Next', the following screen will be displayed.

Source FLEXCUBE Universal Installer 12.0.2.0	
Oracle FLEXCUBE Universal Banking	ORACLE
Welcome To Oracle FLEXCUBE Select the option for installation	
 Oracle FLEXCUBE Universal Banking Solution General Ledger Enterprise Limits & Collateral Open Development Tool Gateway Switch Interface for Gateway Installation Utilities 	
Log Back	Next Exit

- 16. Click 'Open Development Tool'.
- 17. Click 'Next'. The following screen is displayed.



Oracle FLEXCUBE Un	iversal Installer		
Oracle FLEXC	UBE Universal Banking		ORACLE
Welcome To Oracle	FLEXCUBE		
Choose Oracle FLE	XCUBE Component for installation		
Build Application			
Database			
Operating System	Linux		
Application Server	Weblogic 🗸		
DataBase Server	Oracle 🗸		
Log		Back	lext Exit

18. Select 'Database' as Oracle FLEXCUBE component for installation.

19. Specify the following details.

Operating System

Specify the operating system in which you are installing Oracle FLEXCUBE.

Database Server

Specify the database server on which you are installing Oracle FLEXCUBE.



Gracle FLEXCUBE Univ	ersal Installer	
Oracle FLEXCU	BE Universal Banking	ORACLE
Database Installation Specify source and de	stination path.	
Source Directory Destination Directory	Consolidated Multiple Sources D:\INSTALLATIONDIRECTORY D:\DESTTEMPDIR	
Log	Bac	k Next Exit

21. Specify the following source and destination directory details.

Source Directory

Specify the source directory location. The source directory should have the 'rad_ddl.sql' and other corresponding packages. You can use the directory icon to browse to the source directory location.

Destination Directory

Specify the destination directory. You can use the directory icon to browse to the source directory location.

Consolidated

Check this box to indicate a consolidated installation.

If you need to compile a single patch into the database, then you can leave this box unchecked and specify the source directory of the patch in the 'Source Directory' field.

Multiple Sources

In case of Cluster/Patch releases, you can get the files from multiple source directories. If you check this box, the installer will not allow you to specify the source directory in this screen.

22. Click 'Next' button, if' Multiple Sources' is selected, the following screen will be dispalyed.



4	Oracle F	EEXCUBE Universal Installer					
	Oracl	e FLEXCUBE Universal Bankin	g	ORACLE			
ſ	Database Installation						
Current screen provides an option to enter mutilple source path							
	SI No	Source Path	Consolidated	Select			
	1	D:/MULTIPLESrc/11.3.0					
	2	D:/MULTIPLESrc/11.3.3					
	3	D:/MULTIPLESrc/11.3.4					
	4						
	5						
	6						
	Log		Back	Next Exit			

23. Specify the source directories. You can use the directory icon to browse to the source directory location.

The Installer will copy the sources from the multiple locations into the destination directory.

24. Click 'Next'. The following screen is displayed.

Soracle FLEXCUBE Universal Installer	
Oracle FLEXCUBE Universal Banking	ORACLE'
Database Installation Current screen Displays the status of Object sources being copied.	
0%	
Сору	
Log Back	Next Exit

25. Click 'Copy' to copy the source from source directory to the destination directory. Once the source is copied, the following screen is displayed.



Soracle FLEXCUBE Universal Installer	
Oracle FLEXCUBE Universal Banking	ORACLE
Database Installation	
Current screen Displays the status of Object sources being copied.	
100%	
DB Copy Started DB copy completed	
Copy Log Back	Next Exit

26. Click 'Next'. The following screen is displayed.

Database Installation Provide schema details.					
Name	Value				
Username	installer				
Password	•••••				
Service Name	testdb				
IP Address	10.10.10.10				
Port	1521				
TNS Connect Descriptor	testdb.world				

27. Specify the following schema details:

User Name

Specify the user name to access the schema.



Password

Specify the schema password for the above user name.

Service Name

Specify service name of database.

TNS Connect Descriptor

Specify a valid connect string that contains the details for database connectivity.

IP Address

Specify the IP address of the system where the database schema is installed.

Port

Specify the port number.

28. Once you have specified the details, click 'Test Connection' button to test the database schema connection.

Message		×
i	Connection successful	
	ОК	

The above message is displayed if the connection is established sucessfully.



🛓 Oracle FLEXCUBE Universal Insta	ller						
Oracle FLEXCUBE Universal Banking ORACL							
Database Installation Current screen Displays the status of the ODT DDLobjects being comp							
0%							
Object Type	Current Count	Release	Count				
TYPE	225	0					
TABLE	5764	0					
SEQUENCE	311	0					
Load ODT DDL ODT I	DDL Log						
Log		Back	Next Exit				

30. Click 'Load ODT DDL' button to start compiling.

The objects 'Type', 'Table', and 'Sequence' will be compiled and the count will be updated. You can verify the DDL objects compilation by comparing the current count and the release count. The release count is the number of files in the temporary folder to which the files are copied.

Oracle FLEXCUBE Universal In:	staller				
Oracle FLEXCUBE Universal Banking					
Database Installation Current screen Displays the status of the ODT DDLobjects being c 100%					
Object Type	Current Count	Release	Count		
ТҮРЕ	0	0			
TABLE	76	76			
SEQUENCE	5	5			
Load ODT DDL	T DDL Log				
Log		Back	Next Exit		

- 31. Click on ODT DDL log to see the log.
- 32. Click 'Next'. The following screen is displayed.



Database Installation Current screen Displays the status of the ODT App objects being c					
Current screen Disp	plays the status of the	0%	bjects being c		
Objec	ct Type	Include	Current Count	Release Count	
FUNCTION		~	0	0	
PROCEDURE		V	0	0	
VIEW		r	0	0	
TRIGGER		v	0	0	
PACKAGE		V	0	0	
PACKAGE BODY		V	0	0	

33. In the 'Include' column, check this box to indicate the object you need to load.

34. Click 'Load ODT Objects' button to compile APP objects. The installer loads the functions, procedures, views, triggers and packages as per your selection and compiles them.

You can verify the application objects compilation by comparing the count shown in this screen with the release count.

- 35. Click 'ODT Objects Log' to view the log. The log file 'LoadODTObj.log' will be available in the destination directory under the folder 'DBLogs'.
- 36. Click 'Next'. The following screen is displayed.



Current screen Displays the number of invalids in the DB. 0%				
Object Type	Invalid Count	Total Count]	
FUNCTION	17	160	1	
PROCEDURE	27	176	1	
VIEW	78	2717	1	
TRIGGER	124	396	1	
PACKAGE	1579	9858	1	
PACKAGE BODY	7232	9511	1	

- 37. Click 'Invalids List' button to view the count of invalid objects in the database. You can view the file 'InvalidList.txt' created by the installer in the destination directory under the folder 'DBLogs'.
- 38. Click 'Recompile' to re-compile any invalid objects If present. This reduces the invalid object count.

The Installer allows 'Recompile' multiple times in order to reduce the invalid objects count.

The following screen is displayed on successful re-compilation of ODT Objects.

Current screen Displays the number of invalids in the DB. 100%					
Object Type	Invalid Count	Total Count			
FUNCTION	0	0			
PROCEDURE	0	4			
VIEW	0	0			
TRIGGER	0	0			
PACKAGE	0	56			
PACKAGE BODY	0	56			
ACKAGE BODY	0	56			

The database is set up for the ODT installation.



3. Open development Tool (ODT) Application Full Deployment

- 39. Launch Oracle FLEXCUBE Universal Banking Solution Installer.
- 40. Click on 'Next' to display the screen below.

S Oracle FLEXCUBE Universal Installer	
Oracle FLEXCUBE Investor Servicing	ORACLE
Welcome To Oracle FLEXCUBE Choose Oracle FLEXCUBE Application to be installed. P-]
Open Development Tool Gateway	
 Switch Interface Installation 	
Log	Next Exit

- 41. Select 'Open Development Tool'.
- 42. Click 'Next' to display the screen below.

실 Oracle FLEXCUBE Universal						
Oracle FLEXCUBE	Universal Banking		ORACLE			
Welcome To Oracle FLEXC	UBE					
Choose Oracle FLEXCUBE Component for installation.						
Property File						
Database						
Build Application						
Deploy Application						
Release	KERNEL					
Server's Operating System	Windows -					
Application Server	Weblogic 👻					
DataBase Server	Oracle 👻					
Log		Back	Next Exit			

43. Select 'Deploy Application'.

Release

Select the release in which you are installing the FCUBS application. Select the appropriate one from the adjoining drop-down list.

Server's Operating System

Select the server's operating system in which you are installing the FCUBS application. Select the appropriate one from the adjoining drop-down list.

Application Server

Select 'Weblogic' from the adjoining drop down list.

Database Server

Select the database server in which you are installing the FCUBS application. Select the appropriate one from the adjoining drop-down list.

44. WeblogicClick 'Next' to display the screen below.

🙆 Oracle FLEXCUBE Universal Installer				
Oracle FLEXCUBE Univer	ORACLE			
Application Deployment Provide server details for connecting to the server.				
Name	Value			
Admin IP	10.10.10.10			
Admin Port	1111			
Admin Username	<user_name></user_name>			
Server Admin Password	•••••			
	Test Connection			
Type of Deployment	Full Deployment			
Log	Back	Next Exit		

45. Specify the following details:

Admin IP

By default it will display local host and user can not edit it.

Admin Port

Specify port number of weblogic server.

Admin UserName

Specify the appropriate admin username of the weblogic application server.

Admin Password

Specify the appropriate admin password of the weblogic application server.

Type of Deployment

Select 'Full Deployment'.

46. Click 'Test Connection' to test the connection with the application server. On successful connection, the following message will be displayed.



47. Click 'OK' and click 'Next' to display the screen below.

🙆 Oracle FLEXCUBE Universal Installer			- • ×
Oracle FLEXCUBE Universal Banking			ORACLE
Application deployme Provide the Application	nt n Details For the Deployment of EAR		
EAR Path	/Please use the browse button/		
Property File Path			
Application Name			
Application Context			
	Mange Resources		
Log		Back	Next Exit

48. Specify the following details

EAR Path

Select the application EAR to be deployed using the browse button.

The Application EAR path cannot be copied and pasted on to the text box, thereby demanding the use of the browse button to the select the EAR.

Property File Path

If the property file is internal to the application EAR, it gets displayed here on selection of EAR path. If the property file is external, specify the location. You can use the directory button to browser and select the directory.

Application Name

Application name gets displayed on selection of EAR path.

Application Context

Application context gets displayed on selection of EAR path.

Manage Resources

Check this box if resources are to be created along with deployment.

49. Click on 'Next' to display the screen below.

ORACLE
pyment
Resource Type
DataSource
Back Next Exit
oyment Resource Type DataSource

The current screen shows a list and type of resources that are created..

Oracle FLEXCUBE Universal Installer Oracle FLEXCUBE Universal Banking ORAC				
Applicat	ion deployment			
Please se	elect the resource and update the details			
Resource				
S.No.	Property Name	Property Value		
1	DataSource Driver	oracle.jdbc.OracleDriver		-
2	DataSource Type	NXA		
3	Schema UserName	abc		
4	Schema PAssword	•••		=
5	IP Address	10.184.86.27		
6	Port Number	1522		
7	Service Name	avast1		
8	Initial Capacity 15			-
Test Connection Save Changes Modify JDBC url				
Log Back Next Exit				

51. Specify the following details

Resource ID

Select the data source needs to get created from the adjoining drop down list.

DataSource Driver

Specify the JDBC driver URL with which the connection is established. Ex: oracle.jdbc.OracleDriver for Non-XA datasources

DataSource Type

Specify the type of datasource that is to be created, XA or Non-XA.

Schema Username

Specify the username of the schema to which the connection is established.

Schema Paasword

Specify the password of the schema.

IP Address:

Specify to provide the host address of the schema.

Port Number

Specify the port number of schema.

Service Name

Specify the schema name.

Initial Capacity

The number of physical connections to create when creating the connection pool in the data source

Maximum Capacity

The maximum number of physical connections that this connection pool can contain.

Capacity Increment

The increment by which this JDBC connection pool's capacity is expanded.

Shrink Frequency

The number of seconds to wait before shrinking a connection pool that has incrementally increased to meet demand.

Connection Reserve Timeout

The number of seconds after which a call to reserve a connection from the connection pool will timeout.

- 52. Click 'Save Changes' to save the values provided In the table against corresponding value of Resource ID.
- 53. Click 'Test Connection' to try to establish connection with required details provided in the table.
- 54. Click on 'Next' to get the following screen.

Modify JDBC URL

- 55. Select 'Modify JDBC URL' for editing the generated URL.
- 56. If 'Modify JDBC URL' is selected, on click of 'Next', the following screen will be displayed.

Gracle FLEXCUBE Universal Installer	
Oracle FLEXCUBE Universal Banking	ORACLE [.]
JDBC Url JDBC url to get connected to the Application server Resource ID ODT_DATASOURCE	
jdbc:oracle:thin:@10.184.86.152:1522:avast1	
Log	Back Next Exit

57. Click 'Next', the following screen will be displayed.

실 Oracl	e FLEXCU	BE Universal Installer		- • •
Ora	cle FLE	ORACLE		
		Deployment ivironment details for deployment		
Domaiı	n Name	Default_domain	Get D	etails
S.No.		Server Name		Deploy
1	AdminSe	erver		
2	Manage			
3	ClusterT	est		
4	AVAST			
Log		Back		Next Exit

- 58. The Domain Name shows the weblogic domains name.
- 59. Click 'Get Details', the list of available servers are displayed in the table. Atleast one server should be selected to proceed to next screen.
- 60. Click 'Next' to display the screen below.

🛃 Oracle FLEXCUBE Universal Installer		
Oracle FLEXCUBE Universal Banking	ORACLE	
Application Full Deployment		
Current screen Displays the status of Applications being deployed.		
Start Deployment Undeploy		
Log	Next Exit	

61. Click 'Start Deployment' to begin the process of application deployment.

On successful deployment, you will get the following message and the screen is expected to look like below.

Message	
i	Application FCUBSApp123 deployed successfully
	ОК

62. Click 'OK' and the following screen is displayed:

🛃 Oracle FLEXCUBE Universal Installer	- • ×	
Oracle FLEXCUBE Universal Banking	ORACLE	
Application Full Deployment Current screen Displays the status of Applications being deployed.		
Application FCUBSApp123 deployed successfully. Start Deployment Undeploy		
Log	Next Exit	

63. If the deployment is not successfull, the 'Undeploy' button will be enabled.

Soracle FLEXCUBE Universal Installer	
Oracle FLEXCUBE Universal Banking	ORACLE
Application Partial Deployment Current screen Displays the status of Applications being dep	ployed.
Start Deployment Undeploy	•
Log	Back Next Exit

64. Click 'Undeploy' for undeploying the partially deployed EAR from the server.

4. Development Tool (ODT) Application Full Deployment

65. Launch Oracle FLEXCUBE Universal Banking Solution Installer.

66. Click on 'Next' to display the screen below.

Source FLEXCUBE Universal Installer 12.0.3	
Oracle FLEXCUBE Universal Banking	ORACLE
Welcome To Oracle FLEXCUBE Choose Oracle FLEXCUBE Application to be installed.	
← ☐ Utilities	
Log Back	Next Exit

- 67. Select 'Open Development Tool'.
- 68. Click 'Next' to display the screen below.

Source FLEXCUBE Universal Installer 12.0.3				
Oracle FLEXCUBE Universal Banking			ORACLE	
Welcome To Oracle		actallation		
Choose Oracle FLE	CUBE Component for i	nstallation.		
Build Application Database				
Deploy Application				
Operating System	Windows 👻			
Application Server	Websphere 💌			
DataBase Server	Oracle 💌			
Log			Back N	lext Exit

- 69. Select 'Deploy Application'.
- 70. Specify the following details:

Operating System

Select the server's operating system in which you are installing the FCUBS application. Select the appropriate one from the adjoining drop-down list.

Application Server

Select 'Websphere' from the adjoining drop down list.

Database Server

Select the database server in which you are installing the FCUBS application. Select the appropriate one from the adjoining drop-down list.

SelectSelectWebsphere

71. Click on 'Next' to display the screen below.

Oracle FLEXCUBE Universal Ins	taller 12.0.3	
Oracle FLEXCUBE U	niversal Banking	ORACLE
Application Deployment		
Provide server details for conne	ecting to the server.	
Name	Value	
Admin IP	Not Applicable	
Admin Port	Not Applicable	
Admin Username	websphere	
Admin Password	•••••	
	Test Connection	
Type of Deployment	Full Deployment	
Log	Back	Next Exit

72. Specify the following details:

Admin IP

Not applicable.

Admin Port

Not applicable.

Admin UserName

Specify the appropriate admin username of the websphere application server.

Admin Password

Specify the appropriate admin password of the websphere application server.

Type of Deployment

Select 'Full Deployment'.

73. Click on 'Test Connection' to test the connection with the application server. On successful connection, the following message will be displayed.

Message		x
i	Connection successful	
	ОК	

74. Click on 'OK' and click on 'Next' to display the screen below.

🛃 Oracle FLEXCUBE Unit	versal Installer 12.0.3		• X
Oracle FLEXCL	JBE Universal Banking		ACLE.
Application deployment Provide the Application	nt Details For the Deployment of EAR		
WAR Path	/Please use the browse button/		
Property File Path			
Application Name			
Application Context			
	Mange Resources		
Log	Back	Next	Exit

75. Specify the following details:

WAR Path

Select the application WAR to be deployed using the browse button.

The Application WAR path cannot be copied and pasted on to the text box, thereby demanding the use of the browse button to the select the WAR.

Property File Path

If the property file is internal to the application EAR, it gets displayed here on selection of EAR path. If the property file is external, specify the location. You can use the directory button to browser and select the directory..

Application Name

Application name gets displayed on selection of EAR path.

Application Context.

Application context gets displayed on selection of EAR path.

Manage Resources

Not Applicable for websphere application server.

76. Click 'Next' to display the screen below.

Source FLEXCUBE Universal Installer	12.0.3		
Oracle FLEXCUBE Unive	rsal Banking		ORACLE
Application deployment			
Provide the Application Details For th	e Deployment of EAR		
Application Name		Get	Details
Status			
Cell Name			
Node Name			
Target Type	Server	-	
Server Name			
Cluster Name			
	1]	
Log		Back	Next Exit

77. Specify the following details:

Application Name

Not applicable for application full deployment.

Status

Not applicable for application full deployment.

Cell Name

Specify the appropriate cell name.

Node Name

Specify the appropriate node name.

Target Type

Select the appropriate target type.

Server Name

Specify the appropriate server name if the selected target type is 'Server'.

Cluster Name

Specify the appropriate cluster name if the selected target type is 'Cluster'.

The values fed in the above screen are not validated at the screen level as a result of a limitation and hence, Specify accurate information.

78. Click 'Next' to display the screen below.

🛃 Oracle FLEXCUBE Universal Installer	
Oracle FLEXCUBE Universal Banking	ORACLE
Application Full Deployment Current screen Displays the status of Applications being deployed.	
Start Deployment	
Log Back	Next Exit

- 79. Click 'Start Deployment' to begin the process of application deployment.
- 80. On successful deployment, you will get the following message is displayed:.



81. Click 'OK' and following screen is displayed:

🛃 Oracle FLEXCUBE Universal Installer	- • •
Oracle FLEXCUBE Universal Banking	ORACLE
Application Full Deployment Current screen Displays the status of Applications being deployed.	
Application FCUBSApp123 deployed successfully.	
Start Deployment	
Log	Next Exit



Open Development Tool Installation [September] [2015] Version 12.1.0.00

Oracle Financial Services Software Limited Oracle Park Off Western Express Highway Goregaon (East) Mumbai, Maharashtra 400 063 India

Worldwide Inquiries: Phone: +91 22 6718 3000 Fax:+91 22 6718 3001 www.oracle.com/financialservices/

Copyright © 2007, 2015, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing. This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing. This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products.