

FCIS Property File Setup
Oracle FLEXCUBE Investor Servicing
Release 12.3.0.0.0
[September] [2016]



Table of Contents

1.	CREATING PROPERTY FILE FOR ORACLE FLEXCUBE INVESTOR SERVICING	1-1
1.1	INTRODUCTION	1-1
1.2	CREATING PROPERTY FILE	1-1
1.2.1	Setting Oracle FLEXCUBE Investor Servicing Plug-ins.....	1-4
1.2.2	Setting Common Properties	1-6
1.2.3	Setting Language Properties	1-14
1.2.4	Setting CSS Style.....	1-16
1.2.5	Setting Hashing Algorithm Iteration Count.....	1-17
1.2.6	Setting Email Details	1-18
1.2.7	Setting FCIS UBS Adapter Properties	1-19
1.2.8	Setting Oracle IPM Adapter Properties.....	1-20
1.2.9	Configuring Scheduler.....	1-22
1.2.10	Setting EMS Properties.....	1-27
1.2.11	Setting BIP and BIP Advice Report	1-32
1.2.12	Setting GI Upload Properties	1-34
1.2.13	Setting Report Properties.....	1-36
1.2.14	Setting BPEL Properties.....	1-38
1.2.15	Saving Property File.....	1-41

1. Creating Property File for Oracle FLEXCUBE Investor Servicing


1.1 Introduction

This chapter explains the steps to create property files for Oracle FLEXCUBE Investor Servicing Application.

1.2 Creating Property File


To create the property file for Oracle FLEXCUBE Investor Servicing, follow the steps given below:

1. Launch Oracle FLEXCUBE Investor Servicing Installer.



2. Choose 'Oracle FLEXCUBE IS'. Click 'Next'.

3. The following screen is displayed:



4. Choose the option 'Property File'.

5. Specify the following details:

Operating System

Specify the operating system in which you are creating the property file. Choose the appropriate one from the drop-down list

Application Server

Specify the application server in which you are creating the property file. Choose the appropriate one from the drop-down list.

Database Server

Specify the database server in which you are creating the property file. Choose the appropriate one from the drop-down list.

Once you have specified the details, click 'Next' to continue. The following screen is displayed.




In this screen, choose either Default or Custom installation.

Default – Only the minimum list of details are asked for. Insulation plug-in is de-selected. SSO is by default No.


If there are any issues with the default values then, the property file created can be loaded and choosing custom Installation option it can be corrected.

Click 'Next' to continue.



ORACLE

Click 'Next' to continueCustom – All details are to be provided.



6. Specify the following details:

Centralized Property File

The property file needs to be built before the EAR file. If you are creating a new property file, leave the field blank. If you wish to modify an existing property file, you can manually specify the location of the property file.

1.2.1 Setting Oracle FLEXCUBE Investor Servicing Plug-ins

Default Installation steps are as below

BPEL and RTT should be chosen explicitly while, other plug-ins are defaulted. Insulation is not there.

Oracle FLEXCUBE Investor Servicing **ORACLE**

Default Installation
Choose the available plugins for including them in the current installation.

Plugin Description	Include
BPEL	<input checked="" type="checkbox"/>
Regression Testing Tool	<input checked="" type="checkbox"/>
DMS	<input checked="" type="checkbox"/>
REPORTS	<input checked="" type="checkbox"/>
SCHEDULER	<input checked="" type="checkbox"/>

Log Back Next Exit

Once you have selected the plug-ins, click 'Next'. You will be navigated to the 'Common Properties' screen

Custom Installation steps are as below

This section describes the process of setting plug-ins.

1. You can select the plug-ins from the following screen.

Oracle FLEXCUBE Investor Servicing **ORACLE**

Property File Creation
Choose the available plugins for including them in the current installation.

Plugin Description	Include
Oracle Flexcube Testing Workbench	<input checked="" type="checkbox"/>
Insulation	<input checked="" type="checkbox"/>
Document Management System	<input checked="" type="checkbox"/>
Scheduler	<input checked="" type="checkbox"/>
Reports	<input checked="" type="checkbox"/>
BPEL	<input checked="" type="checkbox"/>

Is Scheduler Standalone ☐

Log Back Next Exit

2. You need to select the plug-ins to be included in the installation. Check the box against the required plug-ins. The following plug-ins are available for Oracle FLEXCUBE Investor Servicing:

- BPEL
- Document Management System
- Reports
- Scheduler
- Regression Testing Tool
- Insulation

Note: If scheduler is required then, one can chose if scheduler is required as standalone.

For to choose standalone scheduler, one should go through scheduler option of building the EAR and deploy the EAR ahead of FCIS application

Scheduler URL: The value for the URL should be the scheduler URL that will be available once scheduler application is deployed.

3. Once you have selected the plug-ins, click 'Next'. You will be navigated to the 'Common Properties' screen.

1.2.2 Setting Common Properties

This section describes the process of setting common properties of Oracle FLEXCUBE Investor Servicing.

Default Installation steps are as below

Oracle FLEXCUBE Universal Installer

Oracle FLEXCUBE Investor Servicing ORACLE

Default Installation
Current screen provides an option for modifying the Common property values.

Debug Logs Required: Yes

Work Area: /BrnDbgs/

Signature Path: /BrnDbgs/

Excel Path: /BrnDbgs/

Log Back Next Exit

Debug

If you require debug option, select 'Yes' from the drop-down list. If you do not require debug option, select 'No'.

Signature Path

Specify the location at which the signature images will be placed.


Excel Path

Specify the location at which the excel files will be generated.

On click on Next, details mentioned under section '**Setting Email Details**' needs to be followed. Please refer to that section for further flow in Default Installation option.

Custom Installation steps are as below

1. The installer displays the 'Common Properties' screen.



2. The following are the common properties required for FCIS Application:

Debug

If you require debug option, select 'Yes' from the drop-down list. If you do not require debug option, select 'No'.

Signature Path

Specify the location at which the signature images will be placed.

Excel Path

Specify the location at which the excel files will be generated.

Data Source

Specify the JNDI location which points to SMS schema The standard format is 'jdbc/fcisdevDS'.

Request Time Out

Specify the database request timeout value in seconds. This is the maximum number of seconds the database will wait for a query to return the result.

Connection Time Out


Specify the database connection timeout value in seconds. This is the maximum number of seconds the application will wait for a connection to the database to open.

LOV Fetch Required

If you check this box, the option lists in Oracle FLEXCUBE Investor Servicing will display the matching values based on the first characters that you enter in a field. That is, if you specify the first three characters of a value to be entered in an option list and tab out, the system will display the complete list of values that are matching the first three characters.

If you do not check this, option lists will not show the matching values based on the first few characters. You need to specify the complete value against the field.

3. Click 'Next'. The following screen is displayed.



The screenshot shows the 'Oracle FLEXCUBE Universal Installer' window. The title bar says 'Oracle FLEXCUBE Universal Installer'. The main window has a red header with 'Oracle FLEXCUBE Investor Servicing' and the 'ORACLE' logo. Below the header, the section is titled 'Property File Creation' with a description: 'Current screen provides an option for modifying the OBIEE and other property values.' There are five input fields: 'Help File Name' with the value 'fciswebhelp.htm', 'OBIEE ENABLED' with a dropdown menu set to 'No', 'OBIEE URL' with the value '/analytics/saw.dll?Portal&syndicate=Siebel', 'OBIEE FOLDER' with the value 'D:\BrnDbgs\', and 'OBIEE SIGNOUT URL' with the value '//10.10.10.10:1234/analytics/saw.dll?Logoff'. At the bottom, there are four buttons: 'Log', 'Back', 'Next', and 'Exit'.

Enter following details

Help File Name

Enter Help File name

OBIEE Enabled

Whether OBIEE is enabled.

OBIEE URL

Mention URL


OBIEE Folder

OBIEE folder

OBIEE Signout URL

Mention URL

On click of next following screen is shown.




4. Specify the following details:

SSO Required

Check this box to enable single sign-on (SSO). If you check this box, you need to enter the SSO Key.

SSO Key

Specify the SSO key. If you have checked the box 'SSO Required', it is mandatory to specify the SSO key.



External Password Required

Check this box to allow the user-login using MSAD/LDAP password irrespective of the user ID. If you check this box, the user ID can be either the MSAD/LDAP user ID or the FCIS user ID. And the password can be MSAD/LDAP server password only.


By default, this check box is unchecked. However, you can change this.

If you do not check this box, the installer skips the following screen and directly navigates you to the SSL screen shown below in this manual.

If you check the box, then click 'Next' and the following screen is displayed:

External User Login Required

Check this box to enable user login using MSAD/LDAP user ID.

 If you check this box, the user can login using MSAD/LDAP server user ID as well as using FCIS user ID.

ORACLE

Authentication Type

Select the authentication type from the adjoining drop-down list. This is the type of external server that is used. You can select one of the following options:

- MSAD (Microsoft Active Directory)
- LDAP (Lightweight Directory Access Protocol)

By default, 'MSAD' is selected; however, you can change it.

5. The default option is MSAD; however, you can change it.

If you check the box, then the installer navigates to the following screen on clicking 'Next' button.

The screenshot shows the 'Oracle FLEXCUBE Universal Installer' window. The title bar says 'Oracle FLEXCUBE Universal Installer'. The main window has a red header with 'Oracle FLEXCUBE Investor Servicing' and the 'ORACLE' logo. Below the header, the text 'Property File Creation' and 'LDAP Server Details for Branch' is displayed. A table with 3 columns: 'No.', 'Name', and 'Value' is shown. The table contains 5 rows of data. Below the table, there is a 'Log' button and 'Back', 'Next', and 'Exit' buttons.

No.	Name	Value
1	LDAP SERVER URL	LDAP://10.10.10.10:111
2	LDAP SSL ENABLED	<input type="checkbox"/>
3	SECURITY AUTHENTICAT...	Simple
4	DOMAIN NAME	I-FLEX.COM
5	LDAP SERVER TIMEOUT	0

6. Specify the following details:

LDAP Server URL

Specify the URL to access the LDAP server where the external user Ids or passwords are maintained.

LDAP SSL Enabled

Check this box if the LDAP server is SSL enabled.

Note: If you check this box, then you need to specify the SSL port in the field 'LDAP SERVER URL'.

Security Authentication Type

Depending on the authentication mechanism supported by the LDAP server, you need to select one of the following:

- Simple (in most cases)
- Strong

Note: Different servers support different authentication mechanisms. By default, the security authentication type is 'Simple'; however, you can change it.

Domain Name

Specify the domain name.

LDAP Server Timeout

Specify the LDAP server timeout in milliseconds.

Note: Note the following:

- By default, the LDAP server timeout is zero; however, you can change this.
- You must enter a positive integer value. For example, 1000, 10000, 5000, etc.
- If the value specified is zero or less, it indicates that no read timeout is specified. Then, the wait for the response infinite until it is received.

Once you have specified the above details, click 'Next'.


7. The following screen is displayed:

The screenshot shows a dialog box titled "Oracle FLEXCUBE Investor Servicing" with the Oracle logo in the top right corner. The main heading is "Property File Creation". Below it, the instruction reads: "Choose Enable SSL option for Securing confidential user information". There are two checkboxes: "SSL Enabled?" which is checked, and "OPSS Available" which is unchecked. A red warning box contains the text: "If the SSL Enabled option is unchecked then this setting will put your application at risk. OFSS will not hold any responsibility for the Data Loss." Below the warning box, there is a text block: "OPSS □ CSF : A credential store is used for secure storage of credentials. CSF is used to access and perform operations on the credential store. The Credential Store Framework enables to manage credentials securely". At the bottom of the dialog, there are four buttons: "Log", "Back", "Next", and "Exit".

8. Specify the following details.

SSL Enabled

Indicate whether SSL is enabled or not. If SSL is required, choose 'Yes'. If SSL is not enabled, the Installer will pop-up a window.



However, it is recommended that you enable SSL.

OPSS Available

OPSS is available only for weblogic and is not supported for Websphere.

9. IF OPSS available is checked for weblogic the symmetric key is not stored in the property file for security reasons. If OPSS available is unchecked the symmetric key is available in the property file and a warning message is displayed to the user. Click 'Next'. You will be navigated to the next screen.

1.2.3 Setting Language Properties

This section describes the process of setting language packs of Oracle FLEXCUBE Investor Servicing.

1. The system displays the following screen.

[illegible]

2. Specify the following details.

Language

Specify the language in which you wish to see Oracle FLEXCUBE Investor Servicing. English is the default language. However, based on the requirement, you can set a different language. Choose the appropriate one from the drop-down list.

Based on the language selected, the installer displays the ISO code.

Application Title

Specify the application title.

E.g.: FLEXCUBE IS

Version

Specify the application version.

E.g.: 12.0.0

Copy Rights

Specify the copyright details.


E.g.: Copyright@2007-2012 Oracle Financial Software Services Limited. All rights reserved.

3. Once you have specified the details, click 'Next'. You will be navigated to the CSS setting screen.

1.2.4 Setting CSS Style

This section describes the process of setting CSS style.

1. The following screen is displayed.



2. Specify the following details:

CSS Style

Specify the CSS style to be used. You can choose one of the following CSS styles:

- Default – choose this to apply the default style provided along with Oracle FLEXCUBE Investor Servicing
- Custom – choose this to apply a custom style

Name


Specify the name of the CSS style.

3. Once you have specified the above details, click 'Next'. You will be navigated to the Hashing Algorithm Count Settings screen.

1.2.5 Setting Hashing Algorithm Iteration Count

This section describes the method of setting hashing algorithm iteration count.

1. The following screen is displayed.



2. Specify the following details:

Hashing Algorithm Iteration Count


Specify the hashing algorithm iteration count. This count implies the time required for logging into the application. An increase in this count increases the login time.

3. Once you have specified the details, click 'Next'.

1.2.6 Setting Email Details

This section describes the method to configure email details.

1. The following screen is displayed.



Oracle FLEXCUBE Universal Installer

Oracle FLEXCUBE Investor Servicing ORACLE

Property File Creation
Current screen provides an option for Mail configuring using SMTPS Protocol.

No.	Name	Value
1	Host	samplename.mail.com
2	User Id	infra
3	User Password	••••••••
4	JNDI Name	mail/FCUBSMail

Log Back Next Exit

2. Specify the following details.

Host

Specify the SMTP host name.

User ID

Specify the user ID.

User Password

Specify the user password.

JNDI Name


Specify the JNDI name.

3. Once you have specified the above details, click 'Next'.

1.2.7 Setting FCIS UBS Adapter Properties

Only for Custom Installation

This section describes the FCIS UBS Adapter properties setup.



Oracle FLEXCUBE Universal Installer


Oracle FLEXCUBE Investor Servicing ORACLE

Property File Creation
Current screen provides an option for specifying Call Out Adapter Properties.

Name	Value
FCUBSAccService Url	htt://10.10.10.10:1111

Log Back Next Exit

1. Specify the 'FCUBSAccService Url' and click 'Next'.



Oracle FLEXCUBE Universal Installer

Oracle FLEXCUBE Investor Servicing ORACLE

Property File Creation
Current screen provides an option for specifying MDB Adapter Queue Properties.

S.No	Name	Value
1	MDB ADAPTER Datasource	jdbc/fcjddevIS123
2	Inbound Queue Name	MDB_QUEUE
3	ADAPTER Queue Connection ...	MDBQCF

Log Back Next Exit

Specify MDB Datasource, Queue name and Queue Connection Factory.

1.2.8 Setting Oracle IPM Adapter Properties

In case you have included DMS in the installation, you need to set the Oracle IPM adapter properties. Navigate to 'Oracle IPM DMS Properties' screen.

1. Set the server type in the following screen.

Oracle FLEXCUBE Universal Installer

Oracle FLEXCUBE Investor Servicing ORACLE

Property File Creation

Choose the adapter for enabling Document management system.

Server Type: Oracle IPM

Oracle IPM - Document Management System with Server Type has Oracle Image and Process Management

Log Back Next Exit

2. Choose 'Oracle IPM' as the server type.
3. Click 'Next, the following screen is displayed.

Oracle FLEXCUBE Universal Installer

Oracle FLEXCUBE Investor Servicing ORACLE

Property File Creation

Current screen provides an option for modifying the DMS/IPM property values.

No.	Name	Value
1	Login Service Address	http://10.10.10.10:1010/imaging/ws/LoginService
2	Document Service Ad...	http://10.10.10.10:1010/imaging/ws/DocumentServi...
3	Document Content Se...	http://10.10.10.10:1010/imaging/ws/DocumentCont...
4	IPM User Name
5	IPM Password
6	IPM Application Name	OFSS
7	Http Session Maintain	<input checked="" type="checkbox"/>

Log Back Next Exit

4. Specify the following details:

Login Service Address

This is the endpoint address of the web service (OracleIPM.WebService.EndpointAddress).

Document Service Address

This is the URL to which the Oracle IPM adapter uploads the documents (OracleIPM11G.DocumentService.EndpointAddress).

Document Content Service Address

This is the URL to which the Oracle IPM adapter uploads the documents (OracleIPM11G.DocumentContentService.EndpointAddress).

Note: For websphere application server, the above three service address must end with “?wsdl”

Example for Login Service Address:

Webpsphere: <http://10.10.10.10:1010/imaging/ws/LoginService?wsdl>

Weblogic: <http://10.10.10.10:1010/imaging/ws/LoginService>

Similarly, this is applicable for Document Service Address and Document Content Service Address as well.

IPM User Name

This is the user name accessing Oracle IPM (OracleIPM11G.Authentication.UserName).

IPM Password

This is the password for the above IPM user name (OracleIPM11G.Authentication.Password).

IPM Application Name

This indicates the license that provides login rights to Oracle IPM (OracleIPM11G.Application).

HTTP Session Maintain

This checkbox indicates whether HTTP session to be maintained or not (OracleIPM11G.MaintainSession).

Once you have specified the above details, click 'Next'.

1.2.9 Configuring Scheduler

Only for Custom Installation

This section describes the method to configure scheduler data source. The following screen is displayed.

The screenshot shows the 'Oracle FLEXCUBE Universal Installer' window. The title bar includes the Oracle logo and the text 'Oracle FLEXCUBE Universal Installer'. The window has a red header bar with 'Oracle FLEXCUBE Investor Servicing' on the left and the 'ORACLE' logo on the right. The main content area is titled 'Property File Creation' and contains the text: 'Current screen provides an option for Scheduler configuration.' Below this, there are two input fields: 'Scheduler Datasource' with the value 'jdbcfcjSchedulerDS' and 'Scheduler Log Rotation Interval' with a dropdown menu set to 'WEEKLY'. A grey box contains instructions: 'Provide the Scheduler Datasource Name in the field Scheduler Datasource.' and 'Provide the Scheduler Log Rotation Value To move old Scheduler Log to another file at specific time intervals .'. At the bottom, there are four buttons: 'Log', 'Back', 'Next', and 'Exit'.

5. Specify the Scheduler Datasource which Oracle FLEXCUBE Investor Servicing will access.
6. Click 'Next'. The following screen is displayed.

The screenshot shows the 'Oracle FLEXCUBE Universal Installer' window. The title bar includes the Oracle logo and the text 'Oracle FLEXCUBE Universal Installer'. The window has a red header bar with 'Oracle FLEXCUBE Investor Servicing' on the left and the 'ORACLE' logo on the right. The main content area is titled 'Property File Creation' and contains the text: 'Current screen provides an option for configuring Scheduler Destination Queue.' Below this, there are four input fields: 'Notify Destination' with a dropdown menu set to 'QUEUE', 'Queue Name' with the value 'NOTIFY_DEST_QUEUE', 'Queue Connection Factory' with the value 'NotifyDestQCF' and a 'Secure' checkbox, and 'Notify Queue Location' with a dropdown menu set to 'Internal'. At the bottom, there are four buttons: 'Log', 'Back', 'Next', and 'Exit'.

7. Specify the following details:

Notify Destination

Specify the notify destination. Choose one of the following options:

- QUEUE
- TOPIC

Queue Name

Set 'NOTIFY_DEST_QUEUE' as the destination queue name.

Queue Connection Factory

Set 'NotifyDestTCF' as the queue connection factory.

Secure

Check this box to indicate that it is a secured queue connection factory. If you check this box, you will be prompted to specify the caller ID and caller password as shown in the following screen.

Oracle FLEXCUBE Universal Installer

Oracle FLEXCUBE Investor Servicing ORACLE

Property File Creation

Current screen provides an option for configuring Scheduler Destination Queue.

Notify Destination: QUEUE

Queue Name: NOTIFY_DEST_QUEUE

Queue Connection Factory: NotifyDestQCF ☒ Secure

Caller ID:

Caller Password:

Notify Queue Location: Internal

Log Back Next Exit

Caller ID

Specify the caller ID for the secured queue connection factory.

Caller Password

Specify the password for the caller ID to access the secured queue connection factory.

Note: If the queue connection factory is not secured, i.e., if you have not checked the box 'Secure', the installer will not display the fields 'Caller ID' and 'Caller Password'. You need not provide these details in that case.

Notify Queue Location

Specify the notify queue location. Choose one of the following options:

- Internal
- External

Note: For Oracle WebLogic application server, the notify queue location should be selected as 'Internal'. If you choose 'Internal' as the 'Notify Queue Location', the screen provided in the following step will not be displayed. You will be navigated to next step where you can specify the notify deferred queue name and connection factory.

8. If you choose 'External', you will be navigated to the following screen.

The screenshot shows the 'Oracle FLEXCUBE Universal Installer' window. The title bar says 'Oracle FLEXCUBE Universal Installer'. The main window has a red header with 'Oracle FLEXCUBE Investor Servicing' and the 'ORACLE' logo. Below the header, the text 'Property File Creation' is displayed, followed by 'Current screen provides an option for External Server configuration for Destination Queue.' A table with three columns: 'No.', 'Name', and 'Value' is shown. The table contains three rows: 1. 'Provide Url' with value 'iiop://localhost:1010', 2. 'Security Principal' with a masked value '.....', and 3. 'Security Credential' with a masked value '.....'. Below the table is a large empty text area. At the bottom of the window are four buttons: 'Log', 'Back', 'Next', and 'Exit'.

No.	Name	Value
1	Provide Url	iiop://localhost:1010
2	Security Principal
3	Security Credential

9. You need to specify the following details of the external queue.

Provider URL

Specify the provide URL (iiop://localhost:1010).

1010 is the default IIOP port.

Security Principal


Specify the login ID to access the application server.

Security Credentials

Specify the password to access the application server.

10. Click 'Next' to proceed with scheduler configuration.

Note: If you choose 'Internal' as the 'Notify Queue Location', you will be directly navigated to the following screen. In that case, the installer will not show the screen explained in the previous step.



11. Specify the following details:

Notify Deferred Queue Name

Set 'DEFERRED_DEST_QUEUE' as the notify deferred queue name.

Deferred Queue Connection Factory

Set 'DeferredDestQcf' as the deferred queue connection factory.

Secure

Check this box to indicate that it is a secured deferred queue connection factory. If you check this box, you will be prompted to enter the caller ID and caller password as shown in the following screen.

Oracle FLEXCUBE Universal Installer

Oracle FLEXCUBE Investor Servicing ORACLE

Property File Creation

Current screen provides an option for Scheduler configuration.

Notify Deferred Queue Name

Deferred Queue Connection Factory ☒ Secure

Caller ID

Caller Password

Log Back Next Exit

12. Specify the caller ID and caller password for the secured deferred queue connection factory.

13. Click 'Next'. The following screen is displayed.

Oracle FLEXCUBE Universal Installer

Oracle FLEXCUBE Investor Servicing ORACLE

Property File Creation

Current screen provides an option for Scheduler Notify Internal Queue configuration.

Notify Queue Name

Dead Letter Queue Name

Notify Queue Connection Factory ☐ Secure

Log Back Next Exit

14. Specify the following details:

Notify Queue Name

Set 'NOTIFY_QUEUE' as the notify queue name.

Dead Letter Queue Name


Set 'NOTIFY_QUEUE DLQ' as the dead letter queue name.

Notify Queue Connection Factory

Set 'NOTIFY_MDB_QCF' as the notify queue connection factory.

Secure

Check this box to indicate that it is a secured queue connection factory. If you check this box, you will be prompted to enter the caller ID and caller password as shown in the following screen.



15. Specify the caller ID and caller password for the secured notify queue connection factory.


Click 'Next'. The following screen is displayed.

1.2.10 Setting EMS Properties

Only for Custom Installation except EMS FTP/FTPS

You will be navigated to the 'Scheduler EMS Properties' screen. Here, you need to set the EMS details.

1. Set the EMS properties:
2. Specify the following details:



Incoming Dead Letter Queue Name

Set 'EMS_QUEUE_DLQ' as the incoming dead letter queue name.

Incoming Backup Queue Name

Set 'EMS_QUEUE_BACK' as the incoming backup queue name.

Incoming Connection Factory

Specify the name of the incoming connection factory to which EMS listens. You need to create this connection factory at the application server.

For details on connection factory creation, follow the steps described for creation of notify connection factories.

Secure Incoming Queue Connection

Check this box to indicate that it is a secured queue connection.

Incoming Queue Caller ID

Specify the caller ID for the secured queue connection.

Incoming Queue Caller Password

Specify the caller password for the secured queue connection.

Outgoing Dead Letter Queue Name

Set 'EMS_QUEUE_DLQ' as outgoing dead letter queue name.

OutGoing Connection Factory

Specify the name of the outgoing connection factory to which EMS listens. You need to create this connection factory at the application server.

For details on connection factory creation, follow the steps described for creation of notify connection factories.

Secure Outgoing Queue Connection

Check this box to indicate that it is a secured outgoing queue connection.

Outgoing Queue Caller ID

Specify the caller ID for the secured queue connection.

Outgoing Queue Caller Password

Specify the caller Password for the secured queue connection.

Outgoing Queue Provider URL

In case EMS OUT MDB is to be configured to queue, you need to specify the URL for outgoing provider based on the application server. By default, the Installer displays the outgoing queue provider URL for Oracle WebLogic.

This value is application server dependent.

The details of Outgoing Queue Provider URL to be used for different application servers are given below:

Application Server	EMS Out Initial Context Factory
Oracle WebLogic	t3://<ip_adress>:port E.g.: t3://10.10.10.10:1010 Here, 10.10.10.10 represents the local host and 1010 to the target server default port (AdminServer/ManagedServer).
IBM WebSphere	iiop://<ip_adress>:port E.g.: iiop://10.10.10.10:1010 Here, 1010 represents the default iiop port

Queue Principal

If EMS OUT MDB has to be configured to queue, you need to specify the EMS out queue principal. This is the user name for the application server in which the queue is configured.

Queue Credential

If EMS OUT MDB has to be configured to queue, you need to specify the EMS out queue credential. This is the password for the above user name created for application server in which the queue configured.

Incoming Queue Name

Specify the name of the incoming queue for which EMS is configured. By default, this is set as 'NOTIFY_QUEUE_DLQ'.

Outgoing Queue Name

Specify the name of the outgoing queue for which EMS is configured. By default, this is set as 'NOTIFY_QUEUE_DLQ'.

SFMS Incoming Queue

Specify the SFMS Incoming Queue.

RTGS Incoming Queue

Specify the RTGS incoming Queue.

3. Once you have specified the above details, click 'Next'.

The screenshot shows the 'Oracle FLEXCUBE Universal Installer' window. The title bar reads 'Oracle FLEXCUBE Universal Installer'. The main window has a red header bar with 'Oracle FLEXCUBE Investor Servicing' and the 'ORACLE' logo. Below the header, the text 'Property File Creation' is displayed, followed by 'Current screen provides an option for Scheduler EMS FTP/FTPS configuring.' A table with 3 columns (No., Name, Value) contains the following data:

No.	Name	Value
1	File TranferMode FTPS	FTPS
2	Server	10.10.10.10
3	User id	OFSS
4	Password
5	File Type	.txt
6	Swift Format	1
7	Swift Message Delimiter	<input checked="" type="checkbox"/>
8	Swift Message Terminator	<input checked="" type="checkbox"/>

At the bottom of the window, there are four buttons: 'Log', 'Back', 'Next', and 'Exit'.

For Default Installation following screen is shown.

No.	Name	Value
1	Server	10.10.10.10
2	User id	OFSS
3	Password

4. Specify the following details:

File Transfer Mode FTPS

Specify the mode of transferring files to EMS. Choose one of the following:

- FTPS(defaulted in default installation)
- SFTP
- HTTP

Server

Specify the server IP address for the selected file transfer mode.

User ID

Specify the user ID to access the server of the file transfer mode.

Password

Specify the password to for the above user ID.

File Type

Specify the type of file that is transferred. By default, the Installer sets it as '.txt'.

SWIFT Message Delimiter

Specify the character which is used as the message delimiter.

SWIFT Message Terminator

Specify the character which is used as the message terminator.

5. Once you have specified the above details, click 'Next'. The following screen is displayed.

The screenshot shows the 'Oracle FLEXCUBE Universal Installer' window. The title bar includes the Oracle logo and window controls. The main window has a red header with 'Oracle FLEXCUBE Investor Servicing' and the 'ORACLE' logo. Below the header, the text 'Property File Creation' and 'EMS-Structured Financial Messaging System configuration Screen.' is displayed. A table with four rows is shown, with columns 'No.', 'Name', and 'Value'. The first row has '1' in the 'No.' column, 'Signature Block' in the 'Name' column, and a checked checkbox in the 'Value' column. The second row has '2' in the 'No.' column, 'Keystore File Name' in the 'Name' column, and '/keystore' in the 'Value' column. The third row has '3' in the 'No.' column, 'Keystore Alias name' in the 'Name' column, and '*****' in the 'Value' column. The fourth row has '4' in the 'No.' column, 'keystore Password' in the 'Name' column, and '*****' in the 'Value' column. Below the table is a large empty text area. At the bottom of the window are four buttons: 'Log', 'Back', 'Next', and 'Exit'.

No.	Name	Value
1	Signature Block	<input checked="" type="checkbox"/>
2	Keystore File Name	/keystore
3	Keystore Alias name	*****
4	keystore Password	*****

6. Specify the following details:

Signature Block

Check this box to enable signature block.

Keystore File Name

Specify the keystore file name.

Keystore Alias Name

Specify the keystore alias name.

Keystore Password

Specify the keystore password.

7. Once you have specified the above details, click 'Next'.

1.2.11 Setting BIP and BIP Advice Report

Only for Custom Installation

This screen describes how to create the property file. Here, you need to set the BIP and BIP Advice report details.

1. The following screen is displayed:

Oracle FLEXCUBE Universal Installer

Oracle FLEXCUBE Investor Servicing ORACLE

Property File Creation
Current screen provides an option for Scheduler BIP and BIP Advice report.

Bip Queue Name: INTERNAL_BIPREPORT_QUEUE

Bip DeadLetter Queue Name: INTERNAL_BIP_QUEUE_DLQ

BipAdvice Queue Name: INTERNAL_BIPADVREPORT_QUEUE

BipAdvice DeadLetter Queue Name: INTERNAL_BIP_ADVICE_QUEUE_DLQ

Queue connection factory: BIPQCF ☐ Secure

Log Back Next Exit

2. Specify the following details to set the EMS properties:

BIP Queue Name

Specify the BIP queue name as 'INTERNAL_BIPREPORT_QUEUE'.

BIP DeadLetter Queue Name

Specify the BIP deadletter queue name as 'INTERNAL_BIP_QUEUE_DLQ'.

BIPAdvice Queue Name

Specify the BIP advice queue name as 'INTERNAL_BIPADVREPORT_QUEUE'.

BIPAdvice DeadLetter Queue Name

Specify the BIP advice dead letter queue name as 'INTERNAL_BIP_ADVICE_QUEUE_DLQ'.

Queue Connection Factory

Specify the queue connection factory as 'BIPQCF'.

Secure

Check this box to indicate that it is a secured deferred queue connection factory. If you check this box, you will be prompted to enter the caller ID and caller password as shown in the following screen.

Oracle FLEXCUBE Universal Installer

Oracle FLEXCUBE Investor Servicing ORACLE

Property File Creation
Current screen provides an option for Scheduler BIP and BIP Advice report.

Bip Queue Name: INTERNAL_BIPREPORT_QUEUE

Bip DeadLetter Queue Name: INTERNAL_BIP_QUEUE_DLQ

BipAdvice Queue Name: INTERNAL_BIPADVREPORT_QUEUE

BipAdvice DeadLetter Queue Name: INTERNAL_BIP_ADVICE_QUEUE_DLQ

Queue connection factory: BIPQCF ☒ Secure

Caller ID:

Caller password:

Log Back Next Exit

3. Specify the caller ID and caller password for the secured queue connection factory.
4. Once you have specified the above details, click 'Next'.

1.2.12 Setting GI Upload Properties

Only for Custom Installation

This screen describes how to specify the GI upload property details. Here you need to set the GI Upload properties.

1. The following screen is displayed:

Oracle FLEXCUBE Universal Installer

Oracle FLEXCUBE Investor Servicing ORACLE

Property File Creation
Current screen provides an queue configuration details for Scheduler GI Upload.

Queue Name: INTERNAL_GI_UPLOAD_QUEUE

Dead Letter Queue Name: INTERNAL_GI_UPLOAD_DLQ

Queue connection factory: GI_UPLOAD_QCF ☐ Secure

Log Back Next Exit

2. Specify the following details:

Queue Name

Specify the queue name as 'INTERNAL_GI_UPLOAD_QUEUE'.

Dead Letter Queue Name


Specify the dead letter queue name as 'INTERNAL_GI_UPLOAD_DLQ'.

Queue Connection Factory

Specify the queue connection factory as 'GI_UPLOAD_QCF'.

Secure

Check this box to indicate that it is a secured deferred queue connection factory. If you check this box, you will be prompted to enter the caller ID and caller password as shown in the following screen.



The screenshot shows the 'Oracle FLEXCUBE Universal Installer' window. The title bar includes the Oracle logo and the text 'Oracle FLEXCUBE Universal Installer'. The main window has a red header bar with 'Oracle FLEXCUBE Investor Servicing' and the 'ORACLE' logo. Below the header, the section is titled 'Property File Creation' with a subtitle 'Current screen provides an queue configuration details for Scheduler GI Upload.' The form contains the following fields and controls:

- Queue Name:** A text box containing 'INTERNAL_GI_UPLOAD_QUEUE'.
- Dead Letter Queue Name:** A text box containing 'INTERNAL_GI_UPLOAD_DLQ'.
- Queue connection factory:** A text box containing 'GI_UPLOAD_QCF'.
- Secure:** A checkbox that is checked, with the label 'Secure' next to it.
- Caller ID:** An empty text box.
- Caller Password:** An empty text box.

At the bottom of the window, there are four buttons: 'Log', 'Back', 'Next', and 'Exit'.

3. Specify the caller ID and caller password for the secured queue connection factory.

4. Once you have specified the above details, click 'Next'.

1.2.13 Setting Report Properties

This section describes the methods to set report properties.

1. The following screen is displayed.

The screenshot shows a window titled "Oracle FLEXCUBE Investor Servicing" with the Oracle logo. Below the title bar, the text "Property File Creation" is displayed, followed by "Current screen provides an option for OFTW Details". A table with three columns: "No.", "Name", and "Value" is shown. The table contains four rows of data. At the bottom of the window, there are three buttons: "Log", "Back", and "Next", and an "Exit" button.

No.	Name	Value
1	OFTW Recording Type	REMOTE
2	OFTW User	infra
3	OFTW Password	*****
4	OFTW Provider URL	t3://ip:port

2. Click 'Next' to navigate to next page.

The screenshot shows a window titled "Oracle FLEXCUBE Universal Installer 12.3.0.0.0" with the Oracle logo. Below the title bar, the text "Property File Creation" is displayed, followed by "Current screen provides an option for modifying the Oracle BI Publisher properties." A table with three columns: "No.", "Name", and "Value" is shown. The table contains eight rows of data. At the bottom of the window, there are three buttons: "Log", "Back", and "Next", and an "Exit" button.

No.	Name	Value
1	Server End Point	http://10.10.10.10:0101/xmlpserver/services/v2/R...
2	Name Space	http://xmlns.oracle.com/oxp/service/PublicReport...
3	User Name	Administrator
4	Password	*****
5	Reports Advice Spool Path	/ReportsSpool
6	Advice Type	NATIVE
7	BIP Server Version	11g
8	BIP Time Zone	IST

3. Specify the following details:

Server End Point

Specify the BIP end point.

If BIP Server Version is 10g, the server end point should end with 'PublicReportService_v11'.

Eg: BIP_END_POINT=http://<bip server url>/xmlpserver/services/PublicReportService_v11

If BIP Server Version is 11g, the server end point should end with 'PublicReportService?WSDL'.

Eg: BIP_END_POINT=http://<bip server url>/xmlpserver/services/PublicReportService?WSDL

Name Space

Specify the BIP name space.

By default, the installer displays 'http://xmlns.oracle.com/oxp/service/PublicReportService'.

User Name

Specify the BIP user name. By default, the Installer displays 'Administrator'.

Password

Specify the password for the above user name. By default, the Installer sets it as 'Administrator'.

Reports Spool Path

Specify the reports spool path. By default, the Installer displays 'D:\\BrnDbgs\\ADV\\'.

Advice Type

Specify the advice type. You can choose one of the following:

- NATIVE – This advice type is used for generating advices in text format
- BIP – This advice type is used for generating advices in PDF format.

BIP Server Version

Specify the qualified BIP server version. You can select the appropriate one from the drop-down list.

BIP Time Zone

Specify valid Time Zone for the BIP server. You can select the appropriate one from the drop-down list.

4. Once you have specified the above details, click 'Next'.

1.2.14 Setting BPEL Properties

If you have included BPEL option in the setup, then you need to set the BPEL properties.

1. Set the BPEL properties.

No.	Name	Value
1	Factory Initial	weblogic.jndi.WLInitialContextFactory
2	Provide Uri	t3://10.10.10.10:0101
3	Security Principal	oc4jadmin
4	Security Credentials	*****
5	Soa Server Name	default
6	Domain Password	*****
7	Dedicated Connection	<input checked="" type="checkbox"/>
8	BPEL Relam Name	FLEXCUBE

2. Specify the following details:

Factory Initial

Specify the factory initial.

Provider URL

Specify the URL of the server. Enter the IP address, target server port (AdminServer/ManagedServer) and the context root.

Security Principal

Specify the user name to access the application server where BPEL is installed.

Security Credential

Specify the password for the above user name.

Soa Server Name

Specify the Soa Server Name. By default it will be the Installer sets it to 'default'.

Domain Password

Specify the domain password for which SOA server is extended

Dedicated Connection

Check this box to indicate that this connection is not used for other purposes.

BPEL Realm Name

Specify the BPEL realm name.

BAM URI

Specify the BAM URI.

BPM Installed

Check this box if the BPM is installed.

3. Once you have specified the above details, click 'Next'.

No.	Name	Value
1	BI User
2	BI Password

4. Specify the following details:

BI User Name

Specify the BI user name.

BI Password

Specify the password for the above user name.

5. Click 'Next'. The following screen is displayed.

Oracle FLEXCUBE Investor Servicing **ORACLE**

Property File Creation
Current screen provides an option for modifying the BPEL Load Balancing properties.

External Alerts Required

Enabling Load Balance ☒

Frequency

Task Counts

CutOff Time

6. Specify the following details:

Enabling Load Balance

Check this box to enable BPEL load balance.

Frequency

Specify the balance load frequency.

Task Counts

Specify the balance load task count.

Cut-off Time


Specify the balance load cut-off time.

7. Once you have specified the above details, click 'Next'.


1.2.15 Saving Property File

After completing all the required settings explained above, you need to save the property file.


1. Save the property file.



2. You can view the status of property file creation in the above screen. Once the file is saved, the installer displays the following message.



On click of OK installer displays the following message



3. This completes the properties file creation.



Setting up Property File
[September] [2016]
Version 12.3.0.0.0

Oracle Financial Services Software Limited
Oracle Park
Off Western Express Highway
Goregaon (East)
Mumbai, Maharashtra 400 063
India

Worldwide Inquiries:
Phone: +91 22 6718 3000
Fax: +91 22 6718 3001
www.oracle.com/financialservices/

Copyright © [2007], [2016], Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

