Oracle FLEXCUBE Core Banking

Security Management User Manual Release 11.7.0.0.0

Part No. E87095-01

May 2017





Security Management User Manual May 2017

Oracle Financial Services Software Limited Oracle Park Off Western Express Highway Goregaon (East) Mumbai, Maharashtra 400 063 India Worldwide Inquiries:

Phone: +91 22 6718 3000 Fax: +91 22 6718 3001

www.oracle.com/financialservices/

Copyright © 2017, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.



Table of Contents

1. Secu	ırity Management System (SMS)	4
	7011 - Event Log Inquiry	
	752 - Reset Primary Password	
1.3.	· · · · · · · · · · · · · · · · · · ·	
1.4.	755 - Modify Login Status	
1.5.	•	
1.6.	1 7	
1.7.		
1.8.	BA777 - Audit Trail Inquiry for Non-Financial Txns	
1.9.	· · · · · · · · · · · · · · · · · · ·	
1.10.	BAM10 - Restricted Accounts Maintenance	



1. Security Management System (SMS)



1.1. **7011 - Event Log Inquiry**

User logged in from different computer under a core banking network is allowed (although concurrent user log-ins is not allowed).

Using this option you can log the IP's under which the user ID was entered in the posting date. The system displays the date, time and action performed. The system displays the date, time and action performed.

This option refers to UBS infra to perform the transactions.

Definition Prerequisites

Not Applicable


Modes Available

Not Applicable

To perform event log inquiry

- 1. Type the fast path **7011** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Inquiries > Event Log Inquiry**.
- The system displays the Event Log Inquiry screen.

Event Log Inquiry






Field Name	Description
User Name	[Display] This field displays the name of the user who is logged in.
From	[Mandatory, dd/mm/yyyy] Type the date from which the event log inquiry is to be made.
То	[Mandatory, dd/mm/yyyy] Type the date till which the event log inquiry is to be made.
Column Name	Description
Seq No	[Display] This column displays the sequence number of the event.
User ID	[Display] This column displays the user id.
Date	[Display] This column displays the date and time of the event.
Terminal IP	[Display] This column displays the terminal IP from where the user had logged in.
Action	[Display] This column displays the action performed by the user.

- 3. Enter the from and to date.
- 4. Click the **Get** button. The system displays the event log details.



Event Log Inquiry



5. Click the Cancel button.



1.2. 752 - Reset Primary Password

Using this option you can reset the password without entering the old one .This option is used by the system administrator to reset the password if the user has forgotten his password or if the SM does not want the user to log into the system. If the user knows the new password, he will be prompted to change it on login.

This option utilises the UBS framework to complete the transaction.

Definition Prerequisites

Not Applicable


Modes Available

Not Applicable

To reset the primary password

- 1. Type the fast path **752** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Security > Reset primary password**.
- 2. The system displays the **Reset Primary Password** screen.

Reset Primary Password





Field Name	Description
Branch Code	[Mandatory, Numeric, Four, Pick List] Type the branch code or select it from the pick list. The name of the branch is displayed in the adjacent field.
User ID	[Mandatory] Enter the user ID whose password you want to reset. These user IDs are added and maintained in the User Profile Maintenance (Fast Path: SMM02) option.
User Name	[Display] This field displays the user name whose password you want to reset.
Password	[Mandatory, Alphanumeric, 10] Type the password, for the selected user ID. The password should have a minimum of six characters. It should be a combination of an uppercase and lowercase letter and a numeric digit. The password cannot have three or more successive characters or digits. For example, abc, xyz etc.
Verify Password	[Mandatory, Alphanumeric, 10] Type the new password to verify it. It should be the same as entered in the Password field.

- 3. Enter the user ID and username.
- 4. Enter the required information in the various fields.
- 5. Click the **Ok** button.



1.3. 753 - Enable/Disable User

Using this option you can enable/ disable a user of any branch through single administrator log in. The user IDs are created in the **User Profile Maintenance** (Fast Path: SMM02) option.

This option refers to UBS infra to perform the transactions.

Note: The system cannot disable the already logged in users.

Definition Prerequisites

Not Applicable


Modes Available

Not Applicable

To enable or disable a user

- 1. Type the fast path **753** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Security > Enable / Disable user**.
- 2. The system displays the Enable / Disable User screen.

Enable / Disable User






Field Name	Description
Branch Code	[Display] This field displays the branch code. The name of the branch is displayed in the adjacent field.
User Id	[Mandatory, Pick List] Select the ID of the user, who has to be enabled or disabled, from the pick list. These user ID's are maintained in the User Profile Maintenance (Fast Path: SMM02) option.
User Name	[Display] This field displays the name of the user for the selected user ID.
Current Status	[Display] This field displays the current status of the user. The status can be enable, disable, and lock.
Change Status	[Mandatory, Drop-Down]Select the option to change the status of the user from the drop-down list.The options are:ENABLEDISABLE
Permanently Disable	[Conditional, Check Box] Select the check box to permanently disable a user. This field is enabled only if DISABLE option is selected in the Change Status drop-down list.
Logged in	 [Display] This field displays the logged in status of the user. The options are: Y: User is logged in. N: User is not logged in.

- 3. Select the branch code and user ID from the pick list.
- 4. Select the change status from the drop-down field.



Enable / Disable User



- 4. If the user is enabled, the system displays the message "Do you wish to permanently disable the user?".
- 5. If the user is disabled, the system displays the message "User is Disabled. Do You Want to Enable".
- 6. If the user is not logged in, the system displays the "User Not Logged in. Want to Disable?".
- 7. Click the Ok button.



1.4. 755 - Modify Login Status

Using this option you are forcibly logged out of the system . This option is used when you have logged into **FLEXCUBE** and the application/system crashes. When you try to login after the system is restored, it does not allow , as the system still maintains the user status as logged in. Also, the system will not permit a login more than once. In such cases this option is used to modify the login status.

This screen refers to UBS infra to perform the transactions.

Definition Prerequisites

Not Applicable


Modes Available

Not Applicable

To modify login status

- 1. Type the fast path **755** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Security > Modify Login Status**.
- 2. The system displays the **Modify Login Status** screen.

Modify Login Status





Field Name	Description
User ID	[Mandatory]
	Enter the user ID of the user, whose login status is to be modified.
	These user ID's are maintained in the Defining User Profile (Fast Path: SMM02) option.
User Name	[Display]
	This field displays the user name of the user, whose login status is to be modified.

- 3. Enter the user ID and user name.
- 4. The system displays the message "User already logged in do you want to log out the user". Click the **Ok** button.
- 5. Click the **OK** button.



1.5. 757 - Inquiry For Logged In Users

Using this option you can view the list of users that are logged in to the system in their own branch.

The system provides information on user ID, user name, the terminal ID in which the user has logged in and the login date and time. You can refresh the screen to get the latest status.

This screen refers to UBS infra to perform the transactions.

Definition Prerequisites

Not Applicable


Modes Available

Not Applicable

To view a list of currently logged in users

- Type the fast path 757 and click Go or navigate through the menus to Transaction Processing > Internal Transactions > Security > Inquiry For Logged In Users.
- 2. The system displays the **Inquiry For Logged In Users** screen.

Inquiry For Logged In Users





Column Name	Description
User ID	[Display]
	This column displays the user ID for all those users who are currently logged into the system.
User Name	[Display]
	This column displays the list of users who are currently logged into the system.
Terminal ID	[Display]
	This column displays the identification code of the terminal where each user has logged into the system.
Login Time	[Display]
	This column displays the login date and time when the users have logged into the system.

- 3. The system displays the users who are currently logged in to the system.
- 4. Click the **Refresh** button to refresh the screen with the latest details.



1.6. 768 - Change Password

Using this option you can change your own password by entering the old one. You can not use the passwords which are prohibited specifically in **User Prohibited Passwords** (Fast Path: 756) option. These are commonly used words specific to the person such as place of residence, spouse name, name of son/daughter, etc.

This option utilises the UBS framework to complete the transaction.

Definition Prerequisites

Not Applicable


Modes Available

Not Applicable

To change primary password

- 1. Type the fast path **768** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Security > Change Primary Password**.
- 2. The system displays the Change Primary Password screen.

Change Primary Password






Field Name	Description
Old Password	[Mandatory, Alphanumeric]
	Type the valid current or old password.
New Password	[Mandatory, Alphanumeric]
	Type the new password, which you would like to use.
	Password must meet at least 3 out of the following four complexity rules:
	 at least 1 uppercase character (A-Z)
	 at least 1 lowercase character (a-z)
	• at least 1 digit (0-9)
	at least 1 special character (!"£\$%&)
	The password should have a minimum of six characters.
	The password cannot have three or more successive characters or digits. For example, abc, xyz etc.
Verify Password	[Mandatory, Alphanumeric]
	Type the new password again to verify it.

- 3. Type the old password.
- 4. Type the new password and re-type it for confirmation.



Change Primary Password



- 5. Click the Ok button.
- 6. The system changes the primary password.



1.7. AT002 - Audit Trail Financial Transactions Inquiry

Using this option you can view the audit trail of financial transactions performed on **Oracle FLEXCUBE**. The audit trail can be queried using this maintenance on any of the following parameters:

- · Originating Branch
- Date Range
- Teller ID or Super ID
- · Customer ID or Account Number
- Transaction mnemonic and/or Amount range
- Type of transaction, Transaction number

Definition Prerequisites

• Financial Transactions should have been performed

Modes Available


Not Applicable

To inquire on audit trail

- Type the fast path AT002 and click Go or navigate through the menus to Transaction Processing > Internal Transactions > Inquiries > Audit Trail Financial Transactions Inquiry.
- 2. The system displays the **Audit Trail Financial Transactions Inquiry** screen.

Audit Trail Financial Transactions Inquiry





Field Name	Description
Originating Branch	[Mandatory, Drop-Down] Select the originating branch, for which the audit trail is required, from the drop-down list.
Mnemonic	[Optional, Pick List] Select the maintenance task code to be be audited from the pick list.
Date From	[Mandatory, Pick List, dd/mm/yyyy] Select the date from which the data has to be retrieved from the pick list.
Date To	[Mandatory, Pick list, dd/mm/yyyy] Select the date up to which the data has to be retrieved from the pick list.
Customer ID	[Optional, Alphanumeric, 10] Type the id of the customer on whom the maintenance was done.
Account Number	[Optional, Numeric, 14] Type the account number on which the maintenance was done.



Field Name	Description
Teller ID	[Mandatory, Drop-Down] Select the id of the teller who has performed the maintenance from the drop-down list.
Super ID	[Optional, Drop-Down] Select the id of the authoriser who has authorised the maintenance from the drop-down list.
Amount From	[Optional, Alphanumeric, 13, Two] Type the minimum amount from which the records are to be displayed.
Amount To	[Optional, Alphanumeric, 13, Two] Type the maximum amount upto which the records are to be displayed.
DR/CR	[Optional, Character, One] Enter the type of transaction. You can type D or C to view the debit or credit transactions.
Txn No	[Optional, Alphanumeric, 40] Type the transaction number for which the records are to be
	displayed.
Column Name	displayed. Description
Column Name Txn Date	
	Description [Display]
Txn Date	Description [Display] This column displays the date of transaction. [Display]
Txn Date Posting Date	Description [Display] This column displays the date of transaction. [Display] This column displays the posting date. [Display]
Txn Date Posting Date Txn Type	[Display] This column displays the date of transaction. [Display] This column displays the posting date. [Display] This column displays the type of tansaction. [Display] This column displays the id of the customer on whom the




Column Name	Description
Dr/Cr	[Display] This column displays the type of tansaction i.e Debit or Credit.
Currency	[Display] This column displays the account currency.
Mnemonic	[Display] This column displays the transaction mnemonic.
Narration	[Display] This column displays the narration for the transaction.
Tran No	[Display] This column displays the transaction number.
Teller ID	[Display] This column displays the id of the teller who has performed the transaction.
Auth ID	[Display] This column displays the id of the authoriser who has authorised the transaction.

- 3. Select the originating branch and teller id from the drop-down list.
- 4. Enter the date range for which transactions are to be displayed.
- 5. Click the **Ok** button. The system displays the financial tansactions based on the criteria entered.



Audit Trail Financial Transactions Inquiry



6. Click the Close button.



1.8. BA777 - Audit Trail Inquiry for Non-Financial Txns

A bank can view the trail of both financial and non-financial transactions performed on **FLEXCUBE**. Only those non-financial transactions for which audit trails are required can be inquired in this inquiry. This requirement is maintained in Audit Task Maintenance. The audit trail can be queried using this maintenance on any of the following parameters:

- 1. Originating Branch
- 2. Task ID
- 3. Date Range
- 4. Teller ID
- 5. Authorizer ID
- 6. Action

Using this option, the date as well as the user that has done the addition / modification / deletion in Customer Master for Aadhaar related fields can be identified..

Definition Prerequisites

• BAM04 - BA Audit Tasks Maintenance-Inquire

Modes Available


Not Applicable

To inquire on audit trail

- 1. Type the fast path **BA777** and click **Go** or navigate through the menus to **Global Definitions > Other >Audit Trail Inquiry for Non-Financial Txns**.
- 2. The system displays the Audit Trail Inquiry for Non-Financial Txns screen.



Audit Trail Inquiry for Non-Financial Txns



Field Name	Description	
Action	[Mandatory, Dropdown]	
	Select the maintenance action being audited from the drop-down list.	
	The options are:	
	• Inquiry	
	Add	
	Modify	
	Delete	
	• All	
	All Unauthorised	
Originating Branch	[Optional, Pick List]	
	Select the originating branch, for which the audit trail is required, from the pick list.	
	The Branch Code will be defaulted to SMS User Branch.	




Description
[Optional, Alphanumeric, Five] Type the maintenance task code being audited.
[Optional, Alphanumeric, 48] Type the id of the customer (if any) on whom the maintenance was done
[Optional, Numeric, 14] Type the account number (if any) on which the maintenance was done.
[Optional, Pick List, dd/mm/yyyy] Select the date from which the data has to be retrieved from the pick list.
[Optional, Pick list, dd/mm/yyyy] Select the date up to which the data has to be retrieved from the pick list.
[Optional, Alphanumeric, 16] Type the id of the teller who performed the maintenance.
[Optional, Alphanumeric, 36] Type the id of the authoriser who authorised the maintenance.
[Optional, Pick-List] Select the file type and XF system from the pick list.
[Optional, Checkbox] By default, checkbox is selected for all action types except for the last option All Unauthorised. If checkbox is not selected, the record log will display changes done through FCR screens as well as uploads.

- 3. Select the action from the drop-down list and enter the required details in the remaining fields.
- 4. Click the **Inquire** button.
- 5. The system displays the records matching the entered criteria in the **Record Log** tab.
- 6. Double-click a record to view its details in the **Record Details** tab.
- 7. Reports can be executed by clicking Report button (Only Record Details Tab), Detail Report button (Only Record Details Tab for a particular selection) or Exhaustive Report button (Complete details of all Record Log records).
- 8. Click the Close button.



Record Log



Field Name	Description
Branch	[Display] This column displays the originating branch for which the audit trail is required.
Task ID	[Display] This column displays the maintenance task code being audited.
Posting Date	[Display] This column displays the date from which the data has to be retrieved.
Teller ID	[Display] This column displays the id of the teller who performed the maintenance.
Authorizer ID	[Display] This column displays the id of the authoriser who authorised the maintenance.
Action	[Display] This column displays the maintenance action being audited.




Field Name	Description
Txn Date	[Display] This column displays the date of transaction.
Key Field 1	[Display] This field display the value in key field 1.
Key Field 2	[Display] This field display the value in key field 2.
Key Field 3	[Display] This field display the value in key field 3.
Key Field 4	[Display] This field display the value in key field 4.
Key Field 5	[Display] This field display the value in key field 5.
Account No	[Display] This column displays the account number (if any) on whom the maintenance was done.
Customer ID	[Display] This column displays the id of the customer (if any) on whom the maintenance was done.
Source	[Display]
	This column displays the source.
	If changes are done from screen the value in source column is displayed as MOW, whereas the changes from uploads will have the value in source as GEFU ¹ .



¹(Generic External File Upload)

Record Details



Field Name	Description
Originating Branch	[Display] This field displays the originating branch for which the audit trail is required.
Task Description	[Display] This field displays the maintenance task description.
Posting Date	[Display] This field displays the date from which the data has to be retrieved.
Teller ID	[Display] This field displays the id of the teller who performed the maintenance.
Authorizer ID	[Display] This field displays the id of the authoriser who authorised the maintenance.



Field Name	Description
Account No	[Display] This field displays the account number (if any) on whom the maintenance was done.
Customer ID	[Display] This field displays the id of the customer (if any) on whom the maintenance was done
Column Name	Description
Туре	[Display] This column indicates if this is a Key to identify the particular record in the FLEXCUBE database.
	Blank value indicates that this is not a Key field.
Field	[Display]
	This column displays the field name in the database which has changed.
	For a Key field, the actual value will also be indicated here.
	For Task ID - BA995 field names Cod_cc_brn and Cod_Xfer_brnhave been relabled as Old Branch Code and New Branch Code respectively
Old Value	[Display]
	This column displays the previous value for the field being modified.
	This will be blank in case of Add option.
New Value	[Display]
	This column displays the new value for the field being modified.
	This will be blank in case of Delete option.

Note: 1)"From actual number of records, the system displays only 100 records."
2) The report output can then be viewed by navigating to the **Advice/Report Status Inquiry** option (Fast Path: 7778).



1.9. BAM04 - BA Audit Tasks Maintenance-Inquire

Using this option you can decide the auditing matrix for a particular task. This option can be used to define whether an audit is allowed on a maintenance option, and the actions (add, modify, delete, etc.) from that window should be recorded in an audit log.

All online transactions with financial impact except for Voucher Entry transaction are recorded in the Electronic Journal (EJ) stored at the respective branch. This maintenance is used for auditing all the other transactions. The audit log is stored in the central host and is common to all the branches.

Definition Prerequisites

Not Applicable


Modes Available

Add By Copy, Add, Modify, Delete, Cancel, Amend, Authorize, Inquiry. For more information on the procedures of every mode, refer to **Standard Maintenance Procedures**.

To add audit task details

- Type the fast path BAM04 and click Go or navigate through the menus to Global Definitions > Other > BA Audit Tasks Maintenance-Inquire.
- 2. The system displays the **BA Audit Tasks Maintenance-Inquire** screen.

BA Audit Tasks Maintenance-Inquire






Field Name	Description
Task ID	[Mandatory, Pick List]
	Select the task ID from the pick list.
	Task ID lists all the transaction codes maintained in the Transaction Mnemonic Codes (Fast Path: BAM15) option.
	This ID acts like a fast path. The fast path is a mnemonic which allows the user to access the options.
Task Description	[Display]
	This field displays the description of the selected task code.
Maintenance Options	5
Auditing Flag	[Mandatory, Check Box]
	Select the Auditing Flag check box, to enable the auditing flag.
	If the check box is selected, the details of the transaction will be recorded and stored for audit purposes.
	The maintenance options will also be enabled if the auditing flag is selected.
Inquire	[Conditional, Check Box]
	Select the Inquire check box, if you want the system to record the inquire actions and store the same for audit purposes.
	If the Inquire check box is selected it enables you to inquire about an authorised record.
	This field is enabled only if the Auditing Flag check box is selected.
Add	[Conditional, Check Box]
	Select the Add check box to enable you to add a new record to the selected task id.
	If the Add check box is selected, the system records the add actions and stores the same for audit purposes.
	This field is enabled only if the Auditing Flag check box is selected.
Modify	[Conditional, Check Box]
	Select the Modify check box to enable you to modify a record in the selected task id.
	If the Modify check box is selected, the system records the modify actions and stores the same for audit purposes.
	This field is enabled only if the Auditing Flag check box is selected.



Field Name	Description
Delete	[Conditional, Check Box]
	Select the Delete check box to enable you to delete a record from the selected task id.
	If the Delete check box is selected, the system records the delete actions and stores the same for audit purposes.
	This field is enabled only if the Auditing Flag check box is selected.

- 3. Click the Add button.
- 4. Select the task ID from the pick list.
- 5. Select the auditing flag check box and the appropriate maintenance option check boxes.

BA Audit Tasks Maintenance-Inquire



- 6. Click the **Ok** button.
- 7. The system displays the message "Record Added...Authorisation Pending..Click Ok to Continue". Click the **OK** button.
- 8. The audit task is added once the record is authorised.



1.10. BAM10 - Restricted Accounts Maintenance

Using this option you can restrict a particular teller from accessing the details of particular customer or GL accounts.

For example: If the bank decides to restrict the access to income and expenses accounts this option can be used. For a restricted account, the teller is not allowed to post any transaction, inquire, or maintain details.

Definition Prerequisite

Not Applicable


Modes Available

Add By Copy, Add, Modify, Delete, Cancel, Amend, Authorize, Inquire. For more information on the procedures of every mode, refer to **Standard Maintenance Procedures**.

To add a teller restricted account

- 1. Type the fast path **BAM10** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Others > Restricted Accounts Maintenance**.
- 2. The system displays the Restricted Accounts Maintenance screen.

Restricted Accounts Maintenance






Field Name	Description
User ID	[Mandatory, Pick List]
	Select the user ID from the drop-down list.
	These user IDs are added and maintained in the Defining User Profile (Fast Path: SMM02) option.
	Once added, this field cannot be modified or amended.
Account Type	[Mandatory, Drop-Down]
	Select the account type on which restriction is to be imposed from the drop-down list.
	The options are:
	 Customer A/C: It enables the Account No field in which you enter the customer account number.
	 General Ledger A/C: It enables the Account No field in which you enter the GL account number.
	Once added, this field cannot be modified or amended.
Account No	[Mandatory, Alphanumeric, 14]
	Type the account number based on the selected account type.
	The system does not validate the status of the account.
Customer Name	[Display]
	This field displays the name of the customer if you select the Customer A/C option from the Account Type drop-down list.
Remarks	[Optional, Alphanumeric, 40]
	Type the reason for the restriction. This is for information purposes only.

- 3. Click the **Add** button.
- 4. Select the user ID from the pick list and the account type from the drop-down list.
- 5. Enter the account number and press the **<Tab> or <Enter>** key.



Restricted Accounts Maintenance



- 6. Click the **OK** button.
- 7. The system displays the message "Record Added...Authorisation Pending...". Click the **OK** button.
- 8. The teller restricted account is added once the record is authorised.

