Oracle Banking Digital Experience

User Interface Build Guide Release 18.2.0.0.0

Part No. E97823-01

June 2018



User Interface Build Guide
June 2018

Oracle Financial Services Software Limited

Oracle Park

Off Western Express Highway

Goregaon (East)

Mumbai, Maharashtra 400 063

India

Worldwide Inquiries:

Phone: +91 22 6718 3000 Fax:+91 22 6718 3001

www.oracle.com/financialservices/

Copyright © 2018, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Table of Contents

1.	Pre	face	. 4
•	1.1	Intended Audience	4
	1.2	Documentation Accessibility	. 4
	1.3	Access to Oracle Support	. 4
	1.4	Structure	. 4
	1.5	Related Information Sources	. 4
2.	Use	er Interface Build	. 5

1. Preface

1.1 Intended Audience

This document is intended for the following audience:

- Customers
- Partners

1.2 Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at http://www.oracle.com/pls/topic/lookup?ctx=accandid=docacc.

1.3 Access to Oracle Support

Oracle customers have access to electronic support through My Oracle Support. For information, visit

http://www.oracle.com/pls/topic/lookup?ctx=accandid=info or visit

http://www.oracle.com/pls/topic/lookup?ctx=accandid=trs if you are hearing impaired.

1.4 Structure

This manual is organized into the following categories:

Preface gives information on the intended audience. It also describes the overall structure of the User Manual.

The subsequent chapter covers the following:

- Task performed in the User Interface Build
- Steps to run the User Interface Build

1.5 Related Information Sources

For more information on Oracle Banking Digital Experience Release 18.2.0.0.0, refer to the following documents:

- Oracle Banking Digital Experience Licensing Guide
- Oracle Banking Digital Experience Installation Manuals

2. User Interface Build

The current GUI build is based on Grunt.

Grunt is a JavaScript Task Runner - an automation tool for performing repetitive tasks like minification, compilation, unit testing, linting etc.

The tasks performed during a typical GUI build are:

- Pre Build checks (For Some development rules)
- ESLint for the JS files.
- SCSS compilation to CSS
- CSS optimization
- HTML minification
- JS minification
- r.js Optimization to pack all the dependencies of a component into single file.
- Updating the files with configuration specified in the properties.json file.
- Generate integrity for all component files.
- Cache Busting for resources.
- Generate resource bundle for English language

Running UI Build:

Follow steps below to run UI Build:

- First make sure that Node is is installed on the machine and grunt is available in global scope.
- Run npm install command inside _build folder.
- Now run build.sh to run the build.

The properties.json file under _build folder is a configuration file having parameters to be set during build time:

- resource_base_path: The base path from which the JS and HTML resources are to be fetched. It can be a relative path pointing to the same domain the page is running or fully qualified path to server. This can be configured to implement Domain Sharding. Default value of it set as "/"
- image_base_path: The base path from which the image resources are to be fetched. It can also be a relative path pointing to the same domain the page is running on or a fully qualified path to different server on which images are hosted. Default value of it set as "/images".
- 3. brand_base_path: This property is same as image_base_path used for those images which are brand dependent.
- 4. application_base_url: The application base resource path to which all the ajax calls are directed to. Default value of it set as "/digx".
- 5. application_base_url: This property hold the value of REST Application version. Default value of it set as "v1".

- 6. default_entity: This property hold the value of default entity of the application. This value used when entity not available to use. All request used this value
- 7. oam_base_url: This is the URL of OAM server for validating username and password.
- 8. obdx_base_path: To fund wallet using own bank account, need to redirect to bank portal.
- 9. secure_page: Set the protected page pathname, for example, "/pages/home.html".
- 10. public page: Set the public page pathname, for example, "/index.html".
- 11. rtl_languages: In this property user can define the list of languages which supports RTL(Right To Left). This property supports array of languages. Default value of it is ['ar']
- 12. localCurrency: This property stores the common currency used for implementation. This common currency is the default currency used in OBDX Application. All the origination request are using this property.
- 13. fb_sdk_url: This property stores the facebook SDK API URL. It is being used in OBDX Facebook component of social media module.
- 14. fb_api_key: This property stores the API key for the Facebook application. This API key is used for initializing and authenticating Facebook API.
- 15. linkedin_sdk_url: This property stores the Linkedin SDK API URL. It is being used in OBDX Linkedin component of social media module.
- 16. linkedin_api_key: This property stores the API key for the Linkedin app. This API key is used for initializing and authenticating Linkedin API.
- 17. google_map_sdk: This property is a unique key of google map to be integrated in OBDX application User need to enable the used API for respective key in on developer.google.com after creating the key from same.
- 18. google_map_url: This URL is used to launch Google Maps with the location details passed as query parameters. Default value of it set as http://maps.google.com/maps
- 19. web_analytics: This property used to determine the analytic engine. Application will search same name file under <CHANNEL>/web-analytics folder for the analytics.
- 20. axe_url: This property will required if run time accessibility check is required. This property hold the URL of axe js.

Home