

Oracle Financial Services Analytical Applications Reconciliation Framework

User Guide

Release 8.1.0.0.0

March 2023

F33269-01

ORACLE
Financial Services

OFS Analytical Applications Reconciliation Framework User Guide

Copyright © 2023 Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are “commercial computer software” pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

For information on third party licenses, click [here](#).

Document Control

Version Number	Revision Date	Change Log
1.2	March 2023	Updated the Dashboard: Drill Down section (Doc 34974777).
1.1	June 2022	Updated the Target Parameters Section (Doc 33326953).
1.0	July 2020	The initial release of the document

Table of Contents

1	Preface.....	7
1.1	Intended Audience.....	7
1.2	Access to Oracle Support	7
1.3	Related Information Sources.....	7
1.4	Conventions and Acronyms	8
2	Introduction.....	9
2.1	Features of OFSAA Reconciliation Framework.....	9
3	Process Flow.....	11
3.1	Overview.....	11
3.2	User Role and Actions	13
3.2.1	<i>Creating Application Users</i>	13
3.2.2	<i>Mapping Application User(s) to User Group</i>	13
3.3	Key Terms and Concepts	14
3.3.1	<i>Consolidation Type</i>	14
3.3.2	<i>Inherit to Child</i>	15
3.3.3	<i>Manual Reconciliation Definition</i>	15
3.3.4	<i>GL Level Reconciliation</i>	15
3.3.5	<i>Map Level Reconciliation</i>	16
3.4	Common Icons.....	16
4	Data Requirement.....	18
4.1	Setup Table.....	19
4.2	Stage Table	19
4.3	Product Processors.....	20
4.4	Measures List	21
5	Setting up Data	23
5.1	Entity Configuration	23
5.1.1	<i>Navigation within the Entity Configuration</i>	24
5.1.2	<i>To Configure New Entity</i>	26
5.1.3	<i>Balance measure to GL code mapping</i>	27

5.2	Type Configuration.....	28
5.2.1	<i>General Ledger to Product Processor</i>	29
5.2.2	<i>Ledger to Ledger</i>	34
5.2.3	<i>Management Ledger to Product Processor</i>	35
6	Reconciliation Rules	37
6.1	Navigation within the Summary Page	37
6.1.1	<i>Search Section</i>	38
6.1.2	<i>Definition List</i>	39
6.1.3	<i>Reconciliation Definition</i>	40
6.1.4	<i>Adjustment Attributes</i>	49
7	Execution of Rule	51
7.1	Execution Part.....	51
7.1.1	<i>Execute the rules Using Command Line Utility</i>	54
7.2	Process Flow Monitor	55
8	Process Execution Summary.....	57
8.1	Summary Part	57
9	Data Adjustment.....	60
9.1	Navigation within Data Adjustments Summary page.....	60
9.1.1	<i>Navigation within the Adjustment Entry Window</i>	61
9.1.2	<i>Navigation within the Adjustment Run Details page</i>	62
10	Reconciliation Summary	66
11	OFS Analytical Applications Reconciliation Framework Dashboards and Reports.....	73
11.1	Overview of OFS Analytical Applications Reconciliation Framework Reports and Dashboards	73
11.2	Accessing the Standard Reports and Dashboards.....	73
11.3	Report Descriptions	75
11.3.1	<i>Dashboard: Home</i>	75
11.3.2	<i>Dashboard: Threshold Breach</i>	79
11.3.3	<i>Dashboard: Reconciliation Execution Audit Trail</i>	82
11.3.4	<i>Dashboard: Drill Down</i>	82

12	Adding Custom Reconciliation Dimensions in Detailed Reconciliation Reports	84
13	Annexure A	85
13.1	Entity Details	85
13.2	Adjustment Auto Approval Concept	87
13.3	Data Model and Metadata Extensions	89
13.3.1	Steps to Configure an Additional Table in the Application	89
13.4	Procedure to Add Optional Dimensions	94
13.5	Optimization of GL Reconciliation Processing Package	94
13.6	Map Level Recon Parent Node Selection	95
13.7	GL Nodes Configuration	96
13.8	Hierarchy Refresh	96
13.8.1	Problem	96
13.8.2	Expected Behavior	96
13.8.3	Solution	97
13.8.4	Batch to be executed	97
13.9	Creating Filter for Load Run ID	97
13.10	Duplicate Adjustments	98
13.11	VPAT-keystrokes and access keys	98
13.11.1	GL Parameters	99
13.11.2	Target Parameters	99
14	Glossary	100
14.1	Adjustment Entry	100
14.2	Adjustment Entry Floor	100
14.3	Auto Approval	100
14.4	Global Threshold	100
14.5	Inherit to Child	100
14.6	Reconciliation Difference	101
14.7	Threshold	101
14.8	Positive Threshold	101
14.9	Negative Threshold	101
14.10	Threshold Breached Type	101

1 Preface

This chapter provides a brief description of the audience, the references, the organization of the user guide, and conventions incorporated into the user guide.

Topics:

- [Intended Audience](#)
- [Access to Oracle Support](#)
- [Related Information Sources](#)
- [Conventions and Acronyms](#)

1.1 Intended Audience

Welcome to Release 8.1.0.0.0 of the Oracle Financial Services Analytical Applications Reconciliation Framework User Guide.

This guide is intended for the following users:

- **Technical Analyst:** Ensures that the data is populated in the relevant tables as per the specifications. This user executes, schedules, and monitors the execution of Runs as batches.
- **Business Analyst:** Reviews the functional requirements and information sources, like reports.
- **Data Analyst:** Helps to clean, validate, and import data into the OFSAA Download Specification format.
- **Administrator:** Maintains user accounts and roles, archives data, loads data feeds, and so on. The administrator controls the access rights of users.

1.2 Access to Oracle Support

Oracle customers have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info>

Or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

1.3 Related Information Sources

For more information, see the following documents in OTN Documentation Library:

- [Oracle Financial Services Analytical Applications Reconciliation Framework Pack Installation Manual Release 8.1.0.0.0](#)

1.4 Conventions and Acronyms

Table 1 List of the Conventions and Definition.

Conventions	Description
Actions are indicated in Bold .	
Command or query is indicated in <code>Monospace</code> .	
AIX	Advanced Interactive Executive
OFSAAI	Oracle Financial Services Analytical Applications Infrastructure
OFS AAAI	Oracle Financial Services Advanced Analytical Applications Infrastructure Application Pack
RHEL	Red Hat Enterprise Linux
ML	Maintenance Level
R	Third-party open-source software. Open-source R is governed by the GNU General Public License (GPL).
PP	Product Processor
GL	General Ledger
NPT	Negative Percentage Threshold
PPT	Positive Percentage Threshold
NAT	Negative Absolute Threshold
PAT	Positive Absolute Threshold (PAT)
NB	Not Breached
Oracle R Distribution	Oracle R Distribution is Oracle's free distribution of open-source R.
Oracle R Enterprise	Oracle R Enterprise integrates R, the open-source scripting language and environment, with Oracle Database.
Atomic Schema	Database schema where the application data model is uploaded.
Config Schema	Database schema which contains setup related configurations and metadata.
Infodom	Information Domain

2 Introduction

Oracle Financial Services Analytical Applications (OFSAA) Reconciliation Framework, Release 8.1.0.0.0 (GL Reconciliation) reconciles the balances from the operational systems of a bank with the balances as maintained in General Ledger (hereinafter referred to as *GL*) of the bank. With this application, banks can also reconcile between General Ledgers maintained in the bank. The balances in the GL of a bank are the ones that are audited and duly certified by the internal and external auditors. The GL balances are considered to be the final version of the *truth* in a bank. Therefore, all data extracted from any other operating systems of a bank must be reconciled with the balances maintained in the GL to ensure that they are complete, accurate, and comprehensive. It then acts as an authentic and reliable base for any further decision making.

2.1 Features of OFSAA Reconciliation Framework

The Oracle Financial Services Analytical Applications Reconciliation Framework, Release 8.1.0.0.0 primarily compares the balances received from the operational systems with the balances as received from the bank's financial systems - which are reflected in the GL - and thus finds out differences between the two, if any. Based on such reconciliations definition, adjustment entries are passed where it is required to ensure that the data from the operational systems tally with the balances in the GL. If there is scope for any corrections, then these are allowed on the data received from operational systems. The balances received from the bank's financial systems are deemed to be true and correction of these balances is strictly not permitted. The Oracle Financial Services Analytical Applications Reconciliation Framework, Release 8.1.0.0.0 also can compare the balances between the General Ledgers maintained by the bank and computes differences if any.

Thus, GL Reconciliation definition, on one hand, computes the difference, if any, between the operating system and the financial system of the bank, while, on the other hand, brings the operational system at par with the financial system bypassing adjustment entries or correction entries, or both.

Broadly, Oracle Financial Services Analytical Applications Reconciliation Framework, Release 8.1.0.0.0, has the following features:

- Computes the GL Reconciliation differences.
- Option to include existing adjustment balances of the target table also in the reconciliation process.
- Attribute values of the adjustments that are created can default in various ways like, for example using a static value.
- Ability to post differences as adjustment balances in the target table based on the granularity of reconciliation dimension plus other columns of the target table together.
- Post adjustment entries when differences are encountered within the specified threshold and reports these adjustment entry details. For more information about the threshold, see the [Glossary](#).
- Ability to select the GL reconciliation parameters such as:
 - The GL to be considered for the process.
 - The operational system data to be reconciled.
 - The threshold and adjustment Entry floor to be considered before passing adjustments. For more information on threshold and adjustment entry floor see the [Glossary](#).

- Ability to monitor and track the status of the GL reconciliation process through a series of reports.
- A different allocation ratio can be fixed for passing the adjustment entry into the different Product Processors (PP) that participate in the mapping. Product Processor is an entity in the OFSAAI System used to store data that are received from the operational system of the bank.
- The GL Reconciliation application handles the consolidation concept as prescribed by Basel II guidelines. It handles intercompany adjustments by ignoring the intra-group transactions while summing up balances from the operational system.

NOTE

User Mapping: The Oracle Financial Services Analytical Application Reconciliation Framework, Release 8.1.0.0.0, is designed only to compare the balances in the operating system with the balances in the financial system of the bank. It does not aim at finding out the cause and source of the difference.

3 Process Flow

This chapter provides an understanding of the Oracle Financial Services Analytical Application Reconciliation.


Topics:

- [Overview](#)
- [User Role and Actions](#)
- [Key Terms and Concepts](#)
- [Common Icons](#)

3.1 Overview

The GL structure is designed in such a way that, it facilitates verification of the differences which arise by comparing the GL source systems with the bank's operational systems (Product Processor within OFSAA). At a global level, you must input GL and Product Processor setting details which form a base at a reconciliation level. The input provided in the Settings window is reflected at a global level.

Figure 1: Settings window Process Flow




The predefined reconciliation definition types that can be used during a reconciliation definition are:

- General Ledger to Product Processor
- Ledger to Ledger
- Management Ledger to Product Processor


The reconciliations are defined, which forms a part of execution and data verification. This can be defined as **Manual Reconciliation Definition**, as shown in *Figure 2*. This reconciliation is defined in the Reconciliation Management screen. For more information on **Manual Reconciliation Definition**, see the [Key Terms and Concepts](#).

Figure 2: Reconciliation Definition Process Flow



After reconciliations are defined, executions are performed from the Process Modelling Framework of OFSAA infrastructure. When reconciliation differences arise, then adjustment entries are passed (either manually or by the application).

Figure 3: Reconciliation Rule Definition Process Flow



3.2 User Role and Actions

NOTE It is imperative to map each function to a specific user role to be able to work with the OFSAA Reconciliation Framework application. The responsibility to map the various function codes of the OFSAA Reconciliation Framework application (such as Add, View, and Delete access) to a particular user role lies with the System Administrator.

3.2.1 Creating Application Users

To create application users in the OFSAA setup, see the User Administrator section in the [Oracle Financial Services Analytical Applications Infrastructure User Guide](#).

3.2.2 Mapping Application User(s) to User Group

For details, see the User Administrator section in the [Oracle Financial Services Analytical Applications Infrastructure User Guide](#).

Beginning with the OFSAA 8.1.0.0.0 release, with the installation of the OFSAA Reconciliation Framework application pack, preconfigured Application user groups are seeded. These user groups are unique to every OFSAA Application Pack and have application roles pre-configured.

For more information on seeded User Groups, see OFSAA Reconciliation Framework application pack User Group Names.

Map the application user (s) to the respective Application User Group (s) and subsequently authorize the entitlements by logging in as SYSAUTH (System Authorizer) user.

For details, see the Mapping/Unmapping Users section in the [Oracle Financial Services Analytical Applications Infrastructure User Guide](#).

The **User UserGroup Map** facilitates you to map user(s) to a specific user group which in turn is mapped to a specific Information Domain and role. Every UserGroup mapped to the infodom must be authorized. Else, it cannot be mapped to users.

The *User UserGroup Map* screen displays details such as User ID, Name, and the corresponding Mapped Groups. You can view and modify the existing mappings within the User UserGroup Maintenance screen.

With the installation of the OFSAA Reconciliation Framework Pack, pre-configured Application user groups are seeded. These user groups are unique to every OFSAA Application Pack and have application roles pre-configured.

You can access the User UserGroup Map by expanding the **User Administrator** section within the tree structure of the LHS menu.

After the user is created for Reconciliation Framework, map them to the following user groups:

1. Recon Administrator
2. Recon Framework Analyst
3. Recon Framework Authorizer
4. Adjustment Super Group

3.3 Key Terms and Concepts

This section aims to explain the key terms and concepts of the OFSAA Reconciliation Framework.

Topics:

- [Consolidation Type](#)
- [Inherit to Child](#)
- [Manual Reconciliation Definition](#)
- [GL Level Reconciliation](#)
- [Map Level Reconciliation](#)

3.3.1 Consolidation Type

There are two consolidation types supported by the application:

- [Solo](#)
- [Consolidated](#)


3.3.1.1 Solo

When a legal entity is selected with consolidation type as *Solo*, then all the exposures of that particular legal entity are selected for processing. Manual reconciliation definition can process solo legal entity data.

3.3.1.2 Consolidated

When a parent legal entity is selected as *Consolidated*, then all the exposures of that legal entity and exposure of each level (or levels) of descendant child legal entities (without intra-group exposures) are selected for processing. In intra-group exposures, the counterparty is a child descendant of any level. For an intra-group scenario (where GL structure has specific intra-group GL code in addition to regular GL codes), intra GL codes are considered only from the GL side for processing. Non-Intra is a scenario where no GL codes are present for reconciliation definition.

Figure 4: Consolidated Process Flow



In this case, LE 1 is the parent legal entity, and LE2 and LE3 are the immediate child legal entities of LE1. Similarly, LE4 and LE5 are immediate child legal entities of LE2, but second-level descendant legal entities of LE1.

If you select LE2 (parent) for consolidated treatment, then exposure to LE 4, LE 5, and LE7 are considered as intra-group exposures.

NOTE The application only aggregates data on the PP side for a *consolidation* reconciliation type; such aggregation is only to reconcile data and does not consider minority or majority holdings.

Intra-group exposures are identified by the customer reference ID in the Product Processor. For LE2, if the customer reference ID is LE4, LE5, and LE7, then these are considered as intra-group exposures. Exposures to LE3 or LE6 are not considered as intra-group exposures as they are not the child descendant of LE 2. If you select LE7 for consolidated treatment, then no exposures are considered as intra-group exposure since LE7 has no child legal entity.

NOTE Intra-group exposures are identified by the customer reference ID in the PP table.

3.3.2 Inherit to Child

This feature is used to find child legal entities under the hierarchy node of a Legal Entity that is selected at the definition level. If this feature is used when defining the GL Reconciliation rule, then all child nodes will participate in the reconciliation process.

3.3.3 Manual Reconciliation Definition

In manual reconciliation definition, user input is sought on the GL side and PP side to determine the course of reconciliation. This is applicable for both GL level and map level reconciliation. In GL level reconciliation, unique GL codes are identified from the GL code mapping. In the map level, GL codes do not form a part of the reconciliation definition. A manual reconciliation definition can be used for a solo or consolidated legal entity. Reconciliation definition for a consolidated GL, having an intra-group GL structure, is computed from GL data and not from PP data. Therefore, any account present in the PP but unavailable in GL is not captured in the reconciliation definition.

3.3.4 GL Level Reconciliation

In GL level reconciliation the difference between GL system and Product Processors systems at each reconciliation dimension node level within a GL code is identified. For manual reconciliation definition, unique GL codes are identified from the GL side. If it is at the solo level, then exposures originating in the legal entity are selected. If it is at the consolidated level, then exposures originating in the selected legal entity and its child entities (with or without intra-group exposures depending on GL structure) are selected.

The adjustment entry allocation depends on the reconciliation type selected. In GL level reconciliation after a definition is executed, the differences that emerge as a part of the reconciliation definition (GL–PP level reconciliation) are reported in the adjustment entry table. This table shows all the entries of an executed map which requires adjustment. In GL level reconciliation, the difference in amount can either be posted to Product Processors or an external table. For more information on the external table, see the [Data Requirement](#).

NOTE In GL level reconciliation the adjustment allocation is always automatic, that is, you do not have the option of editing the allocation ratio

3.3.5 Map Level Reconciliation

In map level reconciliation the difference between GL data and PP data at each reconciliation dimension node level across all PPs, are identified. Unlike GL level reconciliation, map level reconciliation is computed at an aggregate level of the reconciliation definition; by ignoring the GL code and by considering reconciliation dimensions. Map level reconciliation is applied at the legal entity level - either solo or consolidated. If it is at the solo level, then exposures originating in a particular legal entity are selected. If it is at the consolidated level, then exposures originating in the selected legal entity and its child entities (excluding intra-group exposure depending on GL structure) are selected.

NOTE In a map level reconciliation, adequate filters for the PP data must be selected to ensure that actual data selected on both sides are the same.







The adjustment entry allocation depends on the reconciliation type selected. In map level reconciliation, once a definition has executed the differences that emerge as a part of the reconciliation (General Ledger–Product Processor level reconciliation) are reported in the adjustment entry table. This table shows all the entries of an executed map which requires adjustment. In map level reconciliation, the difference in amount can either be posted to Product Processors or an external table. In map level reconciliation, the adjustment allocation can either be automatic or manual.

3.4 Common Icons

The common icons which you come across in the GL reconciliation UIs are as follows.

Table 2: List of common icons and their descriptions

Buttons Name	Icon	Description
Pagination Options		It helps in navigating from one page to another.
View		It helps to view details of GL reconciliation parameters.

Buttons Name	Icon	Description
Edit		It allows you to update details of GL reconciliation parameters.
Add		Helps in defining new GL reconciliation parameters
Copy		It helps to copy the details of GL reconciliation parameters.
Delete		Click this icon to delete the GL reconciliation parameters.
Search		The search feature allows you to search for the entry you are looking for instead of manually searching for data.
Reset		The Reset icon refreshes the field name back to the default blank field.


4 Data Requirement

After the OFSAAI platform is deployed, the OFSAA Reconciliation Framework has to be deployed. For more information on installing the OFSAA Reconciliation Framework, see the [OFSAA Reconciliation Framework, Release 8.1.0.0.0 Installation Manual](#).

You now have the choice to perform model upload through the installer or manually. To perform model upload manually, follow these steps:


1. Click **Data Model Management** on the left pane of the OFSAAI platform.
2. Navigate to **Data Model Management**, and select **Data Model Maintenance**.

Figure 5: Business Model Upload Summary Page



3. Click **+ Add** icon to open up the **Business Model Upload** window.

Figure 6: Business Model Upload Window



4. In the **Business Model Upload** window, enter the Mandatory fields.
5. In the **Upload Details** pane, enter the Model **Name** and Select **Upload Options** as **Erwin**.
6. Select the **Upload Model** from the drop-down list. You can select **Incremental**, **Rebuild**, or **Sliced** upload mode.
7. Select the **Object Registration Mode** from the drop-down list as **Full Object Registration** or **Incremental Object Registration**. You can select **Incremental Object Registration** for the Upload Mode as **Incremental** and **Sliced**. It is recommended to select incremental only if the changes are minimal.
8. Select the **Erwin XML** or **Database XML** file for upload from the **File Name** drop-down list.
9. In the **Additional Options** pane, select the required options.

10. Click the **Upload Model** icon to upload the model.

For more details, see the **Model Upload Utility** section of the [OFS Analytical Applications Infrastructure User Guide](#).

The most important activity, to commence working on the application, is the configuration of data. Data can be divided into two categories:

- **Setup Table:** SETUP_GL_DIMENSIONS_MAP
- **Stage Table:** STG_SRC_GLCODE_MAP

A setup table is a set of data that is static and does not change at regular intervals. This is a set of seeded data that refers to the initial data that is provided with the application. Stage table data consists of Product Processors and a set of other stage tables for which you can see the Download Specifications document. The seeded tables of Currency and GAAP Codes can be edited to add specific currencies and GAAP codes in use.

Topics:

- [Setup Table](#)
- [Stage Table](#)
- [Product Processors](#)

4.1 Setup Table

Additional dimensions can be made available for the Reconciliation types using the below-mentioned setup table (**SETUP_GL_DIMENSIONS_MAP**). This table is being used to set up the additional dimensions used for the reconciliation process.

Figure 7: Setup Table

V_TABLE_NAME	V_HIERARCHY_CODE	V_HIERARCHY_NAME	F_RECON_OR_MANDATORY
DIM_GEOGRAPHY	HGL003	Branch for Reconciliation	R
DIM_ORG_UNIT	HGL006	Organization Unit for Reconciliation	R

4.2 Stage Table

While uploading data into **STG_SRC_GLCODE_MAP** ensure the following:

If a new set of data is to be added in the table **STG_SRC_GLCODE_MAP**, then ensure that this data is added to the existing set of records as incremental data for the batch to be executed successfully. Once new data is uploaded, for all subsequent executions see the new mapping. Execution based on old GL code mapping is not permitted.

The application automatically matches similar GL codes from the Product Processor entity and general ledger entity and the reconciliation definition difference is computed. However, you must create mappings when GL codes differ across the Product Processor entity and general ledger entity.

Table 3: Stage Table

FIC_MIS_DATE	V_SOURCE_GL_CODE	V_TARGET_GL_CODE
12/31/2010	GL1001	GL1001

For any other not null attribute a dummy value can be provided.

4.3 Product Processors

GL Reconciliation application also requires you to specify the physical column names of (for example, End of Period Balance (N_EOP_BAL), Accrued Interest) Product Processor (PP) entities, for which the reconciliation definition process must be executed. See [Setting up Data](#) for more information.

NOTE You also have the option to reconcile GL codes with other operational data used by the bank, which does not flow into the standard Product Processors configured in the application. For more information on adding operational data tables to the data, see [Data Model and Metadata Extensions](#).

The list of Product Processor supported by this application is as follows:

Table 4: Product Processor supported by this application

Product Processor	Table Name
BILLS	STG_BILLS_CONTRACTS
BORROWINGS	STG_BORROWINGS
CARDS	STG_CARDS
CASA	STG_CASA
EQUITY	STG_EQUITY_EXPOSURES
FUTURES	STG_FUTURES
FX_CONTRACTS	STG_FX_CONTRACTS
INVESTMENTS	STG_INVESTMENTS
LC	STG_LC_CONTRACTS
LEASES_CONTRACTS	STG_LEASES_CONTRACTS
LOANS	STG_LOAN_CONTRACTS
MM CONTRACTS	STG_MM_CONTRACTS
MUTUAL_FUNDS	STG_MUTUAL_FUNDS
OD	STG_OD_ACCOUNTS
OPTIONS	STG_OPTION_CONTRACTS
REPO_CONTRACTS	STG_REPO_CONTRACTS
TD_CONTRACTS	STG_TD_CONTRACTS

4.4 Measures List

The following table provides the list of entity name and its corresponding measures.

Table 5: Entity name and its measures list


Entity Name	Measures
Stage General Ledger Data	<ul style="list-style-type: none"> • Amount In Accounting Currency • Amount In Local Currency
Stage Management Ledger	<ul style="list-style-type: none"> • Average Balance Amount • Balance • Movement Amount • Movement Mtd • Movement Ytd
Stage Repo Contracts	<ul style="list-style-type: none"> • End Of Period Balance • Write Off Amount
Stage Option Contracts	<ul style="list-style-type: none"> • End Of Period Balance
Stage Investments	<ul style="list-style-type: none"> • End Of Period Balance
Stage Loan Contracts	<ul style="list-style-type: none"> • Accrued Interest • End Of Period Balance • End Of Period Book Balance • Provisions Amount
Stage Casa Account	<ul style="list-style-type: none"> • Commission Amount • End Of Period Balance • Write Off Amount
Stage Cards	<ul style="list-style-type: none"> • Accrued Interest • Account Attrition Score • End Of Period Balance
Stage Term Deposit Contracts	<ul style="list-style-type: none"> • Commission Amount • End Of Period Balance
Stage Mutual Funds	<ul style="list-style-type: none"> • Commission Amount • End Of Period Balance
Stage Futures Contracts	<ul style="list-style-type: none"> • End Of Period Balance • Write Off Amount
Stage Leases Contracts	<ul style="list-style-type: none"> • End Of Period Balance • Write Off Amount
Stage Bill Contracts	<ul style="list-style-type: none"> • End Of Period Balance
Stage Money Market Contracts	<ul style="list-style-type: none"> • Commission Amount • End Of Period Balance
Stage Letter Of Credit Contracts	<ul style="list-style-type: none"> • End Of Period Balance

Entity Name	Measures
Stage Borrowings	<ul style="list-style-type: none">• Commission Amount• End Of Period Balance
Stage Foreign Exchange Contracts	<ul style="list-style-type: none">• End Of Period Balance
Stage Over Draft Accounts	<ul style="list-style-type: none">• End Of Period Balance• Write Off Amount

5 Setting up Data

This section provides information on the Setup page related to the setting and maintenance of metadata related to the reconciliation rules. This is a one-time activity and defines the boundaries of GL reconciliation. The Setup page consists of **Entity Configuration** and **Type Configuration**.

Figure 8: Setup Navigation Pane



The **Configuration** screens present in the above links allows you to perform the following:

- **Entity Configuration:**
 - Including the Reconciliation Entities in the GL Reconciliation process.
- **Type Configuration:**
 - Defining various types of reconciliations as a part of a standard release, where the **Stage Ledger Data** contains the Ledger data. Other entities, having a Dataset with the GL dimension, can participate as GL.
 - The mandatory dimensions, optional dimensions, and MEMBRES OF THE DIMENSION participating in the GL Reconciliation process.


Topics:

- [Entity Configuration](#)
- [Type Configuration](#)

5.1 Entity Configuration

From the **Oracle Financial Services Analytical Applications Reconciliation Framework** Navigation List, select **Reconciliation Framework**, select **Setup**, and then select **Entity Configuration**.

Figure 9: Entity Configuration Page



NOTE

The Reconciliation Entities window consists of the predefined data. You can **Add**, **View**, **Edit**, or **Delete** the reconciliation entities using these predefined data.

Topics:

- [Navigation within the Entity Configuration](#)
- [To Configure New Entity](#)

5.1.1 Navigation within the Entity Configuration

When you navigate to the **Reconciliation Entities** screen, the settings are presented as a list. This **Settings** page displays the following information about the entity:

- **Entity Name:** The name of the Reconciliation Entity.
- **Grain:** The Granularity of data within the entity, for example, Ledger, and Account.
- **DataSet:** Add the Dataset from the drop-down list for the selected Entity.

You can add the new entities in this **Reconciliation Entities** window, each entity can further be viewed, edited, or deleted.

You can perform various activities on the selected entity in the **Reconciliation Entities** window.

- **Add:** Click **Add** icon to add a new entity to the **Reconciliation Entities** window. The **Add Entity** window is displayed.

Figure 10: Add Entity Window

Enter the information in the following fields:

- **Grain:** The Granularity of data within the entity, ex, Ledger, Account.
- **Entity:** The name of the Reconciliation Entity.
- **DataSet:** Add the Dataset from the drop-down list for the selected Entity.
- **Measures:** Select the relevance Balance attribute. Multiple selections are permitted.
- **View:** Click **View** icon to view the detailed definition of an entity in read-only mode. For example, the following window is displayed for the **Stage General Ledger Data** is displayed.

Figure 11: View Entity Window

- **Edit:** Click the **Edit** icon to modify the entity settings. The Edit functionality is only enabled for **DataSet** and **Measures**.

NOTE If you modify **DataSet** and **Measures** it might impact the rules in which this entity is being used.

Figure 12: Edit Entity Window

- **Delete:** Click the **Delete** icon to delete the selected entity. A Confirmation pop-up window appears before deleting the entity.

NOTE

You cannot delete if the entity if it is used in the Type Configuration and subsequently in the Reconciliation Rules.

5.1.2 To Configure New Entity

To configure the new entity and its respective measures, follow the following steps:

1. Insert data into the SETUP_GL_GRAIN_ENTITY_MAP Table:
 - V_GRAIN_CODE column takes grain code of entity based on entity, grain codes like Product Processor (PP), Ledger (GL), and Management Ledger (MGL).
 - V_TABLE_NAME column takes an entity physical name.

For example:

V_GRAIN_CODE	V_TABLE_NAME
PP	STG_TD_CONTRACTS

2. Insert data into the SETUP_BAL_GL_CODE_MAP Table:
 - V_TABLE_NAME column takes entity physical name.
 - V_BALANCE_COL_NAME column takes entity balance column physical name.
 - V_GL_CODE_COL_NAME column takes entity GL Code column physical name.

For example:

V_TABLE_NAME	V_BALANCE_COL_NAME	V_GL_CODE_COL_NAME
STG_TD_CONTRACTS	N_EOP_BAL	V_GL_CODE

3. Insert data into the SETUP_GL_ENTITY_ATTRIBUTES Table:

- V_TABLE_NAME column takes entity physical name.
- V_ATTR_LOGIC_COL_NAME column takes attribute logical name.
- V_ATTR_COL_NAME column takes attribute physical name.
- F_GL_MEASURE_FLAG column takes measure flag (N or Y), to say an attribute is a measure or not.
- V_ATTRIBUTE_CODE column takes a fixed constant attribute code.
- Entry for entity grain code PP.

For example:

V_TABLE_NAME	V_ATTR_LOGIC_COL_NAME	V_ATTR_COL_NAME	F_GL_MEASURE_FLAG	V_ATTRIBUTE_CODE
STG_TD_CONTRACTS	Exposure Id	v_account_number	N	EXPID
STG_TD_CONTRACTS	Extraction Date	fic_mis_date	N	EXTDATE
STG_TD_CONTRACTS	Customer Reference Code	v_cust_ref_code	N	CUSTREFCODE

4. Navigate to the **Entity Configuration** screen, create a new entry for the same entity configured earlier, and click the **Save** button.
5. Navigate to the **Type Configuration** screen, add this newly created entity as a target entity to a particular type and save the type, so that type will be updated with the new entity.

5.1.3 Balance measure to GL code mapping

The following table provides the balance measure to GL code mapping present in the installation kit.

Table 6: Balance measure to GL code mapping

Entity Names	Balance Attribute	GL Code Attribute
Stage Bill Contracts	End Of Period Balance	General Ledger Account Code
Stage Borrowings	Commission Amount	Commission GI Code
Stage Borrowings	End Of Period Balance	General Ledger Account Code
Stage Cards	Commission Amount	Commission GI Code
Stage Cards	End Of Period Balance	General Ledger Account Code
Stage Cards	Write Off Amount	Write-Off GI Code

Entity Names	Balance Attribute	GL Code Attribute
Stage Casa Account	Commission Amount	Commission GI Code
Stage Casa Account	End Of Period Balance	General Ledger Account Code
Stage Casa Account	Write Off Amount	Write-Off GI Code
Stage Futures Contracts	End Of Period Balance	General Ledger Account Code
Stage Futures Contracts	Write Off Amount	Write-Off GI Code
Stage Foreign Exchange Contracts	End Of Period Balance	General Ledger Account Code
Stage Letter Of Credit Contracts	End Of Period Balance	General Ledger Account Code
Stage Investments	End Of Period Balance	General Ledger Account Code
Stage Loan Contracts	Commission Amount	Commission GI Code
Stage Loan Contracts	End Of Period Balance	General Ledger Account Code
Stage Loan Contracts	Write Off Amount	Write-Off GI Code
Stage Leases Contracts	End Of Period Balance	General Ledger Account Code
Stage Leases Contracts	Write Off Amount	Write-Off GI Code
Stage Mutual Funds	Commission Amount	Commission GI Code
Stage Over Draft Accounts	End Of Period Balance	General Ledger Account Code
Stage Over Draft Accounts	Write Off Amount	Write-Off GI Code
Stage Mutual Funds	End Of Period Balance	General Ledger Account Code
Stage Money Market Contracts	Commission Amount	Commission GI Code
Stage Money Market Contracts	End Of Period Balance	General Ledger Account Code
Stage Option Contracts	End Of Period Balance	General Ledger Account Code
Stage Repo Contracts	End Of Period Balance	General Ledger Account Code
Stage Repo Contracts	Write Off Amount	Write-Off GI Code
Stage Term Deposit Contracts	Commission Amount	Commission GI Code
Stage Term Deposit Contracts	End Of Period Balance	General Ledger Account Code


5.2 Type Configuration

The Type Configuration page lists the predefined reconciliation definition types that can be used during a reconciliation definition. These configurations are:

- General Ledger to Product Processor
- Ledger to Ledger
- Management Ledger to Product Processor

You can **View**, **Edit**, or **Delete** these configurations from the Type Configuration page.

Figure 13: Type Configuration Page



The Type Configuration page provides options to provide the following actions:

- **View:** Click **View** icon, to view the **Settings** and **Dimensions** of the reconciliation type on a read-only basis.

The view displays two panes:

- Settings
- Dimensions

- **Edit:** Click **Edit** icon, to modify the **Settings** and **Dimensions** of the reconciliation type. It allows you to modify an existing reconciliation definition except for the Name.

Edit displays two panes:

- Settings
- Dimensions

- **Delete:** Click **Delete** icon, to delete the **Settings** and **Dimensions** of the reconciliation type that you wish to delete. A dialog box is displayed if the selected Reconciliation type is used in any rule, with the following message *“This Recon Type is used by some Rules, unable to delete the Recon Type”*.

Topics:

- [General Ledger to Product Processor](#)
- [Ledger to Ledger](#)
- [Management Ledger to Product Processor](#)

5.2.1 General Ledger to Product Processor

General Ledger to Product Processor Reconciliation is to identify the difference between GL system and the Product Processor data. It nullifies the difference by posting the adjustment entries up to the amount of difference.

If the reconciliation difference is greater than the threshold value, then the difference is reported. A threshold is specified Product Processor level and these values are specified in the terms of percentage or an absolute amount. The Percentage value represents the difference in percent to the General Ledger side amount. If the threshold is specified in the terms of the amount, then it must be read in connection with a currency of the threshold amount. The reconciliation difference is reported in the base currency. If the currency specified here is different than that of the reconciliation dimension, then the difference amount must be converted in the threshold currency using the exchange rate of execution date or the latest available rate of the five preceding days. While

reconciling General Ledger and Product Processor, differences can arise in two ways: either when the General Ledger amount is greater than the Product Processor amount or when the General Ledger amount is less than the Product Processor amount. Hence, there are two threshold values to address differences arising out of this condition. For more information, see [Target Parameters](#).

- GL to PP reconciliation is performed at the following levels:
 - GL Level Reconciliation
 - Map Level Reconciliation
- GL to PP reconciliation can be defined in the following way:
 - Manual Reconciliation Definition

Topics:

- [Navigation within the Settings](#)
- [Navigation within the Dimensions](#)

5.2.1.1 Navigation within the Settings

You can navigate to **Type Configuration**, and select **General Ledger to Product Processor**, to **View**, **Edit**, or **Delete** General Ledger to Product Processor type.

It consists of two tabs:

- Settings
- Dimensions

The **Settings** tab displays the name and the description of the reconciliation type that you want to view (General Ledger to Product Processor configuration for this section).

It is further divided into two panes:

- **Source:** This pane displays the **Source Grain** and the **Source Entity** for General Ledger to Product Processor type. The Stage General Ledger data is the default source entity used for reconciliation definition.
- **Target:** This pane displays the **Target Grain** and **Target Entity** for General Ledger to Product Processor type. The Target entities refer to the Stage instrument tables (Product Processors) of the Oracle Financial Services Data Foundation.

When you click **View** icon, you can only view the selected reconciliation type, on the Settings page. All the panes in the Settings page are disabled for modifying the Reconciliation type in the Read-only mode.

Click the **Edit** icon to edit the selected reconciliation type. All the panes in the **Settings** tab are enabled for editing except the Name.

Figure 14: General Ledger to Product Processor Settings Tab for Edit

The screenshot shows the 'Type Configuration' interface with the 'Dimensions' tab selected. The interface includes a 'Save' button and a 'Cancel' button in the top right corner. Below the navigation bar, there are two main sections: 'Source' and 'Target'. The 'Source' section has two dropdown menus: 'Source Grain' set to 'Ledger' and 'Source Entity' set to 'Stage General Ledger Data'. The 'Target' section has two dropdown menus: 'Target Grain' set to 'Account' and 'Target Entity' set to 'Stage Cards' and 'Stage Loan Contracts'.

5.2.1.2 Navigation within the Dimensions

The **Dimensions** tab consists of two panes such as **Dimension Mapping**, and **Dimension Attribute Selection**. The dimensions such as Legal Entity, Currency, and GAAP Code are mandatory dimensions and must be selected to proceed with GL Reconciliation executions.


NOTE It is assumed that mandatory reconciliation dimensions are present in all the bank's GL source systems.

- **Dimension Mapping:** This pane displays the **Legal Entity**, **Currency**, and **GAAP Code** for the selected dimension. The dimensions **Legal Entity**, **Currency**, and **GAAP Code** must be selected to proceed with the GL Reconciliation executions. You can configure additional optional dimensions based on the requirement.
- **Dimension Attribute Selection:** This pane allows you to map the respective dimension attribute to each of the entities selected in the Settings view. As an example, the **Stage Cards**, **Stage General Ledger Data**, and **Stage Loan Contracts** have been configured for dimensions.

When you click **View** icon in this pane, the corresponding mappings of the entities present in the Dimension mapping pane are displayed with the selected dimension attributes in a read-only mode.

NOTE The Dimensions tab functionalities remain same for all the three types of configurations.


Figure 15: Dimensions Tab for View



5.2.1.2.1 Editing Dimension

When you select the **Dimension** from the drop-down list in this pane, the mapping of the respective dimension is done for all the entities defined in the **Settings** tab.

Figure 16: Dimensions Tab Edit



You can select the optional dimensions such as **Product**, **Organization Unit**, and so on and map these dimensions to the Reconciliation type, so for each dimension respective attributes of the entities must be selected. For more information on the optional dimensions, see the [Data Requirement](#) section.


By default, these mandatory dimensions **Legal Entity**, **Currency**, and **GAAP Code** are available in the reconciliation type.

For example, only a Legal Entity dimension must be selected against the Legal Entity and any other dimension cannot be selected. You are expected to select a valid Legal Entity, GAAP, and Currency hierarchy while configuring the mandatory dimensions.

You can select one or more entities to map the attributes for the respective dimension.

Select any of the entities within the **Dimension Attributes Selection** pane to enable the **Attribute** icon. Click **Attributes** to add optional Dimension Attributes.


Figure 17: Attribute Icon on Dimensions Tab



The **Attributes list** displays the list of the attributes that can be associated with the selected Dimension Attributes, as shown in *Figure 18*. The attribute list shows the combined attributes for all the Stage tables selected.

Select the attributes and click the **OK** icon.

Figure 18: Attribute List window



5.2.2 Ledger to Ledger

In the **Ledger to Ledger** (GL to GL) reconciliation, the difference between two sources of the GL for the same Legal Entity and the Consolidation Type is identified. This difference is identified at the granularity of the GL code for the selected hierarchy, the mandatory dimensions, and the selected optional dimensions. Adjustments are not passed in the Ledger to Ledger reconciliation. Also, the difference is identified by comparing the **Source Ledger** with the **Target Ledger**, to ensure that all the GL codes' amount is covered to calculate the difference.

A Legal Entity in the bank can maintain the same GL data (either solo or consolidated) in one or more source systems. If GL data is maintained in the multiple source systems, then it is essential to compare the GL balances among such GL sources to ensure that all GL sources reflect the accurate and uniform balance. Any difference, between two GL source systems, is expected to be rectified outside the framework. Reconciliation definition is applied at Legal Entity Level - either Solo or Consolidated

NOTE The Adjustment Entry is not passed in the GL to GL reconciliation.

NOTE The **STG_MANAGEMENT_LEDGER** table is included in the data model of the OFSAA Reconciliation Framework. This table can be used as a Target Ledger table. The **STG_MANAGEMENT_LEDGER** is a single table to store the thick ledger of the bank and its configuration.

Topics:

- [Navigation within the Settings](#)
- [Navigation within the Dimensions](#)

5.2.2.1 Navigation within the Settings

You can navigate to **Type Configuration**, and selecting **Ledger to Ledger**, to either **View**, **Edit**, or **Delete** Ledger to Ledger type.

It consists of two tabs:

- Settings
- Dimensions

The Settings tab displays the name and the description of the reconciliation type that you want to view (Ledger to Ledger configuration for this pane).

It is further divided into two panes:

- **Source:** This pane displays the **Source Grain** (Ledger) and the **Source Entity** for the Ledger to Ledger type. The Stage General Ledger data is the default Source Entity used for reconciliation.
- **Target:** This pane displays the **Target Grain** (Management Ledger) and the **Target Entity** for the Ledger to Ledger type. The Target entities refer to the Stage Management Ledger tables (Ledger) of the Oracle Financial Services Data Foundation application.

When you click **View** icon for the selected reconciliation type, you cannot make any changes on the settings page, as it is in the read-only mode. All the panes on the **Settings** tab are disabled for making any changes when you click **View** icon.

Changes can be made to this page when you click the **Edit** icon for the selected reconciliation type. All the panes in the Settings tab are enabled for editing except the Name.

Figure 19: Ledger to Ledger Settings tab for Edit

The screenshot shows the 'Type Configuration' interface for a 'Ledger to Ledger' reconciliation type. The interface is divided into two tabs: 'Settings' and 'Dimensions'. The 'Settings' tab is active and contains the following fields:

- Name:** Ledger to Ledger
- Description:** Ledger to Ledger
- Source:**
 - Source Grain:** Ledger
 - Source Entity:** Stage General Ledger Data
- Target:**
 - Target Grain:** Management Ledger
 - Target Entity:** Stage Management Ledger

Buttons for 'Save' and 'Cancel' are located in the top right corner.

5.2.2.2 Navigation within Dimensions

For information on Navigating within Dimensions tab see the [Navigation within the Dimensions](#) section.

5.2.3 Management Ledger to Product Processor

Management Ledger to Product Processor Reconciliation definition is to identify the difference between management ledger system and Product Processor data. It is also used to nullify the difference by posting adjustment entries up to the amount of difference.

Topics:

- [Navigation within Settings](#)
- [Navigation within Dimensions](#)

5.2.3.1 Navigation within Settings

You can navigate to **Type Configuration**, and select **Management Ledger to Product Processor**, to either View, Edit, or Delete **Management Ledger to Product Processor type**.

It consists of two tabs:

- Settings
- Dimensions

The Settings tab displays the name and the description of the reconciliation type that you want to view (**Management Ledger to Product Processor** configuration for this pane).

The tab is further divided into two panes:

- **Source:** This pane displays **Source Grain** (Management Ledger) and **Source Entity** for **Management Ledger to Product Processor** type. Stage Management Ledger data is defined here as the default source entity to be used for reconciliation definition.
- **Target:** This pane displays the **Target Grain** (Account) and **Target Entity** for **Management Ledger to Product Processor** type. Target entities refer to Stage instrument tables (Product Processors) of the Oracle Financial Services Data Foundation application.

When you click **View** icon for the selected reconciliation type, you cannot make any changes on the **Settings** tab, as it is in the read-only mode. All the panes on the **Settings** tab are disabled for making any changes when you click **View** icon.

Changes can be made to this tab when you click the **Edit** icon for the selected reconciliation type. All the panes in the **Settings** tab are enabled for editing except the Name.

Figure 20: Management Ledger to Product Processor Settings tab for Edit

The screenshot shows the 'Type Configuration' interface for 'Management Ledger to Product Processor' in edit mode. The interface is divided into two tabs: 'Settings' and 'Dimensions'. The 'Settings' tab is active. At the top right, there are 'Save' and 'Cancel' buttons. Below the tabs, there is a header section with 'Name' and 'Description' fields. The 'Name' field contains 'Management Ledger to Product Proces' and the 'Description' field contains 'Management Ledger to Product Processor'. Below this, there are two sections: 'Source' and 'Target'. The 'Source' section has 'Source Grain' set to 'Management Ledger' and 'Source Entity' set to 'Stage Management Ledger'. The 'Target' section has 'Target Grain' set to 'Account' and 'Target Entity' set to 'Stage Cards' and 'Stage Loan Contracts'.


5.2.3.2 Navigation within Dimensions

For information on Navigating within Dimensions tab see the [Navigation within the Dimensions](#) section.

6 Reconciliation Rules

Reconciliation management is the designated level at which the account balances are reconciled in the system. It stores information that specifies the granular level at which account balances are reconciled across one or many entities.

Figure 21: Reconciliation Rules Summary Page



Configuration types can be processed in two ways:

- **GL Level Recon:** In the GL level reconciliation, the difference between the GL system and the Product Processors systems at each reconciliation dimension node level within a GL code, is identified.
- **Map Level Recon:** In the map level reconciliation, the difference between the GL data and the Product Processor data at each reconciliation dimension node level across all the Product Processors, are identified.

For a detailed explanation on GL Level Recon and Map Level Recon, see the [Key Terms and Concepts](#) section.

Topics:

- [Navigation within the Summary Page](#)

6.1 Navigation within the Summary Page


You can navigate to **Reconciliation Definition**, and select **Reconciliation Rules**, to view the summary page which displays all the defined reconciliation types. Select a method and by using search criteria, you can control the set of reconciliations definition that is displayed. When you **Add**, **Edit**, or **View** the reconciliations, the corresponding details page is displayed.

The Reconciliation Definition page consists of five tabs:

- Settings
- GL Parameters
- Target Parameters
- Dimensions
- Allocations

The Summary page of the Reconciliation Rules offers several icons that allow you to perform different functions when a defined reconciliation is selected.

Figure 22: Summary Page Icons




- **Add:** Click **Add** icon, this begins the process of building new reconciliation rules. The Add is disabled if any row in the grid is selected.
- **View:** Select a single reconciliation definition, this enables the **View** icon. Click **View** icon to view the detailed definition of reconciliation in the read-only mode. This icon is enabled only when a single reconciliation definition is selected.
- **Edit:** Select a single reconciliation definition, this enables the **Edit** icon. Click the **Edit** icon to modify an existing reconciliation definition with some restrictions. The Legal Entity and Consolidation Type field are disabled during an edit. This icon is enabled only when a single reconciliation definition is selected.
- **Copy:** Select a single reconciliation definition, this enables the **Copy** icon. Click **Copy** icon to copy the detailed definition in a new Definition screen. You can change any field and save it as a new definition. The Name and the Description fields are enabled on the new definition screen and you can give a unique name and a description. This icon is enabled only when a single reconciliation definition is selected.
- **Delete:** Select one reconciliation definition, this enables the **Delete** icon. Click the **Delete** icon to delete the selected reconciliations definition.

Topics:

- [Search Section](#)
- [Definition List](#)
- [Reconciliation Definition](#)
- [Adjustment Attributes](#)

6.1.1 Search Section

You can search for any reconciliation rule in the search pane.



6.1.2 Definition List

The Definition List displays a list of all the definitions that match your search criteria in two views.

- Tile Menu
- Pane Menu

This list offers several icons that allow you to perform different functions when a defined reconciliation is selected for both the views.

Figure 23: Definition List-Tile menu





Figure 24: Definition List-Pane menu



You can navigate to another page using the pagination option in the pane menu as shown in *figure 24*.

The following columns are displayed in this grid:

- **Measures:** The number of measures defined in the reconciliation rule.
- **GL Accounts:** The number of GL Codes users have selected in the reconciliation definition.
- **Consolidation:** The Consolidation Type displays as Solo or Consolidated.
- **Adjustment:** The status is displayed either Yes or No if the Adjustment Allocation has been applied to the selected reconciliation definition or not.

6.1.3 Reconciliation Definition

To add the reconciliation definitions, follow these steps:

- From the menu bar, click **Add** icon, the **Reconciliation Definition** window with the following tabs is displayed:
 - [Settings](#)
 - [GL Parameters \(Source Ledger Parameters\)](#)
 - [Target Parameters](#)
 - [Dimensions](#)
 - [Allocation](#)

6.1.3.1 Settings

To create the Reconciliation definition enter and select the displayed details in the Settings tab.

Figure 25: Reconciliation Definition - Settings tab

Enter and select the following details in the Settings tab:

- Rule Name:** Enter the **Rule Name** to add the Reconciliation definition.
- Rule Description:** Enter the **Rule Description** for the defined rule.
- Reconciliation Type:** The Reconciliation Type can be selected as General Ledger to Product Processor, Ledger to Ledger, or Management Ledger to Product Processor.
- Reconciliation Definition Type:** The Reconciliation Definition Type is by default selected as **Manual** for General Ledger to Product Processor and Management Ledger to Product Processor reconciliation type, but is disabled for **Ledger to Ledger** reconciliation type.
- Legal Entity:** Click **Hierarchy** to select the Legal Entity from the drop-down list.
- Consolidation Type:** Select the Consolidation Type from the drop-down list as **Solo** or **Consolidated**. If Consolidated is selected, then only one Parent Legal Entity must be part of the definition.
- Inherit to Child:** Select the **Inherit to Child** toggle button, consolidation type is disabled if you select this option. If you select this option and value defaults to **Solo**. For more information on Inherit to Child, see the [Key Terms and Concepts](#) section.
- Balance Type:** If the **Reconciliation Type** is selected as Ledger to Ledger or Management Ledger to Product Processor, then only the End of Period Balance is available as balance types.

For General Ledger to Product Processor reconciliation type, the available Balance Types are:

- End of Period Balance
 - Monthly Average
 - Yearly Average
 - Month-to-date
 - Quarter-to-date
 - Year-to-date
- **Reconciliation Definition:** Select the level at which the balances must be reconciled, that is, the **GL Level Recon** or the **Map Level Recon**.
 - **Adjustment Allocation Required:** Select **Yes** in this field if you want the application to pass an automated adjustment entry for any reconciliation difference found, else select **No**. If the value is No, then the reconciliation differences are calculated but adjustment entry will not be passed.


For more information on the details in the Settings pane, see the [Dashboard: Home](#) section.

Click the **Next** icon, the next tab **GL Parameter** is displayed.

6.1.3.2 GL Parameters (Source Ledger Parameters)

Select the displayed details in the **GL Parameters** tab.

Figure 26: Reconciliation Definition- GL Parameters tab



In the **GL Parameter** tab, update the following:



- **GL Hierarchy:** Click Hierarchy  icon, to launch the GL Hierarchy window as shown in *Figure 27*. You can select the values for **GL Hierarchy** pane from the available list of values.
- **Add Filters:** You can **Add Filters** (for example, product, business unit, and so on) defined in the **Settings** tab. A comparison between the GL system and PPs is based on the filters set on these dimensions.

Figure 27: Reconciliation Definition GL Hierarchy window



You can move the Available Values using the Move, Move All, Remove, Remove All, Move to Top, Move Up, Move Down, and Move to Bottom buttons as shown in *Figure 28*.

Click **OK**.

Click **Next** icon, the next tab **Target Parameter** is displayed.

6.1.3.3 Target Parameters

This is a configuration page required to configure the target side entities and measures.


Topics:

- [GL Level Reconciliation \(If GL Level is selected in the Settings tab\)](#)
- [Map Level Reconciliation \(If Map Level is selected in the Settings tab\)](#)

6.1.3.3.1 GL Level Reconciliation (If GL Level is selected in the Settings tab)

This section explains the GL Level Reconciliation in Target Parameters tab if the GL Level is selected in the Settings tab.

Figure 28: GL Level Reconciliation Definition- Target Parameters tab



Select the following details:

- **Target Entity**
 - **Target Entity Name:** Select the name of the entity that contains the Ledger data from the drop-down list.

NOTE

For a Ledger to Ledger Reconciliation, the Source and the Target cannot have the same table name.


For example, Stage General Ledger Data (STG_GL_DATA Table) in the Source and the Target.

Therefore, you must Select only Stage Management Ledger (STG_MANAGEMENT_LEDGER Table) as the Target Entity.

- **GL Reconciliation Column:** Select the reconciliation column from the drop-down list.
- **Threshold Amount Currency:** Select the Threshold Amount of currency from the drop-down list.

Click the **Settings** icon, the Target Parameters pane is displayed, as shown in *Figure 29*.

Figure 29: GL Level Reconciliation Definition- Target Parameters Pane



Select the following details:

- **Target Parameters**
 - **Threshold Specification:** Specify the threshold from this drop-down list. If the value is specified in terms of percentage, then the **Threshold Amount Currency** Field is disabled.
 Specify the threshold from the drop-down list. The threshold value can be in both absolute terms and percentage terms at a PP Level. If the selection in all the PPs is a percentage, then the threshold amount currency field is disabled.
 - **Positive Threshold:** Specify the Positive Threshold value. These values are used to identify the breach types, categorized as:
 - Negative Percentage Threshold (NPT)

- Positive Percentage Threshold (PPT)
- Negative Absolute Threshold (NAT)
- Positive Absolute Threshold (PAT) and
- Not Breached (NB)


The Breach Type is identified at runtime during the Reconciliation Process and Audit Trail Entries are posted with this information. For GL Level reconciliation, values can be updated at different PP Levels. For Map Level reconciliation, you have to manually enter only one value for all the PPs.

- **Negative Threshold:** Specify the Negative Threshold value. These values are used to identify the breach types, categorized as
 - Negative Percentage Threshold (NPT)
 - Positive Percentage Threshold (PPT)
 - Negative Absolute Threshold (NAT)
 - Positive Absolute Threshold (PAT) and
 - Not Breached (NB)

The Breach Type is identified at runtime during the Reconciliation Process and Audit Trail Entries are posted with this information. For GL Level reconciliation, values can be updated at different PP Levels. For Map Level reconciliation, you have to manually enter only one value for all the PPs.

- **Adjustment Entry Floor:** Specify the value required to pass an adjustment entry. If the (GL-PP) difference is less than the Adjustment entry floor specified in the definition, then the calculated difference is not eligible for the adjustment and the entry is not logged in Adjustment Entry table.

Figure 30: GL Level Reconciliation Definition- Target Entity Filters



- **Filter:** Select the currency to specify the Threshold Amount. Additionally, click the **Filter** pane to add more details to the additional dimensions selected.

You can also add filters to the optional dimensions (product, business unit, and so on) defined in the **Settings** tab. A comparison between the GL source system and PPs is based on the filters set on these dimensions. See the following steps to add filters:


- a. Click the **Filters from the drop-down list** as highlighted in *Figure 30*.
- b. Select the relevant dimension from the **Filters** pane.
- c. Click the selected dimension, which enables a second drop-down list to select the relevant members for the dimension under consideration.

Click the **Next** icon, the next tab **Dimensions** are displayed.

6.1.3.3.2 Map Level Reconciliation (If Map Level is selected in the Settings tab)

This section explains the Map Level Reconciliation in **Target Parameters** tab if the Map Level is selected in the **Settings** tab.

Figure 31: Map Level Reconciliation page for Target Parameter



In this window, the **GL Reconciliation Column** is disabled when the Map Level Reconciliation is selected, click **Add** to update the PP entity or Target entity details.

For more information to update the Target entity details, see the [GL Level Reconciliation \(If GL Level is selected in the Settings tab\)](#) section.


6.1.3.4 Dimensions

In this tab, the **Mandatory Dimensions** are displayed. Click the **Reconciliation Dimensions** drop-down list to add the dimension to the map definition. Click **Save** to save the changes made, else click **Cancel**.

NOTE STG_MANAGEMENT_LEDGER Table is included in the Datamodel of the OFSAA Reconciliation Framework. This table can be used as a Target Ledger Table.

STG_MANAGEMENT_LEDGER is a Single Table to store a thick ledger of banks and it is configurable.

Figure 32: Reconciliation Definition- Dimensions tab



The **Legal Entity**, **Currency**, and **GAAP Code** are the mandatory dimensions. These dimensions which are defined in the Settings window appear in the Dimensions window as well, which indicates that comparison between the GL system and the PP system and any reconciliation difference is populated based on these Dimensions. The **Reconciliation Dimensions** are optional dimensions which are also populated in this window as defined in the Type Configuration page.


Click the **Next** icon, the next tab **Allocation** is displayed.

6.1.3.5 Allocation

In the **Allocation** tab, select the following fields:

- **Adjustment Allocation:** Select the **Automatic** option if you want the application to pass automated adjustment entries or select **Manual**.
- **Adjustment Posted to:** Select the Target table where the adjustments are to be posted that is, select the Product Processor option if the adjustment entry must be posted to the Product Processor selected in the **Product Processor Parameter** window, or select **Other**.


Figure 33: Reconciliation Definition Allocation tab



- **Target Entity:** As per the selections made in the preceding two fields, the fields in the **Target Entity** is disabled or enabled accordingly.
- **Allocation Amount column:** Balance Attribute.
- **Adjustment Rule:** Select the Adjustment Rule from the drop-down list.
- **Allocation Ratio:** If adjustment entry is to be passed to more than one PP entity, then the ratio at which these the entry is to be passed is updated in the Allocation Ratio field.
- **Adjustment Attributes:** You can use this field to split the adjustments further based on non-dimension columns of the target table. The Reconciliation definition differences that arise from

the definition execution can be adjusted back to the target table, based on the values of non-dimension columns. This can be done apart from the dimension columns.

Figure 34: Adjustment Attribute pane



For post adjustments with more granularity, perform the following steps:

- a. Click on the Selector under **Adjustment Attributes**. A right pane is displayed.
- b. Select the **Attributes** from the Attribute List and click the **Done** icon.
- c. Click **Save** icon to save the selected attributes.

The following types of Attributes should not be selected in the field list of Adjustment Attributes:

- a. Reconciliation dimensions
- b. Number data type columns
- c. Date data type columns

NOTE Reconciliation differences are created based on reconciliation dimensions alone but not on **Adjustment Attributes** selected.

Adjustment attributes play their role when creating adjustments with the differences that are observed. The applications read the values in the selected adjustment attributes of the participating columns of aggregation and based on the unique combination of values in these attribute columns, the number of adjustments is created and the same values default in the respective adjustments. The reconciliation definition differences are split among the adjustments based on the weighted average ratio of the participating target balance values.

For more information about Adjustment Attributes and Defaulting Account Level with an example, see [Adjustment Attributes and Defaulting Account Level](#).


Topics:

- [Map Level Reconciliation \(if Map Level Reconciliation is selected in the Settings tab\)](#)
- [GL Level Reconciliation \(if GL Level Reconciliation is selected in the Settings tab\)](#)

6.1.3.5.1 GL Level Reconciliation (if GL Level Reconciliation is selected in the Settings window)

This section explains the GL Level Reconciliation in the **Allocation** tab if the GL Level is selected in the **Settings** tab.

Figure 36: GL Level Reconciliation page for Allocation



In the **Allocation** pane, the following fields must be selected:

- **Adjustment Allocation:** If the GL Level Reconciliation is selected, then the Adjustment Allocation is by default considered as Automatic.
- **Adjustment Posted to** Select the Target table where the adjustments are to be posted that is if the adjustment entry is to be posted to PP selected in the **Product Processor Parameter** window then select Product Processor or else select **Others**.
- **Target Entity Details:** As per the selections made in the preceding two fields, the fields in the **Target Entity** is disabled or enabled accordingly. See the following cases for more details:

Case 1: If the Target table is the Product Processor

The **Default Values** is the only column that is updated. This is the mandatory column to be updated for populating the Target Entity results.


Case 2: If the Target table is Other

The **Target Entity**, the **Default Values**, the **Allocation GL Column**, and the **Allocation Ratio** are updated. If the adjustment entry is to be passed to more than one Product Processor entity, then the ratio at which the entry is passed is updated in the **Allocation Ratio** field.

6.1.3.5.2 Map Level Reconciliation (if Map Level Reconciliation is selected in the Setting pane)

This section explains the Map Level Reconciliation in the **Allocation** tab if the Map Level is selected in the **Settings** tab.

Figure 35: Map Level Reconciliation page for Allocation



In the **Allocation** pane, the following fields must be selected:

- **Adjustment Allocation:** If you want the application to pass automated adjustment entries, then select Automatic, or select Manual.
- **Adjustment Posted to:** Select the Target table where the adjustments are to be posted that is, if the adjustment entry is to be posted to PP selected in the **Product Processor Parameter** window, then select Product Processor or select **Other**.
- **Target Entity:** As per the selections made in the preceding two fields, the fields in the **Target Entity** is disabled or enabled accordingly. See the following cases for more details:
 - **Case 1:** If the Adjustment Allocation is Automatic and the Target table is the Product Processor
 The **Default Values** is the only column that is updated. This is the mandatory column to be updated for populating the Target Entity results.
 - **Case 2:** If the Adjustment Allocation is Manual and the Target table is the Product Processor
 The **Default Values** and the **Allocation Ratio** are the only two columns to be updated. If the adjustment entry is to be passed to more than one Product Processor entity, then the ratio at which the entry is to be passed is updated in the **Allocation Ratio** field.
 - **Case 3:** If the Adjustment Allocation is Automatic and the Target Table is Other
 If the **Other option** is selected as the Target table, then the corresponding Target Entity, Default Values have to be updated.
 - **Case 4:** If the Adjustment Allocation is Manual and the Target table is Other
 The Target Entity, the Default Values, and the Allocation Ratio columns must be updated.

6.1.4 Adjustment Attributes

The following is an example that briefly explains the ADJUSTMENT ATTRIBUTES functionality.

Sample data has dimensions lv code, ccy code, and gaap code. The ownership type attribute is used as an adjustment attribute.

Table 7: STG_CASA

v_account_number	v_lv_code	v_ccy_code	v_gaap_code	n_eop_bal	v_ownership_type	v_default_1
------------------	-----------	------------	-------------	-----------	------------------	-------------

Acc01	LE1	USD	USGAAP	4000	IND	A
Acc02	LE1	USD	USGAAP	2000	JOINT	B
Acc03	LE1	USD	USGAAP	3000	JOINT	C

Assuming source balance is 9300, the following are the differences that are created.

Table 8: DIFFERENCE TABLE

Source Balance	Target Balance	Difference
9300	9000	300

The following are the adjustments that are posted considering the ownership type column into the granularity.

Two unique values, IND and JOINT are used to split the differences and create adjustments.

Adjustment 1 has the value IND for ownership type and the balance is $(4000/9000)*300$.

Adjustment 2 has the value JOINT for ownership type and the balance will be $((2000+3000)/9000)*300$.

Table 9: ADJUSTMENTS

v_account_number	v_lv_code	v_ccy_code	_gaap_code	n_eop_bal (diff)	v_ownership_type	v_default_1
GL_01	LE1	USD	USGAAP	133.33	IND	A
GL_02	LE1	USD	USGAAP	166.66	JOINT	A

7 Execution of Rule

After defining the parameters on both the GL side and the Product Processor side, defined reconciliation rules must be executed, and thereby the differences between the GL data and PP data must be computed. The Processing Modelling framework is used for executing the reconciliation rules. The Processing Modelling Framework is a unique feature of the OFS Analytical Infrastructure Reconciliation Framework which enables a business user *without assistance from a technical analyst* - to easily define and execute a Run. This framework allows you to define a Run by selecting a combination of different GL reconciliation parameters.

Topics:

- [Execution Part](#)
- [Process Flow Monitor](#)

7.1 Execution Part

To execute the process run, perform the following steps:



1. From the **Home** page, click **Administration**  icon.
The **Administration** page appears.
2. Select the **Infodom** from the **Information Domain** drop-down list.
3. Click **Processing Modelling Framework** and select the **Process Modeller** option.

Figure 37: Process Modeller - Administration Page



In the **Process Modeller** page, you must set the Run parameters for the highlighted Process that is, **Reconciliation Framework Run**.

Reconciliation Framework Run: The seeded run is provided in the installer that helps to execute the reconciliation rules. For each execution, parameters can be provided to execute the run.


Figure 38: Process Modeler Page

Process Modeler					
Home > Process Modeler					
<input type="text"/> <input type="button" value="Q C"/> Sort By Select any one option <input type="button" value="+"/>					
D	DataAdjustments Code: DataAdjustments Description: DataAdjustments for GL	0 Version	11 Instances	Application: Reconciliation Framework Type: PMF	Last Modified By: GLUSER2 Last Modified Date: 2020-05-06 19:00:17
R	Reconciliation Framework Run Code: GLRUN Description: Reconciliation Framework Run	0 Version	15 Instances	Application: Reconciliation Framework Type: RUN	Last Modified By: GLUSER2 Last Modified Date: 2020-05-06 18:53:26

- To see the definition of **Reconciliation Framework Run**, click the **Process Link**.

This link displays the Process flow, Definition, Application Rules, and Data Fields associated with selected Process Modeler reconciliation.

Figure 39: Process Flow window



- Click icon and select the **Execute Run** to select the run parameters for the reconciliation Framework Run.

Figure 40: Execute Run on Process Modeler Page

D	DataAdjustments Code: DataAdjustments Description: DataAdjustments for GL	0 Version	11 Instances	Application: Reconciliation Framework Type: PMF	Last Modified By: GLUSER2 Last Modified Date: 2020-05-06 19:00:17
R	Reconciliation Framework Run Code: GLRUN Description: Reconciliation Framework Run	0 Version	15 Instances	Application: Reconciliation Framework Type: RUN	Last Modified By: GLUSER2 Last Modified Date: 2020-05-06 18:53:26
D	DML_workflow Code: DML_workflow Description: DML_workflow	0 Version	7 Instances	Application: DMI Type: PMF	Last Modified By: SUPERUSER Last Modified Date: 2019-01-28 11:16:41
Q	Questionnaire Process Code: QTNR Description: Questionnaire Process	0 Version	0 Instances	Application: Questionnaire Type: PMF	Last Modified By: Last Modified Date:
A	Adjustment Manul Data Workflo Code: Adjustment Manul Data Workflo Description: Adjustment Manul Data Workflo	0 Version	0 Instances	Application: Adjustment Manul Data Workflo Type: PMF	Last Modified By: Last Modified Date:

A context menu is open over the 'Reconciliation Framework Run' row, with the 'Execute Run' option highlighted. The menu items are: View, Copy, Process Flow Monitor, Test Process Flow, **Execute Run**, Export Process, and Filter.

- In the **Select Run Params** window, set the parameters for all the defined functions.

Figure 41: Select Run Parameter Window

The field description is as follows:


- Reconciliation Definition:** Click  icon to enter the parameters defined in the Reconciliation Definition section. The following window is displayed to enter the parameters.

Figure 42: Reconciliation Definition window

- Scenario Type:** Select the scenario type from the drop-down list, to identify the differences for the Actual Data or the Reported Data. The Reported Data indicates that the GL reconciliation differences are identified for the actual data.

- **Execution on Threshold Breach:** In this field, you can choose Continue or No. If Continue is selected and if the GL reconciliation breaches the global threshold level, then the execution continues, else the execution is discontinued.
 - **Global Threshold:** A Global Threshold is applied over and above the mapping level threshold. If this threshold is breached during the execution, then you have the choice to select continue or you can stop the execution process. A Global Threshold is compared with the cumulative percentage difference across all the reconciliation definitions that are executed in a Run.
 - **FIC MIS Date:** Enter the extraction date in this field.
 - **Run Execution Description:** Enter a longer description of the Run.
 - **Auto Approval:** If the Auto Approval value is selected as Yes, then it is directly be updated in the Target Table.
7. Click **Save**; a batch with the defined Run execution parameters is created.
 8. Click **Execute** to execute the created batch.

7.1.1 Execute the rules Using Command Line Utility

A command line utility `./wfExecExternal.sh` is available in `$FIC_DB_HOME/bin` folder.

To execute the Run Pipeline using the command-line utility

1. Navigate to `$FIC_DB_HOME/bin` folder.
2. Execute the script file using the following command:

```
./wfExecExternal.sh processInstanceId processId '$objectId' objectType
infodom userID segment locale 'applicationparams' 'securityparams'
```

- `processInstanceId` - Instance Id of the Process or Run Pipeline
- `processId` - Process ID of the Run Pipeline. This is a mandatory parameter.
- `objectId` - This is an auto-generated unique Object ID. Enter '`$objectId`' as mandatory parameter value.
- `objectType` - Specify the Object Type if it is defined in the `aai_wf_app_definition_map` table.
- `infodom` - Information Domain Name
- `userID` - Specify the user ID
- `segment` - Segment Name
- `locale` - Locale selected. For example, `en_US`
- '`applicationparams`' - Specify values for the Run execution parameters stored in `APP_COMP_ATTR_MAP_ID` within single quotes separated by comma.
- '`securityparams`' - Specify any security parameters within single quotes separated by comma

For example:

```
./wfExecExternal.sh null GLRUN '$objectId' null FSDFINFO GLUSER GLSEG en_US
'{"hierDetailsRECONNAME_HIER":[{"hierValueCode":"1-1","value":"PMFRule-
```

```

1", "hierNodeCode": "1-1", "leafCondition": "CASE WHEN
FSI_GL_MAPPING_MASTER.F_IS_DELETED = 'N' THEN
FSI_GL_MAPPING_MASTER.V_GL_MAP_ID || '-' ||
FSI_GL_MAPPING_MASTER.N_VERSION_NUMBER END = '1-1'", "hierNodeDesc": "PMFRule-
1"}, {"hierValueCode": "22-1", "value": "regression_consolidated-
1", "hierNodeCode": "22-1", "leafCondition": "CASE WHEN
FSI_GL_MAPPING_MASTER.F_IS_DELETED = 'N' THEN
FSI_GL_MAPPING_MASTER.V_GL_MAP_ID || '-' ||
FSI_GL_MAPPING_MASTER.N_VERSION_NUMBER END = '22-
1'", "hierNodeDesc": "regression_consolidated-1"}, {"hierValueCode": "24-
1", "value": "regression_maplevel-1", "hierNodeCode": "24-
1", "leafCondition": "CASE WHEN FSI_GL_MAPPING_MASTER.F_IS_DELETED = 'N' THEN
FSI_GL_MAPPING_MASTER.V_GL_MAP_ID || '-' ||
FSI_GL_MAPPING_MASTER.N_VERSION_NUMBER END = '24-
1'", "hierNodeDesc": "regression_maplevel-1"}, {"hierValueCode": "21-
1", "value": "regression_solo_filters-1", "hierNodeCode": "21-
1", "leafCondition": "CASE WHEN FSI_GL_MAPPING_MASTER.F_IS_DELETED = 'N' THEN
FSI_GL_MAPPING_MASTER.V_GL_MAP_ID || '-' ||
FSI_GL_MAPPING_MASTER.N_VERSION_NUMBER END = '21-
1'", "hierNodeDesc": "regression_solo_filters-1"}, {"hierValueCode": "23-
1", "value": "regression_two_pp-1", "hierNodeCode": "23-1", "leafCondition": "CASE
WHEN FSI_GL_MAPPING_MASTER.F_IS_DELETED = 'N' THEN
FSI_GL_MAPPING_MASTER.V_GL_MAP_ID || '-' ||
FSI_GL_MAPPING_MASTER.N_VERSION_NUMBER END = '23-
1'", "hierNodeDesc": "regression_two_pp-
1"}}, {"SCR_TYPE": "A", "THR_BREACH": "C", "GLB_THR": "80", "FIC_MIS_DATE": "2020-06-
03", "V_RUN_MAIN_DESC": "RegressionRun#1", "AUTO_APPROVAL": "Y"}' null

```

NOTE Null should be passed if you do not want to pass the value for a parameter.


For more details to execute the rules using command line utility see section *Using Command Line Utility* in the [Oracle Financial Services Analytical Applications Infrastructure Process Modelling Framework Orchestration Guide](#).

7.2 Process Flow Monitor

To view the Execution ID status of the reconciliation run in the process flow monitor perform the following steps:


1. From the **Administration** page, select the **Infodom** from the **Information Domain** drop-down list.
2. Click **Processing Modelling Framework** and select the **Process Monitor** option.

Figure 43: Administration Page- Process Monitor



The **Process Monitor** page displays the list of Execution IDs that are generated after the **Reconciliation Framework Run** is triggered.

Figure 44: Process Monitor Page



Each ID displays the following information:


- **Entity Name:** The description of the Reconciliation Framework Run provided.
- **Process Name:** The Reconciliation Framework Run appears as the process name when the user executes the GL Reconciliation Run.
- **Process Description:** The Reconciliation Framework Run appears as the process description when the user executes the GL Reconciliation Run.
- **Execution Start Time:** The Execution Date and Execution Time when the Execution Run starts.
- **Last Execution Time:** The Last Execution Date and Last Execution Time.
- **Last updated by:** The name of the User who defined the Run.
- **Status:** The status of the Execution as Completed, Failed, or Ongoing.

8 Process Execution Summary

This chapter provides information on the Runs that are applicable for this release that is, **DataAdjustments** and **Reconciliation Framework Run**. The **Process Execution Summary** is launched once the rules are executed from the Processing Modelling Framework.

The following figure displays the **Process Execution Summary** with the data that is retrieved from the **Process Modeler** on the **Administration** page.


Figure 45: Process Execution Summary page



8.1 Summary Part


After the Run execution, the **Process Execution Summary** is generated in the list format as illustrated in *Figure 46*. The summary page displays the process names for which the Run Parameters were generated, such as, Reconciliation Framework Run for Reconciliation Framework application.

Figure 46: Process Execution Summary- View







1. Click **View** icon to see the **Process Execution Details** page. This allows you to view the detailed definition of a Run on a read-only basis. The **Process Execution Details** page displays the execution details for the selected Execution Key with the color band displaying the status of each Execution Key. The color band legend is displayed on the **Process Execution Details** page.

Figure 47: Process Execution Details Page



The execution keys and the corresponding execution details are as follows:

- **Process Description:** The Reconciliation Framework Run appears as the process description when the user executes the GL Reconciliation Run.
- **MIS Date:** The process date is displayed in this field.
- **Start Time:** The Execution Date and the Execution Time when the Execution Run starts (Post-run details).
- **End Time:** The End Execution Date and Execution Time.
- **Process Execution Key:** Unique identifier assigned to each Process Execution.
- **Approval Status:** The Approval status of the Execution as Completed, Failed, or Ongoing.
- **Process Monitor:** The process monitor icons show the run definition as defined in the process modeling framework. These 4 icons are:
 - **PMF Launch:** Click **View**  icon, to view the Process flow associated with the selected run.
 - **Request Report Flag:** Click **Request for Reporting Flag**  icon, to request for a Reporting Run, select an **Execution ID** in the **Process Execution Summary** page, and click the **Request for Reporting Flag** icon. A dialog box will appear for you to input your comments. Click **Submit** and the status of this Run is displayed in the Reporting Flag section. Only a successful execution can be requested for reporting. For the selected Run and Execution date, there can be only one reporting flag.
 - **Approve Report Flag:** After submitting the Reporting Run in the **Request for Reporting Flag** icon, the **Approval for Reporting Flag**  icon is enabled. Click the icon a dialog box with the User Comments and Approver Comments. The Approver can update the comments in the **Approver Comments** and then click **Approve** or **Reject** accordingly.
 - **Override Report Flag:** Any reporting execution can be overwritten with another execution. Select a successfully triggered batch in the **Process Execution Summary** page. The **Override the Reporting Flag**  icon is enabled if the execution is already marked as a Reporting Flag. You can override the execution by updating your comments. This must be approved by the approver and the procedure is similar to the procedure detailed in the section for Approval of Reporting Flag.

NOTE

Only Run Pipelines will have the workflow options.

9 Data Adjustment

The Data Adjustment Module provides capabilities to define templates that can be used for various types of Adjustments. The entities on which templates can be defined refer to the Stage instrument tables of OFS Data foundation Applications. The templates are used by a reconciliation framework to define default values for various attributes for the instrument tables. While posting adjustment Data Adjustment Modules apply the defaults for the adjustments created by the reconciliation framework.

Figure 48: Data Adjustment Summary page

The screenshot shows the 'Data Adjustments Summary' page. On the left is a sidebar with 'Data Adjustment' and 'Adjustment Rules'. The main area has a search bar and a table of adjustment templates. Each row includes the template name, its associated entity, and its status. Action icons for 'Add' and 'View' are present for each entry.

Adjustment Rule	Entity	Status	Actions
Customer_Account_Asset_AdjRule	Customer_Account_Asset_AdjRule Stage Loan Contracts	Draft	[Add] [View]
Testcase6	TestCase6 Stage Casa Accounts	Approved	[Add] [View]
TestCase5	TestCase5 Stage Loan Contracts	Approved	[Add] [View]
Adjustment_Assets_1	Adjustment_Assets_1 Stage Loan Contracts	Approved	[Add] [View]
Adjustment_Rule_Static	Adjustment_Rule_Static Stage Loan Contracts	Approved	[Add] [View]
Loan_Adjustment	Loan_Adjustment Stage Loan Contracts	Approved	[Add] [View]
Adj1	Adj1 Stage Loan Contracts	Approved	[Add] [View]

Topics:

- [Navigation within Data Adjustments Summary page](#)

9.1 Navigation within Data Adjustments Summary page

You can navigate to **Data Adjustment**, and select **Adjustment Rules**, the Data Adjustments Summary window displays all the Adjustment templates defined for various entities. Select an **Adjustment Entry** and use search criteria, you can use the icon the set of adjustment entries that are displayed. When you click **Add** or **View** icon, the details page is displayed.

Figure 49: Data Adjustment Summary page features

Data Adjustments Summary		
Search Adjustment <input type="text"/> <input type="button" value="Add"/>		
Adjustment_STG_CARDS Adjustment_STG_CARDS Stage Cards	Approved	<input type="button" value="Add"/> <input type="button" value="Delete"/>
Customer_Account_Asset_AdjRule Customer_Account_Asset_AdjRule Stage Loan Contracts	Draft	<input type="button" value="Add"/> <input type="button" value="Delete"/>
Testcase6 TestCase6 Stage Casa Accounts	Approved	<input type="button" value="Add"/> <input type="button" value="Delete"/>
TestCase5 TestCase5 Stage Loan Contracts	Approved	<input type="button" value="Add"/> <input type="button" value="Delete"/>
Adjustment_Assets_1 Adjustment_Assets_1 Stage Loan Contracts	Approved	<input type="button" value="Add"/> <input type="button" value="Delete"/>
Adjustment_Rule_Static Adjustment_Rule_Static Stage Loan Contracts	Approved	<input type="button" value="Add"/> <input type="button" value="Delete"/>

Topics:

- [Navigation within the Adjustment Entry Window](#)
- [Navigation within the Adjustment Run Details page](#)

9.1.1 Navigation within the Adjustment Entry Window

When you first navigate to the Adjustment Entry window, the Adjustment entries associated with the first dimension is presented in a summary list. The Adjustment Entry Page has two sections:

- [Search Section](#)
- [Adjustment Entry Status Section](#)

9.1.1.1 Search Section

Among other properties, each Adjustment Entry consists of a **Run Execution ID**, a **GL Date**, and a **Definition**. You may search on any of these properties in the Search section.

Figure 50: Search Adjustment section



9.1.1.2 Adjustment Entry Status Section

The **Adjustment Entry Status** section presents a list containing all of the Adjustment Entries that meet your search criteria. This list also offers several icons that allow you to perform different functions when an Adjustment Entry is selected. The following icons are:

- **Add:** Click the **Add** icon, to add the Adjustment Entry and its parameters that are further displayed on the **Adjustment Entry Summary** window.
- **View:** Click the **View** icon, to view the detailed parameters of an Adjustment Entry on a read-only mode.
- **Delete:** Click the **Delete** icon, to delete the Adjustment Entry from the list.

9.1.2 Navigation within the Adjustment Run Details page

When you click **Add** button or **View** icon the **Adjustment Entry** details page is displayed.

This **Adjustment Rule Details** page consists of four tabs:

- Name
- Dataset
- Details
- Review & Save

Topics:

- [Name tab](#)
- [Dataset tab](#)
- [Details tab](#)
- [Review & Save tab](#)

9.1.2.1 Name tab

In the **Data Adjustments Summary** Window, click **Add** icon, the **Adjustment Rule Details** page is displayed.

Figure 51: Adjustment Rule Details Page- Name tab

Adjustment Rule Details
Home > Adjustment Rule Details

< Back 1 2 3 4 Next >

Name Dataset Details Review & Save

Adjustment Definition

ID 200067

* Name

Description

Type

* Adjustment Type Business Based

* Assignment Type User Input Rule Driven

Cancel

In the Adjustment Rule Details window, enter the following fields:


- **Definition ID:** The ID of the Adjustment template that is defined. The **Definition ID** is an auto-generated for every new Adjustment Rule.
- **Definition Name:** The name of the Adjustment template.
- **Definition Description:** The description of the Adjustment template.
- **Assignment Type:** Select the Assignment Type as either User Input or Rule Driven.

Click **Next** icon, the next tab **Dataset** is displayed.

9.1.2.2 Dataset tab

In the **Dataset Details** pane, select a value from the **Adjustment Entry** dropdown-list, as displayed in *Figure 52*.

Figure 52: Adjustment Rule Details Page- Dataset tab




Click **Next** icon, the next tab **Details** are displayed.

9.1.2.3 Details tab

In the **Details** tab, click the **Add Expression**, to add expressions such as **Columns**, **Functions**, **Operators**, and **Expressions** for the Adjustment Rules.

Figure 53: Adjustment Rule Details Page- Details tab



In the **Add Expression** window, enter values in the following fields:

Table 10: Add Expression fields

Field	Description
Column	Select a value from the drop-down box, for example, Indicator, Account Branch Code, Account Classification Code, Account Display Name, etc.
String	Select a value from the drop-down box, for example, ASCII(CHAR), LENGTH(STRING), LOWERS(STRING), etc.
Date and Time	Select a value from the drop-down box, for example, ADD_MONTH(DATE, NUMBER), TO_CHAR(STRING, FORMAT)
Aggregate	Select a value from the drop-down box, for example, AVG(NUMBER), MAX(EXPRESSION), MIN(EXPRESSION)
Others	Select a value from the drop-down box, for example, GREATEST (String1, String2, String3...), and LEAST (String1, String2, String3...).
Mathematical	Select a value from the drop-down box, for example, ABS (NUMBERS), ACOS (FLOAT), ATAN (FLOAT), etc.
Concatenation	Select a value from the drop-down box, for example, , -.
Mathematical operators	Select a value from the drop-down box, for example, +, -, %, *, and /.
Others	Select a value from the drop-down box, for example, PRIOR, ENCLOSED (+), (, and).
Comparison	Select a value from the drop-down box, for example, =, !=, <>, >, etc.
Logical Operators	Select a value from the drop-down box, for example, NOT, AND, and OR.
Expression	Enter an expression.

NOTE

The functions and operators in the expression window that are irrelevant to the **Reconciliation Framework** are as follows:

- String
- Date and Time
- Aggregate
- Others
- Mathematical
- Concatenation
- Mathematical operators
- Others
- Comparison
- Logical Operators

Figure 54: Add Expression Window

Click the **OK** icon.

Click **Next** icon, the next tab **Review & Save** is displayed.

9.1.2.4 Review & Save page

In the **Adjustment Rule Details** page, click the **Save** icon.


Figure 55: Adjustment Rule Details Page- Review & Save tab

10 Reconciliation Summary

The Reconciliation Summary screen provides a visual representation of the list of executions that are completed successfully along with its details.


1. Navigate to **Reconciliation Framework** and select the **Reconciliation Summary**.

Figure 56: Reconciliation Summary Navigation Pane



2. When you navigate to the **Reconciliation Summary** screen, the **Reconciliation History** screen appears.


Figure 57: Reconciliation History page



3. This screen provides a list of all the successful executions complete for the previous period, by default. You can zoom in to a particular day of a month and check the list of executions.
4. Click one execution, it gives a high-level summary of that particular execution. Once the execution is selected, Two panels appear on the right side,. The first panel provides the details

about the number of definitions executed in that execution and the second panel provides the time taken for that execution in seconds along with the Start and End timestamps.

Figure 58: Reconciliation History page for single execution details





5. Click **Rule**  icon. The details about the execution along with the reconciled balances are displayed.

Figure 59: Reconciliation History page-List of Rules








6. Click  icon. The details of the execution entity name along with the balance type is displayed. You can open the report details using the additional icons (highlighted in the following screen).

Figure 60: Reconciliation History page-List of Rules navigations



For executions that have been executed with Auto Approval Flag as Yes, the Adjustments are directly posted in the target tables. For other Executions that are executed with Auto Approval Flag as No, the user has the choice to review the adjustments, modify the default values, and then approve the adjustments.

- **Export:** Click **Export**  icon, to export the values to an excel sheet and save it.
- **Import:** Click **Import**  icon, to open the Business Model Upload window.
- **Approve:** Click **Approve**  icon, it displays the total amount approved by the Authorizer.
- **Adjustment template:** Click the Adjustment template link, it opens the Post Adjustment Data window displaying the Number of Rows Adjusted and the list of the adjustments.

From the list of Entity Type with its Balance Type, click the displayed link that directs to the Post Adjustment Data window. This window displays the Number of Rows Adjusted along with the details of the adjustment, as shown in *Figure 62*.

Among other properties, each Adjustment Entry consists of a Run Execution ID, a GL Date, and a Definition. You may search on any of these properties in the Search section.

Figure 61: Post Adjustment Data window

Post Adjustment Data

Number of Rows Adjusted :2

Search Adjustment 🔍 x

GL_481_662
Legal Entity: LE1
Load Run Id: 1
Currency Code: USD
GAAP Code: USGAAP


Attribute: N_EOP_BAL
 Adjusted Value: -92000
 Attribute: V_BRANCH_CODE
 Adjusted Value: XYZ

GL_481_661
Legal Entity: LE1
Load Run Id: 1
Currency Code: INR
GAAP Code: USGAAP

Attribute: N_EOP_BAL
 Adjusted Value: -91800
 Attribute: V_BRANCH_CODE
 Adjusted Value: XYZ

- From the list of rules, click the required rule. The chart representations are displayed for all the dimensions in Reconciliation for a default Currency available in the Definition.

Figure 62: Reconciliation History page-Chart representation






- Click  icon on the Left-Hand Side of the screen, as shown in *Figure 64*. This has the list of dimensions that are used in the rules involved with the execution. You can select any number of dimensions and check the different balances for the selected dimensions. A drop-down list with all the available currencies for the selected definition is available and you can select the required currency.

Figure 63: Reconciliation History page- Chart representation Dimensions settings



9. The **Reconciliation History** screen displays two charts:

Figure 64: Reconciliation History page- two charts representation




10. **Bubble Chart** with X-Y plot, where X-axis gives the Source balance and Y-axis gives the Absolute Target balance. The size of the bubble is determined by the ratio of Absolute Recon Difference to Source Balance.

The following are the color representation of the bubble with there descriptions:

- The color of the bubble is green when none of the differences has breached the Threshold (NB).
- The color of the bubble is Red if at least one of the differences is breached (NPT, PPT, NAT, PAT).

For more information on NPT, PPT, NAT, and PAT see the [Glossary](#) section.

Figure 65: Reconciliation History page- Bubble Chart



11. Click the **Bubble** to view the tabular format of all the differences aggregated to form that bubble.


Figure 66: Tabular format view for Bubble chart

Execution Identifier	GI Mapping Id	Version Number	Source Balance	Target Balance
INFODOM7_1535982606070_20141114_1	1	1	95000	830

Close

12. You can view the **FCT_RECONCILIATION_DIFFERENCE** table in a flexible format.
13. **Histogram** with X-Y plot, where X-axis is the buckets of Absolute Recon Differences, and Y-axis is the number of definitions in a bucket.

Figure 67: Reconciliation History page- Histogram Chart







- Click  icon, to navigate to the Grid visualization of the aggregated differences for the selected dimensions and currency.

Figure 68: Reconciliation History page- Application icon view

Reconciliation History
View Execution History Information

Execution Identifier	GI Mapping Id	Version Number	Source Balance	Target Balance	Reconciliation Difference	Iso Currency Code	Gaap Code	Legal
1592217754191_50821844_20101231_1	22	2	276.685	41.246	237.439	AUD	AUGAAP	LE1

Page 1 of 1 (1 of 1 items)

- Click  icon on the grid to export the grid values to an excel sheet and save it.
- Click  icon, to return to the Bubble chart and Histogram.
- Click  icon, to navigate to the Reconciliation Summary screen.

11 OFS Analytical Applications Reconciliation Framework Dashboards and Reports

Topics:

- [Overview of OFS Analytical Applications Reconciliation Framework Reports and Dashboards](#)
- [Accessing the Standard Reports and Dashboards](#)
- [Report Descriptions](#)

11.1 Overview of OFS Analytical Applications Reconciliation Framework Reports and Dashboards


OFS Analytical Applications Reconciliation Framework integrates the results generated by the OFS Analytical Applications Reconciliation Framework with Oracle Business Intelligence. It provides you with a reporting-cum-information framework which can be used for generating reports and viewing information relevant to computations and other aspects of the OFS Analytical Applications Reconciliation Framework Application. It serves as a single regulatory and management reporting solution. OFS Analytical Applications Reconciliation Framework leverages the capabilities of Oracle Business Intelligence Enterprise Edition, to provide out of the box reporting of your OFS Analytical Applications Reconciliation Framework Application results. Through OBIEE, you have access to a robust reporting engine for managing all of your business intelligence requirements. The key elements are listed as follows:

- Tabular and pivot table reporting
- Drill across capability
- Dashboard publishing
- Export options, such as Excel, PowerPoint, and PDF

11.2 Accessing the Standard Reports and Dashboards

You can access the standard dashboards and reports by accessing the OBIEE end user URL and logging in to the application. When you sign-on to the application, you are directed to the Home Page, which will show basic summary reports. At the top right-hand corner of the window, click the dashboards drop-down menu containing the listing of all of the seeded dashboards that you can select for navigating to the desired location.

Figure 69: Business Intelligence page- Seeded Dashboards




OFS Analytical Applications Reconciliation Framework Analytics consists of three dashboards:

- Home


- Threshold Breach
- Reconciliation Execution Audit Trail

Figure 70: Business Intelligence page- Reconciliation Framework Analytics



Each seeded dashboard contains a set of prompts at the top of the page, which require selections for the reports to produce results. Make the appropriate selections for each prompt to correctly filter the query for your results. The **Home** and **Threshold Breach** dashboard consists of the following page level prompts:

Figure 71: Home and Threshold Breach dashboard level prompts



- **Extraction Date:** Select the FIC MIS Date and click the Calendar icon.
- **Scenario Type:** Select the Scenario Type from the drop-down as Reported or Actual. Reported data indicates that the GL reconciliation differences are identified based on forecasted figures.
- **Execution ID:** All successful Run executions with the status as complete in the Run Execution Summary window is populated here. Select the appropriate Run Execution ID from the drop-down.

After updating the prompts click the **Apply** button. To refresh the data in the fields click **Reset**.

The **Reconciliation Execution Audit Trail** Dashboard consists of the following page level prompts:

Figure 72: Reconciliation Execution Audit Trail dashboard level prompts



- **User ID:** Data is displayed based on the User ID selected from the drop-down list.
- **Information Type:** Select the information type from the drop-down list as Null, Error, or Info.
- **Execution Date:** Select the date on which the Run is executed.

A few reports also have filters at each reporting level which are detailed in the section Report Descriptions. Select the appropriate report filters so that data is displayed accordingly. Each report within a dashboard contains the following features:

- **Refresh:** Click this button to update the values displayed in the report.
- **Print:** Click this button to print a particular report.
- **Export:** Click this button to export data into multiple formats such as PDF, Excel, PowerPoint, and so on.
- **Return:** To navigate back to the previous window click **Return**.

- **Create Bookmark Link:** To share or save a browsed page click **Create Bookmark Link**. Sort icons also appear on each tabular report to sort the data in ascending or descending order. A few reports also consist of a drill through capability wherein you can navigate to the most granular level of data.

11.3 Report Descriptions

Topics:

- [Dashboard: Home](#)
- [Dashboard: Threshold Breach](#)
- [Dashboard: Reconciliation Execution Audit Trail](#)
- [Dashboard: Drill Down](#)

11.3.1 Dashboard: Home

This section provides information about the Dashboard Home page used in the Reconciliation Framework application.

Table 11: Reconciliation Execution Summary information

Report Name	Reconciliation Execution Summary
Report Level Filters	Not Applicable
Report Description	<p>This tabular report displays, in a nutshell, the following parameters of the selected Run Execution ID:</p> <ul style="list-style-type: none"> • Map Name: This is the name of the reconciliation as defined in the Reconciliation Management window. • Map-Version Number: This is the version number of the defined reconciliation. The version number indicates the number of times the reconciliation is edited at the reconciliation definition stage. • Legal Entity: The Legal Entity as defined for this particular map and the version number is displayed here. • Consolidation Type: The consolidation type as Solo, Consolidation, or Aggregate is displayed here. • Reconciliation Type: The reconciliation type, that is, a Ledger to Ledger Reconciliation, General Ledger to Product Processor (Manual Reconciliation), or General Ledger to Product Processor (Auto Reconciliation) is displayed here. • Reconciliation Level: Displays the level at which the reconciliation is performed, that is, GL Level or Map Level. • Adjustment Allocation: Adjustment Allocation is displayed here as 'Yes' or 'No' as defined in the Reconciliation Management windows. • Balance Type: The Reconciliation period as defined in the Reconciliation Management window is displayed here. • Reconciliation Dimensions: The Mandatory Dimensions and as well as Optional Reconciliation Dimensions (if any) are displayed here.

Drill-through On	Not Applicable
------------------	----------------

Figure 73: Reconciliation Execution Summary page

Map Name	Map Version Number	Legal Entity	Consolidation Type	Reconciliation Type	Reconciliation Level	Adjustment Allocation	Balance Type	Reconciliation Dimensions
GL_PP_18_1	1	Bank Holding Company	Solo	General Ledger to Product Processor - Manual	GL Level	Yes	End of Period	Currency for Reconciliation GAAP Code for Reconciliation Legal Entity for Reconciliation

Edit - Refresh - Print - Export

Table 12: Reconciliation Difference Report information

Report Name	Reconciliation Difference Report
Report Level Filters	<p>Map Name: This is the name of the reconciliation as defined in the Reconciliation Management window.</p> <p>Map Version: This is the version number of the defined reconciliation. The version number indicates the number of times the reconciliation is edited at the reconciliation definition stage.</p> <p>Reconciliation Difference Value Display: If the Reconciliation Difference is to be displayed in actual format, select Actual, or else select Percentage.</p>
Report Description	<p>This tabular report displays, in a nutshell, the identified Reconciliation Differences for a particular Map. The following parameters are displayed</p> <ul style="list-style-type: none"> • GL Name: The name of the specific GL entity code of the selected Map name is displayed • Currency: Displays the currency in which the actual reconciliation difference is displayed • Source Balance: The account balance at the source GL entity level is displayed here <ul style="list-style-type: none"> ▪ Target Balance: The account balance at the target GL entity level (for Ledger to Ledger reconciliation) or Product Processor is displayed here. ▪ Positive Reconciliation Difference: Any positive reconciliation difference based on the source entity balance is displayed here. ▪ Negative Reconciliation Difference: Any negative reconciliation difference based on the target entity balance is displayed here. <p>Note: If the percentage is selected in the Reconciliation Difference Value Display field, then the positive reconciliation difference and negative reconciliation difference are compared and the relevant percentage value is populated. For example: If Actual Positive Reconciliation Difference is 5000 and Actual Negative Reconciliation Difference is 0, then the percentage is displayed as 100 for positive reconciliation difference.</p> <p>Absolute Reconciliation Difference: This is calculated as the total difference by ignoring the signs between the negative and positive reconciliation differences. For example: if Positive Reconciliation Difference is 19,500 and Negative Reconciliation Difference is 23,000, then the absolute difference is 42,500.</p> <p>Net Reconciliation Difference: This is the net difference between negative and positive reconciliation differences. For example: if Positive Reconciliation</p>

	Difference is 19,500 and Negative Reconciliation Difference is 23,000, then the net difference is 3,500.
Drill-through On	GL Name
Drill-through	Report Name: Reconciliation Difference Detailed Report
Description	<p>Navigation Path: Click GL Name in the Reconciliation Difference Report to view the detailed report. This detailed report is displayed for the particular Map Name and Version number selected in the Report Level Filters.</p> <p>This tabular report provides a detailed view of the identified reconciliation differences and the following parameters are reported:</p> <ul style="list-style-type: none"> • GL Name: The name of the specific GL entity code of the selected Map Name is displayed. • Legal Entity: The Legal Entity as defined for the particular map and version number is displayed here. • GAAP Code: The GAAP code defined in the reconciliation is displayed here. • Currency: Displays the currency in which the actual reconciliation difference is displayed. • Other optional dimensions: Values against respective optional dimensions (if any) are reported here. • Source Balance: The account balance at the source GL entity level is displayed here. • Target Balance: The account balance at the target GL entity level (for Ledger to Ledger reconciliation) or Product Processor is displayed here. • Reconciliation Difference: The net reconciliation difference is displayed here.

Figure 74: Reconciliation Difference Report

Reconciliation Difference Report

Map Name: GL_PP_18_1 | Map Version: 1 | Reconciliation Difference Value Display: Actual

GL Name	Gaap Code	Currency	Legal Entity	Source Balance	Target Balance	Positive Reconciliation Difference	Negative Reconciliation Difference	Absolute Reconciliation Difference	Net Reconciliation Difference
10301	USGAAP	INR	LE1	45,000	43,000	2,000	0	2,000	2,000
		USD	LE1	45,000	50,060	0	5,060	5,060	5,060
10302	USGAAP	INR	LE1	50,000	50,100	0	100	100	100
		USD	LE1	50,000	48,020	1,980	0	1,980	1,980

[Edit](#) - [Refresh](#) - [Print](#) - [Export](#)

Figure 75: Reconciliation Difference Detailed Report

Reconciliation Difference Detailed Report

GL Name	Legal Entity	Currency	GAAP Code	Organization unit	Product	Customer Class	Business Unit	Geography	Source Balance	Target Balance	Reconciliation Difference
10301	Bank Holding Company	Indian Rupee	United States of America GAAP	-	-	-	-	-	45,000	91,789	-46,789
		US Dollar	United States of America GAAP	-	-	-	-	-	45,000	538,236	-493,236

[Return](#) - [Edit](#) - [Refresh](#) - [Print](#) - [Export](#) - [Create Bookmark Link](#)

Table 13: Reconciliation Adjustment Report information

Report Name	Reconciliation Adjustment Report
--------------------	----------------------------------

Report Level Filters	<ul style="list-style-type: none"> • Map Name: This is the name of the reconciliation as defined in the Reconciliation Management window. • Map Version: This is the version number of the defined reconciliation. The version number indicates the number of times the reconciliation is edited at the reconciliation definition stage. • Reconciliation Difference Value Display: If the Reconciliation Difference is to be displayed in Actual format select Actual, or else select Percentage.
Report Description	<p>This tabular report is displayed if Adjustment Allocation is selected as 'Yes' while defining reconciliation. This report displays in a nutshell, the adjustment amount pass</p> <p>The following parameters are displayed:</p> <ul style="list-style-type: none"> • GL Name: The name of the specific GL entity code of the selected Map Name is displayed. • Currency: Displays the currency in which the Adjustment Entry is processed. • Reconciliation Difference: The net reconciliation difference is displayed here. • Legal Entity: The Legal Entity as defined for this particular map and the version number is displayed here. • Approved Adjustment Amount: The adjustment amount authorized by the approver is displayed here. • Pending Adjustment Amount: The adjustment amount pending to be submitted from the Adjustment Entry window is displayed here. • Submitted Adjustment Amount: The adjustment amount submitted from the Adjustment Entry window, however waiting to be approved by authorizer is displayed here. • Rejected Adjustment Amount: The adjustment amount rejected by the authorizer from the Adjustment Entry Approval window is displayed here
Drill-through On	GL Name
Drill-through	<p>Report Name: Reconciliation Adjustment Detailed Report</p> <p>Navigation Path: Click GL Name in the Reconciliation Adjustment Report to view the detailed report. This detailed report is displayed for the particular Map Name and Version number selected in the Report Level Filters.</p> <p>This tabular report provides a detailed view of the adjustment entries passed and the following parameters are reported:</p> <ul style="list-style-type: none"> • GL Name: The name of the specific GL entity code of the selected Map Name is displayed. • Legal Entity: The Legal Entity as defined for this particular map and the version number is displayed here. • Currency: Displays the currency in which the actual reconciliation difference is displayed. • GAAP Code: The GAAP code defined in the reconciliation is displayed here. • Other optional dimensions: Values against respective optional dimensions (if any) are reported here. • Exposure Amount: The Adjustment Entry amount is displayed here. • Authorization Status: If the Adjustment Entry is approved, pending to be submitted, or submitted but pending to be approved, then the relevant status is displayed here.

- Product Processor: The PP to which the Adjustment Entry is passed is displayed here.
- Product Processor Balance Column: The specific column in the PP to which the Adjustment Entry is passed is displayed here

Figure 76: Reconciliation Adjustment Report

Reconciliation Adjustment Report											
Map Name		GL_PP_18_1		Map Version		1		Reconciliation Adjustment Value Display			Actual
GL Name	GAAP Code	Currency	Legal Entity	Reconciliation Difference	Significant Reconciliation Difference	Approved Adjustment Amount	Pending Adjustment Amount	Submitted Adjustment Amount	Rejected Adjustment Amount		
10301	USGAAP	INR	LE1	2,000	2,000	2,000	0	0	0		
		USD	LE1	5,060	5,060	0	5,060	0	0		
10302	USGAAP	USD	LE1	1,980	1,980	0	0	1,980	0		

[Edit](#) - [Refresh](#) - [Print](#) - [Export](#)

Figure 77: Reconciliation Adjustment Detailed Report

Reconciliation Adjustment Detailed Report												
GL Name	Entity name	Currency	GAAP Code	Organization Unit	Product	Customer Class	Business Unit	Geography	Exposure Amount	Authorization Status	Product Processor	Product Processor Balance Column
10301	Bank Holding Company	Indian Rupee	United States of America GAAP	-	-	-	-	-	2,000	Approved	STG_LOAN_CONTRACTS	N_EOP_BAL
		US Dollar	United States of America GAAP	-	-	-	-	-	-5,060	Pending For Submission	STG_LOAN_CONTRACTS	N_EOP_BAL
10302	Bank Holding Company	US Dollar	United States of America GAAP	-	-	-	-	-	1,980	Submitted For Approval	STG_LOAN_CONTRACTS	N_EOP_BAL

[Return](#) - [Edit](#) - [Refresh](#) - [Print](#) - [Export](#) - [Create Bookmark Link](#)

11.3.2 Dashboard: Threshold Breach

Table 14: Threshold Breach Summary information

Report Name	Threshold Breach Summary
Report Level Filters	Not Applicable
Report Description	<p>This report displays in a nutshell, the threshold parameters of the selected Run Execution ID. The following parameters are reported:</p> <p>Global Threshold: Global Threshold displayed here indicates the point of reconciliation difference greater than which execution process may stop or continue at the time of execution. Global Threshold is compared with cumulative percentage difference across all reconciliation definition getting executed in a Run.</p> <ul style="list-style-type: none"> • Execution on Threshold Breach: Depending upon your selection in the Run Execution Parameters window, Continue or Stop is displayed here. • Auto Approval: The value as selected in the Run Execution Parameter window that is, Yes or No, is displayed here. • Global Threshold: If the Global Threshold Level is breached or not breached, then the relevant information is displayed here. • In a tabular form the following parameters are reported: • Map Name: This is the name of the reconciliation as defined in the Reconciliation Management window.

	<ul style="list-style-type: none"> • Map-Version Number: This is the version number of the defined reconciliation. The version number indicates the number of times the reconciliation is edited at the reconciliation definition stage. • Number of Observations: The number of times the same map and version is executed is displayed here. • Number of Breaches: The number of breaches reported based on the threshold value specified in the Reconciliation Management window is displayed here.
Drill-through On	Map Name
Drill-through Description	<p>Report Name: Threshold Breach Detailed Report</p> <p>Navigation Path: Click Map Name in the Threshold Breach Summary to view the detailed report.</p> <p>Map Level Filters: Map Name, Map Version</p> <p>This tabular report provides a detailed view of the threshold value breaches and the following parameters are reported:</p> <ul style="list-style-type: none"> • GL Name: The name of the specific GL entity code of the selected Map Name is displayed. • Legal Entity: The Legal Entity as defined for this particular map and the version number is displayed here. • Currency: Displays the currency in which the actual reconciliation difference is displayed. • GAAP Code: The GAAP code defined in the reconciliation is displayed here. • Other optional dimensions: Values against respective optional dimensions (if any) are reported here • Source Balance: The account balance at the source GL entity is displayed here. • Target Balance: The account balance at the target GL entity (for Ledger to Ledger reconciliation) or Product Processor is displayed here. • Reconciliation Difference: The net reconciliation difference amount is displayed here. • Threshold Breach Type: The threshold breach type is displayed here as a negative or positive breach. This is based on positive and negative reconciliation differences. • Threshold Value: The value as per the breach type is displayed here. • Threshold Currency: The Threshold currency is displayed if the Threshold value is in Absolute format. • Threshold Breached by The value or percentage by which the threshold value is breached based on the reconciliation difference is reported here.

Figure 78: Threshold Breach Summary



Figure 79: Threshold Breach Detailed Summary

Threshold Breach Detailed Report

Map Name: Map Version:

GL Name	Entity Name	Currency	GAAP Code	Organization Unit	Product	Customer Class	Business Unit	Geography	Source Balance	Target Balance	Reconciliation Difference	Threshold Breach Type	Threshold Value	Threshold Currency	Threshold Breached By
10301	Bank Holding Company	Indian Rupee	United States of America GAAP	-	-	-	-	-	45,000	43,000	2,000	Positive Percentage Threshold	1 %		3.444 %
		US Dollar	United States of America GAAP	-	-	-	-	-	45,000	50,060	-5,060	Negative Percentage Threshold	1 %		-10.244 %
10302	Bank Holding Company	US Dollar	United States of America GAAP	-	-	-	-	-	50,000	48,020	1,980	Positive Percentage Threshold	1 %		2.96 %

[Return](#) - [Edit](#) - [Refresh](#) - [Print](#) - [Export](#) - [Create Bookmark Link](#)

Table 15: Global Threshold Breach Summary information

Report Name	Global Threshold Breach Summary
Report Level Filters	Not Applicable
Report Description	<p>This report displays in a nutshell, the global threshold parameters of the selected Ru Execution ID. The following parameters are reported:</p> <ul style="list-style-type: none"> • Global Threshold Percentage: Global Threshold displayed here indicates the point at which the execution process may stop or continue at the time of execution if the reconciliation difference surpasses the defined Global Threshold level. Global Threshold is compared with the cumulative percentage difference across all reconciliation definitions getting executed in a Run. • Difference Percentage: The absolute percentage difference is displayed here. • Breach Percentage: The percentage by which the Global Threshold is breached based on the reconciliation difference is displayed here.
Drill-through On	Not Applicable

Figure 80: Global Threshold Breach Summary




Table 16: Threshold Definition information

Report Name	Threshold Definition
Report Level Filters	<p>GL Map Name: The name of the specific GL entity map name must be selected here.</p> <p>Map Version: This is the version number of the selected map name. The version number indicates the number of times the reconciliation is edited at the reconciliation definition stage.</p>
Report Description	<p>This tabular report displays the following parameters:</p> <ul style="list-style-type: none"> • Target Entity: The name of the Product Processor is displayed here in case of a GL to PP reconciliation or name of the Target GL entity is displayed here.

Drill-through On	<ul style="list-style-type: none"> • Target Balance Column: The specific column in the Product Processor (for GL – PP reconciliation) or target GL entity (for GL-GL reconciliation) is displayed here. • The threshold in: Displays the type of threshold that is absolute or percentage. • Threshold Currency: The currency, in which the threshold value is defined, displayed here. Currency is not displayed when the Percentage is selected. • Positive Correction Threshold: The positive correction threshold value as defined in the Reconciliation Management window is displayed here. • Negative Correction Threshold: The negative correction threshold value as defined in the Reconciliation Management window is displayed here.
	Not Applicable

Figure 81: Threshold Definition

Target Entity	Target Balance Column	Threshold In	Threshold Currency	Positive Correction Threshold	Negative Correction Threshold
STG_LOAN_CONTRACTS	N_EOP_BAL	Percentage	NA	1	1

11.3.3 Dashboard: Reconciliation Execution Audit Trail

This dashboard provides evidence on the sequence of activities performed by a User ID on a particular execution date. This audit trail is useful for the following reasons:

It provides a record of the history of a defined Reconciliation for the benefit of senior management.

It is useful for maintaining the security of the system. Errors can be easily detected.

Select the value from the page level prompts, the following report is populated in a tabular format:

Figure 82: Reconciliation Execution Audit Trail Dashboard

Execution Identifier	Map Id	Map Version Number	Information Type	Details
1594339277327_54880272_20141114_1	461	1	INFO	Threshold has been breached for Execution ID = 1594339277327_54880272_20141114_1,Map ID = 461,Version No = 1,GL CODE = 10301 Threshold Breached By = -93,Breach type = NPT,v_iso_currency_cd : INR,v_entity_code : LE1,v_gaap_code : USGAAP
		1		Threshold has been breached for Execution ID = 1594339277327_54880272_20141114_1,Map ID = 461,Version No = 1,GL CODE = 10301 Threshold Breached By = -93,Breach type = NPT,v_iso_currency_cd : USD,v_entity_code : LE1,v_gaap_code : USGAAP
		1		Threshold has been breached for Execution ID = 1594339277327_54880272_20141114_1,Map ID = 461,Version No = 1,GL CODE = 10302 Threshold Breached By = -93,Breach type = NPT,v_iso_currency_cd : INR,v_entity_code : LE1,v_gaap_code : USGAAP
		1		Threshold has been breached for Execution ID = 1594339277327_54880272_20141114_1,Map ID = 461,Version No = 1,GL CODE = 10302 Threshold Breached By = -93,Breach type = NPT,v_iso_currency_cd : USD,v_entity_code : LE1,v_gaap_code : USGAAP


11.3.4 Dashboard: Drill Down

- **Extraction Date:** Select the FIC MIS Date and click the Calendar icon.
- **Execution ID:** All successful Run executions with the status as complete in the Run Execution Summary window is populated here. Select the appropriate Run Execution ID from the drop-down.

NOTE Run Name field is not required for this particular report.

This report is used to view the sum of 'Source Balance', 'Target Balance' and 'Reconciliation Difference' across 'Legal Entity', 'GAAP Code', 'Currency', 'Organization Unit', 'Customer Class', 'Business Unit', 'Geography' along with 'GL Hierarchy' and 'Product'.

Figure 83: Drill Down Dashboard



12 Adding Custom Reconciliation Dimensions in Detailed Reconciliation Reports

To add custom dimensions in reports, perform the following steps:

1. Open the RPD.
2. Provide the Database connection details in 'Physical Layer'.
3. Keep the 'Physical Schema' name similar to that of the Database Schema Username.
4. Add the Dimension Table to the Physical Layer.
5. Create required join or joins between the Dimension and Fact Table or Tables.
6. Drag the Physical Dimension Table into the 'Business Model and Mapping' Layer.
7. Create required join or joins between the Dimension and Fact Table or Tables in 'Business Model and Mapping' Layer.
8. If required, create hierarchies in Business Model and Mapping Layer.
9. Drag the Logical Dimension table from Business Model and Mapping Layer into Presentation Layer.
10. Deploy the RPD and restart services.

The newly added dimension is now ready to be used in the reports.

Finally, the 'Physical Schema' name in Physical Layer can be changed to any other required name.

13 Annexure A

Topics:

- [Entity Details](#)
- [Adjustment Auto Approval Concept](#)
- [Data Model and Metadata Extensions](#)
- [Procedure to Add Optional Dimensions](#)
- [Optimization of GL Reconciliation Processing Package](#)
- [Map Level Recon Parent Node Selection](#)
- [GL Nodes Configuration](#)
- [Hierarchy Refresh](#)
- [Creating Filter for Load Run ID](#)
- [Duplicate Adjustments](#)
- [VPAT-keystrokes and access keys](#)

13.1 Entity Details

The following provides a brief description of the various tables:

Table 17: Entity Details Names

Name	Comment	Download or DT
GL Master	This table stores a list of all available GL codes. Select a subset of GL codes that is to be considered for the GL Reconciliation.	Partly DL & Partly Setup
Product Processors	This table stores a list of all PPs supported by the GBS data model. Select a subset of Product Processors for which GL Recon is required.	DL
Setup GL Balances	This table stores the table name of the table which stores the GL data along with the mapping of various columns within that table.	DL
Stage GL Data	This table stores the values of each of the GL codes which is present in the table GL Master.	DL
GL Mapping Master	This table stores the information about mapping for its reconciliation treatment and any thresholds that must be applied at a mapping level during the GL Reconciliation.	Setup
GL PP Map	This table stores the mapping between a GL and a PP and the associated granularity of the GL that must be reconciled with a certain granularity in the PP. The same GL can be mapped to multiple PPs and conversely, a PP can be mapped to multiple GLs. The mapping stored in this entity drives all other processes for GL Reconciliation.	Setup

Name	Comment	Download or DT
PP Default Values	This table stores the default values that must be used for mandatory columns within the PP in the event an adjustment entry is to be posted into the corresponding PPs.	Setup
Product Processor(s)	It receives for every processing period, the account level information across various products.	DL
GL Adjustment Entries	This table stores the information about the adjustment entries after the differences are found out.	Processing
GL Execution Master	This table stores the information on each execution.	Processing
GL Threshold Breaches	This table stores the breaches from the thresholds as specified in the Rule Configuration, if any.	Processing
GL Recon Audit Trail	This table stores a trace of all add, modify or delete operations performed through User Interfaces.	Log
GL Execution Info	At the time of batch execution, this table gets updated and it checks if the mapping which is chosen for GL Reconciliation pertains to the entity which is selected	Processing
Dynamic SQL error log	This table stores the processing specific dynamic SQL queries as well as Error details if any.	Log
Fact Reconciliation Difference	This table stores the results of executing a defined reconciliation, that is, it stores the reconciliation difference amount if any.	Processing

The requirement for Purging or Archiving FACT tables must be analyzed, developed, and executed as per the implementation site requirements; for better performance and space management.

13.2 Adjustment Auto Approval Concept

Table 18: Adjustment Auto Approval Concept Results table

GL or Map level Reconciliation (In Reconciliation Management page)	Allocation required (In Reconciliation Management page)	Auto Approval (In PMF Execution Parameter)	Result - Auto Approval (Y, N) of Adjustment Entry
GL	N	N	N - GL Code where Auto Approval flag is N will not be used for reconciliation and no adjustment entry is passed against it. Allocation required and auto-approval will not be considered for the GL code.
GL	N	N	N - The difference for the GL code is taken to the FCT_RECONCILIATION_DIFFERENCE and a threshold check is performed. No impact on FCT_GL_ADJUSTMENT_ENTRIES.
GL	N	Y	N - GL Code where Auto Approval flag is N is not used for reconciliation and no adjustment entry is passed against it. Allocation required and auto-approval is not considered for the GL code.
GL	N	Y	N - The difference for the GL code is taken to the FCT_RECONCILIATION_DIFFERENCE. Auto Approval (In Run Management Screen) will not be considered.
GL	Y	N	N - GL Code where Auto Approval flag is N is not used for reconciliation and no adjustment entry is passed against it. Allocation required and auto-approval is not considered for the GL code.
GL	Y	N	N - The adjustment entry for the GL code is in FCT_GL_ADJUSTMENT_ENTRIES.
GL	Y	Y	Y - The adjustment entry for the GL code is taken to the target entity or PP.
GL	Y	Y	N - GL Code where Auto Approval flag is N will not be used for reconciliation and no adjustment entry is passed against it. Allocation required and auto-approval will not be considered for the GL code.
Map	N	N	N - GL Code where the Auto Approval flag is N will not be used for reconciliation.

GL or Map level Reconciliation (In Reconciliation Management page)	Allocation required (In Reconciliation Management page)	Auto Approval (In PMF Execution Parameter)	Result - Auto Approval (Y, N) of Adjustment Entry
Map	N	N	N - Accounts having such GL codes will participate in map level reconciliation. The difference is taken to the FCT_RECONCILIATION_DIFFERENCE and a threshold check is performed. No impact on FCT_GL_ADJUSTMENT_ENTRIES.
Map	N	Y	N - GL Code where the Auto Approval flag is N will not be used for reconciliation. Auto Approval (in PMF Execution Framework) will not be considered.
Map	N	Y	N - Accounts having such GL codes will participate in map level reconciliation. The difference for the GL code is taken to the FCT_RECONCILIATION_DIFFERENCE and a threshold check is performed. No impact on FCT_GL_ADJUSTMENT_ENTRIES. Auto Approval (in the PMF Execution Framework page) will not be considered.
Map	Y	N	N - GL Code where the Auto Approval flag is N will not be used for reconciliation. The adjustment entry is in FCT_GL_ADJUSTMENT_ENTRIES with status as pending for approval. It'll not be taken to the target entity or PP.
Map	Y	N	N - Accounts having such GL codes will participate in map level reconciliation. The adjustment entry for the GL code is in FCT_GL_ADJUSTMENT_ENTRIES with status as pending for approval. It'll not be taken to the target entity or PP.
Map	Y	Y	Y - Accounts having such GL codes will not participate in map level reconciliation. The adjustment entry for the rest of the reconciliation is taken to the target entity or PP.
Map	Y	Y	Y - Accounts having such GL codes will participate in map level reconciliation. The adjustment entry for the rest of the reconciliation is taken to the target entity – PP.

13.3 Data Model and Metadata Extensions

Topics:

- [Steps to Configure an Additional Table in the Application](#)

13.3.1 Steps to Configure an Additional Table in the Application

To add a Ledger entity, Product Processor entity, or Dimension table in OFS Analytical Application Reconciliation Framework, follow these steps.

For example, to add a GL Entity for General Ledger to General Ledger reconciliation, perform the following steps:

1. Open the OFS_GLRECON.erwin file in Erwin Data Modeler.
2. Change the view mode to Physical.
3. If Target ledger Structure is different than STG_GL_DATA:
 - a. Place the cursor on the tables in OFSAA Tree View, right-click, and select New. This creates a new table. Rename it to the required table name.
 - b. Expand the table and click the '+' icon to view the columns mapped against the tables.
 - c. Place the cursor on the columns mapped against the tables, right-click, and select New. It adds a new column to that table. Rename it to the required column name.
 - d. Repeat the above-mentioned steps to add multiple tables and columns.
 - e. Navigate to Logical View and provide the logical table name and logical column names to the added columns.
4. If Target ledger Structure is the same as STG_GL_DATA:
 - a. In the OFSAA tree view, you can see Tables.
 - b. Navigate to STG_GL_DATA in OFSAA tree view; right-click and select Go to Diagram.
 - c. Press CTRL+C (to copy) and then CTRL+V (to paste), to create a new table with the same name as STG_GL_DATA. Rename the table name in both the Physical View and Logical View.
 - d. Rename the constraints and index names on the newly added table.
5. Save the newly added tables as .xml file. Choose save as type to XML Types (*.xml).
6. Select option **AllFusion Repository Format** in the dialog box. Click **OK** to generate a new .xml file.
7. Copy that XML file to server for fast processing under ftpshare/infodom/erwin/erwinXML
8. Navigate to the OFSAAI UI and log in. Select an appropriate infodom and navigate to Unified Analytical Metadata. To process further see the following steps:
9. Click Import Model.
10. Select Incremental Changes or Sliced Model in Choose Type to Upload.
11. Select the file from the server. It will list out the files present in the path.

12. Select your XML file and click upload to begin the process to upload the data model. On successful upload, a dialog box pops up.
13. Similarly, follow the steps mentioned above to add a Stage General Ledger Master (STG_GL_ACCOUNT_MASTER), General ledger account dimension (Example DIM_GL_ACCOUNT), or Product processor (Example STG_CARDS).
14. Perform the following steps to continue further (these steps are not applicable for a Product Processor entity):
15. Insert a new unique map_ref_num in two tables **SYS_TBL_MASTER** and **SYS_STG_JOIN_MASTER** for creating SCD for data movement from new Stage general ledger master to new General ledger account dimension.
16. Example: **SYS_TBL_MASTER** – Table contains table level information Stage to Dimension. Table names must be changed according to the new stage general ledger master (**STG_TBL_NM**) to the new General ledger account dimension (**TBL_NM**).

MAP_REF_NUM	TBL_NM	STG_TBL_NM	SRC_PRTY	SRC_PROC_SEQ	SRC_TYP	DT_OFFSET	SRC_KEY
491	DIM_GL_ACCOUNT	STG_GL_ACCOUNT_MASTER		8	MASTER	0	

17. Example: **SYS_STG_JOIN_MASTER** – Column level mapping information from Stage to Dimension. Column names and data types must be modified according to the new Stage general ledger master (**STG_COL_NM**) to the new General ledger account dimension (**COL_NM**).

MAP_REF_NUM	COL_NM	COL_TYP	STG_COL_NM	SCD_TYP_ID	PRTY_LOOKUP_FLG	COL_DATATYPE	COL_FORMAT
491	D_END_DATE	ED	31-Dec-99		N	DATE	
491	D_START_DATE	SD	SD		N	DATE	
491	F_DIFF_AUTO_APPROVE_FLAG	DA	F_DIFF_AUTO_APPROVE_FLAG	2	N	VARCHAR	
491	F_INTRA_GROUP	DA	F_INTRA_GROUP	2	N	CHAR	
491	F_LATEST_RECORD_INDICATOR	LRI	Y		N	CHAR	
491	N_GL_ACCOUNT_ID	SK	SEQ_DIM_GL_ACCOUNT.CURRVAL		N	NUMBER	

MAP_REF_NUM	COL_NM	COL_TYP	STG_COL_NM	SCD_TYP_ID	PRTY_LOOKUP_REQD_FLG	COL_DATA_TYPE	COL_FORMAT
491	N_GL_ACCOUNT_SKEY	SK	SEQ_DIM_GL_ACCOUNT.NEXTVAL		N	NUMBER	
491	V_GL_ACCOUNT_CODE	PK	V_GL_CODE		N	VARCHAR	
491	V_GL_ACCOUNT_NAME	NN	V_GL_NAME	2	N	VARCHAR	
491	V_GL_BOOK_CODE	DA	V_GL_BOOK_CODE	2	N	VARCHAR	
491	V_GL_PARENT_ACCOUNT_CODE	DA	V_PARENT_GL_CODE	2	N	VARCHAR	
491	V_GL_TYPE	DA	V_GL_TYPE	2	N	VARCHAR	

18. Navigate to Operations and see the following steps:

- a. Click Batch Maintenance.
- b. Add a new batch, provide an appropriate name and description, and click Save.

Figure 84: Batch Maintenance Window

The screenshot shows a 'Batch Maintenance' dialog box. It has a title bar with 'Batch Maintenance' and a help icon. Below the title bar, there are 'Save' and 'Cancel' buttons. The main area contains a 'Batch Maintenance' section with a 'Batch Name' text box containing 'BATCH1', a 'Batch Description' text box, and a 'Batch ID' dropdown menu. There are also two checkboxes: 'Duplicate Batch' and 'Sequential Batch', both of which are currently unchecked.

- c. Add a task to the newly created batch.
- d. Select Run Executable under Components.
- e. Select appropriate Datastore type, Datastore Name, IP Address.
- f. Update scd,<<MAP_REF_NUM>> in the executable with the unique number which is provided while inserting in SYS_TBL_MASTER and SYS_STG_JOIN_MASTER. Select Wait as 'N' and Batch Parameter as 'Y'. Click Save as shown in the following figure:

Figure 85: Task Definition Window

Task Definition

Save Reset Close

Task ID Task1 Description

Components EXTRACT DATA

Property	Value
Datastore Type	EDW
Datastore Name	OFSDMINFO
Primary IP For Runtime Processes	10.40.81.109
Source Name	
Extract Name	
Default Value	

Audit Panel

Created By: Creation Date

Last modified by: Last Modification Date

Navigate to Unified Analytical Metadata and see the following steps to proceed further:

- a. Click Data Sets under Business Metadata Management.
 - b. Add a new dataset and provide code, short description, and long description.
 - c. Select the entities that are participating in the Dataset.
 - d. Define Ansi join.
19. Example: where STG_GL_DATA is your Ledger table and DIM_GL_ACCOUNT is your General ledger account dimension.

```
STG_GL_DATA
```

```
INNER JOIN DIM_CURRENCY ON DIM_CURRENCY.V_ISO_CURRENCY_CD =
STG_GL_DATA.V_CCY_CODE
```

```
INNER JOIN DIM_ORG_STRUCTURE ON DIM_ORG_STRUCTURE.V_ENTITY_CODE =
STG_GL_DATA.V_LV_CODE AND
DIM_ORG_STRUCTURE.f_latest_record_indicator='Y'
```

```
INNER JOIN DIM_DATES ON DIM_DATES.D_CALENDAR_DATE =
STG_GL_DATA.FIC_MIS_DATE INNER JOIN DIM_GL_ACCOUNT ON
DIM_GL_ACCOUNT.V_GL_ACCOUNT_CODE =
```

```
STG_GL_DATA.V_GL_CODE AND DIM_GL_ACCOUNT.f_latest_record_indicator='Y'
```

```
INNER JOIN DIM_GAAP ON DIM_GAAP.V_GAAP_CODE = STG_GL_DATA.V_GAAP_CODE
AND
```

```
DIM_GAAP.f_latest_record_indicator='Y' LEFT OUTER JOIN
DIM_BUSINESS_UNIT ON DIM_BUSINESS_UNIT.V_BUSINESS_UNIT_CODE =
STG_GL_DATA.V_BUSINESS_UNIT_CODE AND
```

```
DIM_BUSINESS_UNIT.f_latest_record_indicator='Y'
```

```
LEFT OUTER JOIN DIM_ORG_UNIT ON DIM_ORG_UNIT.V_ORG_UNIT_CODE =
STG_GL_DATA.V_ORG_UNIT_CODE AND
DIM_ORG_UNIT.f_latest_record_indicator='Y'
```

```
LEFT OUTER JOIN DIM_GEOGRAPHY ON DIM_GEOGRAPHY.V_ACCT_BRANCH_CODE =
STG_GL_DATA.V_BRANCH_CODE AND
DIM_GEOGRAPHY.f_latest_record_indicator='Y'
```


```
LEFT OUTER JOIN DIM_PRODUCT ON DIM_PRODUCT.V_PROD_CODE =
STG_GL_DATA.V_PROD_CODE
AND DIM_PRODUCT.f_latest_record_indicator='Y'
```

20. Click **Save**.

21. Navigate to **Unified Analytical Metadata** and click **Business Hierarchy** under **Business Metadata Management**.

22. Add two new Hierarchies on new Ledger Account Dimension, for GL Code, and GL Type and shown in the following figures:

Figure 86: GL Code Example



23. Perform an excel upload for table **SETUP_GLSOURCE_HIERARCHY**

- V_GL_HCY_CODE – Hierarchy code which is created, as on GL code for new general ledger account dimension.
- V_GL_HCY_DIM_TABLE_NAME –General ledger account dimension table name.
- V_GL_HCY_INTRA_GROUP_COL_NAME – Intragroup Column name.
- V_GL_HCY_GL_TYPE_COL_NAME – GL Type column name.

Example:

V_GL_HCY_CODE	V_GL_HCY_DIM_TABLE_NAME	V_GL_HCY_INTRA_GROUP_COL_NAME	V_GL_HCY_GL_TYPE_COL_NAME
HGL009	DIM_GL_ACCOUNT	F_INTRA_GROUP	V_GL_TYPE

13.4 Procedure to Add Optional Dimensions

1. Create a dimension table in the model if required.
2. Add the table (where the dimension is defined) in the join condition of the GL dataset & Product Processor dataset.
3. Create a Hierarchy with metadata authorization.
4. Add a field from the respective dimension table which is used to join with stage product processor tables in the following tables:
 - a. FCT_RECONCILIATION_DIFFERENCE
 - b. FCT_GL_ADJUSTMENT_ENTRIES
 - c. FCT_GL_CORRECTION_ENTRIES
 - d. FSI_TMP_TARGET_BALANCE
 - e. FSI_TMP_SOURCE_BALANCE
 - f. FSI_GL_THRESHOLD_BREACHES
5. Add a field from respective dimension table which is used to join with stage product processor tables in the unique index of the following tables:
 - a. FCT_RECONCILIATION_DIFFERENCE
 - b. FCT_GL_ADJUSTMENT_ENTRIES
 - c. FCT_GL_CORRECTION_ENTRIES
 - d. FSI_TMP_TARGET_BALANCE
 - e. FSI_TMP_SOURCE_BALANCE
6. Upload the customized data model to see the changes reflected in the database.

13.5 Optimization of GL Reconciliation Processing Package

This section is only applicable for RDBMS installation mode.

Parallel Hint for SELECT statements:

The use of a parallel hint is optional in the queries. Perform the following steps to use the parallel hint in SELECT clause of the queries generated during execution:

Insert a record into the GL_SETUP_CONFIGURATION table and provide a parallel hint in the V_COMPONENT_VALUE column.

For example, insert into GL_SETUP_CONFIGURATION (V_COMPONENT_CODE, V_COMPONENT_DESC, V_COMPONENT_VALUE) values ('GLRECON_SEL_PARALLEL_HINT', 'To use Parallel hint in GL Recon Application.', '/**+ parallel */').

In case a parallel hint is not required then the previous step is not required. The usage of a parallel hint is optional for the GL Processing package.

Parallel Hint for CREATE TABLE statements:

The use of parallelism during intermediate table creation is optional. Perform the following steps to use parallelism to CREATE TABLE clause during execution:

Insert a record into the GL_SETUP_CONFIGURATION table and provide a parallel hint in the V_COMPONENT_VALUE column.

For example, insert into GL_SETUP_CONFIGURATION (V_COMPONENT_CODE, V_COMPONENT_DESC, V_COMPONENT_VALUE) values ('CREATE_TABLE_PARALLEL_HINT', 'To use parallelism while creating intermediate tables', 'PARALLEL').

NOTE HINT can be used with a combination of - NOLOGGING and PARALLEL with different degrees of parallelism as follows:

1. PARALLEL
2. NOLOGGING PARALLEL
3. PARALLEL (DEGREE i*)
4. NOLOGGING PARALLEL (DEGREE i*)

*Any positive integer based on available system resources.

13.6 Map Level Recon Parent Node Selection

To select the Map Level Recon parent node, perform the following steps:

1. Ensure that the General Ledger Product Processor (GL PP) Definition has the following settings:
 - a. Reconciliation Definition Type as Manual
 - b. Consolidation Type as Solo
 - c. Reconciliation Definition as Map Level Recon.
2. Create an entry in the SetUpMaster as 'LAM', for the corresponding Map ID and Version Number.

Figure 87: LAM entry in SetUpMaster

V_COMPONENT_CODE	V_COMPONENT_DESC	V_COMPONENT_VALUE
2-1	LAM	2-1

- a. The parent-child hierarchy for the legal entity selected in the definition is considered for filtration.

13.7 GL Nodes Configuration

In case the GL nodes exceed 2024 then use the following configuration to support the hierarchy browser of GL:

1. Change `<PARAMETER NAME="PC_NONBI_BI_SWITCH" VALUE='<PARAM>' />` in `$FIC_HOME/conf/DynamicServices.xml` and deployed location `<CONTEXT_PATH>/CONTEXT_NAME/conf/DynamicServices.xml`
2. `<PARAM>`: Parameter value to be chosen based on no total number of nodes in a hierarchy (OOB: 2048) For example, if hierarchy nodes are 9000, then VALUE must be 9500.
3. After taking backup of these tables, delete the data from `rev_bihier,rev_locale_hier` for the respective hierarchy code.
4. Restart the web and app servers by clearing the `work/cache/tmp` folder.
5. Resave the respective hierarchy, and verify whether the data is populated into the `rev_bihier` table with version 0.
6. Clear browser cache and create the definition from the start.

13.8 Hierarchy Refresh

Topics:

- [Problem](#)
- [Expected Behavior](#)
- [Solution](#)
- [Batch to be Executed](#)

13.8.1 Problem

For a GL Recon Rule running in production, one of the legal entities has a new parent node in the underlying data and the Legal Entity Hierarchy is refreshed with an automatic batch. Because of this change in the legal entity structure, the GL Recon Rule, where the hierarchy is used, is broken.

GL Recon Rule did not fail, it is executed successfully without returning any results. Hence, there is no way for any user to know that there is an issue. When the GL Recon Rule is opened in the front end, the legal entity field is displayed as blank.

13.8.2 Expected Behavior

Ideally, any changes to the underlying data of the hierarchy must be automatically reflected in the GL Recon Rule.

13.8.3 Solution

A batch has to be executed with the **FIC_MIS_DATE** that will refresh all hierarchies used in the existing rule. Before executing the batch, check the entries in the table:

FSI_GL_HIERARCHY_CONFIGURATION

13.8.4 Batch to be executed

The following batch has to be executed with proper FIC_MIS_DATE and the updated hierarchies will be saved in an Audit Table: **FSI_GL_HIER_REFRESH_AUDIT_DDL** for tracking purposes.

Batch: **##INFODOM##REFRESH_HIERARCHY**

13.9 Creating Filter for Load Run ID

You can filter the load Run ID value and process reconciliation accordingly. One load Run ID in the product processor table can be filtered and reconciled with the respective ledger data. When load Run ID filtration is enabled, adjustments automatically get updated with the filtered load Run ID value, irrespective of the value given in default values.

The following is the procedure to filter load Run ID, reconcile, and default the same:

- Add the following entry in GL_SETUP_CONFIGURATION table:

V_COMPONENT_CODE	V_COMPONENT_DESC	V_COMPONENT_VALUE
GLPPLOADRUNIDFILTER	Flag to set parametrized Load Run filter	N

To enable load Run ID filtration, change the flag to Y in the column V_COMPONENT_VALUE.

- Add the following entry in RUN_EXE_PARAMETERS table for the corresponding RunKey

N_RUN_SKEY	V_PARAM_ID	V_SEGMENT_CODE	V_PARAM_VALUE_CODE	V_HIER_NODE_CODE	V_LEAF_CONDITION	V_HIER_NODE_DESC
53	GLPPLOADRUNIDFILTER	GLSEG802	1			

- **RunKey:** RunKey value can be fetched from the table DIM_RUN.
- The rule must be executed once, before updating the previous tables and V_COMPONENT_VALUE must be N. You must go the DIM_RUN table and fetch the corresponding Skey for the definition you like to filter with load Run ID.
- **V_PARAM_ID:** This must have a value *GLPPLOADRUNIDFILTER*.
- **V_SEGMENT_CODE:** This value must be updated with the corresponding application segment.

- **V_PARAM_VALUE_CODE:** This column must have the value of load Run ID based on which filtration happens in the target data for the selected RunSkey rule.
- Once these tables and values are updated, you can run the batch from the Operations tab and check the results. Adjustments that are created with these changes displays the load Run ID value specified in the V_PARAM_VALUE_CODE.

13.10 Duplicate Adjustments

There is an option to include the adjustments as any other normal account information into the reconciliation process.

The following are the steps you must follow to include the adjustments into the reconciliation process:

- You must make an entry in the GL_SETUP_CONFIGURATION table as follows.

V_COMPONENT_CODE	V_COMPONENT_DESC	V_COMPONENT_VALUE
IGNORE_DEFAULT_ADJUSTMENT_ENTRY	Flag to ignore default adjustment entries for further calculations	Y

- By default V_COMPONENT_VALUE value is set to 'Y'.
- Once the Reconciliation Difference process is executed, the differences between source and target are identified and captured in the table - FCT_RECONCILIATION_DIFFERENCE.

Based on Adjustment entry floor, dummy adjustment entries are generated in table - FCT_GL_ADJUSTMENT_ENTRIES with dummy account number - GL_<MAP_ID>_<Sequence> (GL_45_1).

- If V_COMPONENT_VALUE is set to 'N' then during the next execution of the same definition or any definition which results in the same granularity, the dummy account numbers are considered for calculation and differences are adjusted accordingly.

NOTE	While executing multiple rules together in one run, definitions with different dimensional granularity or similar definitions with different filters have to be carefully executed in a single run as the system randomly allocates the map ID for the order of execution and not for the order of UI rule addition.
-------------	--

13.11 VPAT-keystrokes and access keys

Voluntary Product Accessibility Template (VPAT) is a document that mentions how to access the User Interface elements. Unique keystrokes and Access keys move the focus to a specific UI element (and trigger the command). They are usually a button, link, or control that triggers the command. Access keys relocate cursor or selection focus to specific interface components. Every component on the page with definable focus is accessible by tab traversal (using Tab and Shift+Tab); however, access keys provide quick focus to frequently used components. Access keys must be unique within a page.

Oracle Financial Services Reconciliation Framework requires to use the additional below mentioned keys.

13.11.1 GL Parameters

Table 19: Vpat Target, Keys and its Action for GL Parameters

Target	Key	Action
Add Filter	Enter	Opens the panel.
Dropdown	UpArrow or DownArrow	Highlight the option item in the direction of the arrow.
Dimension cards	Enter	To select the card
	Q or q	If the focus is on a card, pressing Q will make its contents accessible using TAB
	X or x	When Q mode is enabled, press X to exit Q mode
	Tab	Navigates to next card
Button on card	Space	Activates the button
	Tab	When Q mode is activated, the tab is used to move focus to the next button

13.11.2 Target Parameters

Table 20: Vpat Target, Keys and its Action for Target Parameters

Target	Key	Action
Dropdown	UpArrow or DownArrow	Highlight the option item in the direction of the arrow.
Measures/Dimension cards/Filter cards	Enter	To select the card
	Q or q	If the focus is on a card, pressing Q will make its contents accessible using TAB
	X or x	When Q mode is enabled, press X to exit Q mode
	Tab	Navigates to next card
Buttons on card	Space	Activates the button
	Tab	When Q mode is activated, the tab is used to move focus to the next button

14 Glossary

Topics:

- [Adjustment Entry](#)
- [Adjustment Entry Floor](#)
- [Auto Approval](#)
- [Global Threshold](#)
- [Inherit to Child](#)
- [Reconciliation Difference](#)
- [Threshold](#)
- [Positive Threshold](#)
- [Negative Threshold](#)
- [Threshold Breached Type](#)

14.1 Adjustment Entry

An entry passed in the Product Processor (PP) to reconcile it with the associated GL for the amount equivalent to the difference and an entry in the Contra GL Account with the opposite sign for the same amount is an adjustment entry.

14.2 Adjustment Entry Floor

If the (GL-PP) difference is less than the Adjustment Entry Floor specified in the definition, then the calculated difference is not eligible for adjustment and entry will not be logged in Adjustment Entry table.

14.3 Auto Approval

The user gives rights to a certain party to authorize an adjustment entry.

14.4 Global Threshold

Global Threshold is applied at an execution level where all the reconciliation differences for execution are added and checked across the absolute sum of source balance.

14.5 Inherit to Child

This feature is used to find child legal entities under the hierarchy node of a Legal Entity that is selected at the definition level. If this feature is used while defining the GL Reconciliation rule, then all child nodes will participate in the reconciliation process.

14.6 Reconciliation Difference

Reconciliation difference refers to the difference in the balance between the GL and its associated PP.

14.7 Threshold

A tolerance level to be set by the user in terms of either the maximum difference allowed in any single Product Processor and its corresponding GL or the maximum number of Product Processors having differences in the GL Reconciliation.

14.8 Positive Threshold

These values are used to identify the breach types, categorized as Negative Percentage Threshold (NPT), Positive Percentage Threshold (PPT), Negative Absolute Threshold (NAT), Positive Absolute Threshold (PAT) and Not Breached (NB). The Breach Type is identified at runtime during the reconciliation process and Audit Trail entries are posted with this information.

14.9 Negative Threshold

These values are used to identify the breach types, categorized as Negative Percentage Threshold (NPT), Positive Percentage Threshold (PPT), Negative Absolute Threshold (NAT), Positive Absolute Threshold (PAT) and Not Breached (NB). The Breach Type is identified at runtime during the reconciliation process and Audit Trail entries are posted with this information.

14.10 Threshold Breached Type

The different types of threshold breaches are listed as follows:

- PAT - Positive Absolute Threshold
- NAT -Negative Absolute Threshold
- PPT - Positive Percentage Threshold
- NPT - Negative Percentage Threshold
- G- Global
- NB: Not breached

OFSAA Support

Raise a Service Request (SR) in [My Oracle Support \(MOS\)](#) for queries related to the OFSAA applications.

Send Us Your Comments

Oracle welcomes your comments and suggestions on the quality and usefulness of this publication. Your input is an important part of the information used for revision.

- Did you find any errors?
- Is the information clearly presented?
- Do you need more information? If so, where?
- Are the examples correct? Do you need more examples?
- What features did you like most about this manual?

If you find any errors or have any other suggestions for improvement, indicate the title and part number of the documentation along with the chapter/section/page number (if available) and contact the Oracle Support.

Before sending us your comments, you might like to ensure that you have the latest version of the document wherein any of your concerns have already been addressed. You can access My Oracle Support site that has all the revised/recently released documents.

