Oracle Banking Trade Finance - Oracle Banking Corporate Lending Integration User Guide

Oracle Banking Corporate Lending

Release 14.5.0.0.0

Part Number F41496-01

May 2021



Oracle Banking Trade Finance - Oracle Banking Corporate Lending Integration User Guide May 2021
Oracle Financial Services Software Limited

Oracle Park

Off Western Express Highway Goregaon (East) Mumbai, Maharashtra 400 063 India Worldwide Inquiries: Phone: +91 22 6718 3000 Fax:+91 22 6718 3001

www.oracle.com/financialservices/

Copyright © 2007, 2021, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.



# **Contents**

1.	Preface			1-1
	1.1	Introdu	uction	1-1
	1.2	Audience		1-1
	1.3	Docum	nentation Accessibility	1-1
	Organization			
				1-2
	1.6	Glossary of Icons		
2.	OBCL - OBTF Integration			2-1
	2.1	Introdu	uction	2-1
	2.2	2 Maintenances in OBCL		2-1
		2.2.1	External System Maintenance	2-1
		2.2.2	Branch Maintenance	2-2
		2.2.3	Host Parameter Maintenance	2-2
		2.2.4	Integration Parameters Maintenance	2-3
		2.2.5	External System Functions	2-5
		2.2.6	Loan Parameter Maintenance	2-10
		2.2.7	External LOV And Function ID Service Mapping	2-10
	2.3	Maintenances in OBTF		2-11
		2.3.1	External Service Maintenance	2-11
		2.3.2	Integration Parameter Maintenance	2-12
		2.3.3	External System Functions	2-12
3.	Fun	ction I	D Glossary	3-1

## 1. Preface

## 1.1 Introduction

This document is designed to help acquaint you with the integration of Oracle Banking Corporate Lending and Oracle Banking Trade Finance.

Besides this user manual, while maintaining the interface related details, you can invoke the context sensitive help available for each field. This help describes the purpose of each field within a screen. You can obtain this information by placing the cursor on the relevant field and pressing the <F1> key on the keyboard.

### 1.2 Audience

This manual is intended for the following User/User Roles:

Role	Function
Implementation Partners	Provide customization, configuration and implementation services

# 1.3 <u>Documentation Accessibility</u>

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <a href="http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc">http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc</a>.

## 1.4 Organization

This manual is organized into the following chapters:

Chapter	Description
Chapter 1	Preface gives information on the intended audience. It also lists the various chapters covered in this User Manual.
Chapter 2	This chapter helps you integrate Oracle Banking Corporate Lending and Trade product in a single instance.



# 1.5 Acronyms and Abbreviations

Abbreviation	Description
FCUBS	Oracle FLEXCUBE Universal Banking
OBCL	Oracle Banking Corporate Lending
OBTF	Oracle Banking Trade Finance
OL	Oracle Lending
System	Unless and otherwise specified, it shall always refer to Oracle FLEX- CUBE Universal Banking Solutions system
WSDL	Web Services Description Language

# 1.6 Glossary of Icons

This user manual may refer to all or some of the following icons.

Icons	Function
×	Exit
+	Add row
-	Delete row
٥	Option List



# 2. OBCL - OBTF Integration

This chapter contains the following sections:

- Section 2.1, "Introduction"
- Section 2.2, "Maintenances in OBCL"
- Section 2.3, "Maintenances in OBPM"

### 2.1 Introduction

You can integrate Oracle Banking Corporate Lending (OBCL) with trade. To integrate these two products, you need to do specific maintenances in OBTF (Oracle Banking Trade Finance) and OBCL.

## 2.2 Maintenances in OBCL

The integration between OBCL and OBTF enables the linkage to support for the below features,

- Packing Credit Loan to be liquidated on purchase of Export Bill
- On Liquidation of Import Bill Loan has to be created
- Loan has to be created as collateral of shipping guarantee
- Link to Loan

This section contains the following topics:

- Section 2.2.1, "External System Maintenance"
- Section 2.2.2, "Branch Maintenance"
- Section 2.2.3, "Host Parameter Maintenance"
- Section 2.2.4, "Integration Parameters Maintenance"
- Section 2.2.5, "External System Functions"
- Section 2.2.6, "Loan Parameter Maintenance"
- Section 2.2.7, "External LOV And Function ID Service Mapping"

### 2.2.1 <u>External System Maintenance</u>


You can invoke this screen by typing 'GWDETSYS' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

You need to define an external system for a branch that communicates with the OBCL using integration gateway.

#### Note

Ensure in OBCL you maintain an active record with all the required fields and 'External System' as "OLIFOBTF" in 'External System Maintenance' screen.





For more information external system maintenances, refer to Common Core - Gateway User Guide.

### 2.2.2 Branch Maintenance

You need to create a branch in 'Branch Core Parameter Maintenance' (STDCRBRN) screen.

You can use this screen for capturing basic branch details like branch name, branch code, branch address, weekly holiday, and so on.

You can invoke this screen by typing 'STDCRBRN' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

You can specify a host for every branch created.


### 2.2.3 Host Parameter Maintenance

You can invoke this screen by typing 'PIDHSTMT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

### Note

- In OBCL, ensure you maintain host parameter with an active record with all the required fields.
- OBTF system is for trade integration, you have to provide 'OLIFOBTF' as value for this field.





Specify the following details

### **Host Code**

Specify the host code.

### **Host Description**

Specify the brief description for the host.

### **OBTF System**

Specify the external system. For trade integration system, it is 'OLIFOBTF'


### 2.2.4 Integration Parameters Maintenance


You can invoke this screen by typing 'OLDINPRM' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



### Note

Ensure you maintain an active record with all required fields and Service Name as "OBTFIFService" in 'Integration Parameters Maintenance' screen





#### **Branch Code**

Specify as 'ALL' in case the integration parameters are common for all branches.

Or

Maintain for individual branches.

### **External System**

Specify external system as 'OLIFOBTF'.



#### **Service Name**

Specify service name as 'OBTFIFService'.

#### **Communication Channel**

Specify the communication channel as 'Web Service'.

#### **Communication Mode**

Specify the communication mode as 'ASYNC'.

#### **WS Service Name**

Specify the web service name as 'OBTFIFService'.

### **WS Endpoint URL**

Specify the WSDL of the services as 'OBTFIFService' WSDL link.

#### **WS User**

Maintain the OBTF user with access to all branches.

### 2.2.5 External System Functions

You can invoke this screen by typing 'GWDETFUN' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.




























For more information external system maintenances, refer to Common Core - Gateway User Guide

### **External System**

Specify external system as 'OLIFOBTF'.

### **Function**

Maintain for the functions

- OLGIFPMT
- OLGTRONL

### **Action**

Specify the action as

Function	Action
OLGTRONL/OLGIFPMT	NEW
	AUTHORIZE
	DELETE
	REVERSE

### **Service Name**

Specify the service name as 'FCUBSOLService'.

### **Operation Code**


Specify the operation code as



Function	Operation Code
OLGTRONL	CreateContract
	AuthorizeContractAuth
	DeleteContract
	ReverseContract
OLGIFPMT	CreateMultiLoanPayment
	AuthorizeMultiLoanPayment
	DeleteMultiLoanPayment
	ReverseMultioanPayment

### 2.2.6 Loan Parameter Maintenance

You can invoke this screen by typing 'OLDLNPRM' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



#### **Param Label**

Specify the param label as 'TRADE INTEGRATION'.

### **Param Value**

Enable the check box to specify the value as 'Y'.

### 2.2.7 External LOV And Function ID Service Mapping

You can invoke this screen by typing 'CODFNLOV' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.






### 2.3 Maintenances in OBTF

- Section 2.3.1, "External Service Maintenance"
- Section 2.3.2, "Integration Parameter Maintenance"
- Section 2.3.3, "External System Functions"

### 2.3.1 External Service Maintenance

You can invoke this screen by typing 'IFDTFEPM' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.





For more information external system maintenances, refer to Common Core - Gateway User Guide

### **External System**

Specify the external system as 'OBCL'.

#### **External User**

Specify the external User. Maintain the user in SMDUSRDF.

#### Type

Specify the type as 'SOAP Request'

### **Service Name**


Specify the Service name as 'FCUBSOLService'.

### **WS Endpoint URL**

Select the WSDL of the services as 'FCUBSOLService' WSDL link.

### 2.3.2 Integration Parameter Maintenance


You can invoke this screen by typing 'IFDINPRM' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



### 2.3.3 External System Functions

You can invoke this screen by typing 'GWDETFUN' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.





For more information external system maintenances, refer to Common Core - Gateway User Guide

### **External System**

Specify external system as 'OLIFOBTF'.

#### **Function**

Maintain for the functions 'IFGOLCON' and 'IFGOLPRT'.

#### **Action**

Specify the action as 'NEW'.

Function	Action
IFGOLCON	NEW
	UNLOCK
	DELETE
IFGOLPRT	NEW
	UNLOCK

### **Service Name**

Specify the service name as 'OBTFIFService'.

### **Operation Code**

Specify the operation code as 'CreateOLContract' for the function 'IFGOLCON' – this service will consumed by OBCL to propagate OL contracts.

Specify the operation code as 'CreateOLProduct' for the function 'IFGOLPRT' – this service will be consumed by OBCL to propagate OL Products during creation and modification.



# 3. Function ID Glossary

С		0	
CODFNLOV	2-10	OLDINPRM	2-3
		OLDLNPRM	2-10
G		OLIFOBTF	2-3
GWDETFUN	2-5, 2-12		
GWDETSYS	2-1	P	
		PIDHSTMT	2-2
1			
IFDINPRM	2-12	S	
IEDTEEDM	2-11	STDCRRRN	2_2

