

Oracle
Primavera Unifier
Adobe Sign Configuration Guide

Version 24
December 2024

Oracle Primavera Unifier Adobe Sign Configuration Guide

Copyright © 1998, 2024, Oracle and/or its affiliates.

Primary Author: Oracle Corporation

Contents

Overview 5

Adobe Sign Setup 7

Configuring OAuth..... 11

Overview

Note: The information provided in this document is subject to change.

The Adobe Sign admin must complete steps to assist in the initial setup and configuration of Adobe Sign as a delivery option within the Unifier Stage Environment (also known as the Development Environment).

Specific setup instructions for the Adobe Sign integration with Unifier Stage Environment are provided in this document and are subject to change. Contact your Unifier Production Environment administrator or Technical Support with any questions about the Adobe Sign and Unifier Stage Environment integration.

Note: Documents sent to DocuSign or Adobe Sign are done over SSL (Secured Socket Layer), which is an encryption-based Internet security protocol.

Adobe Sign Setup

This section explains how to integrate Adobe Sign into the system.

Download (On-Premises Only)


If you are using an on-premises deployment and encounter an SSL Handshake Error when you try to configure Adobe Sign for use with Unifier, download the Adobe Sign certificate from the Adobe Acrobat Sign (formerly EchoSign, eSign, and Adobe Sign) URL and import it to all the Unifier nodes and restart them.

Configure

Note: You will need a developer account.


- 1) Log on to **Adobe Sign**.
- 2) Click the **Account** tab.
- 3) In the left Navigator, select **Account Settings**, and then select **Global Settings**.
- 4) Deselect the **Limited Document Visibility** option, if it is selected.
- 5) Click **Account Setup**.
- 6) Enter your company name and hostname.

Note: Ensure that you record the hostname and URL as this information must be used for Unifier.



The screenshot shows the Adobe Sign web interface. At the top, there's a navigation bar with 'Home', 'Send', 'Manage', 'Reports', and 'Account'. Below this is a search bar and a sidebar menu. The sidebar menu includes 'Personal Preferences', 'Users', 'Groups', and 'Account Settings'. Under 'Account Settings', there's a list of options: 'Global Settings', 'Account Setup' (which is highlighted), 'Signature Preferences', 'Digital Signatures', 'Report Settings', 'Security Settings', 'Send Settings', 'Message Templates', 'Bio-Pharma Settings', and 'Signer Messaging'. The main content area is titled 'Account Setup' and contains three steps: 'Step 1: Account Information', 'Step 2: Upload Logo', and 'Step 3: Create Users'. Step 1 includes a 'Company Name' field and a checkbox for 'Set company name for all users in account'. Step 2 includes a 'Hostname' field and an 'Upload' button. Step 3 includes a link to 'Click here to manage the users in your account'.

7) Go to the **Adobe Sign API**, and select **API Applications**.



- 8) On the right side of the window, click the plus symbol (+).

API Applications 

 Search  

[View](#) / [Edit](#) | [Deactivate](#) | [Configure OAuth for Application](#)

Oracletest2	CBjCHCAABAAAMdHs843uXSikPsdBRUKQ-6zy6QJvVL	06/03/2020 04:48	ACTIVE
Oracletest1	CBjCHCAABAAAPVupMWLbeKTEb9I-rhAbikuogOBKFZ_	06/03/2020 04:48	DISABLED
oracletest	CBjCHCAABAAIggJUnfAIRsaIT9p2l8xrvlenc8Bvkj	06/03/2020 04:47	DISABLED

- 9) In the **Create** block, enter values for the **Name** and **Display Name** fields.

- 10) Select **Partner**, and click **Save**.

Create 

Provide a name for your application to issue a set of credentials for use with Adobe Sign's API

Name:

Display Name:

Domain:

☐ CUSTOMER (This application will only have access to data within your account)

☒ PARTNER (This application will have access to any authorized Adobe Sign account)

- 11) Proceed to configure OAuth.

Configuring OAuth

In the **Configure OAuth** block, enter the Unifier redirect URL in the **Redirect URL** field box.

Ensure the following fields are enabled:

- ▶ **user_read**
- ▶ **user_write**
- ▶ **user_login**
- ▶ **agreement_read**
- ▶ **agreement_write**
- ▶ **agreement_send**

To configure OAuth:

- 1) Sign in to Unifier.
- 2) Go to the **Company Workspace** tab and switch to **Admin** mode.
- 3) In the left Navigator, select the company name.
- 4) From the toolbar, click **Open** to open the **Edit Company** window.
- 5) Click the **E-signatures** tab.
- 6) From the **Default E-Signature Type** drop-down, select **Adobe Sign**.
- 7) Click to select, or check, the **Adobe Sign** block.
- 8) Enter values in the **URL**, **Client ID**, and **Client ID** fields.
- 9) Click **Generate Token**.
- 10) Enter the Adobe Sign login credentials on the pop-up window.
- 11) Click **Test Connection** and select **Active**.
- 12) Click **OK**.