

Open Development Tool Installation
Oracle FLEXCUBE Universal Banking

Release 14.8.1.0.0

Part No. G41973-01

[October] [2025]



Table of Contents

- 1. OPEN DEVELOPMENT TOOL INSTALLATION 1-1
 - 1.1 INTRODUCTION 1-1
 - 1.2 CREATING PROPERTY FILE FOR OPEN DEVELOPMENT TOOL 1-1
- 2. SETTING UP DATABASE FOR OPEN DEVELOPMENT TOOL..... 2-1
- 3. BUILDING WAR FOR OPEN DEVELOPMENT TOOL 3-1

1. Open Development Tool Installation


1.1 Introduction

This document explains about the creation of property file and war for ODT (Open Development Tool) and setting up database for ODT installation.

1.2 Creating Property File for Open Development Tool

To create property file for ODT, follow the steps given below:

1. Run 'FCUBSInstaller.bat' batch file in windows or FCUBSInstaller.sh in Linux to launch Oracle FLEXCUBE Universal Banking Solution Installer.



```
C:\windows\system32\cmd.exe
checking whether Installer is running.....
creating a new flag file.....
sucessfully created the flag File.

initializing the errorLevel to 0

checking Java Home.....
Please input Java path [Example: D:\Program Files\Java\jdk1.6.0_17]
@@@@@JAVAHOME NOT DEFINED@@@@@
Enter JAVA HOME Directory:C:/Program Files/Java/jdk1.8.0_144
JAVA HOME has been set
initializing the errorLevel to 0

checking Java Home.....
Java Home Path has been set sucessfully.

The system cannot find the path specified.
ojdbc0.jar
@@@@ORACLE HOME NOT DEFINED@@@
Enter Oracle Home Directory:D:/12Client/app/client/siramakr/product/12.1.0/client_1
Oracle Home set
ojdbc7.jar
Oracle Home set succesfully
clearing the compiled files.....
clearing the jar file.
clearing the compiled classes files.
ojdbc7.jar
Jar to be copied from D:/12Client/app/client/siramakr/product/12.1.0/client_1\jdbc\lib\ojdbc7.jar
copying jars into the library...
1 file(s) copied.

checking logs Folder.....
--Current Folder--
--avast--
this InstallationShipment "SOFT"
inside Checking APPSERVER HOME.....
appserverhome
```

Need to provide the following details:

JAVA HOME PATH

Provide the JAVA 8 home path.


ORACLE HOME PATH

Provide the Oracle Client Path.

APPSERVER PATH

Provide the Application Server Path.

2. After providing these details, INSTALLER-GUI is generated. After that follow the below details.



3. Enter the following details.

JDK Path

Maintain Home folder path of JDK1.8

Oracle Home

Maintain home folder path of Oracle Client or Database.

Select one of the radio buttons

- a) Property File creation
 - b) Utilities
4. Based on the selection, Next screen will be shown. Click Property File creation for the current case. Click 'Next'. The following screen is displayed.

Oracle FLEXCUBE Universal Installer 12.5.0.0.0

Oracle Banking Installer

Select one of the Components

Load Existing Property File

☒ INFRA
 ☐ Scheduler
 ☐ Gateway
 ☐ Switch Interface Installation

Select Oracle Product Processors

☐ Oracle FLEXCUBE Universal Banking
☐ Oracle FLEXCUBE Enterprise Limits and Collateral Management (CO-DEPLOY)
☐ Oracle Banking Payments
☐ Oracle Banking Corporate Lending ☒ **Open Development Tool**
☐ Oracle Banking Treasury ☐ Oracle FLEXCUBE Universal Banking for JAPAN
☐ Oracle Banking Trade Finance

Select Plugins to be Installed

☐ Branch Load Existing Branch Property File

Host Address 10.10.10.10 1010 ☐ Origination ☐ Scheduler Standalone

☐ Reports 10.10.10.10 1010 ☐ OFTW ☐ SIANET Adapter

☐ DMS 10.10.10.10 1010 ☐ Insulation ☐ ELCM Adapter required

5. Select 'Open Development Tool' component for installation.
6. Click 'Next'. The following screen is displayed.

Oracle FLEXCUBE Universal Installer 12.5.0.0.0

Oracle Banking Installer

Welcome To Oracle FLEXCUBE

ODT Property file creation

Operating System: SYMMETRIC K...:

Application Server: Logger Path:

DataBase Server: PROVIDER_URL:

ODT JNDI: War File Name:

Source Path:

Ear Destination Path:

Name	Value
Username	installer
Password	*****
Service Name	testdb
IP Address	10.10.10.10
Port	1521
TNS Connect Descriptor	testdb.world

☐ DB Compilation Required

- Specify the following details.

Operating System

Specify the operating system in which you are installing Oracle FLEXCUBE.

Application Server

Specify the application server on which you are installing Oracle FLEXCUBE.

ODT JNDI

Specify the JNDI for the ODT.

SYMMETRIC KEY

Specify the symmetric key as "oraclefinancials".

Logger Path

Specify the path where the logs have to be written.

Provider_URL

Specify the provider URL.

WAR File Name

Specify the war file Name.

Source Directory

Specify the source directory location. The source directory should have the 'rad_ddl.sql' and other corresponding packages. You can use the directory icon to browse to the source directory location.

Destination Directory

Specify the destination directory. You can use the directory icon to browse to the source directory location.

8. Specify the following ODT schema details.

User Name

Specify the user name to access the schema.

Password

Specify the schema password for the above user name.

Service Name

Specify service name of database.

TNS Connect Descriptor

Specify a valid connect string that contains the details for database connectivity.

IP Address

Specify the IP address of the system where the database schema is installed.


Port

Specify the port number.

DB Complication Required


Check this box to indicate execute ODT scripts in provided ODT schema. ODT schema details will be appended to env.properties file.

9. Once you have specified the details, click 'Test Connection' button to test the database schema connection.




10. The above message is displayed if the connection is established successfully.

11. Click save button to save the env.properties file.



12. Browse to the folder to save file and click on save button. The following image will display.



13. The property file named odt.properties will be available in the custom location .Path will be written as ODT_PROPERTIES_PATH IN env.properties file .Please copy this file to SOFT/Logs folder and proceed for war building.

2. Setting up Database for Open Development Tool

To set up database for Open Development Tool (ODT), follow the steps given below:

Environment Setup Steps:

Below are the sequences of steps to be followed during Environment Setup:

1. Property File Creation:

Follow CREATING PROPERTY FILE FOR OPEN DEVELOPMENT TOOL steps to create property file.

2. Copy environment property file:

The env.properties file which got generated in \INSTALLER\SOFT\GUI\logs path need to be manually copied to \INSTALLER\SOFT\logs path.

Backend Setup using Silent Installer

Backend Setup has to be done using Silent Installer. DDL Compilation, Object Compilation and Static Data load will be taken care as part of Backend Setup.

Run ODTDBCompileRun.bat in windows (ODTDBCompileRun.sh in Linux).

DDL Compilation, Object Compilation and Static Data load will be done. Check for the Invalid Count and make sure that the Invalid count is '0'.

3. Building WAR for Open Development Tool

- Run ODTWarRun.bat in windows (ODTWarRun.sh in Linux).
- Check the war file is generated in EAR destination folder path provided in env.properties file.



Open Development Tool Installation
[October] [2025]
Version 14.8.1.0.0

Oracle Financial Services Software Limited
Oracle Park
Off Western Express Highway
Goregaon (East)
Mumbai, Maharashtra 400 063
India

Worldwide Inquiries:
Phone: +91 22 6718 3000
Fax: +91 22 6718 3001
www.oracle.com/financialservices/

Copyright © 2007, 2025, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.