

## **Oracle® Transportation Management**

Integrating Oracle Transportation Management with Oracle E-Business Suite

Release 12.2

**Part No. E48827-08**

October 2025

Oracle Transportation Management Integrating Oracle Transportation Management with Oracle E-Business Suite, Release 12.2

Part No. E48827-08

Copyright © 2004, 2025, Oracle and/or its affiliates.

Primary Author: Gajjala Prashanti

Contributing Author: Ankuj Varshney, Sandeep Uppal

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, MySQL, and NetSuite are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

#### Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

#### Access to Oracle Support

Oracle customer access to and use of Oracle support services will be pursuant to the terms and conditions specified in their Oracle order for the applicable services.



---

# Contents

## Send Us Your Comments

## Preface

## 1 Introduction

Overview of Oracle Transportation Management Integration with Oracle E-Business Suite .....	1-1
Oracle Transportation Management and Oracle E-Business Suite Requirements.....	1-1
Overview of Oracle Business Process Execution Language.....	1-4

## 2 Oracle Order Management

Overview of Oracle Transportation Management Integration with Oracle Order Management .....	2-1
Rating and Routing at Order Booking.....	2-1
Implementing Oracle Transportation Management with Oracle Order Management.....	2-1

## 3 Oracle Shipping Execution

Overview of Oracle Transportation Management Integration with Oracle Shipping Execution .....	3-1
XML Messages.....	3-8
Functional Changes with Oracle Transportation Management Installed.....	3-9
Delivery Splitting.....	3-9
Delivery Splitting Rules.....	3-10
Delivery Line Splitting Rules.....	3-10
Packing.....	3-11
Shipping Transactions Window Actions.....	3-11
Delivery Interface Statuses.....	3-18

Planned Shipment Interface Message Corrections.....	3-19
Viewing Oracle Transportation Applied Freight Costs.....	3-24
Carrier Manifesting.....	3-25
Third Party Warehousing.....	3-25
Oracle Warehouse Management.....	3-26
Automated Shipping (Oracle Shipping Execution).....	3-27
<b>Implementing Oracle Transportation Management with Oracle Shipping Execution.....</b>	<b>3-27</b>
System Configuration and Setup Changes (Oracle Transportation Management) .....	3-27
Setting Up an External System.....	3-28
Setting Up Profile Options.....	3-29
Shipping Configuration and Setup Changes (Oracle E-Business Suite).....	3-33
Setting Up Profile Options and Parameters.....	3-33
Changes to the Shipping Windows.....	3-37
Shipping Exceptions.....	3-39
Concurrent Programs.....	3-42

## 4 Oracle Payables

<b>Overview of Oracle Transportation Management Integration with Oracle Payables.....</b>	<b>4-1</b>
Send Voucher Interface.....	4-1
<b>Implementing Oracle Transportation Management with Oracle Payables.....</b>	<b>4-2</b>

## 5 Oracle Purchasing

<b>Overview of Oracle Purchasing Integration with Oracle Transportation Management.....</b>	<b>5-1</b>
<b>Functional Changes with Oracle Transportation Management Installed.....</b>	<b>5-2</b>
Responsibility for Inbound Freight.....	5-2
Impact of Purchase Order Status Changes on Oracle Transportation Management.....	5-3
<b>Implementing Oracle Transportation Management with Oracle Purchasing.....</b>	<b>5-3</b>
System Configuration and Setup Changes (Oracle Transportation Management).....	5-3
Setting Up Profile Options.....	5-3
Oracle Purchasing Configuration and Setup Changes (Oracle E-Business Suite).....	5-4
Mapping Oracle Purchasing to Oracle Transportation Management.....	5-4
Configuring the BPEL Process Manager.....	5-5
XML Translation via XSL in BPEL.....	5-6
Web Services.....	5-7

## 6 Oracle Warehouse Management

<b>Overview of Oracle Transportation Management Integration With Oracle Warehouse Management .....</b>	<b>6-1</b>
<b>Setting Up Dock Door Synchronization with Oracle Transportation Management.....</b>	<b>6-2</b>
<b>Defining Dock Doors in Oracle Warehouse Management.....</b>	<b>6-4</b>

Synchronizing Dock Doors with Oracle Transportation Management.....	6-4
Synchronizing Dock Appointments with Oracle Transportation Management.....	6-5
Creating the Transportation Plan and Managing Appointments in Oracle Transportation Management.....	6-7

## 7 Oracle Advanced Planning and Scheduling

<b>Overview of Oracle Transportation Management Integration With Oracle Advanced Planning and Scheduling.....</b>	<b>7-1</b>
Understanding Arrival Time Updates.....	7-2
<b>Implementing Oracle Transportation Management with Oracle Advanced Planning and Scheduling.....</b>	<b>7-3</b>
System Configuration and Setup Changes (Oracle Transportation Management).....	7-4
Transportation Management Exceptions Exception Group .....	7-5
Setting Up the BPEL Process.....	7-7
Setting Up External System and Web Service in Oracle Transportation Management .....	7-8
Setting Up an Automatic Agent in Oracle Transportation Management.....	7-9
<b>Setting Up Profile Options in Oracle Advanced Supply Chain Planning .....</b>	<b>7-10</b>

## A XML Mapping

<b>Oracle Transportation Management to Oracle E-Business Suite XML Mapping.....</b>	<b>A-1</b>
Oracle Advanced Planning and Scheduling XML Mapping.....	A-1
Oracle Order Management XML Mapping.....	A-2
Oracle Payables XML Mapping.....	A-8
APIInvoice Interface XML Mapping.....	A-8
Oracle Purchasing XML Mapping.....	A-10
Purchasing Fields to Order Base XML Mapping.....	A-10
Oracle Shipping Execution XML Mapping.....	A-35
Location XML Transaction - Carrier.....	A-35
Release XML Transaction - Deliveries.....	A-35
Release XML Transaction - Delivery Lines (Release.ReleaseLine).....	A-41
Release XML Transaction - Ship Unit (Release.ShipUnit).....	A-43
Release XML Transaction - Packaged Item (Release.ReleaseLine.PackagedItemRef) .....	A-44
Planned Shipment XML Transaction - Trip.....	A-45
Planned Shipment XML Transaction - Trip Stop.....	A-51
PlannedShipment XML Transaction - Delivery Leg.....	A-56
ActualShipment XML Transaction.....	A-57
Shipping-Transportation Carrier Synchronization XML Mapping.....	A-64
Shipping-Transportation Outbound Interface XML Mapping.....	A-73

## Index

---

# Send Us Your Comments

## **Oracle Transportation Management Integrating Oracle Transportation Management with Oracle E-Business Suite, Release 12.2**

**Part No. E48827-08**

Oracle welcomes customers' comments and suggestions on the quality and usefulness of this document. Your feedback is important, and helps us to best meet your needs as a user of our products. For example:

- Are the implementation steps correct and complete?
- Did you understand the context of the procedures?
- Did you find any errors in the information?
- Does the structure of the information help you with your tasks?
- Do you need different information or graphics? If so, where, and in what format?
- Are the examples correct? Do you need more examples?

If you find any errors or have any other suggestions for improvement, then please tell us your name, the name of the company who has licensed our products, the title and part number of the documentation and the chapter, section, and page number (if available).

Note: Before sending us your comments, you might like to check that you have the latest version of the document and if any concerns are already addressed. To do this, access the new Oracle E-Business Suite Release Online Documentation CD available on My Oracle Support and [www.oracle.com](http://www.oracle.com). It contains the most current Documentation Library plus all documents revised or released recently.

Send your comments to us using the electronic mail address: [appsdoc\\_us@oracle.com](mailto:appsdoc_us@oracle.com)

Please give your name, address, electronic mail address, and telephone number (optional).

If you need assistance with Oracle software, then please contact your support representative or Oracle Support Services.

If you require training or instruction in using Oracle software, then please contact your Oracle local office and inquire about our Oracle University offerings. A list of Oracle offices is available on our Web site at [www.oracle.com](http://www.oracle.com).



---

# Preface

## Intended Audience

Welcome to Release 12.2 of the *Oracle Transportation Management Integrating Oracle Transportation Management with Oracle E-Business Suite*.

See Related Information Sources on page xii for more Oracle E-Business Suite product information.

## Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

## Access to Oracle Support

Oracle customer access to and use of Oracle support services will be pursuant to the terms and conditions specified in their Oracle order for the applicable services.

## Structure

- 1 Introduction
- 2 Oracle Order Management
- 3 Oracle Shipping Execution
- 4 Oracle Payables
- 5 Oracle Purchasing
- 6 Oracle Warehouse Management
- 7 Oracle Advanced Planning and Scheduling
- A XML Mapping

## Related Information Sources

### Integration Repository

The Oracle Integration Repository is a compilation of information about the service endpoints exposed by the Oracle E-Business Suite of applications. It provides a complete catalog of Oracle E-Business Suite's business service interfaces. The tool lets users easily discover and deploy the appropriate business service interface for integration with any system, application, or business partner.

The Oracle Integration Repository is shipped as part of the Oracle E-Business Suite. As your instance is patched, the repository is automatically updated with content appropriate for the precise revisions of interfaces in your environment.

### Do Not Use Database Tools to Modify Oracle E-Business Suite Data

Oracle **STRONGLY RECOMMENDS** that you never use SQL\*Plus, Oracle Data Browser, database triggers, or any other tool to modify Oracle E-Business Suite data unless otherwise instructed.

Oracle provides powerful tools you can use to create, store, change, retrieve, and maintain information in an Oracle database. But if you use Oracle tools such as SQL\*Plus to modify Oracle E-Business Suite data, you risk destroying the integrity of your data and you lose the ability to audit changes to your data.

Because Oracle E-Business Suite tables are interrelated, any change you make using an Oracle E-Business Suite form can update many tables at once. But when you modify Oracle E-Business Suite data using anything other than Oracle E-Business Suite, you may change a row in one table without making corresponding changes in related tables. If your tables get out of synchronization with each other, you risk retrieving erroneous information and you risk unpredictable results throughout Oracle E-Business Suite.

When you use Oracle E-Business Suite to modify your data, Oracle E-Business Suite automatically checks that your changes are valid. Oracle E-Business Suite also keeps track of who changes information. If you enter information into database tables using database tools, you may store invalid information. You also lose the ability to track who has changed your information because SQL\*Plus and other database tools do not keep a record of changes.

---

## Introduction

### Overview of Oracle Transportation Management Integration with Oracle E-Business Suite

Oracle Transportation Management integrates with Oracle E-Business Suite to enable transportation features and functionality by adding to existing Oracle E-Business Suite products, including Oracle Order Management, Oracle Shipping Execution, Oracle Payables, Oracle Warehouse Management, and Oracle Purchasing.

Oracle Transportation Management combines transportation planning and execution with freight payment, inbound freight logistics, and freight rating and routing.

Oracle Transportation Management adds the following features and enhancements to Oracle E-Business Suite:

- Carrier selection and tender
- Freight rating and routing
- Actual ship quantities update and re-rate
- Freight payment, freight payment audit, and approval
- Visible in-transit statuses
- Inbound carrier selection
- Inbound in-transit statuses

### Oracle Transportation Management and Oracle E-Business Suite Requirements

To use Oracle Transportation Management, you must have the following Oracle

Applications installed:

- Oracle Order Management
- Oracle Shipping Execution
- Oracle Payables
- Oracle Purchasing


Other Oracle applications, such as Oracle Warehouse Management, can further enhance your supply chain management processes.

See:

- *Oracle Purchasing User's Guide*
- *Oracle Shipping Execution User's Guide*
- *Oracle Order Management User's Guide*
- *Oracle Order Management Implementation Manual*
- *Oracle Payables User's Guide*
- *Oracle E-Business Suite User's Guide*
- *Oracle BPEL Process Manager Quick Start Guide*


**Note:** The integration of Oracle E-Business Suite and Oracle Transportation Management replaces Oracle Transportation Execution and Oracle Transportation Planning. Once Oracle Transportation Management is enabled, you cannot use Oracle Transportation Execution and Oracle Transportation Planning.

This figure shows the integration of Oracle Transportation Management with Oracle E-Business Suite Applications as well as the services used to transact the data between Oracle Transportation Management and Oracle E-Business Suite Applications:




This figure shows the integration of Oracle Transportation Management with Oracle


Payables, including audit/pay/approve and invoice paid:




This figure shows the integration of Oracle Transportation Management with Oracle Order Management, including rate and route flow and estimation:



This figure shows the integration of Oracle Transportation Management with Oracle Shipping Execution, including trip creation, ship confirm, order interface, and inventory interface:



This figure shows the integration of Oracle Transportation Management with Oracle Purchasing, including PO creation and PO close:



## Overview of Oracle Business Process Execution Language

The Oracle BPEL (Business Process Execution Language) processes are delivered through My Oracle Support patches. Patch application does not deploy the .jar files into the BPEL middle tier. You must manually deploy the BPEL processes.

For more information, see My Oracle Support for the note: *Oracle Transportation Management Integration with Oracle E-Business Suite Post-Update Steps*.



---

# Oracle Order Management

## Overview of Oracle Transportation Management Integration with Oracle Order Management

Oracle Transportation Management integrates with Oracle Order Management to enable transportation rating and routing at the time of order entry. Oracle Order Management also provides outbound data to Oracle Transportation Management that Oracle Transportation Management uses to plan shipments.

### Rating and Routing at Order Booking

The implementation of Oracle Transportation Management enables you to offer an estimate of the shipping rate and route at the time of order entry. After you have entered the order line, you select the appropriate action as needed.

Oracle Transportation Management leverages the following Oracle Order Management actions, which are enhanced by the introduction of Oracle Transportation Management:

- Choose Ship Method: Enables you to select the ship method, costs, and transit times
- Get Ship Method: Returns the ship method
- Get Ship Method and Rates: Returns the ship method and rate
- Get Freight Rates: Returns the freight cost for the ship method returned

Each action returns the appropriate ship method and rate for the given order line.

## Implementing Oracle Transportation Management with Oracle Order Management

You must define the following profile options to enable the Oracle Order Management to Oracle Transportation Management integration:

- OTM: Domain Name
- OTM: Domain User
- OTM: Integration Enabled
- OTM: Proxy Port
- OTM: Proxy Server
- OTM: Servlet URL

For information on Oracle Order Management XML mapping, see Oracle Order Management XML Mapping, page A-2

---

## Oracle Shipping Execution

### Overview of Oracle Transportation Management Integration with Oracle Shipping Execution

The integration of Oracle Transportation Management with Oracle Shipping Execution includes reference data synchronization, release transactions, planned shipment transactions, and actual shipment transactions. All of these transactions enable Oracle E-Business Suite to send and receive information to and from Oracle Transportation Management.


The following figures display the integration of Oracle Transportation Management with Oracle Shipping Execution, including trip creation, ship confirm, order interface, and inventory interface. You can integrate Oracle Shipping Execution with Oracle Transportation Management using either delivery based integration or batch based integration.



be activated in Oracle Transportation Management to trigger the PlannedShipment interface to an external system (BPEL) and sets its status in Oracle Transportation Management to SENT TO EBS\_SENT. Default automation agents are delivered inactive in the E-Business Suite (EBS) domain and must be reviewed and copied into the operational domain. An external system must also be defined for each outbound flow from Oracle Transportation Management. (Step by step instructions for this setup are available in OTM > Help > How To > EBS to OTM). This interface is used to transmit the shipments from Oracle Transportation Management to Oracle Shipping Execution to create the corresponding trips and trip stops and to assign the deliveries to them.

5. If the delivery is updated with changes that are relevant to transportation planning decisions (for example, change in delivery details weight), then the delivery is marked as Update Required.
6. The next run of the Shipping-Transportation Outbound Interface concurrent request with the appropriate interface action parameter (Update or All Except ActualShipment) selects the update-required deliveries and sends them to Oracle Transportation Management using the OTM XML release transaction. Order Releases are updated in Oracle Transportation Management based on these transactions.
7. Update to order releases might provoke changes in the routing decision and therefore change in the shipments configuration. Based on Oracle Transportation Management Automation agents, these changes trigger the PlannedShipment interface to update the corresponding trips in Oracle Shipping Execution.
8. Eventually, once deliveries of a trip are ship confirmed and all pick up stops of this trip are closed in Shipping Execution, the last pick up stop is marked as ActualShipment Required.
9. The next run of the Shipping-Transportation Outbound Interface concurrent request with the appropriate interface action parameter (ActualShipment) selects the ActualShipment Required stops and sends their corresponding details to Oracle Transportation Management using the OTM XML ActualShipment transaction. Shipments and order releases are updated in Oracle Transportation Management based on these transactions (actual shipped quantities, vehicle information, and so on).

**Transaction Cycle Between Oracle Shipping Execution and Oracle Transportation Management (Batch Based Integration)**



The figure displays the following steps to illustrate how deliveries are marked for internal processing:

1. Delivery line is created. When a delivery line is created it is marked as Include for Planning,
2. Delivery creation: During batch integration, deliveries can be created before the batch is created or deliveries can be created by the Planned Shipment Interface concurrent program after the batch is created and has been sent to Oracle Transportation Management.
3. Batch creation: When a batch with contents is created by the Create Batches for Transportation Planning concurrent program, it is marked as Creation Required.
4. Shipping-Transportation Outbound Interface concurrent request runs with the appropriate interface action parameter (Create or All Except Actual Shipment) and the interface basis parameter of batch. The concurrent request selects the delivery lines associated to the creation-required batch and sends them to Oracle Transportation Management using the OTM XML release transaction. Order

Releases are updated in Oracle Transportation Management based on these transactions.

5. Transportation planning activities then take place in Oracle Transportation Management for the new order releases, including carrier selection, rating, tendering, and so on, which results in the creation of shipments (equivalent to trips in Oracle Shipping Execution) to which the order releases are assigned.
6. After the shipment is created, and the tender is accepted, an automation agent can be activated in Oracle Transportation Management to trigger the PlannedShipment interface to an external system (BPEL) and sets its status in Oracle Transportation Management to SENT TO EBS\_SENT. Default automation agents are delivered inactive in the E-Business Suite (EBS) domain and must be reviewed and copied into the operational domain. An external system must also be defined for each outbound flow from Oracle Transportation Management. (Step by step instructions for this setup are available in OTM > Help > How To > EBS to OTM). This interface is used to transmit the shipments from Oracle Transportation Management to Oracle Shipping Execution to create the corresponding trips and trip stops and to assign or create the deliveries to them.
7. If the delivery is updated with changes that are relevant to transportation planning decisions (for example, change in delivery details weight), then the batch is marked as Update Required.
8. The next run of the Shipping-Transportation Outbound Interface concurrent request with the appropriate interface action parameter (Update or All Except ActualShipment) selects the update-required batches and sends them to Oracle Transportation Management using the OTM XML release transaction. Order Releases are updated in Oracle Transportation Management based on these transactions.
9. Update to order releases might provoke changes in the routing decision and therefore change in the shipments configuration. Based on Oracle Transportation Management Automation agents, these changes trigger the PlannedShipment interface to update the corresponding trips and update the delivery if required in Oracle Shipping Execution.
10. Eventually, once deliveries of a trip are ship confirmed and all pick up stops of this trip are closed in Shipping Execution, the last pick up stop is marked as ActualShipment Required.
11. The next run of the Shipping-Transportation Outbound Interface concurrent request with the appropriate interface action parameter (ActualShipment) selects the ActualShipment Required stops and sends their corresponding details to Oracle Transportation Management using the OTM XML ActualShipment transaction. Shipments and order releases are updated in Oracle Transportation Management based on these transactions (actual shipped quantities, vehicle information, and so

on).

### **Ignore for Planning Trips and Deliveries**

To allow "out of the cycle" expedited shipments, you create a delivery and set the status to Ignore for Planning, or set the status of an existing delivery to Ignore for Planning (for example, by unassigning the delivery from the Oracle Transportation Management issued trip).

Deliveries set to Ignore for Planning are not sent to Oracle Transportation Management for planning activities.

You can then create Ignore for Planning trips, assign deliveries to them, and ship confirm. After the pickup stops are closed, the deliveries are marked as Actual Shipment Required and are sent to Oracle Transportation Management through the next run of the Shipping-Transportation Outbound Interface concurrent program.

### **Visibility on Interface Activities Through Shipping Exceptions**

For each interface operations (required or executed) shipping exceptions are logged against the delivery or the batch. For example, when a delivery is created in Shipping Execution, WSH\_OTM\_DEL\_CREATE\_REQ is logged, indicating that creation is required in Oracle Transportation Management. After the Shipping-Transportation Outbound Interface concurrent process has processed this delivery, the WSH\_OTM\_DEL\_AWAITING\_TRIP is logged against the delivery, indicating that the transaction has been transmitted and the delivery is now awaiting a planned trip from Oracle Transportation Management; however, interface processes are driven by delivery level and stops level interface flags, which are not visible to the user. Equivalent batch exception messages are logged when performing the same process above using the batch basis integration with Oracle Transportation Management.

### **Changes for Allowed Actions and Updates to Shipping Entities**

- Trips and trips stops: With the integration Oracle Transportation Management can be considered the "master system" for Include for Planning trips. Therefore, certain actions or updates to trips are not allowed in Shipping Execution when they are marked as Include for Planning (issued from Oracle Transportation Management). For example, it is not possible to add new stops or change their sequence.
- Deliveries and delivery details: Conversely, Shipping Execution is the "master system" for deliveries in delivery based integration. In the case of batch based integration, deliveries may get created as part of the Planned Shipment interface. Therefore, the majority of actions and updates are allowed. Certain actions have been disabled (for example Select Carrier and Get freight Costs) or function differently (assigning a delivery line with non-null weights to delivery marks the delivery as Update Required) or are prevented on Include for Planning deliveries, such as Assign to Trip.

## Delivery Splitting

Oracle Transportation Management includes algorithms that split large deliveries across multiple parallel shipments or assign multiple equipment to the same trip. To avoid this, the integration avoids sending large deliveries to Oracle Transportation Management. Instead, integration:

1. Splits delivery lines with a net weight exceeding a defined net weight limit, ensuring that once packed, the delivery does not exceed the gross weight limit. This split is performed at delivery line import from Order Management or other sources.
2. Splits deliveries that exceed a defined gross weight limit. This split is performed during the Shipping-Transportation Outbound interface concurrent request on deliveries sent to the interface for creation or update.

Both weight limits are part of the shipping parameter setup.

**Note:** Delivery splitting functionality is not supported when integrating with Oracle Transportation Managements using the batch based integration functionality (WSH: Delivery Based OTM Integration profile option is set to No).

## Enabling Organizations

Oracle Transportation Management integration can be enabled at the organization level by selecting the Transportation enabled check box on the Shipping Parameters window. Note the following behavior differences:

- Enabled organizations:
  - Delivery details are created with the Include for Planning status by default. Integration with Oracle Transportation Management functions as described in this documentation.
  - Enabled Organizations can be selected in the Shipping-Transportation Outbound Interface concurrent request for transaction processing (if no organization is selected, then transactions for all enabled organizations are transmitted to Oracle Transportation Management).
- Disabled organizations:
  - Delivery details are created as Ignore for Planning for planning.
  - Disabled organizations cannot be selected in the Shipping-Transportation Outbound Interface concurrent request for any interface actions.
  - Delivery details, deliveries, and trips cannot be changed to Include for

Planning.

## Reference Data Integration

Certain data must be synchronized between the two systems using one of the following three methods:

- Manual synchronization: This data must be set and synchronized manually between the two systems:
  - Freight terms, FOB codes
  - UOMs: Weight UOM, Dimensions UOM, Distance UOM, Volume UOM, Quantity UOM, Time UOM
  - Currency codes
  - Service levels, Transport modes
  - Vehicle items
  - LPN types
  - Country codes

The ID entered in Oracle Transportation Management and code entered in Oracle Shipping Execution must match exactly.

- Carrier and carrier sites: The carrier must be primarily set in Oracle E-Business Suite. A stand alone interface enables the interface to create the carriers in Oracle Transportation Management.
- Ship from ship to location customers; organizations; and items: No separate synchronization is needed for this information. Information needed by Oracle Transportation Management for these entities is sent along with the operational transactions (XML Release and ActualShipment).

**Note:** You must define item weights and volumes as well as item container weights, volumes, and dimensions in the Oracle E-Business Suite. The accuracy of Oracle Transportation Management planning is decreased if these attributes are not properly defined.

## XML Messages

The following XML messages are used to pass order information to and from Oracle Transportation Management:

- Location transaction: Location XML transaction is used to send carrier information to Oracle Transportation Management. This is achieved by running the Shipping-Transportation Carriers Synchronization.
- Release transaction: Release XML transaction is used to send delivery information or batch information to Oracle Transportation Management by running the Shipping-Transportation Outbound Interface. After the interface has run, the XML can be viewed in the BPEL Process Manager.
- PlannedShipment transaction: PlannedShipment XML is used to send confirmation to Oracle Shipping Execution when a delivery or group of deliveries has been planned by Oracle Transportation Management and is ready to ship. This transaction is used to create trips, stops, and delivery legs in Shipping Execution based on the shipments created in Transportation Management. After the interface has run, the incoming PlannedShipment XML message is viewable in the BPEL Process Manager.
- ActualShipment transaction: ActualShipment XML is used to send ship confirmation information to Oracle Transportation Management when the pickup trip-stops of a trip are closed. The Shipping-Transportation Outbound Interface delivers the information. After you run the interface, you can view the XML in the BPEL Process Manager.

## Related Topics

Oracle Shipping Execution XML Mapping, page A-35

# Functional Changes with Oracle Transportation Management Installed

## Delivery Splitting

Delivery splitting occurs after a delivery has been created in Oracle Shipping Execution and before the delivery information is sent to Oracle Transportation Management, whenever a delivery gross weight exceeds the Gross Weight Limit.

**Note:** Delivery splitting functionality is not supported when integrating with Oracle Transportation Managements using the batch based integration functionality (WSH: Delivery Based OTM Integration profile option is set to No).

Delivery Splitting does not occur when delivery lines are packed, even if the packed line exceeds the weight limit. You must manually unpack and split these lines before sending to Oracle Transportation Management.

***Delivery Splitting Example Max Gross Weight limit is set at 20 LBS:***

---

<b>Delivery Name (Before Split)</b>	<b>Weight (Before Split)</b>
DL4451	35 LBS
<b>Delivery Name (After Split)</b>	<b>Weight (After Split)</b>
DL4451	20
(DL4460)	15

---

Two shipping parameters (located on the Delivery tab) are used to determine when a delivery or delivery line must be split to accommodate a carrier's capacity. See Shipping Parameters, page 3-37

### **Delivery Splitting Rules**

Only Include for Planning deliveries are considered for splitting. LPNs are not split, instead, LPNs are added to child deliveries after the split takes place. Splitting cannot take place if:

- The delivery is assigned to a trip
- The delivery has Released to Warehouse or Staged lines
- The delivery's weights have been manually overridden
- The split cannot be performed without splitting an LPN
- The split cannot be performed without splitting delivery details
- Delivery is Content Firm

**Note:** Delivery splitting functionality is not supported when integrating with Oracle Transportation Managements using the batch based integration functionality (WSH: Delivery Based OTM Integration profile option is set to No).

### **Delivery Line Splitting Rules**

Delivery lines are split when the net weight of a line exceeds the Net Weight field on the Shipping Parameters window. The line is split to be equal to the Net Weight limit. If

the split fails (due to an indivisible quantity), then the WSH\_OTM\_DET\_SPLIT\_FAILED exception is logged.

**Note:** The Gross Weight must exceed the Net Weight, otherwise the split will fail.

**Note:** Delivery line splitting functionality is not supported when integrating with Oracle Transportation Managements using the batch based integration functionality (WSH: Delivery Based OTM Integration profile option is set to No).

## Packing

Any packing operation involving non-null weights in an enabled organization requires an update to Oracle Transportation Management and changes the delivery status or batch status to Update Required (UR). Overpick and underpick, in a pick-pack-ship flow, also requires an updated plan from Oracle Transportation Management, changing the status to UR.

## Shipping Transactions Window Actions

When Oracle Transportation Management is implemented, some actions available on the Shipping Transactions window function differently than they do without Oracle Transportation Management installed for Include for Planning deliveries and trips. Certain delivery actions, however, are disabled, prevented, or will function differently.

All Include for Planning deliveries that have been interfaced to Oracle Transportation Management, in the case of delivery based integration, are controlled by Oracle E-Business Suite; you can update them until ship confirmation.

All Include for Planning trips are controlled by Oracle Transportation Management until ship confirmation is run. All delivery assignments to trips are performed in Oracle Transportation Management; therefore, restrictions to what modifications you can make to trips within Oracle E-Business Suite will occur. These restrictions include the following:

- You cannot delete or cancel Include for Planning trips
- You cannot remove or add from/in trip stops Include for Planning trips
- You cannot change Trip stop sequences in Include for Planning trips
- Trips cannot be Firm or Firm Routing.
- All trips created in Oracle E-Business Suite are Ignore for Planning

- You cannot change Ignore for Planning trips to Include for Planning
- You cannot change Include for Planning trips to Ignore for Planning

The following tables describe (by trip, trip stop, delivery, and delivery details) how the Actions function with Oracle Transportation Management implemented. (OTM = Oracle Transportation Management. EBS = Oracle E-Business Suite).

**Note:** The following tables include: Allowed (controlled by exception), which indicates that the ability to ship confirm is driven by the setup of OTM exceptions. For example, for delivery based integration, a delivery assigned to an OTM Trip Not Current might have the WSH\_OTM\_UPDATE\_REQ or WSH\_OTM\_DEL\_AWAIT\_TRIP exception logged, therefore ship confirm is possible if the setup is Information Only or Warning for these exceptions. For batch based integration, a delivery assigned to an OTM Trip Not Current might have the WSH\_OTM\_BATCH\_UPDATE\_REQ or WSH\_OTM\_BATCH\_AWAIT\_TRIP exception logged, therefore ship confirm is possible if the setup is Information Only or Warning for these exceptions.

***Include for Planning Trips Changed Actions***

Action	Delivery Created Not Assigned to Trip (Sent to OTM or Not)	Delivery Assigned to Trip, Not Current	Delivery Assigned to Trip, Current
Firm Routing	NA	Not Allowed	Not Allowed
Firm Routing and Contents	NA	Not Allowed	Not Allowed
Ignore for Planning	NA	Not Allowed	Not Allowed
Ship Confirm	NA	Allowed (controlled by exception)	Allowed (controlled by exception)
Unfirm	NA	Not Allowed	Not Allowed

***Include for Planning Trips Allowed for Maintenance Attributes***

---

**Attribute**

Trip Name

Seal Code

Routing instruction, operator

Vehicle information (organization code, item name, prefix, vehicle number)

Flex Fields

---

***Include for Planning Trip Stops Changed Actions***

---

Action	Delivery Created Not Assigned to Trip (Sent to OTM or Not)	Delivery Assigned to Trip, Not Current	Delivery Assigned to Trip, Current
Delete	NA	Not Allowed	Not Allowed
Insert New Stops	NA	Not Allowed	Not Allowed

---

***Include for Planning Trip Stops Allowed for Maintenance Attributes***

---

**Attribute**

Weight / Volume

Actual arrival / departure date

Departure fill %

Departure seal code

Unloading start end time

---

---

Flex fields

---

***Include for Planning Deliveries Changed Actions***

---

<b>Action</b>	<b>Delivery Created Not Assigned to Trip (Sent to OTM or Not)</b>	<b>Delivery Assigned to Non-Current Trip (Waiting for OTM Re-Planning)</b>	<b>Delivery Assigned to Current Trip (Trip from OTM Up to Date)</b>
Assign to Trip	Not Allowed	Not Allowed	Not Allowed
Auto-create Trip	Not Allowed	Not Allowed	Not Allowed
Cancel Ship Method	Disabled  (Not available in role definition when OTM is installed).	Disabled	Disabled
Get Freight Costs	Disabled  (Not available in role definition when OTM is installed).	Disabled	Disabled
Ignore for Planning	Allowed	Allowed	Delivery will be Ignore for Planning if unassigned from the OTM trip.
Pick Release Form	Allowed	Allowed	Allowed
Pick and Ship	Allowed (controlled by exception)	Allowed (controlled by exception)	Allowed

---

---

Pick, Pack, and Ship	Allowed (controlled by exception, delivery will be ignored for planning in the process)	Allowed (controlled by exception)	Allowed  Packing will update tms_interface_flag of the delivery. Based on the exception setting, the delivery may or may not be ship confirmed.
Select Carrier	Disabled (Action is not available in role definition when OTM is installed).	Disabled	Disabled
Send Outbound Message	Allowed for Third Party Warehouse. Disabled for Carrier Manifesting	Allowed for Third Party Warehouse. Disabled for Carrier Manifesting	Allowed for Third Party Warehouse. Disabled for Carrier Manifesting
Ship Confirm	Allowed (controlled by exception, delivery will be ignored for planning in the process)	Allowed (controlled by exception)	Allowed (controlled by exception)
Unassign from Trip	NA	Allowed. Will set the delivery to Ignore for Planning	Allowed. Will set the delivery to Ignore for Planning
UPS Address Validation	Disabled.  (Action is not available in role definition when OTM is installed).	Disabled	Disabled
UPS Rate and Service	Disabled.  (Action is not available in role definition when OTM is installed).	Disabled	Disabled

---

---

UPS Time in Transit	Disabled.  (Action is not available in role definition when OTM is installed).	Disabled	Disabled
---------------------	--	----------	----------

---

***Include for Planning Deliveries Allowed for Maintenance Attributes***

---

<b>Attribute</b>	<b>Allowed / Disallowed</b>
Delivery name	Allowed
Freight term code	Allowed
Weights / volume	Allowed
Reason of transport	Allowed
Description	Allowed
Ship method	Allowed if delivery is not assigned to a trip. Disabled if assigned to a trip.
Carrier ID	Allowed if delivery is not assigned to a trip. Disabled if assigned to a trip.
Service level	Allowed if delivery is not assigned to a trip. Disabled if assigned to a trip.
Mode of transport	Allowed
Number of LPNs	Allowed
Earliest / latest pickup dates	Allowed
Earliest / latest drop off dates	Allowed
Flex field update	Allowed

---

***Include for Planning Delivery Lines (Details) Changed Actions***

<b>Action</b>	<b>Delivery Detail Not Assigned to Delivery</b>	<b>Delivery Created Not Assigned to Trip (Sent to OTM or Not)</b>	<b>Delivery Assigned to Trip, Not Current</b>	<b>Delivery Assigned to Trip, Current</b>
Auto-create Trip	Not Allowed	Not Allowed	Not Allowed	Not Allowed
Pick and Ship	Allowed  (Delivery details will be changed to Ignore for Planning).	Not Allowed	Not Allowed	Not Allowed
Pick, Pack, and Ship	Allowed  (Delivery details will be changed to Ignore for Planning).	Not Allowed	Not Allowed	Not Allowed
UPS Address Validation	Disabled  (Action is not available in role definition when OTM is installed).	Disabled	Disabled	Disabled
UPS Rate and Service	Disabled  (Action is not available in role definition when OTM is installed).	Disabled	Disabled	Disabled
UPS Time in Transit	Disabled  (Action is not available in role definition when OTM is installed).	Disabled	Disabled	Disabled

### ***Include for Planning Delivery Details Allowed for Maintenance Attributes***

---

<b>Attribute</b>	<b>Allowed / Disallowed</b>
Requested Quantity	Allowed from Order Management
Cancelled Quantity	Allowed from Order Management
Shipped Quantity	Allowed
Secondary Quantities	Allowed from Order Management
Lot Number	Allowed
Serial Number / to Serial Number	Allowed
Weights and Volumes	Allowed
Requested / Schedule Ship Date	Allowed from Order Management
Customer PO	Allowed from Order Management

---

### **Related Topics**

Shipping Exceptions, page 3-39

### **Delivery Interface Statuses**

The following interface statuses are used by Oracle Shipping Execution to track the required actions for Oracle Transportation Management integration. These interface statuses are internal and not visible through the user interface.

#### **Delivery Interface Statuses**

- **CREATION\_REQUIRED (CR):** Delivery must be created in Oracle Transportation Management
- **UPDATE\_REQUIRED (UR):** Delivery has been updated and must be sent to Oracle Transportation Management
- **DELETE\_REQUIRED (DR):** Delivery has been emptied or has been ignored for planning (no delivery lines or delivery lines with empty LPNs only) and must be deleted in Oracle Transportation Management

- **AWAITING\_ANSWER (AW):** Create or Update has taken place on a delivery and an answer is expected from Oracle Transportation Management
- **ANSWER\_RECEIVED (AR):** An answer has been received from Oracle Transportation Management
- **NOT\_TO\_BE\_SENT (NS):** Delivery is either Ignore for Planning or has no delivery lines (or has delivery lines empty LPNs)
- **COMPLETED (CMP):** Delivery has been ship confirmed and pick up trip stops are closed
- **CREATE\_IN\_PROCESS (CP):** Creation is in process
- **UPDATE\_IN\_PROCESS (UP):** Update is in process
- **DELETE\_IN\_PROCESS (DP):** Deletion is in process

#### **Trip Stops Interface Statuses**

- **ACTUAL\_SHIP\_REQUIRED (ASR):** Last pickup trip stop is set to this status after it is closed.

The TMS interface flag of the last pick up stop is set to ASR when the stop is closed as long as the following conditions are met:

- Trip does not include any deliveries that belong to third party warehousing
- Trip does not include any consolidated deliveries
- Trip includes at least one delivery that belongs to an Oracle Transportation Management enabled organization
- **COMPLETED (CMP):** Last pickup trip stop is set to this status once the ActualShipment transaction has been sent to Oracle Transportation Management
- **Shipment in Process (ASP):** The trip and stop is in the process of being sent to Oracle Transportation Management.
- **NOT TO BE SENT (NS):** Used when a trip stop is not to be sent to Oracle Transportation Management.

## **Planned Shipment Interface Message Corrections**

Using the Shipment Message Corrections window in Oracle Shipping Execution you can view interface messages and transactions and correct interface errors. In addition, any Oracle Transportation Management interface error corrections can be viewed and corrected using the Shipment Message Corrections window. The integration of Oracle Transportation Management Planned Shipment included changes to the Shipment

Message Corrections window. The Trip tab includes the following new fields:

- Freight Terms
- Vehicle Item Name
- Mode of Transport
- Service Level

The Trip Stops tab includes the new field Time Zone Code.

**To View and Correct Interface Errors:**

1. Navigate to the Shipment Message Corrections window.  
The Find Shipment Message window appears.
2. Enter the following information:

<b>Field</b>	<b>Description</b>
Creation Date Range (From and To)	(Optional) Select the creation date range for the shipping interface messages.
Organization	(Optional) Select the organization associated to the shipping interface messages.
Source Type	<i>Shipping</i> appears by default and cannot be changed.

Field	Description
Action Code	<p>(Optional) Select an action code. Action codes are:</p> <ul style="list-style-type: none"> <li>• 94X_INBOUND</li> <li>• TMS_RELEASE</li> <li>• 94X_STANDALONE</li> <li>• YARD_DOCUMENT</li> </ul> <p>After you select YARD_DOCUMENT, the Yard Document Name field becomes available.</p> <p>To search for Oracle Transportation Management related messages, select TMS_RELEASE.</p>
Entity Name	<p>(Optional) Select the entity associated with the shipping interface messages. When searching for Oracle Transportation Management interface messages, select an entity name associated with an entity type of delivery or transportation sub batch.</p>
Yard Document Name	<p>Select a yard document name.</p> <p>This field is only available if you have selected YARD_DOCUMENT as the Action Code.</p>
Transactions check box	<p>(Optional) Select this check box to view the shipping interface transactions.</p>
Transaction Type	<p>(Optional) Select the transaction type.</p>
Transaction Number	<p>(Optional) Select the transaction number.</p>
Trading Partner	<p>(Optional) Select the trading partner associated with the transaction.</p>

**Find Shipment Messages window**

Creation Date Range  -

Organization

Source Type **Shipping**

Action Code **TMS\_RELEASE**

Entity Name 183-1

Yard Document Name

Transactions

Transaction Type

Transaction Number

Trading Partner

Clear Cancel Find

3. Click Find.

The system displays a message asking if you want to find all of the records in this folder?

4. Click Yes.

### Shipment Message Corrections window

The screenshot shows the 'Shipment Message Corrections' window with three tabs: 'Delivery/Transportation Sub Batch', 'Trip', and 'Messages History'. The 'Delivery/Transportation Sub Batch' tab is active, displaying a table with the following data:

Interface ID	Entity ID	Entity Name	Entity Ty	Pl	Stat	Pickup Date	Pickup Loc ID
12003	183	183-1	Transport	Y	OP		207

Below this table are 'Lines' and 'Legs' tabs. The 'Lines' tab is active, displaying a table with the following data:

Delivery Detail Int	Delivery Detail ID	Source Code	Source Header ID	Source Line ID	Customer ID
11003	4001244	OE	605442	746775	1006
11004	4001245	OE	605443	746776	1006

At the bottom of the window, there are three buttons: 'Freight', 'Error', and 'Process'.

The Shipment Messages Correction window appears displaying all of the information related to the search criteria that you entered.

5. View the delivery or transportation sub batch information errors:
  1. Select the Delivery/Transportation Sub Batch tab.
  2. Select the Interface ID.
  3. Click Error.
  
6. Process the delivery or transportation sub batch information errors:
  1. Select the Delivery/Transportation Sub Batch tab.
  2. Select the Interface ID.
  3. Click Process.
  
7. View the trip interface errors:

1. Select the Trip tab.
  2. Select the Trip Interface ID.
  3. Click Error.
- 
8. Process the trip interface errors:
    1. Select the Trip tab.
    2. Select the Trip Interface ID.
    3. Click Process.
- 
9. View the message history:
    1. Select the Messages History tab.
    2. Select the Transaction ID.
    3. Click Error.
- 
10. Process the message history:
    1. Select the Messages History tab.
    2. Select the Transaction ID.
    3. Click Process.

## Viewing Oracle Transportation Applied Freight Costs

Oracle Transportation Execution applied freight costs are viewed on the Freight Costs window within Oracle Shipping Execution. (From the Shipping Transactions window, find your delivery and invoke the Action Assign Freight Costs). After the PlannedShipment message has been received, the freight costs are viewable at the delivery level as OTM Freight Cost.

Applied freight costs are allocated to order lines through the use of the Order Management interface.


When integrating with Oracle Transportation Management using the batch basis, Oracle Transportation Management creates freight costs at the order release shipment level. In Oracle E-Business Suite there can be multiple deliveries for a order release, so the freight costs from the order release level are prorated to the delivery detail level using the basis (weight/volume/quantity). If all three of these attributes (weight, volume, and quantity) are available on the delivery details interface, then the system

gives precedence to weight, then volume, then quantity. If only one attribute is available then the system uses that attribute.

## Carrier Manifesting

When Oracle Transportation Management is integrated, all Oracle E-Business Suite enabled carrier manifest features are disabled. All carrier manifest deliveries are sent to Oracle Transportation Management as non-carrier manifesting deliveries. Oracle Transportation Management manages the carrier manifest system outside of the Oracle E-Business Suite.

### *Carrier Manifesting with Oracle Transportation Management*



## Third Party Warehousing

Third party warehousing functionality remains the same in Oracle E-Business Suite with or without Oracle Transportation Management integrated. Oracle Transportation Execution is not required to use Third Party Warehousing.

**Note:** Deliveries created by the third party warehouse instance, when Oracle E-Business Suite is used to manage the third party warehouse

are communicated to Oracle Transportation Management for planning.

See *Oracle Transportation Execution User's Guide*.

## Oracle Warehouse Management

Oracle Warehouse Management supports several methods to ship, also called mobile ship confirm, the deliveries using radio frequency (RF) devices. The methods include the following:

- Quick Ship
- LPN Ship
- Dock Door Ship
- Direct Ship

If the delivery lines and deliveries are created with Include for Planning, but are not yet sent to Oracle Transportation Management for planning, then Oracle Warehouse Management will allow ship confirmation using any of the above methods after changing the deliveries and delivery lines to Ignore for Planning.

If the associated delivery is Include for Planning and the delivery is not yet planned, then either a Warning (proceed and complete the transaction) or Error (cannot proceed) message is issued depending on the severity of the TMS\_Flag status for the delivery or batch. The following delivery or batch based exceptions determine the severity:

- WSH\_OTM\_DEL\_CREATE\_REQ
- WSH\_OTM\_BATCH\_CREATE\_REQ
- WSH\_OTM\_DEL\_UPDATE\_REQ
- WSH\_OTM\_BATCH\_UPDATE\_REQ
- WSH\_OTM\_DEL\_AWAIT\_TRIP
- WSH\_OTM\_BATCH\_AWAIT\_TRIP

**Note:** For example, a delivery assigned to an OTM Trip Not Current might have the WSH\_OTM\_UPDATE\_REQ or the WSH\_OTM\_DEL\_AWAIT\_TRIP exception logged, therefore ship confirm is possible if the setup is Information Only or Warning for these exceptions. Equivalent batch exception messages are logged when performing the same process using the batch basis integration with

## Oracle Transportation Management.

For more information, see Shipping Exceptions, page 3-39.

### Automated Shipping (Oracle Shipping Execution)

Oracle Shipping Execution enables automated shipping flows to speed the various shipping processes. The automated flows are available through actions on the Shipping Transactions window. See the *Oracle Shipping Execution User's Guide* for information on One Step Shipping.

The automated flows are enabled with the integration of Oracle Transportation Management; however, in some cases the functionality of the flows changes with the integration of Oracle Transportation Management, including the following:

---

Action	Delivery – Ignore for Planning	Delivery not on a Trip Waiting for OTM Planning	Delivery on a Trip Waiting for OTM Re-Planning	Delivery on a Trip Planned by OTM	Delivery Details
Auto Ship Confirm	Allowed	Allowed (controlled by exception, delivery will be ignored for planning in the process)	Allowed (controlled by exception)	Allowed (controlled by exception)	NA
Process Deliveries SRS	Allowed and creates Ignore for Planning Trip	Not Allowed	Not Allowed	Not Allowed	Allowed

---

## Implementing Oracle Transportation Management with Oracle Shipping Execution

### System Configuration and Setup Changes (Oracle Transportation Management)

The following section describes the system configuration and setup changes required in Oracle Transportation Management.

## Setting Up an External System

An external system is required for each flow coming out of Oracle Transportation Management, for example, the Voucher Interface. The following steps outline how to set up an external system in Oracle Transportation Management.

### To create external systems in Oracle Transportation Management to receive the outbound messages (Planned Shipment and Voucher)

1. Retrieve the WSDL for the BPEL flow and save the WSDL locally to your hard drive. Note that the endpoint location will be used as the Service Endpoint when setting up the external system.
2. Create the external system in Oracle Transportation Management with Web Services defined.
  1. Enter the External System ID.
  2. Navigate to the Web Services region and click N to create a new web service.
  3. Within the Web Service Manager page, click N to create a new WSDL document.
  4. Click Document Detail.
  5. Within the ID field, enter an ID, for example WSHRECEIVEPSHIPMENTFROMOTM or OTMVOUCHERTOORACLEAPINVOICE.
  6. Within the Storage field, select Text.
  7. Click Upload to upload the WSDL file you retrieved from the BPEL server. Mime Type is automatically populated after the WSDL file is uploaded.
  8. Click Finished.
  9. Click Service Details.
  10. Within the Web Service Details page, click Service Details.
  11. Enter a Service ID, for example WSHRECEIVEPSHIPMENTFROMOTM or OTMVOUCHERTOORACLEAPINVOICE.
  12. Review the Operations section. The process operation should, by default, be designated as For Integration.

At least one operation must have For Integration enabled.

3. Enter the Service Endpoint and click Save and Finished.

The Service Endpoint is the URL from the BPEL WSDL endpoint location.

4. On the External System, enable the Trans Ack Expected check box.

Enabling the Trans Ack Expected check box indicates that a TransmissionAck XML is expected to be returned by the BPEL flow. WshReceivePShipmentFromOtm and OtmVoucherToOracleApInvoice both return the TransmissionAck.

5. Enable the Use Ack Status check box (for Voucher External System only).

Enabling the Use Ack Status check box indicates that the status in the TransmissionAck should be used as the status of the transmission, for example PROCESSED or ERROR.

6. Click Finished to save your work.

**Note:** When sending transmissions to these external systems, you must use the Notify Type of SERVICE.

## Setting Up Profile Options

During implementation, you set a value for each user profile option to specify how Oracle Transportation Management controls access to and processes data. Generally, the system administrator sets and updates profile values. See *Oracle E-Business Suite Setup Guide*.

The following table indicates whether you (the user) can view or update profile options and at which System Administrator level that profile option can be updated. The System Administrator level includes User, Responsibility, Application, and Site levels. Profile options are considered either optional or required:

- **Optional:** An optional profile option indicates that a value is not mandatory. You can either provide a value or leave the default value as is.
- **Required:** A required profile option indicates that a value is mandatory.

The following terms are used in the table to identify if you can view or update profile option information:

- **Updatable:** You can update the profile option.
- **View Only:** You can view the profile option value but you cannot change it.
- **No Update or View:** You cannot view or change the profile option value.

Profile Option	User	Resp	App	Site	Required?	Default Value
OTM: Integration Enabled	--	--	--	Updatable	Yes	Neither
OTM: Domain Name	--	--	--	Updatable	Yes	Blank/Empty
OTM: Domain User	--	--	--	Updatable	Yes	Blank/Empty
OTM: Proxy Server	--	--	--	Updatable	Yes	Blank/Empty
OTM: Proxy Port	--	--	--	Updatable	Yes	Blank/Empty
OTM: Servlet URI	--	--	--	Updatable	Yes	Blank/Empty
OTM: Corporation Country Code	--	--	--	Updatable	Yes	Blank/Empty

Profile Option	Used By
OTM: Integration Enabled	All outbound (Sales Order Integration, Outbound Deliveries Integration, and Ref Data) and Purchasing Integration
OTM: Domain Name	All outbound (Sales Order Integration, Outbound Deliveries Integration, and Ref Data) and Purchasing Integration

<b>Profile Option</b>	<b>Used By</b>
OTM: Domain User	All outbound (Sales Order Integration, Outbound Deliveries Integration, and Ref Data) and Purchasing Integration
OTM: Domain Password	This profile option is not used. The password for the Oracle Transportation Management domain user name is in the FND Vault.
OTM: Proxy Server	All outbound (Sales Order Integration, Outbound Deliveries Integration, and Ref Data)
OTM: Proxy Port	All outbound (Sales Order Integration, Outbound Deliveries Integration, and Ref Data)
OTM: Servlet URI	Outbound (Sales Order Integration)
OTM: Corporation Country Code	Outbound (Ref Data)

#### **OTM: Corporation Country Code**

This profile is used by Oracle Shipping Execution for customer and carrier synchronization. The code in this profile identifies the default country code of the headquarters' carriers and customers.

#### **OTM: Domain Name**

Oracle Shipping Execution and Oracle Purchasing use this profile. It is communicated on the outbound messages from Oracle E-Business Suite Applications and used by Oracle Transportation Management to identify an instance of Oracle E-Business Suite. The profile must be a valid domain name defined in Oracle Transportation Management.

#### **OTM: Domain User**

Oracle Shipping Execution and Oracle Purchasing use this profile. It must be a valid user in Oracle Transportation Management and is not case sensitive.

#### **OTM: Domain Password**

The OTM domain password is now stored in FND Vault rather than in a profile option. During OTM integration, if the OTM domain password is not present in FND Vault, it is obtained from this FND profile option and moved to FND Vault.

To set the OTM domain password in FND Vault:

1. Connect to the apps schema.
2. Run the SQL script patch/115/sql/wshotmfndvlt.sql to place the OTM password in FND Vault. For example, @/u01/R122\_EBS/fs2/EBSapps/appl/wsh/12.0.0/patch/115/sql/wshotmfndvlt.sql
3. Enter an OTM password for the user that is specified in the profile option OTM: Domain User.

**Important:** You can also use these steps to change the password.

To view the OTM domain password in FND Vault, execute the following code:

```
SET SERVEROUTPUT ON;
DECLARE OTM_PWD VARCHAR2(200);
BEGIN OTM_PWD:=FND_VAULT.GET('OTM_INTEGRATION','OTM_PASSWORD');
DBMS_OUTPUT.PUT_LINE('Password from FND Vault : '||OTM_PWD);
END;
/
```

### **OTM: Integration Enabled**

Oracle Shipping Execution and Oracle Purchasing use this profile to determine which components of the Oracle Transportation Management integration are enabled.

Values are:

- Neither Order Management Nor Purchasing: Oracle Transportation Management integration with Order Management and Purchasing is not enabled.
- Order Management Only: Only the sales order outbound flow is integrated with Oracle Transportation Management; inbound purchasing flow is not.
- Purchasing Only: Only the purchase order flow is integrated with Oracle Transportation Management; outbound sales orders are not.
- Both Order Management and Purchasing: Both Order Management and Purchasing transactions integrations are enabled with Oracle Transportation Management.

### **OTM: Proxy Port**

This profile is used to store the port number for the HTTP proxy server on Oracle E-Business Suite instance. Oracle Shipping Execution uses this profile to make a connection to an Oracle Transportation Management instance.

### OTM: Proxy Server

This profile is used to store the HTTP proxy server on the Oracle E-Business Suite instance. Oracle Shipping Execution uses this profile to make a connection to an Oracle Transportation Management instance.

### OTM: Servlet URI

This profile is used to store Oracle Transportation Management Servlet URI for the Oracle E-Business Suite instance to connect to Oracle Transportation Management. This is used for freight estimation at sales order integration only.

## Shipping Configuration and Setup Changes (Oracle E-Business Suite)

### Setting Up Profile Options and Parameters

During implementation, set a value for each user profile option to specify how Oracle Shipping Execution controls access to and processes data. Generally, the system administrator sets and updates profile values. See *Oracle E-Business Suite Setup Guide*.

The following table indicates whether you (the user) can view or update profile options and at which System Administrator level that profile option can be updated. The System Administrator level includes User, Responsibility, Application, and Site levels. Profile options are considered either optional or required:

- **Optional:** An optional profile option indicates that a value is not mandatory. You can either provide a value or leave the default value as is.
- **Required:** A required profile option indicates that a value is mandatory.

**Note:** If you are using a multi-organization structure, your system administrator must change the OM Item Validation Organization profile option to be visible and updatable at the responsibility level. This change enables Shipping Execution to apply the default tax code and revenue account information correctly. See *Oracle E-Business Suite Multiple Organizations Implementation Manual*.

The following terms are used in the table to identify if you can view or update profile option information:

- **Updatable:** You can update the profile option
- **View Only:** You can view the profile option value but you cannot change it
- **No Update or View:** You cannot view or change the profile option value

<b>Profile Option</b>	<b>User</b>	<b>Resp</b>	<b>App</b>	<b>Site</b>	<b>Required?</b>	<b>Default Value</b>
WSH: BPEL Domain Name	--	--	--	Updatable	Yes	Blank/Empty
WSH: BPEL Webservice URI for OTM	--	--	--	Updatable	Yes	Blank/Empty
WSH: Currency Conversion Type for OTM	--	--	--	Updateable	No	Corporate
WSH: Default Shipping User for OTM	--	--	--	Updatable	Yes	Blank/Empty
WSH: Default Shipping Responsibility for OTM	--	--	--	Updatable	Yes	Blank/Empty
WSH: Delivery Based OTM Integration	--	--	--	Updatable	No	Blank/Empty

Profile Option	User	Resp	App	Site	Required?	Default Value
WSH: Enable Multi-Leg Shipment for Delivery-Based OTM Integration	--	--	--	Updatable	No	Blank/Empty
Server Timezone	--	--	--	Updatable	Yes	Blank/Empty
Client Timezone	Updatable	--	--	--	Yes	Blank/Empty
Enable Timezone Conversions	--	--	--	Updatable	Yes	Blank Empty

Profile Option	Used By
WSH: BPEL Domain Name	All outbound from WSH to OTM integration
WSH: BPEL Webservice URI for OTM	All outbound (Sales Order Integration, Outbound Deliveries Integration, and Ref Data)
WSH: Currency Conversion Type for OTM	Planned Shipment Request to process the inbound requests coming from OTM and in RIQ
WSH: Default Shipping User for OTM	Only for inbound from OTM to WSH integration
WSH: Default Shipping Responsibility for OTM	Only for inbound from OTM to WSH integration

<b>Profile Option</b>	<b>Used By</b>
WSH: Delivery Based OTM Integration	All inbound and outbound between WSH and OTM
WSH: Enable Multi-Leg Shipment for Delivery-Based OTM Integration	All inbound and outbound between WSH and OTM
Server Timezone	Only for inbound from OTM to WSH integration
Client Timezone	All
Enable Timezone Conversions	All

#### **WSH: BPEL Domain Name**

This profile option stores the BPEL domain information, which is used by the outbound and carrier synchronization concurrent programs to enable the system to invoke corresponding programs. The default value is Default.

#### **WSH: BPEL Web Service URI for OTM**

This profile option is used by freight estimation at sales order, outbound orders, and reference data integration. It stores the HTTP location of the BPEL Process Manager and tells the concurrent request where the BPEL outbound processes are located.

#### **WSH: Currency Conversion Type for OTM**

This profile is used for currency conversion type in RIQ and Planned Shipment. The profile provides a list of values containing all conversion types defined in the system.

#### **WSH: Default Shipping User for OTM**

This profile determines the default user that receives the inbound messages from Oracle Transportation Management. The BPEL process sends the inbound message to the Oracle E-Business Suite user identified by this profile. This profile option is required and there is no default value.

#### **WSH: Default Shipping Responsibility for OTM**

This profile determines the user responsibility required to receive inbound messages from Oracle Transportation Management. The BPEL process sends the inbound message to the default Oracle E-Business Suite user with the responsibility defined by this profile. This profile option is required and there is no default value.

**WSH: Delivery Based OTM Integration**

This profile option determines the basis for the integration between Oracle Shipping Execution and Oracle Transportation Management (OTM). If the profile is set to Yes or Null, then the integration is delivery based. If set to No, then the integration is batch based. You create the batches that are sent to OTM by running the Create Batches for Transportation Planning concurrent program in Oracle Shipping Execution. The default for the profile option is Null (means Yes).

**WSH: Enable Multi-Leg Shipment for Delivery-Based OTM Integration**

This profile option enables adding multiple trips to a delivery for delivery-based integration between Oracle Shipping Execution and Oracle Transportation Management. This profile is set at the site level and the default value is blank. If the profile option is set to Yes, then the integration supports the multi-leg feature for delivery-based integration. If the profile is set to No, then the integration supports the multi-leg feature for batch-based integration.

**Server Timezone**

This profile determines the time zone in which the server has been set to run, or the standard corporate time zone. This profile should be set at the site level and should not be changed once set, as existing data will not be updated.

**Client Timezone ID**

This profile specifies the user preferred time zone. This profile is used when your corporate time zone differs from your local time zone. This profile is set at the user level and is available from the self service Preferences window and from the forms-based Profiles window.

**Enable Timezone Conversions**

This profile enables the automatic conversion of all date and time fields to the preferred user time zone. If set to No, then the date and time fields default to the corporate time zone.

This profile option must be set when integrating your applications with Oracle Transportation Management. If it is not set, then the BPEL process will fail in Purchasing because of the lack of time zone conversions.

**Changes to the Shipping Windows**

The following changes occur to the shipping windows when Oracle Transportation Management is installed.

**Shipping Parameters Window**

When Oracle Transportation Management is installed, the following changes occur in the Shipping Parameters window:

- The Transportation tab is disabled.
- The Delivery tab includes the Transportation region and the Delivery Weight Limits region. These regions contain the following fields:

- Enabled

The Enabled check box determines whether Oracle Transportation Management integration is enabled for a given organization. This parameter can be enabled only if Oracle Transportation Management is installed and the profile option: OTM: Integration Enabled is set to Order Management Only or Both Order Management and Purchasing.

**Warning:** After you enable an organization, it cannot be disabled.

- Delivery Detail Max Net Weight

The Max Net Weight is compared to the weight of a delivery line to ensure that the delivery line weight is not greater than the Max Net Weight, and that splitting is done at delivery line import. This field is not mandatory, and the default value is null; however, if a Max Gross Weight is entered, then the Max Net Weight becomes a required field (and vice versa). The Max Net Weight must be less than or equal to the Max Gross Weight.

- Delivery Max Gross Weight

This weight is compared to the total weight of the delivery lines within a delivery to ensure that it is not greater than the Max Gross Weight. This field is not mandatory and the default value is null; however, if a Max Net Weight is entered, then the Max Gross Weight becomes a required field (and vice versa). The Max Gross Weight must be greater than or equal to the Max Net Weight.

- UOM

This field is automatically populated from the Weight Class UOM code field from the Global Parameters window, if specified. This field cannot be updated in the Shipping Parameters window.

**Note:** The Weight Class UOM is not a mandatory field in the Global Parameters window. Therefore, you have to enter it manually in the Global Parameters window.

### Global Shipping Parameters Window

When Oracle Transportation Management is installed, the following changes occur in the Global Parameters window:

- The Transportation tab (used only with the installation of Oracle Transportation Execution) is completely disabled.
- The Delivery Date Calculation Method field is moved from the Transportation tab to the General tab.

The Defer Planned Shipment Interface parameter on this window gives you the option to defer to the Planned Shipment Interface concurrent request. If you select this parameter, the concurrent request must be run manually or you can schedule it. If you do not select this parameter, the system runs the concurrent request automatically every time the planned shipment is received from Oracle Transportation Management.

### Shipping Transactions Window

When Oracle Transportation Management is installed, the following changes occur in the Shipping Transactions window:

- Transportation Batch field and Transportation Sub Batch field can be added as search criteria to the Query Manager window when searching for shipping transactions associated to Deliveries, Lines, LPNs, and Lines and LPNs. The Transportation Batch field and Transportation Sub Batch field are folder-enabled fields.
- Transportation Batch column and Transportation Sub Batch column can be added to the Delivery tab of the Shipping Transactions window for deliveries. The Transportation Batch field and Transportation Sub Batch field are folder-enabled fields.
- Transportation Batch column and Transportation Sub Batch column can be added to the Lines/LPN tab of the Shipping Transactions window for lines and LPNs. The Transportation Batch field and Transportation Sub Batch field are folder-enabled fields.

### Shipping Exceptions

During the shipping and transportation of goods, unforeseen shipping exceptions can occur that conflict with the actual requirements of the shipper, transportation carrier, or customer. Tracking exceptions can also be helpful to identify and correct defects in the business process. Seeded exceptions are logged automatically against delivery lines, LPNs, batches, deliveries, and trip stops when specific events occur. The following exceptions are seeded with the integration of Oracle Transportation Management:

**Note:** Oracle Transportation Management exceptions cannot be logged manually.

- **Oracle Transportation Management Interface Exceptions:**

---

Interface Exception Name	Description
WSH_OTM_DEL_D ELETE_REQ	This exception is a delivery level exception that is logged when a Delete transaction must be sent to Oracle Transportation Management. Seeded value is Information Only, recommended setting is Information Only.
WSH_OTM_BATC H_DELETE_REQ	This exception is a batch level exception that is logged when a Delete transaction must be sent to Oracle Transportation Management. Seeded value is Information Only, recommended setting is Information Only.
WSH_OTM_DEL_C REATE_REQ	This exception is a delivery level exception that is logged when a Create transaction must be sent to Oracle Transportation Management. Seeded value is Warning, recommended setting is Error, Warning, or Information Only.
WSH_OTM_BATC H_CREATE_REQ	This exception is a batch level exception that is logged when a Create transaction must be sent to Oracle Transportation Management. Seeded value is Warning, recommended setting is Error, Warning, or Information Only.
WSH_OTM_DEL_U PDATE_REQ	This exception is a delivery level exception that is logged when a Update transaction must be sent to Oracle Transportation Management. Seeded value is Warning, recommended setting is Error, Warning, or Information Only.
WSH_OTM_BATC H_UPDATE_REQ	This exception is a batch level exception that is logged when a Update transaction must be sent to Oracle Transportation Management. Seeded value is Warning, recommended setting is Error, Warning, or Information Only.
WSH_OTM_DEL_A WAIT_TRIP	This exception is a delivery level exception that is logged when a Create or Update transaction has been sent to Oracle Transportation Management or trip configuration has changed, and the system is now awaiting for trip updates. Seeded value is Warning, recommended setting is Error, Warning, or Information Only.
WSH_OTM_BATC H_AWAIT_TRIP	This exception is a batch level exception that is logged when a Create or Update transaction has been sent to Oracle Transportation Management or trip configuration has changed for the batch, and the system is now awaiting for trip updates. Seeded value is Warning, recommended setting is Error, Warning, or Information Only.

---

---

WSH_OTM_DEL_D ELETED	This exception is logged when the delivery is set to Ignore for Planning or the delivery has no associated delivery lines and has been deleted in Oracle Transportation Management. Seeded value is Information Only as is the recommended setting.
WSH_OTM_BATC H_DELETED	This exception is logged when the batch has no associated delivery lines and has been deleted in Oracle Transportation Management. Seeded value is Information Only as is the recommended setting.
WSH_OTM_UOM_ SETUP	This exception is logged when the trip fails the ActualShipment interface because the Shipping Parameter weight or volume UOM Class or because corresponding inventory base UOMs were not set up. Seeded value is Information Only as is the recommended setting.
WSH_OTM_SHIPM ENT_ERROR	This exception is logged when an error occurs while processing data from Oracle Transportation Management. Seeded value is Error as is the recommended setting.
WSH_OTM_SHIPM ENT_REC	This exception is a delivery level exception that is logged when a shipment received response message has been received from Oracle Transportation Management. Seeded value is Information only, as is the recommended setting.
WSH_OTM_BATC H_SHIPMENT_REC	This exception is a batch level exception that is logged when a batch shipment received response message has been received from Oracle Transportation Management. Seeded value is Information only, as is the recommended setting.
WSH_OTM_BATC H_SUCCESS	This exception is a batch level exception that is logged when a batch success response message has been received from Oracle Transportation Management. Seeded value is Information only, as is the recommended setting.
WSH_OTM_INVAL ID_LOC_ERROR	This exception is logged when the response message from Oracle Transportation Management includes an invalid stop location. Seeded value is Error as is the recommended setting.

---

- **Delivery Detail Import Splitting Exception:**

WSH\_OTM\_DET\_OVERSIZED: This exception is logged when the delivery detail failed to be split at delivery detail import. Seeded value is Information Only, recommended setting is Error, Warning, or Information Only.

**Note:** The Delivery Detail Import Splitting Exception is not relevant

when integrating with Oracle Transportation Management using the batch based integration functionality.

- **OTM Interface Splitting Exceptions:**

---

Interface Exception Name	Description
WSH_OTM_DEL_S PLIT_FAIL	This exception is logged when Oracle Shipping Execution failed to split a delivery. Seeded value is Information Only, recommended setting is Error, Warning, or Information Only.
WSH_OTM_DEL_S PLIT	This exception is logged when Oracle Shipping Execution has successfully split a delivery. This exception is used when the delivery is split into five or less child deliveries. The exception is logged against the parent delivery. Seeded value is Information Only as is the recommended setting.
WSH_OTM_DEL_S PLIT_LARGE	This exception is logged when Oracle Shipping Execution has successfully split a delivery. This exception is used when the delivery is split into six or more child delivery lines. The exception is logged against the parent delivery. Seeded value is Information Only as is the recommended setting.
WSH_OTM_DEL_S PLIT_CHILD	This exception is logged when Oracle Shipping Execution has created the child delivery after the split. The exception is logged against the child delivery. Seeded value is Information Only as is the recommended setting.
WSH_OTM_DEL_O VERSIDED	This exception is logged when Oracle Shipping Execution transportation interface rejects a delivery that exceeds the gross weight limit, while the interface parameter Auto Split Deliveries is set to No. Seeded value is Information Only, recommended setting is Error, Warning, or Information Only.

---

**Note:** OTM Interface Splitting Exceptions are not relevant when integrating with Oracle Transportation Management using the batch based integration functionality.

## Concurrent Programs

Oracle Shipping Execution provides the following concurrent programs:

- Shipping-Transportation Carriers Synchronization
- Shipping-Transportation Locations Synchronization
- Create Batches for Transportation Planning
- Shipping-Transportation Outbound Interface
- Planned Shipment Interface

**Note:** If an order release is not deleted in Oracle Transportation Management after running the Shipping-Transportation outbound *Delete* interface, ensure that the delete transaction is processed before the other delivery related transactions. For example, you could create a concurrent request set that includes the different interface actions in the following order:

1. Delete
2. Update
3. Create

or, alternatively:

1. Delete
2. All except actual shipment

### Shipping-Transportation Carriers Synchronization

Carriers and carrier sites are defined in Oracle Shipping Execution; however the implementation of Oracle Transportation Management includes changes to the Carrier form. The following changes are part of the integration of Oracle Transportation Management:

- When Oracle Transportation Management is not installed, all fields on the Rating, Payment tab are disabled with the exception of the Enable Manifesting field.
- When Oracle Transportation Management is installed, all fields on the Rating, Payment tab are disabled with the exception of the fields in the Freight Payment and Audit region (that is, the Supplier and Default Supplier Site fields).
- When Oracle Transportation Management is installed, the Mode Limits tab is disabled.
- When Oracle Transportation Management is installed, the Mode Limits tab, within

the Services tab, is disabled.

- When Oracle Transportation Management is installed, the Transportation tab within the Addresses/Sites tab, is disabled with the exception of the Supplier Site field.

The Shipping - Transportation Carriers Synchronization concurrent program enables Oracle E-Business Suite to communicate carrier and carrier site information to Oracle Transportation Management through the use of the Location XML transaction. The carrier and carrier site information from the Oracle E-Business Suite tables/columns is interfaced to Oracle Transportation Management tables/columns through the concurrent program.

During the implementation of Oracle Transportation Management, the Shipping - Transportation Carriers Synchronization concurrent program is executed to move all carrier and carrier site data from the Oracle E-Business Suite tables / columns to the Oracle Transportation Management tables/columns. After the implementation is complete, the concurrent program can be run whenever a Carrier/Carrier Site is updated or new Carriers and Carrier Sites are created.

BPEL is used to control the flow of data sent by the concurrent program.

#### **Interface Parameters**

The Shipping-Transportation Carriers Synchronization is executed from the Interfaces menu. The program includes the following parameters:

- Carrier Name From: Carrier name range low.
- Carrier Name To: Carrier name range high.
- Last Date Update From: If left blank, then the program will apply to all carriers within the restrictions of the other parameters defined.
- Last Date Update To: If left blank, then the program will apply to all carriers within the restrictions of the other parameters defined.

#### **Transferred Carrier Data**

The following table details all carrier data, whether Oracle E-Business Suite or Oracle Transportation Management owns the data, and details how (if at all) the data is transferred from one to the other. (OTM = Oracle Transportation Management. EBS = Oracle E-Business Suite.)

#### ***Transferred Carrier Data***

---

<b>EBS Entity</b>	<b>OTM Entity</b>	<b>Owner</b>	<b>Transfer Data Method</b>
-------------------	-------------------	--------------	-----------------------------

---

---

Vehicle Types	Equipment Types / Groups	OTM	None
Carrier Commitments	Carrier Commitments	OTM	None
Vehicle Availability	Carrier Capacity	OTM	None
Carriers	Corporation ID	EBS	From EBS to OTM
Carrier Sites	Location ID	EBS	From EBS to OTM
Service Levels	Rate Service	EBS	Manual
Modes	Mode	EBS	Manual
Calendars (Shipping, Receiving, and Carrier)	Calendars	OTM	None

---

### Shipping-Transportation Locations Synchronization

The Shipping-Transportation Locations Synchronization concurrent program synchronizes the locations between EBS and OTM. You must create the location in EBS and then use this concurrent program to synchronize the EBS locations with OTM. After you run this concurrent program, OTM can use the new locations for itineraries and setup data.

#### Interface Parameters

The Shipping-Transportation Locations Synchronization concurrent program is submitted from the Interfaces menu. The program includes the following parameters:

- **Organization:** An OTM-enabled inventory organization
- **Location Name:** The name of the internal location associated with the inventory organization set in the Organization parameter
- **Last Update Date From and To:** The date range during which the internal location was last updated

### Create Batches for Transportation Planning

The Create Batches for Transportation Planning concurrent program groups delivery details for the selected parameters into a transportation batch and subbatches. A transportation batch can contain delivery details from multiple sales orders or from a

Oracle Warehouse Management wave. The subbatches are created based on the Ship-From and Ship-To locations of the sales order lines. If you select Cancel Unshipped Lines check box in the sales order header, then different subbatches are created for each sales order.

The following batch group attributes are mandatory:

- Ship-From Location
- Ship-To Location

The following batch group attributes are optional:

- Customer
- Freight Terms
- FOB Code
- Ship Method

Transportation sub batches are sent to Oracle Transportation Management (OTM) for transportation planning. Transportation sub batch name is equivalent to an order release in OTM. OTM using the order release can plan and create single or multiple shipments that are then sent back to Oracle Shipping Execution to create trips.

When entering the parameters for the Create Batches for Transportation Planning concurrent program, you can select whether you want the concurrent program to send the transportation batch immediately to OTM after the batch is created or if you want to send the batch at a later date. If you select Yes in the Submit Outbound Request parameter, the system automatically runs the Shipping-Transportation Outbound Interface concurrent program after the transportation batch is created. If you select No in the Submit Outbound Request parameter, you would have to manually run or have the system periodically run the Shipping-Transportation Outbound Interface concurrent program.

### **Submission**

1. Navigate to the **Shipping Interfaces** window.
2. Select Create Batches for Transportation Planning in the **Name** field.
3. Enter the parameters and click **OK**.
4. Click **Submit**.

### **Parameters**

Enter values in the following parameters:

1. **Source System:** Select a source system.

2. **Organization:** Optionally, select the organization.
3. **Wave:** Optionally, select the Oracle Warehouse Management wave.  
After you select a wave, the other parameters become unavailable for entry.
4. **Consignee/Customer:** Optionally, select a customer or supplier. For an ISO return delivery line, select a ship-to organization.
5. **Ship To Location:** Optionally, select a consignee's or customer's ship to address.
6. **Source Header Type:** Optionally, select the source header type.
7. **Source Header Number (Low/High):** Optionally, select the range of source header numbers.
8. **Request Date (Low/High):** Optionally, select the range of request dates.
9. **Schedule Date (Low/High):** Optionally, select the range of schedule dates.
10. **Shipment Priority:** Optionally, select the shipment priority.
11. **Line Status:** Optionally, select the line status.
12. **Submit Outbound Request:** Select Yes to have the system automatically run the Shipping-Transportation Outbound Interface concurrent program after the batch is successfully created. Select No if you do not want the system to run the Shipping-Transportation Outbound Interface concurrent program. Yes is the default.
13. **Log Level:** Select 1 to turn debugging on and 0 to turn debugging off.

### Output File

After the concurrent program completes successfully, you can view the transportation batch number and sub batches created through the output file.

To view the output file:

1. Navigate to the **Requests** window.
2. Select the **Request ID** associated with the Create Batches for Transportation Planning concurrent program.
3. Click **View Output**.

## Shipping-Transportation Outbound Interface

The Shipping-Transportation Outbound Interface concurrent program passes Oracle Shipping Execution information to Oracle Transportation Management (OTM). The interface passes the information to BPEL using XML. The setting for the profile option

WSH: Delivery Based OTM Integration determines whether the information that is passed from Oracle Shipping Execution to OTM is delivery based or batch based.

If you set the WSH: Delivery Based OTM Integration profile option to Yes or Null, the integration is delivery based. If you set the profile option to No, the integration is batch based. Depending on the type of integration you are using, the system parameters enabled to run the Shipping-Transportation Outbound Interface concurrent are different.

Shipping-Transportation Outbound Interface concurrent program includes the following parameters:

#### **Shipping-Transportation Outbound Interface Parameters**

- **Interface Action:**

Delivery based interface actions:

- **Create:** Send all Include for Planning created deliveries to Oracle Transportation Management
- **Update:** Send all Include for Planning updated deliveries to Oracle Transportation Management
- **Delete:** Send all deliveries that must be removed from Oracle Transportation Management
- **ActualShipment:** Collect all of the Include for Planning and Ignore for Planning trips and send the trips to Oracle Transportation Management. Only trips with all pickup stops closed are included in the ActualShipment interface.
- **Create, Update:** Send all Include for Planning created or updated deliveries to Oracle Transportation Management.
- **All Except Actual Shipment:** Send all Include for Planning created and updated deliveries to Oracle Transportation Management and all deliveries that must be deleted in Oracle Transportation Management.

Batch based interface actions:

- **Create:** Send all batches to Oracle Transportation Management.
- **Update:** Send all updated batches to Oracle Transportation Management.
- **Delete:** Send all batches that must be removed from Oracle Transportation Management.
- **Actual Shipment:** Collect all of the Include for Planning and Ignore for Planning trips and send the trips to Oracle Transportation Management. Only trips with all pickup stops closed are included in the Actual Shipment interface.

- **Create, Update:** Send all created or updated batches to Oracle Transportation Management.
- **All Except Actual Shipment:** Send all created and updated batches to Oracle Transportation Management and all batches that must be deleted in Oracle Transportation Management.
- **Interface Basis:** This field appears by default from the selection you made in the WSH: Delivery Based OTM Integration profile option. **Delivery** is displayed for delivery based integration and **Batch** is displayed for batch based integration.
- **Auto Split Deliveries:** If set to Yes, then deliveries with weight greater than the gross weight specified in Shipping Parameters is split automatically. If set to No, then deliveries with a weight greater than the weight specified in Shipping Parameters are not automatically split. This parameter is disabled if Actual Shipment or Delete is the setting for the Interface Action parameter or if the Interface Basis parameter is set to Batch.
- **Client:** Select the client name from the list if you have set LSP mode as the value for the WMS: Deployment Mode profile option. See *Oracle Warehouse Management User's Guide*.
- **Ship from Organization:** Specify the organization from which you are submitting deliveries or batches and stops. If left as Null, then all Transportation enabled organizations are selected. This parameter is disabled when the interface action is Actual Shipment.
- **Planned Shipments Only:** Set the parameter to Yes to exclude trips that are marked as Ignore for Planning. This parameter is applicable when the interface action is Actual Shipment. Select No to include the planned and not planned shipments. The default value is No.
- **Trip Name (Low/High):** The range of trips to be submitted. These fields are disabled unless Actual Shipment is the setting for the Interface Action parameter.
- **Delivery Name (Low/High):** The range of deliveries to be submitted. These fields are not applicable when Actual Shipment is the setting for the Interface Action parameter or if the Interface Basis parameter is Batch. If entered while action is Actual Shipment, then a warning message is issued by the concurrent request. The value entered is ignored by the process.
- **Delivery Pick up date (low/high):** Delivery pick-up date range. These fields are not applicable and not used for processing when Actual Shipment is the setting for the Interface Action parameter or the Interface Basis parameter is set to Batch.
- **Transportation Batch Name (Low/High):** The range of transportation batches to be

submitted. These fields are not available if the Interface Basis parameter is set to Delivery.

- **Transportation Batch Creation Date (Low/High):** The range of transportation batch creation dates to be submitted. These fields are not available if the Interface Basis parameter is set to Delivery.
- **No (Number) of Transactions in Batch:** Number of delivery, transportation batch, or trip transactions that are run per batch. If this number is exceeded, then another concurrent request is run in parallel to execute the remaining transactions. 50 appears by default.
- **No (Number) of Child Processes:** The number of child batches to be run in parallel. One appears by default.

When scheduling the Shipping-Transportation Outbound Interface, it is recommended that you ensure that the Delete action is processed with the highest priority. For example, by scheduling the action with a higher frequency, or by creating a concurrent request set that performs the action ahead of other interface actions. This lowers the risk of double assignment of ship units or order release lines in Oracle Transportation Management, which might prevent proper deletion of the order release.

#### Reference Data and Mapping

Item, Customer/Customer Site, and Organizations/Ship From Locations are included as reference data that is sent as part of the Shipping-Transportation Outbound Interface concurrent request.

### Planned Shipment Interface

The Planned Shipment Interface concurrent program picks up the shipments that were created in Oracle Transportation Management and places them in Oracle Shipping Execution. You can automatically run the Planned Shipment Interface request every time a planned shipment is received from Oracle Transportation Management. However, for situations that may result in too many Planned Shipment Interface concurrent requests being run simultaneously, you may want to run this request either manually or on a scheduled interval. Several concurrent requests running at the same time may reduce system performance.

The *Defer Planned Shipment Interface* checkbox on the Global Parameters window (General tab) controls the default setting for running the Planned Shipment Interface concurrent program. Select this checkbox if you want to run the program manually (or to schedule it), or clear this checkbox if you want to run the request automatically every time the planned shipment is received from Oracle Transportation Management.

To provide additional information in the descriptive flexfields (DFF) for trips and trip stops, set the attribute values in the following custom APIs:

- WSH\_CUSTOM\_PUB.POST\_OTM\_TRIP\_DFF

- WSH\_CUSTOM\_PUB.POST\_OTM\_TRIP\_STOP\_DFF

These APIs are called when data is inserted into the shipping interface table. The DFF values entered in the interface tables are processed by the Planned Shipment Interface and are visible in the **Shipping Transactions** window after enabling the standard DFFs for trips and trip stops.

Alternatively, additional information in Oracle Transportation Management (OTM) can be stored in **Shipment Reference Number** and **Shipment Stop Reference Number** according to the mapping in the tables in the *Appendix A, XML Mapping, Planned Shipment XML Transaction - Trip* and *Planned Shipment XML Transaction - Trip Stop*. This allows you to integrate these reference number values to the DFFs for trips and trip stops. The Planned Shipment Interface then maps the OTM Shipment Reference Number and Shipment Stop Reference Number to the standard DFFs for trips and trip stops.

For multi-leg shipments, the Planned Shipment Interface concurrent program does the following:

1. Creates multi-leg trips in EBS
2. Creates or assigns delivery to multi-leg trips
3. Assigns freight cost information at the trip level
4. Processes trip updates that are already received in EBS

### **Submission**

1. Navigate to the **Shipping Interfaces** window.
2. Select Planned Shipment Interface in the **Name** field.
3. Enter the parameters and click **OK**.
4. Click **Submit**.

### **Parameters**

- **Process Latest Version Only:** Determines whether the latest version of the deliveries or transportation batches must be selected for processing. The default value is Yes.
  - Yes: Processes all deliveries or transportation batches for a trip (even if only one delivery is to be processed in the list of parameters).
  - No: The concurrent request processes the earlier versions of the deliveries or transportation batches (the current status of the delivery or transportation batch in the E-Business Suite should be in Open status waiting for an Update status from Oracle Transportation Management).

**Note:** The incoming trip can have deliveries or transportation batches (releases) belonging to one or more organizations.

- **Interface Basis:** This field appears by default from the selection you made in the WSH: Delivery Based OTM Integration profile option. **Delivery** is displayed for delivery based integration and **Batch** is displayed for batch based integration.
- **Transportation Plan Name (Low/High):** The range of transportation plan names
- **Client:** The client name if you have set logistics service provider (LSP) mode as the value for profile option WMS: Deployment Mode. See *Oracle Inventory User's Guide* for setting up client.
- **Organization:** The OTM-enabled inventory organization
- **Delivery Name (Low/High):** The range of delivery names
- **Delivery Pick Up Date (Low/High):** The range of delivery pick-up dates
- **Transportation Batch Name (Low/High):** The range of transportation batches to be submitted. These fields are not available if the Interface Basis parameter is set to Delivery.
- **Transportation Batch Creation Date (Low/High):** The range of transportation batch creation dates to be submitted. These fields are not available if the Interface Basis parameter is set to Delivery.

## Related Topics

Item XML Mapping, page A-73

Customer XML Mapping, page A-73

Customer Site XML Mapping, page A-73

Organization XML Mapping, page A-73

Carrier XML Mapping, page A-64

Carrier Site XML Mapping, page A-64

---

# Oracle Payables

## Overview of Oracle Transportation Management Integration with Oracle Payables

Oracle Transportation Management integrates with Oracle Payables to enable freight payment. Oracle Transportation Management performs an audit and approval of freight payments, and then passes the payment information to Oracle Payables, through the use of the Send Voucher interface. The Send Voucher interface transmits the voucher data to Oracle Payables through BPEL. The Payables Open Interface Import interface is run to import the vouchers into the Oracle Payables tables. The invoice is then created, validated, and ultimately paid in Oracle Payables.

### Send Voucher Interface

The Send Voucher interface enables you to send freight payment vouchers from Oracle Transportation Management to Oracle Payables through the use of Oracle Transportation Execution external systems and BPEL.

### Interface Parameters

The following defines the setup for the Voucher Interface.

1. Within Oracle Transportation Management, define an external system to send to the BPEL instance. See: Oracle Transportation Management External System Configuration.

The BPEL instance will be configured as a web service in Oracle Transportation Management and each outbound flow requires its own web service and external system. Further details regarding how to configure the OTM External System are available in the OTM Help documentation (Help > How To > EBS to OTM).

2. Select the voucher that you are sending.

3. Run the Action Send Voucher Interface.
4. Select the External System that is configured with the Web Service for BPEL.
5. Set the Notify Type to Service.

You can also configure an automation agent to trigger the voucher to be sent to E-Business Suite automatically.

## **Implementing Oracle Transportation Management with Oracle Payables**

The implementation of Oracle Transportation and Oracle Payables consists of the APInvoice XML transaction. The XML mapping is detailed in the Oracle Payables XML Mapping, page A-8 section of the XML Mapping appendix.

---

# Oracle Purchasing

## Overview of Oracle Purchasing Integration with Oracle Transportation Management

Oracle Transportation Management integrates with Oracle Purchasing, enabling you to manage inbound freight from your suppliers.


The integration of Oracle Transportation Management enables you to plan and track the progress and status of inbound purchase order-related shipments. Purchase orders created in Oracle Purchasing are communicated to Oracle Transportation Management after approval, enabling you to execute (rate, route, track, and reconcile) the related shipment. Purchase order changes are also communicated to Oracle Transportation Management upon re-approval in Oracle Purchasing.

As part of the shipment process, Oracle Transportation Management enables suppliers to submit "ready to ship" information.

After shipping takes place, purchasing agents access carrier-provided shipment status updates within Oracle Transportation Management. After goods are delivered, invoices for freight payment are collected and processed for payment.

**Note:** With Oracle Purchasing, the item container weights, volumes, and dimensions are entered in Oracle Transportation by the supplier and are not sent from the Oracle E-Business Suite.

### Inbound Purchase Order Flow



## Functional Changes with Oracle Transportation Management Installed

### Responsibility for Inbound Freight

Purchasing is enhanced with the Professional Buyers Work Center and web-based user interfaces. These interfaces are in addition to the forms user interfaces. The Purchase Order can be authored both in the web-based user interface as well as in application forms. In the forms version of the Purchase Order the inbound freight responsibility is determined by the purchase order header attribute named Transportation Arranged. This attribute is set in the Terms and Conditions window through the Purchase Orders window in Oracle Purchasing. In the web based user interface of the Purchase Order, the attribute is Transportation Arranger and is available in the Terms region of the Purchase Order Header tab. The attribute has the following values:

- **Buying Organization:** The payment method code for inbound shipments in Oracle Transportation Management is set to Collect (buying organization is responsible for managing and paying for inbound transportation).
- **Supplier:** The payment method code is set to Prepaid (supplier is responsible for managing and paying for inbound transportation).
- **Blank value or None:** Purchase orders are not communicated to Oracle Transportation Management.

**Note:** Purchase Orders that have Progress Payments will not be

communicated to Oracle Transportation Management.

## Impact of Purchase Order Status Changes on Oracle Transportation Management

---

<b>Purchase Order Event</b>	<b>Impact in Oracle Transportation Management</b>
Cancel Purchase Order	Prevents future releasing against all relevant PO shipments.
Open PO Shipment for Receiving	Allows future releasing against this PO shipment.
Close PO Shipment for Receiving	Prevents future releasing against this PO shipment.
Close Purchase Order	Prevents future releasing against this PO.
Finally Close Purchase Order	Prevents future releasing against this PO.
Place Purchase Order on Hold	Prevents future releasing against this PO.
Release Purchase Order Hold	Allows future releasing against this PO.

---

## Implementing Oracle Transportation Management with Oracle Purchasing

The following section describes the system configuration and setup changes required when you implement Oracle Transportation Management with Oracle Purchasing.

### System Configuration and Setup Changes (Oracle Transportation Management)

The following section describes the system configuration and setup changes required in Oracle Transportation Management when integrating with Oracle Purchasing.

#### Setting Up Profile Options

The following profile options are required for the integration with Oracle Purchasing:

- Client Timezone
- Enable Timezone Conversions

- Server Timezone
- OTM: Domain Name
- OTM: Domain User
- OTM: Integration Enabled

#### **Related Topics**

For more information about profile options specific to the integration of Oracle Transportation Management with the Oracle E-Business Suite, see *Profile Options and Parameters*, page 3-33.


### **Oracle Purchasing Configuration and Setup Changes (Oracle E-Business Suite)**

The following section describes the system configuration and setup changes required in Oracle Purchasing and the Oracle E-Business Suite when integrating with Oracle Transportation Management

#### **Mapping Oracle Purchasing to Oracle Transportation Management**

In the Oracle E-Business Suite, the purchase order or blanket release schedule is concatenated with the relevant line information to create an order baseline in Oracle Transportation Management, as shown in the following figure:

### Mapping Purchase Order Shipments to Order Base Lines




For detailed mapping of Oracle Purchasing to Order Base XML, see the XML Mapping appendix, Purchasing Fields to Order Base XML Mapping, page A-10.

**Note:** Purchase Orders that have Progress Payments will not be communicated to Oracle Transportation Management.

### Configuring the BPEL Process Manager

All communication between Oracle Purchasing and Oracle Transportation Management is through the BPEL process PoSendPoToOtm. The Oracle E-Business Suite Business Event "oracle.apps.po.event.document\_action\_event" activates this process. Upon activation, the process calls an Oracle Purchasing API to extract the appropriate document data. It then converts the document data to a message in the Oracle Transportation Management schema and invokes the Oracle Transportation Management servlet.

### Oracle Purchasing to XML



### XML Translation via XSL in BPEL

Oracle Purchasing purchase order and release data are extracted from Oracle E-Business Suite in the database object PO\_OTM\_ORDER\_TYPE. In the BPEL process, an XSL translation converts the data to an Oracle Transportation Management transmission.

The form of the transmission depends upon the action performed. In the case of a document approval or re-approval, the transmission consists of an Oracle Transportation Management TransOrder object, along with a set of Location and Contact objects. For control actions on existing documents, such as cancellation or closure, a GenericStatusUpdate object is transmitted.

The XSL translation implements integration-specific business logic, such as rounding quantities and selecting the appropriate contact methods for involved parties. The XSL step also performs some Oracle Transportation Management specific transformations to Oracle E-Business Suite data, such as generation of unique keys.

## **Web Services**

The BPEL process communicates with Oracle E-Business Suite through the Business Event queue and the PO\_OTM\_INTEGRATION\_PVT API. It terminates with a call to the Oracle Transportation Management servlet.



---

# Oracle Warehouse Management

## Overview of Oracle Transportation Management Integration With Oracle Warehouse Management

Integrating Oracle Transportation Management with Oracle Warehouse Management can improve shipment processing and capacity usage by providing more accurate committed dock appointments and load sequencing information.

To use the Oracle Transportation Management appointment and load sequencing features in Oracle Warehouse Management, you need to synchronize dock door information and organization location information with Oracle Transportation Management (OTM). When you synchronize the dock door information, the organization's default location is sent along with the dock door details to Oracle Transportation Management.

Dock door scheduling and load sequencing integration are controlled by setups in the Shipping Parameters window at the organization level. These setups are applicable only if the organization has installed and enabled Oracle Warehouse Management and Oracle Transportation Management.

### Dock Scheduling

Integrating with Oracle Transportation Management helps you optimize dock door usage, keep dock doors synchronized with the transportation plan, and ensure that material is staged to the correct dock door.

### Load Sequencing

Load sequencing is the order in which the LPNs are loaded onto a carrier's truck or vehicle. Typically, the LPNs that need to be dropped off first should be loaded last onto the vehicle (last-in first-out method).

To manage order releases based on shipment itinerary, you can use the shipment itinerary feature in Oracle Transportation Management to sequence loads in Oracle

Warehouse Management. You can direct outbound staging based on loading sequence, validate loading sequence during trailer loading, and minimize material handling during loading and unloading.


**Note:** No extra setup is required for load sequencing integration with Oracle Transportation Management. If the organization is Oracle Transportation Management-enabled and it is an Oracle Warehouse Management organization, then load sequence information is available.

## Setting Up Dock Door Synchronization with Oracle Transportation Management

The following steps describe how to synchronize dock door information from Oracle Warehouse Management to Oracle Transportation Management by using setups in both Oracle Warehouse Management and Oracle Transportation Management. For setting up Oracle Warehouse Management features, see the Oracle Warehouse Management documentation.

The following graphic shows the steps for integrating Oracle Warehouse Management with Oracle Transportation Management:

**Integration Steps for Oracle Warehouse Management and Oracle Transportation Management**



1. Define dock doors (Oracle Warehouse Management).
2. Enable dock door parameters (Oracle Shipping Execution).  
Select the *Enabling the Dock Door Appointment Scheduling* check box on the Shipping Parameters window for the organization. Even if the organization is enabled for Oracle Transportation Management, if this option is not selected, the dock door appointments from Oracle Transportation Management will not be synchronized with the Oracle E-Business Suite.
3. Run the *Synchronize Dock Doors with Transportation Management* concurrent program (Oracle Warehouse Management).

**Related Topics**

*Oracle Warehouse Management Implementation Guide, Setting Up Dock Door to Staging Lane Relationships*

## Defining Dock Doors in Oracle Warehouse Management

In Oracle Warehouse Management, dock doors and staging lanes are defined as stock locators. Locators identify physical areas within subinventories where you store item such as rack/bin or aisle/row/bin locations, storage locations, consolidation locations, and packing stations.

When you synchronize dock door information with Oracle Transportation Management, the organization's default location is sent along with the dock door information. This enables you to use door scheduling and load sequencing integration features in Oracle Transportation Management.

**Important:** Dock doors must already be set up in Oracle Inventory (use the Stock Locators window to create a dock door) before you can synchronize dock door information with Oracle Transportation Management.

### Related Topics

*Oracle Inventory User's Guide, Defining Stock Locators*

*Oracle Warehouse Management Implementation Guide, Setting Up Dock Door to Staging Lane Relationships*

## Synchronizing Dock Doors with Oracle Transportation Management

In Oracle Transportation Management, dock doors are linked to a location. When the dock door information is synchronized between Oracle Warehouse Management and Oracle Transportation Management, the default location of the organization is also sent with the dock door to Oracle Transportation Management. After the dock door information is synchronized with Oracle Warehouse Management, you can complete the following actions in Oracle Transportation Management:

- Select staging lane based on dock appointment.
- Select lines for wave creation based on dock appointment.

### Prerequisites

- Dock doors must already be set up before you can synchronize them with Oracle Transportation Management. For more information see, *Oracle Inventory User's Guide, Defining Stock Locators*

**To synchronize dock doors using the Synchronize Dock Doors with Transportation Management concurrent program:**

1. Navigate to the Submit Request window.  
  
(N) From the Warehouse Manager responsibility, select Outbound Logistics, then select *Synchronize Dock Doors with OTM*.
2. Enter the parameters such as the Organization and update dates.
3. Click Submit to run the concurrent request to synchronize the dock doors.  
  
The *Synchronize Dock Doors with Transportation Management* concurrent program sends all the selected dock doors and their corresponding location information from Oracle Warehouse Management to Oracle Transportation Management.
4. After you run the concurrent program, verify that it has completed successfully by reviewing its status in the Requests window.  
  
After the dock door information is synchronized, you can view the dock doors in Oracle Transportation Management when viewing or setting up appointments (typically in the Manage Appointments page).

## **Synchronizing Dock Appointments with Oracle Transportation Management**

When Oracle Transportation Management is integrated with Oracle Warehouse Management, you can optimize dock door usage, ensure dock doors are synchronized with the transportation plan, and stage material accurately to the correct dock door. You can use Oracle Transportation Management to maintain all dock door appointments and send the trip-related appointments to Oracle Warehouse Management.

The following steps outline the process for synchronizing dock door appointments with Oracle Transportation Management:

Step Number	Step	Set Up/Run This Step in Following Oracle Application
1	<p>Create deliveries.</p> <p>Create deliveries and view delivery information associated with the trip in the Shipping Transactions window.</p> <p><b>Important:</b> Delivery lines must be in the status of <i>Ready to Release</i>.</p>	Oracle Shipping Execution
2	<p>Run the <i>Shipping-Transportation Outbound Interface</i> program to send the delivery information to Oracle Transportation Management.</p>	Oracle Shipping Execution
3	<p>Create appointments in Oracle Transportation Management.</p> <p>After the appointment is created, you can view the available appointment in the Manage Appoints page.</p>	Oracle Transportation Management
4	<p>Running the interface transmission.</p> <p>Oracle Transportation Management maintains all dock door appointments and sends the trip-related appointments to Oracle Warehouse Management.</p>	Oracle Transportation Management
5	<p>View or change dock door appointments.</p> <p>You can use Oracle Warehouse Management to modify the dock appointments at any time. If the material has been loaded to the dock door or staging lane, you will have to manually modify the dock appointments. This may include changes to Dock Door.</p>	Oracle Warehouse Management

Step Number	Step	Set Up/Run This Step in Following Oracle Application
6	<p>Load Sequencing: Verify appointments and delivery load sequencing</p> <p>Load Sequencing is the order in which the LPNs are loaded onto a carrier's truck or vehicle. Usually, the LPNs that need to be dropped off first are loaded last onto the vehicle (last-in first-out method). As part of the existing integration between Oracle Shipping Execution and Oracle Transportation Management, the stop sequence numbers are sent from Oracle Transportation Management to create the trip stops in shipping. The same sequence will be used as the Loading Sequence (in reverse).</p>	Oracle Shipping Execution
7	<p>Load Sequencing: Release the trip for pick release execution.</p> <p>After the load sequence is determined and the trip stops are returned to Oracle Shipping Execution, you can then release the order for picking.</p>	Oracle Shipping Execution
8	Load Sequencing: Associate the staging lane to dock door.	Oracle Warehouse Management
9	Load Sequencing: Stage the delivery.	Oracle Warehouse Management

## Creating the Transportation Plan and Managing Appointments in Oracle Transportation Management

After you run the *Shipping-Transportation Outbound Interface* program to send the delivery information to Oracle Transportation Management, you can create transportation plans and manage the dock door appointments in Oracle Transportation Management.

In Oracle Transportation Management, you can reserve a time period (or *appointment*) for unloading or loading a trailer at the dock door. Appointments can be created at the following levels:

- Organization level
- Dock door level

External users such as suppliers, carriers, and customers can create appointments only at the organization level; internal users such as facility managers can create appointments at both the organizational and dock door levels. An appointment can be created at the organization or dock door levels only if:

- there is an availability in the warehouse calendar for the time slot requested.
- a dock door is available and not reserved by existing organization level and dock door level appointments.

**Note:** Overbooking dock doors is not permitted.

### To create the transportation plan and manage appointments:


1. Navigate to the Order Release page in Oracle Transportation Management.

#### Order Release Search page

The screenshot shows the Oracle Transportation Management (OTM) Order Release Search page. The page title is "OTM Version 5.5" and the user is "ML4YS210.ADMIN" with the role "ADMIN". The page has a navigation bar with tabs: "Order Release", "Release Lines", "Scheduling", "Locations", "Order Base", "Status", "General", and "Advanced". The main content area contains search criteria fields: "Order Release ID" (with a "Begins With" dropdown), "Quote ID" (with a "Begins With" dropdown), "Domain Name" (with a "Begins With" dropdown), "Indicator" (with a dropdown), "Order Release Attribute" (with a list box containing "APPROVED" and "CUSTOMER\_ORDER"), "Insert Time" (with a "Same As" dropdown), "Early Pickup Date" (with a "Same As" dropdown), "Late Pickup Date" (with a "Same As" dropdown), and "Early Delivery Date" (with a "Same As" dropdown). At the bottom, there is a search bar with buttons for "Search", "New", "Sort Order", "Lists", "Actions", "Export", and "Execute Query", along with a "Saved Query" dropdown.


2. Enter your delivery number in the Order Release ID field and click Search to display the search results.
3. Select the ID from the navigation tree, and then expand the Order Release ID.

### Order Releases page



4. Select one of the following:
  - To build a shipment: From the Actions menu, select Create Buy Shipment, then select Build Buy Shipment on Primary Leg.
  - If you have already built a shipment, select Buy Shipments and select the buy shipment number. Alternatively, to maintain an appointment for a particular stop, expand the Shipment Stops tab to select a shipment stop.

### Order Releases-Buy Shipments



5. Double-click the buy shipments ID to display the shipment in the Shipment Manager page.


### Shipment Manager page

The screenshot displays the OTM Shipment Manager interface. At the top, it shows the user is logged in as ML4YS210.ADMIN with the role ADMIN. The page title is "Shipment Manager" and it indicates "1 of 1" shipment is displayed. Navigation tabs include Identification, Equipment, Stops, Financials, Involved Parties, Mode, Remarks, and Groups and Charges. The main content area is divided into several sections:

- Identification:** Shipment ID (01064), Shipment Name (empty field).
- Domain Name:** ML4YS210
- Service Provider ID:** CAR-12521
- Transport Mode:** PARCEL (dropdown menu)
- Shipment Type ID:** TRANSPORT (dropdown menu)
- Enroute Status:** ENROUTE\_NOT STARTED
- Planned Transport Mode:** PARCEL
- Planned Service Provider:** CAR-12521
- Memo BL:**
- \* Start Time:** 2008-05-26 05:23:44
- \* End Time:** 2008-05-27 06:23:44
- Duration:** 1D
- Earliest Start Time:** 2008-05-26 05:23:44
- Latest Start Time:** 2008-05-26 05:23:44
- Feasibility Code ID:** FEASIBLE
- Temp. Controlled:**
- Hazardous:**
- Hazmat Mode ID:** (empty field)
- Intermediary Corporation ID:** (empty field)
- Total Number Of Reference Units:** (empty field)
- Bulk Plan ID:** (empty field)
- Itinerary ID:** (empty field)
- Main Itinerary Logo:** (empty field)
- Delivering Service Provider:** (empty field)
- Originator:** (empty field)


6. To schedule dock appointments for the shipment: From the Actions menu, select Dock Scheduling, then select Schedule Appointment.

**Shipment Manager page**



7. Select the stop location for the appointment. You can define additional search options by clicking Show Options.

**Select Stop Location for Appointment page**



- Click Schedule to schedule the dock door appointment. You can then click View Appointment to view the appointment details.

After the dock door information is sent Oracle Warehouse Management (by running the Send Interface Transmission program), you can modify the dock appointments at any time from Oracle Warehouse Management. If the material has been loaded to the dock door or staging lane, you will have to manually modify the dock appointments.


The screenshot shows the 'Manage Appointments' interface in OTM. The title bar reads 'OTM' and the main header is 'Manage Appointments - ML4YS210.ORG-1884-2402'. The interface displays a grid with columns for time slots (04:30, 05:00, 05:30, 06:00, 06:30, 07:00, 07:30, 08:00, 08:30, 09:00) and rows for different dock doors and locators. A legend at the bottom identifies appointment types: Fixed Appointment (blue), Working Appointment (green), Blocked Slot (black), Infeasible Appointment (red), and Unavailable (grey). Buttons for 'Save', 'Search', 'Refresh', and 'Create Appointment' are visible at the bottom.

DOCK DOOR	04:30	05:00	05:30	06:00	06:30	07:00	07:30	08:00	08:30	09:00
DOCK DOOR 1								ML4YS210.01060:16272		
DOCK DOOR 121516										
DOCK DOOR 2										
DOCK DOOR FOR OTM										
DOCK DOOR LOCATOR A										
DOCK DOOR LOCATOR B										
DOCK DOOR LOCATOR C										
DOCK DOOR LOCATOR GP										
DOCK DOOR LOCATOR GS										
DOCK DOOR LOCATOR JR										
DOCK DOOR LOCATOR MO										
DOCK DOOR LOCATOR MSDD1										
DOCK DOOR LOCATOR PKMD1										
DOCK DOOR LOCATOR PUPD1								ML4YS210.01064:16931		

- Oracle Transportation Management maintains all dock door appointments and sends the trip-related appointments to Oracle Warehouse Management. These appointments are sent as part of the existing planned shipment updates to Oracle Warehouse Management at the pickup stop(s).

To send the information from Oracle Transportation Management to Oracle Warehouse Management, run the Send Interface Transmission program. On the Shipment Manager page, from the Actions menu, select Utilities, then select Send Interface Transmission.

### Shipment Manager page-Send Utilities



10. Select your interface transmission criteria in the Get Interface Transmission page.  
Use the interface page to send delivery information to external systems such as Oracle Warehouse Management. The stop sequence numbers are sent from Oracle Transportation Management to create the trip stops in Oracle Shipping Execution (this information is mapped to the Inbound Trip XML).

### Get Interface Transmission page

**OTM**

Get Interface Transmission

Send Full Text  
 Send Summary Only

**Remarks**  
[Text Box]

**\* External System**  
EBS-OUTBOUND-SH [Icon]

**Notify Type**  
HTTP [Dropdown]

**Guarantee Delivery**

**Send**

11. Click Send to run the interface transmission.

After you run the interface transmission, you can complete related steps in the following Oracle applications. Refer to the application-specific documentation for additional details on completing each step:

1. View or change dock door appointments. (Oracle Warehouse Management)
2. Verify appointments and delivery load sequencing. (Oracle Shipping Execution)
3. Release the trip for pick release execution. (Oracle Shipping Execution)
4. Associate the staging lane to dock door. (Oracle Warehouse Management)
5. Stage the delivery. (Oracle Warehouse Management)

## Related Topics

Setting Up Dock Door Synchronization with Oracle Transportation Management, page 6-2

---

# Oracle Advanced Planning and Scheduling

## Overview of Oracle Transportation Management Integration With Oracle Advanced Planning and Scheduling

Oracle Transportation Management tracks the current estimated arrival date of in-transit shipments when transportation plans are updated or when carriers provide updated information about shipments in-transit. Tracking unexpected changes, for example, orders being delivered later or earlier than expected from suppliers or changes to internal shipments between organizations, is important because these changes can affect the rest of the supply chain.

Oracle Transportation Management monitors business events such as order changes and then sends XML messages to update applications with the changes. An Oracle customer who has deployed both Oracle Transportation Management and Oracle Advanced Planning and Scheduling (APS) can configure a web service and BPEL process (provided by Oracle APS) to provide updates to planning when the arrival date of an order changes. (Updated dates collected from Oracle Transportation Management can be used for planning in advanced supply chain planning, distribution requirement planning, and collaborative planning in Oracle Collaborative Planning.) The system then notifies planners when changes to arrival or order dates occur. These updated dates are evaluated during planning, and exceptions are generated if dates are later or earlier than expected.

**Important:** The integration process applies only to purchase orders (planned and in-transit) and internal transfer orders (planned and in-transit internal sales order and internal sales order) because planning does not manage arrival of outbound shipments after they have shipped.

### Prerequisites

The following products and modules are required for fully integrating Oracle

Transportation Management and Oracle Advanced Planning and Scheduling. These product and modules are required for getting the latest estimated arrival dates for internal requisitions (IR), internal sales orders (ISO), and purchase orders (PO), and for other technical requirements.

- Oracle Transportation Management 5.5 CU4
- Oracle Advanced Planning and Scheduling 12.1.CU1 Release
- Oracle Purchasing, Oracle Shipping Delivery Based, Oracle Order Entry (12.0.4 or 12.1)
- SOA 10.1.3.3

## Understanding Arrival Time Updates

This section describes what actions occur when Oracle Transportation Management detects a change in an estimated arrival time:

### Arrival Time Updates

If you use Oracle Transportation Management, you can update your production plans with the current status of estimated arrival times of purchase and transfer orders in transit. These changes occur either because of a change in the transportation plan or because of carries updates.

When Oracle Transportation Management detects a change in an estimated arrival time, it:

- Notes the estimated arrival time in your production plans for purchase requisitions, internal requisitions, and internal sales orders
- Compares its estimated arrival time to the corresponding plan dock date or scheduled arrival date
- Issues exception messages if the dates differ--Order will be delivered later than scheduled or Order will be delivered earlier than scheduled
- Sends a notification to the planner with a link to drill down to Oracle Transportation Management for details
- Updates the arrival date in Oracle Collaborative Planning
- Arranges for the Oracle Collaborative Planning exception process to evaluate the updates and issue exceptions as necessary

When the next production plan runs, it:

- Updates the dock date with the estimated arrival time
- Firms the order
- Issues exception messages as necessary when the new arrival time has an effect on demand satisfaction—late replenishment, early replenishment, order at risk

You can view transportation updates in form View Transportation Updates

## Implementing Oracle Transportation Management with Oracle Advanced Planning and Scheduling

The following section describes the system configuration and setup changes required when you implement Oracle Transportation Management with Oracle Advanced Planning and Scheduling.

### Overview of Process Flow

The following steps outline the process flow of the integration with starting from when a carrier updates or creates a new transportation schedule in Oracle Transportation Management.

**Additional Information:** The following terms are used:

- OTM: Oracle Transportation Management
- ASCP: Oracle Advanced Supply Chain Planning
- APS: Oracle Advanced Planning and Scheduling
- DRP: Distribution Requirements Planning, a component of ASCP
- BPEL: Business Process Execution Language

#### Step 1: Oracle Transportation Management (OTM)

1. A new transportation schedule or an update from a carrier in Oracle Transportation Management updates the arrival dates for one or more orders.
2. Oracle Transportation Management sends an XML message with updates for BPEL processing.

#### Step 2: Business Process Execution Language (BPEL)

1. The XML message is processed and a BPEL flow is initiated to update the purchase orders and internal requisition and internal sales order in the APS workbench with the new date. A new record is stored in the MSC\_TRANSPORTATION\_UPDATES table for each updated record.

2. Sends a notification about the updates including a link to OTM from APS to view updates. To view notifications, the profile option *MSC: Generate Notifications for Transportation Updates* must be set to Yes.
3. Confirms if the order also exists in Oracle Collaborative Planning: if yes, updates Updated Arrival Date (new column). If not, the following step is completed.
4. Reviews the profile option *MSC: Production Plan for Transportation Updates*. If a plan exists, the next step is completed: if not, the BPEL flow ends and the user process starts.
5. Stores dates in new column `msc_supplies` and `msc_demands` as Updated Arrival Date in the planning data store for the plan specified in the profile option.
6. Generates new exceptions when Oracle Transportation Management date is not equal to the date from ERP for the order:
  - Where OTM date is greater than dock date: order will be delivered later than scheduled.
  - Where OTM date is less than dock date: order will be delivered earlier than scheduled.

#### **Step 3: User**

- Planner runs either an online or batch replanning process. ENGINE process: The online planner and batch replanning recognizes the updated records and includes them in the replanning, OR
- Planner runs a plan using dates collected from Oracle Transportation Management. ENGINE process: The transportation date is used where it exists, otherwise the current date is used.

#### **Step 4: Engine Processing**

1. The plan generates new exceptions when the Oracle Transportation Management date is not equal to the date collected from ERP for the order. These existing exceptions are generated whenever a purchase order or internal requisition will arrive later than required.
2. The plan generates and identifies new related exceptions as Late Replenishment exceptions, Early Replenishment exceptions, and Order at Risk exceptions.

## **System Configuration and Setup Changes (Oracle Transportation Management)**

The following section describes the system configuration and setup changes required in Oracle Transportation Management.

## Transportation Management Exceptions Exception Group

This table shows the exceptions in this exception group and states whether the planning engine issues the exception for each plan type.

Exception Message	Available In Unconstrained Plans	Available In Constrained Plans with Enforce Demand Dates	Available In Constrained Plans with Enforce Capacity Constraints	Available In Optimized Plans	Available In Inventory Optimization
1: Order will be delivered later than scheduled	No	Yes	Yes	Yes	No
2: Order will be delivered earlier than scheduled	No	Yes	Yes	Yes	No

### 1: Order will be delivered later than scheduled

#### Explanation

The planning engine issues this exception when Updated Arrival Date is later than:

- For purchase requisitions and internal requisitions, Dock Date
- For internal sales orders, Scheduled Arrival Date

#### Information Displayed

The information displayed for this exception message is:

- Organization
- Item
- Order Number
- Current Date
- Updated Arrival Date
- Quantity
- Planner

- Product Family
- Item Category
- Supplier (for purchase order and internal requisition only)
- Supplier Site (for purchase order and internal requisition only)
- Source Organization (for internal sales order only)

#### **Resolution Suggestion**

Run either an online replan or a batch replan. The planning engine issues related exceptions when the new arrival time has an effect on demand satisfaction—late replenishment, early replenishment, order at risk

#### **2: Order will be delivered earlier than scheduled**

##### **Explanation**

The planning engine issues this exception when Updated Arrival Date is earlier than:

- For purchase requisitions and internal requisitions, Dock Date
- For internal sales orders, Scheduled Arrival Date

##### **Information Displayed**

The information displayed for this exception message is:

- Organization
- Item
- Order Number
- Current Date
- Updated Arrival Date
- Quantity
- Planner
- Product Family
- Item Category
- Supplier (for purchase order and internal requisition only)
- Supplier Site (for purchase order and internal requisition only)
- Source Organization (for internal sales order only)

### Resolution Suggestion

Run either an online replan or a batch replan. The planning engine issues related exceptions when the new arrival time has an effect on demand satisfaction—late replenishment, early replenishment, order at risk

## Setting Up the BPEL Process

First, you must define the database connection for the BPEL process.

**Note:** There are similar setups for Oracle Shipping Execution and Oracle Order Management.

### To set up the BPEL process into the SOA (service-oriented architecture) server:

Complete the following steps to deploy the `MscReceiveUpdateFromOtm` BPEL process for a BPEL domain.

1. Verify that the domain(s) are created appropriately in the BPEL server.
2. Create a temporary directory on either the same server as BPEL or on a server accessible to the BPEL server.
3. Under the temporary directory, create the following directory structure:  
oracle/apps/msc/bpel/util.
4. Copy the following .jar files from the `$MSC_TOP/patch/115/jar/bpel` directory to the temporary directory: `msc_bpel_receiveUpdatefromOTM.jar`.
5. Copy the following .xml and Java class files from `$JAVA_TOP/oracle/apps/msc/bpel/util` directory to the temporary directory: `mscUpdateOTMBpel.class`, `MscJarOTMBuild.xml`.
6. Move `mscUpdateOTMBpel.class` under the `/oracle/apps/msc/bpel/util` directory structure.
7. Ensure the `CLASSPATH` and `PATH` are set correctly so that the ant-related .jar files are present in the path. The `obant` utility is typically present in `/bpel/bin`. Set the classpath inside `obant` (either `obant.bat` or `obant.sh`) so that the class `oracle.apps.msc.bpel.util.mscUpdateOTMBpel.class` is visible to the `obant` utility.
8. To run `obant` successfully, review the following parameters and identify relevant values for each E-Business Suite, BPEL domain, and Oracle Transportation Management instance that you are configuring:
  - `BPEL_HOME_DIR`  
The home/root directory of the BPEL server. This is a mandatory parameter.

- DB CONNECTION NAME

JNDI Name for the EBS database connection name specified in the oc4j-ra.xml. This is an optional parameter and if not specified, the database connection name will be retained as eis/DB/OracleConnection. Ensure that whatever connection name you specify here is defined in oc4j-ra.xml.

- BPEL DOMAIN

Name of the BPEL domain to which the processes will be deployed. This is an optional parameter. If you desire multi-domain support, you should have a unique name for each integration. If not specified, all of the processes will be deployed to the default domain and will overwrite the PO BPEL process.

9. Run the following command: `obant -buildfile MscJarOTMBuild.xml -DbpelHome=<BPEL_HOME_DIR> -DnewDbConnName=<DB_CONNECTION_NAME> -Ddeploy=<BPEL_DOMAIN>`

**Note:** Note that when the OBAnt command is run, it creates a directory named `OtmModifiedBpelJarHYPERLINK "http://twiki.ca.oracle.com/bin/edit/Architect/OtmModifiedBpelJar?topicparent=Architect.ArchMscOtmSetup" ?` under the current directory; the new directory stores the modified BPEL jar files.

10. Verify that the processes were successfully deployed to the corresponding BPEL domain by viewing the processes from the BPEL console of the respective domain.
11. Restart the SOA server.

## Setting Up External System and Web Service in Oracle Transportation Management

The following section describes how to set up an external system and web service in Oracle Transportation Management.

**To set up external system and web service in Oracle Transportation Management:**

### **To set up external system and web service in Oracle Transportation Management:**

1. In Oracle Transportation Management, click the Business Process Automation icon, select Communication Management, then select External Systems.
2. Click New.
3. Enter an External System ID: for example BPEL\_FLOW.

4. On the Web Service field, click *n* to create a new web service.
5. On the Web Service page, click *n* to create a new WSDL (web services description language) document.
6. Click Document Detail to display the Document page.
7. Enter a new ID (MSCRECEIVEUPDATES).
8. From the Storage field, select Text.
9. Click Upload to upload your WSDL file for the BPEL server.
10. Click Finished.

### Setting Up an Automatic Agent in Oracle Transportation Management

The following steps describe how to set up an automatic agent in Oracle Transportation Management.

#### To set up an automatic agent in Oracle Transportation Management:

1. Create a new agent named as OR\_UPDATE\_SEND\_TO\_APS.
2. In Oracle Transportation Management, click the Business Process Automation icon, select Agents and Milestones, then select Automation Agent.
3. Click the New button to display the Agent Manager page.
4. On the Agent Manager page, complete the following entries:
  - Agent ID: OR\_UPDATE\_SEND\_TO\_APS
  - Agent Type: Order Release
5. On the Event field, click the *f* icon to display the Agent Events Finder page.
6. In the Agent Event ID field, enter ORDER - DATES MODIFIED then click Search.
7. After the search results appear, click Finish to display the agent event details in the Agent Manager page.
8. In the Restrictions field, select a restriction value such as INTEGRATION or INTERNAL or USER (click the Information icon on the Restrictions field to display the available parameters).
9. Click the Save button located to the right of the Restrictions field.
10. Click the View/Enter Actions button to go the next tab.

11. Click Add Action to display the Agent Action Selection page. Select the following values:
  - Action list: Send Integration.
  - Notify Method: SERVICE
  - External System: Click the *f* (Find) icon, and search for the service id you created in the prior steps.
12. Click Save. The parent window displays the newly added action.
13. Click Finish.

## Setting Up Profile Options in Oracle Advanced Supply Chain Planning

During implementation, you set a value for each user profile option to specify how Oracle Advanced Supply Chain Planning controls access to and processes data for its integration with Oracle Transportation Management.

### Profile Options

You must set a value for profile options followed by the word "required," no default is supplied. Ordinary users can see profile options followed by the word "exposed," only system administrators can see the rest. Further details follow the list, click an item to find them.

MSC: EBS source instance for OTM

MSC: Generate Exceptions in CP

MSC: Generate Notifications for Transportation Updates

MSC: OTM Punchout URL

MSC: OTM Responsibility

MSC: OTM User

MSC: Production Plan for Transportation Updates

### MSC: EBS source instance for OTM

Oracle Advanced Planning and Scheduling (APS) can be run as a separate instance from Oracle E-Business Suite (EBS) source instances. Typically, APS can be integrated with multiple EBS source instances. In Oracle Transportation Management, you can set up multiple domains and each domain is mapped to a single EBS source instance.

However, when EBS, APS, and OTM are integrated, only a single EBS source instance (domain) for the APS-OTM integration is supported. Therefore, you need to enter an

instance code for the profile option *MSC: EBS source instance for OT* (for example, *TST*) to update the data in APS for the source instance that maps to the OTM domain that triggers the BPEL process.

The default value is Null.

### **MSC: Generate Exceptions in CP**

Instructs the BPEL process whether the late or earlier exceptions should be generated in Oracle Collaborative Planning.

#### **Values**

- Yes
- No

The default value is No.

### **MSC: Generate Notifications for Transportation Updates**

Specifies whether the process that passes estimated arrival time updates from Oracle Transportation Management should create workflow notifications.

#### **Values**

- Yes: Create workflow notifications. When set to Yes, the BPEL process uses the values for user and responsibility defined in the profile options *MSC: OTM User* and *MSC: OTM Responsibility* to run the workflow notification.
- No: Do not create workflow notifications.

The default value is Yes.

### **MSC: OTM Punchout URI**

Identifies the URL (for example, <http://otm.oracle.com/>) of the Oracle Transportation Management instance that is providing the updates. Use this URL for drilling down in Oracle Transportation Management to find details about the order that has been rescheduled.

**Note:** Enter a value for this profile option to ensure that the APS workbench and the link in the notification operate correctly.

The default value is Null (no default value).

### **MSC: OTM Responsibility**

Define a default user and responsibility to enable the BPEL process to call the Oracle E-Business Suite workflow notification (in Oracle Transportation Management and Oracle Advanced Supply Chain Planning integration). For example, a default user and

responsibility could be *sjones* (user) and Advanced Supply Chain Planner (responsibility).

The default value is Null (no default value).

### **MSC: OTM User**

Define a default user and responsibility to enable the BPEL process (business process execution language) to call the Oracle E-Business Suite workflow notification in Oracle Transportation Management and Oracle Advanced Supply Chain Planning integration. For example, a default user and responsibility could be *sjones* (user) and Advanced Supply Chain Planner (responsibility).

The default value is Null (no default value).

### **MSC: Production Plan for Transportation Updates**

Specifies the production plans that receive estimated arrival time updates from Oracle Transportation Management.

#### **Values**

- Null: Do not pass updates to any plan.
- All Production Plans: Pass updates to all plans with Production flag selected.
- <specific plan name>: Pass updates only to the plan that is specified.

The default value is Null.

---

## XML Mapping

### Oracle Transportation Management to Oracle E-Business Suite XML Mapping

The following sections describe the XML mapping for Oracle Advanced Planning and Scheduling, Oracle Order Management, Oracle Payables, Oracle Purchasing, and Oracle Shipping Execution.

#### Oracle Advanced Planning and Scheduling XML Mapping

The following table shows the mapping of the referenced XML data between Oracle Advanced Planning and Scheduling and Oracle Transportation Management, whether the data is required or optional, and a brief description.

##### *Purchase Order (PO) and PO Shipment*

Optional/Required	OTM Element	EBS Table.Column	Description
R	N/A	MSC_TRANSPORTATION_UPDATES. ORDER_TYPE,	1 is for PO
R	TransOrderLineGid. Gid.Xid	MSC_TRANSPORTATION_UPDATES. PO_LINE_LOCATION_ID	xid = LINE- <PO_LINE_ID>- SCHED- <LINE_LOCATION_ID>

Optional/Required	OTM Element	EBS Table.Column	Description
R	TransOrderLineGid. Gid.Xid	MSC_TRANSPORTA TION_UPDATES. PO_LINE_ID	xid = LINE- <PO_LINE_ID>- SCHED- <LINE_LOCATION_I D>
R	Release.ReleaseLine. LatestEstimatedArriv alDate	MSC_TRANSPORTA TION_UPDATES. UPDATED_ARRIVA L_DATE	This is the latest estimated arrival date passed from Oracle Transportation Management.

***IR/ISO and IR/ISO Shipment***

Optional/Required	OTM Element	EBS Table.Column	Description
R	Release.ReleaseLine. ReleaseLineGid	MSC_TRANSPORTA TION_UPDATES. WSH_DELIVERY_DE TAIL_ID	ReleaseLineGid =delivery_detail_id
R	Release.ReleaseLine. LatestEstimatedArriv alDate	MSC_TRANSPORTA TION_UPDATES. UPDATED_ARRIVA L_DATE	This is the latest estimated arrival date passed from Oracle Transportation Management.

## Oracle Order Management XML Mapping

### Oracle Order Management to Oracle Transportation Execution XML Mapping

The following table shows the mapping of the referenced XML carrier data between Oracle E-Business Suite and Oracle Transportation Management, whether the data is required or optional, and a brief description. (OTM = Oracle Transportation Management. EBS = Oracle E-Business Suite)

Optional/Required	OTM Element	EBS Table.Column	Description
R	LocationGid.Xid	Ship_From/To location id from the PL/SQL FTE_PROCESS_REQ UESTS. fte_source_line_tab In the following format: Use same domain name (Profile Option OTM: Domain Name) for all different locations. (customer/supplier/ca rrier/org).XID part of GID will be concatenation of three fields to generate a unique combination. For example, for customer site it could be CUS-201-101 where 201 is customer ID and 101 is location_id. For carrier site, it could be CAR-301-401 where 301 is carrier ID and 401 is carrier_site_id. For organization location, it could be ORG-501-601 where 501 is organization ID and 601 is location_id.	Order source location ID
O	SourceAddress. CorporationGid.Xid	ORG-201 (if 201 is the org ID)	Source address ID
O	DestAddress. CorporationGid.Xid	CUS-1091 (if 1091 is the customer ID)	Destination address ID

Optional/Required	OTM Element	EBS Table.Column	Description
O	City	Is queried from the database using the location ID. WSH_LOCATIONS. CITY	City. DataType: A30
O	ProvinceCode	Use the Region Location mapping to see if the state code exists. If not, and if the state length is two, then use that as the state code. If not, then no state code is passed.	A two-character province code. In the United States, ProvinceCode corresponds to a two character state code such as PA. DataType: A2.
O	CountryCode3Gid	WSH_LOCATIONS. COUNTRY has the 2 letter ISO code. For the three letter codes FND_TERRITORIES. ISO_TERRITORY_CODE must be used. FND_TERRITORIES. TERRITORY_CODE maps to WSH_LOCATIONS. COUNTRY. For a given location ID, the three letter country code can be determined by: SELECT t. iso_territory_code from FND_TERRITORIES t, WSH_LOCATIONS l where l.location_id= X and l.country=t. territory_code. The domain is PUBLIC. Same as not specifying a domain.	The three character ISO country code global identifier. Validation: References COUNTRY_CODE table.

Optional/Required	OTM Element	EBS Table.Column	Description
O	PostalCode	WSH_LOCATIONS. POSTAL_CODE	The postal code component of Address. For United States, this is a 3, 5 or 9 character zip code. DataType: A15
O	EstimatedShipDate	Ship_date from PL/SQL records formatted into YYYYMMDDHHMMSS	Estimated ship date. Format: YYYYMMDDHHMMSS
O	EstimatedArrivalDate	Arrival_date from PL/SQL records formatted into YYYYMMDDHHMMSS	Estimated arrival date. Format: YYYYMMDDHHMMSS
O	TimeZoneGid	Obtained using FND_TIMEZONES.get_server_timezone_code. The domain is PUBLIC. Same as not specifying a domain.	The time zone global identifier. Validation: References TIME_ZONE table. This is the Java timezone code
O	ShipUnitCount	1	Hardcoded to 1
O	PackagedItemGid.Xid	Inventory_item_id from PL/SQL records, "inventory_organizational_id" + "-" + "inventory_item_id" (example: 207-149).	Packaged item ID
O	WeightValue. VolumeValue	Weight/Volume from PL/SQL records	Weight and Volume values

Optional/Required	OTM Element	EBS Table.Column	Description
O	WeightUOMGid.Xid, VolumeUOMGid.Xid	Check Attribute15 of descriptive flex field for the UOM in the PL/SQL Record. If there is a value, then use that; otherwise, use the uom_code. The domain for the UOM is PUBLIC. Same as not specifying a domain.	Weight and Volume UOM ID
O	Length/Width/Height and UOMs	Queried using inventory_item_id. Check Attribute15 of descriptive flex field for the UOM in the PL/SQL Record. If there is a value, then use that; otherwise, use the uom_code. The domain for the UOM is PUBLIC. Same as not specifying a domain.	Length, width, height, and UOMs
O	PaymentMethodCode	Freight_terms_code from PL/SQL records. The domain is PUBLIC. Same as not specifying a domain.	Payment method code.
O	TransportModeGid	Same as mode of transport code. Mode_of_transport from PL/SQL records.	Mode of transportation Global ID
O	ServiceProviderGid	Same as carrier ID. Carrier_id from PL/SQL records.	Service provider Global ID

Optional/Required	OTM Element	EBS Table.Column	Description
O	RateServiceGid	Same as service_level_code. From service_level from PL/SQL records.	Service rate Global ID
O	RIQRequestType	For CHOOSE SHIP METHODS: All Options  For GET FREIGHT RATES: LowestCost.	Delivery Request. Validation: (LowestCost, FastestTransit, AllOptions). Default: LowestCost.
O	Perspective	For CHOOSE SHIP METHODS: B  For GET FREIGHT RATES: B	Shipment Perspective. Used to ensure that the order and shipment data shown to the end user makes sense from that users perspective or point of reference. Possible values are B = Buy Side, and S = Sell Side. For the RIQQuery element, a value of 'A' can be used to query for both Buy Side and Sell Side.
O	UseRIQRoute	For CHOOSE SHIP METHODS: N  For GET FREIGHT RATES: N	Y, N. Specifies whether to use the RIQ Route functionality, or use the RIQ Rate behavior. Default is N.
O	UserName, Password	From the profile options.  The OTM domain password is moved from the FND profiles to FND Vault.	

## Oracle Payables XML Mapping

### API Invoice Interface XML Mapping

The following table shows the mapping of the required referenced data between Oracle E-Business Suite and Oracle Transportation Management and a brief description of each. (OTM = Oracle Transportation Management. EBS = Oracle E-Business Suite)

Target AP Invoices Interface	Source OTM / BPEL AP Integration Usage
exchangeRateType	In BPEL set to "CORPORATE."
invoiceAmount	Map from OTM Voucher AmountToPay
invoiceCurrencyCode	ISO standard OTM GlobalCurrencyCode
invoiceDate	Map to InvoiceDate from voucher. Supplier's invoice date This date is used to drive Accounting Date/GL Date.
invoiceId	Call AP to retrieve sequence, and then apply to header and lines.
invoiceNum	Concatenated field InvoiceNum plus VoucherGid AP Invoice Number <= 50 characters. Must be a unique number for the supplier. Carrier Invoice Num = "JBHT-1002322-1" Voucher Gid = "EBS.12345678." Invoice number will be a concatenated field of CarrierInvoiceNum plus VoucherGID = "JBHT-1002322-1 EBS.2345678"
invoiceTypeLookupCode	BPEL transformation. Positive amount voucher = "STANDARD," Negative amounts on voucher = "CREDIT."
source	Source = "TRANSPORTATION MANAGEMENT."
vendorNum	Map to ServiceProvider Alias Qualf = "VENDOR_NUM."

Target AP Invoices Interface	Source OTM / BPEL AP Integration Usage
vendorSiteCode	Map from SeerviceProvider Alias Qualf = "VENDOR_SITE_CODE."
amount	Represents the amount for this invoice line. One line per invoice in delivered integration. "CREDIT" = negative "STANDARD" = positive.
lineTypeLookupCode	BPEL set to "FREIGHT"
DistCodeConcatenated	BPEL conditional logic in mapped to location reference number qualifier "ACCOUNT_NUMBER" from the source location or if not available on the source location the value is taken from "ACCOUNT_NUMBER" on the service provider location.

### APIInvoices Interface Sample XML

```

<PushToEBS_insert_InputVariable>
<part name="ApInvoicesInterfaceCollection" >
<ApInvoicesInterfaceCollection>
<ApInvoicesInterface>
<description>-002647*GUEST.02420*</description>
<exchangeRateType>CORPORATE</exchangeRateType>
<invoiceAmount>1300.0</invoiceAmount>
<invoiceCurrencyCode>USD</invoiceCurrencyCode>
<invoiceDate>2006-04-03T08:00:00</invoiceDate>
<invoiceId>46836</invoiceId>
<invoiceNum>ZIPPY-000004|GUEST.20060402-0001</invoiceNum>
<invoiceTypeLookupCode>STANDARD</invoiceTypeLookupCode>
<source>TRANSPORTATION MANAGEMENT</source>
<vendorSiteCode>ZIPPY</vendorSiteCode>
<apInvoiceLinesInterfaceCollection>
<ApInvoiceLinesInterface>
<amount>1300.0</amount>
<distCodeConcatenated>01-000-2210-0000-000</distCodeConcatenated>
<invoiceLineId>77910</invoiceLineId>
<lineTypeLookupCode>FREIGHT</lineTypeLookupCode>
</ApInvoiceLinesInterface>
</apInvoiceLinesInterfaceCollection>
</ApInvoicesInterface>
</ApInvoicesInterfaceCollection>
</part>
</PushToEBS_insert_InputVariable>

```

## Oracle Purchasing XML Mapping

### Purchasing Fields to Order Base XML Mapping

**Warning:** You must ensure that for each address in Oracle E-Business Suite, the Country Code is defined. An address passed to Oracle Transportation Management without a Country Code will fail.

Required/Optional	OTM Element	EBS Table.Column	Description
O	TransOrderHeader. TransOrderGid.Gid. DomainName	Profile Option: OTM_DOMAIN_NAME (OTM: Domain Name)	
O	TransOrderHeader. TransOrderGid.Gid. Xid	Concatenation: In the case of a std PO:PO- <PO_HEADERS_ALL .po_header_id>  In the case of a blanket release:PO- <PO_HEADERS_ALL .po_header_id>-REL- <PO_RELEASES_ALL .po_release_id>	Standard PO:PO- Blanket Release:PO- REL-  SPO: PO- 12341Release: PO- 12345-REL-1
O	TransOrderHeader. OrderTypeGid.Gid. DomainName	Profile Option: OTM_DOMAIN_NAME ME	OTM: Domain Name profile option
O	TransOrderHeader. OrderTypeGid.Gid. Xid	Constant: PURCHASE_ORDER	PURCHASE_ORDER

Required/Optional	OTM Element	EBS Table.Column	Description
O	TransOrderHeader. OrderRefNum. OrderRefNumQualifi erGid.Gid.Xid	Constant: PO	Order refnum qualifiers and values are used to send reference information, such as the EBS document number, supplier, operating unit, and so on.  PO
O	TransOrderHeader. OrderRefNum. OrderRefNumValue	PO_HEADERS_ALL. segment1	PO Number
O	TransOrderHeader. OrderRefNum. OrderRefNumQualifi erGid.Gid.Xid	Constant: RELEASE_NUMBER	RELEASE_NUMBER
O	TransOrderHeader. OrderRefNum. OrderRefNumValue	PO_RELEASES_ALL. release_num	PO Release Number
O	TransOrderHeader. OrderRefNum. OrderRefNumQualifi erGid.Gid.Xid	Constant: SELL_TOP	SELL_TO
O	TransOrderHeader. OrderRefNum. OrderRefNumValue	HR_LOCATIONS_A LL.location_code	Operating Unit Name
O	TransOrderHeader. OrderRefNum. OrderRefNumQualifi erGid.Gid.Xid	Constant: SUPPLIER	SUPPLIER
O	TransOrderHeader. OrderRefNum. OrderRefNumValue	PO_VENDORS. vendor_name	Supplier Name

Required/Optional	OTM Element	EBS Table.Column	Description
O	TransOrderHeader. OrderRefNum. OrderRefNumQualifi erGid.Gid.Xid	Constant: SUPPLIER_SITE	
O	TransOrderHeader. OrderRefNum. OrderRefNumValue	PO_VENDOR_SITES _ALL. vendor_site_code	Supplier Site
O	TransOrderHeader. OrderRefNum. OrderRefNumQualifi erGid.Gid.Xid	Constant: BILL_TO	BILL_TO
O	TransOrderHeader. OrderRefNum. OrderRefNumValue	HR_LOCATIONS_A LL.location_code	Bill To Site (Inventory Org)
O	TransOrderHeader. TransactionCode	Constant: IU	I or U (Insert or Update)
O	TransOrderHeader. CommercialTerms. PaymentMethodCode	If PO_HEADERS_ALL. shipping_control = 'BUYER':Constant: COLOtherwise: Constant: SUP	Transportation Arranged By  COL . PPD (Codes correspond to Freight Collect or Freight Prepaid)
O	TransOrderHeader. InvolvedParty. InvolvedPartyQualifi erGid.Gid.Xid	Constant: SUPPLIER	SUPPLIER
O	TransOrderHeader. InvolvedParty. LocationRef. LocationGid.Gid. DomainName	Profile Option: OTM_DOMAIN_NA ME (OTM: Domain Name)	OTM: Domain Name profile option

Required/Optional	OTM Element	EBS Table.Column	Description
O	TransOrderHeader. InvolvedParty. LocationRef. LocationGid.Gid.Xid	Concatenation:SUP- <PO_HEADERS_ALL .vendor_id>  <PO_HEADERS_ALL .vendor_site_id>	SUP <SupplierID>- <Site ID>
O	TransOrderHeader. InvolvedParty. Contact.ContactGid. Gid.DomainName	Profile Option: OTM_DOMAIN_NA ME (OTM: Domain Name)	OTM: Domain Name profile option
O	TransOrderHeader. InvolvedParty. Contact.ContactGid. Gid.Xid	In order of preference:  1. PO_VENDOR_CONT ACTS.email_address  2. Concatenation: PO_VENDOR_CONT ACTS.area_code PO_VENDOR_CONT ACTS.phone_number  3. Concatenation: PO_VENDOR_CONT ACTS.first_name PO_VENDOR_CONT ACTS.last_name	Supplier contact ID (mapped to the email address, phone number or name in that order)
O	Location.Corporation. CorporationName	Concatenation:  SUP- <PO_HEADERS_AL. vendor_id>	SUP-<Vendor ID>
O	Location. LocationName	PO_VENDOR_SITES _ALL. vendor_site_code	Supplier Site Name  SAN JOSE-ERS
O	Location. LocatioRefNum. Qualifier	Constant: EBS_NAME	EBS_NAME

Required/Optional	OTM Element	EBS Table.Column	Description
O	Location. LocatioRefNum. Value	PO_VENDOR_SITES _ALL. vendor_site_code	Supplier Site Name
O	LocationGid.Gid.Xid	Concatenation:  SUP- <PO_HEADERS_AL. vendor_id>- <PO_HEADERS_ALL .vendor_site_id>	SUP <Supplier ID>- <Site ID>
O	Location. LocationRole	Constant: SHIPFROM-SHIPTO	SHIPFROM >SHIPTO
O	Location.Address. AddressLine1 to AddressLine3	Concatenation: PO_VENDOR_SITES _ALL.address_line1 PO_VENDOR_SITES _ALL.address_line2 PO_VENDOR_SITES _ALL.address_line3	Supplier Site Address Lines
O	Location.Address. City	PO_VENDOR_SITES _ALL.city	Supplier Site Address City
O	Location.Address. CountryCode3	PO_VENDOR_SITES _ALL.country	Supplier Site Address Country
O	Location.Address. PostalCode	PO_VENDOR_SITE, S_ALL.zip	Supplier Site Address Postal Code

Required/Optional	OTM Element	EBS Table.Column	Description
O	Location.Address. Province	In order of preference:  1. PO_VENDOR_SITES _ALL.state  2. PO_VENDOR_SITES _ALL.province  3. PO_VENDOR_SITES _ALL.county	Supplier Site Address Province
O	Location.Address. ProvinceCode	In order of preference:  1. PO_VENDOR_SITES _ALL.state  2. PO_VENDOR_SITES _ALL. provincePO_VENDO R_SITES_ALL.county	Supplier Site Address Province Code
O	Contact.ContactGid. Gid.DomainName	Profile Option: OTM_DOMAIN_NAME (OTM: Domain Name)	OTM: Domain Name profile option

Required/Optional	OTM Element	EBS Table.Column	Description
O	Contact.ContactGid. Gid.Xid	In order of preference:  1. PO_VENDOR_CONT ACTS.email_address  2. Concatenation: PO_VENDOR_CONT ACTS.area_code PO_VENDOR_CONT ACTS.phone_number  3. Concatenatio: PO_VENDOR_CONT ACTS.first_name PO_VENDOR_CONT ACTS.last_name	Supplier contact ID (mapped to the email address, phone number or name in that order)
O	Contact.FirstName	PO_VENDOR_CONT ACTS.first_name	Supplier Contact First Name
O	Contact.LastName	PO_VENDOR_CONT ACTS.last_name	Supplier Contact Last Name
O	Contact.Phone1	Concatenation: PO_VENDOR_CONT ACTS.area_code PO_VENDOR_CONT ACTS.phone_number	Supplier Contact Phone Number
O	Contact. EmailAddress	PO_VENDOR_CONT ACTS.email_address	Supplier Contact Email ID
O	Contact.Fax	Concatenation: PO_VENDOR_CONT ACTS.fax_area_code PO_VENDOR_CONT ACTS.fax	Supplier contact fax number

Required/Optional	OTM Element	EBS Table.Column	Description
O	Contact. CommunicationMethod	Constant. In order of preference: 1. EMAIL 2. FAX 3. MANUAL	Email/Fax/Manual (Phone)
O	TransOrderHeader. InvolvedParty. InvolvedPartyQualifierGid.Gid.Xid	Constant: SELL_TO	This involved party is the purchasing operating unit  SELL_TO
O	TransOrderHeader. InvolvedParty. LocationRef. LocationGid.Gid. DomainName	Profile Option: OTM_DOMAIN_NAME (OTM: Domain Name)	OTM: Domain Name profile option
O	TransOrderHeader. InvolvedParty. LocationRef. LocationGid.Gid.Xid	Concatenation: ORG- <PO_HEADERS_ALL.org_id>- <HR_LOCATIONS_ALL.location_id>	ORG-<Org ID>-<Location ID>
O	TransOrderHeader. InvolvedParty. Contact.ContactGid.Gid.DomainName	Profile Option: OTM_DOMAIN_NAME (OTM: Domain Name)	OTM: Domain Name profile option

Required/Optional	OTM Element	EBS Table.Column	Description
O	TransOrderHeader. InvolvedParty. Contact.ContactGid. Gid.Xid	In order of preference:  1. PER_ALL_PEOPLE_F .email_address  2. PER_PHONES. phone_number  3. Concatenation: PER_ALL_PEOPLE_F .first_name PER_ALL_PEOPLE_F .last_name	Buyer contact ID (mapped to the email address, phone number or name in that order)
O	Location. CorporationXID	Concatenation:  ORG- <PO_HEADERS_ALL .org_id>	ORG-<Operating Unit ID>  ORG-204
O	Location. LocatioRefNum. Qualifier	Constant: EBS_NAME	EBS_NAME
O	Location. LocatioRefNum. Value	HR_LOCATIONS_A LL.location_code	Operating Unit Default Location Name
O	Location. LocationGid.Gid.Xid	Concatenation:  ORG- <PO_HEADERS_ALL .org_id>- <HR_LOCATIONS_A LL.location_id>	ORG-<Org ID>- <Location ID>  ORG-204-4848
O	Location. LocationRole	Constant: SHIPFROM-SHIPTO	SHIPFROM->SHIPTO

Required/Optional	OTM Element	EBS Table.Column	Description
O	Location.Address. AddressLine1 to AddressLine3	Concatenation:  HR_LOCATIONS_A LL.address_line_1 HR_LOCATIONS_A LL.address_line_2 HR_LOCATIONS_A LL.address_line_3	OU Default Location Address Lines
O	Location.Address. City	HR_LOCATIONS_A LL.town_or_city	OU Default Location Address City
O	Location.Address. CountryCode3	FND_TERRITORIES. iso_territory_code	OU Default Location Address Country
O	Location.Address. PostalCode	HR_LOCATIONS_A LL.postal_code	OU Default Location Address Postal code
O	TransOrderHeader. InvolvedParty. LocationRef.Location. Address.Province	Either HR_LOCATIONS_A LL.region_1  or  HR_LOCATIONS_A LL.region_2, depending on address style.	OU Default Location Address Province
O	Location.Address. ProvinceCode	Either HR_LOCATIONS_A LL.region_1  or  HR_LOCATIONS_A LL.region_2, depending on address style.	OU Default Location Address Province Code
O	Contact.ContactGid. Gid.DomainName	OTM: Domain Name profile option	OTM: Domain Name profile option

Required/Optional	OTM Element	EBS Table.Column	Description
O	Contact.ContactGid. Gid.Xid	In order of preference:  1. PER_ALL_PEOPLE_F .email_address  2. PER_PHONES. phone_number  3. Concatenation: PER_ALL_PEOPLE_F .first_name PER_ALL_PEOPLE_F .last_name	Supplier contact ID (mapped to the email address, phone number or name in that order)
O	Contact.FirstName	PER_ALL_PEOPLE_F .first_name	Buyer Contact First Name
O	Contact.LastName	PER_ALL_PEOPLE_F .last_name	Buyer Contact Last Name
O	Contact.Phone1	PER_PHONES. phone_number	Buyer Contact Phone Number
O	Contact. EmailAddress	PER_ALL_PEOPLE_F .email_address	Buyer Contact Email ID
O	Contact.Fax	PER_PHONES. phone_number	Buyer Contact Fax Number
O	Contact. CommunicationMethod	Constant. In order of preference:  1. EMAIL  2. FAX  3. MANUAL	Email/Fax/Manual (Phone)
O	TransOrderHeader. InvolvedParty. InvolvedPartyQualifi erGid.Gid.Xid	Constant: BILL-TO	BILL-TO

Required/Optional	OTM Element	EBS Table.Column	Description
O	TransOrderHeader. InvolvedParty. InvolvedPartyLocationRef.LocationRef. LocationGid.Gid. DomainName	Profile Option: OTM_DOMAIN_NAME (OTM: Domain Name)	OTM: Domain Name profile option
O	TransOrderHeader. InvolvedParty. InvolvedPartyLocationRef.LocationRef. LocationGid.Gid.Xid	Concatenation:ORG-<PO_HEADERS_ALL.org_id>-<PO_HEADERS_ALL.bill_to_location_id>	ORG-<Org ID>-<Bill to Location ID>
O	TransOrderHeader. InvolvedParty. Contact.ContactGid.Gid.DomainName	Profile Option: OTM_DOMAIN_NAME (OTM: Domain Name)	OTM: Domain Name profile option
O	TransOrderHeader. InvolvedParty. Contact.ContactGid.Gid.Xid	In order of preference: 1. PER_ALL_PEOPLE_F.email_address 2. PER_PHONES.phone_number 3. Concatenation: PER_ALL_PEOPLE_F.first_name PER_ALL_PEOPLE_F.last_name	Buyer contact ID (mapped to the email address, phone number or name in that order)
O	Location. LocationGid.Gid. DomainName	Profile Option: OTM_DOMAIN_NAME (OTM: Domain Name)	OTM: Domain Name profile option
O	Location. LocationGid.Gid.Xid	Concatenation: ORG-<PO_HEADERS_ALL.org_id>-<PO_HEADERS_ALL.bill_to_location_id>	ORG-<Org ID>-<Bill to Location ID>

Required/Optional	OTM Element	EBS Table.Column	Description
O	Location. CorperationXID	Concatenation:ORG- <PO_HEADERS_ALL .org_id>	ORG-<Org ID>
O	Location. LocatioRefNum. Qualifier	Constant: EBS_NAME	EBS_NAME
O	Location. LocatioRefNum. Value	HR_LOCATIONS_A LL.location_code	Bill To Location Name
O	Location.Address. AddressLine1 to AddressLine3	Concatenation: HR_LOCATIONS_A LL.address_line_1 HR_LOCATIONS_A LL.address_line_2 HR_LOCATIONS_A LL.address_line_3	Bill To Location Address Lines
O	Location.Address. City	HR_LOCATIONS_A LL.town_or_city	Bill To Location Address City
O	Location.Address. CountryCode3	FND_TERRITORIES. iso_territory_code	Bill To Location Address Country
O	Location.Address. PostalCode	HR_LOCATIONS_A LL.postal_code	Bill To Location Address Postal Code
O	Location.Address. Province	Either HR_LOCATIONS_A LL.region_1  or  HR_LOCATIONS_A LL.region_2, depending on address style.	Bill To Location Address Province

Required/Optional	OTM Element	EBS Table.Column	Description
O	Location.Address. ProvinceCode	Either HR_LOCATIONS_A LL.region_1  or  HR_LOCATIONS_A LL.region_2, depending on address style.	Bill To Location Address Province Code
O	Location.Contact. ContactGid	In order of preference:  1. PER_ALL_PEOPLE_F .email_address  2. PER_PHONES. phone_number  3. Concatenation: PER_ALL_PEOPLE_F .first_name PER_ALL_PEOPLE_F .last_name	
O	Contact.ContactGid. Gid.DomainName	Profile Option: OTM_DOMAIN_NAME (OTM: Domain Name)	OTM: Domain Name profile option
O	Contact.ContactGid. Gid.Xid	In order of preference:  1. PER_ALL_PEOPLE_F .email_address  2. PER_PHONES. phone_number  3. Concatenation: PER_ALL_PEOPLE_F .first_name PER_ALL_PEOPLE_F .last_name	Buyer contact ID (mapped to the email address, phone number or name in that order)

Required/Optional	OTM Element	EBS Table.Column	Description
O	Contact.FirstName	PER_ALL_PEOPLE_F .first_name	Buyer Contact First Name
O	Contact.LastName	PER_ALL_PEOPLE_F .last_name	Buyer Contact Last Name
O	Contact.Phone1	PER_PHONES. phone_number	Buyer Contact Phone Number
O	Contact. EmailAddress	PER_ALL_PEOPLE_F .email_address	Buyer Contact Email ID
O	Contact.Fax	PER_PHONES. phone_number	Buyer Contact Fax Number
O	Contact. CommunicationMethod	Constant. In order of preference:  1. EMAIL  2. FAX  3. MANUAL	Email/Fax/Manual (Phone)
O	TransOrderLineDetail. TransactionCode	Constant: IU	IU (Insert/Update)
O	TransOrderLineDetail. TransOrderLineGid. Gid.Xid	Concatenation:LINE-<PO_LINES_ALL. po_line_id>-SCHED-<PO_LINE_LOCATIONS_ALL. line_location_id>	LINE-<Line ID>-SCHED-<Schedule ID>
O	TransOrderLineDetail. TransOrderLineGid. Gid.DomainName	Profile Option: OTM_DOMAIN_NAME (OTM: Domain Name)	OTM: Domain Name profile option

Required/Optional	OTM Element	EBS Table.Column	Description
O	TransOrderLineDetail .ItemQuantity. ItemTag1	Concatenation: LINE/SCHEDUL: <PO_LINES_ALL. line_num>/<PO_LINE _LOCATIONS_ALL. shipment_num>	LINE->SCHEDULE: <Line Number>- <Schedule Number>  These tags are displayed in the Ready to Ship screen in OTM.
O	TransOrderLineDetail .ItemQuantity. ItemTag2	Concatenation: SUPPLIER ITEM: <PO_LINES_ALL. vendor_product_num >	SUPPLIER ITEM: <Supplier Item>
O	TransOrderLineDetail .ItemQuantity. ItemTag3	Concatenation: REV: <PO_LINES_ALL. item_revision>	REV: <Item Revision>
O	TransOrderLineDetail .ItemQuantity. PackagedItemCount	PO_LINE_LOCATIO NS_ALL.quantity	Shipment or Schedule Quantity  Quantity changes in Purchasing will not affect released or shipped quantities in OTM – only the order base line quantity.

Required/Optional	OTM Element	EBS Table.Column	Description
O	TransOrderLineDetail .PackagedItemRef. PackagedItemGid. XID	Concatenation:  If UOM code is same in EBS and OTM: <MTL_SYSTEM_ITE MS_KFV. concatenated_segmen ts>_<MTL_UNITS_O F_MEASURE. uom_code>  Otherwise: <MTL_SYSTEM_ITE MS_KFV. concatenated_segmen ts>_<MTL_UNITS_O F_MEASURE. attribute15 >	<EBS Item ID>_<UOM> For one time items:<Item Description>_<UOM>
O	TransOrderLineDetail .PackagedItemRef. ItemGid.XID	Concatenation:  If UOM code is same in EBS and OTM: <MTL_SYSTEM_ITE MS_KFV. concatenated_segmen ts>_<MTL_UNITS_O F_MEASURE. uom_code>  Otherwise: <MTL_SYSTEM_ITE MS_KFV. concatenated_segmen ts>_<MTL_UNITS_O F_MEASURE. attribute15 >	<EBS Item ID>_<UOM> For one time items:<Item Description>_<UOM>
O	TransOrderLineDetail .ItemQuantity. DeclaredValue. MonetaryAmount	Calculated field: PO_LINE_LOCATIO NS_ALL. price_override * CIEL (PO_LINE_LOCATIO NS_ALL.quantity)	Line Amount  Does not include tax

Required/Optional	OTM Element	EBS Table.Column	Description
O	TransOrderLineDetail .DeclaredValue. FinancialAmount. GlobalCurrencyCode	PO_HEADERS_ALL. currency_code	PO Currency
O	TransOrderLineDetail .TransOrderLine. ItemAttributes. ItemFeatureQualGid. Gid.DomainName	Profile Option: OTM_DOMAIN_NA ME (OTM: Domain Name)	OTM: Domain Name profile option  Item Feature Qualifiers are used to display additional item information.
O	TransOrderLineDetail .TransOrderLine. ItemAttributes. ItemFeatureQualGid. Gid.Xid	Constant: DESCRIPTION	DESCRIPTION
O	TransOrderLineDetail .TransOrderLine. ItemAttributes. ItemFeatureValue	PO_LINES_ALL. item_description	PO Line Description
O	TransOrderLineDetail .TransOrderLine. ItemAttributes. ItemFeatureQualGid. Gid.DomainName	Profile Option: OTM_DOMAIN_NA ME (OTM: Domain Name)	OTM: Domain Name profile option
O	TransOrderLineDetail .TransOrderLine. ItemAttributes. ItemFeatureQualGid. Gid.Xid	Constant: REVISION	REVISION
O	TransOrderLineDetail .TransOrderLine. ItemAttributes. ItemFeatureValue	PO_LINES_ALL. item_revision	Item Revision

Required/Optional	OTM Element	EBS Table.Column	Description
O	TransOrderLineDetail .TransOrderLine. ItemAttributes. ItemFeatureQualGid. Gid.DomainName	Profile Option: OTM_DOMAIN_NA ME (OTM: Domain Name)	OTM: Domain Name profile option
O	TransOrderLineDetail .TransOrderLine. ItemAttributes. ItemFeatureQualGid. Gid.Xid	Constant: SUPPLIER_ITEM	SUPPLIER_ITEM
O	TransOrderLineDetail .TransOrderLine. ItemAttributes. ItemFeatureValue	PO_LINES_ALL. vendor_product_num	Supplier Item
O	TransOrderLineDetail .TransOrderLine. ItemAttributes. ItemFeatureQualGid. Gid.DomainName	Profile Option: OTM_DOMAIN_NA ME (OTM: Domain Name)	OTM: Domain Name profile option
O	TransOrderLineDetail .TransOrderLine. ItemAttributes. ItemFeatureQualGid. Gid.Xid	Constant: SUPPLIER_CONFIG_ ID	SUPPLIER_CONFIG_ ID
O	TransOrderLineDetail .TransOrderLine. ItemAttributes. ItemFeatureValue	PO_LINES_ALL. supplier_ref_number	Supplier Config ID  This is the configuration ID got from the supplier. For example, a user configured desktop purchased from Dell Web site via punch- out.

Required/Optional	OTM Element	EBS Table.Column	Description
O	TransOrderLineDetail .TransOrderLine. TimeWindow. LateDeliveryDate	Calculated field. In order of preference:  1. PO_LINE_LOCATIO NS_ALL. promised_date + PO_LINE_LOCATIO NS_ALL. days_late_receipt_alle wed  2. PO_LINE_LOCATIO NS_ALL. need_by_date + PO_LINE_LOCATIO NS_ALL. days_late_receipt_alle wed	Promised or Need-by Date + Days late receiving tolerance on PO  Promised Date if it exists, else Need-By Date
O	TransOrderLineDetail .TransOrderLine. TimeWindow. EarlyDeliveryDate	Calculated field. In order of preference:  1. PO_LINE_LOCATIO NS_ALL. promised_date - PO_LINE_LOCATIO NS_ALL. days_early_receipt_alle lowed  2. PO_LINE_LOCATIO NS_ALL. need_by_date - PO_LINE_LOCATIO NS_ALL. days_early_receipt_alle lowed	Promised or Need-by Date - Days early receiving tolerance on PO  Promised Date if it exists, or else the Need-By Date
O	TransOrderlineDetail. TransOrderLine. InvolvedParty. InvolvedPartyQualifierGid.Gid.Xid	Constant: SHIP TO	SHIP TO

Required/Optional	OTM Element	EBS Table.Column	Description
O	TransOrderHeader. InvolvedParty. InvolvedPartyLocationRef.LocationRef. LocationGid.Gid. DomainName	Profile Option: OTM_DOMAIN_NA ME (OTM: Domain Name)	OTM: Domain Name profile option
O	TransOrderHeader. InvolvedParty. InvolvedPartyLocationRef.LocationRef. LocationGid.Gid.Xid	Concatenation:  ORG- <PO_HEADERS_ALL .org_id>- <PO_HEADERS_ALL .bill_to_location_id>	ORG-<Org ID>-<Bill to Location ID>
O	TransOrderHeader. InvolvedParty. Contact.ContactGid. Gid.DomainName	Profile Option: OTM_DOMAIN_NA ME (OTM: Domain Name)	OTM: Domain Name profile option
O	TransOrderHeader. InvolvedParty. Contact.ContactGid. Gid.Xid	In order of preference:  1. PER_ALL_PEOPLE_F .email_address  2. PER_PHONES. phone_number  3. Concatenation: PER_ALL_PEOPLE_F .first_name PER_ALL_PEOPLE_F .last_name	Requestor contact ID – This is mapped to the email address, phone number or name in that order  Requestor, if it exists, or else the buyer

Required/Optional	OTM Element	EBS Table.Column	Description
O	Location. LocationGid.Gid.Xid	Concatenation. If internal location: ORG- <PO_LINE_LOCATI ONS_ALL. ship_to_organization _id>- <PO_LINE_LOCATI ONS_ALL. ship_to_location_id>  If drop-ship:CUS-000- <PO_LINE_LOCATI ONS_ALL. ship_to_location_id>	ORG-<Org ID>-<Ship- To Location ID> or CUS-000-<Ship-To Location ID>
O	Location. LocationRole	Constant: SHIPFROM-SHIPTO	SHIPFROM-SHIPTO
O	Location. CorperationXID	Concatenation. If internal location: ORG- <PO_LINE_LOCATI ONS_ALL. ship_to_organization _id>  If drop-ship:CUS-000	ORG-<Org ID> or CUS-000  Use 'CUS-000' for drop ship orders.
O	Location. LocatioRefNum. Qualifier	Constant: EBS_NAME	EBS_NAME
O	Location. LocatioRefNum. Value	HR_LOCATIONS_A LL.location_code	Ship-to Location Name
O	Location.Address. AddressLine1 to AddressLine3	Concatenation:  HR_LOCATIONS_A LL.address_line_1 HR_LOCATIONS_A LL.address_line_2 HR_LOCATIONS_A LL.address_line_3	Ship-to Location Address Lines

Required/Optional	OTM Element	EBS Table.Column	Description
O	Location.Address. City	HR_LOCATIONS_A LL.town_or_city	Ship-to Location Address City
O	Location.Address. CountryCode3	FND_TERRITORIES. iso_territory_code	Ship-to Location Address Country
O	Location.Address. PostalCode	HR_LOCATIONS_A LL.postal_code	Ship-to Location Address Postal Code
O	Location.Address. Province	Either HR_LOCATIONS_A LL.region_1  or  HR_LOCATIONS_A LL.region_2, depending on address style.	Ship-to Location Address Province
O	Location.Address. ProvinceCode	Either HR_LOCATIONS_A LL.region_1  or  HR_LOCATIONS_A LL.region_2, depending on address style.	Ship-to Location Address Province Code
O	Contact.ContactGid. Gid.DomainName	Profile Option: OTM_DOMAIN_NAME (OTM: Domain Name)	OTM: Domain Name profile option

Required/Optional	OTM Element	EBS Table.Column	Description
O	Contact.ContactGid. Gid.Xid	In order of preference:  1. PER_ALL_PEOPLE_F .email_address  2. PER_PHONES. phone_number  3. Concatenation: PER_ALL_PEOPLE_F .first_name PER_ALL_PEOPLE_F .last_name	Supplier contact ID (mapped to the email address, phone number or name in that order)
O	Contact.FirstName	PER_ALL_PEOPLE_F .first_name	Requestor Contact First Name
O	Contact.LastName	PER_ALL_PEOPLE_F .last_name	Requestor Contact Last Name
O	Contact.Phone1	PER_PHONES. phone_number	Requestor Contact Phone Number
O	Contact. EmailAddress	PER_ALL_PEOPLE_F .email_address	Requestor Contact Email ID
O	Contact.Fax	PER_PHONES. phone_number	Requestor Contact Fax Number
O	Contact. CommunicationMethod	Constant. In order of preference:  1. EMAIL  2. FAX  3. MANUAL	Email/Fax/Manual (Phone)
O	TransOrderLineDetail .TransOrderLine. ShipFromLocationRef .LocationRef. LocationGid.Gid. DomainName	Profile Option: OTM_DOMAIN_NAME (OTM: Domain Name)	OTM: Domain Name profile option

Required/Optional	OTM Element	EBS Table.Column	Description
O	TransOrderLineDetail .TransOrderLine. ShipFromLocationRef .LocationRef. LocationGid.Gid.Xid	Concatenation:SUP- <PO_HEADERS_ALL .vendor_id- <PO_HEADERS_ALL .vendor_site_id>	SUP-<Supplier ID>_<Site ID>  Note: Although the supplier site need not be the ship-from location, this is a required attribute in OTM and therefore is mapped to supplier site. This can however be updated with the true ship- from location downstream in OTM. EBS PO does not currently carry the ship-from location.
O	TransOrderLineDetail .TransOrderLine. ShipToLocationRef. LocationRef. LocationGid.Gid. DomainName	Profile Option: OTM_DOMAIN_NA ME (OTM: Domain Name)	OTM: Domain Name
O	TransOrderLineDetail .TransOrderLine. ShipToLocationRef. LocationRef. LocationGid.Gid.Xid	Concatenation. If internal location: ORG- <PO_LINE_LOCATI ONS_ALL. ship_to_organization _id>- <PO_LINE_LOCATI ONS_ALL. ship_to_location_id>  If drop-ship:CUS-000- <PO_LINE_LOCATI ONS_ALL. ship_to_location_id>	ORG-<Ship-To Org ID>_<Ship-To Location ID> or CUS- 000-<Location ID>

## Oracle Shipping Execution XML Mapping

### Location XML Transaction - Carrier

See Concurrent Programs, page 3-42 for details, including XML mapping, of the Location XML transaction for carriers.

### Release XML Transaction - Deliveries

The following table shows the XML mapping for the Release XML transaction. Elements that are not mapped are not shown. Item, Customer, Customer Site, and Organization reference data is sent using the Order Release Message. (OTM = Oracle Transportation Management. EBS = Oracle E-Business Suite.)

Required/Optional	OTM Attribute	EBS Table.Column	Description
R	ReleaseGid	Delivery Based: WSH_NEW_DELIVERIES.DELIVERY_ID  Batch Based: WSH_TMS_SUB_BATCHES.NAME	Release Global ID
R	TransactionCode	"I" for creation, RC for update, and D for delete.	Internally sent to OTM as 'RC' for both Update/Create
O	ReleaseHeader. ReleaseName	Delivery Based: WSH_NEW_DELIVERIES.NAME  Batch Based: WSH_TMS_SUB_BATCHES.NAME	Release name
O	ReleaseHeader. ReleaseMethodGid	Delivery Based: PREPACK	EBS dictates the contents of the Ship units
O	ReleaseHeader. CommercialTerms		Commercial terms

Required/Optional	OTM Attribute	EBS Table.Column	Description
O	ReleaseHeader. CommercialTerms. PaymentMethodCodeGid	Delivery Based: WSH_NEW_DELIVERIES. FREIGHT_TERMS_CODE  Batch Based: WSH_TMS_SUB_BATCHES. FREIGHT_TERMS_CODE	Payment method code global ID
O	ReleaseHeader. CommercialTerms. IncoTermGid	Delivery Based: WSH_NEW_DELIVERIES.FOB_CODE  Batch Based: WSH_TMS_SUB_BATCHES.FOB_CODE	FOB code
O	ReleaseHeader. TimeWindowEmphasisGid	BOTH	Time window emphasis specification
O	ReleaseHeader. RateServiceGid	Delivery Based: WSH_NEW_DELIVERIES.SERVICE_LEVEL  Batch Based: WSH_TMS_SUB_BATCHES. SERVICE_LEVEL	Rate service global ID
O	ReleaseHeader.A. ServiceProviderGid	Delivery Based: WSH_NEW_DELIVERIES.CARRIER_ID  Batch Based: WSH_TMS_SUB_BATCHES.CARRIER_ID	Service provider global ID

Required/Optional	OTM Attribute	EBS Table.Column	Description
O	ReleaseHeader.B. TransportModeGid	Delivery Based: WSH_NEW_DELIVERIES. MODE_OF_TRANSPORT  Batch Based: WSH_TMS_SUB_BATCHES. MODE_OF_TRANSPORT	Transportation mode global ID
R	ShipFromLocationRef. LocationGid	Delivery Based: DELIVERY_SHIPFROM_LOCATION  Batch Based: BATCH_SHIPFROM_LOCATION (WSH_TMS_SUB_BATCHES. SHIP_FROM_LOCATION_ID)	Location global ID
O	ShipToLocationRef		

Required/Optional	OTM Attribute	EBS Table.Column	Description
R	ShipToLocationRef. LocationGid	Delivery Based: DELIVERY SHIP TO/ULTIMATE DROP-OFF LOCATION GID  Batch Based: BATCH SHIP TO/ULTIMATE DROP-OFF LOCATION GID (WSH_TMS_SUB_BATCHES. SHIP_TO_LOCATION_ID)	Location ID. If the location is mapped to an internal location (e.g., Internal Sales Order) then the internal location ID will be sent.
O	TimeWindow. EarlyPickupDate	Delivery Based: WSH_NEW_DELIVERIES. EARLIEST_PICKUP_DATE  Batch Based: WSH_TMS_SUB_BATCHES. EARLIEST_PICKUP_DATE	Early pickup date
O	TimeWindow. LatePickupDate	Delivery Based: WSH_NEW_DELIVERIES. LATEST_PICKUP_DATE  Batch Based: WSH_TMS_SUB_BATCHES. LATEST_PICKUP_DATE	Late pickup date

Required/Optional	OTM Attribute	EBS Table.Column	Description
O	TimeWindow. EarlyDeliveryDate	Delivery Based:  WSH_NEW_DELIVERIES. EARLIEST_DROPOFF_DATE  Batch Based:  WSH_TMS_SUB_BATCHES. EARLIEST_DROPOFF_DATE	Early delivery date
O	TimeWindow. LateDeliveryDate	Delivery Based:  WSH_NEW_DELIVERIES. LATEST_DROPOFF_DATE  Batch Based:  WSH_TMS_SUB_BATCHES. LATEST_DROPOFF_DATE	Late delivery date
R	TotalWeightVolume. Weight	Delivery Based:  WSH_NEW_DELIVERIES.GROSS_WEIGHT, WSH_NEW_DELIVERIES. WEIGHT_UOM_CODE  Batch Based:  WSH_TMS_SUB_BATCHES. GROSS_WEIGHT, WSH_TMS_SUB_BATCHES. WEIGHT_UOM_CODE	Total gross weight and UOM

Required/Optional	OTM Attribute	EBS Table.Column	Description
R	TotalWeightVolume. Volume	Delivery Based:  WSH_NEW_DELIVERIES. WEIGHT_UOM_CODE  Batch Based:  WSH_TMS_SUB_BATCHES. WEIGHT_UOM_CODE	Total gross volume and UOM
R	TotalNetWeightVolume. Weight	Delivery Based:  WSH_NEW_DELIVERIES.VOLUME, WSH_NEW_DELIVERIES. VOLUME_UOM_CODE  Batch Based:  WSH_TMS_SUB_BATCHES.VOLUME, WSH_TMS_SUB_BATCHES. VOLUME_UOM_CODE	Total net weight and UOM
O	TotalPackagedItemCount		Total quantities of Item regardless of the UOM. A sum of quantities of the item.
O	ReleaseRefnum	Delivery Based:  REVNUM  Batch Based:  REVNUM, INTG_TYPE	Delivery revision number Qualifier: REVNUM

Required/Optional	OTM Attribute	EBS Table.Column	Description
O	Remarks	WSH_NEW_DELIVERIES. REASON_OF_TRANS PORTWSH_NEW_DELIVERIES. DESCRIPTIONWSH_NEW_DELIVERIES. ADDITIONAL_SHIPMENT_INFOWSH_NEW_DELIVERIES. ROUTING_INSTRUCTIONS	Qualifiers: TRSP_REASON DEL_DESCRIPTION ADD_INFOS ROUTING_INSTR ACTUALS_RECEIVED ACTUALS_RECEIVED is a qualified value used when sending the release transaction in the actual shipment context. (Value = Y)

### Release XML Transaction - Delivery Lines (Release.ReleaseLine)

The following table shows the XML mapping for the Release XML transaction for delivery lines. Elements that are not mapped are not shown. (OTM = Oracle Transportation Management. EBS = Oracle E-Business Suite.)

Optional/Required	OTM Attribute	EBS Table.Column	Description
R	ReleaseLineGid	WSH_DELIVERY_DE TAILS. DELIVERY_DETAIL_ID	Release line global ID
R	PackagedItemGid	DELIVERY DETAIL ITEM GID as per reference data GID	Item GID as per reference data.
O	ItemQuantity. ItemTag1	WSH_DELIVERY_DE TAILS. LOT_NUMBER	Item lot number
O	ItemQuantity. ItemTag2	WSH_DELIVERY_DE TAILS. SERIAL_NUMBER	Item serial number

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	ItemQuantity. ItemTag3	WSH_DELIVERY_DE TAILS. TO_SERIAL_NUMBE R	Item to serial number
O	ItemQuantity. IsSplitAllowed	N	
R	ItemQuantity. WeightVolume. Weight	WSH_DELIVERY_DE TAILS. GROSS_WEIGHTWS H_DELIVERY_DETA ILS. WEIGHT_UOM_CO DE	Note: UOM codes are PUBLIC data in Oracle Transportation Management. Domain is not mapped in this case.
R	ItemQuantity. WeightVolume. Volume	WSH_DELIVERY_DE TAILS. VOLUMEWSH_DELI VERY_DETAILS. VOLUME_UOM_CO DE	Adjusted to the QUANTITY_SHIPPE D when ship confirmation occurs.
O	ItemQuantity. PackagedItemCount	Delivery not ship confirmed WSH_DELIVERY_DE TAILS. REQUESTED_QUAN TITY.  Delivery ship confirmed WSH_DELIVERY_DE TAILS. SHIPPED_QUANTIT Y	Packaged item count
O	Refnum	WSH_DELIVERY_DE TAILS. CUST_PO_NUMBER WSH_DELIVERY_DE TAILS. SOURCE_HEADER_ NUMBER	Qualifiers: CUST_PO SO_NUM

## Release XML Transaction - Ship Unit (Release.ShipUnit)

The following table shows the XML mapping for the Release XML transaction for ship units. Elements that are not mapped are not shown. (OTM = Oracle Transportation Management. EBS = Oracle E-Business Suite.)

**Note:** Item, customer, customer site, and organization reference data is sent using the Order Release Message.

Optional/Required	OTM Attribute	EBS Table.Column	Description
R	ShipUnitGid	<b>Unpacked:</b> WSH_DELIVERY_DE TAILS. DELIVERY_DETAIL_ <b>IDPacked:</b> WSH_DELIVERY_DE TAILS. DELIVERY_DETAIL_ ID of the outer most LPN	Unpacked content: One ship unit per delivery detail is generated, thus ship unit and or line use the same ID
O	TransactionCode	I when creating a release RC when updating	Transaction code
O	ShipUnit. ShipUnitSpecGid	<b>Unpacked:</b> Not mapped <b>Packed:</b> Type of the LPN container item (example STANDARD PALLET)	
O	WeightVolume	<b>Unpacked:</b> Delivery detail content gross weight and volumes. <b>Packed:</b> LPN gross Weights and volume.	UOM codes are PUBLIC data in Oracle Transportation Management. Domain is not mapped in this case.

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	UnitNetWeightVolume	<b>Packed:</b> LPN net weights and volume. <b>Unpacked:</b> Delivery detail weights and volumes.	
O	LengthWidthHeight		LPN container item dimensions
O	ShipUnitSeal	WSH_DELIVERY_DE TAILS.SEAL_CODE	Seal code for the ship unit
O	ShipUnitContent. LineNumber	Incremental value	Incremental value per content line : 1,2, 3, etc.
O	ShipUnitContent. ReleaseGid	Delivery Based:  WSH_NEW_DELIVERIES.DELIVERY_ID  Batch Based:  WSH_TMS_SUB_BATCHES.NAME	ReleaseGID of the DD contained in the ship unit
O	ShipUnitContent. ReleaseLineGid	WSH_DELIVERY_DE TAILS. DELIVERY_DETAIL_ID	ReleaselineGID of the DD contained in the ship unit
O	ShipUnitCount	Delivery Based:  1  Batch Based:  Sum of Packed Item Quantity	Ship unit count

### Release XML Transaction - Packaged Item (Release.ReleaseLine.PackagedItemRef)

The following table shows the XML mapping for the Release XML transaction for packaged items. Elements that are not mapped are not shown. (OTM = Oracle Transportation Management. EBS = Oracle E-Business Suite.)

Optional/Required	OTM Attribute	EBS Table.Column	Description
R	PackagedItemGid	DELIVERY_DETAIL_ ITEM_GID	Item comes from reference data as a result only.

### Planned Shipment XML Transaction - Trip

The following table shows the XML mapping for the Planned Shipment XML transaction for trips. Elements that are not mapped are not shown. (OTM = Oracle Transportation Management. EBS = Oracle E-Business Suite.)

Optional/Required	OTM Attribute	EBS Table.Column	Description
R	Shipment. ShipmentHeader. ServiceProviderGid. Gid.Xid	WSH_TRIPS. CARRIER_ID	Carrier ID
O	Shipment. ShipmentHeader. RateServiceGid.Gid. Xid	WSH_TRIPS. SERVICE_LEVEL	Rate service ID
O	Shipment. ShipmentHeader. TransportModeGid. Xid	WSH_TRIPS. MODE_OF_TRANSP ORT	Transportation mode ID
O	Shipment. ShipmentHeader. CommercialTerms. PaymentMethodCode Gid	WSH_TRIPS. FREIGHT_TERMS_C ODE	Payment method global ID
O	Shipment. Sequipment. EquipmentGroupGid	WSH_TRIPS. VEHICLE_ITEM_ID	Equipment type global ID
O	Shipment. Sequipment. EquipmentInitial	WSH_TRIPS. VEHICLE_NUMBER _PREFIX	Equipment prefix

Optional/Required	OTM Attribute	EBS Table.Column	Description
R	Shipment. Sequipment. EquipmentNumber	WSH_TRIPS. VEHICLE_NUMBER	Equipment number
O	Shipment. ShipmentHeader. ShipmentGid.Gid.Xid	WSH_TRIPS. TP_PLAN_NAME	Shipment header global ID
O	Shipment.Release. ReleaseAllocationInfo .ReleaseAllocByType. ReleaseAllocShipmen t.TotalAllocCost  (XSL Mapping chooses the Cost for ReleaseAllocByType = "PLANNING")	WSH_FREIGHT_COS TS. TOTAL_AMOUNT	Freight cost allocated at the release level.
O	Shipment. ShipmentHeader. ShipmentRefnum. ShipmentRefnumVal ue (XSL Mapping chooses the refnum value for ShipmentRefnumQua lifierGid.Gid.Xid = "SHIPMENT_ATTRIB UTE_CATEGORY")	WSH_TRIPS. ATTRIBUTE_CATEG ORY	DFE Attribute Category
O	Shipment. ShipmentHeader. ShipmentRefnum. ShipmentRefnumVal ue (XSL Mapping chooses the refnum value for ShipmentRefnumQua lifierGid.Gid.Xid = "SHIPMENT_ATTRIB UTE1")	WSH_TRIPS. ATTRIBUTE1	DFE Attribute 1

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	Shipment. ShipmentHeader. ShipmentRefnum. ShipmentRefnumValue (XSL Mapping chooses the refnum value for ShipmentRefnumQualifierGid.Gid.Xid = "SHIPMENT_ATTRIBUTE2")	WSH_TRIPS. ATTRIBUTE2	DDF Attribute 2
O	Shipment. ShipmentHeader. ShipmentRefnum. ShipmentRefnumValue (XSL Mapping chooses the refnum value for ShipmentRefnumQualifierGid.Gid.Xid = "SHIPMENT_ATTRIBUTE3")	WSH_TRIPS. ATTRIBUTE3	DDF Attribute 3
O	Shipment. ShipmentHeader. ShipmentRefnum. ShipmentRefnumValue (XSL Mapping chooses the refnum value for ShipmentRefnumQualifierGid.Gid.Xid = "SHIPMENT_ATTRIBUTE4")	WSH_TRIPS. ATTRIBUTE4	DDF Attribute 4

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	Shipment. ShipmentHeader. ShipmentRefnum. ShipmentRefnumValue (XSL Mapping chooses the refnum value for ShipmentRefnumQualifierGid.Gid.Xid = "SHIPMENT_ATTRIBUTE5")	WSH_TRIPS. ATTRIBUTE5	DFE Attribute 5
O	Shipment. ShipmentHeader. ShipmentRefnum. ShipmentRefnumValue (XSL Mapping chooses the refnum value for ShipmentRefnumQualifierGid.Gid.Xid = "SHIPMENT_ATTRIBUTE6")	WSH_TRIPS. ATTRIBUTE6	DFE Attribute 6
O	Shipment. ShipmentHeader. ShipmentRefnum. ShipmentRefnumValue (XSL Mapping chooses the refnum value for ShipmentRefnumQualifierGid.Gid.Xid = "SHIPMENT_ATTRIBUTE7")	WSH_TRIPS. ATTRIBUTE7	DFE Attribute 7

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	Shipment. ShipmentHeader. ShipmentRefnum. ShipmentRefnumValue (XSL Mapping chooses the refnum value for ShipmentRefnumQualifierGid.Gid.Xid = "SHIPMENT_ATTRIBUTE8")	WSH_TRIPS. ATTRIBUTE8	DDF Attribute 8
O	Shipment. ShipmentHeader. ShipmentRefnum. ShipmentRefnumValue (XSL Mapping chooses the refnum value for ShipmentRefnumQualifierGid.Gid.Xid = "SHIPMENT_ATTRIBUTE9")	WSH_TRIPS. ATTRIBUTE9	DDF Attribute 9
O	Shipment. ShipmentHeader. ShipmentRefnum. ShipmentRefnumValue (XSL Mapping chooses the refnum value for ShipmentRefnumQualifierGid.Gid.Xid = "SHIPMENT_ATTRIBUTE10")	WSH_TRIPS. ATTRIBUTE10	DDF Attribute 10

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	Shipment. ShipmentHeader. ShipmentRefnum. ShipmentRefnumValue (XSL Mapping chooses the refnum value for ShipmentRefnumQualifierGid.Gid.Xid = "SHIPMENT_ATTRIBUTE11")	WSH_TRIPS. ATTRIBUTE11	DFE Attribute 11
O	Shipment. ShipmentHeader. ShipmentRefnum. ShipmentRefnumValue (XSL Mapping chooses the refnum value for ShipmentRefnumQualifierGid.Gid.Xid = "SHIPMENT_ATTRIBUTE12")	WSH_TRIPS. ATTRIBUTE12	DFE Attribute 12
O	Shipment. ShipmentHeader. ShipmentRefnum. ShipmentRefnumValue (XSL Mapping chooses the refnum value for ShipmentRefnumQualifierGid.Gid.Xid = "SHIPMENT_ATTRIBUTE13")	WSH_TRIPS. ATTRIBUTE13	DFE Attribute 13

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	Shipment. ShipmentHeader. ShipmentRefnum. ShipmentRefnumValue (XSL Mapping chooses the refnum value for ShipmentRefnumQualifierGid.Gid.Xid = "SHIPMENT_ATTRIBUTE14")	WSH_TRIPS. ATTRIBUTE14	DFE Attribute 14
O	Shipment. ShipmentHeader. ShipmentRefnum. ShipmentRefnumValue (XSL Mapping chooses the refnum value for ShipmentRefnumQualifierGid.Gid.Xid = "SHIPMENT_ATTRIBUTE15")	WSH_TRIPS. ATTRIBUTE15	DFE Attribute 15

### Planned Shipment XML Transaction - Trip Stop

The following table shows the XML mapping for the Planned Shipment XML transaction for trip stops. Elements that are not mapped are not shown. (OTM = Oracle Transportation Management. EBS = Oracle E-Business Suite.)

Optional/Required	OTM Attribute	EBS Table.Column	Description
R	Shipment. ShipmentStop. LocationRef	WSH_TRIP_STOPS. STOP_LOCATION_ID	Trip stop ID
O	Shipment. ShipmentStop. StopSequence	WSH_TRIP_STOPS. STOP_SEQUENCE_NUMBER	Trip stop sequence number

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	Shipment. ShipmentStop. ArrivalTime. EventTime. PlannedTime	WSH_TRIP_STOPS. PLANNED_ARRIVAL_DATE	Trip stop planned arrival date
O	Shipment. ShipmentStop. DepartureTime. EventTime. PlannedTime	WSH_TRIP_STOPS. PLANNED_DEPARTURE_DATE	Trip stop planned departure date
O	Shipment.Location. Address. TimezoneGid	WSH_TRIP_STOPS. TIMEZONE_XID	Trip stop time zone
O	Shipment. ShipmentStop. Refnum. RefnumValue (XSL Mapping chooses the refnum value for RefnumQualifierGid. Gid.Xid = "STOP_ATTRIBUTE_CATEGORY")	WSH_TRIP_STOPS. ATTRIBUTE_CATEGORY	DFF Attribute Category
O	Shipment. ShipmentStop. Refnum. RefnumValue (XSL Mapping chooses the refnum value for RefnumQualifierGid. Gid.Xid = "STOP_ATTRIBUTE1")	WSH_TRIP_STOPS. ATTRIBUTE1	DFF Attribute 1

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	Shipment. ShipmentStop. Refnum. RefnumValue (XSL Mapping chooses the refnum value for RefnumQualifierGid. Gid.Xid = "STOP_ATTRIBUTE2 ")	WSH_TRIP_STOPS. ATTRIBUTE2	DFF Attribute 2
O	Shipment. ShipmentStop. Refnum. RefnumValue (XSL Mapping chooses the refnum value for RefnumQualifierGid. Gid.Xid = "STOP_ATTRIBUTE3 ")	WSH_TRIP_STOPS. ATTRIBUTE3	DFF Attribute 3
O	Shipment. ShipmentStop. Refnum. RefnumValue (XSL Mapping chooses the refnum value for RefnumQualifierGid. Gid.Xid = "STOP_ATTRIBUTE4 ")	WSH_TRIP_STOPS. ATTRIBUTE4	DFF Attribute 4
O	Shipment. ShipmentStop. Refnum. RefnumValue (XSL Mapping chooses the refnum value for RefnumQualifierGid. Gid.Xid = "STOP_ATTRIBUTE5 ")	WSH_TRIP_STOPS. ATTRIBUTE5	DFF Attribute 5

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	Shipment. ShipmentStop. Refnum. RefnumValue (XSL Mapping chooses the refnum value for RefnumQualifierGid. Gid.Xid = "STOP_ATTRIBUTE6 ")	WSH_TRIP_STOPS. ATTRIBUTE6	DFF Attribute 6
O	Shipment. ShipmentStop. Refnum. RefnumValue (XSL Mapping chooses the refnum value for RefnumQualifierGid. Gid.Xid = "STOP_ATTRIBUTE7 ")	WSH_TRIP_STOPS. ATTRIBUTE7	DFF Attribute 7
O	Shipment. ShipmentStop. Refnum. RefnumValue (XSL Mapping chooses the refnum value for RefnumQualifierGid. Gid.Xid = "STOP_ATTRIBUTE8 ")	WSH_TRIP_STOPS. ATTRIBUTE8	DFF Attribute 8
O	Shipment. ShipmentStop. Refnum. RefnumValue (XSL Mapping chooses the refnum value for RefnumQualifierGid. Gid.Xid = "STOP_ATTRIBUTE9 ")	WSH_TRIP_STOPS. ATTRIBUTE9	DFF Attribute 9

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	Shipment. ShipmentStop. Refnum. RefnumValue (XSL Mapping chooses the refnum value for RefnumQualifierGid. Gid.Xid = "STOP_ATTRIBUTE1 0")	WSH_TRIP_STOPS. ATTRIBUTE10	DFF Attribute 10
O	Shipment. ShipmentStop. Refnum. RefnumValue (XSL Mapping chooses the refnum value for RefnumQualifierGid. Gid.Xid = "STOP_ATTRIBUTE1 1")	WSH_TRIP_STOPS. ATTRIBUTE11	DFF Attribute 11
O	Shipment. ShipmentStop. Refnum. RefnumValue (XSL Mapping chooses the refnum value for RefnumQualifierGid. Gid.Xid = "STOP_ATTRIBUTE1 2")	WSH_TRIP_STOPS. ATTRIBUTE12	DFF Attribute 12
O	Shipment. ShipmentStop. Refnum. RefnumValue (XSL Mapping chooses the refnum value for RefnumQualifierGid. Gid.Xid = "STOP_ATTRIBUTE1 3")	WSH_TRIP_STOPS. ATTRIBUTE13	DFF Attribute 13

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	Shipment. ShipmentStop. Refnum. RefnumValue (XSL Mapping chooses the refnum value for RefnumQualifierGid. Gid.Xid = "STOP_ATTRIBUTE1 4")	WSH_TRIP_STOPS. ATTRIBUTE14	DFE Attribute 14
O	Shipment. ShipmentStop. Refnum. RefnumValue (XSL Mapping chooses the refnum value for RefnumQualifierGid. Gid.Xid = "STOP_ATTRIBUTE1 5")	WSH_TRIP_STOPS. ATTRIBUTE15	DFE Attribute 15

### PlannedShipment XML Transaction - Delivery Leg

The following table shows the XML mapping for the PlannedShipment XML transaction for delivery leg. Elements that are not mapped are not shown. (OTM = Oracle Transportation Management. EBS = Oracle E-Business Suite.)

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	ShipUnit. ShipFromLocationRef	WSH_TRIP_STOPS. STOP_LOCATION_I D corresponding to WSH_DELIVERY_LE GS. PICK_UP_STOP_ID	Delivery leg pick up stop ID

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	ShipUnit. ShipToLocationRef	WSH_TRIP_STOPS. STOP_LOCATION_I D corresponding to WSH_DELIVERY_LE GS. DROP_OFF_STOP_I D	Delivery leg drop off stop ID

### ActualShipment XML Transaction

The following table shows the XML mapping for the ActualShipment XML transaction. Elements that are not mapped are not shown. (OTM = Oracle Transportation Management. EBS = Oracle E-Business Suite.)

Optional/Required	OTM Attribute	EBS Table.Column	Description
R	ShipmentHeader. ShipmentGid	Include for planning WSH_TRIPS. TP_PLAN_NAME Ignore for planning prefix WSH - WSH_TRIPS.TRIP_ID (GID example EBS. WSH-12345)	Shipment global ID
O	ShipmentHeader. ShipmentName	WSH_TRIPS.NAME	Shipment name
O	ShipmentHeader. ShipmentRefnum	WSH_TRIPS.TRIP_ID WSH_TRIPS. MASTER_BOL_NUM BER WSH_TRIPS. PLANNED_FLAG Total manually entered Freight Costs. Manually entered freight cost currency WSH_TRIPS. OPERATOR	Shipment reference number  Qualifiers: TRIP_ID MBOL_NUMBER PLANNED_TRIP MANUAL_FREIGHT _COSTS MAN_FREIGHT_CO ST_CUR OPERATOR
R	ShipmentHeader. TransactionCode	IU: Ignore for planning.	Transaction code

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	ShipmentHeader. ServiceProviderGid	GID of WSH_TRIPS. CARRIER_ID	Service provider global ID
O	ShipmentHeader. IsServiceProviderFixed	Y: Ignore for planning	Whether or not service provider is fixed.
O	ShipmentHeader. TransportModeGid	WSH_TRIPS. MODE_OF_TRANSP ORT	Mode of transportation global ID

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	ShipmentHeader. TotalWeightVolume. Weight	Sum of TRIP_STOPS. Departure gross weights. NOTE: Rules for trip's Weights and Volumes UOM get UOM Class defined in Shipping Parameters (Org-specific) and Base UOM defined for this UOM Class in Inventory > Units Of Measure. In the Outbound concurrent request, the system checks that for each trip that gets picked-up, the base UOM exists for the first stop location's organization's UOM Class and for each trip, it's base UOM is used to calculate total weight/volume at the trip level for Actuals. End-Users have to ensure that both forms are defined at set-up time and that OTM has defined this UOM (or UOMs if it's different across Orgs).  Note: UOM domain: because UOMs are in the PUBLIC domain in OTM we do not map a DOMAIN for UOM GIDs.	Total gross weight
O	ShipmentHeader. TotalWeightVolume. Volume	Sum of TRIP_STOPS departure volumes	Total gross volume of the trip

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	TotalNetWeight. Volume		Total net volume of the trip
O	ShipmentHeader. TotalNetWeightVolume.Weight	Sum of TRIP_STOPS departure net weights	Total net weight
O	ShipmentHeader. TotalShipUnitCount	Count of Ship_units = count of outermost LPNs + 1 unpacked content	Ship unit count.
O	ShipmentHeader. TotalPackagedItemCount	Total quantity of items regardless of UOM.	Packaged item count for the trip
O	CommercialTerms. PaymentMethodCode	WSH_TRIPS. FREIGHT_TERMS_CODE	Payment method code
O	ShipmentHeader. Remark	WSH_TRIPS. ROUTING_INSTRUCTIONS	Miscellaneous remarks
O	ShipmentHeader. StopCount		Number of stops within the trip.
O	ShipmentHeader2. ShipmentAsWork	N= Include for Planning Y= for Ignore for Planning	
O	SEquipment. IntSavedQuery. IntSavedQueryGID	Include for Planning trips only. S_EQUIPEMENT_1	Saved query global ID
O	SEquipment. IntSavedQuery. IntSavedQueryArg. ArgName	Include for Planning trips only. SHIPMENT_GID	

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	SEquipment. IntSavedQuery. IntSavedQueryArg. Value	Include for Planning trips only SHIPMENT_GID = DOMAIN. WSH_TRIPS. TP_PLAN_NAME	Saved query value
R	SEquipmentGid	Ignore for Planning trips only. SHIPMENT_GID = DOMAIN.WSH- WSH_TRIP.TRIP_ID (for example EBS. WSH-12345).	Equipment global ID  If Ignore, then populate SEquipmentGid. DomainName and SEquipmentGid. Value  If Include, then populate IntSavedQueryGid, IntSavedQueryArgVa lue, IntSavedQueryArgNa me
O	SEquipment. EquipmentInitial	WSH_TRIP. VEHICLE_NUMBER _PREFIX	Equipment prefix
O	SEquipment. EquipmentNumber	WSH_TRIP. VEHICLE_NUMBER	Equipment number
O	SEquipment. EquipmentGroupGid	Item name of item WSH_TRIP. VEHICLE_ITEM_ID (for example 40ft trailer)	Equipment group global ID
O	SEquipment. SEquipmentSeal	WSH_TRIP. SEAL_CODE	Equipment seal code
O	SEquipment. SEquipmentSeal. SequenceNumber	Incremental number, 1 because there is one seal number for the trip.	Equipment sequence number.

Optional/Required	OTM Attribute	EBS Table.Column	Description
R	ShipmentStop. StopSequence	WSH_TRIP. STOP_SEQUENCE_N UMBER	Stop sequence number
O	ShipmentStop. TransactionCode	I: Ignore for planning trips IU: Include for planning	Transaction code
O	ShipmentStop. StopDuration	Pick up stop only Difference between start of loading end of loading	Stop duration
	ShipmentStop. LocationRef. locationGid	GID of WSH_TRIP_STOPS. LOCATION_ID	Location global ID
O	ShipmentStop. ArrivalTime. EventTime. ActualTime. GLogDate	Ignore for planning - pick up stop WSH_TRIP_STOPS. ACTUAL_ARRIVAL_ DATE Ignore for Planning - drop stop WSH_TRIP_STOPS. PLANNED_ARRIVA L_DATE Include for Planning - Pick up stop WSH_TRIP_STOPS. ACTUAL_ARRIVAL_ DATE	Arrival time

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	ShipmentStop. DepartureTime.. EventTime. ActualTime. GLogDate	Ignore for planning - Pick up stop WSH_TRIP_STOPS. ACTUAL_DEPARTU RE_DATE Ignore for Planning - Drop stop WSH_TRIP_STOPS. PLANNED_DEPART URE_DATE Include for Planning - Pick up stop WSH_TRIP_STOPS. ACTUAL_DEPARTU RE_DATE	Actual arrival time
R	ShipmentStop. ShipmentStopDetail. Activity	P if the ship unit is to be picked up D if the ship unit is to be dropped off.	Activity information
R	ShipmentStop. ShipmentStopDetail. ShipUnitGid	Release's ShipUnit Gid picked up or dropped off.	Ship unit global ID
O	ShipmentStop. ShipmentStopDetail. Refnum	WSH_TRIP_STOPS. DEPARTURE_SEAL_ CODE	Reference number
O	ShipUnit. ShipUnitGid.Xid	Delivery Based:  WSH_DELIVERY_DE TAILS.LPN_ID  Batch Based:  WSH_DELIVERY_DE TAILS. TMS_SSHIPUNIT_ID	Ship unit Global ID
O	ShipUnit. ShipUnitCount	Delivery Based:  For loose items, always qty 1  Batch Based:  Sum of shipped qty	Ship unit count

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	ShipUnit. ShipUnitContent. ItemQuantity. WeightVolume. Weight.WeightValue	Delivery Based: GROSS_WEIGHT Batch Based: Sum of gross weight of shipped units	Weight
O	ShipUnit. ShipUnitContent. ItemQuantity. WeightVolume. Volume. VolumeValue	Delivery Based: VOLUME Batch Based: Sum of volume of shipped units	Volume
O	ShipUnit. ShipUnitContent. ItemQuantity. PackagedItemCount	Delivery Based: ITEM_QUANTITY Batch Based: Sum of quantity of shipped units	Packaged item count
O	ShipUnit. ShipUnitContent. ReleaseGid.Gid.Xid	Delivery Based: WSH_NEW_DELIVE RIES.DELIVERY_ID Batch Based: WSH_TMS_SUB_BA TCHES.NAME	Release global ID

## Shipping-Transportation Carrier Synchronization XML Mapping

### Carrier XML Mapping

The following table shows the mapping of the referenced XML carrier data between Oracle E-Business Suite and Oracle Transportation Management, whether the data is required or optional, and a brief description. (OTM = Oracle Transportation Management. EBS = Oracle E-Business Suite)

**Note:** All null fields must contain a tilde (~) and must not be left blank.

### Carrier XML Mapping

---

Optional/Required	OTM Element	EBS Table.Column	Description
	Corporation		Structure containing corporate information specific to a corporation headquarters.
O	CorporationName	AR.HZ_PARTIES.PARTY_NAME (via CARRIER_ID)	Corporation name
	Location		Structure containing place where transportation related activities occur, for example, a loading and unloading freight location. In addition, a location might represent a corporation, and/or a service provider.
R	Location.TransactionCode	CONSTANT =IU	Specifies how the XML transaction should be processed." I" adds new data. "U" updates existing data. "IU" updates if present, insert otherwise. "D" to delete."RC" to replace children.

---

Optional/Required	OTM Element	EBS Table.Column	Description
R	Location.LocationGid	DomainName = Profile Option "OTM: Domain Name" value  XID = CAR  "-"  WSH. WSH_CARRIERS. CARRIER_ID	A global ID that uniquely identifies a location.
O	Location.LocationName	AR.HZ_PARTIES. PARTY_NAME (via CARRIER_ID)	Location name. Truncated to 30 characters because of size limitations in OTM.
R	Location.Address. CountryCode3Gid	DomainName = PUBLIC  XID = Profile Option "WSH: OTM Corporation Country Code value	The three character ISO country code global identifier.
R	Location.LocationRefnum. LocationRefnumQualifierGid	DomainName = PUBLIC  XID = ORIGIN	Location reference number global ID.
R	Location.LocationRefnum. LocationRefnumValue	CONSTANT = CARRIER	Location reference number is used to provide smart EBS values. For example, when Qualifier = ORIGIN, Value is the origin EBS data such as Customer, Carrier, or Organization.
R	Location.LocationRefnum. LocationRefnumQualifierGid	DomainName = PUBLIC  XID = ORIGIN	Location reference number qualifier global ID.

Optional/Required	OTM Element	EBS Table.Column	Description
R	Location.LocationRefnum. LocationRefnumValue	WSH. WSH_CARRIERS. CARRIER_ID	Location reference number is used to provide smart EBS values. For example, when Qualifier = CARID, Value is the origin EBS data is the EBS carrier ID known by EBS users.
R	Location.LocationRefnum. LocationRefnumQualifierGid	DomainName = PUBLIC  XID = CARNM	Location reference number qualifier Global ID.
R	Location.LocationRefnum. LocationRefnumValue	WSH: AR. WSH_CARRIERS. SCAC_CODE	Location reference number is used to provide smart EBS values. For example, when Qualifier = CARNM, Value is the EBS carrier short name known by EBS users.
O	Location.LocationRoleGid	DomainName = PUBLIC  XID = CARRIER	A structure specifying a location role.
O	Location.Corporation. CorporationName	AR.HZ_PARTIES. PARTY_NAME (via CARRIER_ID)	Corporation name. Truncated to 30 characters because of size limitations in OTM.
	ServiceProvider		An optional structure containing a location represents a service provider.

Optional/Required	OTM Element	EBS Table.Column	Description
R	ServiceProvider Alias. ServiceProviderAliasQualifier Gid	DomainName = PUBLIC  XID = SUPPLIER_ID	Indicates the type of value in the ServiceProviderAlias Value element.
R	ServiceProvider Alias. ServiceProviderAliasValue	DomainName = Profile Option OTM: Domain Name value  XID = SUP "  WSH. WSH_CARRIERS. SUPPLIER_ID	Service provider alias is used to provide EBS information. For example, when Qualifier = SUPPLIER_ID, Value is the EBS link between carrier and supplier.

### Carrier Site XML Mapping

The following table shows the mapping of the referenced XML carrier site data between Oracle E-Business Suite and Oracle Transportation Management, whether the data is required or optional, and a brief description. (OTM = Oracle Transportation Management. EBS = Oracle E-Business Suite)

**Note:** All null fields must contain a tilde (~) and must not be left blank.

### Carrier Site XML Mapping

Optional/Required	OTM Element	EBS Table.Column	Description
R	Location		Structure containing a place where transportation related activities occur, such as loading and unloading freight.

Optional/Required	OTM Element	EBS Table.Column	Description
R	Location.TransactionCode	CONSTANT =IU	TransactionCode specifies how the XML transaction should be processed. "I" adds new data. "U" updates existing data. "IU" updates if present, inserts otherwise. "D" to delete. "RC" to replace children
R	Location.LocationGid	DomainName = Profile Option "OTM: Domain Name" value  XID= CAR  "_"  WSH. WSH_CARRIERS. CARRIER_ID  "_"  AR. HZ_PARTY_SITES. LOCATION_ID	Global ID that uniquely identifies a location.
O	Location.LocationName	AR.HZ_PARTIES. PARTY_NAME (via CARRIER_ID)  ","  AR.HZ_LOCATIONS. CITY  ","  AR.HZ_LOCATIONS. STATE  ","  AR.HZ_LOCATION. COUNTRY	The total length for LocationName should be 30 characters. Therefore, 10 characters from ten character from NAME + "," + ten characters from CITY + "," + four characters from STATE + "," + three characters from COUNTRY.

Optional/Required	OTM Element	EBS Table.Column	Description
O	Location.Address.AddressLines	AR.HZ_LOCATIONS.ADDRESS1AR. HZ_LOCATIONS.ADDRESS2AR. HZ_LOCATIONS.ADDRESS3AR. HZ_LOCATIONS.ADDRESS4	Contains the sequence number and address lines.
O	Location.Address.City	AR.HZ_LOCATIONS.CITY	City
O	Location.Address.Province	AR.HZ_LOCATIONS.STATE Only if length is not 2 letters or AR. HZ_LOCATIONS.PROVINCE Only if length is not 2 letters or AR. HZ_LOCATIONS_AL.L.REGION_2 Only if length is not 2 letters or AR. HZ_LOCATIONS_AL.L.REGION_1 Only if length is not 2 letters.	Province is a long description corresponding to ProvinceCode.

Optional/Required	OTM Element	EBS Table.Column	Description
O	Location.Address. ProvinceCode	AR.WSH_REGIONS. STATE Only if length is 2 letters; if not, then nothing or AR. HZ_LOCATIONS. STATE Only if length is 2 letters; if not, then nothing or AR. HZ_LOCATIONS. PROVINCE Only if length is 2 letters; if not, then nothing or AR. HZ_LOCATIONS_AL L.REGION_2 Only if length is 2 letters; if not, then nothing or AR. HZ_LOCATIONS_AL L.REGION_1 Only if length is 2 letters; if not, then nothing.	ProvinceCode is a two character province code.  In the United States, ProvinceCode corresponds to a two character state code such as PA.
O	Location.Address.PostalCode	AR.HZ_LOCATIONS. POSTAL_CODE	PostalCode is the postal code component of Address. For United States, this is a 3, 5 or 9 character zip code.
R	Location.Address. CountryCode3Gid	DomainName = PUBLIC  XID = FND_TERRITORIES. ISO_TERRITORY_CO DEAR	CountryCode3Gid is the three-character ISO country code global identifier.
R	Location.LocationRefnum. LocationRefnumQualifierGid	DomainName = PUBLIC  XID =ORIGIN	LocationRefnumQualif ierGid is a location reference number qualifier global identifier. (For example: Gid.Xid = DUNS)

Optional/Required	OTM Element	EBS Table.Column	Description
R	Location.LocationRefnum. LocationRefnumValue	CONSTANT = CARRIER	Used to provide smart EBS values. For example, when Qualifier = ORIGIN, Value is the origin EBS data such as Customer, Carrier, or Organization
R	Location.LocationRefnum. LocationRefnumQualifierGid	DomainName = PUBLIC  XID = CARID	Location reference number qualifier global ID.
R	Location.LocationRefnum. LocationRefnumValue	WSH. WSH_CARRIERS. CARRIER_ID	Used to provide smart EBS values. For example, when Qualifier = CARID, Value is the EBS carrier ID known by EBS user.
R	Location.LocationRefnum. LocationRefnumQualifierGid	DomainName = PUBLIC  XID = LOCID	Location reference number qualifier global ID.
R	Location.LocationRefnum. LocationRefnumValue	AR. HZ_PARTY_SITES. PARTY_SITE_NUMBER	Used to provide smart EBS values. For example, when Qualifier = CARNM, Value is the EBS carrier short name known by EBS user.
R	Location.LocationRefnum. LocationRefnumQualifierGid	DomainName = PUBLIC  XID = LOCID	Location reference number qualifier global ID.

Optional/Required	OTM Element	EBS Table.Column	Description
R	Location.LocationRefnum. LocationRefnumValue	AR. HZ_PARTY_SITES. PARTY_SITE_NUMBE R	Used to provide smart EBS values. For example, when Qualifier = LOCID, Value is the EBS carrier location ID known by EBS user.
O	Location.LocationRoleGid	DomainName = PUBLIC  XID = DISPATCH LOCATION	LocationRole is a structure specifying a location role. Locations may play multiple roles. Examples of location roles include warehouse, crossdock, loading dock, etc.
R	Location.ParentLocationGid	DomainName = Profile Option "OTM: Domain Name" value  XID = CAR  "_"  WSH. WSH_CARRIERS. CARRIER_ID	Within the Location element, the ParentLocationGid specifies the parent corporation for this location. Within the OperationalLocation element, ParentLocationGid specifies the main location to which the operational location belongs.

### Shipping-Transportation Outbound Interface XML Mapping

The following table shows the mapping of the referenced data between Oracle E-Business Suite and Oracle Transportation Management, whether the data is required or optional, and a brief description of each. (OTM = Oracle Transportation Management and EBS = Oracle E-Business Suite)

### Item XML Mapping

Optional/Required	OTM Attribute	EBS Table.Column	Description
R	Item.TransactionCode	CONSTANT =IU	TransactionCode specifies how the XML transaction should be processed. "I" adds new data. "U" updates existing data. "IU" updates if present, inserts otherwise. "D" to delete. "RC" to replace children.
R	Item.ItemGid	DomainName = Profile Option "OTM: Domain Name" value  XID = MTL_SYSTEM_ITEM S_B. ORGANIZATION_ID  "  MTL_SYSTEM_ITEM S_B. INVENTORY_ITEM_ ID	Item global ID
O	Item.ItemName	MTL_SYSTEM_ITEM S_B.segment1.. segment15	Item name  Truncated to 30 characters because of size limitations in OTM.
O	Item.Description	MTL_SYSTEM_ITEM S_TL.DESCRPTION	Item description  Truncated to 120 characters because of size limitations in OTM

Optional/Required	OTM Attribute	EBS Table.Column	Description
R	Packaging, PackagedItemGid	DomainName = Profile Option "OTM: Domain Name" value  XID = MTL_SYSTEM_ITEM S_B. ORGANIZATION_ID  "  MTL_SYSTEM_ITEM S_B. INVENTORY_ITEM_ ID	Packaged item global ID
O	Packaging, Description	MTL_SYSTEM_ITEM S_TL.DESCRPTION	Packaging description  Truncated to 120 characters because of size limitations in OTM.

#### *Customer XML Mapping*

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	CorporationName	AR.HZ_PARTIES. PARTY_NAME (via CUST_ACCOUNT_I D)	Corporation name
R	Location.TransactionCode	CONSTANT =IU	TransactionCode specifies how the XML transaction should be processed. "I" adds new data. "U" updates existing data. "IU" updates if present, inserts otherwise. "D" to delete. "RC" to replace children.

Optional/Required	OTM Attribute	EBS Table.Column	Description
R	Location.LocationGid	DomainName = Profile Option "OTM: Domain Name" value  XID = CUS "  AR. HZ_CUST_ACCOU NTS. CUST_ACCOUNT_I D	Location global ID
O	Location.LocationName	AR.HZ_PARTIES. PARTY_NAME (via CUST_ACCOUNT_I D)	Location name  Truncated to 30 characters because of size limitations in OTM.
R	Location.Address. CountryCode3Gid	DomainName = PUBLIC  XID = Profile Option "OTM: Corporation Country Code" value	The three character ISO country code global identifier
R	Location.LocationRefnum. LocationRefnumQualifierGid	DomainName = PUBLIC  XID = ORIGIN	Reference number qualifier global ID
R	Location.LocationRefnum. LocationRefnumValue	CONSTANT = CUSTOMER	Used to provide EBS values. For example, when Qualifier = ORIGIN, Value is the origin EBS data such as Customer, Carrier, or Organization.
R	Location.LocationRefnum. LocationRefnumQualifierGid	DomainName = PUBLIC  XID = CUSID	Reference number qualifier global ID

Optional/Required	OTM Attribute	EBS Table.Column	Description
R	Location.LocationRefnum. LocationRefnumValue	AR. HZ_CUST_ACCOUNT_NUMBE R	Location reference number is used to provide EBS values. For example, when Qualifier = CUSID, Value is the origin EBS data is the EBS customer ID known by EBS users.
R	Location.LocationRefnum. LocationRefnumQualifierGid	DomainName = PUBLIC  XID = CUSNM	Location reference number qualifier global ID
R	Location.LocationRefnum. LocationRefnumValue	AR.HZ_PARTIES. PARTY_NAME (via CUST_ACCOUNT_ID)	Location reference number is used to provide EBS values. For example, when Qualifier = CUSNM, Value is the EBS customer name known by EBS users.
R	Location.LocationRole. LocationRoleGid	DomainName = PUBLIC  XID = CUSTOMER	Location role global ID
O	Location.Corporation. CorporationName	AR.HZ_PARTIES. PARTY_NAME (via CUST_ACCOUNT_ID)	Corporation name

**Customer Site XML Mapping**

Optional/Required	OTM Attribute	EBS Table.Column	Description
R	Location.TransactionCode	CONSTANT =IU	TransactionCode specifies how the XML transaction should be processed. "I" adds new data. "U" updates existing data. "IU" updates if present, inserts otherwise. "D" to delete. "RC" to replace children
R	Location.LocationGid		Location global ID
O	Location.LocationName	AR.HZ_PARTIES. PARTY_NAME (via CUST_ACCOUNT_ID) ; AR. HZ_LOCATIONS. CITY ; AR. HZ_LOCATIONS. STATE ; AR.HZ_LOCATION. COUNTRY	The total length for LocationName should be 30 characters; therefore, ten character from NAME + ";" + ten characters from CITY + ";" + four characters from STATE + ";" + three characters from COUNTRY

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	Location.Address.AddressLines	AR. HZ_LOCATIONS. ADDRESS1AR. HZ_LOCATIONS. ADDRESS2AR. HZ_LOCATIONS. ADDRESS3AR. HZ_LOCATIONS. ADDRESS4	Contains the sequence number and address lines.
O	Location.Address.City	AR. HZ_LOCATIONS. CITY	City
O	Location.Address.Province	AR. HZ_LOCATIONS. STATE Only if length is not 2 letters, or AR. HZ_LOCATIONS. PROVINCE Only if length is not 2 letters, or AR. HZ_LOCATIONS_A LL.REGION_2 Only if length is not 2 letters, or AR. HZ_LOCATIONS_A LL.REGION_1 Only if length is not 2 letters	Province is a long description corresponding to ProvinceCode.

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	Location.Address. ProvinceCode	AR.WSH_REGIONS. STATE Only if length is 2 letters; if not, then nothing, or AR. HZ_LOCATIONS. STATE Only if length is 2 letters; if not, then nothing, or AR. HZ_LOCATIONS. PROVINCE Only if length is 2 letters; if not, then nothing, or AR. HZ_LOCATIONS_A LL.REGION_2 Only if length is 2 letters; if not, then nothing, or AR. HZ_LOCATIONS_A LL.REGION_1 Only if length is 2 letters; if not, then nothing	A two character province code. In the United States, ProvinceCode corresponds to a two character state code such as PA.
O	Location.Address.PostalCode	AR. HZ_LOCATIONS. POSTAL_CODE	Postal code
R	Location.Address. CountryCode3Gid	DomainName = PUBLIC XID = FND_TERRITORIES. ISO_TERRITORY_CO DEAR	Three character ISO country code global identifier.
R	Location.LocationRefnum. LocationRefnumQualifierGid	DomainName = PUBLIC  XID =ORIGIN	Location reference number qualifier global ID

Optional/Required	OTM Attribute	EBS Table.Column	Description
R	Location.LocationRefnum. LocationRefnumValue	CONSTANT = CUSTOMER	Used to provide EBS values. For example, when Qualifier = ORIGIN, Value is the origin EBS data such as Customer, Carrier, or Organization
R	Location.LocationRefnum. LocationRefnumQualifierGid	DomainName = PUBLIC  XID =CUSID	Location reference number qualifier global ID
R	Location.LocationRefnum. LocationRefnumValue	AR. HZ_CUST_ACCOUNTS. ACCOUNT_NUMBER	Used to provide EBS values. For example, when Qualifier = CUSID, Value is the EBS customer ID known by EBS user
R	Location.LocationRefnum. LocationRefnumQualifierGid	DomainName = PUBLIC  XID =CUSNM	Location reference number qualifier global ID
R	Location.LocationRefnum. LocationRefnumValue	AR.HZ_PARTIES. PARTY_NAME (via CUST_ACCOUNT_ID)	Location reference number is used to provide EBS values. For example, when Qualifier = CUSNM, Value is the EBS customer name known by EBS users.
R	Location.Contact.ContactGid	DomainName = Profile Option "OTM: Domain Name" value  XID = AR. RA_CONTACTS. CONTACT_ID	Contact global ID

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	Location.Contact.TransactionCode	CONSTANT = IU	) TransactionCode specifies how the XML transaction should be processed. "I" adds new data. "U" updates existing data. "IU" updates if present, inserts otherwise. "D" to delete. "RC" to replace children
O	Location.Contact.EmailAddress	AR. HZ_CONTACT_POINTS. EMAIL_ADDRESS	Contact Email address
O	Location.Contact.FirstName	AR.HZ.PARTIES. PERSON_FIRST_NAME	Contact first name
O	Location.Contact.LastName	AR.HZ.PARTIES. PERSON_LAST_NAME	Contact last name
O	Location.Contact.JobTitle	AR. HZ_ORG_CONTACTS.JOB_TITLE	Contact job title
O	Location.Contact.Phone1	AR. HZ_CONTACT_POINTS. PHONE_COUNTRY_CODEAR. HZ_CONTACT_POINTS. PHONE_AREA_CODEAR. HZ_CONTACT_POINTS. PHONE	Contact phone number

Optional/Required	OTM Attribute	EBS Table.Column	Description
R	Location.LocationRole. LocationRoleGid	DomainName = Profile Option "OTM: Domain Name" value  XID = SHIPFROM / SHIPTO	Location role global ID
R	Location.ParentLocationGid	DomainName = Profile Option "OTM: Domain Name" value  XID = CUS  "  AR. HZ_CUST_ACCOUN TS. CUST_ACCOUNT_I D	Parent location global ID
R	Location. SubstituteLocationGid	DomainName = Profile Option "OTM: Domain Name" value  XID = CUS  "  AR. HZ_CUST_ACCOUN TS. CUST_ACCOUNT_I D  "  AR. HZ_LOCATIONS. LOCATION_ID	Substitute location global ID

### Organization XML Mapping

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	CorporationName	HR. HR_ALL_ORGANIZATION_UNITS. NAME	Corporation name
R	Location.TransactionCode	CONSTANT =IU	TransactionCode specifies how the XML transaction should be processed. "I" adds new data. "U" updates existing data. "IU" updates if present, inserts otherwise. "D" to delete. "RC" to replace children.
R	Location.LocationGid	DomainName = Profile Option "OTM: Domain Name" value  XID = ORG  "_"  HR. HR_ALL_ORGANIZATION_UNITS. ORGANIZATION_ID  "_"  HR. HR_LOCATIONS_ALL.LOCATION_ID	Location global ID
O	Location.LocationName	HR. HR_ALL_ORGANIZATION_UNITS. NAME	Location name  Truncated to 30 characters because of size limitations in OTM.

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	Location.Address.AddressLines	HR. HR_LOCATIONS_AL L. ADDRESS_LINE_1HR . HR_LOCATIONS_AL L. ADDRESS_LINE_2HR . HR_LOCATIONS_AL L.ADDRESS_LINE_3	Contains the sequence number and address lines.
O	Location.Address.City	HR. HR_LOCATIONS_AL L.TOWN_OR_CITY	City
O	Location.Address.Province	HR. HR_LOCATIONS_AL L.REGION_1	Province is a long description corresponding to ProvinceCode
O	Location.Address.ProvinceCode	HR. HR_LOCATIONS_AL L.REGION_2 Only if length is 2 letters; if not, then nothing.	ProvinceCode is a two character province code. In the United States, ProvinceCode corresponds to a two character state code such as PA.
O	Location.Address.PostalCode	HR. HR_LOCATIONS_AL L.POSTAL_CODE	Postal code
R	Location.Address.CountryCode3Gid	DomainName = PUBLIC  XID=  HR. HR_LOCATIONS_AL L.COUNTRY	CountryCode3Gid is the three character ISO country code global identifier

Optional/Required	OTM Attribute	EBS Table.Column	Description
R	Location.LocationRefnum. LocationRefnumQualifierGid	DomainName = PUBLIC  XID = ORIGIN	Location reference number qualifier global ID
R	Location.LocationRefnum. LocationRefnumValue	CONSTANT = ORGANIZATION	Used to provide EBS values. For example, when Qualifier = ORIGIN, Value is the origin EBS data such as Customer, Carrier, or Organization.
R	Location.LocationRefnum. LocationRefnumQualifierGid	DomainName = PUBLIC  XID = ORGID	Location reference number qualifier global ID
R	Location.LocationRefnum. LocationRefnumValue	MTL_PARAMETERS. ORGANIZATION_CODE	Location reference number is used to provide EBS values. For example, when Qualifier = ORGID, Value is the EBS organization ID known by EBS users.
R	Location.LocationRefnum. LocationRefnumQualifierGid	DomainName = PUBLIC  XID = ORGNM	Location reference number qualifier global ID
R	Location.LocationRefnum. LocationRefnumValue	HR. HR_ALL_ORGANIZATION_UNITS. NAME	Location reference number is used to provide EBS values. For example, when Qualifier = ORGNM, Value is the EBS organization name known by EBS users.

Optional/Required	OTM Attribute	EBS Table.Column	Description
R	Location.Contact.ContactGid	DomainName = Profile Option "OTM: Domain Name" value  XID = ORG  "-"  HR. HR_ALL_ORGANIZ ATION_UNITS. ORGANIZATION_ID  "-"  HR. HR_LOCATIONS_AL L.LOCATION_ID	Contact global ID
O	Location.Contact. TransactionCode	CONSTANT = IU	) TransactionCode specifies how the XML transaction should be processed. "I" adds new data. "U" updates existing data. "IU" updates if present, inserts otherwise. "D" to delete. "RC" to replace children.
O	Location.Contact.Phone1	HR. HR_LOCATIONS_AL L. TELEPHONE_NUMB ER_1	Contact phone number
O	Location.Contact.Phone2	HR. HR_LOCATIONS_AL L. TELEPHONE_NUMB ER_2	Contact phone number

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	Location.Contact.Fax	HR. HR_LOCATIONS_AL L. TELEPHONE_NUMB ER_3	Contact fax number
R	Location.LocationRole. LocationRoleGid	DomainName = Profile Option "OTM: Domain Name" value  XID = SHIPFROM / SHIPTO	Location role global ID
O	Location.Corporation. CorporationName	HR. HR_ALL_ORGANIZ ATION_UNITS. NAME	Corporation name
R	Location.Corporation. VatRegistration. CountryCode3Gid	DomainName = PUBLIC  XID = HR. HR_LOCATIONS_AL L.COUNTRY	Country code
O	Location.IsShipperKnown	CONSTANT = Y	

**Supplier XML Mapping**

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	CorporationName	HZ_PARTIES. PARTY_NAME (through VENDOR_ID)	Corporation name

Optional/Required	OTM Attribute	EBS Table.Column	Description
R	Location. TransactionCode	CONSTANT =IU	Transaction code specifies how the XML transaction should be processed. Meanings of the codes are: "I" adds new data "U" updates existing data "IU" updates if present, otherwise inserts data "D" deletes data "RC" replaces children
R	Location.LocationGid	DomainName = Profile Option "OTM: Domain Name" value XID = SUP"- "PO_VENDORS. VENDOR_ID	Location global ID
O	Location. LocationName	HZ_PARTIES. PARTY_NAME (through VENDOR_ID)	Location name
R	Location.Address. CountryCode3Gid	DomainName = PUBLIC XID = Profile Option "OTM: Corporation Country Code" value	The three character ISO country code global identifier
R	Location. LocationRefnum. LocationRefnumQualifierGid	DomainName = PUBLIC XID = ORIGIN	Reference number qualifier global ID
R	Location. LocationRefnum. LocationRefnumValue	CONSTANT = SUPPLIER	Used to provide EBS values. For example, when Qualifier = ORIGIN, value is the origin EBS data such as Customer, Carrier, Supplier, or Organization.

Optional/Required	OTM Attribute	EBS Table.Column	Description
R	Location. LocationRefnum. LocationRefnumQual ifierGid	DomainName = PUBLIC XID = CUSID	Reference number qualifier global ID
R	Location. LocationRefnum. LocationRefnumValu e	PO_VENDORS. VENDOR_ID	Location reference number used to provide EBS values. For example, when origin is Supplier then, EBS data is the EBS Supplier ID known by EBS users.
R	Location. LocationRefnum. LocationRefnumQual ifierGid	DomainName = PUBLIC XID = CUSNM	Location reference number qualifier global ID
R	Location. LocationRefnum. LocationRefnumValu e	PO_VENDORS. SEGMENT1	Location reference number used to provide EBS values. For example, when origin is Supplier then, EBS data is the EBS Supplier Number known by EBS users.
R	Location. LocationRole. LocationRoleGid	DomainName = PUBLIC XID = CUSTOMER	Location role global ID
O	Location.Corporation. CorporationName	HZ_PARTIES. PARTY_NAME (through VENDOR_ID)	Corporation name

**Supplier Site XML Mapping**

<b>Optional/Required</b>	<b>OTM Attribute</b>	<b>EBS Table.Column</b>	<b>Description</b>
R	Location. TransactionCode	CONSTANT =IU	Transaction code specifies how the XML transaction should be processed. Meanings of the codes are: "I" adds new data "U" updates existing data "IU" updates if present, otherwise inserts data "D" deletes data "RC" replaces children
R	Location.LocationGid	DomainName = Profile Option "OTM: Domain Name" value XID = SUP"- "PO_VENDORS. VENDOR_ID"- "WSH_LOCATIONS. WSH_LOCATION_I D	Location global ID
O	Location. LocationName	PO_VENDORS. PARTY_NAME (via VENDOR_ID) "," HZ_LOCATIONS. CITY "," HZ_LOCATIONS. STATE "," HZ_LOCATION. COUNTRY"	The total length for location. Location name should be 30 characters; therefore, ten characters from NAME + "," + ten characters from CITY + "," + four characters from STATE + "," + three characters from COUNTRY
O	Location.Address. AddressLines	HZ_LOCATIONS. ADDRESS1 HZ_LOCATIONS. ADDRESS2 HZ_LOCATIONS. ADDRESS3 HZ_LOCATIONS. ADDRESS4	Contains the sequence number and address lines.

Optional/Required	OTM Attribute	EBS Table.Column	Description
O	Location.Address. City	HZ_LOCATIONS. CITY	City
O	Location.Address. Province	HZ_LOCATIONS. PROVINCE	Province is a long description corresponding to the province code.
O	Location.Address. ProvinceCode	HZ_LOCATIONS. STATE Only if length is not 2 letters, or HZ_LOCATIONS. PROVINCE Only if length is not 2 letters, or HZ_LOCATIONS_A LL.REGION_2 Only if length is not 2 letters, or HZ_LOCATIONS_A LL.REGION_1 Only if length is not 2 letters	A two character province code. For example, the province code corresponds to a two character state code such as PA.
O	Location.Address. PostalCode	HZ_LOCATIONS. POSTAL_CODE	Postal code
R	Location.Address. CountryCode3Gid	DomainName = PUBLIC XID = FND_TERRITORIES. ISO_TERRITORY_CO DE	Three character ISO country code global identifier.
R	Location. LocationRefnum. LocationRefnumQual ifierGid	DomainName = PUBLIC XID = ORIGIN	Reference number qualifier global ID

Optional/Required	OTM Attribute	EBS Table.Column	Description
R	Location. LocationRefnum. LocationRefnumValue	CONSTANT = SUPPLIER	Used to provide EBS values. For example, when Qualifier = ORIGIN, value is the origin EBS data such as Customer, Carrier, Supplier, or Organization.
R	Location. LocationRefnum. LocationRefnumQualifierGid	DomainName = PUBLIC XID = CUSID	Reference number qualifier global ID
R	Location. LocationRefnum. LocationRefnumValue	PO_VENDORS. VENDOR_ID	Location reference number used to provide EBS values. For example, origin is Supplier then, EBS data is the EBS Supplier ID known by EBS users.
R	Location. LocationRefnum. LocationRefnumQualifierGid	DomainName = PUBLIC XID = CUSNM	Location reference number qualifier global ID
R	Location. LocationRefnum. LocationRefnumValue	PO_VENDORS. SEGMENT1	Location reference number used to provide EBS values. For example, origin is Supplier then, EBS data is the EBS Supplier Number known by EBS users.



---

# Index

## Symbols

3rd party warehousing, 3-25

---

### A

actual shipment xml, A-57  
apinvoice interface, A-8  
arrival time updates, 7-2, 7-2  
automated shipping, 3-27

---

### B

BPEL, 1-4

---

### C

carrier manifesting, 3-25  
carrier synchronization XML mapping, A-64  
concurrent programs, 3-42

---

### D

delivery line splitting rules, 3-10  
delivery split, 3-7  
delivery splitting, 3-9  
delivery splitting rules, 3-10

---

### E

exception groups  
    transportation management exceptions, 7-5

---

### F

freight costs, 3-24

---

### G

global parameters, 3-38

---

### I

interface status, 3-18

---

### L

location xml, A-35

---

### M

message corrections, 3-19

---

### O

oracle payables, 4-1, 4-2  
Oracle Warehouse Management, 6-1  
order base XML, A-10  
order management, 2-1  
outbound interface XML mapping, A-73  
overview, 1-1

---

### P

packing, 3-11  
parameters, 3-37  
planned shipment xml, A-45, A-51, A-56  
profile options, 2-1, 3-33  
purchase orders, 5-1  
purchasing, 5-1

---

### R

rating and routing, 2-1

release xml

deliveries, A-35

delivery lines, A-41

packaged item, A-44

ship unit, A-43

Reports

Synchronizing Dock Doors with OTM, 6-4

requirements, 1-1

## **S**

---

send voucher interface, 4-1

shipping exceptions, 3-39

shipping execution, 3-1

shipping execution xml, A-35

shipping implementation, 3-27

shipping transactions window actions, 3-11

## **T**

---

transportation management exceptions exception group, 7-5

## **U**

---

updating arrival times, 7-2

## **W**

---

warehouse management, 3-26

## **X**

---

xml

order management, A-2

shipping execution, 3-8

XML mapping, A-1