

Setting up Property File
Oracle FLEXCUBE Investor Servicing
Version 12.0.1.1.3
[May] [2013]



Table of Contents

1.	SETTING UP PROPERTY FILE	1-1
1.1	INTRODUCTION	1-1
1.2	PREREQUISITES FOR ORACLE FLEXCUBE INVESTOR SERVICING	1-1
1.2.1	<i>Prerequisites for Scheduler Plug-in.....</i>	<i>1-1</i>
1.3	PREREQUISITES FOR GATEWAY APPLICATION	1-2
1.3.1	<i>Prerequisites for Gateway EJB Application</i>	<i>1-2</i>
1.3.2	<i>Prerequisites for Gateway MDB Application</i>	<i>1-3</i>
1.3.3	<i>Prerequisites for Gateway HTTP Application</i>	<i>1-3</i>
1.3.4	<i>Prerequisites Gateway Web Service Application.....</i>	<i>1-3</i>
2.	CREATING PROPERTY FILE FOR ORACLE FLEXCUBE INVESTOR SERVICING	2-1
2.1	INTRODUCTION	2-1
2.2	CREATING PROPERTY FILE	2-1
2.2.1	<i>Setting Oracle FLEXCUBE Investor Servicing Plug-ins.....</i>	<i>2-6</i>
2.2.2	<i>Setting Common Properties</i>	<i>2-6</i>
2.2.3	<i>Setting Language Properties.....</i>	<i>2-12</i>
2.2.4	<i>Setting CSS Style.....</i>	<i>2-13</i>
2.2.5	<i>Setting Hashing Algorithm Iteration Count.....</i>	<i>2-13</i>
2.2.6	<i>Setting Email Details</i>	<i>2-14</i>
2.2.7	<i>Setting BPEL Properties.....</i>	<i>2-15</i>
2.2.8	<i>Setting DMS Properties</i>	<i>2-18</i>
2.2.9	<i>Setting Report Properties.....</i>	<i>2-19</i>
2.2.10	<i>Configuring Scheduler.....</i>	<i>2-21</i>
2.2.11	<i>Setting EMS Properties.....</i>	<i>2-26</i>
2.2.12	<i>Saving Property File.....</i>	<i>2-29</i>
3.	CREATING PROPERTY FILE FOR GATEWAY APPLICATIONS	3-1
3.1	INTRODUCTION	3-1
3.2	CREATING PROPERTY FILES	3-1
3.2.1	<i>Gateway EJB Application.....</i>	<i>3-1</i>
3.2.2	<i>Gateway MDB Application.....</i>	<i>3-6</i>
3.2.3	<i>Gateway HTTP Application.....</i>	<i>3-13</i>
3.2.4	<i>Gateway Web Service Application.....</i>	<i>3-18</i>

1. Setting up Property File

1.1 Introduction

This document explains the method to create and modify property files for Oracle FLEXCUBE Investor Servicing Application.

1.2 Prerequisites for Oracle FLEXCUBE Investor Servicing

Based on the Application and required plug-ins, you will require various components explained in the sections below.

1.2.1 Prerequisites for Scheduler Plug-in

In case you are going to include scheduler in your property file, make sure that the following queues and connection factories are created in the application server you are going to use.

Data Sources for JDBC Resource

If you need to include Scheduler plug-in in the Application, you need to create the following data sources:

Data Source	Example
XA data source	dbc/fcisSchedulerDS
XA data source	The name of this data source should be in the following format: Name of the data source created for Oracle FLEXCUBE IS_XA If you take the above example of data source for Oracle FCIS, the data source name will be 'jdbc/fcisdevDS_XA'.

JMS Resources

You need the following FCIS notification JMS resources:

Resource	Example
XA enabled connection factory	(ApplicationName)/NOTIFY_MDB_QCF
XA enabled connection factory	(ApplicationName)/NotifyDestQCF
XA enabled connection factory	(ApplicationName)/DeferredDestQCF
Queue name	(ApplicationName)/NOTIFY_QUEUE
Queue name	(ApplicationName)/NOTIFY_DEST_QUEUE
Queue name	(ApplicationName)/NOTIFY_QUEUE_DLQ

Resource	Example
Queue name	(ApplicationName)/DEFERRED_DEST_QUEUE

You need the following EMS JMS resources:

Resource	Example
XA enabled connection factory	(ApplicationName)/EmsQcf
Queue name	(ApplicationName)/EMS_INQUEUE
Queue name	(ApplicationName)/EMS_OUTQUEUE
Queue name	(ApplicationName)/EMS_EXTQUEUE

You need the following SFMS JMS resources:

Resource	Example
XA enabled connection factory	(ApplicationName)/ SFMSQCF
Queue name	(ApplicationName)/SFMS_INQUEUE

For details on creation of necessary resources, refer to the chapter 'Resource_Creation_WL'.

The '(ApplicationName)' is not mandatory in all the cases. If the environment has only one application with scheduler, you may create the JMS resources with or without 'ApplicationName'.

E.g.: NOTIFY_MDB_QCF

However, if the environment has more than one application with scheduler, the JMS resource names must contain the 'ApplicationName' of the respective application.

E.g.: The environment has two applications, viz. FCIS1 and FCIS2. In that case, you need to create two sets of JMS resources as follows:

- Set of JMS resources with the 'ApplicationName' FCIS1 - FCIS1/NOTIFY_MDB_QCF
- Set of JMS resources with the 'ApplicationName' FCIS2 - FCIS2/NOTIFY_MDB_QCF

1.3 **Prerequisites for Gateway Application**

There are four gateway applications. The prerequisites for each are discussed under the following headings.

1.3.1 **Prerequisites for Gateway EJB Application**

You need to create the following data sources for JDBC resources:

Resource	Example
XA data source for Gateway EJB Application	FLEXTTEST.WORLD and POSSTEST.WORLD

For details on creation of necessary resources, refer to the chapter 'Resource_Creation_WL.doc.

1.3.2 Prerequisites for Gateway MDB Application

You need the following JDBC resource:

Resource	Example
XA data source for Gateway EJB Application	FLEXTTEST.WORLD and POSSTEST.WORLD

You need the following JMS resource:

Resource	Example
XA enabled Connection Factory	MDBQCF
Queue name	MDB_QUEUE
Queue name	MDB_QUEUE_RESPONSE
Queue name	MDB_QUEUE_DLQ

For details on creation of necessary resources, refer to the chapter 'Resource_Creation_WL.doc.

1.3.3 Prerequisites for Gateway HTTP Application

For Gateway HTTP Application, ensure that the EJB Application is already deployed.

1.3.4 Prerequisites Gateway Web Service Application

For Gateway Web Service Application, ensure that the EJB Application is already deployed.

2. Creating Property File for Oracle FLEXCUBE Investor Servicing


2.1 Introduction

This chapter explains the steps to create property files for Oracle FLEXCUBE Investor Servicing Application.

2.2 Creating Property File


To create the property file for Oracle FLEXCUBE Investor Servicing, follow the steps given below:

1. Launch Oracle FLEXCUBE Investor Servicing Installer.



2. Choose 'Universal Banking Solution'. Click 'Next'.

The following screen is displayed:



3. Choose the option 'Property File'.
4. Specify the following details:

Operating System and Version

Specify the operating system in which you are creating the property file. Choose the appropriate one from the drop-down list. You also need to specify the version of the selected operating system.


Application Server and Version

Specify the application server in which you are creating the property file. Choose the appropriate one from the drop-down list. You also need to specify the version of the selected application server.


Database Server and Version

Specify the database server in which you are creating the property file. Choose the appropriate one from the drop-down list. You also need to specify the version of the selected database server.

5. Once you have specified the details, click 'Next' to continue. The following screen is displayed.



6. Select the type of application deployment. You can choose one of the following options:
 - **Centralized:** Choose if you require centralized installation.
 - **Decentralized:** Choose if you require decentralized installation. In this case, Installer generates the following files at the end of the build process:
 - {Application_name}.ear – This can be deployed as Decentralized Host Application
 - {Application_name}.war – This can be deployed as Decentralized Branch Application
 - **Hybrid:** Choose if you require Hybrid Installation. In this case, the Installer generates the following files at the end of the build process:
 - {Application_name}.ear - This can be deployed as Centralized Host Application
 - {Application_name}.war This can be deployed as Decentralized Branch Application
7. Click 'Next'. Based on the application deployment type selected, the Installer will navigate to the appropriate screen. See the following steps for details.
8. In case of **centralized deployment**, the following screen is displayed.




9. Specify the following details:

Centralized Property File

The property file needs to be built before the EAR file. If you are creating a new property file, leave the field blank. If you wish to modify an existing property file, you can manually specify the location of the property file.

10. In case of **decentralized deployment**, the following screen is displayed.



11. Specify the following details:


Host Property File

If you are creating a new property file, you can leave this field blank. However, if you wish to modify an existing property file, specify the location. You can use the directory button to browser and select the directory.

Web Property File

If you are creating a new property file, you can leave this field blank. However, if you wish to modify an existing property file, specify the location. You can use the directory button to browser and select the directory.

12. In case of **hybrid deployment**, the following screen is displayed.



13. Specify the following details:

Centralized Property File

If you are creating a new property file, you can leave this field blank. However, if you wish to modify an existing property file, specify the location. You can use the directory button to browser and select the directory.

Decentralized Property File


If you are creating a new property file, you can leave this field blank. However, if you wish to modify an existing property file, specify the location. You can use the directory button to browser and select the directory.

Click 'Next' to continue.

2.2.1 Setting Oracle FLEXCUBE Investor Servicing Plug-ins

This section describes the process of setting plug-ins.

1. You can select the plug-ins from the following screen.



2. You need to select the plug-ins to be included in the installation. Check the box against the required plug-ins. The following plug-ins are available for Oracle FLEXCUBE Investor Servicing:
 - BPEL
 - Document Management System
 - Reports
 - Scheduler
3. Once you have selected the plug-ins, click 'Next'. You will be navigated to the 'Common Properties' screen.


Note the following:

- The Installer allows you to set the properties for the selected plug-ins only.
- If the deployment type is 'Decentralized', then you can have only 'Reports' as a plug-in. You cannot select the other plug-ins in decentralized deployment.

2.2.2 Setting Common Properties

This section describes the process of setting common properties of Oracle FLEXCUBE Investor Servicing.

1. The installer displays the 'Common Properties' screen.



2. The following are the common properties required for FCIS Application:

Debug

If you require debug option, select 'Yes' from the drop-down list. If you do not require debug option, select 'No'.

Signature Path

Specify the location at which the signature images will be placed.

Excel Path

Specify the location at which the excel files will be generated.

Data Source

Specify the JNDI location. The standard format is 'jdbc/fcisdevDS'.

Request Time Out

Specify the database request timeout value in seconds. This is the maximum number of seconds the database will wait for a query to return the result.

Connection Time Out

Specify the database connection timeout value in seconds. This is the maximum number of seconds the application will wait for a connection to the database to open.

Session Time Out


Enter the session time out value in seconds. This is the maximum number of seconds during which the application will be active without any user intervention. If there is no user intervention continuously for the duration specified here, then the user session will expire.

LOV Fetch Required

If you check this box, the option lists in Oracle FLEXCUBE Investor Servicing will display the matching values based on the first characters that you enter in a field. That is, if you specify the first three characters of a value to be entered in an option list and tab out, the system will display the complete list of values that are matching the first three characters.

If you do not check this, option lists will not show the matching values based on the first few characters. You need to specify the complete value against the field.

3. Click 'Next'. The following screen is displayed.



4. Specify the following details:

SSO Required

Check this box to enable single sign-on (SSO). If you check this box, you need to enter the SSO Key.


SSO Key

Specify the SSO key. If you have checked the box 'SSO Required', it is mandatory to specify the SSO key.

If you have checked the box 'SSO Required', the Installer will skip the following two screens and directly navigate to the SSL screen shown below in this manual.

If you have not checked the box 'SSO Required', then on clicking the 'Next' button, the following screen is displayed.

5. Here you need to specify the external authentication details.



Specify the following details:

MSAD/LDAP User Login Required

Check this box to enable user login using MSAD or LDAP user ID. If you check this, the user can login with MSAD/LDAP server user ID as well as FCUBS user ID. If you do not check this, the user can login with FCUBS user ID only.

By default, this check box is unchecked. However, you can change this.

External Password Required

Check this box to allow user login using MSAD or LDAP password irrespective of the user ID. If you check this box, the user can login with MSAD/LDAP server password only. The user ID can be either the MSAD/LDAP user ID or FCUBS user ID.

By default, this check box is unchecked. However, you can change this.

If you do not check this box, the installer skips the following screen and directly navigates you to the SSL screen shown below in this manual.

If you check the box 'External Password Required', the installer navigates to the following screen on clicking 'Next' button.

Note: On checking option 'MSAD/LDAP User Login Required' or 'External Password Required' the 'Authentication Type' is enabled.


Authentication Type

Select the authentication type. This is the type of external server that is used. You can select one of the following options:

- MSAD (Microsoft Active Directory)
- LDAP (Lightweight Directory Access Protocol)

The default option is MSAD; however, you can change it.

6. Here you need to specify the LDAP server details.



The screenshot shows the 'Oracle FLEXCUBE Investor Service' window with the 'Property File Creation' section. Under 'LDAP Server Details', there is a table with 5 rows and 3 columns: No., Name, and Value.

No.	Name	Value
1	LDAP SERVER URL	LDAP://10.184.75.249:389
2	LDAP SSL ENABLED	<input checked="" type="checkbox"/>
3	SECURITY AUTHENTICATION TYPE	simple
4	DOMAIN NAME	I-FLEX.COM
5	LDAP SERVER TIMEOUT	0

At the bottom of the window, there are buttons for 'Log', 'Back', 'Next', and 'Exit'.

Specify the following details:

LDAP Server URL

Specify the URL to access the LDAP server where the external user ID/passwords are maintained.

LDAP SSL Enabled

Check this box if the LDAP server is SSL enabled. If you check this box, then you need to specify the SSL port also in the field LDAP SERVER URL.

By default, this check box is unchecked. However, you can change this.

Security Authentication Type

Depending on the authentication mechanism supported by the LDAP server, you need to select 'SIMPLE' (in most cases) or 'STRONG'. Different servers support different authentication mechanisms.

By default, the security authentication type is SIMPLE. However, you can change this.

Domain Name


Specify the domain name.

LDAP Server Timeout

Specify the LDAP server timeout in milliseconds. This must be a positive integer value. For example you can specify 1000, 10000 or 5000. If it is zero or less, it indicates that no read timeout is specified. Then the wait for the response infinite until it is received.

By default, the LDAP server timeout is zero. However, you can change this.


7. Click 'Next'. The following screen is displayed.



8. Specify the following details.

SSL Enabled

Indicate whether SSL is enabled or not. If SSL is required, choose 'Yes'. If SSL is not enabled, the Installer will pop-up a window.




However, it is recommended that you enable SSL.

9. Click 'Next'. You will be navigated to the next screen.

2.2.3 Setting Language Properties

This section describes the process of setting language packs of Oracle FLEXCUBE Investor Servicing.

1. The system displays the following screen.



2. Specify the following details.

Language

Specify the language in which you wish to see Oracle FLEXCUBE Investor Servicing. English is the default language. However, based on the requirement, you can set a different language. Choose the appropriate one from the drop-down list.

Based on the language selected, the installer displays the ISO code.

Application Title

Specify the application title.

E.g.: FLEXCUBE IS

Version

Specify the application version.

E.g.: 12.0.0

Copy Rights

Specify the copyright details.


E.g.: Copyright@2007-2012 Oracle Financial Software Services Limited. All rights reserved.

3. Once you have specified the details, click 'Next'. You will be navigated to the CSS setting screen.

2.2.4 **Setting CSS Style**

This section describes the process of setting CSS style.

1. The following screen is displayed.



2. Specify the following details:

CSS Style

Specify the CSS style to be used. You can choose one of the following CSS styles:

- Default – choose this to apply the default style provided along with Oracle FLEXCUBE Investor Servicing
- Custom – choose this to apply a custom style

Name


Specify the name of the CSS style.

3. Once you have specified the above details, click 'Next'. You will be navigated to the Hashing Algorithm Count Settings screen.

2.2.5 **Setting Hashing Algorithm Iteration Count**

This section describes the method of setting hashing algorithm iteration count.

1. The following screen is displayed.



2. Specify the following details:

Hashing Algorithm Iteration Count


Specify the hashing algorithm iteration count. This count implies the time required for logging into the application. An increase in this count increases the login time.

3. Once you have specified the details, click 'Next'.

2.2.6 Setting Email Details

This section describes the method to configure email details.

1. The following screen is displayed.



2. Specify the following details.

Host

Specify the SMTP host name.

User ID

Specify the user ID.

User Password

Specify the user password.

JNDI Name


Specify the JNDI name.

3. Once you have specified the above details, click 'Next'.

2.2.7 Setting BPEL Properties

This section describes the methods to set BPEL properties.

1. The following screen is displayed.



2. Specify the following details:

Factory Initial

Specify the factory initial.

Provide URL

Specify the URL of the server. The URL includes the IP address, target server, port (AdminServer/ManagedServer) and the context root.

The URL may be as follows:

- For Websphere: iiop://localhost:2809 (2809 is the default iiop port)
- For Websphere(SSL): iiops://localhost:2809 (2809 is the default iiop port)
- For Weblogic: t3://localhost:7001 (7001 is the default port)
- For Weblogic(SSL): t3s://localhost:7001 (7001 is the default port)

Security Principal

Specify the user name.

Security Credentials

Specify the password for the above user name.

Domain Name

Specify the domain name. By default, the Installer displays 'default'.

Domain Password

Specify the domain password for which SOA server is extended.

Dedicated Connection

Check to indicate that the connection is dedicated for this activity.

3. Once you have specified the above details, click 'Next'.

No.	Name	Value
1	BI User
2	BI Password

4. Specify the following details:


BI User Name

Specify the BI user name.

BI Password

Specify the password for the above user name.

5. Click 'Next'. The following screen is displayed.




6. In this screen, you can modify the BPEL load balancing properties. Specify the details and click 'Next'.

2.2.8 Setting DMS Properties

This section describes the methods to set DMS properties. This is applicable only if you have selected to include DMS plug-in.

1. The following screen is displayed.



2. Click 'Next'. The following screen is displayed.

Oracle FLEXCUBE Investor Service **ORACLE**

Property File Creation
Current screen provides an option for modifying the ORACLE I/PM property values.

No.	Name	Value
1	Login Service Address	http://127.0.0.1:16000/imaging/ws/LoginService
2	Document Service Ad...	http://127.0.0.1:16000/imaging/ws/DocumentService
3	Document Content Se...	http://127.0.0.1:16000/imaging/ws/DocumentConte...
4	IPM User Name
5	IPM Password
6	IPM Application Name	OFSS
7	Http Session Maintain	<input checked="" type="checkbox"/>

Log 4 of 12 Back Next Exit

3. Specify the following details:

Login Service Address

Specify the end point address of the web service.

Document Service Address

Specify the URL to which the document should be uploaded by the IPM adapter.

Document Content Service Address

Specify the URL to which the document should be uploaded by the IPM adapter.

IPM User Name

Specify the user name to access Oracle IPM.

IPM Password

Specify the password for the above user name.

IPM Application Name

Specify the IPM application against which the authentication is done.

HTTP Session Maintain

Check this box to indicate that an HTTP session needs to be maintained. If you do not check this, it denotes that the HTTP session maintenance is not required.

4. Once you have specified the above details, click 'Next'.

2.2.9 Setting Report Properties

This section describes the methods to set report properties.

1. The following screen is displayed.

Oracle FLEXCUBE Universal Installer 12.0.0

Oracle FLEXCUBE Investor Service ORACLE

Property File Creation
Current screen provides an option for modifying the Oracle BI Publisher properties.

No.	Name	Value
1	Server End Point	http://cvrhp0707:9704/xmlpserver/services/Publi...
2	NAME SPACE	http://xmlns.oracle.com/oxp/service/PublicRepo...
3	User Name	Administrator
4	Password
5	Reports Spool Path	D:\
6	Advice Type	NATIVE
7	BIP Server Version	10g
8	BIP Time Zone	IST

Log 5 of 14 Back Next Exit

2. Specify the following details:

Server End Point

Specify the BIP end point.

The default value is 'http://cvrhp0707:9704/xmlpserver/services/PublicReportService_v11?wsdl'. However, you need to change the URL based on the IP and port where BIP Application is installed.

Name Space

Specify the BIP name space.

By default, the installer displays 'http://xmlns.oracle.com/oxp/service/PublicReportService'.

User Name

Specify the BIP user name. By default, the Installer displays 'Administrator'.

Password

Specify the password for the above user name. By default, the Installer sets it as 'Administrator'.

Reports Spool Path

Specify the reports spool path. By default, the Installer displays 'D:\\BrnDbgs\\ADV\\'.

Advice Type

Specify the advice type. You can choose one of the following:

- NATIVE – This advice type is used for generating advices in text format
- BIP – This advice type is used for generating advices in PDF format.

BIP Server Version

Specify the qualified BIP server version. You can select the appropriate one from the drop-down list.

BIP Time Zone


Specify the time zone of the BIP server.

3. Once you have specified the above details, click 'Next'.


2.2.10 Configuring Scheduler

This section describes the method to configure scheduler data source.

1. The following screen is displayed.



2. Specify the Scheduler Datasource which Oracle FLEXCUBE Investor Servicing will access.
3. Click 'Next'. The following screen is displayed.



4. Specify the following details:

Notify Destination

Specify the notify destination. Choose one of the following options:

- QUEUE
- TOPIC

Queue Connection Factory

Set 'NotifyDestQCF' as the destination connection factory.

Queue Name

Set 'NOTIFY_DEST_QUEUE' as the destination queue name.

Topic Connection Factory

Set 'NotifyDestTCF' as the destination connection factory.

Topic Name

Set 'NOTIFY_DEST_QUEUE' as the destination queue name.

Notify Queue Location

Specify the notify queue location. Choose one of the following options:

- Internal
- External

Note: For Oracle WebLogic application server, the notify queue location should be selected as 'Internal'.

If you choose '**External**', you will be navigated to the following screen. Here you can specify the external queue details.

No.	Name	Value
1	Provide Uri	iiop://localhost:2809
2	Security Principal
3	Security Credential

You need to specify the following details of the external queue.

Provider URL

Specify the provide URL (iiop://localhost:2809).

2809 is the default IIOP port.


Security Principal

Specify the login ID to access the application server.

Security Credentials

Specify the password to access the application server.

If you choose '**Internal**', you will be navigated to the following screen. Here you can specify the external queue details.



Specify the following details:

Notify Queue Connection Factory

Set 'NOTIFY_MDB_QCF' as the notify connection factory.

Notify Queue Name

Set 'NOTIFY_QUEUE' as the notify queue name.

DeadLetter Queue Connection Factory

Set 'NOTIFY_MDB_QCF' as the DeadLetter connection factory.

DeadLetter Queue Name

Set 'NOTIFY_QUEUE_DLQ' as the DeadLetter queue name.

Deferred Queue Connection Factory

Set 'DeferredDestQCF' as the deferred connection factory.

Deferred Queue Name

Set 'DEFERRED_DEST_QUEUE' as the deferred queue name.

Note: The values provided here should be the same as the values provided while creating resources for Oracle WebLogic/IBM WebSphere.

For further details, refer to the chapters 'Resource Creation for Oracle WebLogic' and 'Resource Creation for IBM WebSphere'.

5. Once you have captured the details, click 'Next'.

No.	Name	Value
1	Queue Auto Acknowledge	AUTO_ACKNOWLEDGE
2	Queue Trasaction	<input checked="" type="checkbox"/>
3	Queue Delivery Option	2
4	Queue Time To Live	0
5	Queue Priority	1

6. Specify the following details:
- Queue Auto Acknowledge
 - Queue Transaction
 - Queue Delivery Option
 - Queue Time to Live
 - Queue Priority

Note: For IBM WebSphere application server, you need to specify the following additional details.

Scheduler EJB Lookup Type

Set this to 'LOCAL' if you deploy the Application on IBM WebSphere application server. In case of you deploy the Application on other application servers, set this to 'REMOTE'.

When the scheduler EJB lookup type is set to 'LOCAL', it is mandatory to set the following properties.

Initial Context Factory

Specify the initial context factory (com.ibm.websphere.naming.WsnInitialContextFactory).

Provider URL

Specify the provide URL (iiop://localhost:2809).

2809 is the default IIOP port.

Security Principal

Specify the login ID to access the application server.

Security Credentials

Specify the password to access the application server.

Scheduler EJB JNDI Name

This is defaulted to 'ejb/SchedulerEJBHome'. You will have to provide the JNDI name of the scheduler EJB while deploying the application.

Note: Ensure that the properties set here match the properties set during JMS Destination and JMS Connection Factories.


For further details on creating JMS destination and connection factories, refer to the chapter 'Resource_Creation_WL.doc'.

7. Once you have set the above properties, click 'Next'.

2.2.11 Setting EMS Properties

You will be navigated to the 'Scheduler EMS Properties' screen. Here, you need to set the EMS details.

1. Set the EMS properties:



Oracle FLEXCUBE Universal Installer 12.0.0

Oracle FLEXCUBE Investor Service ORACLE

Property File Creation
Current screen provides an option for Scheduler EMS Queue configuring.

No.	Name	Value
1	Outgoing Queue Connection Factory	EmsQcf
2	Incoming Queue Connection Factory	EmsQcf
3	Outgoing Queue Name	NOTIFY_QUEUE_DLQ
4	Incoming Queue Name	NOTIFY_QUEUE_DLQ
5	Incoming backup Queue Name	NOTIFY_QUEUE_BACK
6	Outgoing Queue Provider Url	t3://127.0.0.1:7001
7	Queue Principal	infra
9	Queue Credential

Log 11 of 14 Back Next Exit

2. Specify the following details:

OutGoing Connection Factory

Specify the name of the outgoing connection factory to which EMS listens. You need to create this connection factory at the application server.

For details on connection factory creation, follow the steps described for creation of notify connection factories.

Incoming Connection Factory

Specify the name of the incoming connection factory to which EMS listens. You need to create this connection factory at the application server.

For details on connection factory creation, follow the steps described for creation of notify connection factories.

Outgoing Queue Name

Specify the name of the outgoing queue for which EMS is configured. By default, this is set as 'NOTIFY_QUEUE_DLQ'.

Incoming Queue Name

Specify the name of the incoming queue for which EMS is configured. By default, this is set as 'NOTIFY_QUEUE_DLQ'.

Incoming Backup Queue Name

Specify the name of the incoming backup queue for which EMS is configured.

Outgoing Queue Provider URL

In case EMS OUT MDB is to be configured to queue, you need to specify the URL for outgoing provider based on the application server. By default, the Installer displays the outgoing queue provider URL for Oracle WebLogic.

This value is application server dependent.

The details of Outgoing Queue Provider URL to be used for different application servers are given below:

Application Server	EMS Out Initial Context Factory
Oracle WebLogic	t3://<ip_address>:port E.g.: t3://127.0.0.1:7001 Here, 127.0.0.1 represents the local host and 7001 to the target server default port (AdminServer/ManagedServer).
IBM WebSphere	iiop://<ip_address>:port E.g.: iiop://127.0.0.1:2809 Here, 2809 represents the default iiop port

Queue Principal

If EMS OUT MDB has to be configured to queue, you need to specify the EMS out queue principal. This is the user name for the application server in which the queue is configured.

Queue Credential

If EMS OUT MDB has to be configured to queue, you need to specify the EMS out queue credential. This is the password for the above user name created for application server in which the queue configured.

3. Once you have specified the above details, click 'Next'.

No.	Name	Value
1	File TransferMode FTPS	FTPS
2	Server	127.0.0.1
3	User id	OFSS
4	Password
5	File Type	.txt
6	Swift Format	1
7	Swift Message Delimiter	<input checked="" type="checkbox"/>
8	Swift Message Terminator	<input checked="" type="checkbox"/>

4. Specify the following details:

File Transfer Mode FTPS

Specify the mode of transferring files to EMS. Choose one of the following:

- FTPS
- SFTP
- HTTP

Server

Specify the server IP address for the selected file transfer mode.

User ID

Specify the user ID to access the server of the file transfer mode.

Password

Specify the password to for the above user ID.

File Type

Specify the type of file that is transferred. By default, the Installer sets it as '.txt'.

Swift Format

Specify the format used for swift messages.

SWIFT Message Delimiter

Specify the character which is used as the message delimiter.

SWIFT Message Terminator

Specify the character which is used as the message terminator.

5. Once you have specified the above details, click 'Next'. The following screen is displayed.

No.	Name	Value
1	Signature Block	<input checked="" type="checkbox"/>
2	Keystore File Name	/keystore
3	Keystore Alias name
4	keystore Password

6. Specify the following details:

Signature Block

Check this box to enable signature block.

Keystore File Name

Specify the keystore file name.

Keystore Alias Name

Specify the keystore alias name.

Keystore Password


Specify the keystore password.

7. Once you have specified the above details, click 'Next'.


2.2.12 Setting Oracle IPM Adapter Properties

If you have included DMS in the installation, then you need to set the Oracle IPM adapter properties. Navigate to 'Oracle IPM DMS Properties' screen.

1. Set the server type in the following screen.



2. Choose 'Oracle IPM' as the server type.
3. Click 'Next', the following screen is displayed.



4. You can modify the following Oracle I/PM property values:

Login Service Address

This is the endpoint address of the web service (OracleIPM.WebService.EndpointAddress).

Document Service Address

This is the URL to which the Oracle IPM adapter uploads the documents (OracleIPM11G.DocumentService.EndpointAddress).

Document Content Service Address

This is the URL to which the Oracle IPM adapter uploads the documents (OracleIPM11G.DocumentContentService.EndpointAddress).

IPM User Name

This is the user name accessing Oracle IPM (OracleIPM11G.Authentication.UserName).

IPM Password

This is the password for the above IPM user name (OracleIPM11G.Authentication.Password).

IPM Application Name

This indicates the license that provides login rights to Oracle IPM (OracleIPM11G.Application).

HTTP Session Maintain

This checkbox indicates whether HTTP session must be maintained or not (OracleIPM11G.MaintainSession).

Permanent Delete


This checkbox indicates whether a document must be permanently deleted or not (OracleIPM11G.PermanentDelete).

5. Once you have confirmed/modified the above details, click 'Next'.


2.2.13 Saving Property File

After completing all the required settings explained above, you need to save the property file.


1. Save the property file.



2. You can view the status of property file creation in the above screen. Once the file is saved, the installer displays the following message.



3. If you do not use the 'Save' or 'Save As' buttons, the installer will save the properties file in '<InstallerSources>\config\PropertyFiles' folder. In that case, you will see the message below.



4. This completes the properties file creation.

3. Creating Property File for Gateway Applications


3.1 Introduction

This chapter explains the steps to create the property file for the gateway components viz. Enterprise Java Bean (EJB), Message Driven Beans (MDB) and Web Services and Servlet.

3.2 Creating Property Files

Follow the steps given below:


1. Start Oracle FLEXCUBE Investor Servicing Installer 1.0. Welcome screen is displayed.



2. Select 'Oracle FLEXCUBE Gateway' and click 'Next'.

3.2.1 Gateway EJB Application

The following screen is displayed:



1. Choose the option 'Property File'.
2. Specify the following details:

Operating System and Version

Specify the operating system in which you are creating the property file. Choose the appropriate one from the drop-down list. You also need to specify the version of the selected operating system.


Application Server and Version

Specify the application server in which you are creating the property file. Choose the appropriate one from the drop-down list. You also need to specify the version of the selected application server.


Database Server and Version

Specify the database server in which you are creating the property file. Choose the appropriate one from the drop-down list. You also need to specify the version of the selected database server.

3. Once you have specified the details, click 'Next' to continue. The following screen is displayed.



4. Select 'Gateway EJB'.
5. Click 'Next'. The following screen is displayed.




6. Specify the following details:

Load Property File

If you are creating a new property file, leave the field blank. If you wish to modify an existing property file, you can manually specify the location of the property file.

Note: Before proceeding, ensure that the folder structures used in the following steps are created.

7. Click 'Next'. The following screen is displayed:



8. Specify the following details.

XSD Path

Specify the path to the XSD file. File name is not required. File separator must be '/'. There must be a '/' at the end. All the relevant XSD files must be manually copied to this location.

E.g.:

For windows: D:\Kernel11.1\GW_EJB\XSD\

For Linux: /Kernel11.1/GW_EJB/XSD/

Logger File

Specify the path to the 'gw_ejb_logger.properties' file with the file name. The file must be manually copied to the specified location.

E.g.:

For windows: D:\Kernel11.1\GW_EJB\config\gw_ejb_logger.properties

For Linux: /Kernel11.1/GW_EJB/config/gw_ejb_logger.properties

Debug Path

Specify the path to the folder where the application creates the logs. There must be a '/' at the end. You need to manually create the specified folder structure.


E.g.:

For windows: D:\Kernel11.1\GW_EJB\log\

For Linux: /Kernel11.1//GW_EJB/log/

9. Click 'Next'.

Note: The Installer creates two files viz. 'gw_ejb_logger.xml' and 'GW_EJB_Prop.xml' in the path provided to save the files.



10. Specify the following details:

DataSource

The JDBC data source is an object bound to JNDI tree and provides database connectivity through a pool of JDBC connections.

POSS Datasource


Check this box if POSS is required. If you check this box, you need to specify the POSS Datasource Name in the field below this.

Distributed Schema

If the schema is distributed, select 'Yes'.

If the schema is not distributed, select 'No'.

11. Click 'Next'. The following screen is displayed.




12. Click 'Continue' to continue the installation process with gateway application type.

13. Click 'Next' to navigate to the installer home screen.

3.2.2 Gateway MDB Application

Follow the steps given below:

1. Start Oracle FLEXCUBE Investor Servicing Installer. Select 'Gateway' and click 'Next'. Following screen is displayed.



2. Choose the option 'Property File'.
3. Specify the following details:

Operating System and Version

Specify the operating system in which you are creating the property file. Choose the appropriate one from the drop-down list. You also need to specify the version of the selected operating system.


Application Server and Version

Specify the application server in which you are creating the property file. Choose the appropriate one from the drop-down list. You also need to specify the version of the selected application server.

Database Server and Version


Specify the database server in which you are creating the property file. Choose the appropriate one from the drop-down list. You also need to specify the version of the selected database server.

4. Click 'Next'. The following screen is displayed.



5. Select 'Gateway MDB' to create configuration files for the application. Click 'Next'.

Following screen is displayed:




6. Specify the following details:

Load Property File

If you are creating a new property file, leave the field blank. If you wish to modify an existing property file, you can manually specify the location of the property file.

Note: Before proceeding, ensure that the folder structures used in the following steps are created.

7. Click 'Next'. The following screen is displayed:



8. Specify the following details.

XSD Path

Specify the path to the XSD file. File name is not required. File separator must be '/'. There must be a '/' at the end. All the relevant XSD files must be manually copied to this location.

E.g.:

For Windows: D:\Kernel11.1\GW_MDB\XSD\

For Linux: /Kernel11.1/GW_MDB/XSD/

Logger File

Specify the path to the 'gw_mdb_logger.properties' file with the file name. The file must be manually copied to the specified location.

E.g.:

For windows: D:\Kernel11.1\GW_MDB\config\gw_mdb_logger.properties

For Linux: /Kernel11.1/GW_MDB/config/gw_mdb_logger.properties

Debug Path

Specify the path to the folder where the application creates the logs. There must be a '/' at the end. You need to manually create the folder structure.


E.g.:

For windows: D:\Kernel11.1\GW_MDB\log\

For Linux: /Kernel11.1/GW_MDB/log/

9. Click 'Next'.

Note: The Installer creates two files viz. 'gw_mdb_logger.xml' and 'GW_MDB_Prop.xml' in the path provided to save the files.



10. Specify the following details:

DataSource

The JDBC data source is an object bound to JNDI tree and provides database connectivity through a pool of JDBC connections.

POSS Datasource

Check this box if POSS is required. If you check this box, you need to specify the POSS Datasource Name in the field below this.


Distributed Schema

If the schema is distributed, select 'Yes'.

If the schema is not distributed, select 'No'.

Note: The Installer creates two files viz. 'gw_mdb_logger.xml' and 'GW_MDB_Prop.xml' in the path provided to save the files.

11. Click 'Next'. The following screen is displayed.



12. Specify the following details:

Connection Factory

Specify the connection configuration parameters to create connections for JMS clients.

E.g.: MDBQCF.

Request Queue

Specify the request queue. This is the point-to-point destination type used for asynchronous peer communication.

E.g.: MDB_QUEUE

Response Queue

Specify the response queue name.

E.g.: MDB_QUEUE_RESPONSE


DL Queue

Specify the dead letter queue name.

E.g.: MDB_QUEUE_DLQ

Note: The Installer creates two files viz. 'gw_mdb_logger.xml' and 'GW_MDB_Prop.xml' in the path provided to save the files.

13. Click 'Next'. The following screen is displayed.




14. Click 'Continue' to continue the installation process with gateway application type.

15. Click 'Next' to navigate to the installer home screen.

3.2.3 Gateway HTTP Application

Follow the steps given below:

1. Start Oracle FLEXCUBE Investor Servicing Installer. Select 'Gateway' and click 'Next'. Following screen is displayed.



2. Choose the option 'Property File'.
3. Specify the following details:

Operating System and Version

Specify the operating system in which you are creating the property file. Choose the appropriate one from the drop-down list. You also need to specify the version of the selected operating system.


Application Server and Version

Specify the application server in which you are creating the property file. Choose the appropriate one from the drop-down list. You also need to specify the version of the selected application server.


Database Server and Version

Specify the database server in which you are creating the property file. Choose the appropriate one from the drop-down list. You also need to specify the version of the selected database server.

4. Once you have specified the details, click 'Next' to continue. The following screen is displayed.



5. Select 'Gateway Http Servlet' to create configuration files for the application, and click 'Next'. Following screen is displayed.




6. Specify the following details:

Load Property File

If you are creating a new property file, leave the field blank. If you wish to modify an existing property file, you can manually specify the location of the property file.

Note: Before proceeding, ensure that the folder structures used in the following steps are created.

7. Click 'Next'. The following screen is displayed:



8. Specify the following details.

XSD Path

Specify the path to the XSD file. File name is not required. File separator must be '/'. There must be a '/' at the end. All the relevant XSD files must be manually copied to this location.

E.g.:

For Windows: D:\Kernel11.1\GW_HTTP\XSD\

For Linux: /Kernel11.1 /GW_HTTP/XSD/

Logger File

Specify the path to the 'gw_http_logger.properties' file with the file name. The file must be manually copied to the specified location.

E.g.:

For windows: D:\Kernel11.1\GW_HTTP\config\gw_http_logger.properties

For Linux: /Kernel11.1/GW_HTTP/config/gw_http_logger.properties

Debug Path

Specify the path to the folder where the application creates the logs. There must be a '/' at the end. You need to manually create the folder structure.

E.g.:


For windows: D:\Kernel11.1\GW_HTTP\log\

For Linux: /Kernel11.1/GW_HTTP/log/

9. Click 'Next'.

Note: The Installer creates two files viz. 'gw_http_logger.xml' and 'GW_HTTP_Prop.xml' in the path provided to save the files

10. The following screen is displayed.



11. Specify the following details:

EJB Application Name

Specify the name of the EJB application deployed.

E.g.: GWEJB

12. Click 'Next'. The following screen is displayed.

No.	Name	Value
1	EJB JNDI Name	ejb/GW_EJB_Bean
2	Application Server IP	http://10.184.74.143
3	EJB Port	7002
4	User Name	infra
5	Password

13. Specify the following details:

EJB JNDI Name

This is the reference name of the EJB by which it has been deployed. This should be '<EJB_APPLICATION_NAME>_GW_EJB_Bean'

E.g.: GWEJB_GW_EJB_Bean

If you build the EJB application with GWEJB name, this should be the name with which the EJB EAR file is built.

If you select EJB Call Type as REMOTE, this should be '<EJB_APPLICATION_NAME>/ejb/GW_EJB_Bean'.

E.g.: GWEJB/ejb/GW_EJB_Bean

If you build the EJB application with GWEJB name, this should be the name the EJB EAR file which is built.

Application Server IP

Specify the IP address of the application server where the EJB application is deployed.

E.g.: localhost

EJB Port

Specify the EJB port number on application server.

E.g.: 7001

User Name

Specify the user name to access the application server where the EJB application is deployed.


E.g.: oc4jadmin

Password

Specify the password for the above user name.

Note: The Installer creates two files viz. 'gw_http_logger.xml' and 'GW_HTTP_Prop.xml' in the path provided to save the files.

14. Click 'Next'. The following screen is displayed.



15. Click 'Continue' to continue the installation process with gateway application type.

16. Click 'Next' to navigate to the installer home screen.


The property file will be created in the specified folder.

3.2.4 Gateway Web Service Application

Follow the steps given below:

1. Start Oracle FLEXCUBE Investor Servicing Installer. Select 'Gateway' and click 'Next'.

Following screen is displayed.



2. Choose the option 'Property File'.
3. Specify the following details:

Operating System and Version

Specify the operating system in which you are creating the property file. Choose the appropriate one from the drop-down list. You also need to specify the version of the selected operating system.


Application Server and Version

Specify the application server in which you are creating the property file. Choose the appropriate one from the drop-down list. You also need to specify the version of the selected application server.


Database Server and Version

Specify the database server in which you are creating the property file. Choose the appropriate one from the drop-down list. You also need to specify the version of the selected database server.

4. Click 'Next'.



5. Select 'Gateway WebServices' to create configuration files for the application. Click 'Next'. The following screen is displayed.




6. Specify the following details:

Load Property File

If you are creating a new property file, leave the field blank. If you wish to modify an existing property file, you can manually specify the location of the property file.

Note: Before proceeding, ensure that the folder structures used in the following steps are created.

7. Click 'Next'. The following screen is displayed:



8. Specify the following details.

XSD Path

Specify the path to the XSD file. File name is not required. File separator must be '/'. There must be a '/' at the end. All the relevant XSD files must be manually copied to this location.

E.g.:

For Windows: D:\Kernel11.1\GW_WS\XSD\

For Linux: //GW_WS/XSD/

Logger File

Specify the path to the 'gw_ws_logger.properties' file with the file name. The file must be manually copied to the specified location.

E.g.:

For windows: D:\Kernel11.1\GW_WS\config\gw_ws_logger.properties

For Linux: /Kernel11.1/GW_WS/config/gw_ws_logger.properties

Debug Path

Specify the path to the folder where the application creates the logs. There must be a '/' at the end. You need to manually create the folder structure.

E.g.:


For windows: D:\Kernel11.1\GW_WS\log\

For Linux: /Kernel11.1/GW_WS/log/

9. Click 'Next'.

Note: The Installer creates two files viz. 'gw_ws_logger.xml' and 'GW_WS_Prop.xml' in the path provided to save the files.

10. The following screen is displayed.



11. Specify the following details:

EJB Application Name

Specify the name of the EJB application deployed.

E.g.: GWEJB

12. Click 'Next'. The following screen is displayed.

13. Click 'Next'. The following screen is displayed.

No.	Name	Value
1	EJB JNDI Name	/ejb/GW_EJB_Bean
2	Application Server IP	http://10.184.74.143
3	EJB Port	7002
4	User Name	infra
5	Password	*****

14. Specify the following details:

EJB JNDI Name

This is the reference name of the EJB by which it has been deployed. This should be '`<EJB_APPLICATION_NAME>_GW_EJB_Bean`'

E.g.: GWEJB_GW_EJB_Bean

If you build the EJB application with GWEJB name, this should be the name with which the EJB EAR file is built.

If you select EJB Call Type as REMOTE, this should be '`<EJB_APPLICATION_NAME>/ejb/GW_EJB_Bean`'.

E.g.: GWEJB/ejb/GW_EJB_Bean

If you build the EJB application with GWEJB name, this should be the name the EJB EAR file which is built.

Application Server IP

Specify the IP address of the application server where the EJB application is deployed.

E.g.: localhost

EJB Port

Specify the EJB port number on application server.

E.g.: 7001

User Name

Specify the user name to access the application server where the EJB application is deployed.


E.g.: oc4jadmin

Password

15. Specify the password for the above user name.

Note: The Installer creates two files viz. 'gw_WS_logger.xml' and 'GW_WS_Prop.xml' in the path provided to save the files.

16. Click 'Next'. The following screen is displayed.



17. Click 'Continue' to continue the installation process with gateway application type.

18. Click 'Next' to navigate to the installer home screen.

The property file will be created in the specified folder.



Setting up Property File
May [2013]
Version 12.0.1.1.3

Oracle Financial Services Software Limited
Oracle Park
Off Western Express Highway
Goregaon (East)
Mumbai, Maharashtra 400 063
India

Worldwide Inquiries:
Phone: +91 22 6718 3000
Fax: +91 22 6718 3001
www.oracle.com/financialservices/

Copyright © [2007], [2013], Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.