

Oracle® Identity Manager

Connector Guide for PeopleSoft User Management

Release 9.0.4

E10167-02

June 2007

The Programs (which include both the software and documentation) contain proprietary information; they are provided under a license agreement containing restrictions on use and disclosure and are also protected by copyright, patent, and other intellectual and industrial property laws. Reverse engineering, disassembly, or decompilation of the Programs, except to the extent required to obtain interoperability with other independently created software or as specified by law, is prohibited.

The information contained in this document is subject to change without notice. If you find any problems in the documentation, please report them to us in writing. This document is not warranted to be error-free. Except as may be expressly permitted in your license agreement for these Programs, no part of these Programs may be reproduced or transmitted in any form or by any means, electronic or mechanical, for any purpose.

If the Programs are delivered to the United States Government or anyone licensing or using the Programs on behalf of the United States Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the Programs, including documentation and technical data, shall be subject to the licensing restrictions set forth in the applicable Oracle license agreement, and, to the extent applicable, the additional rights set forth in FAR 52.227-19, Commercial Computer Software--Restricted Rights (June 1987). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

The Programs are not intended for use in any nuclear, aviation, mass transit, medical, or other inherently dangerous applications. It shall be the licensee's responsibility to take all appropriate fail-safe, backup, redundancy and other measures to ensure the safe use of such applications if the Programs are used for such purposes, and we disclaim liability for any damages caused by such use of the Programs.

Oracle, JD Edwards, PeopleSoft, and Siebel are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

The Programs may provide links to Web sites and access to content, products, and services from third parties. Oracle is not responsible for the availability of, or any content provided on, third-party Web sites. You bear all risks associated with the use of such content. If you choose to purchase any products or services from a third party, the relationship is directly between you and the third party. Oracle is not responsible for: (a) the quality of third-party products or services; or (b) fulfilling any of the terms of the agreement with the third party, including delivery of products or services and warranty obligations related to purchased products or services. Oracle is not responsible for any loss or damage of any sort that you may incur from dealing with any third party.

Contents

Preface	vii
Audience	vii
Documentation Accessibility	vii
Related Documents	viii
Documentation Updates	viii
Conventions	viii
 What's New in the Oracle Identity Manager Connector for PeopleSoft User Management?	ix
Software Updates	ix
Documentation-Specific Updates.....	x
 1 About the Connector	
Reconciliation Module	1-1
Lookup Fields Reconciliation	1-1
User Reconciliation	1-2
Reconciled Resource Object Fields	1-2
Reconciled Xellerate User Fields.....	1-2
Types of User Data Reconciliation	1-3
Provisioning Module	1-3
Supported Functionality	1-4
Multilanguage Support	1-5
Files and Directories That Comprise the Connector	1-6
Determining the Release Number of the Connector	1-8
Before Deployment	1-9
After Deployment	1-9
 2 Deploying the Connector	
Step 1: Verifying Deployment Requirements	2-1
Step 2: Copying the Connector Files and External Code Files	2-1
Step 3: Configuring the Oracle Identity Manager Server	2-3
Changing to the Required Input Locale.....	2-3
Clearing Content Related to Connector Resource Bundles from the Server Cache	2-3
Enabling Logging	2-4
Step 4: Importing the Connector XML Files	2-6

Defining IT Resources	2-7
-----------------------------	-----

3 Configuring the Connector

Configuring Reconciliation	3-1
Partial Reconciliation	3-1
Specifying the Number of Records to Be Reconciled.....	3-2
Configuring the PeopleSoft Listener Web Service for Change-Based Reconciliation.....	3-2
Configuring the Target System for Reconciliation	3-5
Creating and Publishing the Message	3-5
Creating and Publishing the Message on PeopleTools 8.22	3-5
Creating and Publishing the Message on PeopleTools 8.45 Through 8.47.....	3-7
Configuring PeopleSoft Enterprise Portal.....	3-8
Configuring PeopleSoft Enterprise Portal on PeopleTools 8.22	3-8
Configuring PeopleSoft Enterprise Portal on PeopleTools 8.45 Through 8.47.....	3-11
Creating the Application Engine Program.....	3-13
Running the Application Engine Program.....	3-14
Running the Application Engine Program on PeopleTools 8.22	3-14
Running the Application Engine Program on PeopleTools 8.45 Through 8.47.....	3-15
Configuring Trusted Source Reconciliation.....	3-15
Configuring the Reconciliation Scheduled Tasks.....	3-16
Specifying Values for the Scheduled Task Attributes	3-17
Lookup Fields Reconciliation Scheduled Task.....	3-17
User Reconciliation Scheduled Task	3-18
Adding Custom Attributes for Reconciliation.....	3-19
Adding a Custom Attribute for Reconciliation on PeopleTools 8.22	3-19
Adding a Custom Attribute for Reconciliation on PeopleTools 8.45 Through 8.47.....	3-21
Encrypting a New Oracle Identity Manager Password.....	3-23
Configuring Provisioning	3-23
Compiling Adapters	3-24
Adding Custom Attributes for Provisioning	3-25
Configuring the Target System for Provisioning	3-27
Creating the APIs for the Component Interface.....	3-27
Creating the Java Template for the Component Interface	3-28
Configuring the Connector for Multiple Installations of the Target System	3-28

4 Testing and Troubleshooting

Testing Reconciliation	4-1
Prerequisites for Testing the PeopleSoft Listener Web Application.....	4-1
Testing the PeopleSoft Listener Web Application.....	4-1
Performing Trial Reconciliation	4-2
Testing Provisioning	4-2
Troubleshooting	4-3

5 Known Issues

A Attribute Mappings Between Oracle Identity Manager and PeopleSoft User Management

Index

Preface

Oracle Identity Manager Connector Guide for PeopleSoft User Management provides information about integrating Oracle Identity Manager with PeopleSoft User Management.

Note: Some parts of the product and documentation still refer to the original Thor company name and Xellerate product name and will be rebranded in future releases.

Audience

This guide is intended for users who want to deploy the Oracle Identity Manager connector for PeopleSoft User Management.

Documentation Accessibility

Our goal is to make Oracle products, services, and supporting documentation accessible, with good usability, to the disabled community. To that end, our documentation includes features that make information available to users of assistive technology. This documentation is available in HTML format, and contains markup to facilitate access by the disabled community. Accessibility standards will continue to evolve over time, and Oracle is actively engaged with other market-leading technology vendors to address technical obstacles so that our documentation can be accessible to all of our customers. For more information, visit the Oracle Accessibility Program Web site at

<http://www.oracle.com/accessibility/>

Accessibility of Code Examples in Documentation

Screen readers may not always correctly read the code examples in this document. The conventions for writing code require that closing braces should appear on an otherwise empty line; however, some screen readers may not always read a line of text that consists solely of a bracket or brace.

Accessibility of Links to External Web Sites in Documentation

This documentation may contain links to Web sites of other companies or organizations that Oracle does not own or control. Oracle neither evaluates nor makes any representations regarding the accessibility of these Web sites.

TTY Access to Oracle Support Services

Oracle provides dedicated Text Telephone (TTY) access to Oracle Support Services within the United States of America 24 hours a day, seven days a week. For TTY support, call 800.446.2398.

Related Documents

For more information, refer to the following documents in the Oracle Identity Manager documentation library:

- *Oracle Identity Manager Release Notes*
- *Oracle Identity Manager Installation Guide for JBoss*
- *Oracle Identity Manager Installation Guide for Oracle Containers for J2EE*
- *Oracle Identity Manager Installation Guide for WebLogic*
- *Oracle Identity Manager Installation Guide for WebSphere*
- *Oracle Identity Manager Administrative and User Console Guide*
- *Oracle Identity Manager Administrative and User Console Customization Guide*
- *Oracle Identity Manager Design Console Guide*
- *Oracle Identity Manager Tools Reference Guide*
- *Oracle Identity Manager Audit Report Developer Guide*
- *Oracle Identity Manager Best Practices Guide*
- *Oracle Identity Manager Globalization Guide*
- *Oracle Identity Manager Glossary of Terms*

The following document is available in the Oracle Identity Manager Connector Pack documentation library:

- *Oracle Identity Manager Connector Framework Guide*

Documentation Updates

Oracle is committed to delivering the best and most recent information available. For information about updates to the Oracle Identity Manager Connector Pack Release 9.0.4 documentation library, visit Oracle Technology Network at

<http://www.oracle.com/technology/documentation/index.html>

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
<code>monospace</code>	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

What's New in the Oracle Identity Manager Connector for PeopleSoft User Management?

This chapter provides an overview of the updates made to the software and documentation for the PeopleSoft User Management connector in releases 9.0.4 of the Oracle Identity Manager connector pack.

See Also: The 9.0.3 release of this guide for information about updates that were new for the 9.0.3 release

The updates discussed in this chapter are divided into the following categories:

- [Software Updates](#)

These include updates made to the connector software.

- [Documentation-Specific Updates](#)

These include major changes made to the connector documentation. These changes are not related to software updates.

See Also: *Oracle Identity Manager Release Notes*

Software Updates

This section discusses updates made to this release of the connector software.

Enabling Logging

By following the instructions in the "[Enabling Logging](#)" section on page 2-4, you can configure the generation of log information that is specific to the target system.

Partial Reconciliation

You can customize the reconciliation process by specifying the subset of added or modified target system records that must be reconciled. This feature is discussed in the "[Partial Reconciliation](#)" section on page 3-1.

Specifying the Number of Records to Be Reconciled

In this release of the connector, you can specify the number of records to be reconciled. This feature is discussed in the "[Specifying the Number of Records to Be Reconciled](#)" section on page 3-2.

Separate Scheduled Tasks for Trusted and Nontrusted Source Reconciliation

In this release of the connector, there are separate user reconciliation scheduled tasks for trusted and nontrusted source reconciliation. In the ["User Reconciliation Scheduled Task"](#) section on page 3-18, the attributes of these scheduled tasks are described.

Timeout Feature During Reconciliation and Provisioning

In this release of the connector, you can specify the number of retries and the delay between retries for connection attempts from Oracle Identity Manager to the target system. The ["Defining IT Resources"](#) section on page 2-7, describes the following parameters that are used to implement this feature:

- NumberOfRetries
- DelayBetweenRetries

Changes to the Testing Utility

The testing utility has been modified. Changes corresponding to the new functionality of the testing utility have been made in the following sections:

- [Files and Directories That Comprise the Connector](#) on page 1-6
- [Step 2: Copying the Connector Files and External Code Files](#) on page 2-1
- [Defining IT Resources](#) on page 2-7

The following changes have been made in this section:

- The `IsDebug` parameter has been removed.
- The `IndexOfLastReconciledRecord` parameter has been added.

Adding Custom Attributes

This release of the connector supports the adding of custom attributes for reconciliation and provisioning. This feature is described in the ["Adding Custom Attributes for Reconciliation"](#) section on page 3-19 and the ["Configuring the Target System for Provisioning"](#) section on page 3-27.

Documentation-Specific Updates

The following documentation-specific updates have been made in this release of the guide:

- Instructions in the ["Files and Directories That Comprise the Connector"](#) section on page 1-6 have been revised.
- In Step 3 of the procedure described in the ["Configuring PeopleSoft Enterprise Portal on PeopleTools 8.45 Through 8.47"](#) section ["Configuring PeopleSoft Enterprise Portal on PeopleTools 8.45 Through 8.47"](#), the name of the message channel has been changed from `USR_MGMT_MSG_CH` to `USR_MGMT_MSGCH`.
- In the ["Creating the Application Engine Program"](#) section on page 3-13, the `addemp` step has been added to the list of steps to be created.
- Information from Appendix B, "Encrypting a New Oracle Identity Manager Password" of the earlier release of this guide has been moved to the ["Encrypting a New Oracle Identity Manager Password"](#) section on page 3-23. The old Appendix B has been removed.
- Information from Appendix C, "Adding Custom Attributes" of the earlier release of this guide has been moved to the following sections of Chapter 3:

- [Adding Custom Attributes for Reconciliation](#) on page 3-19
- [Adding Custom Attributes for Provisioning](#) on page 3-25

The old Appendix C has been removed.

- Information from Appendix D, "Additional Steps to Be Performed on the Target System" of the earlier release of this guide has been moved to the "[Configuring the Target System for Provisioning](#)" section on page 3-27. The old Appendix D has been removed.
- Some of the content from the Chapter 2 of the earlier release of this guide has been moved to [Chapter 3](#).

About the Connector

Oracle Identity Manager automates access rights management, security, and provisioning of IT resources. Oracle Identity Manager connectors are used to integrate Oracle Identity Manager with third-party applications. The connector for PeopleSoft User Management is used to integrate Oracle Identity Manager with PeopleSoft User Management.

Note: Oracle Identity Manager connectors were referred to as *resource adapters* prior to the acquisition of Thor Technologies by Oracle.

This chapter contains the following sections:

- [Reconciliation Module](#)
- [Supported Functionality](#)
- [Multilanguage Support](#)
- [Files and Directories That Comprise the Connector](#)
- [Determining the Release Number of the Connector](#)

Reconciliation Module

Reconciliation involves duplicating in Oracle Identity Manager additions of and modifications to user accounts on the target system. It is an automated process initiated by a scheduled task that you configure.

See Also: The "Deployment Configurations of Oracle Identity Manager" section in *Oracle Identity Manager Connector Framework Guide* for conceptual information about reconciliation configurations

Based on the type of data reconciled from the target system, reconciliation can be divided into the following types:

- [Lookup Fields Reconciliation](#)
- [User Reconciliation](#)

Lookup Fields Reconciliation

The following lookup fields are reconciled:

- LanguageCode

- EmployeeId
- CurrencyCode
- PermissionList
- EmailTypes

The EmailTypes lookup field is reconciled only in PeopleTools 8.45 through 8.47, because PeopleTools 8.22 does not support multiple e-mail types.

- UserRoles

User Reconciliation

User reconciliation involves reconciling the following fields of PeopleSoft User Management:

Reconciled Resource Object Fields

The following target system fields are reconciled:

- UserId
- UserDescription
- EmployeeId
- PrimaryEmailAddress (PeopleTools 8.45 through 8.47 only)
- PrimaryEmailType (PeopleTools 8.45 through 8.47 only)
- Email Address (PeopleTools 8.22 only)
- MultiLanguageCode
- LanguageCD
- CurrencyCode
- Alias (PeopleTools 8.45 through 8.47 only)
- RowSecurityPermission
- ProcessProfilePermission
- NavigatorHomePagePermission
- PrimaryPermission
- Secondary EmailAddresses (PeopleTools 8.45 through 8.47 only)
- Secondary EmailTypes (PeopleTools 8.45 through 8.47 only)
- Role

Reconciled Xellerate User Fields

The following target system fields are reconciled only if trusted source reconciliation is implemented:

- User ID
- First Name
- Last Name
- Organization
- User Type

- Employee Type

Types of User Data Reconciliation

The connector supports user data reconciliation in two ways:

- **Bulk reconciliation (first-time reconciliation)**

Bulk reconciliation involves reconciling records of existing users using a flat file. The flat file is generated using an Application Engine program written in PeopleCode. This program is run using PeopleSoft Application Designer.

- **Change-based reconciliation**

In change-based reconciliation, data for any newly created or updated user is reconciled instantaneously. This type of reconciliation is performed using PeopleSoft Application Messaging Architecture.

Change-based reconciliation involves the use of:

- A PeopleCode trigger that generates an XML message containing updated information
- Attribute definitions (usually resource parameters) to be synchronized
- A Web service that acts as a passive listener for XML messages from PeopleSoft
- An XML file, `USR_MGMT_MSG.xml`, that defines the schema of the XML message received from PeopleSoft

The synchronization process from PeopleSoft User Management to Oracle Identity Manager involves the following steps:

1. User information is updated in PeopleSoft User Management. This activates a PeopleCode trigger.
2. The PeopleCode trigger generates an XML message containing the updated user information and sends it to the listener for the PeopleSoft User Management connector.
3. The listener forwards the XML message to the PeopleSoft User Management connector using HTTP.
4. The PeopleSoft User Management connector receives the XML message and sends a reconciliation event to the Oracle Identity Manager.

Provisioning Module

Provisioning involves creating or modifying a user's account information on the target system through Oracle Identity Manager. You use the Administrative and User Console to perform provisioning operations.

See Also: The "Deployment Configurations of Oracle Identity Manager" section in *Oracle Identity Manager Connector Framework Guide* for conceptual information about provisioning

For this target system, the following fields are provisioned:

- UserId
- UserDescription
- PrimaryPermissionList

- RowSecurityPermissionList
- ProcessProfilePermissionList
- NavigatorHomePermissionList
- SymbolicID
- LanguageCode
- CurrencyCode
- PrimaryEmailAddress
- PrimaryEmailType (for 8.45 and 8.47 only)
- EmpId
- RecName
- Password
- UserIdAlias (for PeopleTools 8.45 and 8.47 only)
- MultiLanguageCode

Supported Functionality

The following table lists the functions that are available with this connector.

Note: The "PeopleTools Release" column of this table indicates the release of PeopleTools for which the corresponding function is available.

Function	PeopleTools Release	Type	Description
Add User	8.22 and 8.45 through 8.47	Provisioning	Creates a user account
Password Updated	8.22 and 8.45 through 8.47	Provisioning	Updates the password of a user
User Description Updated	8.22 and 8.45 through 8.47	Provisioning	Updates the description of a user
Multi Language Code Updated	8.22 and 8.45 through 8.47	Provisioning	Updates the multilanguage code of a user
Primary Email Address Updated	8.22 only	Provisioning	Updates the primary e-mail address of a user
Email Address Updated	8.22 only	Provisioning	Updates the e-mail address of a user
Primary Email Type Updated	8.45 through 8.47 only	Provisioning	Updates the primary e-mail address type of a user
Language Code Updated	8.22 and 8.45 through 8.47	Provisioning	Updates the language code of a user
Currency Code Updated	8.22 and 8.45 through 8.47	Provisioning	Updates the currency code of a user
Employee Id Updated	8.22 and 8.45 through 8.47	Provisioning	Updates the employee ID of a user

Function	PeopleTools Release	Type	Description
Primary Permission List Updated	8.22 and 8.45 through 8.47	Provisioning	Updates the Primary Permission list of a user
Process Profile Permission List Updated	8.22 and 8.45 through 8.47	Provisioning	Updates the Process Profile Permission list of a user
Navigator Home Permission List Updated	8.22 and 8.45 through 8.47	Provisioning	Updates the Navigator Home Permission list of a user
Row Security Permission List Updated	8.22 and 8.45 through 8.47	Provisioning	Updates the Row Security Permission list of a user
User Id Alias Updated	8.45 through 8.47 only	Provisioning	Updates the user ID alias of a user
Add RoleName	8.22 and 8.45 through 8.47	Provisioning	Adds a role to a user
Delete RoleName	8.22 and 8.45 through 8.47	Provisioning	Deletes a role from a user
Add EmailAddress	8.45 through 8.47 only	Provisioning	Adds an e-mail address to a user
Delete EmailAddress	8.45 through 8.47 only	Provisioning	Deletes the e-mail address of a user
Enables a User	8.22 and 8.45 through 8.47	Provisioning	Enables a user
Disables a User	8.22 and 8.45 through 8.47	Provisioning	Disables a user
Reconcile Lookup Field	8.22 and 8.45 through 8.47	Reconciliation	Reconciles lookup fields
Reconcile User Data	8.22 and 8.45 through 8.47	Reconciliation	<p>Trusted mode: Reconciles user data from PeopleSoft User Management to Oracle Identity Manager. A corresponding user is created in Oracle Identity Manager. If the user already exists in Oracle Identity Manager, then this user is updated.</p> <p>Nontrusted mode: Reconciles user data from PeopleSoft User Management to Oracle Identity Manager. A user is not created in Oracle Identity Manager.</p>

See Also: [Appendix A](#) for information about attribute mappings between Oracle Identity Manager and PeopleSoft User Management.

Multilanguage Support

The connector supports the following languages:

- Chinese Simplified
- Chinese Traditional
- English
- French
- German
- Italian

- Japanese
- Korean
- Portuguese (Brazilian)
- Spanish

See Also: *Oracle Identity Manager Globalization Guide* for information about supported special characters

Files and Directories That Comprise the Connector

The files and directories that comprise this connector are compressed in the following ZIP file on the installation media:

Enterprise Applications/PeopleSoft Enterprise Applications/PeopleSoft User Management

These files and directories are listed in the following table.

File in the Installation Media Directory	Description
For PeopleTools 8.22: xml/PT822/PSFTBaseConnector.xml	This XML file contains definitions for the following components of the connector: <ul style="list-style-type: none">■ IT resource type
For PeopleTools 8.45 through 8.47: xml/PSFTBaseConnector.xml	<ul style="list-style-type: none">■ IT resource■ Resource object■ Process definition■ Process tasks■ Adapters■ Custom Process Form
For PeopleTools 8.22: xml/PT822/PSFTBaseXellerateUser.xml	This XML file contains the configuration for the Xellerate User. You must import this file only if you plan to use the connector for trusted source reconciliation.
For PeopleTools 8.45 through 8.47: xml/PSFTBaseXellerateUser.xml	
lib/JavaTasks/PSFTBaseProvisioning.jar	This JAR file contains the class files that are required for provisioning.
lib/ScheduleTask/PSFTBaseReconciliation.jar	This JAR file contains the class files that are required for reconciliation.
lib/peopleSoftUserMgmt.war	This WAR file contains all the classes and configuration files required for the PeopleSoft listener Web application to run.

File in the Installation Media Directory	Description
<p>For PeopleTools 8.22, the following files in the test/cbrecon directory:</p> <p>pingRequest.xml pingResponse.xml publishRequest.xml publishResponse.xml</p> <p>For PeopleTools 8.45 through 8.47, the following files in the test/cbrecon directory:</p> <p>pingRequest.xml pingResponse.xml publishRequest.xml publishResponse.xml</p>	<p>These XML files are required by the psft-xel-test.vbs file for communicating with the PeopleSoft listener Web service using XML over HTTP.</p>
lib/ext/csv.jar	The csv.jar file is a third-party library that is used to read comma-separated files.
<p>For PeopleTools version 8.22, the following files in the PeopleCode/PT822 directory:</p> <p>AddEmp.txt CurrencyCode.txt EmployeeId.txt LanguageCode.txt PermissionList.txt UserRoles.txt</p> <p>For PeopleTools version 8.45 through 8.47 the following files in the PeopleCode directory:</p> <p>AddEmp.txt CurrencyCode.txt EmployeeId.txt EmailType.txt LanguageCode.txt PermissionList.txt UserRoles.txt</p>	<p>These files contain the PeopleCode for the steps that you define for the Application Engine program. Refer to "Creating the Application Engine Program" section on page 3-13 for details.</p>
<p>For PeopleTools 8.22:</p> <p>PeopleCode/PT822/UserMgmtCBRecon.txt</p> <p>For PeopleTools 8.45 through 8.47:</p> <p>PeopleCode/UserMgmtCBRecon.txt</p>	<p>This file contains the code that you must add to the PeopleCode for the SavePostChange event while performing the "Publishing the Message" procedure described in the "Creating and Publishing the Message" section on page 3-5.</p>
<p>For PeopleTools 8.22, the following files in the MsgPublisher directory:</p> <p>xliMsgPublisher.jar publish.bat</p>	<p>The JAR file contains the class file that transfers the XML messages generated by the PeopleTools 8.22 file handler on the PeopleSoft Web server to the PeopleSoft connector listener servlet.</p> <p>The publish.bat file is a Windows batch file that triggers the message transfer on a periodic basis. Refer to the "Configuring PeopleSoft Enterprise Portal" section on page 3-8 for more information.</p>
<p>For PeopleTools 8.22:</p> <p>test/cbrecon/PT822/psft-xel-test.vbs</p> <p>For PeopleTools 8.45 through 8.47:</p> <p>test/cbrecon/psft-xel-test.vbs</p>	<p>This VBScript file is used to test the PeopleSoft listener Web service by creating XML messages similar to the ones created by PeopleSoft User Management Reconciliation.</p>

File in the Installation Media Directory	Description
<p>For PeopleTools 8.22, the following files in the test/cbrecon/PT822 directory:</p> <p>pingRequest.xml pingResponse.xml publishRequest.xml publishResponse.xml</p> <p>For PeopleTools 8.45 through 8.47, the following files in the test/cbrecon directory:</p> <p>pingRequest.xml pingResponse.xml publishRequest.xml publishResponse.xml</p>	<p>These XML files are required by the psft-xel-test.vbs file for communicating with the PeopleSoft listener Web service using XML over HTTP.</p>
<p>For PeopleTools 8.22:</p> <p>test/cbrecon/PT822/USR_MGMT_MSG.xml</p> <p>For PeopleTools 8.45 through 8.47:</p> <p>test/cbrecon/USR_MGMT_MSG.xml</p>	<p>This XML file is used by the psft-xel-test.vbs file to define the schema of the XML message that is received from PeopleSoft.</p>
test/config/config.properties	This file is used to specify the parameters and settings required to connect to the target system by using the testing utility.
test/config/log.properties	This file is used to specify the log level and the directory in which the log file is to be created when you run the testing utility.
test/config/attributemapping_prov.properties	This file contains the parameters required for dynamic provisioning.
test/config/attributemapping_recon.properties	This file contains the parameters required for dynamic reconciliation.
test/scripts/psftBase.bat test/scripts/psftBase.sh	The BAT file or UNIX shell script calls the testing utility when the Oracle Identity Manager server is running Microsoft Windows or UNIX, respectively.
<p>For PeopleTools 8.22, the files in the resources/PT822 directory</p> <p>For PeopleTools 8.45 through 8.47, the files in the resources directory</p>	<p>Each of these files contains locale-specific information that is used by the connector.</p>

Note: The files in the test directory are used only to run tests on the connector.

The "Step 2: Copying the Connector Files and External Code Files" section on page 2-1 provides instructions to copy these files into the required directories.

Determining the Release Number of the Connector

You can use any one of the following methods to determine the release number of the connector.

Before Deployment

To determine the release number of a connector:

1. Extract the contents of the `PSFTBaseReconciliation.jar` file. This file is in the following directory on the installation media:

`Enterprise Applications/PeopleSoft Enterprise Applications/PeopleSoft User Management/lib/ScheduleTask`

2. Open the `manifest.mf` file in a text editor. The `manifest.mf` file is one of the files bundled inside the `PSFTBaseReconciliation.jar` file.

In the `manifest.mf` file, the release number of the connector is displayed as the value of the `Version` property.

Note: If you maintain a copy of the `PSFTBaseReconciliation.jar` file after deployment, you can use this method to determine the release number of the connector at any stage. After you deploy the connector, it is recommended that you use the "After Deployment" method, which is described in the following section.

After Deployment

To determine the release number of a connector that has already been deployed:

See Also: *Oracle Identity Manager Design Console Guide*

1. Open the Oracle Identity Manager Design Console.
2. In the Form Designer, open the process form. The release number of the connector is the value of the **Version** field.

Deploying the Connector

Deploying the connector involves the following steps:

- [Step 1: Verifying Deployment Requirements](#)
- [Step 2: Copying the Connector Files and External Code Files](#)
- [Step 3: Configuring the Oracle Identity Manager Server](#)
- [Step 4: Importing the Connector XML Files](#)

Step 1: Verifying Deployment Requirements

The following table lists the deployment requirements for the connector.

Item	Requirement
Oracle Identity Manager	Oracle Identity Manager release 8.5.3 or later
Target systems	<p>The target system can be any one of the following:</p> <ul style="list-style-type: none">■ PeopleSoft Enterprise Applications 8.3 SP 1■ PeopleSoft Enterprise Applications 8.9■ PeopleTools 8.22 and 8.45 through 8.46 <p>You must ensure that the following components are installed and configured:</p> <ul style="list-style-type: none">■ Tuxedo and Jolt (the application server)■ PeopleSoft Internet Architecture■ PeopleSoft Application Designer (2-tier mode)
Target system host platforms	Microsoft Windows
Target system user account	<p>PS user</p> <p>Oracle Identity Manager uses this user account to connect to and exchange data with PeopleSoft User Management. You provide the credentials of this user account while performing the procedure in the "Defining IT Resources" section on page 2-7.</p>

Step 2: Copying the Connector Files and External Code Files

The connector files to be copied and the directories to which you must copy them are given in the following table.

Note: The directory paths given in the first column of this table correspond to the location of the connector files in the following directory on the installation media:

Enterprise Applications/PeopleSoft Enterprise
Applications/PeopleSoft User Management

Refer to the "[Files and Directories That Comprise the Connector](#)" section on page 1-6 for more information about these files.

File in the Installation Media Directory	Destination Directory
lib/JavaTasks/PSFTBaseProvisioning.jar	OIM_home/xellerate/JavaTasks
lib/ScheduleTask/PSFTBaseReconciliation.jar	OIM_home/xellerate/ScheduleTask
lib/ext/csv.jar	OIM_home/xellerate/ThirdParty
For PeopleTools 8.22, copy the files from the MsgPublisher directory	OIM_home/xellerate/MsgPublisher
For PeopleTools 8.22, copy the files from the PeopleCode/PT822 directory	OIM_home/xellerate/Scripts
For PeopleTools 8.45 through 8.47, copy the files from the PeopleCode directory	Note: You must copy the files for either PeopleTools 8.22 or PeopleTools 8.45 through 8.47, not both.
For PeopleTools 8.22, copy the files from the resources/PT822 directory	OIM_home/xellerate/connectorResources
For PeopleTools 8.45 through 8.47, copy the files from the resources directory	Note: You must copy the files for either PeopleTools 8.22 or PeopleTools 8.45 through 8.47, not both.
For PeopleTools 8.22, copy the files from the test/cbrecon/PT822 directory	OIM_home/xellerate/XLIntegrations/PSFTBASE/cbrecon
For PeopleTools 8.45 through 8.47, copy the files from the test/cbrecon directory	Note: You must copy the files for either PeopleTools 8.22 or PeopleTools 8.45 through 8.47, not both.
Files in the test/config directory	OIM_home/xellerate/XLIntegrations/PSFTBASE/config
For PeopleTools 8.22:	OIM_home/xlclient
xml/PT822/PSFTBaseConnector.xml xml/PT822/PSFTBaseXellerateUser.xml	Note: You must copy the files for either PeopleTools 8.22 or PeopleTools 8.45 through 8.47, not both.
For PeopleTools 8.45 through 8.47:	
xml/PSFTBaseConnector.xml xml/PSFTBaseXellerateUser.xml	

After you copy the connector files, copy the following files from the *PeopleSoft_home/PT8xx/web/PSJOA* directory into the *OIM_home/xellerate/ThirdParty* directory.

- psjoa.jar

This is the PeopleSoft Java object adapter file.

- peoplesoft.jar

This JAR file contains APIs for the USER_PROFILE component interface.

The "[Creating the APIs for the Component Interface](#)" section on page 3-27 for information about the procedure to generate this file for the specific release of PeopleTools, 8.22 or 8.45 through 8.47, that you are using.

- `pshttp.jar` (PeopleTools 8.45 through 8.47 only)

Create this JAR file using the PeopleSoft class files that are in the `pshttp` and `cache` directories on the PeopleSoft server. The location of these directories depends on the PeopleTools release that you are using. For PeopleTools 4.5, the directories are located at the following paths:

```
pt8.45/class/psft/pt8/pshttp
pt8.45/class/psft/pt8/cache
```

The `pstools.properties` file contains the Tuxedo parameter settings used by the PeopleSoft Integration Gateway. You must copy it into the `OIM_home/xellerate/bin` directory.

Note: While installing Oracle Identity Manager in a clustered environment, you copy the contents of the installation directory to each node of the cluster. Similarly, you must copy the `connectorResources` directory and the JAR files to the corresponding directories on each node of the cluster.

Step 3: Configuring the Oracle Identity Manager Server

Configuring the Oracle Identity Manager server involves the following procedures:

Note: In a clustered environment, you must perform this step on each node of the cluster.

- [Changing to the Required Input Locale](#)
- [Clearing Content Related to Connector Resource Bundles from the Server Cache](#)
- [Enabling Logging](#)

Changing to the Required Input Locale

Changing to the required input locale (language and country setting) involves installing the required fonts and setting the required input locale.

You may require the assistance of the system administrator to change to the required input locale.

Clearing Content Related to Connector Resource Bundles from the Server Cache

While performing the instructions described in the "[Step 2: Copying the Connector Files and External Code Files](#)" section on page 2-1, you copy files from the `resources` directory on the installation media into the `OIM_home/xellerate/connectorResources` directory. Whenever you add a new resource bundle in the `connectorResources` directory or make a change in an existing resource bundle, you must clear content related to connector resource bundles from the server cache.

To clear content related to connector resource bundles from the server cache:

1. In a command window, change to the `OIM_home/xellerate/bin` directory.

Note: You must perform Step 1 before you perform Step 2. If you run the command described in Step 2 as follows, then an exception is thrown:

OIM_home/xellerate/bin/script_file_name

2. Enter one of the following commands:

- On Microsoft Windows:

PurgeCache.bat ConnectorResourceBundle

- On UNIX:

PurgeCache.sh ConnectorResourceBundle

Note: You can ignore the exception that is thrown when you perform Step 2.

In this command, `ConnectorResourceBundle` is one of the content categories that you can remove from the server cache. Refer to the following file for information about the other content categories:

OIM_home/xellerate/config/xlConfig.xml

Enabling Logging

When you enable logging, Oracle Identity Manager automatically stores in a log file information about events that occur during the course of provisioning and reconciliation operations. To specify the type of event for which you want logging to take place, you can set the log level to one of the following:

- ALL

This level enables logging for all events.

- DEBUG

This level enables logging of information about fine-grained events that are useful for debugging.

- INFO

This level enables logging of informational messages that highlight the progress of the application at coarse-grained level.

- WARN

This level enables logging of information about potentially harmful situations.

- ERROR

This level enables logging of information about error events that may still allow the application to continue running.

- FATAL

This level enables logging of information about very severe error events that could cause the application to stop functioning.

- OFF

This level disables logging for all events.

The file in which you set the log level depends on the application server that you use:

■ **BEA WebLogic**

To enable logging:

1. Add the following line in the *OIM_home/xellerate/config/log.properties* file:
`log4j.logger.Adapter.PSFTBase=log_level`
2. In this line, replace *log_level* with the log level that you want to set.

For example:

```
log4j.logger.Adapter.PSFTBase=INFO
```

After you enable logging, log information is written to the following file:

WebLogic_home/user_projects/domains/domain_name/server_name/server_name.log

■ **IBM WebSphere**

To enable logging:

1. Add the following line in the *OIM_home/xellerate/config/log.properties* file:
`log4j.logger.Adapter.PSFTBase=log_level`
2. In this line, replace *log_level* with the log level that you want to set.

For example:

```
log4j.logger.Adapter.PSFTBase=INFO
```

After you enable logging, log information is written to the following file:

WebSphere_home/AppServer/logs/server_name/startServer.log

■ **JBoss Application Server**

To enable logging:

1. In the *JBoss_home/server/default/conf/log4j.xml* file, locate the following lines:

```
<category name="Adapter.PSFTBase">
  <priority value="log_level"/>
</category>
```

2. In the second XML code line, replace *log_level* with the log level that you want to set. For example:

```
<category name="Adapter.PSFTBase">
  <priority value="INFO"/>
</category>
```

After you enable logging, log information is written to the following file:

JBoss_home/server/default/log/server.log

■ **OC4J**

To enable logging:

1. Add the following line in the `OIM_home/xellerate/config/log.properties` file:
`log4j.logger.Adapter.PSFTBase=log_level`
2. In this line, replace `log_level` with the log level that you want to set.

For example:

```
log4j.logger.Adapter.PSFTBase=INFO
```

After you enable logging, log information is written to the following file:

```
OC4J_home/opmn/logs/default_group-home~default_group~1.log
```

Step 4: Importing the Connector XML Files

To import the connector files into Oracle Identity Manager:

1. Open the Oracle Identity Manager Administrative and User Console.
2. Click the **Deployment Management** link on the left navigation bar.
3. Click the **Import** link under Deployment Management. A dialog box for locating files is displayed.
4. Locate and open the `PSFTBaseConnector.xml` file, which is in the `OIM_home/xlclient` directory. Details of the XML file are shown on the File Review page.
5. Click **Add File**. The Substitutions page is displayed.
6. Click **Next**. The Confirmation page is displayed.
7. Click **Next**. The Provide IT Resource Instance Data page for the PSFT Base Server IT resource is displayed.
8. Specify values for the parameters of the PSFT Base Server IT resource. Refer to the ["Defining IT Resources"](#) section on page 2-7 for information about the values to be specified.
9. Click **Next**. The Provide IT Resource Instance Data page for a new instance of the PSFTBase IT resource type is displayed.
10. Click **Skip** to specify that you do not want to define another IT resource. The Confirmation page is displayed.

See Also: If you want to define another IT resource, then refer to *Oracle Identity Manager Tools Reference Guide* for instructions.

11. Click **View Selections**.

The contents of the XML file are displayed on the Import page. You *may* see a cross-shaped icon along with some nodes. These nodes represent Oracle Identity Manager entities that are redundant. Before you import the connector XML file, you must remove these entities by right-clicking each node and then selecting **Remove**.

12. Click **Import**. The connector file is imported into Oracle Identity Manager.

After you import the connector XML file, proceed to the next chapter.

Defining IT Resources

You must specify values for the PSFT Base Server IT resource parameters listed in the following table.

Parameter	Description
Admin	User ID of the PeopleSoft User Management administrator Default value: PS
AdminCredentials	Password of the PeopleSoft User Management administrator
ComponentInterfaceName	Component interface used to load user data in PeopleSoft User Management Default value: USER_PROFILE
ServerName	IP address or computer name of the PeopleSoft User Management server
ServerPort	Port at which the PeopleSoft User Management server is listening Default value: 9000
IsSecure	Specify whether or not the SSL feature is enabled The value can be YES or NO. The default value is NO. Note: It is recommended that you enable SSL to secure communication with the target system.
SymbolicId	Specifies the AccessId associated with the user profile The AccessId specifies whether or not the user has sufficient privileges on the PeopleSoft User Management database. Sample value: PS89
RecordName	Used to validate the employee ID during user provisioning in PeopleSoft User Management Default value: PERSONAL_DATA
NumberOfRetries	Number of times the connection to the target system must be retried before the InvocationTargetException is thrown Default value: 2 Note: The timeout feature is enabled only for bulk reconciliation and provisioning. It is not applied during change-based reconciliation.
DelayBetweenRetries	Time difference between subsequent retries (in milliseconds) Default value: 20000
IndexOfLastReconciledRecords	Stores the index of last successful reconciled record Default value: -1

After you specify values for these IT resource parameters, go to Step 9 of the procedure to import connector XML files.

Configuring the Connector

After you deploy the connector, you must configure it to meet your requirements. This chapter discusses the following connector configuration procedures:

Note: These sections provide both conceptual and procedural information about configuring the connector. It is recommended that you read the conceptual information before you perform the procedures.

- [Configuring Reconciliation](#)
- [Configuring Provisioning](#)
- [Configuring the Connector for Multiple Installations of the Target System](#)

Configuring Reconciliation

As mentioned earlier in this guide, reconciliation involves duplicating in Oracle Identity Manager additions of and modifications to user accounts on the target system. This section discusses the following topics related to configuring reconciliation:

- [Partial Reconciliation](#)
- [Configuring the PeopleSoft Listener Web Service for Change-Based Reconciliation](#)
- [Configuring the Target System for Reconciliation](#)
- [Configuring Trusted Source Reconciliation](#)
- [Configuring the Reconciliation Scheduled Tasks](#)
- [Adding Custom Attributes for Reconciliation](#)
- [Encrypting a New Oracle Identity Manager Password](#)

Partial Reconciliation

By default, all target system records that are added or modified after the last reconciliation run are reconciled during the current reconciliation run. You can customize this process by specifying the subset of added or modified target system records that must be reconciled. You do this by creating filters for the reconciliation module.

Creating a filter involves specifying values for the following scheduled task attributes, which will be used in the query SELECT criteria to retrieve the records to be reconciled:

- `UserId`
- `UserType` (This attribute is used only in trusted source reconciliation)

If you want to use multiple target system attributes to filter records, then you must also specify the logical operator (AND or OR) that you want to apply to the combination of target system attributes that you select.

For example, suppose you specify the following values for these attributes:

- `UserId=jdoe`

This will return results of all users who have the string `jdoe` in their user IDs. For example, records of users with user ID `njdoehn`, `cajdoe`, `jdoettir`, and so on are fetched.

- `UserType=Employee`

Because you are using the OR operator, during reconciliation, only user records for which *any one* of these criteria is met are reconciled. If you were to use the AND operator, then only user records for which *all* of these criteria are met are reconciled.

While deploying the connector, follow the instructions in the ["Specifying Values for the Scheduled Task Attributes"](#) section on page 3-17 to specify values for these attributes and the logical operator that you want to apply.

Specifying the Number of Records to Be Reconciled

During a reconciliation run, all changes in the target system records are reconciled into Oracle Identity Manager. Depending on the number of records to be reconciled, this process may require a large amount of time. In addition, if the connection breaks during reconciliation, then the process would take longer to complete.

You can specify the number of records to be reconciled. To do this, you use the `NoOfRecordsToBeReconciled` scheduled task attribute.

You specify a value for the `NoOfRecordsToBeReconciled` attribute by following the instructions described in the ["Specifying Values for the Scheduled Task Attributes"](#) section on page 3-17.

Configuring the PeopleSoft Listener Web Service for Change-Based Reconciliation

This section describes how to configure the listener for the connector. In the following procedure, *OIM_home* refers to the local Oracle Identity Manager installation directory.

To configure the PeopleSoft Listener Web service:

1. Enter the following command to extract the contents of the `peopleSoftUserMgmt.war` file. This file is in the `OIM_home/xlclient/lib` directory.

```
jar -xvf peopleSoftUserMgmt.war
```

Note: All the files mentioned in the remaining steps of this procedure are extracted from the `peopleSoftUserMgmt.war` file.

2. Edit the `deployment.properties` file. This file contains the message property that corresponds to the name of the XML message from the PeopleSoft feed. The default value of this attribute is `USR_MGMT_MSG`. Obtain the correct value for this attribute from the PeopleSoft administrator.

3. If you are using PeopleTools 8.22, then you must modify the `PSFTBase.Roles` property in the `attributemap.properties` file as follows:

- a. Search for the following line:

```
PSFTBase.Roles=//Transaction/PSROLEUSER_VW/ROLES
```

- b. Replace it with the following line:

```
PSFTBase.Roles=//Transaction/PSROLEUSER_VW/ROLENAME
```

4. Edit the `xlsession.properties` file. This file contains the following Oracle Identity Manager connection parameters:

- **ObjectName:** This is the name of the resource object in Oracle Identity Manager against which the reconciliation event is created. The default value is `PSFTBase`. For nontrusted source reconciliation, you can change it to any other resource object.
- **Username:** This is the user name for logging in to Oracle Identity Manager. The default value is `xelsysadm`.
- **Password:** This is the password for logging in to Oracle Identity Manager. You must enter the encrypted value for the default password:

```
Kk3821YZhIoG36lvDH2YTW==
```

Note: If the password for Oracle Identity Manager is different from the default password, then refer to the ["Encrypting a New Oracle Identity Manager Password"](#) section on page 3-23 for information about encrypting a plaintext password.

5. Edit the `xlclient.properties` file. This file contains the following system properties that enable an API client to communicate with Oracle Identity Manager:

- **xl.homedir:** This property specifies the Oracle Identity Manager client directory. Typically, the Oracle Identity Manager client directory is `OIM_home/xlclient`.
- **java.security.policy:** This property specifies the path of the security policy file. Typically, this file is located in the `OIM_home/xlclient/config` directory.
- **java.security.auth.login.config:** This property specifies the path of the authentication configuration file. Typically, this file is located in the `OIM_home/xlclient/config` directory.

Each application server uses a different authentication configuration file:

IBM WebSphere: `authws.conf`

BEA WebLogic: `authwl.conf`

JBoss Application Server: `auth.conf`

- **java.naming.provider.url:** This property specifies the JNP URL of the application server. This URL is given in the `<Discovery><CoreServer><java.naming.provider.url>` tag of the `OIM_home/xlclient/config/xlconfig.xml` file.

6. Edit the following properties in the `configureReconciliation.properties` file:

- **reconciliationMode:** This property can accept one of two possible values:
 - If you want to perform reconciliation in trusted mode, then set this property to `trusted`.
 - If you want to perform reconciliation in nontrusted mode, then set this property to `nontrusted`.
 - **Serverdateformat:** This property specifies the date format that is used by the PeopleSoft User Management server. You can select one of the following date formats:
 - `dd-mmm-yy`
 - `ddmmyy`
 - `yyddmm`
 - `yymmdd`
 - **xellerateOrganization:** This property specifies the name of the Oracle Identity Manager organization. The default value of this parameter is `XellerateUsers`. The value that you assign to this property must exist in Oracle Identity Manager.
 - **nullDate:** This property specifies the default value for a date field. The value is `2200/01/01 00:00:00 PST`. This value is used if the date field is left empty.
 - **PeoplesoftstartingYEAR:** This property specifies the year in two digits. If the number represented by these two digits (`xx`):
 - Is greater than or equal to 50, then it is assumed that the year is 19xx.
 - Is less than 50, then it is assumed that the year is 20xx.This specifies a range of 1950 to 2049 for the property.
 - **XelServerDate:** This property contains the date format that is used for the Oracle Identity Manager server.
Sample value: `yyyy/MM/dd hh:mm:ss z`
7. Copy the following files from the `OIM_home/xellerate/lib` directory to the `WEB-INF/lib` directory:
- `wlXLSecurityProviders.jar`
 - `xlAPI.jar`
 - `xlAuthentication.jar`
 - `xlBackOfficeBeans.jar`
 - `xlBackofficeClient.jar`
 - `xlCache.jar`
 - `xlCrypto.jar`
 - `xlDataObjectBeans.jar`
 - `xlDataObjects.jar`
 - `xlLogger.jar`
 - `xlUtils.jar`
 - `xlVO.jar`

Copy the following files from the *OIM_home/xellerate/ext* directory to the *WEB-INF/lib* directory:

- `oscache.jar`
 - `javagroups-all.jar`
8. Delete the `peopleSoftUserMgmt.war` file from the temporary directory into which you extract it, and then use the following command to re-create the file:


```
jar -cvf peopleSoftUserMgmt.war
```
 9. Ensure that the old version of the `peopleSoftUserMgmt.war` file is removed from the application server (JBoss Application Server, IBM WebSphere, BEA WebLogic, or OC4J) deployment directory and the *OIM_home/xellerate/webapp* directory.
 10. Copy the newly created `peopleSoftUserMgmt.war` file into the application server deployment directory and the *OIM_home/xellerate/webapp* directory.
 11. Restart the Oracle Identity Manager server and client.

Note: You can add custom attributes to be reconciled during change-based reconciliation. However, you must complete the deployment procedure before you can add custom attributes.

Refer to the "[Adding Custom Attributes for Reconciliation](#)" section on page 3-19 for information about the procedure to add custom attributes for reconciliation.

Configuring the Target System for Reconciliation

Configuring the target system involves performing the following procedures:

- [Creating and Publishing the Message](#)
- [Configuring PeopleSoft Enterprise Portal](#)
- [Creating the Application Engine Program](#)

Creating and Publishing the Message

The procedure to create and publish the message depends on the release of PeopleTools that you are using:

- [Creating and Publishing the Message on PeopleTools 8.22](#)
- [Creating and Publishing the Message on PeopleTools 8.45 Through 8.47](#)

Creating and Publishing the Message on PeopleTools 8.22 Creating and publishing the message on PeopleTools 8.22 involves the following steps:

1. To create the message channel:
 - a. Click **Start, Programs**, and **Application Designer**. The Application Designer window is displayed.
 - b. Select **New** from the **File** menu. The New Definition dialog box is displayed.
 - c. Select **Message Channel**, and then click **OK**.
 - d. Save the new message channel as `USR_MGMT_MSGCH`.

- e. Select **Object Properties** from the **File** menu. The Message Channel Properties dialog box is displayed.
 - f. Select the **Run** option, and then select **Archive Messages**.
 - g. Click **OK**, and then save the message.
2. To create the message:
 - a. In the Application Designer, select **New** from the **File** menu. The New Definition dialog box is displayed.
 - b. Select **Message** from the list, and then click **OK**.
 - c. Select **Object Properties** from the **File** menu. The Message Properties dialog box is displayed.
 - d. Click the **Use** tab.
 - e. On the Use tab, select the **USR_MGMT_MSGCH** message channel and the version of the message that you create.
 - f. Select **Active** to make the message an active message, and then click **OK**.
 - g. Right-click **VERSION_1**, and select the **Insert Child Record** option. The Insert Record window is displayed.
 - h. Enter **PSOPRDEFN** in the **Name** field, click **Insert**, and then click **Close**.

Note: PSOPRDEFN is a record defined in the *OIM_home/xellerate/test/cbrecon/USR_MGMT_MSG.xml* file. Refer to this file for information about the fields that comprise the PSOPRDEFN record.

- i. Click **PSOPRDEFN** under **VERSION_1**. All the fields comprising the PSOPRDEFN record are displayed.

By default, all the fields appear as selected. Deselect the fields that are not required for the message XML file to be generated.

- j. Repeat Steps g through i for the PSROLEUSER_VW record.

Note: PSROLEUSER_VW is the second record defined in the *OIM_home/xellerate/test/cbrecon/USR_MGMT_MSG.xml* file.

- k. Save the message as **USR_MGMT_MSG**.
3. To publish the message:
 - a. Select **Open** from the **File** menu. The Open Definition dialog box is displayed.
 - b. Select **Component** from the **Definition** list, enter **USERMAINT** in the **Name Selection Criteria** field, and then click **Enter**. All component names starting with the text **USERMAINT** are displayed.
 - c. Select **USERMAINT** from the list, and then click **Open**. The details of the **USERMAINT** component are displayed.
 - d. Click the **Structure** tab, right-click **USERMAINT**, and then select **View PeopleCode**. The PeopleCode for the **USERMAINT** component is displayed.

- e. Select the `SavePostChange` event from the list in the upper-left corner of the window. The `PeopleCode` for this event is displayed.
- f. Copy the code given in the following file immediately after the import definitions in the `PeopleCode` for the `SavePostChange` event:

```
OIM_home/xellerate/Scripts/UserMgmtCBRecon.txt
```

- g. Select **Save** from the **File** menu to save the changes to the `USERMAINT` component.

After you complete this procedure, proceed to the "[Configuring PeopleSoft Enterprise Portal](#)" section on page 3-8.

Creating and Publishing the Message on PeopleTools 8.45 Through 8.47 Creating and publishing the message on PeopleTools 8.45 through 8.47 involves the following steps:

1. To create the message channel:
 - a. Click **Start, Programs, and Application Designer**. The Application Designer window is displayed in the 2-tier mode.
 - b. Select **New** from the **File** menu. The New Definition dialog box is displayed.
 - c. Select **Message Channel**, and then click **OK**.
 - d. Save the new message channel as `USR_MGMT_MSGCH`.
 - e. Select **Definition Properties** from the **File** menu. The Message Channel Properties dialog box is displayed.
 - f. Select the **Run** option, and then select **Archive Messages**.
 - g. Click **OK** and save the message channel.
2. To create the message:
 - a. In PeopleSoft Application Designer, select **New** from the **File** menu. The New Definition dialog box is displayed.
 - b. Select **Message** from the list, and then click **OK**.
 - c. Select **Definition Properties** from the **File** menu. The Message Properties dialog box is displayed.
 - d. Click the **Use** tab.
 - e. On the Use tab, select the `USR_MGMT_MSGCH` message channel and the version of the message that you create.
 - f. Select **Active** to make the message an active message.
 - g. Save the message as `USR_MGMT_MSG`.
3. To publish the message:
 - a. Select **Open** from the **File** menu. The Open Definition dialog box is displayed.
 - b. Select **Component** from the **Definition** list, enter `USERMAINT` in the **Name Selection Criteria** field, and then press **Enter**. All component names starting with the text `USERMAINT` are displayed.
 - c. Select `USERMAINT` from the list, and then click **Open**. The details of the `USERMAINT` component are displayed.
 - d. Click the **Structure** tab, right-click `USERMAINT`, and then select **View PeopleCode**. The `PeopleCode` for the `USERMAINT` component is displayed.

- e. Select the **SavePostChange** event from the list in the upper-left corner of the window. The PeopleCode for this event is displayed.
- f. Copy the code given in the following file immediately after the import definitions in the PeopleCode for the *SavePostChange* event:

OIM_home/xellerate/Scripts/UserMgmtCBRecon.txt

- g. Add the following function call at the end of the PeopleCode for the *SavePostChange* event:

Note: Perform this step only after you copy the code from the *UserMgmtCBRecon.txt* file.

```

/*****
/*  Calling the GENERATEUSER function to generate the
USR_MGMT_MSG message*/
*****/
If Len(%CompIntfcName) = 0 Then
    Local string &OPID;
    &OPID = PSOPRDEFN.OPRID;
    GENERATEUSR(&OPID);
End-If;

```

- h. Select **Save** from the **File** menu to save the changes to the *USERMAINT* component.

Configuring PeopleSoft Enterprise Portal

Note: If your PeopleSoft installation does not include PeopleSoft Enterprise Portal, then you cannot perform this procedure. Change-based reconciliation cannot be enabled if you do not use PeopleSoft Enterprise Portal. However, you can perform provisioning and bulk reconciliation.

Refer to the "[User Reconciliation](#)" section on page 1-2 for information about change-based and bulk reconciliation.

PeopleSoft Enterprise Portal provides a single gateway to critical information in PeopleSoft User Management Reconciliation and other PeopleSoft applications.

The procedure to configure PeopleSoft Enterprise Portal depends on the release of PeopleTools that you are using:

- [Configuring PeopleSoft Enterprise Portal on PeopleTools 8.22](#)
- [Configuring PeopleSoft Enterprise Portal on PeopleTools 8.45 Through 8.47](#)

Configuring PeopleSoft Enterprise Portal on PeopleTools 8.22 Configuring PeopleSoft Enterprise Portal on PeopleTools 8.22 involves the following steps:

1. To create the *USR_MGMT_NODE* remote node:
 - a. In the Application Designer, select **New** from the **File** menu. The New Definition dialog box is displayed.
 - b. Select **Message Node** from the list, and then click **OK**.

- c. Right-click anywhere in the white space, and then select **Insert Location**. The Location dialog box is displayed.
 - d. Enter the URL for the PeopleSoft Application Gateway in the following format:

```
http://hostname:port/servlets/gateway
```

In this URL, *hostname* is the application server that hosts PeopleSoft and *port* is the port number at which the application server is listening.
 - e. Select **Object Properties** from the **File** menu. The Message Node Properties dialog box is displayed.
 - f. Select the **Use** tab. Ensure that **Local Node** is not selected.
 - g. Save the remote node as `USR_MGMT_NODE`.
2. To configure the `USR_MGMT_MSGCH` message channel:
 - a. From the **File** menu, select **Open** and then click **Message Channel**.
 - b. To open the `USR_MGMT_MSGCH` message channel, select **USR_MGMT_MSGCH**.
 - c. Click the **Routing Rules** tab.
 - d. Right-click anywhere in the empty area of the right pane, and then select **Insert Message Node**. The Insert Message Node dialog box is displayed.
 - e. Select the `USR_MGMT_NODE` message node, and then click **Insert**.
 - f. Click **Cancel** to close the dialog box.
 - g. Right-click the message node displayed on the Routing Rules tab.
 - h. Point to **Routing Direction**, and then select **Publish To**.
 - i. Save the message channel.
 3. To configure the PeopleSoft Enterprise Portal gateway so that messages can be sent through the gateway to third-party systems:

Note: The Simple File Handler mentioned in the following procedure is a utility in PeopleTools 8.22 that can receive messages published by a PeopleSoft node and write these messages to a file that can be used by third-party systems.

- a. In a Web browser, use a URL with the following format to launch the PeopleSoft configuration servlet interface (handler directory):

```
http://hostname:port/servlets/gateway.administration
```

In this URL, *hostname* is the application server that hosts PeopleSoft and *port* is the port number at which the application server is listening.

- b. Click **Add Handler**. The Add Handler window is displayed.
- c. Enter the full name of the Simple File Handler class,
`psft.pt8.filehandler.SimpleFileHandler`.
- d. Click **Save**. The Handler Directory window is displayed.
- e. To load the handler, click **Load**. After the handler loads, the "Loaded successfully" message is displayed in the Status column.

- f. Click **Configure**.
 - g. Click **Add a file handler node**. The Add File Handler Node window is displayed.
 - h. In the **Node Name** field, enter the name of the message node that you create, `USR_MGMT_NODE`.
 - i. Specify the output directory in which the published messages are to be stored.
 - j. Select **Include Header**.
 - k. Click **Save**.
 - l. Restart the Web server.
4. XML messages are generated by the Simple File Handler. To publish these messages to the PeopleSoft Connector Listener servlet, you must create a scheduled task as follows:

Note: The scheduled task calls a Java program that communicates with the servlet deployed on the Oracle Identity Manager server. The servlet parses the message and sends reconciliation events to Oracle Identity Manager.

The servlet sends a return code based on the status of the reconciliation event. If the reconciliation event is successfully sent, then the message is deleted or archived. Otherwise, the message file is left unchanged. The next time the scheduled task is run, another attempt is made to send the message.

- a. Copy the `publish.bat` and `xlMsgPublisher.jar` files from the `OIM_home/xellerate/MsgPublisher` directory to any directory on the PeopleSoft User Management server.
- b. Use a text editor to open the `publish.bat` file, and then make the following changes in the file:
 - i. Change the value of the `JAVA_HOME` variable so that it points to the JDK installation directory on the PeopleSoft Web server.
 - ii. Specify the following values in the Java command given at the end of the file:
 - * `PeopleSoft_listener_servlet_URL`: This is the URL of the servlet that listens for reconciliation events generated using PeopleSoft Application Messaging.
 - * `Output_directory_for_XML_messages`: This is the PeopleSoft Web server directory in which you want published messages to be stored. You have already specified the output directory while performing Step 3.i of this procedure.
 - * `XML_message_name`
 - * `console_log_file_path`

The command is in the following format:

```
java Com.thortech.xl.Integration.msgpublisher.PeopleSoftPublisher
"PeopleSoft_listener_servlet_URL" "Output_directory_for_XML_messages"
XML_message_name >> console_log_file_path
```

For example:

```
java Com.thortech.xl.Integration.msgpublisher.PeopleSoftPublisher
"http://host:port/peopleSoftUserMgmt/do/peopleSoftAction" "C:/test/file"
USR_MGMT_MSG >> c:/test/consolelog.log
```

In the PeopleSoft listener servlet URL specified in this example, *host* is the IP address or host name of the application server on which Oracle Identity Manager is running and *port* is the HTTP port at which the application server listens for incoming messages.

- c. Save and close the batch file.
- d. On the PeopleSoft Web server, click **Start, Settings, and Control Open**.
- e. Double-click **Scheduled Tasks**.
- f. Click **Add Schedule Task**, and then click **Next**.
- g. Click **Browse**, and then select the `publish.bat` file from the directory in which you save it.
- h. Select **Daily**, click **Next**, and then click **Next** again.
- i. Enter the user ID and password for the scheduled task to run.
- j. Select **Open Advance properties**.
- k. Click **Finish**.
- l. On the Schedule tab, click **Advanced**.
- m. Select **Repeat Task**.
- n. Select the frequency at which you want the task to run.
- o. Click **OK**, and then click **OK** again to close the window.

Configuring PeopleSoft Enterprise Portal on PeopleTools 8.45 Through 8.47 Configuring PeopleSoft Enterprise Portal on PeopleTools 8.45 through 8.47 involves the following steps:

1. To configure the PeopleSoft Enterprise Portal gateway so that messages can be sent through the gateway to the connector:

- a. Open a Web browser and enter the URL for PeopleSoft Enterprise Portal.

This URL is in the following format:

```
http://servername/psp/Databasename/?cmd=login
```

Here, `psp` is the name of the Web application. For example:

```
http://psftserver.acme.com/psp/TestDB/?cmd=login
```

- b. Expand **PeopleTools, Integration Broker**, and then **Gateways** in the list on the portal page. The Gateway component details are displayed.
- c. Enter `LOCAL` in the **Integration Gateway ID** field, and then click **Search**. The `LOCAL` gateway is a default gateway that is created when you install PeopleSoft Enterprise Portal.
- d. Ensure that the IP address specified in the URL of the PeopleSoft listening connector is the IP address of the Web server on which PeopleSoft User Management is installed. The PeopleSoft listening connector is a module

provided by PeopleSoft. The URL of the PeopleSoft listening connector is in the following format:

```
http://computer_name/PSIGW/PeopleSoftListeningConnector
```

For example:

```
http://172.19.151.53/PSIGW/PeopleSoftListeningConnector
```

- e. Click **Load Gateway Connectors** to load all target connectors that are registered with the LOCAL gateway.
 - f. Click **Save**.
2. To create the USR_MGMT_NODE remote node:
- a. In the PeopleSoft Enterprise Portal window, expand **PeopleTools**, **Integration Broker**, and **Node Definitions**.
 - b. Click the **Add a New Value** tab.
 - c. On the Add a New Value tab, enter USR_MGMT_NODE as the node name and then click **Add**. The Node Definition page is displayed.
 - d. Enter a description for the node in the **Description** field.
 - e. Make this node a remote node by deselecting the **Local Node** check box and selecting the **Active Node** check box.
 - f. On the **Connectors** tab, enter the following information and then perform a lookup:

Gateway ID: LOCAL

Connector ID: PSFT81TARGET
 - g. On the **Properties** tab, enter the following information:

Property ID: PSFT81TARGET

Property Name: URL

Required value: Enter the URL of the PeopleSoft servlet that is to receive the XML message. This URL is in the following format:


```
http://computer_name:port/peopleSoftUserMgmt/do/peopleSoftAction
```


For example:


```
http://172.21.109.75:8080/peopleSoftUserMgmt/do/peopleSoftAction
```
 - h. Click **Save**.
 - i. Click the **Transactions** tab, and then click **Add Transaction**. The Add Transaction page is displayed.
 - j. Enter the following details to define the new transaction:

Transaction Type: Outbound Asynchronous

Request Message: USR_MGMT_MSG

Request Message Version: VERSION_1
 - k. Click **Add**.
 - l. To keep the status as active, select **Active**.
 - m. Click **Save** to save the changes.

3. To secure the USR_MGMT_MSGCH message channel:
 - a. Navigate to **PeopleTools, Security, Permission & Roles, and Permission Lists**.
 - b. Select **AEAE1000**. The AEAE1000 permission list is displayed.
 - c. Select the **Message Monitor** tab, and then click the button with the plus sign (+).
 - d. Enter USR_MGMT_MSGCH as the channel name.
 - e. Select **Full Access** from the list, and then click **Save**.
 - f. Click **PeopleTools, Integration Broker, Monitor, Monitor Message, and Channel Status** to check the status of the message channel.

If the status of the USR_MGMT_MSGCH message channel is **Pause**, then click the **Run** button to activate it.

Creating the Application Engine Program

To create the Application Engine program:

1. Click **Start, Programs, PeopleSoft8.x**, and then **Application Designer**. The Application Designer window is displayed.
2. Select **New** from the **File** menu. The New Definition dialog box is displayed.
3. Select **Application Engine** from the Definition list. The App Engine Program window is displayed, and the Step01 step is created by default.
4. In the App Engine Program window, select Step01 and then select **Action** from the **Insert** menu.
5. Rename Step01 to currency.
6. From the list on the action, select **PeopleCode**.
7. Select **Save** from the **File** menu, and save the Application Engine program with the name BLKPRCS_USER.
8. Double-click the **PeopleCode** action.
9. Copy the code from the CurrencyCode.txt file, which is in the *OIM_home/xellerate/Scripts* directory.
10. The code that you copy has the following default path for the output file in which the currency code data changes are to be stored:

C:/PT822/data/log/currency.txt

In the code, retain the file name (`currency.txt`) but change the path to any directory location on the PeopleSoft server. For example:

C:/MyDirectory/currency.txt

11. Save the **PeopleCode** action and close the window.
12. In the App Engine Program window, select the **MAIN** section and then select **Step/Action** from the **Insert** menu.
13. Repeat Steps 5 through 12 to create the remaining steps, which are listed in the following table.

Step Name	File Containing the Required PeopleCode
language	LanguageCode.txt
emplid	EmployeeId.txt
userrole	UserRoles.txt
permiss	PermissionList.txt
EmailType (PeopleTools 8.45 through 8.47 only)	EmailType.txt
addemp	AddEmp.txt

14. Save the Application Engine program.

Running the Application Engine Program

The procedure to run the Application Engine program depends on the release of PeopleTools that you are using:

- [Running the Application Engine Program on PeopleTools 8.22](#)
- [Running the Application Engine Program on PeopleTools 8.45 Through 8.47](#)

Running the Application Engine Program on PeopleTools 8.22 To run the Application Engine program on PeopleTools 8.22:

1. Log in to the PeopleSoft Enterprise Portal.
2. Click **People Tools, Process Scheduler Manager, Use, and Process Definitions**. The Process Definitions page is displayed.
3. Click **Add a New value**.
4. Select **Application Engine** from the **Process Type** list.
5. Enter the name of the Application Engine program as the process name, for example, **BLKPRCS_USER**.
6. Click **Add**.
7. Select the Application Engine Program from the search results that are displayed.
8. On the Process Definition Options tab, specify the following values:
 - **Run Location:** Server
 - **Server Name:** PSNT
 - **Component:** PRCSMULTI
 - **Process Groups:** ALLPANLS
9. Click **Save**.
10. Return to the home page.
11. Click **People Tools, Process Scheduler Manager, Process, and Sample Processes**. The Sample Processes page is displayed.
12. Click **Add a New value**.
13. Specify a run control ID, and then click **Add**.

Note: A run control ID is used as a key for records that contain the parameters required by a process at run time. If the parameters are stored in a table that the process can query using the run control ID and user ID, then the process can run without user intervention.

14. Click **Run**. The Process Scheduler Request page is displayed
15. Specify the server name.
16. Select the Application Engine program name, and then click **OK**.
17. Click **Process Monitor** to verify the status of the process.

After the process status changes to *Success*, the comma-separated file is created at the location specified in the code that you copy from the `AddEmp.txt` file.

Running the Application Engine Program on PeopleTools 8.45 Through 8.47 To run the Application Engine program on PeopleTools 8.45 through 8.47:

Note: For the Application Engine program to run in 2-tier mode, the database client must be installed on the server used for accessing the application designer. To switch to the 2-tier mode, you select `Connection Type` as the database on the PeopleSoft sign-on screen.

1. Open the application designer in 2-tier mode.
2. Specify the connection type, user ID, and password.
3. To open the Application Engine program that you create:
 - a. From the **File** menu, select **Open** and then select **Application Engine Program** from the **Object Type** list.
 - b. Select **BLKPRCS_USER**, and then click **Open**.
4. Click the RUN PROGRAM control on the toolbar below the menu bar. The code for the PeopleCode action is run. The comma-separated file containing user records is created at the location specified in the code.

Configuring Trusted Source Reconciliation

While configuring the connector, the target system can be designated as a trusted source or a target resource. If you designate the target system as a **trusted source**, then both newly created and modified user accounts are reconciled in Oracle Identity Manager. If you designate the target system as a **target resource**, then only modified user accounts are reconciled in Oracle Identity Manager.

Note: You can skip this section if you do not want to designate the target system as a trusted source for reconciliation.

1. Import the XML file for trusted source reconciliation, `PSFTBaseXellerateUser.xml`, by using the Deployment Manager. This section describes the procedure to import the XML file.

Note: Only one target system can be designated as a trusted source. If you import the `PSFTBaseXellerateUser.xml` file while you have another trusted source configured, then both connector reconciliations would stop working.

2. Specify values for the attributes of the `PSFT Base Trusted User Reconciliation` scheduled task. This procedure is described later in this guide.

To configure trusted source reconciliation:

1. Open the Oracle Identity Manager Administrative and User Console.
2. Click the **Deployment Management** link on the left navigation bar.
3. Click the **Import** link under Deployment Management. A dialog box for locating files is displayed.
4. Locate and open the `PSFTBaseXellerateUser.xml` file, which is in the `OIM_home/xlclient` directory. Details of this XML file are shown on the File Preview page.
5. Click **Add File**. The Substitutions page is displayed.
6. Click **Next**. The Confirmation page is displayed.
7. Click **Import**.
8. In the message that is displayed, click **Import** to confirm that you want to import the XML file and then click **OK**.

Configuring the Reconciliation Scheduled Tasks

When you perform the procedure described in the ["Step 4: Importing the Connector XML Files"](#) section on page 2-6, the scheduled tasks for lookup fields, trusted source user, and nontrusted user reconciliations are automatically created in Oracle Identity Manager. To configure these scheduled tasks:

1. Open the Oracle Identity Manager Design Console.
2. Expand the **Xellerate Administration** folder.
3. Select **Task Scheduler**.
4. Click **Find**. The details of the predefined scheduled tasks are displayed on two different tabs.
5. Enter a number in the Max Retries field. This number represents the number of times Oracle Identity Manager must attempt to complete the task before assigning the ERROR status to the task.
6. Ensure that the **Disabled** and **Stop Execution** check boxes are not selected.
7. In the Start region, double-click the **Start Time** field. From the date-time editor that is displayed, select the date and time at which you want the task to run.
8. To set the task to run only once, select the **Once** option in the Interval region.
9. Provide values for the attributes of the scheduled task. Refer to the ["Specifying Values for the Scheduled Task Attributes"](#) section on page 3-17 for information about the values to be specified.

10. Click **Save**. The scheduled task is created. The INACTIVE status is displayed in the **Status** field, because the task is not currently running. The task is run at the date and time that you set in Step 7.

11. Repeat Steps 5 through 10 to create the second scheduled task.

After you create both scheduled tasks, proceed to the ["Adding Custom Attributes for Reconciliation"](#) section on page 3-19.

Specifying Values for the Scheduled Task Attributes

This section provides information about the values to be specified for the following scheduled tasks:

- [Lookup Fields Reconciliation Scheduled Task](#)
- [User Reconciliation Scheduled Task](#)

Lookup Fields Reconciliation Scheduled Task You must specify values for the following attributes of the PSFT Base LookUp Reconciliation scheduled task.

Note:

- Attribute values are predefined in the connector XML file that you import. Specify values only for those attributes that you want to change.
 - Values (either default or user-defined) must be assigned to all the attributes. If even a single attribute value were left empty, then reconciliation would not be performed.
-
-

Attribute	Description
ServerName	Name of the IT resource Default value: PSFT Base Server
LookupType	The type of data that is being looked up in the target system. The value can be any one of the following: <ul style="list-style-type: none"> ■ EmployeeId ■ LanguageCode ■ EmailTypes ■ CurrencyCode ■ PermissionList ■ UserRoles
FilePath	Directory path on the Oracle Identity Manager server where the reconciliation lookup .txt file is stored Sample value: C:/PSFTBase/LookupRecon/EmployeeIds.txt

Attribute	Description
LookupName	<p>Name of the lookup definition configured in Oracle Identity Manager</p> <p>The value can be any one of the following:</p> <ul style="list-style-type: none"> ■ Lookup.PSFTBase.EmployeeId ■ Lookup.PSFTBase.LanguageCode ■ Lookup.PSFTBase.EmailType ■ Lookup.PSFTBase.CurrencyCode ■ Lookup.PSFTBase.PermissionList ■ Lookup.PSFTBase.Roles
TargetSystem	<p>Name of the resource object</p> <p>Default value: PSFTBase</p>

After you specify values for these task attributes, go to Step 10 of the procedure to create scheduled tasks.

User Reconciliation Scheduled Task Depending on whether you want to implement trusted or nontrusted sourced reconciliation, you must specify values for the attributes of one of the following user reconciliation scheduled tasks:

- PSFT Base Trusted User Reconciliation (Scheduled task for trusted source reconciliation)
- PSFT Base Non Trusted User (Scheduled task for nontrusted source reconciliation)

The following table describes the attributes of both scheduled tasks.

Note:

- Attribute values are predefined in the connector XML file that you import. Specify values only for those attributes that you want to change.
 - Values (either default or user-defined) must be assigned to all the attributes. If even a single attribute value were left empty, then reconciliation would not be performed.
-

Attribute	Description
MultiValueSeperator	## is the multivalue separator in the flat file that is used for bulk reconciliation
ServerName	<p>Name of the IT resource instance</p> <p>Default value: PSFTBase</p>
IsTrusted	<p>Specifies whether or not reconciliation is to be carried out in trusted mode</p> <p>Specify Yes for trusted source reconciliation.</p> <p>Specify No for nontrusted source reconciliation.</p>

Attribute	Description
XellerateOrganization	Default name of the Oracle Identity Manager organization This value is used to create the Xellerate User in trusted mode. Note: This attribute is specific to the scheduled task for trusted source reconciliation.
FolderPath	Directory path on the Oracle Identity Manager server where the reconciliation lookup .txt file is stored
TargetSystem	Name of the resource object Default value: PSFTBase

After you specify values for these task attributes, go to Step 10 of the procedure to create scheduled tasks.

Adding Custom Attributes for Reconciliation

Note: In this section, the term "attribute" refers to the identity data fields that store user data.

Standard change-based reconciliation involves the reconciliation of predefined attributes. If required, you can add custom attributes to the list of fields that are reconciled.

The procedure to add a custom attribute for reconciliation depends on the release of PeopleTools that you are using:

- [Adding a Custom Attribute for Reconciliation on PeopleTools 8.22](#)
- [Adding a Custom Attribute for Reconciliation on PeopleTools 8.45 Through 8.47](#)

Adding a Custom Attribute for Reconciliation on PeopleTools 8.22

To add a custom attribute for reconciliation on PeopleTools 8.22:

1. In PeopleSoft Application Designer:
 - a. Select **Open** from the **File** menu. The Open Definition dialog box is displayed.
 - b. Select **Message** from the **Definition** list, enter `USR_MGMT_MSG` in the **Name Selection Criteria** field, and then click Enter. The details of the `USR_MGMT_MSG` message are displayed.
 - c. Click the record to which you want to add custom attributes.
For example, suppose you want to add the job location attribute, `LOCATION`, then click **JOB** under **VERSION_1**.
 - d. Select the check box for the required attribute, and then save the message.
For example, select the **LOCATION** check box.
2. Make the required changes in the PeopleCode given in the `UserMgmtCBRecon.txt` file. This file is in the `OIM_home/xellerate/Scripts` directory. The required changes are as follows:
 - a. At the end of the SQL statements section, edit the SQL statement to retrieve the column values for the new attribute and store the values in local variables.

For example, suppose you want to add the job location attribute, `LOCATION`, to the list of attributes that are reconciled. Then, performing this step involves editing the SQL statement as follows, so that it retrieves the values of the `LOCATION` column from the `JOB` table:

```
SQLExec("select DEPTID, JOBCODE, LOCATION from ps_job a where emplid =:1
and effdt=(select max(effdt) from ps_job b where a.emplid=b.emplid and
effseq =(select max(effseq) from ps_job c where b.emplid = c.emplid and
b.effdt=c.effdt))", &empid, &deptid, &jobcd, &location);
```

- b. Add the required lines at the end of the block of code for adding data to the XML message. For example, to add the `LOCATION` column to the `JOB` tag, add the lines highlighted in bold in the following code sample:

```
/* FOR JOB RECORD */
&MSG_ROWSET.GetRow(1).JOB.JOBCODE.Value = &jobcd;
&MSG_ROWSET.GetRow(1).JOB.DEPTID.Value = &deptid;
&MSG_ROWSET.GetRow(1).JOB.LOCATION.Value = &location;
```

3. To extract the contents of the `peopleSoftUserMgmt.war` file into a temporary directory, enter the following command:

```
jar -xvf peopleSoftUserMgmt.war
```

Copies of this file are in the application server deployment directory and the `OIM_home/xellerate/webapp` directory.

4. In the `attributemap.properties` file, add the XPath (key-value entry) of the custom attribute. For example, you can add the following XPath for the `LOCATION` attribute:

```
Users.LOCATION=//Transaction/DEPT_TBL/LOCATION
```

5. Delete the existing `peopleSoftUserMgmt.war` file from the temporary directory into which you extract it, and then enter the following command to re-create the file:

```
jar -cvf peopleSoftUserMgmt.war .
```

6. Delete the old version of the `peopleSoftUserMgmt.war` file from the application server deployment directory and the `OIM_home/xellerate/webapp` directory.
7. Copy the newly created `peopleSoftUserMgmt.war` file into the application server deployment directory and the `OIM_home/xellerate/webapp` directory.
8. In the Oracle Identity Manager Design Console, make the required changes as follows:

See: *Oracle Identity Manager Design Console* for detailed instructions on performing the following steps

- a. Add a column corresponding to the new attribute in the User Defined process form, `UD_PSFT_BAS`. For the example described earlier, you can add the `UD_PSFT_BAS_LOCATION` column.
- b. Add a reconciliation field corresponding to the new attribute in the resource object, `PSFTBase`. For the example described earlier, you can add the `Users.LOCATION` reconciliation field.

- c. Modify the PSFTBase process definition to include the mapping between the newly added attribute and the corresponding reconciliation field. For the example described earlier, the mapping is as follows:

```
Users.LOCATION = UD_PSFT_BAS_LOCATION
```

- d. Modify the `attributemapping_recon.properties` file, which is in the `OIM_home/xellerate/XLIntegrations/PSFTBASE/config` directory.

You can also add new attributes in this file. The format that you must use is as follows:

```
TargetAttribute=Users.OimAttributeName
```

For example:

```
LOCATION=Users.LOCATION
```

In this example, `LOCATION` is the reconciliation field and also the equivalent target system attribute. As a standard, the prefix `"Users."` is added at the start of all reconciliation field names.

9. Restart the Oracle Identity Manager server and client.

Adding a Custom Attribute for Reconciliation on PeopleTools 8.45 Through 8.47

To add a custom attribute for reconciliation on PeopleTools 8.45 through 8.47:

1. Make the required changes in the PeopleCode given in the `UserMgmtCBRecon.txt` file. This file is in the `OIM_home/xellerate/Scripts` directory. The required changes are as follows:

- a. At the end of the SQL statements section, add a SQL statement to retrieve the column values for the new attribute and store the values in local variables.

For example, suppose you want to add the department location attribute, `LOCATION`, to the list of attributes that are reconciled. Then, performing this step involves adding the following SQL statement to retrieve the values of the `LOCATION` column from the `PS_DEPT_TBL` table:

```
SQLExec("SELECT DESCR, LOCATION FROM PS_DEPT_TBL WHERE DEPTID=:1", &deptid, &deptname, &location);
```

- b. Add the required lines at the end of the block of code for adding data to the XML message. For example, to add the `LOCATION` column to the `DEPT_TBL` tag, add the lines highlighted in bold in the following code sample:

```
&recnode = &fieldtypenode.AddElement("DEPT_TBL");
&recnode.AddAttribute("class", "R");
&fields = &recnode.AddElement("DEPTNAME");
&fields.AddAttribute("type", "CHAR");
&fields = &recnode.AddElement("LOCATION");
&fields.AddAttribute("type", "CHAR");
```

- c. Add the required lines at the end of the block of code for adding data to the XML message. For example, to add the `LOCATION` column to the `DEPT_TBL` tag, add the lines highlighted in bold in the following code sample:

```
&datarecnode = &transnode.AddElement("DEPT_TBL");
&datarecnode.AddAttribute("class", "R");
&datafldnode = &datarecnode.AddElement("DEPTNAME");
&textnode = &datafldnode.AddText(&deptname);
&datafldnode = &datarecnode.AddElement("LOCATION");
```

```
&textnode = &datafldnode.AddText(&location);
```

2. In PeopleSoft Application Designer, copy the contents of the UserMgmtCBRecon.txt file into the savePostChange event for the PERSONAL_DATA component.
3. To extract the contents of the peopleSoftUserMgmt.war file into a temporary directory, enter the following command:

```
jar -xvf peopleSoftUserMgmt.war
```

Copies of this file are in the application server deployment directory and the *OIM_home/xellerate/webapp* directory.

4. In the attributemap.properties file, add the XPath (key-value entry) of the custom attribute. For example, you can add the following XPath for the LOCATION attribute:

```
Users.LOCATION=//Transaction/DEPT_TBL/LOCATION
```

5. Delete the existing peopleSoftUserMgmt.war file from the temporary directory into which you extract it, and then enter the following command to re-create the file:

```
jar -cvf peopleSoftUserMgmt.war .
```

6. Delete the old version of the peopleSoftUserMgmt.war file from the application server deployment directory and the *OIM_home/xellerate/webapp* directory.
7. Copy the newly created peopleSoftUserMgmt.war file into the application server deployment directory and the *OIM_home/xellerate/webapp* directory.
8. In the Oracle Identity Manager Design Console, make the required changes as follows:

See: *Oracle Identity Manager Design Console* for detailed instructions on performing the following steps

- a. Add a column corresponding to the new attribute in the User Defined process form, UD_PSFT_BAS. For the example described earlier, you can add the UD_PSFT_BAS_LOCATION column.
- b. Add a reconciliation field corresponding to the new attribute in the resource object, PSFTBase. For the example described earlier, you can add the Users.LOCATION reconciliation field.
- c. Modify the PSFTBase process definition to include the mapping between the newly added attribute and the corresponding reconciliation field. For the example described earlier, the mapping is as follows:

```
Users.LOCATION = UD_PSFT_HR_LOCATION
```

- d. Modify the attributemapping_recon.properties file, which is in the *OIM_home/xellerate/XLIntegrations/PSFTBASE/config* directory.

You can also add new attributes in this file. The format that you must use is as follows:

```
TargetAttribute=Users.OimAttributeName
```

For example:

LOCATION=Users.LOCATION

In this example, LOCATION is the reconciliation field and also the equivalent target system attribute. As a standard, the prefix "Users." is added at the start of all reconciliation field names.

9. Restart the Oracle Identity Manager server and client.

Encrypting a New Oracle Identity Manager Password

If the password of the Oracle Identity Manager administrator is different from the default password, then you must encrypt the Oracle Identity Manager password as follows:

Note: The default administrator user ID is xelsysadm.

1. On the Oracle Identity Manager server, open a command window.
2. In the command window, change to the *OIM_home/xellerate/ScheduleTask* directory.
3. Enter the following command:

```
java -classpath PSFTBaseReconciliation .jar \
Com.thortech.xl.Integration.peoplesoft.util.tcUtilEncryption -e \
OIM_plaintext_password
```

In this command, *OIM_plaintext_password* is the new Oracle Identity Manager administrator password that you want to encrypt.

The encrypted password is displayed in the command window.

4. Copy the encrypted password into the *xlsession.properties* file. This file is compressed in the *OIM_home/xlclient/lib/peopleSoftUserMgmt.war* file.
5. Delete the *peopleSoftUserMgmt.war* file from the temporary directory where you extracted its contents, and then use the following command to re-create the file:

```
jar -cvf peopleSoftUserMgmt.war
```

6. Ensure that the old version of the *peopleSoftUserMgmt.war* file is removed from the application server (JBoss Application Server, IBM WebSphere, BEA WebLogic, or OC4J) deployment directory and the *OIM_home/xellerate/webapp* directory.
7. Copy the newly created *peopleSoftUserMgmt.war* file into the application server (JBoss Application Server, IBM WebSphere, BEA WebLogic or OC4J) deployment directory and the *OIM_home/xellerate/webapp* directory.
8. Restart the Oracle Identity Manager server and client.

Configuring Provisioning

As mentioned earlier in this guide, provisioning involves creating or modifying a user's account information on the target system through Oracle Identity Manager. Refer to the ["Supported Functionality"](#) section on page 1-4 for a listing of the provisioning functions that are available with this connector.

This section discusses the following topics related to configuring provisioning:

- [Compiling Adapters](#)
- [Adding Custom Attributes for Provisioning](#)
- [Configuring the Target System for Provisioning](#)

Compiling Adapters

Note: You must perform this procedure if you want to use the provisioning features of the connector.

Adapters are used to implement provisioning functions. The following adapters are imported into Oracle Identity Manager when you import the connector XML file:

See Also: The "[Supported Functionality](#)" section on page 1-4 for a listing of the provisioning functions that are available with this connector

- adpPSFTCREATEUSER
- adpPSFTUPDATEUSER
- adpPSFTRESETPASSWORD
- adpPSFTUNLOCKUSER
- adpPSFTLOCKUSER
- adpPSFTUPDATEUSEREMPID
- adpPSFTADDORDELETEROLE
- adpPSFTADDORDELETEEMAIL (PeopleTools 8.45 through 8.47 only)

You must compile these adapters before they can be used in provisioning operations.

To compile adapters by using the Adapter Manager form:

1. Open the Adapter Manager form.
2. To compile all the adapters that you import into the current database, select **Compile All**.

To compile multiple (but not all) adapters, select the adapters you want to compile. Then, select **Compile Selected**.

Note: Click **Compile Previously Failed** to recompile only those adapters that were not compiled successfully. Such adapters do not have an OK compilation status.

3. Click **Start**. Oracle Identity Manager compiles the selected adapters.
4. If Oracle Identity Manager is installed in a clustered environment, then copy the compiled adapters from the *OIM_home/xellerate/Adapter* directory to the same directory on each of the other nodes of the cluster. If required, overwrite the adapter files on the other nodes.

If you want to compile one adapter at a time, then use the Adapter Factory form.

See Also: *Oracle Identity Manager Tools Reference Guide* for information about using the Adapter Factory and Adapter Manager forms

To view detailed information about an adapter:

1. Highlight the adapter in the Adapter Manager form.
2. Double-click the row header of the adapter, or right-click the adapter.
3. Select **Launch Adapter** from the shortcut menu that is displayed. Details of the adapter are displayed.

Adding Custom Attributes for Provisioning

Note: In this section, the term "attribute" refers to the identity data fields that store user data.

To add a custom attribute for provisioning:

See Also: *Oracle Identity Manager Design Console Guide*

1. Modify the `attributemapping_prov.properties` file, which is in the `OIM_home/xellerate/XLIntegrations/PSFTBase/config` directory. At the end of this file, some of the attribute definitions are preceded by comment characters. You can uncomment the definitions of attributes that you want to use any one of them to make it a part of the provisioning attributes.

You can also add new attributes in this file. The format that you must use is as follows:

```
OimAttributeName=TargetAttributeName
```

For example:

If you want to add the `AlternateUserID` field, then add the following line in the `attributemapping_prov.properties` file:

```
AlternateUserID=AlternateUserID
```

2. Add a new column in the process form.
 - a. Open the process form. This form is in the **Development Tools** folder of the Oracle Identity Manager Design Console
 - b. Click **Create New Version**.
 - c. In the Create a New Version dialog box, specify the version name in the **Label** field, save the changes, and then close the dialog box.
 - d. From the **Current Version** list, select the newly created version.
 - e. On the Additional Columns tab, click **Add**.
 - f. Specify the new field name and other values.
3. Add a new variable in the variable list.
 - a. Open the Adapter Factory form. This form is in the Development Tools folder of the Oracle Identity Manager Design Console.

- b. Click the **Query for Records** icon.
 - c. On the Adapter Factory Table tab, double-click the **adpPSFTCREATEUSER** adapter from the list.
 - d. On the Variable List tab, click **Add**.
 - e. In the Add a Variable dialog box, specify the required values and then save and close the dialog box.
 4. Define an additional adapter task for the newly added variable in the **adpPSFTCREATEUSER** adapter.
 - a. On the Adapter Tasks tab of the Adapter Factory form, click **Add**.
 - b. In the Adapter Task Selection dialog box, select **Functional Task**, select **Java** from the list of functional task types, and then click **Continue**.
 - c. In the Object Instance Selection dialog box, select the Persistent instance and then click **Continue**.
 - d. In the Add an Adapter Factory Task dialog box, specify the task name, select the **setProperty** method from the **Method** list, and then click **Save**.
 - e. Map the application method parameters, and then save and close the dialog box. To map the application method parameters:

For the "Output: String Return variable (Adapter Variable)" parameter:

 - i. From the **Map to** list, select **Literal**.
 - ii. From the **Name** list, select **Return variable**.

For the "Input: String input (Adapter Variable)" parameter:

 - i. From the **Map to** list, select **Adapter Variables**.
 - ii. From the **Name** list, select **Input**.

For the "Input: String Status (Literal)" parameter:

 - i. From the **Map to** list, select **Literal**.
 - ii. From the **Name** list, select **String**.
 - iii. In the **Value** field, enter **Status**.

For the "Input: String Status (Adapter Variable)" parameter:

 - i. From the **Map to** list, select **Adapter Variables**.
 - ii. From the **Name** list, select **Status**.
 - f. Repeat Steps b through g' to create more adapter tasks.
 5. Create an additional adapter task to set the input variable.
 - a. Open the Adapter Factory form. This form is in the Development Tools folder in the Oracle Identity Manager Design Console.
 - b. On the Adapter Tasks tab, click **Add**.
 - c. In the Adapter Task Selection dialog box, select **Logic Task**, select **SET VARIABLE** from the list, and then click **Continue**.
 - d. In the Edit Set Variable Task Parameters dialog box, select **input** from the **Variable Name** list, select **Adapter Task** from the **Operand Type** list, and the Operand Qualifier as the Adapter Task that you have created in the previous step. Then, click **Save**.

6. Map the process form columns and adapter variables for the Create User process task as follows:
 - a. Open the Process Definition form. This form is in the Process Management folder of the Design Console.
 - b. Click the **Query for Records** icon.
 - c. On the Process Definition Table tab, double-click the **PSFTBase** process.
 - d. On the Tasks tab, double-click the **Create User** task.
 - e. In the Closing Form dialog box, click **Yes**.
 - f. On the Integration tab of the Editing Task Columns Create User dialog box, map the unmapped variables, and then save and close the dialog box. To map an unmapped variable:
 - i. Double-click the row in which **N** is displayed in the Status column. The value **N** signifies that the variable is not mapped.
 - ii. From the **Map to** list in the Edit Data Mapping for Variables dialog box, select **Process Data**.
 - iii. From the **Qualifier** list, select the name of the variable.
 Repeat Steps i through iii for all unmapped variables.
 Repeat Steps 1 through 6 if you want to add more attributes.

Configuring the Target System for Provisioning

This section describes the following procedures to be performed on the target system:

- [Creating the APIs for the Component Interface](#)
- [Creating the Java Template for the Component Interface](#)

Creating the APIs for the Component Interface

To create the APIs for the component interface:

1. Open the Application Designer by clicking **Start** and then selecting **Programs**, **Peoplesoft8.x**, and **Application Designer**. The Application Designer window is displayed.
2. In the Application Designer window, select **Open** from the **File** menu. The Open Definition dialog box is displayed.
3. In the Open Definition dialog box, select **Component Interface** from the **Definition** list.
4. Enter **USER_PROFILE** in the **Name** field, and then press **Enter**.
All the component interfaces with names that start with **USER_PROFILE** are displayed in the Open Definition dialog box.
5. Select the **USER_PROFILE** entry, and then click **Open**.
6. Click **Yes** in the message that is displayed. The properties of the **USER_PROFILE** component interface are displayed.
7. In the window for the **USER_PROFILE** component interface, select **PeopleSoft APIs** from the **Build** menu. The Build PeopleSoft API Bindings dialog box is displayed.
8. In the Java Classes region, select the **Build** check box.

9. From the **Select APIs to Build** list, select **CompIntfc.CompIntfcPropertyInfo**, **CompIntfc.CompIntfcPropertyInfoCollection**, and the APIs with names that start with **CompIntfc.USER_PROFILE**.
10. In the **Target Directory** field, specify the path of the directory in which you want the Java API classes to be created, and then click **OK**.
11. Ensure that the `psjoa.jar` file is set in the `CLASSPATH` environment variable. This file is in the `OIM_home/xellerate/ThirdParty` directory.
12. Compile the APIs from the target directory specified in the preceding step.
13. Bundle the compiled class files in a JAR named `peoplesoft.jar` as follows:

```
jar -cvf peoplesoft.jar PeopleSoft/Generated/CompIntfc/*.class
```

Creating the Java Template for the Component Interface

To create the Java template for the component interface:

1. On the right pane of the window for the `USER_PROFILE` component interface, right-click **USER_PROFILE**.
2. Select **Generate Java Template** from the shortcut menu. A message showing the name and path of the Java template is displayed.
3. Click **OK** to close the message.

Configuring the Connector for Multiple Installations of the Target System

Note: Perform this procedure only if you want to configure the connector for multiple installations of PeopleSoft User Management.

You may want to configure the connector for multiple installations of PeopleSoft User Management. The following example illustrates this requirement:

The Tokyo, London, and New York offices of Acme Multinational Inc. have their own installations of PeopleSoft User Management. The company has recently installed Oracle Identity Manager, and they want to configure Oracle Identity Manager to link all the installations of PeopleSoft User Management.

To meet the requirement posed by such a scenario, you must configure the connector for multiple installations of PeopleSoft User Management.

To configure the connector for multiple installations of the target system:

See Also: *Oracle Identity Manager Design Console Guide* for detailed instructions on performing each step of this procedure

1. Create and configure one IT resource for each target system installation.

The IT Resources form is in the Resource Management folder. An IT resource is created when you import the connector XML file. You can use this IT resource as the template for creating the remaining IT resources, of the same IT resource type.
2. Configure reconciliation for each target system installation. Refer to the "[Partial Reconciliation](#)" section on page 3-1 for instructions. Note that you only need to modify the attributes that are used to specify the IT resource and to specify whether or not the target system installation is to be set up as a trusted source.

3. If required, modify the fields to be reconciled for the Xellerate User resource object.

Additional Steps for Configuring Change-Based Reconciliation

For change-based reconciliation, you must perform the procedure described in the following sections:

- [Configuring the Target System for Reconciliation](#) on page 3-5
- [Configuring the PeopleSoft Listener Web Service for Change-Based Reconciliation](#) on page 3-2

The following are actions that you must perform differently from the procedure described in these sections:

- In Step 4.b of the "[Configuring PeopleSoft Enterprise Portal on PeopleTools 8.22](#)" section on page 3-8:

Note: Perform this step only if you use PeopleTools 8.22.

Change the Java command in the `publish.bat` file as shown in the following example:

```
java Com.thortech.xl.Integration.msgpublisher.PeopleSoftPublisher
"http://host:port/peopleSoftUserMgmt1/do/peopleSoftAction" "C:/test/file"
USR_MGMT_MSG >> c:/test/consolelog.log
```

Similarly, change the name of the Web application for each WAR file that you create.

- In Step 7 of the procedure to create the XL_NODE node, given in the "[Configuring PeopleSoft Enterprise Portal on PeopleTools 8.45 Through 8.47](#)" section on page 3-11:

Note: Perform this step only if you use PeopleTools 8.45 through 8.47.

Change the name of the application in the URL as shown in the following example:

```
http://computer_name:port/peopleSoftUserMgmt1/do/peopleSoftAction
```

Similarly, change the name of the Web application in the URL for each WAR file that you create.

- In the "[Configuring the PeopleSoft Listener Web Service for Change-Based Reconciliation](#)" section on page 3-2:

In Step 3, the value that you specify for the `ObjectName` parameter in the `xlsession.properties` file must be the name of the resource object that you create.

In Step 7, specify a different file name in the command that you use to re-create the WAR file. For example:

```
jar -cvf peopleSoftUserMgmt1.war
```

Similarly, change the name of the WAR file for each target system installation

Testing and Troubleshooting

After you deploy the connector, you must test it to ensure that it functions as expected. This chapter discusses the following topics related to connector testing:

- [Testing Reconciliation](#)
- [Testing Provisioning](#)
- [Troubleshooting](#)

Testing Reconciliation

Running test cases for reconciliation involves verifying that the PeopleSoft Listener Web application can reconcile employees into Oracle Identity Manager. The following sections provides instructions to perform this test.

Prerequisites for Testing the PeopleSoft Listener Web Application

The following are prerequisites for testing the PeopleSoft Listener Web application:

- Ensure that the Microsoft Windows scripting engine is installed. This is required to run VBScript files.
- Ensure that the PeopleSoft XML message schema is described in the `USR_MGMT_MSG.xml` file, which is in the `OIM_home/xellerate/test` directory.

Testing the PeopleSoft Listener Web Application

To test the PeopleSoft Listener Web application:

1. In the `OIM_home/xellerate/test/cbrecon/psft-xel-test.vbs` file:
 - Modify the value of the `ps_server_url` variable so that it points to the URL for the PeopleSoft Listener Web application.
 - Specify the required PeopleSoft attributes and employee data values in the `ExecuteATM` function.
2. Run `psft-xel-test.vbs`. Ensure that the script runs without any errors.

When the script is run, it creates a reconciliation event. Verify that the reconciliation event is created in Oracle Identity Manager and that the event contains the data that you specify in the VBScript file.

Performing Trial Reconciliation

Refer to the ["Partial Reconciliation"](#) section on page 3-1.

Testing Provisioning

You can use the testing utility to identify the cause of problems associated with connecting to the target system and performing basic operations on the target system.

Before you use the testing utility, you must set the required values in the `config.properties` file. This file is in the `OIM_home/xellerate/XLIntegrations/PSFTBase/config` directory.

Use the information in the following table to modify the default attributes of the `config.properties` file.

Name	Description	Sample Value
serverName	IP address or host name of the PeopleSoft User Management server	172.21.109.95
serverPort	Port at which the PeopleSoft User Management server is listening	9000
admin	User ID of the PeopleSoft User Management server administrator	PS
ciName	Component interface used to load user data in PeopleSoft User Management	USER_PROFILE
NumberOfRetries	Number of times the connection to the target system must be retried before the <code>InvocationTargetException</code> is thrown	2
DelayBetweenRetries	Time difference between subsequent retries (in milliseconds)	10000
action	Action to be performed	You can specify one of the following values: CONNECT CREATE UPDATEUSERINFO UPDATEUSER_EMPID UPDATEPASSWORD
userId	User login ID	PSFTTEST
userDescription	Description of the user	PSFTTEST
primaryEmailAddress	Primary e-mail address	PSFTTEST@psft.com
primaryEmailType	E-mail type of the primary e-mail account	BUS
password	Password of the user	password
languageCode	Language code for the user	ENG
currencyCode	Currency code for the user	USD
recName	Used to validate the employee ID during user provisioning in PeopleSoft User Management	PERSONAL_DATA
empId	Employee ID for the user	A10000

Name	Description	Sample Value
<code>primaryPermissionList</code>	Primary permission list for the user	HCCPAM1
<code>userIdAlias</code>	User ID alias	PSFTTEST1
<code>symbolId</code>	Specifies the AccessId associated with the user profile The AccessId specifies whether or not the user has sufficient privileges on the PeopleSoft User Management database.	PS89
<code>attrName</code>	Name of the attribute to be updated	You can specify one of the following values: USER_DESCRIPTION EMAIL_ADDRESS EMAILTYPE MULTI_LANGUAGE_CODE LANGUAGE_CODE CURRENCY_CODE
<code>attrValue</code>	Value of the attribute to be updated	The value that you provide must correspond to the attribute name that you specify as the value of the <code>attrName</code> parameter.

After you specify values in the `config.properties` file, run one of the following files:

For UNIX:

```
OIM_home/xellerate/XLIntegrations/tests/scripts/PSFTBase.sh
```

For Microsoft Windows

```
OIM_home\xellerate\XLIntegrations\tests\scripts\PSFTBase.bat
```

Troubleshooting

The following table lists solutions to some commonly encountered issues associated with the PeopleSoft User Management connector.

Problem Description	Solution
Oracle Identity Manager cannot establish a connection with the PeopleSoft User Management server.	<ul style="list-style-type: none"> ■ Ensure that the PeopleSoft User Management server is running. ■ Ensure that Oracle Identity Manager is running. ■ Ensure that all the adapters have been compiled. ■ Use the IT Resources form to examine the Oracle Identity Manager record. Ensure that the IP address, admin ID, and admin password are correct.

Problem Description	Solution
The Operation Fail message is displayed on the Oracle Identity Manager Administrative and User Console.	<ul style="list-style-type: none"> ■ Ensure that the values for the attributes do not contain delimiter characters, such as white space and commas. ■ Ensure that the attribute values do not exceed allowable length.
The Create User adapter is triggered even when the pre-populate adapter is run successfully.	Set the property associated with the user ID attribute in the process form as required.

Known Issues

The following are known issues associated with this release of the connector:

- Secure Sockets Layer (SSL) connections are not supported.
- The connector files for PeopleTools 8.22 and PeopleTools 8.45 through 8.47 cannot be deployed on the same Oracle Identity Manager installation.
- Some Asian languages use multibyte character sets. If the character limit for the fields in the target system is specified in bytes, then the number of Asian-language characters that you can enter in a particular field may be less than the number of English-language characters that you can enter in the same field. The following example illustrates this limitation:

Suppose you can enter 50 characters of English in the User Last Name field of the target system. If you were using the Japanese language and if the character limit for the target system fields were specified in bytes, then you would not be able to enter more than 25 characters in the same field.

Attribute Mappings Between Oracle Identity Manager and PeopleSoft User Management

The following table discusses attribute mappings between Oracle Identity Manager and PeopleSoft User Management.

Oracle Identity Manager Attribute	PeopleSoft User Management Attribute	Description
Lookup Fields		
LanguageCode	PSXLATITEM.FIELDVALUE , PSXLATITEM.XLATLONGNAME	Language code
EmployeeId	PS_PERSONAL_DATA.EMP LID, PS_PERSONAL_DATA.NA ME	Employee ID
CurrencyCode	PS_CURRENCY_CD_TBL.C URRENCY_CD, PS_CURRENCY_CD_TBL.D ESCR	Currency Code
PermissionList	PSCLASSDEFN.CLASSID,PS CLASSDEFN.CLASSDEFND ESC	Permission List
EmailType	PSXLATITEM.FIELDVALUE , PSXLATITEM.XLATLONGNAME	E-mail Type
UserRoles	PSROLEDEFN.ROLENAM, PSROLEDEFN.DESC	User Roles
User Attributes		
User Id	PSOPRDEFN.OPRID	User login ID
User Description	PSOPRDEFN.OPRDEFNDESC	Description of user
Employee Id	PSOPRDEFN.EMPLID	Employee ID
Primary Email Address	PSUSEREMAIL.EMAILID	E-mail address (primary e-mail account)
Primary Email Type	PSUSEREMAIL.EMAILTYPE	Email type (primary e-mail account)
Multi Language Code	PSOPRDEFN.MULTILANG	Multilanguage code

Oracle Identity Manager Attribute	PeopleSoft User Management Attribute	Description
Language Code	PSOPRDEFN.LANGUAGE_CD	Language code
Currency Code	PSOPRDEFN.CURRENCY_CD	Currency code
User Id Alias	PSOPRDEFN.USERIDALIAS	Alias of user login ID
Row Security Permission List	PSOPRDEFN.ROWSECCLASS	Row security parameter
Process Profile Permission List	PSOPRDEFN.PRCSPRFLCLS	Process profile parameter
Navigator Home Permission List	PSOPRDEFN.DEFAULTNAVHP	Navigator home page address
Primary Permission List	PSOPRDEFN.OPRCLASS	Primary permission list
Email Address	PSUSEREMAIL.EMAILID	E-mail address
Email Type	PSUSEREMAIL.EMAILTYPE	E-mail type
RoleName	PSROLEUSER_VW.ROLENAME	Role name

Index

A

Adapter Manager form, 3-24
adapters, compiling, 3-23
Administrative and User Console, 2-6, 3-16, 4-4
attributes
 lookup fields reconciliation scheduled task, 3-17
 user reconciliation scheduled task, 3-18
attributes mappings, A-1

B

bulk reconciliation, 1-3

C

change-based reconciliation, 1-3
changing input locale, 2-3
clearing server cache, 2-3
compiling adapters, 3-23
configuring
 connector for multiple installations of the target system, 3-28
 gateway, 3-11
 Oracle Identity Manager server, 2-3
 PeopleSoft Enterprise Portal, 3-8
 PeopleSoft listener, 3-2
configuring provisioning, 3-23
configuring target system for provisioning, 3-27
configuring target system for reconciliation, 3-5
connector customization, 3-1
connector files and directories
 copying, 2-1
 description, 1-6
 destination directories, 2-1
 installation directory, 2-2
 installation media file, 1-6
connector testing, 4-1
connector version number, determining, 1-8
connector XML files
 See XML files
creating
 APIs for component interface, 3-27
 Application Engine program, 3-13
 Java template for component interface, 3-28
 message, 3-7

 message channel, 3-7
 remote node, 3-12
creating scheduled tasks, 3-16
customizing connector, 3-1

D

defining
 IT resources, 2-7
 scheduled tasks, 3-16
deployment requirements, 2-1
determining version number of connector, 1-8

E

enabling logging, 2-4
encrypting password, 3-23
errors, 4-3

F

files and directories of the connector
 See connector files and directories
functionality supported, 1-4
functions available, 1-4

G

globalization features, 1-5

I

importing connector XML files, 2-6
input locale, changing, 2-3
issues, 5-1
IT resources
 defining, 2-7
 parameters, 2-7
 PSFT Base Server, 2-6

L

logging enabling, 2-4
lookup fields reconciliation, 1-1
lookup fields reconciliation scheduled task, 3-17

M

mapping between attributes of target system and
 Oracle Identity Manager, A-1
multilanguage support, 1-5

O

Oracle Identity Manager Administrative and User
 Console, 2-6, 3-16, 4-4
Oracle Identity Manager server, configuring, 2-3

P

parameters of IT resources, 2-7
password, encrypting, 3-23
problems, 4-3, 5-1
process tasks, 1-4
provisioning
 functions, 1-4
publishing message, 3-7

R

reconciliation
 functions, 1-4
 lookup fields, 1-1
 module, 1-1
 trusted source mode, 1-6, 2-2
 user, 1-2
reconciliation type
 bulk, 1-3
 change-based, 1-3
requirements for deploying, 2-1
running Application Engine program, 3-14

S

scheduled tasks
 defining, 3-16
 lookup fields reconciliation, 3-17
 user reconciliation, 3-18
securing message channel, 3-13
server cache, clearing, 2-3
Simple File Handler, 3-9
supported
 functionality, 1-4
 languages, 1-5
 releases of Oracle Identity Manager, 2-1
 target system host platforms, 2-1
 target systems, 2-1

T

target system, multiple installations, 3-28
target systems
 host platforms supported, 2-1
 supported, 2-1
testing, 4-1
testing provisioning, 4-2
testing reconciliation, 4-1

testing the connector, 4-1
testing utility, 4-1, 4-2
troubleshooting, 4-3
trusted source reconciliation, 1-6, 2-2

U

user attribute mappings, A-1
user reconciliation, 1-2
user reconciliation scheduled task, 3-18

V

version number of connector, determining, 1-8

X

XML files
 description, 1-6, 2-2
 for trusted source reconciliation, 1-6, 2-2
 importing, 2-6