Oracle® Receivables

Reference Guide Release 12.2

Part No. F10312-08

September 2024



Oracle Receivables Reference Guide, Release 12.2

Part No. F10312-08

Copyright © 1988, 2024, Oracle and/or its affiliates.

Primary Author: Mathew Daniel

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, MySQL, and NetSuite are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

Access to Oracle Support

Oracle customer access to and use of Oracle support services will be pursuant to the terms and conditions specified in their Oracle order for the applicable services.

Contents

Send Us Your Comments

Preface

T	Using Oracle Receivables APIS	
	Major Features	1-1
	Solution Outline	1-2
2	Adjustment API User Notes	
	Overview	2-1
	API Usage	2-1
	Ar_Adjust_pub.Create_Adjustment	2-4
	Ar_Adjust_pub.Approve_Adjustment	2-13
	Ar_Adjust_pub.Modify_Adjustment	2-18
	Ar_Adjust_pub.Reverse_Adjustment	2-24
	Ar_Adjust_pub.Create_Linelevel_Adjustment	2-26
	Messages	2-28
3	Credit Memo Approval and Creation API User Notes	
	Overview	3-1
	API Usage	3-2
	AR_CREDIT_MEMO_API_PUB.Create_Request	3-2
	AR_CREDIT_MEMO_API_PUB.Get_Request_Status	3-9
	AR_CM_API_PUB.Apply_On_Account	3-12
	AR_CM_API_PUB.Unapply_On_Account	3-12
	Messages	3-12

Credit Memo Application API User Notes	
Overview	4-1
API Usage	4-1
ar_cm_application_pub.activity_application	4-1
ar_cm_application_pub.activity_unapplication	4-10
Messages	4-14
Deposit API User Notes	
Overview	5-1
API Usage	5-1
AR_DEPOSIT_API_PUB.Create_deposit	5-2
AR_DEPOSIT_API_PUB.insert_non_rev_salescredit	5-27
Messages	5-32
Invoice Creation API User Notes	
Overview	6-1
API Usage	6-2
AR_INVOICE_API_PUB	6-2
Prepayments API User Notes	
Overview	7-1
API Usage	7-2
AR_PREPAYMENTS_PUB.Create_Prepayment	7-2
AR_PREPAYMENTS_PUB.Get_Installment	7-9
Messages	7-11
Receipt API User Notes	
Overview	8-1
API Usage	8-2
Ar_receipt_api_pub.Create_cash	
Ar_receipt_api_pub.Apply	8-20
Ar_receipt_api_pub.Create_and_apply	8-34
Ar_receipt_api_pub.Unapply	
Ar_receipt_api_pub.Apply_on_account	8-60
Ar_receipt_api_pub.Unapply_on_account	
Ar_receipt_api_pub.Reverse	8-69
Ar_receipt_api_pub.activity_application	8-74
Ar_receipt_api_pub.activity_unapplication	8-82
	Overview API Usage

	Ar_receipt_api_pub.Create_misc	8-86
	Ar_receipt_api_pub.apply_other_account	8-100
	Ar_receipt_api_pub.unapply_other_account	8-107
	Ar_receipt_api_pub.apply_open_receipt	8-111
	Ar_receipt_api_pub.unapply_open_receipt	8-118
	Ar_receipt_api_pub.Create_apply_on_acc	8-120
	Messages	8-136
9	Revenue Adjustment API User Notes	
	Overview	9-1
	API Usage	9-2
	AR_RevenueAdjust_PUB.Unearn_Revenue	9-2
	AR_RevenueAdjust_PUB.Earn_Revenue	9-16
	AR_RevenueAdjust_PUB.Transfer_Sales_Credits	9-18
	AR_RevenueAdjust_PUB.Add_Non_Revenue_Sales_Credits	9-23
	AR_Revenueadjust_PUB.Record_Customer_Acceptance	9-27
	AR_Revenueadjust_PUB.Update_Contingency_Expirations	9-28
	Messages	9-31
Α	Predefined Setup for Oracle Subledger Accounting	
	Data that Oracle Receivables Predefines for Oracle Subledger Accounting	A-1
В	Oracle Receivables Table and Column Descriptions	
	AutoInvoice Table and Column Descriptions	B-1
	Lockbox Table and Column Descriptions	
	Receipt and QuickCash Tables	B-62
	Lockbox Interface Table and Column Descriptions	
С	Seeded Match Rules	
	Seeded Search Match Rules	
	SAMPLE: BASIC SEARCH RULE	C-1
	SAMPLE: ADVANCED SEARCH RULE	C-4
D	XML Transactions	
	XML Receivables Documents Mapping	D-1
	XML Receivables Documents Mapping. Process Invoice XML Message Map	
		D-1

Index

Send Us Your Comments

Oracle Receivables Reference Guide, Release 12.2

Part No. F10312-08

Oracle welcomes customers' comments and suggestions on the quality and usefulness of this document. Your feedback is important, and helps us to best meet your needs as a user of our products. For example:

- Are the implementation steps correct and complete?
- Did you understand the context of the procedures?
- Did you find any errors in the information?
- Does the structure of the information help you with your tasks?
- Do you need different information or graphics? If so, where, and in what format?
- Are the examples correct? Do you need more examples?

If you find any errors or have any other suggestions for improvement, then please tell us your name, the name of the company who has licensed our products, the title and part number of the documentation and the chapter, section, and page number (if available).

Note: Before sending us your comments, you might like to check that you have the latest version of the document and if any concerns are already addressed. To do this, access the new Oracle E-Business Suite Release Online Documentation CD available on My Oracle Support and www.oracle.com. It contains the most current Documentation Library plus all documents revised or released recently.

Send your comments to us using the electronic mail address: appsdoc_us@oracle.com

Please give your name, address, electronic mail address, and telephone number (optional).

If you need assistance with Oracle software, then please contact your support representative or Oracle Support Services.

If you require training or instruction in using Oracle software, then please contact your Oracle local office and inquire about our Oracle University offerings. A list of Oracle offices is available on our Web site at www.oracle.com.

Preface

Intended Audience

Welcome to Release 12.2 of the Oracle Receivables Reference Guide.

This guide assumes you have a working knowledge of the following:

- The principles and customary practices of your business area.
- Computer desktop application usage and terminology

If you have never used Oracle E-Business Suite, we suggest you attend one or more of the Oracle E-Business Suite training classes available through Oracle University.

See Related Information Sources on page xii for more Oracle E-Business Suite product information.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

Access to Oracle Support

Oracle customer access to and use of Oracle support services will be pursuant to the terms and conditions specified in their Oracle order for the applicable services.

Structure

- 1 Using Oracle Receivables APIs
- 2 Adjustment API User Notes
- 3 Credit Memo Approval and Creation API User Notes
- 4 Credit Memo Application API User Notes

- 5 Deposit API User Notes
- 6 Invoice Creation API User Notes
- 7 Prepayments API User Notes
- 8 Receipt API User Notes
- 9 Revenue Adjustment API User Notes
- A Predefined Setup for Oracle Subledger Accounting
- **B** Oracle Receivables Table and Column Descriptions
- C Seeded Match Rules
- **D XML Transactions**

Related Information Sources

Integration Repository

The Oracle Integration Repository is a compilation of information about the service endpoints exposed by the Oracle E-Business Suite of applications. It provides a complete catalog of Oracle E-Business Suite's business service interfaces. The tool lets users easily discover and deploy the appropriate business service interface for integration with any system, application, or business partner.

The Oracle Integration Repository is shipped as part of the Oracle E-Business Suite. As your instance is patched, the repository is automatically updated with content appropriate for the precise revisions of interfaces in your environment.

Do Not Use Database Tools to Modify Oracle E-Business Suite Data

Oracle STRONGLY RECOMMENDS that you never use SQL*Plus, Oracle Data Browser, database triggers, or any other tool to modify Oracle E-Business Suite data unless otherwise instructed.

Oracle provides powerful tools you can use to create, store, change, retrieve, and maintain information in an Oracle database. But if you use Oracle tools such as SQL*Plus to modify Oracle E-Business Suite data, you risk destroying the integrity of your data and you lose the ability to audit changes to your data.

Because Oracle E-Business Suite tables are interrelated, any change you make using an Oracle E-Business Suite form can update many tables at once. But when you modify Oracle E-Business Suite data using anything other than Oracle E-Business Suite, you may change a row in one table without making corresponding changes in related tables. If your tables get out of synchronization with each other, you risk retrieving erroneous information and you risk unpredictable results throughout Oracle E-Business Suite.

When you use Oracle E-Business Suite to modify your data, Oracle E-Business Suite automatically checks that your changes are valid. Oracle E-Business Suite also keeps track of who changes information. If you enter information into database tables using database tools, you may store invalid information. You also lose the ability to track who has changed your information because SQL*Plus and other database tools do not keep a record of changes.

Using Oracle Receivables APIs

Major Features

Before you begin

Initialization of ARP_STANDARD and ARP_GLOBAL

Custom code that uses AR or HZ APIs will set the ORG_ID via dbms_application_info. set_client_info() and then call the APIs. The APIs in turn might access either ARP_STANDARD and ARP_GLOBAL, which initialize the global variables that are used across Oracle Receivables when the package is first called. Most of these global variable values are organization dependent, and the first such call sets the global variables based on the current ORG_ID.

If additional custom code then changes the ORG_ID via another call to dbms_application_info.set_client_info(), then the ORG context changes, but the ARP_STANDARD and ARP_GLOBAL context does not.

In such cases, you should explicitly re-initialize the global variables by a call to these two public procedures:

- ARP_GLOBAL.INIT_GLOBAL: For setting public variables in ARP_GLOBAL.
- ARP_STANDARD.INIT_STANDARD: For setting public variables in ARP_STANDARD.

Flexibility

Per Oracle API coding standards, the various Oracle Receivables APIs let you specify an ID or its associated value for any attribute that is an INPUT parameter of the API.

If both an ID and value have been specified, then the ID takes precedence over the value. This provides a wide degree of flexibility when using the API, both as a base table of the form and as a server-side routine call from the PL/SQL code.

The extensive defaulting mechanism for the input parameters ensures that you will be able to achieve your basic business needs by calling the relevant APIs with a minimum number of parameters. This gives you many options to achieve your requirements when you call the relevant API.

Modular Approach

The API has been designed in a highly modular fashion, resulting in code that is:

- Easy to understand
- Easy to maintain
- Easy to expand

Error Handling

Oracle Receivables APIs provide an extensive error-handling and error-reporting mechanism whereby all errors encountered in the Defaulting and Validation phases are reported and put on the message stack. The calling program can look up all error messages, or the first error message on the stack.

If only one error exists on the message stack, then you do not need to fetch the message from the stack because the message will return as one of the output parameters of the API routine.

Robust Validation

The validations that Oracle Receivables APIs perform are robust in nature. The APIs collect all encountered validation errors and put them on the message stack. The relevant entity handler is called only if no errors are reported during the Defaulting and Validation phases.

Debug Messages

Extensive debug messages have been incorporated to simplify the troubleshooting process when problems are encountered with any API.

Debug messages can be written to the log file by calling the appropriate routines described in Exception Handling and Result Messages, page 1-3.

Solution Outline

Modular Approach

To modularize an API, the basic structure of the API is divided into four parts:

- 1. Defaulting the IDs from the values and cross validating, if you provide both the values and the IDs.
- Defaulting all the entity level information, which you have not entered or which the API needs internally.
- Validating the entity level information that you entered.
- Calling to the entity handlers to perform the relevant task.

This results in code that is easy to understand and easy to maintain. Any new functionality can be added by a simple code plug-in at each of the four parts.

Defaulting

In general, the various parameters in each API call get defaulted, if not entered, based on the following:

- The values of the other parameters in the API call.
- The values set in the AR_SYSTEM_PARAMETERS table entered through the System Options form.
- The relevant profile option values.

Depending on the above three factors and the exact business requirement, the minimum number of parameters required to perform certain business tasks may vary.

Null values are defaulted for the parameters that could not be defaulted by the API defaulting routines.

For various attributes of the business objects, you can pass either the ID or the value of the attribute.

If you specify only the value, then the value is used to derive the ID; otherwise, the ID (if specified) is taken directly. If you specify both the ID and the value, then the ID takes precedence over the value and a warning message informs you of this.

Exception Handling and Result Messages

Each Oracle Receivables API returns three types of information to its calling programs:

- Overall status.
- Messages describing the operations performed or errors encountered by the APIs.
- Some output values that the API caller might want to use (this is different for different API routines and is described in each API's relevant chapter, in the API Usage section).

Return Status

The return status (x_return_status) of the API informs the caller about the result of the operation (or operations) performed by the API. The different possible values for an API return status are:

- Success (FND_API.G_RET_STS_SUCCESS)
- Error (FND_API.G_RET_STS_ERROR)
- Unexpected error (FND_API.G_RET_STS_UNEXP_ERROR)

The following section describes the different values of return status and their meanings:

Success

A success return status means that the API was able to perform all the operations requested by its caller. A success return status may be accompanied by informative messages in the API message list.

Error

An error return status means that the API failed to perform some or all of the operations requested by its caller. An error return status is usually accompanied by messages describing the error (or errors) and how to fix it.

In most cases, you should be able to take corrective action to fix regular, expected errors such as missing attributes or invalid date ranges.

Unexpected error

An unexpected error status means that the API has encountered an error condition it did not expect or could not handle. In this case, the API is unable to continue with its regular processing. Examples of such errors are irrecoverable data inconsistency errors, memory errors, and programming errors (such as attempting a division by zero).

In most cases, only system administrators or application developers can fix these unexpected errors.

Messages

The APIs put result messages into a message list. Programs calling the APIs can then get the messages from the list and process them by issuing them, loading them into a database table, or writing them to a log file.

Messages are stored in an encoded format to let the API callers find message names using the standard functions provided by the message dictionary. It also allows the storing of these messages in database tables and reporting off these tables in different languages.

The API message list must be initialized every time a program calls an API. API callers can either call the message list utility function FND MSG PUB.Initialize or request that the API do the initialization on their behalf by setting the p_init_msg_list parameter to

TRUE.

The program calling the API can retrieve messages from the message stack using the existing FND API functions FND_MSG_PUB.Count_Msg and FND_MSG_PUB.Get.

Message Level Threshold

The message level threshold is stored in a profile option named FND_API_MSG_LEVEL_THRESHOLD. This profile option can be updated at all levels (site, application, or user). The API checks against this threshold before writing a message to the API message list.

Debug Messages

You must enable debugging by calling the routine arp_standard.enable_file_debug. The routine requires 2 parameters: path_name and file_name.

```
arp_standard.enable_file_debug(<pathname>, <filename>)
```

The path name can be identified by using the following select statement:

```
select value from v$parameter where name = 'utl_file_dir',
```

See: My Oracle Support Knowledge Document 2525754.1, Using UTL_FILE_DIR or Database Directories for PL/SQL File I/O in Oracle E-Business Suite Releases 12.1 and 12.2.

The file name can be any name that you choose.

Example

```
arp_standard.enable_file_debug ('/sqlcom/log','txt.log')
```

This call would write the output debug file 'txt.log' in the path '/sqlcom/log'.

Calling Program Context

The program calling these APIs should have set up the application, responsibility, and user in the context of Oracle Application.

If the calling program does not set up this context, then it can be programmed by calling the following FND API.

```
fnd_global.apps_initialize
(user_id in number,
resp_id in number,
resp_appl_id in number,
security_group_id in number default 0);
```

Adjustment API User Notes

Overview

This document outlines the use of the Adjustment API. This API allows users to create, approve, update, and reverse adjustments for invoices using simple calls to PL/SQL functions.

The Adjustment API is not intended to replace the existing Adjustment form, Adjustment Approval form, or the batch Auto-Adjust program.

> Note: The Adjustment API requires the following receivable activity setup: the GL Account Source must be Activity.

You can access the API in two ways:

- With standard PL/SQL servers-side routine calls.
- Through Forms to have a procedure as its underlying base table.

API Usage

To create, modify, approve, or reverse adjustments, use the following routines:

- Ar_Adjust_pub.Create_Adjustment, page 2-4: Use this routine to create an adjustment for an invoice.
- Ar_Adjust_pub.Create_Linelevel_Adjustment, page 2-26: Use this routine to create an adjustment for an invoice/debit memo at line level.
 - Line level adjustments result in distributions being created only for the invoice line being adjusted. Such distributions are not

prorated across all invoice lines but are applicable only to the specified invoice line using the remaining balances of the invoice line.

- This routine creates the adjustment at the line level, and maintains the line level balances of the transactions.
- This routine is restricted to do line level adjustment for adjustment type – LINE. The tax amount is prorated based on the receivable activity tax code source passed for the line adjustment.
- Tax, freight and charges adjustments can only be done at the header level of the invoice. Use the standard Create Adjustment API to create tax, freight and charges adjustments applicable to the invoice header.
- You cannot modify the line level adjustment using modify routine in the API. However, you can use the Reverse Adjustment routine to reverse an existing adjustment by passing the applicable adjustment identifier.
- Receivables does not support line level adjustment functionality for invoices with installments. You can make adjustments against an invoice with multiple installments only at the invoice header level.
- You cannot create line level adjustments against Invoices or debit memos that were created prior to Release 12 and have activity against them.
- Ar_Adjust_pub.Modify_Adjustment, page 2-18: Use this routine to modify an adjustment's status, comments, and reason code.

Note: If the existing status of the adjustment is A or R, then it cannot be modified.

- Ar_Adjust_pub.Approve_Adjustment, page 2-13: Use this routine to approve an adjustment.
- Ar_Adjust_pub.Reverse_Adjustment, page 2-24: Use this routine to reverse an adjustment at either header or line level.

The Adjustment API has a defaulting mechanism for input parameters. This lets you

create, approve, update, and reverse adjustments while passing a minimal number of API parameters.

Note: You can pass an adjustment account and override the default account (derived from the adjustment's receivable activity), provided that:

- The GL account source on the adjustment's receivable activity is *Activity* and the tax code source is *None*.
- The AR: Override Adjustment Activity Account Option profile option is set to Yes.

The following table shows standard API parameters that are common to all routines in the Adjustment API:

Parameter	Typ e	Data-type	Require d	Default Value	Description
p_api_version	IN	NUMBER	Yes		Used to compare version numbers of incoming calls to its current version number.
p_init_msg_list	IN	VARCHAR2		FND_API.G_FALSE	Allows API callers to request that the API does initialization of the message list on their behalf.
p_commit	IN	VARCHAR2		FND_API.G_FALSE	Used by API callers to ask the API to commit on their behalf.
p_validation_level	IN	NUMBER		FND_API. G_VALID_LEVEL_F ULL	Not currently for use by the user. Allow this parameter to default.
p_return_status	OUT	VARCHAR2			Represents the API overall return status. For possible values, see Error Handling, page 1-2.
p_msg_count	OUT	NUMBER			Number of messages in the API message list

Parameter	Typ e	Data-type	Require d	Default Value	Description
p_msg_data	OUT	VARCHAR2			This is the message in encoded format if p_msg_count=1

Ar_Adjust_pub.Create_Adjustment

Use this routine to create adjustments to invoices. The API returns the Out parameter p_new_adjust_id, which represents the newly-created adjustment ID. The following is a breakdown of parameters for this routine, divided according to parameter type:

Input Parameters

Standard API parameters: 4

Create Adjustment parameters: 6 required parameters (might vary depending on the adjustment type)

Output Parameters

Standard API parameters: 3

Create Adjustment parameters: 2

Since the Create Adjustment API allows users to pass the adjustment record type to the procedure, it is not recommended that users enter values for unnecessary fields. These fields could be populated for internal use only.

Parameter Descriptions

The following table lists parameters that pertain specifically to the Create Adjustment routine:

Parameter	Туре	Data-type	Required	Default Value	Description
p_adj_rec.type	IN	VARCHAR 2	Yes		The type of adjustment to be created. Possible Values: 'INVOICE', 'LINE', 'TAX', 'FREIGHT', 'CHARGES', 'FINCHRG'
p_adj_rec. payment_schedu le_id	IN	NUMBER	Yes		Payment Schedule ID of the transaction for which the transaction is to be created.

Parameter	Туре	Data-type	Required	Default Value	Description
p_adj_rec. amount	IN	NUMBER	Yes/No		If the adjustment type is any other value than 'INVOICE' then this is a required field. The amount indicates the amount to be adjusted.
p_adj_rec. customer_trx_lin e_id	IN	NUMBER	Yes/No		If the adjustment type is 'LINE' then the customer_trx_line_id indicates the line to be adjusted. For all the other adjustment types the value is not required.
p_adj_rec. receivables_trx_i d	IN	NUMBER	Yes		The ID of the activity name (from ar_receivables_trx) should be passed.
p_adj_rec. code_combinatio n_id	IN	NUMBER	No		The code combination ID is not required. If the value is not passed, then the default is the code combination id specified in the receivables_trx_id record. If the value passed is not the same as the code_combination_id and the AR: Override Adjustment Activity Account Option profile option is set to No, then this would error out.
p_adj_rec. apply_date	IN	DATE	Yes		The apply date should be equal to or greater than the transaction date.
p_adj_rec. gl_date	IN	DATE	Yes		The GL date should be equal to or greater than the transaction GL date, and the date should be from the open/future period.
p_adj_rec. reason_code	IN	VARCHAR 2	No		The reason code should a valid reason code in ar_lookups with lookup_type = 'ADJUST_REASON'.
p_adj_rec. comments	IN	VARCHAR 2	No		The user can enter comments, up to 2000 bytes, for creating the adjustments which could be useful for the user, for future reference.

Parameter	Туре	Data-type	Required	Default Value	Description
p_adj_rec. associated_cash_ receipt_id	IN	NUMBER	No		The associated cash receipt ID is the ID of a valid cash receipt, and is to be associated with the adjustment.
p_adj_rec. ussgl_transactio n_code	IN	VARCHAR 2	No		The USSGL transaction code should be a valid USSGL transaction code in gl_ussgl_transaction_codes.
p_adj_rec. created_from	IN	VARCHAR 2	Yes		Some value that indicates to the user that it was created through the Adjustment API such as "ADJ-API."
p_adj_rec. attribute_categor y, p_adj_rec. attribute1 - p_adj_rec. attribute15	IN	VARCHAR 2	No		This attribute_category and the attribute1 through attribute15 can be entered if the user want to enter the details of the descriptive flexfield for the adjustment.
p_adj_rec. adjustment_id	IN		No. Entered values will be overwritte n.		
p_adj_rec. acctd_amount	IN		No. Entered values will be overwritte n.		
p_adj_rec. gl_posted_date	IN		No. Entered values will be overwritte n.		

Parameter	Туре	Data-type	Required	Default Value	Description
p_adj_rec. set_of_books_id	IN		No. Entered values will be overwritte n.		
p_adj_rec. adjustment_type	IN		No. Entered values will be overwritte n.		
p_adj_rec.status	IN		No. Entered values will be overwritte n.		
p_adj_rec. line_adjusted	IN		No. Entered values will be overwritte n.		
p_adj_rec. freight_adjusted	IN		No. Entered values will be overwritte n.		
p_adj_rec. tax_adjusted	IN		No. Entered values will be overwritte n.		

Parameter	Туре	Data-type	Required	Default Value	Description
p_adj_rec. receivables_char ges_adjusted	IN		No. Entered values will be overwritte n.		
p_adj_rec. batch_id	IN		No. Entered values will be overwritte n.		
p_adj_rec. customer_trx_id	IN		No. Entered values will be overwritte n.		
p_adj_rec. subsequent_trx_i d	IN		No. Entered values will be overwritte n.		
p_adj_rec. chargeback_cust omer_trx_id	IN		No. Entered values will be overwritte n.		
p_adj_rec. distribution_set_ id	IN		No. Entered values will be overwritte n.		

Parameter	Туре	Data-type	Required	Default Value	Description
p_adj_rec. associated_appli cation_id	IN		No. Entered values will be overwritte n.		
p_adj_rec. automatically_ge nerated	IN		No. Entered values will be overwritte n.		
p_adj_rec. postable	IN		No. Entered values will be overwritte n.		
p_adj_rec. approved_by	IN		No. Entered values will be overwritte n.		
p_adj_rec. adjustment_num ber	IN		No. Entered values will be overwritte n.		
p_adj_rec. doc_sequence_v alue	IN		No. Entered values will be overwritte n.		

Parameter	Туре	Data-type	Required	Default Value	Description
p_adj_rec. doc_sequence_id	IN		No. Entered values will be overwritte n.		
p_adj_rec. posting_control_ id	IN		No. Entered values will be overwritte n.		
p_adj_rec. last_updated_by	IN		No. Entered values will be overwritte n.		
p_adj_rec. last_updated_da te	IN		No. Entered values will be overwritte n.		
p_adj_rec. last_updated_log in	IN		No. Entered values will be overwritte n.		
p_adj_rec. created_by	IN		No. Entered values will be overwritte n.		

Parameter	Туре	Data-type	Required	Default Value	Description
p_adj_rec. creation_date	IN		No. Entered values will be overwritte n.		
p_adj_rec. program_applica tion_id	IN		No. Entered values will be overwritte n.		
p_adj_rec. program_id	IN		No. Entered values will be overwritte n.		
p_adj_rec. program_update _date	IN		No. Entered values will be overwritte n.		
p_adj_rec. request_id	IN		No.		
p_chk_approval _limits	IN	VARCHAR 2	No.	FND_API. G_TRUE	This value can be set to 'F' if the adjusted amount should not be validated against the users approval limit.
p_move_deferre d_tax	IN	VARCHAR 2	No.	Y	This parameter is only used for BR.
p_check_amount	IN	VARCHAR 2	No.	FND_API. G_TRUE	This value should never be set to 'F'. It is used for some internal logic.

Parameter	Туре	Data-type	Required	Default Value	Description
p_new_adjust_n umber	OUT	ar_adjustm ent. adjustment _number% type			If the adjustment is created successfully, then this parameter will contain the value of the new adjustment number.
p_new_adjust_id	OUT	ar_adjustm ent. adjustment _id%type			If the adjustment is created successfully, then this parameter will contain the value of the new adjustment id.
p_called_from	IN	VARCHAR 2	No	NULL	This flag is only used for BR.

Note: If the user passes values for any parameter not reported in the table above, then those values will be ignored and will not show up in the record.

Default values for API parameters derive from the following:

- Values of the other parameters in the API call
- Values set in the ar_system_parameters table entered through the System Options form
- Relevant profile option values

Depending on the user's particular business needs, the minimum number of parameters required to create an adjustment may vary.

Validation of the parameters passed

All the parameters that are passed to the API are validated, and if any of the required fields are missing or invalid, then the API returns an error message. A list of possible error messages appears in Messages, page 2-28.

Example

The following is the simplest test case for creating an adjustment.

Objective:

To create an adjustment, passing the minimum number of parameters.

Entered parameters:

```
p_adj_rec.type = 'INVOICE',
p_adj_rec.payment_schedule_id = 22222,
p_adj_rec.receivables_trx = 15,
p_adj_rec.apply_date = to_date('12-FEB-00', 'DD-MON-RR'),
p_adj_rec.gl_date = to_date('12-FEB-00', 'DD-MON-RR'),
p_adj_rec.created_from = 'ADJ-API'
```

Call to the API:

```
AR_ADJUST_PUB.Create_Adjustment
(p_api_name => 'AR_ADJUST_PUB',
p_api_version => 1.0,
p_msg_count => msg_count,
p_msg_data => msg_data,
p_return_status => return_status,
p_adj_rec => adj_rec,
p_new_adjust_number => new_adj_num,
p_new_adjust_id => new_adj_id );
```

Result:

Creates an adjustment, passing two standard required parameters and six adjustment record related parameters.

Ar_Adjust_pub.Approve_Adjustment

Use this routine to approve an adjustment. The following is a breakdown of parameters for this routine, divided according to parameter type:

Input Parameters

Standard API parameters: 4

Approve Adjustment parameters: 1 required parameter

Output Parameters

Standard API parameters: 3

Parameter Descriptions

Although the Approve Adjustments API allows users to pass the adjustment record type to the procedure, all the values are overwritten by the values in the existing adjustment record except for the status and gl_date.

The following table shows parameters that pertain specifically to the Approve Adjustment routine.

> Note: If required parameters are not passed in a call to this API, then the call will fail. If values are not required, then the values for those

fields will be copied from the existing values of the adjustment.

Parameter	Туре	Data-type	Require d	Default Value	Description
p_old_adjust_id	IN	NUMBER	Yes		The id of the adjustment that needs to be approved.
p_adj_rec.type	IN	VARCHAR2	No		
p_adj_rec. payment_schedu le_id	IN	NUMBER	No		
p_adj_rec. amount	IN	NUMBER	No		
p_adj_rec. customer_trx_lin e_id	IN	NUMBER	No		
p_adj_rec. receivables_trx_i d	IN	NUMBER	No		
p_adj_rec. code_combinatio n_id	IN	NUMBER	No		
p_adj_rec. apply_date	IN	DATE	No		
p_adj_rec. gl_date	IN	DATE	No	GL date of adjustment	The GL date should be entered if it is going to be different from the one in the old adjustment.
p_adj_rec. reason_code	IN	VARCHAR2	No		
p_adj_rec. comments	IN	VARCHAR2	No		

Parameter	Туре	Data-type	Require d	Default Value	Description
p_adj_rec. associated_cash_ receipt_id	IN	NUMBER	No		
p_adj_rec. ussgl_transactio n_code	IN	VARCHAR2	No		
p_adj_rec. created_from	IN	VARCHAR2	No		
p_adj_rec. attribute_categor y, p_adj_rec. attribute1 - p_adj_rec. attribute15	IN	VARCHAR2	No		
p_adj_rec. adjustment_id	IN		No		
p_adj_rec. acctd_amount	IN		No		
p_adj_rec. gl_posted_date	IN		No		
p_adj_rec. set_of_books_id	IN		No		
p_adj_rec. adjustment_type	IN		No		
p_adj_rec.status	IN		No	'A' if the status is null.	Possible Value: 'A' which indicates Approval
p_adj_rec. line_adjusted	IN		No		
p_adj_rec. freight_adjusted	IN		No		

Parameter	Туре	Data-type	Require d	Default Value	Description
p_adj_rec. tax_adjusted	IN		No		
p_adj_rec. receivables_chag es_adjusted	IN		No		
p_adj_rec. batch_id	IN		No		
p_adj_rec. customer_trx_id	IN		No		
p_adj_rec. subsequent_trx_i d	IN		No		
p_adj_rec. chargeback_cust omer_trx_id	IN		No		
p_adj_rec. distribution_set_ id	IN		No		
p_adj_rec. associated_appli cation_id	IN		No		
p_adj_rec. automatically_ge nerated	IN		No		
p_adj_rec. postable	IN		No		
p_adj_rec. approved_by	IN		No		
p_adj_rec. adjustment_num ber	IN		No		

Parameter	Туре	Data-type	Require d	Default Value	Description
p_adj_rec. doc_sequence_v alue	IN		No		
p_adj_rec. doc_sequence_id	IN		No		
p_adj_rec. posting_control_ id	IN		No		
p_adj_rec. last_updated_by	IN		No		
p_adj_rec. last_updated_da te	IN		No		
p_adj_rec. last_updated_log in	IN		No		
p_adj_rec. created_by	IN		No		
p_adj_rec. creation_date	IN		No		
p_adj_rec. program_applica tion_id	IN		No		
p_adj_rec. program_id	IN		No		
p_adj_rec. program_update _date	IN		No		
p_adj_rec. request_id	IN		No		

Parameter	Туре	Data-type	Require d	Default Value	Description
p_chk_approval _limits	IN	VARCHAR2	No	FND_API. G_TRUE	This value can be set to 'F' if the adjusted amount should not be validated against the users approval limit.
p_move_deferre d_tax	IN	VARCHAR2	No	Y	This flag is used only for Bills Receivable.

Validation of the parameters passed

All the parameters that are passed to the API are validated, and if any required fields are missing or invalid, then the API returns an error message. A list of possible error messages appears in Messages, page 2-28.

Example

The following is the simplest test case for approving an adjustment.

Objective:

To approve an adjustment, passing the minimum number of parameters.

Entered parameters:

adjustment_id = 88888;

Call to the API:

```
AR_ADJUST_PUB.Approve_Adjustment
(p_api_name => 'AR_ADJUST_PUB',
p_api_version => 1.0,
p_msg_count => msg_count,
p_msq_data => msq_data,
p_return_status => return_status,
p_old_adjust_id => adjustment_id );
```

Approves an adjustment, passing 2 standard required parameters and 1 adjustment record parameter.

Ar_Adjust_pub.Modify_Adjustment

Use this routine to update an adjustment. The attributes that can be modified are comments, gl date, and status. If the status of the adjustment is already 'A' (the adjustment has already been approved), then you cannot update the adjustment. The following is a breakdown of parameters for this routine, divided according to parameter type:

Input Parameters

Standard API parameters: 4

Modify Adjustment parameters: 1 required parameter

Output Parameters

Standard API parameters: 3

Parameter Descriptions

Although the Modify Adjustments API allows users to pass the adjustment record type to the procedure, all the values are overwritten by the existing adjustment record except for the status, comments, and gl_date.

The following table shows parameters that pertain specifically to the Modify Adjustments routine.

> **Note:** If required parameters are not passed in a call to this API, then the call will fail. If values are not required, then the values for those fields will be copied from the existing values of the adjustment.

Parameter	Туре	Data-type	Required	Default Value	Description
p_old_adjust_id	IN	NUMBER	Yes		The id of the adjustment that needs to be modified.
P_adj_rec.type	IN	VARCHAR2	No		
p_adj_rec. payment_schedule_ id	IN	NUMBER	No		
p_adj_rec.amount	IN	NUMBER	No		
p_adj_rec. customer_trx_line_i d	IN	NUMBER	No		
p_adj_rec. receivables_trx_id	IN	NUMBER	No		

Parameter	Туре	Data-type	Required	Default Value	Description
p_adj_rec. code_combination_i d	IN	NUMBER	No		
p_adj_rec. apply_date	IN	DATE	No		
p_adj_rec.gl_date	IN	DATE	No	GL date of adjustment	The GL date should be entered if the user wishes to modify the existing gl date of the adjustment.
P_adj_rec. reason_code	IN	VARCHAR2	No		
p_adj_rec. comments	IN	VARCHAR2	No		The comments should be entered if the user wishes to modify the existing comments of the adjustment.
P_adj_rec. associated_cash_rec eipt_id	IN	NUMBER	No		
p_adj_rec. ussgl_transaction_c ode	IN	VARCHAR2	No		
p_adj_rec. created_from	IN	VARCHAR2	No		
p_adj_rec. attribute_category, p_adj_rec.attribute1 - p_adj_rec. attribute15	IN	VARCHAR2	No		
p_adj_rec. adjustment_id	IN		No		
p_adj_rec. acctd_amount	IN		No		

Parameter	Туре	Data-type	Required	Default Value	Description
p_adj_rec. gl_posted_date	IN		No		
p_adj_rec. set_of_books_id	IN		No		
p_adj_rec. adjustment_type	IN		No		
p_adj_rec.status	IN		No		The status should be entered if the user wishes to change the existing status of the adjustment. Possible Value: 'A', 'R', 'M', 'W'.
p_adj_rec. line_adjusted	IN		No		
p_adj_rec. freight_adjusted	IN		No		
p_adj_rec. tax_adjusted	IN		No		
p_adj_rec. receivables_chages_ adjusted	IN		No		
p_adj_rec.batch_id	IN		No		
p_adj_rec. customer_trx_id	IN		No		
p_adj_rec. subsequent_trx_id	IN		No		
p_adj_rec. chargeback_custom er_trx_id	IN		No		
p_adj_rec. distribution_set_id	IN		No		

Parameter	Туре	Data-type	Required	Default Value	Description
p_adj_rec. associated_applicati on_id	IN		No		
p_adj_rec. automatically_gene rated	IN		No		
p_adj_rec.postable	IN		No		
p_adj_rec. approved_by	IN		No		
p_adj_rec. adjustment_number	IN		No		
p_adj_rec. doc_sequence_valu e	IN		No		
p_adj_rec. doc_sequence_id	IN		No		
p_adj_rec. posting_control_id	IN		No		
p_adj_rec. last_updated_by	IN		No		
p_adj_rec. last_updated_date	IN		No		
p_adj_rec. last_updated_login	IN		No		
p_adj_rec. created_by	IN		No		
p_adj_rec. creation_date	IN		No		

Parameter	Туре	Data-type	Required	Default Value	Description
p_adj_rec. program_applicatio n_id	IN		No		
p_adj_rec. program_id	IN		No		
p_adj_rec. program_update_d ate	IN		No		
p_adj_rec. request_id	IN		No		
p_chk_approval_li mits	IN	VARCHAR2	No	FND_API. G_TRUE	This value can be set to 'F' if the adjusted amount should not be validated against the users approval limit.
p_move_deferred_t ax	IN	VARCHAR2	No	Y	This flag is only used for Y.

Validations of the parameters passed

All the parameters that are passed to the API are validated, and if any of the required fields are missing or invalid, then the API returns an error message. A list of possible error messages appears in Messages, page 2-28.

Example

The following is the simplest test case for updating an adjustment.

Objective:

To update an adjustment, passing the minimum number of parameters. For this example, assume the user wants to update comments.

Entered parameters:

old_adjustment_id = 88888

adj_rec.comments = 'This is the new comment'

Call to the API:

```
AR_ADJUST_PUB.Create_Adjustment
(p_api_name = 'AR_ADJUST_PUB',
p_{api_version} => 1.0,
p_msg_count => msg_count,
p_msg_data => msg_data,
p_return_status => return_status,
p_adj_rec => adj_rec,
p_old_adjust_id => old_adjustment_id );
```

Updates an adjustment, passing two standard required parameters and one adjustment record parameter. Users should also pass values for other parameters that the user wishes to update in the adjustment record.

Ar_Adjust_pub.Reverse_Adjustment

Use this routine to reverse an adjustment. The following is a breakdown of parameters for this routine, divided according to parameter type:

Input Parameters

Standard API parameters: 4

Reverse Adjustment parameters: 1 required parameter

Output Parameters

Standard API parameters: 3

Reverse Adjustment parameters: 1

Parameter Descriptions

The following table shows parameters that pertain specifically to the Reverse Adjustment routine:

Parameter	Туре	Data-type	Required	Default Value	Description
p_old_adjust_id	IN	NUMBER	Yes		The id of the adjustment that needs to be modified.
p_comments	IN	VARCHAR 2	No		The user can specify any comments that should appear in the reverse adjustment.
p_reversal_gl_da te	IN	DATE	No	Old adjustments gl date	The user can enter a gl date if he wishes it to be different from the old adjustments gl date.

Parameter	Туре	Data-type	Required	Default Value	Description
p_reversal_date	IN	DATE	No	Old adjustments date	The user can enter a date if he wishes it to be different from the old adjustments date.
p_new_adj_id	OUT	NUMBER			
p_chk_approval _limits	IN	VARCHAR 2	No	FND_API. G_TRUE	This value can be set to 'F' if the adjusted amount should not be validated against the users approval limit.
p_move_deferre d_tax	IN	VARCHAR 2	No	Y	This flag is used only for Bills Receivable.
p_called_from	IN	VARCHAR 2	No	NULL	This flag is used only for Bills Receivable.

Validation of the parameters passed

All the parameters that are passed to the API are validated, and if any of the required fields are missing or invalid, then the API returns an error message. A list of possible error messages appears in Messages, page 2-28.

Example

The following is the simplest test case for reversing an adjustment.

Objective:

To reverse an adjustment, passing the minimum number of parameters.

Entered parameters:

old_adjustment_id = 88888

Call to the API:

```
AR_ADJUST_PUB.Reverse_Adjustment(
           p_api_name => 'AR_ADJUST_PUB',
p_api_version => 1.0,
p_msg_count => msg_count,
p_msg_data => msg_data,
p_return_status => return_status,
p_old_adjust_id => old_adjustment_id
p_new_adj_id => new_adjustment_id);
```

Result:

Reverses an adjustment, passing two standard required parameters and one adjustment

record parameter.

Ar_Adjust_pub.Create_Linelevel_Adjustment

Use this routine to create adjustments to invoices at line level. This routine uses some parameters that are specific to this routine, and all the Standard API and other input and output parameters used by the Create_Adjustment routine described in Ar_Adjust_pub.Create_Adjustment, page 2-4.

Parameter Descriptions

The following table lists parameters that pertain specifically to the Create_Linelevel_Adjustment routine:

Parameter	Туре	Data-type	Required	Default Value	Description
p_llca_adj_trx_li nes_tbl. customer_trx_lin e_id	IN	NUMBER	Yes		Customer_trx_line_id indicates the line to be adjusted.
p_llca_adj_trx_li nes_tbl. receivable_trx_id	IN	NUMBER	Yes		The ID of the activity name (from ar_receivables_trx) should be passed.
p_llca_adj_trx_li nes_tbl. line_amount	IN	NUMBER	Yes		The amount indicates the amount to be adjusted (Including Tax amount).
p_llca_adj_create _tbl_type. adjustme_numbe r	OUT	NUMBER			If the adjustment is created successfully, then this parameter contains the value of the new adjustment number.
p_llca_adj_create _tbl_type. adjustment_id	OUT	NUMBER			If the adjustment is created successfully, then this parameter contains the value of the new adjustment_id.
p_llca_adj_create _tbl_type. customer_trx_lin e_id	OUT	NUMBER			If the adjustment is created successfully, then this parameter contains the value of the corresponding customer trx_line_id.

Note: You should populate the line level details on p_llca_adj_trx_lines_tbl for particular transactions, so that the system creates an adjustment for each line on p_llca_adj_trx_lines_tbl . You can retrieve the created adjustment details by using p_llca_adj_create_tbl_type as an out parameter.

The adjustment amount, receivable trx id, customer trx line id are not required at the Header Level. The routine ignores these parameters and gives precedence to the p_llca_adj_trx_lines_tbl input parameters.

Validation of the parameters passed

All the parameters that are passed to the API are validated, and if any of the required fields are missing or invalid, then the API returns an error message. A list of possible error messages appears in Messages, page 2-28.

The API populates all error messages in the global temporary table ar_llca_adj_trx_errors_gt. Programs calling the API can then get the messages from this table and process them by issuing them, loading them into a database table, or writing them to a log file.

You need to check if a record exist in error table. If no records exist for a customer trx id and customer trx line id, only then adjustment are created for a line against the transaction.

Example

The following is the simplest test case for creating an adjustment at the line level.

Objective:

To create an adjustment at line level, passing the minimum number of parameters.

Entered parameters:

```
p_adj_rec.type = 'LINE',
p_adj_rec.payment_schedule_id = 220175,,
p_adj_rec.receivables_trx = 684090,
p_adj_rec.apply_date = to_date('10-FEB-2008', 'DD-MON-YYYY'),
p_adj_rec.gl_date = to_date('10-FEB-2008', 'DD-MON-YYYY'),
p_adj_rec.created_from = 'ADJ-API'
p_llca_adj_trx_lines_tbl(1).customer_trx_line_id := 1228207;
p_llca_adj_trx_lines_tbl(1).line_amount := -10;
p_llca_adj_trx_lines_tbl(1).receivables_trx_id := 1280;
p_llca_adj_trx_lines_tbl(2).customer_trx_line_id := 1228208;
```

```
p_llca_adj_trx_lines_tbl(2).line_amount := -20;
p_llca_adj_trx_lines_tbl(2).receivables_trx_id := 3095;
```

Call to the API:

```
AR_ADJUST_PUB.Create_Linelevel_Adjustment(
    p_llca_adj_create_tbl_type => p_llca_adj_create_tbl_type,
p_called_from => p_adj_rec.created_from,
old_adjust_id => NULL);
  p_old_adjust_id
```

Note: The p move deferred tax => 'Y' flag is used only for bills receivables.

Result:

```
Creates an adjustment for each line; and the output parameter
p_llca_adj_create_tbl_type contains the adjustment information as described below:
p_llca_adj_create_tbl_type.customer_trx_line_id(1) = 1228207
p_llca_adj_create_tbl_type.adjustment_number(1) = 6032
p_llca_adj_create_tbl_type.adjustment_id(1) = 22012
p_llca_adj_create_tbl_type.customer_trx_line_id(2)= 1228208
p_llca_adj_create_tbl_type.adjustment_number(2) = 6033
p_llca_adj_create_tbl_type.adjustment_id(2) = 22013
```

Messages

The following table describes the possible messages returned by the Adjustment API.

Message Number	Message Name	Message Description	Additional Comments
42963	AR_AAPI_ADJ_AMOU NT_ZERO	No Adjustment amount passed.	
42964	AR_AAPI_ADR_ZERO_ INV	Cannot adjust, because the amount due in the Payment Schedule is zero, and the type specified is INVOICE.	

Message Number	Message Name	Message Description	Additional Comments
42965	AR_AAPI_APPLYDAT E_LT_TRXDATE	The Apply date &APPLY_DATE is earlier than the transaction date &TRX_DATE.	
42966	AR_AAPI_DOC_SEQ_ NOT_REQD	The specified document sequence: &DOCUMENT_SEQ is not required as the Unique Sequence Number profile option does not allow it.	
42967	AR_AAPI_GLDATE_IN VALID_PERIOD	The GL date: &GL_DATE is not in an open or future enterable period.	
42968	AR_AAPI_GLDATE_LT _APPLYDATE	The GL date &GL_DATE is earlier than the apply date &APPLY_DATE.	
42969	AR_AAPI_GLDATE_LT _TRXGLDATE	The Adjustment GL date &GL_DATE is earlier than the transaction GL date &TRX_GL_DATE.	
42970	AR_AAPI_INVALID_A DJ_ID	Invalid adjustment ID: &ADJUSTMENT_ID specified.	
42971	AR_AAPI_INVALID_C CID	Invalid code combination ID: &CCID	
42972	AR_AAPI_INVALID_C REATE_STATUS	Invalid status: &STATUS passed during creation of Adjustment	
42973	AR_AAPI_INVALID_D ESC_FLEX	Invalid Descriptive Flexfield has been provided.	
42974	AR_AAPI_INVALID_P AYSCHD	Invalid Payment Schedule ID: &PAYMENT_SCHEDULE_ID	
42975	AR_AAPI_INVALID_R CVABLE_TRX_ID	Invalid receivables trx ID: &RECEIVABLES_TRX_ID	
42976	AR_AAPI_INVALID_R EASON_CODE	The reason code &REASON_CODE is invalid.	

Message Number	Message Name	Message Description	Additional Comments
42977	AR_AAPI_INVALID_R ECEIPT_ID	Invalid Associated Cash Receipt ID &ASSOCIATED_CASH_RECEIPT_ID has been specified.	
42978	AR_AAPI_INVALID_T RX_CLASS	Adjustment not allowed for transactions of class: &CLASS	
42979	AR_AAPI_INVALID_T YPE	Invalid type of adjustment: &TYPE	
42980	AR_AAPI_INVALID_U SSGL_CODE	Invalid USSGL Transaction Code &USSGL_CODE has been specified	
42981	AR_AAPI_LINE_ID_FO R_NONLINE	Customer trx line ID: &CUSTOMER_TRX_LINE_ID passed for type = &TYPE	
42982	AR_AAPI_NO_APPLY_ DATE	Apply date has not been specified	
42983	AR_AAPI_NO_APPRO VAL_CODES	No valid approval codes exists for Adjustments in the Lookup table	
42984	AR_AAPI_NO_CCID	No valid code combinations exist for Adjustment	
42985	AR_AAPI_NO_CCID_F OR_ACTIVITY	No code combination id exists for receivables trx ID: &RECEIVABLES_TRX_ID and no code combination has been specified	
42986	AR_AAPI_NO_CHAN GE_OR_REVERSE	No changes allowed for Adjustment with &STATUS status	
42987	AR_AAPI_NO_CREAT ED_FROM	No values specified for the Created From attribute of the adjustment	
42988	AR_AAPI_NO_CUSTO MER_ID	No customer ID exists for payment schedule ID: &PAYMENT_SCHEDULE_ID	

Message Number	Message Name	Message Description	Additional Comments
42989	AR_AAPI_NO_CUSTO MER_TRX_ID	No customer trx id exists for payment schedule ID: &PAYMENT_SCHEDULE_ID	
42990	AR_AAPI_NO_CUSTO MER_TRX_LINEID	Invalid customer trx line id: &CUSTOMER_TRX_LINE_ID passed for customer trx id: &CUSTOMER_TRX_ID	
42991	AR_AAPI_NO_GL_DA TE	GL date has not been specified	
42992	AR_AAPI_NO_OPEN_ FUTURE_PERIOD	No valid open or future enterable GL periods exist for the ledger ID &SET_OF_BOOKS_ID	
42993	AR_AAPI_NO_REASO N_CODES	No valid reason codes exist for Adjustments in the Lookup table	
42994	AR_AAPI_NO_RECEIV ABLES_TRX	No valid receivables activity exists for Adjustments	
42995	AR_AAPI_NO_TYPE_C ODES	No valid type codes exists for Adjustments in the Lookup table	
42996	AR_AAPI_NO_USSGL_ CODES	No valid USSGL Codes exist for Adjustment	
42997	AR_AAPI_OVERRIDE_ CCID_DISALLOW	Override Activity profile option does not allow to override the Code Combination ID provided in the Receivables Activity	
42998	AR_AAPI_USSGL_COD E_DISALLOW	USSGL code is not allowed as the USSGL profile option does not allow it	
4667279	AR_LL_ADJ_INSTALL_ NOT_ALLOWED	You cannot create a line-level adjustment for a transaction with installments	

Message Number	Message Name	Message Description	Additional Comments
4667280	AR_LL_ADJ_LEGACY_ NOT_ALLOWED	You cannot create a line-level adjustment for a transaction with activity.	This is applicable to invoices and debit memos created in Release 11 <i>i</i> and having prior activity on them.
4667283	AR_ADJ_API_CUST_LI NE_ID_IG	The line-level customer transaction line ID takes precedence over header-level customer transaction line ID.	If you passed the customer_trx_line_id in p_adj_rec and it is also passed for the line in the PLSQL table (used to pass line level adjustment data), this warning message is displayed.
4667282	AR_ADJ_API_AMOUN T_IG	The line-level amount takes precedence over the header-level amount.	If you passed the line_amount in p_adj_rec and it is also passed for the line in the PLSQL table (used to pass line level adjustment data), this warning message is displayed.
4667284	AR_ADJ_API_RECV_T RX_ID_IG	The line-level Receivables transaction ID takes precedence over the header-level Receivables transaction ID	If you passed the receivables_trx_id in p_adj_rec and it is also passed for the line in the PLSQL table (used to pass line level adjustment data), this warning message is displayed.
4667285	AR_ADJ_API_TYPE_DI SALLOW	Receivables allows a line-level adjustment only for the line adjustment type	
4667281	AR_LL_ADJ_MODIFY_ NOT_ALLOWED	You cannot modify an adjustment created at the line level	Use the reverse adjustment routine as stated in the earlier section of the documentation.

Credit Memo Approval and Creation API User Notes

Overview

This document outlines the use of the Credit Memo Approval and Creation API. This API lets you achieve the following task using simple calls to PL/SQL functions:

- Initiate a Credit Memo Request workflow process request for the creation of a credit memo against a specified transaction either with or without an approval process
- Check the status of an existing Credit Memo Request workflow process request
- Apply on-account credit memos to a debit item
- Unapply on-account credit memos to a debit item

To create a credit memo using an existing, user-defined Credit Memo Request workflow approval process, set the p_skip_workflow_flag parameter to N. In this case, the workflow process proceeds independently of the Credit Memo Approval and Creation API. If the disputed amount of the invoice is approved, then a credit memo is automatically created.

Note: You must set up the Credit Memo Request workflow before using the Credit Memo Approval and Creation API. For more information, see the *Oracle Receivables User Guide*.

To create a credit memo directly, without sending a request through the workflow approval process, set the p_skip_workflow_flag parameter to Y. If you set the p_skip_workflow_flag parameter to Y, then the Credit Memo Approval and Creation API bypasses the workflow process and calls code to automatically create the credit memo.

When you set the p_skip_workflow_flag parameter to Y, you might also have to set

values for its associated parameters: p_credit_method_installments, p_credit_method_rules, and p_batch_source_name. For more information, see the description of the AR_CREDIT_MEMO_API_PUB.Create_Request routine, page 3-2.

You cannot use the Credit Memo Approval and Creation API to generate on-account credit memos. You must specify an existing transaction to credit.

API Usage

To initiate a Credit Memo Request workflow process request, to check the status of an existing Credit Memo Request workflow process request, and to apply and unapply onaccount credit memos to a debit item, use the following routines:

- AR_CREDIT_MEMO_API_PUB.Create_Request, page 3-2: Use this routine to initiate the Credit Memo Request workflow process by making a credit memo workflow request.
- AR_CREDIT_MEMO_API_PUB.Get_Request_Status, page 3-9: Use this routine to view the status of an existing request
- AR_CM_API_PUB.Apply_On_Account, page 3-12: Use this routine to apply onaccount credit memos to a debit item.
- AR_CM_API_PUB.Unapply_On_Account, page 3-12: Use this routine to unapply on-account credit memo applied to a debit item.

Prerequisites

You must define three HTML pages that display this information:

- The credit memo dispute request
- The original transaction details
- The transaction activities

You provide the API with the URLs of these pages. When workflow notifications are sent to the collector, approver, and receivable roles, links to the URLs are set in the message body of the notification. If the URLs are not correctly set up, then you will receive an error message such as "URL not found" when you click on the links.

You must also set up the Credit Memo Request workflow before you use the Credit Memo Approval and Creation API. For more information, see: Setting Up Credit Memo Request Workflow, Oracle Receivables User Guide.

AR CREDIT MEMO_API_PUB.Create_Request

You can call this routine to create the Credit Memo Request workflow process request.

When the workflow request has been created, the API returns a unique request ID number (p_request_id) that you can use to track the status of the request. The following is a breakdown of this routine's parameters, based upon parameter type:

Standard Parameters

This table lists and describes the standard parameters common to all routines in the Credit Memo Approval and Creation API.

Parameter	Туре	Data-type	Required	Default Value	Description
p_api_version	IN	NUMBER	Yes		Used to compare version numbers of incoming calls to current version number.
p_init_msg_list	IN	VARCHAR 2		FND_API. G_FALSE	Set to TRUE to have the API automatically initialize the message list.
p_commit	IN	VARCHAR 2		FND_API. G_FALSE	Set to TRUE to have the API commit automatically.
x_return_status	OUT	VARCHAR 2			Overall return status of the API.
x_msg_count	OUT	NUMBER			Number of messages in the API message list.
x_msg_data	OUT	VARCHAR 2			Message in encoded format if x_msg_count=1.

Create_Request Parameters

This table lists and describes parameters that specifically pertain to the Create_Request routine:

See Legend, page 3-8 for this table's legend.

Parameter	Туре	Data-type	Required	Description
p_customer_trx_id	IN	ra_customer_trx. customer_trx_id%type	Yes	Customer_trx_id of the disputed invoice.

Parameter	Туре	Data-type	Required	Description
p_line_credit_flag	IN	ra_cm_request.line_credit_flag% type	Yes	This value should be set to Y if the dispute is at the line level.
p_line_amount	IN	ra_cm_request.line_amount%type	Yes/No	Amount of the line dispute at the header level. If the dispute is at the header level, you should enter either the line_amount, tax_amount or freight_amount.
p_tax_amount	IN	ra_cm_request.tax_amount	Yes/No	Amount of the tax dispute at the header level.
p_freight_amount	IN	ra_cm_request.freight_amount	Yes/No	Amount of the freight dispute at header level.
p_cm_reason_code	IN	ra_cm_requests. cm_reason_code%type	YES	User defined lookup code that represents the reason for the invoice dispute. Should be a valid lookup_code for the lookup_type CREDIT_MEMO_REASON.
p_comments	IN	ra_cm_requests.comments%type	No	Comments about the credit memo request, entered if required. These comments appear in the notes region of the Transaction window. This also includes the internal
				comments posted by user and are not visible to customers.
p_orig_trx_number	IN	VARCHAR2	No	Enter the duplicate invoice number if using the "Duplicate Billing" reason code.
p_tax_ex_cert_num	IN	VARCHAR2	No	Tax exemption certificate number.

Parameter	Туре	Data-type	Required	Description
p_request_url*	IN	VARCHAR2	No**	URL that displays the information of the actual credit memo dispute request.*
				See Legend, page 3-8 for this table's legend.
p_transaction_url	IN	VARCHAR2	No**	URL that displays the information of the original transaction.
				See Legend, page 3-8 for this table's legend.
p_trans_act_url	IN	VARCHAR2	No**	URL that displays information about the original transaction activities.
				See Legend, page 3-8 for this table's legend.
<pre>p_cm_line_tbl(x). customer_trx_line_id</pre>	IN	cm_line_tbl_type_cover%type	Yes/No	This value must be entered only if the dispute is at the line level. This value indicates the line_id that is in dispute.
				Note: Where p_cm_line_tbl (x), x indicates the index. The dispute can be for multiple lines.
p_skip_workflow_fl ag	IN	VARCHAR2	No	Defaults to N. If this value is set to Y, the entire workflow is skipped for that particular request and the credit memo is directly created.

	Туре	Data-type	Required	Description
p_credit_method_ins tallments	IN	VARCHAR2	No	The p_credit_method_installments is the credit method that is used for crediting a transaction that uses split payment terms. Choices include PRORATE, LIFO, FIFO, or NULL. This value may be required if the p_skip_workflow_flag is set to Y. This parameter is mandatory if the credit memo is against a transaction that uses split payment terms and LINE_TYPE = LINE or CHARGES, or you are passing header freight. Do not enter a value for this parameter if LINE_TYPE = TAX, or if
				you are passing freight for a specific line.

Parameter	Туре	Data-type	Required	Description
p_credit_method_rul es	IN	VARCHAR2	No	The p_credit_method_rules is the credit method for crediting a transaction which uses an accounting rule. Choices include PRORATE, LIFO, UNIT, or NULL.
				This value may be required if the p_skip_workflow_flag is set to Y.
				• This parameter is mandatory if the credit memo is against a transaction which uses an accounting rule and LINE_TYPE = LINE or CHARGES, or you are passing header freight.
				 Do not enter a value for this parameter if LINE_TYPE = TAX, or if you are passing freight for a specific line.
p_batch_source_nam e	IN	VARCHAR2	No	This value is required if the p_skip_workflow_flag is set to Y.
p_org_id	IN	NUMBER	No	This value is required and it is used to identify the organization where the credit memo is sourced from.
x_request_id	OUT	VARCHAR2	Yes	Request_id of the credit memo that is returned if the data passed is valid and the credit memo request is created.
p_attribute_rec	IN	arw_cmreq_cover. pq_attribute_rec_type	No	Default value is ATTRIBUTE_REC_CONST.
p_interface_attribute _rec	IN	arw_cmreq_cover. pq_interface_rec_type	No	Default value is ATTRIBUTE_REC_CONST

Parameter	Туре	Data-type	Required	Description
p_global_attribute_r ec	IN	arw_cmreq_cover. pq_global_attribute_rec_type	No	Default value is GLOBAL_ATTRIBUTE_REC_CO NST.
P_DISPUTE_DATE	IN	DATE	No	NULL

Legend

* The request confirmation page might need the request_id as a parameter to query the information. This will not be available to the calling program when creating the p_request_url parameter because the request_id is the out parameter of the API. Calling programs should leave the request_id value blank and the table handler will add the request id value and pass it to Workflow. The code searches for the "req id=" string and replaces it with req_id="req_id". The parameter name must be req_id.

For example: For the old technology stack (PL/SQL), the following represents the request URL in iReceivables to call the "Request Confirmation" page. Note that no value has been entered for the req_id.

```
'arw_single_trx.single_cm_page?
req_id='||'req_id='||'`&component='||glb_inv_part||'`&pct_change='||glb_
percent_change;
```

** If the calling application does not enter the request, transaction, and transaction activities URLs, then you will see a default page reading "Unavailable" when you click on these links in the notifications screen. It is strongly recommended that the calling application have the UI (user interface) display these pages and pass these URLs to the API.

Parameter validation

The API validates all parameters that you enter. If any of the required fields are missing or invalid, then the API returns an error message. A list of error messages is documented in Messages, page 3-12.

Example

This example shows a simple test case for creating a credit memo request for a dispute at the header level:

Objective:

To create a credit memo request.

Parameters entered:

```
customer trx id = 99999
line_credit_flag = N
```

```
line_amount = -100
cm_reason_code = RETURN
```

Call to the API:

AR_CREDIT_MEMO_API_PUB.Get_Request_Status

Use this routine to view the Credit Memo Request workflow process request status. The API returns the status of the request and information about where the request is in the workflow. The following is a breakdown of parameters for this routine, based on parameter type:

Standard parameters

This table shows the standard API parameters common to all routines in the Credit Memo Approval and Creation API:

Parameter	Туре	Data-type	Required	Default Value	Description
p_api_version	IN	NUMBER	Yes		Used to compare version numbers of incoming calls to its current version number.
p_init_msg_list	IN	VARCHAR2		FND_API. G_FALSE	Set to TRUE to have the API automatically initialize the message list.
x_return_status	OUT	VARCHAR2			Overall return status of the API.
x_msg_count	OUT	NUMBER			Number of messages in the API message list.

Parameter	Туре	Data-type	Required	Default Value	Description
x_msg_data	OUT	VARCHAR2			Message, in encoded format if x_msg_count=1.

Get_Request_Status parameters

This table shows parameters that specifically pertain to the Get_Request_Status routine:

Parameter	Туре	Data-type	Require d	Description
p_request_id	IN	ra_cm_requests.request_id%type	YES	ID of the credit memo request whose status you are checking.
x_status_meaning	OUT	VARCHAR2		Status of the credit memo request.
x_reason_meaning	OUT	VARCHAR2		Reason for the dispute of the credit memo request.
x_customer_trx_id	OUT	ra_customer_trx. customer_trx_id%type		Customer transaction ID for the dispute of the credit memo request.
x_cm_customer_trx_id	OUT	ra_customer_trx. customer_trx_id%type		Credit memo transaction ID that was created for the dispute.
x_line_amount	OUT	ra_cm_requests.line_amount% type		Total amount of dispute for lines.
x_tax_amount	OUT	ra_cm_requests.tax_amount% type		Total amount of dispute for tax.
x_freight_amount	OUT	ra_cm_requests. freight_amount%type		Total amount of dispute for freight.
x_line_credits_flag	OUT	ra_cm_requests. line_credits_flag%type		Indicates whether the dispute is at the line level or the header level. If the value is set to Y, the dispute is at the line level.
x_created_by	OUT	wf_users.display_name%type		Name of the requestor.

Parameter	Туре	Data-type	Require d	Description
x_creation_date	OUT	DATE		Date of the request.
x_approval_date	OUT	DATE		Credit memo approval date if the credit memo has been created for the request.
x_comments	OUT	ra_cm_requests.comments% type		Comments entered by the requestor.
x_cm_line_tbl	OUT	cm_line_tbl_type_cover		Table that contains the line level dispute information. The values in the table will be set if the x_line_credits_flag = Y.
x_cm_activity_tbl	OUT	cm_activity_tbl_type_cover		Table that contains the status of the activities for the request.
x_cm_notes_tbl	OUT	cm_notes_tbl_type_cover		Table that contains the notes inserted for the transaction that is disputed.

Note:

```
TYPE CM LINE REC TYPE COVER IS RECORD
    customer_trx_line_id: ra_customer_trx_lines.customer_trx_line_id%
    extended_amount: ra_customer_trx_lines.extended_amount%type,
    quantity_credited: number,
    price: number;
TYPE CM_LINE_TBL_TYPE_COVER
    IS TABLE OF
    CM_LINE_REC_TYPE_COVER
    INDEX BY BINARY INTEGER;
x_cm_line_tbl CM_LINE_TBL_TYPE_COVER;
TYPE CM_ACTIVITY_REC_TYPE_COVER IS RECORD
    begin_date: DATE,
    activity_name: VARCHAR2(80),
    status: wf_item_activity_statuses.activity_status%type,
    user: wf_item_activity_statuses.activity_user%type);
TYPE CM_ACTIVITY_TBL_TYPE_COVER
    IS TABLE OF
    CM_ACTIVITY_REC_TYPE_COVER
    INDEX BY BINARY INTEGER;
x_cm_activity_tbl
                  CM_ACTIVITY_TBL_TYPE_COVER;
TYPE CM_NOTES_REC_TYPE_COVER IS RECORD
     ( NOTES ar_notes.text%type);
TYPE CM_NOTES_TBL_TYPE_COVER
    IS TABLE OF
    CM_NOTES_REC_TYPE_COVER
    INDEX BY BINARY INTEGER;
```

Parameter validation

The API validates all parameters that you enter. If any of the required fields are missing or invalid, then the API returns an error message. A list of error messages is documented in Messages, page 3-12.

Example

The following example is a simple test case for viewing the status of the credit memo request.

Objective:

To get the status of the credit memo request.

Parameters entered:

request id = 122

Call to the API:

```
AR_CREDIT_MEMO_API_PUB.Get_Request_Status(
                     p_api_version => 1.0,

x_msg_count => msg_count ,

x_msg_data => msg_data,

x_return_status => return_status,

p_request_id => request_id,

x_status_meaning => status_meaning,

x_reason_meaning => reason_meaning,

x_customer_trx_id => customer_trx_id,

x_line_amount => line_amount
                     x_cm_customer_trx_id => cm_customer_trx_id
x_line_amount => line_amount,
x_tax_amount => tax_amount,
x_freight_amount => freight_amount,
x_line_credits_flag => line_credits_flag,
x_created_by => created_by,
x_creation_date => creation_date,
x_cm_line_tbl => cm_line_tbl,
x_cm_activity_tbl => cm_activity_tbl,
x_cm_notes_tbl => cm_notes_tbl);
```

AR_CM_API_PUB.Apply_On_Account

Use this routine to apply on-account credit memos to a debit item.

AR_CM_API_PUB.Unapply_On_Account

Use this routine to unapply on-account credit memo applied to a debit item.

Messages

The following table describes the possible messages returned by the Credit Memo Approval and Creation API.

Message Number	Message Name	Message Description
11936	AR_RAXTRX-1719	You must supply a reason code for your credit memo transaction.
11091	AR_CKAP_OVERAPP	You cannot overapply this transaction.
42711	AR_TAPI_LINE_NOT_EXIST	Line does not exist (customer_trx_line_id: [customer_trx_line_id]).
42756	AR_TAPI_TRANS_NOT_EXIST	Transaction does not exist (customer_trx_id: [customer_trx_id]).
294003	AR_CMWF_API_INVALID_VAL UE	You specified an invalid value for the LINE_CREDIT_FLAG parameter. The valid values are Y and N.
294004	AR_CMWF_API_NO_LINES_INF O	The value for LINES_CREDIT_FLAG is Y, please provide at least one line level information.
294002	AR_CMWF_API_INVALID_REQ UEST_ID	Request does not exist (REQUEST_ID: &REQUEST_ID)

Credit Memo Application API User Notes

Overview

This document outlines in detail the Credit Memo Application API. This public API currently allows the application of an on-account credit memo to an activity such as Electronic Refund, which creates a customer refund for the credit memo via the creation of a negative miscellaneous receipt.

Please refer to the Oracle Receivables User Guide for more detail on customer credit refund functionality.

Basic Business Needs

The Credit Memo Application API enables the following business actions:

Application of an on-account memo to the Electronic Refund activity, resulting in subsequent refund of the credit memo to the customer.

API Usage

To apply or unapply an on-account credit memo to an activity, call the following APIs:

- ar_cm_application_pub.activity_application, page 4-1: Applies an on-account credit memo to an activity.
- ar_cm_application_pub.activity_unapplication, page 4-10: Unapplies an onaccount credit memo from an activity.

ar_cm_application_pub.activity_application

Use this routine to apply an on-account credit memo to an activity, such as Electronic Refund. The API returns the receivable_application_id of the receivable_application created.

Input Parameters

Standard API parameters: 4

Activity application parameters: 12 (including 1 descriptive flexfield parameter and 1 global descriptive flexfield parameter)

Output Parameters

Standard API parameters: 3

Activity application parameters: 4 required parameters (might vary depending on the adjustment type)

Parameter Descriptions

The input descriptive flexfield parameter is a record of type attribute_rec_type:

```
TYPE attribute_rec_type IS RECORD
                            (p_attribute_category IN VARCHAR2, p_attribute1 IN VARCHAR2,
                              (p_attribute_category<br/>p_attribute1<br/>p_attribute2<br/>p_attribute3<br/>p_attribute4<br/>p_attribute5<br/>p_attribute5<br/>p_attribute6<br/>p_attribute6<br/>p_attribute7<br/>p_attribute7<br/>p_attribute8<br/>p_attribute8<br/>p_attribute9<br/>p_attribute9<br/>p_attribute10<br/>p_attribute11<br/>p_attribute12<br/>p_attribute13<br/>p_attribute13<br/>p_attribute14<br/>p_attribute14<br/>p_attribute15IN VARCHAR2<br/>IN VARCHAR2</br/>IN VARCHAR2</br/>IN VARCHAR2</br/>IN VARCHAR2</br/>IN VARCHAR2</br/>IN VARCHAR2
                                                                                                                                                                                                                   IN VARCHAR2);
```

The input global descriptive flexfield parameter is a record of type global_ attribute_rec_type:

```
global_attribute_rec_type IS RECORD

(p_global_attribute_category p_global_attribute1 IN VARCHAR2, p_global_attribute2 IN VARCHAR2, p_global_attribute3 IN VARCHAR2, p_global_attribute4 IN VARCHAR2, p_global_attribute5 IN VARCHAR2, p_global_attribute6 IN VARCHAR2, p_global_attribute7 IN VARCHAR2, p_global_attribute8 IN VARCHAR2, p_global_attribute9 IN VARCHAR2, p_global_attribute10 IN VARCHAR2, p_global_attribute11 IN VARCHAR2, p_global_attribute12 IN VARCHAR2, p_global_attribute12 IN VARCHAR2, p_global_attribute13 IN VARCHAR2, p_global_attribute14 IN VARCHAR2, p_global_attribute15 IN VARCHAR2, p_global_attribute15 IN VARCHAR2, p_global_attribute16 IN VARCHAR2, p_global_attribute17 IN VARCHAR2, p_global_attribute18 IN VARCHAR2, p_global_attribute18 IN VARCHAR2, p_global_attribute19 IN VARCHAR2, p_global_attribute19 IN VARCHAR2, p_global_attribute20 IN VARCHAR2, in VARCHAR2, p_global_attribute19 IN VARCHAR2, p_global_attribute19 IN VARCHAR2, p_global_attribute20 IN VARCHAR2, in VARCHAR2, p_global_attribute20 IN VARCHAR2, in VARCHAR
TYPE global_attribute_rec_type IS RECORD
```

The following table lists the standard API parameters which are common to all the routines in the credit memo application API:

Parameter	Туре	Data-type	Required	Default Value	Description
p_api_version	IN	NUMBER	Yes		Used to compare version numbers of incoming calls to its current version number.
					Unexpected error is raised if version in-compatibility exists.
					In the current version of the API, you should pass in a value of 1.0 for this parameter.
p_init_msg_list	IN	VARCHAR2		FND_API. G_FALSE	Allows API callers to request that the API does initialization of the message list on their behalf.
p_commit	IN	VARCHAR2		FND_API. G_FALSE	Used by API callers to ask the API to commit on their behalf.
p_validation_lev el	IN	NUMBER		FND_API. G_VALID_LEV EL_FULL	Not to be used currently as this is a public API .
x_return_status	OUT	VARCHAR2			Represents the API overall return status. See: Exception Handling and Result Messages, page 1-3.
x_msg_count	OUT	NUMBER			Number of messages in the API message list
x_msg_data	OUT	VARCHAR2			This is the message in encoded format if x_msg_count=1

The following table lists the parameters that are relevant to the activity_application routine:

Parameter	Туре	Data-type	Required *	Description
p_customer_trx_id	IN	NUMBER	Yes	Customer transaction identifier of the on account credit memo to be applied.
				Default: None
				Validation:
				Must be a completed on-account credit memo (not a regular credit memo related to an invoice where previous_customer_trx_id has a value).
				Must have a receipt method.
				Receipt method must belong to a receipt class that allows remittance.
				Receipt method must have a remittance bank account.
				Must have customer bank account details.
				Must have a negative original amount due.
				Must not be negative due to overpayment.
				Errors:
				AR_REF_NO_PAYMENT_METHOD, AR_REF_NO_CUST_BANK, AR_REF_NOT_OACM, AR_REF_CM_INCOMPLETE, AR_REF_CM_POSITIVE, AR_REF_MORE_THAN_CM_AMT, AR_REF_RCT_CLASS_REMIT, AR_REF_NO_REMIT_BANK

Parameter	Туре	Data-type	Required	Description
p_amount_applied	IN	NUMBER	Yes	The amount of the credit memo to apply to an activity.
				Default: None
				Validation:
				Must be greater than zero.
				Must not cause the credit memo to be overapplied.
				Total applied to Electronic Refund, including this application and other applications on the same credit memo, must not fall outside the approval limits or Credit Memo refunds specified for the user/currency.
				Errors:
				AR_CKAP_OVERAPP, AR_REF_CM_APP_NEG, AR_REF_USR_LMT_OUT_OF_RANGE
p_applied_payment_sc hedule_id	IN	NUMBER	Yes	The payment_schedule_id of the activity being applied to.
				Default: None
				Validation:
				Only 1 value is currently allowed: -8 (Electronic Refund)
				Error:AR_RAPI_APP_PS_ID_INVALID
p_receivable_trx_id	IN	NUMBER	Yes	Receivables Transaction Identifier of the activity being applied to.
				Default: None
				Validation: Must be of type Credit Memo Refund.
				Error: AR_RAPI_ACTIVITY_X_INVALID

Parameter	Туре	Data-type	Required *	Description
p_apply_date	IN	DATE	No	The date the credit memo is applied to the activity.
				Default: The greater of system date and transaction date.
				Validation: Must not precede the transaction date of the credit memo.
				Error: AR_APPLY_BEFORE_TRANSACTION
p_apply_gl_date	IN	DATE	No	Date that this application will be posted to the General Ledger.
				Default: Gets defaulted to the system date if it is in an open or future enterable period, otherwise:
				• If the most recent open period is prior to the transaction date: last date of that period
				• If there is a period open after the transaction date: first date of the last open period
				Validation:
				It is valid if the following conditions are true:
				• The date is in an Open or Future period
				• The period cannot be an Adjustment period
				Must not precede the credit memo GL date
				Error: AR_INVALID_APP_GL_DATE, AR_VAL_GL_INV_GL
p_ussgl_transaction_co	IN	VARCHAR2 (30)	No	Code defined by public sector accounting.
de				Default: None
				Validation: None
				Error: None

Parameter	Туре	Data-type	Required *	Description
p_called_from	IN	VARCHAR2 (20)	No	This parameter is used to identify the calling routine.
				Default: Null
				Validation: None
				Error: None
p_attribute_record	IN	attribute_rec_t ype	No	This is a record type which contains all 15 descriptive flexfield segments and one descriptive flexfield structure defining column. It represents the Receivable Application Information flexfield.
				Default: DFF APIs used to do the defaulting
				Validation: DFF APIs used to do the validation depending on setup
				Error: AR_RAPI_DESC_FLEX_INVALID
p_global_attribute_rec ord	IN	global_attribut e_rec_type	No	This is a record type which contains all 20 global descriptive flexfield segments and one global descriptive flexfield structure defining column.
				Default: None
				Validation: None
p_comments	IN	VARCHAR2 (240)	No	User's comments
p_chk_approval_limit_ flag	IN	VARCHAR2(1)	No	Flag used to optionally override user approval limits for Credit Memo refunds.
				Values: 'Y' = Yes (check limits), 'N' = No (do not check limits)
				Default: 'Y'
				Validation: None

Parameter	Туре	Data-type	Required *	Description
p_application_ref_type	IN OUT	VARCHAR2 (30)	No	The context of application ref number/id is passed back in this parameter. For Electronic refunds this will be MISC_RECEIPT
				Default: None
				Validation: None
				Error: None
P_application_ref_id	IN OUT	NUMBER	No	For Electronic Refunds, the cash_receipt_id of the negative miscellaneous receipt created for the refund is passed back in this parameter.
				Default: None
				Validation: None
				Error: None
p_application_ref_nu m	IN OUT	VARCHAR2 (30)	No	For Electronic Refunds, the receipt number for the resulting miscellaneous receipt will be passed back in this parameter.
				Default: None
				Validation: None
				Error: None
p_receivable_applicati on_id	OUT	NUMBER(15)	No	The receivable application identifier of the activity application.

*If the values for the Required parameters are not passed in a call to this API, then the call itself will fail. However, depending on the business scenario, you must pass in values for other parameters to successfully create the business object. Otherwise, error messages will be reported.

Validation

This section explains the validation in this API, which does not relate directly to any of the above columns.

User Approval Limits

Only checked if $p_{chk_approval_limits_flag \Leftrightarrow 'N'$.

- Limits must exist for the user calling the credit memo application API for the credit memo currency.
- The total amount applied to Electronic Refund for a particular credit memo must fall within the limits.

Example

Objective: To apply an on-account credit memo to the Electronic Refund activity using a call to ar_cm_application_pub.activity_application and passing the minimum number of input parameters.

This table lists the entered parameters:

Parameter	Entered Value	Default Value
p_api_version	1.0	
p_init_msg_list	FND_API.G_TRUE	
p_customer_trx_id	1001	
p_amount_applied	100	
p_applied_payment_schedule _id	1071	
p_receivables_trx_id	1089	

This table lists the defaulted input parameters, which were not entered:

Parameter	Entered Value	Default Value
p_apply_date		sysdate
p_apply_gl_date		sysdate
p_chk_approval_limit_flag		Y

The API call in this case would be:

```
Ar_cm_application_pub.activity_application(
       p_api_version => 1.0,
p_init_msg_list => FND_API.G_TRUE,
p_customer_trx_id => 1001,
p_amount_applied => 100,
       p_applied_payment_schedule_id => 1071,
       p_receivables_trx_id => 1089,
       p_receivables_tix_id => 1cos,
x_return_status => l_return_status,
x_msg_count => l_msg_count,
x_msg_data => l_msg_data,
       p_application_ref_type => l_application_ref_type,
       p_application_ref_id => l_application_ref_id,
p_application_ref_num => l_application_ref_num);
```

The warnings and error messages put on the message stack by the API are retrieved after execution of this API by the calling program in the following manner:

```
IF l_msg_count = 1 Then
  --there is one message raised by the API, so it has been sent out
  --in the parameter x_msg_data, get it.
l_msg_data_out := l_msg_data;
ELSIF l_msg_count > 1 Then
--the messages on the stack are more than one so call them in a loop
-- and put the messages in a PL/SQL table.
  loop
   count := count +1 ;
    l_mesg := FND_MSG_PUB.Get;
    If l_mesg IS NULL Then
     Mesg_tbl(count).message := l_mesg;
   End if;
end loop;
END IF;
```

Depending on the message level threshold set by the profile option FND_API_MSG_LEVEL_THRESHOLD, the messages put on the message stack may contain both the error messages and the warnings.

Result: An electronic refund can be created for an on account credit memo by specifying only 6 input parameters in the above API call.

ar_cm_application_pub.activity_unapplication

Call this routine to reverse an activity application on an on-account credit memo. Such applications currently include only Electronic Refunds.

Input Parameters

Standard API parameters: 4

Activity unapplication parameters: 4

Output Parameters

Standard API parameters: 3

Activity unapplication parameters: 0

Parameter Descriptions

For descriptions of the seven standard API parameters, see ar_cm_application_pub. activity_application, page 4-1.

The following table lists the parameters that are relevant to the activity_unapplication routine:

Parameter	Туре	Data-type	Required *	Description	
p_customer_trx_id	IN	NUMBER(15)	No	The customer transaction identifier of the on- account credit memo from which the activity application is to be unapplied.	
				Default: Null	
				Validation:	
				 Must have at least one Electronic Refund application 	
				2. Must have only 1 Electronic Refund application if receivable_application_id is not supplied	
				3. Must be specified if receivable_application_id is not specified	
				Error: AR_RAPI_CUST_TRX_ID_INVALID AR_RAPI_MULTIPLE_ACTIVITY_APP	

Parameter	Туре	Data-type	Required *	Description
p_receivable_applica tion_id	IN	NUMBER(15)	No	Identifies the receivable application. Used to derive the customer trx id if not specified. Default: If only one Electronic Refund application exists, then receivable-application_id is taken from it. Validation: 1. applied_payment_schedule_id must be -8 2. Display flag = 'Y' (latest application) and status = 'ACTIVITY' 3. Must correspond to the customer_trx_id specified.
				Error: AR_RAPI_REC_APP_ID_INVALID

Parameter	Туре	Data-type	Required *	Description
p_reversal_gl_date	IN	DATE		The reversal gl date used for the accounting entries.
				Default: Gets defaulted to the application gl date if it is a valid gl_date, otherwise:
				• If the most recent open period is prior to the transaction date: last date of that period
				• If there is a period open after the transaction date: first date of the last open period
				Validation:
				1. It is valid if the following conditions are true:
				• The date is in an Open or Future period.
				 The period cannot be an Adjustment period.
				2. reversal GL date >= application GL date.
				3. reversal GL date >= transaction GL date.
				Error: AR_INVALID_APP_GL_DATE, AR_RW_BEFORE_APP_GL_DATE, AR_VAL_GL_INV_GL
p_called_from	IN	VARCHAR2(20)	Yes	Used to indicate which program is calling this API.
				Default: None
				Validation: None
				Error: None

Example

Objective: To unapply an activity application using a call to ar_cm_application_pub. activity_unapplication, and passing a minimum number of input parameters.

This table lists the entered parameters:

Parameter	Entered Value	Default Value
p_api_version	1.0	
p_receivable_application_id	10051	

This table lists the defaulted input parameters, which were not entered:

Parameter	Entered Value	Default Value
p_customer_trx_id		20338
p_reversal_gl_date		01-JUN-2000
p_called_from		

The retrieval and handling of the warnings and error messages, put on the message stack by the API during execution, are the same as described in Exception Handling and Result Messages, page 1-3.

Messages

The following table lists all the error messages raised by the Credit Memo Application API:

TYPE

E: Error message

W: Warning message

MESSAGE_CODE	MESSAGE_TEXT	EXPLANATION	TYP E
AR_APPLY_BEFORE_TRANSACTIO N	Apply Date must be greater than or equal to the Transaction Date.		E
AR_CKAP_OVERAPP	You cannot over apply this transaction.	This message will appear if the amount being applied to the credit memo results in a change of sign of the balance due remaining	Е

MESSAGE_CODE	MESSAGE_TEXT	EXPLANATION	TYP E
AR_INVALID_APP_GL_DATE	GL date, &GL_DATE, is not in an open or future-enterable period.	Either the GL date must be changed, or the period in which it falls must be opened or made future-enterable.	E
AR_RAPI_ACTIVITY_INVALID	The receivables activity name is invalid.		Е
AR_RAPI_ACTIVITY_X_INVALID	The specified combination of payment schedule identifier and receivables transaction identifier is invalid.	The activity type derived from the receivables_trx_id does not match with the activity type of the specified payment_schedule_id.	E
AR_RAPI_APP_PS_ID_INVALID	Applied payment schedule identifier has an invalid value.		E
AR_RAPI_APP_PS_RA_ID_X_INVA LID	Invalid receivable application identifier for the specified applied payment schedule identifier.		E
AR_RAPI_APPLIED_AMT_NULL	Applied amount could not be defaulted.	The p_applied_amount was not specified by the user and it could not be defaulted from the specified transaction	E
AR_RAPI_CUST_TRX_ID_INVALID	Invalid customer transaction identifier.		E
AR_RAPI_CUST_TRX_ID_NULL	Customer transaction identifier is null.		E
AR_RAPI_DESC_FLEX_INVALID	The entered values for the descriptive flexfield &DFF_NAME is invalid.		E
AR_RAPI_RCT_MD_ID_INVALID	Invalid receipt method identifier.		E
AR_RAPI_REC_APP_ID_INVALID	Invalid receivable application identifier.		Е

MESSAGE_CODE	MESSAGE_TEXT	EXPLANATION	TYP E
AR_RAPI_REC_APP_ID_NULL	Receivable application identifier is null.		Е
AR_RAPI_REC_TRX_ID_INVALID	Invalid receivable transaction identifier.		E
AR_RAPI_REC_TRX_ID_NULL	Please enter a receivables transaction identifier.		E
AR_RAPI_REV_GL_DATE_NULL	Reversal GL date is null.		E
AR_RAPI_TRX_PS_ID_X_INVALID	Invalid applied payment schedule identifier for the specified transaction.	The p_applied_payment_schedule _id specified by the user does not match with the payment_schedule_id derived from the p_customer_trx_id and the p_installment.	Е
AR_RAPI_TRX_PS_NOT_DEF_CUS	The customer could not be defaulted from the entered transaction and the applied payment schedule identifier.		E
AR_RAPI_TRX_RA_ID_X_INVALID	The activity type for the entered receivable transaction identifier does not match with the activity of the entered payment schedule identifier.		E
AR_REF_BEFORE_CM_GL_DATE	The GL date cannot be before the credit memo GL date.		E
AR_REF_CM_APP_NEG	Only positive credit memo refund amounts are allowed.		E
AR_REF_CM_INCOMPLETE	Please complete this credit memo.		E
AR_REF_CM_POSITIVE	Credit memo refunds are only allowed on negative credit memos.		Е

MESSAGE_CODE	MESSAGE_TEXT	EXPLANATION	TYP E
AR_REF_MORE_THAN_CM_AMT	You cannot refund more than the credit memo amount.		Е
AR_REF_NO_CUST_BANK	To enable credit memo refunds, please add customer bank details to the credit memo.		E
AR_REF_NO_APPROVAL_LIMIT	Credit memo refund approval limits do not exist for this user and currency.		Е
AR_REF_NO_PAYMENT_METHOD	To enable credit memo refunds, please add a receipt method to the credit memo.		E
AR_REF_NO_REMIT_BANK	To enable credit memo refunds, the credit memo receipt method must belong to a receipt class with an assigned remittance bank.		E
AR_REF_NOT_OACM	Credit memo refunds are only allowed for on-account credit memos.	Only transactions with Credit Memo class and unattached to another transaction are allowed.	E
AR_REF_RCT_CLASS_REMIT	To enable credit memo refunds, the receipt class associated with this credit memo receipt method must require remittance.		E
AR_REF_USR_LMT_OUT_OF_RAN GE	The total refund amount must be within &FROM_AMOUNT and &TO_AMOUNT.		E
AR_RW_BEFORE_APP_GL_DATE	Reversal GL Date must be on or after original GL Date of &GL_DATE.		E
AR_VAL_GL_INV_GL	The GL date should not be prior to the invoice's GL date.		E

Deposit API User Notes

Overview

This document outlines the specifications and the methodology for using the various Commitment (Deposit) APIs. These APIs provide an extension to existing functionality of creating and manipulating deposits through the standard Oracle Receivables Transactions workbench.

You can access these APIs:

- As standard PL/SQL servers-side routine calls
- Through Forms, utilizing the capability of Forms6 to have a procedure as its underlying base table

Basic Business Needs

The Commitment (Deposit) API provides the following basic functionality via different API calls:

- Creates a commitment of type Deposit
- Creates non-revenue sales credit for a deposit

API Usage

To create a deposit, you can call the following PL/SQL APIs:

- AR_DEPOSIT_API_PUB.Create_deposit, page 5-2: Creates a single deposit and completes it.
- AR_DEPOSIT_API_PUB.insert_non_rev_salescredit, page 5-27: Creates nonrevenue sales credit for a deposit.

AR_DEPOSIT_API_PUB.Create_deposit

This routine is called to create a deposit for the transactions.

Only one owner can be assigned to a commitment.

This API routine has 8 output and 136 input parameters in total. Of the output parameters, the API returns CUSTOMER_TRX_ID, CUSTOMER_TRX_LINE_ID, and new TRX_NUMBER, if generated during deposit creation.

The following is the breakdown of the parameters:

Input

Standard API parameters: 4

Deposit parameters: 132 + 2 (global descriptive flexfield parameter)

Output

Standard API parameters: 3

Deposit parameters: 5

Parameter Descriptions

The input global descriptive flexfield parameter is a record of type global_attr_rec_type.

```
TYPE global_attr_rec_type IS RECORD(
     global_attribute_category
                                   VARCHAR2(30) default null,
     global_attribute1
                                   VARCHAR2(150) default NULL,
     global_attribute2
                                   VARCHAR2(150) DEFAULT NULL,
                                  VARCHAR2(150) DEFAULT NULL,
     global_attribute3
    global_attribute4
                                 VARCHAR2(150) DEFAULT NULL,
     global_attribute5
                                 VARCHAR2(150) DEFAULT NULL,
    global_attribute6
                                  VARCHAR2(150) DEFAULT NULL,
     global_attribute7
                                  VARCHAR2(150) DEFAULT NULL,
                                 VARCHAR2(150) DEFAULT NULL,
    global_attribute8
    global_attribute9
                                 VARCHAR2(150) DEFAULT NULL,
                                  VARCHAR2(150) DEFAULT NULL,
     global_attribute10
     global_attribute11
                                  VARCHAR2(150) DEFAULT NULL,
     global_attribute12
                                   VARCHAR2(150) DEFAULT NULL,
    global_attribute13
                                  VARCHAR2(150) DEFAULT NULL,
    global_attribute14
                                 VARCHAR2(150) DEFAULT NULL,
     global_attribute15
                                  VARCHAR2(150) DEFAULT NULL,
     global_attribute16
                                  VARCHAR2(150) DEFAULT NULL,
     global_attribute17
                                  VARCHAR2(150) DEFAULT NULL,
                                 VARCHAR2(150) DEFAULT NULL,
    global_attribute18
    global_attribute19
                                  VARCHAR2(150) DEFAULT NULL,
                                  VARCHAR2(150) DEFAULT NULL,
    global_attribute20
                                  VARCHAR2(150) DEFAULT NULL,
     global_attribute21
     global_attribute22
                                  VARCHAR2(150) DEFAULT NULL,
    global_attribute23
                                  VARCHAR2(150) DEFAULT NULL,
    global_attribute24
                                 VARCHAR2(150) DEFAULT NULL,
                                  VARCHAR2(150) DEFAULT NULL,
     global_attribute25
     global_attribute26
                                   VARCHAR2(150) DEFAULT NULL,
                                  VARCHAR2(150) DEFAULT NULL,
     global_attribute27
    global_attribute28
                                  VARCHAR2(150) DEFAULT NULL,
     global_attribute29
                                  VARCHAR2(150) DEFAULT NULL,
     global_attribute30
                                  VARCHAR2(150) DEFAULT NULL);
```

The following table lists standard API parameters that are common to all the routines in the Commitment (Deposit) API.

Note: If required parameters are not passed in a call to this API, then the call will fail. However, depending on the business scenario, you will have to pass in values for other parameters to successfully create the business object; otherwise, error messages will be reported.

Parameter	Туре	Data-type	Require d	Default Value	Description
p_api_version	IN	NUMBER	Yes		Used to compare version numbers of incoming calls to its current version number. Unexpected error is raised if version incompatibility exists. In the current version of the API, you should pass a value of 1.0 for this parameter.

Parameter	Туре	Data-type	Require d	Default Value	Description
p_init_msg_list	IN	VARCHAR2		FND_API. G_FALSE	Allows API callers to request that the API does initialization of the message list on their behalf.
p_commit	IN	VARCHAR2		FND_API. G_FALSE	Used by API callers to ask the API to commit on their behalf.
p_validation_lev el	IN	NUMBER		FND_API. G_VALID_LEVEL_ FULL	Not to be used currently as this is a public API.
x_return_status	OUT	VARCHAR2			Represents the API overall return status.
x_msg_count	OUT	NUMBER			Number of messages in the API message list.
x_msg_data	OUT	VARCHAR2			This is the message in encoded format if x_msg_count=1.

The following table lists the parameters that pertain specifically to the deposit.

Parameter	Туре	Data-type	Required*	Description
p_deposit_number	IN	VARCHAR2		The deposit number of the deposit to be created.
				Default: Null
				Validation: If AR_RA_BATCH_AUTO_NUM_FLAG set by batch source is true, then it is derived automatically; else it is required to be present.
				Error: AR_DAPI_DEPOSIT_NO_NULL

Parameter	Туре	Data-type	Required*	Description
p_deposit_date	IN	DATE		The deposit date of the entered deposit.
				Default: System date
				Validation: This field is mandatory.
				Error: None
p_usr_currency_cod e	IN	VARCHAR2		The translated currency code. Used to derive the p_currency_code if it is not entered.
				Default: None
				Validation: Should be a valid currency, so that the corresponding currency code can be derived.
				Error: AR_RAPI_USR_CURR_CODE_INVALID
p_currency_code	IN	VARCHAR2		The actual currency code that gets stored in AR tables.
				Default: Derived from p_usr_currency_code if entered, else defaults to the functional currency code.
				Validation: Validated against the currencies in FND_CURRENCIES table.
				Error: AR_RAPI_CURR_CODE_INVALID
				Warning: AR_RAPI_FUNC_CURR_DEFAULTED
p_usr_exchange_rate _type	IN	VARCHAR2		The translated exchange rate type. Used to derive the p_exchange_rate_type if it has not been entered.
				Default: None
				Validation: Should be a valid rate type.
				Error: AR_RAPI_USR_X_RATE_TYP_INVALID

Parameter	Туре	Data-type	Required*	Description
p_exchange_rate_ty	IN	VARCHAR2		Exchange rate type stored in AR tables.
pe				Default: In case of foreign currency receipt, the value is derived from p_usr_exchange_rate_type. If p_usr_exchange_rate_type is null, then the value defaults from the AR: Default Exchange Rate Type profile option.
				Validation: Validated against values in GL_DAILY_CONVERSION_TYPES table.
				Error: AR_RAPI_X_RATE_TYPE_INVALID
p_exchange_rate	IN	NUMBER		The exchange rate between the receipt
				currency and the functional currency.
				Default: Derived from the Daily Rates table for rate_type \Leftrightarrow User in case of nonfunctional currency. If Journals: Display Inverse Rate profile option = Y, set user-entered value to 1/ p_exchange_rate. The entered value is rounded to a precision of 38.
				Validation: In case of nonfunctional currency, the rate should have a positive value for rate type=User For nonfunctional currency and type is User, do not specify any value.
				Error: AR_RAPI_X_RATE_INVALID, AR_RAPI_X_RATE_NULL
p_exchange_rate_dat e	IN	DATE		The date on which the exchange rate is valid.
				Default: Receipt date
				Validation: For a nonfunctional currency and type is ⇔User, there should be a valid rate existing in the database for this date. This is a cross validation of type, currency, and date.
				Error: AR_NO_RATE_DATA_FOUND

Parameter	Туре	Data-type	Required*	Description
p_batch_source_id	IN	NUMBER		Batch source identifier for the commitment.
				Default: Same as ar_ra_batch_source profile option.
				Validation: It should be a valid batch source and it should exist in the database. This field is mandatory if not defined in profile option.
				Error: AR_DAPI_BS_NAME_INVALID, AR_DAPI_BS_NAME_IGN, AR_DAPI_BS_ID_INVALID
p_batch_source_nam	IN	VARCHAR2		Batch source name for the commitment.
e				Default: Same as ar_ra_batch_source_name profile option.
				Validation: It should be a valid batch source and it should exist in the database.
				Error: AR_DAPI_BS_NAME_INVALID, AR_DAPI_BS_NAME_IGN AR_DAPI_BS_ID_INVALID
p_cust_trx_type_id	IN	NUMBER		Transaction Type identifier.
				Default: Based on the value of batch source
				Validation: It should be a valid transaction type. This field is mandatory.
				Error: AR_DAPI_TRANS_TYPE_INVALID, AR_RAPI_TRANS_TYPE_IGN, AR_DAPI_TRANS_TYPE_ID_INVALID
p_cust_trx_type	IN	VARCHAR2		Transaction Type name.
				Default: Based on the value of batch source
				Validation: It should be a valid transaction type.
				Error: AR_DAPI_TRANS_TYPE_INVALID, AR_RAPI_TRANS_TYPE_IGN, AR_DAPI_TRANS_TYPE_ID_INVALID

Parameter	Туре	Data-type	Required*	Description
p_class	IN	VARCHAR2		Constant value = DEP. Keeping as an input for a future enhancement.
p_gl_date	IN	DATE		Date that this deposit will be posted to the general ledger.
				Default: Gets defaulted to the current date if it is a valid gl_date, otherwise:
				 If the most recent open period is prior to the receipt date: last date of that period.
				 If there is a period open after the deposit date: first date of the last open period.
				Validation: The gl date is valid if the following conditions are true:
				 The date is in an Open or Future period.
				 The period cannot be an Adjustment period.
				Error: AR_INVALID_APP_GL_DATE

Parameter	Туре	Data-type	Required*	Description
p_bill_to_customer_i	IN	NUMBER		The CUSTOMER_ID for the bill-to customer.
				Default: Defaulted from customer name/number. If all name, number, and ID are null, then it is same as ship-to CUSTOMER_ID.
				Validation: Customer exists and has prospect code = CUSTOMER. Customer has a profile defined at the customer level. Either bill-to or ship-to customer must exist.
				Error: AR_RAPI_CUST_ID_INVALID, AR_RAPI_CUS_NAME_INVALID, AR_RAPI_CUS_NUM_INVALID, AR_RAPI_CUS_NAME_NUM_INVALID, AR_RAPI_CUS_NAME_NUM_IGN, AR_DAPI_BILL_OR_SHIP_CUST_REQ
p_bill_to_customer_ name	IN	VARCHAR2		The name for the entered customer. Used to default the customer ID if not specified.
				Default: None
				Validation: None
				Error: AR_RAPI_CUS_NAME_INVALID
p_bill_to_customer_ number	IN	VARCHAR2		The number for the entered customer. Used to default the customer ID if not specified.
				Default: None
				Validation: None
				Error: AR_RAPI_CUS_NAME_INVALID
p_bill_to_location	IN	VARCHAR2		The location for the bill-to customer.
				Default: Defaulted from the primary bill-to customer location, if defined. Otherwise, null.
				Validation: This field is mandatory.
				Error: AR_DAPI_CUS_LOC_INVALID

Parameter	Туре	Data-type	Required*	Description
p_bill_to_contact_id	IN	NUMBER		The contact identifier for the bill-to customer.
				Default: Defaulted from the bill-to customer site level, then customer level, if defined. Otherwise, null.
				Validation: Yes
				Error: AR_DAPI_BIII_CONTACT_NAME_INV, AR_DAPI_CUS_CONTACT_INVALID
p_bill_to_contact_fir st_name	IN	VARCHAR2		The first name of contact for the bill-to customer.
				Default: Defaulted from bill-to customer site level, then customer level, if defined. Otherwise, null.
				Validation: This field is mandatory.
				Error: AR_DAPI_BIII_CONTACT_NAME_INV, AR_DAPI_CUS_CONTACT_INVALID
p_bill_to_contact_las t_name	IN	VARCHAR2		The last name of contact for the bill-to customer.
				Default: Defaulted from bill-to customer site level, then customer level, if defined. Otherwise, null.
				Validation: This field is mandatory.
				Error: AR_DAPI_BIII_CONTACT_NAME_INV, AR_DAPI_CUS_CONTACT_INVALID

Parameter	Туре	Data-type	Required*	Description
p_ship_to_customer _id	IN	NUMBER		The CUSTOMER_ID for the ship-to customer.
				Default: Defaulted from customer name/number. Null otherwise.
				Validation: Customer exists and has prospect code = CUSTOMER. Customer has a profile defined at the customer level. Either bill-to or ship-to customer must exist.
				Error: AR_RAPI_CUST_ID_INVALID, AR_RAPI_CUS_NAME_INVALID, AR_RAPI_CUS_NUM_INVALID, AR_RAPI_CUS_NAME_NUM_INVALID, AR_RAPI_CUS_NAME_NUM_IGN, AR_DAPI_BILL_OR_SHIP_CUST_REQ
p_ship_to_customer _name	IN	VARCHAR2		The name for the entered customer. Used to default the customer ID, if not specified.
				Default: None
				Validation: None
				Error: AR_RAPI_CUS_NAME_INVALID
p_ship_to_customer _number	IN	VARCHAR2		The number for the entered customer. Used to default the customer ID, if not specified.
				Default: None
				Validation: None
				Error: AR_RAPI_CUS_NAME_INVALID
p_ship_to_location	IN	VARCHAR2		The location for the bill-to customer.
				Default: Defaulted from primary bill-to customer location, if defined. Otherwise, null.
				Validation: This field is mandatory.
				Error: AR_DAPI_CUS_LOC_INVALID

Parameter	Туре	Data-type	Required*	Description
p_ship_to_contact_i	IN	NUMBER		The contact identifier for the bill-to customer.
				Default: Defaulted from bill-to customer site level, then from customer level, if it is defined. If not defined, then it is not defaulted.
				Validation: Yes
				Error: AR_DAPI_BIII_CONTACT_NAME_INV, AR_DAPI_CUS_CONTACT_INVALID
p_ship_to_contact_first_name	IN	VARCHAR2		The first name of contact for the bill-to customer.
				Default: Defaulted from bill-to customer site level, then customer level, if defined. Otherwise, null.
				Validation: This field is mandatory.
				Error: AR_DAPI_BIII_CONTACT_NAME_INV, AR_DAPI_CUS_CONTACT_INVALID
p_ship_to_contact_la st_name	IN	VARCHAR2		The last name of contact for the bill-to customer.
				Default: Defaulted from bill-to customer site level, then customer level, if defined. Otherwise, null.
				Validation: This field is mandatory.
				Error: AR_DAPI_BIII_CONTACT_NAME_INV, AR_DAPI_CUS_CONTACT_INVALID

Parameter	Туре	Data-type	Required*	Description
p_term_id	IN	NUMBER		Payment terms identifier for the transactions. You can override payment terms.
				Default: Following hierarchy is used to default payment terms:
				1. Customer bill-to site level
				2. Customer address level
				3. Customer level transaction type
				Validation: It should be a valid payment term.
				Error: AR_DAPI_TERM_NAME_INVALID, AR_DAPI_TERM_ID_INVALID
p_term_name	IN	VARCHAR2		Payment terms name for the transactions. You can override payment terms.
				Default: Following hierarchy is used to default payment terms name:
				1. Customer bill-to site level
				2. Customer address level
				3. Customer level transaction type
				Validation: It should be a valid payment term.
				Error: AR_DAPI_TERM_NAME_INVALID, AR_DAPI_TERM_ID_INVALID

Parameter	Туре	Data-type	Required*	Description
p_salesrep_id	IN	NUMBER		Salesperson identifier for the transactions. You can override salesperson.
				Default: Default the primary ID from the bill-to customer. If sales credits are required and no ID is defaulted from the bill-to customer, then p_salesrep_id is set to -3, which means "No sales credit".
				Validation: It should be a valid salesperson in the system.
				Error: AR_DAPI_SALESREP_NAME_INVALID AR_DAPI_SALESREP_ID_INVALID
p_salesrep_name	IN	VARCHAR2		Salesperson name for the transactions. You can override salesperson.
				Default: Default the primary from the bill- to customer. If sales credits are required and no salesperson is defaulted from the bill-to customer, then p_salesrep_name is set to -3, which means "No sales credit".
				Validation: It should be a valid salesperson in the system.
				Error: AR_DAPI_SALESREP_NAME_INVALID, AR_DAPI_SALESREP_ID_INVALID
p_interface_header_	IN	VARCHAR2		Interface header context.
context				Default: Null
				Validation: Null
				Error: Null
p_interface_header_	IN	VARCHAR2		Interface header attribute value
attribute1 to p_interface_header_				Default: Null
attribute15				Validation: Null
				Error: Null

Parameter	Туре	Data-type	Required*	Description
p_attribute_category	IN	VARCHAR2		Descriptive Flexfield structure defining column.
				Default: Null
				Validation: It should be a valid structure.
				Error: Null
p_attribute1 to	IN	VARCHAR2		Descriptive Flexfield segment column.
p_attribute15				Default: Null
				Validation: It should be a valid segment.
				Error: Validate_Desc_Flexfield
p_global_attr_cust_r ec	IN	global_ attr_rec_ type		This is a record type that contains all the 25 global descriptive flexfield segments and one global descriptive flexfield structure defining column.
				Default: None
				Validation: None
				Error:
p_document_numbe	IN	NUMBER		Value assigned to document receipt.
r				Default: Null.
				Validation: User should not pass the value if the current document sequence is automatic. Document sequence value should not be entered if the Sequential Numbering profile option is set to Not Used.
				Error: AR_RAPI_DOC_SEQ_AUTOMATIC, AR_RAPI_DOC_SEQ_NOT_EXIST_A, AR_RAPI_DOC_SEQ_NOT_EXIST_P

Parameter	Туре	Data-type	Required*	Description
p_ussgl_transaction_	IN	VARCHAR2		Code defined by public sector accounting.
code				Default: None
				Validation: None
				Error: None
p_printing_option	IN	VARCHAR2		Printing option for the invoice.
				Default: Default is print option of transaction type.
				Validation: Can be 'PRI' or 'NOT'
				Error: AR_DAPI_PO_INVALID
p_default_tax_exem pt_flag	IN	VARCHAR2		Tax exempt flag. You can enter value for the field only if the TAX: Allow Override of Customer Exception profile option is yes.
				Default: 'S' (Standard)
				Validation: From lookup table for lookup_type = 'TAX_CONTROL_FLAG'
				Error: AR_DAPI_STATUS_TRX_INVALID
p_status_trx	IN	VARCHAR2		Status of the transaction. This is a user- maintainable field and it can be defined in lookup table.
				Default: OP, can be CL, PEN, or VD.
				Validation: from lookup table for LOOKUP_TYPE = 'INVOICE_TRX_STATUS'
				Error: AR_DAPI_STATUS_TRX_INVALID
p_financial_charges	IN	VARCHAR2		Indicates whether financial charges are calculated.
				Default: Null
				Validation: can be null, Y, N
				Error: AR_DAPI_FC_INVALID

Parameter	Туре	Data-type	Required*	Description
p_agreement_id	IN	NUMBER		Agreement associated with transaction for the customer.
				Default: Null
				Validation: Null
				Error: Null
p_special_instructio	IN	VARCHAR2		Any special instruction for the transaction, up to 240 characters.
				Default: Null
				Validation: Null
				Error: Null
p_comments				User's comments.
p_purchase_order	IN	VARCHAR2		Purchase order number.
				Default: Null
				Validation: Null
				Error: Null
p_purchase_order_r	IN	VARCHAR2		Purchase order revision number.
evision				Default: Null
				Validation: Null
				Error: Null
p_purchase_order_d	IN	DATE		Purchase order date.
ate				Default: Null
				Validation: Null
				Error: Null

Parameter	Туре	Data-type	Required*	Description
p_remit_to_address_ id	IN	NUMBER		Remit-to address ID for the customer
				Default: Remit_to_address assigned to country, state, and postal code combination for the customer's address.
				Validate from the view: AR_ACTIVE_REMIT_TO_ADDRESSES_V
				Error: AR_DAPI_LOC_SITE_NUM_IGN, AR_DAPI_REMIT_ADDR_ID_INVD
p_sold_to_customer	IN	NUMBER		The customer_id for the sold-to customer.
_id				Default: Bill_to_customer_id
				Validation:
				• Customer exists and has prospect code = CUSTOMER
				 Customer has a profile defined at customer level
				• Either bill-to or ship-to customer must exist
				Error: AR_DAPI_SOLD_CUST_COM_INVALID, AR_DAPI_SOLD_CUS_IGN, AR_DAPI_SOLD_CUST_ID_INVALID

Parameter	Туре	Data-type	Required*	Description
p_sold_to_customer _name	IN	VARCHAR2		The name for the entered/defaulted sold-to customer.
				Default: None
				Validation:
				1. Customer exists and has prospect code = CUSTOMER
				2. Customer has a profile defined at customer level
				3. Either bill-to or ship-to customer must exist
				Error: AR_DAPI_SOLD_CUST_NAME_INVALI D, AR_DAPI_SOLD_CUST_COM_INVALID
p_sold_to_customer _number	IN	VARCHAR2		The number for the entered/defaulted sold-to customer.
				Default: None
				Validation: Customer exists and has prospect code = CUSTOMER. Customer has a profile defined at customer level. Either bill-to or ship-to customer must exist.
				Error: AR_DAPI_SOLD_CUST_NUM_INVALID, AR_DAPI_SOLD_CUST_COM_INVALID

Parameter	Туре	Data-type	Required*	Description
p_paying_customer_ id				The customer_id associated with the customer bank account assigned to your transaction.
				Default: Same as bill-to customer
				Validation: Customer exists and has prospect code = CUSTOMER. Customer has a profile defined at customer level. Either bill-to or ship-to customer must exist.
				Error: AR_DAPI_CUS_NAME_NUM_IGN, AR_DAPI_PAY_CUST_ID_INVALID
p_paying_customer_ name				The name for the entered/defaulted paying customer.
				Default: None
				Validation: Customer exists and has prospect code = CUSTOMER. Customer has a profile defined at customer level. Either bill-to or ship-to customer must exist.
				Error: AR_DAPI_PAY_CUST_NAME_INVALID, AR_DAPI_PAY_CUST_COM_INVALID
p_paying_customer_ number				The number for the entered/defaulted paying customer.
				Default: None
				Validation: Customer exists and has prospect code = CUSTOMER. Customer has a profile defined at customer level. Either bill-to or ship-to customer must exist.
				Error: AR_DAPI_PAY_CUST_NUM_INVALID, AR_DAPI_PAY_CUST_COM_INVALID

Parameter	Туре	Data-type	Required*	Description
p_paying_location				The location for the paying customer.
				Default: Null
				Validation: This field is mandatory.
				Error: AR_DAPI_CUS_LOC_INVALID
p_receipt_method_i d	IN	NUMBER		Identifies the receipt method of the transactions.
				Default: From receipt method name.
				Validation: Validation detailed in Example, page 5-25.
				Error: AR_RAPI_RCPT_MD_NAME_IGN, AR_RAPI_RCPT_MD_ID_INVALID
p_receipt_method_n ame	IN	VARCHAR2		The receipt method name of the transactions.
				Default: None
				Validation: None
				Error: AR_RAPI_RCPT_MD_NAME_INVALID
p_cust_bank_accoun	IN	NUMBER		Customer bank account identifier.
t_id				Default: None
				Validation: From AP_BANK_ACCOUNTS table.
				Error: AR_RAPI_CUS_BK_NAME_NUM_IGN, AR_RAPI_CUS_BK_AC_ID_INVALID
p_cust_bank_accoun	IN	VARCHAR2		Customer bank account name.
t_name				Default: None
				Validation: From AP_BANK_ACCOUNTS table.
				Error: AR_RAPI_CUS_BK_AC_NAME_INVALID , AR_RAPI_CUS_BK_AC_2_INVALID

Parameter	Туре	Data-type	Required*	Description
p_cust_bank_accoun	IN	VARCHAR2		Customer bank account number.
t_number				Default: None
				Validation: From AP_BANK_ACCOUNTS table.
				Error: AR_RAPI_CUS_BK_AC_NUM_INVALID, AR_RAPI_CUS_BK_AC_2_INVALID
p_start_date_commit	IN	DATE		Start date of commitment.
ment				Default: Sysdate
				Validation: Based on end date, etc.
				Error: AR_TW_BAD_COMMITMT_DATE_RAN GE, AR_TW_COMMIT_END_TRX_DATE, AR_TW_BAD_DATE_COMMITMENT
p_end_date_commit	IN	DATE		End date of commitment.
ment				Default: Null
				Validation: Based on start date, etc.
				Error: AR_TW_BAD_COMMITMT_DATE_RAN GE, AR_TW_COMMIT_END_TRX_DATE, AR_TW_BAD_DATE_COMMITMENT
p_amount	IN	NUMBER		Deposit amount.
				Default: Cannot be negative.
				Validation: Based on start date, etc. This field is mandatory.
				Error: AR_DAPI_COMM_AMOUNT_NULL, AR_TW_COMMIT_AMOUNT_NEGATIV E

Parameter	Туре	Data-type	Required*	Description
p_inventory_id	IN	NUMBER		Item ID of commitment. You can enter memo or item ID.
				Default: Null
				Validation: Based on MTL_SYSTEM_ITEMS_B table.
				Error: AR_DAPI_INV_ID_INVALID, AR_DAPI_INV_MEMO_COM
p_memo_line_id	IN	NUMBER		Memo line ID. You can enter memo or item ID.
				Default: Null
				Validation: Based on AR_MEMO_LINES table.
				Error: AR_DAPI_MEMO_NAME_INVALID, AR_DAPI_MEMO_WRG, AR_DAPI_INV_MEMO_COM
p_memo_line_name	IN	VARCHAR2		Deposit amount.
				Default: Null
				Validation: Based on AR_MEMO_LINES table.
				Error: AR_DAPI_MEMO_NAME_INVALID, AR_DAPI_MEMO_WRG
p_description	IN	VARCHAR2		Description of deposit.
				Default: Null
				Validation: Null
				Error: Null
p_comm_interface_li	IN	VARCHAR2		Interface line context for deposit.
ne_context				Default: Null
				Validation: Null
				Error: Null

Parameter	Туре	Data-type	Required*	Description
p_comm_interface_li	IN	VARCHAR2	NULL	Interface line attribute value for deposit.
ne_attr1 to p_comm_interface_li				Default: Null
ne_ attr15				Validation: Null
				Error: Null
p_comm_attr_catego ry	IN	VARCHAR2	NULL	Descriptive Flexfield structure defining column for deposit lines.
				Default: Null
				Validation: It should be a valid structure.
				Error: Null
p_comm_attr1 to p_comm_attr15	IN	VARCHAR2	NULL	Descriptive Flexfield segment column for deposit lines.
				Default: Null
				Validation: It should be a valid segment.
				Error: Validate_Desc_Flexfield
p_global_attr_cust_li nes_rec	IN	global_attr_rec _type	NULL	This is a record type that contains all the 25 global descriptive flexfield segments for deposit lines and one global descriptive flexfield structure defining column.
				Default: None
				Validation: None
				Error: None
p_owner_id	IN	NUMBER	Null	ID of the commitment owner.
				Default: None
				Validation: Yes (same as customer contact).
				Error: N/A

Parameter	Туре	Data-type	Required*	Description
p_owners_name	IN	NUMBER	Null	Name of the commitment owner.
				Default: None
				Validation: Yes (same as customer contact)
				Error: N/A
X_new_trx_number	OUT	VARCHAR2		New transaction number, if generated.
X_new_customer_trx _id	OUT	VARCHAR2		New CUSTOMER_TRX_ID of the deposit created.
X_new_customer_trx _line_ id	OUT	VARCHAR2		New CUSTOMER_TRX_LINE_ID of the deposit created.
X_new_rowid	OUT	VARCHAR2		Row ID of the deposit created.
X_new_status	OUT	VARCHAR2		Status of the deposit created.

Example

Objective:

To create a deposit using a call to ar_deposit_api_pub.Create_deposit and passing a minimum number of Input parameters.

Entered parameters:

```
p_currency_code ='USD',
p_batch_source_id = Choose a Valid Batch source ID
p_cust_trx_type_id = Choose a Valid Transaction Type ID of class
"Deposit'
p_class
                      ='DEP' (Deposit)
p_bill_to_customer_number = Choose a Valid Customer Number
p_start_date_commitment = sysdate
p_amount = Choose deposit Amount
p_description = Your Deposit T
                       = Your Deposit Description
```

Before calling the APIs you should set up the application, responsibility and the user in the context of Oracle Applications by calling the following FND API.

```
fnd_global.apps_initialize ( user_id =>'Your user id', resp_id => 'Your
Responsibility id', resp_appl_id => 'Your Application id');
```

For example:

```
fnd_global.apps_initialize ( user_id => 1318, resp_id => 50559,
resp_appl_id => 222);
```

The API call in this case would be:

```
1_return_status VARCHAR2(1);
l_new_trx_number ra_customer_trx.trx_number%type;
l_new_customer_trx_id ra_customer_trx.customer_trx_id%type;
l_new_customer_trx_line_id ra_customer_trx_lines.
customer_trx_line_id%type;
fnd_global.apps_initialize ( user_id => 1318, resp_id => 50559,
resp_appl_id => 222);
ar_deposit_api_pub.CREATE_DEPOSIT(
```

1. Standard API parameters.

```
=> 1.0,
p_api_version
p_batch_source_id => 'Choose a Valid Batch source ID',
p_cust_trx_type_id => 'Choose a Valid Transaction Type ID of class
Deposit',
p_class
                     => 'DEP'
p_bill_to_customer_number => 'Choose a Valid Customer Number',
p_start_date_commitment => sysdate,
p_amount => 'Choose deposit Amount',
X_new_customer_trx_line_id =>l_new_customer_trx_line_id,
           =>l_new_rowid,
X_new_rowid
X_new_status
                     =>1_new_status ) ;
IF l_msg_count = 1 Then
```

- 2. There is one message raised by the API, so it has been sent out.
- **3.** In the parameter x_msg_data, get it.

```
dbms_output.put_line('l_msg_data '||l_msg_data);
ELSIF l_msg_count > 1 Then
```

- The messages on the stack are more than one, so call them in a loop.
- **5.** And print the messages.

```
LOOP
  IF nvl(l_count,0) < l_msg_count THEN</pre>
  1_count := nvl(1_count,0) +1 ;
  l_msg_data := FND_MSG_PUB.Get(FND_MSG_PUB.G_NEXT,FND_API.G_FALSE);
                  IF l_count = 1 THEN
                 dbms_output.put_line('l_msg_data 1 '||l_msg_data);
                   ELSIF l_count = 2 THEN
                dbms_output.put_line('l_msg_data 2 '||l_msg_data);
                   ELSIF 1_count = 3 THEN
                dbms_output.put_line('l_msg_data 3 '||l_msg_data);
                   ELSIF 1_count = 4 THEN
                dbms_output.put_line('l_msg_data 4 '||l_msg_data);
                   ELSIF 1_count = 5 THEN
                dbms_output.put_line('l_msg_data 5 '||l_msg_data);
                   ELSIF l_count = 6 THEN
                dbms_output.put_line('l_msg_data 6 '||l_msg_data);
                   END IF;
                   dbms_output.put_line('l_msg_data '||to_char
(l_count)||': '||l_msg_data);
                  ELSE
                    EXIT;
                  END IF;
               END LOOP;
             END IF;
Commit;
END;
```

Depending on the message level threshold set the profile option FND_API_MSG_LEVEL_THRESHOLD, the messages put on the message stack may contain both the error messages and the warnings.

AR DEPOSIT API PUB.insert non rev salescredit

This routine is called to assign nonrevenue sales credit to salespersons for a deposit. You can create as many of the nonrevenue credit assignments as you need.

This API routine has 4 output and 22 input parameters in total.

The following is the breakdown of the parameters:

Input

Standard API parameters: 4

Owners parameters: 22

Output

Standard API parameters: 3

Owners parameters: 0

Parameter Descriptions

The following table lists the API parameters.

Parameter	Туре	Data-type	Required	Default Value	Description
p_api_version	IN	NUMBER	Yes		Used to compare version numbers of incoming calls to its current version number. Unexpected error is raised if version incompatibility exists. In the current version of the API, you should pass in a value of 1.0 for this parameter.
p_init_msg_list	IN	VARCHAR 2		FND_API. G_FALSE	Allows API callers to request that the API does initialization of the message list on their behalf.
p_commit	IN	VARCHAR 2		FND_API. G_FALSE	Used by API callers to ask the API to commit on their behalf.
p_validation_lev el	IN	NUMBER		FND_API. G_VALID_LEVEL_ FULL	Not to be used currently as this is a public API.
x_return_status	OUT	VARCHAR 2			Represents the API overall return status.
x_msg_count	OUT	NUMBER			Number of messages in the API message list.
x_msg_data	OUT	VARCHAR 2			This is the message in encoded format if x_msg_count=1.

The following table lists the parameters relevant to the deposit.

Parameter	Туре	Data-type	Required	Description
p_deposit_number	IN	VARCHAR 2	Null	Deposit number, same as trx_number for the transaction number.
				Default: None
				Validation: Yes
				Error: N/A

Parameter	Туре	Data-type	Required	Description
p_customer_trx_id	IN	NUMBER		Customer_trx_id of the deposit created.
				Default: None
				Validation: Yes
				Error: N/A
p_salesrep_number	IN	NUMBER	Null	Salesperson number.
				Default: None
				Validation: Yes (same as customer contact).
				Error: N/A
p_salesrep_id	IN	NUMBER		Salesrep_id of the salesperson.
				Default: None
				Validation: Yes
				Error: N/A
p_non_revenue_amo unt_split	IN	NUMBER		Nonrevenue credit amount associated with salesperson.
				Default: None
				Validation: Yes
				Error: N/A
p_non_revenue_perc ent_split	IN	NUMBER		Nonrevenue credit percent associated with salesperson.
				Default: None
				Validation: Yes
				Error: N/A
p_attribute_category	IN	VARCHAR		Descriptive Flexfield structure defining column.
		2		Default: Null
				Validation: It should be a valid structure.
				Error: Null

Parameter	Туре	Data-type	Required	Description
p_attribute1 to	IN	VARCHAR		Descriptive Flexfield segment column.
p_attribute15 2		Default: Null		
				Validation: It should be a valid segment.
				Error: Validate_Desc_Flexfield

Example

Objective:

To create owner assignment using ar_deposit_api_pub.insert_non_rev_salescredit and passing a minimum number of Input parameters.

Entered parameters:

```
p_api_version
                 => 1.0 ,
p_init_msg_list => 'F',
,p_customer_trx_id => 'Valid Customer Trx ID, Must be a deposit'
,p_salesrep_id => -3 , means no Sales Rep
p_non_revenue_percent_split => 300
```

Before calling the APIs you should set up the application, responsibility and the user in the context of Oracle Application by calling the following FND API.

```
fnd_global.apps_initialize ( user_id =>'Your user id', resp_id => 'Your
Responsibility id', resp_appl_id => 'Your Application id');
```

For example:

```
fnd_global.apps_initialize ( user_id => 1318, resp_id => 50559,
resp_appl_id => 222);
```

The API call in this case would be:

```
DECLARE
1_return_status VARCHAR2(1);
l_msg_count NUMBER;
1_msg_data VAKCRAC
NUMBER;
               VARCHAR2(240);
BEGIN
fnd_global.apps_initialize ( user_id => 1318, resp_id => 50559,
resp_appl_id => 222);
  ar_deposit_api_pub.insert_non_rev_salescredit(
```

1. Standard API parameters.

```
p_api_version => 1.0,
              p_init_msg_list => FND_API.G_TRUE,
              p_commit
                               => FND_API.G_TRUE,
              p_validation_level => FND_API.G_VALID_LEVEL_FULL,
              x_return_status => l_return_status,
              p_customer_trx_id => ' Valid Customer Trx ID ,
Must be a deposit',
                             => -3,
               p_salesrep_id
              p_non_revenue_amount_split => 300);
        dbms_output.put_line('return status '||l_return_status);
        dbms_output.put_line('l_msg_count '||to_char
(l_msg_count));
IF l_msg_count = 1 Then
```

- There is one message raised by the API, so it has been sent out.
- In the parameter x_msg_data, get it.

```
dbms_output.put_line('l_msg_data '||l_msg_data);
ELSIF l_msg_count > 1 Then
```

- The messages on the stack are more than one, so call them in a loop.
- And print the messages.

```
LOOP
  IF nvl(l_count,0) < l_msg_count THEN</pre>
  l\_count := nvl(l\_count,0) +1 ;
  1_msg_data := FND_MSG_PUB.Get(FND_MSG_PUB.G_NEXT,FND_API.G_FALSE);
                   IF l_count = 1 THEN
                 dbms_output.put_line('l_msg_data 1 '||l_msg_data);
                   ELSIF 1_count = 2 THEN
                dbms_output.put_line('l_msg_data 2 '||l_msg_data);
                   ELSIF 1_count = 3 THEN
                dbms_output.put_line('l_msg_data 3 '||l_msg_data);
                   ELSIF l_count = 4 THEN
                dbms_output.put_line('l_msq_data 4 '||l_msq_data);
                   ELSIF 1_count = 5 THEN
                dbms_output.put_line('l_msg_data 5 '||l_msg_data);
                   ELSIF l_count = 6 THEN
                dbms_output.put_line('l_msg_data 6 '||l_msg_data);
                   END IF;
                dbms_output.put_line('l_msg_data '||to_char(l_count)
||': '||1_msq_data);
                  ELSE
                    EXIT;
                  END IF;
               END LOOP;
             END IF;
Commit;
END;
```

Depending on the message level threshold set the profile option FND_API_MSG_LEVEL_THRESHOLD, the messages put on the message stack may contain both the error messages and the warnings.

Messages

Messages play an important role in the effectiveness of your API calls. The right message is raised at the right point to convey to you the exact error that has occurred or any warnings that have been raised.

In the Commitment (Deposit) API, all error messages and warnings raised during the execution are put on the message stack and can be retrieved by the user as described in Exception Handling and Result Messages, page 1-3.

WARNINGS AND ERRORS

The following table contains the list of all the error messages raised by the Commitment (Deposit) API.

Message Number	Message Code	Message Text	Туре
294849	AR_DAPI_COMM_AMOUNT_NULL	The commitment amount requires a value.	Е
294850	AR_DAPI_CUS_LOC_INVALID	The customer location is invalid.	E
294851	AR_DAPI_CUS_SITE_DFT_INVALID	The customer site use ID could not be defaulted.	E
294852	AR_DAPI_CUS_CONTACT_INVALID	The customer contact is invalid.	E
294853	AR_DAPI_CUST_NULL	A value for the customer ID, name, or number is required.	E
294854	AR_DAPI_COMM_BATCH_INVALID	The batch name or ID is invalid.	E
294855	AR_DAPI_TRANS_TYPE_ID_INVALID	The transaction type ID is invalid.	E
294856	AR_DAPI_TRANS_TYPE_INVALID	The transaction type is invalid.	E
294857	AR_DAPI_TERM_NAME_INVALID	The term name is invalid.	E
294858	AR_DAPI_TERM_ID_INVALID	The term ID is invalid.	E
294859	AR_DAPI_SALESREP_NAME_INVALID	The sales representative name is invalid.	E
294860	AR_DAPI_SALESREP_ID_INVALID	The sales representative ID is invalid.	Е

Message Number	Message Code	Message Text	Туре
294861	AR_DAPI_BS_NAME_INVALID	The batch source name is invalid.	Е
294862	AR_DAPI_BS_ID_INVALID	The batch source ID is invalid.	E
	AR_DAPI_BS_NAME_IGN	The batch source name has been ignored.	W
294863	AR_DAPI_SOLD_CUST_NAME_INVALI D	The sold-to customer name is invalid.	E
294864	AR_DAPI_SOLD_CUST_COM_INVALID	The combination of sold-to customer name and number must be valid.	E
294865	AR_DAPI_PAY_CUST_NAME_INVALI D	The paying customer name is invalid.	E
	AR_DAPI_SOLD_CUST_DFT	The sold-to customer defaulted to the bill-to customer.	W
294866	AR_DAPI_PAY_CUST_COM_INVALID	The combination of paying customer name and number must be valid.	E
294867	AR_DAPI_PAY_CUST_NUM_INVALID	The paying customer number is invalid.	E
	AR_DAPI_CUS_NAME_NUM_IGN	The paying customer name and number have been ignored.	W
294868	AR_DAPI_PAY_CUST_ID_INVALID	The paying customer ID is invalid.	E
294869	AR_DAPI_SOLD_CUST_ID_INVALID	The sold-to customer ID is invalid.	E
	AR_DAPI_SOLD_CUS_IGN	The sold-to customer name and number have been ignored.	W
	AR_DAPI_PO_INVALID	The printing option is invalid.	E
294871	AR_DAPI_STATUS_TRX_INVALID	The transaction status is invalid.	E
294872	AR_DAPI_TAX_FLAG_INVALID	The default tax flag is invalid.	E
	AR_DAPI_NO_BATCH	A batch or a batch in the profile is required.	Е

Message Number	Message Code	Message Text	Туре
294874	AR_DAPI_MEMO_NAME_INVALID	The memo name is invalid.	Е
	AR_DAPI_MEMO_WRG	The memo ID, not the provided memo name, has been used.	W
	AR_DAPI_TRANS_TYPE_IGN	The type ID, not the provided type, has been used.	W
	AR_DAPI_INV_ID_INVALID	The inventory item ID is invalid.	E
	AR_DAPI_INV_MEMO_COM	Enter either a memo or inventory item ID.	E
294877	AR_DAPI_BILL_OR_SHIP_CUST_REQ	A bill-to or ship-to customer is required.	E
294878	AR_DAPI_BILL_CONTACT_NAME_IN V	Both a first and last name are required for the bill-to contact.	E
294879	AR_DAPI_SHIP_CONTACT_NAME_IN V	Both a first and last name are required for the ship-to contact.	E
	AR_DAPI_DEPOSIT_NO_NULL	A deposit number is required.	E
294881	AR_DAPI_FC_INVALID	The finance charges are invalid.	E
	AR_DAPI_LOC_SITE_NUM_IGN	The location site number has been ignored.	W
294882	AR_DAPI_REMIT_ADDR_ID_INVD	The remit-to address ID is invalid.	E
294883	AR_DAPI_CUST_LOC_SITE_NUM_INV	The customer location site number is invalid.	E
294884	AR_DAPI_REMIT_ADDRESS_DFT_ERR	The remit-to address did not successfully default.	E
294885	AR_DAPI_TRANS_TYPE_NULL	A value for either the transaction type or ID is required.	E
294886	AR_DAPI_BIII_CONTACT_COM_INV	The combination of the bill-to contact's first and last name must be valid.	E

Message Number	Message Code	Message Text	Туре
294887	AR_DAPI_SHIP_CONTACT_COM_INV	The combination of the ship-to contact's first and last name must be valid.	Е
294888	AR_DAPI_POST_COMMIT_ST	The deposit did not successfully post.	E
294889	AR_DAPI_INSERT_HEADER_ST	The header was not successfully inserted for the deposit.	E
	AR_DAPI_BILL_VAL_SHIP_IGN	The bill-to customer was defaulted from the ship-to customer because a value for the bill-to customer did not exist.	W
294890	AR_DAPI_LOC_INV	The location is invalid.	E
294891	AR_DAPI_SALESREP_ST	The salesperson was not successfully inserted for the deposit.	E
294892	AR_DAPI_SALESREP_NO_ID_NAME	The salesperson ID and name are required.	E
294893	AR_DAPI_NON_REV_AMT_PCT	A percentage or amount of nonrevenue sales credit is required.	E
294894	AR_DAPI_DEP_NO_ID_REQ	A deposit number or customer transaction ID is required.	
	AR_DAPI_DEP_NO_ING	The deposit number has been ignored.	W
294895	AR_DAPI_DEP_ID_INVALID	The customer transaction ID is invalid.	E
294896	AR_DAPI_DEP_NO_INVALID	The deposit number is invalid.	E
	AR_DAPI_REV_AMT_IGN	The nonrevenue sales credit amount has been ignored.	W

Invoice Creation API User Notes

Overview

This document outlines the use of Invoice Creation API. This API allows users to create an invoice using simple calls to PL/SQL functions.

The Invoice Creation API is not intended to replace the existing Transaction workbench, AutoInvoice, or the Transaction API program.

You can access this API in two ways:

- As standard PL/SQL servers-side routine calls
- Through Forms, utilizing the capability of Forms6 to have a procedure as its underlying base table

Modular Approach

To modularize the Invoice Creation API, the basic structure of the API is divided into four parts:

- Get all the default values from profiles and AR_SYSTEM_PARAMETERS table.
- Populate four global temporary tables for Header, Lines, Distributions and Sales Credits from PL/SQL tables and Default values (if user has not entered).
- Validate all the parameters entered by the user.
- Call the entity handlers to perform the relevant task (such as Create).

This results in easy to understand and easy to maintain code. Any new functionality can be added by a simple code plug-in at each of the four parts.

Debug Messages

The Invoice Creation API uses the Oracle Applications Logging Framework to log all debug messages in a central repository. Please query using module name, ar.plsql. InvoiceAPI.

The debugging can be enabled by the setting the following profile options:

- FND: Debug Log Enabled(AFLOG_ENABLED) to 'Y'.
- FND: Debug Log Level (AFLOG_LEVEL) to 'Statement'.

Once the above parameters are set, the message will be logged in the FND repository. The API to log accepts log level, module name, and the actual text.

An example is given below:

```
FND_LOG.STRING(P_LOG_LEVEL,P_MODULE_NAME, P_MESSAGE);
```

All Invoice Creation API debug messages use a module name of 'ar.plsql.InvoiceAPI'.

API Usage

To create an invoice, you can call the following PL/SQL APIs:

- AR_INVOICE_API_PUB.CREATE_INVOICE: Creates multiple invoices in a batch.
- AR_INVOICE_API_PUB.CREATE_SINGLE_INVOICE: Create a single invoice and return customer_trx_id.

See: AR_INVOICE_API_PUB, page 6-2.

AR INVOICE API PUB

The API contains 2 public procedures to create either a single invoice, or multiple invoices in batch mode. The input parameters are the same for both procedures and are explained in the following section.

Use the CREATE INVOICE procedure to create multiple invoices in a batch. The procedure returns a global record type structure which contains the batch_id to retrieve the necessary data from the transaction tables. The structure is defined in the package specification of ar_invoice_api_pub. Please refer to Example for Creating Multiple Invoices in a Batch, page 6-18 for usage.

```
TYPE api_outputs_type IS RECORD
batch_id NUMBER DEFAULT NULL
```

Use the CREATE_SINGLE_INVOICE procedure to create a single invoice. The procedure returns customer_trx_id as an out parameter, but the procedure does not create a batch for the single invoice. Please refer to Example for Creating a Single Invoice, page 6-21 for usage.

API Parameters

The API accepts the following parameters:

p_api_version	IN	NUMBER,
p_init_msg_list	IN	<pre>VARCHAR2 := FND_API.G_FALSE,</pre>
p_commit	IN	<pre>VARCHAR2 := FND_API.G_FALSE,</pre>
<pre>p_batch_source_rec</pre>	IN	<pre>batch_source_rec_type,</pre>
p_trx_header_tbl	IN	<pre>trx_header_tbl_type,</pre>
p_trx_lines_tbl	IN	<pre>trx_line_tbl_type,</pre>
p_trx_dist_tbl	IN	trx_dist_tbl_type,
p_trx_salescredits_tbl	IN	<pre>trx_salescredits_tbl_type,</pre>
<pre>p_trx_contingencies_tbl</pre>	IN	trx_contingencies_tbl_type
x_customer_trx_id	OUT NOCOPY	NUMBER,
x_return_status	OUT NOCOPY	VARCHAR2,
x_msg_count	OUT NOCOPY	NUMBER,
x_msg_data	OUT NOCOPY	VARCHAR2,

The following table shows the list of standard API parameters.

Parameter	Туре	Data Type	Required	Default Value	Description
p_api_version	IN	NUMBER	Yes	1.0	Compare version numbers of incoming calls to its current versions
p_init_msg_list	IN	VARCHAR2		FND_API. G_FALSE	Allow API callers to request that API does initialize the message list on their behalf.
p_commit	IN	VARCHAR2		FND_API. G_FALSE	Used by API callers to ask the API to commit on their behalf.
x_customer_trx_i d	OUT	NUMBER			Returns customer_trx_id in case it is called for creating a single invoice. This parameter works only with CREATE_SINGLE_INVOICE procedure.
x_return_status	OUT	VARCHAR2			Represent the API status.
x_msg_count	OUT	NUMBER			Number of messages in the PI message list (not used by this API).

Parameter	Туре	Data Type	Required	Default Value	Description
x_message_data	OUT	VARCHAR2			Message in case API encounters any unexpected error.

P_BATCH_SOURCE_REC Parameter

The P_BATCH_SOURCE_REC parameter is of PL/SQL record type, and has the following attributes, as described in this table:

Attribute Name	Data Type	Requir ed	Default Value	Description
batch_source_id	NUMBER		Null	If batch_source_id is null then value will be derived from AR_RA_BATCH_SOURCE profile option. In case the value is passed then it will be validated against ra_batch_sources. Only 'Manual' batch sources are allowed.
default_date	DATE		Null	If the value is null then Sysdate will be taken.

P_TRX_CONTINGENCIES_TBL Parameter

The P_TRX_CONTINGENCIES_TBL parameter is of PL/SQL table type TRX_CONTINGENCIES_REC_TYPE.

TRX_CONTINGENCIES_REC_TYPE has the following attributes, as described in this table:

Attribute Name	Data Type	Requir ed	Default Value	Description
trx_contingency_id	NUMBER			Unique identifier for each contingency on a line.
trx_line_id	NUMBER			Identifies rows in the user defined line table.
contingency_code	VARCHA R2(30)			Obsolete.
contingency_id	NUMBER			Identifies the actual revenue contingency being requested. Valid values are maintained in the AR_DEFERRAL_REASONS table.

Attribute Name	Data Type	Requir ed	Default Value	Description
expiration_event_dat e	DATE		NULL	Indicates the expiration of the contingency removal event. Normally defaulted by the API, the expiration_event_date is set as one of the following based on settings in AR_DEFERRAL_REASONS: transaction date, fulfillment date, ship confirm date, or proof of delivery date. However, you can override the default date.
expiration_days	NUMBER		NULL	The offset days that are added to the expiration_event_date to calculate the actual expiration_date.
expiration_date	DATE		NULL	The date on which a contingency is scheduled to expire (unless another event causes it to expire earlier). The actual expiration_date is calculated by adding the expiration_days to the expiration_event_date.
attribute_category	VARCHA R2(30)		NULL	Descriptive flexfield structure definition column.
attribute1 - 15	VARCHA R2 (150)		Null	Descriptive flexfield segment.
completed_flag	VARCHA R2(1)		'N'	Determines if the contingency is active or expired at the time of creation. If set to 'Y', then the contingency does not bar or withhold revenue from being recognized.
completed_by	NUMBER		NULL	User who completed the contingency.

P_TRX_HEADER_TBL Parameter

The P_TRX_HEADER_TBL parameter is of PL/SQL table type TRX_HEADER_REC_TYPE.

TRX_HEADER_REC_TYPE has the following attributes, as described in this table:

Attribute Name	Data Type	Require d	Default Value	Description
trx_header_id	NUMBER	Yes		Identifier for the Invoice header record. This must be unique for each record. This column can be generated based on a sequence or any number value. The value does not get recorded into any table.
trx_number	VARCHAR2 (30)		Null	This is the transaction number for the invoice. This field should not be populated if the batch source has Copy Document Sequence Number to Transaction Number checked or if Automatic Transaction Numbering is enabled.
trx_date	DATE		Null	Invoice Date. If no value is passed then p_batch_source_rec.default_date is used. If that too is not passed then sysdate is used.
gl_date	DATE		Null	General ledger Date. If no date is passed then p_batch_source_rec.default_date is used. If that too is not passed then sysdate is used.
trx_currency	VARCHAR2 (30)		Null	Transaction Currency. If not populated then ar_system_parameters is used to retrieve it. The currency if populated must be active as of the transaction date.
cust_trx_type_id	NUMBER		Null	Transaction Type Identifier. This can have any one of the following three values: 'INV', 'DM', or 'CM'. Validated against ra_cust_trx_types. If not populated, then it is retrieved from the batch source.
bill_to_customer_id	NUMBER	Yes		Bill To Customer ID. This must exist in hz_cust_accounts table. The customer must be an active ('A') customer. Validated against hz_cust_accounts.cust_account_id.
bill_to_account_num ber	VARCHAR2 (30)		Null	Bill To Customer Number. If both Bill To Customer ID and Bill To Customer Number are passed, then the former will take precedence. Validated against hz_cust_accounts.account_number.

Attribute Name	Data Type	Require d	Default Value	Description
bill_to_customer_na me	VARCHAR2 (260)		Null	Bill To Customer Name. If all three are passed, the precedence is as follows: Customer ID, Customer Number, then Customer Name.
bill_to_contact_id	NUMBER		Null	Bill To Customer Contact ID. This must exist for the Bill To Customer and Bill To Address combination.
bill_to_address_id	NUMBER		Null	Bill To Address ID. This must exist in hz_cust_acct_sites for the populated Bill To Customer ID
bill_to_site_use_id	NUMBER		Null	Bill To Site use ID. The site use ID must exist in combination with Ship To Customer ID, Ship To Address ID.
ship_to_customer_id	NUMBER			Ship To Customer ID. This must exist in hz_cust_accounts table.
ship_to_account_nu mber	VARCHAR2 (30)		Null	Ship To Customer Number. If both Bill To Customer ID and Ship To Customer Number are passed, then the former will take precedence.
ship_to_customer_n ame	VARCHAR2 (260)		Null	Ship To Customer Name. If all three are passed, the precedence is as follows: Customer ID, Customer Number, then Customer Name.
ship_to_contact_id	NUMBER		Null	Ship To Customer Contact ID. This must exist for the Ship To Customer and Ship To Address combination.
ship_to_address_id	NUMBER		Null	Ship To Address ID. This must exist in hz_cust_acct_sites for the populated Ship To Customer ID.
ship_to_site_use_id	NUMBER		Null	Ship To Site use ID. The site use ID must exist in combination with Ship To Customer ID, Ship To Address ID.
sold_to_customer_id	NUMBER		Null	Ship To Customer ID. This must exist in hz_cust_accounts table.

Attribute Name	Data Type	Require d	Default Value	Description
term_id	NUMBER		Null	Payment Terms Identifier. The Term ID must be valid for the transaction date. If not populated, then it is retrieved from ra_terms based on bill_to_customer_id and bill_to_site_use_id.
primary_salesrep_id	NUMBER		Null	Primary Salesrep ID. This is required if Salesperson check box is checked in the System Options form. If not populated, then it is derived based on bill-to_customer_id and bill_to_site_use_id.
primary_salesrep_na me	VARCHAR2 (240)		Null	Primary Salesrep name. If both salesrep ID and name are passed, then Salesrep ID will take precedence.
exchange_rate_type	VARCHAR2 (60)		Null	Exchange Rate Type. This must exist in gl_daily_conversion_types. Required if trx_currency is different from functional currency. If not populated, then it will derive from gl.
exchange_date	DATE		Null	Exchange Date. Required if trx_currency is different from functional currency. If not populated, then it will derive from gl.
exchange_rate	NUMBER		Null	Exchange Rate. This should be entered only if transaction currency is different from the functional currency and exchange rate type is 'User'.
territory_id	NUMBER		Null	Territory ID. If not populated, then it is defaulted based on the following hierarchy: The Bill To site use
				 The Ship To Site Use The Primary Salesrep's territory depending on the value of the DEFAULT_TERRITORY system option

Attribute Name	Data Type	Require d	Default Value	Description
remit_to_address_id	NUMBER		Null	Remit To Address ID. If not populated, then it is defaulted based on country, state, and postal code of bill_to_site_use_id. If populated, then validated against ar_active_remit_to_addresses_v.
invoicing_rule_id	NUMBER		Null	Invoicing Rule ID. Valid values are -2 and -3. If you enter a value here, then you must populate accounting rule for line type = 'LINE'.
printing_option	VARCHAR2 (20)		Null	Revenue Accounting lookup code for INVOICE_PRINT_OPTIONS. Valid codes are PRI - Print and NOT - Do not Print.
purchase_order	VARCHAR2 (50)		Null	Purchase Order Number for this transaction.
purchase_order_revi	VARCHAR2 (50)		Null	Purchase Order Revision. This must not be entered if purchase order is not populated.
purchase_order_date	DATE		Null	Purchase Order date. This must not be entered if purchase order is not populated.
comments	VARCHAR2 (240)		Null	Comments. Value can be printed on an invoice using the Print Invoice view.
internal_notes	VARCHAR2 (240)		Null	Stores the special instruction. Value can be printed on an invoice using the Print Invoice view.
finance_charges	VARCHAR2(1)		Null	Indicates if finance charges are included. Y for yes, N otherwise.

Attribute Name	Data Type	Require d	Default Value	Description
receipt_method_id	NUMBER		Null	This is the payment identifier for this transaction. If not populated, then it is defaulted based on the following hierarchy:
				1. Primary receipt method of parent primary bill to site
				2. Primary receipt method of the parent customer
				3. Primary receipt method of the bill to site
				4. Primary receipt method of the bill-to customer
related_customer_tr x_id	NUMBER		Null	Customer transaction ID of the document to which this transaction is related. Validated against ra_customer_trx_all.customer_trx_id. Not required for on-account credit memos.
agreement_id	NUMBER		Null	Customer Agreement identifier for this transaction. If not populated, then it will be defaulted from the commitment. Must exist in SO_AGREEMENTS. (For future use.)
ship_via	VARCHAR2 (30)		Null	Ship Via Code. If populated, then validated against org_freight.
ship_date_actual	DATE		Null	Ship Date
waybill_number	VARCHAR2 (50)		Null	Waybill Number
fob_point	VARCHAR2 (30)		Null	Free on Board Point. Validated against AR_LOOKUPS.LOOKUP_TYPE='FOB'.

Attribute Name	Data Type	Require d	Default Value	Description
customer_bank_acco unt_id	NUMBER		Null	Customer bank account ID. If the receipt method is Automatic, then it is required. If not populated, then it will be default using the following hierarchy.
				1. Primary bank account assigned to the primary site.
				2. Primary bank assigned to parent customer.
				3. Primary bank assigned to bill to site use.
				4. Primary bank assigned to bill to customer.
default_ussgl_transa ction_code	VARCHAR2 (30)		Null	Default value for the USSGL Transaction Code Flexfield (for future use)
status_trx	VARCHAR2 (30)		Null	The status of the transaction. If not populated, then defaulted from Transaction Type. Valid values are 'OP', 'CL', 'PEN', 'VD.
paying_customer_id	NUMBER		Null	This column is required when the RECEIPT_METHOD_ID column is an automatic receipt method.
paying_site_use_id	NUMBER		Null	This column is required when the RECEIPT_METHOD_ID column is an automatic receipt method.
doc_sequence_value	NUMBER(15)		Null	Document Number. Must not exist in Oracle Receivables.
attribute_category	VARCHAR2 (30)		Null	Descriptive flexfield structure definition column.
attribute1 - 10	VARCHAR2 (150)		Null	Descriptive flexfield segment.
global_attribute_cate gory	VARCHAR2 (30)		Null	Reserved for country-specific functionality. (For future use.)

Attribute Name	Data Type	Require d	Default Value	Description
global_attribute1-30	VARCHAR2 (150)		Null	Reserved for country-specific functionality. (For future use.)
interface_header_co ntext	VARCHAR2 (30)		Null	Interface header context.
interface_header_att ribute1 - 15	VARCHAR2 (30)		Null	Interface header attribute value.

P_TRX_LINES_TBL Parameter

The P_TRX_LINES_TBL parameter is of PL/SQL table type TRX_LINE_REC_TYPE. $TRX_LINE_REC_TYPE \ has the following \ attributes, \ as \ described \ in \ this \ table:$

Attribute Name	Data Type	Required	Default Value	Description
trx_header_id	NUMBER	Yes		Identifier for the Invoice header record. This column can be generated based on a sequence or any number value. The value does not get recorded into any table. This column ties back with P_TRX_HEADER_TBL.
trx_line_id	NUMBER	Yes		Identifier for the Invoice lines record. This column can be generated based on a sequence or any number value. The value does not get recorded into any table.
link_to_trx_line_id	NUMBER			This column is required only if line type is 'TAX' and 'FREIGHT' (if it is associated with any line).
line_number	NUMBER	Yes		Line number of the invoice
reason_code	VARCHAR2 (30)			Reason code. Validated against AR_LOOKUPS.LOOKUP_TYPE = 'INVOICING_REASON'.

Attribute Name	Data Type	Required	Default Value	Description
inventory_item_id	NUMBER			Inventory item identifier. Mutually exclusive with the column MEMO_LINE_ID. Validated against mtl_system_items.inventory_item_id and invoice_enabled_flag = 'Y'.
description	VARCHAR2 (240)			Line description. Required if inventory_item_id or memo_line_id is not provided.
quantity_ordered	NUMBER			Quantity of an order
quantity_invoiced	NUMBER			Quantity of invoice line. Required for Invoices.
unit_standard_price	NUMBER			List price per unit.
unit_selling_price	NUMBER			Selling price per unit for a transaction line. Required for Invoices.
sales_order	VARCHAR2 (50)			Sales order number for this transaction.
sales_order_line	VARCHAR2 (30)			Sales order line number for this transaction.
sales_order_date	DATE			Sales order date for this transaction.
accounting_rule_id	NUMBER			Accounting rule identifier. Must provide a value for invoice with Rule ID. Validated against RA_RULES.
line_type	VARCHAR2 (20)	Yes		Receivables lookup code for STD_LINE_TYPE.
attribute_category	VARCHAR2 (30)			Descriptive flexfield structure definition column.
attribute1-15	VARCHAR2 (150)			Descriptive flexfield segment.
rule_start_date	DATE			First GL date of the invoice. Only used for invoice with rules.

Attribute Name	Data Type	Required	Default Value	Description	
interface_line_contex t	VARCHAR2 (30)			Interface line context.	
interface_line_attrib ute1-15	VARCHAR2 (30)			Interface line attribute value.	
sales_order_source	VARCHAR2 (50)			The source of the sales order.	
amount	NUMBER			Transaction line revenue amount. If line type = 'FREIGHT' or 'TAX', then amount must be populated.	
tax_precedence	NUMBER			This column is obsolete and should not be populated.	
tax_rate	NUMBER			Tax rate for a line. Required for TAX line in case amount is not populated.	
memo_line_id	NUMBER			Memo line description identifier. Mutually exclusive with the column INVENTORY_ITEM_ID. Not required for 'TAX' and 'FREIGHT' lines.	
uom_code	VARCHAR2 (3)			Unit of measure code. Required for line type of 'LINE' and has a item on the line. Not required for 'TAX' and 'FREIGHT' lines.	
default_ussgl_transa ction_code	VARCHAR2 (30)			Default value for the USSGL Transaction Code Flexfield. (For future use.)	
default_ussgl_trx_co de_context	VARCHAR2 (30)			Default context value for the USSGL Transaction Code Flexfield. (For future use.)	
vat_tax_id	NUMBER			Unique identifier for AR_VAT_TAX. Required for 'TAX' Lines.	
tax_exempt_flag	VARCHAR2 (1)			Tax Lines are controlled by the lookup (TAX_CONTROL_FLAG), which allows for standard tax, exempt tax, and required tax.	

Attribute Name	Data Type	Required	Default Value	Description
tax_exempt_number	VARCHAR2 (80)			Exemption certificate number for item lines that have TAX_EXEMPT_FLAG set to E for exempt.
tax_exempt_reason_ code	VARCHAR2 (30)			Tax Exempt Reason, for item lines that have tax_exempt_flag set to "E" (exempt).
movement_id	NUMBER			Intrastate movement ID number that is tied to the shipment information.
global_attribute1-20 -20	VARCHAR2 (150)			Reserved for country-specific functionality. (For future use.)
global_attribute_cate gory	VARCHAR2 (30)			Reserved for country-specific functionality. (For future use.)
amount_includes_ta x_flag	VARCHAR2 (1)			Y indicates tax is inclusive. N indicates tax is exclusive. NULL for lines indicates tax cannot be overridden or tax is a tax group. Cannot be NULL for tax types. Must be NULL for other types.
warehouse_id	NUMBER			Foreign key to the HR_ORGANIZATIONS table. The warehouse identifies the ship-from location and can be used to control taxation. Within the US, the Warehouse ID is important when calculating tax on the origin/modified origin state sales tax. Outside the US you can use tax groups and conditions to build a schedule of multiple conditional taxes based on both the ship-from and ship-to county/county/state or provinces.
contract_line_id	NUMBER			Identifies the contract line from Oracle Contracts Core that is associated with this line.
source_data_key1-5	VARCHAR2 (150)			Identifies source data from original system.
invoiced_line_acctg_ level	VARCHAR2 (15)			Identifies accounting level for invoiceable lines in original system.

P_TRX_DIST_TBL Parameter

The P_TRX_DIST_TBL parameter is of PL/SQL table type TRX_DIST_REC_TYPE. TRX_DIST_REC_TYPE has the following attributes, as described in this table:

Attribute Name	Data Type	Require d	Default Value	Description
trx_line_id	NUMBER	Yes		Identifier for the Invoice lines record. This column can be generated based on a sequence or any number value. The value does not get recorded into any table.
trx_header_id	NUMBER			Identifier for the Invoice header record. This column can be generated based on a sequence or any number value. The value does not get recorded into any table. This column ties back with P_TRX_HEADER_TBL. Required in case of 'REC' distribution type.
trx_dist_id	NUMBER	Yes		Identifier for the Distribution record. This column can be generated based on a sequence or any number value. The value does not get recorded into any table.
account_class	VARCHAR2(20)	Yes		Account Class for this distribution. Freight, Receivable, Revenue, AutoInvoice Clearing, Tax, Unbilled Receivable, Unearned Revenue, or Charges account type.
amount	NUMBER			Amount of this record in the foreign currency. Required if percentage is not passed.
acctd_amount	NUMBER			Amount of this record in the functional currency. If not populated, then it will be populated based on amount passed.
percent	NUMBER			Percent of the line amount represented by this record. Required if amount is not passed.
code_combination_i d	NUMBER	Yes		Code combination ID for Accounting Flexfield. Validated against gl_code_combinations. code_combination_id.

Attribute Name	Data Type	Require d	Default Value	Description
attribute_category	VARCHAR2(30)			Descriptive flexfield structure definition column.
attribute1-15	VARCHAR2(150)			Descriptive flexfield segment.
comments	VARCHAR2(240)			Comment about the revenue distribution.

P_TRX_SALESCREDITS_TBL Parameter

The P_TRX_SALESCREDITS_TBL parameter is of PL/SQL table type TRX_SALESCREDITS_REC_TYPE.

TRX_ SALESCREDITS _REC_TYPE has the following attributes, as described in this table:

Attribute Name	Data Type	Required	Default Value	Description
trx_salescredit_id	NUMBER	Yes		Identifier for the Salesperson on the lines record. This column can be generated based on a sequence or any number value. The value does not get recorded into any table.
trx_line_id	NUMBER	Yes		Identifier for the Invoice lines record. This column can be generated based on a sequence or any number value. The value does not get recorded into any table.
salesrep_id	NUMBER	Yes		Identifies the salesperson for this sales credit assignment. Validated against ra_salesreps. salesrep_id.
salesrep_number	VARCHAR2 (30)			Salesrep Number assignment. Validated against ra_salesreps.salesrep_number. If both number and ID is passed, then ID will take precedence.
sales_credit_type_na me	VARCHAR2 (30)			Sales Credit Type Name. Validated against so_sales_credit_types.name.

Attribute Name	Data Type	Required	Default Value	Description
sales_credit_type_id	NUMBER	Yes		Sales Credit Type Identifier. Validated against so_sales_credit_types.sales_credit_type_id. If both ID and name are passed, then ID will take precedence.
salescredit_amount_ split	NUMBER			The amount of revenue/non-revenue credit for this salesperson/customer. Required if salescredit_percent_split is not passed.
salescredit_percent_s plit	NUMBER			The percent of revenue/non-revenue credit for this salesperson/customer. Required if salescredit_amount_split is not passed.
attribute_category	VARCHAR2 (30)			Descriptive flexfield structure definition column.
attribute1-15	VARCHAR2 (150)			Descriptive flexfield segment.

Example for Creating Multiple Invoices in a Batch Objective:

To create an Invoice using a call to ar_invoice_api_pub.Create_invoice and passing a minimum number of Input parameters.

1. DECLARE

```
l_return_status
                      varchar2(1);
l_msg_count
                      number;
                      varchar2(2000);
l_msg_data
l_batch_id
                       number;
l_batch_source_rec
                      ar_invoice_api_pub.batch_source_rec_type;
l_trx_header_tbl
                       ar_invoice_api_pub.trx_header_tbl_type;
l_trx_lines_tbl
                       ar_invoice_api_pub.trx_line_tbl_type;
l_trx_dist_tbl
                       ar_invoice_api_pub.trx_dist_tbl_type;
l_trx_salescredits_tbl ar_invoice_api_pub.
trx_salescredits_tbl_type;
CURSOR cBatch IS
       select customer_trx_id
       from ra_customer_trx_all
       where batch_id = l_batch_id;
CURSOR cValidTxn IS
       SELECT trx_header_id
       From ar_trx_header_gt
       WHERE trx_header_id not in (
             SELECT trx_header_id
             FROM ar_trx_errors_gt);
```

BEGIN

1. Set applications context if not already set.

```
fnd_global.apps_initialize(1318, 50559, 222,0);
```

2. Populate header information.

```
l_trx_header_tbl(1).trx_header_id := 101;
l_trx_header_tbl(1).trx_number := 'Test Invoice API';
l_trx_header_tbl(1).bill_to_customer_id := 1006;
l_trx_header_tbl(1).cust_trx_type_id := 2376;
```

3. Populate batch source information.

```
l_batch_source_rec.batch_source_id := 1188;
```

4. Populate line 1 information.

```
l_trx_lines_tbl(1).trx_header_id := 101;
l_trx_lines_tbl(1).trx_line_id := 101;
l_trx_lines_tbl(1).line_number := 1;
l_trx_lines_tbl(1).memo_line_id := 8;
l_trx_lines_tbl(1).quantity_invoiced := 10;
l_trx_lines_tbl(1).unit_selling_price := 12;
l_trx_lines_tbl(1).line_type := 'LINE';
```

5. Populate line 2 information.

```
l_trx_lines_tbl(2).trx_header_id := 101;
l_trx_lines_tbl(2).trx_line_id := 102;
l_trx_lines_tbl(2).line_number := 2;
l_trx_lines_tbl(2).description := 'Test';
l_trx_lines_tbl(2).quantity_invoiced := 12;
l_trx_lines_tbl(2).unit_selling_price := 12;
l_trx_lines_tbl(2).line_type := 'LINE';
```

6. Populate freight information and link it to line 1.

```
l_trx_lines_tbl(3).trx_header_id := 101;
l_trx_lines_tbl(3).trx_line_id := 103;
l_trx_lines_tbl(3).link_to_trx_line_id := 101;
l_trx_lines_tbl(3).line_number := 1;
l_trx_lines_tbl(3).line_type := 'FREIGHT';
l_trx_lines_tbl(3). amount := 25;
```

7. Call the invoice api to create multiple invoices in a batch.

```
AR_INVOICE_API_PUB.create_invoice(
 x_return_status => l_return_status,
x_msq_count => l_msg_count,
 x_msg_data
                      => l_msg_data);
IF l_return_status = fnd_api.g_ret_sts_error OR
  l_return_status = fnd_api.g_ret_sts_unexp_error THEN
  dbms_output.put_line('unexpected errors found!');
ELSE
```

8. Check if there are record exist in error table. If no records exist for a trx_header_id, then only Invoice will create in the system; otherwise not.

```
For cValidTxnRec IN cvalidTxn
loop
       IF (ar_invoice_api_pub.g_api_outputs.batch_id IS NOT NULL)
THEN
       dbms_output.put_line('Invoice(s) successfully created!') ;
       dbms_output.put_line('Batch ID: ' || ar_invoice_api_pub.
q_api_outputs.batch_id);
       l_batch_id := ar_invoice_api_pub.g_api_outputs.batch_id;
```

To see all customer_trx_id for this batch:

```
for cBatchRec in cBatch
    loop
        dbms_output.put_line ( 'Cust Trx Id '|| cBatchRec.
customer_trx_id );
    end loop;
       dbms_output.put_line('Errors found!');
      END IF;
   End loop;
   END IF;
END;
```

10. See all the validation errors.

```
SET LINESIZE 200
COLUMN trx_header_id HEADING 'Header ID'
COLUMN trx_line_id HEADING 'Line ID'
COLUMN error_message HEADING 'Message'
COLUMN invalid_value HEADING 'Invalid Value'
COLUMN trx_header_id FORMAT 9999999
COLUMN trx_line_id FORMAT 9999999
COLUMN error_message FORMAT a30
COLUMN invalid_value FORMAT a20
SELECT trx_header_id, trx_line_id, error_message, invalid_value
FROM ar_trx_errors_gt;
```

Example for Creating a Single Invoice

Objective:

To create an Invoice using a call to ar_invoice_api_pub.Create_invoice and passing a minimum number of Input parameters.

1. DECLARE

```
l_return_status varchar number;
                          varchar2(1);
l_msg_count number;
l_msg_data varchar2(2000);
l_batch_id number;
number := 0;
1_cnt
l_batch_source_rec ar_invoice_api_pub.batch_source_rec_type;
l_trx_header_tbl ar_invoice_api_pub.trx_header_tbl_type;
l_trx_dist_tbl ar_invoice_api_pub.trx_dist_tbl_type;
l_trx_salescredits_tbl ar_invoice_api_pub.
l_customer_trx_id number;
```

2. BEGIN

Set applications context if not already set.

```
fnd_global.apps_initialize(1318, 50559, 222,0);
```

2. Populate header information.

```
l_trx_header_tbl(1).trx_header_id := 101;
l_trx_header_tbl(1).trx_number := 'Test Invoice API';
l_trx_header_tbl(1).bill_to_customer_id := 1006;
l_trx_header_tbl(1).cust_trx_type_id := 2376;
```

3. Populate batch source information.

```
l_batch_source_rec.batch_source_id := 1188;
```

Populate line 1 information.

```
l_trx_lines_tbl(1).trx_header_id := 101;
l_trx_lines_tbl(1).trx_line_id := 101;
l_trx_lines_tbl(1).line_number := 1;
l_trx_lines_tbl(1).memo_line_id := 8;
l_trx_lines_tbl(1).quantity_invoiced := 10;
l_trx_lines_tbl(1).unit_selling_price := 12;
l_trx_lines_tbl(1).line_type := 'LINE';
```

5. Populate line 2 information.

```
l_trx_lines_tbl(2).trx_header_id := 101;
l_trx_lines_tbl(2).trx_line_id := 102;
l_trx_lines_tbl(2).line_number := 2;
l_trx_lines_tbl(2).description := 'Test';
l_trx_lines_tbl(2).quantity_invoiced := 12;
l_trx_lines_tbl(2).unit_selling_price := 12;
l_trx_lines_tbl(2).line_type := 'LINE';
```

6. Populate freight information and link it to line 1.

```
l_trx_lines_tbl(3).trx_header_id := 101;
l_trx_lines_tbl(3).trx_line_id := 103;
l_trx_lines_tbl(3).link_to_trx_line_id := 101;
l_trx_lines_tbl(3).line_number := 1;
l_trx_lines_tbl(3).line_type := 'FREIGHT';
l_trx_lines_tbl(3). amount := 25;
```

7. Call the invoice api to create multiple invoices in a batch.

```
AR_INVOICE_API_PUB.create_single_invoice(
 p_trx_salescredits_tbl => l_trx_salescredits_tbl,
 x_customer_trx_id => l_customer_trx_id,
x_return_status => l_return_status,
x_msg_count => l_msg_count,
x_msg_dota
  x_msg_data
                          => l_msg_data);
IF l_return_status = fnd_api.g_ret_sts_error OR
   l_return_status = fnd_api.g_ret_sts_unexp_error THEN
  dbms_output.put_line('unexpected errors found!');
ELSE
```

8. Check whether any record exist in error table

```
SELECT count(*)
Into
         cnt
From ar_trx_errors_gt;
IF cnt = 0
dbms_output.put_line ( 'Customer Trx id '|| l_customer_trx_id);
ELSE
dbms_output.put_line ( 'Transaction not Created, Please check
ar_trx_errors_gt table');
END IF;
END;
```

9. See all the validation errors.

```
SET LINESIZE 200
COLUMN trx_header_id HEADING 'Header ID'
COLUMN trx_line_id HEADING 'Line ID'
COLUMN error_message HEADING 'Message'
COLUMN invalid_value HEADING 'Invalid Value'
COLUMN trx_header_id FORMAT 9999999
COLUMN trx_line_id FORMAT 9999999
COLUMN error_message FORMAT a30
COLUMN invalid_value FORMAT a20
SELECT trx_header_id, trx_line_id, error_message, invalid_value
FROM ar_trx_errors_gt;
```

Note: In the above examples, we did not pass distribution, sales credits, or contingencies . Note, however, that you can create an invoice passing distributions, sales credits, and contingencies.

Prepayments API User Notes

Overview

This document outlines the specifications and the methodology for using the Prepayments API.

Use the Prepayments API to:

- Generate a unique payment grouping identifier (payment_set_id)
- Create a prepayment receipt flagged with this payment_set_id
- Apply the prepayment receipt to a receivable activity of type Prepayment

You can access this API:

- As standard PL/SQL server-side routine calls
- Through forms, utilizing the capability of Forms6 to have a procedure as its underlying base table

Basic Business Needs

The Prepayments API addresses the following business needs:

- Enables the creation of a receipt in advance of the invoicing event
- Provides a mechanism of matching a prepayment receipt to a prepaid invoice

The Prepayments API lets you model down payments, deposits, or prepayments as receipts created in Oracle Receivables in advance of the invoice creation event.

It is not intended for the purpose of creating receipts for existing invoices, simply before the invoices.

API Usage

This section describes how to use the Prepayments API to:

- Create a prepayment receipt
- Apply the prepayment receipt to the prepayment activity
- Calculate the amount of all the installments of a particular payment term

To create, apply, and refund a prepayment receipt, you can call the following PL/SQL routine:

- AR_PREPAYMENTS_PUB.Create_Prepayment, page 7-2: Use this routine to create a prepayment receipt.
- AR_PREPAYMENTS_PUB.Get_Installment, page 7-9: Use this routine to calculate the amount of all installments of a given payment term.

AR_PREPAYMENTS_PUB.Create_Prepayment

This routine is called to create a prepayment receipt.

This API routine has 5 output, 8 input-output, and 56 input parameters. Of the output parameters, the API returns 5.

Input

Standard API parameters: 4

Prepayment parameters: 48 + 8 (INOUT) parameters

4 (global descriptive flexfield parameters)

Output

Standard API parameters: 3

Prepayment parameters: 2 + 8 (INOUT) parameters

Parameter Descriptions

The input descriptive flexfield parameter is a record of type *attribute_rec_type*.

```
TYPE attribute_rec_type IS RECORD(
      attribute1
      VARCHAR2(150) DEFAULT NULL,
                                  VARCHAR2(150) DEFAULT NULL,
      attribute3
                               VARCHAR2(150) DEFAULT NULL,
                               VARCHAR2(150) DEFAULT NULL,
      attribute4
                         VARCHAR2(150) DEFAULT NULL,
      attribute5
      attribute6
attribute7
      attribute8
      attribute9
      attribute10
      attribute11
                                 VARCHAR2(150) DEFAULT NULL,
      attribute12
                                 VARCHAR2(150) DEFAULT NULL,
      attribute13
                                VARCHAR2(150) DEFAULT NULL,
      attribute14
                                VARCHAR2(150) DEFAULT NULL,
                                 VARCHAR2(150) DEFAULT NULL);
      attribute15
```

The input global descriptive flexfield parameter is a record of type *global_attr_rec_type*.

```
TYPE global_attribute_rec_type IS RECORD(
                                  VARCHAR2(30) default null,
     global_attribute_category
     global_attribute1
                                   VARCHAR2(150) default NULL,
     global_attribute2
                                  VARCHAR2(150) DEFAULT NULL,
     global_attribute3
                                  VARCHAR2(150) DEFAULT NULL,
     global_attribute4
                                  VARCHAR2(150) DEFAULT NULL,
                                  VARCHAR2(150) DEFAULT NULL,
    global_attribute5
    global_attribute6
                                  VARCHAR2(150) DEFAULT NULL,
     global_attribute7
                                  VARCHAR2(150) DEFAULT NULL,
     global_attribute8
                                  VARCHAR2(150) DEFAULT NULL,
                                  VARCHAR2(150) DEFAULT NULL,
     global_attribute9
    global_attribute10
                                  VARCHAR2(150) DEFAULT NULL,
    global_attribute11
                                  VARCHAR2(150) DEFAULT NULL,
                                  VARCHAR2(150) DEFAULT NULL,
     global_attribute12
     global_attribute13
                                  VARCHAR2(150) DEFAULT NULL,
                                  VARCHAR2(150) DEFAULT NULL,
     global_attribute14
    global_attribute15
                                  VARCHAR2(150) DEFAULT NULL,
     global_attribute16
                                  VARCHAR2(150) DEFAULT NULL,
     global_attribute17
                                  VARCHAR2(150) DEFAULT NULL,
     global_attribute18
                                  VARCHAR2(150) DEFAULT NULL,
                                  VARCHAR2(150) DEFAULT NULL,
     global_attribute19
                                  VARCHAR2(150) DEFAULT NULL);
     global_attribute20
```

The following table lists the parameters that pertain specifically to the Create Prepayment routine:

Parameter	Туре	Mandatory/Op tional	Data-type	Default Value	Description
p_api_version	IN	M	NUMBER		Constant 1.0
p_init_msg_list	IN	О	VARCHAR2		Default FND_API.G_FALSE
p_commit	IN	0	VARCHAR2		Default FND_API.G_FALSE
p_validation_lev el	IN	O	NUMBER		Default FND_API. G_VALID_LEVEL_FULL

Parameter	Туре	Mandatory/Op tional	Data-type	Default Value	Description
x_return_status	OUT	M	VARCHAR2		Return status of the prepayment call
x_msg_count	OUT	M	NUMBER		Message counts in message stack
x_msg_data	OUT	M	VARCHAR2		Message text in message stack.
p_usr_currency_ code	IN	0	VARCHAR2		Translated currency code
p_currency_code	IN	M	VARCHAR2		Currency of the receipt
p_usr_exchange_ rate_type	IN	O	VARCHAR2		User exchange rate type
p_exchange_rate _type	IN	0	VARCHAR2		Exchange rate type, if other than functional currency (if functional currency is different than receipt)
p_exchange_rate _date	IN	0	DATE		Exchange rate date
p_exchange_rate	IN	0	NUMBER		Exchange rate
p_amount	IN	M	NUMBER		Receipt amount
p_factor_discoun t_amount	IN	O	NUMBER		Factor discount amount
p_receipt_numb er	INO UT	0	VARCHAR2		Receipt number, need to pass if doc sequence is not enabled
p_receipt_date	IN	О	DATE		Receipt creation Date
p_gl_date	IN	О	DATE		GL date of the receipt
p_maturity_date	IN	О	DATE		Maturity date of the receipt
p_postmark_dat e	IN	О	DATE		Postmark date of receipt

Parameter	Туре	Mandatory/Op tional	Data-type	Default Value	Description
p_customer_id	IN	M	NUMBER		Customer ID of the receipt
p_customer_nam e	IN	0	VARCHAR2		Customer Name
p_customer_nu mber	IN	0	NUMBER		Customer Number
p_customer_ban k_account_id	IN	M	NUMBER		Customer bank account ID
p_customer_ban k_account_num	IN	O	VARCHAR2		Customer bank account number
p_customer_ban k_account_name	IN	O	VARCHAR2		Customer bank account name
p_location	IN	О	VARCHAR2		Location
p_customer_site _use_id	IN	M	NUMBER		Site use ID
p_customer_rece ipt_reference	IN	0	VARCHAR2		Reference information on receipt header
p_override_remi t_account_flag	IN	0	VARCHAR2		Remittance account override flag
p_remittance_ba nk_account_id	IN	M	VARCHAR2		Remittance bank account ID
p_remittance_ba nk_account_num	IN	O	VARCHAR2		Remittance bank account number
p_remittance_ba nk_account_nam e	IN	0	VARCHAR2		Remittance bank account name
p_deposit_date	IN	O	DATE		Deposit date

Parameter	Туре	Mandatory/Op tional	Data-type	Default Value	Description
p_receipt_metho d_id	IN	M	NUMBER		Remittance method ID (receipt method)
p_receipt_metho d_name	IN	O	VARCHAR2		Receipt method name
p_doc_sequence _value	IN	0	NUMBER		Doc sequence value, if doc sequence is enabled (mandatory if doc sequence is enabled)
p_ussgl_transaction_code	IN	0	NUMBER		USSGL transaction code, if exists, on receipt header
p_anticipated_cl earing_date	IN	0	DATE		Anticipated receipt clearing date
p_called_from	IN	M	NUMBER		Which program called this routine?
p_attribute_rec	IN	0	RECORD TYPE		Receipt Header attributes
p_global_attribut e_rec	IN	O	RECORD TYPE		Global attributes on receipt header (GDF)
p_receipt_comm ents	IN	O	VARCHAR2		Receipt header comments
p_issuer_name	IN	О	VARCHAR2		AR Notes Issuer name
p_issue_date	IN	О	DATE		AR Notes Issue Date
p_issuer_bank_b ranch_id	IN	0	NUMBER		AR Notes Issuer bank branch ID
p_cr_id	OUT	M	NUMBER		Cash receipt ID
p_applied_paym ent_schedule_id	IN	M	NUMBER		For prepayment, it will be -7
p_amount_appli ed	IN	0	NUMBER		Specify amount which needs to be put in prepayment out of the receipt amount

Parameter	Туре	Mandatory/Op tional	Data-type	Default Value	Description
p_application_re f_type	IN	0	VARCHAR2		Prepayment application reference from a lookup code for lookup type AR_PREPAYMENT_TYPE to indicate where it is created from. For example, OM.
p_application_re f_id	IN OUT	M	NUMBER		Application reference ID. For example, order ID.
p_application_re f_num	IN OUT	M	VARCHAR2		Reference number. For example, order number.
p_secondary_ap plication_ref_id	IN OUT	O	NUMBER		Additional reference, if exists
p_receivable_trx _id	IN	O	NUMBER		Receivable activity ID, default if not passed for prepayment.
p_amount_appli ed_from	IN	0	NUMBER		Amount applied in functional currency
p_apply_date	IN	0	DATE		If null, takes sysdate
p_apply_gl_date	IN	O	DATE		Application GL date
app_ussgl_trans action_code	IN	O	VARCHAR2		USSGL transaction type code on application
p_show_closed_i nvoices	IN	O	VARCHAR2		Default FALSE
p_move_deferre d_tax	IN	O	VARCHAR2		Default Y
app_attribute_re	IN	0	RECORD TYPE		Application attributes
app_global_attri bute_rec	IN	O	RECORD TYPE		Global application attributes (GDF)
app_comments	IN	O	VARCHAR2		comments on application

Parameter	Туре	Mandatory/Op tional	Data-type	Default Value	Description
p_payment_serv er_order_num	IN OUT	M	VARCHAR2		Payment server order number
p_call_payment_ processor	IN	О	VARCHAR2		Decides whether to call Oracle Payments. DEFAULT FND_API. G_FALSE
p_payment_resp onse_error_code	IN OUT	M	VARCHAR2		Oracle Payments return error code
p_approval_cod e	IN OUT	M	VARCHAR2		Credit Card Approval code
p_receivable_ap plication_id	OUT	M	NUMBER		Receivable applications ID of the application
p_payment_set_i d	IN OUT	M	NUMBER		If passed, it will take the passed payment_set_id while creating prepayment application. Otherwise, generate a new number and pass it back.

Example

The following is a test case for creating a prepayment.

Objective:

To create a prepayment, passing the minimum number of parameters.

Entered parameters:

- p_api_version
- p_currency_code
- p_amount
- p_customer_id
- p_customer_bank_account_id
- p_customer_site_use_id

- p_remittance_bank_account_id
- p_receipt_method_id
- p_called_from
- p_applied_payment_schedule_id
- p_application_ref_id
- p_application_ref_num

The API call in this case would be:

```
AR_PREPAYMENTS_PUB.create_prepayment(
    p_customer_site_use_id => l_site_use_id,
    p_customer_bank_account_id => p_bank_account_id,
    p_applied_payment_schedule_id => p_payment_schedule_id,
    p_application_ref_type => l_application_ref_type , --Order type
    p_application_ref_num => l_application_ref_num, --Order Number
    p_application_ref_id => l_application_ref_id, --Order Id
p_cr_id => l_cr_id --OUT,
    p_receivable_application_id => l_receivable_application_id --OUT
p_call_payment_processor => l_call_payment_processor
    p_payment_response_error_code => l_payment_response_error_code
    p_payment_set_id => l_payment_set_id -If not passed generate a new
number
```

AR PREPAYMENTS PUB.Get Installment

This routine is called to calculate the amount of all installments of a given payment

This API routine has 4 output and 5 input parameters. Of the output parameters, the API returns 5.

Input

Standard API parameters: 0

Prepayment parameters: 5

Output

Standard API parameters: 3

Prepayment parameters: 1

Parameter Descriptions

The following table lists the parameters that pertain specifically to the Get Installment routine:

Parameter	Туре	Mandatory/O ptional	Data-Type	Default Value	Details
p_term_id	IN	M	NUMBER		Payment term ID
p_amount	IN	M	NUMBER		Line amount and additional charges (if any)
p_tax	IN	O	NUMBER		Tax amount
p_freight	IN	O	NUMBER		Freight charges
p_currency_code	IN	M	VARCHAR2		Currency code for calculating the installment amount
p_installment_tb	OUT	O	NUMBER		A table consisting of installment number and installment amount
x_return_status	OUT	M	VARCHAR2		Return status of the API call
x_msg_count	OUT	M	NUMBER		Message counts in message stack
x_msg_data	OUT	M	VARCHAR2		Message text in message stack.

Example

The following is a test case for get_installment.

Objective:

To get the installment amount given an amount, payment term and currency code.

Entered parameters:

p_term_id

- p_amount
- p_currency_code

```
AR_PREPAYMENTS_PUB.get_installment(
     p_currency_code => l_currency_code,
     p_installment_tbl => l_installment_tbl , --OUT
    x_return_status => x_return_status,
x_msg_count => x_msg_count,
x_msg_data => x_msg_data);
```

Messages

Messages play an important role in the effectiveness of your API calls. The right message is raised at the right point to convey to you the exact error that has occurred or any warnings that have been raised.

In the Prepayments API, all error messages and warnings raised during the execution are put on the message stack and can be retrieved by the user as described in Robust Validation, page 1-2.

The following is the list of all error messages raised by the Prepayments API.

Message Number	Message Name	Message Description
96735	AR_RAPI_CUS_BK_AC_2_INVALID	Invalid combination of customer bank account name and number.
294347	AR_RAPI_PREPAY_SEQ_FAILED	The prepayment sequence generation has failed. Please contact your system administrator.
	AR_PPAY_PAY_TERM_INVALID	Payment term ID is invalid.
	AR_PPAY_BASE_AMOUNT_INVALID	The amount can not be null, 0, or negative.
96734	AR_RAPI_CURR_CODE_INVALID	Currency code is invalid.

Since this API also calls the Receipt API AR_RECEIPT_API_PUB, it could also throw messages raised by the Receipt API.

Please refer to messages listed in Receipt API Messages, page 8-136.

Receipt API User Notes

Overview

This document outlines the specifications and the methodology for using the various Receipt APIs. These APIs provide an extension to existing functionality of creating and manipulating receipts through standard AR Receipts forms and lockboxes.

You can access these APIs:

- As standard PL/SQL server-side routine calls
- Through forms, utilizing the capability of Forms6 to have a procedure as its underlying base table

Basic Business Needs

The Receipt API provides the following basic functionality via different API calls:

- Creating a cash receipt
- Applying a cash receipt to a debit item
- Creating a cash receipt and applying it to a debit item in one pass
- On-account application
- Unapplying the on-account application
- Unapplying the receipt application to a particular transaction
- Reversing the receipt
- Activity application, such as Receipt Write-off

- Creating a miscellaneous receipt
- Other account application, such as Claim Investigation
- Receipt-to-receipt application
- Creating a cash receipt and an on-account application in one pass

Integration with Oracle Payments

The following table illustrates the integration between Oracle Payments and the Receipt API routines that create receipts:

Receipt API Routine	Calls Oracle Payments?
Ar_receipt_api_pub.Create_cash	No
Ar_receipt_api_pub.Create_and_apply	Yes
Ar_receipt_api_pub.Create_misc	No
Ar_receipt_api_pub.Create_apply_on_acc	Yes

API Usage

To create, apply, unapply, or reverse a cash receipt, you can call the following PL/SQL APIs:

- Ar_receipt_api_pub.Create_cash, page 8-3: Creates a single cash receipt, as in the case of manually created cash receipts.
- Ar_receipt_api_pub.Apply, page 8-20: Applies a cash receipt to a particular installment of a debit item. The application can also be a cross currency application.
- Ar_receipt_api_pub.Create_and_apply, page 8-34: Creates a cash receipt and applies it to a specified installment of a debit item in one pass. Application fails if the creation fails due to some reason.
- Ar_receipt_api_pub.Unapply, page 8-54: Unapplies the application of a particular installment of a debit item against the specified cash receipt.
- Ar_receipt_api_pub.Apply_on_account, page 8-60: Creates an on-account application for a cash receipt.

- Ar_receipt_api_pub.Unapply_on_account, page 8-65: Unapplies the on-account application on the specified receipt.
- Ar_receipt_api_pub.Reverse, page 8-69: Reverses the specified receipt.
- Ar_receipt_api_pub.activity_application, page 8-74: Applies to an activity, such as Receipt Write-off.
- Ar_receipt_api_pub.activity_unapplication, page 8-82: Unapplies from an activity, such as a Receipt Write-off.
- Ar_receipt_api_pub.Create_misc, page 8-86: Creates a single miscellaneous receipt.
- Ar_receipt_api_pub.apply_other_account, page 8-100: Applies to other account activities, such as Claim Investigation (for Trade Management customers only).
- Ar_receipt_api_pub.unapply_other_account, page 8-107: Unapplies from other account activities, such as Claim Investigation.
- Ar_receipt_api_pub.apply_open_receipt, page 8-111: Creates a receipt-to-receipt application (payment netting).
- Ar_receipt_api_pub.unapply_open_receipt, page 8-118: Unapplies a receipt-toreceipt application.
- Ar_receipt_api_pub.Create_apply_on_acc, page 8-120: Creates a cash receipt and an on-account application in one pass. If the receipt creation fails, then the application fails as well.

Ar receipt api pub.Create cash

This routine is called to create cash receipts for the payment received in the form of a check or cash. Cash receipts can be created as identified (with a customer) or as unidentified (without a customer).

Note: This routine does *not* call Oracle Payments directly. See Integration with Oracle Payments, page 8-2.

This API routine has 4 output and 47 input parameters in total. As one of the output parameters, the API returns the cash_receipt_id of the cash receipt created. The following is the breakdown of the parameters:

Input

Standard API parameters: 4

Cash Receipt parameters: 41 + 1 (descriptive flexfield parameter)

+ 1 (global descriptive flexfield parameter)

Output

Standard API parameters: 3 Cash Receipt parameters: 1

Parameter Descriptions

The input descriptive flexfield parameter is a record of type *attribute_rec_type*.

```
E attribute_rec_type IS RECORD

(p_attribute_category p_attribute1 IN VARCHAR2, p_attribute2 IN VARCHAR2, p_attribute3 IN VARCHAR2, p_attribute4 IN VARCHAR2, p_attribute5 IN VARCHAR2, p_attribute6 IN VARCHAR2, p_attribute7 IN VARCHAR2, p_attribute8 IN VARCHAR2, p_attribute9 IN VARCHAR2, p_attribute10 IN VARCHAR2, p_attribute11 IN VARCHAR2, p_attribute12 IN VARCHAR2, p_attribute13 IN VARCHAR2, p_attribute14 IN VARCHAR2, p_attribute14 IN VARCHAR2, p_attribute15 IN VARCHAR2, in VARCHAR2, p_attribute15 IN VARCHAR2, in VARCHAR2);
TYPE attribute_rec_type IS RECORD
```

The input global descriptive flexfield parameter is a record of type global_ attribute_rec_type.

```
TYPE global_attribute_rec_type IS RECORD
                                                                 (p_global_attribute_rec_type IS NEOND
p_global_attribute1
p_global_attribute1
p_global_attribute2
IN VARCHAR2,
p_global_attribute3
IN VARCHAR2,
p_global_attribute4
p_global_attribute5
p_global_attribute6
p_global_attribute7
p_global_attribute8
p_global_attribute9
p_global_attribute10
p_global_attribute11
p_global_attribute12
p_global_attribute12
p_global_attribute13
p_global_attribute14
p_global_attribute15
p_global_attribute15
p_global_attribute16
p_global_attribute12
p_global_attribute15
p_global_attribute15
p_global_attribute15
p_global_attribute16
p_global_attribute16
p_global_attribute17
p_global_attribute18
p_global_attribute19
p_global_attribute19
p_global_attribute19
p_global_attribute20
IN VARCHAR2,
p_global_attribute19
p_global_attribute20
IN VARCHAR2);

fellowing table lists standard ADI parameters that are secondary and account to the area of the content to the content to the area of the content to the content 
                                                                   (p_global_attribute_category IN VARCHAR2,
```

The following table lists standard API parameters that are common to all the routines in the Receipt API.

Parameter	Typ e	Data-type	Require d	Default Value	Description
p_api_version	IN	NUMBER	Yes		Used to compare version numbers of incoming calls to its current version number. Unexpected error is raised if version incompatibility exists. In the current version of the API, you should pass in a value of 1.0 for this parameter.
p_init_msg_list	IN	VARCHAR 2		FND_API. G_FALSE	Allows API callers to request that the API does initialization of the message list on their behalf.
p_commit	IN	VARCHAR 2		FND_API. G_FALSE	Used by API callers to ask the API to commit on their behalf.
p_validation_lev el	IN	NUMBER		FND_API. G_VALID_LEVEL _FULL	Not to be used currently as this is a public API.
x_return_status	OUT	VARCHAR 2			Represents the API overall return status. Detailed in Return Status, page 1-4.
x_msg_count	OUT	NUMBER			Number of messages in the API message list
x_msg_data	OUT	VARCHAR 2			This is the message in encoded format if x_msg_count=1

The following table lists the parameters that pertain specifically to the cash receipt routine.

Note: If required parameters are not passed in a call to this API, then the call will fail. However, depending on the business scenario, you will have to pass in values for other parameters to successfully create the business object. Otherwise, error messages will be reported.

Parameter	Туре	Data-type	Required	Description
p_usr_currency_cod	IN	VARCHAR2		The translated currency code.
e				Used to derive the p_currency_code if it is not entered.
				Default: None
				Validation: Should be a valid currency, so that the corresponding currency code can be derived.
				Error: AR_RAPI_USR_CURR_CODE_INVALID
p_currency_code	IN	VARCHAR2		The actual currency code that gets stored in AR tables.
				Default:
				1. Derived from p_usr_currency_code if entered, else
				2. Defaults to the functional currency code
				Validation: Validated against the currencies in fnd_currencies table.
				Error: AR_RAPI_CURR_CODE_INVALID
				Warning: AR_RAPI_FUNC_CURR_DEFAULTED
p_usr_exchange_rate	IN	VARCHAR2		The translated exchange rate type.
_type				Used to derive the p_exchange_rate_type if it has not been entered.
				Default: None
				Validation: Should be a valid rate type.
				Error: AR_RAPI_USR_X_RATE_TYP_INVALID

Parameter	Туре	Data-type	Required	Description
p_exchange_rate_ty	IN	VARCHAR2		Exchange rate type stored in AR tables.
pe				Default:
				 In case of foreign currency receipt, derived from p_usr_exchange_rate_type.
				2. In case of foreign currency receipt, defaults from profile option 'AR: Default Exchange Rate Type'
				Validation: Validated against values in gl_daily_conversion_types table.
				Error: AR_RAPI_X_RATE_TYPE_INVALID
p_exchange_rate	IN	NUMBER		The exchange rate between the receipt currency and the functional currency.
				Default:
				 Derived from the Daily Rates table for rate_type ⇔'User' in case of non-functional currency
				2. If profile option Journals: Display Inverse Rate = 'Y', set user entered value to 1/ p_exchange_rate
				3. The entered value is rounded to a precision of 38.
				Validation:
				1. In case of non-functional currency the rate should have a positive value for rate type= 'User'
				2. For non-functional currency and type is ⇔ 'User', do not specify any value.
				Error: AR_RAPI_X_RATE_INVALID, AR_RAPI_X_RATE_NULL

Parameter	Туре	Data-type	Required	Description
p_exchange_rate_dat	IN	DATE		The date on which the exchange rate is valid.
e				Default: Receipt date
				Validation: For a non-functional currency and type is 'User' there should be a valid rate existing in the database for this date. This is a cross validation of type, currency, and date.
				Error: AR_NO_RATE_DATA_FOUND
p_amount	IN	NUMBER	Yes	The cash receipt amount.
				Default: Null
				Validation: >0
				Error: AR_RAPI_REC_AMT_NEGATIVE, AR_RAPI_RCPT_AMOUNT_NULL
p_factor_discount_a	IN	NUMBER		The bank charges on the cash receipt.
mount				Default: None
				Validation:
				1. Bank charges not allowed if profile option AR: Create Bank Charges = 'No'.
				2. Bank charges not allowed if the receipt state, derived from the receipt class of the receipt method ⇔ 'CLEARED'.
				3. If allowed then >=0
				Error: AR_JG_BC_AMOUNT_NEGATIVE, AR_BK_CH_NOT_ALLWD_IF_NOT_CLR
p_receipt_number	IN	VARCHAR2		The receipt number of the receipt to be created.
		(30)		Default: If not specified, the receipt number is defaulted from the document sequence value.
				Validation: Receipt number should not be null.
				Error: AR_RAPI_RCPT_NUM_NULL

Parameter	Туре	Data-type	Required	Description
p_receipt_date	IN	DATE		The receipt date of the entered cash receipt.
				Default: System date
				Validation: None
				Error: None
p_gl_date	IN	DATE		Date that this receipt will be posted to the General Ledger.
				Default: Gets defaulted to the receipt date if it is a valid gl_date.
				Validation: The date is valid if the following conditions are true:
				• The date is in an Open or Future period
				• The period cannot be an Adjustment period
				If the date is invalid, then:
				• If the most recent open period is prior to the receipt date: last date of that period
				• If there is a period open after the receipt date: first date of the last open period
				Error: AR_INVALID_APP_GL_DATE
p_maturity_date	IN	DATE		Receipt maturity date.
				Default: Deposit date
				Validation: >= p_receipt_date
				Error: AR_RW_MAT_BEFORE_RCT_DATE
p_postmark_date	IN	DATE		The postmark date
				Default: None
				Validation: None
				Error: None

Parameter	Туре	Data-type	Required	Description
p_customer_id	IN	NUMBER(15)		The customer_id for the paying customer.
				Default: Defaulted from customer name/number
				Validation:
				1. Customer exists and has prospect code = 'CUSTOMER'
				2. Customer has a profile defined at the customer level
				Error: AR_RAPI_CUST_ID_INVALID
p_customer_name	IN	VARCHAR2 (50)		The name for the entered customer. Used to default the customer id if not specified.
				Default: None
				Validation: None
				Error: AR_RAPI_CUS_NAME_INVALID
p_customer_number	IN			The customer number. Used to default the customer_id if not specified
				Default: None
				Validation: None
				Error: AR_RAPI_CUS_NUM_INVALID

Parameter	Туре	Data-type	Required	Description
p_customer_bank_ac	IN	NUMBER(15)		The customer bank account id.
count_id				Default: From bank account id/number
				Validation:
				1. It must be a valid Bank Account of the paying customer
				2. The inactive date (if defined) of the Bank Account, should be greater than the receipt_date
				3. The receipt date has to be within the Start date and the End date of the Bank Account
				Error: AR_RAPI_CUS_BK_AC_2_INVALID, AR_RAPI_CUS_BK_AC_ID_INVALID
p_customer_bank_ac count_num	IN	VARCHAR2 (30)		The customer bank account number. Used to default the customer bank account id, if not specified
				Default: None
				Validation: None
				Error: None
p_customer_bank_ac count_name	IN	VARCHAR2 (80)		The customer bank account name. Used to default the customer bank account id, if not specified
				Default: None
				Validation: None
				Error: None
p_location	IN	VARCHAR2 (40)		The Bill_To location for the customer. Used to derive the p_customer_site_use_id
				Default: None
				Validation: None
				Error: AR_RAPI_CUS_LOC_INVALID

Parameter	Туре	Data-type	Required	Description
p_customer_site_use	IN	NUMBER(15)		The Bill_To site_use_id for the customer
_id				Default:
				1. Defaulted from customer location, else
				2. Primary Bill_To customer site_use_id of the customer.
				Validation: It should be a valid Bill_To site of the paying customer.
				Error: AR_RAPI_CUS_SITE_USE_ID_INVALID
p_customer_receipt_ reference	IN	VARCHAR2 (30)		This column is used to store a customer receipt reference value supplied by the customer at the confirmation time.
				Default: None
				Validation: None
				Error: None
p_override_remit_ba nk_account_flag	IN	VARCHAR2 (1)		The flag value decides when the remittance bank account can be overridden by the remittance selection process.
				Default: 'Y'
				Validation: valid values 'Y' and 'N'
				Error: AR_RAPI_INVALID_OR_REMIT_BK_AC

Parameter	Туре	Data-type	Required	Description
p_remittance_bank_ account_id	IN	NUMBER(15)		Identifies the user's bank account for depositing the receipt.
				Default:
				1. From remittance bank account number
				2. From the receipt method based on logic mentioned in Defaulting, page 8-18.
				Validation: Validation logic detailed in Validation, page 8-17.
				Error: AR_RAPI_REM_BK_AC_ID_INVALID, AR_RAPI_REM_BK_AC_ID_NULL
p_remittance_bank_ account_num	IN	VARCHAR2 (30)		The remittance bank account number. Used to default the remittance bank account id if not specified.
				Default: None
				Validation: None
				Error: AR_RAPI_REM_BK_AC_NUM_INVALID
p_remittance_bank_ account_name	IN	VARCHAR2 (50)		The remittance bank account name. Used to default the remittance bank account id if not specified
				Default: None
				Validation: None
				Error: AR_RAPI_REM_BK_AC_NAME_INVALID
p_deposit_date	IN	DATE		The deposit date.
				Default: receipt date
				Validation: None
				Error: None

Parameter	Туре	Data-type	Required	Description
p_receipt_method_i	IN	NUMBER(15)		Identifies the receipt method of the receipt
d				Default: From receipt method name
				Validation: Validation detailed in Validation, page 8-17
				Error: AR_RAPI_INVALID_RCT_MD_ID
p_receipt_method_n ame	IN	VARCHAR2 (30)		The receipt method name of the receipt. Used to default the receipt method id if not specified.
				Default: None
				Validation: None
				Error: AR_RAPI_RCPT_MD_NAME_INVALID
p_doc_sequence_val	IN	NUMBER		Value assigned to document receipt.
ue				Default: Detailed in Defaulting, page 8-18
				Validation:
				 User should not pass in the value if the current document sequence is automatic.
				 Document sequence value should not be entered if profile option Sequential Numbering is set to Not Used
				Error: AR_RAPI_DOC_SEQ_AUTOMATIC, AR_RAPI_DOC_SEQ_VAL_INVALID
p_ussgl_transaction_	IN	VARCHAR2		Code defined by public sector accounting.
code		(30)		Default: None
				Validation: None
				Error: None
p_anticipated_cleari	IN	DATE		Date the receipt is expected to be cleared.
ng_date	ng_date			Default: None
				Validation: ≻= gl_date
				Error: AR_RW_EFFECTIVE_BEFORE_GL_DATE

Parameter	Туре	Data-type	Required	Description
p_event	IN	VARCHAR2		The event that resulted in the creation of the receipt. Currently used only by Bills Receivable.
				Default: None
				Validation: None
				Error: None
p_called_from	IN	VARCHAR2 (20)		This parameter is used to identify the calling routine. Currently used to identify only the 'BR_REMIT' program.
				Default: None
				Validation: None
				Error: None
p_attribute_record	IN	attribute_rec_t ype (PL/SQL defined record type)		This is a record type which contains all the 15 descriptive flexfield segments and one descriptive flexfield structure defining column. It represents the Receipt Information flexfield.
				Default: DFF APIs used to do the defaulting and validation
				Validation: DFF APIs used to do the defaulting and validation
				Error: AR_RAPI_DESC_FLEX_INVALID
p_global_attribute_r ecord	IN	global_attribut e_rec_type		This is a record type which contains all the 20 global descriptive flexfield segments and one global descriptive flexfield structure defining column.
				Default: None
				Validation: None
				Error:
p_comments	IN	VARCHAR2 (240)		User's comments

Parameter	Туре	Data-type	Required	Description
p_issuer_name	IN	VARCHAR2 (50)		Issuer name of Notes Receivable (Asia Pacific Requirement)
				Default: None
				Validation: None
				Error:
p_issue_date	IN	DATE		Date Notes receivable was issued (Asia Pacific Requirement)
				Default: None
				Validation: None
				Error: None
p_issuer_bank_branc h_id	IN	NUMBER(15)		Bank/ Branch issuing the Notes Receivable (Asia Pacific Requirement)
				Default: None
				Validation: None
				Error: None
p_cr_id	OUT	NUMBER(15)	Yes	The cash receipt id of the receipt created by the API call.
p_default_site_use	IN	VARCHAR2	No	Indicates if you want to default the site use from p_customer_site_use_id.
				The default value is Y. Pass N to default nothing.
				If the Require Billing Location for Receipts system option is selected, then no value is required here.
p_payment_trxn_ext ension_id				Payment transaction extension identifier
p_org_id				

Parameter	Туре	Data-type	Required	Description
p_installment	IN	NUMBER(15)		The installment (or term_sequence_number) of the debit item. Used in conjunction with customer_trx_id to derive the applied payment schedule id if not specified.
				Default: 1, if only one installment exists for the debit item
				Validation:
				1. >0;
				2. valid installment of transaction.

Validation

This section explains the validation mechanisms for the various parameters of this API which are relatively more complex and could not be explained in the Description column of the preceding table.

Validating Receipt Method ID

The receipt method ID is validated per the following conditions:

- It must be a valid receipt method ID in the AR RECEIPT METHOD table.
- Receipt date must lie between the receipt method start date and end date (if not null).
- The creation method code for the receipt class of this particular receipt method ID should be 'AUTOMATIC,' the remit flag = 'Y,' and the confirm flag = 'N' or 'MANUAL.'
- At least one remittance bank account associated with this receipt method ID must have either the multi-currency flag set to 'Y' or the same currency as the receipt currency. In addition, this should have a bank account type = 'INTERNAL' and its inactive date (if specified) greater than the receipt_date.

Validating Remittance Bank Account ID

A remittance bank account ID, which is associated with a particular receipt method, is validated after validating the receipt method ID. If the receipt method ID is invalid, then the validation for the remittance bank account ID is not completed. An error message raised for an invalid value is AR_RAPI_INVALID_REMIT_BK_AC_ID.

The remittance bank account ID must:

- Be a valid remittance bank account ID for the current receipt method.
- Have the multi-currency flag set to 'Y' or the same currency as the receipt currency. In addition, this should have a bank account type = 'INTERNAL' and its inactive date (if specified) greater than the receipt_date.

Validating for Duplicate Receipt

If the combination of the receipt_date, receipt_number, and amount on this receipt matches any existing receipts which have not been reversed, then the error message AR_RW_CASH_DUPLICATE_RECEIPT is raised.

Defaulting

This section explains the defaulting mechanisms for the various parameters of this API which are relatively more complex and could not be explained in the Description column of the preceding table.

Defaulting the Remittance Bank Account ID

In addition to being defaulted from the remittance bank account name and/or remittance bank account number, the remittance bank account identifier is defaulted from the receipt method that is specified for the cash receipt. If only one remittance bank account is associated with the specified receipt method that has the multi-currency flag = 'Y' or has same currency as the receipt currency, and the receipt date is within its start date and end date range, then that remittance bank account is used as the default value.

Example

Objective:

To create an identified cash receipt using a call to Ar_receipt_api_pub.Create_cash and passing a minimum number of input parameters.

This table lists the entered parameters:

Parameter	Entered Value	Default Value
p_api_version	1.0	
p_init_msg_list	FND_API.G_TRUE	
p_receipt_number	'aj_test_api_1'	
p_amount	1000	

Parameter	Entered Value	Default Value
p_receipt_method_id	1001	
p_customer_name	'Computer Service and Rentals'	

This table lists the defaulted input parameters, which were not entered:

Parameter	Entered Value	Default Value
p_customer_id		1006
p_currency_code		USD
p_receipt_date		10-FEB-2000
p_gl_date		10-FEB-2000
p_deposit_date		10-FEB-2000
p_customer_site_use_id		1025
p_override_remit_bank_acco unt_flag		'Y'
p_remittance_bank_account_i d		10001
p_maturity_date		10-FEB-2000

The API call in this case would be:

```
Ar_receipt_api_pub.Create_cash(
       p_receipt_method_id => 1001,
       p_receipt_method_id => 1001,
p_customer_name => 'Computer Service and Rentals',
p_cr_id => l_cr_id,
x_return_status => l_return_status,
x_msg_count => l_msg_count,
x_msg_data => l_msg_data);
```

The warnings and the error messages that the API puts on the message stack are retrieved after execution of this API by the calling program in the following manner:

```
IF l_msq_count = 1 Then
  --there is one message raised by the API, so it has been sent out
  --in the parameter x_msg_data, get it.
l_msg_data_out := l_msg_data;
ELSIF l_msg_count > 1 Then
-- the messages on the stack are more than one so call them in a loop
-- and put the messages in a PL/SQL table.
   count := count +1 ;
   l_mesg := FND_MSG_PUB.Get;
    If l_mesg IS NULL Then
     EXIT;
     Mesg_tbl(count).message := l_mesg;
   End if;
end loop;
END IF;
```

Depending on the message level threshold set by the profile option FND_API_MSG_LEVEL_THRESHOLD, the messages put on the message stack may contain both the error messages and the warnings.

Result:

We were able to create an identified cash receipt by specifying only six input parameters in our call to this API.

Similarly, without initializing the message stack (p_init_msg_list not passed and defaulted), you can create an unidentified cash receipt (without a customer) by passing only four input parameters to this API call.

Ar_receipt_api_pub.Apply

Call this routine to apply the cash receipts of a customer (identified cash receipt) to a debit item. This debit item could be of the same customer or related customer, or an unrelated customer, depending on the value of the Allow Payment of Unrelated Transactions system option. This API routine has 3 output and 34 input parameters in total. Based on the type, the following is the breakdown of the parameters:

Input

Standard API parameters: 4

Application parameters: 28 + 1 (descriptive flexfield record parameters)

+ 1 (global descriptive flexfield record parameters)

Output

Standard API parameters: 3 Application parameters: 0

Parameter Descriptions

For a description of this routine's standard parameters, see Ar receipt api pub.

Create_cash, page 8-3.

The following table lists the parameters that pertain specifically to the Apply routine.

Note: If required parameters are not passed in a call to this API, then the call will fail. However, depending on the business scenario, you will have to pass in values for other parameters to successfully create the business object. Otherwise, error messages will be reported.

Parameter	Туре	Data-type	Required	Description
p_cash_receipt_id	IN	NUMBER(15)		The cash_receipt_id of the receipt which needs to be applied to a given debit item.
				Default: None
				Validation:
				1. Type must be 'CASH'
				2. Status must not be Reversed or Approved
				3. The receipt must not be Unidentified
				Error: AR_RAPI_CASH_RCPT_ID_INVALID, AR_RAPI_CASH_RCPT_ID_NULL
p_receipt_number	IN	VARCHAR2(30)		The receipt number of the receipt to be applied. Used to default the cash_receipt_id.
				Default: None
				Validation: None
				Error: AR_RAPI_RCPT_NUM_INVALID
p_customer_trx_id	IN	NUMBER(15)		The customer_trx_id of the debit item to which the receipt is to be applied
				Default: None
				Validation: Detailed in Validation, page 8-30
				Error: Detailed in Validation, page 8-30

Parameter	Туре	Data-type	Required	Description
p_trx_number	IN	VARCHAR2(20)		The trx_number of the debit item to which the receipt is to be applied. Used to default the customer_trx_id
				Default: None
				Validation: None
				Error: AR_RAPI_TRX_NUM_INVALID
p_installment IN	IN	NUMBER(15)		The installment (or term_sequence_number) of the debit item. Used in conjunction with customer_trx_id to derive the applied payment schedule id if not specified.
				Default: 1, if only one installment exists for the debit item
				Validation:
				1. >0;
				2. valid installment of transaction.
				Also see Validation, page 8-30
				Error: AR_RAPI_INSTALL_NULL
p_applied_payment IN _schedule_id	IN	NUMBER(15)		The payment schedule id of the debit item. Also used to derive the customer_trx_id if not specified
				Default: Defaulted based on the installment and the customer_trx_id
				Validation:
				1. > 0
				2. It must correspond to Customer trx id and installment specified.
				3. It must have the status <> 'CL' if the show closed invoices flag <> 'Y'
				Error: AR_RAPI_APP_PS_ID_INVALID

Parameter	Туре	Data-type	Required	Description
p_amount_applied	IN	NUMBER		The transaction amount to which the receipt is to be applied, in the transaction currency.
				Default: The default amount applied can be either the open amount of the transaction or the unapplied amount of the receipt, but you can change it. Use the AR: Always Default Transaction Balance for Applications profile option, <i>Oracle Receivables Implementation Guide</i> to control how Receivables defaults the applied amount.
				The profile option's defaulting rules are:
			• If you set the profile option to <i>Yes</i> , then the default amount applied is the remaining transaction amount.	
				• If you set the profile option to <i>No</i> , or if a null value exists, then the defaulting rule is:
			1. If the unapplied receipt amount is greater than or equal to the transaction, then the default amount applied is the remaining transaction amount.	
			2. If the unapplied receipt amount is less than the remaining transaction amount, then the default amount applied is the unapplied receipt amount.	
			3. If the unapplied receipt amount is negative, then the default amount applied is the remaining transaction amount.	
				Discounts, if applicable, are taken into account by the discounts routine which calculates the amount applied.
				Validation: Detailed in Validation, page 8-30
				Error: Detailed in Validation, page 8-30

Parameter	Туре	Data-type	Required	Description
p_amount_applied_f rom	IN	NUMBER		The allocated receipt amount in receipt currency.
				Use only for cross currency receipt applications. Do not use when transaction and receipt currencies are the same.
				Default:
				 For a same currency application, defaults to null
				• For the cross currency application, defaults to trans_to_receipt_rate * amount_applied
				Validation: Detailed in Validation, page 8-30
				Error: Detailed in Validation, page 8-30
p_trans_to_receipt_r ate	IN	NUMBER		For cross currency receipts, the exchange rate used to convert an amount from a foreign currency to functional currency
				Default: Detailed in Defaulting, page 8-29
				Validation: Detailed in Validation, page 8-30
				Error: Detailed in Validation, page 8-30
p_discount	IN	NUMBER		Discount on the debit item, entered in the invoice currency
				Default: Detailed in Defaulting, page 8-29
				Validation: Detailed in Validation, page 8-30
				Error: Detailed in Validation, page 8-30

Parameter	Туре	Data-type	Required	Description
p_apply_date	IN	DATE		Date the application was applied.
				Default:
				1. Receipt date, if receipt date >= system date
				2. System date, if receipt date < system date
				Validation: apply date >= transaction date apply date >= receipt date
				Error: AR_APPLY_BEFORE_TRANSACTION, AR_APPLY_BEFORE_RECEIPT
p_gl_date	IN	DATE		Date that this application will be posted to the General Ledger
				Default: Detailed in Defaulting, page 8-29
				Validation:
				1. Validated as per standard gl date validation described for the gl date in Create_cash routine
				2. >= transaction gl date
				3. >= receipt gl date
				Error:
				AR_INVALID_APP_GL_DATE
				AR_VAL_GL_INV_GL
				AR_RW_GL_DATE_BEFORE_REC_GL
p_ussgl_transaction_	IN	VARCHAR2(30)		Code defined by public sector accounting.
code				Default: None
				Validation: None
				Error: None

Parameter	Туре	Data-type	Required	Description
p_customer_trx_line _id	IN	NUMBER(15)		The customer trx line id of the debit item to which the payment is applied.
				Default: From the line number if specified
				Validation: This should be a valid line id for the specified customer trx id.
				Error: AR_RAPI_TRX_LINE_ID_INVALID
p_line_number	IN	NUMBER		The line number of the debit item to which the payment is applied.
				Default: None
				Validation: None
				Error: AR_RAPI_TRX_LINE_NO_INVALID
p_show_closed_invo ices	IN	VARCHAR2(1)		This flag decides whether to do the receipt application against closed invoices. The valid values are 'Y' and 'N'
				Default: 'N'
				Validation: Any other value is treated as 'N'.
				Error: None
p_event	IN	VARCHAR2(50)		The event that resulted in the creation of the receipt. Currently used only by Bills Receivables.
				Default: None
				Validation: None
				Error: None
p_move_deferred_ta	IN	VARCHAR2(1)		Depending on maturity date, this flag indicates when deferred tax should be moved on the accounting event.
				Default: None
				Validation: None
				Error: None

Parameter	Туре	Data-type	Required	Description
p_attribute_record	IN	attribute_rec_typ e		This is a record type which contains all the 15 descriptive flexfield segments and one descriptive flexfield structure defining column. It represents the Receipt Application Information flexfield.
				Default: DFF APIs used to do the defaulting and validation
				Validation: DFF APIs used to do the defaulting and validation
				Error: AR_RAPI_DESC_FLEX_INVALID
p_global_attribute_r ecord	IN	global_attribute_ rec_type		This is a record type which contains all the 20 global descriptive flexfield segments and One global descriptive flexfield structure defining column.
				Default: None
				Validation: None
				Error: None
p_comments	IN	VARCHAR2 (240)		User's comments
p_payment_set_id	IN	NUMBER(15)		Payment set ID is populated only for a prepayment receipt that needs to be applied to a given debit item.
				Default: None
				Validation: None
p_application_ref_ty pe	IN	VARCHAR2(30)		Application reference type – this determines the context of the application reference fields.
				Default: None
				Validation: Must be Null or, if a Trade Management deduction is being created, then must be 'CLAIM' (Trade Management must be installed).
				Error: AR_RAPI_INVALID_APP_REF

Parameter	Туре	Data-type	Required	Description
p_application_ref_id	IN	NUMBER(15)		Must be NULL.
p_application_ref_n um	IN	VARCHAR2(30)		The reference number relating to the application reference type. If application reference type is 'CLAIM', then this would be a deduction number.
				Default: None
				Validation: If populated, then must be an existing deduction number in Trade Management.
				Error: AR_RAPI_INVALID_CLAIM_NUM
p_secondary_applica tion_ref_id	IN	NUMBER(15)		The secondary application reference ID related to the application reference type.
				Default: None
				Validation: If populated, and if the application reference type is 'CLAIM', then this must contain a valid claim ID in Trade Management.
				Error: AR_RW_INVALID_CLAIM_ID
p_application_ref_re ason	IN	VARCHAR2(30)		The reason code related to the application reference type.
				Default: None
				Validation: If populated, and if the application reference type is 'CLAIM', then this must contain a valid reason code ID in Trade Management.
				Error: AR_RAPI_INVALID_REF_REASON
p_customer_referenc e	IN	VARCHAR2(100)		Reference supplied by customer.

Parameter	Туре	Data-type	Required	Description
p_customer_reason	IN	VARCHAR2(30)		Reason code supplied by customer, in the context of an application reference type of 'CLAIM'.
				Default: None
				Validation: None in Oracle Receivables (the attempt to match to an Oracle reason code is made in Trade Management).

Defaulting

This section explains the defaulting mechanisms for the various parameters of this API, which are relatively more complex in nature and could not be explained in the Description column of the preceding table.

Trans to receipt rate

For a cross currency application, the transaction to receipt rate is defaulted by the following rules:

- Check if a fixed rate exists (using the GL APIs) between the transaction currency and the receipt currency. If yes, then get it and use it as the default.
- If there is no fixed rate relationship between the transaction currency and the receipt currency, and the profile option AR: Cross Currency Exchange Rate Type has a value, then try to derive a rate from the database using the profile option value and the cash receipt date as the exchange rate date. If you get a rate from the database, then use it as default.
- If the amount_applied and the amount_applied_from are specified, then derive the transaction to receipt rate using the following equation: $trans_to_receipt_rate = amount_applied_from/amount_applied.$

GL Date

The application GL date is defaulted to the greater of the Receipt GL date or, depending on the value of the profile option AR: Application GL Date Default, the system date or transaction GL date.

Discount

Defaults to the maximum discount available on the transaction, as of the date of application, which is internally calculated by the discounts routine.

Validation

This section explains the validation mechanisms for the various parameters of this API which are relatively more complex in nature and could not be explained in the Description column of the preceding table.

Customer Trx ID

The customer_trx_id is validated using the conditions mentioned below:

- If the Show Closed Invoices flag is set to 'Y,' then the current transaction + installment can have a payment schedule status of Closed ('CL'). Otherwise, the payment schedule status must be Open ('OP').
- If the Allow Payment of Unrelated Transactions system option = 'Y,' then the current transaction can be for a customer who is not related to the customer on the receipt. Otherwise, the transaction must be for the same or related customer on the receipt.
- The transaction must be an Invoice, Credit Memo, Debit Memo, Deposit, or Chargeback.

Note: This transaction can be in a currency that is different from the receipt currency.

Depending on the specified input parameters, one of the following error messages is raised for an invalid transaction:

- AR_RAPI_TRX_ID_INST_INVALID
- AR RAPI TRX NUM INST INVALID
- AR_RAPI_CUST_TRX_ID_INVALID
- AR_RAPI_TRX_NUM_INVALID
- AR_RAPI_APP_PS_ID_INVALID

For details of these messages, refer to Messages, page 8-136.

Amount Applied

- The amount applied cannot be null. The error message raised for an invalid value is AR_RAPI_APPLIED_AMT_NULL.
- The amount applied must not be greater than the line amount for the given customer_trx_line ID (if specified). The error message raised for an invalid value is AR RW APPLIED GREATER LINE.

- Depending on the creation sign, natural application flag, allow overapplication flag, and the amount due remaining of the specified transaction installment, the amount applied is validated to check for overapplication and natural application. The error messages raised for invalid values are AR_CKAP_OVERAPP, AR_CKAP_NATURALAPP, and AR_CKAP_CT_SIGN. For details of the messages, refer to Messages, page 8-136.
- For a cross currency application, the following equation should always be valid: amount applied * trans to receipt rate = amount applied from The error message raised is AR RAPI INVALID CC AMTS.

Amount Applied From

- During a cross-currency receipt application, the amount applied from cannot be null. The error message raised for an invalid value is AR_RAPI_AMT_APP_FROM_NULL.
- The amount applied from cannot be greater than the unapplied amount available on the receipt. The error message raised for invalid values is AR_RW_APP_NEG_UNAPP.
- If the transaction currency and the receipt currency are the same, then the amount applied from must always be null. The error message raised for an invalid value is AR_RAPI_AMT_APP_FROM_INVALID.
- As mentioned previously for a cross currency application, the following equation must always be valid:

amount applied * trans to receipt rate = amount applied from

Trans to Receipt Rate

- For a cross currency application, the trans to receipt rate should have a positive value. The error message raised for an invalid value is AR_RW_CC_RATE_POSITIVE.
- If the transaction currency and the receipt currency are the same, then the rate should not have any value specified. The error message raised for an invalid value is AR_RAPI_INVALID_CC_RATE.
- For a cross currency application, the following equation should always be valid:

amount applied * trans to receipt rate = amount applied from

If this condition is violated, then the error raised is AR_RAPI_CC_RATE_AMTS_INVALID.

Discount

- If the amount due original on the transaction (debit item) is negative, then discount = 0 or null. The error message raised for an invalid value is AR_RW_NO_DISCNT.
- If amount applied > 0, then the discount cannot be negative. The error message raised for an invalid value is AR_RW_VAL_NEG_DISCNT.
- If partial discount flag = 'N' and the transaction has not been completely paid off by the receipt application, then the discount = 0 or null. The error message raised for an invalid value is AR_NO_PARTIAL_DISC.
- The discount must not be greater than the maximum discount allowed on the transaction, which is internally calculated in the API by the discounts routine. The error message raised for an invalid value is AR_RW_VAL_DISCOUNT.

If the Allow Unearned Discounts system option = 'N,' then the discount must be less than or equal to the allowed earned discount, which gets internally calculated in the API by the discounts routine for the given transaction. The error message raised for an invalid value is AR_RW_VAL_UNEARNED_DISCOUNT.

Application Ref Number

If p_application_ref_type is 'CLAIM', then the application reference number can be populated with a valid deduction number from Trade Management. This deduction/overpayment must be in the same currency as the debit item being applied to. Otherwise, the error message raised is AR RAPI INVALID CLAIM NUM.

Secondary Application Ref ID

If p_application_ref_type is 'CLAIM', then the secondary application reference ID can be populated with a valid claim ID from Trade Management. This deduction/overpayment must be in the same currency as the debit item being applied to. Otherwise, the error message raised is AR_RAPI_INVALID_CLAIM_NUM.

If both the application reference number and the secondary application reference ID are left null, and p_application_ref_type is 'CLAIM', then a new claim will be created in Trade Management.

Example

Objective:

To apply a cash receipt in functional currency to an invoice in functional currency having only one installment using a call to the API Ar receipt api pub. Apply and passing a minimum number of input parameters.

This table lists the entered parameters:

Parameter	Entered Value	Default Value
p_api_version	1.0	
p_trx_number	'aj_test_trx_1'	
p_receipt_number	'aj_test_cr_2'	

This table lists the defaulted input parameters, which were not entered:

Parameter	Entered Value	Default Value
p_customer_trx_id		187807
p_installment		1
p_cash_receipt_id		23927
p_gl_date		10-FEB-2000
p_applied_payment_schedule _id		36271
p_apply_date		10-FEB-2000
p_amount_applied		98
p_amount_applied_from		98
p_discount		2
p_show_closed_invoices		'N'

Result:

We were able to apply the cash receipt against the specified transaction by specifying only three input parameters in our call to this API. The retrieval and handling of the warnings and the error messages, put on the message stack by the API during execution, are the same as described in Defaulting, page 8-18.

Ar_receipt_api_pub.Create_and_apply

Call this routine to create a cash receipt and apply it to a specified installment of a debit item. This debit item could be for the same customer or related customer, or for an unrelated customer, depending on the Allow Payment of Unrelated Transactions system option.

This is essentially a superset of the *ar_receipt_api_pub.Create_cash* and *Ar_receipt_api_pub.* Apply APIs, and contains the same parameters as contained in those two APIs. During the call to this API, if the creation of the receipt is successfully completed but its application to the debit item fails, then the receipt creation is also rolled back.

This routine calls Oracle Payments, where required. See Integration with Oracle Payments, page 8-2.

> **Note:** To create credit card receipts that need to be processed by Oracle Payments APIs, you must pass the p_call_payment_processor parameter as fnd_api.g_true. Additionally, you must specify the p_customer_bank_account_id parameter.

This API routine has 3 output and 59 input parameters in total. Based on the type, the following is the breakdown of the parameters:

Input

Standard API parameters: 4

Application parameters: 47 + 2 (descriptive flexfield record parameter)

+ 2 (global descriptive flexfield record parameter)

Output

Standard API parameters: 3

Application parameters: 0

Parameter Descriptions

For a description of this routine's standard parameters, see Ar_receipt_api_pub. Create_cash, page 8-3.

The following table lists the parameters that are relevant to the receipt creation and application for the API.

Note: If required parameters are not passed in a call to this API, then the call will fail. However, depending on the business scenario, you will have to pass in values for other parameters to successfully create the business object. Otherwise, error messages will be reported.

Parameter	Туре	Data-type	Required	Description
p_usr_currency_cod e	IN	VARCHAR2		The translated currency code. Used to derive the p_currency_code if it is not entered.
				Default: None
				Validation: Should be a valid currency, so that we can derive the corresponding currency code.
				Error: AR_RAPI_USR_CURR_CODE_INVALID
p_currency_code	IN	VARCHAR2(15)		The actual currency code that gets stored in AR tables.
				Default:
				1. Derived from p_usr_currency_code if entered. Otherwise,
				2. Defaulted to the functional currency code.
				Validation: Validated against the currencies in fnd_currencies table.
				Error: AR_RAPI_CURR_CODE_INVALID
				Warning: AR_RAPI_FUNC_CURR_DEFAULTED
p_usr_exchange_rate _type	IN	VARCHAR2		The translated exchange rate type. Used to derive the p_exchange_rate_type if it has not been entered.
				Default: None
				Validation: Should be a valid rate type.
				Error: AR_RAPI_USR_X_RATE_TYP_INVALID

Parameter	Туре	Data-type	Required	Description
p_exchange_rate_ty pe	IN	VARCHAR2(30)		Exchange rate type stored in AR tables.
PC				Default:
				 In case of foreign currency receipt, derived from p_usr_exchange_rate_type
				2. If p_usr_exchange_rate_type is null, then defaulted from AR: Default Exchange Rate Type profile option
				3. Should be left null, if the receipt is in the same denomination as functional currency
				Validation: Validated against values in gl_daily_conversion_types table
				Error: AR_RAPI_X_RATE_TYPE_INVALID

Parameter	Туре	Data-type	Required	Description
p_exchange_rate	IN	NUMBER		The exchange rate between the receipt currency and the functional currency.
				Default:
				1. Derived from the Daily Rates table for rate_type <>'User' in case of non-functional currency
				2. If profile option Journals: Display Inverse Rate = 'Y', set user entered value to 1/ p_exchange_rate
				3. The entered value is rounded to a precision of 38.
				Validation:
				1. In case of non-functional currency the rate should have a positive value for rate type= 'User'
				2. For non-functional currency and type \Leftrightarrow 'User' the user should not specify any value.
				Error: AR_RAPI_X_RATE_INVALID, AR_RAPI_X_RATE_NULL
p_exchange_rate_dat	IN	DATE		The date on which the exchange rate is valid.
e				Default: Receipt date
				Validation: For a non-functional currency and type ♦ 'User' there should be a valid rate existing in the database for this date. This is a cross validation of type, currency and date
				Error: AR_NO_RATE_DATA_FOUND

Parameter	Туре	Data-type	Required	Description
p_amount	IN	NUMBER	Yes	The cash receipt amount.
				Default: Null
				Validation: >0
				Error: AR_RAPI_REC_AMT_NEGATIVE, AR_RAPI_RCPT_AMOUNT_NULL
p_factor_discount_a	IN	NUMBER		The bank charges on the cash receipt.
mount				Default: None
				Validation:
				1. Bank charges are not allowed if profile option AR: Create Bank Charges = 'No'.
				2. Bank charges not allowed if the receipt state, derived from the receipt class of the receipt method, <> 'CLEARED'.
				3. If allowed, then ≥ 0 .
				Error: AR_BK_CH_NOT_ALLWD_IF_NOT_CLR, AR_JG_BC_AMOUNT_NEGATIVE
p_receipt_number	IN	VARCHAR2(30)		The receipt number of the receipt to be created.
				Default: If not specified, the receipt number is defaulted from the document sequence value.
				Validation: Receipt number should not be null
				Error: AR_RAPI_RCPT_NUM_NULL
p_receipt_date	IN	DATE		The receipt date of the entered cash receipt.
				Default: System date
				Validation: None
				Error: None

Parameter	Туре	Data-type	Required	Description
p_gl_date	IN	DATE		Date that this receipt will be posted to the General Ledger.
				Default: Gets defaulted to the receipt date if it is a valid gl_date.
				Validation: The date is valid if the following conditions are true:
				• The date is in an Open or Future period
				 The period cannot be an Adjustment period
				If the date is invalid, then:
				• If the most recent open period is prior to the receipt date: last date of that period
				• If there is a period open after the receipt date: first date of the last open period
				Error: AR_INVALID_APP_GL_DATE
p_maturity_date	IN	DATE		Receipt maturity date.
				Default: Deposit date
				Validation: >= p_receipt_date
				Error: AR_RW_MAT_BEFORE_RCT_DATE
p_customer_id	IN	NUMBER(15)		The customer_id for the paying customer.
				Default: Refer to Defaulting, page 8-52
				Validation:
				1. Customer exists and has prospect code = 'CUSTOMER'
				2. Customer has a profile defined a customer level
				Error: AR_RAPI_CUST_ID_INVALID

Parameter	Туре	Data-type	Required	Description
p_customer_name	IN	VARCHAR2(50)		The name for the entered customer. Used to default the customer id if not specified.
				Default: None
				Validation: None
				Error: AR_RAPI_CUS_NAME_INVALID
p_customer_number	IN	VARCHAR2(30)		The customer number. Used to default the customer_id if not specified.
				Default: None
				Validation: None
				Error: AR_RAPI_CUS_NUM_INVALID
p_customer_bank_ac	IN	NUMBER(15)		The customer bank account ID.
count_id				Default: From bank account ID/number.
				Validation:
				1. It must be a valid bank account of the paying customer.
				2. The inactive date (if defined) of the bank account should be greater than the receipt_date.
				3. The receipt date must be within the Start date and the End date of the bank account uses.
				Error: AR_RAPI_CUS_BK_AC_2_INVALID AR_RAPI_CUS_BK_AC_ID_INVALID
p_customer_bank_ac count_num	IN	VARCHAR2(30)		The customer bank account number. Used to default the customer bank account id, if not specified.
				Default: None
				Validation: None
				Error: None

Parameter	Туре	Data-type	Required	Description
p_customer_bank_ac count_name	IN	VARCHAR2(80)		The customer bank account name. Used to default the customer bank account id, if not specified.
				Default: None
				Validation: None
				Error: None
p_customer_location	IN	VARCHAR2(40)		The Bill_To location for the customer. Used to derive the p_customer_site_use_id.
				Default: None
				Validation: None
				Error: AR_RAPI_CUS_LOC_INVALID
p_customer_site_use _id	IN	NUMBER(15)		The Bill_To site_use_id for the customer.
				Default:
				1. Defaulted from customer location. Otherwise,
				2. Primary Bill_To customer site_use_id of the customer.
				Validation: It should be a valid Bill_To site of the paying customer.
				Error: AR_RAPI_CUS_SITE_USE_ID_INVALID
p_customer_receipt_ reference	IN	VARCHAR2(30)		This column is used to store a customer receipt reference value that the customer supplies at the confirmation time.
				Default: None
				Validation: None
				Error: None

Parameter	Туре	Data-type	Required	Description
p_override_remit_ba nk_account_flag	IN	VARCHAR2(1)		The flag value decides when the remittance bank account can be overridden by the remittance selection process.
				Default: 'Y'
				Validation: valid values 'Y' and 'N'
				Error: AR_RAPI_INVALID_OR_REMIT_BK_AC
p_remittance_bank_ account_id	IN	NUMBER(15)		Identifies the user's bank account for depositing the receipt.
				Default:
				1. From remittance bank account number
				2. From the receipt method based on logic mentioned in Defaulting, page 8-18
				Validation: Validation logic detailed in Validation, page 8-17
				Error: AR_RAPI_REM_BK_AC_ID_INVALID AR_RAPI_REM_BK_AC_ID_NULL
p_remittance_bank_ account_num	IN	VARCHAR2(30)		The remittance bank account number. Used to default the remittance bank account id if not specified.
				Default: None
				Validation: None
				Error: AR_RAPI_REM_BK_AC_NUM_INVALID
p_remittance_bank_ account_name	IN	VARCHAR2(50)		The remittance bank account name. Used to default the remittance bank account id if not specified.
				Default: None
				Validation: None
				Error: AR_RAPI_REM_BK_AC_NAME_INVALID

Parameter	Туре	Data-type	Required	Description
p_deposit_date	IN	DATE		The deposit date.
				Default: receipt date
				Validation: None
				Error: None
p_receipt_method_i	IN	NUMBER(15)		Identifies the receipt method of the receipt.
d				Default: From receipt method name
				Validation: Validation detailed in Validation, page 8-17
				Error: AR_RAPI_INVALID_RCT_MD_ID
p_receipt_method_n ame	IN	VARCHAR2(30)		The receipt method name of the receipt. Used to default the receipt method id if not specified.
				Default: None
				Validation: None
				Error: None
				Note: To use credit card refund functionality, ensure that remittance of the original receipt is performed within Oracle Receivables. Do this by setting the remittance method on the receipt method's associated receipt class to <i>Standard</i> .
				Warning: If you use this API to both authorize and capture credit card payments, then set the remittance method to <i>None</i> . Note, however, that with this setting, you cannot use standard credit card refund functionality. Instead, you must refund such payments <i>outside</i> Receivables.

Parameter	Туре	Data-type	Required	Description
p_doc_sequence_val	IN	NUMBER		Value assigned to document receipt.
ue				Default: Detailed in Defaulting, page 8-18.
				Validation:
				 You should not pass a value, if the current document sequence is automatic.
				 Document sequence value should not be entered if profile option Sequential Numbering is set to Not Used.
				Error: AR_RAPI_DOC_SEQ_AUTOMATIC AR_RAPI_DOC_SEQ_VAL_INVALID
p_ussgl_transaction_	IN	VARCHAR2(30)		Code defined by public sector accounting.
code				Default: None
				Validation: None
				Error: None
p_anticipated_cleari	IN	DATE		Date the receipt is expected to be cleared.
ng_date				Default: None
				Validation: >= gl_date
				Error: AR_RW_EFFECTIVE_BEFORE_GL_DATE
p_event	IN	VARCHAR2		The event that resulted in the creation of the receipt. Currently used only by Bills Receivables.
				Default: None
				Validation: None
				Error: None

Parameter	Туре	Data-type	Required	Description
p_called_from	IN	VARCHAR2(20)		This parameter is used to identify the calling routine. Currently used to identify only the 'BR_REMIT' program.
				Default: None
				Validation: None
				Error: None
p_attribute_record	IN	attribute_rec_type		This is a record type which contains all the 15 descriptive flexfield segments and one descriptive flexfield structure defining column. It represents the Receipt Information flexfield.
				Default: DFF APIs used to do the defaulting and validation
				Validation: DFF APIs used to do the defaulting and validation
				Error: AR_RAPI_DESC_FLEX_INVALID
p_global_attribute_r ecord	IN	global_attribute_r ec_type		This is a record type which contains all the 20 global descriptive flexfield segments and one global descriptive flexfield structure defining column.
				Default: None
				Validation: None
				Error:
p_issuer_name	IN	VARCHAR2(50)		Issuer name of Notes Receivable (Asia Pacific Requirement).
				Default: None
				Validation: None
				Error: None

Parameter	Туре	Data-type	Required	Description
p_issue_date	IN	DATE		Date when the note receivable was issued (Asia Pacific Requirement).
				Default: None
				Validation: None
				Error: None
p_customer_trx_id	IN	NUMBER(15)		The customer_trx_id of the debit item to which the receipt is to be applied.
				Default: None
				Validation: Detailed in Validation, page 8-30
				Error: Detailed in Validation, page 8-30
p_trx_number	IN	VARCHAR2(20)		The trx_number of the debit item to which the receipt is to be applied. Used to default the customer_trx_id.
				Default: None
				Validation: None
				Error: AR_RAPI_TRX_NUM_INVALID
p_installment	IN	NUMBER(15)		The installment (or term_sequence_number) of the debit item. Used in conjunction with customer_trx_id to derive the applied payment schedule id if not specified.
				Default: 1, if only one installment exists for the debit item
				Validation:
				1. >0
				2. valid installment of transaction.
				Also see Validation, page 8-30
				Error: AR_RAPI_INSTALL_NULL

Parameter	Туре	Data-type	Required	Description	
p_applied_payment _schedule_id	IN	NUMBER(15)		The payment schedule id of the debit item. Also used to derive the customer_trx_id if not specified.	
				Default: Defaulted based on the installment and the customer_trx_id	
				Validation:	
				1. > 0	
				2. It must correspond to Customer trx id and installment specified.	
				3. It must have the status ⇔ 'CL' if the show closed invoices flag ⇔ 'Y'	
				Error: AR_RAPI_APP_PS_ID_INVALID	
p_amount_applied	IN	NUMBER		The transaction amount to which the receipt is to be applied. This in the transaction currency.	
				Default: The default amount applied can be either the open amount of the transaction or the unapplied amount of the receipt, but you can change it. Use the AR: Always Default Transaction Balance for Applications profile option, <i>Oracle Receivables Implementation Guide</i> to control how Receivables defaults the applied amount.	
				For the profile option's defaulting rules, see Ar_receipt_api_pub.Apply, page 8-20.	
				Discounts, if applicable, are taken into account by the discounts routine which calculates the amount applied.	
				Validation: Detailed in Validation, page 8-30	
				Error: Detailed in Validation, page 8-30.	

Parameter	Туре	Data-type	Required	Description
p_amount_applied_f rom	IN	NUMBER		The allocated receipt amount in receipt currency.
				Use only for cross currency receipt applications. Do not use when transaction and receipt currencies are the same.
				Default:
				 For a same currency application, defaults to null.
				 For the cross currency application, defaults to trans_to_receipt_rate * amount_applied.
				Validation: Detailed in Validation, page 8-30
				Error: Detailed in Validation, page 8-30.
p_trans_to_receipt_r ate	IN	NUMBER		For cross currency receipts, the exchange rate used to convert an amount from a foreign currency to functional currency.
				Default: Detailed in Defaulting, page 8-29
				Validation: Detailed in Validation, page 8-30
				Error: Detailed in Validation, page 8-30
p_discount	IN	NUMBER		Discount on the debit item, entered in the invoice currency.
				Default: Detailed in Defaulting, page 8-29
				Validation: Detailed in Validation, page 8-30
				Error: Detailed in Validation, page 8-30

Parameter	Туре	Data-type	Required	Description
p_apply_date	IN	DATE		Date the application was applied.
				Default:
				 Receipt date, if receipt date >= system date
				2. System date, if receipt date < system date
				Validation: apply date >= transaction date apply date >= receipt date
				Error: AR_APPLY_BEFORE_TRANSACTION AR_APPLY_BEFORE_RECEIPT
p_apply_gl_date	IN	DATE		Date that this application will be posted to the General Ledger.
				Default: Detailed in Defaulting, page 8-29
				Validation:
				 Validated as per standard gl date validation described for the gl date in Create_cash routine
				2. Greater than or equal to transaction gl date
				3. Greater than or equal to receipt gl date
				Error:
				AR_INVALID_APP_GL_DATE
				AR_VAL_GL_INV_GL
				AR_RW_GL_DATE_BEFORE_REC_GL
p_app_ussgl_transac	IN	VARCHAR2(30)		Code defined by public sector accounting.
tion_code				Default: None
				Validation: None
				Error:

Parameter	Туре	Data-type	Required	Description
p_customer_trx_line _id	IN	NUMBER(15)		The customer trx line id of the debit item to which the payment is applied.
				Default: From the line number if specified
				Validation: This should be a valid line id for the specified customer trx id.
				Error: AR_RAPI_TRX_LINE_ID_INVALID
p_line_number	IN	NUMBER		The line number of the debit item to which the payment is applied.
				Default: None
				Validation: None
				Error: AR_RAPI_TRX_LINE_NO_INVALID
p_show_closed_invo ices	IN	VARCHAR2(1)		This flag decides whether to do the receipt application against closed invoices. The valid values are 'Y' and 'N'.
				Default: 'N'
				Validation: Check for the valid values.
				Error: AR_RAPI_INVALID_SHOW_CL_INV
p_event	IN	VARCHAR2(50)		The event that resulted in the creation of the receipt. Currently used only by Bills Receivables.
				Default: None
				Validation: None
				Error: None
p_move_deferred_ta x	IN	VARCHAR2(1)		Depending on maturity date, this flag indicates when deferred tax should be moved on the accounting event.
				Default: None
				Validation: None
				Error: None

Parameter	Туре	Data-type	Required	Description
p_app_attribute_rec ord	IN	attribute_rec_type		This is a record type which contains all the 15 descriptive flexfield segments and one descriptive flexfield structure defining column. It represents the Receipt Application Information flexfield.
				Default: DFF APIs used to do the defaulting and validation
				Validation: DFF APIs used to do the defaulting and validation
				Error: AR_RAPI_DESC_FLEX_INVALID
p_app_global_attrib ute_record	IN	global_attribute_r ec_type		This is a record type which contains all the 20 global descriptive flexfield segments and one global descriptive flexfield structure defining column.
				Default: None
				Validation: None
				Error:
p_comments	IN	VARCHAR2(240)		User's comments for the application.
p_call_payment_pro cessor	IN	VARCHAR2 (1)	FND_API. G_FALSE	This is the payment processing indicator flag. Pass as FND_API.G_TRUE, if you want to call Oracle Payments for credit card processing.
p_default_site_use	IN	VARCHAR2	No	Indicates if you want to default the site use from p_customer_site_use_id.
				The default value is Y. Pass N to default nothing.
				If the Require Billing Location for Receipts system option is selected, then no value is required here.
p_payment_trxn_ext ension_id				Payment transaction extension identifier
p_org_id				

Defaulting

This section explains the defaulting mechanisms for the various parameters of this API which are relatively more complex in nature and could not be explained in the Description column of the preceding table.

Customer ID

The p_customer_id is required for the create_and_apply routine because an unidentified receipt cannot be applied to a transaction. If not specified, then the customer ID gets defaulted from one of the following:

- Customer number, customer name, or both
- Bill_to customer on the transaction or drawee customer on the bill (for receipt application against a bill)

If the customer ID is not defaulted by one of the above, then the AR_RAPI_CUST_ID_NULL error is raised.

Example

Objective:

To create a cash receipt in the functional currency against an invoice in USD having only one installment, using a call to the API *Ar_receipt_api_pub.Create_and_Apply* and passing a minimum number of input parameters.

This table lists the entered parameters:

Parameter	Entered Value	Default Value
p_api_version	1.0	
p_receipt_number	'aj_test_api_3'	
p_amount	1000	
p_receipt_method_id	1001	
p_customer_name	'Computer Service and Rentals'	
p_trx_number	'aj_test_trx_3'	

This table lists the defaulted input parameters, which were not entered:

Parameter	Entered Value	Default Value
p_customer_id		1006
p_currency_code		USD
p_receipt_date		10-FEB-2000
p_gl_date		10-FEB-2000
p_deposit_date		10-FEB-2000
p_customer_site_use_id		1025
p_override_remit_bank_acco unt_flag		Y
p_remittance_bank_account_i d		10001
p_maturity_date		10-FEB-2000
p_customer_trx_id		187809
p_installment		1
p_apply_gl_date		10-FEB-2000
p_applied_payment_schedule _id		36277
p_apply_date		10-FEB-2000
p_amount_applied		1000
p_amount_applied_from		1000
p_discount		0
p_show_closed_invoices		'N'

Result:

We were able to create the cash receipt 'aj_test_api_3' and then apply it against the

invoice 'aj_test_trx_3' by specifying only six input parameters in our call to this API. Both the receipt and the invoice are in the functional currency. The retrieval and handling of the warnings and the error messages, put on the message stack by the API during execution, are the same as described in Defaulting, page 8-18.

Ar_receipt_api_pub.Unapply

Call this routine to unapply a cash receipt application against a specified installment of a debit item or payment_schedule_id. This API routine has 3 output and 14 input parameters in total. Based on the type, the following is the breakdown of the parameters:

Input

Standard API parameters: 4

Application parameters: 10

Output

Standard API parameters: 3

Application parameters: 0

Parameter Descriptions

For a description of this routine's standard parameters, see Ar_receipt_api_pub. Create_cash, page 8-3.

The following table lists the parameters that are specific to the unapplication for the API.

Note: If required parameters are not passed in a call to this API, then the call will fail. However, depending on the business scenario, you will have to pass in values for other parameters to successfully create the business object. Otherwise, error messages will be reported.

Parameter	Туре	Data-type	Required	Description
p_cash_receipt_id	IN	NUMBER(15)		The cash_receipt_id of the receipt whose application has to be unapplied.
				Default: None
				Validation:
				1. Status must not be Reversed or Approved
				2. The receipt should have an application on it.
				Error: AR_RAPI_CASH_RCPT_ID_NULL
p_receipt_number	IN	VARCHAR2(30)		The receipt number of the receipt whose application is to be unapplied. Used to default the cash_receipt_id.
				Default: None
				Validation: None
				Error: AR_RAPI_RCPT_NUM_INVALID, AR_RAPI_TRX_NUM_INST_INVALID
p_customer_trx_id	IN	NUMBER(15)		The customer_trx_id of the debit item against which the specified receipt has an application.
				Default: None
				Validation: The transaction must have an application against the specified receipt.
				Error: AR_RAPI_CUST_TRX_ID_INVALID, AR_RAPI_TRX_ID_INST_INVALID
p_trx_number	IN	VARCHAR2(20)		The trx_number of the debit item against which the specified receipt has an application. Used to default the customer_trx_id.
				Default: None
				Validation: None
				Error: None

Parameter	Туре	Data-type	Required	Description
p_installment	IN	NUMBER(15)		The installment (or term_sequence_number) of the debit item. Used in conjunction with customer_trx_id to derive the applied payment schedule id if not specified.
				Default: 1, if only one installment exists for the debit item
				Validation:
				1. >0
				2. valid installment of transaction
				Error: AR_RAPI_INSTALL_NULL, AR_RAPI_TRX_ID_INST_INVALID, AR_RAPI_TRX_NUM_INST_INVALID
p_applied_payment _schedule_id	IN	NUMBER(15)		The payment schedule id of the debit item. Also used to derive the customer_trx_id, if not specified.
				Default: Derived from the installment and the customer_trx_id.
				Validation:
				1. > 0
				2. It must correspond to Customer trx id and installment, if specified.
				3. For applications with Bills Receivables installed, you cannot unapply a bill that is in the process of remittance.
				Error: AR_RAPI_APP_PS_ID_INVALID

Parameter	Туре	Data-type	Required	Description	
p_receivable_applica tion_id	IN	NUMBER(15)		Identifies the receivable application. Used to derive the customer_trx_id, cash_receipt_id, and the applied_payment_schedule_id, if not specified.	
				Default: Defaulted from the specified transaction and the receipt.	
				Validation:	
				1. Application type must be 'CASH'.	
				2. Display flag = 'Y' (latest application).	
				3. The applied payment schedule id of the receivable application record must correspond to the p_applied_payment_schedules_id, if specified.	
				4. The cash receipt id must correspond to the cash receipt id specified.	
				5. For applications with Bills Receivables installed, you cannot unapply the application of a bill that is in the process of remittance.	
				Error: AR_RAPI_REC_APP_ID_NULL, AR_RAPI_REC_APP_ID_INVALID	

Parameter	Туре	Data-type	Required	Description
p_reversal_gl_date	IN	DATE		The reversal gl date.
				Default: Gets defaulted to the application gl date if it is a valid gl_date.
				Validation:
				It is valid if the following conditions are true:
				• The date is in an Open or Future period.
				 The period cannot be an Adjustment period.
				 The reversal GL date >= application GL date.
				• The reversal GL date >= receipt GL date.
				If the date is invalid, then:
				 If the most recent open period is prior to the receipt date: last date of that period
				• If there is a period open after the receipt date: first date of the last open period
				Error: AR_INVALID_APP_GL_DATE AR_RW_BEFORE_APP_GL_DATE AR_RW_BEFORE_RECEIPT_GL_DATE
p_called_from	IN	VARCHAR2(20)		This parameter is used to identify the calling routine.
				Default: None
				Validation: None
				Error: None
p_cancel_claim_flag	IN	VARCHAR2(1)		Not used – leave null.

Defaulting

This section explains the defaulting mechanisms for the various parameters of this API which are relatively more complex and could not be explained in the Description column of the preceding table.

Receivable Application ID

If not specified, then the receivable application ID can be defaulted by one of the following:

- Using the specified installment and p_customer_trx_id (derived from p_trx_number if not specified) and p_cash_receipt_id (derived from the receipt number if not specified).
- Using the specified value of p_applied_payment_schedule_id and p_cash_receipt_id (derived from the receipt number if not specified).

Validation

This section explains the cross validations for the various parameters of this API which are relatively more complex and could not be explained in the Description column of the preceding table.

Cross validation between customer trx id, applied payment schedule id, cash receipt id, and receivable_application_id

- If p_customer_trx_id, p_installment, and p_applied_payment_schedule_id are specified and the two do not point to the same transaction, then the error AR_RAPI_TRX_PS_ID_X_INVALID is raised.
- If the combination of the specified p_applied_payment_schedule_id (or derived from the p customer trx id and p installment) and the specified p_receivable_application_id is invalid, then the error AR_RAPI_APP_PS_RA_ID_X_INVALID or AR_RAPI_TRX_RA_ID_X_INVALID is raised, depending on the input parameters.

Example

Objective:

To unapply the receipt application against an invoice using the call to API *Ar_receipt_api_pub.Unapply* and passing a minimum number of input parameters.

This table lists the entered parameters:

Parameter	Entered Value	Default Value
p_api_version	1.0	
p_receipt_number	'aj_test_api_4'	

Parameter	Entered Value	Default Value
p_applied_payment_schedule _id	1001	

This table lists the defaulted input parameters, which were not entered:

Parameter	Entered Value	Default Value
p_cash_receipt_id		1006
p_customer_trx_id		USD
p_reversal_gl_date		10-FEB-2000
p_receivable_application_id		29711

The retrieval and handling of the warnings and the error messages, put on the message stack by the API during execution, are the same as described in Defaulting, page 8-18.

Ar_receipt_api_pub.Apply_on_account

Call this routine to apply an on-account application of the specified cash receipt. This API routine has 3 output and 21 input parameters in total. Based on the type, the following is the breakdown of the parameters:

Input

Standard API parameters: 4

Application parameters: 14 + 1 (descriptive flexfield record type)

+ 1 (global descriptive flexfield record type)

Output

Standard API parameters: 3 Application parameters: 0

Parameter Descriptions

For a description of this routine's standard parameters, see Ar_receipt_api_pub. Create_cash, page 8-3.

The following table lists the descriptions of the on-account application-related

parameters of the API.

Note: If required parameters are not passed in a call to this API, then the call will fail. However, depending on the business scenario, you will have to pass in values for other parameters to successfully create the business object. Otherwise, error messages will be reported.

Parameter	Туре	Data-type	Required	Description
p_cash_receipt_id	IN	NUMBER(15)		The cash_receipt_id of the receipt which is to be applied on account.
				Default: None
				Validation:
				1. Type must be 'CASH'
				2. Status must not be Reversed or Approved
				The receipt must not be Unidentified
				Error:
				AR_RAPI_CASH_RCPT_ID_INVALID
				AR_RAPI_CASH_RCPT_ID_NULL
p_receipt_number	IN	VARCHAR2(30)		The receipt number of the receipt to be applied on account. Used to default the cash_receipt_id.
				Default: None
				Validation: None
				Error: AR_RAPI_RCPT_NUM_INVALID

Parameter	Туре	Data-type	Required	Description
p_amount_applied	IN	NUMBER		The amount on the cash receipt that is to be applied on account.
				Default: Amount due remaining on the receipt.
				Validation:
				1. Greater than or equal to 0.
				2. Less than or equal to the amount due remaining on the receipt.
				Error:
				AR_RAPI_APPLIED_AMT_NULL, AR_RW_APP_NEG_UNAPP, AR_RW_AMOUNT_LESS_THAN_AP P
p_apply_date	IN	DATE		Date the application was applied.
				Default:
				1. Receipt date, if receipt date >= system date
				2. System date, if receipt date < system date
				Validation: apply date >= receipt date
				Error: AR_APPLY_BEFORE_RECEIPT

Parameter	Туре	Data-type	Required	Description
p_apply_gl_date	IN	DATE		Date that this application will be posted to the General Ledger.
				Default: Defaulted to greater of the receipt date and the system date.
				Validation:
				1. Validated as per standard gl date validation described for the gl date in Create_cash routine.
				2. >= receipt gl date.
				Error:
				AR_INVALID_APP_GL_DATE, AR_RW_GL_DATE_BEFORE_REC_GL
p_ussgl_transaction_ Incode	IN VARCHAR2(3	VARCHAR2(30)		Code defined by public sector accounting.
				Default: None
				Validation: None
				Error: None
p_attribute_rec	IN	attribute_rec_typ e		This is a record type which contains all the 15 descriptive flexfield segments and one descriptive flexfield structure defining column. It represents the Receipt Application Information flexfield.
				Default: DFF APIs used to do the defaulting and validation
				Validation: DFF APIs used to do the defaulting and validation
				Error: AR_RAPI_DESC_FLEX_INVALID

Parameter	Туре	Data-type	Required	Description
p_global_attribute_r ec	IN	global_attribute_ rec_type		This is a record type which contains all the global descriptive flexfields: One global descriptive flexfield structure defining column and 20 segments. Default: None
				Validation: None
				Error: None
p_comments	IN	VARCHAR2(240)		User comments.
p_application_ref_n um	IN	VARCHAR2(30)		Deduction number, if resulting from Trade Management claim settlement.
p_secondary_applica tion_ref_id	IN	NUMBER(15)		Claim ID, if resulting from Trade Management claim settlement.
p_customer_referenc e	IN	VARCHAR2(100)		Reference supplied by customer.
p_called_from	IN	VARCHAR2(20)		This parameter is used to identify the calling routine.
				Default: None
				Validation: None
				Error: None
p_customer_reason	IN	VARCHAR2(30)		Reason code supplied by customer.
p_secondary_app_re f_type	IN	VARCHAR2(30)		Used for automated receipt handling. Leave null.
p_secondary_app_re f_num	IN	VARCHAR2(30)		Used for automated receipt handling. Leave null.

Note: With an on-account application, you cannot apply a negative amount, as you can do in a regular application of a receipt to a debit item.

Objective:

To apply a cash receipt in the functional currency to an invoice in the functional currency having only one installment, using a call to the API *Ar_receipt_api_pub*. *Apply_on_account* and passing a minimum number of input parameters.

This table lists the entered parameters:

Parameter	Entered Value	Default Value
p_api_version	1.0	
p_receipt_number	'aj_test_cr_2'	

This table lists the defaulted input parameters, which were not entered:

Parameter	Entered Value	Default Value
p_cash_receipt_id		23927
p_gl_date		01-JUN-2000
p_apply_date		01-JUN-2000
p_amount_applied		100

The retrieval and handling of the warnings and error messages, put on the message stack by the API during execution, are the same as described in Defaulting, page 8-18.

Ar_receipt_api_pub.Unapply_on_account

Call this routine to unapply an on-account application on the specified cash receipt. This API routine has 3 output and 9 input parameters in total. Based on the type, the following is the breakdown of the parameters:

Input

Standard API parameters: 4 Application parameters: 5

Output

Standard API parameters: 3 Application parameters: 0

Parameter Descriptions

For a description of this routine's standard parameters, see Ar_receipt_api_pub. Create_cash, page 8-3.

The following table lists the parameters that are relevant to the on-account unapplication for the API.

Parameter	Туре	Data-type	Required	Description
p_cash_receipt_id	IN	NUMBER(15)		The cash_receipt_id of the receipt whose application has to be unapplied.
				Default: None
				Validation:
				1. Status must not be Reversed or Approved.
				2. The receipt must have an on-account application on it.
				Error: AR_RAPI_CASH_RCPT_ID_INVALID
p_receipt_number	IN	VARCHAR2 (30)		The receipt number of the receipt which is to be unapplied. Used to default the cash_receipt_id.
				Default: None
				Validation: None
				Error: AR_RAPI_RCPT_NUM_INVALID

Parameter	Туре	Data-type	Required	Description
p_receivable_applica tion_id	IN	NUMBER(15)		Identifies the receivable application. Used to derive the customer trx id, cash_receipt_id and the applied_ps_id, if not specified.
				Default: Refer to Validation, page 8-73.
				Validation:
				1 . Application type = 'CASH'.
				2. Display flag = 'Y' (latest application) and status = 'ACC'.
				3. The applied payment schedule id of the receivable application record must correspond to the p_applied_payment_schedules_id, if specified.
				4. The cash receipt id must correspond to the cash receipt id specified.
				Error: AR_RAPI_REC_APP_ID_INVALID

Parameter	Туре	Data-type	Required	Description
p_reversal_gl_date	IN	DATE		The reversal gl date.
				Default: Gets defaulted to the application gl date if it is a valid gl_date.
				Validation:
				It is valid if the following conditions are true:
				• The date is in an Open or Future period.
				 The period cannot be an Adjustment period.
				 The reversal GL date >= application GL date.
				• The reversal GL date >= receipt GL date.
				If the date is invalid, then:
				 If the most recent open period is prior to the receipt date: last date of that period
				• If there is a period open after the receipt date first date of the last open period
				Error: AR_INVALID_APP_GL_DATE AR_RW_BEFORE_APP_GL_DATE, AR_RW_BEFORE_RECEIPT_GL_DATE
p_org_id				

Defaulting

This section explains the defaulting mechanisms for the various parameters of this API which could not be explained in the Description column of the preceding table.

Receivable Application ID

The value for p_receivable_application_id, if not specified, is defaulted from the p_cash_receipt_id (or p_receipt_number). If the receipt does not have an on-account application, then the error AR_RAPI_CASH_RCPT_ID_INVALID is raised. If there is more than one on-account application on the receipt and the value for

p_receivable_application_id has not been specified, then the error AR_RAPI_MULTIPLE_ON_AC_APP is raised.

Example

Objective:

To unapply the receipt application using the call to API *Ar_receipt_api_pub*. *Unapply_on_account* and passing a minimum number of input parameters.

This table lists the entered parameters:

Parameter	Entered Value	Default Value
p_api_version	1.0	
p_receipt_number	'aj_test_api_6'	

This table lists the defaulted input parameters, which were not entered:

Parameter	Entered Value	Default Value
p_cash_receipt_id		20338
p_reversal_gl_date		01-JUN-2000

The retrieval and handling of the warnings and error messages, put on the message stack by the API during execution, are the same as described in Defaulting, page 8-18.

Ar_receipt_api_pub.Reverse

Call this routine to reverse cash as well as miscellaneous receipts. This API routine has 3 output and 15 input parameters in total. Based on the type, the following is the breakdown of the parameters:

Input

Standard API parameters: 4

Application parameters: 12 + 1 (descriptive flexfield record type)

1 (global descriptive flexfield record type)

Output

Standard API parameters: 3

Application parameters: 0

Parameter Descriptions

For a description of this routine's standard parameters, see Ar_receipt_api_pub. Create_cash, page 8-3.

The following table lists the descriptions of the reversal-related parameters of the API.

Parameter	Туре	Data-type	Required	Description
p_cash_receipt_id	IN	NUMBER(15)		The cash_receipt_id of the receipt which needs to be reversed.
				Default: None
				Validation: Detailed in Defaulting, page 8-68.
				Error:
p_receipt_number	IN	VARCHAR2 (30)		The receipt number of the receipt to be reversed. Used to default the cash_receipt_id.
				Default: None
				Validation: None
				Error: AR_RAPI_RCPT_NUM_INVALID
p_reversal_category _code	IN	VARCHAR2 (20)		Identifies the reason why the payment entry was reversed.
				Default: None
				Validation: Validated against the values in ar_lookups for lookup_type = 'REVERSAL_CATEGORY_TYPE
				Error:
				AR_RAPI_REV_CAT_CD_NULL, AR_RAPI_REV_CAT_CD_INVALID

Parameter	Туре	Data-type	Required	Description
p_reversal_category _name	IN	VARCHAR2 (80)		This is the translated lookup meaning for the reversal category code. Used to default the reversal category code if not specified.
				Default: None
				Validation: None
				Error: AR_RAPI_REV_CAT_NAME_INVALID
p_reversal_gl_date	IN	DATE		The General Ledger Date that is used to credit the Account CCID for the reversed receipt.
				Default: System date
				Validation:
				1. Validated as per standard gl date validation described for the gl date in Create_cash routine
				2. Greater than or equal to receipt gl date
				Error:
				AR_INVALID_APP_GL_DATE, AR_RW_BEFORE_RECEIPT_GL_DATE
p_reversal_date	IN	DATE		Date on which the payment entry reversed
				Default:
				 System date if system date >= receipt date, else
				• Receipt date if receipt date > system date
				Validation: Greater than or equal to receipt date
				Error: AR_RW_REV_BEFORE_RCT_DATE

Parameter	Туре	Data-type	Required	Description
p_reversal_reason_c	IN	VARCHAR2		Indicates the reason for reversing receipt
ode	ode	(30)	(30)	Default: None
				Validation: Validated against the values in ar_lookups for lookup_type = 'CKAJST_REASON'
				Error: AR_RAPI_REV_REAS_CD_INVALID AR_RAPI_REV_REAS_CD_NULL
p_reversal_reason_n ame	IN	VARCHAR2 (80)		This is the translated lookup meaning for reversal reason code. Used for defaulting the reversal reason code if not specified.
				Default: None
			Validation: None	
				Error: AR_RAPI_REV_REAS_NAME_INVALID
p_reversal_comment s	IN	VARCHAR2 (240)		Comments regarding reversal
p_atttribute_rec	IN	p_attribute_rec		This is a record type which contains all the descriptive flexfields: One descriptive flexfield structure defining column and 15 segments.
				Default: None
				Validation: None
				Error: None
p_global_attribute_r IN ec	IN	global_attribut e_rec_type	global descriptive flexfields: One	This is a record type which contains all the global descriptive flexfields: One global descriptive flexfield structure defining column and 20 segments.
				Default: None
				Validation: None
				Error: None
p_cancel_claims_flag	IN	VARCHAR2(1)		Not used. Leave null.

Parameter	Туре	Data-type	Required	Description
p_called_from	IN	VARCHAR2 (20)		This parameter is used to identify the calling routine.
				Default: None
				Validation: None
				Error: None
p_org_id				

Validation

This section explains the validation mechanisms for the various parameters of this API which are relatively more complex in nature and could not be explained in the Description column of the preceding table.

Cash Receipt ID

We have to validate whether this is a valid cash receipt ID, and whether we can reverse this receipt.

The validation steps are:

- This is a valid value in the database. For an invalid value, the error message AR RAPI CASH RCPT ID INVALID is raised.
- Status should not be 'Reversed' for this receipt because you cannot reverse an already reversed receipt. The error message raised for an invalid value is AR_RAPI_CASH_RCPT_ID_INVALID.

The receipt is not standard reversible if any two of the following conditions are true:

- If a chargeback was created against an invoice that is applied to the payment to be reversed.
- If there are any payments, adjustments, credit memos, or chargebacks against the above chargeback records in the AR_PAYMENT_SCHEDULES table.
- If the above chargeback has already been posted to the general ledger.

The AR_RAPI_NON_REVERSIBLE error message is raised for invalid values. In these cases, you can create a debit memo reversal to reverse the receipt. Since the Receipt API does not currently support debit memo reversals, you can manually create them using the Receipts workbench.

Objective:

To reverse a cash receipt using a call to the API Ar_receipt_api_pub.Reverse and passing a minimum number of input parameters.

This table lists the entered parameters:

Parameter	Entered Value	Default Value
p_api_version	1.0	
p_receipt_number	'aj_test_cr_7'	
p_reversal_category_code	'NSF'	
p_reversal_reason_code	'PAYMENT REVERSAL'	

This table lists the defaulted input parameters, which were not entered:

Parameter	Entered Value	Default Value
p_cash_receipt_id		20340
p_reversal_date		01-JUN-2000
p_reversal_gl_date		01-JUN-2000

The retrieval and handling of the warnings and error messages, put on the message stack by the API during execution, are the same as described in Defaulting, page 8-18.

Ar_receipt_api_pub.activity_application

Call this routine to do an activity application on a cash receipt. Such applications include Short Term Debit (STD) and Receipt Write-off applications.

This API routine has 4 output and 41 input parameters in total. Based on the type, the following is the breakdown of the parameters:

Input

Standard API parameters: 4

Application parameters: 35 + 1 (descriptive flexfield record type)

1 (global descriptive flexfield record type)

Output

Standard API parameters: 3

Application parameters: 1

Parameter Descriptions

For a description of this routine's standard parameters, see Ar_receipt_api_pub. Create_cash, page 8-3.

The following table lists the descriptions of the activity application-related parameters of the API.

Parameter	Туре	Data-type	Require d*	Description
p_cash_receipt_id	IN	NUMBER(15)		The cash_receipt_id of the receipt which is to be used for the activity application.
				Default: None
				Validation:
				1. Type must be 'CASH'
				2. Status must not be Reversed or Approved
				3. The receipt must not be Unidentified
				Error: AR_RAPI_CASH_RCPT_ID_INVALID AR_RAPI_CASH_RCPT_ID_NULL

Parameter	Туре	Data-type	Require d*	Description
p_receipt_number	IN	VARCHAR2(30)		The receipt number of the receipt to be applied. Used to default the cash_receipt_id.
				Default: None
				Validation: None
				Error: AR_RAPI_RCPT_NUM_INVALID
p_amount_applied	IN	NUMBER		The amount on the cash receipt that is to be applied against the specified activity.
				Default: Amount due remaining on the receipt.
				Validation:
				1. Greater than or equal to 0.
				2. Less than or equal to the amount due remaining on the receipt.
				3. If a receipt write-off, then must fall within user and system limits (limits must be set).
				Error:
				AR_RAPI_APPLIED_AMT_NULL, AR_RW_APP_NEG_UNAPP, AR_RW_AMOUNT_LESS_THAN_APP, AR_WR_NO_LIMIT, AR_WR_USER_LIMIT, AR_SYSTEM_WR_NO_LIMIT_SET, AR_WR_TOTAL_EXCEED_MAX_AMOU NT

Parameter	Туре	Data-type	Require d*	Description
p_applied_payment _schedule_id	IN	NUMBER(15)	Yes	The payment schedule identifier here corresponds to special seeded values, such as -2.
				Default:
				Validation: The value should correspond to the special seeded values, such as: -2 (Short Term Debt).
				Error: AR_RAPI_APP_PS_ID_INVALID
p_link_to_customer_ trx_id	IN	NUMBER(15)		The customer_trx_id of the Bill for which the activity (such as Short Term Debt) application is being done.
				Default:
				Validation: The customer_trx_id should correspond to that of a Bill which has a current status of FACTORED or MATURED_PEND_RISK_ELIMINATION.
				Error: AR_RAPI_LK_CUS_TRX_ID_INVALID
p_receivables_trx_id	IN	NUMBER(15)		Identifier of the receivables activity.
				Default: None
				Validation:
				1. Valid database value.
				2. The activity_type for the receivables_trx_id should be in sync with the applied payment schedule identifier passed in.
				Error:
				AR_RAPI_REC_TRX_ID_INVALID, AR_RAPI_ACTIVITY_X_INVALID

Parameter	Туре	Data-type	Require d*	Description
p_apply_date	IN	DATE		Date the application was applied.
				Default:
				1. Receipt date, if receipt date >= system date.
				2. System date, if receipt date < system date.
				Validation: apply date >= receipt date
				Error: AR_APPLY_BEFORE_RECEIPT
p_apply_gl_date	IN	DATE		Date that this application will be posted to the General Ledger.
				Default: Defaulted to greater of the receipt date and the system date.
				Validation:
				 Validated as per standard GL date validation described for the GL date in Create_cash routine.
				2. >= receipt GL date
				Error: AR_INVALID_APP_GL_DATE AR_RW_GL_DATE_BEFORE_REC_GL
p_ussgl_transaction_	IN	VARCHAR2(30)		Code defined by public sector accounting.
code				Default: None
				Validation: None
				Error: None

Parameter	Туре	Data-type	Require d*	Description
p_attribute_rec	IN	attribute_rec_type		This is a record type which contains all 15 descriptive flexfield segments and one descriptive flexfield structure defining column. It represents the Receipt Application Information flexfield.
				Default: DFF APIs used to do the defaulting and validation
				Validation: DFF APIs used to do the defaulting and validation
				Error: AR_RAPI_DESC_FLEX_INVALID
p_global_attribute_r ec	IN	global_attribute_rec_type		This is a record type which contains all the global descriptive flexfields: one global descriptive flexfield structure defining column and 20 segments.
				Default: None
				Validation: None
				Error: None
p_comments	IN	VARCHAR2 (240)		User's comments for the activity application.
p_application_ref_ty pe	IN	VARCHAR2(30)		Not used. Leave null.
p_application_ref_id	IN	NUMBER(15)		Not used. Leave null.
p_application_ref_n um	IN	VARCHAR2(30)		If resulting from a settlement of a claim, then this will contain the deduction number.
p_secondary_applica tion_ref_id	IN	NUMBER(15)		If resulting from a settlement of a claim, then this will contain the claim ID.

Parameter	Туре	Data-type	Require d*	Description
p_payment_set_id	IN	NUMBER(15)		Payment set ID is populated only when doing a prepayment activity application on a prepayment receipt.
				Default: None
				Validation: None
p_receivable_applica tion_id	OUT	NUMBER(15)		The ID of the resulting activity receivable application.
p_customer_referenc e	IN	VARCHAR2 (100)		Customer supplied reference.
electroencephalogra phic	IN	VARCHAR2(1)		Flag to indicate whether user-level write-off limits should apply.
				Default: Y
				Validation: None
				Error: None
p_called_from	IN	VARCHAR2(20)		This parameter is used to identify the calling routine.
				Default: None
				Validation: None
				Error: None
p_netted_receipt_fla	IN	VARCHAR2(1)		Used for payment netting. Leave null.
p_netted_cash_recei pt_id	IN	NUMBER(15)		Used for payment netting. Leave null.
p_secondary_app_re f_type	IN	VARCHAR2(30)		Used for automated receipt handling. Leave null.
p_secondary_app_re f_num	IN	VARCHAR2(30)		Used for automated receipt handling. Leave null.
p_org_id				

Parameter	Туре	Data-type	Require d*	Description
p_pay_group_looku p_code	IN	Electroencephalographic %TYPE		
p_pay_alone_flag	IN	VARCHAR2		
p_payment_method _code	IN	ap_invoices. payment_method_code% TYPE		
p_payment_reason_c ode	IN	ap_invoices. payment_reason_code% TYPE		
p_payment_reason_c omments	IN	ap_invoices. payment_reason_comme nts%TYPE		
p_delivery_channel_ code	IN	ap_invoices. delivery_channel_code% TYPE		
p_remittance_messa ge1	IN	ap_invoices. remittance_message1% TYPE		
p_remittance_messa ge2	IN	ap_invoices. remittance_message2% TYPE		
p_remittance_messa ge3	IN	ap_invoices. remittance_message3% TYPE		
p_party_id	IN	particularization%TYPE		
p_party_site_id	IN	hz_party_sites. party_site_id%TYPE		
p_bank_account_id	IN	ar_cash_receipts. customer_bank_account_ id%TYPE		

Objective:

To apply a cash receipt in then functional currency to a receipt write-off activity in the functional currency, using a call to the API Ar_receipt_api_pub.activity_application and passing a minimum number of input parameters.

This table lists the entered parameters:

Parameter	Entered Value	Default Value
p_api_version	1.0	
p_receipt_number	'aj_test_cr_2'	
p_receivables_trx_id	1300	
p_applied_payment_schedule _id	-3	

This table lists the defaulted input parameters, which were not entered:

Parameter	Entered Value	Default Value
p_cash_receipt_id		23927
p_gl_date		01-JUN-2000
p_apply_date		01-JUN-2000
p_amount_applied		100

The retrieval and handling of the warnings and error messages, put on the message stack by the API during execution, are the same as described in Defaulting, page 8-18.

Ar_receipt_api_pub.activity_unapplication

Call this routine to do a reversal of an activity application on a cash receipt. Such applications include Short Term Debt and Receipt write-off.

This API routine has 3 output and 10 input parameters in total. Based on the type, the following is the breakdown of the parameters:

Input

Standard API parameters: 4

Application parameters: 6

Output

Standard API parameters: 3

Application parameters: 0

Parameter Descriptions

For a description of this routine's standard parameters, see Ar_receipt_api_pub. Create_cash, page 8-3.

The following table lists the descriptions of the activity unapplication-related parameters of the API.

Parameter	Туре	Data-type	Required	Description
p_cash_receipt_id	IN	NUMBER(15)		The cash_receipt_id of the receipt on which the activity application needs to be reversed.
				Default: None
				Validation:
				1. Type must be 'CASH'
				2. Status must not be Reversed or Approved
				3. The receipt must not be Unidentified
				Error: AR_RAPI_CASH_RCPT_ID_INVALID, AR_RAPI_CASH_RCPT_ID_NULL

Parameter	Туре	Data-type	Required	Description
p_receipt_number	IN	VARCHAR2(30)		The receipt number of the receipt to be reversed. Used to default the cash_receipt_id.
				Default: None
				Validation: None
				Error: AR_RAPI_RCPT_NUM_INVALID
p_receivable_applica tion_id	IN	NUMBER(15)		Identifies the receivable application. Used to derive the customer trx id, cash_receipt_id and the applied_ps_id if not specified.
				Default: Refer to Validation, page 8-73.
				Validation:
				1. Application type = 'CASH'.
				2. Display flag = 'Y' (latest application) and status = 'ACTIVITY'.
				3. The applied payment schedule id of the receivable application record must correspond to the p_applied_payment_schedule_id, if specified.
				4. Must correspond to the cash receipt id specified.
				Error: AR_RAPI_REC_APP_ID_INVALID

Parameter	Туре	Data-type	Required	Description
p_reversal_gl_date	IN	DATE		The reversal GL date.
				Default: Gets defaulted to the application GL date if it is a valid gl_date.
				Validation:
				It is valid if the following conditions are true:
				• The date is in an Open or Future period
				 The period cannot be an Adjustment period
				• Reversal GL date >= application GL date
				• Reversal GL date >= receipt GL date
				If the date is invalid, then:
				• If the most recent open period is prior to the receipt date: last date of that period
				• If there is a period open after the receipt date: first date of the last open period
				Error: AR_INVALID_APP_GL_DATE, AR_RW_BEFORE_APP_GL_DATE, AR_RW_BEFORE_RECEIPT_GL_DATE
p_called_from	IN	VARCHAR2(20)	Yes	Indicates which program is calling this API. For example, the BR_REMIT program would be calling this routine for short term debt applications.
				Default: None
				Validation: None
				Error: None
p_org_id				

Objective:

To unapply an activity application, using a call to the API *Ar_receipt_api_pub*.

activity_unapplication and passing minimum number of input parameters.

This table lists the entered parameters:

Parameter	Entered Value	Default Value
p_api_version	1.0	
p_receivable_application_id	10051	
p_called_from	NULL	

This table lists the defaulted input parameters, which were not entered:

Parameter	Entered Value	Default Value
p_cash_receipt_id		20338
p_reversal_gl_date		01-JUN-2000

The retrieval and handling of the warnings and error messages, put on the message stack by the API during execution, are the same as described in Defaulting, page 8-18.

Ar_receipt_api_pub.Create_misc

Call this routine to create a miscellaneous receipt.

Note: This routine does *not* call Oracle Payments directly. See Integration with Oracle Payments, page 8-2.

This API routine has 4 output and 37 input parameters in total. Based on the type, the following is the breakdown of the parameters:

Input

Standard API parameters: 4 Application parameters: 33

Output

Standard API parameters: 3 Application parameters: 1

Parameter Descriptions

The following table lists the standard API parameters, which are common to all the routines in the Receipt API:

Parameter	Туре	Data-type	Required	Default Value	Description
p_api_version	IN	NUMBER	Yes		Used to compare version numbers of incoming calls to its current version number.
					Unexpected error is raised if version incompatibility exists.
					In the current version of the API, you should pass in a value of 1.0 for this parameter.
p_init_msg_list	IN	VARCHAR2		FND_API. G_FALSE	Allows API callers to request that the API does initialization of the message list on their behalf.
p_commit	IN	VARCHAR2		FND_API. G_FALSE	Used by API callers to ask the API to commit on their behalf.
p_validation_lev el	IN	NUMBER		FND_API. G_VALID_LEVE L_FULL	Not to be used currently as this is a public API.
x_return_status	OUT	VARCHAR2			Represents the API overall return status. Detailed in Return Status, page 1-4.
x_msg_count	OUT	NUMBER			Number of messages in the API message list.
x_msg_data	OUT	VARCHAR2			This is the message in encoded format if x_msg_count=1.

The following table lists the parameters that are relevant to the miscellaneous receipt:

Parameter	Туре	Data-type	Required	Description
p_usr_currency_cod e	IN	VARCHAR2		The translated currency code. Used to derive the p_currency_code if it is not entered.
				Default: None
				Validation: Should be a valid currency, so that the corresponding currency code can be derived.
				Error: AR_RAPI_USR_CURR_CODE_INVALID
p_currency_code	IN	VARCHAR2		The actual currency code that gets stored in AR tables.
				Default:
				1. Derived from p_usr_currency_code if entered. Otherwise,
				2. Defaults to the functional currency code
				Validation: Validated against the currencies in fnd_currencies table.
				Error: AR_RAPI_CURR_CODE_INVALID
				Warning: AR_RAPI_FUNC_CURR_DEFAULTED
p_usr_exchange_rate _type	IN	VARCHAR2		The translated exchange rate type. Used to derive the p_exchange_rate_type if it has not been entered.
				Default: None
				Validation: Should be a valid rate type.
				Error: AR_RAPI_USR_X_RATE_TYP_INVALID

Parameter	Туре	Data-type	Required	Description
p_exchange_rate_ty	IN	VARCHAR2		Exchange rate type stored in AR tables.
pe				Default:
				 In case of foreign currency receipt, derived from p_usr_exchange_rate_type.
				2. In case of foreign currency receipt, defaults from profile option AR: Default Exchange Rate Type
				Validation: Validated against values in gl_daily_conversion_types table.
				Error: AR_RAPI_X_RATE_TYPE_INVALID
p_exchange_rate	IN	NUMBER		The exchange rate between the receipt currency and the functional currency.
				Default:
				 Derived from the Daily Rates table for rate_type <> 'User' in case of non- functional currency
				2. If profile option Journals: Display Inverse Rate = 'Y', set user-entered value to 1/p_exchange_rate
				3. The entered value is rounded to a precision of 38
				Validation:
				1. In case of non-functional currency, the rate should have a positive value for rate type = 'User'
				2. For non-functional currency and type is <> 'User', do not specify any value
				Error: AR_RAPI_X_RATE_INVALID, AR_RAPI_X_RATE_NULL

Parameter	Туре	Data-type	Required	Description
p_exchange_rate_dat	IN	DATE		The date on which the exchange rate is valid.
				Default: Receipt date
				Validation: For a non-functional currency and type is \Leftrightarrow 'User', there should be a valid rate existing in the database for this date. This is a cross validation of type, currency, and date.
				Error: AR_NO_RATE_DATA_FOUND
p_amount	IN	NUMBER	Yes	The miscellaneous receipt amount.
				Default: Null
				Validation: None
				Error: None
p_receipt_number	IN	VARCHAR2 (30)		The receipt number of the receipt to be created.
				Default: If not specified, the receipt number is defaulted from the document sequence value.
				Validation: Receipt number should not be null
				Error: AR_RAPI_RCPT_NUM_NULL
p_receipt_date	IN	DATE		The receipt date of the entered cash receipt.
				Default: System date
				Validation: None
				Error: None

Parameter	Туре	Data-type	Required	Description
p_gl_date	IN	DATE		Date when this receipt will be posted to the general ledger.
				Default: Gets defaulted to the receipt date if it is a valid gl_date, otherwise:
				 If the most recent open period is prior to the receipt date: last date of that period
				• If there is a period open after the receipt date: first date of the last open period
				Validation: It is valid if the following conditions are true:
				 The date is in an Open or Future period
				 The period cannot be an Adjustment period
				Error: AR_INVALID_APP_GL_DATE

Parameter	Туре	Data-type	Required	Description
p_receivables_trx_id	IN	NUMBER(15)		Identifies the receivables activity.
				Default: If not specified, it is derived from p_activity.
				Validation: Validates it against the values in the ar_receivables_trx table
				 Type column having values: 'MISCCASH', 'BANK_ERROR', 'CCREFUND'.
				 Checks the receipt_date to be within start_date_active and end_date_active column values.
				• Status is Active or null.
				• Not null.
				Error: AR_RAPI_ACTIVITY_INVALID, AR_RAPI_REC_TRX_ID_INVALID, AR_RAPI_REC_TRX_ID_NULL
p_activity	IN	VARCHAR2 (50)		Name of the receivables activity. This is used to derive the p_receivables_trx_id.
				Default: None
				Validation: None
				Error: None
p_misc_payment_so urce	IN	VARCHAR2 (30)		Identifies the source of the miscellaneous receipt.
				Default: None
				Validation: None
				Error: None

Parameter	Туре	Data-type	Required	Description
p_tax_code	IN	VARCHAR2 (50)		Depending on the sign of the amount entered, it is the asset tax code (for positive sign or zero) or the liability tax code (negative sign). This is used to derive the p_vat_tax_id. Default: None Validation: None Error: None

Parameter	Туре	Data-type	Required	Description
p_vat_tax_id	IN	NUMBER(15)		The VAT tax identifier for the current miscellaneous receipt.
				Default:
				 defaulted from p_tax_code
				 defaulted from receivables_trx_id/activity
				Validation:
				 For 'Accrual' accounting method, the vat_tax_id is validated against the values in Artaxerxes having
				 receipt_date between start_date_active and end_date_active column values
				• enabled_flag = 'Y'
				tax_type should not be 'TAX_GROUP', 'LOCATION', 'SALES_TAX'
				• displayed_flag = 'Y'
				 The tax_class is 'O' (output) for positive or zero amount and 'I' (input) for negative amount
				 ledger should match the current ledger
				2. For 'Cash basis' accounting method, the vat_tax_id should not be specified.
				Error: AR_RAPI_VAT_TAX_ID_INVALID, AR_RAPI_TAX_CODE_INVALID

Parameter	Туре	Data-type	Required	Description
p_tax_rate	IN	NUMBER		The new tax rate specified when you override the rate for an ad-ho tax code.
				Default:
				1. Defaulted from the tax rate on the tax code (p_tax_code/p_vat_tax_id).
				2. Defaulted from the p_tax_amount when the tax amount is specified for the ad-hoc tax code case.
				Validation: For 'Accrual' accounting method, tax rate can be specified only in case of an ad-hoc tax code (p_tax_code/p_vat_tax_id) and the profile option 'Tax: Allow Ad Hoc Tax Changes' set to Yes. For 'Cash basis' accounting method, the tax_rate should never be specified.
				Error: AR_RAPI_TAX_RATE_INVALID, AR_RAPI_TAX_RATE_AMT_X_INVALI D
p_tax_amount	IN	NUMBER		The tax amount specified in case where you override the rate for an ad-hoc tax code. It is used to derive the tax_rate.
				Default: None
				Validation: This needs to be specified only in case of an ad-hoc tax code (p_tax_code/p_vat_tax_id) and the profile option 'Tax: Allow Ad Hoc Tax Changes' set to Yes. For 'Cash basis' accounting method, the tax_amount should never be specified
				Error: AR_RAPI_TAX_RATE_AMT_X_INVALI D

Parameter	Туре	Data-type	Required	Description
p_deposit_date	IN	DATE		The deposit date.
				Default: Receipt date
				Validation: None
				Error: None
p_reference_type	IN	VARCHAR2 (30)		Indicates whether this miscellaneous receipt is a 'PAYMENT', 'RECEIPT', 'PAYMENT_BATCH' or 'REMITTANCE'.
				Default: None
				Validation:
				 Check it for the specified valid values.
				 Should not have a null value if either p_reference_id or p_reference_num i specified.
				Error: AR_RAPI_REF_TYPE_INVALID, AR_RAPI_REF_TYPE_NULL
p_reference_id	IN	NUMBER(15)		A foreign key to AR_BATCHES, AR_CASH_RECEIPTS, AP_INVOICE_SELECTION_CRITERIA of AP_CHECKS, depending on the specified value of p_reference_type.
				Default: None
				Validation: Detailed in Validation, page 8 17.
				Error: AR_RAPI_REF_NUM_INVALID, AR_RAPI_REF_ID_INVALID
p_reference_num	IN	VARCHAR2 (30)		The reference number. It is used for deriving the p_reference_id.
				Default: None
				Validation: None
				Error: None

Parameter	Туре	Data-type	Required	Description
p_remittance_bank_ account_id	IN	NUMBER(15)		Identifies the user's bank account for depositing the receipt.
				Default:
				1. From remittance bank account number
				2. From the receipt method based on logic mentioned in Defaulting, page 8-18.
				Validation: In addition to the validation logic detailed in Validation, page 8-17, those receipt methods which have notes_receivable = 'Y' or bill_of_exchange_flag = 'Y' on the receipt class are excluded for miscellaneous receipts.
				Error: AR_RAPI_REM_BK_AC_ID_INVALID, AR_RAPI_REM_BK_AC_ID_NULL
p_remittance_bank_ account_num	IN	VARCHAR2 (30)		The remittance bank account number. Used to default the remittance bank account id if not specified.
				Default: None
				Validation: None
				Error: AR_RAPI_REM_BK_AC_NUM_INVALI D
p_remittance_bank_ account_name	IN	VARCHAR2 (50)		The remittance bank account name. Used to default the remittance bank account id if not specified.
				Default: None
				Validation: None
				Error: AR_RAPI_REM_BK_AC_NAME_INVALI D

Parameter	Туре	Data-type	Required	Description
p_ussgl_transaction_ code	IN	VARCHAR2 (30)		Code defined by public sector accounting. Default: None Validation: None
				Error: None
p_receipt_method_i d	IN	NUMBER(15)		Identifies the receipt method of the receipt.
				Default: From receipt method name
				Validation: In addition to the validation logic detailed in Validation, page 8-17, those receipt methods which have notes_receivable = 'Y' or bill_of_exchange_flag = 'Y' on the receipt class are excluded for the miscellaneous receipts.
				Error: AR_RAPI_INVALID_RCT_MD_ID
p_receipt_method_n ame	IN	VARCHAR2 (30)		The receipt method name of the receipt. Used to default the receipt method id if not specified
				Default: None
				Validation: None
				Error: AR_RAPI_RCPT_MD_NAME_INVALID

Parameter	Туре	Data-type	Required	Description
p_doc_sequence_val	IN	NUMBER		Value assigned to document receipt.
ue				Default: Detailed in Defaulting, page 8-18.
				Validation:
				 User should not pass in the value if the current document sequence is automatic
				 Document sequence value should not be entered if profile option Sequential Numbering is set to Not Used
				Error: AR_RAPI_DOC_SEQ_AUTOMATIC AR_RAPI_DOC_SEQ_VAL_INVALID
p_anticipated_cleari	IN	DATE		Date the receipt is expected to be cleared.
ng_date				Default: None
				Validation: greater than or equal to gl_date
				Error: AR_RW_EFFECTIVE_BEFORE_GL_DAT E
p_attribute_rec	IN	attribute_rec_ty pe		This is a record type which contains all 15 descriptive flexfield segments and one descriptive flexfield structure defining column. It represents the Receipt Information flexfield.
				Default: DFF APIs used to do the defaulting and validation
				Validation: DFF APIs used to do the defaulting and validation
				Error: AR_RAPI_DESC_FLEX_INVALID

Parameter	Туре	Data-type	Required	Description
p_global_attribute_r ec	IN	global_attribute _rec_type		This is a record type which contains all 20 global descriptive flexfield segments and one global descriptive flexfield structure defining column.
				Default: None
				Validation: None
				Error:
p_comments	IN	VARCHAR2 (240)		User's comments.
p_misc_receipt_id	OUT	NUMBER(15)	Yes	The cash_receipt_id of the receipt created by the API call.
p_called_from	IN	VARCHAR2 (20)		This parameter is used to identify the calling routine.
				Default: None
				Validation: None
				Error: None
p_org_id				

Ar_receipt_api_pub.apply_other_account

Call this routine to do an "other" account application on a cash receipt. Typically this would be to create a claim investigation application with a noninvoice related deduction or overpayment in Trade Management (if installed).

This API routine has 4 output and 27 input parameters in total. Based on the type, the following is the breakdown of the parameters:

Input

Standard API parameters: 4

Application parameters: 19 + 1 (descriptive flexfield record type)

1 (global descriptive flexfield record type)

Output

Standard API parameters: 3

Application parameters: 1

Parameter Descriptions

For a description of this routine's standard parameters, see Ar_receipt_api_pub. Create_cash, page 8-3.

The following table lists the descriptions of the other account application-related parameters of the API:

Parameter	Туре	Data-type	Required	Description
p_cash_receipt_id	IN	NUMBER (15)		The cash_receipt_id of the receipt which is to be applied to the "other" account.
				Default: None
				Validation:
				1. Type must be 'CASH'.
				2. Status must not be Reversed or Approved.
				3. The receipt must not be Unidentified.
				Error: AR_RAPI_CASH_RCPT_ID_INVALID AR_RAPI_CASH_RCPT_ID_NULL
p_receipt_number	IN	VARCHAR2 (30)		The receipt number of the receipt to be applied to the "other" account. Used to default the cash_receipt_id.
				Default: None
				Validation: None
				Error : AR_RAPI_RCPT_NUM_INVALID

Parameter	Туре	Data-type	Required	Description
p_amount_applied	IN	NUMBER		The amount on the cash receipt that is to be applied to the "other" account.
				Default: Amount due remaining on the receipt.
				Validation: Less than or equal to the amount due remaining on the receipt.
				Error:
				AR_RAPI_APPLIED_AMT_NULL, AR_RW_AMOUNT_LESS_THAN_APP
p_applied_payment _schedule_id	IN	NUMBER (15)	Yes	This payment schedule identifier corresponds to special seeded values, such as –4 (for Claim Investigation).
				Default:
				Validation: The value should correspond to the special seeded values, such as -4 (Claim Investigation).
				Error: AR_RAPI_APP_PS_ID_INVALID
p_receivables_trx_id	IN	NUMBER		Identifier of receivables activity.
		(15)		Default: None
				Validation:
				1. Valid database value.
				2. The activity_type for the receivables_trx_id should be in sync with the provided applied payment schedule identifier.
				Error:
				AR_RAPI_REC_TRX_ID_INVALID, AR_RAPI_ACTIVITY_X_INVALID

Parameter	Туре	Data-type	Required	Description
p_apply_date	IN	DATE		Date the application was applied.
				Default:
				1. Receipt date, if receipt date >= system date.
				2. System date, if receipt date < system date.
				Validation: apply date >= receipt date
				Error: AR_APPLY_BEFORE_RECEIPT
p_apply_gl_date	IN	DATE		Date when this application will be posted to the General Ledger.
				Default: Defaulted to greater of the receipt date and the system date.
				Validation:
				 Validated as per standard gl date validation described for the gl date in the Create_cash routine.
				2. >= receipt gl date
				Error:
				AR_INVALID_APP_GL_DATE
				AR_RW_GL_DATE_BEFORE_REC_GL
p_ussgl_transaction_	IN	VARCHAR2		Code defined by public sector accounting.
code		(30)		Default: None
				Validation: None
				Error: None

Parameter	Туре	Data-type	Required	Description
p_attribute_rec	IN	attribute_rec _type		This is a record type which contains all the 15 descriptive flexfield segments and one descriptive flexfield structure defining column. It represents the Receipt Application Information flexfield.
				Default: DFF APIs used to do the defaulting and validation.
				Validation: DFF APIs used to do the defaulting and validation.
				Error : AR_RAPI_DESC_FLEX_INVALID
p_global_attribute_r ec	IN	global_attrib ute_rec_type		This is a record type which contains all the global descriptive flexfields: one global descriptive flexfield structure defining column and 20 segments.
				Default: None
				Validation: None
				Error: None
p_comments	IN	VARCHAR2 (240)		User's comments for the other account application.
p_application_ref_ty pe	IN	VARCHAR2 (30)	Yes	Defines the context of the application reference columns. For Trade Management, the value should be 'CLAIM'.
				Default: None
				Validation: Must be 'CLAIM' if a Trade Management deduction is being created (Trade Management must be installed).
				Error: AR_RAPI_INVALID_APP_REF
p_application_ref_id	IN	NUMBER (15)		Not used. Leave null.

Parameter	Туре	Data-type	Required	Description
p_application_ref_n um	IN	VARCHAR2 (30)		The reference number relating to the application reference type. If application reference type is 'CLAIM', then this would be a deduction number.
				Default: None
				Validation: If populated, then must be an existing deduction number in Trade Management.
				Error: AR_RAPI_INVALID_CLAIM_NUM
p_secondary_applica tion_ref_id	IN	NUMBER (15)		The secondary application reference ID related to the application reference type.
				Default: None
				Validation: If populated, and if application reference type is 'CLAIM', then this must contain a valid claim ID in Trade Management.
				Error: AR_RW_INVALID_CLAIM_ID
p_payment_set_id	IN	NUMBER (15)		Payment set ID is populated only for a prepayment receipt which is to be applied to the "other" account.
				Default: None
				Validation: None
p_receivable_applica tion_id	OUT	NUMBER (15)		The ID of the resulting activity receivable application.
p_application_ref_re ason	IN	VARCHAR2 (30)		The reason code related to the application reference type.
				Default: None
				Validation: If populated, and if application reference type is 'CLAIM', then this must contain a valid reason code ID from Trade Management.
				Error: AR_RAPI_INVALID_REF_REASON
p_customer_referenc e	IN	VARCHAR2 (100)		Customer supplied reference.

Parameter	Туре	Data-type	Required	Description
p_customer_reason	IN	VARCHAR2 (30)		Reason code supplied by customer, in the context of an application reference type of 'CLAIM'.
				Default: None
				Validation: None in Oracle Receivables (the attempt to match to an Oracle reason code is made in Trade Management).
p_called_from	IN	VARCHAR2 (20)		This parameter is used to identify the calling routine.
				Default: None
				Validation: None
				Error: None
p_org_id				

Objective:

To apply a cash receipt in functional currency to Claim Investigation, and to create a non-invoice overpayment in the functional currency using a call to the API Ar_receipt_api_pub.apply_other_account and passing a minimum number of input parameters.

This table lists the entered parameters:

Parameter	Entered Value	Default Value
p_api_version	1.0	
p_receipt_number	'aj_test_cr_2'	
p_receivables_trx_id	1400	
p_application_ref_type	'CLAIM'	
p_applied_payment_schedule _id	-4	

This table lists the defaulted input parameters, which were not entered:

Parameter	Entered Value	Default Value
p_cash_receipt_id		23927
p_gl_date		01-JUN-2000
p_apply_date		01-JUN-2000
p_amount_applied		100

The retrieval and handling of the warnings and error messages, put on the message stack by the API during execution, are the same as described in Defaulting, page 8-18.

Ar_receipt_api_pub.unapply_other_account

Call this routine to do a reversal of an "other" account application on a cash receipt.

This API routine has 3 output and 11 input parameters in total. Based on the type, the following is the breakdown of the parameters:

Input

Standard API parameters: 4 Application parameters: 7

Output

Standard API parameters: 3 Application parameters: 0

Parameter Descriptions

For a description of this routine's standard parameters, see Ar_receipt_api_pub. Create_cash, page 8-3.

The following table lists the descriptions of the other account unapplication-related parameters of the API:

Parameter	Туре	Data-type	Required	Description
p_cash_receipt_id	IN	NUMBER (15)		The cash_receipt_id of the receipt which is to be applied to the "other" account.
				Default: None
				Validation:
				1. Type must be 'CASH'.
				2. Status must not be Reversed or Approved.
				3. The receipt must not be Unidentified.
				Error:
				AR_RAPI_CASH_RCPT_ID_INVALID, AR_RAPI_CASH_RCPT_ID_NULL
p_receipt_number	IN	VARCHAR2 (30)		The receipt number of the receipt from which the "other" account application is to be unapplied. Used to default the cash_receipt_id.
				Default: None
				Validation: None
				Error: AR_RAPI_RCPT_NUM_INVALID

Parameter	Туре	Data-type	Required	Description
p_receivable_applica tion_id	IN	NUMBER (15)		Identifies the receivable application. Used to derive the customer trx id, cash_receipt_id, and the applied_ps_id, if not specified.
				Default: Refer to Validation, page 8-73.
				Validation:
				1. Application type = 'CASH'.
				2. Display flag = 'Y' (latest application) and status = 'OTHER ACC'.
				3. The applied payment schedule id of the receivable application record must correspond to the p_applied_payment_schedules_id, if specified.
				4. The cash receipt id must correspond to the cash receipt id specified.
				Error: AR_RAPI_REC_APP_ID_INVALID

Parameter	Туре	Data-type	Required	Description
p_reversal_gl_date	IN	DATE		The reversal gl date.
				Default: Gets defaulted to the application gl date if it is a valid gl_date.
				Validation:
				It is valid if the following conditions are true:
				• The date is in an Open or Future period.
				 The period cannot be an Adjustment period.
				 The reversal GL date >= application GL date.
				• The reversal GL date >= receipt GL date.
				If the date is invalid, then:
				 If the most recent open period is prior to the receipt date: last date of that period
				• If there is a period open after the receipt date: first date of the last open period
				Error: AR_INVALID_APP_GL_DATE, AR_RW_BEFORE_APP_GL_DATE, AR_RW_BEFORE_RECEIPT_GL_DATE
p_called_from	IN	VARCHAR2		Indicates which program is calling this API.
		(20)		Default: None
				Validation: None
				Error: None
p_cancel_claim_flag	IN	VARCHAR2 (1)		Not used. Leave null.
p_org_id				

Objective:

To unapply an "other" account application using the call to API *Ar_receipt_api_pub*. unapply_other_account and passing a minimum number of input parameters.

This table lists the entered parameters:

Parameter	Entered Value	Default Value
p_api_version	1.0	
p_receivable_application_id	10053	

This table lists the defaulted input parameters, which were not entered:

Parameter	Entered Value	Default Value
p_cash_receipt_id		20338
p_reversal_gl_date		01-JUN-2000

The retrieval and handling of the warnings and error messages, put on the message stack by the API during execution, are the same as described in Defaulting, page 8-18.

Ar_receipt_api_pub.apply_open_receipt

Call this routine to apply a cash receipt to another open receipt. Open receipts include unapplied cash, on-account cash, and claim investigation applications. Claim investigation applications can be applied only if Trade Management is installed.

This API routine has 8 output and 19 input parameters in total. Based on the type, the following is the breakdown of the parameters:

Input

Standard API parameters: 4

Application parameters: 13 + 2 (descriptive and global descriptive flexfield record type)

Output

Standard API parameters: 3

Application parameters: 5

Parameter Descriptions

For a description of this routine's standard parameters, see Ar_receipt_api_pub.

Create_cash, page 8-3.

The following table lists the descriptions of the apply open receipt-related parameters of the API:

Parameter	Туре	Data-type	Required	Description
p_cash_receipt_id	IN	NUMBER (15)		The cash_receipt_id of the receipt which is to be applied to an open receipt.
				Default: None
				Validation:
				1. Type must be 'CASH'.
				2. Status must not be Reversed or Approved.
				3. The receipt must not be Unidentified.
				4. The receipt being applied and the open receipt must have the same currency.
				Error: AR_RAPI_CASH_RCPT_ID_INVALID, AR_RAPI_CASH_RCPT_ID_NULL, AR_RW_NET_DIFF_RCT_CURR
p_receipt_number	IN	VARCHAR2 (30)		The receipt number of the receipt to be applied to an open receipt. Used to default the cash_receipt_id. The receipt being applied and the open receipt must have the same currency.
				Default: None
				Validation: None
				Error: AR_RAPI_RCPT_NUM_INVALID AR_RW_NET_DIFF_RCT_CURR
p_applied_payment _schedule_id	IN	NUMBER (15)		Not used. Leave null.

Parameter	Туре	Data-type	Required	Description
p_open_cash_receipt _id	IN	NUMBER (15)		The cash_receipt_id of the open receipt which is to be applied to.
				Default: None
				Validation:
				1. Type must be 'CASH'.
				2. Status must not be Reversed or Approved.
				3. The receipt must not be Unidentified.
				4. The receipt being applied and the open receipt must have the same currency.
				Error: AR_RAPI_CASH_RCPT_ID_INVALID, AR_RAPI_CASH_RCPT_ID_NULL, AR_RW_NET_DIFF_RCT_CURR
p_open_receipt_num ber	IN	VARCHAR2 (30)		The receipt number of the open receipt. Used to default the open cash_receipt_id. The receipt being applied and the open receipt must have the same currency.
				Default: None
				Validation: None
				Error: AR_RAPI_RCPT_NUM_INVALID, AR_RW_NET_DIFF_RCT_CURR
p_open_rec_app_id	IN	NUMBER (15)		The ID of the receivable application of the open receipt, if on-account or claim investigation.
				Default: None
				Validation: Must have status of ACC or OTHER ACC, and display must be 'Y'.
				Errors: AR_RAPI_REC_APP_ID_INVALID, AR_RW_NET_OPEN_RCT_ONLY

Parameter	Туре	Data-type	Required	Description
p_amount_applied	IN	NUMBER (15)		The amount on the cash receipt that is to be applied to an open receipt.
				Default: None
				Validation: Must be a natural application, that is. it must move the balance on the open receipt closer to zero.
				Error:
				AR_RAPI_APPLIED_AMT_NULL, AR_RW_AMOUNT_LESS_THAN_APP, AR_RW_NET_OPEN_AMT_INC
p_apply_date	IN	DATE		Date the application was applied.
				Default:
				1. Receipt date, if receipt date >= system date.
				2. System date, if receipt date < system date.
				Validation: apply date >= receipt date.
				Error: AR_APPLY_BEFORE_RECEIPT

Parameter	Туре	Data-type	Required	Description
p_apply_gl_date	IN	DATE		Date when this application will be posted to the General Ledger.
				Default: Defaulted to greater of the receipt GL date, the open receipt GL date, and the system date.
				Validation:
				 Validated as per standard gl date validation described for the gl date in the Create_cash routine.
				2. >= receipt gl date.
				Error:
				AR_INVALID_APP_GL_DATE
				AR_RW_GL_DATE_BEFORE_REC_GL
				AR_RW_GL_DATE_BEFORE_OPEN_REC
p_ussgl_transaction_	IN	VARCHAR2 (30)		Code defined by public sector accounting.
code				Default: None
				Validation: None
				Error: None
p_attribute_rec	IN	attribute_rec_ type		This is a record type which contains all the 15 descriptive flexfield segments and one descriptive flexfield structure defining column. It represents the Receipt Application Information flexfield.
				Default: DFF APIs used to do the defaulting and validation.
				Validation: DFF APIs used to do the defaulting and validation.
				Error: AR_RAPI_DESC_FLEX_INVALID

Parameter	Туре	Data-type	Required	Description
p_global_attribute_r ec	IN	global_attribu te_rec_type		This is a record type which contains all the global descriptive flexfields: One global descriptive flexfield structure defining column and 20 segments.
				Default: None
				Validation: None
				Error: None
p_comments	IN	VARCHAR2 (240)		User's comments for the other account application.
x_application_ref_nu m	OUT	VARCHAR2 (30)		The reference number from the open receipt application, if applicable. If the application reference type is 'CLAIM', then this would be a deduction number.
x_receivable_applica tion_id	OUT	NUMBER (15)		The ID of the resulting payment netting receivable application.
x_applied_rec_app_i d	OUT	NUMBER (15)		The ID of the corresponding payment netting receivable application created on the applied-to receipt.
x_acctd_amount_ap plied_from	OUT	NUMBER (15)		Amount applied from the receipt, in functional currency and converted using the main receipt's exchange rate.
x_acctd_amount_ap plied_to	OUT	VARCHAR2 (30)		Amount applied to the open receipt, in functional currency and converted using the open receipt's exchange rate. Used in conjunction with x_applied_amount_applied_from to determine exchange gain/loss.
p_called_from	IN	VARCHAR2 (20)		This parameter is used to identify the calling routine.
				Default: None
				Validation: None
				Error: None

Parameter	Туре	Data-type	Required	Description
p_org_id				

Objective:

To apply a cash receipt in your functional currency to unapplied cash on another receipt, using a call to the API Ar_receipt_api_pub.apply_open_receipt and passing a minimum number of input parameters.

This table lists the entered parameters:

Parameter	Entered Value	Default Value
p_api_version	1.0	
p_receipt_number	'aj_test_cr_10'	
p_open_receipt_number	'aj_test_cr_30'	
p_amount_applied	-200	

This table lists the defaulted input parameters, which were not entered:

Parameter	Entered Value	Default Value
p_cash_receipt_id		23935
p_open_cash_receipt_id		23973
p_gl_date		01-JUN-2000
p_apply_date		01-JUN-2000

The retrieval and handling of the warnings and error messages, put on the message stack by the API during execution, are the same as described in Defaulting, page 8-18.

Ar_receipt_api_pub.unapply_open_receipt

Call this routine to reverse a payment netting application on a cash receipt.

This API routine has 3 output and 8 input parameters in total. Based on the type, the following is the breakdown of the parameters:

Input

Standard API parameters: 4 Application parameters: 4

Output

Standard API parameters: 3 Application parameters: 0

Parameter Descriptions

For a description of this routine's standard parameters, see Ar_receipt_api_pub. Create_cash, page 8-3.

The following table lists the descriptions of the unapply open receipt-related parameters of the API:

Parameter	Туре	Data-type	Required	Description
p_receivable_applica tion_id	IN	NUMBER(15)		Identifies the receivable application to be unapplied.
				Default: Refer to Validation, page 8-73.
				Validation:
				1. Application type = 'CASH'.
				2. Display flag = 'Y' (latest application) and status = 'ACTIVITY', receivables_trx_id = -163.
				3. Unapplying this application must not result in either receipt becoming negative.
				Error: AR_RAPI_REC_APP_ID_INVALID AR_RW_NET_UNAPP_OVERAPP

Parameter	Туре	Data-type	Required	Description
p_reversal_gl_date	IN	DATE		The reversal gl date.
				Default: Gets defaulted to the application gl date if it is a valid gl_date.
				Validation:
				It is valid if the following conditions are true:
				• The date is in an Open or Future period.
				 The period cannot be an Adjustment period.
				 The reversal GL date >= application GL date.
				• The reversal GL date >= receipt GL date.
				If the date is invalid, then:
				• If the most recent open period is prior to the receipt date: last date of that period
				• If there is a period open after the receipt date: first date of the last open period
				Error: AR_INVALID_APP_GL_DATE AR_RW_BEFORE_APP_GL_DATE AR_RW_BEFORE_RECEIPT_GL_DATE
p_called_from	IN	VARCHAR2	Yes	Indicates which program is calling this API.
		(20)		Default: None
				Validation: None
				Error: None
p_org_id				

Objective:

To unapply an open receipt/payment netting application using the call to API Ar_receipt_api_pub.unapply_open_receipt and passing a minimum number of input parameters.

This table lists the entered parameters:

Parameter	Entered Value	Default Value
p_api_version	1.0	
p_receivable_application_id	10055	

This table lists the defaulted input parameters, which were not entered:

Parameter	Entered Value	Default Value
p_reversal_gl_date		01-JUN-2000

The retrieval and handling of the warnings and error messages, put on the message stack by the API during execution, are the same as described in Defaulting, page 8-18.

Ar_receipt_api_pub.Create_apply_on_acc

This routine is called to create a cash receipt and place it on account. Use this routine when no specific debit item is referenced for receipt application, but you do not want to leave the cash as an unapplied liability.

This is essentially a superset of Ar_receipt_api_pub.Create_cash, page 8-3 and Ar_receipt_api_pub.Apply_on_account, page 8-60 APIs, and contains the same parameters as contained in those two APIs. During the call to this API, if the receipt is successfully created but its on-account application fails, then the receipt creation is also rolled back.

This routine calls Oracle Payments, where required. See Integration with Oracle Payments, page 8-2.

Note: To create credit card receipts that need to be processed by Oracle Payments APIs, you must pass the p_call_payment_processor parameter as fnd_api.g_true. Additionally, you must specify the p_customer_bank_account_id parameter.

This API routine has 4 output and 57 input parameters:

Input

Standard API parameters: 4

Application parameters: 49 + 2 (descriptive flexfield parameter)

+ 2 (global descriptive flexfield parameter)

Output

Standard API parameters: 3 Application parameters: 1

Parameter Descriptions

For a description of this routine's standard parameters, see Ar_receipt_api_pub. Create_cash, page 8-3.

The following table lists the parameters that pertain specifically to the receipt creation and on-account application routine:

Parameter	Туре	Data-type	Required	Description
p_usr_currency_cod	IN	VARCHAR2		The translated currency code.
e				Used to derive the p_currency_code if it is not entered.
				Default: None
				Validation: Should be a valid currency, so that the corresponding currency code can be derived.
				Error: AR_RAPI_USR_CURR_CODE_INVALID
p_currency_code	IN	VARCHAR2 (15)		The actual currency code that gets stored in AR tables.
				Default:
				1. Derived from p_usr_currency_code if entered, else
				2. Defaults to the functional currency code
				Validation: Validated against the currencies in the fnd_currencies table.
				Error: AR_RAPI_CURR_CODE_INVALID
				Warning: AR_RAPI_FUNC_CURR_DEFAULTED

Parameter	Туре	Data-type	Required	Description
p_usr_exchange_rate	IN	VARCHAR2		The translated exchange rate type.
_type				Used to derive the p_exchange_rate_type if it has not been entered.
				Default: None
				Validation: Should be a valid rate type.
				Error: AR_RAPI_USR_X_RATE_TYP_INVALID
p_exchange_rate_ty	p_exchange_rate_ty IN VARCHAR2 pe (30)	VARCHAR2		Exchange rate type stored in AR tables.
pe		(30)		Default:
			1. In case of foreign currency receipt, derived from p_usr_exchange_rate_type.	
				2. In case of foreign currency receipt, defaults from AR: Default Exchange Rate Type profile option.
				3. Should be left null, if receipt is in the same denomination as functional currency.
				Validation: Validated against values in gl_daily_conversion_types table
				Error: AR_RAPI_X_RATE_TYPE_INVALID

Parameter	Туре	Data-type	Required	Description
p_exchange_rate	IN	NUMBER		The exchange rate between the receipt currency and the functional currency.
				Default:
				 Derived from the Daily Rates table for rate_type <> 'User' in case of non- functional currency.
				2. If profile option Journals: Display Inverse Rate = 'Y', set user-entered value to 1/ p_exchange_rate.
				3. The entered value is rounded to a precision of 38.
				Validation:
				1. In case of non-functional currency, the rate should have a positive value for rate type='User'.
				2. For non-functional currency and type ⇔ 'User', do not specify any value.
				Error: AR_RAPI_X_RATE_INVALID, AR_RAPI_X_RATE_NULL
p_exchange_rate_dat	IN	DATE		The date on which the exchange rate is valid.
e				Default: Receipt date
				Validation: For a non-functional currency and type ⇔ 'User', a valid rate should exist in the database for this date. This is a cross validation of type, currency, and date.
				Error: AR_NO_RATE_DATA_FOUND
p_amount	IN	NUMBER	Yes	The cash receipt amount.
1-				Default: Null
				Validation: > 0
				Error: AR_RAPI_REC_AMT_NEGATIVE AR_RAPI_RCPT_AMOUNT_NULL

Parameter	Туре	Data-type	Required	Description
p_factor_discount_a mount	IN	NUMBER		The bank charges on the cash receipt.
				Default: None
				Validation:
				1. Bank charges are not allowed if profile option AR: Create Bank Charges = 'No'.
				2. Bank charges not allowed if the receipt state, derived from the receipt class of the receipt method, \Leftrightarrow 'CLEARED'.
				3. If allowed, then ≥ 0 .
				Error: AR_BK_CH_NOT_ALLWD_IF_NOT_CLR, AR_JG_BC_AMOUNT_NEGATIVE
p_receipt_number	IN	VARCHAR2 (30)		The receipt number of the receipt to be created.
				Default: If not specified, the receipt number is defaulted from the document sequence value.
				Validation: Receipt number should not be null.
				Error: AR_RAPI_RCPT_NUM_NULL
p_receipt_date	IN	DATE		The receipt date of the entered cash receipt.
				Default: System date
				Validation: None
				Error: None

Parameter	Туре	Data-type	Required	Description
p_gl_date	IN	DATE		Date that this receipt will be posted to the general ledger.
				Default: Gets defaulted to the receipt date if it is a valid gl_date.
				Validation: The date is valid if the following conditions are true:
				• The date is in an Open or Future period
				 The period cannot be an Adjustment period
				If the date is invalid, then:
				 If the most recent open period is prior to the receipt date: last date of that period
				• If there is a period open after the receipt date: first date of the last open period
				Error: AR_INVALID_APP_GL_DATE
p_maturity_date	IN	DATE		Receipt maturity date.
				Default: Deposit date
				Validation: >= p_receipt_date
				Error: AR_RW_MAT_BEFORE_RCT_DATE
p_customer_id	IN	NUMBER (15)		The customer_id for the paying customer.
				Default: Refer to Defaulting, page 8-52.
				Validation:
				1. Customer exists and has prospect code = 'CUSTOMER'
				2. Customer has a profile defined at the customer level
				Error: AR_RAPI_CUST_ID_INVALID

Parameter	Туре	Data-type	Required	Description
p_customer_name	IN	VARCHAR2 (50)		The name for the entered customer. Used to default the customer id if not specified.
				Default: None
				Validation: None
				Error: AR_RAPI_CUS_NAME_INVALID
p_customer_number	IN	VARCHAR2 (30)		The customer number. Used to default the customer_id if not specified.
				Default: None
				Validation: None
				Error: AR_RAPI_CUS_NUM_INVALID
p_customer_bank_ac	IN	NUMBER (15)		The customer bank account id.
count_id				Default: From bank account id/number
				Validation:
				1. It must be a valid bank account of the paying customer .
				2. The inactive date (if defined) of the bank account should be greater than the receipt_date.
				3. The receipt date must be within the Start date and the End date of the bank account uses.
				Error: AR_RAPI_CUS_BK_AC_2_INVALID, AR_RAPI_CUS_BK_AC_ID_INVALID
p_customer_bank_ac count_num	IN	VARCHAR2 (30)		The customer bank account number. Used to default the customer bank account id, if not specified.
				Default: None
				Validation: None
				Error: None

Parameter	Туре	Data-type	Required	Description
p_customer_bank_ac count_name	IN	VARCHAR2 (80)		The customer bank account name. Used to default the customer bank account id, if not specified.
				Default: None
				Validation: None
				Error: None
p_location	IN	VARCHAR2 (40)		The Bill_To location for the customer. Used to derive the p_customer_site_use_id.
				Default: None
				Validation: None
				Error: AR_RAPI_CUS_LOC_INVALID
1	IN	NUMBER (15)		The Bill_To site_use_id for the customer.
_id				Default:
				1. Defaulted from customer location. Otherwise,
				2. Primary Bill_To customer site_use_id of the customer.
				Validation: It should be a valid Bill_To site of the paying customer.
				Error: AR_RAPI_CUS_SITE_USE_ID_INVALID
p_customer_receipt_ reference	IN	VARCHAR2 (30)		This column is used to store a customer receipt reference value supplied by the customer at the confirmation time.
				Default: None
				Validation: None
				Error: None

Parameter	Туре	Data-type	Required	Description
p_override_remit_ba nk_account_flag	IN	VARCHAR2 (1)		The flag value decides when the remittance bank account is can be overridden by the remittance selection process.
				Default: 'Y'
				Validation: valid values 'Y' and 'N'
				Error: AR_RAPI_INVALID_OR_REMIT_BK_AC
p_remittance_bank_ account_id	IN	NUMBER (15)		Identifies the user's bank account for depositing the receipt.
				Default:
				1. From remittance bank account number
				2. From the receipt method based on logic mentioned in Defaulting, page 8-18.
				Validation: Validation logic detailed in Validation, page 8-17.
				Error: AR_RAPI_REM_BK_AC_ID_INVALID, AR_RAPI_REM_BK_AC_ID_NULL
p_remittance_bank_ account_num	IN	VARCHAR2 (30)		The remittance bank account number. Used to default the remittance bank account id, if not specified.
				Default: None
				Validation: None
				Error: AR_RAPI_REM_BK_AC_NUM_INVALID
p_remittance_bank_ account_name	IN	VARCHAR2 (50)		The remittance bank account name. Used to default the remittance bank account id, if not specified.
				Default: None
				Validation: None
				Error: AR_RAPI_REM_BK_AC_NAME_INVALID

Parameter	Туре	Data-type	Required	Description
p_deposit_date	IN	DATE		The deposit date.
				Default: receipt date
				Validation: None
				Error: None
p_receipt_method_i	IN	NUMBER (15)		Identifies the receipt method of the receipt.
d				Default: From receipt method name.
				Validation: Validation detailed in Validation, page 8-17.
				Error: AR_RAPI_INVALID_RCT_MD_ID
p_receipt_method_n ame	IN	VARCHAR2 (30)		The receipt method name of the receipt. Used to default the receipt method id if not specified.
				Default: None
				Validation: None
				Error: None
				Note: To use credit card refund functionality, ensure that remittance of the original receipt is performed within Oracle Receivables. Do this by setting the remittance method on the receipt method's associated receipt class to <i>Standard</i> .
				Warning: If you use this API to both authorize and capture credit card payments, then set the remittance method to <i>None</i> . Note, however, that with this setting, you cannot use standard credit card refund functionality. Instead, you must refund such payments <i>outside</i> Receivables.

Parameter	Туре	Data-type	Required	Description
p_doc_sequence_val ue	IN	NUMBER		Value assigned to document receipt.
				Default: Detailed in Defaulting, page 8-18.
				Validation:
				 User should not pass in the value if the current document sequence is automatic.
				 Document sequence value should not be entered if profile option Sequential Numbering is set to Not Used.
				Error: AR_RAPI_DOC_SEQ_AUTOMATIC, AR_RAPI_DOC_SEQ_VAL_INVALID
p_ussgl_transaction_	IN	VARCHAR2 (30)		Code defined by public sector accounting.
code				Default: None
				Validation: None
				Error: None
p_anticipated_cleari IN ng_date	IN	DATE		Date the receipt is expected to be cleared.
				Default: None
				Validation: >= gl_date
				Error: AR_RW_EFFECTIVE_BEFORE_GL_DATE
p_event	IN	VARCHAR2		The event that resulted in the creation of the receipt. Currently used only by Bills Receivable.
				Default: None
				Validation: None
				Error: None

Parameter	Туре	Data-type	Required	Description
p_called_from	IN	VARCHAR2 (20)		This parameter is used to identify the calling routine. Currently used to identify only the 'BR_REMIT' program.
				Default: None
				Validation: None
				Error: None
p_attribute_record	IN	attribute_rec_t ype		This is a record type which contains all the 15 descriptive flexfield segments and one descriptive flexfield structure defining column. It represents the Receipt Information flexfield.
				Default: DFF APIs complete the defaulting and validation.
				Validation: DFF APIs complete the defaulting and validation.
				Error: AR_RAPI_DESC_FLEX_INVALID
p_global_attribute_r ecord	IN	global_attribut e_rec_type		This is a record type which contains all the 20 global descriptive flexfield segments and one global descriptive flexfield structure defining column.
				Default: None
				Validation: None
p_receipt_comments	IN	VARCHAR2 (240)		User's comments for the application.
p_issuer_name	IN	VARCHAR2 (50)		Issuer name of notes receivable (Asia Pacific requirement).
				Default: None
				Validation: None
				Error: None

Parameter	Туре	Data-type	Required	Description
p_issue_date	IN	DATE		Date when notes receivable was issued (Asia Pacific requirement).
				Default: None
				Validation: None
				Error: None
p_issuer_bank_branc h_id	IN	NUMBER (15)		Bank/ Branch issuing the notes receivable (Asia Pacific Requirement).
				Default: None
				Validation: None
				Error: None
p_cr_id	OUT	NUMBER (15)		The cash_receipt_id of the receipt created by the API call.
p_amount_applied	IN	NUMBER		The amount on the cash receipt that is to be applied to an account.
				Default: The default amount applied can be either the open amount of the transaction or the unapplied amount of the receipt, but you can change it. Use the AR: Always Default Transaction Balance for Applications profile option, <i>Oracle Receivables Implementation Guide</i> to control how Receivables defaults the applied amount.
				For the profile option's defaulting rules, see Ar_receipt_api_pub.Apply, page 8-20.
				Validation: Less than or equal to the amount due remaining on the receipt.
				Error: AR_RAPI_APPLIED_AMT_NULL, AR_RW_AMOUNT_LESS_THAN_APP

Parameter	Туре	Data-type	Required	Description
p_apply_date	IN	DATE		Date the application was applied.
				Default:
				1. Receipt date, if receipt date >= system date.
				2. System date, if receipt date < system date.
				Validation: apply date >= receipt date
				Error: AR_APPLY_BEFORE_RECEIPT
p_apply_gl_date	IN	DATE		Date that this application will be posted to the general ledger.
				Default: Defaulted to greater of the receipt date and the system date.
				Validation:
				 Validated as per standard gl date validation described for the gl date in create_cash routine
				2. >= receipt gl date
				Error: AR_INVALID_APP_GL_DATE AR_RW_GL_DATE_BEFORE_REC_GL
p_app_ussgl_transac	IN	VARCHAR2 (30)		Code defined by public sector accounting.
tion_code				Default: None
				Validation: None
p_app_attribute_rec ord	IN	attribute_rec_t ype		This is a record type which contains all the 15 descriptive flexfield segments and one descriptive flexfield structure defining column. It represents the Receipt Application Information flexfield.
				Default: DFF APIs complete the defaulting and validation.
				Validation: DFF APIs complete the defaulting and validation.
				Error: AR_RAPI_DESC_FLEX_INVALID

Parameter	Туре	Data-type	Required	Description
p_app_global_attrib ute_record	IN	global_attribut e_rec_type		This is a record type which contains all the 20 global descriptive flexfield segments and one global descriptive flexfield structure defining column.
				Default: None
				Validation: None
app_comments	IN	VARCHAR2 (240)		User's comments for the application.
p_application_ref_n um	IN	VARCHAR2 (30)		Deduction number, if resulting from Trade Management claim settlement.
p_secondary_applica tion_ref_id	IN	NUMBER (15)		Claim ID, if resulting from Trade Management claim settlement.
p_customer_referenc e	IN	VARCHAR2 (100)		Reference supplied by customer.
p_customer_reason	IN	VARCHAR2 (20)		Reason code supplied by customer.
p_secondary_app_re f_type	IN	VARCHAR2 (30)		Used for automated receipt handling, leave null.
p_secondary_app_re f_num	IN	VARCHAR2 (30)		Used for automated receipt handling, leave null.
p_call_payment_pro cessor	IN	VARCHAR2 (1)		This is the payment processing indicator flag. Pass as FND_API.G_TRUE, if you want to call it Payment payment APIs for credit card processing.
p_default_site_use	IN	VARCHAR2	No	Indicates if you want to default the site use from p_customer_site_use_id.
				The default value is Y. Pass N to default nothing.
				If the Require Billing Location for Receipts system option is selected, then no value is required here.

Example

Objective:

To create a cash receipt and apply to On Account in the functional currency using a call to the API Ar_receipt_api_pub.Create_Apply_on_acc and passing a minimum number of input parameters.

This table lists the entered parameters:

Parameter	Entered Value	Default Value
p_api_version	1.0	
p_receipt_number	'aj_test_api_3'	
p_amount	1000	
p_receipt_method_id	1001	
p_customer_name	'Computer Service and Rentals'	

This table lists the defaulted input parameters, which were not entered:

Parameter	Entered Value	Default Value
p_customer_id		1006
p_currency_code		USD
p_receipt_date		19-APR-2004
p_gl_date		19-APR-2004
p_deposit_date		19-APR-2004
p_customer_site_use_id		1025
p_override_remit_bank_acco unt_flag		'Υ'

Parameter	Entered Value	Default Value
p_remittance_bank_account_i d		10001
p_maturity_date		19-APR-2004
p_apply_gl_date		19-APR-2004
p_apply_date		19-APR-2004
p_amount_applied		1000
p_amount_applied_from		1000
p_call_payment_processor*		fnd_api.g_false

Result:

We were able to create the cash receipt 'aj_test_api_3' and then apply it to 'On account' by specifying only 5 input parameters in our call to this API. The receipt is in the functional currency. The retrieval and handling of the warnings and the error messages, put on the message stack by the API during execution, are the same as described in Defaulting, page 8-18.

Messages

Messages play an important role in the effectiveness of your API calls. The right message is raised at the right point to convey to you the exact error that has occurred or any warnings that have been raised.

The Receipt API puts on the message stack all error messages and warnings raised during execution. You can retrieve messages and warnings as described in Exception Handling and Result Messages, page 1-3.

WARNINGS AND ERRORS

The following table lists all the error messages raised by the Receipt API:

TYPE

E: Error message

W: Warning message

MESSAGE_CODE	MESSAGE_TEXT	EXPLANATION	TYPE
AR_APPLY_BEFORE_RECEIPT	Apply Date must be greater than or equal to the Receipt Date.		Е
AR_APPLY_BEFORE_TRANSACT ION	Apply Date must be greater than or equal to the Transaction Date.		E
AR_BK_CH_NOT_ALLWD_IF_NO T_CLR	For a receipt status other than cleared, bank charges are not allowed.		E
AR_EXCHANGE_RATE_NEGATI VE	Please enter a positive exchange rate.		E
AR_EXCHANGE_RATE_ZERO	The exchange rate cannot be zero.		Е
AR_INVALID_APP_GL_DATE	GL date, &GL_DATE, is not in an open or future-enterable period.		E
AR_JG_BC_AMOUNT_NEGATIVE	The Bank Charges amount cannot be negative.		E
AR_NO_PARTIAL_DISC	No discounts allowed on this installment unless it is fully paid.		E
AR_NO_RATE_DATA_FOUND	There is no rate for this currency, rate date and rate type in the database.		E
AR_OVERR_REM_BK_FLAG_INV ALID	Override remittance bank flag has invalid value.		E
AR_RAPI_CUS_BK_NAME_NUM _IGN	Customer bank account identifier has taken a precedence over the customer bank account name and number.		W
AR_RAPI_ACTIVITY_INVALID	The receivables activity name is invalid.		E

MESSAGE_CODE	MESSAGE_TEXT	EXPLANATION	TYPE
AR_RAPI_ACTIVITY_IGN	Both a receivables transaction identifier and a receivables activity exist for this record. The receivables transaction identifier takes precedence over the receivables activity.		W
AR_RAPI_TAX_RATE_AMT_X_IN VALID	Please enter a different combination of receipt amount, tax amount, and tax rate.		Е
AR_RAPI_TAX_CODE_INVALID	The tax code is invalid.		E
AR_RAPI_TAX_RATE_INVALID	The tax rate is invalid.		Е
AR_RAPI_TAX_CODE_IGN	Both a VAT identifier and a tax code exist for this record. The VAT identifier takes precedence over the tax code.		W
AR_RAPI_REC_TRX_ID_NULL	Please enter a receivables transaction identifier.		Е
AR_RAPI_VAT_TAX_ID_INVALI D	The VAT identifier is invalid.		Е
AR_RAPI_REF_TYPE_INVALID	The reference type is invalid.		Е
AR_RAPI_REF_NUM_INVALID	The reference number is invalid.		E
AR_RAPI_REF_NUM_IGN	Both a reference identifier and a reference number exist for this record. The reference identifier takes precedence over the reference number.		W
AR_RAPI_REF_ID_INVALID	The reference identifier is invalid.		E
AR_RAPI_REF_ID_NULL	Please enter a reference identifier.		Е

MESSAGE_CODE	MESSAGE_TEXT	EXPLANATION	TYPE
AR_RAPI_REF_TYPE_NULL	Please enter a reference type.		Е
AR_RAPI_ACTIVITY_X_INVALID	The specified combination of payment schedule identifier and receivables transaction identifier is invalid.	The activity type derived from the receivables_trx_id does not match with the activity type of the specified payment_schedule_id.	Е
AR_RAPI_AMT_APP_FROM_INV ALID	The allocated receipt amount and the applied amount should be same for the functional currency receipt.		Е
AR_RAPI_APP_PS_ID_INVALID	Applied payment schedule identifier has an invalid value.		E
AR_RAPI_APP_PS_RA_ID_X_INV ALID	Invalid receivable application identifier for the specified applied payment schedule identifier.		Е
AR_RAPI_APPLIED_AMT_NULL	Applied amount could not be defaulted.	The p_applied_amount was not specified by the user and it could not be defaulted from the specified receipt or the specified transaction. For explanation on defaulting mechanism refer Defaulting, page 8-29	E
AR_RAPI_CASH_RCPT_ID_INVA LID	Invalid cash receipt identifier.		E
AR_RAPI_CASH_RCPT_ID_NULL	Cash receipt identifier is null.		E
AR_RAPI_CC_RATE_AMTS_INV ALID	The entered combination of the applied amount, allocated amount and the cross currency rate is invalid.	This error is raised if the following condition is violated in the cross currency applications: p_trans_to_receipt_rate* p_amount_applied = p_amount_applied_from.	Е

MESSAGE_CODE	MESSAGE_TEXT	EXPLANATION	TYPE
AR_RAPI_CC_RATE_INVALID	Do not enter the cross currency rate if the receipt and the transaction are in same currency.	For the same currency receipt application, p_trans_to_receipt_rate should not be specified.	Е
AR_RAPI_CC_RATE_NULL	Cross currency rate is null.	In case of a cross currency receipt application, the p_trans_to_receipt_rate could neither be defaulted nor derived.	Е
AR_RAPI_CURR_CODE_INVALI D	Currency code is invalid.	The specified currency code has an invalid value.	E
AR_RAPI_CUS_BK_AC_2_INVALI D	Invalid combination of customer bank account name and number.	The specified combination of the p_customer_bank_account_num ber and p_customer_bank_account_nam e is invalid and cannot be used to derive the p_customer_bank_account_id.	E
AR_RAPI_CUS_BK_AC_ID_INVA LID	Customer bank account identifier is invalid.	The specified value of p_customer_bank_account_id is invalid.	Е
AR_RAPI_CUS_BK_AC_NAME_I NVALID	Customer bank account name is invalid.	The specified value of p_customer_bank_account_nam e is invalid.	E
AR_RAPI_CUS_BK_AC_NUM_IN VALID	Customer bank account number is invalid.	The specified value of p_customer_bank_account_num ber is invalid.	E
AR_RAPI_CUS_LOC_INVALID	Customer location is invalid for the specified customer.	The specified value of p_location has an invalid value.	E
AR_RAPI_CUS_NAME_INVALID	Invalid customer name.		E
AR_RAPI_CUS_NAME_NUM_IN VALID	Invalid combination of customer name and number.		E
AR_RAPI_CUS_NUM_INVALID	Invalid customer number.		E

MESSAGE_CODE	MESSAGE_TEXT	EXPLANATION	TYPE
AR_RAPI_CUS_SITE_USE_ID_INV ALID	Customer site use identifier is invalid for the specified customer.	The specified value of p_customer_site_use_id is invalid for the given customer. It should be a valid BILL_TO site_use_id for the customer.	Е
AR_RAPI_CUS_STE_USE_ID_NOT _DEF	Location could not be defaulted for the specified customer.	Neither the user had passed in any value for the p_location / p_customer_site_use_id, nor could it be defaulted to the primary Bill_To location for the given customer.	W
AR_RAPI_CUST_ID_INVALID	Customer identifier is invalid.		E
AR_RAPI_CUST_ID_NULL	Customer identifier is null.	The p_customer_id is null. For details, refer to API Usage, page 8-2.	E
AR_RAPI_CUS_NAME_NUM_IG N	Customer identifier has taken a precedence over name and number.	The specified values of p_customer_number and/or p_customer_name are ignored if the value for p_customer_id has been passed in.	W
AR_RAPI_CUST_TRX_ID_INVALI D	Invalid customer transaction identifier.		E
AR_RAPI_CUST_TRX_ID_NULL	Customer transaction identifier is null.		E
AR_RAPI_DEF_TAX_FLAG_INVA LID	Invalid deferred tax flag.	The valid values are 'Y'/'N'	Е
AR_RAPI_DESC_FLEX_INVALID	The entered values for the descriptive flexfield &DFF_NAME is invalid.		Е
AR_RAPI_DOC_SEQ_AUTOMATI C	You have passed in the document sequence value, even though the current document sequence is automatic.		E

MESSAGE_CODE	MESSAGE_TEXT	EXPLANATION	TYPE
AR_RAPI_DOC_SEQ_NOT_EXIST _A	Document sequence does not exist for the current document even though profile option Sequential Numbering is set to Always Used.		E
AR_RAPI_DOC_SEQ_NOT_EXIST _P	Document sequence does not exist for the current document even though profile option Sequential Numbering is set to Partially Used.		W
AR_RAPI_DOC_SEQ_VAL_INVA LID	Document sequence value should not be entered if profile option Sequential Numbering is set to Not Used.		E
AR_RAPI_DOC_SEQ_VALUE_NU LL_A	The profile option Sequential Numbering is set to Always Used and the document sequence is manual. The document sequence value is null.		E
AR_RAPI_DOC_SEQ_VALUE_NU LL_P	The profile option Sequential Numbering is set to Partially Used and the document sequence is manual. The document sequence value is null.		W
AR_RAPI_FUNC_CURR_DEFAUL TED	Functional currency defaulted as the receipt currency.		W
AR_RAPI_INS_PS_NOT_DEF_CUS	The customer could not be defaulted from the applied payment schedule identifier and the installment.	This error is raised if the customer_id cannot be derived from the p_applied_payment_schedule_i d and the p_installment specified in the create_and_apply routine.	Е
AR_RAPI_INSTALL_NULL	The installment number is null.		E
AR_RAPI_INVALID_APP_REF	Please supply a valid application reference type.		E

MESSAGE_CODE	MESSAGE_TEXT	EXPLANATION	TYPE
AR_RAPI_INVALID_CLAIM_ID	A valid claim ID &CLAIM_ID does not exist for the specified receipt and amount.		Е
AR_RAPI_INVALID_CLAIM_NU M	The claim is invalid. Please enter a different claim number.		Е
AR_RAPI_INVALID_REF_REASO N	Please supply a valid reference reason.		Е
AR_RAPI_MULTIPLE_ON_AC_A PP	More than one On Account application exists for the current receipt. Please specify the receivable application identifier.	This error is raised in the unapply_on_account routine if for the specified cash receipt, more than one On Account application exists and the p_receivable_application_id is not specified.	Е
AR_RAPI_NON_REVERSIBLE	Standard reversal not possible for this receipt.	Explanation: refer to Defaulting, page 8-68.	E
AR_RAPI_PSID_NOT_DEF_CUS	The customer could not be defaulted from the applied payment schedule identifier.	This error is raised in the create_and_apply routine if the customer is not entered and cannot be derived from the specified p_applied_payment_schedule_i d.	E
AR_RAPI_RCPT_AMOUNT_NUL L	Receipt amount is null.	This is a required field in the create_cash and the create_and_apply routines.	Е
AR_RAPI_RCPT_MD_ID_NULL	Receipt method identifier is null.		E
AR_RAPI_RCPT_MD_NAME_IGN	Receipt method identifier has taken precedence over receipt method name.		W

MESSAGE_CODE	MESSAGE_TEXT	EXPLANATION	TYPE
AR_RAPI_RCPT_MD_NAME_INV ALID	Invalid receipt method name.	This error is raised if the p_receipt_method_id is not passed in and the specified p_receipt_method_name is invalid.	Е
AR_RAPI_RCPT_NOT_APP_TO_I NV	There is no application of the entered receipt against the entered transaction.	This error is raised in the Unapply routine, if the specified receipt has no application against the specified transaction.	Е
AR_RAPI_RCPT_NUM_IGN	Cash receipt identifier has taken a precedence over the receipt number.		W
AR_RAPI_RCPT_NUM_INVALID	Invalid receipt number.		E
AR_RAPI_RCPT_RA_ID_X_INVA LID	Invalid combination of receivable application identifier and the cash receipt identifier.	The p_cash_receipt_id derived from the p_receivable_application_id specified by the user does not match with the p_cash_receipt_id which is either specified by the user or defaulted from the p_receipt_number.	Е
AR_RAPI_RCT_MD_ID_INVALID	Invalid receipt method identifier.		E
AR_RAPI_RCPT_MD_NAME_INV ALID	Invalid receipt method name.		Е
AR_RAPI_REC_APP_ID_INVALID	Invalid receivable application identifier.		E
AR_RAPI_REC_APP_ID_NULL	Receivable application identifier is null.	BR	E
AR_RAPI_REC_TRX_ID_INVALID	Invalid receivable transaction identifier.		E

MESSAGE_CODE	MESSAGE_TEXT	EXPLANATION	TYPE
AR_RAPI_REM_BK_AC_2_INVAL ID	Invalid combination of remittance bank account name and number.	The specified combination of the p_remittance_bank_account_nu mber and p_remittance_bank_account_na me is invalid, and cannot be used to derive the p_remittance_bank_account_id.	E
AR_RAPI_REM_BK_AC_ID_INVA LID	Invalid remittance bank account identifier.	This error is raised if the specified p_remittance_bank_account_id is not associated with the specified p_receipt_method_id.	Е
AR_RAPI_REM_BK_AC_ID_NULL	Remittance bank account identifier is null.		E
AR_RAPI_REM_BK_AC_NAME_I NVALID	Invalid remittance bank account name.		E
AR_RAPI_REM_BK_AC_NAME_N UM_IGN	Remittance bank account identifier has taken a precedence over the remittance bank account name and number.		W
AR_RAPI_REM_BK_AC_NUM_IN VALID	Invalid remittance bank account number.		E
AR_RAPI_REV_CAT_CD_INVALI D	Invalid reversal category code.		E
AR_RAPI_REV_CAT_CD_NULL	Reversal category code is null.		E
AR_RAPI_REV_CAT_NAME_IGN	Reversal category code has taken precedence over the reversal category name.		W
AR_RAPI_REV_CAT_NAME_INV ALID	Invalid reversal category name.		E
AR_RAPI_REV_GL_DATE_NULL	Reversal GL date is null.		E

MESSAGE_CODE	MESSAGE_TEXT	EXPLANATION	TYPE
AR_RAPI_REV_REAS_CD_INVAL ID	Invalid reversal reason code.		E
AR_RAPI_REV_REAS_CD_NULL	Reversal reason code is invalid.		Е
AR_RAPI_REV_REAS_NAME_IG N	Reversal reason code has taken a precedence over the reversal reason name.		W
AR_RAPI_REV_REAS_NAME_IN VALID	Invalid reversal reason name.		E
AR_RAPI_TRX_ID_INST_INVALI D	Invalid combination of the customer transaction identifier and installment.		E
AR_RAPI_TRX_INS_NOT_DEF_C US	The customer could not be defaulted from the entered transaction and the installment.	This error is raised in the create_and_apply routine if the customer is not entered and cannot be derived from the specified transaction and installment.	Е
AR_RAPI_TRX_INS_PS_NOT_DEF _CUS	The customer could not be defaulted from the entered transaction, installment and applied payment schedule identifier.	This error is raised in the create_and_apply routine if the customer is not entered and cannot be derived from the specified p_customer_trx_id/trx_number, p_installment and p_applied_payment_schedule_i d.	Е
AR_RAPI_TRX_LINE_AMT_DEFL T	Amount applied has been defaulted to the line amount of the specified transaction line.		W
AR_RAPI_TRX_LINE_ID_INVALI D	Invalid customer transaction line identifier.		E
AR_RAPI_TRX_LINE_NO_INVAL ID	Invalid transaction line number.		E

MESSAGE_CODE	MESSAGE_TEXT	EXPLANATION	TYPE
AR_RAPI_TRX_NOT_DEF_CUST	The customer could not be defaulted from the entered transaction.	This error is raised in the create_and_apply routine if the customer is not entered and cannot be derived from the specified p_customer_trx_id/trx_number.	Е
AR_RAPI_TRX_NUM_IGN	Customer transaction identifier has taken a precedence over the transaction number.		W
AR_RAPI_TRX_NUM_INST_INVA LID	Invalid combination of transaction number and installment.		E
AR_RAPI_TRX_NUM_INVALID	Invalid transaction number.		E
AR_RAPI_TRX_PS_ID_X_INVALI D	Invalid applied payment schedule identifier for the specified transaction.	The p_applied_payment_schedule_i d specified by the user does not match with the payment_schedule_id derived from the p_customer_trx_id and the p_installment.	Е
AR_RAPI_TRX_PS_NOT_DEF_CU S	The customer could not be defaulted from the entered transaction and the applied payment schedule identifier.	This error is raised in the create_and_apply routine if the customer is not entered and cannot be derived from the specified p_customer_trx_id/trx_number and the p_applied_payment_schedule_i d.	Е
AR_RAPI_TRX_RA_ID_X_INVALI D	The activity type for the entered receivable transaction identifier does not match with the activity of the entered payment schedule identifier.	This message is to be used by the API, activity_application, added as part of the Bills Receivables changes.	E
AR_RAPI_USR_CURR_CODE_IG N	Currency code took a precedence over the user currency code.		W

MESSAGE_CODE	MESSAGE_TEXT	EXPLANATION	TYPE
AR_RAPI_USR_CURR_CODE_INV ALID	User currency code is invalid.		Е
AR_RAPI_USR_X_RATE_TYP_IN VALID	User exchange rate type is invalid.		E
AR_RAPI_USR_X_RATE_TYPE_IG N	Exchange rate type took a precedence over the User exchange rate type.		W
AR_RAPI_X_RATE_DATE_INVAL ID	Invalid exchange rate date.		E
AR_RAPI_X_RATE_INVALID	Exchange rate should not be entered. This would be raised if the exchange rate type is not 'User and the exchange rate has been specified.		Е
AR_RAPI_X_RATE_NULL	Exchange rate is null.		Е
AR_RAPI_X_RATE_TYPE_INVALI D	Invalid exchange rate type.		E
AR_RAPI_X_RATE_TYPE_NULL	Exchange rate type is null.		E
AR_RW_AMOUNT_LESS_THAN_APP	The receipt amount cannot be less than the sum of the applied and on-account amounts.		Е
AR_RW_APP_NEG_ON_ACCT	Amount applied cannot be negative for an On Account application.		Е
AR_RW_APP_NEG_UNAPP	You may not apply more than the receipt amount.	This error is raised if you try to apply more than the unapplied amount on the receipt against a transaction.	Е

MESSAGE_CODE	SSAGE_CODE MESSAGE_TEXT		TYPE
AR_RW_APPLIED_GREATER_LI NE	Amount applied cannot be greater than the original line amount of &AMOUNT.	This error is raised in the apply and create_and_apply routines if the line number of transaction has been specified and the amount applied is greater than the original line amount of the transaction line.	Е
AR_RW_BEFORE_APP_GL_DATE	Reversal GL Date must be on or after original GL Date of &GL_DATE.		E
AR_RW_BEFORE_RECEIPT_GL_D ATE	The Reversal GL Date cannot be before the Receipt GL Date.		E
AR_RW_CASH_DUPLICATE_REC EIPT	A cash receipt with this number, date, amount and customer already exists.		E
AR_RW_CC_RATE_POSITIVE	Cross currency rate must be greater than zero.	This error is raised in the apply and create_and_apply routines if the p_trans_to_receipt_rate has a negative value.	E
AR_RW_GL_DATE_BEFORE_REC _GL	The GL date cannot be before the receipt GL date.	This error is raised in the apply and the create_and_apply routines if the apply gl_date is before the receipt gl_date.	E
AR_RW_GL_DATE_BEFORE_OPE N_REC_GL	The application GL date must be later than the open receipt GL date for a receipt-to-receipt application.		E
AR_RW_MAT_BEFORE_RCT_DA TE	The Maturity Date cannot be before the Receipt Date.		Е
AR_RW_NET_DIFF_RCT_CURR	Both receipts in a receipt to receipt application must have the same currency.		E

MESSAGE_CODE	MESSAGE_TEXT	EXPLANATION	TYPE
AR_RW_NET_OPEN_AMT_INC	A receipt-to-receipt application must decrease the open receipt balance or bring the receipt balance closer to zero.		E
AR_RW_NET_OPEN_RCT_ONLY	Netting is allowed on open receipts only (unapplied cash, on-account cash and claim investigation applications).		E
AR_RW_NET_UNAPP_OVERAPP	Unapplying this payment netting application is not allowed because it would cause the applied receipt balance to become negative.		
AR_RW_NO_DISCNT	Discounts are not permitted for transactions with a negative original balance.		Е
AR_RW_PAID_INVOICE_TWICE	You have paid the same invoice twice. Please correct.		Е
AR_RW_RCT_AMOUNT_NEGATI VE	You cannot enter a negative receipt amount for cash receipts.		Е
AR_RW_VAL_DISCOUNT	Discount taken is greater than the discount available (&DISC_AVAILABLE).		E
AR_RW_VAL_NEG_DISCNT	Discount cannot be negative.		E
AR_RW_VAL_ONACC_DISC	Discount not allowed for On Account application. Clear discount amount field or enter zero.		E
AR_RW_VAL_UNEARNED_DISC OUNT	Cannot take unearned discount because the Allow Unearned Discount system option is set to No.		Е

MESSAGE_CODE	MESSAGE_TEXT	EXPLANATION	TYPE
AR_SYSTEM_WR_NO_LIMIT_SET	Please set the receipt write-off limits range system option.		E
AR_VAL_GL_INV_GL	The GL date should not be prior to the invoice's GL date.		E
AR_WR_NO_LIMIT	User Write-off limit does not exist.		E
AR_WR_TOTAL_EXCEED_MAX_AMOUNT	The total write-off amount must fall within the receipt write-off limits range system option.		E
AR_WR_USER_LIMIT	Total write-off amount must be in the range of &FROM_AMOUNT to &TO_AMOUNT.		Е

Revenue Adjustment API User Notes

Overview

This document outlines the specifications and the methodology for using the various Revenue Adjustment APIs. These APIs provide an extension to existing functionality of adjusting revenue and sales credits through the standard AR Revenue Management form.

You can access these APIs:

- As standard PL/SQL servers-side routine calls
- Through Forms, utilizing the capability of Forms6 to have a procedure as its underlying base table

Basic Business Needs

The Revenue Adjustment API addresses the following basic functionality via different API calls:

- Unearning revenue
- Earning revenue
- Transferring sales credits between salespersons
- Adding new non-revenue sales credits

Presently, the main business need for the API is the requirement to have event-based revenue recognition. In Receivables, you can defer revenue recognition, and earn the revenue at a later date using the API. Throughout the process, the API uses AutoAccounting to determine the accounts to be debited/credited with each operation.

API Usage

To earn and unearn revenue, transfer sales credits, and add non-revenue sales credits at the transaction, item, category, or transaction line level, you can call the following four PL/SQL APIs:

- AR RevenueAdjust PUB. Unearn Revenue, page 9-2: Transfers the specified amount of revenue from the revenue account to the unearned revenue account on the specified transaction lines.
- AR_RevenueAdjust_PUB.Earn_Revenue, page 9-16: Transfers the specified amount of revenue from the unearned revenue account to the revenue account on the specified transaction lines.
- AR_RevenueAdjust_PUB.Transfer_Sales_Credits, page 9-18: Transfers revenue and/or non-revenue sales credits between salespersons on the specified transaction lines. In the case of revenue sales credits, the associated revenue is also transferred between cost centers, assuming that AutoAccounting derives the cost center segment of the accounting flexfield from the salesperson.
- AR_RevenueAdjust_PUB.Add_Non_Revenue_Sales_Credits, page 9-23: Adds nonrevenue sales credits for any salesperson to the specified transaction lines.
- AR_Revenueadjust_PUB.Record_Customer_Acceptance, page 9-27: Removes customer acceptance contingencies and enables revenue recognition.
- AR_Revenueadjust_PUB.Update_Contingency_Expirations, page 9-28: Updates the expiration date and period for specific time-based contingencies.

For all options, a specific amount or percentage of the total value can be specified. All available revenue can also be specified, except for Add_Non_Revenue_Sales_Credits, where this is not applicable.

Note: You cannot specify *both* revenue and nonrevenue sales credits when passing sales group information to the above APIs.

AR_RevenueAdjust_PUB.Unearn_Revenue

Call this routine to move revenue from the earned revenue account to the unearned revenue account using AutoAccounting. This API routine has 4 input and 5 output parameters in total. One of the input parameters is a record type that holds all the revenue adjustment information and has 120 elements. The output parameters include the revenue_adjustment_number and revenue_adjustment_id of the revenue adjustment.

The following is the breakdown of the parameters:

Input

Standard API parameters: 3

Revenue Adjustment parameters: 1 (revenue adjustment record type)

Output

Standard API parameters: 3

Revenue Adjustment parameters: 2

Parameter Descriptions

The input revenue adjustment parameter is a record of type $AR_Revenue_Adjustment_PVT.Rev_Adj_Rec_Type.$

```
TYPE Rev_Adj_Rec_Type IS RECORD
     (CUSTOMER_TRX_ID
                                   NUMBER (15)
     ,TRX_NUMBER
                                  RA_CUSTOMER_TRX.trx_number%TYPE
     ,BATCH_SOURCE_NAME
                                   RA_BATCH_SOURCES.name%TYPE
     ,ADJUSTMENT_TYPE
                                  VARCHAR2(15) DEFAULT 'UN'
     ,FROM_SALESREP_ID
                                  NUMBER (15)
     ,FROM_SALESREP_NUMBER
                                  RA_SALESREPS.salesrep_number%TYPE
     ,TO_SALESREP_ID
                                  NUMBER (15)
     ,TO_SALESREP_NUMBER
                                  RA_SALESREPS.salesrep_number%TYPE
     ,FROM_SALESGROUP_ID
                                   jtf_rs_groups_b.group_id%TYPE
     ,TO_SALESGROUP_ID
                                   jtf_rs_groups_b.group_id%TYPE
                                   VARCHAR2(15) DEFAULT 'R'
     ,SALES_CREDIT_TYPE
     , AMOUNT_MODE
                                   VARCHAR2(15) DEFAULT 'T'
     , AMOUNT
                                   NUMBER
     , PERCENT
                                  NUMBER
     ,LINE_SELECTION_MODE
                                  VARCHAR2(15) DEFAULT 'A'
     ,FROM_CATEGORY_ID
                                  NUMBER (15)
     ,FROM_CATEGORY_SEGMENT1
                                  VARCHAR2 (40)
     ,FROM_CATEGORY_SEGMENT2
                                   VARCHAR2 (40)
     ,FROM_CATEGORY_SEGMENT3
                                  VARCHAR2(40)
     ,FROM_CATEGORY_SEGMENT4
                                   VARCHAR2 (40)
     ,FROM_CATEGORY_SEGMENT5
                                  VARCHAR2 (40)
     , {\tt FROM\_CATEGORY\_SEGMENT6}
                                   VARCHAR2 (40)
     ,FROM_CATEGORY_SEGMENT7
                                   VARCHAR2 (40)
     ,FROM_CATEGORY_SEGMENT8
                                   VARCHAR2 (40)
     ,FROM_CATEGORY_SEGMENT9
                                   VARCHAR2 (40)
     ,FROM_CATEGORY_SEGMENT10
                                  VARCHAR2(40)
     ,FROM_CATEGORY_SEGMENT11
                                   VARCHAR2 (40)
     ,FROM_CATEGORY_SEGMENT12
                                   VARCHAR2 (40)
     ,FROM_CATEGORY_SEGMENT13
                                   VARCHAR2 (40)
     ,FROM_CATEGORY_SEGMENT14
                                  VARCHAR2 (40)
     ,FROM_CATEGORY_SEGMENT15
                                   VARCHAR2 (40)
     ,FROM_CATEGORY_SEGMENT16
                                   VARCHAR2 (40)
     ,FROM_CATEGORY_SEGMENT17
                                   VARCHAR2 (40)
     FROM CATEGORY SEGMENT18
                                   VARCHAR2 (40)
     ,FROM_CATEGORY_SEGMENT19
                                  VARCHAR2 (40)
     ,FROM_CATEGORY_SEGMENT20
                                  VARCHAR2 (40)
     ,TO_CATEGORY_ID
                                  NUMBER (15)
     ,TO_CATEGORY_SEGMENT1
                                  VARCHAR2(40)
     ,TO_CATEGORY_SEGMENT2
                                   VARCHAR2 (40)
     ,TO_CATEGORY_SEGMENT3
                                   VARCHAR2 (40)
     ,TO_CATEGORY_SEGMENT4
                                   VARCHAR2 (40)
     ,TO_CATEGORY_SEGMENT5
                                   VARCHAR2 (40)
     ,TO_CATEGORY_SEGMENT6
                                   VARCHAR2 (40)
     ,TO_CATEGORY_SEGMENT7
                                   VARCHAR2 (40)
     ,TO_CATEGORY_SEGMENT8
                                  VARCHAR2 (40)
     ,TO_CATEGORY_SEGMENT9
                                   VARCHAR2 (40)
     ,TO_CATEGORY_SEGMENT10
                                   VARCHAR2 (40)
     ,TO_CATEGORY_SEGMENT11
                                   VARCHAR2 (40)
     ,TO_CATEGORY_SEGMENT12
                                   VARCHAR2 (40)
                                   VARCHAR2(40)
     ,TO_CATEGORY_SEGMENT13
     ,TO_CATEGORY_SEGMENT14
                                   VARCHAR2 (40)
     ,TO_CATEGORY_SEGMENT15
                                   VARCHAR2 (40)
     ,TO_CATEGORY_SEGMENT16
                                   VARCHAR2 (40)
     ,TO_CATEGORY_SEGMENT17
                                   VARCHAR2 (40)
     ,TO_CATEGORY_SEGMENT18
                                   VARCHAR2 (40)
     ,TO_CATEGORY_SEGMENT19
                                   VARCHAR2 (40)
     ,TO_CATEGORY_SEGMENT20
                                   VARCHAR2 (40)
     ,FROM_INVENTORY_ITEM_ID
                                  NUMBER (15)
     ,FROM_ITEM_SEGMENT1
                                   VARCHAR2 (40)
     ,FROM_ITEM_SEGMENT2
                                   VARCHAR2 (40)
                                   VARCHAR2 (40)
     ,FROM_ITEM_SEGMENT3
     ,FROM_ITEM_SEGMENT4
                                  VARCHAR2 (40)
     FROM ITEM SEGMENT5
                                  VARCHAR2 (40)
     ,FROM_ITEM_SEGMENT6
                                  VARCHAR2 (40)
                                  VARCHAR2 (40)
     ,FROM_ITEM_SEGMENT7
```

```
,FROM_ITEM_SEGMENT8
                                                                                             VARCHAR2(40)
                , FROM_ITEM_SEGMENT10 VARCHAR2(40)
,FROM_ITEM_SEGMENT11 VARCHAR2(40)
,FROM_ITEM_SEGMENT11

        ,FROM_ITEM_SEGMENTI1
        VARCHAR2 (40)

        ,FROM_ITEM_SEGMENT12
        VARCHAR2 (40)

        ,FROM_ITEM_SEGMENT13
        VARCHAR2 (40)

        ,FROM_ITEM_SEGMENT14
        VARCHAR2 (40)

        ,FROM_ITEM_SEGMENT15
        VARCHAR2 (40)

        ,FROM_ITEM_SEGMENT16
        VARCHAR2 (40)

        ,FROM_ITEM_SEGMENT17
        VARCHAR2 (40)

        ,FROM_ITEM_SEGMENT18
        VARCHAR2 (40)

        ,FROM_ITEM_SEGMENT19
        VARCHAR2 (40)

        ,FROM_ITEM_SEGMENT20
        VARCHAR2 (40)

        ,FROM_ITEM_SEGMENT1
        VARCHAR2 (40)

        ,FROM_ITEM_SEGMENT2
        VARCHAR2 (40)

        ,TO_INVENTORY_ITEM_ID
        NUMBER (15)

        ,TO_ITEM_SEGMENT1
        VARCHAR2 (40)

        ,TO_ITEM_SEGMENT3
        VARCHAR2 (40)

        ,TO_ITEM_SEGMENT3
        VARCHAR2 (40)

        ,TO_ITEM_SEGMENT5
        VARCHAR2 (40)

        ,TO_ITEM_SEGMENT6
        VARCHAR2 (40)

        ,TO_ITEM_SEGMENT7
        VARCHAR2 (40)

        ,TO_ITEM_SEGMENT10
        VARCHAR2 (40)

        ,TO_ITEM_SEGMENT11
        VARCHAR2 (40)

        ,TO_ITEM_SEGMENT13
        VARCHAR2 (40)

        ,TO_ITEM_SEGMENT16
        VARCHAR2 (40)

        ,TO_ITEM_SEGMENT17

                 ,FROM_ITEM_SEGMENT12
                                                                                                              VARCHAR2(40)
                COMMENTS VARCHAR2(15)

ATTRIBUTE_CATEGORY VARCHAR2(30)

ATTRIBUTE1 VARCHAR2(150)

ATTRIBUTE2
                                                                                                             VARCHAR2(150)
                ,ATTRIBUTE2
                                                                                                              VARCHAR2(150)
                ,ATTRIBUTE3
                ,ATTRIBUTE4
                                                                                                                VARCHAR2(150)
                 ,ATTRIBUTE5
                                                                                                                  VARCHAR2(150)
                                                                                                            VARCHAR2(150)
                 ,ATTRIBUTE6
                                                                                                            VARCHAR2(150)
                ,ATTRIBUTE7
                                                                                                              VARCHAR2(150)
                ,ATTRIBUTE8
                                                                                                            VARCHAR2(150)
                ,ATTRIBUTE9
                                                                                                                   VARCHAR2(150)
                 ,ATTRIBUTE10
                                                                                                                VARCHAR2(150)
                 ,ATTRIBUTE11
                 ,ATTRIBUTE12
                                                                                                                VARCHAR2(150)
                ,ATTRIBUTE13
                                                                                                                 VARCHAR2(150)
                 ,ATTRIBUTE14
                                                                                                                   VARCHAR2(150)
                                                                                                                    VARCHAR2(150));
                 ,ATTRIBUTE15
```

The following table lists standard API parameters that are common to all the routines in the Revenue Adjustment API.

Parameter	Туре	Data-type	Required	Default Value	Description
p_api_version	IN	NUMBER	Yes		Used to compare version numbers of incoming calls to its current version number. Unexpected error is raised if version incompatibility exists. In the current version of the API, you should pass in a value of 1.0 for this parameter.
p_init_msg_list	IN	VARCHAR2		FND_API. G_FALSE	Allows API callers to request that the API does initialization of the message list on their behalf.
p_commit	IN	VARCHAR2		FND_API. G_FALSE	Used by API callers to ask the API to commit on their behalf.
p_rev_adj_rec	IN	AR_Revenue _Adjustment _PVT. Rev_Adj_Rec _Type	Yes	See break- down below for individual elements	Revenue Adjustment record type
x_return_status	OUT	VARCHAR2			Represents the API overall return status. Detailed in Return Status, page 1-4.
x_msg_count	OUT	NUMBER			Number of messages in the API message list.
x_msg_data	OUT	VARCHAR2			This is the message in encoded format if x_msg_count=1.
x_adjustment_id	OUT	NUMBER			The ID of the resulting revenue adjustment.
x_adjustment_n umber	OUT	VARCHAR2			The user visible number of the resulting revenue adjustment.

The following table lists Rev_Adj_Rec_Type elements that are relevant to Unearn_Revenue:

> Note: If required parameters are not passed in a call to this API, then the call will fail. However, depending on the business scenario, you

will have to pass in values for other parameters to successfully create the business object. Otherwise, error messages will be reported.

At least one of the numbered sets of parameters is required.

Parameter	Data-type	Required	Description
p_customer_trx_id	NUMBER(15)	1	The ID of the transaction on which revenue is to be adjusted.
			Default: None
			Validation: Must exist if specified. Must not have a class of 'CB','DM','BR','DEP','GUAR' (that is. chargeback, debit memo, bills receivable, deposit, guarantee). Must not have had credit memo(s) raised against the full transaction value. Warning if partial credit memo has been raised. Every line must have revenue sales credits adding to 100%.
			Errors: AR_TAPI_TRANS_NOT_EXIST AR_TW_INCORRECT_SALESCREDIT AR_RA_CB_DISALLOWED AR_RA_DM_DISALLOWED AR_RA_BR_DISALLOWED AR_RA_DEP_DISALLOWED AR_RA_GUAR_DISALLOWED AR_TW_INCORRECT_SALESCREDIT AR_RA_FULL_CREDIT
			Warnings: AR_RA_PARTIAL_CREDIT
trx_number	ra_customer_trx. trx_number%TYPE	1	The user visible transaction number Default: None Validation: Ignored if customer_trx_id has a
			value. Must be unique. Batch source can be optionally passed as extra assurance of uniqueness - then must be unique for that batch source. Otherwise, validation is the same as for customer_trx_id.
			Errors: AR_RA_TRX_NOTFOUND AR_RA_TRX_TOO_MANY_ROWS

Parameter	Data-type	Required	Description
batch_source_name	ra_batch_sources. name%TYPE		Name of the batch source associated with the trx_number, if specified. Only used in association with trx_number to help ensure uniqueness.
			Default: None
			Validation: Ignored if trx_number is not passed. If an invalid string is passed, the trx not found message will result.
adjustment_type	VARCHAR2(15)		Type of revenue adjustment. This element should be left null.
			Default: 'UN'
from_salesrep_id	NUMBER(15)		The ID of the salesperson whose revenue is being adjusted.
			Validation: If specified, must exist, must be currently active, and must have been active on transaction date. Must have revenue sales credits on at least one line on the transaction.
			Error: AR_TAPI_INVALID_SALESREP_ID AR_RA_SALESREP_NOT_ON_TRX
from_salesrep_number	ra_salesreps. salesrep_number%		The user visible number of the salesperson whose revenue is being adjusted.
	TYPE		Validation: Ignored if from_salesrep_id is specified. Otherwise, validation is as for from_salesrep_id.
			Error: AR_RA_INAVLID_SALESREP_NUMBER
to_salesrep_id	NUMBER		Not used for unearning revenue and should be left null.
to_salesrep_number	VARCHAR2(30)		Not used for unearning revenue and should be left null.

Parameter	Data-type	Required	Description
from_salesgroup_id	jtf_rs_groups_b. group_id%TYPE		The ID of the sales group of the salesperson whose revenue is being adjusted.
			Validation: Must have revenue sales credits on at least one line on the transaction.
			Error: AR_RA_SALESREP_NOT_ON_TRX
to_salesgroup_id	jtf_rs_groups_b. group_id%TYPE		Not used for unearning revenue and should be left null.
sales_credit_type	VARCHAR2(15)		Not used for unearning revenue and should be left null.
amount_mode	VARCHAR2(15)		The amount mode specifies whether an amount, a percentage (of total value of selected lines), or all adjustable revenue is to be adjusted. Possible values are:
			T - total adjustable revenue
			• A - amount
			• P - percent
			Default: 'T'
			Validation: Must be one of the above values
			Error: AR_RA_INVALID_AMOUNT_MODE
amount	NUMBER		The amount of revenue to be adjusted
			Default: None
			Validation: Ignored unless amount_mode = 'A', in which case it must have a value. Must be =< total recognized revenue for selected lines, and salesperson (if specified).
			Errors: AR_RA_AMT_EXCEEDS_AVAIL_REV AR_RA_ZERO_AMOUNT

Parameter	Data-type	Required	Description
percent	NUMBER		The percentage of total selected transaction line value to be adjusted.
			Default: None
			Validation: Ignored unless amount_mode = 'P' in which case it must have a value. Must be =< percentage of total value of selected lines represented by recognized revenue for selected lines, and salesperson (if specified).
			Errors: AR_RA_PCT_EXCEEDS_AVAIL_PCT AR_RA_ZERO_AMOUNT
line_selection_mode	VARCHAR2(15)		The line selection mode determines how lines were selected for adjustment.
			Possible values are:
			• A - All transaction lines
			C - Specific category
			• I - Specific item
			• S - Specific line.
			Default: 'A'
			Validation: Must be one of the above values
			Error: AR_RA_INVALID_LINE_MODE
from_category_id	NUMBER(15)		The ID of the item category used to identify the lines to be adjusted.
			Default: None
			Validation: Must be a valid category ID, and there must be lines on the transaction that have items belonging to this category. Must be specified if line selection mode = 'C'.
			Errors: AR_RA_NO_FROM_CATEGORY AR_RA_INVALID_CATEGORY_ID AR_RA_CATEGORY_NOT_ON_TRX

Parameter	Data-type	Required	Description
from_category_segment1 -	VARCHAR2(40)		Segments 1 to 20 of the category flexfield
from_category_segment20			Default: None
			Validation: Ignored if from_category_id has a value. Enough segment values to uniquely identify a category must be passed - ideally all defined segments. Otherwise, validation is the same as for from_category_id.
			Error: AR_RA_INVALID_CAT_SEGMENTS
to_category_id	NUMBER(15)		Not currently used and should be left null.
to_category_segment1 - to_category_segment20	VARCHAR2(40)		Not currently used and should be left null.
from_inventory_item_id	NUMBER(15)		The ID of the inventory item used to identify the lines to be adjusted.
			Default: None
			Validation: Must be a valid inventory item ID and there must be lines on the transaction that have items with this ID. Must be specified if line selection mode = 'I'.
			Errors: AR_RA_NO_FROM_ITEM AR_RA_INVALID_ITEM_ID AR_RA_ITEM_NOT_ON_TRX
from_item_segment1 -	VARCHAR2(40)		Segments 1 to 20 of the item flexfield
from_item_segment20			Default: None
			Validation: Ignored if from_inventory_item_id has a value. Enough segment values to uniquely identify an item must be passed - ideally all defined segments. Otherwise, validation is the same as for from_inventory_item_id.
			Error: AR_RA_INVALID_ITEM_SEGMENTS
to_inventory_item_id	NUMBER(15)		Not currently used and should be left null.

Parameter	Data-type	Required	Description
to_item_segment1 - to_item_segment20	VARCHAR2(40)		Not currently used and should be left null.
from_cust_trx_line_id	NUMBER(15)		The ID of the transaction line to be adjusted.
			Default: None
			Validation: Must be a valid line ID on the transaction. Must be specified if line selection mode = 'S' and from_line_number is null.
			Errors: AR_RA_NO_FROM_LINE AR_RA_INVALID_LINE_ID
from_line_number	NUMBER(15)		The user visible transaction line number.
			Default: None
			Validation: Ignored if from_cust_trx_line_id has a value. Must be a valid line number on the transaction.
			Errors: AR_RA_NO_FROM_LINE AR_RA_LINE_NOT_ON_TRX

Parameter	Data-type	Required	Description
gl_date	DATE		Date that adjusted revenue will be posted to the general ledger if revenue is recognized immediately. Start date of revenue recognition if revenue is deferred.
			Default: Gets defaulted to the current date if it is a valid gl_date.
			Validation: Ignored for lines that have non- deferred accounting rules AND a duration > 1. It is valid if the following conditions are true:
			 The date is in an Open or Future period, or it is in a Never Opened period and the Allow Not Open Flag is set to Yes.
			 The date is greater than or equal to the trx_date
			 The period cannot be an Adjustment period.
			If the date passed is not valid, then a warning message is written to the stack and the date is automatically overridden with a valid date using the default:
			• If the most recent open period is prior to the current date: last date of that period
			• If there is a period open after the current date: first date of the last open period
			Warning: AR_RA_GL_DATE_CHANGED
reason_code	VARCHAR2(15)	Yes	Lookup code for revenue adjustment reason
			Default: None
			Validation: Must be defined under AR lookup type 'REV_ADJ_REASON'
			Error: AR_RA_INVALID_REASON_CODE

Parameter	Data-type	Required	Description
comments	VARCHAR2 (2000)		Free text
			Default: None
			Validation: None
attribute_category	VARCHAR2(30)		Context of the revenue adjustment descriptive flexfield.
			Default: None
			Validation: None
attribute1 - attribute15	VARCHAR2(150)		Attributes of the revenue adjustment descriptive flexfield
			Default: None
			Validation: Standard descriptive flexfield validation

Example

Objective:

To unearn all revenue on a transaction using a call to *AR_RevenueAdjust_PUB*. *Unearn_Revenue* and passing a minimum number of input parameters.

This table lists the entered parameters:

Parameter	Entered Value	Default Value
p_api_version	2.0	
p_init_msg_list	FND_API.G_TRUE	
p_rev_adj_rec.trx_number	'test_api_1'	
p_rev_adj_rec.reason_code	'RA'	

This table lists the defaulted input parameters, which were not entered:

Parameter	Entered Value	Default Value
p_rev_adj_rec.amount_mode		'T'
p_rev_adj_rec. line_selection_mode		'A'
p_rev_adj_rec.gl_date		SYSDATE

The API call in this case would be:

```
AR_RevenueAdjust_PUB.Unearn_Revenue(
  p_rev_adj_rec.trx_number => 'test_api_1',
  p_rev_adj_rec.reason_code => 'RA',
```

After execution of this API, the calling program retrieves the warnings and the error messages, put on the message stack by the API, in the following manner:

The warnings and the error messages put on the message stack by the API are retrieved after the execution of this API by the calling program, in the following manner:

```
IF l_msg_count = 1 Then
  --there is one message raised by the API, so it has been sent out
  --in the parameter x_msg_data, get it.
l_msg_data_out := l_msg_data;
ELSIF l_msg_count > 1 Then
--the messages on the stack are more than one so call them in a loop
-- and put the messages in a PL/SOL table.
    count := count +1 ;
    l_mesg := FND_MSG_PUB.Get;
    If l_mesg IS NULL Then
      EXIT;
    else
     Mesg_tbl(count).message := l_mesg;
    End if;
 end loop;
END IF;
```

Depending on the message level threshold set by the profile option FND API MSG LEVEL THRESHOLD, the messages put on the message stack may contain both the error messages and the warnings.

Result:

All revenue on this transaction was unearned by specifying only four input parameters in the call to this API.

AR_RevenueAdjust_PUB.Earn_Revenue

Call this routine to move revenue from the unearned revenue account to the earned revenue account using AutoAccounting. This API routine has 4 input and 5 output parameters in total and is almost exactly the same as the Unearn_Revenue routine described above in AR_RevenueAdjust_PUB.Unearn_Revenue, page 9-2.

The following is the breakdown of the parameters:

Input

Standard API parameters: 3

Revenue Adjustment parameters: 1 (revenue adjustment record type)

Output

Standard API parameters: 3

Revenue Adjustment parameters: 2

Parameter Descriptions

For a description of this routine's standard parameters, see AR_RevenueAdjust_PUB. Unearn_Revenue, page 9-2.

The Rev_Adj_Rec_Type elements that are relevant to Earn_Revenue are exactly the same as already listed in AR_RevenueAdjust_PUB.Unearn_Revenue, with the following exceptions listed in this table:

Parameter	Data-type	Required	Description
to_salesrep_id	NUMBER		Not used for earning revenue and should be left null.
to_salesrep_number	VARCHAR2		Not used for earning revenue and should be left null.
to_salesgroup_id	jtf_rs_groups_b. group_id%TYPE		Not used for earning revenue and should be left null.
sales_credit_type	VARCHAR2(15)		Not used for earning revenue and should be left null.

Example

Objective:

To earn all revenue on a transaction using a call to *AR_RevenueAdjust_PUB*. Earn_Revenue and passing a minimum number of input parameters.

This table lists the entered parameters:

Parameter	Entered Value	Default Value
p_api_version	2.0	
p_init_msg_list	FND_API.G_TRUE	
p_rev_adj_rec.trx_number	'test_api_1'	
p_rev_adj_rec.reason_code	'RA'	

This table lists the defaulted input parameters, which were not entered:

Parameter	Entered Value	Default Value
p_rev_adj_rec.amount_mode		'T'
p_rev_adj_rec. line_selection_mode		'A'
p_rev_adj_rec.gl_date		SYSDATE

The API call in this case would be:

```
AR_RevenueAdjust_PUB.Earn_Revenue(
      p_rev_adj_rec.trx_number => 'test_api_1',
       p_rev_adj_rec.reason_code => 'RA',
      p_rev_adj_rec.reason_code => 'RA',
x_return_status => l_return_status,
x_msg_count => l_msg_count,
x_msg_data => l_msg_data,
x_adjustment_id => l_adjustment_id,
x_adjustment_number => l_adjustment_number);
```

The warnings and the error messages put on the message stack by the API are retrieved after the execution of this API by the calling program, as described in Example, page 9-14.

Result:

All revenue on this transaction was earned by specifying only four input parameters in the call to this API.

AR_RevenueAdjust_PUB.Transfer_Sales_Credits

Call this routine to transfer sales credits from any salesperson with sales credits on the transaction to any other salesperson. In addition, if revenue sales credits are transferred, then the associated revenue is transferred between cost centers if the AutoAccounting rules call the salesperson table and the cost center segment is derived from the salesperson.

This API routine has 4 input and 5 output parameters in total and is similar to the Unearn_Revenue routine described above in AR_RevenueAdjust_PUB. Unearn Revenue, page 9-2. The following is the breakdown of the parameters:

Input

Standard API parameters: 3

Revenue Adjustment parameters: 1 (revenue adjustment record type)

Output

Standard API parameters: 3

Revenue Adjustment parameters: 2

Parameter Descriptions

For a description of this routine's standard parameters, see AR_RevenueAdjust_PUB. Unearn_Revenue, page 9-2.

The Rev_Adj_Rec_Type elements that are relevant to Transfer_Sales_Credits are the same as already listed in AR_RevenueAdjust_PUB.Unearn_Revenue, with the following exceptions/additions listed in this table.

Note: If required parameters are not passed in a call to this API, then the call will fail. However, depending on the business scenario, you will have to pass in values for other parameters to successfully create the business object. Otherwise, error messages will be reported.

Parameter	Data-type	Required	Description
p_customer_trx_id	NUMBER(15)	1	The ID of the transaction on which sales credits are to be adjusted.
			Default: None
			Validation: Must exist if specified. Must not have a class of 'CB', 'BR', 'GUAR' (that is. chargeback, bills receivable, guarantee). Must not have had credit memo(s) raised against the full transaction value. Warning if partial credit memo has been raised. Every line must have revenue sales credits adding to 100%.
			Errors: AR_TAPI_TRANS_NOT_EXIST AR_TW_INCORRECT_SALESCREDIT AR_RA_CB_DISALLOWED AR_RA_BR_DISALLOWED AR_RA_GUAR_DISALLOWED AR_TW_INCORRECT_SALESCREDIT AR_RA_FULL_CREDIT
			Warnings: AR_RA_PARTIAL_CREDIT
from_salesrep_id	NUMBER(15)		The ID of the salesperson from whom sales credits are being transferred.
			Default: Null
			Validation: If specified, must exist, must be currently active, and must have been active on transaction date. Must have revenue sales credits on at least one line on the transaction. If neither from_salesrep_id nor from_salesrep_number are specified, sales credits of the specified type are transferred belonging to all salesreps on the transaction (that is. null = all).
			Error: AR_TAPI_INVALID_SALESREP_ID AR_RA_SALESREP_NOT_ON_TRX

Parameter	Data-type	Required	Description
from_salesrep_number	ra_salesreps. salesrep_numbe		The user visible number of the salesperson from whom sales credits are being transferred.
	r%TYPE		Validation: Ignored if from_salesrep_id is specified. Otherwise, validation is as for from_salesrep_id.
			Error: AR_RA_INVALID_SALESREP_NUMBER
to_salesrep_id	NUMBER(15)	2	The ID of the salesperson to whom sales credits are being transferred.
			Validation: If specified, must exist, and must be currently active and must have been active on transaction date.
			Errors: AR_TAPI_INVALID_SALESREP_ID AR_RA_NO_TO_SALESREP
to_salesrep_number	ra_salesreps. salesrep_numbe r%TYPE	2	The user visible number of the salesperson to whom sales credits are being transferred.
			Validation: Ignored if to_salesrep_id is specified. Otherwise, validation is as for to_salesrep_id.
			Error: AR_RA_INVALID_SALESREP_NUMBER
from_salesgroup_id	jtf_rs_groups_b. group_id%		The ID of the sales group of the salesperson from whom sales credits are being transferred.
	TYPE		Default: Null
			Validation: Must have sales credits (of the type being transferred) on at least one line on the transaction. If FROM_SALESGROUP_ID is not specified, then all sales credits of the specified type for the chosen salesperson are transferred (that is. null = all).
			Error: AR_RA_SALESREP_NOT_ON_TRX

Parameter	Data-type	Required	Description
to_salesgroup_id	jtf_rs_groups_b. group_id%		The ID of the sales group of the salesperson to whom sales credits are being transferred.
	TYPE		Validation: If specified, then must exist and must be currently active. Salesperson must have been an active member of this group at some time between:
			 the earliest of the transaction date and any parent commitment/invoice dates, and
			 the latest of the current date, transaction date, and any parent commitment/invoice dates.
			Error: AR_INVALID_SALESGROUP_ID
sales_credit_type	VARCHAR2 (15)	Yes	The type of sales credit being transferred. Possible values:
			• R = revenue sales credits
			• N = non-revenue sales credits
			• $B = both$
			Default: 'R'
			Validation: Must be one of the above values.
			Note: The value B cannot be used if either FROM_SALESGROUP_ID or TO_SALESGROUP_ID is specified.
			Error: AR_INCOMPATIBLE_CREDIT_TYPE AR_RA_INVALID_SALESCRED_TYPE

Example

Objective:

To transfer all revenue sales credits on a transaction from a salesperson to a new salesperson using a call to $AR_RevenueAdjust_PUB.Transfer_Sales_Credits$ and passing a minimum number of input parameters.

This table lists the entered parameters:

Parameter	Entered Value	Default Value
p_api_version	2.0	
p_init_msg_list	FND_API.G_TRUE	
p_rev_adj_rec.trx_number	'test_api_1'	
p_rev_adj_rec. from_salesrep_number	'101'	
p_rev_adj_rec. to_salesrep_number	'299'	
p_rev_adj_rec.reason_code	'RA'	

This table lists the defaulted input parameters, which were not entered:

Parameter	Entered Value	Default Value
p_rev_adj_rec.amount_mode		'T'
p_rev_adj_rec. sales_credit_type		'R'
p_rev_adj_rec. line_selection_mode		'A'
p_rev_adj_rec.gl_date		SYSDATE

The API call in this case would be:

```
AR_RevenueAdjust_PUB.Transfer_Sales_Credits(
  p_rev_adj_rec.from_salesrep_number => '101',
   p_rev_adj_rec.to_salesrep_number => '299'
   p_rev_adj_rec.reason_code
                        => 'RA',
```

The warnings and the error messages put on the message stack by the API are retrieved

after execution of this API by the calling program, as described in Example, page 9-14.

Result:

All revenue sales credits on this transaction belonging to salesperson 101 were transferred to salesperson 299 by specifying only six input parameters in the call to this API. Additionally, all associated revenue was transferred between corresponding cost centers. Note that if salesrep number 101 was the only salesperson with revenue sales credits on this transaction, then from_salesrep_number could have been omitted. This is because no specified salesperson means all salespersons, thereby cutting the required number of parameters to five.

AR RevenueAdjust PUB.Add Non Revenue Sales Credits

Call this routine to add non-revenue sales credits to any existing or new salesperson on a transaction. This does not involve a transfer of revenue. This API routine has 4 input and 5 output parameters in total and is similar to the Unearn Revenue routine described in AR RevenueAdjust PUB.Unearn Revenue, page 9-2.

The following is the breakdown of the parameters:

Input

Standard API parameters: 3

Revenue Adjustment parameters: 1 (revenue adjustment record type)

Output

Standard API parameters: 3

Revenue Adjustment parameters: 2

Parameter Descriptions

For a description of this routine's standard parameters, see AR_RevenueAdjust_PUB. Unearn_Revenue, page 9-2.

The Rev_Adj_Rec_Type elements that are relevant to Add_Non_Revenue_Sales_Credits are the same as already listed in AR_RevenueAdjust_PUB.Unearn_Revenue, with the following exceptions/additions listed in this table:

Note: If required parameters are not passed in a call to this API, then the call will fail. However, depending on the business scenario, you will have to pass in values for other parameters to successfully create the business object. Otherwise, error messages will be reported.

At least one of the numbered sets of parameters is required.

Parameter	Data-type	Required	Description
p_customer_trx_id	NUMBER(15)	1	The ID of the transaction on which sales credits are to be adjusted.
			Default: None
			Validation: Must exist if specified. Must not have a class of 'CB','BR','GUAR' (that is. chargeback, bills receivable, guarantee). Must not have had credit memo(s) raised against the full transaction value. Warning if partial credit memo has been raised. Every line must have revenue sales credits adding to 100%.
			Errors: AR_TAPI_TRANS_NOT_EXIST AR_TW_INCORRECT_SALESCREDI T AR_RA_CB_DISALLOWED AR_RA_BR_DISALLOWED AR_RA_GUAR_DISALLOWED AR_TW_INCORRECT_SALESCREDI T AR_RA_FULL_CREDIT
			Warnings: AR_RA_PARTIAL_CREDIT
from_salesrep_id	NUMBER(15)		Not applicable in this context and should be left null.
from_salesrep_number	ra_salesreps. salesrep_number%TYPE		Not applicable in this context and should be left null.
to_salesrep_id	NUMBER(15)	2	The ID of the salesperson to whom non-revenue sales credits are being added.
			Validation: If specified, must exist, and must be currently active and must have been active on transaction date.
			Errors: AR_TAPI_INVALID_SALESREP_ID AR_RA_NO_TO_SALESREP

Parameter	Data-type	Required	Description
to_salesrep_number	ra_salesreps. salesrep_number%TYPE	2	The user visible number of the salesperson to whom sales credits are being transferred.
			Validation: Ignored if to_salesrep_id is specified. Otherwise, validation is as for to_salesrep_id.
			Error: AR_RA_INVALID_SALESREP_NUM BER
from_salesgroup_id	jtf_rs_groups_b. group_id%TYPE		Not applicable in this context and should be left null.
to_salesgroup_id	jtf_rs_groups_b. group_id%TYPE		The ID of the sales group of the salesperson to whom nonrevenue sales credits are being added.
			Validation: If specified, then must exist and must be currently active. Salesperson must have been an active member of this group at some time between:
			 the earliest of the transaction date and any parent commitment/invoice dates, and
			 the latest of the current date, transaction date, and any parent commitment/invoice dates.
			Error: AR_INVALID_SALESGROUP_ID
sales_credit_type	VARCHAR2(15)		Not applicable in this context and should be left null.

Parameter	Data-type	Required	Description
amount_mode	VARCHAR2(15)		The amount mode specifies whether an amount, a percentage (of total value of selected lines) is to be adjusted. Possible values are: A - amount P - percent Default: 'T', or all adjustable revenue is not applicable in this context. Validation: Must be one of the above values (A or P). Error: AR_RA_INVALID_AMOUNT_MOD E

Example

Objective:

To add 50% of the total transaction value in non-revenue sales credits to a new salesperson on a transaction, using a call to AR_RevenueAdjust_PUB. Add_Non_Revenue_Sales_Credits and passing a minimum number of input parameters.

This table lists the entered parameters:

Parameter	Entered Value	Default Value
p_api_version	2.0	
p_init_msg_list	FND_API.G_TRUE	
p_rev_adj_rec.trx_number	'test_api_1'	
p_rev_adj_rec. to_salesrep_number	'299'	
p_rev_adj_rec.amount_mode	· 'P'	

Parameter	Entered Value	Default Value
p_rev_adj_rec.percent	50	
p_rev_adj_rec.reason_code	'RA'	

This table lists the defaulted input parameters, which were not entered:

Parameter	Entered Value	Default Value
p_rev_adj_rec. line_selection_mode		'A'
p_rev_adj_rec.gl_date		SYSDATE

The API call in this case would be:

```
AR_RevenueAdjust_PUB.Add_Non_Revenue_Sales_Credits(
    p_api_version => 2.0,
p_init_msg_list => FND_API.G_TRUE,
    p_rev_adj_rec.trx_number => 'test_api_1',
    p_rev_adj_rec.to_salesrep_number => '299'
    p_rev_adj_rec.amount_mode => 'P',
    p_rev_adj_rec.percent => 50,
    p_rev_adj_rec.reason_code => 'RA',
```

The warnings and the error messages put on the message stack by the API are retrieved after execution of this API by the calling program, as described in Example, page 9-14.

Result:

Non-revenue sales credits were added to salesperson 299 on this transaction by specifying only seven input parameters in the call to this API.

AR Revenueadjust PUB.Record Customer Acceptance

Call this routine to accept post-billing customer acceptance clauses in Receivables, and, if required, in Order Management, to remove these type of contingencies and to recognize revenue. This API routine has 5 input and 5 output parameters in total and is similar to the Unearn_Revenue routine described in AR_RevenueAdjust_PUB. Unearn_Revenue, page 9-2.

The following is the breakdown of the parameters:

Input

Standard API parameters: 3

Revenue Adjustment parameters: 1 (revenue adjustment record type)

Organization Identifier parameter: 1

Output

Standard API parameters: 3

Revenue Adjustment parameters: 2

Parameter Descriptions

For a description of this routine's standard parameters, see AR_RevenueAdjust_PUB. Unearn_Revenue, page 9-2.

The Rev_Adj_Rec_Type elements that are relevant to Record_Customer_Acceptance are exactly the same as already listed in AR_RevenueAdjust_PUB.Unearn_Revenue, with the following exceptions listed in this table:

Parameter	Data-type	Required	Description
p_org_id	jtf_rs_salesreps. org_id%type	Yes	Organization Identifier

AR_Revenueadjust_PUB.Update_Contingency_Expirations

Call this routine to update the expiration date and period for specific time-based contingencies. This API routine has 5 input and 5 output parameters in total and is almost exactly the same as the Unearn Revenue routine described in AR_RevenueAdjust_PUB.Unearn_Revenue, page 9-2.

The following is the breakdown of the parameters:

Input

Standard API parameters: 3

Revenue Adjustment parameters: 1 (revenue adjustment record type)

Organization Identifier parameter: 1

Output

Standard API parameters: 3

Revenue Adjustment parameters: 2

Parameter Descriptions

For a description of this routine's standard parameters, see AR_RevenueAdjust_PUB. Unearn_Revenue, page 9-2.

The Rev_Adj_Rec_Type elements that are relevant to Update_Contingency_Expirations are exactly the same as already listed in AR_RevenueAdjust_PUB.Unearn_Revenue, with the following exceptions listed in this table:

Parameter	Data-type	Required	Description
p_org_id	jtf_rs_salesreps. org_i d%type	Yes	Organization Identifier.
p_customer_trx_id	ra_customer_trx. customer_trx_id	Yes	Identifies the affected invoices; affects all contingencies for the transaction.
p_customer_trx_line_id	ra_customer_trx_li nes. customer_trx_line_ id		Identifies the specific affected line and contingencies.
p_contingency_id	ar_line_conts. contngency_id		Restricts updates to a specific type of contingency for the previously identified transaction or line.
p_expiration_date	ar_line_conts. expiration_date		The new or resulting expiration date for the contingencies.
p_expiration_days	ar_line_conts. expiration_days		The new offset for calculating the expiration date on the contingencies. The new expiration date is calculated as follows:
			Expiration Date = Expiration Event Date + Expiration Days

Example

Objective:

To update the expiration dates for all contingencies associated with a transaction to 31-DEC-2008, using a call to AR_Revenueadjust_PUB.Update_Contingency_Expirations and passing a minimum number of input parameters.

This table lists the input parameters:

Parameter	Entered Value	Default Value
p_api_version	2.0	
p_init_msg_list	FND_API.G_TRUE	
p_commit	FND_API.G_TRUE	
p_org_id	204	
p_customer_trx_id	1112234	
p_customer_trx_line_id	NULL	
p_contingency_id	NULL	
p_expiration_date	31-DEC-2008	
p_expiration_days	NULL	

Important: For updating contingency expirations, you must enter a value for either the p_expiration_date or the p_expiration_days parameter. Not providing a value for either of the parameters raises a validation error. If you provide both the values, the API honors the p_expiration_date first.

The API call in this case would be:

```
AR_RevenueAdjust_PUB.update_contingency_expirations(
  x_msg_data
                   => l_msg_data);
```

The warnings and the error messages put on the message stack by the API are retrieved after execution of this API by the calling program, as described in Example, page 9-14.

Result:

All existing contingencies associated with this transaction now have their expiration dates set to 31-DEC-2008. On the expiration date, provided no other activity has already released the revenue, these contingencies will expire and revenue will be earned.

Messages

Messages play an important role in the effectiveness of API calls. The right message is raised at the right point to convey the exact error that has occurred or any warnings that have been raised. In the Revenue Adjustment API, all error messages and warnings raised during execution are put on the message stack and can be retrieved by the user as described in Exception Handling and Result Messages, page 1-3.

WARNINGS AND ERRORS

The following table lists all the error messages raised by the Revenue Adjustment API:

TYPE

E: Error message

W: Warning message

MESSAGE CODE	MESSAGE TEXT	DESCRIPTION	TYPE
AR_INCOMPATIBLE_CREDIT_T YPE	The option of transferring "both" sales credit types is not available in conjunction with sales group transfers.		E
AR_INVALID_SALESGROUP_ID	Please provide a valid sales group ID for sales credit transfers or additions.		Е
AR_RA_AMT_EXCEEDS_AVAIL_ REV	The amount entered is greater than &TOT_AVAIL_REV, the total available revenue on the lines selected	This message is generated by the revenue adjustment API when there is insufficient adjustable revenue on the selected transaction lines to meet the specified amount.	Е
AR_RA_BR_DISALLOWED	Revenue cannot be adjusted on bills receivable		E
AR_RA_CATEGORY_NOT_ON_T RX	There are no lines with items for category ID &CATEGORY_ID on this transaction.		E

MESSAGE CODE	MESSAGE TEXT	DESCRIPTION	TYPE
AR_RA_CB_DISALLOWED	Revenue cannot be adjusted on chargebacks		E
AR_RA_DEP_DISALLOWED	Revenue cannot be adjusted on deposits.		E
AR_RA_DM_DISALLOWED	Revenue cannot be adjusted on debit memos or debit memo reversals		E
AR_RA_FULL_CREDIT	One or more credit memos have been applied for the full amount of this invoice		E
AR_RA_GL_DATE_CHANGED	GL date, &GL_DATE, is not in an open or future-enterable period. GL date has been changed to &NEW_GL_DATE		W
AR_RA_GUAR_DISALLOWED	Revenue cannot be adjusted on guarantees.		E
AR_RA_INVALID_AMOUNT_M ODE	Amount mode &AMOUNT_MODE is invalid.		E
AR_RA_INVALID_CAT_SEGME NTS	This combination of category segments is invalid: &CONCAT_SEGS.		E
AR_RA_INVALID_CATEGORY	A valid category to which items belong that are currently on one or more lines on this transaction must be entered		E
AR_RA_INVALID_CATEGORY_I D	Category ID &CATEGORY_ID is invalid.		Е

MESSAGE CODE	MESSAGE TEXT	DESCRIPTION	TYPE
AR_RA_INVALID_CODE_COMB	An error occurred while generating the following accounting flexfield code combination: &CODE_COMBINATION	This message is generated by the revenue adjustment API because of an error with the specified accounting flexfield code combination. Possible causes: segment values could not be found by AutoAccounting or have been disabled.	Е
AR_RA_INVALID_ITEM	A valid item that is currently on one or more lines on this transaction must be entered		E
AR_RA_INVALID_ITEM_ID	Inventory item ID &ITEM_ID is invalid.		Е
AR_RA_INVALID_ITEM_SEGME NTS	This combination of item segments is invalid: &CONCAT_SEGS.		E
AR_RA_INVALID_LINE_ID	Transaction line ID &CUST_TRX_LINE_ID is invalid.		E
AR_RA_INVALID_LINE_MODE	Line selection mode &LINE_MODE is invalid.		E
AR_RA_INVALID_REASON	Reason code &REASON_CODE is not a valid lookup code.		E
AR_RA_INVALID_SALESCRED_ TYPE	Sales credit type &SALESCRED_TYPE is invalid.		E
AR_RA_INVALID_SALESREP_N UMBER	Salesperson number &SALESREP_NUMBER is invalid.		E
AR_RA_ITEM_NOT_ON_TRX	There are no lines with item &ITEM_ID on this transaction.		E
AR_RA_LINE_NOT_ON_TRX	There are no lines with line number &LINE_NUMBER on this transaction.		E

MESSAGE CODE	MESSAGE TEXT	DESCRIPTION	TYPE
AR_RA_NO_EARNED_REVENU E	There is no earned revenue on this transaction	This message is generated by the revenue adjustment API when there is no earned revenue on the selected transaction lines.	Е
AR_RA_NO_FROM_CATEGORY	Please provide a from-category.		E
AR_RA_NO_FROM_ITEM	Please provide a from-item.		E
AR_RA_NO_FROM_LINE	Please provide a from-line.		E
AR_RA_NO_OPEN_PERIODS	The transaction date must fall during an open period or prior to a future period	This message is generated by the revenue adjustment API because there are no open or future periods relating to the transaction date or following the transaction date. Revenue cannot be posted to periods prior to the transaction date.	E
AR_RA_NO_REV_SALES_CREDI T	Line &LINE_NUMBER has no revenue sales credits	This message is generated by the revenue adjustment API when a transaction line with no sales credits is encountered.	Е
AR_RA_NO_REV_TO_ADJUST	There is no adjustable revenue on the selected lines	This message is generated by the revenue adjustment API when there is no adjustable revenue on the selected transaction lines.	Е
AR_RA_NO_SELECTED_SALESC RED	There are no sales credits for this line selection available to transfer		E
AR_RA_NO_TO_SALESREP	Please provide a valid salesperson number or ID for sales credit transfers or additions.		E
AR_RA_NO_TRX_NUMBER	Please provide a valid transaction number or ID.		E

MESSAGE CODE	MESSAGE TEXT	DESCRIPTION	TYPE
AR_RA_NO_UNEARNED_REVE NUE	There is no unearned revenue on this transaction	This message is generated by the revenue adjustment API when there is no unearned revenue on the selected transaction lines.	Е
AR_RA_PARTIAL_CREDIT	One or more partial credit memos have been applied against this invoice		W
AR_RA_PCT_EXCEEDS_AVAIL_ PCT	The percentage entered is greater than &TOT_AVAIL_PCT, the total available percentage of adjustable revenue on the lines selected	This message is generated by the revenue adjustment API when there is insufficient adjustable revenue on the selected transaction lines to meet the specified percentage.	Е
AR_RA_SALES_CREDIT_LIMIT	Revenue and non-revenue sales credits exceed &SALES_CREDIT_LIMIT percent for salesperson &SALESREP_NAME on line &LINE_NUMBER	This message is generated by the revenue adjustment API when the total percentage of revenue and non-revenue sales credits per salesperson per line exceeds the limit specified in system options.	E
AR_RA_SALESREP_NOT_ON_TR X	Salesperson &SALESREP_NAME does not have any sales credits on this transaction.		Е
AR_RA_TRX_NOTFOUND	Transaction number &TRX_NUMBER cannot be found.		E
AR_RA_TRX_TOO_MANY_ROW S	There is more than one transaction with the transaction number &TRX_NUMBER. Please also provide a batch source to ensure uniqueness of the transaction.		E
AR_RA_ZERO_AMOUNT	Amount entered cannot be zero	This message is generated by the revenue accounting API when attempting to adjust an amount of zero.	E

MESSAGE CODE	MESSAGE TEXT	DESCRIPTION	TYPE
AR_RAPI_DESC_FLEX_INVALID	The entered values for the descriptive flexfield &DFF_NAME is invalid.		E
AR_TW_INCORRECT_SALESCR EDIT	Revenue sales credit not equal to line amount or 100% for line &LINE_NUMBER.		E
AR_TAPI_TRANS_NOT_EXIST	Transaction does not exist. (CUSTOMER_TRX_ID: &CUSTOMER_TRX_ID).		E
AR_TAPI_INVALID_SALESREP_I D	Invalid salesrep id. (SALESREP_ID: &SALESREP_ID)		E

Predefined Setup for Oracle Subledger Accounting

Data that Oracle Receivables Predefines for Oracle Subledger Accounting

Oracle Receivables provides predefined data for Oracle Subledger Accounting that you can use to integrate the two applications. When you run the Create Accounting program to create draft or final subledger accounting, the program uses the predefined data to determine how to create the accounting. Receivables predefines setup for Subledger Accounting so that the Create Accounting program accepts the default accounting information from AutoAccounting without change. Subledger Accounting transfers the final accounting to Oracle General Ledger.

You can optionally define your own subledger accounting rules to overwrite the default accounts from the accounting events.

Note: You must use an Oracle Receivables responsibility to query predefined data that is associated with the *Receivables* application.

The following sections describe the data that Receivables predefines in Subledger Accounting:

- Applications, page A-2
- Event Entities, page A-2
- Event Classes and Event Types, page A-3
- Process Categories, page A-4
- Accounting Event Class Options, page A-4
- Sources, Source Assignments, and Accounting Attribute Assignments, page A-5

- Journal Line Types, page A-6
- Account Derivation Rules, page A-12
- Journal Lines Definitions, page A-13
- Application Accounting Definitions, page A-15
- Subledger Accounting Methods, page A-17

Applications

Oracle Receivables predefines one application in Oracle Subledger Accounting named Receivables. Most of the data that Oracle Receivables predefines for Oracle Subledger Accounting is associated with the *Receivables* application.

The following table shows the attribute values that Oracle Receivables predefines for the Receivables application. The first column lists the fields and the second column lists the values for each field.

Predefined Receivables Application

Field	Value
Application Name	Receivables
Drilldown Procedure	AR_DRILLDOWN_PUB_PKG.DRILLDOWN
Use Security	Yes
Policy Function	XLA_SECURITY_POLICY_PKG.MO_POLICY
Journal Source	Receivables
Third Party Control Account Type	Customer
Subject to Validation	No
Calculate Reporting Currency Amounts	Yes

Event Entities

The following table lists the setup information that Oracle Receivables predefines for the event entities.

Predefined Event Entities

Application	Entity Name	Description	Gapless Event Processing
Receivables	Adjustments	Adjustments	No
Receivables	Bills Receivable	Bills Receivable	No
Receivables	Receipts	Receipts	No
Receivables	Transactions	Transactions	No

Event Classes and Event Types

Oracle Receivables predefines event classes and event types for each event entity that belongs to the *Receivables* application.

The following table lists the event classes and event types that Oracle Receivables predefines for the Receivables application.

Predefined Event Classes and Event Types for the Receivables Application

Entity	Event Class Name
Adjustments	Adjustment
Bills Receivable	Bills Receivable
Receipts	Miscellaneous Receipt
Receipts	Receipt
Transactions	Chargeback
Transactions	Credit Memo
Transactions	Debit Memo
Transactions	Deposit

Entity	Event Class Name
Transactions	Guarantee
Transactions	Invoice

Process Categories

Oracle Receivables predefines the following process categories:

- Adjustments
- Bills Receivable
- Miscellaneous Receipts
- Standard Receipts
- Third Party Merge
- Transactions

Accounting Event Class Options

Accounting event class options define attributes of an event class. Oracle Receivables defines the accounting event class options for each predefined event class.

The following table lists the accounting event class options that Oracle Receivables predefines for the Receivables application.

Predefined Accounting Event Class Options for the Receivables Application

Event Class	Process Category	Default Journal Category	Transaction View	Balance Types
Adjustment	Adjustments	Adjustment	AR_ADJ_INF_V	Actual
Bills Receivable	Bills Receivable	Bills Receivable	AR_TRX_INF_V	Actual
Miscellaneous Receipt	Miscellaneous Receipts	Misc Receipts	AR_CR_INF_V	Actual

Event Class	Process Category	Default Journal Category	Transaction View	Balance Types
Receipt	Standard Receipts	Receipts	AR_CR_INF_V	Actual
Chargeback	Transactions	Chargebacks	AR_TRX_INF_V	Actual
Credit Memo	Transactions	Credit Memos	AR_TRX_INF_V	Actual
Debit Memo	Transactions	Debit Memos	AR_TRX_INF_V	Actual
Deposit	Transactions	Sales Invoices	AR_TRX_INF_V	Actual
Guarantee	Transactions	Sales Invoices	AR_TRX_INF_V	Actual
Invoice	Transactions	Sales Invoices	AR_TRX_INF_V	Actual

Sources, Source Assignments, and Accounting Attribute Assignments

Oracle Receivables predefines sources, source assignments, and accounting attribute assignments for Oracle Subledger Accounting.

You can use the Accounting Methods Builder to review the sources, source assignments, and accounting attribute assignments. You must access the Accounting Methods Builder using an Oracle Receivables responsibility if you want to review the sources, source assignments, and accounting attribute assignments associated with the Receivables application.

Note: You cannot make changes to predefined sources, source assignments, or accounting attribute assignments. However, you can define your own custom sources.

If you choose to define your own journal line types or application accounting definitions, then you can override the default accounting attribute assignments.

Oracle Receivables provides numerous predefined sources. When you use the Sources window to review the predefined sources, you can optionally export the queried sources from the application to a Microsoft Excel spreadsheet.

To export a list of sources:

- From an Oracle Receivables responsibility, navigate to the Sources window.
- Query the records you want to export.

- Place your cursor in the multi-row block that contains the records to be exported.
- Choose Export from the File menu.

See: Exporting Records to a File, Oracle E-Business Suite User's Guide.

Journal Line Types

Oracle Receivables predefines journal line types for each predefined event class. Oracle Receivables specifies conditions for the use of each journal line type.

The following table lists the journal line types that Oracle Receivables predefines for the Receivables application.

Predefined Journal Line Types for the Receivables Application

Event Class	Name	Balance Type	Side
Adjustment	Adjustment	Actual	Credit
Adjustment	Adjustment Bills Receivable Endorsement	Actual	Credit
Adjustment	Adjustment Charge	Actual	Credit
Adjustment	Adjustment Default Receivable	Actual	Credit
Adjustment	Adjustment Deferred Tax	Actual	Credit
Adjustment	Adjustment Charge Non- Recoverable Tax	Actual	Credit
Adjustment	Adjustment Non-Recoverable Tax	Actual	Credit
Adjustment	Adjustment Tax	Actual	Credit
Bills Receivable	Bills Receivable Deferred Tax	Actual	Credit
Bills Receivable	Bills Receivable Factoring	Actual	Credit
Bills Receivable	Bills Receivable Receivables	Actual	Credit

Event Class	Name	Balance Type	Side
Bills Receivable	Bills Receivable Remittance	Actual	Credit
Bills Receivable	Bills Receivable Tax	Actual	Credit
Bills Receivable	Bills Receivable Unpaid	Actual	Credit
Chargeback	Chargeback Default Receivable	Actual	Debit
Chargeback	Chargeback Revenue	Actual	Credit
Credit Memo	Credit Memo Default Deferred Tax Application	Actual	Credit
Credit Memo	Credit Memo Default Application	Actual	Credit
Credit Memo	Credit Memo Default Tax Application	Actual	Credit
Credit Memo	Credit Memo Refund Application	Actual	Credit
Credit Memo	Credit Memo Charges	Actual	Credit
Credit Memo	Credit Memo Default Receivable	Actual	Debit
Credit Memo	Credit Memo Default Revenue	Actual	Credit
Credit Memo	Credit Memo Default Tax	Actual	Credit
Credit Memo	Credit Memo Rounding	Actual	Credit
Credit Memo	Credit Memo Unbilled Receivable	Actual	Credit
Credit Memo	Credit Memo Deferred Revenue	Actual	Credit

Event Class	Name	Balance Type	Side
Debit Memo	Debit Memo Charges	Actual	Credit
Debit Memo	Debit Memo Default Receivable	Actual	Debit
Debit Memo	Debit Memo Freight	Actual	Credit
Debit Memo	Debit Memo Revenue	Actual	Credit
Debit Memo	Debit Memo Rounding	Actual	Credit
Debit Memo	Debit Memo Tax	Actual	Credit
Debit Memo	Debit Memo Unbilled Receivable	Actual	Debit
Debit Memo	Debit Memo Deferred Revenue	Actual	Credit
Deposit	Deposit Default Receivable	Actual	Debit
Deposit	Deposit Offset	Actual	Credit
Guarantee	Guarantee Default Receivable	Actual	Debit
Guarantee	Guarantee Revenue	Actual	Credit
Invoice	Invoice Charges	Actual	Credit
Invoice	Invoice Default Receivable	Actual	Debit
Invoice	Invoice Freight	Actual	Credit
Invoice	Invoice Revenue	Actual	Credit
Invoice	Invoice Rounding	Actual	Credit
Invoice	Invoice Tax	Actual	Credit
Invoice	Invoice Unbilled Receivable	Actual	Credit

Event Class	Name	Balance Type	Side
Invoice	Invoice Deferred Revenue	Actual	Credit
Miscellaneous Receipt	Miscellaneous Receipt Bank Charges	Actual	Credit
Miscellaneous Receipt	Miscellaneous Receipt Cleared Cash	Actual	Credit
Miscellaneous Receipt	Miscellaneous Receipt Confirmed Cash	Actual	Credit
Miscellaneous Receipt	Miscellaneous Receipt Short Term Debt	Actual	Credit
Miscellaneous Receipt	Miscellaneous Receipt Factored Cash	Actual	Credit
Miscellaneous Receipt	Miscellaneous Receipt Miscellaneous Cash	Actual	Credit
Miscellaneous Receipt	Miscellaneous Receipt Remitted Cash	Actual	Credit
Miscellaneous Receipt	Miscellaneous Receipt Tax	Actual	Credit
Receipt	Receipt On Account Application	Actual	Credit
Receipt	Receipt Application to Freight	Actual	Credit
Receipt	Receipt Application to Revenue	Actual	Credit
Receipt	Receipt Application to Rounding	Actual	Credit
Receipt	Receipt Application to Suspense Revenue	Actual	Credit
Receipt	Receipt Application to Tax	Actual	Credit

Event Class	Name	Balance Type	Side
Receipt	Receipt Application to Unbilled Revenue	Actual	Credit
Receipt	Receipt Application to Earned Revenue	Actual	Credit
Receipt	Receipt Bank Charges	Actual	Credit
Receipt	Receipt Cleared Cash	Actual	Credit
Receipt	Receipt Credit Card Chargeback Application	Actual	Credit
Receipt	Receipt Chargeback Application	Actual	Credit
Receipt	Receipt Claim Investigation Application	Actual	Credit
Receipt	Receipt Confirmed Cash	Actual	Credit
Receipt	Receipt Currency Rounding	Actual	Credit
Receipt	Receipt Short Term Debt	Actual	Credit
Receipt	Receipt Default Application	Actual	Credit
Receipt	Receipt Deferred Tax	Actual	Credit
Receipt	Receipt Earned Discount	Actual	Credit
Receipt	Receipt Earned Discount on Freight	Actual	Debit
Receipt	Receipt Earned Discount Non-Recoverable Tax	Actual	Credit
Receipt	Receipt Earned Discount on Revenue	Actual	Debit

Event Class	Name	Balance Type	Side
Receipt	Receipt Earned Discount on Tax	Actual	Debit
Receipt	Receipt Exchange Gain	Actual	Credit
Receipt	Receipt Exchange Gain Loss	Actual	Gain/Loss
Receipt	Receipt Exchange Loss	Actual	Credit
Receipt	Receipt Factored Cash	Actual	Credit
Receipt	Receipt Factored Bills Receivable	Actual	Credit
Receipt	Receipt Payment Netting Application	Actual	Credit
Receipt	Receipt Prepayment Application	Actual	Credit
Receipt	Receipt Refund Application	Actual	Credit
Receipt	Receipt Remitted Cash	Actual	Credit
Receipt	Receipt Remitted Bills Receivable	Actual	Credit
Receipt	Receipt Tax	Actual	Credit
Receipt	Receipt Unapplied Cash	Actual	Debit
Receipt	Unapplied Cash	Actual	Debit
Receipt	Receipt Unapplied for Gain Loss lines	Actual	Debit
Receipt	Receipt Unearned Discount	Actual	Credit
Receipt	Receipt Unearned Discount on Freight	Actual	Debit

Event Class	Name	Balance Type	Side
Receipt	Receipt Unearned Discount on Non Recoverable Tax	Actual	Credit
Receipt	Receipt Unearned Discount on Revenue	Actual	Debit
Receipt	Receipt Unearned Discount on Tax	Actual	Debit
Receipt	Receipt Unidentified Cash	Actual	Credit
Receipt	Receipt Write-Off Application	Actual	Credit

Account Derivation Rules

Oracle Receivables predefines account derivation rules. When Oracle Subledger Accounting uses the predefined account derivation rules that Oracle Receivables provides, it accepts the default accounting that Oracle Receivables generates using AutoAccounting without change.

You can optionally define your own account derivation rules for an Accounting Flexfield or for a segment. In this case, Oracle Subledger Accounting overrides the default accounts that Oracle Receivables generates, or individual segment values in the default accounts, when it creates the draft or final subledger accounting.

The name account derivation rules that Oracle Receivables predefines for the Receivables application are as follows:

- Credit Memo Distribution GL Account
- Collection Bank Charges Account
- Bills Under Collection Account
- Bills Under Discount Account
- Collection Bank Account Cash Account
- Collection Endorsement Account
- Discount Endorsement Account
- Collection Bank Factoring Charges Account

- Distribution GL Account
- Remit Bank Unapplied account
- System Gain GL Account
- System Loss GL Account
- Transaction Distribution GL Account
- Transaction Distribution GL Account with reference

Journal Lines Definitions

Oracle Receivables predefines journal lines definitions that group the predefined journal line types and account derivation rules within each of the predefined event types. Oracle Receivables assigns each predefined journal lines definition to all event types within an event class.

The following table lists the journal lines definitions that Oracle Receivables predefines for the Receivables application.

Predefined Journal Lines Definitions for the Receivables Application

Event Class	Journal Lines Definition Name	Journal Line Types
Adjustment	Adjustments - Default Accrual	Adjustment, Adjustment Bills Receivable Endorsement, Adjustment Charge, Adjustment Charge Non-Recoverable Tax, Adjustment Default Receivable, Adjustment Deferred Tax, Adjustment Non-Recoverable Tax, Adjustment Tax
Bills Receivable	Receivables Bills Journal Lines Definition	Bills Receivable Deferred Tax, Bills Receivable Factoring, Bills Receivable Receivables, Bills Receivable Remittance, Bills Receivable Tax, Bills Receivable Unpaid
Chargeback	Chargebacks - Default Accrual	Chargeback Default Receivable, Chargeback Revenue
Credit Memo	Credit Memos - Default Accrual	Credit Memo Charges, Credit Memo Default Application, Credit Memo Default Deferred Tax Application, Credit Memo Default Receivable, Credit Memo Default Revenue, Credit Memo Default Tax, Credit Memo Default Tax Application, Credit Memo Deferred Revenue, Credit Memo Refund Application, Credit Memo Rounding, Credit Memo Unbilled Receivable

Event Class	Journal Lines Definition Name	Journal Line Types
Debit Memo	Debit Memos - Default Accrual	Debit Memo Charges, Debit Memo Default Receivable, Debit Memo Deferred Revenue, Debit Memo Freight, Debit Memo Revenue, Debit Memo Rounding, Debit Memo Tax, Debit Memo Unbilled Receivable
Deposit	Deposits - Default Accrual	Deposit Default Receivable, Deposit Offset
Guarantee	Guarantees - Default Accrual	Guarantee Default Receivable, Guarantee Revenue
Invoice	Invoices - Default Accrual	Invoice Charges, Invoice Default Receivable, Invoice Deferred Revenue, Invoice Freight, Invoice Revenue, Invoice Rounding, Invoice Tax, Invoice Unbilled Receivable
Miscellaneous Receipt	Miscellaneous Receipts	Miscellaneous Receipt Bank Charges, Miscellaneous Receipt Cleared Cash, Miscellaneous Receipt Confirmed Cash, Miscellaneous Receipt Factored Cash, Miscellaneous Receipt Miscellaneous Cash, Miscellaneous Receipt Remitted Cash, Miscellaneous Receipt Short Term Debt, Miscellaneous Receipt Tax
Receipt	Receipts - Default Accrual	Receipt Bank Charges, Receipt Chargeback Application, Receipt Claim Investigation Application, Receipt Cleared Cash, Receipt Confirmed Cash, Receipt Credit Card Chargeback Application, Receipt Currency Rounding, Receipt Default Application, Receipt Deferred Tax, Receipt Earned Discount, Receipt Earned Discount Non-Recoverable Tax, Receipt Exchange Gain Loss, Receipt Factored Bills Receivable, Receipt Factored Cash, Receipt On Account Application, Receipt Payment Netting Application, Receipt Prepayment Application, Receipt Refund Application, Receipt Remitted Bills Receivable, Receipt Remitted Cash, Receipt Short Term Debt, Receipt Tax, Receipt Unapplied Cash, Receipt Unearned Discount, Receipt Unearned Discount on Non Recoverable Tax, Receipt Unidentified Cash, Receipt Write-Off Application, Unapplied Cash

Event Class	Journal Lines Definition Name	Journal Line Types
Receipt	Receipt - Basis Journal Lines Definition	Receipt Application to Earned Revenue, Receipt Application to Freight, Receipt Application to Revenue, Receipt Application to Rounding, Receipt Application to Suspense Revenue, Receipt Application to Tax, Receipt Application to Unbilled Revenue, Receipt Bank Charges, Receipt Claim Investigation Application, Receipt Cleared Cash, Receipt Confirmed Cash, Receipt Currency Rounding, Receipt Earned Discount, Receipt Earned Discount on Freight, Receipt Earned Discount on Revenue, Receipt Earned Discount on Tax, Receipt Exchange Gain Loss, Receipt Factored Bills Receivable, Receipt Factored Cash, Receipt On Account Application, Receipt Payment Netting Application, Receipt Prepayment Application, Receipt Refund Application, Receipt Remitted Bills Receivable, Receipt Remitted Cash, Receipt Short Term Debt, Receipt Unapplied Cash, Receipt Unapplied for Gain Loss lines, Receipt Unearned Discount, Receipt Unearned Discount on Freight, Receipt Unearned Discount on Revenue, Receipt Unearned Discount on Tax, Receipt Unidentified Cash, Receipt Write-Off Application, Unapplied Cash

Application Accounting Definitions

Oracle Receivables predefines the Receivables Default Accrual and the Receivables Default Cash Basis Accounting Definition application accounting definitions.

The following table lists the assignments for the Receivables Default Accrual application accounting definition that Oracle Receivables predefines for the Receivables application.

Assignments for the Predefined Receivables Default Accrual Application Accounting Definition

Event Class Assignments	Event Type Assignments	Create Accounting	Journal Line Definition Assignments
Adjustment	All	Yes	Adjustments - Default Accrual
Bills Receivable	All	Yes	Receivables Bills Journal Lines Definition
Chargeback	All	Yes	Chargebacks - Default Accrual

Event Class Assignments	Event Type Assignments	Create Accounting	Journal Line Definition Assignments	
Credit Memo	All	Yes	Credit Memos - Default Accrual	
Debit Memo	All	Yes	Debit Memos - Default Accrual	
Deposit	All	Yes	Deposits - Default Accrual	
Guarantee	All	Yes	Guarantees - Default Accrual	
Invoice	All	Yes	Invoices - Default Accrual	
Miscellaneous Receipt	All	Yes	Miscellaneous Receipts	
Receipt	All	Yes	Receipts - Default Accrual	

The following table lists the assignments for the Receivables Default Cash Basis Accounting Definition application accounting definition that Oracle Receivables predefines for the Receivables application.

Assignments for the Predefined Receivables Default Cash Basis Accounting Definition **Application Accounting Definition**

Event Class Assignments	Event Type Assignments	Create Accounting	Journal Line Definition Assignments
Adjustment	All	No	
Bills Receivable	All	No	
Chargeback	All	No	
Credit Memo	All	No	
Debit Memo	All	No	
Deposit	All	No	
Guarantee	All	No	

Event Class Assignments	Event Type Assignments	Create Accounting	Journal Line Definition Assignments
Invoice	All	No	
Miscellaneous Receipt	All	Yes	Miscellaneous Receipts
Receipt	All	Yes	Receipt - Basis Journal Lines Definition

Subledger Accounting Methods

Oracle Subledger Accounting provides predefined subledger accounting methods that group the predefined application accounting definitions for subledger applications. You can optionally create your own subledger accounting methods.

Oracle Receivables assigns the predefined Receivables Default Accrual application accounting definition to the predefined Standard Accrual subledger accounting method, and the Receivables Default Cash Basis Accounting Definition application accounting definition to the predefined Standard Cash subledger accounting method.

You can assign these subledger accounting methods to your ledgers.

Oracle Receivables Table and Column Descriptions

AutoInvoice Table and Column Descriptions

Below is a detailed description of the four interface tables Receivables uses to temporarily store transaction data from your original system. Each column has important, detailed information you need to know to successfully run AutoInvoice. AutoInvoice uses the fifth table, RA INTERFACE ERRORS ALL, to store information about interface data that failed validation.

Interface Tables

- RA INTERFACE LINES ALL, page B-1
- RA_INTERFACE_SALESCREDITS_ALL, page B-49
- RA_INTERFACE_DISTRIBUTIONS_ALL, page B-53
- AR_INTERFACE_CONTS_ALL, page B-59
- RA_INTERFACE_ERRORS_ALL, page B-61

Table Name: RA INTERFACE LINES ALL

This table stores transaction header and line information. AutoInvoice uses Transaction Flexfields to uniquely identify each transaction that you import into Receivables. AutoInvoice always uses the Line Transaction Flexfield structure for both the Link-to and Reference information when importing invoices. For more information, see: Transaction Flexfields, Oracle Receivables User Guide.

Important: The following columns of the AutoInvoice interface table RA INTERFACE LINES ALL have become obsolete in R12:

- CUSTOMER_BANK_ACCOUNT_ID
- CUSTOMER_BANK_ACCOUNT_NAME
- PAYMENT_SERVER_ORDER_NUM
- APPROVAL_CODE

Instead of these fields, AutoInvoice requires you to populate the PAYMENT_TRXN_EXTENSION_ID. You can obtain this by calling the IBY_FNDCPT_TRXN_PUB.Create_Transaction_Extension before populating the AutoInvoice tables.

ACCOUNTING RULE DURATION

Enter the accounting rule duration for this transaction.

If LINE_TYPE = 'LINE' or you are passing header freight, and this transaction uses a variable duration accounting rule, you must enter a value in this column.

If LINE_TYPE = 'TAX' ', 'CHARGES' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos and on-account credits, do not enter a value in this column.

Validation: Accounting periods must be defined for the duration of the

accounting rule in GL PERIODS and

RA_INTERFACE_LINES_ALL.GL_DATE and

RA_INTERFACE_LINES_ALL.RULE_START_DATE must be in a period that has a status of 'Open' or 'Future'. The

value in this column must be a positive integer.

Destination: RA_CUSTOMER_TRX_LINES_ALL.

ACCOUNTING_RULE_DURATION

ACCOUNTING_RULE_ID

Enter the accounting rule ID for this transaction.

If LINE_TYPE = 'LINE' or you are passing header freight, this column is optional. For invoice lines with rules, you must enter either a value in this column or in ACCOUNTING_RULE_NAME, depending on the value you entered for your batch source. If you entered a value in ACCOUNTING_RULE_NAME, AutoInvoice defaults a value in this column.

If LINE_TYPE = 'TAX', 'CHARGES' or you are passing freight for a specific line, do not

enter a value in this column.

For credit memos, do not enter a value in this column; AutoInvoice uses the accounting rule from the transaction you are crediting.

Must exist in RA_RULES.RULE_ID and RA_RULES.TYPE Validation:

= 'A' or 'ACC DUR'. If LINE TYPE = 'CHARGES', then this

column must be null.

Destination: RA CUSTOMER TRX LINES ALL.

ACCOUNTING_RULE_ID

ACCOUNTING RULE NAME

Enter the accounting rule name for this transaction.

If LINE_TYPE = 'LINE' or you are passing header freight, this column is optional. For invoice lines with rules, you must enter either a value in this column or in ACCOUNTING_RULE_ID, depending on the value you entered for your batch source.

If LINE TYPE = 'TAX,' 'CHARGES,' or if you are passing freight for a specific line, do not enter a value in this column.

For credit memos do not enter a value in this column. AutoInvoice uses the accounting rule from the transaction you are crediting.

Validation: Must exist in RA RULES.NAME and RA RULES.TYPE =

'A' or 'ACC DUR'. If LINE_TYPE = 'CHARGES', then this

column must be null.

Destination: None

ACCTD_AMOUNT

Do not enter a value. Receivables does not currently use this column.

Validation: None

Destination: None

AGREEMENT NAME

Enter the name of the customer agreement for this transaction.

If LINE_TYPE = 'LINE', 'CHARGES' or you are passing header freight, this column is optional. Depending on the value you entered for your batch source, you can enter either a value in this column or in AGREEMENT ID. For invoice lines against a commitment, AutoInvoice will default the agreement from the commitment if AGREEMENT NAME and AGREEMENT ID are null and a agreement exists for the commitment.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos, do not enter a value in this column, AutoInvoice uses the customer agreement from the transaction you are crediting.

Validation: Must exist in SO AGREEMENTS.NAME

Destination: None

AGREEMENT ID

Enter the customer agreement ID for this transaction.

If LINE_TYPE = 'LINE', 'CHARGES' or you are passing header freight, this column is optional. Depending on the value you entered for your batch source, you can enter either a value in this column or in AGREEMENT_NAME. For invoice lines against a commitment, AutoInvoice will default the agreement from the commitment if AGREEMENT NAME and AGREEMENT ID are null and a agreement exists for the commitment.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line do not enter a value in this column.

For credit memos, do not enter a value in this column, AutoInvoice uses the customer agreement from the transaction you are crediting.

Must exist in SO_AGREEMENTS.ID Validation:

Destination: None

AMOUNT

Enter the revenue amount for this transaction.

If LINE_TYPE = 'LINE' and this transaction is neither a freight-only nor a tax-only line, you must enter a value in this column. If this transaction is a dummy line for freightonly or tax-only, do not enter a value in this column. AutoInvoice ignores any values you enter in this column if this transaction is a dummy line.

If LINE_TYPE = 'TAX', a value must be entered in either this column or the tax_rate column. Any exemptions must be factored into either of the two columns.

If LINE_TYPE = 'FREIGHT' and you are passing either header freight or freight for a specific line, you must enter a value in this column.

If LINE_TYPE = 'CHARGES', do not enter a value in this column.

If this line has AMOUNT_INCLUDES_TAX set to Yes, the sales credits and line amounts for this column must include tax.

For credit memos and on-account credits, enter the credit amount for this transaction.

Validation: If LINE TYPE = 'CHARGES', then this column must be

null. AutoInvoice will correct revenue amounts that have

the wrong currency precision.

Destination: If Create Clearing is set to No for this transaction batch

source (suspense/clearing account not used),

RA_CUSTOMER_TRX_LINES_ALL.REVENUE_AMOUNT

and RA_CUSTOMER_TRX_LINES_ALL.

EXTENDED_AMOUNT.

If Create Clearing is set to Yes for this transaction batch

source (suspense/clearing account used), RA_CUSTOMER_TRX_LINES_ALL.

REVENUE_AMOUNT.

AMOUNT_INCLUDES_TAX_FLAG

This column controls whether the amount for this transaction line includes tax. If this column is set to 'Y', this line is assigned to a tax inclusive tax code. If this is a tax group, this column should be null.

AutoInvoice only uses this column if the tax code assigned to this line has Allow Override set to Yes for the Tax Inclusive calculation.

Populate this column for invoices only. For regular credit memos, AutoInvoice always uses the AMOUNT_INCLUDES_TAX_FLAG value from the invoice that you are crediting.

Validation: If this is a tax code and Allow Override is set to No, this

> should be equal to either the setting of the Amount Includes Tax option for this tax code or null. Additionally, if Allow Override is set to No the Amount Includes Tax flag at the line level must equal the Allow Override flag for

this tax code.

Destination: RA CUSTOMER TRX LINES ALL.

AMOUNT_INCLUDES_TAX_FLAG

ADDRESS VERIFICATION CODE

The credit card address verification code provided by Oracle Payment Server.

None Validation

Destination RA CUSTOMER TRX ALL.

ADDRESS_VERIFICATION_CODE

ATTRIBUTE1-15

Enter the Invoice Line Information Flexfield attribute information for this transaction. Descriptive Flexfield attributes allow you to store additional columns, the contents of which you define. These columns are optional.

Validation: None

Destination: RA_CUSTOMER_TRX_LINES_ALL.ATTRIBUTE1-15

> **Note:** To ensure that AutoInvoice accurately groups your imported invoices, do not include newline or carriage return characters (chr(10) or chr(13)) in these Descriptive

Flexfield columns.

ATTRIBUTE CATEGORY

Enter the Invoice Line Information Flexfield category information for this transaction. Descriptive Flexfield categories allow you to store different categories of attributes. This column is optional.

Validation: None

Destination: RA CUSTOMER TRX LINES ALL.

ATTRIBUTE CATEGORY

BATCH_SOURCE_NAME

Enter the name of the batch source for this transaction. AutoInvoice uses your batch source to determine your transaction and batch numbering method and your AutoInvoice processing options. You must enter a value in this column.

Validation: Must exist in RA BATCH SOURCES ALL.NAME and

RA_BATCH_SOURCES_ALL.BATCH_SOURCE_TYPE =

'FOREIGN'

RA_BATCHES_ALL.BATCH_SOURCE_ID and Destination:

RA CUSTOMER TRX ALL.BATCH SOURCE ID

COMMENTS

Enter comments about this transaction.

If LINE_TYPE = 'LINE', 'CHARGES' or you are passing header freight, this column is optional.

If LINE_TYPE = 'TAX' or your are passing freight for a specific line, do not enter text in this column.

Validation: None

Destination: RA_CUSTOMER_TRX_ALL.COMMENTS

CONS_BILLING_NUMBER

Enter the number for this consolidated bill.

A consolidated bill number is used for grouping a set of invoices under one bill.

Validation: Must not already exist in AR CONS INV ALL.

CONS BILLING NUMBER and AR CONS INV ALL.

CONS_INV_TYPE='MINV'

Destination: AR_CONS_INV_ALL.CONS_BILLING_NUMBER

CONVERSION DATE

Enter the exchange rate date for this transaction. If you do not enter a date, AutoInvoice uses the transaction date as the default. If the currency of the transaction line is the same as the base currency, then leave this column null. If a credit memo is being processed, AutoInvoice uses the conversion date of the invoice that the credit memo is against, and not the credit memo transaction date.

Validation: None

Destination: RA_CUSTOMER_TRX_ALL.EXCHANGE_DATE

CONVERSION RATE

Enter the exchange rate for this transaction.

If CONVERSION_TYPE is User, you MUST enter a value in this column; otherwise do not enter a value. If the currency of the transaction is the same as the base currency, enter 'User' and set CONVERSION RATE to 1.

Validation: If RA_INTERFACE_LINES_ALL.CONVERSION_TYPE =

'User' then this column must not be null; otherwise, it must

be null.

Destination: RA CUSTOMER TRX ALL.EXCHANGE RATE

CONVERSION TYPE

Enter the exchange rate type for this transaction. If the currency of the transaction is the same as the base currency, enter 'User' and set CONVERSION_RATE to 1. You must enter a value in this column.

Validation: Must exist in GL DAILY CONVERSION TYPES.

CONVERSION_TYPE

Destination: RA_CUSTOMER_TRX_ALL.EXCHANGE_RATE_TYPE

CREDIT METHOD FOR ACCT RULE

Enter the credit method for crediting a transaction which uses an accounting rule. Choices include PRORATE, LIFO, or UNIT.

If this transaction is a credit memo against a transaction which uses an accounting rule and LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, you must enter a value in this column.

If this transaction is a credit memo against a transaction which uses an accounting rule and CREDIT METHOD FOR ACCT RULE is UNIT, then AutoInvoice rejects the credit memo if the credit quantity exceeds the quantity on the target invoice line.

If LINE TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column. AutoInvoice will ignore any value that you enter in this column.

For on-account credits do not enter a value in this column.

Must be either 'PRORATE', 'LIFO', 'UNIT' or NULL Validation:

Destination: RA CUSTOMER TRX ALL.

CREDIT_METHOD_FOR_RULES

CREDIT METHOD FOR INSTALLMENTS

Enter the credit method for crediting a transaction that uses split payment terms. Choices include PRORATE, LIFO, or FIFO.

If this transaction is a credit memo against a transaction that uses split payment terms and LINE TYPE = 'LINE', 'CHARGES', or you are passing header freight, you may enter a value in this column. If you do not enter a value, AutoInvoice defaults to PRORATE.

If LINE TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column. AutoInvoice will ignore any value that you enter in this column.

For on-account credits do not enter a value in this column.

Validation: Must be either 'PRORATE', 'LIFO', 'FIFO' or NULL.

Destination: RA CUSTOMER TRX ALL.

CREDIT METHOD FOR INSTALLMENTS

CURRENCY_CODE

Enter the currency code for this transaction. You must enter a value in this column.

For credit memos enter the currency code of the invoice you are crediting.

Validation: Must exist in FND_CURRENCIES.CURRENCY_CODE

Destination: RA_CUSTOMER_TRX_ALL.

> INVOICE CURRENCY CODE and AR_PAYMENT_SCHEDULES_ALL. INVOICE CURRENCY CODE

CUSTOMER TRX ID

This column is used by AutoInvoice and should be left null. AutoInvoice defaults a value into this column using your grouping rules.

Validation: None

Destination: RA CUSTOMER TRX ALL.CUSTOMER TRX ID,

> AR PAYMENT SCHEDULES ALL.CUSTOMER TRX ID, RA CUSTOMER TRX LINES ALL.CUSTOMER TRX ID,

and RA CUST TRX LINE GL DIST ALL.

CUSTOMER_TRX_ID.

CUST_TRX_TYPE_ID

Enter the transaction type ID for this transaction.

This column is optional, but depending on the value you entered for your batch source you must enter either a value in this column or in CUST TRX TYPE NAME. If you entered a value in CUST_TRX_TYPE_NAME, AutoInvoice defaults a value in this column.

For invoice lines against a commitment, AutoInvoice defaults the invoice transaction type from the transaction type of the commitment if CUST_TRX_TYPE_ID and CUST_TRX_TYPE_NAME are null.

For credit memos you must enter the ID of the credit memo transaction type which has been assigned to the transaction you are crediting.

Validation: Must exist in RA_CUST_TRX_TYPES_ALL.

CUST_TRX_TYPE_ID

RA_CUSTOMER_TRX_ALL.CUST_TRX_TYPE ID Destination:

CUST_TRX_TYPE_NAME

Enter the transaction type name for this transaction.

This column is optional, but depending on the value you entered for your batch source you must enter either a value in this column or in CUST_TRX_TYPE_ID.

For invoice lines against a commitment, AutoInvoice defaults the invoice transaction type from the transaction type of the commitment if CUST_TRX_TYPE_ID and

CUST_TRX_TYPE_NAME are null.

For credit memos you must enter the name of the credit memo transaction type which has been assigned to the transaction you are crediting.

RA_CUST_TRX_TYPES_ALL.NAME Validation:

Destination: None

DESCRIPTION

This is a required column in AutoInvoice. Enter the description for this transaction.

Validation: None

Destination: RA_CUSTOMER_TRX_LINES_ALL.DESCRIPTION

DOCUMENT NUMBER

Enter the document number for this transaction.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight and the creation method for the sequence numbering of this transaction is Manual, you must enter a value in this column.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight and the creation method is Automatic, do not enter a value in this column. AutoInvoice will create a unique document number.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

Validation: Number must not already exist in Oracle Receivables

RA CUSTOMER TRX ALL.DOC SEQUENCE VALUE Destination:

DOCUMENT_NUMBER_SEQUENCE_ID

This column is used by AutoInvoice and should be left null. AutoInvoice uses this column to store the document sequence ID for this transaction.

Validation: None

Destination: RA_CUSTOMER_TRX_ALL.DOC_SEQUENCE_ID

EXCEPTION ID

This column is used by AutoInvoice and should be left null. AutoInvoice defaults a value in this column when a tax exception occurs.

If your transaction is a credit memo, AutoInvoice defaults the tax exemption ID of the

transaction you are crediting.

Validation: None

Destination: RA CUSTOMER TRX LINES ALL.

ITEM_EXCEPTION_RATE_ID

EXEMPTION ID

This column is used by AutoInvoice and should be left null. AutoInvoice defaults a value in this column when this transaction is partially or fully exempt from tax.

For credit memos AutoInvoice defaults the tax exception ID of the transaction you are crediting.

Validation: None

Destination: RA_CUSTOMER_TRX_LINES_ALL.TAX_EXEMPTION_ID

FOB POINT

Enter the FOB point for this transaction.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional.

If LINE TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos do not enter a value in this column. AutoInvoice uses the FOB point from the transaction you are crediting.

Validation: Must exist in AR LOOKUPS.LOOKUP CODE and

AR_LOOKUPS.LOOKUP_TYPE = 'FOB'. Must be less than

or equal to 30 characters in length.

Destination: RA CUSTOMER TRX ALL.FOB POINT

GL DATE

Enter the general ledger date for this transaction. The GL date determines the accounting period that you record this transaction to your general ledger. If the Post To GL option on the transaction type of the transaction being passed is set to No, the GL_DATE column should be NULL.

If LINE_TYPE = 'LINE', 'CHARGES', and you are passing transactions without rules or you are passing header freight, this column is optional.

If LINE_TYPE = 'LINE' and you are importing transactions with rules, do not enter a date in this column.

If LINE_TYPE = 'TAX' or 'FREIGHT', do not enter a value in this column.

For credit memos, AutoInvoice defaults to the date you run AutoInvoice, unless the transaction you are crediting is billed in arrears. In that case, AutoInvoice defaults to the GL date of the transaction you are crediting.

For a more details on general ledger dates, see: Determining Dates, Oracle Receivables User Guide.

Validation: Must be in an open or future enterable accounting period

> and the period must exist in GL_PERIOD_STATUSES. If 'Post To GL' is set to No on the transaction type of the transaction being passed, column must be NULL.

If your invoice uses Bill in Arrears as the invoicing rule,

then the GL DATE column should be NULL.

Destination: RA_CUST_TRX_LINE_GL_DIST_ALL.GL_DATE

HEADER ATTRIBUTE1-15

Enter Descriptive Flexfield attribute information for the Transaction Information Flexfield. Descriptive Flexfield attributes let you store additional columns, the contents of which you define.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional.

If LINE TYPE = 'TAX' or 'FREIGHT', do not enter values in these columns.

Validation: None

Destination: RA_CUSTOMER_TRX_ALL.ATTRIBUTE1-15

> Note: To ensure that AutoInvoice accurately groups your imported invoices, do not include newline or carriage return characters (chr(10) or chr(13)) in these Descriptive

Flexfield columns.

HEADER ATTRIBUTE CATEGORY

For the Transaction Information Flexfield, enter Descriptive Flexfield attribute category information which is shared between this transaction and other transactions. Descriptive Flexfield categories allow you to store different categories of attributes.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional.

If LINE TYPE = 'TAX' or you are passing freight for a specific line', do not enter values in these columns.

Validation: None Destination: RA CUSTOMER TRX ALL.ATTRIBUTE CATEGORY

HEADER GDF ATTRIBUTE1-30

Reserved for country-specific functionality.

Performed by Oracle Global Financials Validation:

Destination: RA_CUSTOMER_TRX_ALL.GLOBAL_ATTRIBUTE1-30

HEADER GDF ATTR CATEGORY

Reserved for country-specific functionality.

Validation: Performed by Oracle Global Financials

Destination: RA_CUSTOMER_TRX_ALL.

GLOBAL ATTRIBUTE CATEGORY

INITIAL CUSTOMER TRX ID

This column is used by AutoInvoice and should be left null.

If this transaction is not a credit memo, AutoInvoice defaults a value into this column using RA_INTERFACE_LINES_ALL.REFERENCE_LINE_ID.

Validation: None

Destination: RA_CUSTOMER_TRX_ALL.

INITIAL_CUSTOMER_TRX_ID

INTERFACE LINE ATTRIBUTE1-15

Enter the Line Transaction Flexfield for this transaction. The Line Transaction Flexfield is a combination of attribute values that you use to uniquely identify this transaction line in your original system. The reference value you enter here provides you with an audit trail from Receivables back to your original system. You must enter values for enabled attributes.

Receivables copies the Line Transaction Flexfield to the Invoice Transaction Flexfield. When you import transactions with multiple lines using AutoInvoice, the attributes of the first line from the ordered lines will appear in the Invoice Transaction Flexfield.

Note: Interface lines belonging to the same transaction are ordered by the following SQL clause:

waybill_number||ship_via asc,

ship_date_actual desc

If a transaction has only one line, then the Invoice Transaction Flexfield will be the same as the Line Transaction Flexfield.

Validation: Must not already exist together with

> INTERFACE_LINE_CONTEXT in RA INTERFACE LINES ALL and RA_CUSTOMER_TRX_LINES_ALL.

All enabled attributes for a given

INTERFACE_LINE_CONTEXT must have values. Different attribute columns may be enabled depending on the value

in the INTERFACE_LINE_CONTEXT column.

Destination: RA CUSTOMER TRX ALL.

INTERFACE_HEADER_ATTRIBUTE1-15 and

RA_CUSTOMER_TRX_LINES_ALL. INTERFACE_LINE_ATTRIBUTE1-15

Note: To ensure that AutoInvoice accurately groups your imported invoices, do not include newline or carriage return characters (chr(10) or chr(13)) in these Descriptive

Flexfield columns.

INTERFACE LINE CONTEXT

This is a required column in AutoInvoice. Enter the context of the Line Transaction Flexfield entered in columns INTERFACE LINE ATTRIBUTE1-15. If you pass information with global context, set this column to 'Global Data Elements'.

Validation: None

Destination: RA_CUSTOMER_TRX_ALL.

> INTERFACE HEADER CONTEXT and RA CUSTOMER TRX LINES ALL. INTERFACE LINE CONTEXT

INTERFACE LINE ID

This column is used by AutoInvoice and should be left null. AutoInvoice defaults a value in this column using the RA_CUSTOMER_TRX_LINES_S sequence.

Validation: None

Destination: RA_CUSTOMER_TRX_LINES_ALL.

CUSTOMER_TRX_LINE_ID

INTERFACE STATUS

This column is used by AutoInvoice and should be left null. If AutoInvoice sets this

column to 'P' then the line has been transferred successfully.

INTERNAL NOTES

Enter internal notes for this transaction.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing freight header, this column is optional.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter text in this column.

Validation: None

Destination: RA CUSTOMER TRX ALL.INTERNAL NOTES

INVENTORY_ITEM_ID

Enter the inventory item ID for this transaction.

If LINE TYPE = 'LINE', or 'CHARGES' this column is optional. Depending on the value you entered for your batch source you can enter either a value in this column or a combination of segment values in MTL SYSTEM ITEMS SEG1-20. If you specify segments in your batch source, AutoInvoice defaults a value in this column.

If LINE_TYPE = 'TAX' or 'FREIGHT', do not enter a value in this column.

For credit memos do not enter a value in this column. AutoInvoice uses the value from the transaction you are crediting.

Validation: Must exist in MTL_SYSTEM_ITEMS.

INVENTORY ITEM ID and MTL SYSTEM ITEMS.

INVOICE_ENABLED_FLAG = 'Y'.

RA_CUSTOMER_TRX_LINES_ALL. Destination:

INVENTORY ITEM ID

INVOICING RULE ID

Enter the invoicing rule ID for this transaction.

If LINE TYPE = 'LINE' or you are passing header freight, this column is optional. For invoice lines with rules, you must enter either a value in this column or in INVOICING RULE NAME, depending on the value you entered for your batch source. If you specify invoicing rule name in your batch source, AutoInvoice defaults a value in this column.

If LINE_TYPE = 'TAX', 'CHARGES', or you are passing freight for a specific line, do not enter a value in this column.

For credit memos do not enter a value in this column. AutoInvoice uses the invoicing rule from the transaction you are crediting.

Validation: Must exist in RA_RULES.RULE_ID and RA_RULES.

> RULE_ID = -2 or -3. If you enter an invoicing rule you must also enter an accounting rule. If LINE_TYPE = 'CHARGES'

then this column must be null.

Destination: RA CUSTOMER TRX ALL.INVOICING RULE ID

INVOICING RULE NAME

Enter the invoicing rule name for this transaction.

If LINE TYPE = 'LINE' or you are passing header freight, this column is optional. For invoice lines with rules, you must enter either a value in this column or in INVOICING_RULE_ID, depending on the value you entered for your batch source. You can enter a value in this column or in INVOICING_RULE_ID.

If LINE_TYPE = 'TAX', 'CHARGES' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos do not enter a value in this column. AutoInvoice uses the invoicing rule from the transaction you are crediting.

Validation: Must exist in RA_RULES.RULE_ID and RA_RULES.

> RULE_ID = -2 or -3. If you enter an invoicing rule you must also enter an accounting rule. If LINE_TYPE = 'CHARGES'

then this column must be null.

Destination: None

LAST PERIOD TO CREDIT

For unit credit memos, enter the last period number from which you want to start crediting.

If this transaction is a credit memo against a transaction which uses an accounting rule and LINE TYPE = 'LINE', CREDIT METHOD FOR ACCT RULE = 'UNIT', or you are passing header freight, you may enter a value in this column.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column. AutoInvoice will ignore any value that you enter in this column.

Validation: Must be between 0 and the invoice's accounting rule

duration (inclusive).

Destination: RA CUSTOMER TRX LINES ALL.

LAST PERIOD TO CREDIT

LAST UPDATE LOGIN

This column is used by AutoInvoice and should be left null. AutoInvoice updates this

column when it selects rows from the RA_INTERFACE_LINES_ALL table for processing.

Validation: None

Destination: None

LINE GDF ATTRIBUTE1-20

Reserved for country-specific functionality.

Validation: Performed by Oracle Global Financials

Destination: RA CUSTOMER TRX LINES ALL.

GLOBAL_ATTRIBUTE1-20

LINE GDF ATTR CATEGORY

Reserved for country-specific functionality.

Validation: Performed by Oracle Global Financials

Destination: RA CUSTOMER TRX LINES ALL.

GLOBAL_ATTRIBUTE_CATEGORY

LINE NUMBER

This column is used by AutoInvoice and should be left null. AutoInvoice ignores any values passed in this column and always numbers the lines sequentially starting with the number 1 and in the order determined by the line ordering rule.

LINE TYPE

Enter 'LINE', 'TAX', 'FREIGHT' or 'CHARGES' to specify the line type for this transaction. (CHARGES refers to finance charges.) You must enter a value in this column.

For credit memos enter the type of line you are crediting.

Must be 'LINE', 'TAX', 'FREIGHT' or 'CHARGES' Validation:

Destination: RA_CUSTOMER_TRX_LINES_ALL.LINE_TYPE

LINK TO LINE ATTRIBUTE1-15

Enter the link to your Transaction Flexfield attribute values.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, do not enter values in these columns.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, you must enter a value. Use link to line attributes to associate this tax or freight line to another transaction line in RA_INTERFACE_LINES_ALL. All tax lines and freight for specific lines must be associated with a line that has a LINE_TYPE of 'LINE'. Enter the same combination of attribute values as the transaction to which you want to associate with.

For credit memos applied to tax lines, you must use these columns to link your credit memo tax lines to your credit memo transaction. Similarly, for credit memos applied to freight lines you must also use these columns to link your credit memo freight line to your credit memo transaction.

If you are applying a credit memo against a tax line which is linked to a transaction, you must enter a dummy credit memo transaction with a zero revenue amount and use these columns to link to your credit memo tax line. Similarly, if you are applying a credit memo against a freight line which is linked to a transaction, you must also enter a dummy credit memo transaction with a zero revenue amount and use these columns to link to your credit memo freight line.

Validation: The transaction that you link to must have a LINE_TYPE =

'LINE'. You can only link at most one freight line to another

transaction. You cannot link a transaction that has a

LINE_TYPE = 'LINE' or 'CHARGES' to another transaction.

Destination: None

LINK_TO_LINE_CONTEXT

Enter the context name of the Transaction Flexfield data that you entered in RA_INTERFACE_LINES_ALL.LINK_TO_LINE_ATTRIBUTE1-15.

Validation: None

Destination: None

LINK TO LINE ID

This column is used by AutoInvoice and should be left null. AutoInvoice defaults a value into this column using RA_INTERFACE_LINES_ALL. LINK_TO_LINE_ATTRIBUTE1-15 and RA_INTERFACE_LINES_ALL.

LINK_TO_LINE_CONTEXT.

Validation: None

Destination: RA_CUSTOMER_TRX_LINES_ALL.

LINK_TO_CUST_TRX_LINE_ID

LOCATION SEGMENT ID

This column is used by AutoInvoice and should be left null. AutoInvoice defaults a

value into this column if you are crediting a sales tax line.

Validation: None

Destination: RA_CUSTOMER_TRX_LINES_ALL.

LOCATION_SEGMENT_ID

MEMO_LINE_ID

Enter the standard memo line ID for this transaction.

If LINE TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. Depending on the value you entered for your batch source you can enter either a value in this column or in MEMO_LINE_NAME. If you specify memo line name in your batch source, AutoInvoice defaults a value in this column.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos do not enter a value in this column. AutoInvoice uses the memo line from the transaction you are crediting.

Validation: Must exist in AR_MEMO_LINES_ALL.MEMO_LINE_ID

RA CUSTOMER TRX LINES ALL.MEMO LINE ID Destination:

MEMO LINE NAME

Enter the name of the standard memo line for this transaction.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight this column is optional. Depending on the value you entered for your batch source you can enter either a value in this column or in MEMO_LINE_ID.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos do not enter a value in this column. AutoInvoice uses the memo line from the transaction you are crediting.

Validation: Must exist in AR_MEMO_LINES_ALL.NAME

None Destination:

MOVEMENT ID

This column is used to pass movement statistics that are tied to the shipment information and passed through AutoInvoice.

AutoInvoice will populate the column RA CUSTOMER TRX LINES ALL. MOVEMENT ID with RA INTERFACE LINES ALL.MOVEMENT ID and updates MTL_MOVEMENT_STATISTICS with transaction information (for example,

customer_trx_id, batch_id, customer_trx_line_id).

Validation: None

Destination: RA_CUSTOMER_TRX_LINES_ALL.MOVEMENT_ID

MTL_SYSTEM_ITEMS_SEG1-20

Assign a System Item Flexfield value for each segment you enable in Receivables. For example, if you enable six System Item Flexfield segments, you must enter six values in columns MTL_SYSTEM_ITEMS_SEG1-6. Be sure to enter the correct segment value. For example, value '01' is not the same as '1'.

If LINE TYPE = 'LINE' or 'CHARGES', these columns are optional. Depending on the value you entered for your batch source you can enter either values in these columns or in INVENTORY_ITEM_ID.

If LINE TYPE = 'TAX' or 'FREIGHT', do not enter values in these columns.

For credit memos do not enter values in these columns. AutoInvoice uses the values from the transaction you are crediting.

For debit memos do not enter values in these columns.

Validation: Valid combination of System Item Flexfield segment values

Destination: None

ORG ID

Enter the ID of the organization that this transaction belongs to. This column is mandatory in a multiple organization environment.

Validation: AutoInvoice imports transactions whose ORG_ID matches

the value of the MO: Operating Unit profile option.

Destination: None.

ORIGINAL_GL_DATE

Stores the value of the GL DATE column before AutoInvoice modifies the GL date. This column is used by AutoInvoice and should not be populated by the user.

Validation: None

Destination: None

ORIG SYSTEM BATCH NAME

Enter the batch name for this transaction. This column is optional.

AutoInvoice does not perform any validation on this column but uses the value entered when grouping transactions into invoices.

Validation: None

RA_CUSTOMER_TRX_ALL. Destination:

ORIG SYSTEM BATCH NAME

ORIG SYSTEM BILL ADDRESS ID

Enter the Bill-To customer address ID for this transaction. This Bill-To customer address ID is for the Bill-To customer you entered in ORIG SYSTEM BILL CUSTOMER REF or ORIG SYSTEM BILL CUSTOMER ID.

If no default Remit To Address has been specified, then AutoInvoice uses the Bill-To address to determine the Remit-To address for the customer. If the Remit-To address cannot be determined, then AutoInvoice will reject the transaction.

If LINE TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. Depending on the value you entered for your batch source you must enter either a value in this column or in ORIG SYSTEM BILL ADDRESS REF. If you specify the Bill-To customer address reference in your batch source, AutoInvoice defaults a value in this column.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

RA INTERFACE LINES ALL. Validation:

ORIG SYSTEM BILL ADDRESS ID =

HZ_CUST_ACCT_SITE.CUSTOMER_SITE_ID and

RA INTERFACE LINES ALL.

ORIG_SYSTEM_BILL_CUSTOMER_ID =

HZ CUST ACCOUNTS.CUST ACCOUNT ID and HZ CUST ACCOUNTS.CUST ACCOUNT ID = HZ_CUST_ACCT_SITE.CUST_ACCOUNT_ID and HZ CUST ACCT SITE.CUSTOMER SITE ID = HZ CUST SITE USES.CUST ACCT SITE ID and RA SITE USES.SITE USE CODE = 'BILL TO'

Destination: None

ORIG SYSTEM BILL ADDRESS REF

Enter the Bill-To customer address reference from your original system. This reference is for the Bill-To customer you entered in ORIG SYSTEM BILL CUSTOMER REF or ORIG SYSTEM BILL CUSTOMER ID. The reference value you enter here provides you with an audit trail from Receivables back to your original system.

If no default Remit To Address has been specified, then AutoInvoice uses the Bill-To

address to determine the Remit-To address for the customer. If the Remit-To address cannot be determined, then AutoInvoice will reject the transaction.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. Depending on the value you entered for your batch source you must enter either a value in this column or in ORIG SYSTEM BILL ADDRESS ID.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

Validation: RA_INTERFACE_LINES_ALL.

ORIG SYSTEM BILL ADDRESS REF =

HZ_CUST_ACCT_SITES_ALL.

ORIG SYSTEM REFERENCE and CUSTOMER REF = HZ_CUST_ACCOUNTS.ORIG_SYSTEM_REFERENCE and

HZ_CUST_ACCOUNTS.CUST_ACCOUNT_ID = HZ_CUST_ACCT_SITE.CUST_ACCOUNT_ID and HZ_CUST_ACCT_SITE.CUSTOMER_SITE_ID = HZ_CUST_SITE_USES.CUST_ACCT_SITE_ID and RA_SITE_USES.SITE_USE_CODE = 'BILL_TO'

Destination: None

ORIG_SYSTEM_BILL_CONTACT_ID

Enter the Bill-To contact ID for this transaction. This Bill-To contact ID must be for the Bill-To customer that you entered in ORIG_SYSTEM_BILL_CUSTOMER_REF or ORIG_SYSTEM_BILL_CUSTOMER_ID.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. Depending on the value you entered for your batch source you can enter either a value in this column or in ORIG_SYSTEM_BILL_CONTACT_REF. If you specify the Bill-To customer contact reference in your batch source, AutoInvoice defaults a value in this column.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

Validation: RA_INTERFACE_LINES_ALL.

ORIG_SYSTEM_BILL_CUSTOMER_ID =

HZ_CUST_ACCT_ROLES.CUST_ACCOUNT_ID and

RA_INTERFACE_LINES_ALL.

ORIG SYSTEM BILL CONTACT ID = HZ_CUST_SITE_USES.CUSTOMER_SITE_ID

RA_CUSTOMER_TRX_ALL.BILL_TO_CONTACT_ID Destination:

ORIG SYSTEM BILL CONTACT REF

Enter the Bill-To contact reference from your original system. This reference is for the Bill-To customer that you entered in ORIG SYSTEM BILL CUSTOMER REF or ORIG SYSTEM BILL CUSTOMER ID. The reference value you enter here provides you with an audit trail from Oracle Receivables back to your original system.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. Depending on the value you entered for your batch source you can enter either a value in this column or in ORIG_SYSTEM_BILL_CONTACT_ID.

If LINE TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

Validation: RA INTERFACE LINES ALL.

ORIG SYSTEM BILL CUSTOMER ID =

HZ CUST ACCT ROLES.CUST ACCOUNT ID and

RA INTERFACE LINES ALL.

ORIG SYSTEM BILL CONTACT REF = RA CONTACTS.

ORIG SYSTEM REFERENCE

None Destination:

ORIG SYSTEM BILL CUSTOMER ID

Enter the Bill-To customer ID for this transaction.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. Depending on the value you entered for your batch source you must enter either a value in this column or in ORIG_SYSTEM_BILL_CUSTOMER_REF. If you specify the Bill-To customer reference in your batch source, AutoInvoice defaults a value in this column.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos you must enter the Bill-To customer ID or the Bill-To customer ID of a related customer of the transaction you are crediting.

Validation: Must exist in HZ CUST ACCOUNTS.

CUST_ACCOUNT_ID

Destination: RA CUSTOMER TRX ALL.BILL TO CUSTOMER ID

ORIG SYSTEM BILL CUSTOMER REF

Enter a value you can use to uniquely identify this Bill-To customer in your original system. The reference value you enter here provides you with an audit trail from Oracle Receivables back to your original system.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. Depending on the value you entered for your batch source you must enter either a value in this column or in ORIG_SYSTEM_BILL_CUSTOMER_ID.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos you must enter the Bill-To customer reference or the Bill-To customer reference of a related customer of the transaction you are crediting.

Validation: Must exist in HZ_CUST_ACCOUNTS.

ORIG SYSTEM REFERENCE

Destination: None

ORIG SYSTEM SHIP ADDRESS ID

Enter the Ship-To customer address ID for this transaction.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. Depending on the value you entered for your batch source you can enter either a value in this column or in ORIG_SYSTEM_SHIP_ADDRESS_REF. If you specify the Ship-To address reference in your batch source, AutoInvoice defaults a value in this column.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos, do not enter a value in this column; AutoInvoice uses the Ship-To address from the transaction you are crediting.

Validation: RA_INTERFACE_LINES_ALL.

ORIG SYSTEM SHIP ADDRESS ID =

HZ_CUST_ACCT_SITE.CUSTOMER_SITE_ID and

RA INTERFACE LINES ALL.

ORIG_SYSTEM_SHIP_CUSTOMER_ID =

HZ CUST ACCOUNTS.CUST ACCOUNT ID and HZ_CUST_ACCOUNTS.CUST_ACCOUNT_ID = HZ_CUST_ACCT_SITE.CUST_ACCOUNT_ID and HZ_CUST_ACCT_SITE.CUSTOMER_SITE_ID = HZ_CUST_SITE_USES.CUST_ACCT_SITE_ID and HZ_CUST_SITE_USES.SITE_USE_CODE = 'SHIP_TO'

Destination: None

ORIG SYSTEM SHIP ADDRESS REF

Enter a value you can use to uniquely identify this Ship-To customer address in your original system. The reference value you enter here provides you with an audit trail from Receivables back to your original system.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. Depending on the value you entered for your batch source you can enter either a value in this column or in ORIG_SYSTEM_SHIP_ADDRESS_ID.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos do not enter a value in this column, AutoInvoice uses the Ship-To address from the transaction you are crediting.

Validation: RA_INTERFACE_LINES_ALL.

ORIG SYSTEM SHIP ADDRESS REF =

HZ_CUST_ACCT_SITES_ALL. ORIG SYSTEM REFERENCE and RA_INTERFACE_LINES_ALL.

ORIG_SYSTEM_SHIP_CUSTOMER_ID =

HZ_CUST_ACCOUNTS.CUST_ACCOUNT_ID and HZ_CUST_ACCOUNTS.CUST_ACCOUNT_ID = HZ_CUST_ACCT_SITE.CUST_ACCOUNT_ID and HZ_CUST_ACCT_SITE.CUSTOMER_SITE_ID = HZ CUST SITE USES.CUST ACCT SITE ID and HZ_CUST_SITE_USES.SITE_USE_CODE = 'SHIP_TO'

Destination: None

ORIG_SYSTEM_SHIP_CONTACT_ID

Enter the Ship-To contact ID for this transaction.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. Depending on the value you entered for your batch source you can enter either a value in this column or in ORIG_SYSTEM_SHIP_CONTACT_REF. If you specify the Ship-To contact reference in your batch source, AutoInvoice defaults a value in this column.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos, do not enter a value in this column. AutoInvoice uses the Ship-To contact from the transaction you are crediting.

Validation: RA INTERFACE LINES ALL.

ORIG_SYSTEM_SHIP_CUSTOMER_ID =

HZ_CUST_ACCT_ROLES.CUST_ACCOUNT_ID and

RA_INTERFACE_LINES_ALL.

ORIG SYSTEM SHIP CONTACT ID = HZ_CUST_SITE_USES.CUSTOMER_SITE_ID

Destination: RA_CUSTOMER_TRX_ALL.SHIP_TO_CONTACT_ID

ORIG SYSTEM SHIP CONTACT REF

Enter a value you can use to uniquely identify this Ship-To contact in your original system. The reference value you enter here provides you with an audit trail from Receivables back to your original system.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. Depending on the value you entered for your batch source you can enter either a value in this column or in ORIG_SYSTEM_SHIP_CONTACT_ID.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos, do not enter a value in this column. AutoInvoice uses the Ship-To contact from the transaction you are crediting.

Validation: RA INTERFACE LINES ALL.

ORIG SYSTEM SHIP CUSTOMER ID =

HZ_CUST_ACCT_ROLES.CUST_ACCOUNT_ID and

RA INTERFACE LINES ALL.

ORIG_SYSTEM_SHIP_CONTACT_REF =

HZ CUST ACCOUNT ROLES. ORIG_SYSTEM_REFERENCE

Destination: None

ORIG SYSTEM SHIP CUSTOMER ID

Enter the Ship-To customer ID for this transaction.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. Depending on the value you entered for your batch source you can enter either a value in this column or in ORIG SYSTEM SHIP CUSTOMER REF. If you specify the Ship-To customer reference in your batch source, AutoInvoice defaults a value in this column.

If LINE TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos, do not enter a value in this column. AutoInvoice uses the Ship-To customer from the transaction you are crediting.

Validation: Must exist in HZ_CUST_ACCOUNTS.

CUST_ACCOUNT_ID

RA CUSTOMER TRX ALL.SHIP TO CUSTOMER ID Destination:

ORIG SYSTEM SHIP CUSTOMER REF

Enter a value you can use to uniquely identify this Ship-To customer in your original

system. The reference value you enter here provides you with an audit trail from Receivables back to your original system.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. Depending on the value you entered for your batch source you can enter either a value in this column or in ORIG SYSTEM SHIP CUSTOMER ID.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos, do not enter a value in this column. AutoInvoice uses the Ship-To customer from the transaction you are crediting.

Validation: Must exist in HZ_CUST_ACCOUNTS.

ORIG_SYSTEM_REFERENCE

Destination: None

ORIG SYSTEM SOLD CUSTOMER ID

Enter the Sold-To customer ID for this transaction.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. Depending on the value you entered for your batch source you can enter either a value in this column or in ORIG SYSTEM SOLD CUSTOMER REF. If you specify the Sold-To customer reference in your batch source, AutoInvoice defaults a value in this column.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos do not enter a value. AutoInvoice uses the Sold-To customer from the transaction you are crediting.

Validation: Must exist in HZ_CUST_ACCOUNTS.

CUST ACCOUNT ID

Destination: RA_CUSTOMER_TRX_ALL.SOLD_TO_CUSTOMER_ID

ORIG SYSTEM SOLD CUSTOMER REF

Enter a value you can use to uniquely identify this Sold-To customer in your original system. The reference value you enter here provides you with an audit trail from Receivables back to your original system.

If LINE TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. Depending on the value you entered for your batch source you can enter either a value in this column or in ORIG SYSTEM SOLD CUSTOMER ID.

If LINE TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos do not enter a value, AutoInvoice uses the Sold-To customer from the transaction you are crediting.

Validation: Must exist in HZ_CUST_ACCOUNTS.

ORIG_SYSTEM_REFERENCE

Destination: None

OVERRIDE AUTO ACCOUNTING FLAG

This column controls whether the code combination ID of the Accounting Flexfield for this accounting distribution, populated by the feeder system, should override AutoAccounting.

Populate this column for invoices and credit memos.

Validation: Value should be Y or N.

Destination: RA CUSTOMER TRX LINES ALL.

OVERRIDE_AUTO_ACCOUNTING_FLAG

PAYMENT SET ID

This column contains a unique internal ID number that matches prepaid invoices with their prepayment receipts. This column should be populated only within a prepayments flow.

Must exist in AR RECEIVABLE APPLICATIONS ALL. Validation:

PAYMENT_SET_ID

Destination: RA CUSTOMER TRX LINES ALL.PAYMENT SET ID

PAYING CUSTOMER ID

This column is used by AutoInvoice and should be left null. Please refer to the section on Automatic Receipts for details on how AutoInvoice determines the paying customer.

None Validation:

RA CUSTOMER TRX ALL.PAYING CUSTOMER ID Destination:

PAYING SITE USE ID

This column is used by AutoInvoice and should be left null. Please refer to the section on Automatic Receipts for details on how AutoInvoice determines the paying site use.

Validation: None

Destination: RA_CUSTOMER_TRX_ALL.PAYING_SITE_USE_ID

PREVIOUS CUSTOMER TRX ID

This column is used by AutoInvoice and should be left null.

For credit memos, AutoInvoice defaults a value into this column using RA_INTERFACE_LINES_ALL.REFERENCE_LINE_ID.

Validation: None

Destination: RA CUSTOMER TRX ALL.

PREVIOUS CUSTOMER TRX ID and

RA_CUSTOMER_TRX_LINES_ALL.CUSTOMER_TRX_ID

PRIMARY SALESREP ID

Enter the primary salesperson ID for this transaction.

If LINE TYPE = 'LINE', 'CHARGES', or you are passing header freight, and you entered Yes for the Require Salesreps system option, you must enter either a value in this column or in PRIMARY_SALESREP_NUMBER. Otherwise this column is optional. The value that you enter depends on the value you entered for your batch source. If you specify the primary salesrep ID in your batch source, AutoInvoice defaults a value in this column.

If LINE TYPE = "TAX" or you are passing freight for a specific line, do not enter a value in this column.

Validation: Must exist in RA_SALESREPS.SALESREP_ID

RA CUSTOMER TRX ALL.PRIMARY SALESREP ID Destination:

PRIMARY SALESREP NUMBER

Enter the primary salesperson number for this transaction.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, and you entered Yes for the Require Salesreps system option, you must enter either a value in this column or in PRIMARY_SALESREP_ID. Otherwise this column is optional. The value that you enter depends on the value you entered for your batch source.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

Validation: Must exist in RA SALESREPS.SALESREP NUMBER

None Destination:

PRINTING OPTION

Enter the printing option for this transaction.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. AutoInvoice defaults to the printing option that you entered for this transaction type, if one was entered.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

Validation: Must exist in AR_LOOKUPS.LOOKUP_CODE and

> AR_LOOKUP.LOOKUP_TYPE = 'INVOICE_PRINT_OPTIONS'

Destination: RA CUSTOMER TRX ALL.PRINTING OPTION

PROMISED_COMMITMENT_AMOUNT

Enter the amount of an existing deposit to use as payment towards a specific transaction.

When an order is imported into Receivables with a value in this column, Receivables adjusts the resulting invoice and reduces the deposit balance by the lesser of the promised amount, the commitment balance, or the remaining amount due on the invoice.

If this column has no value, then the commitment adjustment will be for the lesser of the total outstanding commitment or the total balance of the transaction.

Validation: None

Destination: None

PURCHASE ORDER

Enter the purchase order number for this transaction.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos do not enter a value in this column. AutoInvoice uses the purchase order number from the transaction you are crediting.

Validation: None

Destination: RA_CUSTOMER_TRX_ALL.PURCHASE_ORDER

PURCHASE ORDER DATE

Enter the date of the purchase order for this transaction.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is

optional.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos, do not enter a value in this column. AutoInvoice uses the purchase order date from the transaction you are crediting.

Validation: None

Destination: RA_CUSTOMER_TRX_ALL.PURCHASE_ORDER_DATE

PURCHASE ORDER REVISION

Enter the purchase order revision for this transaction.

If LINE TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional.

If LINE TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos, do not enter a value in this column. AutoInvoice uses the purchase order revision from the transaction you are crediting.

Validation: None

RA CUSTOMER TRX ALL. Destination:

PURCHASE ORDER REVISION

QUANTITY

If this transaction is an invoice or credit memo line and LINE TYPE = 'LINE' or you are passing header freight, this column is optional. For invoice lines, enter the number of units shipped. For credit memo lines, enter the number of units you are crediting. If you do not enter a value in this column, AutoInvoice uses AMOUNT as the extended amount for this transaction. If this transaction is a dummy line for either freight only or tax only, AutoInvoice ignores the value you enter in this column.

If this is a Credit Memo line and LINE_TYPE = 'LINE', CREDIT_METHOD_FOR_ACCT_RULE = 'UNIT' then this column is mandatory.

If this transaction is a credit memo against a transaction which uses an accounting rule and CREDIT_METHOD_FOR_ACCT_RULE is UNIT, then AutoInvoice rejects the credit memo if the credit quantity exceeds the quantity on the target invoice line.

For Debit Memos, if LINE_TYPE = 'CHARGES', set quantity to 1.

If LINE TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For Credit Memos, if LINE_TYPE = 'CHARGES', set quantity to 1 or -1.

Validation: For Debit Memos lines with LINE TYPE = 'CHARGES',

quantity must be 1. For Credit Memo lines with

LINE_TYPE = 'CHARGES', this column must be 1 or -1.

For Credit Memo lines with LINE_TYPE = 'LINE' and CREDIT METHOD FOR ACCT RULE = 'UNIT' then this

column must not be null.

RA_CUSTOMER_TRX_LINES_ALL. Destination:

QUANTITY_INVOICED if this transaction is an invoice

line. RA CUSTOMER TRX LINES ALL.

QUANTITY CREDITED if this transaction is a credit

memo line.

QUANTITY_ORDERED

Enter the original number of units ordered for this transaction.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing freight for a specific line, this column is optional.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this field.

For credit memos, do not enter a value in this column. AutoInvoice uses the quantity ordered from the transaction you are crediting.

Validation: None

Destination: RA_CUSTOMER_TRX_LINES_ALL.

QUANTITY_ORDERED

REASON_CODE

Enter the reason code for this transaction.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. Depending on the value you entered for your batch source you can enter either a value in this column or in REASON_CODE_MEANING. If you specify the reason code meaning in your batch source, AutoInvoice defaults a value in this column.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos and on-account credits this column is optional.

Validation: Must exist in AR LOOKUPS.LOOKUP CODE. This

lookup type is either INVOICING_REASON or

CREDIT_MEMO_REASON

Destination: RA CUSTOMER TRX LINES ALL.REASON CODE and

RA CUSTOMER TRX ALL.REASON CODE

REASON CODE MEANING

Enter the meaning of the reason code for this transaction.

If LINE TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. Depending on the value you entered for your batch source you can enter either a value in this column or in REASON CODE.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos and on-account credits this column is optional.

Validation: Must exist in AR LOOKUPS.MEANING. This lookup type

is either INVOICING_REASON or

CREDIT_MEMO_REASON

Destination: None

RECEIPT_METHOD_ID

Enter the receipt method ID for this transaction.

If LINE TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. Depending on the value you entered for your batch source you can enter either a value in this column or in RECEIPT METHOD NAME. If you specify the receipt method name in your batch source, AutoInvoice defaults a value in this column.

AutoInvoice always defaults the receipt method using the following hierarchy:

- 1. primary receipt method of the parent primary bill-to site
- 2. primary receipt method of the parent customer
- 3. primary receipt method of the bill-to site
- 4. primary receipt method of the bill-to customer

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this field.

Validation: Must exist in AR_RECEIPT_METHODS.

> RECEIPT METHOD ID and must belong to the bill-to customer or the parent. Additionally, the receipt method must have at least one bank account in the same currency as the transaction or have its Receipts Multi-Currency flag

set to Yes.

Destination: RA CUSTOMER TRX ALL.RECEIPT METHOD ID

RECEIPT_METHOD_NAME

Enter the name of the receipt method for this transaction.

If LINE TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. Depending on the value you entered for your batch source you can enter either a value in this column or in RECEIPT METHOD ID.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this field.

Validation: Must exist in AR_RECEIPT_METHODS.NAME and must

belong to the bill-to customer or the parent.

Destination: None

not enter values in these columns.

REFERENCE LINE ATTRIBUTE1-15

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, and this transaction is a credit memo, you must enter either the Transaction Flexfield of the transaction line you are crediting in these columns or the RA CUSTOMER TRX LINES ALL.CUSTOMER TRX LINE ID of the transaction you are crediting in RA_INTERFACE_LINES_ALL.REFERENCE_LINE_ID. Otherwise, do

If LINE_TYPE = 'TAX' and this transaction is a credit memo, you must enter either the Transaction Flexfield of the tax line you are crediting in these columns or the RA_CUSTOMER_TRX_LINES_ALL.CUSTOMER_TRX_LINE_ID of the transaction tax line you are crediting in RA INTERFACE LINES ALL.REFERENCE LINE ID. Otherwise, do not enter values in these columns.

If LINE TYPE= 'FREIGHT' and this transaction is a credit memo, you must enter either the Transaction Flexfield of the freight line you are crediting in these columns or the RA CUSTOMER TRX LINES ALL.CUSTOMER TRX LINE ID of the transaction freight line you are crediting in RA_INTERFACE_LINES_ALL.REFERENCE_LINE_ID. Otherwise, do not enter values in these columns.

For on-account credits do not enter values in these columns.

Validation: Must exist in RA CUSTOMER TRX LINES ALL.

INTERFACE LINE ATTRIBUTE1-15 or

RA INTERFACE LINES ALL.

INTERFACE_LINE_ATTRIBUTE1-15

Destination: None

REFERENCE LINE CONTEXT

Enter the context name of the Transaction Flexfield data entered in RA INTERFACE LINES ALL.REFERENCE LINE ATTRIBUTE1-15. You must enter a value in this column if you entered values in RA_INTERFACE_LINES_ALL. ATTRIBUTE1-15.

Validation: Must exist in RA CUSTOMER TRX LINES ALL.

> INTERFACE_LINE_CONTEXT or RA INTERFACE LINES ALL. INTERFACE LINE CONTEXT

Destination: None

REFERENCE LINE ID

If LINE TYPE = 'LINE', 'CHARGES', or you are passing header freight, and this transaction is a credit memo, you must enter the RA_CUSTOMER_TRX_LINES_ALL. CUSTOMER TRX LINE ID of the transaction line you are crediting in this column or the Transaction Flexfield in REFERENCE_LINE_ATTRIBUTE1-15. Otherwise, do not enter a value.

If LINE_TYPE = 'LINE' and this transaction is an invoice against a commitment, you must enter the RA CUSTOMER TRX LINES ALL.CUSTOMER TRX LINE ID of the commitment line you are referencing.

Note: Note: An invoice can be attached to only one commitment. Upon import, if an invoice has multiple lines where different commitment line values are provided in the REFERENCE_LINE_ID column, then Receivables creates one or more invoices, accordingly.

Tip: If an invoice has multiple lines but a commitment's balance covers only a partial invoice amount, then Receivables can still create a single invoice upon import. To accomplish this, all lines must have the same commitment line value but, using the

PROMISED_COMMITMENT_AMOUNT column, some invoice lines will deplete the commitment's remaining balance while other invoice lines will have an allocated commitment value of zero.

If LINE_TYPE= 'TAX' and this transaction is a credit memo, you must enter the RA CUSTOMER TRX LINES ALL.CUSTOMER TRX LINE ID of the tax line you are crediting in these columns or the Transaction Flexfield in REFERENCE LINE ATTRIBUTE1-15. Otherwise, do not enter a value in this column.

If LINE TYPE = 'FREIGHT' and this transaction is a credit memo, you must enter the RA CUSTOMER TRX LINES ALL.CUSTOMER TRX LINE ID of the freight line you are crediting in these columns or the Transaction Flexfield in REFERENCE_LINE_ATTRIBUTE1-15. Otherwise, do not enter a value in this column.

For on-account credits, do not enter a value in this column.

Validation: Must exist in RA CUSTOMER TRX LINES ALL.

CUSTOMER_TRX_LINE_ID.

Destination: RA CUSTOMER TRX LINES ALL.

PREVIOUS_CUSTOMER_TRX_LINE_ID if this transaction

is a credit memo. Otherwise,

RA_CUSTOMER_TRX_LINES_ALL. INITIAL CUSTOMER TRX LINE ID

RELATED BATCH SOURCE NAME

Enter the name of the batch source of the document to which this transaction is related.

If LINE TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. Depending on the value you entered for your batch source you can enter a value in this column and the related transaction number in RELATED_TRX_NUMBER. Or, you can enter the related customer transaction ID in RELATED_CUSTOMER_TRX_ID.

If LINE TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos and on-account credits do not enter a value in this column.

Validation: RA INTERFACE LINES ALL.

> RELATED BATCH SOURCE NAME = RA_BATCH_SOURCES_ALL.NAME and

RA INTERFACE LINES ALL.RELATED TRX NUMBER

= RA CUSTOMER TRX ALL.TRX NUMBER and RA_BATCH_SOURCES_ALL.BATCH_SOURCE_ID = RA_CUSTOMER_TRX_ALL.BATCH_SOURCE_ID

Destination: None

RELATED CUSTOMER TRX ID

Enter the customer transaction ID of the document to which this transaction is related.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. Depending on the value you entered for your batch source you can enter a value in this column. Or, you can enter the related transaction number in RELATED TRX NUMBER and the related batch source name in RELATED BATCH SOURCE NAME.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos and on-account credits do not enter a value in this column.

Validation: Must exist in RA_CUSTOMER_TRX_ALL. CUSTOMER_TRX_ID

Destination: RA_CUSTOMER_TRX_ALL.

RELATED CUSTOMER TRX ID

RELATED_TRX_NUMBER

Enter the document number to which this transaction is related.

If LINE TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. Depending on the value you entered for your batch source you can enter a value in this column and the related batch source name in

RELATED BATCH SOURCE NAME. Or, you can enter the related customer transaction ID in RELATED_CUSTOMER_TRX_ID.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos and on-account credits do not enter a value in this column.

Validation: RA INTERFACE LINES ALL.

> RELATED BATCH SOURCE NAME = RA_BATCH_SOURCES_ALL.NAME and

RA INTERFACE LINES ALL.RELATED TRX NUMBER

= RA_CUSTOMER_TRX_ALL.TRX_NUMBER and RA BATCH SOURCES ALL.BATCH SOURCE ID = RA_CUSTOMER_TRX_ALL.BATCH_SOURCE_ID

Destination: None

REQUEST_ID

This column is used by AutoInvoice and should be left null.

Validation: None

The REQUEST_ID column in RA_CUSTOMER_TRX_ALL, Destination:

> RA CUSTOMER TRX LINES ALL, RA CUST TRX LINE GL DIST ALL, AR PAYMENT SCHEDULES ALL, AR RECEIVABLE APPLICATIONS ALL,

AR ADJUSTMENTS ALL and

RA_CUST_TRX_LINE_SALESREPS_ALL.

RULE START DATE

Enter the date that you want to start the accounting rule for this transaction.

If LINE TYPE = 'LINE' or you are passing header freight, this column is optional. If you

specify Specific Date in your accounting rule do not enter a value in this column.

If LINE_TYPE = 'TAX', 'CHARGES', or you are passing freight for a specific line, do not enter a value in this column.

For credit memos do not enter a value in this column.

For more information about rule start dates, see: Determining Dates, Oracle Receivables User Guide.

Validation: None

Destination: RA_CUSTOMER_TRX_LINES_ALL.RULE_START_DATE

RULE END DATE

Enter the date that you want to end the accounting rule for this transaction.

This column is required if the accounting rule is either Daily Revenue Rate, All Periods or Daily Revenue Rate, Partial Periods.

If LINE_TYPE = 'LINE' or you are passing header freight, this column is optional. If you specify Specific Date in your accounting rule do not enter a value in this column.

If LINE_TYPE = 'TAX', 'CHARGES', or you are passing freight for a specific line, do not enter a value in this column.

For credit memos do not enter a value in this column.

For more information about rule start dates, see: Determining Dates, Oracle Receivables User Guide.

Validation: None

Destination: RA_CUSTOMER_TRX_LINES_ALL.RULE_END_DATE

SALES ORDER

Enter the sales order number for this transaction.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos do not enter a value in this column. AutoInvoice uses the sales order number from the transaction you are crediting.

Validation: None

Destination: RA CUSTOMER TRX LINES ALL.SALES ORDER

SALES ORDER DATE

Enter the date of the sales order for this transaction.

If LINE TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos do not enter a value in this column. AutoInvoice uses the sales order date from the transaction you are crediting.

Enter the date of the revenue order for this transaction.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos do not enter a value in this column. AutoInvoice uses the revenue order date from the transaction you are crediting.

Validation: None

Destination: RA_CUSTOMER_TRX_LINES_ALL.

SALES ORDER DATE

SALES ORDER LINE

Enter the sales order line number for this transaction.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos do not enter a value in this column. AutoInvoice uses the sales order line number from the transaction you are crediting.

Validation:

Destination: RA CUSTOMER TRX LINES ALL.SALES ORDER LINE

SALES ORDER REVISION

Enter the sales order revision for this transaction.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value

in this column.

For credit memos do not enter a value in this column. AutoInvoice uses the sales order revision from the transaction you are crediting.

Validation: None

Destination: RA_CUSTOMER_TRX_LINES_ALL.

SALES_ORDER_REVISION

SALES_ORDER_SOURCE

Enter the source of the sales order for this transaction.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos do not enter a value in this column. AutoInvoice uses the source of the sales order from the transaction you are crediting.

Validation: None

Destination: RA_CUSTOMER_TRX_LINES_ALL.

SALES ORDER SOURCE

SALES TAX ID

This column is used by AutoInvoice and should be left null.

For credit memos, AutoInvoice defaults to the sales tax ID of the transaction you are crediting.

Validation: None

Destination: RA CUSTOMER TRX LINES ALL.SALES TAX ID

SET OF BOOKS ID

Optionally enter the ledger ID for this transaction. If no value exists, then Receivables defaults the ledger from the System Options window for the organization that is specified in the ORG_ID column.

Validation: Must exist in AR_SYSTEM_PARAMETERS_ALL.

SET OF BOOKS ID

Destination: RA_CUSTOMER_TRX_ALL.SET_OF_BOOKS_ID

SHIP DATE ACTUAL

Enter the shipment date for this transaction.

If LINE TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos do not enter a value in this column. AutoInvoice uses the earliest shipment date from the transaction you are crediting.

Validation: None

Destination: RA CUSTOMER TRX ALL.SHIP DATE ACTUAL

SHIP_VIA

Enter the ship via code for this transaction.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos do not enter a value in this column. AutoInvoice uses the ship via code from the transaction you are crediting.

Validation: ORG_FREIGHT.FREIGHT_CODE =

> RA INTERFACE LINES ALL.SHIP_VIA and ORG FREIGHT.ORGANIZATION ID =

RA INTERFACE LINES ALL.WAREHOUSE ID.

RA_INTERFACE_LINES_ALL.SHIP_VIA must be less than

or equal to 25 characters in length.

Destination: RA_CUSTOMER_TRX_ALL.SHIP_VIA

SOURCE DATA KEY1-5

Enter line group attributes that link one or more transaction lines into groups.

Receivables uses groups during line-level cash application.

See: Applying Receipts in Detail, Oracle Receivables User Guide.

Validation: None

Destination: RA_CUSTOMER_TRX_LINES_ALL.

SOURCE DATA KEY1-5

TAX CODE

Enter the tax code for this tax line.

If LINE TYPE = 'CHARGES', or 'FREIGHT', do not enter a value in this column.

If LINE_TYPE = 'LINE', this column is optional.

If LINE_TYPE = 'TAX', this column is mandatory.

For credit memos, AutoInvoice defaults the tax code from the transaction you are crediting.

Validation: Must exist in AR VAT TAX.TAX CODE

Destination: None

TAX EXEMPT FLAG

If LINE_TYPE = 'LINE', this column is optional. The value you enter here controls how a line is taxed. Enter 'E' if you want AutoInvoice to exempt an invoice line that would normally be taxed and your system option 'Use Customer Exemptions' is set to Yes. If you enter 'E' you must enter a value for TAX_EXEMPT_REASON_CODE or TAX_EXEMPT_REASON_CODE_MEANING, depending on your batch source option.

Enter 'R' if you want AutoInvoice to force tax on an invoice line, ignoring any exemption certificates that may be on file. Enter 'S' if you want tax to be calculated as per the normal procedures set up in Receivables.

For all other line types and credit memos,, do not enter a value in this column.

Validation: Must exist in AR LOOKUPS.LOOKUP CODE. Lookup

type is TAX_CONTROL_FLAG.

RA CUSTOMER TRX LINES ALL.TAX EXEMPT FLAG Destination:

TAX EXEMPT NUMBER

Enter the tax exempt number for this transaction. If LINE TYPE = 'LINE' and tax_exempt_flag = 'E', then you may enter a value in this column. Otherwise, do not enter a value in this column.

For all other line types, do not enter a value in this column.

For credit memos, do not enter a value in this column.

Validation: None

Destination: RA_CUSTOMER_TRX_LINES_ALL.

TAX_EXEMPT_NUMBER

TAX EXEMPT REASON CODE

Enter the tax exempt reason code for this transaction. If LINE_TYPE = 'LINE' and tax_exempt flag = 'E', then depending on your batch source option, Memo Reason, you must enter a value in this column or in TAX_EXEMPT_REASON_CODE_MEANING. If you specify a tax exempt reason code meaning in your batch source, AutoInvoice defaults the code in this column.

For all other line types, do not enter a value in this column.

For credit memos do not enter a value in this column.

Validation: Must exist in AR_LOOKUPS.LOOKUP_CODE. Lookup

type is TAX_REASON.

Destination: RA CUSTOMER TRX LINES ALL.

TAX_EXEMPT_REASON_CODE

TAX EXEMPT REASON CODE MEANING

Enter the tax exempt reason code meaning for this transaction. If LINE_TYPE = 'LINE' and tax_exempt_flag = 'E', then depending on your batch source option, Memo Reason, you must enter a value in this column or in TAX_EXEMPT_REASON_CODE. Otherwise, do not enter a value in this column.

For all other line types and credit memos, do not enter a value in this column.

Validation: Must exist in AR_LOOKUPS.MEANING. Lookup type is

TAX_REASON.

Destination: None

TAX PRECEDENCE

Important: This column is obsolete and should not be populated.

TAX RATE

Enter the tax rate for this tax line.

If LINE_TYPE = 'LINE', 'CHARGES', or 'FREIGHT', do not enter a value in this column.

If LINE_TYPE = 'TAX', you must enter a value either in this column or the AMOUNT column. Any exemptions for the tax lines must be factored into the tax rate.

Validation: None

Destination: RA_CUSTOMER_TRX_LINES_ALL.TAX_RATE

TERM ID

Enter the payment term ID for this transaction.

If LINE TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. Depending on the value you entered for your batch source you must enter either a value in this column or in TERM_NAME. If you specify term name in your batch source, AutoInvoice defaults a value in this column.

If LINE TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos and on-account credits do not enter a value in this column.

Validation: Must exist in RA_TERMS.TERM_ID

RA_CUSTOMER_TRX_ALL.TERM_ID Destination:

TERM NAME

Enter the name of the payment term for this transaction.

If LINE TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. Depending on the value you entered for your batch source you must enter either a value in this column or in TERM ID.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos and on-account credits do not enter a value in this column.

Validation: Must exist in RA_TERMS.NAME

Destination: None

TERRITORY ID

Enter the territory ID for this transaction.

If LINE_TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. Depending on the value you entered for your batch source you can enter either a value in this column or a combination of territory segment values in TERRITORY_SEGMENT1-20. If you specify the combination of territory segment values in your batch source, AutoInvoice defaults a value in this column.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

For credit memos do not enter a value in this column. AutoInvoice uses the territory from the transaction you are crediting.

Validation: Must exist in RA_TERRITORIES.TERRITORY_ID Destination: RA_CUSTOMER_TRX_ALL.TERRITORY_ID

TERRITORY_SEGMENT1-20

Assign a Territory Flexfield value for each segment you enable in Receivables. For example, if you enable six Territory Flexfield segments, you must enter six values in columns TERRITORY SEGMENT1-6. Be sure to enter the correct segment value. For example, value '01' is not the same as '1'.

If LINE TYPE = 'LINE', 'CHARGES', or you are passing header freight, these columns are optional. Depending on the value you entered for your batch source you can enter either values in these columns or in TERRITORY_ID.

If LINE_TYPE = 'TAX' or you are passing freight for a specific line, do not enter values in these columns.

For credit memos do not enter values in these columns. AutoInvoice uses the territory from the transaction you are crediting.

Validation: Valid combination of Territory Flexfield segment values

from RA_TERRITORIES

Destination: None

TRANSLATED DESCRIPTION

The translated description of this transaction line (used for multi-lingual support)

Validation None

Destination RA CUSTOMER TRX LINES ALL.

TRANSLATED_DESCRIPTION

TRX DATE

Enter the transaction date for this transaction.

If TRX TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. If this transaction is an invoice or debit memo line, you can enter the invoice date. If this transaction is a credit memo line, you can enter the credit memo date. If this transaction is an invoice line and uses an Arrears Invoice invoicing rule, do not enter a value in this column.

If you do not enter a transaction date, AutoInvoice uses the general ledger date for invoice and debit memo lines. For credit memo lines, AutoInvoice uses the following hierarchy: credit memo general ledger date, and the general ledger date for the invoice's receivable distribution or the date in the Run AutoInvoice window, whichever is later.

When child invoices are created against a commitment, AutoInvoice ensures that the child invoice's transaction date falls between the commitment's start and end dates.

If TRX_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

Validation: None

RA_CUSTOMER_TRX_ALL.TRX_DATE Destination:

TRX NUMBER

Enter the number for this transaction.

If TRX TYPE = 'LINE', 'CHARGES', or you are passing header freight, and your batch source has Automatic Invoice Numbering set to No, you must enter a value in this column.

If TRX TYPE = 'LINE', 'CHARGES', or you are passing header freight, and your batch source has Automatic Invoice Numbering set to Yes, do not enter a value in this column. AutoInvoice inserts a unique number in this column.

If TRX_TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

Validation: Must not already exist in RA_CUSTOMER_TRX_ALL.

TRX NUMBER and RA CUSTOMER TRX ALL.

BATCH SOURCE ID

Destination: RA CUSTOMER TRX ALL.TRX NUMBER and

AR_PAYMENT_SCHEDULES_ALL.TRX_NUMBER

UOM CODE

Enter the unit of measure code for this transaction.

If LINE_TYPE = 'LINE' and the line has an item you must enter either a value in this column or in UOM_NAME. If this a freight-only line, a tax-only line, or a line with no item, this column is optional.

If LINE_TYPE = 'LINE' and you are passing a dummy line for either a tax-only or freight-only line, AutoInvoice ignores what you enter here.

If LINE_TYPE = 'TAX', 'CHARGES', or you are passing freight for a specific line, do not enter a value in this column.

For credit memos do not enter a value in this column. AutoInvoice uses the unit of measure from the transaction you are crediting.

Validation: Must exist in MTL UNITS OF MEASURE.UOM CODE. If

Line_type = 'CHARGES', then this column must be null.

Destination: RA_CUSTOMER_TRX_LINES_ALL.UOM_CODE

UOM NAME

Enter the unit of measure name for this transaction.

If LINE TYPE = 'LINE' and the line has an item you must enter either a value in this column or in UOM_CODE. If this a freight-only line, a tax-only line, or a line with no item, this column is optional.

If LINE_TYPE = 'LINE' or you are passing header freight, and you are passing a dummy line for either a tax-only or freight-only line, AutoInvoice ignores what you enter here.

If LINE_TYPE = 'TAX', 'CHARGES', or you are passing freight for a specific line, do not enter a value in this column.

For credit memos do not enter a value in this column. AutoInvoice uses the unit of measure from the transaction you are crediting.

Validation: Must exist in MTL_UNITS_OF_MEASURE.

UNIT OF MEASURE. If LINE TYPE = 'CHARGES' then

this column must be null.

Destination: None

UNIT_SELLING_PRICE

Enter the selling price per unit for this transaction.

If LINE TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional. If you do not enter a value in this column, AutoInvoice defaults to the amount in RA_INTERFACE_LINES_ALL.AMOUNT as the amount/quantity for this transaction.

If LINE_TYPE = 'LINE' or you are passing header freight, and you are passing a dummy line for either a tax-only or freight-only line, AutoInvoice ignores the value you enter here.

If LINE TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value in this column.

Validation: None

RA CUSTOMER TRX LINES ALL. Destination:

UNIT_SELLING_PRICE

UNIT_STANDARD_PRICE

Enter the standard price per unit for this transaction.

If LINE TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional.

If LINE TYPE = 'TAX' or you are passing freight for a specific line, do not enter a value

in this column.

For credit memos do not enter a value in this column. AutoInvoice uses the unit standard price from the transaction you are crediting.

Validation: None

Destination: RA_CUSTOMER_TRX_LINES_ALL.

UNIT_STANDARD_PRICE

USSGL TRANSACTION CODE

Enter the transaction code for this transaction. If this transaction is linked to another transaction, you must enter the same transaction code as the one to which it is linked. This column is optional.

Validation: None

Destination: RA CUSTOMER TRX LINES ALL.

DEFAULT_USSGL_TRANSACTION_CODE

USSGL TRANSACTION CODE CONTEXT

This column is not currently used by AutoInvoice.

Validation: None

Destination: None

VAT TAX ID

This column is used by AutoInvoice and should be left null. If you enter a value in TAX_CODE, AutoInvoice defaults a value in this column.

For credit memos AutoInvoice defaults to the VAT tax ID of the transaction you are crediting.

Validation: None

Destination: RA_CUSTOMER_TRX_LINES_ALL.VAT_TAX_ID

WAREHOUSE ID

This column identifies the ship-from location and can be used to control taxation. Within the US, the Warehouse ID is important when calculating tax on the Origin/Modified Origin state sales tax (outside the US, you can use Tax Groups and Conditions to build a schedule of multiple conditional taxes based on both the shipfrom and ship-to County/County/State or Provinces).

Validation None

WAYBILL NUMBER

Enter the waybill number for this transaction.

If LINE TYPE = 'LINE', 'CHARGES', or you are passing header freight, this column is optional.

If LINE TYPE = 'TAX' or you are passing freight for a specific line do not enter a value in this column.

For credit memos do not enter a value in this column. AutoInvoice uses the waybill number from the transaction you are crediting.

Validation: None

Destination: RA CUSTOMER TRX ALL.WAYBILL NUMBER

Table Name: RA INTERFACE SALESCREDITS ALL

This table stores sales credit information for your transactions. This table must be populated if your AutoAccounting is set up to derive segment values based on the salesrep. If AutoAccounting does not depend on salesrep, then the value you enter in the Require Salesrep field of the System Options window and Allow Sales Credits field in the Transaction Sources window will determine whether you must enter sales credit information. See: AutoAccounting, Oracle Receivables Implementation Guide and Defining Receivables System Options, Oracle Receivables Implementation Guide.

If you are importing invoices, debit memos and on-account credits and your system option requires a salesperson, you must provide sales credit information, regardless of the value entered in the Allow Sales Credit field for your transaction batch source.

If you are importing credit memos and your system option requires that you enter a salesperson, you can provide sales credit information. If you do not provide sales credit information, AutoInvoice uses sales credit information from the invoice you are crediting. If the invoice you are crediting does not have sales credit information, AutoInvoice creates a 100% 'No Sales Credit' line for this invoice. This sales credit line is then used to determine the sales credit amount for the credit memo.

Regardless of the type of transaction you are importing, if your system option does not require salesperson, but your transaction batch source allows sales credits, you can provide sales credit information. AutoInvoice will validate it and pass this information with your transaction. If your system option does not require salesperson and your transaction batch source does not allow sales credits, do not provide sales credit information. AutoInvoice ignores any values that you pass.

ATTRIBUTE1-15

Enter the Descriptive Flexfield attribute information for this sales or revenue credit

assignment. Descriptive Flexfield attributes allow you to store additional columns, the contents of which you define. These columns are optional.

Validation: None

Destination: RA_CUST_TRX_LINES_SALESREPS_ALL.ATTRIBUTE1-

15

ATTRIBUTE CATEGORY

Enter the Descriptive Flexfield category information for this sales credit assignment. Descriptive Flexfield categories allow you to store different categories of attributes. This column is optional.

Validation: None

Destination: RA_CUST_TRX_LINE_SALESREPS_ALL.

ATTRIBUTE CATEGORY

INTERFACE LINE ATTRIBUTE1-15

Enter the same Transaction Flexfield for the transaction with which you want to associate this sales or revenue credit assignment. The values you enter here provide you with an audit trail from Receivables back to your original system. You must enter a value for each attribute you enabled.

INTERFACE LINE CONTEXT

Enter the context name of the Transaction Flexfield data that you entered in RA_INTERFACE_SALESCREDITS_ALL.INTERFACE_LINE_ATTRIBUTE1-15. You must enter a value in this column.

Validation: None

Destination: None

INTERFACE LINE ID

This column is used by AutoInvoice and should be left null. AutoInvoice defaults a value into this column using RA_INTERFACE_SALESCREDITS_ALL. INTERFACE_LINE_ATTRIBUTE1-15.

Validation: None

Destination: RA_CUST_TRX_LINE_SALESREPS_ALL.

CUSTOMER_TRX_LINE_ID

INTERFACE SALESCREDIT ID

This column is used by AutoInvoice and should be left null. AutoInvoice defaults a value into this column using the sequence RA_CUST_TRX_LINE_SALESREPS_S.

Validation: None

Destination: RA_CUST_TRX_LINE_SALESREPS_ALL.

CUST_TRX_LINE_SALESREP_ID

INTERFACE STATUS

This column is used by AutoInvoice and should be left null.

None Validation:

None Destination:

LAST_UPDATE_LOGIN

This column is used by AutoInvoice and should be left null. AutoInvoice updates this column when it selects rows from the RA_INTERFACE_SALESCREDITS_ALL table for processing.

Validation: None

None Destination:

ORG ID

Enter the ID of the organization that this transaction belongs to. This column is mandatory in a multiple organization environment.

Validation: AutoInvoice imports transactions whose ORG_ID matches

the value of the MO: Operating Unit profile option.

Destination: None.

REQUEST_ID

This column is used by AutoInvoice and should be left null.

Validation: None

Destination: None

SALES CREDIT AMOUNT SPLIT

Enter the sales credit amount for this salesperson. This column is optional. Depending

on the value you entered for your batch source you must enter either a value in this column or in SALES_CREDIT_PERCENT_SPLIT. If you specify the sales credit percent in your batch source, AutoInvoice defaults a value in this column.

Validation: If the sales credit for this sales credit assignment is of type

Quota, the sum of sales credit amounts for a transaction

must equal the amount of the transaction.

Destination: RA_CUST_TRX_LINE_SALESREPS_ALL.

> REVENUE_AMOUNT_SPLIT if the sales credit type is Quota. RA CUST TRX LINE SALESREPS ALL.

NON_REVENUE_AMOUNT_SPLIT if the sales credit type

is not Quota.

SALES CREDIT PERCENT SPLIT

Enter the sales credit percent for this salesperson. This column is optional. Depending on the value you entered for your batch source you must enter either a value in this column or in SALES CREDIT AMOUNT SPLIT. If you specify the sales or revenue credit amount in your batch source, AutoInvoice defaults a value in this column.

Validation: Your sales or revenue credit percent must be between 0 and

> 100, and if sales credit type is Quota, the sales credit percentage for a transaction must sum to 100.

SALES CREDIT TYPE ID

Enter the ID of the sales credit type for this sales credit assignment. This column is optional. Depending on the value you entered for your batch source you must enter either a value in this column or in SALES CREDIT TYPE NAME. If you specify the sales credit type name in your batch source, AutoInvoice defaults a value in this column.

Validation: Must exist in SO_SALES_CREDIT_TYPES.

SALES_CREDIT_TYPE_ID

Destination: None

SALES CREDIT TYPE NAME

Enter the name of the sales credit type for this sales credit assignment. This column is optional. Depending on the value you entered for your batch source you must enter either a value in this column or in SALES_CREDIT_TYPE_ID.

Validation: Must exist in SO SALES CREDIT TYPES.NAME

Destination: None

SALES GROUP ID

Enter the sales group ID for this sales credit assignment. This column is optional.

Validation: Must exist in JTF RS GROUP USAGES.GROUP ID and

have JTF_RS_GROUP_USAGES.USAGE = 'SALES'

Destination: RA CUST TRX LINE SALESREPS ALL.

REVENUE SALESGROUP ID or

RA CUST TRX LINE SALESREPS ALL. NON_REVENUE_SALESGROUP_ID

SALESREP ID

Enter the salesperson ID for this sales credit assignment. This column is optional. Depending on the value you entered for your batch source you must enter either a value in this column or in SALESREP_NUMBER. If you specify the salesperson number in your batch source, AutoInvoice defaults a value in this column.

Validation: Must exist in RA_SALESREPS.SALESREP_ID

RA_CUST_TRX_LINE_SALESREPS_ALL.SALESREP_ID Destination:

SALESREP NUMBER

Enter the salesperson number for this sales credit assignment. This column is optional. Depending on the value you entered for your batch source you must enter either a value in this column or in SALESREP_ID.

Validation: Must exist in RA_SALESREPS.SALESREP_NUMBER

Destination: None

Table Name: RA INTERFACE DISTRIBUTIONS ALL

If you do not use AutoAccounting, you must enter accounting distributions for your transactions. Otherwise, AutoInvoice does not require you to enter accounting distributions for your transactions.

If your accounting distributions are for transactions that use accounting rules, you must enter the percentages, but not the amounts. If you enter the amounts, AutoInvoice will ignore those values.

If your accounting distributions are for transactions that do not use accounting rules, you can enter either the percentages or amounts, depending on the value you entered for your batch source. If you enter an amount, AutoInvoice requires that the distribution amounts sum to the amount of the transaction. If you enter a percent, AutoInvoice requires that the distribution percentages sum to 100 for each account class that you pass.

Distributions in this table are linked to the appropriate transaction lines in the ra_interface_lines via the transaction flexfield. Though the distribution for 'REC' account class is at the invoice level, it may be linked to any transaction line of the invoice in ra interface lines. AutoInvoice will then correctly transfer all distributions to RA_CUST_TRX_LINE_GL_DIST_ALL.

ACCOUNT_CLASS

Enter the account class for this accounting distribution. AutoInvoice uses the account class you enter here to determine the type of account you are supplying for this accounting distribution. You must enter a value for this column.

Must be either 'REV', 'FREIGHT', 'TAX', 'REC', 'CHARGES', Validation:

'UNBILL', or 'UNEARN'. If the transaction uses the

'Advance Invoice' invoicing rule, do not enter 'UNBILL' in this column. If the transaction uses the 'Arrears Invoice' invoicing rule, do not enter 'UNEARN' in this column.

RA_CUST_TRX_LINE_GL_DIST_ALL.ACCOUNT_CLASS Destination:

ACCTD_AMOUNT

This column is optional. If you enter 'AMOUNT' for your batch source option 'Revenue Account Allocation', then AutoInvoice will accept whatever is passed in this column without validation. If this column is null, then AutoInvoice will compute the accounted amount for this distribution line. For imported amounts in the functional currency, AutoInvoice will reject the line if you enter a value in the ACCTD_AMOUNT column that does not equal the line amount.

Validation: None

Destination: None

AMOUNT

Enter the amount for this accounting distribution.

If this accounting distribution is for a transaction that does not use an accounting rule and depending on the value you entered for your batch source, you must enter either a value in this column or in PERCENT. If you specify the percent in your batch source, AutoInvoice computes the value in this column.

Do not enter a value in this column if this accounting distribution is for a transaction which uses an accounting rule or if this distribution is a receivables ('REC') account. If this distribution is for a receivables account, you must enter 100 in RA INTERFACE DISTRIBUTIONS ALL.PERCENT.

If this line has AMOUNT INCLUDES TAX set to Yes, the sales credits and line

amounts for this column must include tax.

Validation: If this transaction does not use an accounting rule, the sum

> of all distribution amounts for this transaction of a given line type must equal the amount for the transaction.

AutoInvoice corrects amounts that have incorrect currency

precision.

RA_CUST_TRX_LINE_GL_DIST_ALL.AMOUNT Destination:

ATTRIBUTE1-15

Enter the Descriptive Flexfield attribute information for this accounting distribution. Descriptive Flexfield attributes allow you to store additional columns, the contents of which you define. These columns are optional.

Validation: None

Destination: RA CUST TRX LINE GL DIST ALL.ATTRIBUTE1-15

ATTRIBUTE CATEGORY

Enter the Descriptive Flexfield category information for this accounting distribution. Descriptive Flexfield categories allow you to store different categories of attributes. This column is optional.

Validation: None

Destination: RA_CUST_TRX_LINE_GL_DIST_ALL.

ATTRIBUTE CATEGORY

CODE COMBINATION ID

Enter the code combination ID of the Accounting Flexfield for this accounting distribution.

This column is optional. Depending on the value you entered for your batch source you must enter either a value in this column or a combination of segment values in SEGMENT1-30. If you specify the combination of segment values in your batch source, AutoInvoice defaults a value in this column.

Validation: Must exist in GL CODE COMBINATIONS.

CODE COMBINATION ID

Destination: RA CUST TRX LINE GL DIST ALL.

COLLECTED_TAX_CCID if tax is deferred; otherwise,

RA CUST TRX LINE GL DIST ALL.

CODE COMBINATION ID

COMMENTS

Enter comments about this accounting distribution. This column is optional.

Validation: None

Destination: RA CUST TRX LINE GL DIST ALL.COMMENTS

INTERFACE DISTRIBUTION ID

This column is used by AutoInvoice and should be left null. AutoInvoice defaults a value into this column using the sequence RA_CUST_TRX_LINE_GL_DIST_S. This is the primary key for RA_INTERFACE_DISTRIBUTIONS_ALL.

Validation: None

Destination: RA CUST TRX LINE GL DIST ALL.

CUST_TRX_LINE_GL_DIST_ID

INTERFACE LINE ATTRIBUTE1-15

Enter the same Line Transaction Flexfield for the transaction with which you want to associate this accounting distribution. You must enter a value for each attribute you enabled for the Line Transaction Flexfield.

Validation: None

Destination: None

INTERFACE LINE CONTEXT

This is a required column in AutoInvoice. Enter the context of the Line Transaction Flexfield entered in columns INTERFACE_LINE_ATTRIBUTE1-15.

If you pass lines with global context set this column to Validation:

'Global Data Elements'

Destination: RA CUSTOMER TRX LINES ALL.

INTERFACE_LINE_CONTEXT

INTERFACE LINE ID

This column is used by AutoInvoice and should be left null. AutoInvoice defaults a value into this column using INTERFACE_LINE_ATTRIBUTE1-15 and INTERFACE_LINE_CONTEXT.

Validation: None Destination: RA_CUST_TRX_LINE_GL_DIST_ALL.

CUSTOMER_TRX_LINE_ID

INTERFACE STATUS

This column is used by AutoInvoice and should be left null.

Validation: None

Destination: None

INTERIM TAX CCID

This column identifies the tax account used for deferred tax amounts.

None Validation:

RA_CUST_TRX_LINE_GL_DIST_ALL. Destination:

CODE_COMBINATION_ID

INTERIM TAX SEGMENT1-30

Enter an Accounting Flexfield value for each segment you enable in Receivables. This flexfield represents the Interim (deferred) tax account. For example, if you enable six Accounting Flexfield segments, you must enter six values in columns SEGMENT1-6. Be sure to enter the correct segment value. For example, the value '01' is not the same as '1'.

Depending on the value you entered for your batch source, you must enter either a combination of segment values in these columns or a value in CODE_COMBINATION_ID.

Validation: Valid combination of Accounting Flexfield segment values

must exist in GL_CODE_COMBINATIONS.

Destination: None

LAST_UPDATE_LOGIN

This column is used by AutoInvoice and should be left null. AutoInvoice updates this column when it selects rows from the RA_INTERFACE_DISTRIBUTIONS_ALL table for processing.

Validation: None

Destination: None

ORG_ID

Enter the ID of the organization that this transaction belongs to. This column is

mandatory in a multiple organization environment.

Validation: AutoInvoice imports transactions whose ORG_ID matches

the value of the MO: Operating Unit profile option.

Destination: None.

PERCENT

Enter the percent for this accounting distribution.

If this accounting distribution is for a transaction that does not use an accounting rule and depending on the value you entered for your batch source, you must enter either a value in this column or in AMOUNT. If you specify the amount in your batch source, AutoInvoice defaults a value in this column.

If this accounting distribution is for a transaction which uses an accounting rule, you must enter a value in this column.

Validation: The sum of all accounting distribution percentages for a

transaction must sum to 100 for an account class.

Destination: RA CUST_TRX_LINE GL_DIST_ALL.PERCENT

REQUEST ID

This column is used by AutoInvoice and should be left null.

Validation: None

Destination: None

SEGMENT1-30

Enter an Accounting Flexfield value to each segment you enable in Receivables. For example, if you enable six Accounting Flexfield segments, you must enter six values in columns SEGMENT1-6. Be sure to enter the correct segment value. For example, the value '01' is not the same as '1'.

Depending on the value you entered for your batch source, you must enter either a combination of segment values in these columns or a value in CODE_COMBINATION_ID.

Validation: Valid combination of Accounting Flexfield segment values

must exist in GL_CODE_COMBINATIONS.

Destination: None

Table Name: AR_INTERFACE_CONTS_ALL

This table stores information about contingencies that impact revenue recognition for your imported transactions.

See: Event-Based Revenue Management, Oracle Receivables User Guide.

CONTINGENCY_ID

Identifies the revenue contingency, according to this table:

Contingency Name	Contingency ID
Explicit Acceptance	2
Customer Creditworthiness	3
Doubtful Collectibility	4
Extended Payment Term	5
Cancellation	7
Fiscal Funding Clause	8
Refund	9
Forfeitures	10
Leasing Doubtful Collectibility	12
Impaired Loans	13

Validation:	None.
vanuation:	none.

Destination: AR_LINE_CONTS_ALL.CONTINGENCY_ID

EXPIRATION_DATE

Indicates expiration date of contingency. For time-based contingencies, enter either expiration date or expiration days.

Validation: None. Destination: AR_LINE_CONTS_ALL.CONTINGENCY_CODE

EXPIRATION DAYS

Indicates expiration period of contingency. For time-based contingencies, enter either expiration date or expiration days.

Validation: None.

AR_LINE_CONTS_ALL.CONTINGENCY_CODE Destination:

EXPIRATION EVENT DATE

Indicates the expiration of the contingency removal event.

Validation: None.

Destination: AR_LINE_CONTS_ALL.EXPIRATION_EVENT_DATE

INTERFACE_CONTINGENCY_ID

Contingency identifier.

Validation: None

Destination: None

ORG ID

Enter the ID of the organization that this transaction belongs to. This column is mandatory in a multiple organization environment.

Validation: AutoInvoice imports transactions whose ORG_ID matches

the value of the MO: Operating Unit profile option.

Destination: None.

PARENT LINE ID

Identifies the original parent order line from Oracle Order Management. Child invoice lines inherit contingencies from the parent line, and cannot be updated.

Validation: None

Destination: None

Table Name: RA INTERFACE ERRORS ALL

This table stores information about interface lines that failed validation and were not imported into Receivables tables. Receivables uses the information in this table to generate the AutoInvoice Validation Report, Oracle Receivables User Guide. AutoInvoice identifies all errors for each transaction line, thus reducing multiple validation and correction cycles. When you resubmit AutoInvoice, the program deletes the errors for each line selected for processing. When all of the records have been successfully processed, AutoInvoice purges any remaining data in this table.

Use the Interface Exceptions window to view all of the errors in RA INTERFACE ERRORS ALL. For more information, see: Correcting AutoInvoice Exceptions, Oracle Receivables User Guide.

INTERFACE LINE ID

If both INTERFACE_SALESCREDIT_ID and INTERFACE_DISTRIBUTION_ID are null, then the row in RA INTERFACE LINES ALL associated with this INTERFACE_LINE_ID failed validation.

Validation: None

Destination: None

INTERFACE SALESCREDIT ID

If this column is not null, then the row in RA INTERFACE SALESCREDITS ALL associated with this INTERFACE_SALESCREDIT_ID failed validation.

Validation: None

Destination: None

INTERFACE DISTRIBUTION ID

If this column is not null, then the row in RA_INTERFACE_DISTRIBUTIONS_ALL associated with this INTERFACE_DISTRIBUTION_ID failed validation.

Validation: None

Destination: None

INVALID_VALUE

The invalid value that failed validation displays in this column, if applicable.

Validation: None

Destination:	None
--------------	------

LINK_TO_LINE_ID

This column displays the INTERFACE_LINE_ID of the line to which this line that failed validation is linked. For example, you have a tax line that fails and is linked to an invoice line that fails. In this case, the column stores the INTERFACE_LINE_ID of the invoice line.

Validation: None

Destination: None

MESSAGE TEXT

The message text is stored in this column.

Validation: None

Destination: None

Related Topics

Importing Transactions Using AutoInvoice, Oracle Receivables User Guide

Using AutoInvoice, Oracle Receivables User Guide

Lockbox Table and Column Descriptions

When you submit the Import, Validation, and Post Batch steps of AutoLockbox, Receivables stores receipt information in temporary application tables until it is approved for the next step. For example, the Validation step checks data in the AutoLockbox tables for compatibility with Receivables before passing the information into the Receipt and QuickCash tables. The following sections describe these tables.

Related Topics

Receipt and QuickCash Tables, page B-62

Lockbox Interface Table and Column Descriptions, page B-63

Running AutoLockbox, Oracle Receivables User Guide

Receipt and QuickCash Tables

When you run the Validation step, Lockbox transfers receipt data into the following OuickCash tables:

AR_INTERIM_CASH_RECEIPTS_ALL

AR_INTERIM_CASH_RCPT_LINES_ALL

When you run Post QuickCash, the receipt data is transferred from the QuickCash tables to the following Receipt tables:

AR_CASH_RECEIPTS_ALL

AR_RECEIVABLES_APPLICATIONS_ALL

AR_CASH_RECEIPT_HISTORY_ALL

Related Topics

Lockbox Interface Table and Column Descriptions, page B-63

Lockbox Interface Table and Column Descriptions

When you run the Import step of AutoLockbox, Receivables stores receipt data from your bank file in the AR_PAYMENTS_INTERFACE_ALL Lockbox Interface table. Following is a detailed description of this table.

Each column in the AR_PAYMENTS_INTERFACE_ALL table has important, detailed information you need to successfully run AutoLockbox. The Destination column gives you the interim QuickCash tables and the actual Receivables applications tables to which the data is transferred from the AR PAYMENTS INTERFACE ALL table.

Understanding the AR PAYMENTS INTERFACE ALL Table

This section lists the columns in the AR_PAYMENTS_INTERFACE_ALL table, providing each column's type, source, and destination.

TRANSMISSION_RECORD_ID (NUMBER(15))

- Source AR_PAYMENTS_INTERFACE_S.NEXTVAL
- Destination None

CREATION DATE (DATE)

- Source CURRENT SYSTEM DATE
- Destination None

CREATED_BY (NUMBER(15))

- Source FND_USER.USER_ID
- Destination -

AR BATCHES.CREATED BY

AR_INTERIM_CASH_RECEIPTS.CREATED_BY

AR_INTERIM_CASH_RECEIPT_LINES.CREATED_BY

LAST_UPDATE_LOGIN (NUMBER(15))

- Source UNKNOWN
- Destination None

LAST_UPDATED_BY (NUMBER(15))

- Source FND_USER.USER_ID
- Destination None

LAST_UPDATE_DATE (DATE)

- Source CURRENT SYSTEM DATE
- None

RECORD_TYPE (NOT NULL) (VARCHAR2(2))

- Source AR_TRANS_RECORD_FORMATS.RECORD_IDENTIFIER
- None

STATUS (VARCHAR2(30))

- Source FND_MESSAGES.MESSAGE_NAME
- Destination None

TRANSMISSION_REQUEST_ID (NUMBER(15))

- Source FND_CONCURRENT_REQUESTS.REQUEST_ID
- Destination None

TRANSMISSION_ID (NUMBER(15))

- Source AR_TRANSMISSIONS.TRANSMISSION_ID
- Destination None

DESTINATION_ACCOUNT (VARCHAR2(25))

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination AR_TRANSMISSIONS.DESTINATION

ORIGINATION (VARCHAR2(25))

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination AR TRANSMISSIONS.ORIGIN

DESPOSIT_DATE (DATE)

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination AR_BATCHES.DEPOSIT_DATE

GL DATE (DATE)

- Source DERIVED FROM DEPOSIT DATE, IMPORT DATE OR ENTERED DATE
- Destination -

AR_BATCHES.GL_DATE

AR_INTERIM_CASH_RECEIPTS.GL_DATE

AR_CASH_RECEIPT_HISTORY.GL_DATE

DEPOSIT_TIME (VARCHAR2(8))

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination None

TRANSMISSION_RECORD_COUNT (NUMBER(15))

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination AR_TRANSMISSIONS.COUNT

TRANSMISSION_AMOUNT (NUMBER)

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination AR_TRANSMISSIONS.AMOUNT

TRANSFERRED_RECEIPT_COUNT (NUMBER)

- Source PROGRAM COUNTS NUMBER OF RECORDS TRANSFERRED SUCCESSFULLY
- Destination AR_TRANSMISSIONS.VALIDATED_COUNT

TRANSFERRED_RECEIPT_AMOUNT (NUMBER)

- Source PROGRAM COUNTS RECEIPT AMOUNTS OF RECORDS TRANSFERRED SUCCESSFULLY
- Destination AR_TRANSMISSIONS.VALIDATED_AMOUNT

LOCKBOX_NUMBER (VARCHAR2(30))

- Source PROVIDED BY BANK OR ENTERED BY USER AT RUNTIME
- Destination None

LOCKBOX_BATCH_COUNT (NUMBER)

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination None

LOCKBOX RECORD COUNT (NUMBER)

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination None

LOCKBOX_AMOUNT (NUMBER)

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination None

BATCH_NAME (VARCHAR2(25))

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN' LOCKBOX TRANSMISSION DATA'
- Destination AR_BATCHES.LOCKBOX_BATCH_NAME

BATCH_AMOUNT (NUMBER)

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination AR_BATCHES.CONTROL_AMOUNT

BATCH_RECORD_COUNT (NUMBER(15))

 Source - LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'

Destination - AR_BATCHES.CONTROL_COUNT

ITEM_NUMBER (NUMBER)

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination None

CURRENCY_CODE (VARCHAR2(15))

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination -

AR_BATCHES.CURRENCY_CODE

AR_INTERIM_CASH_RECEIPTS.CURRENCY_CODE

EXCHANGE RATE (NUMBER)

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination -

AR_BATCHES.EXCHANGE_RATE

AR_INTERIM_CASH_RECEIPTS.EXCHANGE_RATE

EXCHANGE_RATE_TYPE (VARCHAR2(30))

- Source DEFAULTS FROM LOCKBOX DEFINITIONS OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination -

AR BATCHES.EXCHANGE RATE TYPE

AR_INTERIM_CASH_RECEIPTS.EXCHANGE_RATE_TYPE

REMITTANCE AMOUNT (NUMBER)

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination AR_INTERIM_CASH_RECEIPTS.AMOUNT

TRANSIT_ROUTING_NUMBER (VARCHAR2(25))

• Source - LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'

Destination -

AP_BANK_BRANCHES.BANK_NAME AP_BANK_BRANCHES.BANK_BRANCH_NAME AP_BANK_BRANCHES.BANK_NUM

ACCOUNT (VARCHAR2(30))

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination AP BANK ACCOUNTS.BANK ACCOUNT NUM

CUSTOMER_BANK_ACCOUNT_ID (NUMBER(15))

- Source AP_BANK_ACCOUNT_USES.EXTERNAL_BANK_ACCOUNT_ID
- Destination AR_INTERIM_CASH_RECEIPTS. CUSTOMER_BANK_ACCOUNT_ID

ANTICIPATED CLEARING DATE (DATE)

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination AR_INTERIM_CASH_RECEIPTS.ANTICIPATED_CLEARING_DATE

CHECK NUMBER (VARCHAR2(30))

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination -

AR_INTERIM_CASH_RECEIPTS.RECEIPT_NUMBER AR_CASH_RECEIPTS.RECEIPT_NUMBER

SPECIAL TYPE (VARCHAR2(20))

- Source PROGRAM DETERMINES THE TYPE
- Destination AR_INTERIM_CASH_RECEIPTS.SPECIAL_TYPE

CUSTOMER_NUMBER (VARCHAR2(30))

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination None

OVERFLOW_INDICATOR (VARCHAR2(1))

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination None

OVERFLOW_SEQUENCE (NUMBER)

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination None

CUSTOMER ID (NUMBER (15))

- Source PROGRAM DETERMINES IT
- Destination -

```
AR_INTERIM_CASH_RECEIPTS.PAY_FROM_CUSTOMER
AR_CASH_RECEIPTS.PAY_FROM_CUSTOMER
```

BILL_TO_LOCATION (VARCHAR2(40))

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination None

CUSTOMER_SITE_USE_ID (NUMBER(15))

- Source PROGRAM DETERMINES IT
- Destination -

```
AR_INTERIM_CASH_RECEIPTS.SITE_USE_ID
AR_CASH_RECEIPTS.CUSTOMER_SITE_USE_ID
```

RECEIPT DATE (DATE)

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination -

```
AR_INTERIM_CASH_RECEIPTS.RECEIPT_DATE
AR_INTERIM_CASH_RECEIPTS.EXCHANGE_DATE
AR_CASH_RECEIPTS.RECEIPT_DATE
AR_CASH_RECEIPTS.EXCHANGE_DATE
```

RECEIPT_METHOD (VARCHAR2(30))

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination None

RECEIPT_METHOD_ID (NUMBER(15))

- Source PROGRAM DETERMINES IT.
- Destination -

AR_INTERIM_CASH_RECEIPTS.RECEIPT_METHOD_ID AR_CASH_RECEIPTS.RECEIPT_METHOD_ID

INVOICE1-8 (VARCHAR2(50))

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination None

MATCHING1_DATE - MATCHING8_DATE (DATE)

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination None

RESOLVED_MATCHING_NUMBER1-8 (NUMBER)

- Source PROGRAM DETERMINES IT
- Destination None

RESOLVED_MATCHING1_DATE - RESOLVED_MATCHING8_DATE (DATE)

- Source PROGRAM DETERMINES IT
- Destination None

MATCH RESOLVED USING (VARCHAR2(30))

- Source PROGRAM DETERMINES IT
- Destination None

RESOLVED_MATCHING1_INSTALLMENT - RESOLVED_ MATCHING8 INSTALLMENT (NUMBER)

• Source - PROGRAM DETERMINES IT

Destination - None

INVOICE1_STATUS - INVOICE8_STATUS (VARCHAR2(30))

- Source PROGRAM DETERMINES IT
- Destination None

COMMENTS (NUMBER)

- Source ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination -

AR_BATCHES.COMMENTS

AR_INTERIM_CASH_RECEIPTS.COMMENTS

ATTRIBUTE_CATEGORY (VARCHAR2(30))

ATTRIBUTE1-15 (CHAR(40))

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination -

AR_INTERIM_CASH_RECEIPTS.ATTRIBUTE1...15

AR_CASH_RECEIPTS.ATTRIBUTE1...15

INVOICE1_INSTALLMENT - INVOICE8_INSTALLMENT (NUMBER)

- Source LOCKBOX DATA FILE OR ENTERED BY USER VIA 'MAINTAIN LOCKBOX TRANSMISSION DATA'
- Destination None

CUSTOMER_NAME_ALT (VARCHAR2(320))

- Source LOCKBOX DATA FILE
- Destination None

CUSTOMER BANK NAME (VARCHAR2(320))

- Source LOCKBOX DATA FILE
- Destination None

CUSTOMER_BANK_BRANCH_NAME (VARCHAR2(320))

• Source - LOCKBOX DATA FILE

Destination - None

REMITTANCE_BANK_NAME (VARCHAR2(320))

- Source PROGRAM DETERMINES IT
- Destination None

REMITTANCE_BANK_BRANCH_NAME (VARCHAR2(320))

- Source PROGRAM DETERMINES IT
- Destination None

BANK_TRX_CODE (VARCHAR2(30))

- Source PROGRAM DETERMINES IT
- Destination None

AMOUNT_APPLIED1-8 (NUMBER)

- Source LOCKBOX DATA FILE OR DERIVED FROM AMOUNT_APPLIED_FROM AND EXCHANGE_RATE
- Destination -

AR_INTERIM_CASH_RECEIPTS_ALL.AMOUNT_APPLIED (if a single application)

AR_INTERIM_CASH_RCPT_LINES_ALL.PAYMENT_AMOUNT (if multiple applications)

AMOUNT_APPLIED_FROM1-8 (NUMBER)

- Source LOCKBOX DATA FILE OR DERIVED FROM AMOUNT_APPLIED_FROM AND EXCHANGE_RATE
- Destination -

AR_INTERIM_CASH_RECEIPTS_ALL.AMOUNT (if a single application)

AR_INTERIM_CASH_RCPT_LINES_ALL.AMOUNT_APPLIED_FROM (if multiple applications)

INVOICE_CURRENCY_CODE1-8 (VARCHAR2(15))

- Source LOCKBOX DATA FILE OR DERIVED FROM AR_PAYMENT_SCHEDULES_ALL
- · Destination -

AR_INTERIM_CASH_RECEIPTS_ALL.INVOICE_CURRENCY_CODE (if a single

application)

AR_INTERIM_CASH_RCPT_LINES_ALL.INVOICE_CURRENCY_CODE (if multiple applications)

TRANS_TO_RECEIPT_RATE1-8 (NUMBER)

- Source LOCKBOX DATA FILE OR DERIVED FROM AMOUNT_APPLIED_FROM AND EXCHANGE_RATE
- Destination TRANS_TO_RECEIPT_RATE

CUSTOMER REFERENCE 1-8 (VARCHAR2(100))

- Source -
- Destination -

CUSTOMER_REASON1-8 (VARCHAR2(30))

- Source -
- Destination -

Assigning Values to Columns

You must assign values to all of the following columns in the AR_PAYMENTS_INTERFACE_ALL table for AutoLockbox to successfully convert data into receipts.

STATUS Enter the value AR_PLB_NEW_RECORD for all records

inserted into this table. The sample SQL*Loader control files Receivables provides fill this column in for you.

DEPOSIT DATE Enter the date on which this transmission was actually

> deposited into your bank account. This date can be on any of the record types in your transmission. Each unique deposit date determines a batch of transmission records. For example, if you enter two unique deposit dates for your transmission, AutoLockbox divides your transmission

into two batches of receipts.

RECORD_TYPE Identify your record type. For example, if this is a batch

> header record, and your bank uses the value 3 to identify batch headers, enter 3 in this column. Find out from your bank what character they use to identify each one. Keep in mind that not all banks use all of the record types. Assign

values to identify the following types of records:

TRANSMISSION HEADER

TRANSMISSION TRAILER

LOCKBOX HEADERS

LOCKBOX TRAILERS

BATCH HEADERS

BATCH TRAILERS

PAYMENT RECORDS

PAYMENT OVERFLOW RECORDS

SERVICE HEADER

Receivables lets you determine what information you want to include in you header, trailer, and receipt records. You can reference any of the above types when you define the different records for your transmission format. Below are examples of how you might want to define these.

Assigning Values to Transmission Header and Trailer Records

If your record type is either a Transmission Header or a Transmission Trailer, then enter the following columns with the values you described. Transmission Headers and Trailers mark the beginning and ends of a specific data file. They usually contain information such as destination account, origination number, deposit date, and deposit time. You may have a Transmission Header without a Transmission Trailer, AutoLockbox does not require that you specify either of these record types in your transmission format. For each transmission you can only have one transmission header and one transmission trailer.

TRANSMISSION	RECORD	CO
UNT		

Enter the number of records that you are importing. Include all of the types of records in the count: headers, trailers, receipts and overflow records. If the transmission format includes the transmission header or trailer, Lockbox counts all records in this transmission. The validated count includes all receipts and detail records transferred to the interim table.

TRANSMISSION AMOUNT Enter the amount of the transmission. This is the sum of all

of the receipt amounts within the transmission.

Enter your account number at the sending bank. DESTINATION_ACCOUNT

ORIGINATION Enter the sending bank's transit routing number.

DEPOSIT DATE Enter the date this transmission was actually deposited in

> your bank account. When you use SQL*Loader to import your data, it converts the date to the Oracle date format.

Assigning Values to Lockbox Header or Trailer Records

If your record type is either a Lockbox Header or a Lockbox Trailer, enter the following columns with the values described. Lockbox Headers usually mark the beginning of a specific lockbox and contain information such as the destination account and origination number. Lockbox Trailers mark the end of specific lockboxes and contain information such as lockbox number, deposit date, lockbox amount and lockbox record count. Although you may have a Lockbox Header without a Lockbox Trailer, AutoLockbox does not require that you specify either of these record types in your transmission format.

LOCKBOX NUMBER Enter the lockbox name or number that your bank

> specifies. This is the same value that you entered in the Lockboxes window. LOCKBOX_NUMBER is mandatory

on all Lockbox Headers and Trailers.

Enter the number of batches in this lockbox. LOCKBOX_BATCH_COUNT

LOCKBOX RECORD COUNT Enter the number of Payment records in this lockbox. Do

not include Payment Overflow records.

LOCKBOX_AMOUNT Enter the total value of the receipts in this lockbox.

DESTINATION_ACCOUNT Enter your account number at the sending bank. If this

value is included in a Transmission Header or Trailer, you

must enter the same value.

ORIGINATION Enter the sending bank's transit routing number. If this

value is included in a Transmission Header or Trailer, you

must have the same value here.

Assigning Values to Batch Header and Trailer Records

If your record type is either a Batch Header or a Batch Trailer, you can enter the following columns with the values described below. Batch Headers mark the beginning of a specific batch and contain information such as batch number, deposit date, and lockbox number. Batch Trailers mark the end of a specific batch and contain information such as batch number, lockbox number, batch record amount, and batch amount. Although you may have a Batch Header without a Batch Trailer, AutoLockbox does not require that you specify either of these record types in your transmission format.

BATCH NAME Enter the name or number that the bank uses to identify the

batch. This is required for each Batch Header and Trailer

record.

BATCH AMOUNT Enter the total value of all receipts in this batch.

BATCH_RECORD_COUNT Enter the number of receipt records in this batch.

LOCKBOX_NUMBER Enter the lockbox number assigned to receipts in this batch.

If the lockbox number is included in your format, it must

appear on every batch record.

COMMENTS Enter any free-form comments about this batch.

Assigning Values to Receipt Records

If your record type is a Payment, you can enter the following columns with the values described below. A Payment record usually contains information such as MICR number, batch number, item number, check number, and remittance amount. Some of the values are mandatory for a Payment record, while others are optional. Every transmission must have Payment records.

LOCKBOX NUMBER Enter the lockbox number assigned to your receipts. If the

> lockbox number is included in your format and you do not have batch records, it must be entered for every receipt

record.

BATCH NAME Enter the batch name for this receipt. If batch name is

> included in your format, it must be entered for every receipt record. Each unique batch name determines a batch of transmission records. For example, if you enter two unique batch names for your transmission, AutoLockbox divides your transmission into two batches of receipts.

ITEM NUMBER Enter a sequential number to indicate the location of this

> receipt in this batch. You must enter a value even if your format does not have batch, lockbox, or transmission records. Item Number must be unique within a batch, a lockbox (if batches are not provided), or within a transmission (if neither batches nor lockboxes are

provided).

REMITTANCE_AMOUNT Enter the value of the receipt. You must enter a value for

each receipt record.

Enter the currency code for each receipt. Receivables CURRENCY_CODE

supports AutoLockbox Transmission receipts in different

currencies.

EXCHANGE RATE Enter the exchange rate you want Receivables to use for

this currency.

Enter the type of exchange rate you are using for this **EXCHANGE RATE TYPE**

receipt. You can enter Corporate, Spot, or User.

RECEIPT DATE Enter the date that is written on your check. If you are

> using MICR numbers to identify customers, Lockbox requires that this date be equal to or earlier than the date of this AutoLockbox submission; otherwise, the receipts will

be unidentified.

RECEIPT_METHOD Enter the receipt method that you want to associate with

> this receipt. Receipt methods contain information about your bank, bank account, and receipt accounts. This receipt method must be the same as the one you assigned to the

batch source for this lockbox.

CHECK NUMBER Enter the number printed on the receipt. You must enter a

value for each receipt record.

TRANSIT ROUTING NUMBER Enter the transit routing number from the receipt. This is

> optional, but you must enter this number if you enter the account number. Receivables uses transit routing number and account number together to identify the customer

(MICR number).

ACCOUNT Enter the bank account number from the receipt. This is

optional, but you must enter this number if you enter the

transit routing number.

CUSTOMER NUMBER Enter the number assigned to your customer. This is

optional.

INVOICE1-8 Enter the invoice numbers to which you apply this receipt.

> You do not have to start with INVOICE1 or use all eight of the INVOICE columns on a record before you create a receipt record. You may find a list of valid values in AR_PAYMENT_SCHEDULES.TRX_NUMBER. Do not look

at transactions with a class of PMT or GUAR. Invoice

numbers are optional.

AMOUNT_APPLIED_FROM1-8 If the receipt currency and the transaction currency are

different, enter the amount of the receipt to apply in the

receipt currency.

INVOICE CURRENCY CODE1

-8

If the receipt currency and the transaction currency are different, enter the currency of the transaction (optional). If

null. AutoLockbox derives this value from

AR_PAYMENT_SCHEDULES_ALL. This field is used for

cross currency receipt applications.

TRANS_TO_RECEIPT_RATE

If the receipt currency and the transaction currency are different, enter the exchange rate used to convert the receipt to the transaction currency. This value is used for cross currency receipt applications when the receipt and transaction currencies do not have a fixed exchange rate.

INVOICE1-8 INSTALLMENT

Enter the installment number if your invoice has multiple payment schedules. If you do not specify the installment number for an invoice with multiple payment schedules, Receivables will apply to the oldest payment schedule first. The installment number must be on the same record as the associated invoice number.

AMOUNT APPLIED1-8

Enter the amount of the receipt to apply to the invoice. You can provide invoice numbers without specifying the amount applied to each of these invoices. If you provide invoice numbers without specifying the amount applied to each invoice, Receivables applies the receipt to the invoices starting with the oldest receipt schedule first. The value of the amount applied column must be on the same record as the invoice number to which it is applied. For example, you cannot have all of the invoice numbers on the receipt record and all of the amounts applied on the overflow. Applied amounts are optional. If the receipt currency and the transaction currency are different, enter the amount of the receipt to apply in the transaction currency.

COMMENTS

Enter any free-form comments about this receipt. Receivables stores this data, but does not display these comments in any of the receipt entry windows.

ATTRIBUTE CATEGORY

Enter the Descriptive Flexfield category information for this receipt.

ATTRIBUTE1-15

Enter the Descriptive Flexfield attributes for this category. You can use this column to transfer additional information about your receipt. For example, if your bank enters and transmits customer name, you can use an attribute column to import this name. The attributes are visible as Descriptive Flexfields in the Receipt windows.

BILL TO LOCATION

To associate receipts with specific customer sites, enter the billing address for this receipt and include billing location in your transmission format. If the system option Require Billing Location for Receipts is set to Yes, you must enter a

value here. In addition, you can set the Require Billing Location field to Yes in the Lockboxes window to require a billing location for a specific lockbox. The value of this field in the Lockboxes window will override the option at the system level. See: Lockboxes, Oracle Receivables Implementation Guide.

CUSTOMER BANK NAME The name of the customer's bank.

CUSTOMER BANK BRANCH

The name of the customer's bank branch.

REMITTANCE BANK NAME The name of the bank that received the payment.

REMITTANCE BANK BRANC

H NAME

The name of the bank branch that received the payment.

Assigning Values To Overflow Records

If your record type is an Overflow record, enter the following columns with the values described. Some of these values are mandatory, while others are optional. Overflow records allow you to transmit additional information about a receipt that does not fit on the receipt record, such as batch number, item number, sequence number, invoice number, debit memo number, or debit item amounts. The most common use for this record type is to import additional invoice numbers to which the receipt should be applied. An overflow record can have up to eight invoice applications.

LOCKBOX_NUMBER Enter the number of the lockbox for this receipt. If the

> lockbox number is included in your format and you do not have any batch records, you must enter this number for

each receipt and overflow record.

Enter the batch for this overflow record. If the batch name BATCH_NAME

is included in your format, you must enter this name for

each overflow record.

ITEM NUMBER Enter a sequential number to indicate the location of the

> overflow record in this batch. All overflow records for a receipt have the same item number as the receipt record. You must enter an item number for each overflow record to

reference the receipt.

OVERFLOW INDICATOR Receivables uses this column to indicate overflow records

for the current receipt. You determine your overflow indicator in your transmission format. To identify the last overflow record, enter a value that is different from your overflow indicator. For example, in the BAI transmission format, '0' indicates an overflow record. You have three overflow records for a receipt, the first two records have '0' as the overflow indicator and the third record has '9'. Since the third record is not '0', it is identified as the last overflow record. You must enter a value for all overflow records.

OVERFLOW_SEQUENCE

Enter a sequential number to indicate the order of overflow records. Within each receipt, the Overflow Sequence usually begins with 1.

AMOUNT APPLIED FROM1-8

If the receipt currency and the transaction currency are different, enter the amount of the receipt to apply in the receipt currency.

INVOICE_CURRENCY_CODE1

If the receipt currency and the transaction currency are different, enter the currency of the transaction (optional). If null, AutoLockbox derives this value from AR_PAYMENT_SCHEDULES_ALL. This field is used for cross currency receipt applications.

TRANS TO RECEIPT RATE

If the receipt currency and the transaction currency are different, enter the exchange rate used to convert the receipt to the transaction currency. This value is used for cross currency receipt applications when the receipt and transaction currencies do not have a fixed exchange rate.

INVOICE1-8

Enter the invoice numbers to which you apply this receipt. You do not have to start with INVOICE1, nor use all eight of the INVOICE columns on a record before you create an overflow record. You can find a list of valid values in AR_PAYMENT_SCHEDULES.TRX_NUMBER. Do not look at transactions with a class of PMT or GUAR. You may supply invoice numbers without specifying the amount applied to each invoice. Invoice numbers are optional.

INVOICE1-8_INSTALLMENT

Enter the installment number if your invoice has multiple payment schedules. If you do not specify the installment number for an invoice with multiple payment schedules, then Receivables will apply to the oldest payment schedule first. The installment number must be on the same record as the associated invoice number.

AMOUNT APPLIED1-8

Enter the amount of the receipt to apply to the invoice. If you specify invoice numbers without specifying the amount applied to each invoice, Receivables applies the receipt to the invoices starting with the oldest receipt first. The value of the amount applied column must be on the same record as the invoice number to which the receipt amount is applied.

System Assigned Columns

Receivables assigns values to the columns listed in the table below during the import process. Your import file must leave these columns blank.

Column Name	Туре
TRANSMISSION_RECORD_ID	NUMBER
CREATION_DATE	DATE
CREATED_BY	NUMBER
LAST_UPDATE_LOGIN	NUMBER
LAST_UPDATED_BY	NUMBER
LAST_UPDATE_DATE	DATE
TRANSMISSION_REQUEST_ID	NUMBER
CUSTOMER_ID	NUMBER
SPECIAL_TYPE	CHAR(20)
GL_DATE	DATE
STATUS	CHAR(30)
INVOICE1-8_STATUS	CHAR(30)
RECEIPT_METHOD_ID	NUMBER(15)
TRANSMISSION_ID	NUMBER(15)
INVOICE1-8_STATUS	VARCHAR2(30)
CUSTOMER_BANK_ACCOUNT_ID	NUMBER(15)
CUSTOMER_SITE_USE_ID	NUMBER(15)
TRANSFERRED_RECEIPT_COUNT	NUMBER

Column Name	Туре
TRANSFERRED_RECEIPT_AMOUNT	NUMBER

Seeded Match Rules

Seeded Search Match Rules

Two seeded match rules, SAMPLE: BASIC SEARCH RULE and SAMPLE: ADVANCED SEARCH RULE, are provided for you to use for the Customer Search page. These rules let you search with the same criteria as in a non-DQM search, but with the robust Data Quality Management matching functionality.

You set either of these two seeded match rules, or one that you define yourself using the Data Quality Management Search Profile Options. See:

- Setting Up DQM, Oracle Receivables Implementation Guide.
- DQM Deployment Category, Oracle Trading Community Architecture Administration Guide.

The acquisition portion of the match rule determines the displayed search criteria and potential matches. Each acquisition attribute corresponds to a search criterion. The scoring portion scores and ranks the search results.

Prerequisite

Run the DQM Compile All Rules Program.

See also: DQM Compile All Rules Program, Oracle Trading Community Architecture Administration Guide.

Related Topics

Match Rules Overview, Oracle Trading Community Architecture Administration Guide

SAMPLE: BASIC SEARCH RULE

This match rule provides search criteria for performing a basic DQM search.

Acquisition

This table shows the seeded attributes and transformation functions for the acquisition part of the matching process.

Attribute Name	Entity	Filter	Attribute Match	Transformation Name
Name	Party	No	Match All Attributes	SOUNDEX WR + CLEANSE
Registry ID	Party	No	Match All Attributes	EXACT
Address	Address	No	Match All Attributes	WR ADDRESS + CLEANSE
City	Address	No	Match All Attributes	CLEANSE
State	Address	No	Match All Attributes	WR STATE
Country	Address	No	Match All Attributes	EXACT
All Account Names	Party	No	Match All Attributes	CLEANSE
Contact Name	Contact	No	Match All Attributes	SOUNDEX WR PERSON + CLEANSE
Phone Number Flexible Format	Contact Point	No	Match All Attributes	EXACT
e-mail Address	Contact Point	No	Match All Attributes	CLEANSE (EMAIL)
Site Number	Address	No	Match All Attributes	EXACT
All Account Numbers	Party	No	Match All Attributes	EXACT (NUMBER)

Scoring

This table shows the seeded thresholds for the scoring part of the matching process.

Threshold	Value
Match Threshold	450
Override Threshold	
Automatic Merge Threshold	

This table shows the seeded attributes and transformations for the scoring part of the matching process.

Attribute Name	Entity	Score	Transformation Name	Weight (%)	Туре	Similarity (%)
Name	Party	50	WR NAMES + CLEANSE	100	Exact	
			SOUNDEX	70	Exact	
Registry ID	Party	100	EXACT	100	Exact	
Address	Address	70	WR ADDRESS	100	Exact	
			WR ADDRESS + CLEANSE	70	Exact	
City	Address	20	CLEANSE	70	Exact	
State	Address	10	WR STATE	100	Exact	
Country	Address	10	EXACT	100	Exact	
All Account Names	Party	60	WR NAMES	100	Exact	
			WR NAMES + CLEANSE	80	Exact	
Contact Name	Contact Point	50	WR PERSON + CLEANSE	100	Exact	
			SOUNDEX	70	Exact	

Attribute Name	Entity	Score	Transformation Name	Weight (%)	Туре	Similarity (%)
Phone Number Flexible Format	Contact Point	80	EXACT	100	Exact	
e-mail Address	Contact Point	80	EXACT (EMAIL)	100	Exact	
			CLEANSE (EMAIL)	70	Exact	
Site Number	Address	50	EXACT	100	Exact	
All Account Numbers	Party	90	EXACT (NUMBER)	100	Exact	

SAMPLE: ADVANCED SEARCH RULE

This match rule provides search criteria for performing an advanced DQM search.

Acquisition

This table shows the seeded attributes and transformation functions for the acquisition part of the matching process.

Attribute Name	Entity	Filter	Attribute Match	Transformation Name
Name	Party	No	Match All Attributes	SOUNDEX WR NAMES + CLEANSE
Registry ID	Party	No	Match All Attributes	EXACT
Tax Name	Party	No	Match All Attributes	CLEANSE
Party Type	Party	Yes	Match All Attributes	EXACT
Category Code	Party	No	Match All Attributes	EXACT
SIC Code	Party	No	Match All Attributes	EXACT

Attribute Name	Entity	Filter	Attribute Match	Transformation Name
SIC Code Version	Party	No	Match All Attributes	EXACT
Tax Registration Number	Party	No	Match All Attributes	EXACT
City	Address	No	Match All Attributes	CLEANSE
State	Address	No	Match All Attributes	WR STATE
Postal Code	Address	No	Match All Attributes	EXACT
County	Address	No	Match All Attributes	CLEANSE
Province	Address	No	Match All Attributes	CLEANSE
Country	Address	No	Match All Attributes	EXACT
All Account Names	Party	No	Match All Attributes	WR NAMES + CLEANSE
Phone Number	Contact Point	No	Match All Attributes	EXACT
All Account Numbers	Party	No	Match All Attributes	EXACT (NUMBER)
Reference Use Flag	Party	No	Match All Attributes	EXACT
Corporation Class	Party	No	Match All Attributes	EXACT

Scoring

This table shows the seeded thresholds for the scoring part of the matching process.

Threshold	Value
Match Threshold	480
Override Threshold	

Threshold	Value
Automatic Merge Threshold	

This table shows the seeded attributes and transformation functions for the scoring part of the matching process.

Attribute Name	Entity	Score	Transformation Name	Weight (%)	Туре	Similarity (%)
Name	Party	50	WR NAMES + CLEANSE	80	Exact	
Name	Party	50	WR NAMES	100	Exact	
Name	Party	50	SOUNDEX	60	Exact	
Registry ID	Party	100	EXACT	100	Exact	
Tax Name	Party	30	CLEANSE	100	Exact	
Reference Use Flag	Party	20	EXACT	100	Exact	
Category Code	Party	10	EXACT	100	Exact	
SIC Code	Party	30	EXACT	100	Exact	
SIC Code Version	Party	10	EXACT	100	Exact	
Tax Registration Number	Party	80	EXACT	70	Exact	
Corporation Class	Party	30	EXACT	100	Exact	
City	Address	30	CLEANSE	70	Exact	
State	Address	20	WR STATE	80	Exact	

Attribute Name	Entity	Score	Transformation Name	Weight (%)	Туре	Similarity (%)
Postal Code	Address	30	EXACT	100	Exact	
County	Address	20	CLEANSE	70	Exact	
Province	Address	10	CLEANSE	70	Exact	
Country	Address	30	EXACT	100	Exact	
All Account Names	Party	50	EXACT	100	Exact	
Phone Area Code	Contact Point	30	EXACT	100	Exact	
All Account Numbers	Party	100	EXACT (NUMBER)	100	Exact	
Phone Number	Contact Point	50	EXACT	100	Exact	
Phone Country Code	Contact Point	10	EXACT	100	Exact	

XML Transactions

XML Receivables Documents Mapping

This appendix provides the mapping for the XML messages used in the XML Invoices process.

For more information about sending XML messages, that contain Receivables documents, to customers, see: XML Receivables Documents, Oracle Receivables User Guide.

Related Topics

Process Invoice XML Message Map, page D-1

Confirm BOD Message Map, page D-5

Transaction Limitations, page D-6

Process Invoice XML Message Map

The XML invoices process uses the Open Applications Group Process Invoice DTD called 171_process_invoice_002.dtd (version 7.2.1).

The following table shows you the mapping between Receivables database columns and the elements of the Process Invoice XML message for the invoice header.

INVHEADER	Target (XML)	Source
	AMOUNT.DOCUMENT.T.VALUE	AR_XML_INVOICE_V.amount
	AMOUNT.DOCUMENT.T.CURRENCY	AR_XML_INVOICE_V. currency_code

INVHEADER	Target (XML)	Source
	DATETIME.DOCUMENT	AR_XML_INVOICE_V.trx_date
	DOCUMENTID	AR_XML_INVOICE_V.trx_number
	PAYMETHOD	AR_XML_INVOICE_V. payment_method
	PARTNER.NAME	AR_XML_INVOICE_V. supplier_name
	PARTNER.PARTNERID	AR_XML_INVOICE_V. supplier_code
	PARTNER.PARTNRTYPE	Supplier
	PARTNER.PARTNERIDX	AR_XML_INVOICE_V. supplier_code
	PARTNER.CONTACT.NAME	AR_XML_INVOICE_V.salesrep
	PARTNER.CONTACT.EMAIL	AR_XML_INVOICE_V. salesrep_email
	DOCUMNTREF.DOCTYPE	AR_XML_INVOICE_V. document_type
	DOCUMNTREF.DOCMENTID	AR_XML_INVOICE_V. reference_number
	DOCUMNTREF.PARTNRID	AR_XML_INVOICE_V. supplier_code
	DOCUMNTREF.PARTNRTYPE	Supplier
one or more	PYMTTERM.AMOUNT.DISCNT.T	AR_XML_PAYMENT_TERMS_V. discount_amount
one or more	PYMTTERM.DATETIME.DISCNT	AR_XML_PAYMENT_TERM_V. discount_date

INVHEADER	Target (XML)	Source
one or more	PYMTTERM.DATETIME.DUE	AR_XML_PAYMENT_TERMS_V. due_date
one or more	PYMTTERM.DATETIME.PYMTTERM	AR_XML_PAYMENT_TERMS_V. term_start_date_effective
one or more	PYMTTERM.DESCRIPTN	AR_XML_PAYMENT_TERMS_V. term_decscription
one or more	PYMTERRM.TERMID	AR_XML_PAYMENT_TERMS_V. term_name
one or more	PYMTERRM.USERAREA.AMOUNT	AR_XML_PAYMENT_TERMS_V. due_amount

The following table shows you the mapping between Receivables database columns and the elements of the Process Invoice XML message for the invoice charges.

INVCHARGE	Target (XML)	Source
zero or more	AMOUNT.EXTENDED.T	AR_XML_INVOICE_CHARGE_V. charge_amount
zero or more	CHARGETYPE	AR_XML_INVOICE_CHARGE_V.line_type
zero or more	DESCRIPTION	AR_XML_INVOICE_CHARGE_V. description
zero or more	LINENUM	AR_XML_INVOICE_CHARGE_V. line_number

The following table shows you the mapping between Receivables database columns and the elements of the Process Invoice XML message for the invoice lines.

INVLINE	Target (XML)	Source
	AMOUNT.EXTENDED.T	AR_XML_INVOICE_LINE_V.line_amount

INVLINE	Target (XML)	Source
	OPERAMT.UNIT.T	AR_XML_INVOICE_LINE_V. unit_selling_price
	QUANTITY.ITEM	AR_XML_INVOICE_LINE_V.quantity
	LINENUM	AR_XML_INVOICE_LINE_V.line_number
	DESCRIPTN	AR_XML_INVOICE_LINE_V.description
	ITEM	AR_XML_INVOICE_LINE_V.item. description
	ITEMX	AR_XML_INVOICE_LINE_V.item
	UNIT	AR_XML_INVOICE_LINE_V.uom
	DOCUMNTREF.DOCTYPE	AR_XML_INVOICE_LINE_V.line_type
	DOCUMNTREF.DOCUMENTID	AR_XML_INVOICE_LINE_V. reference_number
	DOCUMNTREF.PARTNRID	AR_XML_INVOICE_LINE_V.supplier_code
	DOCUMNTREF.PARTNRTYPE	Supplier
	DOCUMNTREF.DOCTYPE	PurchaseOrder
	DOCUMNTREF.DOCUMENTID	AR_XML_INVOICE_LINE_V.po_number
zero or more	INVCHARGE.AMOUNT. EXTENDED.T	AR_XML_INVOICE_CHARGE_V. charge_amount
zero or more	INVCHARGE.CHARGETYPE	AR_XML_INVOICE_CHARGE_V.line_type
zero or more	INVCHARGE.DESCRIPTION	AR_XML_INVOICE_CHARGE_V. description
zero or more	INVCHARGE.LINENUM	AR_XML_INVOICE_CHARGE_V. line_number
zero or more	INVTAX.AMOUNT.TAX.T	AR_XML_INVOICE_TAX_V.tax_amount

INVLINE	Target (XML)	Source
zero or more	INVTAX.AMOUNT.TAXBASE.T	AR_XML_INVOICE_TAX_V. taxable_amount
zero or more	INVTAX.QUANTITY.PERCENT	AR_XML_INVOICE_TAX_V.tax_rate
zero or more	INVTAX.DESCRIPTN	AR_XML_INVOICE_TAX_V.description
zero or more	INVTAX.LINENUM	AR_XML_INVOICE_TAX_V.line_number
zero or more	INVTAX.TAXCODE	AR_XML_INVOICE_TAX_V.tax_code

Confirm BOD Message Map

The message map for the Confirm_BOD XML message used by the XML Receivables Documents feature is Confirm_BOD (XML - XML, Inbound) and the DTD is $002_confirm_bod_004.dtd.$

The Confirm BOD has two control areas. One has the information for the Confirm BOD. The second is an exact copy of the control area from the Process Payment XML message. The second control area provides the context of the Confirm BOD.

The following table shows the mapping of the Confirm BOD XML message.

CONFIRM	Source (XML)	Value	Target (PLSQL)
	STATUSLVL	00: Success 10: AR Invoice Failure	AR_CONFIRMATION. initiate_confirmation_process. P_STATUS
	DESCRIPTIN		

CONFIRM	Source (XML)	Value	Target (PLSQL)
	ORIGREF		AR_CONFIRMATION. initiate_confirmation_process. P_ID.
			ar_document_transfers. document_transfer_id: ra_customer_trx. customer_trx_id: ra_customer_trx_lines. customer_trx_line_id
			Passed from Receivables to your customer's Payables system.
zero or more	CONFIRMMSG. REASONCODE		AR_CONFIRMATION. initiate_confirmation_process. P_REASON_CODE
zero or more	CONFIRMMSG.	Invoice	AR_CONFIRMATION.
	DESCRIPTN	InvoiceLine	initiate_confirmation_process. P_DESCRIPTION
		CreditMemo	
		CreditMemo Line	
		DebitMemo	
		DebitMemo Line	

Transaction Limitations

This feature has certain limitations. They include the following:

- You can only send invoices, debit memos, credit memos, chargebacks, and deposits as XML documents.
- To disable the delivery of XML invoice documents to a customer, you must remove the customer's bill-to site from the Trading Partner Setup window in XML Gateway.

Index

Α	Credit Memo Approval and Creation API, 3-1 Credit Memo Approval and Creation API
account derivation rules, A-12 accounting account derivation rules, A-12 accounting event class options, A-4 application accounting definitions, A-15 applications, A-2 event classes and types, A-3 event entities, A-2 journal lines definitions, A-13 journal line types, A-6 predefined data, A-1 process categories, A-4 sources and assignments, A-5 subledger accounting methods, A-17 accounting event class options, A-4 Adjustment API Ar_Adjust_pub.Approve_Adjustment, 2-13 Ar_Adjust_pub.Create_Adjustment, 2-4 Ar_Adjust_pub.Create_Linelevel_Adjustment, 2-26 Ar_Adjust_pub.Modify_Adjustment, 2-18 Ar_Adjust_pub.Reverse_Adjustment, 2-24 messages, 2-28 overview, 2-1 usage, 2-1 APIs Adjustment API, 2-1 Adjustment API usage, 2-1 Credit Memo Application API, 4-1	usage, 3-2 Deposit API, 5-1 Deposit API usage, 5-1 features, 1-1 Invoice Creation API, 6-1 Invoice Creation API usage, 6-2 Prepayments API usage, 7-2 Receipt API, 8-1 Receipt API usage, 8-2 Revenue Adjustment API, 9-1 Revenue Adjustment API usage, 9-2 solution outline, 1-2 application accounting definitions, A-15 applications, A-2 AutoInvoice AR_INTERFACE_CONTS_ALL, B-59 RA_INTERFACE_DISTRIBUTIONS_ALL, B-53 RA_INTERFACE_ERRORS_ALL, B-61 RA_INTERFACE_LINES_ALL, B-1 RA_INTERFACE_SALESCREDITS_ALL, B-49 table and column descriptions, B-1 AutoLockbox AR_PAYMENTS_INTERFACE_ALL, B-63 assigning values to overflow records, B-79 interface tables and column descriptions, B-63 tables and column descriptions, B-62
Credit Memo Application API usage, 4-1	

columns	overview, 6-1			
AutoInvoice columns and tables, B-1	usage, 6-2			
AutoLockbox columns and tables, B-62				
Credit Memo Application API	J			
ar_cm_application_pub.activity_application,	journal lines definitions, A-13			
4-1	journal line types, A-6			
ar_cm_application_pub.	journal line types, 11 o			
activity_unapplication, 4-10	M			
messages, 4-14				
overview, 4-1	match rules			
usage, 4-1	advanced search rule, C-4			
Credit Memo Approval and Creation API	basic search rule, C-1			
AR_CM_API_PUB.Apply_On_Account, 3-12	seeded, C-1			
AR_CM_API_PUB.Unapply_On_Account, 3-	messages			
12	XML messages mapping, D-1			
AR_CREDIT_MEMO_API_PUB.	Messages			
Create_Request, 3-2	Adjustment API, 2-28			
AR_CREDIT_MEMO_API_PUB.	Credit Memo Application API, 4-14			
Get_Request_Status, 3-9	Credit Memo Approval and Creation API, 3-			
messages, 3-12	12			
overview, 3-1	Deposit API, 5-32			
usage, 3-2	Prepayments API, 7-11			
customers	Receipt API, 8-136			
1.1. (1.1.6. 1.01	Revenue Adjustment API, 9-31			
seeded match rules for search, C-1	Revenue Majustinent M 1, 7-51			
seeded match rules for search, C-1	Revenue Augustinent III I, 7-01			
seeded match rules for search, C-1	O			
D	_			
Data Quality Management	0			
Data Quality Management advanced search rule, C-4	Oracle Subledger Accounting			
Data Quality Management advanced search rule, C-4 basic search rule, C-1	Oracle Subledger Accounting account derivation rules, A-12			
Data Quality Management advanced search rule, C-4 basic search rule, C-1 seeded match rules, C-1	Oracle Subledger Accounting account derivation rules, A-12 accounting event class options, A-4			
Data Quality Management advanced search rule, C-4 basic search rule, C-1 seeded match rules, C-1 Deposit API	Oracle Subledger Accounting account derivation rules, A-12 accounting event class options, A-4 application accounting definitions, A-15			
Data Quality Management advanced search rule, C-4 basic search rule, C-1 seeded match rules, C-1 Deposit API AR_DEPOSIT_API_PUB.Create_deposit, 5-2	Oracle Subledger Accounting account derivation rules, A-12 accounting event class options, A-4 application accounting definitions, A-15 applications, A-2			
Data Quality Management advanced search rule, C-4 basic search rule, C-1 seeded match rules, C-1 Deposit API AR_DEPOSIT_API_PUB.Create_deposit, 5-2 AR_DEPOSIT_API_PUB.	Oracle Subledger Accounting account derivation rules, A-12 accounting event class options, A-4 application accounting definitions, A-15 applications, A-2 event classes and types, A-3			
Data Quality Management advanced search rule, C-4 basic search rule, C-1 seeded match rules, C-1 Deposit API AR_DEPOSIT_API_PUB.Create_deposit, 5-2 AR_DEPOSIT_API_PUB. insert_non_rev_salescredit, 5-27	Oracle Subledger Accounting account derivation rules, A-12 accounting event class options, A-4 application accounting definitions, A-15 applications, A-2 event classes and types, A-3 event entities, A-2			
Data Quality Management advanced search rule, C-4 basic search rule, C-1 seeded match rules, C-1 Deposit API AR_DEPOSIT_API_PUB.Create_deposit, 5-2 AR_DEPOSIT_API_PUB. insert_non_rev_salescredit, 5-27 messages, 5-32	Oracle Subledger Accounting account derivation rules, A-12 accounting event class options, A-4 application accounting definitions, A-15 applications, A-2 event classes and types, A-3 event entities, A-2 journal lines definitions, A-13			
Data Quality Management advanced search rule, C-4 basic search rule, C-1 seeded match rules, C-1 Deposit API AR_DEPOSIT_API_PUB.Create_deposit, 5-2 AR_DEPOSIT_API_PUB. insert_non_rev_salescredit, 5-27 messages, 5-32 overview, 5-1	Oracle Subledger Accounting account derivation rules, A-12 accounting event class options, A-4 application accounting definitions, A-15 applications, A-2 event classes and types, A-3 event entities, A-2 journal lines definitions, A-13 journal line types, A-6			
Data Quality Management advanced search rule, C-4 basic search rule, C-1 seeded match rules, C-1 Deposit API AR_DEPOSIT_API_PUB.Create_deposit, 5-2 AR_DEPOSIT_API_PUB. insert_non_rev_salescredit, 5-27 messages, 5-32	Oracle Subledger Accounting account derivation rules, A-12 accounting event class options, A-4 application accounting definitions, A-15 applications, A-2 event classes and types, A-3 event entities, A-2 journal lines definitions, A-13 journal line types, A-6 predefined data, A-1			
Data Quality Management advanced search rule, C-4 basic search rule, C-1 seeded match rules, C-1 Deposit API AR_DEPOSIT_API_PUB.Create_deposit, 5-2 AR_DEPOSIT_API_PUB. insert_non_rev_salescredit, 5-27 messages, 5-32 overview, 5-1 usage, 5-1	Oracle Subledger Accounting account derivation rules, A-12 accounting event class options, A-4 application accounting definitions, A-15 applications, A-2 event classes and types, A-3 event entities, A-2 journal lines definitions, A-13 journal line types, A-6 predefined data, A-1 process categories, A-4 sources and assignments, A-5			
Data Quality Management advanced search rule, C-4 basic search rule, C-1 seeded match rules, C-1 Deposit API AR_DEPOSIT_API_PUB.Create_deposit, 5-2 AR_DEPOSIT_API_PUB. insert_non_rev_salescredit, 5-27 messages, 5-32 overview, 5-1 usage, 5-1	Oracle Subledger Accounting account derivation rules, A-12 accounting event class options, A-4 application accounting definitions, A-15 applications, A-2 event classes and types, A-3 event entities, A-2 journal lines definitions, A-13 journal line types, A-6 predefined data, A-1 process categories, A-4			
Data Quality Management advanced search rule, C-4 basic search rule, C-1 seeded match rules, C-1 Deposit API AR_DEPOSIT_API_PUB.Create_deposit, 5-2 AR_DEPOSIT_API_PUB. insert_non_rev_salescredit, 5-27 messages, 5-32 overview, 5-1 usage, 5-1 E event classes and types, A-3	Oracle Subledger Accounting account derivation rules, A-12 accounting event class options, A-4 application accounting definitions, A-15 applications, A-2 event classes and types, A-3 event entities, A-2 journal lines definitions, A-13 journal line types, A-6 predefined data, A-1 process categories, A-4 sources and assignments, A-5			
Data Quality Management advanced search rule, C-4 basic search rule, C-1 seeded match rules, C-1 Deposit API AR_DEPOSIT_API_PUB.Create_deposit, 5-2 AR_DEPOSIT_API_PUB. insert_non_rev_salescredit, 5-27 messages, 5-32 overview, 5-1 usage, 5-1	Oracle Subledger Accounting account derivation rules, A-12 accounting event class options, A-4 application accounting definitions, A-15 applications, A-2 event classes and types, A-3 event entities, A-2 journal lines definitions, A-13 journal line types, A-6 predefined data, A-1 process categories, A-4 sources and assignments, A-5 subledger accounting methods, A-17			
Data Quality Management advanced search rule, C-4 basic search rule, C-1 seeded match rules, C-1 Deposit API AR_DEPOSIT_API_PUB.Create_deposit, 5-2 AR_DEPOSIT_API_PUB. insert_non_rev_salescredit, 5-27 messages, 5-32 overview, 5-1 usage, 5-1 E event classes and types, A-3	Oracle Subledger Accounting account derivation rules, A-12 accounting event class options, A-4 application accounting definitions, A-15 applications, A-2 event classes and types, A-3 event entities, A-2 journal lines definitions, A-13 journal line types, A-6 predefined data, A-1 process categories, A-4 sources and assignments, A-5 subledger accounting methods, A-17			
Data Quality Management advanced search rule, C-4 basic search rule, C-1 seeded match rules, C-1 Deposit API AR_DEPOSIT_API_PUB.Create_deposit, 5-2 AR_DEPOSIT_API_PUB. insert_non_rev_salescredit, 5-27 messages, 5-32 overview, 5-1 usage, 5-1 E event classes and types, A-3	Oracle Subledger Accounting account derivation rules, A-12 accounting event class options, A-4 application accounting definitions, A-15 applications, A-2 event classes and types, A-3 event entities, A-2 journal lines definitions, A-13 journal line types, A-6 predefined data, A-1 process categories, A-4 sources and assignments, A-5 subledger accounting methods, A-17 P parties seeded match rules for search, C-1			
Data Quality Management advanced search rule, C-4 basic search rule, C-1 seeded match rules, C-1 Deposit API AR_DEPOSIT_API_PUB.Create_deposit, 5-2 AR_DEPOSIT_API_PUB. insert_non_rev_salescredit, 5-27 messages, 5-32 overview, 5-1 usage, 5-1 E event classes and types, A-3	Oracle Subledger Accounting account derivation rules, A-12 accounting event class options, A-4 application accounting definitions, A-15 applications, A-2 event classes and types, A-3 event entities, A-2 journal lines definitions, A-13 journal line types, A-6 predefined data, A-1 process categories, A-4 sources and assignments, A-5 subledger accounting methods, A-17 P parties seeded match rules for search, C-1 Prepayments API			
Data Quality Management advanced search rule, C-4 basic search rule, C-1 seeded match rules, C-1 Deposit API AR_DEPOSIT_API_PUB.Create_deposit, 5-2 AR_DEPOSIT_API_PUB. insert_non_rev_salescredit, 5-27 messages, 5-32 overview, 5-1 usage, 5-1 E event classes and types, A-3 event entities, A-2	Oracle Subledger Accounting account derivation rules, A-12 accounting event class options, A-4 application accounting definitions, A-15 applications, A-2 event classes and types, A-3 event entities, A-2 journal lines definitions, A-13 journal line types, A-6 predefined data, A-1 process categories, A-4 sources and assignments, A-5 subledger accounting methods, A-17 P parties seeded match rules for search, C-1			

AR_PREPAYMENTS_PUB.Get_Installment, 7-	AR_RevenueAdjust_PUB.
9	Transfer_Sales_Credits, 9-18
messages, 7-11	AR_RevenueAdjust_PUB.Unearn_Revenue, 9-
overview, 7-1	2
usage, 7-2	AR_Revenueadjust_PUB.
process categories, A-4	Update_Contingency_Expirations, 9-28
	messages, 9-31
Q	overview, 9-1
QuickCash	usage, 9-2
tables, B-62	S
R	seeded match rules, C-1
Receipt API	sources and assignments, A-5
Ar_receipt_api_pub.activity_application, 8-74	subledger accounting methods, A-17
Ar_receipt_api_pub.activity_application, 8-	
82	T
Ar_receipt_api_pub.Apply, 8-20	tables
Ar_receipt_api_pub.Apply_on_account, 8-60	AR_INTERFACE_CONTS_ALL, B-59
Ar_receipt_api_pub.apply_open_receipt, 8-111	AutoInvoice tables and column descriptions,
Ar_receipt_api_pub.apply_other_account, 8-	B-1
100	AutoLockbox tables and columns, B-62
Ar_receipt_api_pub.Create_and_apply, 8-34	Lockbox interface table and columns, B-63
Ar_receipt_api_pub.Create_apply_on_acc, 8-	RA_INTERFACE_DISTRIBUTIONS_ALL, B-
120	53
Ar_receipt_api_pub.Create_cash, 8-3	RA_INTERFACE_ERRORS_ALL, B-61
Ar_receipt_api_pub.Create_cast, 6-5 Ar_receipt_api_pub.Create_misc, 8-86	RA_INTERFACE_LINES_ALL, B-1
Ar_receipt_api_pub.Reverse, 8-69	RA_INTERFACE_SALESCREDITS_ALL, B-49
Ar_receipt_api_pub.Unapply, 8-54	receipt and QuickCash tables, B-62
Ar_receipt_api_pub.Unapply_on_account, 8-	receipt and Quickeasit tables, b-02
65	X
Ar_receipt_api_pub.unapply_open_receipt, 8-	
118	XML
Ar_receipt_api_pub.unapply_other_account,	limitations, D-6
8-107	mapping, D-1
messages, 8-136	
overview, 8-1	
usage, 8-2	
receipts	
QuickCash	
tables, B-62	
Revenue Adjustment API	
AR_RevenueAdjust_PUB.	
Add_Non_Revenue_Sales_Credits, 9-23	
AR_RevenueAdjust_PUB.Earn_Revenue, 9-16	
AR_Revenueadjust_PUB.	
Record_Customer_Acceptance, 9-27	
record_cuotomer_receptance, 7-27	