Oracle Banking Digital Experience

Installer Originations OFSLL Manual

Release 17.2.0.0.0

Part No. E88573-01

July 2017



Installer Originations OFSLL Manual July 2017

Oracle Financial Services Software Limited

Oracle Park

Off Western Express Highway

Goregaon (East)

Mumbai, Maharashtra 400 063

India

Worldwide Inquiries:

Phone: +91 22 6718 3000 Fax:+91 22 6718 3001

www.oracle.com/financialservices/

Copyright © 2017, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Table of Contents

1.	Preface
	Introduction
	Prerequisites
	Installation
	Database configuration

1. Preface

1.1 Intended Audience

This document is intended for the following audience:

- Customers
- Partners

1.2 Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

1.3 Access to Oracle Support

Oracle customers have access to electronic support through My Oracle Support. For information, visit

http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info or visit

http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs_if you are hearing impaired.

1.4 Structure

Preface gives information on the intended audience. It also describes the overall structure of the User Manual.

The subsequent chapters cover following

- Introduction
- Prerequisites
- Installation
- Post Installation Steps

1.5 Related Information Sources

For more information on Oracle Banking Digital Experience Release 17.2.0.0.0, refer to the following documents:

- User Manual Oracle Banking Digital Experience Installer Pre-Requisite Setup
- User Manual Oracle Banking Digital Experience Installation Guide

2. Introduction

2.1 Purpose of the Document

The purpose of the OBDX OFSLL Installation Guide is to provide a step by step overview on the installation process of the solution.

It includes:

- Installation of OBDX 17.2.0.0.0 OFSLL with Oracle's own Core Banking and Origination Products.
- Advanced Configurations (Post installation)

3. Prerequisites

OBDX 17.2.0.0.0 with OBP BASE flavor should be installed through OBDX Installer. This installation will be henceforth referred to in this manual as 'OBDX17.2 Base'.

For OBDX 17.2 Base installation, refer documents mentioned in section 1.5 Related Information Sources.

4. Installation

4.1 Pre Installation

OBDX17.2.0.0.0 Base with OBP flavor should be installed through installer.

4.2 Preference

Changes in preference.xml: (refer /config/preference.xml)

1> Preference EnumerationConfig should override preference EnumerationConfigOFSLL143 as given below. <Preference name="EnumerationConfig" overriddenBy="EnumerationConfigOFSLL143" PreferencesProvider="... 2> Preference AdapterFactories should override preference AdapterFactoriesOFSLL143 as given below. <Preference name="AdapterFactories" overriddenBy="AdapterFactoriesOFSLL143" PreferencesProvider="... 3> Preference RepositoryAdapterFactories should override preference RepositoryAdapterFactoriesOFSLL143 as given below. <Preference name="RepositoryAdapterFactories" overriddenBy="RepositoryAdapterFactoriesOFSLL143" PreferencesProvider="... 4> Preference CustomBusinessPolicyPreferences should override preference


4> Preference CustomBusinessPolicyPreferences should override preference CustomBusinessPolicyPreferencesOFSLL143 as given below.

```
<Preference
name="CustomBusinessPolicyPreferences"
overriddenBy="CustomBusinessPolicyPreferencesOFSLL143"
PreferencesProvider="..
/>
```

5> Preference OriginationConfig should override preference

```
OriginationConfig_ofsII143 as given below.
```

```
<Pre><Pre>reference
name="OriginationConfig"
overriddenBy="OriginationConfig_ofsll143"
PreferencesProvider="..
/>
```



4.3 Steps of installation

Download and extract. Post extraction 'OBDX_LZNInstaller' folder would be available.

Ensure before installation following sub-directories are available:

- app
- db
- ui

4.3.1 Application deployment


The 'app' directory will have 3 artifacts to be deployed on the OBDX 17.2.0.0.0 Base Application server.

- com.ofss.digx.lz.us.appx.service.rest.ear
 - Un-deploy 'com.ofss.digx.appx.service.rest.ear' Enterprise
 Application from OBDX 17.2 Application Server. This artifact had
 been deployed as a part of OBDX 17.2 Base Installation.
 - Deploy 'com.ofss.digx.lz.us.appx.service.rest.ear' artifact as an Enterprise Application.
- ii. obdx.lz.us.app.domain.ear
 - Deploy this artifact as a library.
- iii. obdx.lz.us.app.wsdl.domain.ear
 - Deploy this artifact as a library.


Note: First shut down the application server. Go to deployments. Un-deploy the REST application project of the OBDX 17.2.0.0.0 Base and deploy REST application project of the OBDX 17.2.0.0.0 US LZN, two libraries (ii & iii) and an application (iv) as mentioned above. All other libraries of OBDX 17.2.0.0.0 Base are required for OBDX OFSLL setup. Do not remove them. Start the application server.

Steps to Un-deploy library/application -


Login into Weblogic Server. Go to Deployments. Select the library/application and click on delete.



Confirm delete.




Success message will be displayed.





Steps to Deploy library/application -

Click on install to deploy library/application. Click on Upload Button.




Click on 'Choose File' to select the library/application to upload.







Click on NEXT button.




Again click on NEXT button.




Select 'Install as library/application', as per the deployment.




Select the managed server/cluster to deploy on. Click on Next.



Click on Finish.



Confirmation of installation will be displayed.






Figure 1 : Deployments after OBDX17.2.0.0.0 Base Installation





Figure 2: Deployments after OBDX 17.2.0.0.0 OFSLL Installation

4.3.2 Security credential mapping for connector.ear

Please follow following steps

- 1. Login into Weblogic console.
- 2. Click on **Deployments**.
- 3. Expand by clicking '+' icon present in front of **com.ofss.digx.app.connector application** as shown below.




4. Click com.ofss.digx.connector.rar as shown below.





17

5. Click 'Security' tab and then click 'Outbound Credential Mappings' sub tab as shown below.




6. Click on 'New' Button. Following screen will be appearing.






7. Select 'ra/DIGXConnectorAES' and click then 'Next' button. Following screen will be appearing.



8. Select '**Default User**' and then click '**Next**' button. Following screen will be appearing.



9. Enter following details and then click 'Finish' button.

EIS User Name → AES_KEY

EIS Password → OBDX_PASSWORD123


Confirm Password → OBDX_PASSWORD123

10. Restart the manage server to activate the changes.

4.3.3 BI credential mapping for connector.ear

Please follow following steps


- 1. Login into Weblogic console.
- 2. Click on **Deployments**.
- 3. Expand by clicking '+' icon present in front of **com.ofss.digx.app.connector application** as shown below.



4. Click **com.ofss.digx.connector.rar** as shown below.



5. Click 'Security' tab and then click 'Outbound Credential Mappings' sub tab as shown below.



6. Click on 'New' Button. Following screen will be appearing.



Outbound Connection Pool


Which Outbound Connection Pool would you like the credential map to be associate resource adapter. Each Outbound Connection Pool can then configure themselves to

Customize this table


Create a New Security Credential Map Entry for:

	Outbound Connection Pool 🐟			
	ra/DIGXConnectorAES			
	ra/DIGXConnectorBIREPORTS			
	ra/DIGXConnectorFILEUPLOAD			
	ra/DIGXConnectorMERCHANT			
	Resource Adapter Default			
Back Next Finish Cancel				

7. Select 'ra/DIGXConnectorBIREPORTS' and click then 'Next' button. Following screen will be appearing.



8. Select '**Default User**' and then click '**Next**' button. Following screen will be appearing.



- 9. Enter administrative authentication credentials of BIP and then click 'Finish' button.
- 10. Restart the manage server to activate the changes.

4.3.4 Database scripts deployment

The 'db' directory will have two sub-directories: dml and ddl. Executes all scripts present in the dml folder.

Note: There are no ddl scripts to execute.

4.3.5 UI deployment

The 'ui' directory contains all the UI related files. The UI deployed by OBDX 17.2.0.0.0 Base installation should be replaced by the UI contents of this directory.

Note: No change required in OHS.

5. Database configuration

Following configurations need to be done post installation

5.1 System Configuration

These are mandatory configurations for application to work. It should be completed before using the application.

table 'digx_fw_config_var_b'

Property Id	Description
BANK.DEFAULT.CODE	This property contains bank code.
BRANCH.DEFAULT.CODE	This property contains branch code.
HOST_DATE	This property contains host date
OBDX.WEB.HOST	This property contains OHS server host name/IP
OBDX.WEB.PORT	This property contains OHS server port
HOST_IP	This property contains OFSLL (core banking) system's host name/ip
HOST_PORT	This property contains OFSLL (core banking) system's port
EMAIL.SMTP.PORT	This property contains email SMTP server port
EMAIL.SMTP.HOST	This property contains email SMTP server host name/ip
BATCH_REQUEST_URL	This url will be used for forming batch request.
	Example :- http:// <app_server_name>:<app_server's_m anage_server_port>/digx/v1</app_server's_m </app_server_name>
HOST_REPORT_IP	This property contains OFSLL (core banking) report server's host name/ip
HOST_REPORT_PORT	This property contains OFSLL (core banking) report server's port
HOST_IP_RS	This property contains OFSLL (core banking) report server's host name/ip which is to be used for host call through REST services.
HOST_PORT_RS	This property contains OFSLL (core banking) report server's host port which is to be used for host call through REST services.

table 'digx_me_ep_conf_b'

Query to be executed	Description
UPDATE DIGX_ME_EP_CONF_B SET MULTI_ENTITY_CODE='GLBL_N MKT', FROM_ADDR=' <system_email_id>' WHERE MULTI_ENTITY_CODE ='OBP_ME' and Destination_type='EMAIL';</system_email_id>	This property is used to provide system's email id. All system generated mails will be come from this id

5.2 Additional (functional) Configurations

These are non mandatory configurations. Default values for these configurations are available through day 0 scripts. Bank can change these values as per their business need.

table 'digx_fw_config_var_b'

Category Id	Property Id	Description
Origination UserRole	USER_ROLE_CUSTOMER	Default roles for Origination user creation. The prop_id does not matter. All roles for category_id 'OriginationUserRole' would be assigned to the created user.
Origination Config	ORG_DOB_AGE_LIMIT	DOB Age Limit Value. In case the above roperty value is LOCAL, the age limit in number is to be specified for this property.
Origination Config	USERNAME_TYPE	Username type while registering the prospect. Possible values EMAIL/OTHERS
Origination Config	LIST_CANCELLATION_DAY S	Submission Cancellation List Range. This value will be used in Report Generation for Cancelled Applications. This property indicates the number of days for which the cancellation report will be generated.
Origination Config	ORIG_PI_EMAIL_VERIFICA TION_REQUIRED	If Email Verification via OTP is required.
Origination Config	CONTENT_UPLOAD_ALLO WED_TYPE_LIST	File types allowed for document uploading. Example:txt,.png,.xlsx,.doc,.pdf,.jpeg,.jpg
Origination Config	CONTENT_UPLOAD_MIME_ TYPES_WHITE_LIST	Allowed MIME types for file uploading. Example:- application/pdf,image/jpeg,image/png
Origination Config	CONTENT_UPLOAD_MIME_ TYPES_ZIP_LIST	Allowed MIME types for uploading zip document. Example:- application/x-compressed

		,
Origination Config	DRIVING_LICENSE_EXPIRY _DURATION	Value should be in years. Driving License expiry date should be less than current date + this value.
Origination Config	DRIVING_LICENSE_MAX_L ENGTH	Driving License number's maximum length allowed.
Origination Config	EMPLOYMENT_STABILITY_ MONTH_DURATION	Value should be in months. This value is used to decide employment stability.
Origination Config	IS_REGISTRATION_MANDA TORY	This flag used to force mandatory channel registration while submitting application.
Origination Config	MAX_ALLOWED_VEHICLE_ AGE	Maximum age allowed for vehicle.
Origination Config	ORG_REG_LINK_TIMEOUT	Channel registration link time out value
Origination Config	ORIGINATION_WORKFLOW _LOADER	Workflow loader configuration
Origination Config	VEHICLE_MILEAGE_MAX_L IMIT	Maximum mileage of used vehicle needs to be captured
Origination Config	VEHICLE_YEAR_MAX_LIMI T	Maximum duration of used vehicle needs to be captured
Origination Config	RESIDENT_STABILITY_MO NTH_DURATION	Value should be in months. This value is used to decide residential stability.
Origination Config	SSN_MAX_LENGTH	Maximum length allowed for Social Security Number.
Origination Config_ofsl I143	DEALER_APPLICATION_NU MBER	Dealer's application number present in OFSLL application.
Origination Config_ofsl I143	DEALER_ID	Dealer Id present in OFSLL application.
Origination Config_ofsl I143	LENDER_ID	Lender Id present in OFSLL application.
Origination Config_ofsl	LENDER_DEALER_ID	Lender Dealer Id present in OFSLL application.

l143		
Origination Config_ofsl I143	COMPANY_CODE	Company Code present in OFSLL application.
Origination Config_ofsl I143	BRANCH_CODE	Branch Code present in OFSLL application.
Origination Config_ofsl I143	DATA_REQUIRED_FOR_SU BMISSION	Indicates if submission data should be used for submitting application details to host system.
		Value should be 'true' for OFSLL setup.

5.3 Disclosure configurations

Please follow doc (Origination_disclosure_configuration.doc) for configuring disclosures in OBDX OFSLL application.

5.4 Promo code maintenance

Promo codes (which exist in OFSLL application) can be maintained in OBDX database at table 'digx_or_promo_codes'.

5.5 Dealer maintenance

Dealer details can be maintained in OBDX database at table 'digx_or_dealer_details'

5.6 Social Media Integration

Please refer 'User Manual Oracle Banking Digital Experience Origination Social Media Integration.docx' document to have social media integration.