

Installer Decentralized setup
Oracle FLEXCUBE Installer
Release 14.0.0.0.0
[Nov] [2017]



Table of Contents

1. PROPERTY FILE CREATION FOR DECENTRALIZED VIA ORACLE FLEXCUBE INSTALLER...	1
1.1 INTRODUCTION	1
1.2 CREATING PROPERTY FILE	1
2. LOADING OBJECTS INTO HOST & DC SCHEMA VIA FLEXCUBE INSTALLER.....	20
2.1 INTRODUCTION	20
2.2 LOADING OBJECTS INTO HOST & DC SCHEMA.....	20
3. DECENTRALIZED APPLICATION SETUP VIA WEBLOGIC	21
3.1 INTRODUCTION	21
3.2 APPLICATION SETUP.....	21
3.2.1 <i>.ear and war file creation</i>	21
3.2.2 <i>Deploying .ear file in WebLogic server</i>	22
3.2.3 <i>Deploying .war file in WebLogic server</i>	26

1. Property File creation for Decentralized via Oracle FLEXCUBE Installer


1.1 Introduction

This chapter explains the steps to create property file for Oracle Decentralized FLEXCUBE Installer Application. Two property files are created fubs property file and environment property file.

1.2 Creating Property File

To create the property file for Oracle Decentralized FLEXCUBE, follow the steps given below:

1. Launch Oracle FLEXCUBE Installer bat file i.e. **FCUBSInstaller.bat**.



Need to provide the following details:

JAVA HOME PATH

Provide the JDK home path with the latest version.

ORACLE HOME PATH


Provide the Oracle 12C Client Path.

APPSERVER PATH

Provide the Application Server Path.

After providing these details, INSTALLER-GUI gets generated. And follow the below details.

Enter the following details



JDK Path:

Maintain Home folder path of JDK1.8

Oracle Home

Maintain home folder path of Oracle Client or Database

Application Server Home

Maintain home folder path of Application Server

2. Click 'Next' and the following screen is displayed.

Components

Choose components as INFRA.


Product Processors

Choose product processors as Oracle FLEXCUBE Universal Banking.

Plugins


Select Branch and Decentralized option to load objects related to Decentralized.

Scheduler can be Embedded.



3. Click 'Next' and the following screen is displayed:


Specify SMS and Host schema details, Test connection to assure schema details provided are proper.



4. Click 'Next' and the following screen is displayed:

Provide Branch schema details and SMS schema details to create dblinks between two schemas.

Click on Test Connection to assure the connection details provided are proper.



- Click 'Next' and the following screen is displayed:

EAR Name

Specify a name for the Application to be deployed.

You cannot use special characters such as '.' (Dot), ',' (comma), '\$' etc. However, you may use '_' (underscore). – Applicable for both Windows and Linux.

Context Name

Based on the Application type selected, the Installer displays the application context. However,

You may modify the default value.

Application Server

Specify the application server in which you are creating the property file. Select the appropriate one from the adjoining drop-down list.

Source Path


Provide the source path maintained.

Source Path

Provide the source path maintained.

Ear Destination Path

Provide the Ear destination path to place the generated .ear and .war file during generation of .ear and .war files.




The screenshot shows the Oracle Banking Installer 12.5.0.0.0 window. The title bar reads "Oracle FLEXCUBE Universal Installer 12.5.0.0.0". The main window has a header with "Oracle Banking Installer" on the left and the "ORACLE INSTALLER" logo on the right. Below the header, the text "Provide Environment details." is displayed. The configuration fields are as follows:

- EAR Name: FCUBS
- Context Name: FCJNeoWeb
- File Separator Style: Linux (dropdown menu)
- Application Server: Weblogic (dropdown menu)
- External JSUXML Required
- External PropertyFile Required
- Application Server Path: C:/Oracle/Middleware/Oracle_Home/jdeveloper/wlserver (with a "Browse" button)
- Source Path: C:\Work\poorna12_5\DCHOST2\Console_EXEC\Console_EXEC (with a "Browse" button)
- Ear Destination Path: poorna12_5\DCHOST2\PROPERTY_FILE_CREATION_20_NOV_2017 (with a "Browse" button)
- External JSUIXML Path: (empty field with a "Browse" button)
- External PropertyFile Path: (empty field with a "Browse" button)

At the bottom of the window, there are four buttons: "Exit", "Log", "Back", and "Next".


6. Click 'Next' to continue and following screen is displayed:
'Security Key for Encryption Logic' is the key (exact 24 characters) for all encryption logic.



7. Click 'Next' to continue and following screen is displayed:

Datasources:

- | | |
|-----------------------|---|
| SMS Data Source | – Provide proper JNDI names e.g.: jdbc/fcjsmsDS |
| Branch Data Source | – Provide proper JNDI names e.g.: jdbc/fcjDevXADS |
| Scheduler Data Source | – Provide proper JNDI names e.g.: jdbc/fcjSchedulerDS |
| Host Server URL | – Host URL to establish connection from Branch. |



8. Click 'Next' to continue and following screen is displayed:

Debug Logs Required

If you require debug option, select 'Yes' from the drop-down list. If you do not require debug option, select 'No'.

Work Area

Specify the work area.

For example: D:\BrnDbgs\

Signature Path

Specify the location at which the signature images are placed.

Excel Path

Specify the location at which the excel files are generated.

Data Source

Specify the JNDI location. The standard format is 'jdbc/fcjdeVDS'.

Request Time Out

Specify the database request timeout value in milli seconds. This is the maximum number of seconds the database waits for a query to return the result.

Connection Time Out

Specify the database connection timeout value in seconds. This is the maximum number of seconds the application waits for a connection to the database to open.

Session Time Out

Enter the session time out value in seconds. This is the maximum number of seconds during which the application gets active without any user intervention. If there is no user intervention continuously for the duration specified here, the user session gets expire.

LOV Fetch Required

If you check this box, the option lists in Oracle FLEXCUBE displays the matching values based on the first characters that you enter in a field. If you specify the first three characters of a value to be entered in an option list and tab out, the system displays the complete list of values that are matching the first three characters.

If you do not check this, option lists does not show the matching values based on the first few characters. You need to specify the complete value against the field.

Max Image Size

Specifies the maximum image size that can be uploaded. The default size is 1048576 in bytes.

CSS Style


Specify the CSS style to be used from the adjoining drop down list. You can select one of the following CSS styles:

Default – select this to apply the default style provided along with Oracle FLEXCUBE

Custom – select this to apply a custom style

Name

Specify the name of the CSS style.



9. Click 'Next' and the following screen is displayed:

SSO Required

Check this box to enable single sign-on (SSO). If you check this box, you need to enter the SSO Key.


SSO Key

Specify the SSO key. If you have checked the box 'SSO Required, it is mandatory to specify the SSO key.

OPSS


OPSS is available only for weblogic and is not supported for Websphere.

IF OPSS available is checked for weblogic the symmetric key is not stored in the property file for security reasons.



10. Click 'Next' and the following screen is displayed:

Specify the Mail configuring following details:



11. Click 'Next' and the following screen is displayed:

Provide Scheduler Queue details.

Oracle FLEXCUBE Universal Installer 12.5.0.0.0

Oracle Banking Installer

Property File Creation - Scheduler Queues

Option for configuring Scheduler Destination Queue

Notify Destination: QUEUE

Queue Name: NOTIFY_DEST_QUEUE

Queue Connection Factory: NotifyDestQCF

Secure Caller ID:

Caller Password:

Notify Queue Location: internal

Option for configuring Scheduler Deferred Queue

Notify Deferred Queue Name: DEFERRED_DEST_QUEUE

Deferred Queue Connection Factory: DeferredDestQCF

Secure Caller ID:

Caller Password:

Option for configuring Scheduler Notify Internal Queue

Notify Queue Name: NOTIFY_QUEUE

Dead Letter Queue Name: NOTIFY_QUEUE_DLQ

Notify Queue Connection Factory: NOTIFY_MDB_QCF

Secure Caller ID:

Caller Password:

Option for configuring Log Rotation Interval

Scheduler Log Rotation Interval: WEEKLY

Option for External Server configuration for Destination Queue.

No.	Name	Value
1	Provide Url	iiop://localhost:1010
2	Security Principal
3	Security Credential

Exit
Log
Back
Next


12. Click 'Next' and the following screen is displayed:

Provide Scheduler EMS Queue details.

Outgoing Queue Provider URL – It can be Host server URL.


Queue Principal – It should be weblogic login username.

Queue Credential – It should be weblogic login password.



13. Click 'Next' and the following screen is displayed:

Provide EMS FTP/FTPS details



14. Click 'Next' and the following screen is displayed:

Provide Scheduler BIP Advice report configuration details.

Oracle FLEXCUBE Universal Installer 12.5.0.0.0

Oracle Banking Installer

**ORACLE
INSTALLER**

Property File Creation - Scheduler BIP/GI Upload Queue

Option for configuring Scheduler BIP and BIP Advice report.


Bip Queue Name	<input type="text" value="INTERNAL_BIPREPORT_QUEUE"/>
Bip DeadLetter Queue Name	<input type="text" value="INTERNAL_BIP_QUEUE_DLQ"/>
BipAdvice Queue Name	<input type="text" value="ERNAL_BIPADVREPORT_QUEUE"/>
BipAdvice DeadLetter Queue Name	<input type="text" value="RNAL_BIP_ADVICE_QUEUE_DLQ"/>
Queue connection factory	<input type="text" value="BIPQCF"/>
<input type="checkbox"/> Secure	Caller ID <input type="text"/>
Caller password <input type="text"/>	

Option for configuring details for Scheduler GI Upload Queue

Queue Name	<input type="text" value="INTERNAL_GI_UPLOAD_QUEUE"/>
Dead Letter Queue Name	<input type="text" value="INTERNAL_GI_UPLOAD_DLQ"/>
Queue connection factory	<input type="text" value="GI_UPLOAD_QCF"/>
<input type="checkbox"/> Secure	Caller ID <input type="text"/>
Caller Password <input type="text"/>	

15. Click 'Next' and the following screen is displayed:

Provide Scheduler BI publish report configuration details.



16. Click 'Next' and the following screen is displayed:

Click on save property file will be built with latest properties.

Property file can be saved in the respective locations and can be used for subsequent processing.

Property file created will have DC and Host property files.

Enclosed sample files for reference. Checkpoint: INIT_DATASOURCE in fcubs.properties

DC Property File



fcubs.properties

Host Property File





fcubs.properties

Env. Property file



env.properties



Once property file creation is completed. .env property file will also be updated in path INSTALLER\SOFT\GUI\logs.

.env property file created to be placed in \INSTALLER\SOFT\logs while generating .ear and .war files

Update .env property file with DC and Host property file paths generated already.

2. Loading objects into Host & DC schema via FLEXCUBE Installer


2.1 Introduction

This chapter explains the steps to load objects into Decentralized schema using FLEXCUBE Installer.

2.2 Loading Objects into Host & DC Schema

To load objects into Host and Decentralized schema, follow the steps given below:

1. env.properties generated in \INSTALLER\SOURCE\logs to be placed in \INSTALLER\SOFT\logs path.
2. Execute Oracle SMS DB Compiler silent Installer bat file i.e. **SMSDBCompileRun.bat**
After execution is completed, Host schema should be loaded with Host objects. Invalid count should be zero after execution
3. Execute Oracle Host DB Compiler silent Installer bat file i.e. **ROFCDBCompileRun.bat**
After execution is completed, Host schema should be loaded with Host objects. Invalid count should be zero after execution.



```
C:\windows\system32\cmd.exe
Flex Cube UBS : Release 12.4.0.0.0 - Production on 11:48:17.53 Tue 11/21/2017
Copyright (c) 2016, Oracle Financial Services Software Ltd. All rights reserved.

Checking the write permissions.....
checking whether Installer is running.....
Creating a new flag file.....
sucessfully created the flag File.

Initializing the errorLevel to 0

Checking Java Home.....
Please input Java path [Example: D:\Program Files\Java\jdk1.6.0_17]
#####JAVAHOME NOT DEFINED#####
Enter JAVA HOME Directory:
```

Check point: In SSTB_USER table Home Entity should be updated properly after Day-0 setup.

4. Execute Oracle Branch DB Compiler silent Installer bat file i.e. **ROFCBranchDBCompileRun.bat**
After execution is completed, DC schema should be loaded with DC objects. Invalid count should be zero.

```
C:\windows\system32\cmd.exe

Flex Cube UBS : Release 12.4.0.0.0 - Production on 11:48:17.53 Tue 11/21/2017
Copyright (c) 2016, Oracle Financial Services Software Ltd. All rights reserved.

Checking the write permissions.....

checking whether Installer is running.....
Creating a new flag file.....
sucessfully created the flag File.

Initializing the errorLevel to 0

Checking Java Home.....
Please input Java path [Example: D:\Program Files\Java\jdk1.6.0_17]
#####JAVAHOME NOT DEFINED#####
Enter JAVA HOME Directory:
```

3. Decentralized Application setup via WebLogic

3.1 Introduction

This chapter explains the steps to setup application in WebLogic server.

3.2 Application Setup

3.2.1 .ear and war file creation

1. Execute Oracle Ear creation bat, silent Installer bat file i.e. **ROFCEarRun.bat**

```
C:\windows\system32\cmd.exe

Flex Cube UBS : Release 12.4.0.0.0 - Production on 11:48:17.53 Tue 11/21/2017
Copyright (c) 2016, Oracle Financial Services Software Ltd. All rights reserved.

Checking the write permissions.....

checking whether Installer is running.....
Creating a new flag file.....
sucessfully created the flag File.

Initializing the errorLevel to 0

Checking Java Home.....
Please input Java path [Example: D:\Program Files\Java\jdk1.6.0_17]
#####JAVAHOME NOT DEFINED#####
Enter JAVA HOME Directory:
```

- It creates .war file and .ear file.
- Following check points to be verified after .ear and .war file creation.

web.xml file should be proper with xml tags. If not will result in servlet exceptions on deployment.

3.2.2 Deploying .ear file in WebLogic server

- Set SSL port enabled.

The screenshot displays the Oracle WebLogic Server Administration Console interface. The main content area is titled 'Settings for soa_server1' and is divided into several tabs: Configuration, Protocols, Logging, Debug, Monitoring, Control, Deployments, Services, Security, and Notes. The 'Configuration' tab is active, showing various settings for the server instance.

On the left side, there is a 'Change Center' panel with 'View changes and restarts' and buttons for 'Lock & Edit' and 'Release Configuration'. Below it is the 'Domain Structure' tree, showing a hierarchy of nodes like Environment, Servers, Clusters, and Machines. A 'How do I...' panel and a 'System Status' panel are also visible on the left.

The main configuration area contains the following settings:

- Name:** soa_server1 (An alphanumeric name for this server instance. [More Info...](#))
- Template:** (No value specified) ([Change](#)) (The template used to configure this server. [More Info...](#))
- Machine:** Machine1 (The WebLogic Server host computer (machine) on which this server is meant to run. [More Info...](#))
- Cluster:** (Stand-Alone) (The cluster, or group of WebLogic Server instances, to which this server belongs. [More Info...](#))
- Listen Address:** 10.184.157.98 (The IP address or DNS name this server uses to listen for incoming connections. For example, enter 12.34.5.67 or mymachine, respectively. [More Info...](#))
- Listen Port Enabled** (Specifies whether this server can be reached through the default plain-text (non-SSL) listen port. [More Info...](#))
- Listen Port:** 8203 (The default TCP port that this server uses to listen for regular (non-SSL) incoming connections. [More Info...](#))
- SSL Listen Port Enabled** (Indicates whether the server can be reached through the default SSL listen port. [More Info...](#))
- SSL Listen Port:** 8204 (The TCP/IP port at which this server listens for SSL connection requests. [More Info...](#))
- Client Cert Proxy Enabled** (Specifies whether the HttpClusterServlet proxies the client certificate in a special header. [More Info...](#))
- Java Compiler:** javac (The Java compiler to use for all applications hosted on this server that need to compile Java code. [More Info...](#))
- Diagnostic Volume:** Low (Specifies the volume of diagnostic data that is automatically produced by WebLogic Server at run time. Note that the WLDP diagnostic volume setting does not affect explicitly configured diagnostic modules. For example, this controls the volume of events generated for Flight Recorder. [More Info...](#))
- Default Datasource:** (The JNDI name of a system resource data source used to override the default datasource. [More Info...](#))

At the bottom of the configuration area, there is an 'Advanced' link and a 'Save' button. A footer note states: 'Click the Lock & Edit button in the Change Center to modify the settings on this page.'

2. Map Data source as follows

The screenshot displays the Oracle WebLogic Server Administration Console interface. The main content area is titled "Settings for jdbc/fc3devDS" and is under the "Configuration" tab. The "General" sub-tab is active, showing the following configuration details:

Name:	jdbc/fc3devDS	A unique name that identifies this data source in the WebLogic domain. More Info...
Datasource Type:	GENERIC	The data source type. Valid types are: More Info...
Scope:	Global	The scope in which the data source is available in. More Info...
JNDI Name:	jdbc/fc3devDS	The JNDI path to where this data source is bound. By default, the JNDI name is the name of the data source. More Info...
<input type="checkbox"/> Row Prefetch Enabled		Enables multiple rows to be "prefetched" (that is, sent from the server to the client) in one server access. More Info...
Row Prefetch Size:	48	If row prefetching is enabled, specifies the number of result set rows to prefetch for a client. More Info...
Stream Chunk Size:	256	Specifies the data chunk size for streaming data types. More Info...

On the left side of the console, there are several panels: "Change Center" with "View changes and restarts" options; "Domain Structure" showing a tree view of the domain hierarchy; "How do I..."; and "System Status" showing the health of running servers as of 1:36 AM.

Connection pool as follows,

URL:	<input type="text" value="jdbc:oracle:thin:@whf00blr.in.oracle.com:1522/FCPDBR2"/>	The URL of the database to connect to. The format of the URL varies by JDBC driver. More Info...
Driver Class Name:	<input type="text" value="oracle.jdbc.OracleDriver"/>	The full package name of JDBC driver class used to create the physical database connections in the connection pool. (Note that this driver class must be in the classpath of any server to which it is deployed.) More Info...
Properties:	<input type="text" value="user=FC125R2"/>	The list of properties passed to the JDBC driver that are used to create physical database connections. For example: server=observer1. List each property=value pair on a separate line. More Info...
System Properties:	<input type="text"/>	The list of System Properties names passed to the JDBC driver that are used to create physical database connections. For example: server=observer1. List each property=value pair on a separate line. More Info...
Encrypted Properties:	<input type="text"/> <input type="button" value="Add Securely"/>	The list of encrypted Properties passed to the JDBC driver that are used to create physical database connections. For example: password=value. There are two ways to entered the values: You can enter several values at once but the encrypted values will be visible on the screen until you save the changes. To use this option, list each property=value pair on a separate line. Values entered will be encrypted when saved. To enter the information securely, save any other changes that you wish to make to this page and click on the Add Securely button. On the Add a new Encrypted Property page, enter the property name and masked value, and click OK. Repeat for additional encrypted property values. More Info...
Password:	<input type="password"/>	The password attribute passed to the JDBC driver when creating physical database connections. More Info...
Confirm Password:	<input type="password"/>	
Initial Capacity:	<input type="text" value="1"/>	The number of physical connections to create when creating the connection pool in the data source. If unable to create this number of connections, creation of the data source will fail. More Info...
Maximum Capacity:	<input type="text" value="100"/>	The maximum number of physical connections that this connection pool can contain. More Info...
Minimum Capacity:	<input type="text" value="1"/>	The minimum number of physical connections that this connection pool can contain after it is initialized. More Info...
Statement Cache Type:	<input type="text" value="LRU"/>	The algorithm used for maintaining the prepared statements stored in the statement cache. More Info...
Statement Cache Size:	<input type="text" value="10"/>	The number of prepared and callable statements stored in the cache. (This may increase server performance.) More Info...
Advanced		
<input type="button" value="Save"/>		

File Edit View Favorites Tools Help

ORACLE WebLogic Server Administration Console 12c

Home > Summary of Domain Partitions > Summary of Partition Work Managers > Summary of Servers > AdminServer

Welcome, weblogic Connected to: FC125DC

Settings for AdminServer

Configuration Protocols Logging Debug Monitoring Control Deployments Services Security Notes

General Cluster Services Keystores SSL Federation Services Deployment Migration Tuning Overload Concurrency Health Monitoring Server Start Web Services Coherence


Click the **Lock & Edit** button in the Change Center to modify the settings on this page.

Use this page to configure general features of this server such as default network communications.


View JNDI Tree

Name:	AdminServer	An alphanumeric name for this server instance. More Info...
Template:	(No value specified) <input type="button" value="Change"/>	The template used to configure this server. More Info...
Machine:	(None)	The WebLogic Server host computer (machine) on which this server is meant to run. More Info...
Cluster:	(Stand-Alone)	The cluster, or group of WebLogic Server instances, to which this server belongs. More Info...
Listen Address:	<input type="text" value="10.184.152.169"/>	The IP address or DNS name this server uses to listen for incoming connections. For example, enter 12.34.5.67 or mymachine, respectively. More Info...
<input checked="" type="checkbox"/> Listen Port Enabled		Specifies whether this server can be reached through the default plain-text (non-SSL) listen port. More Info...
Listen Port:	<input type="text" value="7201"/>	The default TCP port that this server uses to listen for regular (non-SSL) incoming connections. More Info...
<input checked="" type="checkbox"/> SSL Listen Port Enabled		Indicates whether the server can be reached through the default SSL listen port. More Info...
SSL Listen Port:	<input type="text" value="7202"/>	The TCP/IP port at which this server listens for SSL connection requests. More Info...
<input type="checkbox"/> Client Cert Proxy Enabled		Specifies whether the HttpClusterServlet proxies the client certificate in a special header. More Info...
Java Compiler:	<input type="text" value="javac"/>	The Java compiler to use for all applications hosted on this server that need to compile Java code. More Info...
Diagnostic Volume:	<input type="text" value="Low"/>	Specifies the volume of diagnostic data that is automatically produced by WebLogic Server at run time. Note that the WLDf diagnostic volume setting does not affect explicitly configured diagnostic modules. For example, this controls the volume of events generated for Flight Recorder. More Info...
Default Datasource:	<input type="text"/>	The JNDI name of a system resource data source used to override the default datasource. More Info...

Set the Targets to both admin server and managed server, based on the application pointing to.



3. Install .ear and jax-rs as follows,



whf00bey.in.oracle.com:8201/console/console.portal?_nfpb=true&_pageLabel=AppDeploymentsControlPage&AppDeploymentsControlPortlethandle=com.bea.console.handlers.JMXHandle%28*com.bea%3AName%3DFCTEST2%2CType%3DDomain%29

Start the server e.g.: FCUBSDC1 for first use.

Check Point: Maintain Day 0 Setup, RT related transactions should be completed successfully.

3.2.3 Deploying .war file in WebLogic server

1. Set SSL Port enabled.
2. Add Data Sources as follows.

The screenshot shows the Oracle WebLogic Server Administration Console. The main content area is titled "Settings for jdbc/fcjdeVDSBranch" and includes tabs for Configuration, Targets, Monitoring, Control, Security, and Notes. The "General" tab is active, showing fields for Name (jdbc/fcjdeVDSBranch), Datasource Type (GENERIC), Scope (Global), and JNDI Name (jdbc/fcjdeVDSBranch). There are also checkboxes for "Row Prefetch Enabled" and "Row Prefetch Size" (set to 48), and a "Stream Chunk Size" (set to 256). A "Save" button is visible at the bottom of the configuration area.

The screenshot shows the Oracle WebLogic Server Administration Console. The main content area is titled "Settings for jdbc/fcjdeVDSBranch" and includes tabs for Configuration, Targets, Monitoring, Control, Security, and Notes. The "Connection Pool" tab is active, showing fields for URL (jdbc:oracle:thin:@ofss2311553.in.oracle.com:1521/FC), Driver Class Name (oracle.jdbc.xa.client.OracleXADataSource), and Properties (user=FC125DEC). There are also fields for System Properties and Encrypted Properties. A "Password" field is visible with a masked input, and a "Confirm Password" field. An "Initial Capacity" field is set to 1. A "Save" button is visible at the bottom of the configuration area.

ORACLE WebLogic Server Administration Console 12c

Home Log Out Preferences Record Help Welcome, weblogic Connected to: FC125

Home > Summary of Domain Partitions > Summary of Partition Work Managers > Summary of Servers > AdminServer > Summary of Servers > Summary of Deployments > Summary of JDBC Data Sources

Summary of JDBC Data Sources

Configuration Monitoring

A JDBC data source is an object bound to the JNDI tree that provides database connectivity through a pool of JDBC connections. Applications can look up a data source on the JNDI tree and then borrow a database connection from a data source. This page summarizes the JDBC data source objects that have been created in this domain.

Customize this table

Data Sources (Filtered - More Columns Exist)

Click the Lock & Edit button in the Change Center to activate all the buttons on this page.

New Delete Showing 1 to 2 of 2 Previous Next

Name	Type	JNDI Name	Targets	Scope	Domain Partitions
<input type="checkbox"/> jdbc/fqdevDSBranch	Generic	jdbc/fqdevDSBranch	AdminServer	Global	
<input type="checkbox"/>					

New Delete Showing 1 to 2 of 2 Previous Next

Change Center

View changes and restarts

Click the Lock & Edit button to modify, add or delete items in this domain.

Lock & Edit

Release Configuration

Domain Structure

- Resource Groups
- Resource Group Templates
- Machines
- Virtual Hosts
- Virtual Targets
- Work Managers
- Concurrent Templates
- Resource Management
- Startup and Shutdown Classes
- Deployments
- Services
- Security Realms
- Interoperability
- Diagnostics

How do I...

- Create JDBC generic data sources
- Create JDBC GridLink data sources
- Create JDBC multi data sources
- Create UCP data sources
- Create Proxy data sources

System Status

Health of Running Servers as of 11:06 AM

- Failed (0)
- Critical (0)
- Overloaded (0)
- Warning (0)
- OK (1)

3. Install .war file generated and jax-rs.

ORACLE WebLogic Server Administration Console 12c

Home Log Out Preferences Record Help Welcome, weblogic Connected to: FC125

Home > Summary of Domain Partitions > Summary of Partition Work Managers > Summary of Servers > AdminServer > Summary of Servers > Summary of Deployments

Summary of Deployments

Configuration Control Monitoring

This page displays the list of Java EE applications and standalone application modules installed to this domain.

You can update (redeploy) or delete installed applications and modules from the domain by selecting the checkbox next to the application name and then using the controls on this page.

To install a new application or module for deployment to targets in this domain, click **Install**.

Customize this table

Install Update Delete Showing 1 to 2 of 2 Previous Next

Name	State	Health	Type	Targets	Scope	Domain Partitions	Deployment Order
<input type="checkbox"/> FCUBSAPP (12.4.0.0.0)	Active	OK	Web Application	AdminServer	Global		100
<input type="checkbox"/> jax-rs(2.0.22.1.0)	Active		Library	AdminServer	Global		100

Install Update Delete Showing 1 to 2 of 2 Previous Next

Change Center

View changes and restarts

Click the Lock & Edit button to modify, add or delete items in this domain.

Lock & Edit

Release Configuration

Domain Structure

- Resource Groups
- Resource Group Templates
- Machines
- Virtual Hosts
- Virtual Targets
- Work Managers
- Concurrent Templates
- Resource Management
- Startup and Shutdown Classes
- Deployments
- Services
- Security Realms
- Interoperability
- Diagnostics

How do I...

- Install an enterprise application
- Configure an enterprise application
- Update (redeploy) an enterprise application
- Monitor the modules of an enterprise application
- Deploy EJB modules
- Install a Web application

System Status

Health of Running Servers as of 11:06 AM

- Failed (0)
- Critical (0)
- Overloaded (0)
- Warning (0)
- OK (1)

WebLogic Server Version: 12.2.1.2.0
Copyright (c) 1996, 2016, Oracle and/or its affiliates. All rights reserved.
Oracle is a registered trademark of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

4. After deployment both DC server to be started for further use.

ORACLE Installer Property File Creation
[Nov] [2017]
Version 14.0.0.0.0

Oracle Financial Services Software Limited
Oracle Park
Off Western Express Highway
Goregaon (East)
Mumbai, Maharashtra 400 063
India

Worldwide Inquiries:
Phone: +91 22 6718 3000
Fax: +91 22 6718 3001
www.oracle.com/financialservices/

Copyright © [2016], [2017], Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.